



Sun Cluster Geographic Edition Reference Manual



Sun Microsystems, Inc.
4150 Network Circle
Santa Clara, CA 95054
U.S.A.

Part No: 820-5982-10
January 2009, Revision A

Copyright 2009 Sun Microsystems, Inc. 4150 Network Circle, Santa Clara, CA 95054 U.S.A. All rights reserved.

Sun Microsystems, Inc. has intellectual property rights relating to technology embodied in the product that is described in this document. In particular, and without limitation, these intellectual property rights may include one or more U.S. patents or pending patent applications in the U.S. and in other countries.

U.S. Government Rights – Commercial software. Government users are subject to the Sun Microsystems, Inc. standard license agreement and applicable provisions of the FAR and its supplements.

This distribution may include materials developed by third parties.

Parts of the product may be derived from Berkeley BSD systems, licensed from the University of California. UNIX is a registered trademark in the U.S. and other countries, exclusively licensed through X/Open Company, Ltd.

Sun, Sun Microsystems, the Sun logo, the Solaris logo, the Java Coffee Cup logo, docs.sun.com, Java, and Solaris are trademarks or registered trademarks of Sun Microsystems, Inc. or its subsidiaries in the U.S. and other countries. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. in the U.S. and other countries. Products bearing SPARC trademarks are based upon an architecture developed by Sun Microsystems, Inc. ORACLE is a registered trademark of Oracle Corporation.

The OPEN LOOK and Sun™ Graphical User Interface was developed by Sun Microsystems, Inc. for its users and licensees. Sun acknowledges the pioneering efforts of Xerox in researching and developing the concept of visual or graphical user interfaces for the computer industry. Sun holds a non-exclusive license from Xerox to the Xerox Graphical User Interface, which license also covers Sun's licensees who implement OPEN LOOK GUIs and otherwise comply with Sun's written license agreements.

Products covered by and information contained in this publication are controlled by U.S. Export Control laws and may be subject to the export or import laws in other countries. Nuclear, missile, chemical or biological weapons or nuclear maritime end uses or end users, whether direct or indirect, are strictly prohibited. Export or reexport to countries subject to U.S. embargo or to entities identified on U.S. export exclusion lists, including, but not limited to, the denied persons and specially designated nationals lists is strictly prohibited.

DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID.

Copyright 2009 Sun Microsystems, Inc. 4150 Network Circle, Santa Clara, CA 95054 U.S.A. Tous droits réservés.

Sun Microsystems, Inc. détient les droits de propriété intellectuelle relatifs à la technologie incorporée dans le produit qui est décrit dans ce document. En particulier, et ce sans limitation, ces droits de propriété intellectuelle peuvent inclure un ou plusieurs brevets américains ou des applications de brevet en attente aux Etats-Unis et dans d'autres pays.

Cette distribution peut comprendre des composants développés par des tierces personnes.

Certains composants de ce produit peuvent être dérivées du logiciel Berkeley BSD, licenciés par l'Université de Californie. UNIX est une marque déposée aux Etats-Unis et dans d'autres pays; elle est licenciée exclusivement par X/Open Company, Ltd.

Sun, Sun Microsystems, le logo Sun, le logo Solaris, le logo Java Coffee Cup, docs.sun.com, Java et Solaris sont des marques de fabrique ou des marques déposées de Sun Microsystems, Inc., ou ses filiales, aux Etats-Unis et dans d'autres pays. Toutes les marques SPARC sont utilisées sous licence et sont des marques de fabrique ou des marques déposées de SPARC International, Inc. aux Etats-Unis et dans d'autres pays. Les produits portant les marques SPARC sont basés sur une architecture développée par Sun Microsystems, Inc. ORACLE est une marque déposée registre de Oracle Corporation.

L'interface d'utilisation graphique OPEN LOOK et Sun a été développée par Sun Microsystems, Inc. pour ses utilisateurs et licenciés. Sun reconnaît les efforts de pionniers de Xerox pour la recherche et le développement du concept des interfaces d'utilisation visuelle ou graphique pour l'industrie de l'informatique. Sun détient une licence non exclusive de Xerox sur l'interface d'utilisation graphique Xerox, cette licence couvrant également les licenciés de Sun qui mettent en place l'interface d'utilisation graphique OPEN LOOK et qui, en outre, se conforment aux licences écrites de Sun.

Les produits qui font l'objet de cette publication et les informations qu'il contient sont régis par la législation américaine en matière de contrôle des exportations et peuvent être soumis au droit d'autres pays dans le domaine des exportations et importations. Les utilisations finales, ou utilisateurs finaux, pour des armes nucléaires, des missiles, des armes chimiques ou biologiques ou pour le nucléaire maritime, directement ou indirectement, sont strictement interdites. Les exportations ou réexportations vers des pays sous embargo des Etats-Unis, ou vers des entités figurant sur les listes d'exclusion d'exportation américaines, y compris, mais de manière non exclusive, la liste de personnes qui font objet d'un ordre de ne pas participer, d'une façon directe ou indirecte, aux exportations des produits ou des services qui sont régis par la législation américaine en matière de contrôle des exportations et la liste de ressortissants spécifiquement désignés, sont rigoureusement interdites.

LA DOCUMENTATION EST FOURNIE "EN L'ETAT" ET TOUTES AUTRES CONDITIONS, DECLARATIONS ET GARANTIES EXPRESSES OU TACITES SONT FORMELLEMENT EXCLUES, DANS LA MESURE AUTORISEE PAR LA LOI APPLICABLE, Y COMPRIS NOTAMMENT TOUTE GARANTIE IMPLICITE RELATIVE A LA QUALITE MARCHANDE, A L'APTITUDE A UNE UTILISATION PARTICULIERE OU A L'ABSENCE DE CONTREFACON.

Contents

Preface	5
SC32GEO 1M	9
geoadm(1M)	10
geohb(1M)	17
geopg(1M)	23
geops(1M)	43
Index	51

Preface

The *Sun Cluster Geographic Edition Reference Manual* provides reference information about commands that are supplied with Sun™ Cluster Geographic Edition software. This book is intended for experienced system administrators with extensive knowledge of Sun software and hardware. This book is not to be used as a planning or presales guide. The information in this book assumes knowledge of the Solaris™ Operating System and expertise with the data replication software that is used with Sun Cluster Geographic Edition software.

Both novice users and those familiar with the Solaris Operating System can use online man pages to obtain information about their SPARC™ based system or x86 based system and its features.

A man page is intended to answer concisely the question “What does this command do?” The man pages in general comprise a reference manual. They are not intended to be a tutorial.

Note – Sun Cluster software runs on two platforms, SPARC and x86. The information in this book pertains to both platforms unless otherwise specified in a special chapter, section, note, bulleted item, figure, table, or example.

Overview

The following contains a brief description of each man page section and the information it references.

Section 1M describes, in alphabetical order, commands that are used chiefly for system maintenance and administration purposes.

The following is a generic format for man pages. The man pages of each manual section generally follow this order, but include only needed headings. For example, if no bugs can be reported, no BUGS section is included. See the `intro` pages for more information and detail about each section, and `man(1)` for general information about man pages.

NAME	This section gives the names of the commands or functions that are documented, followed by a brief description of what they do.
------	---

SYNOPSIS

This section shows the syntax of commands or functions. If a command or file does not exist in the standard path, its full path name is shown. Options and arguments are alphabetized, with single-letter arguments first, and options with arguments next, unless a different argument order is required.

The following special characters are used in this section:

- [] Brackets. The option or argument that is enclosed in these brackets is optional. If the brackets are omitted, the argument must be specified.
- . . . Ellipses. Several values can be provided for the previous argument, or the previous argument can be specified multiple times, for example, “filename...“.
- | Separator. Only one of the arguments separated by this character can be specified at a time.
- { } Braces. The options and/or arguments enclosed within braces are interdependent. All characters within braces must be treated as a unit.

PROTOCOL

This section occurs only in subsection 3R and indicates the protocol description file.

DESCRIPTION

This section defines the functionality and behavior of the service. Thus it describes concisely what the command does. DESCRIPTION does not discuss OPTIONS or cite EXAMPLES. Interactive commands, subcommands, requests, macros, and functions are described under USAGE.

IOCTL

This section appears on pages in Section 7 only. Only the device class that supplies appropriate parameters to the `ioctl(2)` system call is called `ioctl` and generates its own heading. `ioctl` calls for a specific device are listed alphabetically (on the man page for that specific device). `ioctl` calls are used for a particular class of devices. All these calls have an `io` ending, such as `mtio(7I)`.

OPTIONS

This section lists the command options with a concise summary of what each option does. The options are listed

	literally and in the order they appear in the SYNOPSIS section. Possible arguments to options are discussed under the option, and where appropriate, default values are supplied.
OPERANDS	This section lists the command operands and describes how they affect the actions of the command.
OUTPUT	This section describes the output – standard output, standard error, or output files – generated by the command.
RETURN VALUES	If the man page documents functions that return values, this section lists these values and describes the conditions under which they are returned. If a function can return only constant values, such as 0 or -1, these values are listed in tagged paragraphs. Otherwise, a single paragraph describes the return values of each function. Functions that are declared void do not return values, so they are not discussed in RETURN VALUES.
ERRORS	On failure, most functions place an error code in the global variable <code>errno</code> that indicates why they failed. This section lists alphabetically all error codes a function can generate and describes the conditions that cause each error. When more than one condition can cause the same error, each condition is described in a separate paragraph under the error code.
USAGE	This section lists special rules, features, and commands that require in-depth explanations. The subsections that are listed here are used to explain built-in functionality: Commands Modifiers Variables Expressions Input Grammar
EXAMPLES	This section provides examples of usage or of how to use a command or function. Wherever possible, a complete example, which includes command-line entry and machine response, is shown. Whenever an example is given, the prompt is shown as <code>example%</code> , or if the user must be superuser, <code>example#</code> . Examples are followed by explanations, variable substitution rules, or returned

	values. Most examples illustrate concepts from the SYNOPSIS, DESCRIPTION, OPTIONS, and USAGE sections.
ENVIRONMENT VARIABLES	This section lists any environment variables that the command or function affects, followed by a brief description of the effect.
EXIT STATUS	This section lists the values the command returns to the calling program or shell and the conditions that cause these values to be returned. Usually, zero is returned for successful completion, and values other than zero are returned for various error conditions.
FILES	This section lists all file names that are referred to by the man page, files of interest, and files created or required by commands. Each file name is followed by a descriptive summary or explanation.
ATTRIBUTES	This section lists characteristics of commands, utilities, and device drivers by defining the attribute type and its corresponding value. See attributes(5) for more information.
SEE ALSO	This section lists references to other man pages, in-house documentation, and outside publications.
DIAGNOSTICS	This section lists diagnostic messages with a brief explanation of the condition that caused the error.
WARNINGS	This section lists warnings about special conditions that could seriously affect your working conditions. WARNINGS is not a list of diagnostics.
NOTES	This section lists additional information that does not belong anywhere else on the page. NOTES covers points of special interest to the user. Critical information is never covered here.
BUGS	This section describes known bugs and, wherever possible, suggests workarounds.

REFERENCE

SC32GEO 1M

Name geoadm– enable or disable the Sun Cluster Geographic Edition infrastructure on the local cluster

Synopsis /usr/cluster/bin/geoadm [*subcommand*] -?
 /usr/cluster/bin/geoadm -V
 /usr/cluster/bin/geoadm show
 /usr/cluster/bin/geoadm start
 /usr/cluster/bin/geoadm status
 /usr/cluster/bin/geoadm stop [-f | -i]

Description The geoadm command enables or disables the Sun Cluster Geographic Edition infrastructure on the local cluster. You can also use this command to check whether the Sun Cluster Geographic Edition software is enabled on the cluster.

After installation, the Sun Cluster Geographic Edition product must be enabled by running the command `geoadm start`. This command enables the cluster to participate in partnerships and to host protection groups. The `geoadm start` command configures the highly available infrastructure that unlocks the Sun Cluster Geographic Edition module on the cluster.

The `geoadm stop` command stops the highly available infrastructure that leaves the Sun Cluster Geographic Edition module locked on the cluster. Run the `geoadm stop` command before you remove product packages.

Note – The `geoadm stop` command can successfully disable the Sun Cluster Geographic Edition module on a cluster only under one condition. All local states of the protection groups in which the cluster is involved must be `Offline` or `Unknown`.

Running the `geoadm start` or the `geoadm stop` command on one node of the cluster affects the entire cluster.

To use the `geoadm` command to enable or disable the Sun Cluster Geographic Edition infrastructure, you must be assigned the proper role-based access control (RBAC) rights profile.

If you have root access, you have permissions to perform any operation. If you do not have root access, the following RBAC rights apply:

- **Basic Solaris User.** You can read information about Sun Cluster Geographic Edition entities by running commands such as `geopg list`, `geohb list`, and `geops list`.
- **Geo Management.** You can perform all the read operations that someone with Basic Solaris User access can perform. You can also perform administrative and configuration tasks such as `geohb create`, `geopg switchover`, `geoadm start`, and `geoadm stop`.

For more information, see the `rbac(5)` man page and “Sun Cluster Geographic Edition Software and RBAC” in *Sun Cluster Geographic Edition System Administration Guide*.

The general form of this command is as follows:

```
geoadm [subcommand] [options] [operands]
```

You can omit *subcommand* only if *options* specifies the option `-?`, `-o`, `-V`, or `-v`.

Each option of this command has a long form and a short form. Both forms of each option are given with the description of the option in the OPTIONS section of this man page.

Subcommands The following subcommands are supported:

`show`

Display whether the Sun Cluster Geographic Edition software is enabled on the cluster.

`start`

Configure and enable the Sun Cluster Geographic Edition infrastructure on the cluster.

`status`

Display the runtime status of the Sun Cluster Geographic Edition entities on the local cluster.

The Sun Cluster Geographic Edition software must be installed on the local cluster before you can run the `status` subcommand. You can run the `status` subcommand whether or not the cluster has been enabled for partnership.

The `status` subcommand displays the following information:

- Whether the local cluster is enabled for partnership.
- Whether the local cluster is involved in a partnership. If the cluster is involved in a partnership, the `status` subcommand lists all partnership members.
- Heartbeat status.
- Protection group status.
- Status of ongoing transactions.

See the EXTENDED DESCRIPTION section for details about the possible values for each status.

`stop`

Disable the Sun Cluster Geographic Edition infrastructure and configuration on the cluster.

Caution – All protection groups on the cluster must be in the `Offline` state to run the `stop` subcommand successfully.

The `stop` subcommand removes the cluster state and Sun Cluster Geographic Edition infrastructure resource groups on the cluster, but the `stop` subcommand does not remove data replication resource groups.

The Sun Cluster Geographic Edition infrastructure is enabled and configured again the first time you run the `start` subcommand after running the `stop` subcommand.

Options The following options are supported:

-?

--help

Displays help information. When this option is used, no other processing is performed.

You can specify this option without a subcommand or with a subcommand.

If you specify this option without a subcommand, the list of subcommands for this command is displayed.

If you specify this option with a subcommand, the usage options for the subcommand are displayed.

The question mark might be interpreted as a special character by some shells. Use quotes ("-?") or an escape character to avoid pattern matching.

-f

--force

Indicates that you want to bypass the command confirmation questions while the Sun Cluster Geographic Edition infrastructure is being disabled.

-i

--interactive

Indicates that you want to display the interactive command confirmation questions while the Sun Cluster Geographic Edition infrastructure is being disabled.

-V

--version

Displays the version of the command.

Do not specify this option with subcommands, operands, or other options. The subcommands, operands, or other options are ignored. The `-V` option only displays the version of the command. No other operations are performed.

Extended Description The following sections list the status descriptions.

Partnership Status Partnership status displays status for the local cluster only. The partnership status can be one of the following:

OK The partner clusters are connected.

Error The partner clusters are disconnected.

Synchronization Status	<p>Synchronization status displays status for all the clusters in a partnership. The partnership synchronization status can be one of the following:</p> <p>OK The configuration is synchronized between partner clusters.</p> <p>Error The configuration on the partner clusters is different. You must synchronize the partnership again.</p> <p>Mismatch The partner clusters have been configured individually. Therefore, you must remove the configuration on one cluster and copy the configuration of the partner cluster.</p> <p>Unknown Information is not accessible because the partners are disconnected.</p>
Intercluster Resource Management Connection Status	<p>Intercluster Resource Management (ICRM) Connection status displays status for the cluster management agent that is running on the remote cluster. The ICRM connection status can be one of the following:</p> <p>OK The ICRM module on each of the partner clusters can communicate with each other.</p> <p>Error The ICRM module on the local cluster is unable to communicate with the ICRM module on the remote cluster.</p>
Heartbeat Status	<p>Heartbeat status displays status for the local cluster only. The heartbeat status can be one of the following:</p> <p>OK Heartbeat monitoring is enabled, and the partner cluster is responding within timeout and retry periods.</p> <p>Error Heartbeat monitoring is running, but the partner cluster is not responding and retries have timed out.</p> <p>Offline Heartbeat monitoring is offline.</p>
Heartbeat Plug-in Status	<p>Heartbeat plug-in status displays status for the local cluster only. The heartbeat plug-in status can be one of the following:</p> <p>OK The partner cluster is responding.</p> <p>Inactive The plug-in is not in use. It is a standby plug-in that is used for retrying if other plug-ins do not respond.</p> <p>No-Response The partner cluster is not responding.</p>
Protection Group Status	<p>Protection group status displays the overall status for all the clusters in the protection group. The overall protection group status can be one of the following:</p> <p>OK The protection group is online, application resource groups are online, and data replication is running.</p>

	Offline	The protection group is inactive.
	Degraded	The protection group and the application resource groups are online, but data replication is either not running or is in a partial error state.
	Error	The protection group is online, but at least one component of the partnership, such as configuration, data replication, or resource groups, is in an error state.
	Unknown	The protection group is online, but the status for at least one component of the partnership, such as configuration, data replication, or resource groups, is unknown.
Configuration Status	The configuration status of a protection group displays the status for a single cluster only. The configuration status of a protection group can be one of the following:	
	OK	The protection group configuration has been validated without errors on the cluster.
	Error	The validation of the protection group configuration resulted in an error. You must validate the protection group again.
	Unknown	Information is not accessible because the partner clusters are disconnected.
Data Replication Status	Data replication status displays the status of data replication that has been configured for the protection group on a single cluster. The data replication status of a protection group can be one of the following:	
	OK	Data replication is configured, online, and running without errors.
	Degraded	Data replication is either off or in a partial error state.
	Error	Data replication is not operating because of an error.
	None	Data replication has not been configured.
	Unknown	Information is not accessible because the partners are disconnected.
Resource Groups Status	Resource group status displays the status of resource groups that have been configured for the protection group on a single cluster. The resource group status of a protection group can be one of the following:	
	OK	All resource groups are online on the primary cluster, and all resource groups are offline or unmanaged on the secondary cluster.
	Error	Not all resource groups are online on the primary cluster, or not all resource groups are offline or unmanaged on the secondary cluster.
	Unknown	Information is not accessible because the partners are disconnected.

Exit Status The following exit values are returned:

0	The command completed successfully.
nonzero	An error has occurred.

Examples **EXAMPLE 1** Enabling the Sun Cluster Geographic Edition Infrastructure

The following `geoadm` command enables the Sun Cluster Geographic Edition control module on the local cluster.

```
# geoadm start
```

EXAMPLE 2 Disabling the Sun Cluster Geographic Edition Infrastructure

The following `geoadm` command removes the infrastructure resource groups that were created when you enabled the Sun Cluster Geographic Edition infrastructure.

```
# geoadm stop
```

EXAMPLE 3 Checking the Status of the Sun Cluster Geographic Edition Infrastructure

The following `geoadm` command displays whether the Sun Cluster Geographic Edition infrastructure is enabled on the local cluster and, if enable, the nodes on which the infrastructure is active.

```
# geoadm show
--- CLUSTER LEVEL INFORMATION ---
Sun Cluster Geographic Edition is active on:
node phys-paris-2, cluster cluster-paris
```

```
Command execution successful
```

```
#
```

EXAMPLE 4 Monitoring the Runtime Status of the Sun Cluster Geographic Edition Software

The following `geoadm` command displays the runtime status of the local Sun Cluster Geographic Edition enabled cluster.

```
# geoadm status
Cluster: cluster-paris

Partnership "paris-newyork-ps": OK
  Partner clusters      : cluster-newyork
  Synchronization      : OK
  ICRM Connection      :OK
```

EXAMPLE 4 Monitoring the Runtime Status of the Sun Cluster Geographic Edition Software
(Continued)

```

Heartbeat "paris-to-newyork" monitoring "cluster-newyork": OK
Heartbeat plug-in "ping_plugin"      : Inactive
Heartbeat plug-in "tcp_udp_plugin"   : OK

Protection group "tcpg"              : OK
Partnership                          : "paris-newyork-ps"
Synchronization                      : OK

Cluster cluster-paris                : OK
Role                                  : Primary
PG activation state                   : Activated
Configuration                         : OK
Data replication                      : OK
Resource groups                      : OK

Cluster cluster-newyork              : OK
Role                                  : Secondary
PG activation state                   : Activated
Configuration                         : OK
Data replication                      : OK
Resource groups                      : OK

Pending operations
Protection group "tcpg" : Start

```

Attributes See [attributes\(5\)](#) for descriptions of the following attributes.

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWscgctl
Interface Stability	Evolving

See Also [rbac\(5\)](#), [geohb\(1M\)](#), [geopg\(1M\)](#), [geops\(1M\)](#)

Name geohb– configure and manage the heartbeat mechanism

Synopsis `/usr/cluster/bin/geohb -?`
`/usr/cluster/bin/geohb -V`
`/usr/cluster/bin/geohb add-plugin pluginname heartbeatname`
`-p property [-p...]`
`/usr/cluster/bin/geohb create heartbeatname -r clusterlist`
`[-p property] [-p...]`
`/usr/cluster/bin/geohb delete heartbeatname`
`/usr/cluster/bin/geohb list heartbeatname ...`
`/usr/cluster/bin/geohb modify-plugin -p property`
`[-p...] pluginname heartbeatname`
`/usr/cluster/bin/geohb remove-plugin pluginname`
`heartbeatname`
`/usr/cluster/bin/geohb set-prop [-p property] [-p...]`
`heartbeatname ...`

Description The geohb command enables you to configure and manage the heartbeat mechanism.

A heartbeat is a monitor between two clusters: a requester cluster and a responder cluster. Creating a partnership establishes two heartbeats, one in each direction. For example, a partnership between a primary cluster, `cluster-paris`, and a secondary cluster, `cluster-newyork`, contains two heartbeats. One heartbeat has `cluster-paris` as the requester and `cluster-newyork` as the responder. The other heartbeat has `cluster-newyork` as the requester and `cluster-newyork` as the responder.

The Sun Cluster Geographic Edition software provides a default heartbeat mechanism that is based on the TCP/UDP plug-in as the primary plug-in and the ping plug-in as backup. The geohb command enables you to configure and maintain heartbeats. You can perform the following tasks:

- Configuring a heartbeat between clusters that participate in a partnership. Configuring a heartbeat includes the configuration of associated plug-ins.
- Creating or deleting a heartbeat property.
- Adding, modifying, and removing plug-ins that are associated with a heartbeat.
- Retrieving the current configuration of a heartbeat and its associated plug-ins.

Run the geohb command on a cluster that has been enabled for partnership.

To run the geohb command to configure and manage the heartbeat mechanism, you must be assigned the proper role-based access control (RBAC) rights profile.

If you have root access, you have permissions to perform any operation. If you do not have root access, the following RBAC rights apply:

- **Basic Solaris User.** You can read information about Sun Cluster Geographic Edition entities by running commands such as `geopg list`, `geohb list`, and `geops list`.
- **Geo Management.** You can perform all the read operations that someone with Basic Solaris User access can perform. You can also perform administrative and configuration tasks such as `geohb create`, `geopg switchover`, `geoadm start`, and `geoadm stop`.

For more information, see the `rbac(5)` man page and “Sun Cluster Geographic Edition Software and RBAC” in *Sun Cluster Geographic Edition System Administration Guide*.

The general form of this command is as follows:

```
geohb [subcommand] [options] [operands]
```

You can omit *subcommand* only if *options* specifies the option `-?`, `-o`, `-V`, or `-v`.

Each option of this command has a long form and a short form. Both forms of each option are given with the description of the option in the OPTIONS section of this man page.

Subcommands The following subcommands are supported:

`add-plugin`

Add a plug-in to an existing heartbeat. If you specify a custom plug-in, you must also specify the path to your custom plug-in command by using the `Query_cmd` property.

`create`

Create a heartbeat. You can monitor heartbeat status by running the `geoadm(1M)` command. You must configure the remote cluster to make the heartbeat operational.

Note – If you create a custom heartbeat, you must add at least one plug-in to prevent the partnership from remaining in degraded mode.

`delete`

Delete a heartbeat.

`list`

Display existing configuration information.

`modify-plugin`

Modify heartbeat plug-in properties.

`remove-plugin`

Remove a plug-in from a heartbeat.

`set-prop`

Modify heartbeat properties.

Options The following options are supported:

`-?`

`--help`

Displays help information. When this option is used, no other processing is performed.

You can specify this option without a subcommand or with a subcommand.

If you specify this option without a subcommand, the list of subcommands for this command is displayed.

If you specify this option with a subcommand, the usage options for the subcommand are displayed.

The question mark might be interpreted as a special character by some shells. Use quotes (-"?) or an escape character to avoid pattern matching.

-p *property*

--property *property*

Specifies the properties of a heartbeat or heartbeat plug-in.

A heartbeat property is assigned a value by using a *name=statement* pair. Multiple properties might be set at one time by using multiple statements.

The values for these properties are assigned at creation and tunable at runtime.

See the EXTENDED DESCRIPTION section for currently defined properties.

-r *clusterlist*

--remote-cluster *clusterlist*

Specifies the name of a remote cluster with which the local cluster should establish heartbeat monitoring.

-V

--version

Displays the version of the command.

Do not specify this option with subcommands, operands, or other options. The subcommands, operands, or other options are ignored. The -V option only displays the version of the command. No other operations are performed.

Operands The following operands are supported:

heartbeatname

Specifies an identifier for the heartbeat on the local cluster. If you are trying to create a new heartbeat, and the specified identifier already exists, the geohb create command fails.

pluginname

Specifies the name of the heartbeat plug-in.

Extended Description The following sections list the heartbeat and heartbeat plug-in properties.

Heartbeat Properties You can specify the following heartbeat property:

Query_interval

Specifies the frequency between heartbeat status requests in seconds. The plug-in enters emergency mode if three `Query_interval` periods pass without response. The plug-in times out and enters error mode if a further `Query_interval` period passes with no response.

Optional property.

Type: Integer.

Tuning recommendations: The value of this property is assigned at creation and tunable at runtime.

Default value: 120 seconds.

Heartbeat Plug-in Properties Heartbeat plug-in properties determine how a heartbeat functions.

Plugin_properties

Specifies a property string that is specific to the plug-in.

Optional property.

Type: String.

Tuning recommendations: The value of this property is assigned at creation and tunable at runtime.

Default value: None, except for heartbeats that use the default heartbeat plug-ins, `tcp_udp_plugin` and `ping_plugin`.

For the `tcp_udp_plugin` plug-in, the format of this string is predefined as *remote_IP_address/UDP/2084/ipsec,remote_IP_address/TCP/2084/ipsec*. The *remote_IP_address* argument specifies the IP address of the partner cluster. The optional */ipsec* string indicates that the plug-in uses IPsec.

For the `ping_plugin`, the format of this string is predefined as *remote_IP_address*, where *remote_IP_address* specifies the IP address of the partner cluster.

Query_cmd

Specifies the path to the command for a heartbeat status request.

Required property if the plug-in does not specify a predefined plug-in.

Type: String.

Tuning recommendations: The value of this property is assigned at creation and tunable at runtime.

Default value: None.

Requester_agent

Specifies the absolute path to requester agent.

Optional property.

Type: String.

Tuning recommendations: The value of this property for the default plug-in should not be tuned except for testing purposes.

Default value: None.

Responder_agent

Specifies the absolute path to the responder agent.

Optional property.

Type: String.

Tuning recommendations: The value of this property for the default plug-in should not be tuned except for testing purposes.

Default value: None.

Type

Specifies the type of plug-in. Set to either `Primary` or `Backup`.

Required property.

Type: Enum.

Tuning recommendations: The value of this property is assigned at creation and tunable at runtime.

Default value: None, except for heartbeats with default heartbeat name `ping_plugin`. In this case, the default value is `Backup`.

Exit Status The following exit values are returned:

<code>0</code>	The command completed successfully, indicating that the remote cluster is alive.
<code>nonzero</code>	An error has occurred, meaning that the remote cluster did not respond to the heartbeat check.

Examples **EXAMPLE 1** Creating a Heartbeat

The following `geohb` command creates a heartbeat that is named `paris-to-newyork`, which communicates between the local cluster and the cluster `cluster-newyork`.

```
# geohb create paris-to-newyork -r cluster-newyork
```

EXAMPLE 2 Creating a Heartbeat Plug-in

The following `geohb` command creates a heartbeat plug-in that is named `command1` for the heartbeat `paris-to-newyork`.

```
# geohb add-plugin command1 paris-to-newyork -p Query_cmd=/usr/bin/hb/
```

EXAMPLE 3 Modifying a Heartbeat

The following `geohb` command modifies the properties for the default heartbeat between `cluster-paris` and `cluster-newyork`.

```
# geohb set-prop -p Query_interval=60 hb_cluster-paris~cluster-newyork
```

EXAMPLE 4 Modifying a Heartbeat Plug-in

The following `geohb` command modifies the properties of the default TCP/UDP plug-in, `tcp_udp_plugin`, to use only TCP.

```
# geohb modify-plugin -p Plugin_properties=paris-cluster/TCP/2084 \
tcp_udp_plugin hb_cluster-paris~cluster-newyork
```

EXAMPLE 5 Deleting a Plug-in From a Heartbeat

The following `geohb` command deletes the plug-in that is named `command1`, from the heartbeat that is named `paris-to-newyork`.

```
# geohb remove-plugin command1 paris-to-newyork
```

Attributes See [attributes\(5\)](#) for descriptions of the following attributes.

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWscgctl
Interface Stability	Evolving

See Also [rbac\(5\)](#), [geops\(1M\)](#)

Name geopg– create or manage protection groups

Synopsis /usr/cluster/bin/geopg -?
 /usr/cluster/bin/geopg -V
 /usr/cluster/bin/geopg add-device-group -p *property* [-p...]
devicegroupname protectiongroupname
 /usr/cluster/bin/geopg add-replication-component -p *property* [-p...]
configurationname protectiongroupname
 /usr/cluster/bin/geopg add-resource-group *resourcegroup*
 [,*resourcegroup*...] *protectiongroupname*
 /usr/cluster/bin/geopg create *protectiongroupname*
 -s *partnershipname* -o *localrole* [-d *datareplicationtype*]
 [-p *property*] [-p...]
 /usr/cluster/bin/geopg delete *protectiongroupname*
 /usr/cluster/bin/geopg get [*protectiongroupname*]
 -s *partnershipname*
 /usr/cluster/bin/geopg list [*protectiongroupname*]
 [...]
 /usr/cluster/bin/geopg modify-device-group *devicegroupname*
protectiongroupname -p *property* [-p...]
 /usr/cluster/bin/geopg modify-replication-component *configurationname*
protectiongroupname -p *property* [-p...]
 /usr/cluster/bin/geopg remove-device-group *devicegroupname*
protectiongroupname
 /usr/cluster/bin/geopg remove-replication-component *configurationname*
protectiongroupname
 /usr/cluster/bin/geopg remove-resource-group *resourcegroup*
 [,*resourcegroup*...] *protectiongroupname*
 /usr/cluster/bin/geopg set-prop *protectiongroupname*
 -p *property* [-p...]
 /usr/cluster/bin/geopg start *protectiongroupname*
 -e [[*local*] | [*global*]] [-n]
 /usr/cluster/bin/geopg stop *protectiongroupname*
 -e [[*local*] | [*global*]] [-D]
 /usr/cluster/bin/geopg switchover -m *newprimaryclustername*
protectiongroupname [-f]
 /usr/cluster/bin/geopg takeover [-f] *protectiongroupname*
 /usr/cluster/bin/geopg update *protectiongroupname*

```
/usr/cluster/bin/geopg validate protectiongroupname
```

Description The `geopg` command enables you to configure and maintain protection groups. You can perform the following tasks:

- Configure a protection group between clusters that participate in a partnership. This task includes the configuration of associated data replication parameters.
- Add or remove resource groups and data-replication disk device groups.
- Add, modify, and remove data replication parameters that are associated with a protection group property.
- Retrieve the current configuration of a specific protection group or all defined protection groups.
- Activate a protection group.
- Deactivate a protection group.
- Switch over the role of a protection group.
- Take over the primary role of a protection group.

Before you create a protection group, ensure that the clusters that will host the protection group are already placed in a partnership.

To run the `geopg` command to create, modify, or delete a protection group, or a data-replication disk device group, you must be assigned the proper role-based access control (RBAC) rights profile.

If you have root access, you have permission to perform any operation. If you do not have root access, the following RBAC rights apply:

- **Basic Solaris User.** You can read information about Sun Cluster Geographic Edition entities by running commands such as `geopg list`, `geohb list`, and `geops list`.
- **Geo Management.** You can perform all the read operations that someone with Basic Solaris User access can perform. You can use commands `geohb create`, `geopg switchover`, `geoadm start`, and `geoadm stop` to perform administrative and configuration operations.

For more information, see the `rbac(5)` man page and “Sun Cluster Geographic Edition Software and RBAC” in *Sun Cluster Geographic Edition System Administration Guide*.

The general form of this command is as follows:

```
geopg [subcommand] [options] [operands]
```

You can omit *subcommand* only if *options* specifies the option `-?`, `-o`, `-V`, or `-v`.

Each option of this command has a long form and a short form. Both forms of each option are given with the description of the option in the OPTIONS section of this man page.

How Protection Groups Start

The `geopg start` command activates the protection group on both the primary and standby clusters. This activation starts the Sun Cluster Geographic Edition management of the resource groups in the protection group. Depending on the form of the command that you use and on the cluster where you issue the command, activating the protection group might not start the resource groups on that cluster. The resource groups start, or are brought online, only on the primary cluster.

The `-e` option defines the scope of the `geopg start` command. If you specify `-e local`, the `geopg start` command runs on the cluster where you issue the command. If you specify `-e global`, the `geopg start` command runs on both clusters in the partnership.

The different forms of the command have the following effects:

- If you run the `geopg start -e local` command on the primary cluster, and if you run the `geopg start -e global` command on either cluster, the Sun Cluster Geographic Edition software activates the protection group on both clusters in the partnership. The software brings online resource groups on the primary cluster only. The resource groups are put in a managed state.
- If you run the `geopg start -e local` command on the standby cluster, the Sun Cluster Geographic Edition software activates the protection group on the standby cluster only. Resource groups are not started on the standby cluster. The resource groups are put in the Unmanaged state.

Subcommands The following subcommands are supported:

`add-device-group`

Enables a data-replication disk device group to be part of a protection group.

`add-replication-component`

Adds a configuration to a protection group on the local cluster and propagates the new configuration to the partner cluster if the partner cluster contains a protection group of the same name.

`add-resource-group`

Enables an application resource group to be part of a protection group.

If a protection group is active when you add a resource group, the resource group must be in either the `Unmanaged` or `Online` state. To start an unmanaged resource group, run the `geopg start` command.

If a protection group is inactive, the resource group must be in the `Unmanaged` state when you add the resource group. If the resource group is offline, bring the resource group to the `Unmanaged` state before adding the resource group to an inactive protection group.

`create`

Creates a protection group within an existing partnership.

When you create a protection group, the management module updates the local configuration and notifies remote clusters of configuration changes.

delete

Deletes a protection group.

get

Creates the local configuration for a protection group that already exists on the remote partner cluster by retrieving the configuration from the partner cluster. If you do not specify a protection group name, all the protection groups that have been configured for the partnership on the remote cluster will be created on the local cluster.

list

Displays the following information about the protection group:

- Defined protection groups
- Resource groups that are wrapped into protection groups
- Operation status information

If you do not specify the name of a protection group, the `list` subcommand displays information for all the protection groups configured on the local cluster.

modify-device-group

Modifies the properties of a data-replication disk device group.

modify-replication-component

Modifies a configuration in a protection group on the local cluster and propagates the modified configuration to the partner cluster if the partner cluster contains a protection group of the same name.

remove-device-group

Removes data-replication disk device groups from a protection group.

Removing a data-replication device group does not stop data replication or change the data-replication status for that data-replication device group.

remove-replication-component

Removes a configuration from a protection group on the local cluster. This subcommand also removes a configuration from the partner cluster if the partner cluster contains a protection group of the same name.

remove-resource-group

Removes resource groups from a protection group.

Removing an application resource group does not change the application resource group to the Unmanaged state.

set-prop

Modifies the properties of a protection group.

start

Starts a protection group. When you start a protection group, the role of the protection group on a cluster is the role that was assigned to the protection group when you created the protection group.

The `start` subcommand uses Sun Cluster commands to bring resources and resource groups under the management of the protection group.

You can start a protection group on the following levels:

- On all clusters where the protection group has been configured
- On either the primary cluster or standby cluster

For more details about activating a protection group and the effects on the resource groups in that protection group, see “How Protection Groups Start” in the DESCRIPTION section of this man page.

Starting a protection group enables the following events to occur:

- The protection group configuration is validated.
- Clusters can determine whether an operation has been completed.
- Data replication can be started, depending on the data replication that you use.
 - When using Sun StorageTek Availability Suite software, you can start data replication from the primary cluster only.
 - When using Hitachi TrueCopy or EMC Symmetrix Remote Data Facility (SRDF) software, you can start data replication from either the primary or standby cluster.
 - When using the Oracle Data Guard software, you can start data replication from the primary cluster by using the local or the global scope.

For all supported data replication software, you must not specify the `-n` option when using this form of the command.

- Protected applications can be started.
- If the partner can be reached, the partner cluster can be notified of the protection group activation.

Note – Protection groups that are referred to as “online” are active protection groups.

stop

Stops a protection group. You can stop a protection group on the following levels:

- On all clusters where the protection group has been configured
- On either the primary or standby cluster

Stopping a protection group enables the following events to occur:

- The protection group becomes inactive.
- Depending on the data replication that you are using, data replication stops. If you are using data replication other than Oracle Data Guard, you can prevent data replication from stopping by taking the resource group out of the protection group before stopping the protection group.
 - When using Sun StorageTek Availability Suite software, you can stop data replication from the primary cluster only.

- When using Hitachi TrueCopy or EMC Symmetrix Remote Data Facility (SRDF) software, you can stop data replication from either the primary or standby cluster.
- When using Oracle Data Guard, you can stop data replication from either the primary or standby cluster, by using either the local or the global scope.
- Protected applications stop.
- If the partner cluster is reachable, the partner cluster is notified that the protection group has been stopped.

switchover

Switches the assigned role of a cluster in the protection group. You must start the protection group before you can perform a switchover.

takeover

Forces a cluster to become the primary cluster without considering the partner cluster state.

If you issue a takeover from the standby cluster and the cluster is able to communicate with the partner cluster, the Sun Cluster Geographic Edition software switches the role of the partner cluster so that the partner cluster becomes the new standby. This operation is not the same as a switchover. The protection group is deactivated on the new standby.

After the `geopg takeover` command successfully completes, reactivating the protection group on the standby cluster might require that you recover and synchronize data.

Note – When possible, run the `geopg switchover` command instead of the `geopg takeover` command to coordinate between partner clusters to avoid loss of replicated data.

Run the `geopg takeover` command only in situations when the primary cluster is not available or during unplanned downtime. The situation must justify a potential loss of data and the time required to repair and to reactivate the protection group on the standby cluster.

update

Resynchronizes the configuration information of the local protection group with the partner's configuration information. The `geopg update` command overwrites the configuration information of the protection group on the local cluster with the configuration information from the partner cluster. This command does not overwrite replicated data.

validate

Validates a protection group on the local cluster by performing a sanity check of the dynamic values.

Options The following options are supported:

- ?

--help

Displays help information. When this option is used, no other processing is performed.

You can specify this option with or without a subcommand.

If you specify this option without a subcommand, the list of subcommands for this command is displayed.

If you specify this option with a subcommand, the usage options for the subcommand are displayed.

The question mark might be interpreted as a special character by some shells. Use quotes ("-?") or an escape character to avoid pattern matching.

-D

--only-datarep

Specifies that only the data replication should be deactivated, leaving the protection group active. If you do not use this option, the entire protection group is deactivated. To stop a protection group that has already had its data replication subsystem stopped, you must run the `geopg stop` command again and omit this option.

-d *datareplicationtype*

--datarep-type *datareplicationtype*

Specifies the data replication mechanism for data replication between the clusters of the protection group.

The *datareplicationtype* must be one of the following strings:

avs	Specifies that the data replication mechanism is Sun StorageTek Availability Suite Remote Mirror, with patches.
odg	Specifies that the data replication mechanism is Oracle Data Guard.
srdf	Specifies that the data replication mechanism is the dynamic EMC Symmetrix Remote Data Facility (SRDF).
truecopy	Specifies that the data replication mechanism is Hitachi TrueCopy.

-e local|global

--scope local|global

Specifies whether the command operates only on the local cluster, `local`, or on both clusters, `global`, where the protection group has been configured.

-f

--force

Forces the command to perform the operation without asking you for confirmation.

-m *newprimarycluster*

--primary *newprimarycluster*

Specifies the name of the cluster that is to be the new primary cluster for the protection group.

-n

--nodatarep

This option is only valid when starting a protection group that is not active. If the protection group is not active, it is started without data replication. If data replication for this protection group is already running independently, it is stopped before the protection group is started.

If the protection group is already active with data replication enabled, data replication is not stopped. An error message is displayed that states that the `geopg stop -D` command should be used to stop data replication for an active protection group.

If this option is omitted, data replication starts at the same time as the protection group.

`-o localrole`

`--role localrole`

Specifies the role of the local cluster as either `primary` or `secondary` when used with the `create` subcommand. You can change the role of a cluster by running the `geopg switchover` command.

`-p property`

`--property property`

Sets the properties of a protection group.

A protection group property is assigned a value by using a `name=statement` pair statement. You can set multiple properties at one time by using multiple statements.

See the EXTENDED DESCRIPTION section for defined properties.

`-s partnershipname`

`--partnership partnershipname`

Specifies the name of the existing partnership where the protection group is configured.

`-V`

`--version`

Displays the version of the command.

Do not specify this option with subcommands, operands, or other options, as they are ignored. The `-V` option only displays the version of the command. No other operations are performed.

Operands The following operands are supported:

configurationname

Specifies the name of any device group or replicated component that you want to add.

devicegroupname

Specifies the name of the disk device group to be created or added to the protection group.

protectiongroupname

Specifies the name of the protection group. The `create` subcommand fails if the protection group that you specify with this option already exists. The `modify` subcommand fails if the specified protection group is not valid.

resourcegroupname

Specifies a comma-separated list of resource groups to add to or delete from the protection group. The specified resource groups must already be defined.

If a protection group is active when you add a resource group, the resource group must be in either the `Unmanaged` or `Online` state. To start an unmanaged resource group, run the `geopg start` command.

If the protection group is inactive when you add a resource group, the resource group must be in the `Unmanaged` state before you add the resource group.

Extended Description

This section contains descriptions of properties that you can specify.

Note – Property values, such as `true` and `false`, are *not* case sensitive.

General Protection Group Properties

Description (string)

Describes the protection group.

Category:

Optional

Default:

None

Tunable:

Assigned at creation and tunable at runtime

External_Dependency_Allowed (boolean)

Specifies whether to allow any dependencies between resource groups and resources that belong to this protection group and resource groups and resources that do not belong to this protection group.

Category:

Optional

Default:

False

Tunable:

Any time

RoleChange_ActionArgs (string)

Specifies the arguments that follow the system-defined arguments that are paired with the role change callback script during a protection group switchover or takeover.

Category:

Optional

Default:

None

Tunable:

Assigned at creation and tunable at runtime

RoleChange_ActionCmd (string)

Specifies the absolute path to the executable file to run when the primary cluster of the protection group changes. This file should exist on all nodes of both partner clusters that host the protection group. This script is run before the application resource group is brought online on the new primary cluster.

Category:

Optional

Default:

None

Tunable:

Assigned at creation and tunable at runtime

Timeout (integer, but you must specify a value equal to or greater than 20)

Specifies, in seconds, the longest time that the Sun Cluster Geographic Edition software waits for a response after running a `geopg` command. Examples of responses include `start`, `stop`, `switchover`, and `takeover`. If the command does not return within the `timeout` period, the Sun Cluster Geographic Edition software reports the operation as timed out, even if the underlying command that was run eventually completes successfully.

The `timeout` period applies to operations on a per-cluster basis. An operation with a local scope times out if the operation is not completed after the specified `timeout` period.

An operation with a global scope consists of an action on the local cluster and an action on the remote cluster. The local and remote actions are timed separately. So, an operation with a global scope times out if the local operation is not completed after the specified `timeout` period or if the remote operation is not completed after the specified `timeout` period.

For example, the following command is started with a local scope:

```
# geopg start -e local protectiongroupname
```

If you set the `timeout` property 3000 seconds, the `geopg start` command times out if the operation does not complete after 3000 seconds.

You can start the same command with a global scope as follows:

```
# geopg start -e global protectiongroupname
```

If the `timeout` property is set to 3000 seconds, the `geopg start` command times out if the operation is not completed on the local cluster after 3000 seconds or if the operation is not completed on the remote cluster after 3000 seconds. If the local action takes 1500 seconds and the remote action takes 1500 seconds, the operation is not timed out.

The protection group `timeout` value is an estimated value that is applied to some sub-operations. The `timeout` value does not apply to the entire operation, so not every operation on a protection group is timed against the `timeout` period. For example, the time taken to initialize the data structure and to check for the precondition of the operation are not timed in the `timeout` period.

You can specify a maximum of 1,000,000 (one million) seconds for the `timeout` property.

Category:

Optional

Default:

3600

Tunable:

Assigned at creation and tunable at runtime

Sun StorageTek
Availability Suite Data
Replication Type
Properties

Device group property: `Enable_volume_set` (boolean)

Defines whether the volume sets that are defined in the `/var/cluster/geo/avs/AVS-devicegroup-volset.ini` file are to be enabled by Sun Cluster Geographic Edition. You can set this property to `True` or `False`.

If the `enable_volume_set` property is set to `True`, volume sets defined in the `/var/cluster/geo/avs/AVS-devicegroup-volset.ini` file are enabled when the device group is added to the protection group or when the protection group that contains the device group is replicated from the partner cluster. Any volume sets of that device group that are not defined in the file are disabled. The `/var/cluster/geo/avs/AVS-devicegroup-volset.ini` file must exist on every node of the primary and standby cluster.

If the `Enable_volume_set` property is set to `False`, you must manually enable volume sets by using the Sun StorageTek Availability Suite commands.

The parameters in the volume set file that are handled by the Sun Cluster Geographic Edition software are described in the following table.

Note – The Sun Cluster Geographic Edition software does not handle other parameters of the volume set file, such as disk queue, size of memory queue, and number of asynchronous threads. You must adjust these parameters manually by using Sun StorageTek Availability Suite commands.

Parameter	Meaning	Description
<code>phost</code>	Primary host	The logical host of the server on which the primary volume resides.
<code>pdev</code>	Primary device	Primary volume partition. Specify full path names only.

pbitmap	Primary bitmap	Volume partition in which the bitmap of the primary partition is stored. Specify full path names only.
shost	Secondary host	The logical host of the server on which the secondary volume resides.
sdev	Secondary device	Secondary volume partition. Specify full path names only.
sbitmap	Secondary bitmap	Volume partition in which the bitmap of the secondary partition is stored. Specify full path names only.
ip	Network transfer protocol	IP address.
sync async	Operating mode	In sync mode the I/O operation is confirmed as complete only when the volume on the standby cluster has been updated. In async mode the primary host I/O operation is confirmed as complete before updating the volumes on the standby clusters.
g iogroupname	I/O group name	An I/O group name. The set must be configured in the same I/O group on both the primary and standby clusters. This parameter is optional and need only be configured if you have an I/O group.
C devicegroupname	Device group name	The device group name or resource tag of the local data and bitmap volumes in cases where this information is not implied by the name of the volume. For example, /dev/md/avsdg/rdisk/vol or /dev/vx/rdisk/avsdg/vol indicates a device group named avsdg. It can be Solaris Volume Manager volumes, Veritas Volume Manager volumes, or raw device volumes.

Category:

Optional

Default:

False

Tunable:

Until you add the device group to a protection group

Device group property: Local_logical_host (string)

Defines the local logical host name that is used for the replication of the disk device group. Do not use an underscore character (_) in the logical host name.

Category:

Required

Default:

None

Tunable:

Until you add the device group to a protection group

Data replication property: `NodeList` (stringarray)

Lists the host names of the machines that can be primary for the replication mechanism. You can specify more than one host name by separating each host name with a comma.

Category:

Optional

Default:

All nodes in the cluster

Tunable:

Only when the protection group is inactive

Device group property: `Remote_logical_host` (string)

Specifies the remote logical host name that is used for the replication of the disk device group.

Category:

Required

Default:

None

Tunable:

Until you add the device group to a protection group

EMC Symmetrix
Remote Data Facility
Data Replication Type
Properties

Data replication property: `Cluster_dgs` (stringarray)

Lists the disk device groups where the data is written. You can specify more than one disk group by separating each disk group with a comma.

Category:

Optional

Default:

Empty

Tunable:

Only when the protection group is inactive on both partner clusters

Data replication property: `DG_or_CG` (string)

Specifies the device group identifier as “SRDF Device Group.” You must set this property to DG.

Category:

Optional

Default:

DG

Tunable:

Never

Data replication property: `NodeList` (stringarray)

Lists the host names of the machines that can be primary for the replication mechanism. This list is comma delimited.

Category:

Optional

Default:

Empty

Tunable:

Any time

Data replication property: `R1_SID` (integer)

Specifies the Symmetrix Remote Data Facility (SRDF) identification of the primary devices.

Note – If you do not specify a value for this property when you add a device group, the Sun Cluster Geographic Edition software searches for the value and sets the property automatically.

Category:

Required

Default:

None, until you add a Symmetrix Remote Data Facility (SRDF) device group

Tunable:

Any time

Data replication property: `R2_SID` (integer)

Specifies the Symmetrix Remote Data Facility (SRDF) identification of the secondary devices.

Note – If you do not specify a value for this property when you add a device group, the Sun Cluster Geographic Edition software searches for the value and sets the property automatically.

Category:

Required

Default:

None, until you add a Symmetrix Remote Data Facility (SRDF) device group

Tunable:

Any time

Hitachi TrueCopy Data Replication Type Properties Data replication property: `Cluster_dgs` (stringarray)

Lists the disk device groups where the data is written. The list is comma delimited.

Category:

Optional

Default:

Empty

Tunable:

Only when the protection group is inactive on both partner clusters

Device group property: `Fence_level` (enum)

Defines the fence level that is used by the disk device group. The fence level determines the level of consistency among the primary and secondary volumes for that disk device group. Possible values are `data`, `status`, `never`, and `async`.

You can set this property to any valid `Fence_level` when the current pair state is `SMPL`.

Caution – If contact with the remote storage box is lost for any reason, to ensure that an application that is running on the primary cluster is not blocked, specify a `Fence_level` of `never` or `async`. If you specify a `Fence_level` of `data` or `status`, the primary storage box refuses updates if the updates cannot be copied to the remote storage box.

Category:

Required

Default:

None

Tunable:

Only when the protection group is inactive

Data replication property: `Nodelist` (stringarray)

Lists the host names of the machines that can be primary for the replication mechanism. This list is comma delimited.

Category:

Optional

Default:

Empty

Tunable:

Any time

Oracle Data Guard Data
Replication Type
Properties

Data replication property: `local_database_name` (string)

Name of the local Oracle database in the Oracle Data Guard Broker configuration that is being replicated to the remote cluster. This name is the Oracle `db_unique_name` initialization parameter for the Oracle RAC database on the local cluster.

Category:

Required

Default:

None

Tunable:

At creation

Data replication property: `local_db_service_name` (string)

Oracle net service name that is used to connect to the local Oracle database.

Category:

Required

Default:

None

Tunable:

Any time

Data replication property: `local_rac_proxy_svr_rg_name` (string)

Name of the local Oracle RAC server proxy resource group that manages the local database in the Oracle Data Guard Broker configuration.

Category:

Required

Default:

None

Tunable:

At creation

Data replication property: `remote_database_name` (string)Name of the remote database in the Oracle Data Guard Broker configuration that is being replicated from the local cluster. This name is the Oracle `db_unique_name` initialization parameter for the Oracle RAC database on the remote cluster.**Category:**

Required

Default:

None

Tunable:

At creation

Data replication property: `remote_db_service_name` (string)

Oracle net service name that is used to connect to the remote Oracle database.

Category:

Required

Default:

None

Tunable:

Any time

Data replication property: `remote_rac_proxy_svr_rg_name` (string)

Name of the remote Oracle RAC server proxy resource group on the partner cluster that manages the remote database in the Oracle Data Guard Broker configuration.

Category:

Required

Default:

None

Tunable:

At creation

Data replication property: `replication_mode` (string)

The Oracle Data Guard replication mode between the primary database and the standby database.

Valid values to which you set this property include `maxAvailability`, `maxPerformance`, and `maxProtection`.

Category:

Required

Default:

None

Tunable:

Any time

Data replication property: `standby_type` (string)

Type of Oracle standby database that is used in the Oracle Data Guard Broker configuration.

Valid values to which you set this property include `logical` and `physical`.

Category:

Required

Default:

None

Tunable:

At creation

Data replication property: `sysdba_password` (string)

Password for the Oracle SYSDBA privileged database user.

Do not specify a password on the command line. If you specify only

`-p sysdba_password=`, the `geopg` command prompts you to type an actual password, which is not displayed as you type it.

Category:
Required

Default:
None

Tunable:
Any time

Data replication property: `sysdba_username` (string)
Name of an Oracle SYSDBA privileged database user who can perform the Oracle Data Guard Broker switchover and takeover operations on both the primary and standby clusters. The Sun Cluster Geographic Edition software uses this property to monitor and manage the Oracle Data Guard Broker configurations.

Category:
Required

Default:
None

Tunable:
Any time

Exit Status The following exit values are returned:

0	The command completed successfully.
nonzero	An error occurred.

Examples EXAMPLE 1 Adding an Oracle Data Guard Broker Configuration to a Protection Group

The following `geopg` command adds the Oracle Data Guard Broker configuration `mysales.com` to the protection group `sales-pg`.

To ensure security, do *not* supply a password when you specify the `sysdba_password` property. If you do not provide a password, the `geopg` command prompts for one.

```
phys-paris-1# geopg add-replication-component \  
-p local_database_name=sales \  
-p remote_database_name=salesdr \  
-p local_db_service_name=sales-svc \  
-p remote_db_service_name=salesdr-svc \  
-p standby_type=physical \  
-p replication_mode=MaxPerformance \  
-p sysdba_username=sys \  
-p sysdba_password= \  
-p local_rac_proxy_svr_rg_name=sales-rac-proxy-svr-rg \  
-p remote_rac_proxy_svr_rg_name=salesdr-rac-proxy-svr-rg \  
mysales.com sales-pg
```


EXAMPLE 1 Adding an Oracle Data Guard Broker Configuration to a Protection Group *(Continued)*

Oracle Data Guard configuration "mysales.com" successfully added to the protection group "sales-pg"

EXAMPLE 2 Creating a Protection Group That Uses Data Replication

The following geopg command creates a Sun StorageTek Availability Suite protection group on the primary cluster cluster-paris.

```
# geopg create -s paris-newyork-ps -d avs -o primary \
  -p Nodelist=phys-paris-1,phys-paris-2 avspg
```

EXAMPLE 3 Creating a Protection Group That Does Not Use Data Replication

The following geopg command creates a protection group that is not configured to use data replication.

```
# geopg create -s paris-newyork-ps -o primary example-pg
```

EXAMPLE 4 Deleting a Protection Group While Keeping Application Resource Groups Online

The following geopg command keeps two application resource groups, apprg1 and apprg2, online while deleting their protection group, avspg. Remove the application resource groups from the protection group, then delete the protection group.

```
# geopg remove-resource-group apprg1,apprg2 avspg
# geopg stop -e global avspg
# geopg delete avspg
```

EXAMPLE 5 Modifying a Protection Group

The following geopg command modifies the timeout property of the protection group avspg.

```
# geopg set-prop -p Timeout=3000 avspg
```

EXAMPLE 6 Adding a Data Replication Device Group to a Sun StorageTek Availability Suite Protection Group

The following geopg command creates a Sun StorageTek Availability Suite data replication device group in the avspg protection group.

```
# geopg add-device-group -p Local_logical_host=lh-paris-1 \
  -p Remote_logical_host=lh-newyork-1 -p Enable_volume_set=True avsdg avspg
```

EXAMPLE 6 Adding a Data Replication Device Group to a Sun StorageTek Availability Suite Protection Group (Continued)

If the command returns successfully, volume sets that are defined in the `/var/cluster/geo/avs/avsdg-volset.ini` file are enabled. The file might look like this for a Solaris Volume Manager device group.

```
lh-paris-1 /dev/md/avsdg/rdisk/d100 /dev/md/avsdg/rdisk/d101
lh-newyork-1 /dev/md/avsdg/rdisk/d100 /dev/md/avsdg/rdisk/d101
ip async C avsdg
```

The description of the parameters is as follows:

- `lhparis-1` — Primary host
- `/dev/md/avsdg/rdisk/d100` — Primary data
- `/dev/md/avsdg/rdisk/d101` — Primary bitmap
- `lh-newyork-1` — Secondary host
- `/dev/md/avsdg/rdisk/d100` — Secondary data
- `/dev/md/avsdg/rdisk/d101` — Secondary bitmap
- `ip` — Protocol
- `async` — Mode
- `C` — C tag
- `avsdg` — Device group

Attributes See [attributes\(5\)](#) for descriptions of the following attributes.

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWscgctl
Interface Stability	Evolving

See Also [geoadm\(1M\)](#), [geohb\(1M\)](#), [geops\(1M\)](#), [rbac\(5\)](#)

Name geops– create, configure, and manage partnerships between clusters

Synopsis /usr/cluster/bin/geops [*subcommand*] -?
 /usr/cluster/bin/geops -V
 /usr/cluster/bin/geops add-trust -c *remotepartnerclustername*
 /usr/cluster/bin/geops create -c *remotepartnerclustername*
partnershipname [-h *heartbeatname*] [-p *property* [,...]]
 /usr/cluster/bin/geops join-partnership *remoteclustername*
partnershipname [-h *heartbeatname*]
 /usr/cluster/bin/geops leave-partnership *partnershipname*
 /usr/cluster/bin/geops list *partnershipname*
 /usr/cluster/bin/geops remove-trust -c *remotepartnerclustername*
 /usr/cluster/bin/geops set-prop *partnershipname*
 -p *property* [,...]
 /usr/cluster/bin/geops update *partnershipname*
 /usr/cluster/bin/geops verify-trust [-c *remotepartnerclustername*]

Description The geops command enables you to create, configure, and manage the partnerships that are defined between clusters. A partnership is a pair of clusters that define a cluster infrastructure on which an application might be protected against disaster.

Two clusters must be configured to trust each other before you create a partnership between two clusters.

A partnership requires a running heartbeat between clusters. Partner clusters monitor each other with heartbeats.

The Sun Cluster Geographic Edition software notifies all remote partners of changes in the partnership configuration.

Run the geops command on a cluster that has been enabled for partnership.

To run the geops command to create, configure, and manage the partnerships, you must be assigned the proper role-based access control (RBAC) rights profile.

If you have root access, you have permissions to perform any operation. If you do not have root access, the following RBAC rights apply:

- **Basic Solaris User.** You can read information about Sun Cluster Geographic Edition entities by running commands such as `geopg list`, `geohb list`, and `geops list`.
- **Geo Management.** You can perform all the read operations that someone with Basic Solaris User access can perform. You can also perform administrative and configuration tasks such as `geohb create`, `geopg switchover`, `geoadm start`, and `geoadm stop`.

Note – You must have root access to run the following subcommands:

- `geops add-trust`
- `geops remove-trust`
- `geops verify-trust`

For more information, see the [rbac\(5\)](#) man page and “Sun Cluster Geographic Edition Software and RBAC” in *Sun Cluster Geographic Edition System Administration Guide*.

The general form of this command is as follows:

```
geops [subcommand] [options] [operands]
```

You can omit *subcommand* only if *options* specifies the option `-?`, `-o`, `-V`, or `-v`.

Each option of this command has a long form and a short form. Both forms of each option are given with the description of the option in the OPTIONS section of this man page.

Subcommands The following subcommands are supported:

`add-trust`

Retrieve public keys of a remote cluster and add the keys to the `truststore` file on every node of the local cluster. The `truststore` file is at `/etc/cacao/instances/default/security/jsse/truststore`.

The new key is not added to the `truststore` file if an entry with the same alias already exists in the `truststore` file on a node. If the existing entry contains a key that is different from the new key, you must delete the entry from the `truststore` file before you add the new key.

`create`

Create a partnership between the local cluster and a remote cluster. The two clusters must be configured to trust each other.

`join-partnership`

Enable the local cluster to join an existing partnership.

Running the `geops join-partnership` command on a cluster that is already a member of a partnership causes the partnership configuration from the remote cluster to overwrite the partnership configuration of the local cluster.

`leave-partnership`

Remove the local cluster from a partnership. This subcommand deletes the partnership when the last participating cluster in the partnership leaves.

`list`

Display partnership configuration information.

remove - trust

Remove all keys for the remote cluster from the `truststore` file on the local node. You must remove all keys for the remote cluster from the local host before you can add a new key.

To remove a key from a cluster, dissolve the partnership between the two clusters (by running `geops leave` on each cluster) and run the `remove - trust` subcommand from each node of the cluster.

set - prop

Modify the properties of a partnership. This subcommand updates the local cluster configuration and notifies remote partner clusters of the configuration change.

update

Synchronize information with the partner cluster. The `geops update` command overwrites the configuration on the local cluster with the configuration from the remote partner cluster.

This subcommand cannot update a partnership while the cluster is disconnected from the partner cluster.

If the remote partner cluster is down, modifications to the local cluster might not be propagated to the remote partner cluster.

verify - trust

Retrieve node information on the remote cluster and establish a secure Java Management Extensions (JMX) connection from the local host to every node of the remote cluster. The `verify - trust` subcommand verifies that the certificates have been exchanged properly between the remote and the local clusters.

If you do not specify a remote cluster, the `verify - trust` subcommand verifies the connections between the local host and other nodes of the local cluster.

Options The following options are supported:

`- ?`

`-- help`

Displays help information. When this option is used, no other processing is performed.

You can specify this option without a subcommand or with a subcommand.

If you specify this option without a subcommand, the list of subcommands for this command is displayed.

If you specify this option with a subcommand, the usage options for the subcommand are displayed.

The question mark might be interpreted as a special character by some shells. Use quotes (`- "?"`) or an escape character to avoid pattern matching.

-c remoteclustername

--cluster remoteclustername

Specifies the logical hostname of the cluster with which to form a partnership. The logical hostname is used by the Sun Cluster Geographic Edition software and maps to the name of the remote partner cluster. For example, a remote partner cluster name might resemble the following:

```
cluster-paris
```

When you use this option with the `add-trust`, `remote-trust`, or `verify-trust` subcommand, the option specifies the alias where the public keys on the remote cluster are stored. An alias for certificates on the remote cluster must have the following pattern:

```
remotepartnercluster.certificate[0-9]*
```

Keys and only keys that belong to the remote cluster should have their alias match this pattern.

Note – The `remove-trust` subcommand removes only keys you have added with the `add-trust` subcommand, and keys with an alias that matches the following pattern:

```
remotepartnercluster.certificate[0-9]*.
```

-h heartbeatname

--heartbeat-name heartbeatname

Specifies an identifier for the heartbeat on a partner cluster that the local cluster can use to monitor partner availability. You must create the heartbeat by running the `geohb` command before you specify the heartbeat in the `geops` command.

If this option is omitted, the Sun Cluster Geographic Edition software uses the default heartbeat mechanism between member clusters.

-p property

--property property

Specifies the value of partnership properties. You can specify multiple properties at one time by using multiple statements.

See the EXTENDED DESCRIPTION section for a description of the properties.

-V

--version

Displays the version of the command.

Do not specify this option with subcommands, operands, or other options. The subcommands, operands, or other options are ignored. The `-V` option only displays the version of the command. No other operations are performed.

Operands The following operand is supported:

partnershipname Specifies the name of the partnership

Extended Description The following section lists the partnership properties. These properties are set at creation and tunable at runtime.

Partnership Properties	Description
	<p>Describes the partnership.</p> <p>Optional property.</p> <p>Type: String.</p> <p>Default value: Empty string.</p>
	<p>Notification_ActionCmd</p> <p>Specifies the path to the script or command that is triggered when a heartbeat-loss notification is issued.</p> <p>Optional property.</p> <p>Type: String.</p> <p>Default value: Empty string.</p> <p>The Sun Cluster Geographic Edition software enables you to specify a command to run when a heartbeat-loss notification is issued. You can specify the path to the command by using the <code>Notification_ActionCmd</code> property. The command runs with root permissions, so the file must have root ownership and execution permissions. If both <code>Notification_ActionCmd</code> and <code>Notification_EmailAddr</code> properties have been configured, an email is sent after the command that is specified in the <code>Notification_ActionCmd</code> property is run.</p> <p>Caution – A heartbeat loss indicates only a lost connection to a remote cluster and not the cause for the lost connection. A remote cluster that has lost a heartbeat connection might still be functioning even though the heartbeat monitoring has lost its connection.</p> <p>Therefore, you must exercise caution in the script you specify for the <code>Notification_actioncmd</code> parameter. For example, if you specify a forced takeover or a switchover in the <code>Notification_actioncmd</code> script, a takeover or a switchover might be run even though one might not be necessary.</p>
	<p>Notification_EmailAddr</p> <p>Specifies the email address to send messages to when a heartbeat-loss notification is issued. You can specify multiple email addresses by separating each email address with a comma.</p> <p>Optional property.</p> <p>Type: String array.</p>

Default value: Empty string.

The `Notification_EmailAddr`s and the `Notification_ActionCmd` properties enable notification in heartbeat-loss events. Heartbeat-loss events are detected locally on each cluster of the partnership, and the notification is triggered locally on the cluster where the event is detected. The email addresses and the notification action path should be valid on each cluster in the partnership.

Exit Status The following exit values are returned:

0	The command completed successfully.
nonzero	An error has occurred.

Examples **EXAMPLE 1** Adding Trust Between Two Clusters

The following `geops` commands add trust between the clusters `cluster-paris` and `cluster-newyork`.

1. Add cluster `cluster-newyork` to the trust on the cluster `cluster-paris`.

```
cluster-paris# /usr/cluster/bin/geops add-trust -c cluster-newyork
```

Keys are stored on every node of cluster `cluster-paris` with alias `cluster-newyork.certificatenumber`.

2. Add cluster `cluster-paris` to the trust on the cluster `cluster-newyork`.

```
cluster-newyork# /usr/cluster/bin/geops add-trust -c cluster-paris
```

3. Verify trust between the two clusters.

```
cluster-paris# /usr/cluster/bin/geops verify-trust -c cluster-newyork
```

```
cluster-newyork# /usr/cluster/bin/geops verify-trust -c cluster-paris
```

EXAMPLE 2 Creating a Partnership

The following `geops` command creates the partnership `paris-newyork-ps`, on the cluster `cluster-paris`.

```
cluster-paris# geops create -c cluster-newyork -p Description=Transatlantic \  
-p Notification_emailaddrs=sysadmin@companyX.com paris-newyork-ps
```

EXAMPLE 3 Joining a Partnership

The following `geops` command joins `cluster-paris` and `cluster-newyork` in the `paris-newyork-ps` partnership.

```
cluster-paris# geops join-partnership cluster-newyork paris-newyork-ps
```


EXAMPLE 4 Modifying a Partnership

The following `geops` command modifies the notification email address for `cluster-paris`.

```
cluster-paris# geops set-prop -p Notification_emailaddrs=operations@companyX.com \
paris-newyork-ps
```

EXAMPLE 5 Leaving a Partnership

The following `geops` command removes the cluster `cluster-paris` from the partnership `paris-newyork-ps`.

```
cluster-paris# geops leave-partnership paris-newyork-ps
```

EXAMPLE 6 Resynchronizing a Partnership

The following `geops` command resynchronizes the partnership `paris-newyork-ps`.

The `geops update` command overwrites the configuration on the local cluster with the configuration from the remote partner cluster.

```
# geops update paris-newyork-ps
```

Attributes See [attributes\(5\)](#) for descriptions of the following attributes.

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWscgctl
Interface Stability	Evolving

See Also [rbac\(5\)](#)

Index

A

activating protection groups, 25

C

configuring and managing the heartbeat mechanism,
geohb, 17

creating, configuring, and managing partnerships
between clusters, geops, 43

creating or managing protection groups, geopg, 23

D

disabling the Sun Cluster Geographic Edition
infrastructure, geoadm, 10

displaying the status of the Sun Cluster Geographic
Edition infrastructure, geoadm, 10

E

enabling the Sun Cluster Geographic Edition
infrastructure, geoadm, 10

G

geoadm, enabling, disabling, or displaying the status of
the Sun Cluster Geographic Edition
infrastructure, 10

geohb, configuring and managing the heartbeat
mechanism., 17

geopg, creating or managing protection groups., 23

geops, creating, configuring, and managing
partnerships between clusters., 43

L

local_database_name, 37

local_db_service_name, 38

local_rac_proxy_svr_rg_name, 38

O

Oracle Data Guard

properties of

local_database_name, 37

local_db_service_name, 38

local_rac_proxy_svr_rg_name, 38

remote_database_name, 38

remote_db_service_name, 38

remote_rac_proxy_svr_rg_name, 38

replication_mode, 39

standby_type, 39

sysdba_password, 39

sysdba_username, 40

P

properties

Oracle Data Guard

- local_database_name, 37
- local_db_service_name, 38
- local_rac_proxy_svr_rg_name, 38
- remote_database_name, 38
- remote_db_service_name, 38
- remote_rac_proxy_svr_rg_name, 38
- replication_mode, 39
- standby_type, 39
- sysdba_password, 39
- sysdba_username, 40

R

- remote_database_name, 38
- remote_rac_proxy_svr_rg_name, 38
- replication_mode, 39

S

- standby_type, 39
- starting protection groups, 25
- starting resource groups, 25
- sysdba_password, 39
- sysdba_username, 40