



# Sun Java System Directory Server Enterprise Edition 6.0 Migration Guide



Sun Microsystems, Inc.  
4150 Network Circle  
Santa Clara, CA 95054  
U.S.A.

Part No: 819-0994  
March 2007

Copyright 2007 Sun Microsystems, Inc. 4150 Network Circle, Santa Clara, CA 95054 U.S.A. All rights reserved.

Sun Microsystems, Inc. has intellectual property rights relating to technology embodied in the product that is described in this document. In particular, and without limitation, these intellectual property rights may include one or more U.S. patents or pending patent applications in the U.S. and in other countries.

U.S. Government Rights – Commercial software. Government users are subject to the Sun Microsystems, Inc. standard license agreement and applicable provisions of the FAR and its supplements.

This distribution may include materials developed by third parties.

Parts of the product may be derived from Berkeley BSD systems, licensed from the University of California. UNIX is a registered trademark in the U.S. and other countries, exclusively licensed through X/Open Company, Ltd.

Sun, Sun Microsystems, the Sun logo, the Solaris logo, the Java Coffee Cup logo, docs.sun.com, Java, and Solaris are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. in the U.S. and other countries. Products bearing SPARC trademarks are based upon an architecture developed by Sun Microsystems, Inc.

The OPEN LOOK and Sun™ Graphical User Interface was developed by Sun Microsystems, Inc. for its users and licensees. Sun acknowledges the pioneering efforts of Xerox in researching and developing the concept of visual or graphical user interfaces for the computer industry. Sun holds a non-exclusive license from Xerox to the Xerox Graphical User Interface, which license also covers Sun's licensees who implement OPEN LOOK GUIs and otherwise comply with Sun's written license agreements.

Products covered by and information contained in this publication are controlled by U.S. Export Control laws and may be subject to the export or import laws in other countries. Nuclear, missile, chemical or biological weapons or nuclear maritime end uses or end users, whether direct or indirect, are strictly prohibited. Export or reexport to countries subject to U.S. embargo or to entities identified on U.S. export exclusion lists, including, but not limited to, the denied persons and specially designated nationals lists is strictly prohibited.

DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID.

---

Copyright 2007 Sun Microsystems, Inc. 4150 Network Circle, Santa Clara, CA 95054 U.S.A. Tous droits réservés.

Sun Microsystems, Inc. détient les droits de propriété intellectuelle relatifs à la technologie incorporée dans le produit qui est décrit dans ce document. En particulier, et ce sans limitation, ces droits de propriété intellectuelle peuvent inclure un ou plusieurs brevets américains ou des applications de brevet en attente aux États-Unis et dans d'autres pays.

Cette distribution peut comprendre des composants développés par des tierces personnes.

Certains composants de ce produit peuvent être dérivés du logiciel Berkeley BSD, licenciés par l'Université de Californie. UNIX est une marque déposée aux États-Unis et dans d'autres pays; elle est licenciée exclusivement par X/Open Company, Ltd.

Sun, Sun Microsystems, le logo Sun, le logo Solaris, le logo Java Coffee Cup, docs.sun.com, Java et Solaris sont des marques de fabrique ou des marques déposées de Sun Microsystems, Inc. aux États-Unis et dans d'autres pays. Toutes les marques SPARC sont utilisées sous licence et sont des marques de fabrique ou des marques déposées de SPARC International, Inc. aux États-Unis et dans d'autres pays. Les produits portant les marques SPARC sont basés sur une architecture développée par Sun Microsystems, Inc.

L'interface d'utilisation graphique OPEN LOOK et Sun a été développée par Sun Microsystems, Inc. pour ses utilisateurs et licenciés. Sun reconnaît les efforts de pionniers de Xerox pour la recherche et le développement du concept des interfaces d'utilisation visuelle ou graphique pour l'industrie de l'informatique. Sun détient une licence non exclusive de Xerox sur l'interface d'utilisation graphique Xerox, cette licence couvrant également les licenciés de Sun qui mettent en place l'interface d'utilisation graphique OPEN LOOK et qui, en outre, se conforment aux licences écrites de Sun.

Les produits qui font l'objet de cette publication et les informations qu'il contient sont régis par la législation américaine en matière de contrôle des exportations et peuvent être soumis au droit d'autres pays dans le domaine des exportations et importations. Les utilisations finales, ou utilisateurs finaux, pour des armes nucléaires, des missiles, des armes chimiques ou biologiques ou pour le nucléaire maritime, directement ou indirectement, sont strictement interdites. Les exportations ou réexportations vers des pays sous embargo des États-Unis, ou vers des entités figurant sur les listes d'exclusion d'exportation américaines, y compris, mais de manière non exclusive, la liste de personnes qui font objet d'un ordre de ne pas participer, d'une façon directe ou indirecte, aux exportations des produits ou des services qui sont régis par la législation américaine en matière de contrôle des exportations et la liste de ressortissants spécifiquement désignés, sont rigoureusement interdites.

LA DOCUMENTATION EST FOURNIE "EN L'ETAT" ET TOUTES AUTRES CONDITIONS, DECLARATIONS ET GARANTIES EXPRESSES OU TACITES SONT FORMELLEMENT EXCLUES, DANS LA MESURE AUTORISEE PAR LA LOI APPLICABLE, Y COMPRIS NOTAMMENT TOUTE GARANTIE IMPLICITE RELATIVE A LA QUALITE MARCHANDE, A L'APTITUDE A UNE UTILISATION PARTICULIERE OU A L'ABSENCE DE CONTREFAÇON.

# Contents

---

<b>Preface</b> .....	15
<b>1 Overview of the Migration Process for Directory Server</b> .....	25
Before You Migrate .....	25
Prerequisites to Migrating a Single Directory Server Instance From 5.1 .....	26
Prerequisites to Migrating a Single Directory Server Instance From 5.2 .....	26
Deciding on the New Product Distribution .....	27
Outline of Migration Steps .....	27
Deciding on Automatic or Manual Migration .....	28
<b>2 Automated Migration Using the <code>dsmig</code> Command</b> .....	29
About the Automatic Migration Tool .....	29
Prerequisites for Running <code>dsmig</code> .....	30
Using <code>dsmig</code> to Migrate the Schema .....	30
Using <code>dsmig</code> to Migrate Security Data .....	31
Using <code>dsmig</code> to Migrate Configuration Data .....	31
Plug-in Configuration Data .....	32
Chained Suffix Configuration Data .....	32
Configuration Data For Suffixes With Multiple Backends .....	33
Replication Configuration Data .....	33
Configuration Data for <code>o=net scapeRoot</code> .....	33
Configuration Attributes Not Migrated by <code>dsmig</code> .....	33
Using <code>dsmig</code> to Migrate User Data .....	35
Tasks to be Performed After Automatic Migration .....	35
<b>3 Migrating Directory Server Manually</b> .....	37
Before You Start a Manual Migration .....	37

Migrating the Schema Manually .....	38
Migrating Configuration Data Manually .....	38
Migration of Specific Configuration Attributes .....	38
Migrating Security Settings Manually .....	48
Migrating User Data Manually .....	49
Migrating User Plug-Ins Manually .....	50
Tasks to be Performed After Manual Migration .....	50
<b>4 Migrating a Replicated Topology .....</b>	<b>51</b>
Overview of Migrating Replicated Servers .....	51
Issues Related to Migrating Replicated Servers .....	52
Issues With the New Password Policy .....	52
Migration of Replication Agreements .....	52
Migration of Referrals .....	52
Manual Reset of Replication Credentials .....	53
Problems Related to Tombstone Purging .....	53
New Replication Recommendations .....	53
Migration Scenarios .....	54
Migrating a Replicated Topology to an Identical Topology .....	54
Migrating a Replicated Topology to a New Topology .....	63
Migrating Over Multiple Data Centers .....	67
<b>5 Architectural Changes in Directory Server 6.0 .....</b>	<b>69</b>
Changes in the Administration Framework .....	69
Removal of the <i>ServerRoot</i> Directory .....	69
Removal of the <i>o=net:scapeRoot</i> Suffix .....	70
Changes to ACIs .....	70
Changes in the ACI Scope .....	70
Changes in Suffix-Level ACIs .....	70
Command Line Changes .....	71
Deprecated Commands .....	73
Changes to the Console .....	74
New Password Policy .....	74
Password Policy Compatibility .....	75
Changes to Plug-Ins .....	77

New Plug-Ins in Directory Server 6.0 .....	77
Plug-Ins Deprecated in Directory Server 6.0 .....	78
Changes to the Plug-In API .....	78
Changes to the Installed Product Layout .....	78
Administration Utilities Previously Under <i>ServerRoot</i> .....	79
Binaries Previously Under <i>ServerRoot/bin</i> .....	79
Libraries and Plug-Ins Previously Under <i>ServerRoot/lib</i> .....	79
Online Help Previously Under <i>ServerRoot/manual</i> .....	79
Plug-Ins Previously Under <i>ServerRoot/plugins</i> .....	80
Utilities Previously Under <i>ServerRoot/shared/bin</i> .....	80
Certificate and Key Files .....	81
Silent Installation and Uninstallation Templates .....	82
Server Instance Scripts Previously Under <i>ServerRoot/slapped-ServerID</i> .....	82
Server Instance Subdirectories .....	82
<b>6 Migrating Directory Proxy Server .....</b>	<b>83</b>
Mapping the Global Configuration .....	83
Mapping the Global Security Configuration .....	85
Mapping the Connection Pool Configuration .....	87
Mapping the Groups Configuration .....	88
Mapping the Group Object .....	88
Mapping the Network Group Object .....	89
Mapping Bind Forwarding .....	90
Mapping Operation Forwarding .....	91
Mapping Subtree Hiding .....	92
Mapping Search Request Controls .....	92
Mapping Compare Request Controls .....	93
Mapping Attributes Modifying Search Requests .....	93
Mapping Attributes Restricting Search Responses .....	94
Mapping the Referral Configuration Attributes .....	95
Mapping the Server Load Configuration .....	96
Mapping the Properties Configuration .....	97
Attribute Renaming Property .....	97
Forbidden Entry Property .....	97
LDAP Server Property .....	98

Load Balancing Property .....	99
Search Size Limit Property .....	101
Log Property .....	101
Mapping the Events Configuration .....	103
Mapping the Actions Configuration .....	104
Configuring Directory Proxy Server 6.0 as a Simple Connection-Based Router .....	104
<b>7 Migrating Identity Synchronization for Windows .....</b>	<b>105</b>
Migration Overview .....	106
Before You Migrate Identity Synchronization for Windows .....	106
Preparing for Identity Synchronization for Windows Migration .....	107
Exporting Version 1.1 Configuration .....	107
Checking for Undelivered Messages .....	114
▼ Using the checktopics Utility .....	114
▼ To Clear Messages .....	115
Forcing Password Changes on Windows NT .....	116
Migrating Your System .....	116
Preparing for Migration .....	117
▼ Preparing to migrate from version 1.1, and 1.1 SP1, to version 6.0 .....	118
Uninstalling Identity Synchronization for Windows .....	120
▼ To Uninstall Identity Synchronization for Windows Version 1.1 .....	120
Installing or Upgrading the Dependent Products .....	122
Installing Identity Synchronization for Windows 6.0 .....	122
▼ To install the Identity Synchronization for Windows 6.0 components: .....	122
What to Do if the 1.1 Uninstallation Fails .....	125
Manually Uninstalling 1.1 Core and Instances from Solaris .....	125
▼ To Manually Uninstall Core From a Solaris Machine: .....	126
Manually Uninstalling 1.1 Core and Instances from Windows 2000 .....	130
▼ To uninstall Core from a Windows 2000 machine: .....	131
▼ Manually Uninstalling a 1.1 Instance from Windows NT .....	135
Other Migration Scenarios .....	139
Multi-Master Replication Deployment .....	140
Multi-Host Deployment with Windows NT .....	141
Checking the Logs .....	144

**Index** ..... 145





# Figures

---

FIGURE 4-1	Existing version 5 Topology .....	55
FIGURE 4-2	Isolating the Consumer From the Topology .....	55
FIGURE 4-3	Migrating the version 5 Consumer .....	56
FIGURE 4-4	Placing the 6.0 Consumer Into the Topology .....	57
FIGURE 4-5	Existing version 5 Topology With Migrated Consumers .....	58
FIGURE 4-6	Isolating the Hub From the Topology .....	58
FIGURE 4-7	Migrating the version 5 Hub .....	59
FIGURE 4-8	Placing the 6.0 Hub Into the Topology .....	60
FIGURE 4-9	Existing version 5 Topology With Consumers and Hubs Migrated .....	61
FIGURE 4-10	Isolating the Master From the Topology .....	62
FIGURE 4-11	Migrating the version 5 Master .....	62
FIGURE 4-12	Placing the 6.0 Master Into the Topology .....	63
FIGURE 4-13	Existing version 5 Topology .....	64
FIGURE 4-14	Existing Topology With Migrated Servers .....	65
FIGURE 4-15	Migrated Topology With Promoted Hub Replicas .....	66
FIGURE 4-16	New Fully-Meshed All-Master Topology .....	67
FIGURE 7-1	Migrating a Single-Host Deployment .....	117
FIGURE 7-2	Migrating a Multi-Master Replication Deployment .....	141
FIGURE 7-3	Migrating a Multi-Host Deployment with Windows NT .....	143



# Tables

---

TABLE 1-1	Migration Matrix Showing Support for Automated Migration .....	28
TABLE 3-1	Change Log Attribute Name Changes .....	41
TABLE 3-2	Fractional Replication Attribute Name Changes .....	41
TABLE 3-3	Mapping Between 5 and 6.0 Password Policy Attributes .....	43
TABLE 5-1	Directory Server 5 and 6 commands .....	71
TABLE 5-2	Directory Server 5 and 6 Commands (Subcommands of the <code>directoryserver</code> Command) .....	73
TABLE 5-3	Version 5 Commands That Have Been Deprecated .....	73
TABLE 5-4	Support for Plug-Ins .....	80
TABLE 5-5	Tools Previously Under <code>ServerRoot/shared/bin</code> .....	80
TABLE 5-6	Location of Certificate and Key Files .....	81
TABLE 5-7	Instance-Specific Subdirectories .....	82
TABLE 6-1	Mapping of Version 5 Global Configuration Attributes to 6.0 Properties .....	84
TABLE 6-2	Mapping of Security Configuration .....	86
TABLE 6-3	Mapping of Connection Pool Attributes .....	87
TABLE 6-4	Mapping Between Version 5 Group Attributes and Version 6 Connection Handler Properties .....	88
TABLE 6-5	Mapping Between Version 5 Network Group Attributes and 6.0 Properties .....	89
TABLE 6-6	Mapping of Directory Proxy Server 5 Bind Forwarding Attributes to Directory Proxy Server 6 Connection Handler Property Settings .....	90
TABLE 6-7	Mapping of Directory Proxy Server 5 Operation Forwarding Attributes to Directory Proxy Server 6 Request Filtering Properties .....	91
TABLE 6-8	Mapping Directory Proxy Server 5 Search Request Control Attributes to Directory Proxy Server 6.0 Properties .....	93
TABLE 6-9	Mapping of Directory Proxy Server 5 Compare Request Control Attributes to Directory Proxy Server 6 Properties .....	93
TABLE 6-10	Mapping of Directory Proxy Server 5 Search Request Modifying Attributes to Directory Proxy Server 6 Properties .....	94
TABLE 6-11	Mapping of Directory Proxy Server 5 Search Response Restriction Attributes to Directory Proxy Server 6.0 Properties .....	95

---

TABLE 6-12	Mapping of Directory Proxy Server 5 Referral Configuration Attributes to Directory Proxy Server 6 resource limits Properties .....	96
TABLE 6-13	Mapping of Directory Proxy Server 5 Server Load Configuration Attributes to Directory Proxy Server 6.0 Resource Limits Properties .....	96
TABLE 6-14	Mapping of Directory Proxy Server 5 Server Load Configuration Attributes to Directory Proxy Server 6 Resource Limits Properties .....	98
TABLE 6-15	Mapping of ids - proxy - sch - LDAPServer Attributes to Data Source Properties .....	99
TABLE 6-16	Mapping of Version 5 Search Size Limit Attributes to 6.0 Properties .....	101
TABLE 6-17	Version 5 and Version 6 Log Functionality .....	102
TABLE 6-18	Mapping Between Version 5 Event Attributes and Version 6 Connection Handler Properties .....	103
TABLE 7-1	Component Distribution in a Multi-Master Replication Deployment .....	140
TABLE 7-2	Multi-Host Deployment .....	142

# Examples

---

EXAMPLE 7-1	Sample Export Configuration File .....	109
-------------	--	-----



# Preface

---

This *Migration Guide* describes how to migrate the components of Directory Server Enterprise Edition to version 6.0. The guide provides migration instructions for Directory Server, Directory Proxy Server, and Identity Synchronization for Windows.

## Who Should Use This Book

This guide is intended for directory service administrators who are migrating to Directory Server Enterprise Edition 6.0. The guide might also be useful to business planners who are considering migrating to the new version.

## Before You Read This Book

If you are not yet familiar with this version of Directory Server Enterprise Edition, you might want to start by evaluating the new features and capabilities of the product. For more information, see the *Sun Java System Directory Server Enterprise Edition 6.0 Evaluation Guide* and the *Sun Java System Directory Server Enterprise Edition 6.0 Release Notes*.

## How This Book Is Organized

[Chapter 1](#) describes the steps involved in migrating to Directory Server 6.0.

[Chapter 2](#) explains how to use the migration tool provided with Directory Server 6.0.

[Chapter 3](#) describes the process for manual migration of each part of Directory Server.

[Chapter 4](#) describes the issues involved in migrating replicated servers.

[Chapter 5](#) describes the architectural changes in Directory Server 6.0 that affect migration from a previous version.

[Chapter 6](#) describes how the configuration properties in Directory Proxy Server 6.0 can be used to simulate a version 5 configuration.

[Chapter 7](#) describes the steps involved in migrating to Identity Synchronization for Windows 6.0.

# Directory Server Enterprise Edition Documentation Set

This Directory Server Enterprise Edition documentation set explains how to use Sun Java System Directory Server Enterprise Edition to evaluate, design, deploy, and administer directory services. In addition, it shows how to develop client applications for Directory Server Enterprise Edition. The Directory Server Enterprise Edition documentation set is available at <http://docs.sun.com/coll/1224.1>.

For an introduction to Directory Server Enterprise Edition, review the following documents in the order in which they are listed.

TABLE P-1 Directory Server Enterprise Edition Documentation

Document Title	Contents
<i>Sun Java System Directory Server Enterprise Edition 6.0 Release Notes</i>	Contains the latest information about Directory Server Enterprise Edition, including known problems.
<i>Sun Java System Directory Server Enterprise Edition 6.0 Documentation Center</i>	Contains links to key areas of the documentation set.
<i>Sun Java System Directory Server Enterprise Edition 6.0 Evaluation Guide</i>	Introduces the key features of this release. Demonstrates how these features work and what they offer in the context of a fictional deployment that you can implement on a single system.
<i>Sun Java System Directory Server Enterprise Edition 6.0 Deployment Planning Guide</i>	Explains how to plan and design highly available, highly scalable directory services based on Directory Server Enterprise Edition. Presents the basic concepts and principles of deployment planning and design. Discusses the solution life cycle, and provides high-level examples and strategies to use when planning solutions based on Directory Server Enterprise Edition.
<i>Sun Java System Directory Server Enterprise Edition 6.0 Installation Guide</i>	Explains how to install the Directory Server Enterprise Edition software. Shows how to select which components to install, configure those components after installation, and verify that the configured components function properly.  For instructions on installing Directory Editor, go to <a href="http://docs.sun.com/coll/DirEdit_05q1">http://docs.sun.com/coll/DirEdit_05q1</a> .  Make sure you read the information in <i>Sun Java System Directory Server Enterprise Edition 6.0 Release Notes</i> concerning Directory Editor before you install Directory Editor.
<i>Sun Java System Directory Server Enterprise Edition 6.0 Migration Guide</i>	Provides instructions for upgrading components from earlier versions of Directory Server, Directory Proxy Server, and Identity Synchronization for Windows.



TABLE P-1 Directory Server Enterprise Edition Documentation (Continued)

Document Title	Contents
<i>Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide</i>	<p>Provides command-line instructions for administering Directory Server Enterprise Edition.</p> <p>For hints and instructions on using the Directory Service Control Center, DSCC, to administer Directory Server Enterprise Edition, see the online help provided in DSCC.</p> <p>For instructions on administering Directory Editor, go to <a href="http://docs.sun.com/coll/DirEdit_05q1">http://docs.sun.com/coll/DirEdit_05q1</a>.</p> <p>For instructions on installing and configuring Identity Synchronization for Windows, see Part II, “Installing Identity Synchronization for Windows,” in <i>Sun Java System Directory Server Enterprise Edition 6.0 Installation Guide</i>.</p>
<i>Sun Java System Directory Server Enterprise Edition 6.0 Developer’s Guide</i>	Shows how to develop server plug-ins with the APIs that are provided as part of Directory Server Enterprise Edition.
<i>Sun Java System Directory Server Enterprise Edition 6.0 Reference</i>	Introduces the technical and conceptual foundations of Directory Server Enterprise Edition. Describes its components, architecture, processes, and features. Also provides a reference to the developer APIs.
<i>Sun Java System Directory Server Enterprise Edition 6.0 Man Page Reference</i>	Describes the command-line tools, schema objects, and other public interfaces that are available through Directory Server Enterprise Edition. Individual sections of this document can be installed as online manual pages.
<i>Sun Java System Identity Synchronization for Windows 6.0 Deployment Planning Guide</i>	Provides general guidelines and best practices for planning and deploying Identity Synchronization for Windows

## Related Reading

The SLAMD Distributed Load Generation Engine (SLAMD) is a Java™ application that is designed to stress test and analyze the performance of network-based applications. It was originally developed by Sun Microsystems, Inc. to benchmark and analyze the performance of LDAP directory servers. SLAMD is available as an open source application under the Sun Public License, an OSI-approved open source license. To obtain information about SLAMD, go to <http://www.slamd.com/>. SLAMD is also available as a java.net project. See <https://slamd.dev.java.net/>.

Java Naming and Directory Interface (JNDI) technology supports accessing the Directory Server using LDAP and DSML v2 from Java applications. For information about JNDI, see <http://java.sun.com/products/jndi/>. The *JNDI Tutorial* contains detailed descriptions and examples of how to use JNDI. This tutorial is at <http://java.sun.com/products/jndi/tutorial/>.

Directory Server Enterprise Edition can be licensed as a standalone product, as a component of Sun Java Enterprise System, as part of a suite of Sun products, such as the Sun Java Identity Management Suite, or as an add-on package to other software products from Sun. Java

Enterprise System is a software infrastructure that supports enterprise applications distributed across a network or Internet environment. If Directory Server Enterprise Edition was licensed as a component of Java Enterprise System, you should be familiar with the system documentation at <http://docs.sun.com/coll/1286.2>.

Identity Synchronization for Windows uses Message Queue with a restricted license. Message Queue documentation is available at <http://docs.sun.com/coll/1307.2>.

Identity Synchronization for Windows works with Microsoft Windows password policies.

- Information about password policies for Windows 2003 is available in the [Microsoft documentation](#) online.
- Information about changing passwords, and about group policies in Windows 2003 is available the [Microsoft documentation](#) online.
- Information about the Microsoft Certificate Services Enterprise Root certificate authority is available in the [Microsoft support documentation](#) online.
- Information about configuring LDAP over SSL on Microsoft systems is available in the [Microsoft support documentation](#) online.

## Redistributable Files

Directory Server Enterprise Edition does not provide any files that you can redistribute.

## Default Paths and Command Locations

This section explains the default paths used in the documentation, and gives the locations of commands on different operating systems and deployment types.

### Default Paths

The table in this section describes the default paths that are used in this document. For full descriptions of the files installed, see also Chapter 15, “Directory Server File Reference,” in *Sun Java System Directory Server Enterprise Edition 6.0 Reference*, Chapter 26, “Directory Proxy Server File Reference,” in *Sun Java System Directory Server Enterprise Edition 6.0 Reference*, or Appendix A, “Directory Server Resource Kit File Reference,” in *Sun Java System Directory Server Enterprise Edition 6.0 Reference*.

TABLE P-2 Default Paths

Placeholder	Description	Default Value
<i>install-path</i>	<p>Represents the base installation directory for Directory Server Enterprise Edition software.</p> <p>The software is installed in directories below this base <i>install-path</i>. For example, Directory Server software is installed in <i>install-path/ds6/</i>.</p>	<p>When you install from a zip distribution using <code>dsee_deploy(1M)</code>, the default <i>install-path</i> is the current directory. You can set the <i>install-path</i> using the <code>-i</code> option of the <code>dsee_deploy</code> command. When you install from a native package distribution, such as you would using the Java Enterprise System installer, the default <i>install-path</i> is one of the following locations:</p> <ul style="list-style-type: none"> <li>■ Solaris systems - <code>/opt/SUNWdsee/</code>.</li> <li>■ HP-UX systems - <code>/opt/sun/</code>.</li> <li>■ Red Hat systems - <code>/opt/sun/</code>.</li> <li>■ Windows systems - <code>C:\Program Files\Sun\JavaES5\DSEE</code>.</li> </ul>
<i>instance-path</i>	<p>Represents the full path to an instance of Directory Server or Directory Proxy Server.</p> <p>The documentation uses <code>/local/ds/</code> for Directory Server and <code>/local/dps/</code> for Directory Proxy Server.</p>	<p>No default path exists. Instance paths must nevertheless always be found on a <i>local</i> file system.</p> <p>The following directories are recommended:</p> <ul style="list-style-type: none"> <li><code>/var</code> on Solaris systems</li> <li><code>/global</code> if you are using Sun Cluster</li> </ul>
<i>serverroot</i>	Represents the parent directory of the Identity Synchronization for Windows installation location	Depends on your installation. Note the concept of a <i>serverroot</i> no longer exists for Directory Server.
<i>isw-hostname</i>	Represents the Identity Synchronization for Windows instance directory	Depends on your installation
<i>/path/to/cert8.db</i>	Represents the default path and file name of the client's certificate database for Identity Synchronization for Windows	<i>current-working-dir/cert8.db</i>
<i>serverroot/isw-hostname/logs/</i>	Represents the default path to the Identity Synchronization for Windows local logs for the System Manager, each connector, and the Central Logger	Depends on your installation
<i>serverroot/isw-hostname/logs/central/</i>	Represents the default path to the Identity Synchronization for Windows central logs	Depends on your installation

## Command Locations

The table in this section provides locations for commands that are used in Directory Server Enterprise Edition documentation. To learn more about each of the commands, see the relevant man pages.

TABLE P-3 Command Locations

Command	Java ES, Native Package Distribution	Zip Distribution
cacaoadm	Solaris -  /usr/sbin/cacaoadm	Solaris -  <i>install-path/dsee6/cacao_2.0/usr/lib/cacao/bin/cacaoadm</i>
	Red Hat, HP-UX -  /opt/sun/cacao/bin/cacaoadm	Red Hat, HP-UX -  <i>install-path/dsee6/cacao_2.0/cacao/bin/cacaoadm</i>
	Windows -  <i>install-path\share\cacao_2.0\bin\cacaoadm.bat</i>	Windows -  <i>install-path\dsee6\cacao_2.0\bin\cacaoadm.bat</i>
certutil	Solaris -  /usr/sfw/bin/certutil	<i>install-path/dsee6/bin/certutil</i>
	Red Hat, HP-UX -  /opt/sun/private/bin/certutil	
dpadm(1M)	<i>install-path/dps6/bin/dpadm</i>	<i>install-path/dps6/bin/dpadm</i>
dpconf(1M)	<i>install-path/dps6/bin/dpconf</i>	<i>install-path/dps6/bin/dpconf</i>
dsadm(1M)	<i>install-path/ds6/bin/dsadm</i>	<i>install-path/ds6/bin/dsadm</i>
dscmcom(1M)	<i>install-path/dscc6/bin/dscmcom</i>	<i>install-path/dscc6/bin/dscmcom</i>
dsccreg(1M)	<i>install-path/dscc6/bin/dsccreg</i>	<i>install-path/dscc6/bin/dsccreg</i>
dscctest(1M)	<i>install-path/dscc6/bin/dscctest</i>	<i>install-path/dscc6/bin/dscctest</i>
dsconf(1M)	<i>install-path/ds6/bin/dsconf</i>	<i>install-path/ds6/bin/dsconf</i>
dsee_deploy(1M)	Not provided	<i>install-path/dsee6/bin/dsee_deploy</i>
dsmig(1M)	<i>install-path/ds6/bin/dsmig</i>	<i>install-path/ds6/bin/dsmig</i>
entrycmp(1)	<i>install-path/ds6/bin/entrycmp</i>	<i>install-path/ds6/bin/entrycmp</i>
fildif(1)	<i>install-path/ds6/bin/fildif</i>	<i>install-path/ds6/bin/fildif</i>
idsktune(1M)	<i>install-path/dsrk6/bin/idsktune</i>	<i>install-path/dsrk6/bin/idsktune</i>

TABLE P-3 Command Locations (Continued)

Command	Java ES, Native Package Distribution	Zip Distribution
insync(1)	<i>install-path/ds6/bin/insync</i>	<i>install-path/ds6/bin/insync</i>
ns-accountstatus(1M)	<i>install-path/ds6/bin/ns-accountstatus</i>	<i>install-path/ds6/bin/ns-accountstatus</i>
ns-activate(1M)	<i>install-path/ds6/bin/ns-activate</i>	<i>install-path/ds6/bin/ns-activate</i>
ns-inactivate(1M)	<i>install-path/ds6/bin/ns-inactivate</i>	<i>install-path/ds6/bin/ns-inactivate</i>
repldisc(1)	<i>install-path/ds6/bin/repldisc</i>	<i>install-path/ds6/bin/repldisc</i>
schema_push(1M)	<i>install-path/ds6/bin/schema_push</i>	<i>install-path/ds6/bin/schema_push</i>
smcwebserver	Solaris, Linux, HP-UX - <i>/usr/sbin/smcwebserver</i>	This command pertains only to Directory Service Control Center, which is not available in the zip distribution.
	Windows - <i>install-path\share\webconsole\bin\smcwebserver</i>	
wcadmin	Solaris, Linux, HP-UX - <i>/usr/sbin/wcadmin</i>	This command pertains only to Directory Service Control Center, which is not available in the zip distribution.
	Windows - <i>install-path\share\webconsole\bin\wcadmin</i>	

## Typographic Conventions

The following table describes the typographic changes that are used in this book.

TABLE P-4 Typographic Conventions

Typeface	Meaning	Example
AaBbCc123	The names of commands, files, and directories, and onscreen computer output	Edit your <code>.login</code> file. Use <code>ls -a</code> to list all files. <code>machine_name%</code> you have mail.
<b>AaBbCc123</b>	What you type, contrasted with onscreen computer output	<code>machine_name% su</code> Password:
<i>AaBbCc123</i>	A placeholder to be replaced with a real name or value	The command to remove a file is <code>rm filename</code> .

TABLE P-4 Typographic Conventions (Continued)

Typeface	Meaning	Example
<i>AaBbCc123</i>	Book titles, new terms, and terms to be emphasized (note that some emphasized items appear bold online)	Read Chapter 6 in the <i>User's Guide</i> . A <i>cache</i> is a copy that is stored locally. Do <i>not</i> save the file.

## Shell Prompts in Command Examples

The following table shows default system prompts and superuser prompts.

TABLE P-5 Shell Prompts

Shell	Prompt
C shell on UNIX and Linux systems	machine_name%
C shell superuser on UNIX and Linux systems	machine_name#
Bourne shell and Korn shell on UNIX and Linux systems	\$
Bourne shell and Korn shell superuser on UNIX and Linux systems	#
Microsoft Windows command line	C:\

## Symbol Conventions

The following table explains symbols that might be used in this book.

TABLE P-6 Symbol Conventions

Symbol	Description	Example	Meaning
[ ]	Contains optional arguments and command options.	ls [-l]	The -l option is not required.
{   }	Contains a set of choices for a required command option.	-d {y n}	The -d option requires that you use either the y argument or the n argument.
\${ }	Indicates a variable reference.	\${com.sun.javaRoot}	References the value of the com.sun.javaRoot variable.
-	Joins simultaneous multiple keystrokes.	Control-A	Press the Control key while you press the A key.

TABLE P-6 Symbol Conventions (Continued)

Symbol	Description	Example	Meaning
+	Joins consecutive multiple keystrokes.	Ctrl+A+N	Press the Control key, release it, and then press the subsequent keys.
→	Indicates menu item selection in a graphical user interface.	File → New → Templates	From the File menu, choose New. From the New submenu, choose Templates.

## Documentation, Support, and Training

The Sun web site provides information about the following additional resources:

- Documentation (<http://www.sun.com/documentation/>)
- Support (<http://www.sun.com/support/>)
- Training (<http://www.sun.com/training/>)

## Third-Party Web Site References

Third-party URLs are referenced in this document and provide additional, related information.

---

**Note** – Sun is not responsible for the availability of third-party web sites mentioned in this document. Sun does not endorse and is not responsible or liable for any content, advertising, products, or other materials that are available on or through such sites or resources. Sun will not be responsible or liable for any actual or alleged damage or loss caused or alleged to be caused by or in connection with use of or reliance on any such content, goods, or services that are available on or through such sites or resources.

---

## Searching Sun Product Documentation

Besides searching for Sun product documentation from the docs.sun.com web site, you can use a search engine of your choice by typing the following syntax in the search field:

```
search-term site:docs.sun.com
```

For example, to search for Directory Server, type the following:

```
"Directory Server" site:docs.sun.com
```

To include other Sun web sites in your search, such as java.sun.com, www.sun.com, and developers.sun.com, use sun.com in place of docs.sun.com in the search field.

## Sun Welcomes Your Comments

Sun is interested in improving its documentation and welcomes your comments and suggestions. To share your comments, go to <http://docs.sun.com> and click Send Comments. In the online form, provide the full document title and part number. The part number is a 7-digit or 9-digit number that can be found on the book's title page or in the document's URL. For example, the part number of this book is 819-0994.



# Overview of the Migration Process for Directory Server

---

This chapter describes the steps involved in migrating to Directory Server 6.0. Directory Server 6.0 provides a migration tool, `dsmig`, that automates aspects of the migration for certain platform/version combinations. If servers within your topology fall outside of these combinations, the same migration steps must be performed manually.

This chapter includes the following topics:

- “Before You Migrate” on page 25
- “Deciding on the New Product Distribution” on page 27
- “Outline of Migration Steps” on page 27
- “Deciding on Automatic or Manual Migration” on page 28

## Before You Migrate

This chapter provides an overview of the upgrade and data migration process.

Before upgrading, familiarize yourself with the new features and fixes available in the current version. Take the opportunity to review design decisions made during implementation of existing directory services. For a description of all new features and fixes, see “What’s New at a Glance” in *Sun Java System Directory Server Enterprise Edition 6.0 Evaluation Guide*. For information about the new features that specifically affect migration, see [Chapter 5](#).

## Prerequisites to Migrating a Single Directory Server Instance From 5.1

Before migrating from a 5.1 server instance, ensure that the following prerequisites are met:

- Directory Server 6.0 must be installed. The new server can be installed on the same machine as the existing server or on a different machine.
- Ensure that the new machine has sufficient local disk space to house binaries and databases for both the old and new servers, and also enough extra space to hold LDIF files containing the entries in all existing suffixes. You can estimate the local disk space required as somewhat larger than the following calculation.

`local space required = 2 * (space for existing server) + (space for LDIF files)`

## Prerequisites to Migrating a Single Directory Server Instance From 5.2

Before migrating from a 5.2 server instance, ensure that the following prerequisites are met:

- Directory Server 6.0 must be installed. The new server can be installed on the same machine as the existing server or on a different machine.
- Ensure that the new machine has sufficient local disk space to house binaries and databases for both the old and new servers, and also enough extra space to hold LDIF files containing the entries in all existing suffixes. You can estimate the local disk space required as somewhat larger than the following calculation.

`local space required = 2 * (space for existing server) + (space for LDIF files)`

- 

If you are using the automatic migration tool, the following two prerequisites must be met:

- The existing server instance must be stopped cleanly.
- If the new server is located on a different machine, a complete image of the original server instance must be created on the new machine. This includes all schema files, configuration files, security files, and database files, in an identical layout to the original server root.

To determine whether you should use automatic or manual migration, see [“Deciding on Automatic or Manual Migration” on page 28](#).

- If your Directory Server deployment includes Identity Synchronization for Windows, you must uninstall Identity Synchronization for Windows before migrating to Directory Server 6.0. For information about migrating Identity Synchronization for Windows, see [Chapter 7](#).

## Deciding on the New Product Distribution

Directory Server 6.0 is provided in two distributions:

- Java Enterprise System distribution. This distribution takes the form of operating system-specific packages, such as `pkg` for Solaris and `rpm` for Linux.
- Compressed archive (`zip`) distribution.

There are two major differences between these two distributions:

1. Installation from `zip` can be done anywhere on the system and as a non-root user. The Java Enterprise System distribution requires installation as a super user. It is also more difficult from an automated deployment perspective to install the packages anywhere but in the default location.
2. The `zip` distribution can be installed as many times as required and multiple distinct versions of the same product can coexist on a single operating system instance. This is not true for the Java Enterprise System distribution. The new version of certain shared component packages required by Directory Server are incompatible with the previous version of these packages. When you migrate to the new version of Directory Server using the Java Enterprise System distribution, the old Directory Server version will no longer run on that machine.

Depending on your environment and the specific requirements of your organization, select the appropriate packaging format. Note that the Sun Java Web Console is currently available only in the Java Enterprise System distribution.

## Outline of Migration Steps

Migration to Directory Server 6.0 can be broken down into the following distinct steps:

1. Migrating the Schema
2. Migrating the Security Settings
3. Migrating the Configuration
4. Migrating the Data
5. Migrating the Plug-Ins
6. Post-migration tasks

To avoid unforeseen problems with the migration, these steps should be performed in the order listed above. In certain cases, you can automate some or all of these steps, using the `ds mig` command. The following section indicates what can be automated and what must be done manually, depending on your existing deployment.

## Deciding on Automatic or Manual Migration

This section provides a table that shows when you can use `dsmig` and when you need to migrate manually. It is based on the migration steps described in the previous section.

TABLE 1-1 Migration Matrix Showing Support for Automated Migration

From	To			Migration Step				
Version	Version	Software (32/64-bit)	OS	Schema	Config	Security	Data	Plug-Ins
5.1	6.0	Any	Any	Manual	Manual	Manual	Manual	Manual
5.2	6.0	Different	Any	<code>dsmig</code>	<code>dsmig</code>	<code>dsmig</code>	Manual	Manual
5.2	6.0	Same	Different	<code>dsmig</code>	<code>dsmig</code>	<code>dsmig</code>	Manual	Manual
5.2	6.0	Same	Same	<code>dsmig</code>	<code>dsmig</code>	<code>dsmig</code>	<code>dsmig</code>	Manual

The following two chapters explain how to perform each migration step outlined above, either automatically, or manually. For information on automatic migration, see [Chapter 2](#). For information on manual migration, see [Chapter 3](#).

# Automated Migration Using the `dsmig` Command

---

Directory Server 6.0 provides a command-line migration tool to help you migrate from a Directory Server 5.2 instance to a Directory Server 6.0 instance. You can only use the migration tool if your deployment satisfies the requirements for automatic migration described in [“Deciding on Automatic or Manual Migration” on page 28](#).

The migration tool provides migration *per instance*. If several instances exist within the same server root, the migration tool must be run for each individual instance.

This chapter explains how to use the migration tool and covers the following topics:

- [“About the Automatic Migration Tool” on page 29](#)
- [“Prerequisites for Running `dsmig`” on page 30](#)
- [“Using `dsmig` to Migrate the Schema” on page 30](#)
- [“Using `dsmig` to Migrate Security Data” on page 31](#)
- [“Using `dsmig` to Migrate Configuration Data” on page 31](#)
- [“Using `dsmig` to Migrate User Data” on page 35](#)
- [“Tasks to be Performed After Automatic Migration” on page 35](#)

## About the Automatic Migration Tool

The migration tool, `dsmig`, is delivered with the Directory Server 6.0 packages. When these packages have been installed, `dsmig` is located in `install-path/ds6/bin`.

`dsmig` must be run on the machine on which the new Directory Server instance will be located. When the command is run, a *migration* directory is created within the new instance directory (`new-instance-path/migration`). This directory is a repository for data produced by the migration, including log files and migration status files.

`dsmig` includes a set of sub-commands and options, that map to the individual migration steps described in [“Outline of Migration Steps” on page 27](#). For information about the usage of `dsmig`, see `dsmig(1M)`.

## Prerequisites for Running `dsmig`

In this section, *old instance* refers to the 5.2 instance and *new instance* refers to the Directory Server 6.0 instance.

Before you use `dsmig` to migrate an instance, ensure that the following tasks have been performed:

- The Directory Server 6.0 packages (either zip, or native packages) have been installed.  
The Directory Server 6.0 packages can be installed on the same machine that holds the Directory Server 5.2 instance, or on a different machine.
- The old instance must have been stopped correctly.  
A disorderly shutdown of the old instance will cause problems during the migration. Even if the old and new instance are on different machines, the old instance must be stopped before the migration is started.
- `dsmig` has access to the old instance files.
- If the old and new instances are on different machines, a *complete image* of the old instance must be created on the machine that hosts the new instance.  
The complete image includes all the files required for migration of the instance (schema, configuration, security and database files). The complete image files must be located in the same directories as they were under the original Server Root. You can run `cp -r` to achieve this, provided none of the files have been relocated outside the Server Root.

You can create and start the new instance manually, but is not mandatory to create the new instance before running `dsmig`. `dsmig` checks whether a new Directory Server instance exists in the specified path. If a new instance exists, the commands are carried out on this instance. If a new instance does not exist, the instance is created automatically.

The new instance can be created anywhere except for the exact location of the old instance.

## Using `dsmig` to Migrate the Schema

Directory Server 5.2 schema files are located in `serverRoot/slapd-instance-path/config/schema`. Directory Server 6.0 schema files are located in `INSTANCE-PATH/config/schema`.

Directory Server 6.0 provides a new schema file, `00ds6pwp.ldif`, that contains new password policy attributes. In addition, certain configuration attributes have been added to `00core.ldif`. Apart from these files, the standard schema files provided with Directory Server 6.0 are identical to those provided in 5.2.

To migrate the schema automatically, run the following command:

```
$ dsmig migrate-schema old-instance-path new-instance-path
```

When you run this command, any custom schema defined in the `99user.ldif` file are copied to the new instance. If the new instance is already in production, and you have already modified the `99user.ldif` file of the new instance, `dsrmig` performs a *best effort* merge of the two files. Custom schema defined in any other files are also copied to the new instance.

During schema migration, all fractional replication information is moved from the schema files. Fractional replication must be redefined in the new instance.

For more information, see `dsrmig(1M)`.

## Using `dsrmig` to Migrate Security Data

To migrate the security settings automatically, run the following command:

```
$ dsrmig migrate-security old-instance-path new-instance-path
```

During the migration of security settings, `dsrmig` performs the following tasks:

- Backs up the certificate and database files in the new instance.
- Copies the certificate database and key database files from the old instance to the new instance.
- Copies the password file from the old instance to the new instance.
- Copies the certificate mapping file from the old instance to the new instance.
- If the old instance uses an external security token, copies the security module database and the external token library to the new instance.

For more information, see `dsrmig(1M)`.

## Using `dsrmig` to Migrate Configuration Data

Directory Server 5.2 configuration is specified in the file `serverRoot/slapd-instance-path/config/dse.ldif`. Directory Server 6.0 configuration is specified in the file `instance-path/config/dse.ldif`.

To migrate the configuration automatically, run the following command:

```
$ dsrmig migrate-config old-instance-path new-instance-path
```

In this step, `dsrmig` reads each LDIF entry in the configuration file (`dse.ldif`) of the 5.2 instance. If these entries exist in the corresponding Directory Server 6.0 configuration file, their values are updated. If the entries do not exist, they are created.

Migration of the configuration is done over LDAP. By default, `dsrmig` binds to the new instance securely, issuing a StartTLS request.

---

**Note** – By default, StartTLS is not enabled on Windows. If you are running dsmig on Windows, use the `-e` or `--unsecured` option to specify an unsecured connection. Alternatively, use the `-Z` or `--use-secure-port` option to specify a secure connection over SSL. If you do not use either of these options on Windows, dsmig issues a warning and the migration process terminates with an error.

---

For more information see dsmig(1M). For details of the specific configuration attributes that are migrated, see [“Migration of Specific Configuration Attributes” on page 38](#).

## Plug-in Configuration Data

dsmig migrates configuration data for certain Directory Server plug-ins only. For most system plug-ins, configuration data is *not* migrated automatically.

dsmig migrates all configuration data for the CoS plug-in. In addition, dsmig migrates the enabled or disabled state for the following system plug-ins:

- 7-bit Check
- DSML Frontend
- Pass-Through Authentication
- Referential Integrity
- Retro Change Log
- UID Uniqueness

When you migrate the configuration in verbose mode, dsmig issues a warning indicating which system plug-in configurations are not migrated.

Plug-ins that you have created are not migrated. However, during the migration process user plug-in configuration data is dumped in the file `new-instance-path/migration/old_userplugins_conf.ldif`. These plug-ins must be recompiled when the migration is complete.

## Chained Suffix Configuration Data

Configuration data for chained suffixes is not migrated. By default, the configuration data is dumped in the file `new-instance-path/migration/old_chaining_conf.ldif`. You can import the chaining configuration data from this file after migration, if required.



## Configuration Data For Suffixes With Multiple Backends

Configuration data for suffixes with multiple backends is not migrated. If `dsmig` detects that a suffix has more than one backend, it does not migrate any of the configuration entries that belong to that suffix. This includes configuration entries for the mapping tree, replicas, replication agreements, LDBM instances, indexes, and encrypted attributes. Instead, all of these entries are dumped in the file `new-instance-path/migration/old_distribution_conf.ldif`. You can import the distribution configuration data from this file after migration, if required.

## Replication Configuration Data

Configuration data for replication is not migrated by default. If you want this data to be migrated, select the `-R` option. By default, the data is dumped in the file `new-instance-path/migration/old_replication_conf.ldif`. You can import the replication configuration data from this file after migration, if required.

## Configuration Data for `o=net scapeRoot`

Configuration data for the `o=Net scapeRoot` suffix is not migrated by default. If this information is required, use the `-N` to migrate the configuration data. If you do not use the `-N` option, the data is dumped in the file `new-instance-path/migration/old_netscape_conf.ldif`. You can import the configuration data from this file after migration, if required.

## Configuration Attributes Not Migrated by `dsmig`

The following common configuration attributes are not migrated automatically.

This is not an exhaustive list. You might have used additional configuration attributes that must be migrated manually.

```
ds-hdsml-dsmlschemalocation
ds-hdsml-soapschemalocation
dsKeyedPassword
dsMappedDN
dsMatching-pattern
dsMatching-regexp
dsSaslPluginsEnable
dsSaslPluginsEnable
dsSaslPluginsPath
dsSearchBaseDN
dsSearchFilter
```

nsabandonedsearchcheckinterval  
nsbindconnectionslimit  
nsbindretrylemit  
nsbindtimeout  
nschecklocalaci  
nsconcurrentbindlimit  
nsconcurrentoperationslimit  
nsconnectionlife  
nshoplmit  
nsMatchingRule  
nsmaxresponsedelay  
nsmaxtestresponsedelay  
nsoperationconnectionslimit  
nspossiblechainingcomponents  
nspossiblechainingcomponents  
nspossiblechainingcomponents  
nspossiblechainingcomponents  
nspossiblechainingcomponents  
nspossiblechainingcomponents  
nsproxiedauthorization  
nsreferralonscopedsearch  
nsslapd-db-durable-transaction  
nsslapd-db-home-directory  
nsslapd-db-logbuf-size  
nsslapd-db-logdirectory  
nsslapd-db-replication-batch-val  
nsslapd-db-transaction-logging  
nsslapd-directory  
nsslapd-disk-full-threshold  
nsslapd-disk-low-threshold  
nsslapd-enquote-sup-oc  
nsslapd-exclude-from-export  
nsslapd-groupevalnestlevel  
nsslapd-localhost  
nsslapd-localuser  
nsslapd-mode  
nsslapd-port  
nsslapd-return-exact-case  
nsslapd-rewrite-rfc1274  
nsslapd-secureport  
nsslapd-security  
nsSSL2  
nsSSL3  
nsSSLActivation  
nsSSLServerAuth  
nsSSLSessionTimeout  
nsState  
nstransmittedcontrols  
plugin-order-preoperation-finish-entry-encode-result

## Using `dsmig` to Migrate User Data

In Directory Server 5.2, data is stored in `serverRoot/slapd-instance-name/db`. Directory Server 6.0 stores user data in `instance-path/db`.

To migrate data automatically, run the following command:

```
$ dsmig migrate-data old-instance-path new-instance-path
```

All suffixes are migrated by default, except the `o=netscapeRoot` suffix. `dsmig` copies the data, the indexes, and the transaction logs. The database context, that is, the state of the database, is not migrated.

In the new Directory Server administration model, there is no Configuration Directory Server. This means that the `o=netscapeRoot` suffix is no longer relevant, unless your deployment includes Identity Synchronization for Windows. By default, `dsmig` does not migrate the `o=netscapeRoot` database, unless specifically requested. To migrate the `o=netscapeRoot` database, use the `-N` option with the `migrate-data` subcommand.

For more information, see `dsmig(1M)`.

---

**Note** – During data migration, Directory Server checks whether nested group definitions exceed 30 levels. Deep nesting can signify a circular group definition, where a nested group contains a group that is also its parent. When a group with more than 30 nesting levels is encountered, Directory Server stops calculating the `isMemberOf` attributes for additional levels.

Each time this happens, Directory Server logs an error. You safely ignore these errors, although you should examine the definition of the group mentioned in the error message for potential circular definitions.

---

## Tasks to be Performed After Automatic Migration

If you have used `dsmig` to migrate your server automatically, only the following two post-migration tasks must be completed:

- If you have customized user plug-ins, these need to be recompiled and added to the new server manually.
- If the migrated server was part of a replicated topology, see [“Issues Related to Migrating Replicated Servers”](#) on page 52.



# Migrating Directory Server Manually

---

If your deployment does not satisfy the requirements for automatic migration described in [“Deciding on Automatic or Manual Migration” on page 28](#), you must migrate the servers manually. This chapter describes the process for manual migration of each part of the server.

The chapter covers the following topics:

- [“Before You Start a Manual Migration” on page 37](#)
- [“Migrating the Schema Manually” on page 38](#)
- [“Migrating Configuration Data Manually” on page 38](#)
- [“Migrating Security Settings Manually” on page 48](#)
- [“Migrating User Data Manually” on page 49](#)
- [“Migrating User Plug-Ins Manually” on page 50](#)
- [“Tasks to be Performed After Manual Migration” on page 50](#)

## Before You Start a Manual Migration

Migrating an instance manually involves migrating each part of the server in the same order as performed by the automatic migration tool (`dsmig`). In this section, *old instance* refers to the version 5 instance and *new instance* refers to the 6.0 instance.

Before you start a manual migration, ensure that the following tasks have been performed:

- Directory Server 6.0 software has been installed.  
Directory Server 6.0 software can be installed on the same machine that holds the Directory Server 5 instance, or on a different machine.

- The new instance has been created.

The new instance can be created anywhere except for the exact location of the old instance. The new instance can be installed on the same LDAP/LDAPS port or on a different port. If you use different ports, any replication agreements to the new instance must be changed accordingly.

- The old instance has been stopped correctly.  
A disorderly shutdown of the old instance will cause problems during migration. Even if the old and new instances are on different machines, the old instance must be stopped before migration is started.

## Migrating the Schema Manually

Directory Server 5 schema files are located in *serverRoot/slapd-serverID/config/schema*.  
Directory Server 6.0 schema files are located in *instance-path/config/schema*.

Directory Server 6.0 provides a new schema file, *00ds6pw.p.ldif*, that contains new password policy attributes. In addition, certain configuration attributes have been added to *00core.ldif*. Apart from these files, the standard schema files provided with Directory Server 6.0 are identical to those provided in version 5.

To migrate the schema, perform the following steps:

1. Copy the *99user.ldif* file from the existing instance to the new instance. If you have already added custom schema to the new instance, you will need to choose which version of the custom schema to keep.
2. If you have defined custom schema in any other files, copy these files to the new instance.
3. Any fractional replication information must be redefined in the new instance.

## Migrating Configuration Data Manually

Directory Server 5 configuration is specified in the file *serverRoot/slapd-serverID/config/dse.ldif*. Directory Server 6.0 configuration is specified in the file *instance-path/config/dse.ldif*.

If you are migrating from 5.1, you must migrate the configuration files manually. The easiest way to do this is to run the `migrateInstance5` migration script to produce a 5.2 configuration, and then to migrate the 5.2 configuration using `dsmig`. For information on using `migrateInstance5`, see the *Directory Server 5.2 2005Q1 Installation and Migration Guide*. For information on using `dsmig` to migrate the configuration, see [“Using `dsmig` to Migrate Configuration Data” on page 31](#).

The following section describes the specific configuration attributes that must be migrated from the old instance to the new instance.

## Migration of Specific Configuration Attributes

The values of the following attribute types must be migrated.

## Global Configuration Attributes

The implementation of global scope ACIs requires all ACIs specific to the rootDSE to have a `targetscope` field, with a value of `base` (`targetscope="base"`). ACIs held in the rootDSE are specific to each Directory Server instance and are not replicated. Therefore there should be no incompatibility problems when running a Directory Server 6.0 server in a topology containing servers of previous versions. For more information about the changes made with regard to ACI scope, see [“Changes to ACIs” on page 70](#).

In addition to the ACI change, the following attributes under `cn=config` must be migrated:

```
nsslapd-accesscontrol
nsslapd-accesslog-level
nsslapd-accesslog-logbuffering
nsslapd-accesslog-logexpirationtime
nsslapd-accesslog-logexpirationtimeunit
nsslapd-accesslog-logging-enabled
nsslapd-accesslog-logmaxdiskpace
nsslapd-accesslog-logminfreediskpace
nsslapd-accesslog-logrotationtime
nsslapd-accesslog-logrotationtimeunit
nsslapd-accesslog-maxlogsize
nsslapd-accesslog-maxlogspedir
nsslapd-attribute-name-exceptions
nsslapd-auditlog-logexpirationtime
nsslapd-auditlog-logexpirationtimeunit
nsslapd-auditlog-logging-enabled
nsslapd-auditlog-logmaxdiskpace
nsslapd-auditlog-logminfreediskpace
nsslapd-auditlog-logrotationtime
nsslapd-auditlog-logrotationtimeunit
nsslapd-auditlog-maxlogsize
nsslapd-auditlog-maxlogspedir
nsslapd-certmap-basedn
nsslapd-ds4-compatible-schema
nsslapd-enquote-sup-oc
nsslapd-errorlog-level
nsslapd-errorlog-logexpirationtime
nsslapd-errorlog-logexpirationtimeunit
nsslapd-errorlog-logging-enabled
nsslapd-errorlog-logmaxdiskpace
nsslapd-errorlog-logminfreediskpace
nsslapd-errorlog-logrotationtime
nsslapd-errorlog-logrotationtimeunit
nsslapd-errorlog-maxlogsize
nsslapd-errorlog-maxlogspedir
nsslapd-groupevalnestlevel
nsslapd-idletimeout
```

```
nsslapd-infolog-area  
nsslapd-infolog-level  
nsslapd-ioblocktimeout  
nsslapd-lastmod  
nsslapd-listenhost  
nsslapd-maxbersize  
nsslapd-maxconnections  
nsslapd-maxdescriptors  
nsslapd-maxpsearch  
nsslapd-maxthreadsperconn  
nsslapd-nagle  
nsslapd-readonly  
nsslapd-referral  
nsslapd-referralmode  
nsslapd-reservedescriptors  
nsslapd-return-exact-case  
nsslapd-rootpwstoragescheme  
nsslapd-schema-repl-useronly  
nsslapd-schemacheck  
nsslapd-search-tune  
nsslapd-securelistenhost  
nsslapd-security  
nsslapd-sizelimit  
nsslapd-threadnumber  
nsslapd-timelimit  
ds-start-tls-enabled
```

## Security Configuration Attributes

All attributes under "cn=encryption,cn=config" must be migrated.

If you are using certificate authentication or the secure port, the key file path and certificate database file path under "cn=encryption,cn=config" must be updated. The values of the following attributes must be migrated:

```
nsKeyfile  
nsCertfile
```

## Feature Configuration Attributes

The values of the aci attributes under "cn=features,cn=config" must be migrated.

In addition, the values of all identity mapping attributes must be migrated.

## Mapping Tree Configuration Attributes

All entries under "cn=mapping tree,cn=config" must be migrated.



The Netscape Root database has been deprecated in Directory Server 6.0. If your old instance made specific use of the Netscape Root database, the attributes under `o=netscaperoot` must be migrated. Otherwise, they can be ignored.

## Replication Configuration Attributes

Before migrating replication configuration attributes, ensure that there are no pending changes to be replicated. You can use the `insync` command to do this.

In addition to the configuration attributes, all entries under `cn=replication`, `cn=config` must be migrated. You must manually update the host and port on all replication agreements to the new instance, as well as the path to the change log database (`nsslapd-change logdir`).

The following sections list the replication configuration attributes that must be migrated:

### Change Log Attributes

TABLE 3-1 Change Log Attribute Name Changes

Old Attribute Name	Directory Server 6.0 Attribute Name
<code>nsslapd-change logmaxage</code>	<code>dschange logmaxage</code>
<code>nsslapd-change logmaxentries</code>	<code>dschange logmaxentries</code>

In addition, these attributes must be moved from `cn=change log5`, `cn=config` to `cn=replica`, `cn=suffixname`, `cn=mapping tree`, `cn=config` entries (for each suffix name).

### Fractional Replication Configuration Attributes

If your topology uses fractional replication, the following attribute names must be changed.

TABLE 3-2 Fractional Replication Attribute Name Changes

Old Attribute Name	Directory Server 6.0 Attribute Name
<code>dsFilterSPType == fractional_include</code>	<code>dsReplFractionalInclude</code>
<code>dsFilterSPType == fractional_exclude</code>	<code>dsReplFractionalExclude</code>

### Replica Configuration Attributes

The values of the following replica configuration attributes must be migrated:

`ds5ReferralDelayAfterInit`  
`nsDS5Flags`  
`nsDS5ReplicaBindDN`

nsDS5ReplicaId  
nsDS5ReplicaLegacyConsumer  
nsDS5ReplicaName  
nsDS5ReplicaPurgeDelay  
nsDS5ReplicaReferral  
nsDS5ReplicaRoot  
nsDS5ReplicaTombstonePurgeInterval  
aci

The `dschangeLogmaxage` and `dschangeLogmaxentries` attributes are added to the replica entry.

## Replication Agreement Configuration

The values of the following attributes must be migrated for each replication agreement:

description  
ds5agreementEnable  
ds5ReplicaTransportCompressionLevel  
ds5ReplicaTransportGroupSize  
ds5ReplicaTransportWindowSize  
nsDS5ReplicaBindDN  
nsDS5ReplicaBindMethod  
nsDS5ReplicaCredentials  
nsDS5ReplicaHost  
nsDS5ReplicaPort  
nsDS5ReplicaRoot  
nsDS5ReplicaTimeout  
nsDS5ReplicaTransportInfo  
nsDS5ReplicaUpdateSchedule  
aci

Issues can arise when you migrate the `nsDS5ReplicaCredentials` attribute. For more information, see [“Manual Reset of Replication Credentials” on page 53](#).

There is no `ds5PartialReplConfiguration` attribute in Directory Server 6.0. This attribute must be removed.

If you are using fractional replication, the `dsReplFractionalInclude` and `dsReplFractionalExclude` attributes are added for each replication agreement.

All attributes under `"cn=replication,cn=config"` are migrated.

## Password Policy Configuration Attributes

Directory Server 6.0 implements a new password policy. For details on configuration of the new password policy, see Chapter 7, “Directory Server Password Policy,” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*. The attributes that define the

password policy are stored in the entry `cn=Password Policy,cn=config`. Note that in Directory Server 5.1, password policy attributes were located directly under `cn=config`.

Directory Server 6.0 introduces the new `pwdPolicy` object class. The attributes of this object class replace the old password policy attributes. For a description of these new attributes see the `pwdPolicy(5dsoc)` man page.

By default, the new password policy is backward compatible with the old password policy. However, because backward compatibility is not guaranteed indefinitely, you should migrate to the new password policy as soon as is convenient for your deployment. For information about password policy compatibility, see [“Password Policy Compatibility” on page 75](#).

The following table provides a mapping of the new password policy attributes whose values must be migrated from the legacy attributes.

**TABLE 3-3** Mapping Between 5 and 6.0 Password Policy Attributes

Legacy Directory Server Attribute	Directory Server 6.0 Attribute
- (password policy is applied to the userPassword attribute only.)	<code>pwdAttribute</code>
<code>passwordMinAge</code>	<code>pwdMinAge</code>
<code>passwordMaxAge</code>	<code>pwdMaxAge</code>
<code>passwordInHistory</code>	<code>pwdInHistory</code>
<code>passwordSyntax</code>	<code>pwdCheckQuality</code>
<code>passwordMinLength</code>	<code>pwdMinLength</code>
<code>passwordWarning</code>	<code>pwdExpireWarning</code>
-	<code>pwdGraceLoginLimit</code>
<code>passwordMustChange</code>	<code>pwdMustChange</code>
<code>passwordChange</code>	<code>pwdAllowUserChange</code>
-	<code>pwdSafeModify</code>
<code>passwordExp</code>	-
<code>passwordStorageScheme</code>	-
<code>passwordExpireWithoutWarning</code>	-
<code>passwordLockout</code>	<code>pwdLockout</code>
<code>passwordLockoutDuration</code>	<code>pwdLockoutDuration</code>
<code>passwordMaxFailure</code>	<code>pwdMaxFailure</code>

TABLE 3-3 Mapping Between 5 and 6.0 Password Policy Attributes (Continued)

Legacy Directory Server Attribute	Directory Server 6.0 Attribute
passwordResetFailureCount	pwdFailureCountInterval
passwordUnlock	-

## SNMP Attributes

The entry `cn=SNMP, cn=config` does not exist in Directory Server 6.0. All attributes under this entry are therefore deprecated. For information about setting up SNMP in Directory Server 6.0, see “Setting Up SNMP for Directory Server” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*.

## UniqueID Generator Configuration Attributes

The `nsState` attribute under `cn=uniqueid generator, cn=config` must be migrated.

## Database Configuration Attributes

General database configuration attributes are stored under `cn=config, cn=ldbm database, cn=plugins, cn=config`. The following attributes must be migrated:

```

nsslapd-lookthroughlimit
nsslapd-allidsthreshold
nsslapd-cache-autosize
nsslapd-cache-autosize-split
nsslapd-cachesize
nsslapd-db-checkpoint-interval
nsslapd-db-circular-logging
nsslapd-db-durable-transactions
nsslapd-db-idl-divisor
nsslapd-db-locks
nsslapd-db-logbuf-size
nsslapd-db-logfile-size
nsslapd-db-page-size
nsslapd-db-transaction-batch-val
nsslapd-db-tx-max
nsslapd-dbncache
nsslapd-import-cachesize
nsslapd-exclude-from-export
nsslapd-disk-low-threshold
nsslapd-disk-full-threshold

```

Database-specific attributes are stored in entries of the form `cn=database instance name, cn=ldbm database, cn=plugins, cn=config`. The following attributes must be migrated:

```
nsslapd-suffix
nsslapd-cachesize
nsslapd-cachememsize
nsslapd-readonly
nsslapd-require-index
```

If your deployment uses the NetscapeRoot suffix, you must migrate the attributes under `cn=netscapeRoot`, `cn=ldb database`, `cn=plugins`, `cn=config`. You must also replace the database location (`nsslapd-directory`) with the location of the new Directory Server 6 instance.

All default index configuration attributes must be migrated, except for system indexes. Default index configuration attributes are stored in the entry `cn=default indexes`, `cn=ldb database`, `cn=plugins`, `cn=config`. Indexes for the NetscapeRoot database do not need to be migrated.

All index configuration attributes must be migrated, except for system indexes. Index configuration attributes are stored in entries of the sort `cn=index name`, `cn=index`, `cn=database instance name`, `cn=ldb database`, `cn=plugins`, `cn=config`.

All attribute encryption configuration attributes must be migrated.

## Chained Suffix Attributes

All chained suffix configuration attributes must be migrated. The following configuration attributes are common to all chained suffixes. These attributes are stored in the entry `cn=config`, `cn=chaining database`, `cn=plugins`, `cn=config`.

```
nsActivechainingComponents
nsTransmittedControls
```

The following configuration attributes apply to a default instance of a chained suffix. These attributes are stored in the entry `cn=default instance config`, `cn=chaining database`, `cn=plugins`, `cn=config`.

```
nsAbandonedSearchCheckInterval
nsBindConnectionsLimit
nsBindRetryLimit
nsBindTimeout
nsCheckLocalACI
nsConcurrentBindLimit
nsConcurrentOperationsLimit
nsConnectionLife
nsHopLimit
nsmaxresponsedelay
nsmaxtestresponsedelay
nsOperationConnectionsLimit
```

```
nsProxiedAuthorization
nsReferralOnScopedSearch
nsslapd-size-limit
nsslapd-time-limit
```

## Plug-In Configuration Attributes

If you have changed the configuration of any standard plug-in, you must update that configuration. You must also update the configuration of all custom plug-ins. At a minimum, you must recompile all custom plug-ins and add their configuration to the directory. For a detailed list of plug-in API changes, see Chapter 2, “Changes to the Plug-In API Since Directory Server 5.2,” in *Sun Java System Directory Server Enterprise Edition 6.0 Developer’s Guide*.

The following sections describe the standard plug-ins whose configuration must be migrated if you have changed it.

### 7-Bit Check Plug-In

The configuration of this plug-in is stored under `cn=7-bit check,cn=plugins,cn=config`. The following attributes must be migrated:

```
nsslapd-pluginarg*
nsslapd-pluginenabled
```

### Class of Service Plug-In

The configuration of this plug-in is stored under `cn=Class of Service,cn=plugins,cn=config`. The following attributes must be migrated:

```
nsslapd-pluginarg0
nsslapd-pluginenabled
```

### DSML Frontend Plug-In

The configuration of this plug-in is stored under `cn=DSMLv2-SOAP-HTTP,cn=frontends,cn=plugins,cn=config`. The following attributes must be migrated:

```
ds-hdsml-port
ds-hdsml-iobuffersize
ds-hdsml-requestmaxsize
ds-hdsml-responsemsgsize
ds-hdsml-poolsize
ds-hdsml-poolmaxsize
ds-hdsml-clientauthmethod
ds-hdsml-rooturl
```

```
ds-hdsml-soapschemalocation
ds-hdsml-dsmlschemalocation
nsslapd-pluginenabled
```

## Pass Through Authentication Plug-In

The configuration of this plug-in is stored under `cn=Pass Through Authentication,cn=plugins,cn=config`. The following attribute must be migrated:

```
nsslapd-pluginenabled
```

The `nsslapd-pluginarg*` attributes must be migrated only if you require the configuration for `o=netscapeRoot` to be migrated.

## Password Synchronization Plug-In

The configuration of this plug-in is stored under `cn=pswsync,cn=plugins,cn=config`. The following attribute must be migrated:

```
nsslapd-pluginenabled
```

## Referential Integrity Plug-In

The configuration of this plug-in is stored under `cn=Referential Integrity Postoperation,cn=plugins,cn=config`. The following attributes must be migrated:

```
nsslapd-pluginarg*
nsslapd-pluginenabled
```

## Retro Change Log Plug-In

The configuration of this plug-in is stored under `cn=Retro ChangeLog PlugIn,cn=plugins,cn=config`. The following attributes must be migrated:

```
nsslapd-changelogmaxage
nsslapd-changelogmaxentries
nsslapd-pluginarg*
nsslapd-pluginenabled
```

## UID Uniqueness Plug-In

The configuration of this plug-in is stored under `cn=UID Uniqueness,cn=plugins,cn=config`. The following attributes must be migrated:

```
nsslapd-pluginarg*
nsslapd-pluginenabled
```

# Migrating Security Settings Manually

When you migrate an instance manually, the order in which you perform the migration of the security and the migration of the configuration is different to when you migrate using `dsmig`. If you migrate the security settings by replacing the default Directory Server 6.0 certificate and key databases with the old databases, as described in this section, you *must* migrate the configuration first.

To migrate the security settings manually, perform the following steps:

1. If you have already started using the new instance, stop the instance.
2. Back up the certificate database and key database files on the new instance.
3. Copy the certificate database and key database files from the existing instance to the new instance.

```
$ cp serverRoot/alias/slapd-serverID-cert8.db instance-path/alias/slapd-cert8db
$ cp serverRoot/alias/slapd-serverID-key3.db instance-path/alias/slapd-key3.db
```

For 5.1 servers and earlier releases of 5.2 servers, the certificate database to be copied is `serverRoot/alias/slapd-serverID-cert7.db`.

4. Copy the password file from the existing instance to the new instance.

```
$ cp serverRoot/alias/slapd-serverID-pin.txt instance-path/alias/slapd-pin.txt
```

5. Update the certificate database password.

```
$ dsadm set-flags instance-path cert-pwd-prompt=on
```

6. Copy the certificate mapping file from the existing instance to the new instance.

```
$ cp serverRoot/shared/config/certmap.conf instance-path/alias/certmap.conf
```

7. If the existing instance uses an external security token, copy the security module database and the external token library to the new instance.

```
$ cp serverRoot/alias/secmod.db instance-path/alias/secmod.db
```

8. Start the new instance.

The security configuration attributes are migrated when you migrate the rest of the configuration attributes. In this sense, migration of the security settings is not complete until you have migrated the configuration. Migration of the configuration is described in the following section.



# Migrating User Data Manually

If your topology does not support automatic data migration, you must migrate the data manually. This involves exporting the data from the existing instance and re-importing it to the new instance.

To migrate data manually from an existing version 5 instance, perform the following steps:

1. If you already have data in the new instance, back up any conflicting suffixes in the new instance.
2. If you are migrating a master server instance in a replicated topology, make sure that the master is synchronized with all servers that are direct consumers of that master.

It is not possible to migrate the change log manually. A new change log is created in the 6.0 instance.

3. Export the required suffixes to LDIF by using the `db2ldif` command. This command exports all the suffix contents to an LDIF file, when the server is either running or stopped.

The following example exports two suffixes to a single LDIF file.

```
$ serverRoot/slapd-serverID/db2ldif -a example.ldif \
  -r -s "ou=people,dc=example,dc=com" -s "ou=departments,dc=example,dc=com"
```

In this example, `-a` specifies the resulting LDIF file, `-r` indicates that replication information should be exported, and `-s` specifies the suffixes to be included in the export.

4. On the new instance, import the LDIF files by using the `dsadm import` command. For example, the following commands import the LDIF file created previously into the two suffixes that were exported.

```
$ dsadm import instance-path example.ldif ou=people,dc=example,dc=com
$ dsadm import instance-path example.ldif ou=departments,dc=example,dc=com
```

5. If the retro change log was configured on the 5.2 instance, export the retro change log to LDIF by using the `db2ldif` command.

```
$ serverRoot/slapd-serverID/db2ldif -a changelog.ldif \
  -s "cn=changelog"
```

In this example, `-a` specifies the resulting LDIF file, and `-s` specifies the changelog suffix.

6. On the new instance, import the retro change log using the `dsadm import` command. For example, the following command imports the change log LDIF file created previously.

```
$ dsadm import instance-path changelog.ldif cn=changelog
```

7. Start the new instance.

---

**Note** – During data migration, Directory Server checks whether nested group definitions exceed 30 levels. Deep nesting can signify a circular group definition, where a nested group contains a group that is also its parent. When a group with more than 30 nesting levels is encountered, Directory Server stops calculating the `isMemberOf` attributes for additional levels.

Each time this happens, Directory Server logs an error. You safely ignore these errors, although you should examine the definition of the group mentioned in the error message for potential circular definitions.

---

## Migrating User Plug-Ins Manually

User plug-ins cannot be migrated. If you have custom user plug-ins, recompile them and add them to the Directory Server 6.0 instance manually. For a detailed list of plug-in API changes, see Chapter 2, “Changes to the Plug-In API Since Directory Server 5.2,” in *Sun Java System Directory Server Enterprise Edition 6.0 Developer’s Guide*.

## Tasks to be Performed After Manual Migration

If you have migrated your server manually, the following post-migration tasks are required before you can run the new server.

- If you have customized user plug-ins, these need to be recompiled and added to the new server manually.
- If the migrated server was part of a replicated topology, see [Chapter 4](#).
- If you have customized backup, recovery, and installation scripts, you need to rewrite these scripts to comply with the new version.

# Migrating a Replicated Topology

---

Directory Server Enterprise Edition 6.0 does not provide a way to migrate an entire replicated topology automatically. Migrating a replicated topology involves migrating each server individually. Usually, however, you should be able to migrate your entire topology without any interruption in service.

This chapter describes the issues involved in migrating replicated servers, and covers the following topics:

- [“Overview of Migrating Replicated Servers” on page 51](#)
- [“Issues Related to Migrating Replicated Servers” on page 52](#)
- [“New Replication Recommendations” on page 53](#)
- [“Migration Scenarios” on page 54](#)

## Overview of Migrating Replicated Servers

Directory Server 6.0 supports an unlimited number of masters in a multi-master topology. This and other changes might mean that you redesign your topology rather than migrate to an identical topology with new servers. See Part III, “Logical Design,” in *Sun Java System Directory Server Enterprise Edition 6.0 Deployment Planning Guide* before continuing.

When migrating replicated version 5 servers, you typically start with the consumers, continue with the hubs, and finish with the masters. This bottom-up approach involves interrupting only one server at a time, rather than interrupting an entire branch of the replication topology. The approach also helps you avoid potential custom schema synchronization issues between masters and consumers.

## Issues Related to Migrating Replicated Servers

Depending on your replication topology, and on your migration strategy, certain issues might arise when you migrate replicated servers. These issues are described in the following sections.

### Issues With the New Password Policy

If you are migrating a multi-master replicated topology, a situation will arise where a 6.0 master is replicating to a version 5 server. In this situation, an object class violation will occur if changes are made to the new password policy attributes on the 6.0 server, and replicated to the version 5 server. The password policy attributes are managed internally by the server but they might be updated in the event of a bind, a user password modify, or the addition of an entry with the `userpassword` attribute.

To avoid the object class violation, the 6.0 password policy schema file (`00ds6pwp.ldif`) *must* be copied to every version 5 server that will be supplied by a 6.0 master. When the password policy schema file has been copied, restart the version 5 server.

### Migration of Replication Agreements

If possible, you should migrate replicated servers to the same host name and port number. If you *must* change the host name or port number of a replicated server, all replication agreements that point to that server must be updated manually to point to the new server. For example, if you migrate a consumer server from `red.example.com:1389` to `blue.example.com:1389`, the replication agreements on all masters that point to `red.example.com:1389` must be updated manually to point to `blue.example.com:1389`.

Replication agreements *from* the migrated master to consumers in the topology are managed by the `dsmig` migration tool. If your topology does not support automated migration, these replication agreements must also be updated manually.

### Migration of Referrals

Referrals are also affected if you migrate a *master* replica to a new host or port. The details of each master in a topology are present in the Replica Update Vector (RUV) of all other servers in the topology. The RUV of each server is used to determine the referrals. When you change the host name or port number of a master server during migration, all referrals to that master from other servers in the topology become invalid. The easiest way to correct this is to use the following steps, in order, when performing the migration.

1. Before migrating a master server, verify that there are no pending changes to be replicated. You can use the `insync` tool to do this.

2. Demote the master server to a hub, as described in “Promoting or Demoting Replicas” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*.
3. Migrate the hub server, either using `dsmig` or the manual migration progress.
4. Promote the hub server to a master, as described in “Promoting or Demoting Replicas” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*. When you promote the hub, you must assign a `replicaID` to the new migrated master. This new `replicaID` must be different to the `replicaID` of the old server that is being migrated, and must be unique within the replicated topology.

## Manual Reset of Replication Credentials

`dsmig` does not migrate the password of the default replication manager entry (`cn=replication manager,cn=replication,cn=config`). Instead, the replication manager password is deleted. Therefore, whether you are using manual or automatic migration, you must reset the replication manager password manually.

To reset the replication manager password, use the following command:

```
$ dsconf set-server-prop -h host -p port def-repl-manager-pwd-file:filename
```

In addition, `dsmig` does not migrate non-default replication manager entries. If a version 5 replica uses an entry other than the default replication manager, and if this entry is under `cn=config`, you must add the default replication manager manually. Please refer to the documentation to add a non-default replication manager entry manually. For information about adding a non-default replication manager, see “Using a Non-Default Replication Manager” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*.

## Problems Related to Tombstone Purging

In some cases, after migrating a replicated topology you might experience problems related to tombstone purging. In some cases, tombstone entries are not purged when they should be. This problem can be resolved by re-indexing the `objectclass` attribute of the corresponding suffix.

## New Replication Recommendations

Directory Server 6.0 does not limit the number of masters in a multi-master topology. A fully-meshed, multi-master topology with no hubs or consumers is recommended in most cases.

Advantages of an all-master topology include the following:

- **Availability.** Write traffic is never disrupted if one of the servers goes down.
- **Simplicity.** In an all-master topology, there is no need to set up referrals to route reads and writes to different servers.

There may be reasons that an all-master topology is not viable in a specific deployment. For example, fractional replication cannot be used in an all-master topology because fractional replication is only supported from masters to consumers.

## Migration Scenarios

This section provides sample migration scenarios for a variety of replicated topologies.

### Migrating a Replicated Topology to an Identical Topology

Before you start migrating replicated servers, determine whether your deployment might not be better served by changing the architecture of the topology. This section describes how to migrate if you want to keep your existing topology. Migrating a replicated topology to an identical topology, involves migrating the consumers, then the hubs, then the masters. The following sections demonstrate a sample migration of a simple multi-master topology.

#### Migrating the Consumers

For each consumer in the replicated topology:

1. Reroute clients to another consumer in the topology.
2. Disable any replication agreements to the consumer you want to migrate.
3. Stop the consumer.
4. Migrate the consumer according to the instructions under [Chapter 1](#).
5. Start the consumer.
6. Enable the replication agreements from the hubs to that consumer.
7. If you have migrated the data, check that replication is in sync.
8. If you have not migrated the data, reinitialize the consumer.
9. Reroute clients back to the consumer.

The following sequence of diagrams illustrate the migration of a consumer, as described above. The first diagram shows the version 5 topology before the migration.




FIGURE 4-1 Existing version 5 Topology

The first step involves rerouting clients and disabling replication agreements, effectively isolating the consumer from the topology.




FIGURE 4-2 Isolating the Consumer From the Topology

The next step involves migrating the version 5 consumer.




FIGURE 4-3 Migrating the version 5 Consumer

The next step involves enabling the replication agreements to the new consumer, initializing the consumer if necessary, and rerouting client applications to the new consumer.






FIGURE 4-4 Placing the 6.0 Consumer Into the Topology

## Migrating the Hubs

For each hub in the replicated topology:

1. Disable replication agreements from the masters to the hub you want to migrate.
2. Disable replication agreements from the hub you want to migrate to the consumers.
3. Stop the hub.
4. Migrate the hub according to the instructions under [Chapter 1](#).
5. Start the hub.
6. Enable the replication agreements from the masters to that hub.
7. Enable the replication agreements from that hub to the consumers.
8. If you have migrated the data, check that replication is in sync.
9. If you have not migrated the data, reinitialize the hub.

The following sequence of diagrams illustrate the migration of a hub, as described above. The first diagram shows the topology before migrating the hubs.




FIGURE 4-5 Existing version 5 Topology With Migrated Consumers

The first migration step involves disabling replication agreements, effectively isolating the hub from the topology.




FIGURE 4-6 Isolating the Hub From the Topology

The next step involves migrating the version 5 hub.




FIGURE 4-7 Migrating the version 5 Hub

The next step involves enabling the replication agreements to the new hub and initializing the hub if necessary.




FIGURE 4-8 Placing the 6.0 Hub Into the Topology

Check that the replication on the consumers is in sync with the rest of the topology before migrating another hub. A server that has just been migrated does not have a change log, and can therefore not update consumer servers that are out of sync. Allow the topology to stabilize and all servers to synchronize before migrating the next supplier server.

## Migrating the Masters

For each master in the replicated topology:

1. If you have client applications that write to the master you want to migrate, reroute these applications to write to another master in the topology.
2. Ensure that the master is no longer receiving write requests. You can do this by enabling read-only mode on the master.
3. Check that replication is synchronized between the master and all its consumers.

Migration of the change log is not supported if you are migrating manually, so the preceding two steps are mandatory in this case. Although automatic migration *does* migrate the change log, you should still perform the above steps to avoid the risk of losing changes.

4. Disable any replication agreements to and from the master you want to migrate.
5. Stop the master.
6. Migrate the master according to the instructions under [Chapter 1](#).
7. Start the master.

8. Enable the replication agreements from the master to the hubs and other masters in the topology.
9. If you have migrated the data, check that replication is in sync.
10. If you have not migrated the data, reinitialize the master from another master in the topology.
11. If you rerouted client applications (Step 2), you can now route the applications to write to the migrated master.

The following sequence of diagrams illustrate the migration of a master, as described above. The first diagram shows the version 5 topology before the migration of the masters.




FIGURE 4-9 Existing version 5 Topology With Consumers and Hubs Migrated

The first step in migrating a master involves disabling replication agreements, effectively isolating the master from the topology.




FIGURE 4-10 Isolating the Master From the Topology

The next step involves migrating the version 5 master.




FIGURE 4-11 Migrating the version 5 Master

The next step involves enabling the replication agreements to and from the new master and initializing the master if necessary.




FIGURE 4-12 Placing the 6.0 Master Into the Topology

Check that the replication on all hubs and consumers is in sync with the rest of the topology before migrating another master. A server that has just been migrated does not have a change log, and can therefore not update servers that are out of sync. Allow the topology to stabilize and all servers to synchronize before migrating the next supplier server.

## Migrating a Replicated Topology to a New Topology

Before you start migrating replicated servers, determine whether your deployment might not be better served by changing the architecture of the topology. This section describes how to migrate a basic version 5 topology to a new all-master topology. Migrating to an all-master topology involves migrating the consumers, hubs, and masters, then promoting the hubs to masters and the consumers to hubs, then to masters. The following sections demonstrate a sample migration of a simple multi-master topology to a new all-master topology.

The following figure shows the existing version 5 topology.




FIGURE 4-13 Existing version 5 Topology

## Migrating All the Servers

The first step is to migrate all the servers individually, as described in “[Migrating a Replicated Topology to an Identical Topology](#)” on page 54. The resulting topology is illustrated in the following figure.






FIGURE 4-14 Existing Topology With Migrated Servers

## Promoting the Hubs

The next step involves promoting the hubs to masters, and creating a fully-meshed topology between the masters. To promote the hubs, follow the instructions in “Promoting or Demoting Replicas” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*.

The following diagram illustrates the topology when the hubs have been promoted.




FIGURE 4-15 Migrated Topology With Promoted Hub Replicas

## Promoting the Consumers

The next step involves promoting the consumers to hubs, and then to masters, and creating a fully-meshed topology between the masters. To promote the consumers, follow the instructions in “Promoting or Demoting Replicas” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*.

The following diagram illustrates the topology when the consumers have been promoted.




FIGURE 4-16 New Fully-Meshed All-Master Topology

## Migrating Over Multiple Data Centers

Migrating servers over multiple data centers involves migrating each server in each data center individually. Before you start migrating replicated servers, determine whether your deployment might not be better served by changing the architecture of the topology. If you want to keep your existing topology, follow the examples in [“Migrating a Replicated Topology to an Identical Topology”](#) on page 54 for each data center. To migrate to a new topology, follow the examples in [“Migrating a Replicated Topology to a New Topology”](#) on page 63 for each data center.



# Architectural Changes in Directory Server 6.0

---

This chapter describes the architectural changes in Directory Server 6.0 that affect migration from a previous version. For information on *all* changes and bug fixes in Directory Server 6.0, see “What’s New at a Glance” in *Sun Java System Directory Server Enterprise Edition 6.0 Evaluation Guide*.

This chapter covers the following topics:

- “Changes in the Administration Framework” on page 69
- “Changes to ACIs” on page 70
- “Command Line Changes” on page 71
- “Changes to the Console” on page 74
- “New Password Policy” on page 74
- “Changes to Plug-Ins” on page 77
- “Changes to the Installed Product Layout” on page 78

## Changes in the Administration Framework

Directory Server 6.0 does not include an administration server, as in previous versions. Servers are now registered in the Directory Service Control Center (DSCC) and can be administered remotely by using the web-based GUI or the command-line tools.

To migrate to the new administration framework, you need to do the following:

- Upgrade each server individually
- Register each server in the DSCC

## Removal of the *ServerRoot* Directory

In the new administration model, a Directory Server instance is no longer tied to a *ServerRoot*. Each Directory Server instance is a standalone directory that can be manipulated in the same manner as an ordinary standalone directory.

## Removal of the o=netscapeRoot Suffix

In previous versions of Directory Server, centralized administration information was kept in o=netscapeRoot. In the new administration model, the concept of a *configuration directory server* no longer exists. The o=netscapeRoot suffix is no longer required, and the netscapeRoot database files are therefore *not* migrated. The configuration data for this suffix can be migrated, if it is specifically required.

## Changes to ACIs

The following changes have been made to ACIs in Directory Server 6.0.

### Changes in the ACI Scope

In Directory Server 5.2 ACIs on the root DSE had base scope. In Directory Server 6.0, ACIs on the root DSE have global scope by default, equivalent to targetscope="subtree".

To reproduce the same behavior as Directory Server 5.2, add targetscope="base" to ACIs on the root DSE. If you use dsmig to migrate the configuration, this is done automatically.

### Changes in Suffix-Level ACIs

In Directory Server 5.2, the following ACI was provided, at the suffix level:

```
aci: (targetattr != "nsroledn || aci || nsLookThroughLimit ||
nsSizeLimit || nsTimeLimit || nsIdleTimeout || passwordPolicySubentry ||
passwordExpirationTime || passwordExpWarned || passwordRetryCount ||
retryCountResetTime || accountUnlockTime || passwordHistory ||
passwordAllowChangeTime")(version 3.0; acl "Allow self entry modification
except for nsroledn, aci, resource limit attributes, passwordPolicySubentry
and password policy state attributes"; allow (write)userdn ="ldap:///self");
```

This ACI allowed self-modification of user passwords, among other things. This ACI is no longer provided in Directory Server 6.0. Instead, the following global ACIs are provided by default:

```
aci: (targetattr != "aci") (targetscope = "base") (version 3.0;
aci "Enable read access to rootdse for anonymous users";
allow(read,search,compare) user dn="ldap:///anyone"; )

aci: (targetattr = "*") (version 3.0; acl "Enable full access
for Administrators group"; allow (all)(groupdn =
"ldap:///cn=Administrators,cn=config"); )
```

```
aci: (targetattr = "userPassword") ( version 3.0; acl "allow
userpassword self modification"; allow (write) userdn = "ldap:///self");)
```

In Directory Server 6.0, the default userPassword ACI at root DSE level provides equivalent access control to the default 5.2 ACI at suffix level. However, if you want to reproduce exactly the same access control as in 5.2, add the following ACI to your suffix. This ACI is the 5.2 ACI, with the new password policy operational attributes for Directory Server 6.0.

```
aci: (targetattr != "nsroledn || aci || nsLookThroughLimit ||
nsSizeLimit || nsTimeLimit || nsIdleTimeout || passwordPolicySubentry ||
passwordExpirationTime || passwordExpWarned || passwordRetryCount ||
retryCountResetTime || accountUnlockTime || passwordHistory ||
passwordAllowChangeTime || pwdAccountLockedTime || pwdChangedTime ||
pwdFailureTime || pwdGraceUseTime || pwdHistory ||
pwdLastAuthTime || pwdPolicySubentry || pwdReset")(version 3.0; acl "Allow self entry modification
except for nsroledn, aci, resource limit attributes, passwordPolicySubentry
and password policy state attributes"; allow (write)userdn ="ldap:///self");)
```

---

**Tip** – Do not allow users write access to everything and then deny write access to specific attributes. Instead, explicitly list the attributes to which you allow write access.

---

## Command Line Changes

In Directory Server 6.0 the functionality of most command-line tools is replaced by only two commands: `dsadm` and `dsconf`.

The following table shows commands used in Directory Server 5, and the corresponding commands for Directory Server 6.0. The default path of these commands when installed from native packages is `/opt/SUNWdsee/ds6/bin`. When installed from the zip installation, the default path is *install-path/ds6/bin*.

TABLE 5-1 Directory Server 5 and 6 commands

Version 5 Command	Version 6.0 Command	Description
bak2db	dsadm restore	Restore a database from backup (locally, offline)
bak2db-task	dsconf restore	Restore a database from backup (remotely, online)
db2bak	dsadm backup	Create a database backup archive (locally, offline)

TABLE 5-1 Directory Server 5 and 6 commands (Continued)

Version 5 Command	Version 6.0 Command	Description
db2bak-task	dsconf backup	Create a database backup archive (remotely, online)
db2index	dsadm reindex	Create and generate indexes (locally, offline)
db2index-task	dsconf reindex	Create and generate indexes (remotely, online)
db2ldif	dsadm export	Export database contents to LDIF (locally, offline)
db2ldif-task	dsconf export	Export database contents to LDIF (remotely, online)
entrycmp	No change	Compare the same entry in multiple replicas
fildif	No change	Create a filtered version of an LDIF file
idsktune	No change	Check patches and verifies system tuning
insync	No change	Indicate synchronization between multiple replicas
ldif2db	dsadm import	Import database contents from LDIF (locally, offline)
ldif2db-task	dsconf import	Import database contents from LDIF (remotely, online)
ldif2ldap	ldapmodify -B	Import data from LDIF over LDAP (remotely, online)
MigrateInstance5	dsmig / manual migration procedure	Migrate data from a previous version
mmldif	No change	Combine multiple LDIF files
monitor	ldapsearch on cn=monitor	Retrieve performance monitoring information
pwdhash	No change	Print the encrypted form of a password
repldisc	No change	Discover a replication topology
restart-slapd	dsadm restart	Restart a Directory Server instance
schema_push	No change	Update schema modification time stamps
start-slapd	dsadm start	Start a Directory Server instance



TABLE 5-1 Directory Server 5 and 6 commands (Continued)

Version 5 Command	Version 6.0 Command	Description
stop-slapd	dsadm stop	Stop a Directory Server instance
suffix2instance	dsconf get-suffix-prop	See the backend name for a suffix
vlvindex	dsadm reindex	Create virtual list view indexes

TABLE 5-2 Directory Server 5 and 6 Commands (Subcommands of the directoryserver Command)

Version 5 Command	Version 6.0 Command	Description
directoryserver accountstatus	ns-accountstatus	Establish account status
directoryserver activate	ns-activate	Activate an entry or group of entries
directoryserver configure	Installation procedure	Install Directory Server
directoryserver inactivate	ns-inactivate	Inactivate an entry or group of entries
directoryserver unconfigure	Uninstallation procedure	Uninstall Directory Server

## Deprecated Commands

Some version 5 commands have been deprecated in Directory Server 6.0. The following table provides a list of these commands.

TABLE 5-3 Version 5 Commands That Have Been Deprecated

Command	Description
getpwenc	Print encrypted password
ns-ldapagt	Starts a Directory Server SNMP subagent. For information about how to do this in Directory Server 6.0, see “To Set Up SNMP” in <i>Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide</i>
restore-config	Restore Administration Server configuration
saveconfig	Save Administration Server configuration

## Changes to the Console

The downloaded, Java Swing-based console has been replaced by Directory Service Control Center (DSCC). DSCC is a graphical interface that enables you to manage an entire directory service by using a web browser. The DSCC requires no migration. Migrated Directory Server instances can be registered in the DSCC. For more information about the DSCC see Chapter 1, “Directory Server Overview,” in *Sun Java System Directory Server Enterprise Edition 6.0 Reference*.

## New Password Policy

Directory Server 6.0 implements a new password policy that uses the standard object class and attributes described in the “[Password Policy for LDAP Directories](#)” Internet-Draft.

The new password policy provides the following new features:

- A grace login limit, specified by the `pwdGraceAuthNLimit` attribute. This attribute specifies the number of times an expired password can be used to authenticate. If it is not present or if it is set to 0, authentication will fail.
- Safe password modification, specified by the `pwdSafeModify` attribute. This attribute specifies whether the existing password must be sent when changing a password. If the attribute is not present, the existing password does not need to be sent.

In addition, the new password policy provides the following new controls:

- `LDAP_CONTROL_PWP_[REQUEST|RESPONSE]`
- `LDAP_CONTROL_ACCOUNT_USABLE_[REQUEST|RESPONSE]`

These controls enable LDAP clients to obtain account status information.

The `LDAP_CONTROL_PWP` control provides account status information on LDAP bind, search, modify, add, delete, modDN, and compare operations.

The following information is available, using the OID `1.3.6.1.4.1.42.2.27.8.5.1` in the search:

- Period of time before the password expires
- Number of grace login attempts remaining
- The password has expired
- The account is locked
- The password must be changed after being reset
- Password modifications are allowed
- The user must supply his/her old password
- The password quality (syntax) is insufficient
- The password is too short

- The password is too young
- The password already exists in history

The LDAP\_CONTROL\_PWP control indicates warning and error conditions. The control value is a BER octet string, with the format {t i i}, which has the following meaning:

- t is a tag defining which warning is set, if any. The value of t can be one of the following:

```
LDAP_PWP_WARNING_RESP_NONE (0x00L)
LDAP_PWP_WARNING_RESP_EXP (0x01L)
LDAP_PWP_WARNING_RESP_GRACE (0x02L)
```

- The first i indicates warning information.

The warning depends on the value set for t as follows:

- If t is set to LDAP\_PWP\_WARNING\_RESP\_NONE, the warning is -1.
- If t is set to LDAP\_PWP\_WARNING\_RESP\_EX, the warning is the number of seconds before expiration.
- If t is set to LDAP\_PWP\_WARNING\_RESP\_GRACE, the warning is the number of remaining grace logins.
- The second i indicates error information. If t is set to LDAP\_PWP\_WARNING\_RESP\_NONE, the error contains one of the following values:

```
pwp_resp_no_error (-1)
pwp_resp_expired_error (0)
pwp_resp_locked_error (1)
pwp_resp_need_change_error (2)
pwp_resp_mod_not_allowed_error (3)
pwp_resp_give_old_error (4)
pwp_resp_bad_qa_error (5)
pwp_resp_too_short_error (6)
pwp_resp_too_young_error (7)
pwp_resp_in_hist_error (8)
```

The LDAP\_CONTROL\_ACCOUNT\_USABLE control provides account status information on LDAP search operations only.

## Password Policy Compatibility

For migration purposes, the new password policy maintains compatibility with previous Directory Server versions by identifying a compatibility mode. The compatibility mode determines whether password policy attributes are handled as *old* attributes or *new* attributes, where *old* refers to Directory Server 5 password policy attributes.

The compatibility mode can be read using `dsconf` command as follows:

```
$ dsconf get-server-prop pwd-compat-mode
```

The `pwd-compat-mode` property can have one of the following values:

**DS5-compatible-mode** If you install a Directory Server instance as part of a replicated topology that includes a version 5 server, the compatibility state should be set to `DS5-compatible-mode`. In this state both old and new password policy attributes are recognized. Only version 5 password policy attributes are replicated, but both sets of attributes are stored in the database.

If you upgrade an existing standalone server to Directory Server 6.0, the compatibility state is set to `DS5-compatible-mode`. The server generates the new equivalent password policy attributes.

If you upgrade an existing server as part of a replicated topology that includes Directory Server 5 servers, the compatibility state should also set to `DS5-compatible-mode`. The server accepts both old and new password policy attributes. Both sets of attributes are stored in the database. Only version 5 attributes can be replicated (using fractional replication).

**DS6-migration-mode** As part of your migration, you can set the compatibility state to `DS6-migration-mode`. In this mode, all servers in the topology are version 6 servers, but there may be some existing Directory Server 5 password policy attributes in the database.

**DS6-mode** If you install a standalone Directory Server instance, set compatibility mode to `DS6-mode`. In this case, only new password policy attributes are recognized.

A server in `DS6-mode` can never be a supplier to or consumer of a Directory Server 5 server. When all servers have been migrated to version 6.0, `DS6-mode` should be the only compatibility mode.

The compatibility mode is set using the `dsconf` command as follows:

```
$ dsconf pwd-compat new-mode
```

The *new-mode* action takes one of the following values:

**to-DS6-migration-mode** Change to `DS6-migration-mode` from `DS5-compatible-mode`.

Once the change is made, only `DS6-migration-mode` and `DS6-mode` are available.

**to-DS6-mode** Change to `DS6-mode` from `DS6-migration-mode`.

Once the change is made, only DS6-mode is available.

The server state can move only towards stricter compliance with the new password policy specifications. Compatibility with the old password policy will not be supported indefinitely. You should therefore migrate to the new password policy as soon as is feasible for your deployment.

When you consider migrating to the new password policy, note that the `pwdChangedTime` attribute did not exist in Directory Server 5.2. This attribute is *required* by the new password policy. When the attribute is not present in the user entry, its value is calculated from the entry's `passwordExpirationTime` attribute. However, writing the calculated `pwdChangedTime` attribute to the user entry would have a large performance impact directly after migration, because the first bind for *every* entry would require a write to the directory.

The calculated `pwdChangedTime` is therefore not written to the user entry during the DS5-compatible mode. You should leave your topology in DS5-compatible-mode until you have been through an entire password expiration cycle (90 days, for example, depending on the value of `passwordMaxAge`). In this way, the `pwdChangedTime` is added gradually across the directory (at the password change of each user entry).

## Changes to Plug-Ins

This section lists the new and deprecated plug-ins in Directory Server 6.0. The section also describes what you need to do if you have custom plug-ins created with the old plug-in API.

### New Plug-Ins in Directory Server 6.0

The following plug-ins have been added in Directory Server 6.0:

```
cn=example,cn=ldbm database,cn=plugins,cn=config
cn=gle,cn=plugins,cn=config
cn=MemberOf Plugin,cn=plugins,cn=config
cn=Monitoring Plugin,cn=plugins,cn=config
cn=ObjectDeletionMatch,cn=plugins,cn=config
cn=pswsync,cn=plugins,cn=config
cn=Replication Repair,cn=plugins,cn=config
cn=RMCE,cn>Password Storage Schemes,cn=plugins,cn=config
cn=Strong Password Check,cn=plugins,cn=config
```

For information about these plug-ins see the `plugin(5dsconf)` man page.

## Plug-Ins Deprecated in Directory Server 6.0

The following plug-ins have been deprecated in Directory Server 6.0:

```
cn=aci,cn=index,cn=userRoot,cn=ldbm database,cn=plugins,cn=config
cn=cn,cn=index,cn=userRoot,cn=ldbm database,cn=plugins,cn=config
cn=encrypted attributes,cn=userRoot,cn=ldbm database,cn=plugins,cn=config
cn=entrydn,cn=index,cn=userRoot,cn=ldbm database,cn=plugins,cn=config
cn=givenName,cn=index,cn=userRoot,cn=ldbm database,cn=plugins,cn=config
cn=index,cn=userRoot,cn=ldbm database,cn=plugins,cn=config
cn=mail,cn=index,cn=userRoot,cn=ldbm database,cn=plugins,cn=config
cn=mailHost,cn=index,cn=userRoot,cn=ldbm database,cn=plugins,cn=config
cn=member,cn=index,cn=userRoot,cn=ldbm database,cn=plugins,cn=config
cn=monitor,cn=userRoot,cn=ldbm database,cn=plugins,cn=config
cn=nsCalXItemId,cn=index,cn=userRoot,cn=ldbm database,cn=plugins,cn=config
cn=nscpEntryDN,cn=index,cn=userRoot,cn=ldbm database,cn=plugins,cn=config
cn=nsRoleDN,cn=index,cn=userRoot,cn=ldbm database,cn=plugins,cn=config
cn=nsUniqueId,cn=index,cn=userRoot,cn=ldbm database,cn=plugins,cn=config
cn=nswcalCALID,cn=index,cn=userRoot,cn=ldbm database,cn=plugins,cn=config
cn=objectclass,cn=index,cn=userRoot,cn=ldbm database,cn=plugins,cn=config
cn=owner,cn=index,cn=userRoot,cn=ldbm database,cn=plugins,cn=config
cn=parentid,cn=index,cn=userRoot,cn=ldbm database,cn=plugins,cn=config
cn=pipstatus,cn=index,cn=userRoot,cn=ldbm database,cn=plugins,cn=config
cn=pipuid,cn=index,cn=userRoot,cn=ldbm database,cn=plugins,cn=config
cn=seeAlso,cn=index,cn=userRoot,cn=ldbm database,cn=plugins,cn=config
cn=sn,cn=index,cn=userRoot,cn=ldbm database,cn=plugins,cn=config
cn=uid,cn=index,cn=userRoot,cn=ldbm database,cn=plugins,cn=config
cn=uniquemember,cn=index,cn=userRoot,cn=ldbm database,cn=plugins,cn=config
cn=userRoot,cn=ldbm database,cn=plugins,cn=config
```

## Changes to the Plug-In API

If you have developed your own custom plug-ins, you need to recompile these to work with Directory Server 6.0. For a complete list of the changes made to the plug-in API, see Chapter 2, “Changes to the Plug-In API Since Directory Server 5.2,” in *Sun Java System Directory Server Enterprise Edition 6.0 Developer’s Guide*.

## Changes to the Installed Product Layout

This section summarizes the changes to the installed product layout from Directory Server 5.2. Several files and utilities have been deprecated since Directory Server 5.2, as described in the following sections.

## Administration Utilities Previously Under *ServerRoot*

In Directory Server 6.0 the Administration Server is no longer used to manage server instances.

The following system administration utilities previously located under *ServerRoot* have therefore been deprecated:

- `restart-admin`
- `start-admin`
- `startconsole`
- `stop-admin`
- `uninstall`

## Binaries Previously Under *ServerRoot/bin*

The following utilities under *ServerRoot/bin* have been deprecated:

- *ServerRoot/bin/admin/admconfig*
- *ServerRoot/bin/https/bin/ns-httpd*
- *ServerRoot/bin/https/bin/uxwdog*
- *ServerRoot/bin/slapd/server/ns-ldapagt*

On Solaris Sparc, the `ns-slapd` daemon is located in *install-path/ds6/bin/lib/sparcvSolaris-Version*. On platforms other than Solaris Sparc, the `ns-slapd` daemon is located in *install-path/ds6/bin/lib*.

## Libraries and Plug-Ins Previously Under *ServerRoot/lib*

Product libraries and plug-ins in Directory Server 5.2 were located under *ServerRoot/lib*. In Directory Server 6.0, on Solaris Sparc, these libraries and plug-ins are located in *install-path/ds6/lib/sparcvSolaris-Version*. On platforms other than Solaris Sparc, they are located directly under *install-path/ds6/lib*.

## Online Help Previously Under *ServerRoot/manual*

Console online help files were previously located under *ServerRoot/manual*. The console online help files for Directory Server 6.0 are located under `opt/SUNWdsee/ds6/dccapp/html`.

## Plug-Ins Previously Under *ServerRoot/plugins*

The following tables describes the new location of sample server plug-ins, and header files for plug-in development.

TABLE 5-4 Support for Plug-Ins

Directory Server 5.2 Plug-In Directory	Directory Server 6.0 Plug-In Directory	Remarks
<i>ServerRoot/plugins/slapd/slapd/examples</i>	<i>install-path/ds6/examples</i>	Sample plug-ins
<i>ServerRoot/plugins/slapd/slapd/include</i>	<i>install-path/ds6/include</i>	Plug-in header files

SNMP support is no longer handled within Directory Server. SNMP monitoring is now handled by the Java Enterprise System Management Framework (Java ES MF). All plug-ins and binaries related to SNMP have therefore been deprecated within Directory Server.

These plug-ins include the following:

- *ServerRoot/plugins/snmp/magt/magt*
- *ServerRoot/plugins/snmp/mibs/*
- *ServerRoot/plugins/snmp/sagt/sagt*

For information about enabling monitoring Java ES MF monitoring, see “Enabling Java ES MF Monitoring” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*.

## Utilities Previously Under *ServerRoot/shared/bin*

The following tables describes the new location of the administrative tools previously under *ServerRoot/shared/bin*. Note that as a result of the change to the administrative framework, some of these tools have been deprecated.

TABLE 5-5 Tools Previously Under *ServerRoot/shared/bin*

5.2 File	6.0 File	Purpose
<i>ServerRoot/shared/bin/admin_ip.pl</i>	Deprecated	Change IP address
<i>ServerRoot/shared/bin/entrycmp</i>	<i>install-path/ds6/bin/entrycmp</i>	Compare entries for replication
<i>ServerRoot/shared/bin/fildif</i>	<i>install-path/ds6/bin/fildif</i>	Dump filtered LDIF
<i>ServerRoot/shared/bin/insync</i>	<i>install-path/ds6/bin/insync</i>	Check replication synchronization



TABLE 5-5 Tools Previously Under *ServerRoot*/shared/bin (Continued)

5.2 File	6.0 File	Purpose
<i>ServerRoot</i> /shared/bin/ldapcompare	/usr/sfw/bin/ldapcompare	Compare attribute value In Directory Server 6.0 you must install the SUN-LDAPCSDK-TOOLS package to get this utility
<i>ServerRoot</i> /shared/bin/ldapdelete	/usr/sfw/bin/ldapdelete	Delete directory entry In Directory Server 6.0 you must install the SUN-LDAPCSDK-TOOLS package to get this utility
<i>ServerRoot</i> /shared/bin/ldapmodify	/usr/sfw/bin/ldapmodify	Modify directory entry In Directory Server 6.0 you must install the SUN-LDAPCSDK-TOOLS package to get this utility
<i>ServerRoot</i> /shared/bin/ldapsearch	/usr/sfw/bin/ldapsearch	Find directory entries In Directory Server 6.0 you must install the SUN-LDAPCSDK-TOOLS package to get this utility
<i>ServerRoot</i> /shared/bin/modutil	Deprecated	Manage PKCS #11 modules
<i>ServerRoot</i> /shared/bin/uconv	Deprecated	Convert from ISO to UTF-8
<i>ServerRoot</i> /shared/bin/repldisc	<i>install-path</i> /ds6/bin/repldisc	Discover replication topology

## Certificate and Key Files

The following table shows the new locations of the certificate and key files in Directory Server 6.0.

TABLE 5-6 Location of Certificate and Key Files

5.2 File	6.0 File	Remarks
<i>ServerRoot</i> /shared/config/certmap.conf	<i>instance-path</i> /alias/certmap.conf	Configuration file for mapping certificates to directory entries
<i>ServerRoot</i> /alias/cert8.db	<i>instance-path</i> /alias/cert8.db	Trusted certificate database file
<i>ServerRoot</i> /alias/key3.db	<i>instance-path</i> /alias/key3.db	Database file containing client keys
<i>ServerRoot</i> /alias/secmod.db	<i>instance-path</i> /alias/secmod.db	Database file containing security modules such as PKCS#11

## Silent Installation and Uninstallation Templates

In Directory Server 5.2, the *ServerRoot/setup5* directory contained sample templates for silent installation and uninstallation. Silent installation and uninstallation are no longer needed for Directory Server 6.0 and these files have therefore been deprecated.

## Server Instance Scripts Previously Under *ServerRoot/slapd-ServerID*

The command-line administration scripts previously under *ServerRoot/slapd-ServerID* have been replaced in the new administration framework and deprecated. These commands and their Directory Server 6.0 equivalents are described in “[Command Line Changes](#)” on page 71.

## Server Instance Subdirectories

The following table describes the new locations for the configuration, log and backup data previously located under *ServerRoot/slapd-instance-name*

TABLE 5-7 Instance-Specific Subdirectories

Version 5 Directory	Version 6 Directory	Remarks
<i>ServerRoot/slapd-ServerID/bak</i>	<i>instance-path/bak</i>	Directory instance database backup
<i>ServerRoot/slapd-ServerID/confbak</i>	Deprecated	Administration Server configuration backup
<i>ServerRoot/slapd-ServerID/conf_bk</i>	<i>instance-path/conf_bk</i>	Directory instance configuration backup
<i>ServerRoot/slapd-ServerID/config</i>	<i>instance-path/config</i>	Directory instance configuration
<i>ServerRoot/slapd-ServerID/config/schema</i>	<i>instance-path/config/schema</i>	Directory instance schema
<i>ServerRoot/slapd-ServerID/db</i>	<i>instance-path/db</i>	Directory instance databases
<i>ServerRoot/slapd-ServerID/ldif</i>	<i>instance-path/ds6/bin/ldif</i>	Sample LDIF files
<i>ServerRoot/slapd-ServerID/locks</i>	<i>instance-path/locks</i>	Run time process locks
<i>ServerRoot/slapd-ServerID/logs</i>	<i>instance-path/logs</i>	Server instance log files
<i>ServerRoot/slapd-ServerID/tmp</i>	<i>instance-path/tmp</i>	Run time temporary files

# Migrating Directory Proxy Server

---

There is no automatic migration path to move from a previous version to Directory Proxy Server 6.0. Directory Proxy Server 6.0 provides much more functionality than previous versions. While a one to one mapping of configuration information is therefore not possible in most instances, it is possible to configure Directory Proxy Server 6.0 to behave like a version 5 server for compatibility.

This chapter describes how the configuration properties in Directory Proxy Server 6.0 can be used to simulate a version 5 configuration.

The chapter covers the following topics:

- “Mapping the Global Configuration” on page 83
- “Mapping the Connection Pool Configuration” on page 87
- “Mapping the Groups Configuration” on page 88
- “Mapping the Properties Configuration” on page 97
- “Mapping the Events Configuration” on page 103
- “Mapping the Actions Configuration” on page 104
- “Configuring Directory Proxy Server 6.0 as a Simple Connection-Based Router” on page 104

## Mapping the Global Configuration

Before you change the Directory Proxy Server 6.0 configuration, back up the configuration by using the `dpadm backup` command. For more information, see `dpadm(1M)`.

You can configure Directory Proxy Server 6.0 by using the Directory Service Control Center (DSCC) or the `dpconf` command-line utility. For more information, see `dpconf(1M)`.

Directory Proxy Server 6.0 configuration can be retrieved as a set of properties. For example, information about the port is returned in the `listen-port` property. This section describes how to map the version 5 global configuration attributes to the corresponding properties in Directory Proxy Server 6.0, where applicable. Not all functionality can be mapped directly.

The global Directory Proxy Server 5 configuration is specified by two object classes:

- **ids-proxy-sch-LDAPProxy.** Contains the name of the Directory Proxy Server server and the DN of the global configuration object.
- **ids-proxy-sch-GlobalConfiguration.** Contains various global configuration attributes.

Because of the way in which Directory Proxy Server 6.0 is configured, Directory Proxy Server 6.0 has no equivalent for the `ids-proxy-sch-LDAPProxy` object class or its attributes.

In Iplanet Directory Access Router 5.0 (IDAR) these configuration attributes are stored under `ids-proxy-con-Config-Name=name, ou=global, ou=pd2, ou=idAR, o=services`. In Directory Proxy Server 5.2, these configuration attributes are stored under `ids-proxy-con-Config-Name=user-defined-name, ou=system, ou=dar-config, o=netscaperoot`.

The functionality of the `ids-proxy-sch-GlobalConfiguration` is provided as properties of various elements in Directory Proxy Server 6.0. The following table maps the attributes of the `ids-proxy-sch-GlobalConfiguration` object class to the corresponding properties in Directory Proxy Server 6.0.

TABLE 6-1 Mapping of Version 5 Global Configuration Attributes to 6.0 Properties

Directory Proxy Server 5 Attribute	Directory Proxy Server 6.0 Property
<code>ids-proxy-con-Config-Name</code>	No equivalent
	<p>Directory Proxy Server 6.0 has two <i>listeners</i>, a non-secure listener and a secure listener. The version 5 listen configuration attributes can be mapped to the following four listener properties. To configure listener properties, use the <code>dpconf</code> command as follows:</p> <pre>\$ dpconf set-ldap-listener-prop PROPERTY \$ dpconf set-ldaps-listener-prop PROPERTY</pre> <p>For more information, see “Configuring Listeners Between Clients and Directory Proxy Server” in <i>Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide</i>.</p>
<code>ids-proxy-con-listen-port</code>	<code>listen-port</code>
<code>ids-proxy-con-listen-host</code>	<code>listen-address</code>
<code>ids-proxy-con-listen-backlog</code>	<code>max-connection-queue-size</code>
<code>ids-proxy-con-ldaps-port</code>	<code>listen-port</code> (property of the <code>ldaps-listener</code> )

TABLE 6-1 Mapping of Version 5 Global Configuration Attributes to 6.0 Properties (Continued)

Directory Proxy Server 5 Attribute	Directory Proxy Server 6.0 Property
ids-proxy-con-max-conns	<p>This attribute can be mapped to the <code>max-client-connections</code> property of a connection handler resource limit. To configure this property, use the <code>dpconf</code> command as follows:</p> <pre>\$ dpconf set-resource-limit-policy-prop POLICY-NAME max-client-connections: VALUE</pre> <p>For more information, see “Creating and Configuring a Resource Limits Policy” in <i>Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide</i>.</p>
ids-proxy-con-userid	<p>This attribute can be mapped to the user and group names specified when an instance is created by using the following command:</p> <pre>\$ dpadm create [-u NAME -g NAME] INSTANCE-PATH</pre> <p>For more information, see “Creating and Deleting a Directory Proxy Server Instance” in <i>Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide</i>.</p>
ids-proxy-con-working-dir	<p>This attribute can be mapped to the <code>INSTANCE-PATH</code> specified when an instance is created by using the following command:</p> <pre>\$ dpadm create INSTANCE-PATH</pre> <p>For more information, see “Creating and Deleting a Directory Proxy Server Instance” in <i>Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide</i>.</p>
ids-proxy-con-include-logproperties	<p>Not equivalent. For information on configuring logging in Directory Proxy Server 6.0, see Chapter 27, “Directory Proxy Server Logging,” in <i>Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide</i>.</p>

## Mapping the Global Security Configuration

In Directory Proxy Server 5, security is configured by using attributes of the global configuration object. In Directory Proxy Server 6.0, you can configure security when you create the server instance by using the `dpadm` command. For more information, see Chapter 19, “Directory Proxy Server Certificates,” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*.

In Iplanet Directory Access Router 5.0 (IDAR) these configuration attributes are stored under `ids-proxy-con-Config-Name=name,ou=global,ou=pd2,ou=idAR,o=services`. In Directory Proxy Server 5.2, these configuration attributes are stored under `ids-proxy-con-Config-Name=user-defined-name,ou=system,ou=dar-config,o=netscape.root`.

The following table maps the version 5 security attributes to the corresponding properties in Directory Proxy Server 6.

TABLE 6-2 Mapping of Security Configuration

Directory Proxy Server 5 Attribute	Directory Proxy Server 6.0 Property
ids-proxy-con-ssl-key	ssl-key-pin
ids-proxy-con-ssl-cert	ssl-certificate-directory ssl-server-cert-alias
ids-proxy-con-send-cert-as-client This attribute enables the proxy server to send its certificate to the LDAP server to allow the LDAP server to authenticate the proxy server as an SSL client.	ssl-client-cert-alias This property enables the proxy server to send a different certificate to the LDAP server, depending on whether it is acting as an SSL Server or an SSL Client.
ids-proxy-con-server-ssl-version ids-proxy-con-client-ssl-version	No equivalent
ids-proxy-con-ssl-cert-required	This feature can be achieved by setting the following server property:  \$ dpconf set-server-prop allow-cert-based-auth:require
ids-proxy-con-ssl-cafile	No equivalent

## Managing Certificates

Directory Proxy Server 5, certificates were managed by using the `cert req` utility, or by using the console. In Directory Proxy Server 6.0, certificates are managed by using the `dpadm` command, or by using the DSCC.

Certificates must be installed on each individual data source in Directory Proxy Server 6.0.

For information about managing certificates in Directory Proxy Server 6.0, see Chapter 19, “Directory Proxy Server Certificates,” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*.

## Access Control on the Proxy Configuration

In Directory Proxy Server 5, access control on the proxy configuration is managed by ACIs in the configuration directory server. In Directory Proxy Server 6.0, access to the configuration file is restricted to the person who created the proxy instance, or to the proxy manager if the configuration is accessed through Directory Proxy Server. Editing the configuration file directly is not supported.

## Mapping the Connection Pool Configuration

Directory Proxy Server 5 can be configured to reuse existing connections to the backend LDAP servers. This can provide a significant performance gain if the backend servers are on a Wide Area Network (WAN). In Directory Proxy Server 6.0, this functionality is provided with connection pools that are configured in the backend server itself. For more information, see Chapter 20, “LDAP Data Sources and Data Source Pools,” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*.

In Iplanet Directory Access Router 5.0 (IDAR) these configuration attributes are stored under `ids-proxy-con-Config-Name=name,ou=global,ou=pd2,ou=idAR,o=services`. In Directory Proxy Server 5.2, these configuration attributes are stored under `ids-proxy-con-Config-Name=user-defined-name,ou=system,ou=dar-config,o=netscaperoot`.

The following table provides a mapping between Directory Proxy Server 5 connection configuration attributes and the corresponding Directory Proxy Server 6.0 properties.

TABLE 6-3 Mapping of Connection Pool Attributes

Directory Proxy Server 5 Attribute	Directory Proxy Server 6.0 Property
<code>ids-proxy-con-connection-pool</code>	No equivalent
<code>ids-proxy-con-connection-pool-interval</code>	<p>The connection pool grows automatically to a configured maximum. The maximum is configured by setting the following properties of an LDAP data source:</p> <p><code>num-bind-init</code>  <code>num-bin-incr</code>  <code>num-bind-limit</code>  <code>num-read-init</code>  <code>num-read-incr</code>  <code>num-read-limit</code>  <code>num-write-init</code>  <code>num-write-incr</code>  <code>num-write-limit</code></p> <p>For information about setting LDAP data source properties, see “To Configure an LDAP Data Source” in <i>Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide</i>.</p>
<code>ids-proxy-con-connection-pool-timeout</code>	<code>backendMaxReadWaitTimeInMilliSec</code>

## Mapping the Groups Configuration

Directory Proxy Server 5 uses groups to define how client connections are identified and what restrictions are placed on the client connections. In Directory Proxy Server 6.0, this functionality is achieved using connection handlers, data views and listeners.

Connection handlers, data views and listeners can be configured by using the Directory Service Control Center or by using the `dpconf` command. For more information, see Chapter 25, “Directory Proxy Server Connection Handlers,” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide* and Chapter 23, “Directory Proxy Server Data Views,” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*.

### Mapping the Group Object

In Directory Proxy Server 5, a group is defined by setting the attributes of the `ids-proxy-sch-Group` object class. Certain attributes of this object class can be mapped to Directory Proxy Server 6.0 connection handler properties. For a list of all the connection-handler properties, run the following command:

```
$ dpconf help-properties | grep connection-handler
```

In Iplanet Directory Access Router 5.0 (IDAR) these configuration attributes are stored under `ids-proxy-con-Name=name`, `ou=groups`, `ou=pd2`, `ou=iDAR`, `o=services`. In Directory Proxy Server 5.2, these configuration attributes are stored under `ou=groups`, `cn=user-defined-name`, `ou=dar-config`, `o=NetscapeRoot`.

The following table maps version 5 group attributes to the corresponding connection handler properties.

**TABLE 6-4** Mapping Between Version 5 Group Attributes and Version 6 Connection Handler Properties

Directory Proxy Server 5 Group Attribute	Directory Proxy Server 6.0 Connection Handler Property
<code>ids-proxy-con-Name</code>	<code>cn</code>
<code>ids-proxy-con-Priority</code>	<code>priority</code>
<code>ids-proxy-sch-Enable</code>	<code>is-enabled</code>
<code>ids-proxy-sch-belongs-to</code>	No equivalent
<code>ids-proxy-con-permit-auth-none:TRUE</code>	<code>allowed-auth-methods:anonymous</code>
<code>ids-proxy-con-permit-auth-sasl:TRUE</code>	<code>allowed-auth-methods:sasl</code>
<code>ids-proxy-con-permit-auth-simple:TRUE</code>	<code>allowed-auth-methods:simple</code>



## Mapping the Network Group Object

Directory Proxy Server 5 groups are configured by setting the attributes of the `ids-proxy-sch-NetworkGroup` object class. These attributes can be mapped to properties of Directory Proxy Server 6.0 connection handlers, data sources and listeners. For a list of all the properties related to these objects, run the `dpconf help-properties` command, and search for the object. For example, to locate all the properties of a connection handler, run the following command:

```
$ dpconf help-properties | grep connection-handler
```

In Iplanet Directory Access Router 5.0 (IDAR) these configuration attributes are stored under `ids-proxy-con-Name=group-name,ou=groups,ou=pd2,ou=idAR,o=services`. In Directory Proxy Server 5.2, these configuration attributes are stored under `ou=groups,cn=user-defined-name,ou=dar-config,o=NetscapeRoot`.

The following table maps Directory Proxy Server 5 network group attributes to the corresponding Directory Proxy Server 6.0 properties and describes how to set these properties by using the command line.

TABLE 6-5 Mapping Between Version 5 Network Group Attributes and 6.0 Properties

Directory Proxy Server 5 Network Group Attribute	Directory Proxy Server 6.0 Property
<code>ids-proxy-con-Client</code>	<code>domain-name-filters</code> and <code>ip-address-filters</code> properties of a connection handler
<code>ids-proxy-con-include-property</code>	No equivalent
<code>ids-proxy-con-include-rule</code>	No equivalent
<code>ids-proxy-con-ssl-policy:ssl_required</code>	Set this as a connection handler property by using the following command:  <pre>\$ dpconf set-connection-handler-prop CONNECTION-HANDLER-NAME is-ssl-mandatory:true</pre>
<code>ids-proxy-con-ssl-policy:ssl_optional</code>	Set this as an LDAP data source property by using the following command:  <pre>\$ dpconf set-ldap-data-source-prop ds1 ssl-policy:client</pre>
<code>ids-proxy-con-ssl-policy:ssl_unavailable</code>	Set this as a connection handler property by using the following command:  <pre>\$ dpconf set-connection-handler-prop CONNECTION-HANDLER-NAME is-ssl-mandatory:false</pre>

TABLE 6-5 Mapping Between Version 5 Network Group Attributes and 6.0 Properties (Continued)

Directory Proxy Server 5 Network Group Attribute	Directory Proxy Server 6.0 Property
ids-proxy-con-tcp-no-delay	Set this as a property for a specific listener port by using the following command:  \$ dpconf set-ldap-listener-prop use-tcp-no-delay:true
ids-proxy-con-allow-multi-ldapv2-bind	No equivalent
ids-proxy-con-reverse-dns-lookup	No equivalent
ids-proxy-con-timeout	This functionality exists but with less granularity than in Directory Proxy Server 5. Set this limit as a property for a specific listener port by using the following command:  \$ dpconf set-ldap-listener-prop connection-idle-timeout:value

## Mapping Bind Forwarding

Directory Proxy Server 5 bind forwarding is used to determine whether to pass a bind request on to an LDAP server or to reject the bind request and close the client's connection. Directory Proxy Server 6.0 forwards either all bind requests or no bind requests. However, by setting the `allowed-auth-methods` connection handler property, successful binds can be classified into connection handlers, according to the authentication criteria. Directory Proxy Server 6.0 can be configured to reject all requests from a specific connection handler, providing the same functionality as Directory Proxy Server 5 bind forwarding.

In Iplanet Directory Access Router 5.0 (IDAR) these configuration attributes are stored under `ids-proxy-con-Name=group-name,ou=groups,ou=pd2,ou=iDAR,o=services`. In Directory Proxy Server 5.2, these configuration attributes are stored under `ou=groups,cn=user-defined-name,ou=dar-config,o=NetscapeRoot`

The following table maps the Directory Proxy Server 5 bind forwarding attributes to the corresponding Directory Proxy Server 6 connection handler property settings.

TABLE 6-6 Mapping of Directory Proxy Server 5 Bind Forwarding Attributes to Directory Proxy Server 6 Connection Handler Property Settings

Directory Proxy Server 5 Attribute	Directory Proxy Server 6 Property
ids-proxy-con-bind-name	No equivalent
ids-proxy-con-permit-auth-none	<code>allowed-auth-methods:anonymous</code>
ids-proxy-con-permit-auth-simple	<code>allowed-auth-methods:simple</code>

TABLE 6-6 Mapping of Directory Proxy Server 5 Bind Forwarding Attributes to Directory Proxy Server 6 Connection Handler Property Settings (Continued)

Directory Proxy Server 5 Attribute	Directory Proxy Server 6 Property
ids-proxy-con-permit-auth-sasl	allowed-auth-methods:sasl

## Mapping Operation Forwarding

Operation forwarding determines how Directory Proxy Server 5 handles requests after a successful bind. In Directory Proxy Server 6.0, this functionality is provided by setting the properties of a request filtering policy. For information on configuring a request filtering policy, see “Creating and Configuring Request Filtering Policies and Search Data Hiding Rules” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*. For a list of all the properties of a request filtering policy, run the following command:

```
$ dpconf help-properties | grep request-filtering-policy
```

In Iplanet Directory Access Router 5.0 (IDAR) these configuration attributes are stored under `ids-proxy-con-Name=group-name,ou=groups,ou=pd2,ou=iDAR,o=services`. In Directory Proxy Server 5.2, these configuration attributes are stored under `ou=groups,cn=user-defined-name,ou=dar-config,o=NetscapeRoot`.

The following table maps the Directory Proxy Server 5 operation forwarding attributes to the corresponding Directory Proxy Server 6 request filtering properties.

TABLE 6-7 Mapping of Directory Proxy Server 5 Operation Forwarding Attributes to Directory Proxy Server 6 Request Filtering Properties

Directory Proxy Server 5 Attribute	Directory Proxy Server 6 Property
ids-proxy-con-permit-op-search	allow-search-operations
ids-proxy-con-permit-op-compare	allow-compare-operations
ids-proxy-con-permit-op-add	allow-add-operations
ids-proxy-con-permit-op-delete	allow-delete-operations
ids-proxy-con-permit-op-modify	allow-modify-operations
ids-proxy-con-permit-op-modrdn	allow-rename-operations
ids-proxy-con-permit-op-extended	allow-extended-operations

## Mapping Subtree Hiding

Directory Proxy Server 5 uses the `ids-proxy-con-forbidden-subtree` attribute to specify a subtree of entries to be excluded in any client request. Directory Proxy Server 6.0 provides this functionality with the `allowed-subtrees` and `prohibited-subtrees` properties of a request filtering policy. For information on hiding subtrees in this way, see “Creating and Configuring a Resource Limits Policy” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*.

If your subtrees are distributed across different backend servers, you can use the `excluded-subtrees` property of a data view to hide subtrees. For more information on hiding subtrees in this way, see “Excluding a Subtree From a Data View” in *Sun Java System Directory Server Enterprise Edition 6.0 Reference* and “To Configure Data Views With Hierarchy and a Distribution Algorithm” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*.

## Mapping Search Request Controls

In Directory Proxy Server 5, search request controls are used to prevent certain kinds of requests from reaching the LDAP server. In Directory Proxy Server 6.0, this functionality is provided by setting properties of a request filtering policy and a resource limits policy.

For information on configuring a request filtering policy, see “Creating and Configuring Request Filtering Policies and Search Data Hiding Rules” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*. For information on configuring a resource limits policy, see “Creating and Configuring a Resource Limits Policy” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*. For a list of all the properties associated with a request filtering policy, or a resource limits policy, run the `dpadm help-properties` command and search for the object. For example, to locate all properties associated with a resource limits policy, run the following command:

```
$ dpconf help-properties | grep resource-limits-policy
```

In Iplanet Directory Access Router 5.0 (IDAR) these configuration attributes are stored under `ids-proxy-con-Name=group-name,ou=groups,ou=pd2,ou=idAR,o=services`. In Directory Proxy Server 5.2, these configuration attributes are stored under `ou=groups,cn=user-defined-name,ou=dar-config,o=NetscapeRoot`.

The following table maps the Directory Proxy Server 5 search request control attributes to the corresponding Directory Proxy Server 6.0 properties.

TABLE 6-8 Mapping Directory Proxy Server 5 Search Request Control Attributes to Directory Proxy Server 6.0 Properties

Directory Proxy Server 5 Attribute	Directory Proxy Server 6.0 Property
ids-proxy-con-filter-inequality	allow-inequality-search-operations property of the request filtering policy
ids-proxy-con-min-substring-size	minimum-search-filter-substring-length property of the resource limits policy

## Mapping Compare Request Controls

In Directory Proxy Server 5, compare request controls are used to prevent certain kinds of search and compare operations from reaching the LDAP server. In Directory Proxy Server 6.0, this functionality is provided by setting properties of a request filtering policy.

For information on configuring a request filtering policy, see “Creating and Configuring Request Filtering Policies and Search Data Hiding Rules” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*.

In Iplanet Directory Access Router 5.0 (IDAR) these configuration attributes are stored under `ids-proxy-con-Name=group-name,ou=groups,ou=pd2,ou=iDAR,o=services`. In Directory Proxy Server 5.2, these configuration attributes are stored under `ou=groups,cn=user-defined-name,ou=dar-config,o=NetscapeRoot`.

The following table maps the Directory Proxy Server 5 compare request control attributes to the corresponding Directory Proxy Server 6 properties.

TABLE 6-9 Mapping of Directory Proxy Server 5 Compare Request Control Attributes to Directory Proxy Server 6 Properties

Directory Proxy Server 5 Attribute	Directory Proxy Server 6 Property
ids-proxy-con-forbidden-compare	prohibited-comparable-attribs
ids-proxy-con-permitted-compare	allowed-comparable-attribs

## Mapping Attributes Modifying Search Requests

In Directory Proxy Server 5, these attributes are used to modify the search request before it is forwarded to the server. In Directory Proxy Server 6, this functionality is provided by setting properties of a request filtering policy and a resource limits policy.

For information on configuring a request filtering policy, see “Creating and Configuring Request Filtering Policies and Search Data Hiding Rules” in *Sun Java System Directory Server*

*Enterprise Edition 6.0 Administration Guide*. For information on configuring a resource limits policy, see “Creating and Configuring a Resource Limits Policy” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*.

In Iplanet Directory Access Router 5.0 (IDAR) these configuration attributes are stored under `ids-proxy-con-Name=group-name,ou=groups,ou=pd2,ou=iDAR,o=services`. In Directory Proxy Server 5.2, these configuration attributes are stored under `ou=groups,cn=user-defined-name,ou=dar-config,o=NetscapeRoot`.

The following table maps the Directory Proxy Server 5 search request modifying attributes to the corresponding Directory Proxy Server 6 properties.

**TABLE 6-10** Mapping of Directory Proxy Server 5 Search Request Modifying Attributes to Directory Proxy Server 6 Properties

Directory Proxy Server 5 Attribute	Directory Proxy Server 6 Property
<code>ids-proxy-con-minimum-base</code>	<code>allowed-subtrees</code> property of the request filtering policy
<code>ids-proxy-con-max-scope</code>	<code>allowed-search-scopes</code> property of the request filtering policy
<code>ids-proxy-con-max-timelimit</code>	<code>search-time-limit</code> property of the resource limits policy

## Mapping Attributes Restricting Search Responses

In Directory Proxy Server 5, these attributes describe restrictions that are applied to search results being returned by the server, before they are forwarded to the client. In Directory Proxy Server 6, this functionality is provided by setting the properties of a resource limits policy and by configuring search data hiding rules.

For information about configuring a resource limits policy, see “Creating and Configuring a Resource Limits Policy” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*. For information about creating search data hiding rules, see “To Create Search Data Hiding Rules” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*. For a list of properties associated with a search data hiding rule, run the following command:

```
$ dpconf help-properties | grep search-data-hiding-rule
```

In Iplanet Directory Access Router 5.0 (IDAR) these configuration attributes are stored under `ids-proxy-con-Name=group-name,ou=groups,ou=pd2,ou=iDAR,o=services`. In Directory Proxy Server 5.2, these configuration attributes are stored under `ou=groups,cn=user-defined-name,ou=dar-config,o=NetscapeRoot`.

The following table maps the Directory Proxy Server 5 search response restriction attributes to the corresponding Directory Proxy Server 6.0 properties.

**TABLE 6-11** Mapping of Directory Proxy Server 5 Search Response Restriction Attributes to Directory Proxy Server 6.0 Properties

Directory Proxy Server 5 Attributes	Directory Proxy Server 6.0 Properties
ids-proxy-con-max-result-size	search-size-limit property of the resource limits policy
ids-proxy-con-forbidden-return	To hide a subset of attributes: rule-action:hide-attributes attributes:attribute-name  To hide an entire entry: rule-action:hide-entry
ids-proxy-con-permitted-return	rule-action:show-attributes attributes:attribute-name
ids-proxy-con-search-reference	No direct equivalent. Search continuation references are governed by the referral-policy property of the resource limits policy

## Mapping the Referral Configuration Attributes

In Directory Proxy Server 5, these attributes determine what Directory Proxy Server should do with referrals. In Directory Proxy Server 6.0, this functionality is provided by setting properties of a resource limits policy.

For information on configuring a resource limits policy, see “Creating and Configuring a Resource Limits Policy” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*.

In Iplanet Directory Access Router 5.0 (IDAR) these configuration attributes are stored under `ids-proxy-con-Name=group-name`, `ou=groups`, `ou=pd2`, `ou=iDAR`, `o=services`. In Directory Proxy Server 5.2, these configuration attributes are stored under `ou=groups`, `cn=user-defined-name`, `ou=dar-config`, `o=NetscapeRoot`.

The following table maps the Directory Proxy Server 5 referral configuration attributes to the corresponding Directory Proxy Server 6 resource limits properties.

TABLE 6-12 Mapping of Directory Proxy Server 5 Referral Configuration Attributes to Directory Proxy Server 6 resource limits Properties

Directory Proxy Server 5 Attribute	Directory Proxy Server 6 Property
ids-proxy-con-reference	referral-policy
ids-proxy-con-referral-ssl-policy	referral-policy
ids-proxy-con-referral-bind-policy	referral-bind-policy
ids-proxy-con-max-refcount	referral-hop-limit

## Mapping the Server Load Configuration

In Directory Proxy Server 5, these attributes are used to control the number of simultaneous operations and total number of operations a client can request on one connection. In Directory Proxy Server 6, this functionality is provided by setting properties of a resource limits policy.

For information on configuring a resource limits policy, see “Creating and Configuring a Resource Limits Policy” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*.

In Iplanet Directory Access Router 5.0 (IDAR) these configuration attributes are stored under `ids-proxy-con-Name=group-name,ou=groups,ou=pd2,ou=iDAR,o=services`. In Directory Proxy Server 5.2, these configuration attributes are stored under `ou=groups,cn=user-defined-name,ou=dar-config,o=NetscapeRoot`.

The following table maps the Directory Proxy Server 5 server load configuration attributes to the corresponding Directory Proxy Server 6.0 resource limits properties.

TABLE 6-13 Mapping of Directory Proxy Server 5 Server Load Configuration Attributes to Directory Proxy Server 6.0 Resource Limits Properties

Directory Proxy Server 5 Attribute	Directory Proxy Server 6.0 Property
ids-proxy-con-max-simultaneous-operations-per-connection	max-simultaneous-operations-per-connection
ids-proxy-con-operations-per-connection	max-total-operations-per-connection
ids-proxy-con-max-conns	max-connections
ids-proxy-con-max-simultaneous-conns-from-ip	max-client-connections



## Mapping the Properties Configuration

The Directory Proxy Server 5 property objects enable you to specify specialized restrictions that LDAP clients must follow. Most of the functionality of property objects is available in Directory Proxy Server 6, although it is supplied by various elements of the new architecture. The following sections describe how to map the Directory Proxy Server 5 property objects to the corresponding 6.0 functionality.

### Attribute Renaming Property

In Directory Proxy Server 5, attribute renaming is defined by the `ids-proxy-sch-RenameAttribute` object class. This object uses the `ids-proxy-con-server-attr-name` and `ids-proxy-con-client-attr-name` attributes to specify which attributes must be renamed by Directory Proxy Server.

The attribute renaming functionality is replaced in Directory Proxy Server 6 by the `attr-name-mappings` property of an LDAP data source. This property is multi-valued, and takes values of the form `client-attribute-name#server-attribute-name`. In a client request, Directory Proxy Server renames the `client-attribute-name` to the `server-attribute-name`. In a response, Directory Proxy Server renames the `server-attribute-name` to the `client-attribute-name`.

To configure this property, use the following command:

```
$ dpconf set-ldap-data-source-prop data-source-name \
  attr-name-mappings:client-attribute-name#server-attribute-name
```

### Forbidden Entry Property

In Directory Proxy Server 5, the `ids-proxy-sch-ForbiddenEntryProperty` object is used to specify a list of entries or attributes that are hidden from client applications. In Directory Proxy Server 6.0 this functionality is achieved by creating a `search-data-hiding-rule` for a request filtering policy.

In Iplanet Directory Access Router 5.0 (IDAR) these configuration attributes are stored under `ids-proxy-con-Name=group-name,ou=groups,ou=pd2,ou=iDAR,o=services`. In Directory Proxy Server 5.2, these configuration attributes are stored under `ou=groups,cn=user-defined-name,ou=dar-config,o=NetscapeRoot`.

The following table maps the attributes of the `ids-proxy-sch-ForbiddenEntryProperty` object to the corresponding properties of a search data hiding rule in Directory Proxy Server 6.0. For information about creating search data hiding rules, see “To Create Search Data Hiding Rules” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*.

TABLE 6-14 Mapping of Directory Proxy Server 5 Server Load Configuration Attributes to Directory Proxy Server 6 Resource Limits Properties

Directory Proxy Server 5 Attribute	Directory Proxy Server 6 Property
ids-proxy-con-dn-exact	target-dns
ids-proxy-con-dn-regexp	target-dn-regular-expressions
ids-proxy-con-ava	target-attr-value-assertions
ids-proxy-con-forbidden-return	To hide a subset of attributes: rule-action:hide-attributes attrs:attribute-name  To hide an entire entry: rule-action:hide-entry
ids-proxy-con-permitted-return	rule-action:show-attributes attrs:attribute-name

## LDAP Server Property

In Directory Proxy Server 5, the `ids-proxy-sch-LDAPServer` property is used to define the backend LDAP servers to which Directory Proxy Server sends requests. In Directory Proxy Server 6.0, this functionality is achieved by using LDAP data sources. You can set properties for LDAP data sources by using the Directory Service Control Center or by using the command line. For more information, see “Creating and Configuring LDAP Data Sources” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*.

In Iplanet Directory Access Router 5.0 (IDAR) these configuration attributes are stored under `ids-proxy-con-Name=server-name,ou=properties,ou=pd2,ou=iDAR,o=services`. In Directory Proxy Server 5.2, these configuration attributes are stored under `ou=groups,cn=user-defined-name,ou=dar-config,o=NetscapeRoot`.

The following table maps the attributes of the `ids-proxy-sch-LDAPServer` object class to the corresponding data source properties in Directory Proxy Server 6.0. Data sources provide additional functionality that was not provided in Directory Proxy Server 5. Not all data source properties are listed here. For a list of all the properties that can be configured for a data source, run the following command:

```
$ dpconf help-properties | grep ldap-data-source
```

TABLE 6-15 Mapping of `ids-proxy-sch-LDAPServer` Attributes to Data Source Properties

Directory Proxy Server 5 Attribute	Directory Proxy Server 6.0 Property
<code>ids-proxy-con-host</code>	<code>ldap-address</code>
<code>ids-proxy-con-port</code>	<code>ldap-port</code>
<code>ids-proxy-con-sport</code>	<code>ldaps-port</code>
<code>ids-proxy-con-supported-version</code>	No equivalent Directory Proxy Server 6.0 supports LDAP v3 backends for both version 2 and version 3 clients. Directory Proxy Server 6.0 supports the proxy authorization control version 1 and version 2.
<code>ids-proxy-con-use-version</code>	No equivalent Directory Proxy Server 6.0 supports LDAP v3 backends for both v2 and v3 clients. Directory Proxy Server 6.0 supports the proxy authorization control version 1 and version 2.
<code>ids-proxy-con-tcp-no-delay</code>	<code>use-tcp-no-delay</code>
<code>ids-proxy-con-link-security-policy</code>	<code>ssl-policy</code>
<code>ids-proxy-con-x509cert-subject</code>	No equivalent. Directory Proxy Server 6.0 does not check the subject of the certificate provided by the backend server.
<code>ids-proxy-con-keepalive-interval</code>	This functionality is achieved by setting the following properties of the LDAP data source: <code>monitoring-bind-timeout</code> <code>monitoring-entry-timeout</code> <code>monitoring-inactivity-timeout</code> <code>monitoring-interval</code> For information about setting LDAP data source properties, see “To Configure an LDAP Data Source” in <i>Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide</i> .

## Load Balancing Property

In Directory Proxy Server 5, the `ids-proxy-sch-LoadBalanceProperty` is used to configure load balancing across multiple LDAP servers. Directory Proxy Server 5 supports proportional

load balancing only, that is, each LDAP server is allotted a certain percentage of the total load. The `ids-proxy-sch-LoadBalanceProperty` object class has one attribute, `ids-proxy-con-Server`, whose value has the following syntax:

```
server-name[#percentage]
```

In Iplanet Directory Access Router 5.0 (IDAR) these configuration attributes are stored under `ids-proxy-con-Name=load-balance,ou=properties,ou=pd2,ou=iDAR,o=services`. In Directory Proxy Server 5.2, these configuration attributes are stored under `ids-proxy-con-name=load-balancing-1,ou=properties,cn=user-defined-name,ou=dir-config,o=NetS`

In Directory Proxy Server 6.0, load balancing is configured as a property of a data source pool. A data source pool is essentially a collection of LDAP servers to which Directory Proxy Server can route requests. For information about setting up a data source pool, see “Creating and Configuring LDAP Data Source Pools” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*. For a list of properties associated with a data source pool, run the following command:

```
$ dpconf help-properties | grep ldap-data-source-pool
```

Directory Proxy Server 6.0 supports proportional load balancing but also supports additional load balancing algorithms. To configure proportional load balancing, set the property of the data source pool as follows:

```
$ dpconf set-ldap-data-source-pool-prop data-source-pool-name load-balancing-algorithm:proportional
```

The percentage of load allotted to each server is configured by setting various properties of an attached data source. An attached data source is a data source that has been attached to a specific data source pool. To configure proportional load, set the weight properties of the attached data source for each operation type as follows:

```
$ dpconf set-attached-ldap-data-source-prop data-source-pool-name attached-data-source-name
add-weight:value
bind-weight:value
compare-weight:value
delete-weight:value
modify-dn-weight:value
modify-weight:value
search-weight:value
```

For more information, see “Configuring Load Balancing” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*.

## Monitoring Backend Servers

To monitor the state of its backend LDAP servers, Directory Proxy Server 5 performs an anonymous search operation on the RootDSE of each server every ten seconds. Directory Proxy

Server 6.0 has a number of properties that can be configured to monitor its backend servers. For more information, see “Retrieving Monitored Data About Data Sources” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*.

## Search Size Limit Property

Directory Proxy Server 5 uses the `ids-proxy-sch-SizeLimitProperty` to apply size limits based on the base and scope of search operations. In Directory Proxy Server 6.0, the search size limit can be configured by setting a property of the resource limits policy. A resource limits policy defines the maximum resource that Directory Proxy Server can process for a given connection handler. Use the `dpconf` command to set the search size limit for a resource policy, as follows:

```
$ dpconf set-resource-limits-policy-prop policy-name search-size-limit:number-of-entries
```

Resource limits policies control much more than just search size limit. For information on configuring resource limits policies, see “Creating and Configuring a Resource Limits Policy” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*.

In Iplanet Directory Access Router 5.0 (IDAR) these configuration attributes are stored under `ids-proxy-con-Name=group-name, ou=groups, ou=pd2, ou=iDAR, o=services`. In Directory Proxy Server 5.2, these configuration attributes are stored under `ou=groups, cn=user-defined-name, ou=dar-config, o=NetscapeRoot`.

The following table maps the attributes of a version 5 size limit property to the corresponding properties in Directory Proxy Server 6.0.

TABLE 6-16 Mapping of Version 5 Search Size Limit Attributes to 6.0 Properties

Directory Proxy Server 5 Attribute	Directory Proxy Server 6.0 Property
<code>ids-proxy-con-Size-Limit</code>	<code>search-size-limit</code>
<code>ids-proxy-con-Dn-One</code>	<code>one-level-search-base-dn</code>
<code>ids-proxy-con-Dn-Sub</code>	No equivalent

## Log Property

The logging functionality available in Directory Proxy Server 5 differs substantially from the functionality available in Directory Proxy Server 6.0.

In Directory Proxy Server 5, the following logs were maintained:

- **System log.** Includes log records of system events and errors.
- **Audit log.** Includes audit trails for all events and errors.

Directory Proxy Server 6.0 maintains an errors log file, an access log file, and administrative alerts.

The errors log and administrative alerts are equivalent to the version 5 system log. Administrative alerts are events raised by Directory Proxy Server. These events can be sent to the `syslog` daemon or to an administrator through email.

The Directory Proxy Server 6.0 access log is equivalent to the version 5 audit log.

Logs in version 5 were configured by using the `ids-proxy-sch-LogProperty` object class. Logs in Directory Proxy Server 6.0 are configured by setting properties for the access and error log, using the `dpconf` command. For example, to set properties for the access log, use the following command:

```
$ dpconf set-access-log-prop PROPERTY:VALUE
```

Directory Proxy Server 6.0 provides new log features, such as log file rotation, and enables log configuration to be fine tuned. For example, one log level can be set per message category.

In Iplanet Directory Access Router 5.0 (IDAR) log configuration attributes are stored under `ids-proxy-con-Config-Name=name,ou=global,ou=pd2,ou=idAR,o=services`. In Directory Proxy Server 5.2, log configuration attributes are stored under `ids-proxy-con-Config-Name=user-defined-name,ou=system,ou=dar-config,o=netscaperoot`.

It is not really possible to map the log configuration between Directory Proxy Server 5 and Directory Proxy Server 6.0 because the logging models between these two versions are very different. The Directory Proxy Server 5 log model combines what is logged with where it is logged. In Directory Proxy Server 6.0, the model is cleaner. One set of properties describes what is logged, and a separate set of properties describes where log messages are sent.

The following table lists the attributes of the `ids-proxy-sch-LogProperty` object class and describes at a high level how the corresponding functionality is achieved in Directory Proxy Server 6.0.

TABLE 6-17 Version 5 and Version 6 Log Functionality

Directory Proxy Server 5 Attribute	Purpose	Directory Proxy Server 6.0 Equivalent
<code>ids-proxy-con-log-level</code>	Level of logging	Global log level
<code>ids-proxy-con-stat-level</code>	Kinds of statistics logged	Monitoring data
<code>ids-proxy-con-log-syslog</code>	Syslog facility code	<code>syslog</code> output for administrative alerts No equivalent for error messages
<code>ids-proxy-con-log-file</code>	Path to log file	<code>log-file-name</code> of the <code>error-log</code> object

TABLE 6-17 Version 5 and Version 6 Log Functionality (Continued)

Directory Proxy Server 5 Attribute	Purpose	Directory Proxy Server 6.0 Equivalent
ids-proxy-con-audit-syslog	Syslog facility code for audit log	No equivalent
ids-proxy-con-audit-file	Path to audit log file	log-file-name of the access-log object

Because a one to one mapping of log configuration is not possible between the two versions, you need to understand the new logging model and then configure your new logs accordingly, rather than migrating your old log configuration. For more information, see Chapter 27, “Directory Proxy Server Logging,” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*.

## Mapping the Events Configuration

Directory Proxy Server 5 event objects are used to specify conditions that Directory Proxy Server should evaluate at predetermined states.

Two types of event objects are supported:

- **OnBindSuccess.** Evaluated when a client successfully completes a bind operation.
- **OnSSLEstablished.** Evaluated when a client successfully established an SSL session.

In Directory Proxy Server 6.0, events are implemented as properties of a connection handler. Use the `dpconf` command to set these properties. For example, run the following command to set the authentication methods for the connection handler:

```
$ dpconf set-connection-handler-prop connection-handler-name \
  allowed-auth-methods:anonymous allowed-auth-methods:sasl allowed-auth-methods:simple
```

In Iplanet Directory Access Router 5.0 (IDAR) these configuration attributes are stored under `ids-proxy-con-Config-Name=name,ou=global,ou=pd2,ou=idar,o=services`. In Directory Proxy Server 5.2, these configuration attributes are stored under `ids-proxy-con-Config-Name=user-defined-name,ou=system,ou=dir-config,o=netscaperoot`.

The following table maps the version 5 event configuration attributes to the corresponding properties in Directory Proxy Server 6.0.

TABLE 6-18 Mapping Between Version 5 Event Attributes and Version 6 Connection Handler Properties

Directory Proxy Server 5 Attribute	Directory Proxy Server 6.0 Property
ids-proxy-sch-OnBindSuccessRule	bind-dn-filters

**TABLE 6-18** Mapping Between Version 5 Event Attributes and Version 6 Connection Handler Properties *(Continued)*

Directory Proxy Server 5 Attribute	Directory Proxy Server 6.0 Property
ids-proxy-con-ssl-required	is-ssl-mandatory
ids-proxy-con-bind-anonymous	allowed-auth-methods:anonymous
ids-proxy-con-bind-simple	allowed-auth-methods:simple
ids-proxy-con-bind-sasl	allowed-auth-methods:sasl

## Mapping the Actions Configuration

Directory Proxy Server 5 supports only one action, specified by the `ids-proxy-sch-ChangeGroupAction` object class. This action enables you to configure Directory Proxy Server to change a client from one access group to another based on the evaluation of a rule. The action uses the multi-valued `ids-proxy-con-to-group` attribute to specify the groups to which the client can change.

Directory Proxy Server 6.0 connection handlers provide this functionality. After being classified into a connection handler, a connection can be automatically reclassified into another connection handler. For example, if a client connects anonymously, the connection is allocated to the connection handler configured for anonymous connections. If the client later provides a bind DN on the same connection, the connection can be reallocated to another connection handler.

For information on how to configure this functionality in Directory Proxy Server 6.0, see “Creating, Configuring, and Deleting Connection Handlers” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*.

## Configuring Directory Proxy Server 6.0 as a Simple Connection-Based Router

It is possible to configure an instance of Directory Proxy Server 6.0 to behave as a simple connection-based router, with the same functionality as Directory Proxy Server 5.2. To do this, map the configuration attributes described previously and follow the procedure describe in “Configuring Directory Proxy Server as a Connection Based Router” in *Sun Java System Directory Server Enterprise Edition 6.0 Administration Guide*



# Migrating Identity Synchronization for Windows

---

This chapter explains how to migrate your system from Identity Synchronization for Windows version 1.1, and 1.1 SP1, to version 6.0.

In the remainder of this chapter, version 1.1 includes version 1.1 SP1.

---

**Note** – When you install Identity Synchronization for Windows version 1.1, Message Queue is also installed on your system. Identity Synchronization for Windows 6.0 does *not* install Message Queue.

For installation and upgrade information about Message Queue, read the installation instructions for Java Enterprise System software at <http://docs.sun.com/coll/1286.2> (<http://docs.sun.com/coll/1286.2>).

---

This chapter includes the following sections:

- “Migration Overview” on page 106
- “Before You Migrate Identity Synchronization for Windows” on page 106
- “Preparing for Identity Synchronization for Windows Migration” on page 107
- “Migrating Your System” on page 116
- “What to Do if the 1.1 Uninstallation Fails” on page 125
- “Other Migration Scenarios” on page 139
- “Checking the Logs” on page 144

# Migration Overview

Migration from Identity Synchronization for Windows version 1.1 to version 6.0 is accomplished in the following major phases:

1. Preparing your Identity Synchronization for Windows 1.1 installation for migration.
2. Uninstalling Identity Synchronization for Windows 1.1.
3. Installing or upgrading dependent products.
4. Installing Identity Synchronization for Windows 6.0 by using the configuration and connector states you backed up.

---

**Note** – Install Identity Synchronization for Windows 6.0 on the same platform and architecture where you installed Identity Synchronization for Windows 1.1.

---

## Before You Migrate Identity Synchronization for Windows

Complete the following tasks before you migrate:

- Familiarize yourself with the new features and functionality provided in Identity Synchronization for Windows 6.0.
- Read Chapter 3, “Understanding the Product,” in *Sun Java System Directory Server Enterprise Edition 6.0 Installation Guide* for installation and configuration information that you can use to plan your migration process.
- Document your version 1.1 deployment and configuration. Be sure to note any customizations you have made to the configuration.
- Schedule migration. Because the migration process requires at least four hours, you might want to schedule migration after normal business hours.

If the input password or attribute changes while you are migrating the system, Identity Synchronization for Windows processes these changes as follows:

- **For Active Directory.** Any password changes made on Active Directory during the migration process will be synchronized on demand by the Directory Server Plug-in after the migration process.
- **For Directory Server.** Any password changes made on Directory Server during the migration process will not be synchronized. However, you can identify affected users in the Identity Synchronization for Windows 6.0 logs after completing the migration process. For more information, see “[Checking the Logs](#)” on page 144.
- **For Windows NT.** Any password changes made on NT during the migration process will not be synchronized.

However, if you use the `forcepwchg` utility, you can identify affected users and force them to change passwords again. For more information, see [“Forcing Password Changes on Windows NT” on page 116](#).

- All other attribute changes made during the migration process (at any directory source) will be synchronized after the migration process.

## Preparing for Identity Synchronization for Windows Migration

Use one or more of the following utilities to migrate from version 1.1 to version 6.0:

- **export11cnf.** A stand-alone utility that enables you to create an export configuration file from your Identity Synchronization for Windows 1.1 configuration. For more information, see [“Exporting Version 1.1 Configuration” on page 107](#).

The exported XML document contains the directory deployment topology and enough information to configure the Identity Synchronization for Windows 6.0 installation.

- **checktopics.** A utility that checks Message Queue synchronization topics in a 1.1 installation and determines if any undelivered messages remain in the queue.

Updates can remain in Message Queue after you stop 1.1 synchronization. You must verify that no updates exist in the Message Queue before you proceed with the migration. For more information, see [“Checking for Undelivered Messages” on page 114](#).

- **forcepwchg.** A Windows NT tool that enables you to identify users who changed passwords during the migration process and forces them to change passwords again when the version 6.0 system is ready. Password changes made on Windows NT are not captured during the migration process. For more information, see [“Forcing Password Changes on Windows NT” on page 116](#) for detailed information.

---

**Note** – These utilities facilitate the migration of Identity Synchronization for Windows version 1.1 to version 6.0. The migration is performed in the same environment where Identity Synchronization for Windows 1.1 is deployed. Consequently, these utilities are available in the Solaris/SPARC and Windows packages only.

You can find the migration utilities in the installation `migration` directory. No additional installation steps are required.

---

## Exporting Version 1.1 Configuration

You can use the `export11cnf` utility to export an existing version 1.1 configuration file to an XML file and then use the `idsync importcnf` command to import the file into the 6.0 system before installing the connectors.

---

**Tip** – Although it is possible to re-enter the 1.1 configuration manually by using the Identity Synchronization for Windows console, it is recommended that you use the `export11cnf` utility. If you do not use `export11cnf`, the state of the connectors is not preserved.

---

Exporting the version 1.1 configuration enables you to:

- Eliminate most of the initial configuration process to be performed from the management Console.
- Guarantee that the connector IDs assigned in version 6.0 match the connector IDs used in version 1.1. This simplifies the task of preserving the existing connector states that can be used directly in the version 6.0 deployment.

Back up the `persist` and `etc` directories, and then restore them later to avoid confusion about the underlying directory structure.

You can find the `export11cnf` utility in the installation `migration` directory. No additional installation steps are necessary.

## Using the `export11cnf` Utility

To export an Identity Synchronization for Windows configuration to an XML file, execute `export11cnf` from the `migration` directory as follows:

In a terminal window, type the following:

```
java -jar export11cnf.jar -h hostname
-p port -D bind DN
-w bind password -s rootsuffix
-q configuration password -Z -P cert-db-path
-m secmod-db-path -f filename
```

For example,

```
java -jar export11cnf.jar -D "cn=dirmanager" -w - -q - -s "dc=example,dc=com" -f
exported-configuration
```

The `export11cnf` utility shares the same common arguments as the Identity Synchronization for Windows command-line utilities. For more information, see “Common Arguments to the Idsync Subcommands” in *Sun Java System Directory Server Enterprise Edition 6.0 Installation Guide*. The `export11cnf` utility exports the current configuration into the file specified in the argument of the `-f` option.

## Inserting Clear-Text Passwords

For security reasons, the `export11cnf` utility does not export clear-text passwords from version 1.1. Instead, the utility inserts empty strings in `clearTextPassword` fields wherever applicable. For example,

```
<Credentials
  userName="cn=iswservice,cn=users,dc=example,dc=com"
  cleartextPassword=""/>
<!-- INSERT PASSWORD BETWEEN THE DOUBLE QUOTES IN THE ABOVE FIELD -->
```

You must enter a password manually, between double quotes, for every `cleartextPassword` field in the exported configuration file, before you can import the file into Identity Synchronization for Windows. `importcnf` validation prevents you from importing a configuration file with empty password values.

For example,

```
<Credentials
  userName="cn=iswservice,cn=users,dc=example,dc=com"
  cleartextPassword="mySecretPassword"/>
<!-- INSERT PASSWORD BETWEEN THE DOUBLE QUOTES IN THE ABOVE FIELD -->
```

## Sample Export Configuration File

In the following sample exported configuration file,

- `ad-host.example.com` refers to the Active Directory domain controller.
- `ds-host.example.com` refers to the host running Directory Server.

### EXAMPLE 7-1 Sample Export Configuration File

```
<?xml version="1.0" encoding="UTF-8"?>

<ActiveConfiguration>
  <SunDirectorySource
    parent.attr="DirectorySource"
    onDemandSSLOption="true"
    maxConnections="5"
    displayName="dc=example,dc=com"
    resyncInterval="1000">

    <SynchronizationHost
      hostOrderOfSignificance="1"
      hostname="ds-host.example.com"
      port="389"
      portSSLOption="true"
      securePort="636"/>

    <Credentials
      userName="uid=PSWConnector,
        dc=example,
        dc=com"

    </SynchronizationHost>
  </SyncScopeDefinitionSet
```

## EXAMPLE 7-1 Sample Export Configuration File (Continued)

```

        index="0"
        location="ou=people,dc=example,dc=com"
        filter=""
        creationExpression="uid=%uid%,ou=people,dc=example,dc=com"
        sulid="SUL1"/>
</SunDirectorySource>

<ActiveDirectorySource
  parent.attr="DirectorySource"
  displayName="example.com"
  resyncInterval="1000">
  <SynchronizationHost
    hostOrderOfSignificance="1"
    hostname="ad-host.example.com"
    port="389"
    portSSLOption="true"
    securePort="636">
    <Credentials
      userName="cn=Administrator,cn=Users,dc=metaqa,dc=com"
      clearTextPassword=""/>
      <!-- INSERT PASSWORD BETWEEN THE DOUBLE QUOTES IN THE ABOVE FIELD -->
    </SynchronizationHost>
  <SyncScopeDefinitionSet
    index="0"
    location="cn=users,dc=example,dc=com"
    filter=""
    creationExpression="cn=%cn%,cn=users,dc=example,dc=com"
    sulid="SUL1"/>
</ActiveDirectorySource>

<ActiveDirectoryGlobals
  flowInboundCreates="true"
  flowInboundModifies="true"
  flowOutboundCreates="true"
  flowOutboundModifies="true">
  <TopologyHost
    parent.attr="SchemaLocation"
    hostname="ad-host.example.com"
    port="3268"
    portSSLOption="true"
    securePort="3269">
    <Credentials
      parent.attr="Credentials"
      userName="cn=Administrator,cn=Users,dc=example,dc=com"

```

## EXAMPLE 7-1 Sample Export Configuration File (Continued)

```

clearTextPassword=""/>
  <!-- INSERT PASSWORD BETWEEN THE DOUBLE QUOTES IN THE ABOVE FIELD -->
</TopologyHost>

<TopologyHost
  parent.attr="HostsTopologyConfiguration"
  hostname="ad-host.example.com"
  port="3268"
  portSSLOption="true"
  securePort="3269">
  <Credentials
    parent.attr="Credentials"
    userName="cn=Administrator,cn=Users,dc=example,dc=com"
    clearTextPassword=""/>
    <!-- INSERT PASSWORD BETWEEN THE DOUBLE QUOTES IN THE ABOVE FIELD -->
  </TopologyHost>

<AttributeMap>
  <AttributeDescription
    parent.attr="WindowsAttribute"
    name="lockouttime"
    syntax="1.2.840.113556.1.4.906"/>
  <AttributeDescription
    parent.attr="SunAttribute"
    name="pwdaccountlockedtime"
    syntax="1.3.6.1.4.1.1466.115.121.1.24"/>
</AttributeMap>

<AttributeDescription
  parent.attr="SignificantAttribute"
  name="lockouttime"
  syntax="1.2.840.113556.1.4.906"/>
<AttributeDescription
  parent.attr="SignificantAttribute"
  name="samaccountname"
  syntax="1.3.6.1.4.1.1466.115.121.1.15"/>
<AttributeDescription
  parent.attr="CreationAttribute"
  name="samaccountname"
  syntax="1.3.6.1.4.1.1466.115.121.1.15"/>
<AttributeMap>
  <AttributeDescription
    parent.attr="WindowsAttribute"
    name="samaccountname"
    syntax="1.3.6.1.4.1.1466.115.121.1.15"/>
  <AttributeDescription

```

**EXAMPLE 7-1** Sample Export Configuration File (Continued)

```
        parent.attr="SunAttribute"
        name="uid"
        syntax="1.3.6.1.4.1.1466.115.121.1.15"/>
</AttributeMap>

<AttributeMap>
  <AttributeDescription
    parent.attr="SunAttribute"
    name="sn"
    syntax="1.3.6.1.4.1.1466.115.121.1.15"/>
  <AttributeDescription
    parent.attr="WindowsAttribute"
    name="sn"
    syntax="1.3.6.1.4.1.1466.115.121.1.15"/>
</AttributeMap>

<AttributeDescription
  parent.attr="SignificantAttribute"
  name="sn"
  syntax="1.3.6.1.4.1.1466.115.121.1.15"/>
<AttributeDescription
  parent.attr="SignificantAttribute"
  name="cn"
  syntax="1.3.6.1.4.1.1466.115.121.1.15"/>
<AttributeDescription
  parent.attr="CreationAttribute"
  name="cn"
  syntax="1.3.6.1.4.1.1466.115.121.1.15"/>
<AttributeMap>
  <AttributeDescription
    parent.attr="SunAttribute"
    name="cn"
    syntax="1.3.6.1.4.1.1466.115.121.1.15"/>
  <AttributeDescription
    parent.attr="WindowsAttribute"
    name="cn"
    syntax="1.3.6.1.4.1.1466.115.121.1.15"/>
</AttributeMap>

<AttributeMap>
  <AttributeDescription
    parent.attr="SunAttribute"
    name="uniquemember"
    syntax="1.3.6.1.4.1.1466.115.121.1.25"/>
  <AttributeDescription
    parent.attr="WindowsAttribute"
```



## EXAMPLE 7-1 Sample Export Configuration File (Continued)

```

        name="member"
        syntax="1.2.840.113556.1.4.910"/>
</AttributeMap>

<AttributeDescription
    parent.attr="SignificantAttribute"
    name="member"
    syntax="1.2.840.113556.1.4.910"/>
</ActiveDirectoryGlobals>

<SunDirectoryGlobals
    userObjectClass="inetOrgPerson"
    flowInboundCreates="true"
    flowInboundModifies="true"
    flowOutboundCreates="true"
    flowOutboundModifies="true">
<AttributeDescription
    parent.attr="SignificantAttribute"
    name="uniquemember"
    syntax="1.3.6.1.4.1.1466.115.121.1.25"/>
<AttributeDescription
    parent.attr="CreationAttribute"
    name="cn"
    syntax="1.3.6.1.4.1.1466.115.121.1.15"/>
<AttributeDescription
    parent.attr="SignificantAttribute"
    name="cn"
    syntax="1.3.6.1.4.1.1466.115.121.1.15"/>
<AttributeDescription
    parent.attr="SignificantAttribute"
    name="pwdaccountlockedtime"
    syntax="1.3.6.1.4.1.1466.115.121.1.24"/>
<TopologyHost
    parent.attr="SchemaLocation"
    hostname="ds-host.example.com"
    port="389"
    portSSLOption="false"
    securePort="636">
    <Credentials
        parent.attr="Credentials"
        userName="cn=directory manager"
        cleartextPassword=""/>
        <!-- INSERT PASSWORD BETWEEN THE DOUBLE QUOTES IN THE ABOVE FIELD -->
    </TopologyHost>
<AttributeDescription
    parent.attr="SignificantAttribute"

```

**EXAMPLE 7-1** Sample Export Configuration File (Continued)

```

        name="uid"
        syntax="1.3.6.1.4.1.1466.115.121.1.15"/>
<AttributeDescription
    parent.attr="CreationAttribute"
    name="sn"
    syntax="1.3.6.1.4.1.1466.115.121.1.15"/>
<AttributeDescription
    parent.attr="SignificantAttribute"
    name="sn"
    syntax="1.3.6.1.4.1.1466.115.121.1.15"/>
</SunDirectoryGlobals>
</ActiveConfiguration>

```

After the completion of configuration export, `export11cnf` reports the result of the operation. If the operation fails, an appropriate error message is displayed with an error identifier.

## Checking for Undelivered Messages

The migration process minimizes system downtime by preserving the connectors' states in the existing deployment. However, these states reflect only the last change received and acknowledged by the Message Queue. Therefore, you do not know whether the message was actually delivered and applied to the destination connector.

This behavior does not cause problems as long as the Message Queue remains the same. However, you will lose any messages on the Message Queue during the migration process when you install Message Queue 3.6.

You must verify that the synchronization topics on the existing Message Queue do not have any undelivered messages before you proceed with the migration. The Identity Synchronization for Windows `checktopics` utility enables you to verify that all the synchronization topics are empty and the system is not causing any problem.

### ▼ Using the `checktopics` Utility

The `checktopics` utility is delivered in the `migration` directory of the Solaris/SPARC and the Windows Identity Synchronization for Windows 6.0 package.

---

**Note** – The prerequisite to run `checktopics` is a Java Virtual Machine.

---

When you run the `checktopics` utility, it connects to the configuration directory, which contains information about Synchronization User Lists (SULs) and current synchronization

topic names used in Message Queue. In addition, when you run `checktopics`, it queries Message Queue to check how many outstanding messages remain on each active synchronization topic and then displays this information for you.

To execute the `checktopics` command line utility:

- 1 **Open a Terminal window and `cd` to the migration directory.**
- 2 **From a command prompt, type the subcommand as follows.**

```
java -jar checktopics.jar -h hostname \  
-p port -D bind-DN \  
-w bind-password -s root-suffix \  
-q configuration-password -Z
```

For example,

```
java -jar checktopics.jar -D "cn=directory manager" -w - -s "dc=example,dc=com" -q -Z
```

---

**Note** – For more information about the `checktopics` arguments, see “Common Arguments to the Idsync Subcommands” in *Sun Java System Directory Server Enterprise Edition 6.0 Installation Guide*. For more information about using `checktopics`, see “[Checking for Undelivered Messages](#)” on page 114.

After running `checktopics`, check your terminal for the following messages:

- If the operation succeeds, the terminal window displays a message stating that there are no outstanding messages in the logs.
  - If the operation fails, an appropriate error message is displayed with an error identifier.
- 

## ▼ **To Clear Messages**

If any of the active synchronization topics contain outstanding messages, use the following procedure to clear the messages.

- 1 **Restart synchronization.**
- 2 **Wait until the messages are applied to the destination connector.**
- 3 **Stop synchronization.**
- 4 **Rerun `checktopics`.**

## Forcing Password Changes on Windows NT

On Windows NT, password changes are not monitored and new password values are not captured during the migration process. Consequently, you cannot determine new password values after the migration process.

Instead of requiring all users to change passwords when you finish migrating to 6.0, you can use the `forcepwchg` command-line utility to require a password change for all the users who changed passwords during the migration process.

---

**Note** – The `forcepwchg` utility is available only in the Windows packages.

---

You can find the `forcepwchg` utility in the Windows migration directory. Execute `forcepwchg` directly from that directory. No additional installation steps are necessary.

You must run `forcepwchg` on the Primary Domain Controller (PDC) host where the NT components (connector, Change Detector DLL, and Password Filter DLL) are installed. You cannot run `forcepwchg` remotely.

The `forcepwchg` utility also prints the account names (one name per line) that it is trying to migrate. If an error occurs during the migration process, look into the next entry to the last printed entry.

## Migrating Your System

This section provides instructions for migrating a single-host deployment to version 6.0.

In a single-host deployment, all Identity Synchronization for Windows components are installed on a single host (Windows 2000 Server, Solaris version 8 or 9, or SPARC), as follows:

- Directory Server (one instance)
- Core (Message Queue, Central Logger, System Manager, and Console)
- Active Directory Connector
- Directory Server Connector
- Directory Server Plugin

---

**Note** – If you are using Solaris as your installation host, then a Windows 2000 machine with Active Directory is required for synchronization purposes only. (No components would be installed on the Windows 2000 machine.)

---

The following figure illustrates the migration process and serves as a checklist to supplement the migration instructions that follow.




FIGURE 7-1 Migrating a Single-Host Deployment

## Preparing for Migration

Use the following procedure to prepare for migration to version 6.0.

## ▼ Preparing to migrate from version 1.1, and 1.1 SP1, to version 6.0

### 1 Open a terminal window or command prompt.

- **On Solaris** type the following command.

```
uncompress -c filename | tar xf -
```

- **On Windows** type the following command or use any archive program for Windows, such as WinZip.

```
%JAVA_HOME%\bin\jar -xf filename
```

When the binaries are unpacked, the following subdirectories contain the required migration tools:

- installer/
- lib/
- migration/

Solaris	Windows
export11cnf.jar	export11cnf.jar
	forcepwchg.exe
checktopics.jar	checktopics.jar

### 2 Export your version 1.1 configuration settings to an XML file.

From the migration directory, execute `export11cnf` as described in [“Using the export11cnf Utility” on page 108](#).

```
java -jar export11cnf.jar -D "cn=directory manager" -w - \
-s "dc=example,dc=com" -q - -f export.cfg
```

### 3 Add passwords to the exported XML file.

Enter a password between the double quotes for each `clearTextPassword` field in the exported configuration file. For more information, see [“Inserting Clear-Text Passwords” on page 108](#).

### 4 Stop synchronization as described in “Starting and Stopping Synchronization” in *Sun Java System Directory Server Enterprise Edition 6.0 Installation Guide*.

## 5 Verify that your system is in a stable state.

From the migration directory, execute `checktopics` as described in “Using the `checktopics` Utility” on page 114. The following example shows the execution of the `checktopics` command.

```
java -jar checktopics.jar -D "cn=directory manager" -w - \
-s "dc=example,dc=com" -q -Z
```

## 6 Stop Identity Synchronization for Windows services (daemons) as described in “Starting and Stopping Services” in *Sun Java System Directory Server Enterprise Edition 6.0 Installation Guide*.

---

**Note** – Do not stop the Sun ONE Message Queue service.

---

## 7 On Windows NT only, perform the following steps.

### a. Stop the Sun One NT Change Detector Service by typing the following command.

```
net stop "Sun One NT ChangeDetector Service"
```

### b. Save the NT Change Detector Service counters.

i. Open the Registry Editor by executing `regedt32.exe`.

ii. Select the `HKEY_LOCAL_MACHINE` window.

iii. Navigate to the `SOFTWARE\Sun Microsystems\PSW\1.1` node.

#### iv. Save the following registry values.

- HighestChangeNumber
- LastProcessedSecLogRecordNumber
- LastProcessedSecLogTimeStamp
- QueueSize

## 8 Save the connector states by backing up the `persist` and `etc` directories from the existing 1.1 installation tree.

- On Solaris, type the following command.

```
cd serverRoot/isw-hostname
tar cf /var/tmp/connector-state.tar persist etc
```

- On Windows, type the following command.

```
cd serverRoot\isw-hostname
zip -r C:\WINNT\Temp\connector-state.zip persist
etc%JAVA_HOME%\bin\jar -cfM %TEMP%\connector-state.jar persist etc
```

Alternatively, use any archive program for Windows, such as WinZip.

- 9 **Start the Identity Synchronization for Windows services. For more information, see “Starting and Stopping Services” in *Sun Java System Directory Server Enterprise Edition 6.0 Installation Guide*.**

## Uninstalling Identity Synchronization for Windows

**Note** – The Identity Synchronization for Windows 1.1 uninstall program removes the `SUNWjss` package if it is not registered for use by another application. In particular, this situation may occur on a Solaris machine if you installed a zip version of Directory Server 5.2, where the uninstall program removes the `js3.jar` file from `/usr/share/lib/mps/secv1`.

If you encounter this situation as you migrate to Identity Synchronization for Windows 6.0, the installer reports that a required file is missing, and logs the file name to the installation log. When this happens, you must re-install the required patches and restart the installation process. For a list of required patches, see (see “Software Dependency Requirements” in *Sun Java System Directory Server Enterprise Edition 6.0 Release Notes*).

### ▼ To Uninstall Identity Synchronization for Windows Version 1.1

- 1 **Uninstall the Directory Server plug-in manually and restart each Directory Server where the plug-in was installed.**

Execute the following steps on each Directory Server where the plug-in was installed:

- a. **Remove the following entries from the Directory Server:**

```
cn=config,cn=pswsync,cn=plugins,cn=configcn=pswsync,cn=plugins,cn=config
```

For example:

```
lddelete -D "cn=directory manager" -w - -p <port \> -c cn=config,  
cn=pswsync,cn=plugins,cn=configcn=pswsync,cn=plugins,cn=config
```

- b. **Restart the Directory Server.**

- **On Solaris:** Type `type <serverRoot \>/slapd-<hostname \>/restart-slapd`
- **On Windows:** Type `type <serverRoot \>\\slapd-<hostname \>\\restart-slapd.bat`

- c. **Remove the Plugin binaries from the system.**

- **On Solaris:** Type `rm <serverRoot \>/lib/psw-plugin.sorm <serverRoot \>/lib/64/psw-plugin.so`
- **On Windows:** Type `del <serverRoot \>\\lib\\psw-plugin.dll`



- 2 Change directory (cd) to `<ServerRoot \>\isw-<hostname\>` and then use the Identity Synchronization for Windows 1.1 (or 1.1 SP1) uninstallation program to uninstall the version 1.1, and 1.1 SP1, Connectors and Core components.**

---

**Note** – You must uninstall Connectors before uninstalling Core components.

---

- **On Solaris or SPARC:** Type `./runUninstaller.sh`
- **On Windows:** Type `\\runUninstaller.bat`

- 3 Back up the product registry file and remove Identity Synchronization for Windows-related entries from the file.**

The location of the file is as follows:

- **On Solaris:** `/var/sadm/install/productregistry`
- **On Windows:** `C:\WINNT\System32\productregistry`

To remove the Identity Synchronization for Windows-related entries from the product registry file, follow the instructions provided in [“Manually Uninstalling 1.1 Core and Instances from Solaris”](#) on page 125.

- 4 *On Windows only.* After uninstalling Core, restart your machine.**

---

**Note** – If the uninstall fails, you might have to manually uninstall the Identity Synchronization for Windows components. Instructions are provided in [“What to Do if the 1.1 Uninstallation Fails”](#) on page 125

---

- 5 *On Windows only.* Verify that Identity Synchronization for Windows is not running. If necessary, you can stop the service from the command line by typing the following command.**

**net stop “Sun ONE Identity Synchronization for Windows”**

If this service continues running after uninstallation, it causes a sharing violation that prevents you from deleting the instance directory.

- 6 Remove the Identity Synchronization for Windows instance directory (`isw-<hostname\>`).**

## Installing or Upgrading the Dependent Products

Use the following steps to upgrade the Java Run Environment, install Message Queue, and upgrade Directory Server.

1. Upgrade the Java 2 Runtime Environment (or Java 2 SDK) on each host (except on Windows NT) where Identity Synchronization for Windows components are installed. The minimum required version is 1.5.0.
  - **Java 2 SDK:** <http://java.sun.com/j2se/1.5.0/install.html>  
(<http://java.sun.com/j2se/1.4.2/install.html>)
  - **Java 2 Runtime Environment:** <http://java.sun.com/j2se/1.5.0/jre/install.html>  
(<http://java.sun.com/j2se/1.4.2/jre/install.html>)
2. Install Message Queue 3.6 by using the instructions provided in *Sun Java System Message Queue 3.6 Installation Guide*.
3. Upgrade Directory Server to version 6.0. For more information, see [Chapter 1](#).

---

**Note** – To keep the Administration Server intact, use the `-N` option while migrating Directory Server (configuration and data) to version 6.0. For more information on migrating configuration data and user data, see “[Using dsrmig to Migrate Configuration Data](#)” on page 31 and “[Using dsrmig to Migrate User Data](#)” on page 35 respectively.

---

The Directory Server upgrade preserves your current Directory Server configuration and database.

## Installing Identity Synchronization for Windows 6.0

Use the following steps to install the Identity Synchronization for Windows 6.0 components.

### ▼ To install the Identity Synchronization for Windows 6.0 components:

- 1 **Install Identity Synchronization for Windows 6.0 Core.** For more information, see “[Installing Core](#)” in *Sun Java System Directory Server Enterprise Edition 6.0 Installation Guide*.
- 2 **Execute `idsync preps` against Directory Server to update the schema.**
  - **On Solaris** type the following commands.
 

```
cd /opt/SUNWisw/bin
idsync preps arguments\
```
  - **On Windows** type the following commands.

```
cd serverRoot\isw-hostname\bin
idsync prepds arguments\
```

For more information about `idsync prepds`, see Appendix A, “Using the Identity Synchronization for Windows Command Line Utilities,” in *Sun Java System Directory Server Enterprise Edition 6.0 Installation Guide*.

**3 Import your version 1.1, and 1.1 SP1, configuration XML file by typing the following command.**

```
idsync importcnf arguments\
```

---

**Note** – If the program detects errors in your input configuration file, an error results. Identity Synchronization for Windows aborts the `importcnf` process and provides the necessary information to correct errors.

For more information about using `idsync importcnf`, see “Using `importcnf`” in *Sun Java System Directory Server Enterprise Edition 6.0 Installation Guide*.

---

- 4 Install the Identity Synchronization for Windows 6.0 Connectors. For more information, see “Installing Connectors” in *Sun Java System Directory Server Enterprise Edition 6.0 Installation Guide*.**
- 5 If you did not select the Configure Identity Synchronization for Windows 6.0 Directory Server Plugin option while installing Directory Server connector, configure it now. For more information, see Appendix A, “Using the Identity Synchronization for Windows Command Line Utilities,” in *Sun Java System Directory Server Enterprise Edition 6.0 Installation Guide*.**
- 6 Stop Identity Synchronization for Windows services (daemons) as described in “Starting and Stopping Services” in *Sun Java System Directory Server Enterprise Edition 6.0 Installation Guide*.**
- 7 On Windows NT only, complete the following steps.**
- a. Stop the NT Change Detector service by typing the following command.**

```
net stop "Sun Java(TM) System NT Change Detector"
```
  - b. Restore the NT Change Detector Service counters.**
    - i. Open the Registry Editor by executing `regedt32.exe`.**
    - ii. Select the `HKEY_LOCAL_MACHINE` window.**
    - iii. Navigate to the `SOFTWARE\Sun Microsystems\Sun Java(TM) System Identity Synchronization for Windows\1.1` node.**

- iv. **Double-click on each of the following entries to restore their values (which you saved prior to uninstalling version 1.1).**
  - HighestChangeNumber
  - LastProcessedSecLogRecordNumber
  - LastProcessedSecLogTimeStamp
  - QueueSize
- c. **Start the NT Change Detector service by typing the following command.**

```
net start "Sun Java(TM) System NT Change Detector"
```
- 8 **Remove the version 6.0 `persist` and `etc` directories (and all their contents) from the instance directory and restore the version 1.1, and 1.1 SP1, `persist` and `etc` directories you backed up in ["Preparing for Migration" on page 117](#).**
  - **On Solaris**, type the following command.

```
cd /var/opt/SUNWiw  
rm -rf etc persisttar xf /var/tmp/connector-state.tar
```
  - **On Windows**, type the following command.

```
cd serverRoot\isw-hostname  
rd /s etc persist%JAVA_HOME%\bin\jar -xf %TEMP%\connector-state.jar
```

Alternatively, use any archive program for Windows, such as WinZip.
- 9 **Start the service and the synchronization.**
  - a. **Start the Identity Synchronization for Windows service as described in ["Starting and Stopping Services"](#) in *Sun Java System Directory Server Enterprise Edition 6.0 Installation Guide*.**
  - b. **Start synchronization as described in ["Starting and Stopping Synchronization"](#) in *Sun Java System Directory Server Enterprise Edition 6.0 Installation Guide*.**
- 10 **Check the central audit log to verify that there are no warning messages.**

---

**Note** – If you have customized the version 1.1 log settings, you must manually apply those customizations to your version 6.0 installation. Use the Identity Synchronization for Windows Console to configure your version 6.0 log settings.

---

---

## What to Do if the 1.1 Uninstallation Fails

If the version 6.0 installation program finds remnants of the version 1.1 system, the 6.0 installation will fail. Verify that all of the 1.1 components are completely removed from the system prior to installing version 6.0.

If the uninstallation program does not uninstall all of the version 1.1 components, you must manually clean up the Identity Synchronization for Windows product registry and Solaris packages.

Detailed instructions for uninstalling Identity Synchronization for Windows version 1.1 manually are provided in the following sections:

- [“Manually Uninstalling 1.1 Core and Instances from Solaris” on page 125](#)
- [“Manually Uninstalling 1.1 Core and Instances from Windows 2000” on page 130](#)
- [“Manually Uninstalling a 1.1 Instance from Windows NT” on page 135](#)

---

**Note** – The instructions provided in this section are for uninstalling Identity Synchronization for Windows *version 1.1, and 1.1 SPI*, only.

*Do not* use the manual uninstallation procedures provided in the following sections unless the Identity Synchronization for Windows uninstallation program fails.

---

## Manually Uninstalling 1.1 Core and Instances from Solaris

Use the instructions provided in this section to manually uninstall Core from a Solaris machine.

---

**Note** – In this section, Identity Synchronization for Windows locations are described in the following manner:

```
<serverRoot \>/ isw-<hostname \>
```

where `<serverRoot \>` represents the parent directory of the Identity Synchronization for Windows installation location.

For example, if you installed Identity Synchronization for Windows in `/var/Sun/mps/isw-<example\>`, the `<serverRoot\>` would be `/var/Sun/mps`.

---

## ▼ To Manually Uninstall Core From a Solaris Machine:

- 1 **Stop all Identity Synchronization for Windows Java processes by typing `/etc/init.d/isw stop` into a terminal window.**

If the preceding command does not stop all of the Java processes, type the following commands.

```
/usr/ucb/ps -gauxwww | grep java
kill -s SIGTERM process IDs from preceding command
```

- 2 **Stop Message Queue.**

- a. **Type the following command to stop the Message Queue broker.**

```
/etc/init.d/imq stop
```

- b. **Type the following commands to stop any remaining `imq` processes.**

```
* ps -ef | grep imqbroker
* kill -s SIGTERM process IDs from preceding command
```

- c. **Use one of the following methods to uninstall the broker packages and directories.**

- Use the Message Queue broker uninstall script to uninstall the broker. This script is located in the Identity Synchronization for Windows instance directory on the host where you installed Core.

```
serverRoot/isw-hostname/imq_uninstall
```

- Manually uninstall the packages and directories.

Use the `pkgrm` command to remove the following packages.

```
SUNWaclg
SUNWiqum
SUNWiqjx
SUNWiqlen
SUNWxsrt
SUNWiqu
SUNWjaf
SUNWiqfs
SUNWjhrt
SUNWiqdoc
SUNWiquc
SUNWiqsup
SUNWiqr
SUNWjmail
```

Use the `rm -rf` command to remove the following directories.

```

/etc/imq
/var/imq
/usr/bin/imq*

```

- 3 To remove the Identity Synchronization for Windows 1.1 Solaris packages, run `pkgrm package-name` for each of the packages listed in “Manually Uninstalling 1.1 Core and Instances from Solaris” on page 125.**

The following example shows the use of `pkgrm` to uninstall packages.

```
pkgrm SUNWidscm SUNWidscn SUNWidscr SUNWidsct SUNWidsoc
```

Package Name	Description
SUNWidscm	Sun ONE Directory Server Identity Synchronization package for Core components and Connectors.
SUNWidscn	Sun ONE Directory Server Identity Synchronization package for Console help files.
SUNWidscr	Sun ONE Directory Server Identity Synchronization package for Core Components.
SUNWidsct	Sun ONE Directory Server Identity Synchronization package for Connectors.
SUNWidsoc	Sun ONE Directory Server Identity Synchronization package for Object Cache.

Type the following command to verify that all of the packages were removed.

```
pkginfo | grep -i "Identity Synchronization"
```

**Note** – Run the `pkgrm package-name` command again to check if there are still existing packages due to dependencies.

- 4 Remove the Directory Server Plugin.**
- Open the Directory Server Console and select the Configuration tab.
  - In the left pane, expand the Plugins node and select the `pswsync` node.
  - In the right pane, clear the Enable plug-in check box.
  - Click Save.

e. From the Directory Server Console, locate and remove the following entry from the Configuration Directory:

```
cn=pswsync,cn=plugins,cn=config
```

f. Stop Directory Server.

g. Remove the Plugin binary by typing the following command.

```
rm -f serverRoot/lib/psw-plugin.so
```

h. Restart Directory Server.

5 Back-up (copy and rename) the current productregistry file located in /var/sadm/install/productregistry.

6 Manually edit the productregistry file in /var/sadm/install/ to remove the following entries, if present:

---

**Note –**

- For best results, use an XML editor. Alternatively, you can use a standard text editor.
- Some of the following components may not be included in your file.
- You must delete the beginning tag (<compid\>), ending tag (</compid\>), and all contents in-between both tags). Ellipses are used in the following list to represent any additional text, or tags that are included as part of these tags. See the example on [“Manually Uninstalling 1.1 Core and Instances from Solaris” on page 125.](#)

- 
- <compid\>Identity Synchronization for Windows . . . </compid\>
  - <compid\>Core . . . </compid\>
  - <compid\>unistaller . . . </compid\>
  - <compid\>wpsyncwatchdog . . . </compid\>
  - <compid\>setenv . . . </compid\>
  - <compid\>Create DIT . . . </compid\>
  - <compid\>Extend Schema . . . </compid\>
  - <compid\>resources . . . </compid\>
  - <compid\>CoreComponents . . . </compid\>
  - <compid\>Connector . . . </compid\>
  - <compid\>DSConnector . . . </compid\>
  - <compid\>Directory Server Plugin . . . </compid\>
  - <compid\>DSSubcomponents . . . </compid\>
  - <compid\>ObjectCache . . . </compid\>
  - <compid\>ObjectCacheDLLs . . . </compid\>
  - <compid\>SUNWidscr . . . </compid\>
  - <compid\>SUNWidscm . . . </compid\>
  - <compid\>SUNWidsct . . . </compid\>



- `<compid>SUNWidscn . . . </compid>`
- `<compid>SUNWidsoc . . . </compid>`
- `<compid>ADConnector . . . </compid>`

The following is an example `<compid>` tag. Remove `<compid>`, `</compid>`, and all the text and tags in-between.

```
<compid>Identity Synchronization for Windows
  <compversion>1.1
    <uniquename>Identity Synchronization for Windows</uniquename>
    <compinstance>1
      <children>
        <compref>ADConnector
          <instance>1
            <version>1.1</version>
          </instance>
        </compref>
        <compref>DSSubcomponents
          . . .
      </children>
    </compinstance>
  </compversion>
</compid>
```

## 7 Remove the following Identity Synchronization for Windows directories and files.

### a. From the installation location, type the following command.

```
rm -rf serverRoot/isw-hostname
```

### b. To remove the bootstrap files, type the following command.

```
rm -rf /etc/init.d/isw
```

## 8 Clean up the configuration directory as follows:

### a. Run the following `ldapsearch` command against the configuration directory where Identity Synchronization for Windows Core is installed to locate the Identity Synchronization for Windows Console subtree:

```
ldapsearch -D "cn=directory manager" -w password \> -b o=netscaperoot
"(nsnickname=isw)" dn
```

---

**Note** – `ldapsearch` is located in Directory Server's `<serverRoot>/shared/bin/ldapsearch`. For example, `/var/Sun/mps/shared/bin/ldapsearch`

---

The resulting entry should be similar to the following. Note that the entry always ends with *o=NetscapeRoot*.

```
"cn=Sun ONE Identity Synchronization for Windows,cn=server group,  
cn=myhost.mydomain.com,ou=mydomain.com,o=NetscapeRoot"
```

- b. Use the Directory Server Console to remove the Identity Synchronization for Windows Console subtree and all subtrees below it.**

**9 Clean up the Identity Synchronization for Windows configuration registry as follows:**

- a. Run the following `ldapsearch` command to locate the Identity Synchronization for Windows configuration registry in Directory Server:**

```
ldapsearch -D "cn=directory manager" -w < password \> -b "dc=my,dc=domain"  
"(&(objectclass=iplanetservice)(ou=IdentitySynchronization))" dn
```

The resulting entry should be similar to the following:

```
"ou=IdentitySynchronization,ou=Services,dc=my,dc=domain"
```

- b. Use the Directory Server Console to remove the Identity Synchronization for Windows configuration registry and all subtrees below it.**

**10 Clean up all other Console-related files as follows:**

- a. Remove all the Console jar files by typing:**

```
rm -rf < serverRoot \>/java/jars/isw* For example, /var/Sun/mps/java/jars/isw*
```

- b. Remove all the Console servlet jar files by typing:**

```
rm -rf <serverRoot \>/bin/isw/ For example, /var/Sun/mps/bin/isw/
```

## Manually Uninstalling 1.1 Core and Instances from Windows 2000

Use the instructions provided in this section to manually uninstall Core from a Windows 2000 machine.

---

**Note** – In this section, Identity Synchronization for Windows locations are described in the following manner:

*serverRoot\isw-hostname\*

where *serverRoot* represents the parent directory of the Identity Synchronization for Windows installation location.

For example, if you installed Identity Synchronization for Windows in C:\Program Files\Sun\mps\isw-*example*, the *serverRoot* would be C:\Program Files\Sun\mps.

---

## ▼ To uninstall Core from a Windows 2000 machine:

- 1 Stop all Identity Synchronization for Windows Java processes using one of the following methods:
  - Select Start → Settings → Control Panel → Administrative Tools → Services to open the Services window. In the right pane, right-click on Identity Synchronization for Windows and select Stop.
  - Open a Command Prompt window and type the following command.

```
net stop "Sun ONE Identity Synchronization for Windows"
```
  - If the preceding methods do not work, use the following steps to stop the Java processes manually.
    - a. Open the Services window, right-click on Identity Synchronization for Windows, and select Properties.
    - b. From the General tab in the Properties window, select Manual from the Startup type drop-down list.

---

**Note** – Although you can view Java processes (such as `pswwat chdog.exe`) from the Windows Task Manager, you cannot determine which processes are specifically related to Identity Synchronization for Windows. For this reason, do not stop processes from the Windows Task Manager.

---

- 2 For a Core uninstallation only, stop the Message Queue using one of the following methods:
  - In the Services window, right-click on iMQ Broker in the right pane and select Stop.

- **From a Command Prompt, type the following command.**  
`net stop "iMQ Broker"`
  - **If the preceding methods do not work, use the following steps to stop Message Queue manually.**
    - a. **Open the Services window, right-click on iMQ Broker and select Properties.**
    - b. **From the General tab in the Properties window, select Manual from the Startup type drop-down list.**
    - c. **Open the Directory Server Console and select the Configuration tab.**
    - d. **In the left pane, expand the Plugins node and select the pswsync node.**
    - e. **In the right pane, uncheck the Enable plug-in check box.**
    - f. **Click Save.**
    - g. **From the Console, locate and remove the following entry from the Configuration Directory:**  
`cn=pswsync,cn=plugins,cn=config`
    - h. **Stop Directory Server.**  
You can stop the server using one of the following methods:
      - **In the Services window, right-click on Sun ONE Directory Server 5.2 in the right pane and select Stop.**
      - **Open a Command Prompt window and type the following command.**  
`net stop slapd-myhostname`
    - i. **Open Windows Explorer to locate and remove the Plugin binary:**  
`<ServerRoot>\lib\psw-plugin.so`
    - j. **Restart Directory Server.**
- 3 Open a Command Prompt window and type `regedit` to open the Registry Editor window.**



**Caution** – Back up your current registry file before proceeding to [“Manually Uninstalling 1.1 Core and Instances from Windows 2000”](#) on page 130.

---

- a. **In the Registry Editor, select My Computer in the left pane.**

- b. Select Registry → Export Registry File from the menu bar.
  - c. When the Export Registry File dialog box is displayed, specify a name for the file and select a location to save the backup registry.
- 4 In the Registry Editor, select Edit → Delete from the menu bar.
- Remove the following Identity Synchronization for Windows keys from the Windows Registry:
- All entries under HKEY\_LOCAL\_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall\Identity Synchronization for Windows.
  - All CurrentControlSet and ControlSet (such as ControlSet001, ControlSet002, and so forth) entries under HKEY\_LOCAL\_MACHINE\SYSTEM\\*, which includes the following entries (if they exist).
    - ... \Control\Session Manager\Environment\< *isw-installation directory* \>
    - ... \Services\Eventlog\Application\Sun ONE Identity Synchronization for Windows
    - ... \Services\Sun ONE Identity Synchronization for Windows
    - ... \Services\iMQBroker
- 5 Backup (copy and rename) the current product registry file located in C:\WINNT\system32.
- 6 Edit the C:\WINNT\system32\product registry file to remove the following tags:

---

**Note–**

- For best results, use an XML editor. Alternatively, you can use a standard text editor.
- Some of the following components may not be included in your file.
- You must delete the beginning tag (<compid>), ending tag (</compid>), and all contents in-between both tags). Ellipses are used in the following list to represent any additional text and/or tags that are included as part of these tags. See the example “[Manually Uninstalling 1.1 Core and Instances from Windows 2000](#)” on page 130.

- 
- <compid>Identity Synchronization for Windows . . . </compid>
  - <compid>Core . . . </compid>
  - <compid>unistaller . . . </compid>
  - <compid>wpsyncwatchdog . . . </compid>
  - <compid>setenv . . . </compid>
  - <compid>Create DIT . . . </compid>
  - <compid>Extend Schema . . . </compid>
  - <compid>resources . . . </compid>
  - <compid>CoreComponents . . . </compid>
  - <compid>Connector . . . </compid>

- `<compid>DSConnector . . . </compid>`
- `<compid>Directory Server Plugin . . . </compid>`
- `<compid>DSSubcomponents . . . </compid>`
- `<compid>ObjectCache . . . </compid>`
- `<compid>ObjectCacheDLLs . . . </compid>`
- `<compid>ADConnector . . . </compid>`

The following is a `<compid>` tag sample. Remove `<compid>`, `</compid>`, and all the text and tags in-between.

```
<compid>Identity Synchronization for Windows
  <compversion>1.1
    <uniquename>Identity Synchronization for Windows</uniquename>
    <compinstance>1
      <children>
        <compref>ADConnector
          <instance>1
            <version>1.1</version>
          </instance>
        </compref>
        <compref>DSSubcomponents
          . . .
        </compref>
      </children>
    </compinstance>
  </compversion>
</compid>
```

**7 Remove the Identity Synchronization for Windows installation folder located at *serverRoot\isw-hostname*.**

For example, C:\Program Files\Sun\mps\isw-example

**8 Clean up the configuration directory as follows:**

- a. **From a Command Prompt window, run the `ldapsearch` command against the configuration directory where Identity Synchronization for Windows Core is installed to locate the Identity Synchronization for Windows Console subtree.**

---

**Note** – `ldapsearch` is located in `<serverRoot>\shared\bin\ldapsearch`.

For example, C:\Program Files\Sun\mps\shared\bin\ldapsearch

---

```
ldapsearch -D "cn=directory manager" -w <password> -b o=netscaperoot
"(nsnickname=isw)" dn
```

The resulting entry should be similar to the following (note that the entry will always end with `o=NetscapeRoot`):

```
"cn=Sun ONE Identity Synchronization for Windows,cn=server group,
cn=myhost.mydomain.com,ou=mydomain.com,o=NetscapeRoot"
```

- b. Use the Directory Server Console to remove the Identity Synchronization for Windows Console subtree that you found and all subtrees under it.

- 9 Clean up the Identity Synchronization for Windows configuration directory (also known as the configuration registry) as follows:

- a. From a Command Prompt window, run the following `ldapsearch` command to locate the Identity Synchronization for Windows configuration directory in Directory Server:

```
ldapsearch -D "cn=directory manager" -w <password \> -b "dc=my,dc=domain"
"(&(objectclass=iplanetservice)(ou=IdentitySynchronization))" dn
```

The resulting entry should be similar to the following:

```
"ou=IdentitySynchronization,ou=Services,dc=my,dc=domain"
```

- b. Use the Directory Server Console to remove the configuration directory subtree that you found, including all subtrees under it.

- 10 Clean up all other Console-related files as follows:

- a. Remove all Console jar files located in `<serverRoot>\>\java\jars\isw*` For example, `C:\Program Files\Sun\mps\java\jars\isw*`

- b. Remove all Console servlet jar files located in `<directory-server-install-root>\>\bin\isw\` For example, `C:\SunOne\Servers\bin\isw\`

**Next Steps** Restart your machine for all changes to take effect.

## ▼ Manually Uninstalling a 1.1 Instance from Windows NT

Use the instructions provided in this section to manually uninstall an instance from a Windows NT machine.

---

**Note** – In this section, Identity Synchronization for Windows locations are described as follows:

`<serverRoot>\>\isw-<hostname>`

where `<serverRoot \>` represents the parent directory of the Identity Synchronization for Windows installation location. For example, if you installed Identity Synchronization for Windows in `C:\Program Files\Sun\mps\isw- example`, the `< serverRoot \>` would be `C:\Program Files\Sun\mps`.

---

**1 Stop all the Identity Synchronization for Windows Java processes (Core and instance installations) using one of the following methods:**

- **Select Start → Settings → Control Panel → Administrative Tools → Services to open the Services window. In the right pane, right-click on Identity Synchronization for Windows and select Stop.**
- **Open a Command Prompt window and type the following command:  
net stop "Sun ONE Identity Synchronization for Windows"**
- **If the preceding methods do not work, use the following steps to stop the Java processes manually:**
  - a. **Open the Services window, right-click on Identity Synchronization for Windows, and select Properties.**
  - b. **From the General tab in the Properties window, select Manual from the Startup type drop-down list.**

---

**Note** – Although you can view Java processes (such as `pswwatchdog.exe`) from the Windows Task Manager, you cannot determine which processes are specifically related to Identity Synchronization for Windows. For this reason, do not stop processes from the Windows Task Manager.

---

**2 Stop the Change Detector service using one of the following methods:**

- **In the Services window, right-click on Sun ONE NT Change Detector Service in the right pane and select Stop.**
- **Open a Command Prompt window and type the following command:  
net stop "Sun ONE NT Change Detector Service"**



- If the preceding methods do not work, use the following steps to stop the Change Detector Service manually:
    - a. Open the Services window, right-click on Change Detector Service and select Properties.
    - b. From the General tab in the Properties window, select Manual from the Startup type drop-down list.
    - c. Restart your Windows NT computer.
- 3 You must remove Identity Synchronization for Windows registry keys. Open a Command Prompt window and type `regedt32` to open the Registry Editor window.



**Caution** – *Do not* use `regedit` because the program does not allow you to edit multi-value strings.

Backup your current Windows registry file before proceeding to [“Manually Uninstalling a 1.1 Instance from Windows NT”](#) on page 135.

- a. In the Registry Editor, select the top node (My Computer) in the left pane.
  - b. Select Registry → Export Registry File from the menu bar.
  - c. When the Export Registry File dialog box is displayed, specify a name for the file and select a location to save the backup registry.
- 4 In the Registry Editor, select Edit → Delete from the menu bar.

Remove the following Identity Synchronization for Windows keys from the Registry:

- All entries under  
HKEY\_LOCAL\_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall\Identity Synchronization for Windows
- All `CurrentControlSet` and `ControlSet` (such as `ControlSet001`, `ControlSet002`) entries under HKEY\_LOCAL\_MACHINE\SYSTEM\\*.

These entries include the following:

- ...\\Control\\Session Manager\\Environment\\ *<isw-installation directory>*
- ...\\Services\\Eventlog\\Application\\Sun ONE Identity Synchronization for Windows
- ...\\Services\\Sun ONE Identity Synchronization for Windows
- ...\\Services\\iMQBroker
- The HKEY\_LOCAL\_MACHINE\SOFTWARE\Sun Microsystems\PSW

- 5 Use **regedt32** (*do not use regedit*) to modify (do not delete) the following registry key:
  - a. Select the registry key entry in the left pane:  
HKEY\_LOCAL\_MACHINE\SYSTEM\CurrentControlSet\CONTROL\LSA  
The registry value type must be REG\_MULTI\_SZ.
  - b. In the right pane, right-click on the Notification Packages value and select Modify.
  - c. Change the PASSFLT value to FPNWCLNT.
- 6 Backup (copy and rename) the current productregistry file located in C:\WINNT\system32.
- 7 Edit the C:\WINNT\system32 productregistry file to remove the following tags:

---

**Note –**

- For best results, use an XML editor. Alternatively, you can use a standard text editor.
- Some of these components might not be included in your file.
- You must delete the beginning tag (<compid>), ending tag (</compid>), and all contents in-between both tags). Ellipses are used in the following list to represent any additional text and/or tags that are included as part of these tags. See the example on [“Manually Uninstalling 1.1 Core and Instances from Windows 2000”](#) on page 130.

- 
- <compid>Identity Synchronization for Windows . . . </compid>
  - <compid>Core . . . </compid>
  - <compid>uninstaller . . . </compid>
  - <compid>wpsyncwatchdog . . . </compid>
  - <compid>setenv . . . </compid>
  - <compid>Create DIT . . . </compid>
  - <compid>Extend Schema . . . </compid>
  - <compid>resources . . . </compid>
  - <compid>CoreComponents . . . </compid>
  - <compid>Connector . . . </compid>
  - <compid>DSConnector . . . </compid>
  - <compid>Directory Server Plugin . . . </compid>
  - <compid>DSSubcomponents . . . </compid>
  - <compid>ObjectCache . . . </compid>
  - <compid>ObjectCacheDLLs . . . </compid>
  - <compid>ADConnector . . . </compid>

The following is an example `<compid>` tag. Remove `<compid>`, `</compid>`, and all the text and tags in-between.

```
<compid>Identity Synchronization for Windows
  <compversion>1.1
    <uniquename>Identity Synchronization for Windows</uniquename>
      <compinstance>1
        <children>
          <compref>ADConnector
            <instance>1
              <version>1.1</version>
            </instance>
          </compref>
          <compref>DSSubcomponents
            . . .
        </compinstance>
      </compversion>
    </compid>
```

- 8 Remove the Identity Synchronization for Windows installation folder located at `<serverRoot>\>\isw-<hostname>`.**

For example, `C:\Program Files\Sun\mps\isw-example`

---

**Note** – You must edit the Windows registry as described in [“Manually Uninstalling a 1.1 Instance from Windows NT” on page 135](#) before proceeding to [“Manually Uninstalling a 1.1 Instance from Windows NT” on page 135](#).

---

- 9 Remove the Password Filter DLL.**

Locate the `passflt.dll` file in the `C:\winnt\system32` folder, and rename the file to `passflt.dll.old`.

- 10 Restart your machine for all changes to take effect.**

## Other Migration Scenarios

Because other deployment topologies are possible, your migration process may differ from the process described for a single-host deployment.

This section describes two alternative deployment scenarios and explains how to migrate in each case.

The sample deployment scenarios include:

- “Multi-Master Replication Deployment” on page 140
- “Multi-Host Deployment with Windows NT” on page 141

## Multi-Master Replication Deployment

In a multi-master replication (MMR) deployment, two Directory Server instances are installed on different hosts. It is possible to run the hosts on different operating systems, but in this scenario, both hosts are running on the same operating system.

Table 7-1 and Figure 7-2 illustrate how the Identity Synchronization for Windows components are distributed between the two hosts.

TABLE 7-1 Component Distribution in a Multi-Master Replication Deployment

Host 1	Host 2
Directory Server (one instance) as the secondary master for synchronized users	Directory Server (one instance) as the preferred master for synchronized users
Core (Message Queue, Central Logger, System Manager, and Console)	Directory Server Plugin
Active Directory Connector	
Directory Server Connector	
Directory Server Plugin	

The migration process keeps on-demand password synchronization running continuously on the preferred master or on the secondary master.

---

**Note** – If both hosts are running on a Solaris operating system, then a third host running Windows 2000 with Active Directory is required for synchronization purposes only. (No components would be installed on the third host.)

---

The following figure illustrates the process for migrating Identity Synchronization for Windows in a MMR deployment.




FIGURE 7-2 Migrating a Multi-Master Replication Deployment

## Multi-Host Deployment with Windows NT

Three hosts are used in this deployment scenario:

- A Windows NT system
- A host for Directory Server with the synchronized users and the Directory Server Connector

- A host for all other components

[Table 7-2](#) and [Figure 7-3](#) illustrate how the Identity Synchronization for Windows components are distributed between the three hosts.

TABLE 7-2 Multi-Host Deployment

Host 1	Host 2	Host 3
Directory Server with configuration repository	Directory Server for synchronized users	Windows NT Connector
Core (Message Queue, Central Logger, System Manager, and Console)	Directory Server Connector	Windows NT Subcomponents (Password Filter DLL and Change Detector Service)
Active Directory Connector	Directory Server Plugin	

In the previous scenario, hosts 1 and 2 are running on the same operating system.

**Note** – Directory Server at host1 contains the configuration registry and the Admin Server console. Ensure you migrate to Directory Server 6.0 using the `-N` option to keep the Admin Server intact. For more information on migrating configuration data and user data, see [“Using dsrmig to Migrate Configuration Data” on page 31](#) and [“Using dsrmig to Migrate User Data” on page 35](#) respectively.

Directory Server at host2 contains the data and the Directory Server plugin. When you migrate Directory Server to 6.0, the plugin configuration is lost. But it does not cause any problem as Identity Synchronization for Windows migration requires the connectors to be reinstalled and plugin to be reconfigured. Therefore, Directory Server at host2 should be migrated after Identity Synchronization for Windows uninstallation.

If both hosts are running a Solaris operating system, then a fourth host running Windows 2000 with Active Directory is required for synchronization purposes only. (No components would be installed on the fourth host.)

[Figure 7-3](#) illustrates the process for migrating Identity Synchronization for Windows for a multi-host deployment




FIGURE 7-3 Migrating a Multi-Host Deployment with Windows NT

## Checking the Logs

After migrating to version 6.0, check the central audit log for messages indicating a problem. In particular, check for Directory Server users whose password changes may have been missed during the migration process. Such errors would be similar to the following:

```
[16/Apr/2004:14:23:41.029 -0500] WARNING    14  CNN101 ds-connector-host.example.com
      "Unable to obtain password of user cn=JohnSmith,ou=people,dc=example,dc=com,
      because the password was encoded by a previous installation of
      Identity Synchronization for Windows Directory Server Plugin.
      The password of this user cannot be synchronized at this time.
      Update the password of    this user again in the Directory Server."
```

You will not see this log message until after you start synchronization in Identity Synchronization for Windows 6.0. This is why checking the logs is the last step of the migration procedure.



# Index

---

## A

- Active Directory
  - during migration, 116
  - hosts, 140, 142
  - MMR deployments, 140
  - multi-host deployments, 142
  - on-demand password synchronization, 106
  - password synchronization during migration, 106
  - synchronizing passwords, 106
- adding, passwords to exported XML files, 118
- arguments
  - checktopics, 115
  - importcnf, 123

## B

- binary files
  - removing, 128
  - unpacking, 118

## C

- central log directories, 19
- certificate database, default path, 19
- Change Detector subcomponents, 123, 124, 136, 142
- checktopics.jar, 118, 119
- checktopics utility
  - checktopics.jar, 118
  - clearing messages, 115
  - default location, 114

## checktopics utility (*Continued*)

- description, 114
- prerequisites, 114
- syntax, 115
- using, 114
- clear-text passwords, inserting, 108-109
- configurations, exporting, 107
- configuring, Identity Synchronization for Windows, 107
- connectors, uninstalling, 121
- consoles
  - help files, 127
  - MMR configuration, 140
  - multi-host deployments, 142
  - removing jar files, 130, 135
- Core
  - uninstalling, 121, 125, 130
- creating
  - XML configuration documents, 107

## D

- default locations, 18-21
- deployments
  - exporting topologies to XML documents, 107
  - MMR, 140
  - multi-host, 141, 142
- deployments, single-host, 116
- detecting, errors, 123
- directories
  - etc, 124

directories (*Continued*)

- isw-hostname, 121, 125, 131
- migration, 107, 108, 114, 116
- persist, 124

## Directory Server

- command line changes, 71-73
- restarting, 120
- upgrading, 122

## Directory Server Plugin

- removing, 127
- synchronizing password changes, 106
- uninstalling, 120

**E**

editing, product registry file, 133

## errors

- detecting, 123
- XML configuration file, 123

## etc directory

- backing up, 108, 119
- removing, 124
- restoring, 124

## examples

- checktopics command, 115
- export11cnf command, 108
- idsync importcnf, 109

export11cnf.jar, 108, 118

export11cnf utility, 107

- description, 107
- export11cnf.jar, 118
- inserting clear-text passwords, 108

## exporting

- 1.1 (or 1.1 SP1) configuration, 107, 108
- version 1.1, and 1.1 SP1, configuration files, 107

**F**

failures, uninstallation, 125

## forcepwchg utility

- description, 107
- forcing password changes, 116
- location, 116

forcepwchg utility (*Continued*)

- preparing for migration, 118
  - requiring password changes, 116
- forcing password changes, 116

**H**

help, removing help files, 127

## hosts

- Active Directory, 140, 142
- deployment scenarios, 141

**I**

Identity Synchronization for Windows,  
configuring, 107

## idsync importcnf

- examples, 109
- importing configuration files, 107, 123

## importcnf subcommand

- examples, 109
- importing configuration files, 107, 123

*install-path*, 19

*instance-path*, 19

instances, uninstalling 1.1 (or 1.1 SP1), 135

isw-hostname directory, 19

isw-hostname directory, 121, 125, 131

**J**

## jar files

- checktopics, 118, 119
- export11cnf, 118
- exportcnf, 108
- jss3.jar, 120
- migration tools, 118

Java Naming and Directory Interface, 17

java processes, stopping, 131

jss3.jar files, removing, 120

**L**

LDAP, ldapsearch, 129  
 ldapsearch, using, 129  
 local log directory, 19

**M**

Message Queue, 18, 131  
   upgrading, 122  
 migration  
   checking for undelivered messages, 114  
   clearing messages, 115  
   directory, 107, 108, 114, 116  
   exporting 1.1 (or 1.1 SP1) configuration, 107  
   forcing password changes, 116  
   from version 1.1 to 1 2004Q3, 105  
   preparing, 117  
   scenarios, 139, 140  
   using checktopics, 114  
 MMR  
   deployments, 140  
   migration scenarios, 140  
 multi-host deployments, 141, 142

**P**

packages  
   removing, 127  
   SUNWidscm, 127  
   SUNWidscn, 127  
   SUNWidscr, 127  
   SUNWidsct, 127  
   SUNWidsoc, 127  
   SUNWjss, 120  
 Password Filter subcomponents, 142  
 password synchronization, on demand, 106  
 passwords  
   clear-text, inserting, 108-109  
   forcing changes, 116  
   synchronizing changes with Directory Server  
   Plugin, 106  
 PDC, running forcepwhg utility, 116

persist directory  
   backing up, 108, 119  
   restoring, 124  
 preparing, for migration, 117  
 prerequisites, for checktopics utility, 114  
 processes, stopping, 131

**R**

regedt32.exe, 119, 123, 137, 138  
 registries, editing, 133  
 removing  
   binary files, 128  
   console jar files, 130, 135  
   Directory Server Plugin, 127  
   help files, 127  
   packages, 127  
   Solaris packages, 127  
 restarting  
   Directory Server, 120  
   synchronization, 115  
 restoring, directories, 124

**S**

schema, updating, 122  
 server root directory, 19  
 single-host, deployments, 116  
 SLAMD Distributed Load Generation Engine, 17  
 Solaris, removing packages, 127  
 stopping  
   java processes, 131  
   Message Queue, 131  
 subcommands  
   importcnf, 107, 109, 123  
 SUNWidscm package, 127  
 SUNWidscn package, 127  
 SUNWidscr package, 127  
 SUNWidsct package, 127  
 SUNWidsoc package, 127  
 SUNWjss package, removing, 120  
 synchronization, restarting, 115

synchronizing, changes with Directory Server Plugin, 106  
syntax  
  checktopics command, 115  
  checktopics utility, 115  
  export11cnf command, 108  
system, verifying quiescence, 114

XML configuration documents (*Continued*)  
  exporting configurations, 107, 108

## U

uninstallation failures, 125  
uninstalling  
  1.1 (or 1.1 SP1) instances, 135  
  connectors, 121  
  Core, 121, 125, 130  
  Directory Server Plugin, 120  
UNIX commands  
  removing binaries, 120  
  restarting Directory Server, 120  
  uninstalling program, 121  
unpacking product binary files, 118  
updating, schema, 122  
using, checktopics utilities, 114  
utilities  
  checktopics, 107, 114  
  export11cnf, 107  
  forcepwchg, 107  
  using checktopics, 114

## V

verifying  
  empty synchronization topics, 114  
  system quiescence, 114

## X

XML configuration documents  
  creating, 107  
  errors, 123  
  export11cnf, 107, 108