

Agile
Enterprise Integration Platform

ORACLE®

Oracle® Agile Engineering Data Management

Installation Manual for Enterprise Integration Platform
2.2.2

Part No. E18855-01

April 2012

Copyright and Trademarks

Copyright © 1995, 2012, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS

Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy and other measures to ensure the safe use of this software. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software in dangerous applications.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

This software and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third party content, products and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third party content, products or services.

CONTENTS

Copyright and Trademarks	iii
Preface	v
Overview.....	1
Prerequisites.....	3
Enterprise Integration Platform	3
Third-Party Libraries	3
Agile EDM.....	4
Basic Installation.....	5
Windows and Unix Installation.....	5
Prerequisites.....	5
Installation Steps	5
Database Creation.....	6
Configuration and Customization	9
Modifying the Configuration Files.....	9
Modifying the Mapping Files	10
Configuring EIP on Linux	10
Testing and Starting	11
Starting as a Windows Service	13
Prerequisites.....	13
Installation Steps	13
Troubleshooting.....	13
Starting as a UNIX Daemon	15
Prerequisites.....	15
Installation Steps	15
Troubleshooting.....	15
Load the Data Model	15
Define the Application Library	16
License Control.....	17
Access to the Plot Order Function	17
Update an Existing Installation.....	17

Preface

The Oracle documentation set includes Adobe® Acrobat™ PDF files. The [Oracle Technology Network \(OTN\) Web site](http://www.oracle.com/technology/documentation/agile.html) (<http://www.oracle.com/technology/documentation/agile.html>) contains the latest versions of the Oracle Agile EDM PDF files. You can view or download these manuals from the Web site, or you can ask your Agile administrator if there is an Oracle Documentation folder available on your network from which you can access the documentation (PDF) files.

Note To read the PDF files, you must use the free Adobe Acrobat Reader™ version 7.0 or later. This program can be downloaded from the [Adobe Web site](http://www.adobe.com) (<http://www.adobe.com>).

Note Before calling Agile Support about a problem with an Oracle Agile EDM manual, please have the full part number, which is located on the title page.

TTY Access to Oracle Support Services

Oracle provides dedicated Text Telephone (TTY) access to Oracle Support Services within the United States of America 24 hours a day, 7 days a week. For TTY support, call 800.446.2398. Outside the United States, call +1.407.458.2479.

Readme

Any last-minute information about Oracle Agile EDM can be found in the Release Notes file on the [Oracle Technology Network \(OTN\) Web site](http://www.oracle.com/technology/documentation/agile.html) (<http://www.oracle.com/technology/documentation/agile.html>)

Agile Training Aids

Go to the [Oracle University Web page](http://www.oracle.com/education/chooser/selectcountry_new.html) (http://www.oracle.com/education/chooser/selectcountry_new.html) for more information on Agile Training offerings.

Accessibility of Code Examples in Documentation


Screen readers may not always correctly read the code examples in this document. The conventions for writing code require that closing braces should appear on an otherwise empty line; however, some screen readers may not always read a line of text that consists solely of a bracket or brace.

Accessibility of Links to External Web Sites in Documentation

This documentation may contain links to Web sites of other companies or organizations that Oracle does not own or control. Oracle neither evaluates nor makes any representations regarding the accessibility of these Web sites.

Overview

The Enterprise Integration Platform is an Integration Framework for integrating Agile EDM with other applications like ERP-Systems. The Integration Platform consists of a kernel (controller, mapping, logging etc.) and connectors for the different applications.



In order to install the Integration Platform, several steps have to be performed:

1. Install the software on the server machine, where the Integration Platform should run.
2. Install the application specific software required by the Integration Platform, e.g. loader files in Agile EDM.
3. Modify the configuration file in order to define the involved connectors, mappings and operations (Business Objects).
4. Modify the mapping files based on the requirements.

5. Test the Integration Platform with the new configuration.

Note This document describes the installation of the Enterprise Integration Platform together with Agile EDM.

Chapter 2

Prerequisites

Enterprise Integration Platform

Since the Enterprise Integration Platform is a Java application, a Java Runtime Environment is required. This is not part of the installation package and therefore needs to be installed beforehand.

Note As the Enterprise Integration Platform now includes a Web Server that is able to handle JSPs, a Java Compiler must be installed. Either you install a Java Development Environment (JDK) where this is included, or you install a Java Runtime Environment and copy the file `tools.jar` from the JDK's `lib` directory to the JRE's `lib` directory.

Please remember to install the Java Runtime Environment on all platforms where you want to run the Enterprise Integration Platform or parts of it. If you installed it on a UNIX system for example, and you want to use the GUI tools on a Windows system from this installation location via a shared network drive, you have to install a Java Runtime Environment on your Windows machine as well.

This version of the Integration Platform runs on Java 1.6.0 (latest patch level recommended). You may download this from the website of the respective operating system provider:

AIX:	http://www-106.ibm.com/developerworks/java/jdk/aix/
Windows, Solaris, Linux/Intel:	http://java.sun.com/j2se/
HP-UX:	http://www.hp.com/products1/unix/java/

Note After the installation of the Java Runtime Environment, please set the environment variable `JAVA_HOME` to point to its installation directory, e.g. `C:\Program Files\Java\jdk1.6.0_24`

Third-Party Libraries

As certain third-party libraries are not shipped with the Enterprise Integration Platform anymore, please download them from the following locations as needed:

Library	Purpose	Download Location	Installation Instructions
<code>js.jar</code>	JavaScript support for XSL transformations	www.mozilla.org/rhino/	Browse to <i>Downloads</i> and then to the <i>Rhino downloads archive</i> . The preferred version to download is

			1.5R3. Copy the file <i>js.jar</i> from the ZIP file to the <i>libs</i> directory.
wsdl4j.jar	WSDL generation for WebServices	sourceforge.net/projects/wsdl4j	Browse to <i>Downloads</i> and to the link to <i>View older releases in the WSDL4J package</i> . The preferred version to download is 1.5.1. Copy the file <i>lib/wsdl4j.jar</i> to the <i>libs</i> directory.

Agile EDM

The minimum Agile EDM version to be used together with the Integration Platform is Agile EDM e6.1.2

Chapter 3

Basic Installation

The software is provided as a distribution package, which includes all files and directories needed for successfully running the application.

Windows and Unix Installation

Prerequisites

The distribution is provided as a gnu zipped tar file because the UNIX execution file rights are not preserved by WinZip.

Note Do not use WinZip to extract the files to a UNIX system!

You should be able to unpack the file (in Installation Step 2) with either WinZip on Windows or with the following command on UNIX:

```
tar xzvf eip-x.x.x-bxx.tar.gz
```

If you get an error, that “z” is an unknown option to tar then try the following:

```
gunzip -dc eip-x.x.x-bxx.tar.gz | tar xvf -
```

If you do not have one of these tools, you might download it from the following locations:

WinZip: <http://www.winzip.com/>
gunzip: <http://www.gzip.org/>

Installation Steps

1. Copy the installation package onto the dedicated server, which should be used for running the Integration Platform. The used server needs to be able to connect to the Agile EDM Java Daemon via ECI and to ERP system via RFC.
2. Uncompress the package into the install directory of the Integration Platform, e.g. into the directory c:\agile\eip on MS-Windows (this will be referred to as <eai.home> in the rest of the document).

Following directory structure will be created under <eai.home>:

- Archive: Directory for archived queue entries

- Bin: Contains the startup scripts for the applications
- Conf: Contains the configuration and mapping files
- Data: Contains the XDOs (data packages) when persistence is activated
- Docs: Contains the documentation/manuals
- Install: Contains all additional installation files, which are required for external applications, e.g. Agile EDM
- Libs: Contains all library files (except JRE files)
- Log: Contains all log/trace files, depending on setting in configuration file
- Tmp: Contains all temporary files, which are neither log files nor XDO data files

Database Creation

Before using the Enterprise Integration Platform, the needed database tables must be created. Before doing this, the Configuration File must be modified (as described in Chapter 4). Especially, the configuration values for <queue> with its sub-values <type>, <host>, <port>, <user>, <password> and <name> must be set to the appropriate database parameters (please refer to the “Administrator Manual” for further information).

Note Although it might be possible to create the EIP’s database objects with same user as other applications (e.g. Agile EDM), it is strongly advised to use a separate user (a schema in Oracle). This prevents data loss in case of a command that deletes the database objects (e.g. with the dbmaint’s purge command). Please read carefully the tools’ chapter in the “Administrator Manual” for further information.

Note It might be recommended to create the new database user with own database files (tablespace in Oracle, database in SQL Server). The advantages of separate database files are independency on other tables and users (e.g. from Agile EDM), and easier backup and replication. Since the tables are constantly growing in size, if they are not cleaned up on a regular basis, the initial size of the database file should not be too small. The definitions for Agile EDM may be used as a guideline for specifying the initial database size and extends. Since this is only a recommendation, you may feel free to use the same database files as an existing Agile EDM installation or even the same database user, especially if you do not expect too much data load.

In order to create the database tables on MS-Windows (NT/2000/XP) please start the script *dbmaint.cmd* in the directory *bin*.

On UNIX servers, please start the script *dbmaint.sh* in the directory *bin*.

The following Oracle PL/SQL script needs to be run against the EIP's database:

```
$EP_ROOT/axalant/db_utils/oracle/sql/ddl_eip_plsql_cln_bpm_que.sql
```

The easiest way to create the database objects is to execute the script with the SQL Plus tool from the same machine where the Oracle instant client for EDM has been installed.

This ensures that a new stored procedure will be created that will speed up the database cleanup tasks configured in *eai_ini.xml*.

For a further description of the Database Maintainer, please refer to the chapter "Tools" in the "Administrator Manual".

Chapter 4

Configuration and Customization

For more information about configuring and customizing the Enterprise Integration Platform, please refer to the “Administrator Manual”.

Modifying the Configuration Files

The configuration has to be done in at least two files in the conf directory: run.conf and eai_ini.xml. Each one of them needs to be set up accordingly in order to have the Integration Platform start up and run properly.

The configuration file run.conf lists the classpaths used by the Integration Platform.

The configuration file **eai_ini.xml** consists of certain sections for the different modules of the Integration Platform, e.g. Controller, Connector and Mapping.

Note The password encryption had been changed due to be compliant with the Oracle Security Guidelines. It will now use the same method as Agile EDM 6.1 and higher uses (e.g. for the encryption of the database password). Therefore all passwords in the eai_ini.xml file needs to be re-generated.

For an Oracle non-RAC databases, it is advised to not use the OCI driver (which is enabled by default) but the JDBC thin driver. This behavior could be altered by the following line in the **eip.conf** file:

```
wrapper.java.additional.9=-Deip.oracle.thin=false
```

When set to **false**, the OCI driver is used that is required for RAC, otherwise the JDBC thin driver is used.

On AIX platform with an IBM Java Virtual Machine (JVM), the following line needs to be the first one in the corresponding section:

```
wrapper.java.additional.1=-Xbootclasspath/p:%EAI_HOME%/libs/xercesImpl-2.9.1.jar
```

All other entries in this section should be renumbered accordingly, e.g.:

```
wrapper.java.additional.2=-Dcommons.home="%EAI_HOME%"
wrapper.java.additional.3=-Deai.home="%EAI_HOME%"
```

Modifying the Mapping Files

As mentioned before, XSL files are used for mapping purposes. Since the connectors create and read XML data (i.e. the message XDO), converting the XDO to a specific format will be done by the XML Mapping engine.

The names of the XSL mapping files, which are used by the Integration Platform, are provided in the *eai_ini.xml* configuration file.

For more information about XSL tools, please refer to the “FAQ_EIP” document.

Configuring EIP on Linux

The EIP 2.2.2 package for Linux x86 downloaded from Oracle Software Delivery Cloud does not contain the Oracle DB client library libclntsh.so.11.1. You have to use the Oracle DB client that is installed with Oracle Agile e612. If the EIP is installed on the same server as Agile e612, it will use the Oracle Client the Oracle Agile e612 installation. If not, the same Oracle Client installation as for Oracle Agile e612 needs to be executed on the EIP server.

The EIP's startup scripts and startup configuration files make reference to the Oracle JDBC JARs and OCI shared libraries from the Oracle Client installation directories via the ORACLE_HOME environment variable. It supports both the Oracle Agile e612 Oracle Client installation and the Oracle Instant Client installation.

To run EIP 2.2.2, the Environment Variable ORACLE_HOME must be set to the root directory of an Oracle Client installation.

Chapter 5

Testing and Starting

For testing and starting the Enterprise Integration Platform, please refer to the chapter “Running the Enterprise Integration Platform” in the “Administrator Manual”.

Chapter 6

Starting as a Windows Service

The EIP Daemon is a Java Service Wrapper for Windows Server 2003. It may be used to start and stop the Enterprise Integration Platform from the Service Control Panel.

Prerequisites

The environment variables EAI_HOME and JAVA_HOME must be set!

Installation Steps

1. Run the script `daemon.cmd` from the `bin` directory with the argument “install” to install the service:

```
bin\daemon.cmd install
```

The service may be removed by calling the script with the argument “remove”.

2. Open **Start > Control Panel > Administrative Tools > Services** and ensure that the service is running with the same user as the Agile EDM server instance (default is `axalantrt`).
3. Use the entry “EnterpriseIntegrationPlatform Daemon” to start or stop the Enterprise Integration Platform.

Troubleshooting

If the service does not start or terminates unexpectedly, check the additional log file *daemon.log* that is located in *logs*. It contains service internal messages and should be reviewed for daemon configuration problems.

Chapter 7

Starting as a UNIX Daemon

The EIP Daemon is a Java Daemon Wrapper for UNIX. It may be used to start and stop the Enterprise Integration Platform from the Service Control Panel.

Prerequisites

The environment variables EAI_HOME and JAVA_HOME must be set!

Installation Steps

1. Run the script `daemon.sh` from the `bin` directory with the argument “start” to install the service:

```
bin/daemon.sh start
```

The service may be stopped by calling the script with the argument “stop”.

2. Check if the daemon is running by calling:

```
bin/daemon.sh status
```

Troubleshooting

If the service does not start or terminates unexpectedly, you may check the additional log file *daemon.log* that is located in *logs*. It contains service internal messages and should be reviewed for daemon configuration problems.

Load the Data Model

1. Start Agile e6.
2. Login with the user **edbcusto**.

Assure that the loader mode for this user is set to BIN.

3. In the **I(nsert)** mode, load the following loader files:

- `dtv_cdd.bin`
- `lgv_cdd.bin`

- lgv_cdd_cust.bin
4. Log out and log in.
 5. Search in the list of data classes for all classes "CDD%".
 6. Select the resulting lines and use "Create Database Object" to include the added tables to the database.

The following message is displayed:

"The view does not contain any Where condition, continue with operation anyway?"

7. Confirm with YES.
8. Search for the class names T_PAC_MUL and select again "Create Database Object" to modify this already existing table in the database.

Note Only if this is the first installation of the Agile e6 Plot Management, please exit Agile e6 and login as the user "plotkernel" or "plotcusto"!

9. Load the loader file axa_cdd_dat.dat with mode I.

Define the Application Library


To make the plot management application library available for the server process, add a new section into your application environment file.

You can do this via the Agile e6 administration desktop:

1. Select "Manage existing environment".
2. Follow the dialog to insert a new section.

Note You can also insert a new section into the application environment file in Agile_e6/init with an editor!

```
The following section entries are necessary:
<Custom>
...
<Cdd Name="Plot Management" Library="epsrv_cdd"
Startup="immediately" Entry="Plotmanagement_Entry"/>
...
</Custom>
```



ID	Name	Version	Type	State	Library	Entry	Sub-m...
Lut	LUT LookUp T...	33.4	DYNAMIC	RUNNING	epsrv lut	Lut Entry	
Mgt	Mgt Drag & Drop	33.2	EMBEDDED	RUNNING		Mgt Entry	
Nmt	NetMeeting		DYNAMIC	UNLOADED	epsrv nmt	Nmt Entry	
Nsv	Number Server	33.6	EMBEDDED	RUNNING		Nsv Entry	
Pac	Folders	33.2	DYNAMIC	RUNNING	epsrv pac	Pac Entry	
Pdm	Generic PDM ...	33.20	DYNAMIC	RUNNING	epsrv pdm	Pdm Entry	Er
Plotm...	Plotmanagement	5.0.1.03	DYNAMIC	RUNNING	epsrv cdd	Plotma...	Fas
PrvPde	ProView PDE ...		DYNAMIC	UNLOADED	epsrv p...	PrvPde...	
PrvPdi	ProView PDI ...		DYNAMIC	UNLOADED	epsrv p...	PrvPdi...	

(Manager > Monitor > Libraries)

License Control

The Plot Management module is part of the Product Data Management solution. Please activate the solution Product Data Management in the Available Licenses mask (System > Licenses).

In the current Agile e6 version the Plot Management is inhibited for the web client. To make the Plot Management available for the Web Client, please set the default parameter E6-PDM-PLT-{H} to ON.

Access to the Plot Order Function

In the shipped version, the user has access to the plot order interface through the document type masks (of type: DRAWING and DRAWFILE) and through the item and project mask.

If access to the plot management interface is required from other document types (forms or lists), please attach the selection CDD-PLOTTEN-CG to the related menu (NOS menu for forms or SEL menu for lists).

Update an Existing Installation

1. Open the Oracle SQLplus Worksheet. (Query-Analyzer for SQL-SERVER)
2. Execute the SQL file cdd_upd.sql with the following command:

```
start cdd_upd.sql.
```

A log file CDD_UPD.LOG will be created in the current directory.

Note Check the log file for errors. The following error may occur:

```
SQL> ALTER TABLE T_PAC_MUL ADD
2 (
3   CDD_FILE_SEL VARCHAR(2000)
4 );
   CDD_FILE_SEL VARCHAR(2000)
*
```

ERROR at line 3:

ORA-01430: column being added already exists in table

3. Start Agile e6.
4. Login with the user:
 - plotkernel and the password PLOTKERNEL OR
 - plotcusto and the password PLOTCUSTO.
5. Search in the list of number variants for the number variant PAC and write down the current number for later use.
6. Assure that the loader mode for this user is set to BIN.

The following loader files have to be loaded:

- dtv_cdd.bin
 - lgv_cdd.bin
 - lgv_cdd_cust.bin
7. Load the files dtv_cdd.bin, lgv_cdd.bin and lgv_cdd_cust.bin with mode O (Overwrite).

Note If you use mode O, keep in mind that all previous data owned by the user plotkernel and plotcusto will be deleted prior to the loading process!
If you use mode O copy the logic model CDD_CUSTOMIZE first. It is also mandatory to load lgv_cdd.bin before lgv_cdd_cust.bin!

Note Please exit Agile e6 and login again as user plotkernel!

8. Set the number variant PAC to the value as described in step 2.
9. Adapt the logic model CDD_CUSTOMIZE.
10. In the shipment version the user has access to the plot order interface through the document type masks of the type DRAWING and DRAWFILE and through the item and project mask.

If access to the plot management interface is required from other document types (forms or lists), please attach the selection CDD-PLOTTEN-CG to the related menu (NOS menu for forms or SEL menu for lists).

