

Release Notes: Oracle AutoVue 20.2, Desktop Deployment

For the most up-to-date version of this document, go to the AutoVue Documentation Web site on the Oracle Technology Network at <http://www.oracle.com/technetwork/documentation/autovue-091442.html>.

Application User License

- AutoVue includes an AutoVue Desktop Version, a Desktop Deployment, and a Client/Server Deployment. For Application User licensing metric (in the Component licensing model) or Custom Suite User licensing metric (in the Custom Applications Suite licensing model), a single license cannot be split or shared between two users (e.g., one user using the AutoVue Desktop Version and a different user using the Desktop Deployment would require two licenses).

Installing AutoVue

Important: If you are migrating from AutoVue Desktop Version to AutoVue Desktop Deployment, a *Migration Guide* is available on the Media Pack in folder *DesktopDeployment* to assist you with the migration.

- The Oracle AutoVue Desktop Deployment 20.2 installer supports the ability to upgrade from version 20.1.x and 20.0. If you have Oracle AutoVue 20.0/20.1.x installed previously, the installer upgrades the previous configuration settings from VueCore.ini (release 20.0 only), allusers.ini, and autovue.properties when you install version 20.2.
- By default, AutoVue installs into the *C:\Oracle\AutoVue Desktop Deployment* directory. If you are installing on UAC enabled systems, ensure that you install at a location to which the user running AutoVue has write permissions.
- For complete installation instructions, refer to the *Oracle AutoVue Installation and Configuration Guide*.

System Requirements

Oracle AutoVue Desktop Deployment is certified on the following platforms:

- Windows XP—32-bit
- Windows Vista—32-bit and 64-bit (AutoVue running in 32-bit mode)
- Windows 7—32-bit and 64-bit (AutoVue running in 32-bit mode)

Hardware Requirements

The recommended requirements for a machine running AutoVue Desktop Deployment is as follows:

- 2 GB of RAM

Note: AutoVue is a 32-bit application. Generally, 32-bit processes are limited to 2 GB of RAM. However, the AutoVue Desktop Deployment executable is large address aware. This means that if AutoVue is running on a 64-bit OS that has 4 GB of RAM, AutoVue can use up to 4 GB of RAM. If AutoVue is running on a 32-bit machine that is booted up with the 3 GB switch, and the machine has 3 GB of RAM, AutoVue can use up to 3 GB of RAM.

- 2 GHz dual-core CPU
- Display driver that supports OpenGL and has dedicated memory (required for 3D support).
- 400 MB of disk space for installation.
- 6 GB of free disk space:
 - 4 GB needed for storing cached files
 - Remainder needed by AutoVue to store temporary files (at the %TEMP% path).
- If streaming file generation is enabled, you must ensure that the disk space specified by `autovue.cache.size` is available to AutoVue.

Refer to the “Configuring AutoVue” section in the *Oracle AutoVue Desktop Deployment Installation and Configuration Guide* for more information on streaming files.

General Enhancements

- Enhancements to markups
 - The Stamp markup entity has been renamed to Symbols.
 - The Intellistamp markup entity has been renamed to Stamp.
 - Enhancements to Stamp (formerly Intellistamp):
 - Stamps can now be defined to have fields that store their values locally or in the back-end system. The original value and constraints (lists of possible values) can come from the back-end system even if the field value is stored locally.
 - Stamps can be defined to have a fixed physical size (e.g. 10cm by 10cm) to comply with industry or corporate standards.
 - Stamps with an Enhanced Metafile (EMF) background image will have a better appearance when resizing - text and the background image will keep the same relatively size and location.
 - Enhanced attribute permissions (read once, read, write and edit).
 - Ability to resize both the Stamp and the Stamp text (supported only when EMF is used as the Stamp background).
 - Ability to specify the Stamp size (fixed, default, resizable).
 - AutoVue now exits markup creation mode after you create a markup entity. In previous releases of AutoVue, you were able to continue adding markups until you right-click the workspace.
- Added Unicode support for Layers, Views, Blocks and 3D attributes.
- Added support for layer printability for AutoCAD and PDF files. AutoVue does not print layers that are markup “non-printable”. Note the following:
 - Layer printability does not take effect when in Compare mode.
 - Layer printability does not apply to conversion.
- Added support for multi-selection of local files in the file open dialog.
- Added support for specifying a page range when converting to PDF.
- Added support for the Dutch language (locale NL) for the AutoVue user interface.

MCAD Formats

- Added support for CATIA 5R21
- Added support for SolidWorks 2012
- Added support for SolidEdge ST3, ST4
- Added support for Creo Parametric 1.0
- Added support for Creo Element\Direct Modeling 17.10, 17.20, 17.25, 17.30 and 18.00
- Added support for PLM XML
- Improved handling of background of AutoDesk Inventor drawings. If drawings contain a background image, AutoVue displays it, but does not print this background image.
- Added support for shaded views in Pro/ENGINEER 2D files.
- Enhanced support for IGES:
 - Added support for 3D layers

- Improved loading performance
- General bug fixes:
 - CATIA 4
 - CATIA 5
 - IGES
 - Autodesk Inventor
 - Creo Parametric (Pro/ENGINEER)
 - Unigraphics
 - SolidWorks
 - SolidEdge
 - STEP

AEC Formats

- Added support for Creo Element/Direct Drafting 17.10 to 18.00
- Enhanced support for AutoCAD DXF:
 - Added support for layout pages
 - Added support for OLE embedded objects
 - Added support for raster embedded entities
 - Added support for Viewports in layout pages
- General bug fixes:
 - AutoCAD (DWG & DXF)
 - MicroStation
 - Creo Element/Direct Drafting (ME10)
 - Visio
 - TIFF

EDA Formats

- Added support for Cadence Concept HDL 16.5
- Added support for Allegro Layout 16.5
- Added support for Orcad Capture 16.5
- Added support for Board Station ASCII Symbol Geometry
- Added support for Cadence Cell Library
- General bug fixes:
 - Cadence Allegro
 - EDIF
 - OrCAD Capture
 - Mentor BoardStation
 - PADS Logic

Desktop/Office Formats

- Added support for Word 2010
- Added support for Excel 2010
- Added support for PowerPoint 2010
- Added support for Outlook 2010
- Enhancements to Desktop/Office formats:
 - Improved handling of PDFs with large JPEG images
 - Added support for PDF files embedded in Excel files
 - Improvements to hyperlinks in Excel

- Added Workbook protection for binary Excel binary files
- Improvements to field display support in PowerPoint (date, time, page, number)
- Improvements to arrow head rendering in PowerPoint
- Added gradient fill support in Word XML
- General bug fixes:
 - Excel
 - Outlook
 - PowerPoint
 - Word
 - PDF
 - TXT

Documentation

- The following documents have been updated in 20.2:
 - Installation and Configuration Guide
 - Viewing and Configuration Guide
 - User's Manual
 - Acknowledgments
 - Supported File Formats
 - Release Notes
 - Product Variations – Feature Matrix

INI Options Updated in AutoVue 20.2

Refer to the *Oracle AutoVue Installation and Configuration Guide* for information regarding these options.

- DISABLE3DMODEL: Extended support to DWF and MicroStation 7 and 8.

New INI File Settings

INI options described in following sections should be set in user INI files.

Acrobat Options

Configure options for Acrobat files.

[Options]

Parameter	Description	Default
PDFOVERPRINTPREVIEW = [0 1]	Displays content that otherwise may be obscured by overprinted fills. Set to 1 so that overprinted fills are not displayed if they use a spot color. Set to 0 so that overprinted content is shown as in Adobe Acrobat.	0

Autodesk Inventor Options

Configure options for Autodesk Inventor files.

[Options]

Parameter	Description	Default
DRAWINGPAGE = [0 1]	Set to 1 to limit the loading of the drawing to the sheet borders. Set to 0 to display the whole drawing.	0
INVENTOR_HIDE_CONSTRUCTION_GEOMETRY = [0 1]	This option is used to control the visibility of construction/non-manifold geometries for Inventor 3D files. Set to 0 to display non-manifold/construction geometries Set to 1 to hide non-manifold/construction geometries	1

CATIA 5 Options

Configure options for CATIA 5files.

[Options]

Parameter	Description	Default
LOAD_ATTRIBUTES = [0 1]	Control the loading of attributes when viewing AutoVue Assembly XML formats. Set to 1 to read attributes and attach them to their appropriate entities. Set to 0 to disable the loading of attributes. This option may be used for performance tweaking for large assembly files with many attributes.	1
MINIMIZETREENODES = [0 1]	Set to 1 to minimize the number of nodes in the model tree and to increase performance. Set to 0 to build a model tree similar to the CATIA 5 feature tree. Note: This option is only valid in BREP mode (LOADFACETEDDATA=0).	0
CATIA5BUILDINTERMEDIATECGMBODIES = [0 1]	This option controls the building and display of intermediate CGM bodies Set to 1 if you wish to process and display all intermediate CGM bodies. (You also need to set the ini option CATIA5BuildInvisibleCGMBodies to 1 if the intermediate bodies are saved as invisible. File will take longer to load if it contains lots of intermediate bodies) Set to 0 to disable the loading and display of intermediate CGM bodies. Note: The option takes effect only in BREP mode (LOADFACETEDDATA=0).	0

Creo Element/Direct Drafting (ME10) Options

Configure options for Creo Element/Direct Drafting (ME10) files.

[Options]

Parameter	Description	Default
ME10_USEHTMLASCIICODES=[0 1]	Specify whether or not to use the HTML ASCII CODES table for character mapping when accessing ME10 native fonts and their equivalent UFF fonts. Set to 0 to use ME10's native character mapping instead of the HTML ASCII CODES table. Set to 1 to use HTML ASCII CODES table for character mapping for special characters.	0

IGES Options

Configure options for IGES files.

[Options]

Parameter	Description	Default
IGESDETAILEDTREE = [0 1]	Set to 1 to display every face (surface) as a separate node in the model tree. Set to 0 to merge all single faces together into one body.	0
IGESHIERARCHYCOLOR = [0 1]	Controls the color overwrite setting of IGES files. Set to 1 so that the child entity color always overwrites the parent entity color. For example, the color of the face, if set, always overwrites color of the body.	1
IGESINVISIBLEPARTS = [0 1 2]	Set to 0 so that hidden entities are not loaded. Set to 1 to load but not display hidden entities. Set to 2 to load and display hidden entities.	1
IGES3DLAYERS = [0 1]	Set to 0 to disable loading of layers in IGES files containing layer information. Set to 1 to enable loading of layers in IGES files containing layer information.	1
IGESFACEORIENTATION = [0 1]	Set to 0 to disable validation of face orientations in IGES 3D files. Set to 1 to enable validation of face orientations in IGES 3D files.	0
IGESSHOWALL = [0 1]	Set to 0 to disable loading of subordinate entities in IGES 3D files. Set to 1 to load subordinate entities (children) in IGES 3D files.	0

Mentor Options

Configure options for Mentor files.

[ECAD]

Parameter	Description	Default
MENTOR_PCB_DESIGNTOOL = [0 1 2]	Controls which Mentor PCB Design Tool's display to match. Set to 0 so that AutoVue matches the display of Mentor Librarian. Set to 1 so that AutoVue matches the display of Mentor Layout. Set to 2 so that AutoVue matches the display of Mentor Fablink.	0 for Mentor ASCII Geometry Symbol file 2 for Mentor PCB designs

Microsoft Office Options

Configure options for Microsoft Office files.

[Options]

Parameter	Description	Default
TRYWITHMSXMLPARSER = [0 1]	Specify which parser to use when loading Office XML files. Set to 1 to use the MSXML parser that is included with Windows OS. Set to 0 to use the Xerces XML parser. Note: This option affects the following formats: WordXML PPTXML, ExcelXML	1

Creo Parametric (Pro/ENGINEER) Options

Configure options for Creo Parametric (Pro/ENGINEER) files.

[Options]

Parameter	Description	Default
PROEBACKGROUNDCOLOR = <integer>	Specify the background color of shaded views in Creo Parametric (Pro/ENGINEER) 2D drawing (when in saved display list and/or picture mode) to the background color used in Creo Parametric at the time the drawing (shaded view) was created. To obtain the background color from Pro/ENGINEER, select View > Display Settings > System Colors > Background Color. Note: If no color is specified (PROEBACKGROUNDOLOR=-1), the hard-coded default Creo Parametric (Pro/ENGINEER) 2D background color is used. <ul style="list-style-type: none">For versions Wildfire, Wildfire2: RGB(183, 183, 183)For versions Wildfire3, Wildfire4: RGB(51, 50, 46)For version Wildfire5: RGB(160, 186, 212)For Creo 1.0: RGB(251, 251, 252)	-1

Parameter	Description	Default
PROE2DVIEWDEFAULTS TYPE = [HIDDEN WIREFRAME SHADING NO HIDDEN]	<p>Specify a default style to display 3D projected views. This option controls the amount of detail in projected views. Showing less detail in views might improve the performance:</p> <ul style="list-style-type: none"> • HIDDEN • WIREFRAME • SHADING • NO HIDDEN <p>This option will work in the following conditions:</p> <ul style="list-style-type: none"> • When the view's display style follows the global style (that is, Proe/Engineer environment variable Display Style is set to Follow Environment) • Loading drawing files in picture mode is turned off (PROE2DLOADPICTURE=0) • Loading drawing files from display list is turned off (PROE2DLOADSAVEDDISPLAYLIST=0) 	NO HIDDEN

Raster Options

Configure options for Raster files.

[Options]

Parameter	Description	Default
APPLYRASTERTRANSPARENCY=[0 1]	<p>Set to 0 to ignore alpha-channel and display the whole bitmap opaque.</p> <p>Set to 1 to use the alpha-channel stored in the file to apply transparency.</p>	1

Text Options

Configure options for Text files.

[Options]

Parameter	Description	Default
DEFAULTDOCMARGINS= leftMargin,rightMargin,top Margin,bottomMargin	<p>Specify page margins in inches for plain Text files.</p> <p>If this option is not set, a default of 1 inch for each margin is set.</p> <p>Sample Syntax: DEFAULTDOCMARGINS=1.2, 1, 0.8, 0.8</p>	1, 1, 1, 1

TIFF Options

Configure options for TIFF files.

[Options]

Parameter	Description	Default
TIFF_LOADPREVIEWS = [0 1]	<p>Specifies if the TIFF images with reduced resolution (that is, preview pages) are displayed.</p> <p>Set to 1 to display all pages including the preview pages.</p> <p>Set to 0 so that the preview pages are not displayed.</p>	0

De-supported in Release 20.2

- The INI option SENDPAGEASIMAGE has been de-supported since it is no longer needed.

Known Issues

For more information on known issues, refer to the Knowledge Base:

<https://support.us.oracle.com/oip/faces/secure/km/DocumentDisplay.jspx?id=1401724.1>

- Copy/Paste feature is not supported for Stamp markup entity.
- Stamping is not supported in 3D files.
- There is a known issue with 64-bit JREs when loading 3D files. In some situations (for instance, using Remote Desktop to access AutoVue), 3D files will not display. This is a known issue with JOGL 1.1.1. See JOGL bug: https://jogamp.org/bugzilla/show_bug.cgi?id=427: https://jogamp.org/bugzilla/show_bug.cgi?id=427.
- There is a known issue with the Universal File Open dialog on Windows 7 Operating Systems. The dialog sometimes does not display the icons. This is a known Java bug. Refer to http://bugs.sun.com/view_bug.do?bug_id=6840086.

Oracle AutoVue 20.1.1, Desktop Deployment

For the most up-to-date version of this document, go to the AutoVue Documentation Web site on the Oracle Technology Network at <http://www.oracle.com/technetwork/documentation/autovue-091442.html>.

Application User License

- AutoVue includes an AutoVue Desktop Version, a Desktop Deployment, and a Client/Server Deployment. For Application User licensing metric (in the Component licensing model) or Custom Suite User licensing metric (in the Custom Applications Suite licensing model), a single license cannot be split or shared between two users (e.g., one user using the AutoVue Desktop Version and a different user using the Desktop Deployment would require two licenses).

Installing AutoVue

Important: If you are migrating from AutoVue Desktop Version to AutoVue Desktop Deployment, a *Migration Guide* is available on the Media Pack in folder *DesktopDeployment* to assist you with the migration.

- The Oracle AutoVue Desktop Deployment 20.1.1 installer supports the ability to upgrade from version 20.1 and 20.0. If you have Oracle AutoVue 20.0/20.1 installed previously, the installer upgrades the previous configuration settings from VueCore.ini (release 20.0 only), allusers.ini, and autovue.properties when you install version 20.1.
- By default, AutoVue installs into the *C:\Oracle\AutoVue Desktop Deployment* directory. If you are installing on UAC enabled systems, ensure that you install at a location to which the user running AutoVue has write permissions.
- For complete installation instructions, refer to the *Oracle AutoVue Installation and Configuration Guide*.

System Requirements

- Windows XP, 32-bit
- Windows Vista, 32-bit and 64-bit (AutoVue running in 32-bit mode)
- Windows 7, 32-bit and 64-bit (AutoVue running in 32-bit mode)
- The installation requires about 400MB of free space

General Enhancements

- Compare Mode Usability Enhancements
 - When comparing two files, it is assumed that the newer version of the file is opened first and then compared with the older version. As a result, to make this feature more intuitive, the newer version of the file appears in the right window and the older version of the file to compare with appears in the left window.
 - The Comparison Results window now displays added, deleted, and unchanged information by default.
 - Compare mode now detects color differences as changes and reports such differences as additions and deletions.

- PDF Enhancements
 - Added support for selecting and copying text from PDF documents which can then be pasted into other text editing software, mail clients, or AutoVue markups.
 - Added support for snapping to entities to take measurements in vector-based PDF files. You can snap to the end-points or mid-points of an entity. AutoVue also allows you to snap to shapes (closed entities) for area measurements. This option also applies when adding a Markup Measure entity to the PDF file.
 - Improved navigation of PDF documents
 - When doing a text search on PDF, AutoVue retains the current zoom level. This provides better user experience on text search. Note that when the text is very small or very large, AutoVue zooms so that the text highlight is visible.
 - When the user right-clicks a Markup entity from the Markup tree and selects **GoTo**, the entity is highlighted in the workspace and the current zoom level of the PDF is maintained. That is, AutoVue no longer zooms to the selected entity.
 - When scrolling through pages of the PDF, the current zoom level of the PDF is maintained.
 - When the **Zoom - Page Width** option is selected, the top of the current page appears and is zoomed to the full page width.
- Stamp Library Enhancements
 - When saving a new stamp with a name of an existing library, AutoVue prompts the user to save the library with a different name. Note that this works when it is saved by the same user. If the new stamp is saved by a different user, the user is not prompted by AutoVue to save the library with a different name. Rather, AutoVue adds a suffix to the file name. For example, AAA (2).
 - A new logger has been added to the log4j.xml file: log4j.logger.com.cimmetry.jvueserver.symbols. This logger lets you enable logging messages for the symbols library. When enabled, mapping between stamp library and stamp files is generated in the log file.
- Markup Enhancements
 - Improved Markup Note entity usability. It is now possible view/edit multiple Notes in a row without having to close the Markup Note dialog each time.
 - When adding a new Markup entity and when sorting the Markup Tree by Last Modified, AutoVue scrolls to the bottom of the Markup Tree to select and display the new entity.

MCAD Formats

- Added support for Autodesk Inventor 2012.
- Added support for Unigraphics NX7 and NX7.5.
- Added native font support for PMI in Pro/ENGINEER.
- Renamed mxCATIA to AutoVue Assembly
 - Added support for attributes (key/value).
 - Added support for file properties.
 - Added support for controlling the loading of attributes from AutoVue Assembly XML formats by setting the LOAD_ATTRIBUTES INI option.
- General bug fixes for:
 - SolidDesigner
 - Unigraphics
 - AutoVue Assembly
 - Pro/ENGINEER
 - Autodesk Inventor
 - CATIA 5
 - DirectModel (JT)

AEC Formats

- Added support for AutoCAD 2012 and AutoCAD Mechanical 2012.
- Added support for AutoCAD Annotation Scales.
- Added support to disable loading of 3D pages for Autodesk DWF, MicroStation7, and MicroStation 8 by setting the Disable3DModel INI option.
- Added support for displaying/hiding line weights in drawings when printing or converting to PDF/TIFF by setting the ACAD_LWDISPLAY INI option.
- Added support for PDF Underlays in AutoCAD files.
- Added support for Cylindrical primitives in DWF 3D files.
- General bug fixes for:
 - AutoCAD/DXF
 - Autodesk DWF 2D/3D
 - MicroStation 7 and 8
 - HPGL

Archive Formats

- General bug fixes for ZIP

EDA Formats

- General bug fixes for:
 - Cadence Allegro
 - Mentor Graphics

Office Formats

- Added support for Adobe Acrobat X (10).
- General bug fixes for:
 - Acrobat PDF
 - Word (Binary/XML)
 - PowerPoint
 - Excel
 - ZIP

Documentation

- The *AutoVue Hotspots API Guide* has now been added to the “Hotspots” chapter of the *AutoVue API Programmer’s Guide* (AutoVueAPIProgrammersGuide.pdf).
- The following documents have been updated in 20.1.1:
 - Installation and Configuration Guide
 - Viewing and Configuration Guide
 - User’s Manual
 - Acknowledgments
 - Supported File Formats
 - Release Notes
 - Product Variations – Feature Matrix

INI Options Updated in AutoVue 20.1.1

Refer to the *Oracle AutoVue Installation and Configuration Guide* for information regarding these options.

- DISABLE3DMODEL: Extended support to DWF and MicroStation 7 and 8.

New INI File Settings

INI options described in following sections should be set in user INI files.

AutoCAD Options

Configure options for AutoCAD files.

[Options]

Parameter	Description	Default
ACAD_LWDISPLAY = [0 1 2]	<p>Specify whether or not to display line weight in the drawing when printing or converting it to PDF/TIFF.</p> <p>Set to 0: Line weight is disabled regardless of the file setting. As a result, entities print without line weight even if they contain line weight.</p> <p>Set to 1: Line weight is enabled regardless of the file setting. As a result, entities print with line weight if they contain line weight.</p> <p>Set to 2: The file setting is used (ON or OFF). AutoVue matches the same initial display as AutoCAD. Line weight is printed based on the saved value of the LWDISPLAY INI option in the AutoCAD file (that is ON->line weight printed, OFF-> line weight not printed)</p>	2

AutoVue Assembly Options

Configure options for AutoVue Assembly files.

[Options]

Parameter	Description	Default
LOAD_ATTRIBUTES = [0 1]	<p>Control the loading of attributes when viewing AutoVue Assembly XML formats.</p> <p>Set to 1 to read attributes and attach them to their appropriate entities.</p> <p>Set to 0 to disable the loading of attributes.</p> <p>Note: This option may be used for performance tweaking for large assembly files with many attributes.</p>	1

File Formats/Versions Desupported in Release 20.1.1

Oracle AutoVue has dropped support for some file formats/versions, which had very limited usage and low demand from our customers. This will allow Oracle AutoVue to focus development efforts on formats which are most strategic to our customers. Below is the list of file formats/versions which are de-supported in release 20.1.1:

Desupported File Formats

- MCAD Formats
 - MicroStation 3D
 - SPATIAL ACIS
 - I-deas
 - Parasolids
 - PointClouds 3D
- AEC Formats
 - AutoCAD Slide
 - AutoCAD Sheet Sets
 - Cadkey
 - HP RTL
 - ESRI Shapefile
 - Adobe Illustrator
- EDA Formats
 - Altium Designer SCH
 - Altium Designer PCB
 - Protel Schematics
 - Protel PCB
 - P-CAD Schematic
 - P-CAD Layout
 - PDIF Schematics
 - PDIF PCB
 - Allegro IPF
 - OrCAD Layout
 - Spectra
 - Zuken CADIF
 - Zuken CADSTAR Schematic
 - Zuken CADSTAR Layout
 - IFF
 - Barco DPF
 - Caltech Interchange Format (CIF)
- Office Formats
 - Rich Text Format (RTF)
- Raster Formats
 - JEDMICS
 - JPEG2000
 - OS/2.1.1 Bitmap
 - AIIM MS53
 - CAD Overlay
 - Dr. Halo PIC
 - Hitachi Tracer
 - IBM IOCA/MODCA
 - Image Center
 - Image Systems
 - Intergraph COT
 - Intergraph Hybrid
 - IRAS/B
 - Neutral Raster File

- Paintbrush PCX
- Portable Bitmap
- RLC File
- Softelec Raster AutoCAD
- Windows 3 Icon-Resource
- X-Windows Dump
- Archive Formats
 - GZip Archive
 - TAR Archive

Desupported File Versions

- MCAD
 - AutoCAD 3D - Prior to version 2000
 - Catia V5 3D - Prior to version 5R17
 - AutoDesk Inventor 3D - Prior to version 10
 - Pro/ENGINEER 3D - Prior to version Wildfire
 - SolidDesigner - Prior to version 15
 - Solid Edge 3D - Prior to version 18
 - SolidWorks 3D - Prior to version 2006
 - Unigraphics 3D - Prior to version NX3
- AEC
 - AutoCAD 2D - Prior to version 2000
 - AutoDesk DXF - Prior to version 2000
 - CATIA V5 2D - Prior to version 5R17
 - AutoDesk DWF - Prior to version 5
 - AutoDesk Inventor 2D - Prior to version 10
 - ME10 - Prior to version 2006/v14
 - Pro/ENGINEER 2D - Prior to version Wildfire
 - Solid Edge 2D - Prior to version 18
 - SolidWorks 2D - Prior to version 2006
 - Unigraphics 2D - Prior to version NX3
- EDA
 - Cadence - Prior to version 15
 - PADS - Prior to version 2005
- Office
 - Excel - Prior to version 2003
 - PowerPoint - Prior to version 2003
 - Word - Prior to version 2003

Known Issues

PDF Measurement Snapping

- If a transparent image is being cropped, measurement snapping still highlights the entire transparent image and ignores the cropping.
- When snapping to a shape, tooltips identifies all types of polygons as a generic *Shape*.
- In Markup mode, measurements have a 1% margin of error. Measurements taken in View mode have higher accuracy.

Oracle AutoVue 20.1, Desktop Deployment

For the most up-to-date version of this document, go to the AutoVue Documentation Web site on the Oracle Technology Network at <http://www.oracle.com/technetwork/documentation/autovue-091442.html>.

Application User License

- AutoVue includes an AutoVue Desktop Version, a Desktop Deployment, and a Client/Server Deployment. For Application User licensing metric (in the Component licensing model) or Custom Suite User licensing metric (in the Custom Applications Suite licensing model), a single license cannot be split or shared between two users (e.g., one user using the AutoVue Desktop Version and a different user using the Desktop Deployment would require two licenses).

Installing AutoVue

Important: If you are migrating from AutoVue Desktop Version to AutoVue Desktop Deployment, a *Migration Guide* is available on the Media Pack in folder *DesktopDeployment* to assist you with the migration.

- The installer for Oracle AutoVue Desktop Deployment has been renamed to *InstallDesktopDeployment.exe*.
- The Oracle AutoVue Desktop Deployment 20.1 installer supports the ability to upgrade from version 20.0. If you have Oracle AutoVue 20.0 installed previously, the installer upgrades the previous configuration settings from *VueCore.ini*, *allusers.ini* and *autovue.properties* when you install version 20.1.
- Configuration options in *VueCore.ini* have been moved to *autovue.properties*.
- By default, AutoVue now installs into the *C:\Oracle\AutoVue Desktop Deployment* directory. If you are installing on UAC enabled systems, ensure that you install at a location to which the user running AutoVue has write permissions.
- For complete installation instructions, refer to the *Oracle AutoVue Installation and Configuration Guide*.

System Requirements

- Windows XP, 32-bit
- Windows Vista, 32-bit and 64-bit (AutoVue running in 32-bit mode)
- Windows 7, 32-bit and 64-bit (AutoVue running in 32-bit mode)
- The installation requires about 400MB of free space

New Features

General Enhancements

- The program shortcut for AutoVue Desktop Deployment has been renamed to *Oracle AutoVue Desktop Deployment*.
- Startup for AutoVue Desktop Deployment is now via an executable (previously used to be a batch file). Version 20 command line options should now be specified as parameters in the “autovue.cmdline” property in file *autovue.properties*.
- Added ability to open a file at startup by specifying the <filename> as a command line option.
- Added System Tray capability to Desktop Deployment.
- Added parameter NEWWINDOW to configure whether or not new files should be opened in new windows.
- Changed the default output location for all log files to <AutoVue Installation Directory>/bin/logs.
- AutoVue Desktop Deployment includes an ActiveX wrapper that provides a migration path for current users of AutoVue Desktop Version’s ActiveX solution. Refer to *ActiveXAPI.htm* and *ActiveXMigrationGuide.pdf* located at <AutoVue Installation Folder>\docs for more information on this ActiveX wrapper.

Hotspots

AutoVue 20.1 supports hotspotting capability. Integrators and developers can integrate AutoVue tightly into other applications so that clicking on sections of text in a document can trigger actions or show information in the other applications. Hotspotting capability is currently supported for text in 2D documents.

Refer to the *Hotspots API Guide* located at `<AutoVue Installation Directory>/docs` folder for more information regarding the Hotspots API.

Markups

- By default, AutoVue Desktop Deployment saves markups in the *avred* directory at the base file location. If the user does not have permission to write into the base file location, they can export the markups into an alternate directory.
- You can save Markup files into a single directory by specifying the full path where the Markup files are to be saved in the `autovue.markups.local.directory` parameter.
- AutoVue no longer relies on the `markups.map` file to map the base file and its associated Markup files. Markup files are now located based on the name of the original document. When saving markups, AutoVue only prompts for the extension of the Markup file. So, Markup files are saved as `<base file name>.<end-user specified extension>`.
Note: If you have multiple files with the same name and different extensions, markups can over-write each other if saved to the same folder.
- If you upgrade from version 20.0 and you have markups saved in the `<AutoVue Install Root>\bin\markups` directory, AutoVue 20.1 can read these markups. However, when you modify and save these markups, they are moved to either the *avred* directory or to the location specified by the `autovue.markups.local.directory` parameter.
- Disabled markups for Microsoft Office formats by default.
Office formats render differently on different machines, if the fonts available on the machines vary. Due to differences in fonts, documents may have line breaks and page breaks that vary from one machine to another. This could result in a situation where markup entities appear misplaced w.r.t underlying text in documents. If you would like to re-enable markup creation for office formats, we recommend that you ensure that all machines viewing the files have the same set of fonts installed.
To enable, set INI option **EnableOfficeMarkups** to 1.
- Added INI option `DEF_TEXTBOXVISIBLE` to control text box outline visibility. See section ["Markup INI Options"](#) for more information regarding this option.
- Added INI option `DEF_LEADERALIGN` to specify leader alignment. See section ["Markup INI Options"](#) for more information regarding this option.

Printing Enhancements

- The default printing in 20.1 is Java Printing. Java Printing is the recommended mode of printing in 20.1. The Java Printing checkbox has been removed from the Print dialog.
- Added support for printing Markup notes.
- Added option to skip blank pages when printing.
- Improved performance for printing documents containing transparent images.
- Improved performance for printing diagonal watermarks.
- Added support for Excel native print settings. A new option **Native settings (from file)** is available in the Print dialog. When selected, AutoVue uses Excel's print settings that are saved in the document. This option only applies to Excel documents.
The following Excel print settings are supported:
 - Page orientation
 - Scaling
 - Paper size
 - Print areas

- Page breaks
- Row and column headers
- Grid lines
- Left/top/bottom/right margins

Note: For a list of unsupported excel print settings, refer to ["Known Issues"](#).

- Added TILELIMIT INI option to control AutoVue print behavior when a single page generates a print output that spans multiple pages. Refer to ["Print Options"](#) for more information.
- Added NativeJavaPrinting INI option to control the usage of native Java graphics. Refer to ["Print Options"](#) for more information.

EDA Functionality Enhancements

- Added ability to measure minimum distance between entities across layers for EDA files.
- Added support for Enhanced Display Modes (EDM) for EDA formats. AutoVue allows users to dynamically control the display of plated and non-plated holes (visibility and color), pad filling and line caps & joins without re-saving and re-loading files. These can be configured via the Options dialog.

For known issues with the Enhanced Display Mode support, refer to ["Known Issues"](#).

- Added ability to modify global transparency for EDA Files. Note that enabling transparency will have an effect on file rendering performance.
- Improved support for Bill of Material (BOM)—AutoVue now provides the ability to select the Board Side attribute. This attribute identifies if a component appears on the top or the bottom side of the PCB board.
- Added ability to modify layer polarity from the layers dialog for Gerber Layer files.

MCAD Formats

- Added support for Autodesk Inventor 2011
- Added support for SolidWorks 2011
- Added support for JT version 9.1
- Added support for CATIA V5 R20
- Added support for SolidDesigner/CoCreate Modeling versions 16.00C, 16.00D, 16.00E, 16.50, 16.50A, 16.50B, and 17.00
- Added support for IGES 3D
- Added support for shaded views in 2D Inventor files
- Added support for SolidEdge assembly features
- Improved support for colors and transparency for SolidEdge parts and assemblies
- General bug fixes:
 - CATIA V5
 - Inventor
 - IGES
 - JT
 - Pro/ENGINEER
 - SolidEdge
 - SolidDesigner
 - SolidWorks

AEC Formats

- Added support for AutoCAD 2011 and AutoCAD Mechanical 2011
- Added support for CoCreate Drafting versions 16.00A, 16.00B, 16.00C, 16.00D, 16.00E, 16.50, 16.50A, 16.50B, and 17.00
- Added support for JPEG compression scheme 7 for TIFF files

- Added support for transparency in JPEG2000 files
- General bug fixes:
 - AutoCAD
 - CGM
 - HPGL
 - TIFF
 - MicroStation
 - Cocreate Drafting
 - Visio
 - JPEG

EDA Formats

- Added support for Zuken CADSTAR 12.0 (PCB/Schematics)
- Added support for Mentor Board Station and Design Architect versions 8.11, 8.12 and 8.13
- Added support for ODB++ version 7.0
- Added support for Orcad Capture 16.3
- Enhanced Cadence project support:
 - Added support for Cadence non-archived projects
 - Added support for Variant views in Cadence projects
 - Added ability to specify site level custom variables for Cadence projects via a cadence.config file
- Added support for the Allegro Module Definition Database files (*.mdd)
- Added support for Cadence Schematic Symbol files (*.css)
- Enhanced support for Gerber Layer File:
 - Added option to specify offset and polarity for layers in a Gerber Layer file
 - Added support for RGB color values and units per Gerber file
- Added support for arc snapping in IPF and IFF files
- General bug fixes for all supported EDA formats

Office Formats

- Enhanced Web services-based text extraction to support Office formats.
- General enhancements for Excel files:
 - Added support for shape transparency
 - Improved support for round-off error
 - Added support for saved print settings
 - Added boolean cell support
 - Improved support for Hyperlinks
- General bug fixes:
 - Word
 - Excel
 - Adobe PDF

Documentation

- The *Installation and System Administration Manual* has been divided into the following manuals:
 - *Oracle AutoVue Installation and Configuration Guide* (InstallGuideDD.pdf)
This document provides information on AutoVue installation and configuration.
 - *Oracle AutoVue Viewing Configuration Guide* (ViewingConfigGuideDD.pdf)
This document contains user-specific INI options.

- Product Limitations document is no longer shipped with AutoVue - The limitations are now available as a KM Note at the Oracle Support site:
<https://support.us.oracle.com/oip/faces/secure/km/DocumentDisplay.jspx?id=1300438.1>
- The following documents are new in 20.1:
 - *Desktop Deployment Migration Guide* (DDMigrationGuide.pdf) - for current users of Desktop Version that are migrating to Desktop Deployment
 - *ActiveX API* (ActiveXAPI.htm) - Desktop Deployment ActiveX API documentation
 - *ActiveX Migration Guide* (ActiveXMigrationGuide.pdf) - for current users of Desktop Version ActiveX that are moving to Desktop Deployment ActiveX
- The following documents have been updated in 20.1:
 - *User's Manual*
 - *Acknowledgments*
 - *Supported File Formats*
 - *Release Notes*
 - *Product Variations - Feature Matrix*

Consolidation of Options in autovue.properties and VueCore.ini

The following options from `VueCore.ini` are now set in `autovue.properties` file located in the <AutoVue Installation folder>\bin directory:

New Options in autovue.properties	Old Options in VueCore.ini		Description
	Section	Parameter	
autovue.users.allusersini	[Users]	AllUsersIni	Name of the allusers INI file.
autovue.users.defaultini	[Users]	DefaultIni	Name of the default INI file.
autovue.users.directory	[Users]	Directory	Contains the directory in which user information is stored (users' initialization files, users' GUI files).
autovue.cache.directory	[Cache]	Directory	Specifies in which directory the cached files should be saved.
autovue.cache.size	[Cache]	Size	Specifies, in Megabytes, the maximum size of the directory containing the cached/streaming files.
autovue.cache.maxnumfiles	[Cache]	MaxNumFiles	Specifies the maximum number of files allowed in the AutoVue cache directory.
autovue.cache.maxlifetime	[Cache]	MaxLifetime	Specifies the maximum number of days a file is kept in the AutoVue cache directory.

New Options in autovue.properties	Old Options in VueCore.ini		Description
	Section	Parameter	
autovue.cache.forceascii	[Cache]	ForceAscii	Forces using ASCII characters in cached files names.
autovue.markups.symbols.directory	[Cache]	SymbolDir	Specifies in which directory the Markups symbol libraries are stored.
autovue.markups.local.directory	[Markups]	Directory	Specifies in which directory the Markups files should be saved.
autovue.markups.permissions	[Markups]	Permissions	Specifies whether all users can see the markups.
autovue.help.file.en	[HELP]	File_en	Entry specifies the URL to the English Help file.
autovue.help.file.fr	[HELP]	File_fr	Entry specifies the URL to the French Help file.
autovue.help.file.de	[HELP]	File_de	Entry specifies the URL to the German Help file.
autovue.help.file.ja	[HELP]	File_ja	Entry specifies the URL to the Japanese Help file.

Desupported Features/Options

- INI options DOCVIEW and DOCVIEWSHOWHEADERS have been desupported in release 20.1. Support for Excel's native print settings has been implemented in 20.1 and these options are no longer required.

INI Options Updated in AutoVue 20.1

- Extended the usage of the CODEPAGE option to be used in AutoCAD DXF files
- Changed the default for EnableOfficeMarkups to 0. Option is set in default.ini.

Refer to the *Oracle AutoVue Viewing Configuration Guide* for information regarding these options.

New autovue.properties options

Parameter	Description	Default
autovue.markups.local.directory= <i>file path</i>	Specify in which directory Markups files should be saved. Markup files are saved as <i><base file name>.<end-user specified extension></i> . By default, AutoVue Desktop Deployment saves markups in the avred directory at the base file location. If the user does not have permission to write into the base file location, they can export the markup into an alternate directory.	<Base file location>\avred
autovue.splash= <i>full path of PNG/JPEG</i>	Specify the splash screen to display while AutoVue starts up. If the full path of the PNG or JPEG is not specified, the splash screen does not display.	

New INI File Settings

All INI options below should be set in user INI files.

Allegro Options

Configure options for Allegro files.

[ECAD]

Parameter	Description	Default
ALLEGRO_ENABLEENHANCEDDISPLAYMODES = [0 1]	Specify whether or not to enable enhanced display modes. Set to 1 to enable enhanced display. Set to 0 to disable them.	1

AutoCAD Options

Configure options for AutoCAD files.

[Options]

Parameter	Description	Default
DISABLE3DMODEL = [0 1]	Specifies whether or not the 3D page of AutoCAD files should be loaded. Set to 0 to include the 3D model in the design. Set to 1 to disable the 3D model. As a result, it is not included in the design and streaming file size is reduced. Note: The option is only applicable to AutoCAD version 2000 files and above.	0

Adobe PDF Options

[Options]

Parameter	Description	Default
ENHANCETHINLINES=[0 1]	Set to 1 to render all geometry that have under one pixel thickness to a thickness of 1 pixel. Set to 0 to disable this option.	1

ECAD Options

Configure options for ECAD files.

[ECAD]

Parameter	Description	Default
ECAD_DISABLE_VARIANTS = [0 1]	Specifies whether to enable or disable variant views. This option can be used to improve performance if the project contains multiple variant views. Set to 1 to disable variant views. Set to 0 to enable variant views. Note: This option currently only supports Cadence/Allegro projects.	0

IGES Options

Configure options for IGES files.

[Options]

Parameter	Description	Default
IGESLOADDRAFTFIRST = [0 1]	Specify whether to display a 2D projection of the 3D model before the full 3D model has finished loading. Set to 1 to display the 2D page first; display of the 3D page as a 2D projection of the 3D model in IGES files. Set to 0 to display the 3D model page first.	0
IGESLOADSUBFIGURED EFINITIONS=[0 1]	Specify whether to display subfigure definition entities when subfigure instances are not found. Subfigure definition entities are used to store a group of entities that occur repeatedly in a file (subfigure instances). Set to 0 so that subfigure definition entities are not found Set to 1 to display subfigure definitions when subfigure instances are not found.	0

Page Size Options in Inches

Configure the parameters for the page size in inches.

[PAGESIZEINCH]

Parameter	Description	Default
A = Width X Height		8.5 x 11.0
B = Width X Height	For example: To set the Imperial page size to be 11.0" x 17.0", add the following section to the end of the configuration file named avwin.ini : [PageSizeInch] B = 11 x 17	11.0 x 17.0
C = Width X Height		17.0 x 22.0
D = Width X Height		22.0 x 34.0
E = Width X Height		34.0 x 44.0

Page Size Options in Millimeters

Configure the parameters for the page size in millimeters.

[PAGESIZEMM]

Parameter	Description	Default
A4 = Width X Height		285 x 198
A3 = Width X Height	For example: To set the metric page size to be 396 mm x 273 mm, add the following section to the end of the configuration file named avwin.ini : [PageSizeMM] A1 = 396X273	396 x 273
A2 = Width X Height		570 x 396
A1 = Width X Height		817 x 570
A0 = Width X Height		165 x 817

2D Output Options

Configure the output options that apply to parameters for 2D file conversion, color correction, page size, and many more.

[Output Options]

Parameter	Description	Default
CONVERTTO =	PCRS_TIF is the default format.	
PCRS_TIF	TIFF: This is the default format.	
PCRS_BMP	Windows Bitmap	

PCRS_GP4	CALS GP4	
PCRS_EPS	Encapsulated Postscript (Raster)	
PCRS_PCL	HP Laserjet Printer (PCL)	
PCRS_PCX	PCX Bitmap	
PCRS_RLC	Run Length RLC File	

PENTHICKNESSFNAM
E = [*fname*]

Specifies the name of the pen mapping file. The pen mapping file contains a mapping of pen index to width. The unit is preset to pixel.
Note: The pen color mapping is format dependent.
AutoCAD - The pen color mapping uses the AutoCAD color palette. You cannot modify the mapping.
HPGL - The pen color mapping is defined in hpglcol.tbl and can be modified by the user.
ME10 - The pen color mapping is defined in me10col.tbl and can be modified by the user.
DWF - The pen color mapping is defined in dwfcol.tbl and can be modified by the user.
Microstation drawings - The pen color mapping is shipped in a binary file, color.tbl. This mapping file can be modified using Microstation. The mapping files are located at <AutoVue Installation Directory> \bin.

CONVERTTOSUB =	Subformat	Format
0	Uncompressed	PCRS_TIF
CONVERTTOSUB =	Subformat	Format
1	PackBits	PCRS_TIF
2	Fax III	PCRS_TIF
3	Fax IV	PCRS_TIF
0	75 dpi	PCRS_PCL
1	150 dpi	PCRS_PCL
2	300 dpi	PCRS_PCL

[Options]

Parameter	Description	Default
COLORDEPTH = [<i>original</i> number]	Set the number of bits for the image plane.	ORIGINAL
CONVERTAREA = [DISPLAY EXTENTS]	Indicates the portion of the drawing to be converted. If CONVERTAREA = EXTENTS , the file extents are printed. If DISPLAY is specified, the area given by the DISPLAY option is used. If the DISPLAY option is not set, the extents are printed.	DISPLAY
OUTPUTPAGESIZE = [A B C D E A4 A3 A2 A1 A0 U MAX1 MAX2]	Specifies the current page size.	A

DEFAULTHEIGHT = [height]	Specifies the default height (in pixels) used when converting from vector to raster formats.	480
DEFAULTWIDTH = [width]	Specifies the default width (in pixels) used when converting from vector to raster formats.	640
FLIPPING = [NONE VERTICAL HORIZONTAL BOTH]	Specifies the flipping direction(s).	NONE
HEIGHT = [height]	Specifies the height in pixels.	0 (in pixels)
INPUTFILE = [fname]	Specifies the name and path of the input file.	No default
LAYER<index> = [0 1]	For drawings containing layers, only the layers which are equal to 1 are converted. Example: LAYER1 = 0	1 for all layers
NCOLORS = [num]	This specifies the number of colors to generate in the output image. The string True Color is used to generate true color images. If the converter does not support the number specified, the closest supported number is used.	The highest number of colors supported for the target format.
NUMLAYERS = [num]	Specifies the number of layers that exist.	
ORIGIN = [unitsX;unitsY]	Both X and Y are given in the current UNITS. This specifies the X and Y offset.	X=0 and Y=0
OUTPUTFILE = [fname]	Specifies the output file name.	No default
OVERLAY<index> = [filename][offsetx. offsety, offsetz] [basex, basey, basez] [scalex, scaley, scalez] [dpix, dpiy, dpiz]	Specifies a file to overlay. Any number of overlay files can be specified by making multiple entries with different indexes.	No default
OVERRIDE THICKLINES = [0 1]	Set to 1 , AutoVue will print as per pen settings. Set to 0 , AutoVue applies pen settings only to thin lines. Thick lines print with their original thickness. Note: Option only applies if pen settings are defined.	1
PAGES = [0 1 2]	Specifies which page(s) to convert for a multi-page input file. Pages are numbered starting at 1. 0 = All pages 1 = Page range 2 = Current page	1
REDLINEFILE = [filename]	Specifies a Markup file to overlay.	
ROTATION = [0 90 180 270]	Specifies the angle (in degrees) that the drawing is rotated.	0
SCALING = [FIT FACTOR]	Indicates the scaling factor for a drawing.	FIT
SCALINGFACTOR = [X; Y]	This indicates the scaling factor by specifying that X input units must correspond to Y output units.	X=1 and Y=1

SKIPMODE = [AUTO AND OR SKIP]	Specifies how to delete raster lines when an image's size is reduced. SKIP : suitable for color images. AND : for monochrome images with a light background. OR : for images with a dark background. AUTO : causes AutoVue to determine the best mode based on the image's characteristics.	SKIP
TILESIZEX	Specifies the number of pixels in tile X.	96
TILESIZEY	Specifies the number of pixels in tile Y.	96
TRUEEXTENTS = [X0,Y0;X1,Y1]	Specifies the true extents of the input file. Used by the conversion when CONVERTAREA = EXTENTS . If not specified, the conversion evaluates the true extents.	
UNITS = [PIXEL INCH MM]	Specifies the units to be used when printing or converting a file.	PIXEL
WIDTH = [width]	Specifies the width in pixels.	0
XResolution YResolution	Specifies the resolution of the output device - in this case the output bitmap. They are used when we have thick lines and we need to compute the output line thickness in pixels so it will match the desired line thickness when the bitmap is shown/printed in this resolution. These options will not affect files with no thickness.	Screen resolution is used if no value is specified

[PCRS_BMP]

Parameter	Description	Default
STEPSPERINCHX = [num]	Specifies the conversion factor between device units and inches.	72
STEPSPERINCHY = [num]	Specifies the conversion factor between device units and inches.	72

[PCRS_EPS]

Parameter	Description	Default
STEPSPERINCHX = [num]	Specifies the conversion factor between device units and inches.	720
STEPSPERINCHY = [num]	Specifies the conversion factor between device units and inches.	720

[PCRS_PLG-1]

Parameter	Description	Default
STEPSPERINCHX = [num]	Specifies the conversion factor between device units and inches.	75
STEPSPERINCHY = [num]	Specifies the conversion factor between device units and inches.	75

[PCRS_PLC-2]

Parameter	Description	Default
STEPSPERINCHX = [<i>num</i>]	Specifies the conversion factor between device units and inches.	150
STEPSPERINCHY = [<i>num</i>]		

[PCRS_PLC-3]

Parameter	Description	Default
STEPSPERINCHX = [<i>num</i>]	Specifies the conversion factor between device units and inches.	300
STEPSPERINCHY = [<i>num</i>]	Specifies the conversion factor between device units and inches.	300

[PCRS_PCX]

Parameter	Description	Default
STEPSPERINCHX = [<i>num</i>]	Specifies the conversion factor between device units and inches.	300
STEPSPERINCHY = [<i>num</i>]	Specifies the conversion factor between device units and inches.	300

[PCRS_RLC]

Parameter	Description	Default
STEPSPERINCHX = [<i>num</i>]	Specifies the conversion factor between device units and inches.	200
STEPSPERINCHY = [<i>num</i>]	Specifies the conversion factor between device units and inches.	200

[PCRS_TIF]

Parameter	Description	Default
STEPSPERINCHX = [<i>num</i>]	Specifies the conversion factor between device units and inches.	200
STEPSPERINCHY = [<i>num</i>]	Specifies the conversion factor between device units and inches.	200
PREVIEW = [0 1]	Specifies if a preview image should be generated. If PREVIEW = 1 , then a 128x128 preview image is generated as the first page of the destination file.	1
TILING = [0 1]	If 1 , tiles the image; otherwise stripes the image.	1

Parameter	Description	Default
NSTRIPS = [0 1]	If 1 , defines the number of stripes for an image.	1
TILESIZEX = [num]	Specifies the number of pixels in tile X.	
TILESIZEY = [num]	Specifies the number of pixels in tile Y.	

Pen Mapping Options

Configure the pen mapping options that apply to pen color, thickness and speed.

[Pen Mapping]

Parameter	Description
PENS_starting_pen_number-ending_pen_number = [color, thickness, speed]	<p>Specifies the numerical index for the pen color, thickness (in inches) and speed (in inches per second). The starting pen number must be a multiple of 8; the ending pen number must equal the starting pen number plus 7.</p> <p>Example: PENS16-23 = [16, 0.0100, 36] [17, 0.0100, 36] [18, 0.0100, 36] [19, 0.0100, 36] [20, 0.0100, 36] [21, 0.0100, 36] [22, 0.0100, 36] [23, 0.0100, 36]</p>

Disable Options

Configure the Disable options parameters to disable options such as **Browse**, **Next**, or being able to change print settings.

[Disable]

Parameter	Description	Default
ANTIALIASING = [0 1 2 4 8]	Specify whether to disable certain types of antialiasing. Set to 0 to allow all types of antialiasing. Set to 1 to disable image antialiasing. This also disables image blurring (value=8). Set to 2 to disable text antialiasing. Set to 4 to disable geometry antialiasing. Geometry includes lines, arcs, polygons, ellipses and rectangles. Set to 8 to disable image blurring. Blurring is an interpolation that is performed when images are magnified to prevent pixelation. Disabling image antialiasing (value=1) also disables blurring. Note: To use this option, ANTIALIAS must be set to 1 .	0
BATCHPRINT = [0 1]	If 1 , disables batch printing.	0
BROWSE = [0 1]	If 1 , disables the File menu's Browse , Next , and Previous options.	0
LAUNCH = [0 1]	If 1 , disables the File menu's Launch option.	0
MARKUP = [0 1]	If 1 , disables Markup mode.	0
MARKUPFORCETOBLACK = [0 1]	Specifies whether to force markup color to black for high resolution printing. Set to 1 so that markup color is not forced to black (even when base file printing is forced to black). Set to 0 to use the same logic as for the base file color.	0
MAIL = [0 1]	If 1 , disables the Mail option in View mode's File menu. If 1 , also disables the Notify option found in the Save and Save As dialog as in Markup mode.	0
PRINT = [0 1]	If 1 , disables printing.	0
PRINTSETTINGS = [0 1]	If 1 , disables changing listed print settings - margins, watermark, headers/ footers, pen settings and stamps.	0
PRINTTOFILE = [0 1]	If 1 , disables option to print to file.	0
PRINTMARGINS = [0 1]	If 1 , disables changing Print-Margins.	0
PRINTHEADERSFOOTERS = [0 1]	If 1 , disables changing Print Headers and Footers.	0
PRINTWATERMARKS = [0 1]	If 1 , disables changing the Print-Watermark.	0
PRINTSTAMPS = [0 1]	If 1 , disables changing the Print-Stamps.	0
PRINTPENSETTINGS = [0 1]	If 1 , disables changing the Print-Pen settings.	0
THUMBNAILS = [0 1]	If 1 , disables the creation of Thumbnails.	0
CONVERT = [0 1]	If 1 , disables converting.	0
CLIPBOARD = [0 1]	If 1 , disables copying to the clipboard.	0

Parameter	Description	Default
SYSTEMTRAY = [0 1]	If 1 , disables the AutoVue system tray icon.	0

Disable Options

Configure the Disable options parameters.

[Disable]

Parameter	Description	Default
SYSTEMTRAY=[0 1]	Specify whether to display the system tray icon. Set to 0 to display the system tray icon. Alternately, you can also leave this option empty to display the icon. Set to 1 to disable the system tray icon.	0

Overlay Options

Configure options that apply to laying files over the current active document.

[Overlay Options]

Parameter	Description	Default
MATCHEXTENTS = [0 1]	Specifies how to scale the overlay. Set to 1 so that the overlay is scaled based on the current file extent (turns off MATCHEXTENTS). Set to 0 so that the overlay is scaled based on file units (turns on MATCHEXTENTS).	1

Memory Options

Configure memory options.

[DisplayMemory]

Parameter	Description	Default
STACKS=<number of zoom levels>	Specifies number of zoom levels to cache. The minimum value is 0. When set to 0, none of the previous zoom levels are cached.	5
TILES=<1 to 9>	Specifies the number of tiles to cache for a given zoom level. Setting TILES to a smaller number reduces memory usage for the interactive options such as zoom, scroll and pan. If you are working primarily with Word and Excel documents and memory is a constraint, we recommend that you set this option to 2.	9

Print Options

Configure print options.

[PrintOptions]

Parameter	Description	Default
NATIVEJAVAPRINTING=[0 1]	Specifies whether to use native Java graphics when printing on Windows operating systems. Set to 0 to use AutoVue's customized printing. This provides better performance and uses windows API calls instead of native Java calls. Set to 1 to use native Java printing.	0
UIEnablePrintTypeSelection=[0 1]	Set to 0 to disable display of the Java Printing checkbox in the Print dialog. Set to 1 to enable display of the Java Printing checkbox in the Print dialog. When enabled, users can control whether they want to use Java Printing or Server Side Printing. By default, AutoVue 20.1 uses Java Printing.	0
TILELIMIT= <i>int</i>	Define the limit of the number of pages to print if a page of the document generates a print output that spans multiple pages. A negative integer (for example, -32), sets a "soft" limit to the number of pages to print. That is, if a single page generates more pages than the absolute value of the integer (for example, 32), then the user is prompted to choose whether to print upto the limit or print to fit onto one page. A positive integer (for example, 32), sets a "hard" limit to the number of pages to print. That is, if a single page generates more pages than the value specified, AutoVue ignores the print settings and prints the document to fit onto one page.	-32

[OPTIONS]

Parameter	Description	Default
SUPPORTLANDSCAPEPRINTING=[AUTO OFF <i>printer1 name; printer2 name;...</i>]	Specifies whether the page layout of a landscape page should be landscape in the print output. AUTO: When printing to a file printer, page layout for a landscape output is forced to landscape. OFF: Does not force the layout for landscape outputs. <i>printer name</i>: Forces layouts for landscape pages to be landscape for specified printer drivers. You can specify multiple printers in a semi-colon (;) separated list. Note: If the specified printers do not support landscape printing, the output may be unusable. As a result, only add printers that support landscape printing.	AUTO

Markup INI Options

[Markup Options]

Parameter	Description	Default
DEF_TEXTBOXVISIBLE=[1 0]	Set the option to 0 or 1 to turn the visibility of markup text box OFF or ON.	1

Parameter	Description	Default
DEF_LEADERALIGN= <i>value</i> <i>from 0 to 8</i>	Set one of following options to specify leader alignment: 0 - Top Left 1 - Top Center 2 - Top Right 3 - Center Left 4 - Center Center 5 - Center Right 6 - Bottom Left 7 - Bottom Center 8 - Bottom Right	7

Known Issues

- Excel Print Settings
 - Excel calculates row and column widths based on the default font set in the file. On different printers, these calculations can differ. As a result, Excel prints differently on different machines. AutoVue attempts to match Excel behavior, but may still differ slightly from Excel in terms of page breaks, line breaks, column widths or row heights. See <http://support.microsoft.com/kb/214394/en-us> and <http://support.microsoft.com/kb/214278> for more information.
 - When Excel's print settings use a paper size that is not supported by the printer that is installed on the AutoVue server, AutoVue defaults to Letter size.
 - Excel has an option called **Scale content for A4 or 8.5x11 paper sizes**. When enabled, Excel chooses to print to A4 even if you specify Letter or vice versa. Excel also automatically scales the drawing to the paper size it chooses. AutoVue, however, always prints to the setting saved in the Excel document and ignores this **Scale content for A4 or 8.5x11 paper sizes** option. See <http://support.microsoft.com/kb/284867> for additional information for this option.
 - The following Excel print settings are not supported in AutoVue:
 - Header and Footer margins
 - Center on Page
 - Header and Footer options other than content and position
 - Print titles (repeat row and columns on each page)
 - Black and White setting
 - Draft quality
 - Comments
 - Cell errors
 - Page Order (Down, then Over); AutoVue prints "Over, then Down" in all cases
 - Object Printing

- When **Native Settings (from file)** option is selected in the Print dialog to enable Excel print settings, some of AutoVue printing abilities are not available. These are:
 - Headers and Footers
 - Scaling settings (Fit to Page, Scale and Factor)
 - Orientation Settings
 - Margin Settings
 - Alignment/Offset settings
 - Page Area settings
 - Print Row and Column headers
 - Paper size selection
- Enhanced Display Modes
 - Enhanced Display Modes are not supported when you convert a file to another format from AutoVue or when you disable Java printing.
 - Enhanced Display Modes are not supported when files are rendered in TILED mode.

Oracle AutoVue 20.0.0, Desktop Deployment

Packaging

- Oracle AutoVue (previously called Oracle AutoVue Web Version) now supports two deployment methods: Client/Server and Desktop deployment methods. The previous AutoVue Web Version product is now the Client/Server deployment of AutoVue. A new Desktop deployment has been developed for users that want to install AutoVue as a standalone product locally.

System Requirements

- Windows XP 32-bit
- Windows Vista 32-bit
- The installation requires about 400MB of free space.

AutoVue Installation

AutoVue installation consists of the following steps:

- 1 “Installing AutoVue”
- 2 “Configuring AutoVue”
- 3 “Command-Line Configurations for AutoVue”
- 4 “Verifying Your AutoVue Installation”

Refer to the *Installation and Administration Manual* for instructions.

3D Functionality Enhancements

- Added 3D Walkthrough capabilities which allow users to view 3D models from within and explore buildings and structures.
- Enhanced 3D distance measurements
 - Improved snapping options for 3D distance and 3D minimum distance measurements. Snapping options let you snap to vertices, lines, arc centers and planes. If you wish to revert to 19.3 measurements (snap to vertices, edges and points on faces), set the SHOW_POINTOPOINT_PAGE INI option. Refer to the *Installation and Administration Manual* for more information.
 - AutoVue now computes the minimum distance between two geometries instead of the distance between points on geometries.
 - Added ability to measure the minimum distance between a 3D part and a sectioning plane.
- Added ability to restore to 3D default view. If you transform or manipulate your model and you would like to restore to the view at which the model loaded initially, you can do so by selecting the **Default View** item that has been added to the Views tree and the **Views** menu.
- Enhanced 3D entity search to allow users to specify a search string. This search feature returns all 3D entities that contain the search string in their attribute names and/or attribute values.

Printing and Conversion Enhancements

- Updated the Conversion to PDF feature. When converting a file to PDF, Markups are now included as graphical elements in the PDF instead of being added as annotations to the PDF. If you wish to revert to the old behavior (convert to PDF annotations), set INI option CONVERTPDFTHROUGHPRINTING to 0.

- Moved printing to the client-side by default. Added **Java Printing** (client-side printing) as the default option in the Print dialog. To use the previous release's native printing, deselect the **Java Printing** checkbox. Refer to the "Printing Options" section of the *User's Manual* for more information.

General Enhancements

- Added ability to align and scale drawings in 2D and EDA compare modes. You can now snap to a point on both drawings to align the drawings, or snap to two points on both drawings to align and scale the drawings.
- Improved support for files created on non-English locales.

Performance Improvements

- Improved performance for MicroStation designs.
- Improved interactive rendering of 3D models.
- Improved ability to load and work with large 3D models.

MCAD Formats

- Added support for Pro/Engineer WildFire 5 and WildFire 4
- Added support for Unigraphics NX6
- Added support for Solid Edge ST and ST2
- Added support for Autodesk Inventor 2010, 2009
- Added support for Cocrete Modeler versions 2008 (16.XX)
- Added support for Revit 2010 (through exchange format)
- Added support for Solidworks 2010 and 2009
- Added support for CATIA 5 R19
- Re-introduced support for DirectModel (JT) versions 8.1, 8, 7, and 6.4
- Added support for Unicode file names
- Added support for Chamfer, Bend Notes, and Revision tags for Autodesk Inventor drawings
- Added support for one-symbol diameter dimensions for CATIA 5 drawings
- Added support for Parasolids version 22.0, 21.0, 20.0 and 19.1
- Added support for STL assemblies
- General enhancements for CATIA 4
 - Performance improvements for CATIA 4
 - Added support for PMIs
 - Improved support for text display (alignment, orientation, and positioning)
 - Improved support for text frames
- Consolidated CATIA 5 INI options CATIA5ShowPMI and CATIA5ShowPMIWithMesh into a single INI option: CATIALOADPMI
- **See "New INI File Settings" on page 39**
- Added support for project-related attributes for IFC
- General bug fixes for:
 - Pro/Engineer
 - Unigraphics
 - CATIA 4
 - CATIA 5
 - SolidWorks
 - SolidEdge
 - Autodesk Inventor
 - Directmodel (JT)
 - IFC
 - STEP

AEC Formats

- Added support for SmartsSketch version 2009
- Added support for Cocreate Drafting 2008 (16.XX)
- Added support for AutoCAD/Autodesk Mechanical Desktop version 2010, 2009
- Added support for AutoCAD 2010
- Added support for MicroStation 8i
- Added support for DWF 3D
- Performance improvement for Microstation 8 3D and Microstation 7 3D
- Added support for hyperlinks associated with WebCGM drawings
- Enhanced parts display in block lists to match the order and representation of Cocreate drafting
- Added new INI option ACADDEFAULTSHAPEFONT to allow users to specify default shape font for AutoCAD drawings

See "New INI File Settings" on page 39

- Added support for user-defined bigfont code-page for AutoCAD. Bigfont information should be added to [BIGFONTCODEPAGES] section of acadfont.map which is located in the <AutoVue install folder>\bin directory. Bigfont code page mapping is only needed for AutoCAD versions 2007 and up. For more information on mapping, refer to the instructions provided in acadfont.map.
- Improved support for non-English text in AutoCAD
- Improved display of dimensions in Microstation 8
- General bug fixes for:
 - AutoCAD
 - MicroStation
 - Cocreate Drafting
 - Autodesk DWF
 - CGM
 - HPGL
 - Shapefile

EDA Formats

- Added support for Allegro PCB Layouts versions 16.3, 16.2, and 16.0
- Added support for Allegro Design Entry HDL 16.3, 16.2, and 16.0
- Added support for Altium Designer versions 6.6, 6.7, 6.8 and 6.9, Summer 2008, Winter 2009, and Summer 2009
- Added support for Zuken Cadstar versions 10.00 and 11.00
- Added support for P-CAD 2006
- Added support for locating external reference files for non-archived Allegro projects, DxDesigner, Expedition, ODB++ and Mentor BoardStation files. There is now no need to specify XRefs path if the resources are located at the base file path.
- Added support for OrCAD Layout and Capture version 16.2
- Reintroduced support for GDS-II
- General bug fixes for:
 - Allegro PCB Layouts
 - Allegro Design Entity HDL
 - P-CAD
 - DxDesigner
 - Expedition
 - Mentor BoardStation

Office Formats

- Added support for Adobe Acrobat PDF 9.0

- Added support for PowerPoint 2007
- Added support for text and shape hyperlinks for PowerPoint files
- Added support for Smart Art for PowerPoint XML
- Improved support for Word:
 - Added support for default Asian line spacing.
 - Added support for search, copy, and paste.
 - Added support for auto-numbering.
- Improved chart support for Excel
- Improved support for PDF transparency and soft masks.
- General bug fixes for:
 - Adobe Acrobat PDF
 - PowerPoint
 - Word
 - Excel
 - RTF

Raster Formats

- Re-introduced support for JEDMICS

Archive Formats

- Added support for TAR and GZIP formats

Documentation

The following documents have been updated in 20.0.0:

- *Installation and Administration Manual*
- *User's Manual*
- *Acknowledgments*
- *Supported File Formats*
- *Product Limitations*
- *Release Notes*
- *Product Variations - Feature Matrix*

Formats Desupported in AutoVue 20.0.0

- Support for IGES 3D has been removed from AutoVue 20.0.0. Customers who work with this format are encouraged to remain with their AutoVue 19.3.x version and not update to 20.0.0. Customers will be notified when support for IGES 3D has been re-introduced.
- Removed support for LHA archive format.

Features Desupported in AutoVue 20.0.0

- Removed support for the following INI options:
 - ME10FORCE19.1MARKUPCOMPATIBILITY
 - DNGPLOTTERDRIVER
 - DGNUSEPLOTTERSETTINGS
 - DGN8LSTYLERSC
 - DGNFONTMAP
 - CATIA5SHOWPMIWITHMESH
 - PDFDPIRESOLUTION
 - PDFCACHELEVEL
 - CATIA5SHOWPMI
 - FIXPRINTING
- In Markup mode, it is not possible to anchor a text box to another markup entity.

INI Options Updated in AutoVue 20.0.0

- ANTIALIAS
- CONTRAST
- VISIOPAGEBKCOLOR
- 3DPERFORMANCEPREFERENCE
- DGN_FAST3D

Refer to the *Installation and Administration Manual* for information regarding these options.

New INI File Settings

General Options

Configure options that apply to parameters such as fonts, performance, and color

[Options]

Parameter	Description	Default
CONVERTPDFTHROUGHPRINTING = <0 1>	Specifies whether markups should be rendered through printing or converted to PDF annotations through markup conversion module. Set to 1 to render through printing. Set to 0 to convert to PDF annotations.	1
ENABLEUFCAUTOCOMPLETE=[0 1]	Specifies whether to enable the filename auto-completion option for the File Open dialog. Set to 1 to enable filename auto-completion option. Set to 0 to disable filename auto-completion option.	1
REPLACEMENTFONTS= <i>font1;font2;...;fontn</i>	Specifies a list of replacement TrueType fonts to use when required TrueType fonts do not have the required glyphs. This option applies to all 2D vector formats containing non-English TrueType text. Specify a semicolon (;) separated list of font face names.	

STATUSBARPATHPREFERREDWIDTH = <numeric value>	Specifies the character width of the file name field in the status bar. When you specify a value for StatusBarPathPreferredWidth, it controls the proportion of the file name field with respect to the other fields displayed in the status bar. The file name field width will vary when loading different types of formats or if the applet size changes. This is because the value specified controls the proportion and does not set it to a fixed width. Note: To be able to display 56 characters in the file name field (STATUSBARPATHPREFERREDWIDTH=56), the client applet width must be greater than 800 pixels when all the default fields are displayed in the status bar.	12
SHOW_POINTOPOINT_PAGE = <0 1>	Set to 1 to hide the Point to Point distance tab. Set to 0 to display the Point to Point distance tab. Note: When snapping to an edge with the Point to Point distance tab enabled, the distance is measured from the exact point you click on the drawing (rather than the midpoint).	1
ZOOMBOXENABLED=<0 1>	When a file is opened, this parameter sets the default mode of the mouse pointer to a zoom box. Note: This parameter only works with non-3D designs. Set to 1 to set the default mode of the mouse pointer to a zoom box. Set to 0 to disable option.	1

Disable Options

Configure the Disable options parameters.

[Disable]

Parameter	Description	Default
MARKUPFORCETOBLACK = <0 1>	Specifies whether to force markup color to black for high resolution printing. Set to 1 to not force markup color to black (even when base file printing is forced to black). Set to 0 to use the same logic as for the base file color.	0

Overlay Options

Configure Overlay options that apply to laying files over the current active document.

[Options]

Parameter	Description	Default
CONVERTWMFT OEMF = <0 1 2>	Specifies if the WMF should be converted to EMF. This is option is useful when troubleshooting display issues with WMF. Set to 0 to disable WMF to EMF conversion. Set to 1 to convert WMF overlays to EMF. Set this value if enhanced functionality such as rotate and mirroring is required. Set to 2 use default behavior of the format handler.	2

Print Options

Set the parameters that define various aspects of how your documents print, including pen and pixel thickness, printing notes and orientation.

[Options]

Parameter	Description	Default
PRINTINGDPI = <i>[DPI]</i>	Specifies the DPI for java printing. This value affects the size of the image that is sent to the printer graphics.	144
PRINTWITHBICUBICINTERPOLATION = <i><0 1></i>	Specifies whether to enable bi-cubic interpolation rendering of the image during printing. Set to 1 to enable bi-cubic interpolation rendering. Print quality is improved but performance might be reduced. Set to 0 to disable bi-cubic interpolation rendering.	1

Markup Options

Configure a variety of Markup options such as symbol for markup dimensions.

[Markup Options]

TRUEBACKGROUND= <i><0 1></i>	Used when a highlight markup is applied on a colored background (for example, graphic/filled cell areas in office document tables). Set to 1 for a dithered highlight markup. Set to 0 for a normal highlight markup.	0
------------------------------------	-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------	---

[Options]

Parameter	Description	Default
ALLOWSTAMPLIBRARYEDIT = <i>[0 1]</i>	Specifies whether you can edit/delete a stamp library. Set to 1 to enable editing/deleting of a stamp library. Set to 0 to disable editing/deleting of a stamp library.	0

Text Options

Configure options for text files.

[Options]

Parameter	Description	Default
MAXPLAINTEXTPAGES = <i>num</i>	Sets the maximum number of plain pages to be loaded to help improve performance. The option only affects unformatted text; other types of documents (Word, RTF, and so on) are not affected. Note: Setting the option value to 0 or less results in the entire file loading.	1000

Acrobat PDF Options

Configure options for Adobe PDF files.

[Options]

Parameter	Description	Default
PDFENHANCELINES	If set to 1 , this option results in enhanced line display similar to the Adobe Acrobat option Enhance Thick Lines. This option is useful for cases when lines start to disappear in the AutoVue display when zooming out. If set to 0 , this option is disabled and the line display is not enhanced.	0
PDFMAXIMAGESIZE = <val>	Allows users to set the maximum image size limit (in Mbytes) of large bitmaps in PDF files after which the PDF decoder starts reducing resolution to reduce memory use.	150

AutoCAD Options

Configure options for AutoCAD drawings.

[Options]

Parameter	Description	Default
ACADDEFAULTSHAPEFONT	Specifies the default shape font filename that should be used if the desired shape font file and an equivalent AutoVue font cannot be found. You can specify a full file path or just the file name. The decoder searches for the font file name in the file path (if provided), the base file folder, XFONTPATHS, and the fonts directory of the installation.	
SHOWNONRECTVIEWPORTS = <0 1>	In AutoCAD it is possible to create non-rectangular viewports. When a file has non-rectangular viewports, it may take AutoVue longer to display the drawing. Set to 1 to display non-rectangular viewports. Set to 0 to disable display of non-rectangular viewports and improve performance. Note that the accuracy of the display will be compromised. Note: This options applies to AutoCAD 2000 and up files.	1
ACAD_MAXNUMLINETYPECYCLES	Specifies the maximum number of times a line type pattern can be repeated for a particular entity segment. Any entity segment that has more cycles than 1000 is drawn with a solid line type. Syntax: [Options] ACAD_MAXNUMLINETYPECYCLES = [0-1000]	256

Cadence Options

Configure options for Cadence Concept HDL file.

[ECAD]

Parameter	Description	Default
CADENCE_CALLOUTS FILE = <file path>	Specifies the full path to a callouts file. The callouts file is used to create abstract mechanical part entities for the design	

CATIA Options

Configure options for CATIA 4 and 5 files.

[Options]

Parameter	Description	Default
CATALOADPMI = <0 1>	Set to 1 to enable displaying of PMIs. Set to 0 to disable displaying of PMIs.	1

CSI Shapefile Project Files

CSI shapefile project files (CSHP files) are used to overlay multiple ESRI shapefile drawings. Project files specify the shapefiles that should be overlayed and general information such as units and point options. Project files are formatted as standard INI configuration settings files. Comments in CSHP files begin with a semi-colon(;).

Note: A CSI shapefile project file must begin with the following line: ;CSI shapefile project file

[PROJECTPROPERTIES]

Parameter	Description	Default
UNITS=<value>	Specifies the file units. Possible values: <ul style="list-style-type: none">• px• inches• millimeters• mm• twips• centimeters• cm• decimeters• dm• meters• m• kilometers• km• feet• yards• miles• millimeters• micromiles• microns• microinches	

POINTTYPE=<value >	Specifies what shape to use when drawing a point. Possible values: <ul style="list-style-type: none"> • Circle • Triangle • Square • Star • Dot • Plus • Cross • Diamond 	Circle
POINTSIZ= <i>int</i>	Specifies what size in pixels to use when drawing a point. You can assign <i>int</i> any integer greater than 0.	7

[LAYERS]

Parameter	Description	Default
OUTLINECOLOR= <i>int</i>	Specifies the color to use when drawing outlines for graphics such as points, lines, polygons, and so on. Possible integer range: [-1, 255] Set to OUTLINECOLOR=-1 so that an internal counter is used to determine the color. The counter is incremented a maximum of two times per layer and only if it is required: once for the outline color (if it is not provided) and once for the fill color (if it is not provided). Example: If a user provides valid outline and fill colors, the counter is not incremented for the given layer. However, if the user only provides a valid outline color, the counter increments once for the given layer.	-1
FILLCOLOR= <i>int</i>	Specifies the color to use when the drawing fills for graphic (such as polygons). Possible integer range = [-1, 255] Set to FILLCOLOR=-1 so that an internal counter is used to determine the color. The counter is incremented a maximum of two times per layer and only if it is required: once for the outline color (if it is not provided) and once for the fill color (if it is not provided). Example: If a user provides valid outline and fill colors, the counter is not incremented for the given layer. However, if the user only provides a valid outline color, the counter increments once for the given layer.	-1
LINEWIDTH= <i>int</i>	Specifies the line width to used when drawing graphics. Possible integer range: [0,100]	0
VISIBLE=<0 1>	Specifies the visibility of the shapefile. Set to 1 to make the shapefile visible when initially loading the CSI shapefile project. Set to 0 to make the shapefile invisible when initially loading the CSI shapefile project.	1

POINTTYPE=<value>	Specifies what shape to use when drawing a point.	Circle
<p>Note: If a POINTTYPE is not provided for a given [LAYER] section, then the POINTTYPE provided in [PROJECTPROPERTIES] section is used.</p> <p>Possible values:</p> <ul style="list-style-type: none"> • Circle • Triangle • Square • Star • Dot • Plus • Cross • Diamond 		
POINTSIZ=um	Specifies size in pixels to use when drawing a point.	7
<p>Note: If a POINTSIZE is not provided for a given [LAYER] section, then the POINTSIZE provided in [PROJECTPROPERTIES] section is used.</p> <p>You can assign <i>num</i> any integer greater than 0.</p>		
FILENAME= <i>file path</i>	Specifies the name of the ESRI shapefile drawing.	

ECAD Options

Specify configuration options for ECAD.

[ECAD]

ECAD_3D_CUTOUTDRILLHOLE S = <0 1>	Specifies whether to cut drill holes out of the 3D model of the board. Set to 1 to cut out drill holes. Set to 0 to disable drill holes. Note: Setting this option to 1 increases the amount of memory required to load the 3D model. Also, for DMU purposes, this option should be set to 1 to correctly check for interference for parts that go through the drill holes.	0
ECAD_SHOW_NATIVE_HIGHLIGHTS = <0 1>	Specifies whether AutoVue should display a file's native highlighting. Set to 0 so that the native highlighting in the file is ignored during display. Set to 1 so that the native highlighting in the file is applied during display.	1

Excel Options

Configure options for Excel files.

[Options]

USESMALLFONTSFORXCELS MALLTEXT = <0 1>	Set to 1 so that the Excel Small Fonts font is used to display text at small fonts sizes of 7 points or less (matching Excel behavior). Set to 0 so that the Small Fonts font is not used. Note: This parameter has effect only if the Small Fonts font is installed on the system (it usually comes with Excel).	0
-------------------------------------------	----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------	---

Gerber Options

Configure options for Gerber files.

[Gerber Format]

ENDOFCOMMAND = <ASTERISK DOLLAR ENDOFFLINE AUTODETECT>	Specifies the end of command character if known. If end of command character is not known, ENDOFCOMMAND can be set to AUTODETECT mode. Available values: ASTERISK: End of command is * DOLLAR: End of command is \$ ENDOFFLINE: End of command is the end of the line. AUTODETECT: AutoVue automatically detects the end of command character.	AUTODETECT
MULTIQUADRANT_ARCS_BY_ DEFAULT = <0 1>	Specifies whether the default circular interpolation is multi-quadrant or single-quadrant. Set to 0 so that the circular interpolation is single-quadrant. Set to 1 so that the circular interpolation is multi-quadrant.	0

DirectModel (JT) Options

Configure options for JT files.

[Options]

Parameter	Description	Default
JTRESOLUTION = <HI MED LO>	When available, enables users to load the model's high, medium, and low resolution meshes. Note: It is recommended to reduce the model's resolution mesh to LO if loading large complex assemblies degrades performance or utilizes significantly high memory resources.	HI

MicroStation Options

Configure options for MicroStation files.

[Options]

DGNDISABLEZCLIP = <0 1>	Specifies whether to take the z-axis into consideration when applying a clip region (a cut-out region) to a 2D drawing. Set to 1 if the contents of the clipped image should not be restricted based on the z-coordinate of individual objects. Set to 0 if the contents of the clipped image should be restricted based on the z-coordinate of individual objects. Note: This option only applies to 2D drawings; it is not considered when loading a 3D model. Note: Option applies to Microstation 7 files.	0
DGNSHOWZEROLENGTHLINES = <0 1>	Set to 1 to display zero-length lines as fixed-sized filled squares. Set to 0 to ignore zero-length lines. Note: Option applies to Microstation 7 files.	0

DGNLSTYLEDASHDOT =
<description>,<number of
patterns>,<pattern1>,<pattern2
>,...,<pattern6>

Defines up to seven line styles (indexed from 1 to 7). Each line style, separated by a comma, can include up to six patterns. Each line style must be preceded by a description and a number specifying the number of patterns for the style.

Example:

DGNSTYLEDASHDOT = style1,5,-1,1,0,-1,2,style2,3,2,-2,-2

In this example, two line styles (index 1 and index 2) are defined. the line styles provided by this parameter replaces the default seven standard styles. A line that uses style index that has not been provided is displayed as a solid line (for example, a line with style3 when only two styles have been defined).

SolidWorks Options

Configure the option for SolidWorks files.

[Options]

Parameter	Description	Default
SWSHOWVIEWPORTBORDER	Set to 1 to view the border (bounding box) of 2D views in a SolidWorks drawing. Set to 0 so that no border is drawn.	0

Copyright © 1999, 2012, Oracle and/or its affiliates. All rights reserved.

Portions of this software Copyright 1996-2007 Glyph & Cog, LLC.

Portions of this software Copyright Unisearch Ltd, Australia.

Portions of this software are owned by Siemens PLM © 1986-2012. All rights reserved.

This software uses ACIS® software by Spatial Technology Inc. ACIS® Copyright © 1994-2008 Spatial Technology Inc. All rights reserved.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS

Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy and other measures to ensure the safe use of this software. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software in dangerous applications.

This software and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third party content, products and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third party content, products or services.