

Name start-local-instance – starts a GlassFish Server instance on the machine where the subcommand is run

Synopsis start-local-instance [--help]
 [--nodedir *node-dir*] [--node *node*]
 [--debug={false|true}] [--sync={normal|full|none}]
 [--upgrade={false|true}] [--verbose={false|true}]
 [*instance-name*]

Description The start-local-instance subcommand starts a GlassFish Server instance on the machine where the subcommand is run. This subcommand does not require secure shell (SSH) to be configured. You must run this command from the machine where the instance resides.

The subcommand can start any GlassFish Server instance, regardless of how the instance was created. For example, this subcommand can start an instance that was created by using the create-instance(1) subcommand.

The start-local-instance subcommand does not contact the domain administration server (DAS) to determine the node on which the instance resides. To determine the node on which the instance resides, the subcommand searches the directory that contains the node directories. If multiple node directories exist, the node must be specified as an option of the subcommand.

This command is supported in remote mode only.

Options --help
 -?
 Displays the help text for the subcommand.

--nodedir
 Specifies the directory that contains the instance's node directory. The instance's files are stored in the instance's node directory. The default is *as-install/nodes*.

--node
 Specifies the node on which the instance resides. This option may be omitted only if the directory that the --nodedir option specifies contains only one node directory. Otherwise, this option is required.

--debug
 Specifies whether the instance is started with [Java Platform Debugger Architecture \(JPDA\)](#) debugging enabled.

Possible values are as follows:

true
 The instance is started with JPDA debugging enabled and the port number for JPDA debugging is displayed.

false
 The instance is started with JPDA debugging disabled (default).

--sync

The type of synchronization between the DAS and the instance's files when the instance is started.

Possible values are as follows:

none

The DAS does not synchronize the instance's files with any changes. This type of synchronization minimizes the time that is required to start the instance.

normal

The DAS synchronizes the instance only with changes since the last synchronization to the following files:

- All changes in the `config` directory
- Changes to files only in the top level of the `applications` directory and the `docroot` directory

If a file below this level is changed, full synchronization is required. In normal operation, files below the top level of these directories are not changed. If an application is deployed and undeployed, full synchronization is not necessary to update the instance with the change.

This value is the default.

full

The DAS synchronizes the instance with all changes since the last synchronization. This type of synchronization might delay the startup of the instance while the DAS updates all files in the instance's directories.

--upgrade

Specifies whether the configuration of the instance is upgraded to the current release. Normally, if the subcommand detects that the configuration is from an older release of GlassFish Server, the configuration is upgraded automatically before being started. You should not need to use this option explicitly.

Possible values are as follows:

true

When the instance is started, the configuration is modified to be compatible with this release of GlassFish Server, and the GlassFish Server process stops.

false

The configuration of the instance is not updated (default).

--verbose**-v**

Specifies whether detailed information is displayed while the instance is being started.

Possible values are as follows:

