

---

# PeopleSoft 9.1 PeopleBook: Data Transformer

---

**April 2012**

Copyright © 1988, 2012, Oracle and/or its affiliates. All rights reserved.

### **Trademark Notice**

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

### **License Restrictions Warranty/Consequential Damages Disclaimer**

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

### **Warranty Disclaimer**

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

### **Restricted Rights Notice**

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

### **Hazardous Applications Notice**

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

### **Third Party Content, Products, and Services Disclaimer**

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

# Contents

## Preface

<b>PeopleSoft Data Transformer Preface .....</b>	<b>vii</b>
PeopleSoft Data Transformer .....	vii
PeopleBooks and the PeopleSoft Online Library .....	vii

## Chapter 1

<b>Getting Started with PeopleSoft Data Transformer .....</b>	<b>1</b>
PeopleSoft Data Transformer Overview .....	1
PeopleSoft Data Transformer Business Processes .....	1
PeopleSoft Data Transformer Implementation .....	2
Setting Up Core PeopleSoft Data Transformer Features .....	2
Creating Source Data Objects .....	2

## Chapter 2

<b>Setting Up Core PeopleSoft Data Transformer Features .....</b>	<b>3</b>
Defining Remote Database Connections .....	3
Understanding Remote Database Connections .....	3
High-Level Steps for Setting Up Data Transformation .....	4
Page Used to Define Remote Database Connections .....	8
Defining Remote Database Connections .....	8
Defining Installation Options .....	10
Page Used to Define Installation Options .....	11
Defining Installation Options .....	11
Defining Subject Areas .....	12
Understanding Subject Areas .....	12
Page Used to Define Subject Areas .....	13
Defining Subject Areas .....	13

## Chapter 3

<b>Creating Source Data Objects .....</b>	<b>15</b>
-------------------------------------------	-----------

Understanding Source Data Objects .....	15
Common Elements Used to Create Source Data Objects .....	15
Creating Basic Source Data Objects .....	15
Pages Used to Create Basic Source Data Objects .....	16
Defining Source Data Objects .....	16
Specifying Source Data Object Fields .....	18
Previewing Results .....	19
Previewing SQL .....	19
(Optional) Creating Expressions .....	20
Understanding Expressions .....	20
Page Used to Create Expressions .....	23
Creating Expression Statements .....	23
(Optional) Creating Filters .....	27
Understanding Filters .....	27
Page Used to Create Filters .....	28
Creating Filters .....	28
(Optional) Joining Records .....	29
Understanding Joins .....	29
Page Used to Join Records .....	29
Defining Join Conditions .....	29

## Chapter 4

<b>Preparing to Create Maps .....</b>	<b>31</b>
Understanding the Mapping Process .....	31
Target Field Default Value Setup .....	31
Translation Set Setup .....	33
Transformation Creation .....	33
Map Rule Setup .....	33
Setting Up Target Field Default Values .....	33
Page Used to Set Up Target Field Default Values .....	34
Setting Up Target Field Default Values .....	34
Setting Up Translation Sets .....	35
Page Used to Set Up Translation Sets .....	35
Setting Up Translation Sets .....	35
Creating Transformations by Using the Transformation Wizard .....	36
Understanding the Transformation Wizard .....	37
Common Element Used in This Section .....	37
Pages Used to Navigate Transformation Wizard .....	38
Creating Transformation Definitions .....	39
Defining Look Ups .....	40
Creating Message Definitions .....	41
Entering Comments .....	42

(Optional) Setting Up Source Conditions .....	43
(Optional) Defining Lookup Conditions .....	43
Using Transformation PeopleCode .....	44
Creating Map Rules .....	46
Understanding Map Rules .....	46
Page Used to Create Map Rules .....	46
Defining Map Rules .....	47

## Chapter 5

<b>Creating Maps .....</b>	<b>49</b>
Creating Map Definitions .....	49
Pages Used to Create Map Definitions .....	49
Defining Map Information .....	50
Defining Map Field Details .....	51
Performing Map Edits .....	54
Previewing Map Results .....	54
Updating Map Processing Options .....	55
Entering Map Definition Comments .....	57

## Chapter 6

<b>Running the Data Transformation Process and Correcting Errors .....</b>	<b>59</b>
Defining Map Groups and Map Group Chunking Criteria .....	59
Pages Used to Define Map Groups and Chunking Criteria .....	59
Defining Map Groups .....	60
Defining Chunking Criteria .....	61
Extracting, Transforming, and Loading Source Data .....	62
Understanding Extracting, Transforming, and Loading Source Data .....	62
Pages Used to Extract, Transform, and Load Source Data .....	62
Running the Data Transformation Process .....	62
Viewing the Run Summary .....	64
Handling Data Transformation Process Errors .....	66
Understanding Data Transformation Process Errors .....	67
Page Used to Handle Data Transformation Process Errors .....	67
Viewing and Correcting Data Transformer Process Errors .....	68

## Appendix A

<b>Setting PeopleSoft Data Transformer Security .....</b>	<b>69</b>
Understanding Security .....	69

User Profiles, Roles, and Permission Lists ..... 69

Delivered Roles and Permission Lists ..... 70

Implementing Security ..... 71

    Understanding Security Tasks ..... 72

    Associating the EOEW1000 Permission List with a Role ..... 72

    Assigning the Map Specialist Role to a User Profile ..... 72

**Index ..... 73**

# PeopleSoft Data Transformer Preface

This preface discusses PeopleSoft Data Transformer.

---

## PeopleSoft Data Transformer

PeopleSoft Data Transformer enables you to extract, transform, and load data from remote or local data sources to a data source of your choice. PeopleSoft Data Transformer handles high volume data transfers and transformation processing and is configured to provide maximum performance between PeopleSoft applications.

Some of the page elements and colors that your product uses may differ slightly from the screen shots presented in this PeopleBook. This book uses a generic style sheet for the purposes of illustration only.

---

## PeopleBooks and the PeopleSoft Online Library

A companion PeopleBook called *PeopleBooks and the PeopleSoft Online Library* contains general information, including:

- Understanding the PeopleSoft online library and related documentation.
- How to send PeopleSoft documentation comments and suggestions to Oracle.
- How to access hosted PeopleBooks, downloadable HTML PeopleBooks, and downloadable PDF PeopleBooks as well as documentation updates.
- Understanding PeopleBook structure.
- Typographical conventions and visual cues used in PeopleBooks.
- ISO country codes and currency codes.
- PeopleBooks that are common across multiple applications.
- Common elements used in PeopleBooks.
- Navigating the PeopleBooks interface and searching the PeopleSoft online library.
- Displaying and printing screen shots and graphics in PeopleBooks.
- How to manage the locally installed PeopleSoft online library, including web site folders.
- Understanding documentation integration and how to integrate customized documentation into the library.
- Application abbreviations found in application fields.

You can find *PeopleBooks and the PeopleSoft Online Library* in the online PeopleBooks Library for your PeopleTools release.





## Chapter 1

# Getting Started with PeopleSoft Data Transformer

This chapter provides an overview of PeopleSoft Data Transformer and discusses:

- PeopleSoft Data Transformer business processes.
- PeopleSoft Data Transformer implementation.

---

## PeopleSoft Data Transformer Overview


PeopleSoft Data Transformer enables organizations to extract, transform, and load data from remote or local data sources to a target data source. Tasks that you perform in PeopleSoft Data Transformer, to prepare the data for transfer, include:

- Setting up default target fields.
- Defining transformation and filtering rules to convert data.
- Creating map rules.
- Creating map definitions.

---

## PeopleSoft Data Transformer Business Processes

The following process flow illustrates the PeopleSoft Data Transformer business processes:



PeopleSoft Data Transformer business process flow

## PeopleSoft Data Transformer Implementation

The PeopleSoft Data Transformer implementation can be divided into two phases:

- Setting up core PeopleSoft Data Transformer features.
- Creating source data objects.

Complete these phases to support PeopleSoft Data Transformer features.

In the planning phase of your implementation, take advantage of all PeopleSoft sources of implementation, including the installation guides and business process maps.

### Setting Up Core PeopleSoft Data Transformer Features

To set up core PeopleSoft Data Transformer features, perform the following steps:

<b>Step</b>	<b>Reference</b>
Define remote database connections.	See <a href="#">Chapter 2, "Setting Up Core PeopleSoft Data Transformer Features," Defining Remote Database Connections, page 3.</a>
Define installation options.	See <a href="#">Chapter 2, "Setting Up Core PeopleSoft Data Transformer Features," Defining Installation Options, page 10.</a>
Define subject areas.	See <a href="#">Chapter 2, "Setting Up Core PeopleSoft Data Transformer Features," Defining Subject Areas, page 12.</a>

### Creating Source Data Objects

To set up source data objects, perform the following steps:

<b>Step</b>	<b>Reference</b>
Create basic source data objects.	See <a href="#">Chapter 3, "Creating Source Data Objects," Creating Basic Source Data Objects, page 15.</a>
(Optional) Create expressions.	See <a href="#">Chapter 3, "Creating Source Data Objects," (Optional) Creating Expressions, page 20.</a>
(Optional) Create filters.	See <a href="#">Chapter 3, "Creating Source Data Objects," (Optional) Creating Filters, page 27.</a>
(Optional) Join records.	See <a href="#">Chapter 3, "Creating Source Data Objects," (Optional) Joining Records, page 29.</a>

## Chapter 2

# Setting Up Core PeopleSoft Data Transformer Features

This chapter discusses how to:

- Define remote database connections.
- Define installation options.
- Define subject areas.

---

**Note.** These activities are typically one-time events and require minimal maintenance.

---

---

## Defining Remote Database Connections

This section provides an overview of remote database connections and discusses how to define remote database connections.

## Understanding Remote Database Connections

Data sources represent the location of the source data that is extracted, transformed, and loaded to the target. Remote data source data is extracted from a separate (remote) database and migrated into the local database. You must define remote database connections to source data from a database other than your local PeopleSoft database instance.

The Remote Database Access Management page enables you to define connectivity information for relational databases to be used for sourcing data for PeopleSoft Data Transformer. You can define connectivity information only for databases of the same type as the Target PeopleSoft database instance. For example, if the PeopleSoft database instance is Oracle, then you can define only Oracle remote connections. Remote database connections are established once for a local connect and once for each database that will be sourced. You must define one local connection for the current PeopleSoft instance. This connection is used during remote database access to retrieve information for the target database.

---

**Note.** If you are accessing data from a local database, then you do not need to set up remote database connections.

---

## High-Level Steps for Setting Up Data Transformation

Here is a recommended procedure for setting up data transformation in an environment (be sure to replace the sample information used in this procedure with your environment and database information):

1. Install JDBC driver for the test database.

For SQL Server, download the appropriate JDBC driver version from the Microsoft Download Center. After the installation, three jar files are created under the JDBC driver library directory, for example, *C:\Program Files\Microsoft SQL Server 2000 Driver for JDBC\lib*. To make these files accessible to the application server, either copy them to *<ps\_home>\class*, or add them to the CLASSPATH line in the *psappsrv.cfg* file (application server configuration file), for example:

```
CLASSPATH=C:\Program Files\Microsoft SQL Server 2000 Driver for JDBC\lib\msbase.jar;C:\Program Files\Microsoft SQL Server 2000 Driver for JDBC\lib\mssqlserver.jar;C:\Program Files\Microsoft SQL Server 2000 Driver for JDBC\lib\msutil.jar
```

2. Set up a local database connection (for example, H881C338).

In PIA, navigate to Enterprise Components, Data Transformation, Setup Remote Database Connection, Remote Database Access Management. Add a local database connection with sample information as follows:

Name: *H881C338*

Local Connect: Selected

Description: *H881C338*

Server: *ECHAN2091903*

User ID: *sa*

Password: *Peoples0*

Save the page and click the Test Connection button to verify that the connection information entered is correct. The *Good Connection* message appears if the information is correct.

3. Set up a remote database connection (for example, HC881TM1)

Navigate to Enterprise Components, Data Transformation, Setup Remote Database Connection, Remote Database Access Management. Add a remote database connection with sample information as follows:

Name: *HC881TM1*

Description: *HC881TM1*

Server: *ADDB0106*

User ID: *satst*

Password: *satst*

Save the page and click the Test Connection button to verify that the connection information entered is correct.

4. Set up data transformation installation options.

Navigate to Enterprise Components, Data Transformation, Data Transformation Installation Options. On the Data Transformation Installation Options page, enter the following sample information:

Maximum Rows to Preview: *10*

Tablespace Name: *EOECLRG*

Message Set Number: *18024*

Save the page.

5. Define subject area.

Navigate to Enterprise Components, Data Transformation, Setup Subject Areas. Add a subject area by entering the following sample information:

Subject Area: *NACNV*

Description/More Information: Enter some text

Default Subject Area: Selected

Create Temporary Table: Selected

Save the change.

6. Define source data object.

Navigate to Enterprise Components, Data Transformation, Define Source Data Objects, Source Data Object. Add a new source data object by entering the following sample information:

Source Data Object: *DEPARTMENT*

Subject Area: *NACNV*

Description: *Department*

Data Source Type: *Remote*

Data Source Name: *HC881TM1*

Source Record (left field): *PS\_DEPT\_TBL*

Source Record (right field): *Department Table*

Navigate to the Fields page and click the Synchronize fields button. Select these fields:

*SETID, DEPTID, EFFDT, EFF\_STATUS, DESCR, DESCRSHORT, and COMPANY*

Save the page.

7. Set default values for target fields.

Navigate to Enterprise Components, Data Transformation, Set Target Field Defaults. Add two target fields using the following sample information:

Target Field: *SETID*

Source Input Value: *SNSZZ*

Target Field: *DEPTID*

Source Input Value: *ABCDE*

Save the change.

8. Define map information.

Navigate to Enterprise Components, Data Transformation, Define Maps. Add a map object using the following sample information:

Map Object: *DEPT*

Subject Area: *NACNV*

Description: *Department ETL*

Source: *DEPARTMENT*

Target: *DEPT\_TBL*

Navigate to the Map Field Detail page and click the Apply AutoMapper button. Next, click the Source Input Type column heading twice to bring the rows with non-blank source input type to the top of the list. Change the source input type for the SETID and DEPTID target fields to *Default*. Change the source input type for the EFFDT target field to *Source* and select *EFFDT* as the source prompt because the Auto Field Mapper sets this to blank by default. Now there should be seven fields with non-blank source input types. Navigate to the Preview Map Results page and click the Preview button. Note that 10 rows of DEPT\_TBL in HC881TM are displayed with SETID and DEPTID showing the default values set up in step 7.

## 9. Test the data transformation setup.

When testing the Data Transformer ETL, note that:

- The 3 jar files in step 1 will need to be added to `psprcs.cfg` (process scheduler configuration file) if they were not copied into `<ps_home>\class`
- A successful run depends on what data exists in the source table and the target table, otherwise the job may end with a duplicate error.

To verify that the ETL can correctly access the remote table data, delete all the rows in my local `PS_DEPT_TBL`, set the seven fields in the map to use *Source* as source input type and run the ETL. To do so, navigate to Enterprise Components, Data Transformation, Run Data Transformations, Run Data Transformations. Add a run control using the following sample information:

Data Transformer Object Type: *Map*

Map Object: *DEPT*

Target Load Option: *Full Load*

Destructive Load: *Clear*

Parallel Processing: *Selected*

Click the Run button. Two processes are executed: *EOEW\_ETL\_EXE* and *EOEW\_ETL\_RUN*.

Note that as the two processes run to *Success*, in Query Analyzer, the `PS_DEPT_TBL` rowcount matches that in the source table.

---

**Note.** If the data transformation process is not loading data into target tables, the problem may originate from the `CLASSPATH`, which was defined in your system. Also, this behavior can be caused by the process scheduler if it doesn't have the right access to the JDBC drivers.

---

## Oracle Database Considerations

If you are using an Oracle database, you need to update the content of both `psappsrv.cfg` and `psprcs.cfg` to reflect your Oracle connectivity settings. Basically you should determine the Oracle home directory and specify it in both `psappsrv.cfg` and `psprcs.cfg` by adding the following two lines under the `;JavaVM Shared Library=` section:

; RDBA Oracle JDBC driver

Add to CLASSPATH=

Add to CLASSPATH=

PREPARE TO CONFIGURE ORACLE -

Before you can use remote data access with Oracle, the appropriate database connectivity software must be installed on the system where the application server or batch server is running. The minimum database connectivity that needs to be installed is the Oracle Client Net9i 9.2.0.2.0 Connectivity Package.

To connect to a remote Oracle database, you must manually edit the application server configuration file, `psappsrv.cfg`, as described below. If the batch server is being used, you must manually edit the batch server configuration file, `psprcs.cfg`, as well.

From the Remote Database Connection page (PeopleTools, Utilities, Administration, Remote Database Connection), you can specify an Oracle datasource as *specific* or with TNSNAMES. *Specific* doesn't require a TNSNAMES entry, and will use the Oracle "thin" JDBC driver. If TNSNAMES is configured for the remote database, you can use the TNSNAMES style entry.

#### CONFIGURING ORACLE 9i OR ORACLE 10g ON UNIX -

Determine the Oracle home directory and specify it in the configuration files by adding the following two lines under the *;JavaVM Shared Library=* section:

; RDBA Oracle JDBC driver

Add to CLASSPATH=%ORACLE\_HOME%\jdbc\lib\ojdbc14.jar

Add to CLASSPATH=%ORACLE\_HOME%\jdbc\lib\orai18n.jar

#### CONFIGURING ORACLE 9i OR ORACLE 10g on WINDOWS -

Determine the Oracle home directory and specify it in the configuration file. For example, if Oracle the home directory is *C:\Apps\DB\Oracle901*, add the following lines under the *;JavaVM Shared Library=* section:

; RDBA Oracle JDBC driver

Add to CLASSPATH=C:\Apps\DB\Oracle901\jdbc\lib\ojdbc14.jar

Add to CLASSPATH=C:\Apps\DB\Oracle901\jdbc\lib\orai18n.jar

## Page Used to Define Remote Database Connections

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Remote Database Access Management	REMOTEDB	Enterprise Components, Data Transformation, Setup Remote Database Connection, Remote Database Access Management	Define remote database connections.

## Defining Remote Database Connections

Access the Remote Database Access Management page (Enterprise Components, Data Transformation, Setup Remote Database Connection, Remote Database Access Management).



### Remote Database Access Management

Name:

REMOTE\_DATABASE\_01

DB Type:

Oracle

\*Connection

TNSNames

☐ Local Connect?

Type:

\*Description:

\*TNS Entry:

\*User ID:

\*Password:

Test Connection

Remote Database Access Management page

**Important!** Different fields may appear on the page based on the database DB type. The preceding page shows fields for *Microsoft, DB2 (OS/390), DB2/UNIX, and Sybase*.

This table illustrates the page variance by database type:

Database Type	Required Information
Microsoft, DB2 (OS/390), DB2/UNIX, and Sybase	Enter a description, server, database, userID, and password.
Informix	Enter a description, server, user ID, password, and Inf Svr (Informix Server) name.
Oracle	<div>For Oracle and a Connection Type of <i>TNSNames</i>, enter a description, TNS Entry, user ID and password.</div> <div><b>Note.</b> TNS Names is a preconfigured file (tnsnames.ora) with previously defined database connection information.</div> <div>Select a connection type of <i>Specific</i> if you want to set up a database that does not already have a TNS Entry defined, or when you don't want to use the TNS entry.</div>

Name

Displays the remote DB name entered on the Search page for your database.

<b>DB Type</b>	Displays the database type of your PeopleSoft database. <hr/> <b>Note.</b> Since your remote database must be of the same type, this field is defaulted to your current local database type. <hr/>
<b>Local Connect</b>	Select if you are defining the remote connection information for your local database. All others must be specified as remote databases. An error displays if you save a page with a connection checked as a Local Connect and there is already one identified as such (in the PSREMOTEDBDEFN table). <hr/> <b>Important!</b> One connection must be defined as the Local Connect, the connection information for the current PeopleSoft instance (the local database). This connection is used during remote database access to retrieve connection information for the source and as the target database for the sourced data. <hr/>
<b>Server</b>	Enter the name of the server where the database resides. <hr/> <b>Note.</b> This field is platform specific. <hr/>
<b>DB Server Port</b>	The DB Server Port number is automatically populated with a default value based on the database type. It may need to be changed depending upon your database server configuration.
<b>User ID and Password</b>	Enter the user ID and password that are required to access the database. The password is not displayed. <hr/> <b>Note.</b> This field is platform specific. <hr/>
<b>Test Connect</b>	Click to access the remote database by using the information that you have entered. This will verify that all of the connection information is correct.

**See Also***PeopleSoft Hardware and Software Guide*

---

## Defining Installation Options

This section discusses how to define installation options.

## Page Used to Define Installation Options

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Data Transformation Installation Options	EOEW_OPTIONS	Enterprise Components, Data Transformation, Data Transformation Installation Options	Define installation options.

## Defining Installation Options

Access the Data Transformation Installation Options page (Enterprise Components, Data Transformation, Data Transformation Installation Options).

Data Transformation Installation Options page

System administrators may use PeopleSoft Data Transformers' installation options to set certain high-level Data Transformer defaults such as the maximum number of rows to return on a preview of sourced or transformed data, a table space name to be used to dynamically build temporary tables, and the default message set number assignment for transformation error correction.

**Maximum Rows to Preview** Enter the maximum number of rows of sourced or transformed data to preview.

Keep this value relatively low, for example 100 rows, as larger values significantly increase the amount of time it takes to retrieve data and render the preview pages.

<b>Tablespace Name</b>	Enter the tablespace name for the temporary table that is built dynamically at runtime. This tablespace name is applied to all of the temporary tables unless overridden at a lower level.
	<b>Note.</b> This name can be overridden at the subject area and map option levels.
<b>Create Temporary Table</b>	Select to create temporary tables dynamically.  A temporary table is created at runtime—it's needed by the engine during processing only, then it's deleted at completion. It is not available in PeopleSoft metadata. If the check box is cleared, you must specify a temporary table record name on the map for use at runtime. This temporary table will be available in PeopleSoft metadata and remain after the engine processing.
	<b>Note.</b> Determining which of these options to use needs to be considered carefully. A dynamic temporary table will automatically change when the map changes, conversely, a non-dynamic temporary table will not change and may require more maintenance.
<b>Message Set Number</b>	Select a message set number that corresponds to a text error message set. When adding a new transformation and associating a specific error message with an error, this default message set number is used as a starting point.

**See Also**

[Chapter 5, "Creating Maps," Previewing Map Results, page 54](#)

[Chapter 5, "Creating Maps," Updating Map Processing Options, page 55](#)

[Chapter 4, "Preparing to Create Maps," Creating Message Definitions, page 41](#)

---

## Defining Subject Areas

This section provides an overview of subject areas and discusses how to define subject areas.

## Understanding Subject Areas

Use subject areas as a grouping mechanism on translation sets, transformations, map rules and map definitions. These objects can only be shared within a subject area. An enterprise subject area can be used for objects that are to be shared by all subject areas.

You need to carefully plan subject areas when you implement PeopleSoft Data Transformer. For example, you need to consider how the Data Transformer objects (translation sets, transformations, map rules, map definitions, and so on) can be grouped most efficiently. Some objects need to be available to all users, while some only to a specific user or functional group.

---

**Note.** Subject areas affect only prompting and object selection and do not reflect object security.

---

You can set up default tablespaces, or you can dynamically create temporary tables by subject area. If an implementation requires that only groups of maps dynamically generate temporary tables, or are built within different tablespaces, you can specify this at the subject area level.

### See Also

Chapter 4, "Preparing to Create Maps," page 31

## Page Used to Define Subject Areas

Page Name	Definition Name	Navigation	Usage
Subject Areas	EOEW_OBJ_OWNER	Enterprise Components, Data Transformation, Setup Subject Areas	Define subject areas to group translation sets, transformations, map rules, and map definitions.

## Defining Subject Areas

Access the Subject Areas page (Enterprise Components, Data Transformation, Setup Subject Areas).


### Subject Areas

Subject Area is used as a grouping mechanism on translation sets, transformations, map rules and map definitions.

**Subject Area:** TEST

**\*Description:**  ☐ Default Subject Area

**\*More Information:**

**Tablespace Name:**  

☒ Create Temporary Table

Select to dynamically create the temporary table associated with a map definition.  
Unselect to specify the table manually.

Subject Areas page

<b>Default Subject Area</b>	Select to use this subject area as your default subject area.
<b>Tablespace Name</b>	<p>Select the tablespace name to use if you want to override the Data Transformation installation options selection for this subject area.</p> <hr/> <p><b>Note.</b> This is needed only when an implementation shares dynamically generated temporary tables over multiple tablespaces.</p> <p>For example, the CEW EO temporary tables may be assigned to a special tablespace because the table size in this area is expected to be larger than other tables. For that subject area, an override tablespace name would be entered. The CEW CM subject area contains unique tables that also need special segmentation. For that subject area, an override tablespace name would be entered. All other subject areas would have a blank tablespace name therefore defaulting to the Data Transformation installation options tablespace name.</p> <hr/>
<b>Create Temporary Table</b>	<p>Select if you want to override the Data Transformation installation options selection for this subject area.</p> <p>This is needed only when an implementation allows or disallows the dynamic temporary table creation per subject area.</p>

## Chapter 3

# Creating Source Data Objects

This chapter provides an overview of source data objects and discusses how to:

- Create basic source data objects.
- Create expressions.
- Create filters.
- Join records.

---

## Understanding Source Data Objects

A source data object is the input to every map definition and defines the data to be extracted from the source. The business requirement of the map definition dictates the appropriate structure of the source data object, which can be as basic as requiring only an object definition and the fields to be used in the extract SQL specified, or quite complex containing expressions, multiple table joins, and filtering criteria.

## Common Elements Used to Create Source Data Objects

<b>Data Source</b>	One or more record definitions joined by common fields.
<b>Source Data Object</b>	<p>Enter a unique value of up to 30 characters, with no spaces or special characters. The system automatically converts the value to uppercase.</p> <p>This value, along with the description from the definition page, appears at the top of each page of the Source Data Object component.</p>

---

## Creating Basic Source Data Objects

This section discusses how to:

- Define source data objects.
- Specify source data object fields.
- Preview results.

- Preview SQL.

---

**Note.** All remote source databases must be of the same database type as the local PeopleSoft database instance. For example, if your PeopleSoft application is running on DB2/UNIX then you may only define DB2/UNIX source databases.

---

## Pages Used to Create Basic Source Data Objects

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Source Data Object	EOEW_SRCDO	Enterprise Components, Data Transformation, Define Source Data Objects, Source Data Object	Create source data object definitions.
Fields	EOEW_SRCFIELD	Enterprise Components, Data Transformation, Define Source Data Objects, Source Data Object, Fields	Specify the fields to include in the source data object.
Preview	EOEW_SRCPREVIEW	Enterprise Components, Data Transformation, Define Source Data Objects, Source Data Object, Preview	Review the results and check the validity of the source data object.
View Query	EOEW_SRCQUERY	Enterprise Components, Data Transformation, Define Source Data Objects, Source Data Object, View Query	Generate and view the SQL based on the source data object definition.

## Defining Source Data Objects

Access the Source Data Object page (Enterprise Components, Data Transformation, Define Source Data Objects, Source Data Object).



The screenshot shows the 'Source Data Object' configuration interface. At the top, there are tabs for 'Source Data Object', 'Fields', 'Expressions', 'Filters', 'Preview', and 'View Query'. The 'Source Data Object' tab is selected. Below the tabs, the title 'Source Data Object' is displayed. To the right of the title is a 'Save as' button. The main form area contains several fields: 'Source Data Object' with the value 'SOURCE\_DATA\_OBJECT\_01', 'Subject Area' with an empty text box and a search icon, '\*Description' with an empty text box, and 'Data Source' with a '\*Data Source Type' dropdown menu set to 'Local'. Below the 'Data Source' section is the 'Source Record' section, which includes a search bar, a list of records (currently empty), and navigation controls like 'Find', 'View All', 'First', '1 of 1', and 'Last'.

Source Data Object page

**Subject Area**

Select a subject area.

For new source data objects, the subject area will be set to the default as defined on the Subject Area page.

**Data Source Type**

*Local:* Select to use PeopleSoft-defined records from the current database.

*Remote:* Select to access the remote database connection information and use records from a remote database. Select the desired data source for remote.

---

**Note.** The Data Source Type can only be selected in Add mode. If you want to change this value, you will need to create a new Source Data Object.

---

**Source Record**

Select the source records from which to extract data. This record is placed in the From clause in the extract SQL.

If multiple records are selected, join conditions are required.

---

**Note.** To change a record that is associated with a source data object, you must delete the existing record and then add the new record.

---

**Save As**

Click to save an existing source data object under a new name.


Use this function to create a new source data object that will only slightly differ from the original object. Once saved, you can make the necessary changes to the new object. The new object is maintained separately.

See Also

Chapter 2, "Setting Up Core PeopleSoft Data Transformer Features," Defining Subject Areas, page 12

Specifying Source Data Object Fields

Access the Fields page (Enterprise Components, Data Transformation, Define Source Data Objects, Source Data Object, Fields).



Fields page

The source field information is populated from the source records that you selected on the Source Data Object page. The selected fields become the select list in the extract SQL.

Source Field Name	Select the fields to include in the source data object. <div><b>Note.</b> At least one field must be selected. Use the Select All and Deselect all icons to make the field selection more efficient.</div>
Field Alias	Change the field alias of any of the selected field names, if needed. <div>The field alias is displayed when defining the map, so descriptive names are important.<div><b>Note.</b> All fields in the source data object must have an alias, and each alias must be unique within the source data object.</div></div>

**Synchronize Fields** Click to synchronize fields with the database record. It is possible over the life span of a source data object that customizations are made. If a field is added or removed from the physical table, the field list must be synchronized.

**Select All** Click to select all of the fields that are listed.

**Clear All** Click to clear all field selections.

### **See Also**

[Chapter 5, "Creating Maps," Creating Map Definitions, page 49](#)

## **Previewing Results**

Access the Preview page (Enterprise Components, Data Transformation, Define Source Data Objects, Source Data Object, Preview).

Click the Preview button to view a subset of the source data object based on the record and fields that are selected.

Use this feature to check the validity of the defined source data object. It is especially helpful in determining if your expressions are defined correctly.

---

**Note.** Attempting to preview complex data sources can quickly consume processing and memory resources on your application server.

The preview maximum row count is set using the Data Transformer Installation Options page. Large row counts take more time and resources to preview. Consider setting your preview row count relatively low.

If no data is returned, verify the SQL that it being used to extract the data is accurate.

---

### **See Also**

[Chapter 2, "Setting Up Core PeopleSoft Data Transformer Features," Defining Installation Options, page 10](#)

## **Previewing SQL**

Access the View Query page (Enterprise Components, Data Transformation, Define Source Data Objects, Source Data Object, View Query).

Click the Generate SQL button to generate SQL text in the Query text box.

Use this to preview the SQL generated by the defined source data object.

---

**Note.** The administrator can verify if the extract SQL is correct and adjust the source data object definition as necessary.

---

## (Optional) Creating Expressions

This section provides an overview of expressions and discusses how to create expression statements.

### Understanding Expressions

Expressions enable you to create virtual columns that are made up of mathematical calculations based on actual fields in a record. Expressions are resolved at runtime so that duplicate information is not stored in the database. Expressions can be numeric, string, date, time, or datetime. Numeric expressions can combine any number of fields, constant values, and math operators, and results are rounded based on the decimal position that is selected. String expressions can be concatenations of any number of character fields and constant values.

#### ***Built-in Functions***

PeopleSoft delivers built-in functions that you can use to make expressions powerful and flexible. You can also nest built-in functions and expressions; for example:

- Concatenate two fields, separate them with a comma, drop trailing blanks, and limit this field to 40 characters:

```
Substring(RTRIM(FirstName) | , | RTRIM(LastName),1,40)
```

- Sum the multiplication of two fields:

```
SUM(PROD_COST * PROD_RATE)
```

This table lists all of the delivered built-in functions with supported meta-SQL and aggregate functions:

<b><i>Function</i></b>	<b><i>Explanation</i></b>	<b><i>Use</i></b>
ABS(Number)	Returns the absolute value of the specified number.	ABS(-5) returns 5.
AddMonth(Date, Number)	Adds a number of months to the specified date and returns the calculated date.	AddMonth("2002-01-10",2) returns 2002-03-10.
Average(Number)	Returns the average value of the specified number (typically a numeric column name).	Average(PRICE) returns the average price of your source data set.
Beginning of Month(Date)	Returns a date representing the first day of the month for the specified date.	Beginning of Month("2002-10-05") returns 2002-10-01.

<b>Function</b>	<b>Explanation</b>	<b>Use</b>
Beginning of Year(Date)	Returns a date representing the first day of the year for the specified date.	Beginning of Month("2002-10-05") returns 2002-01-01.
Count(col)	Returns the number of rows that are found.	Count(PRODUCT_ID) returns the number of rows on your source data set.
DateAdd(Date, Days)	Adds a number of days to the specified date and returns the calculated date.	DateAdd("2002-02-02",5) returns 2002-02-07.
DateDiff(Date, Date)	Returns the number of days that have elapsed between the first and second specified dates.	DateDiff("2002-02-02","2002-02-10") returns 8.
DtTmDiff(Datetime,Datetime)	Returns the number of minutes that have elapsed between the first and second specified datetimes.	DtTmDiff("'2002-01-01 00:00:00.000","2002-01-01 10:00:00.000") returns 600 (10 hours in minutes).
DIFF_H(Datetime, Datetime)	Returns the number of hours that have elapsed between the first and second specified datetimes.	DIFF_H("'2002-01-01 00:00:00.000","2002-01-01 10:00:00.000") returns 10.
DIFF_S (Datetime, Datetime)	Returns the number of seconds that have elapsed between the first and second specified datetimes.	DIFF_S("'2002-01-01 00:00:00.000","2002-01-01 10:00:00.000") returns 36000 (10 hours in seconds).
End of Month(Date)	Returns a date representing the last day of the month for the specified date.	End of Month("2002-10-05") returns 2002-10-31.
End of Year(Date)	Returns a date representing the last day of the year for the specified date.	End of Year("2002-10-05") returns 2002-12-31.
GetDay(Date)	Returns the day of the month for the specified date.	GetDay("2002-10-05") returns 5.
GetMonth(Date)	Returns the month of the specified date.	GetMonth("2002-10-05") returns 10.

<i><b>Function</b></i>	<i><b>Explanation</b></i>	<i><b>Use</b></i>
GetYear(Date)	Returns the year of the specified date.	GetYear("2002-10-05") returns 2002.
MOD(Number, Number)	Returns the modulus (or remainder) of the first number when it is divided by the second number.	MOD(14,3) returns 2 (14 divides into 3 four times with a remainder of 2).
Max(Number)	Returns the maximum value of the specified number (typically a numeric column name).	Max(PRICE) returns the largest price of your source data set.
Min (Number)	Returns the minimum value of the specified number (typically a numeric column name).	Min(PRICE) returns the smallest price of your source data set.
Sum(Number)	Returns the sum of the specified number (typically a numeric column name).	Sum(PRICE) returns the sum of all prices of your source data set.
RTRIM(String)	Returns the specified string, and trims trailing blank characters.	RTRIM("Hello ") returns Hello.
Round(Number, Factor)	Returns a number representing the specified number after being rounded to the given factor or precision.	Round(5.582, 1) returns 5.6. Round(5.512, 0) returns 6.
Substring(String, StartPos, Length)	Returns a section of the specified string starting at the specified position and continuing for the specified length.	Substring("My String Expression", 4,6) returns String.
TO_CHAR(Number)	Returns a string representation of the specified numeric expression.	TO_CHAR(59) returns 59.
TO_NUM(String)	Returns a numeric representation of the specified string expression.	TO_NUM("59") returns 59.  <b>Note.</b> Trying to apply a TO_NUM built-in function on a character that does not translate to a numeric value aborts the processing of your map.

<b>Function</b>	<b>Explanation</b>	<b>Use</b>
TrimSubStr(String, Start, Length)	Returns a section of the specified string starting at the specified position and continuing for the specified length, and trims trailing blank characters.	Substring("My String Expression", 4,7) returns String.
Truncate (Number, Factor)	Returns a number representing the specified number after being truncated to the given factor or precision.	Truncate(5.582, 1) returns 5.5. Truncate(5.512, 0) returns 5.
UPPER(String)	Returns the specified string in uppercase characters.	UPPER("My String Expression", 4,7) returns MY STRING EXPRESSION.
YYMMDD(Date)	Returns the string representation of a specified date in YYMMDD format.	YYMMDD("2002-10-01") returns 021001.

## Page Used to Create Expressions

<b>Page Name</b>	<b>Definition Name</b>	<b>Navigation</b>	<b>Usage</b>
Expressions	EOEW_SRCFIELDEXPR	Enterprise Components, Data Transformation, Define Source Data Objects, Source Data Object, Expressions	Create expression statements by selecting operators, fields, and constant values.

## Creating Expression Statements

Access the Expressions page (Enterprise Components, Data Transformation, Define Source Data Objects, Source Data Object, Expressions).

Source Data Object

Fields

Expressions

Filters

Preview

View Query

Source Data Object: SOURCE\_DATA\_OBJECT\_01

Expression Definition

Find | View All | First | 1 of 1 | Last

\*Name:

+ -

Details

\*Description:

\*Expression Field Type:

Char

Length:

0

Clear

Expression Statement:

Operators

( )

\* /

+ -

|

Data Source

☒ Data Object Column

☐ Built-In Function

☐ Constant Value

Data Object Column

Data Object Column:

Current Element

<< <

> >>

Replace

Insert

Delete

Expressions page

<b>Name</b>	Enter a unique name for this expression.
<b>Expression Field Type</b>	<p>Select to control the set of operators, record fields, and value objects that can be selected when building the expression.</p> <p><i>Numeric:</i> Select to combine any number of record fields, value objects, and math operators.</p> <p><i>String:</i> Select to concatenate any number of character record fields and value objects.</p> <p><i>Date:</i> Select to define a constant value or to create a date field from the source data object or built-in functions.</p>
<b>Expression Statement</b>	<p>Displays your expression as you build it. You cannot type directly into this edit box. Use operators, data source options, and the constant values to create your expressions.</p> <p>You can see what element is being specified by the arrows surrounding it; the selection is also displayed in the Current Element group box.</p>
<b>Clear</b>	Click to delete all entries in the Expression Statement edit box.
<b>Operators</b>	Select from the operator buttons to add operators to the expression.



## Data Source

### Data Object Column

Select this option to display a list of data object fields. Select a field and click Insert to have the selected data object appear in the expression statement.

### Built-in Function

Select this option to display a list of built-in functions. Select a function and click Insert to have the selected built-in function appear in the expression statement.

Built-in functions let you define numeric calculations like Sum, Average, or End of Month, and Minimum/Maximum values.

---

**Note.** All parameters of the selected built-in function must be defined.

---

### Constant Value

Select this option to enter your own character, numeric, or date value. Click Insert to have the value appear in the expression statement.

---

**Note.** Consider how an expression will be used when you want to specify date related value objects. If the expression will be in a WHERE clause, then use the %CurrentDateIn value object. If the expression will be in a SELECT clause, then use the %CurrentDateOut value object.

---

## Current Element



Click to move through the expression statement and identify the text you want to replace or delete or to move to the position in the statement where you want to insert text.

Click the Previous or Next button to move one element forward or backward. Click the First or Last button to move to the beginning or end of the expression statement.

---

**Note.** The element name will be shown in the Current Element group box as well as surrounded by arrows in the Expression Statement edit box.

---

### Replace

Click to replace the current element item in the expression statement with the selected data source.

### Insert

Click to insert the selected data source into the expression statement before the current element item.

### Delete

Click to delete the current element item in the expression statement.

## Example: Creating Expressions by Using Data Object Column

This section provides an example of creating an expression by using a data object column.

The company wants to award its employees with a bonus of \$1000 for each year that they have been employed by the company. To calculate the bonus:

1. Enter *BONUS* for the expression name, and then enter a description.
2. Select the *Number* expression type.
3. Select integer and decimal positions.
4. Select Data Object Column in the Data Source group box.
5. Select the *YEARS\_OF\_EMP* data object column, and click Insert.

The field appears in the Expression Statement edit box.

6. Click the Multiplication (\*) operator to insert it at the end of the expression statement.
7. Select Constant Value in the Data Source group box.
8. Enter a numeric value of *1000*, and click Insert.

This creates the following expression statement:

*YEARS\_OF\_EMP* \* 1000

9. Click Save.

### **Example: Creating Expressions Using Built-in Functions**

This section provides an example of creating an expression by using a built-in function.

You want to define a field called *SHORT\_DESCR* that uses the first 10 characters of the *DESCR* field.

To define the *SHORT\_DESCR* field:

1. Enter *SHORT\_DESCR* for the expression name, and then enter a description.
2. Select the *Char* expression type.
3. Enter the length.
4. Select Built-in Function in the Data Source group box.
5. Select the *Substring (String,Start,Length)* built-in function, and click Insert.

The function appears as *SUBSTRING ( PARAM1 , PARAM2 , PARAM3 )* in the Expression Statement edit box.

6. Use the arrow buttons to navigate through the expression statement and identify the *PARAM1* element.
7. Select Data Object Column in the Data Source group box.
8. Select *DESCR*, and click Replace.

The *DESCR* field appears in place of *PARAM1* in the expression statement.

9. Navigate to *PARAM2*.
10. Select Constant Value in the Data Source group box, and enter a numeric value of *1*.

11. Click Replace.
12. Navigate to *PARAM3*, and replace it with a numeric value of *10*.

This creates the following expression statement:

```
SUBSTRING ( DESCR , 1 , 10 )
```

13. Click Save.

---

## (Optional) Creating Filters

This section provides an overview of filters and discusses how to create filters.

### Understanding Filters

Filters serves as criteria that the system applies to each row of data in the data source. If the row passes the criteria, the system uses the data as an input to the data transformer map; if the row doesn't pass, the system doesn't use the data. A filter compares the value in one of the row's fields to a reference value. For example, suppose that you need only products whose selling price is greater than \$10.00. You would compare the value in the Price field to the constant value of \$10.00. The filter criteria is placed in the WHERE clause in the extract SQL.

The following table describes the operators that you can use to compare values:

Operator	Description
Like	<p>The value in the selected field matches a specified string pattern. The comparison value may be a string that contains wild card characters. The wild card characters that PeopleSoft Data Transformer recognizes are percent (%) and underscore (_).</p> <p>The % matches any string of zero or more characters. For example, <i>C%</i> matches any string starting with <i>C</i>, including <i>C</i> alone.</p> <p>The _ matches any single character. For example, <i>_ones</i> matches any 5-character string ending with <i>ones</i>, such as <i>Jones</i> or <i>bones</i>.</p> <p><b>Note.</b> To use one of the wild card characters as a literal character, (that is, to include % in your string), precede the character with a backslash (\). For example, <i>percent\%</i>.</p>
=	The value in the selected record field exactly matches the comparison value.
<>	The value in the selected record field is not equal to the comparison value.
>	The value in the record field is greater than the comparison value.
<=	The value in the record field is less than or equal to the comparison value.
<	The value in the record field is less than the comparison value.
>=	The value in the record field is greater than or equal to the comparison value.

When you include multiple filters, link them using AND or OR. When you link two filters with AND, a row must meet the first *and* second filter to pass the test. When you link with OR, a row must meet the first *or* second filter, but not necessarily both.

## Page Used to Create Filters

Page Name	Definition Name	Navigation	Usage
Filters	EOEW_SRCFILTER	Enterprise Components, Data Transformation, Define Source Data Objects, Source Data Object, Filters	Create filters.

## Creating Filters

Access the Filters page (Enterprise Components, Data Transformation, Define Source Data Objects, Source Data Object, Filters).

Filters page

To define a filter:

1. Select the record that you want to filter against from the list of records that are defined in the source data object.
2. Select the field on which to base your filter.
3. Select an operator.
4. Enter a comparison value.
5. Click Save.
6. Click Refresh Filter to save any changes that you made to existing filters and reflect those changes in the source data object. Refresh Filter also captures changes made for Save and updates drop-down lists to show your selections on the page.

---

**Note.** If the filter begins to get complicated, use the arrow keys to indent subconditions. Subconditions will be surrounded by parentheses and fully resolved before comparing results with other level results.

---

---

## (Optional) Joining Records

This section provides an overview of joins and discusses how to define join conditions.

### Understanding Joins

PeopleSoft Data Transformer enables you to create source data objects that include multiple-table joins. Joins retrieve data from more than one table, presenting the data as if it came from one table. PeopleSoft Data Transformer links the tables, based on common record fields, and links the rows on the two tables by common values in the shared record fields.

### Page Used to Join Records

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Join Conditions	EOEW_SRCJOIN	Enterprise Components, Data Transformation, Define Source Data Objects, Source Data Object, Join Conditions	Define join conditions.

### Defining Join Conditions

Access the Join Conditions page (Enterprise Components, Data Transformation, Define Source Data Objects, Source Data Object, Join Conditions).

---

**Note.** This page appears only when two or more records are defined in the source data object.

---

Enter the record name and associated field name for the left and right sides of the join.

The content of the field name drop-down list box is filtered to exclude some fields with data types that cannot be qualified (for example, image columns). You need to fully qualify the join criteria of the selected records; otherwise, processing may return unexpected results. The join criteria will become part of the **WHERE** clause in the extract SQL.



## Chapter 4

# Preparing to Create Maps

This chapter provides an overview of the mapping process and discusses how to:

- Set up target field default values.
- Set up translation sets.
- Create transformations by using the Transformation Wizard.
- Use transformation PeopleCode.
- Create map rules.

---

## Understanding the Mapping Process

Mapping translates values from the source data to the format of the target source by using default target values, transformations, translation sets, and map rules to facilitate the process.

This section discusses:

- Target field default value setup.
- Translation set setup.
- Transformation creation.
- Map rule setup.

## Target Field Default Value Setup

Target field default values allow you to set up values, which can be reused across multiple maps, to map to the target field. This allows having a central location for updating a target field value. For example, the target field default value for EFF\_STATUS is set to *A*, and is used in 100 maps. At runtime, *A* is inserted into the target field for all those maps. If the value for EFF\_STATUS is changed to *Active*, the value is updated once and when the 100 maps are run again, the new value will be inserted into the target field. No changes are necessary at the map level.

A default with no value is initialized to a blank, a zero, or the appropriate PeopleSoft null value.

When setting default values, consider the target field data type format:

- Character fields are used for names, codes, and letter values.

Uppercase converts the field value to uppercase and signifies that no other formatting options apply to the field. Mixed case stores uppercase and lowercase characters as entered.

- Number fields and signed number fields are fixed in field length and allow the entry of positive numbers.

Only signed numbers allow the entry of negative numbers.

- Date fields contain calendar dates.

A date field has a field length of 10 characters and is maintained by the system.

The default format of a date field is defined by the database and can be overridden by your browser settings.

The following table discusses data type format considerations:

<b>Source Field</b>	<b>Target Field</b>	<b>Required Considerations</b>	<b>User Warning</b>
Date	Date	NA	NA
Date	DateTime	NA	NA
Char	Char	Truncation occurs as needed.	NA
Char	Number	Data must be numeric in the character source field.	Appears when the character field is greater than the number in bytes.
Number	Number	NA	Appears when the numeric field is smaller in integer positions, decimals, or if the source is signed and the target is not.
Number	Char	Character must be big enough.	NA
DateTime	Date	NA	NA
DateTime	DateTime	NA	NA
Time	Time	NA	NA



<b>Source Field</b>	<b>Target Field</b>	<b>Required Considerations</b>	<b>User Warning</b>
Long	Long	NA	NA

---

**Note.** The default value assigned must match the target field format or an error occurs at runtime. For example, you cannot assign a value of 7A to a numeric field. Specific error messages display during the save if a datatype conversion error occurs.

---

## Translation Set Setup

Use translation sets to define equivalent values or a code set for data conversion. For example: *EA* equals *Each*, *GAL* equals *Gallon*, and *IN* equals *Inch*. Translation sets make the data values consistent.

## Transformation Creation

When data is copied from the source to the target, the data can be transformed by using edits, look ups, or PeopleCode. Transformations enable you to change a column's value. The Transformation Wizard guides you through the process of creating transformations.

## Map Rule Setup

You can create rules to be used by the AutoMapper feature in the map field detail definition where it attempts to match source fields with target fields. Use rules to assign correct default values to target fields when creating maps. By using map rules, you can assign a literal default, transformation, source field, or a translation set to a target field. If the map rule is required, you cannot override the rule when you define map field details.

### **See Also**

[Chapter 5, "Creating Maps," Defining Map Field Details, page 51](#)

---

## Setting Up Target Field Default Values

This section discusses how to set up target field default values.

Page Used to Set Up Target Field Default Values

Page Name	Definition Name	Navigation	Usage
Set Target Field Defaults	EOEW_SET_DFLT_RUL	<ul style="list-style-type: none"><li>Enterprise Components, Data Transformation, Setup Target Field Defaults, Set Target Field Defaults</li><li>Enterprise Components, Data Transformation, Data Transformation Home, Define Maps, Map Field Detail</li></ul> <p>Click the Default link on the Map Field Detail page.</p>	Set target field default values that are used in the map field detail definition.


Setting Up Target Field Default Values

Access the Set Target Field Defaults page (Enterprise Components, Data Transformation, Setup Target Field Defaults, Set Target Field Defaults).

### Set Target Field Defaults

Enter target field default value used in the Data Transformer map field detail definition. AutoMapper will populate the map field details with the field value based on the target field. If the default value is required, you will be unable to override the field value at the map level. A default with no value will be initialized to a blank, zero or the appropriate PeopleSoft null value.

Set Target Field Default Values

Customize | Find | View All |  | First | 1 of 1 | Last

	*Target Field	Source Input Value	Allow Map Override	
1	<input type="text"/>	<input type="text"/>	<input checked="" type="checkbox"/>	<div>+ -</div>

Set Target Field Default page

Target Field	Select the target field for which you want to define defaults.
Source Input Value	Enter the default value for the associated target field. <div><b>Note.</b> This field is free text, so you must consider the target field data type format.</div>
Allow Map Override	Select to allow the field value to be overridden at the map level, otherwise the row will be protected.

## Setting Up Translation Sets

This section discusses how to set up translation sets.

### Page Used to Set Up Translation Sets

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Translation Sets	EOEW_CODE_TBL	<ul style="list-style-type: none"> <li>Enterprise Components, Data Transformation, Setup Translation Set, Translation Sets</li> <li>Enterprise Components, Data Transformation, Define Maps, Map Field Detail</li> </ul> <p>Click the Translation link on the Map Field Detail page.</p> <ul style="list-style-type: none"> <li>Enterprise Components, Data Transformation, Define Maps, Map Field Detail</li> </ul> <p>Click the Add link on the Map Field Detail page.</p>	Enter translation set values for map definition details.

### Setting Up Translation Sets

Access the Translation Sets page (Enterprise Components, Data Transformation, Setup Translation Set, Translation Sets).

### Translation Sets

Enter translation set values for map definition details, used as equivalent values for data transformation.

Translation Set:

TRANSLATION\_SET\_01

\*Subject Area:

\*Description:

\*Undefined Value Options:

Retain undefined data values

Translation Set Values			Customize	Find	View All	First	1 of 1	Last
	*From Value	*To Value	More Information					
1								

Translation Sets page

- Subject Area

Select a subject area.  
  
For new translation sets, the subject area will be set to the default as defined on the Subject Area page.
- Undefined Value Options

Select how to handle undefined values:
  - Default for undefined values:* Rows that contain undefined source values have the defined default value inserted into the target field and then loaded in the target.
  - Do not load undefined values:* Rows that contain undefined source values have spaces inserted into the target field and then loaded in the target table.
  - Retain undefined data values:* Rows that contain undefined source values are retained and loaded in the target.

**Translation Set Values**

Enter the from and to values for each value that you want translated. If needed, enter the rationale for your selections in the More Information field.

**See Also**

[Chapter 2, "Setting Up Core PeopleSoft Data Transformer Features," Defining Subject Areas, page 12](#)

---

## Creating Transformations by Using the Transformation Wizard

This section provides an overview of the Transformation Wizard, lists common elements, and discuss how to:

- Create transformation definitions.
- Define edit, look ups or PeopleCode transformations.
- Create message definitions.
- (Optional) Set up source conditions.
- (Optional) Define look up conditions.

## Understanding the Transformation Wizard

Transformations are created differently based on the transformation type that you select on the definition page. The Transformation Wizard is a tool that guides you step-by-step through the process of creating transformations based on transformation type. The wizard enables you to navigate back and forth through only those pages that are necessary to create the transformation type that you select.

---

**Note.** Transformations occur after data has been extracted from your source.

---

The Transformation Wizard is comprised of up to six steps. The following table lists the steps that are necessary to complete look up, edit, and PeopleCode transformations:

	<i><b>Look Up</b></i>	<i><b>Edit</b></i>	<i><b>PeopleCode</b></i>
Create a transformation definition.	Yes	Yes	Yes
Define look ups.	Yes	No	No
Create a message definition.	Yes	Yes	No
Enter comments.	Yes	Yes	Yes
(Optional) Set up source conditions.	Yes	Yes	No
(Optional) Define look up conditions.	Yes	No	No

## Common Element Used in This Section



The Transformation Wizard navigation tool displays the number of pages that are necessary to create the transformation, and it highlights the current page.

Click a page number to navigate to that page or click the Next and Previous buttons to navigate between pages.

## Pages Used to Navigate Transformation Wizard

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Transformation Wizard - Transformation Definition	EOEW_TRN_DFN_INFO	Enterprise Components, Data Transformation, Define Transformation Definition	Enter transformation definition information.
Transformation Wizard - Look Up	EOEW_TRN_DFN_LU	<ul style="list-style-type: none"> <li>Click the Next button on the Transformation Wizard - Transformation Definition page.</li> <li>Click the Transformation Wizard - Look Up page number on the Transformation Wizard navigation tool.</li> </ul>	Enter a join condition to establish a relationship between this transformation and the look up definition.
Transformation Wizard - Edit	EOEW_TRN_DFN_EDIT	<ul style="list-style-type: none"> <li>Click the Next button on the Transformation Wizard - Look Up page.</li> <li>Click the Transformation Wizard - Edit page number on the Transformation Wizard navigation tool.</li> </ul>	Select the message definition to use for edit processing.
Transformation Wizard - Comments	EOEW_TRN_DFN_COM	<ul style="list-style-type: none"> <li>Click the Next button on the Transformation Wizard - Edit page.</li> <li>Click the Transformation Wizard - Comments page number on the Transformation Wizard navigation tool.</li> </ul>	Enter addition information about this transformation.
Transformation Wizard - Source Condition	EOEW_TRN_DFN_SRC	<ul style="list-style-type: none"> <li>Click the Next button on the Transformation Wizard - Comments page.</li> <li>Click the Transformation Wizard - Source Condition page number on the Transformation Wizard navigation tool.</li> </ul>	Define the source input values for this transformation condition.

Page Name	Definition Name	Navigation	Usage
Transformation Wizard - Look Up Condition	EOEW_TRN_DFN_LUC	<ul style="list-style-type: none"> <li>Click the Next button on the Transformation Wizard - Source Condition page.</li> <li>Click the Transformation Wizard - Lookup Condition page number on the Transformation Wizard navigation tool.</li> </ul>	Enter look up transformation definition properties.

## Creating Transformation Definitions

Access the Transformation Wizard - Transformation Definition page (Enterprise Components, Data Transformation, Define Transformation Definition).

**Transformation Wizard**
1 2 3 4 5 6
<<Previous
Next>>

### Transformation Definition

Enter transformation definition information regarding description or purpose of transformation, subject area and transformation type.

Transformation Object: TRANSFORMATION\_OBJECT\_01

\*Description:

\*Subject Area:  

\*Transformation Type:  

Transformation Wizard - Transformation Definition page

**Transformation Object**

Enter a unique object name for the transformation. The system automatically converts the input to uppercase.

For transformation type of PeopleCode, the name of the transformation object is used to reference the proper method in the PeopleCode transformation class. If the transformation object name does not contain a period (.) in its name, the corresponding method must be in the default class called EOEW\_ETL\_PUB:PeopleCodeTransformation.

To call a class in a proprietary package, use the name of the method in addition to the name of the package and class. For example, if you have created a package called MY\_APP\_PKG, with a class called MYPC and a method called SET\_UNIT\_PRICE, the transformation object name is specified as MY\_APP\_PKG:MYPC.SET\_UNIT\_PRICE.

---

**Note.** For PeopleCode transformations, the transformation object name must match the name of the Application Class method.

For any custom built PeopleCode transformations, use your own Application package and class name. By not putting the PeopleCode in EOEW\_ETL\_PUB:PeopleCodeTransformation, the code will not be affected during an upgrade.

---

**Subject Area**

Select a subject area.

For new transformations, the default subject is defined on the Subject Area page.

**Transformation Type**

*Look up.* Performs a look up against an intermediate table and returns a value. If the value does not exist, an error can be logged. An option is also available to default a value into the target field on error conditions.

*Edit.* Performs edits against the entire source dataset. An edit is applied at a map level, not at a target field level.

*PeopleCode.* Allows for a PeopleCode object reference. A PeopleCode Application Class method can be created to execute code for transformations that cannot be built with the available interfaces.

**See Also**

Chapter 2, "Setting Up Core PeopleSoft Data Transformer Features," Defining Subject Areas, page 12

**Defining Look Ups**

Access the Transformation Wizard - Look Up page (click the Next button on the Transformation Wizard - Transformation Definition page).



Transformation Wizard

1

2

3

4

5

6

<<Previous

Next>>

Look Up

Select or create a Look Up object. The Look Up field name will be returned based on the conditions you specify.

Transformation Object: TRANSFORMATION\_OBJECT\_01

Record (Table) Name:

Field Name:

Enter join condition to establish relationship between the transformation and look up definition.

Join Transformation To Look Up

Customize | Find | View All | First 1 of 1 Last


Source Input Value	Operator	Look Up Field Name		
<input type="text"/>	=	<input type="text"/>	+	-

Transformation Wizard - Look Up page

Record (Table) Name	Select a record for the intermediary look up table.
	<b>Note.</b> This table must exist in the local PeopleSoft database.
Field Name	Select the value to be returned from the transformation and inserted into the target field. The available values are based on the record name that you selected.
<b>Join Transformation to Look Up</b>	
Source Input Value	Select the source fields that are required for the join.
Look Up Field Name	Associate a look up field name value with a source input value to complete the join condition.

Creating Message Definitions

Access the Transformation Wizard - Edit page (click the Next button on the Transformation Wizard - Look Up page).




**Transformation Wizard** 1 2 3 4 5 6 <<Previous Next>>


### Edit

Select message definition that will be used for edit processing. The selected message number will be logged with the error.

☐ Check If Edit Required

**Message Definition**

Message Set Number:  

Message Number:  

Transformation Wizard - Edit page

**Check If Edit Required**

Select if you require an edit to be performed with transformation errors. If this check box is cleared, the edit will still execute at run-time but the results will not be available.

**Message Set Number and Message Number**

Select a message set number and a message number to be logged with any transformation errors.

## Entering Comments

Access the Transformation Wizard - Comments page (click the Next button on the Transformation Wizard - Edit page).



**Transformation Wizard** 1 2 3 4 5 6 <<Previous Next>>

### Comments

Transformation Object: TRANSFORMATION\_OBJECT\_01

Description: Verify job codes

Subject Area: JOB\_CODES

Comments:

Transformation Wizard - Comments page

Use the Comments field to enter commentary specific to this transformation. Try to thoroughly describe this edit to help others reuse it.

(Optional) Setting Up Source Conditions

Access the Transformation Wizard - Source Condition page (click the Next button on the Transformation Wizard - Comments page).

Transformation Wizard

123456

<<PreviousNext>>

Source Condition

Define the source input value(s) for your transformation condition. You may choose to select single or multiple source input values depending on the specific business rule that you are trying to resolve.

Source input values

CustomizeFindView All1 of 1FirstLast

	Source Input Value	Operator	Field Value		
1	<input type="text"/>	<div>▼</div>	<input type="text"/>	<div>+</div>	<div>-</div>

Transformation Wizard - Source Condition page

Use source conditions to further qualify the source data that is used for this transformation. You can enter additional criteria to restrict the rows of the source data that are used in the join to the look up table.

(Optional) Defining Lookup Conditions

Access the Transformation Wizard - Look Up Condition page (click the Next button on the Transformation Wizard - Source Condition page).

Transformation Wizard

123456

<<PreviousNext>>

Look Up Condition

Enter look up transformation definition properties. The definition captures information regarding which output table and field name will be used to return a data value.

Look Up Object:TRANSFORMATION\_OBJECT\_01Subject Area:JOB\_CODES

Description:Verify job codes

Output Properties

Record:

Select record name to be used to return a value.

Field Name:

Select field name that will be used to return a data value.

Default:

Enter a default value that will be used to populate the target field if the look up fails or returns a null value.

Return Look Up Record/Field Conditions

CustomizeFindView All

First1 of 1Last

Look Up Field Name	Operator	Field Value		
<div></div>	<div></div>	<div></div>	<div>+</div>	<div>-</div>

Transformation Wizard - Look Up Condition page

- Record and Field

Displays the record and field to be used to return a value.
- Default

Enter the value for the target field if the look up fails or returns a null value.

Return Look Up Record Field Conditions Grid

The look up condition further qualifies the look up table data that is used for this transformation. You can enter additional criteria to restrict the rows of the look up table that are used in the join to the look up table. The target field is populated based on the look up values that are provided.

Using Transformation PeopleCode

This section provides sample code delivered with your PeopleSoft product and discusses how to use transformation PeopleCode.

**Note.** If you need to create your own package and class, ensure that they adhere to the same format as shown here.

The FUNCLIB object must be imported and your methods must take this object as its only parameter. The HashTable class is a utility providing some of the internal information that you need to code your PeopleCode transformation. PeopleSoft Data Transformer creates a temporary table at runtime to store the fields from your source data object and from which you can access your PeopleCode transformation. In addition, the name of this temporary table is dynamically assigned and cannot be hard-coded into your program. For these reasons, PeopleSoft delivers helper methods for you to access and modify the content of your data:

- `GetSourceFieldList()` method returns a `HashTable` object containing a name-value pair for accessing your Source Data Object fields.
- `GetTransformFieldList()` method returns a `HashTable` object containing a name-value pair for accessing target fields that have transformations associated with them.
- `GetTempTableName()` returns the name of the temporary table that is used by PeopleSoft Data Transformer.

### ***Sample PeopleCode Transformation***

The following example updates the `EOEC_CCI_UNITPRICE` field on the target with a value of the source data object `PROD_PRICE` field plus a constant of 100, by issuing an `UPDATE` statement on the PeopleSoft Data Transformer temporary table.

Because the target field, `EOEC_CCI_UNITPRICE`, has an associated transformation, the actual name on the temporary table is resolved with a `GetValue(EOEC_CCI_UNIT_PRICE)` call on the transformation field's hash table. Similarly, the `PROD_PRICE` source data object field is resolved by making a `GetValue(PROD_PRICE)` call on the source field's hash table.

```
import EOEW_ETLAPI:COMMON:FUNCLIB;
import EOEW_ETLAPI:COMMON:HashTable;

class PeopleCodeTransformation
    method SET_UNIT_PRICE(&COMM As FUNCLIB);
    method MY_OTHER_PCODE_TRANS(&COMM As FUNCLIB);
end-class;

method SET_UNIT_PRICE
    /* + &COMM as EOEW_ETLAPI:COMMON:FUNCLIB +/
    Local HashTable &SDOFields, &TranFields;
    Local string &SQLStatement;

    /* Retrieve the hashtable containing ALIASNAME->TEMPFIELDNAME
    value pair */
    &SDOFields = &COMM.GetSourceFieldList();
    &TranFields = &COMM.GetTransformFieldList();

    /* Update the EOEW_CCI_UNITPRICE to: SDO.PROD_PRICE + SomeNumber
    This would resolve into something like:
    UPDATE ETL_TEMP_TBL SET ETL_TEMP_1 = EOEW_FP_N3_0 + 100
    */
    &SQLStatement = "UPDATE " | &COMM.GetTempTableName() | " SET " |
    &TranFields.GetValue("EOEC_CCI_UNITPRICE") | " = " |
    &SDOFields.GetValue("PROD_PRICE") | " + 100";

    SQLExec(&SQLStatement);
end-method;

method MY_OTHER_PCODE_TRANS
    .
    .
    .
end-method;
```

## Creating Map Rules

This section provides an overview of map rules and discusses how to define map rules.

### Understanding Map Rules

AutoMapper uses the rules that you create in the map field detail definition. Rules may be based on the subject area, the source, the target, or any combination, depending on the business rule being applied. AutoMapper considers only map rules that are defined with a subject area matching the map's subject area or those that are assigned the default enterprise subject area. The rules are made up of transformations, constant default values, translation sets, and field map hints. If the map rule is required, you will not have access to override the rule on the Map Field Detail page.

This order of precedence and conditions applies when you assign different rules to a single target field:

- Source

The source field must exist on the source data object that is associated with the map. The source field type must be compatible with the target field type.

- Transformation

The fields that are defined as joins or constraints from the source data object must exist on the source data object that is associated with the map.

- Translation Set

The fields that are defined as the join to the from value of the translation set must exist on the source data object that is associated with the map.

If no rules were found to match a given target field, processing occurs in this order:

- Exact name match of target field.
- Default value for the target field.
- A zero or NULL is assigned to the field depending on its data type.

### Page Used to Create Map Rules

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Map Rule Definitions	EOEW_RULE_DFN	Enterprise Components, Data Transformation, Define Map Rules, Map Rule Definitions	Define map rules.

## Defining Map Rules

Access the Map Rule Definitions page (Enterprise Components, Data Transformation, Define Map Rules, Map Rule Definitions).

### Map Rule Definitions

Create rules to assign a default for source field, translation set or transformation to your target field to be used by AutoMapper in the map field detail definition.

Map Rule

Map Rule: MAP\_RULE\_01

Subject Area:

☒ Active ☒ Allow Map Override

\*Target Field:

\*Source Input Type: Source

Source Field Alias:

Map Rule Definitions page

Active	Select to make the rule active. Only active rules get used during an AutoMapper run.
Allow Map Override	Select to allow the rule to be overridden on the Map Field Detail page.
Target Field	Select the target field on which to base this rule.
Subject Area	Select a subject area. For new rules, the default subject area is defined on the Subject Area page.
Source Input Type	<p><i>Source:</i> Select to enable the Source Field Alias field, where you enter an alias for your source field if one is defined. If not, leave this field blank. AutoMapper always maps the alias into the selected target field.</p> <p><i>Transformation:</i> Select to enable the Source field, where you enter a transformation object. AutoMapper always maps this transformation into the selected target field.</p> <p><i>Translation Set:</i> Select to enable the Source Field Alias and Source fields, where you enter an alias and translation set. When AutoMapper sees the alias on the source, it always maps this translation set into the selected target field.</p>





## Chapter 5

# Creating Maps

This chapter discusses how to create map definitions.

---

## Creating Map Definitions

This section discusses how to:

- Define map information.
- Define map field details.
- Perform map edits.
- Preview map results.
- Update map processing options.

## Pages Used to Create Map Definitions

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Map Information	EOEW_MAP_DFN	Enterprise Components, Data Transformation, Define Maps, Map Information	Enter general mapping information.
Map Field Detail	EOEW_MAP_FLD	Enterprise Components, Data Transformation, Define Maps, Map Information, Map Field Detail	Enter field-level mapping details.
Map Edits	EOEW_MAP_EDIT	Enterprise Components, Data Transformation, Define Maps, Map Information, Map Edits	Edit map source input values that are used in transformations.
Preview Map Results	EOEW_TARPREVIEW	Enterprise Components, Data Transformation, Define Maps, Map Information, Preview Map Results	View a subset of your data based on the defined map.

Page Name	Definition Name	Navigation	Usage
Map Options	EOEW_MAP_OPT	Enterprise Components, Data Transformation, Define Maps, Map Information, Map Options	Override or select options at the map level.
Map Definition - Comments	EOEW_MAP_COMMENT	Enterprise Components, Data Transformation, Define Maps, Map Information, Comments	Enter comments that are related to the map definition.

## Defining Map Information

Access the Map Information page (Enterprise Components, Data Transformation, Define Maps, Map Information).

Map Information | Map Field Detail | Map Edits | Preview Map Results | Map Options

Map Object: MAP\_OBJECT\_01      \*Subject Area:

\*Description:

**Data Object**

\*Source:

[Add Source Data Object](#)      [Update Source Data Object](#)

\*Target:

**Error Handling**

☒ No Error Handling Needed

☐ Identify Error Row

☐ Correct data error & reprocess

Map Information page

### Subject Area

Select a subject area.

For new maps, the subject area will be set to the default as defined on the Subject Area page.

### Source

Enter the source data object for this map.

**Note.** The source data object prompt is restricted by subject area. You see only those objects that are in the map definition's current subject area and those in the default subject area.

**Add Source Data Object** Click to navigate to the Source Data Object component and create a new source data object to use as the source.

**Update Source Data Object** Click to navigate to the Source Data Object component and change the source data object that you selected as the source.

**Target** Select the target data object.  
This value controls the target fields that are available on the Map Field Details page.

**Error Handling** *No error handling needed:* Select to have the system perform no data validation and insert all rows into the target table.  
*Identify error row:* Select to have the system perform data validation and insert both valid and invalid rows into the target table. You must select a target field to contain the error flag on the Map Field Detail page.

---

**Note.** The error flag will not be available for any other type of mapping.

---

*Correct data error & reprocess:* Select to have the system perform data validation, insert valid rows into the target table, and insert invalid rows into a user-defined error table. You will be prompted to create an error record on the Map Field Detail page.

---

**Note.** The system administrator must build the user-defined error table in PeopleSoft Application Designer before you load the defined map.

The create error record push button will create a record in PeopleSoft metadata that has all of the necessary columns needed at runtime. It must then be build using Application Designer. If your map changes (different transformations, translation sets, and so on), you will need to recreate the error table because it must match exactly.

---

## See Also

Chapter 2, "Setting Up Core PeopleSoft Data Transformer Features," Defining Subject Areas, page 12

Chapter 6, "Running the Data Transformation Process and Correcting Errors," Understanding Extracting, Transforming, and Loading Source Data, page 62

## Defining Map Field Details

Access the Map Field Detail page (Enterprise Components, Data Transformation, Define Maps, Map Information, Map Field Detail).

Map Information	Map Field Detail	Map Edits	Preview Map Results	Map Options	Comments
Map Object: MAP_OBJECT_01					Save Map As
<b>Data Object</b>					
Source:					
Target:					
<b>Error Handling</b>					
No Error Handling Needed					

Map Field Detail page

### Source Input Type

*Blank:* If this field is left blank, the description field will default to a blank, zero, or the appropriate PeopleSoft null value. This null value will be inserted to the target field.

*Source:* Select if the value is from the source file. You are prompted to select a source prompt field from the source data object.

*Constant:* Select if the value is a constant value, and then enter that value. If a constant needs to be applied to more than one map, a default target field should be created.

*Default:* Select to use a default value, and then select a source prompt to select the appropriate target field default. Click the Default link to access the Set Target Field Default page to see the actual prompt value.

*Transformation:* Select to use a transformation, and then select a source prompt to select the appropriate transformation. Click the Transform link to view transformation definitions, or click the Add link to add a new definition by using the Transformation Wizard.

*Translation Set:* Select to use a translation set, and then select a source prompt to select the appropriate source data object field. Select a description which will be the appropriate translation set to apply to the source field. Click the Translation link to view translation set values, or click the Add link to add a new set.

### Source Prompt

Select a source prompt based on your source input type. The prompt will change based on the source input type. Be aware of the mapping that you are setting up.

---

**Note.** Translation set and transformation source prompts are restricted by subject area and transformation type. Only objects that are in the map definition's current subject area and those in the default subject area appear on the page. Only Look Up and PeopleCode type transformations appear.

---


<b>Description</b>	<p>The description will change based on the source input type and source prompt selected. Be aware of the mapping that you are setting up.</p> <p>Enter a description if you selected <i>Constant</i> as the input type. The description is the value that you want mapped to the target field.</p> <p>Enter a translation set if you selected <i>Translation Set</i> as the input type.</p>
<b>Target Field</b>	Lists the name of all of the fields in your target file.
<b>Detail</b>	Displays the Transform, Default, or Translation link, based on the selected input type. This link transfers to the definition page of the selected item.
<b>Add</b>	Appears if the selected input type is <i>Transformation</i> or <i>Translation Set</i> . This link transfers to the definition page of the selected item in Add mode.
<b>Save Map As</b>	<p>Click to save an existing map definition under a new map name.</p> <p>Use this function to create a new map definition that will only slightly differ from the original map. Once saved, you can make the necessary changes to the new map. The new map is maintained separately.</p>
<b>Apply AutoMapper</b>	<p>Click to initially define map field details.</p> <p>AutoMapper automatically attempts to match the source to the target field list. It also applies any required map rules, including target field defaults, translation set values, and transformations. AutoMapper then maps remaining target fields with constant values from the PSRECFIELD.DBFIELDNAME.SQL assembler and coordinates the transformation steps.</p> <p>If you must modify the mapping that is defined by AutoMapper, you can make these changes using the fields on this page.</p> <hr/> <p><b>Warning!</b> Rerunning the AutoMapper overrides any mappings that you have already done. Use caution before doing this-it is as if you are starting over with an Add function.</p> <hr/>
<b>Synchronize fields</b>	<p>Click to realign the source and target fields on the map with any changes that may have occurred since its origination.</p> <p>You can add new fields to the target with PeopleSoft Application designer once a map has been saved. Using Synchronize fields will insert these new fields in the map field detail grid. Additional synchronization is done on source fields (based on the current source data object definition) and prompts. Selecting this button will not override previously saved mappings.</p>
<b>Show/Hide Fields Details</b>	Click to expand the grid to include field format and length information for both source and target fields. Click again to avoid the horizontal scroll.

## See Also

[Chapter 4, "Preparing to Create Maps," page 31](#)

Performing Map Edits

Access the Map Edits page (Enterprise Components, Data Transformation, Define Maps, Map Information, Map Edits).



Map Edits page

Source Input Value

Select an Edit transformation.

**Note.** The source input value prompt is restricted by subject area and transformation type. You see only those objects that are in the map definition's current subject area and those in the default subject area. You also see only edit transformations.

Detail

Click to access the Transformation Definition page and edit transformation definition information.

Add

Click to access the Transformation Definition page and add a new transformation.

See Also

Chapter 4, "Preparing to Create Maps," Creating Transformations by Using the Transformation Wizard, page 36

Previewing Map Results

Access the Preview Map Results page (Enterprise Components, Data Transformation, Define Maps, Map Information, Preview Map Results).

Click the Preview button to view a subset of the results based on your map definition.

Use this feature to check the validity of the map. By previewing what the results of running the map would be against a small set of data, you can determine if your mappings are defined correctly.

---

**Note.** Attempting to preview complex maps can quickly consume processing and memory resources on your application server.

The preview maximum row count is set using the Data Transformer Installation Options page. Large row counts take more time and resources to preview. Consider setting your preview row count relatively low.

---

### See Also

Chapter 2, "Setting Up Core PeopleSoft Data Transformer Features," Defining Installation Options, page 11

## Updating Map Processing Options

Access the Map Options page (Enterprise Components, Data Transformation, Define Maps, Map Information, Map Options).

Map Information   Map Field Detail   Map Edits   Preview Map Results   Map Options

Map Object: MAP\_OBJECT\_01

**Map Process Options**

\*Duplicate Row Handling: Copy duplicate rows to target

☒ Create Temporary Table  
Select to dynamically create the temporary table associated with a map definition. Unselect to specify the table manually.

Temporary Record (Table):

Override Tablespace Name From Subject Area Default.

Select Date/Time Field Name To Be Used For Incremental Load Processing.

Map Options page

---

**Note.** Only system administrators may access this page.

---

**Duplicate Row Handling**

*Copy Duplicates to Error Table:* Select to have the system copy all duplicate rows to the error table.

*Copy first row to Target:* Select so that if the system finds a duplicate row in the error table, it inserts only the first row of the duplicates into the target.

*Copy last row to Target:* Select so that if the system finds a duplicate row in the error table, the system inserts only the last row of the duplicates into the target.

*Reject all duplicate rows:* Select to have the system reject all duplicate rows and not log them in the error table.

---

**Note.** Values are based on the error handling that is specified on the Map Information page. If you don't see all of the preceding values, adjust the error handling option.

---

**(Optional) Create Temporary Table**

Select if you want to override the Data Transformer installation options and Subject Area selections for this map to create a temporary table at runtime.

This is needed only when an implementation allows or disallows the dynamic temporary table creation per subject area.

This temporary table is only needed by the engine and will be deleted at engine completion. It is not available in PeopleSoft metadata.

---

**Note.** If you do not select this check box, you will be required to specify a temporary table record name on the map for use at runtime. This record will be available in PeopleSoft metadata and live permanently after the engine execution. Determining which of these options to use needs to be carefully considered. A dynamic temporary table will automatically change when the map changes, a non-dynamic temporary table requires maintenance.

---

**Override Tablespace Name From Subject Area Default**

Select to override the Data Transformer installation options and Subject Area options for specific maps. This is only necessary if the implementation chooses to spread the temporary tables that are generated at runtime over multiple tablespaces.

**Select Date/Time Field Name To Be Used For Incremental Load Processing**

Only datetime field types appear in the prompt. This field is used at run time to determine the next segment of data to incrementally load.

**See Also**


[Chapter 2, "Setting Up Core PeopleSoft Data Transformer Features," Defining Installation Options, page 10](#)

[Chapter 2, "Setting Up Core PeopleSoft Data Transformer Features," Defining Subject Areas, page 12](#)



## Entering Map Definition Comments

Access the Map Definition - Comments page (Enterprise Components, Data Transformation, Define Maps, Map Information, Comments).



Map Object: MAP\_OBJECT\_01

Comments:

Map Definition - Comments page

Use the Comments field to provide details about the purpose of the map definition.



## Chapter 6

# Running the Data Transformation Process and Correcting Errors

This chapter discusses how to:

- Define map groups and map group chunking criteria.
- Extract, transform, and load source data.
- Handle data transformation process errors.

---

## Defining Map Groups and Map Group Chunking Criteria

This section discusses how to:

- Define map groups.
- Define chunking criteria.

You can configure the data transformation process to run on maps as a group. A map group may contain map groups within the main map group, as well as one or more individual maps. Map groups are submitted as a job unit and can run either in serial or parallel mode. To optimize performance by processing data more efficiently, you can define chunking criteria on the Map Group Filter page.

## Pages Used to Define Map Groups and Chunking Criteria

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Map Groups	EOEW_GRP_DFN	Enterprise Components, Data Transformation, Define Map Groups, Map Groups	Create map groups.
Map Group Filter	EOEW_GRP_FLTR	Click the Chunking link on the Map Groups page.	Define chunking criteria for maps.

## Defining Map Groups

Access the Map Groups page (Enterprise Components, Data Transformation, Define Map Groups, Map Groups).

Map Groups

Setup related data transformation maps into groups of maps to establish a run sequence.

Map Group: MAP\_GROUP\_01

\*Subject Area:

\*Description:

☐ Parallel Processing For Group

Map Group Items		Customize	Find	View All	First	1 of 1	Last
*Group Type	*Map Object	Chunking					
Map	<input type="text"/>	Chunking		<div>+ -</div>			

Map Groups page

<b>Subject Area</b>	Select a subject area.  For new maps groups, the subject area will be set to the default as defined on the Subject Area page.
<b>Parallel Processing For Group</b>	Select to run the process in parallel mode, which runs the processes simultaneously. Clear to run it in serial mode, which runs each process in the map group sequentially.
<b>Group Type and Map Object</b>	Select the maps and/or map groups that you want in the order in which you want them to run.  <b>Note.</b> Map object prompts are restricted by subject area. Only objects that are in the map group's current subject area and those in the default subject area appear.
<b>(Optional) Chunking</b>	Click to access the Map Group Filter page to define chunking criteria for the associated map.  See <a href="#">Chapter 6, "Running the Data Transformation Process and Correcting Errors," Defining Chunking Criteria, page 61.</a>  <b>Note.</b> The Chunking link is only available for Group Types of Map. If you want to chunk a group, you need to go to that group's definition to define the criteria.

See Also

Chapter 2, "Setting Up Core PeopleSoft Data Transformer Features," Defining Subject Areas, page 12

Defining Chunking Criteria

Access the Map Group Filter page (Enterprise Components, Data Transformation, Define Map Groups, Map Groups. Click the Chunking link).

Map Group Filter

Map Object:

☐ Parallel Processing

Chunking Criteria

Customize | Find | View All | First 1 of 1 Last

Chunk Number	Column Alias	Operator	Field Value	And/Or Switch		
1	<input type="text"/>	<div></div> <div><div></div></div>	<div><div></div></div>	<div><div></div></div>	<div><div></div></div>	<div><div></div></div>

Map Group Filter page

Chunking is a mechanism that makes large amounts of processing easier through the use of multiple small parallel processes. By enabling chunking, multiple jobs are spawned from one job stream. These jobs run in parallel or serial to process data efficiently. It is an optional mechanism to help with performance. The user is responsible to define chunks that include all of the source data without duplicating any rows. The system will not verify this. The map group is still the unit of work. The group job is not complete until all of the chunks are also complete.

- Parallel Processing

Select to run the process in parallel mode, which runs the processes simultaneously. Clear to run it in serial mode, which runs each process in the chunk sequentially.
- Column Alias

Select a column alias. Available values are derived from the source data object for the map you are currently chunking.
- Operator

Select an operator to define the chunking condition.
- Field Value

Enter the field value that completes criteria for the chunk number.
- And/Or Switch

Select *And* or *Or* to compound multiple sets of criteria.

**Note.** The chunks you define must be configured to capture all of the source data without duplicating rows.

## Extracting, Transforming, and Loading Source Data

This section provides an overview of source data extraction, transformation and loading, and discusses how to:

- Run the data transformation process.
- View the run summary.

## Understanding Extracting, Transforming, and Loading Source Data

The data transformation process can be run to extract, transform and load source data by a single map or by map groups. When a map or group is executed, it is compiled at runtime. No SQL or code, only metadata, is stored. This reduces the risk of encountering problems late in a multi-map process, guarantees that each parallel process is executing the same version, and insulates the current running job from any changes to the actual map definition.

The data transformation process is run using the Data Transformation Application Engine process (EOEW\_ETL\_EXE).

## Pages Used to Extract, Transform, and Load Source Data

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Run Data Transformations	EOEW_RUN_ETL	Enterprise Components, Data Transformation, Run Data Transformations, Run Data Transformations	Define run control criteria for and run the data transformation process.
Run Data Transformations - Run Summary	EOEW_RUN_ETL_SUM	Click the Run Summary link on the Run Data Transformations page.	View information about only the jobs related to a particular data transformation process run control.

## Running the Data Transformation Process

Access the Run Data Transformations page (Enterprise Components, Data Transformation, Run Data Transformations, Run Data Transformations).

### Run Data Transformations

User ID: VP1

Report ManagerProcess Monitor

Run Control ID: TEST\_01

Run SummaryRun

Run Data Transformer Parameter

\*Data Transformer Object Type: Map

\*Map Object:

\*Target Load Option: Full Load

☐ Destructive Load

Deletes all rows from the target record.

☐ Parallel Processing

Chunking Criteria

Run Data Transformations page

**Note.** The data transformation process uses the Data Transformation Application Engine process (EOEW\_ETL\_EXE).

<b>Data Transformer Object Type</b>	<p>Select a Data Transformer object type. You can run either a <i>Map</i> or <i>Map Group</i>.</p> <hr/> <p><b>Note.</b> PeopleSoft Catalog Management uses the run control ID <i>RUN_MAP</i> to load partner source data. When using this run control ID, the Data Transformer object type must be <i>Map</i>.</p> <hr/>
<b>Map Object</b>	<p>Select a map object. The prompt for available field values is based on the Data Transformer object type.</p>
<b>Target Load Option</b>	<p>Select a target load option.</p> <p><i>Full Load.</i> Extracts all data from the source as defined by the source data object and inserts into the target.</p> <p><i>Incremental Update.</i> Copies all rows from the source table that have been updated or modified since the last load, based on the date/time the row was updated or modified. The Map Options page must have a date/timestamp field defined in order to use incremental load.</p>
<b>Destructive Load</b>	<p>Select to delete all rows from the target table before the new rows are inserted.</p> <hr/> <p><b>Warning!</b> Use this option with caution, as this will delete all rows in the target table.</p> <hr/>

**Parallel Processing**

Select to run the process in parallel mode, which runs the processes simultaneously. Clear to run it in serial mode, which runs each process in the chunk sequentially.

---

**Note.** This option is only available if the Object Type is *Map*.

---

**Chunking Criteria**

Click to access the Map Group Filter page to define chunking criteria for the associated map.

See [Chapter 6, "Running the Data Transformation Process and Correcting Errors," Defining Chunking Criteria, page 61.](#)

---

**Note.** This link is only available for Group Types of *Map*. If you want to chunk a group, you need to go to that group's definition to define the criteria.

---

**Run**

Click to run the data transformation process. A process request is submitted.

Click the Process Monitor link to monitor the status of the request.

**Run Summary**

Click to view information that is related to the status of the data transformation process.

**See Also**

*PeopleTools: PeopleSoft Process Scheduler PeopleBook*

## Viewing the Run Summary

Access the Run Data Transformations - Run Summary page (Enterprise Components, Data Transformation, Run Data Transformations, Run Data Transformations. Click Run Summary).



## Run Summary

### Run Data Transformations

User ID: VP1 Refresh

Run Control ID: TEST\_01

#### Run Data Transformer Parameter

Data Transformer Object Type: Map

Map Object:

#### Processes

Customize | Find | | First 1 of 1 Last

Main Information Times Chunking Criteria

Process Instance	Map Group	Map Object	Run Status

#### Run Data Transformations - Run Summary page

After running a data transformation process by clicking Run on the Run Data Transformations page, you can access the Run Summary page just as you would access Report Manager or Process Monitor.

Although the Process Monitor provides information regarding a process run, the Run Summary feature offers a more granular view of the individual subprocesses, such as chunks, that are not exposed in the Process Monitor. For example, a single map containing chunks or a group can spawn numerous jobs. If you use the Process Monitor to view these jobs, you find that the numerous jobs that are associated with a single map are mixed in with all of the other jobs that are currently running. Depending on the number of jobs that are running, this can make it difficult to view only those jobs that are associated with a particular Data Transformer process run control.

However, by using the Run Summary feature you can view all of the jobs that were spawned for the run control that is associated with a particular run on of the Data Transformer process. The Run Summary feature is especially useful when running parallel processes that are associated with multiple maps. By using the Run Summary feature, you can associate a process instance with each chunk as it runs.

The Run Summary feature enables you to see:

- Which subprocesses are involved within a particular data transformation process run control.
- When a particular subprocess (chunk or map) begins.
- When a particular subprocess (chunk or map) completes.
- Which subprocesses didn't complete successfully.
- Which process instance is associated with a particular chunk or map.

#### **Main Information**

Select the Main Information tab.

**Process Instance**

Displays the PeopleSoft Process Scheduler process instance that is assigned to the individual process. This value also appears on the Times and Chunking Criteria tabs for consistent identification.

---

**Note.** For parallel processes, you see different process instances; for serial processes, you see the same process instance.

---

**Run Status**

Reflects the same status that appears in the Process Monitor. If the run status displays an error, go to the Process Monitor to troubleshoot and restart the process.

**Times**

Select the Times tab.

Use these times to track the performance of the processes.

**Chunking Criteria**

Select the Chunking Criteria tab.

**Chunking Where clause**

Displays information about the chunking criteria that is specified for a particular map, including:

- Relational operators (=, <, >, and so on).
- Boolean operators (AND and OR).

---

**Note.** This page also displays information that is relevant only to the internal aspects of the PeopleSoft mapping functionality.

---

The field names that are used for chunking are converted to an internal format; therefore, the format of the Chunking Where clause may not necessarily be a true reflection. That is, it may contain an extra "AND (", for example. However, determining the chunking criteria that is used can be very useful when you are troubleshooting.

Also, values that are similar to EOEW\_FP\_CHAR30\_0 are used internally by the PeopleSoft system to store data in a temporary table while the data is being transformed and loaded.

---

## Handling Data Transformation Process Errors

This section provides an overview of data transformation process errors and discusses how to view and correct data transformer process errors.

## Understanding Data Transformation Process Errors

After you run the data transformation process for a map with the *Correct data error & reprocess* option selected, use the Error Correction page to check for any errors that were logged during runtime. You can correct these errors online and rerun the data transformation process with the *Include Errors* option selected.

The Error Correction page sources its information from a PeopleSoft table specified on the Map Field Detail page. When the data transformation process runs and finds an error (such as a look-up or edit on an entry not found), it writes an entry into this error table.

The error table comprises:

- Two key fields, PROCESS\_INSTANCE and EOEW\_ETL\_SEQNUM.
- Error message fields from the EOEW\_ERRMSG\_SBR subrecord (EOEW\_ERR\_MSG01..EOEW\_ERR\_MSG10).
- All the fields being sourced from the Source Data Object.

Whenever an error is encountered for a look-up or edit transformation, the data transformation process stores the associated error message set number and message number in the error fields (EOEW\_ERRMSG\_XX) that are found in the error table so that the user can then troubleshoot the rows with errors.

By default, PeopleSoft allocates 10 error messages on the EOEW\_ERRMSG\_SBR subrecord (each error message field includes the message set number and message number), but users can delete or add more error message fields on the subrecord, as needed.

If more errors are encountered during the data transformation process run than are allocated on the error table, those errors that are encountered after the limit was reached are not written to the error table. Every error record must include one or more EOEW\_ERRMSG\_XX fields. The errors that are encountered during the data transformation process appear on the Error Correction page. The Error Correction page displays error messages that are associated with each specific row of data that is found to be in error by the data transformation process.

### See Also

*PeopleTools: PeopleCode Language Reference PeopleBook*

## Page Used to Handle Data Transformation Process Errors

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Error Correction	EOEW_CORRECTION	Enterprise Components, Data Transformation, Correct Errors, Error Correction	View and correct data transformation process errors.

## Viewing and Correcting Data Transformer Process Errors

Access the Error Correction (EOEW\_CORRECTION) page (Enterprise Components, Data Transformation, Correct Errors, Error Correction).

After you use this page to correct all errors, rerun the map.

<b>Edit</b>	Select for the row that you want to correct. The Field list appears at the top of the page with the associated error message for that row.
<b>Delete</b>	Select to remove the current row. This will physically delete the error row from the error table.
<b>Delete All Rows</b>	Select to remove all current rows. This will physically delete all error rows from the error table.
<b>Field</b>	Select the field you want to edit. Enter the new, corrected value for the field.
<b>Update</b>	Click to save the correction to the field.

## Appendix A

# Setting PeopleSoft Data Transformer Security

This appendix provides an overview of security and discusses how to implement security.

---

## Understanding Security

This section discusses:


- User profiles, roles, and permission lists.
- Delivered roles and permission lists.

## User Profiles, Roles, and Permission Lists

You assign roles to user profiles. Roles link user profiles to permission lists, which group authorizations.

Permission lists store sign-on times, page access, PeopleTools access, and so on. You can assign multiple roles to a user profile, and you can assign multiple permission lists to a role.

This diagram illustrates the interaction between user profile, roles, and permission lists:



Security definition hierarchy

Delivered Roles and Permission Lists

Access to PeopleSoft Data Transformer is based on roles and permission lists that are attached to user IDs.

PeopleSoft delivers the following roles that are configured to perform PeopleSoft Data Transformer functions:

Role	Permission List Access	Responsibilities
Enterprise Administrator	EOEW9000	Has access to all warehouse objects and performs all tasks that are related to PeopleSoft Data Transformer, including creating and maintaining source data objects, default target values, translation set values, and map definitions, and running Data Transformer maps.
Map Specialist	EOEW1000	Performs all tasks that are related to PeopleSoft Data Transformer, but typically does not set up complex source data objects or transformations.

Permission lists are delivered to support all PeopleSoft Data Transformer features. This table lists the components that are attached to each of the delivered permission lists.

**Note.** Both permission lists have access to all PeopleSoft Data Transformer-related components.

<i>Permission List</i>	<i>Component</i>	<i>Component Name</i>
EOEW1000 EOEW9000	EOEW_TOOLS_HOMEPG	Warehouse Tools Home Page.
	EOEW_OPTIONS	ETL Installation Options.
	EOEW_OBJ_OWNER	Subject Area.
	EOEW_SRCDO	Source Data Object.
	EOEW_SET_DFLT	Set Default Values.
	EOEW_CODE_SET	Translation Set Values.
	EOEW_LU_DFN_INFO	Look up Definition Info.
	EOEW_TRN_DFN_WIZ	Transformation Definition.
	EOEW_RULE_DFN	Map Rule Definition.
	EOEW_MAP_DFN	Map Definition.
	EOEW_GRP_DFN	Map Group.
	EOEW_CORRECTION	Error Correction.
	EOEW_RUN_ETL	Run Data Transformer.

Although both permission lists have access to all PeopleSoft Data Transformer-related components, the following pages are not accessible for permission list EOEW1000:

<i>Component</i>	<i>Page</i>
EOEW_OPTIONS	ETL Installation Options - Display Only.
EOEW_OBJ_OWNER	Subject Area Owner - Display Only.
EOEW_RULE_DFN	Map Rule Definition - No Access.
EOEW_MAP_DFN	Map Options - No Access.
EOEW_MAP_DFN	Publish Map Option - No Access.

## Implementing Security

This section provides an overview of security tasks and discusses how to:

- Associate the EOEW1000 permission list with a role.
- Assign the Map Specialist role to a user profile.

**See Also**

*PeopleTools: Security Administration PeopleBook*, "Setting Up Permission Lists"

*PeopleTools: Security Administration PeopleBook*, "Setting Up Roles"

*PeopleTools: Security Administration PeopleBook*, "Administering User Profiles"

## Understanding Security Tasks

To allow map specialists to perform data transformer activities you must:

- Associate the permission list EOEW1000 with *all* roles that are assigned to be map specialists.

---

**Note.** PeopleSoft delivers the Map Specialist role for this purpose.

---

- Assign the Map Specialist role to the necessary user profiles.

## Associating the EOEW1000 Permission List with a Role

To associate the EOEW1000 permission list with a role:

1. Select PeopleTools, Security, Permissions & Roles, Roles.
2. Enter a role.
3. Access the Permission List page.
4. Add the EOEW1000 permission list to the list of permission lists that are currently attached to the role.
5. Click Save.

## Assigning the Map Specialist Role to a User Profile

To assign the Map Specialist role to a user profile:

1. Select PeopleTools, Security, User Profiles, User Profiles.
2. Enter a user profile.
3. Access the Roles page.
4. Add the Map Specialist role to the list of roles that are currently attached to the user profile.
5. Click Save.



# Index

## A

ABS(Number) 20  
access management, defining 8  
AddMonth(Date, Number) 20  
AutoMapper 46, 53  
Average(Number) 20

## B

Beginning of Month(Date) 20  
Beginning of Year(Date) 21  
built-in functions, types of 20  
business processes, illustrating 1

## C

chunking criteria *See* map groups  
Comments page - Map Definition 50  
Comments page - Transformation Wizard 38  
comparison values *See* filters  
Count(col) 21  
create temporary table dynamically (map option)  
    56  
criteria *See* filters

## D

database connections  
    *See* remote database connections  
Data Transformation Installation Options page 11  
Data Transformer  
    *See* PeopleSoft Data Transformer  
DateAdd(Date, Days) 21  
DateDiff(Date, Date) 21  
DIFF\_H(Datetime, Datetime) 21  
DIFF\_S (Datetime, Datetime) 21  
DtTmDiff(Datetime, Datetime) 21  
duplicate row handling (map option) 56

## E

Edit page - Transformation Wizard 38  
edits, creating transformation type 41  
End of Month(Date) 21  
End of Year(Date) 21  
enterprise administrator, responsibilities of 70  
EOEW1000 (permission list) 71  
EOEW9000 (permission list) 71  
Error Correction page 67, 68  
error handling  
    for ETL process 68  
    for maps 51

## ETL

*See* extracting, transforming, and loading data (ETL)  
expressions  
    creating 23  
    defining data sources 25  
    understanding 20  
    understanding built-in functions of 20  
    using built-in functions in 26  
    using data object columns in 25  
Expressions page 23  
extracting, transforming, and loading data (ETL)  
    handling errors from 68  
    running the process of 62  
    understanding 62  
    understanding process errors from 67  
    viewing the run summary 64

## F

Fields page 16, 18  
filters  
    creating SDO type 28  
    defining map group type 61  
    understanding SDO type 27  
Filters page 28

## G

GetDay(Date) 21  
GetMonth(Date) 21  
GetYear(Date) 22  
grouping objects *See* subject areas

## I

implementation phases, understanding 2  
installation options, types of 11

## J

Join Conditions page 29  
joins  
    defining 29  
    understanding 29

## L

loading data  
    *See* extracting, transforming, and loading data (ETL)  
Lookup Condition page - Transformation Wizard

- 39
- look up conditions, defining transformation type 43
- Look Up page - Transformation Wizard 38
- look ups, defining transformation type 40

## M

- Map Edits page 49, 54
- Map Field Detail page 49, 51
- Map Group Filter page 59
- map groups
  - defining 60
  - defining chunking criteria in 61
- Map Groups page 59, 60
- Map Information page 49, 50
- Map Options page 50, 55
- mapping process
  - creating transformation definitions 39
  - defining rules for 47
  - entering translation set values during 36
  - setting target field default values during 34
  - setting up translation sets during 35
  - understanding 31
  - understanding rules for 46
  - using the transformation wizard for 37
  - using transformation PeopleCode during 44
- Map Rule Definitions page 46, 47
- map rules
  - defining 47
  - understanding 33, 46
- maps
  - defining 50
  - defining field details for 51
  - entering comments for 57
  - error handling for 51
  - performing edits for 54
  - previewing results for 54
  - selecting a target for 51
  - selecting source data objects for 50
  - updating options for 55
  - using AutoMapper for 53
- map specialist, responsibilities of 70
- Max(Number) 22
- maximum rows to preview (installation option) 11
- message set number (installation option) 12
- Min (Number) 22
- MOD(Number, Number) 22

## O

- Override tablespace name from Subject Area
  - default (map option) 56

## P

- PeopleSoft Data Transformation
  - setting installation default values for 11
- PeopleSoft Data Transformer
  - illustrating business processes of 1
  - understanding 1
  - understanding implementation phases of 2

- permission lists
  - associating to roles 72
  - EOEW1000 71
  - EOEW9000 71
  - understanding 69
- previewing
  - data sources 19
  - map results 54
  - SQL generated by defined source data objects 19
- Preview Map Results page 49
- Preview page 16
- process errors
  - understanding 67
  - viewing and correcting 68

## R

- Remote Database Access Management page 8
- remote database connections
  - defining 8
  - understanding 3
- roles
  - assigning to user profiles 72
  - associating permission lists to 72
  - enterprise administrator 70
  - map specialist 70
  - understanding 69
- Round(Number, Factor) 22
- RTRIM(String) 22
- Run Data Transformations page 62
- run summary
  - understanding 64
  - viewing chunking criteria 66
  - viewing main information 65
  - viewing times 66
- Run Summary - Run Data Transformations page 64
- Run Summary page - Run Data Transformations 62

## S

- SDOs *See* source data objects (SDOs)
- security
  - accessing components 71
  - assigning roles to user profiles 72
  - associating permission lists to roles 72
  - understanding 69
- Set Target Field Defaults page 34
- Source Condition page - Transformation Wizard 38
- source conditions, setting up transformation type 43
- Source Data Object page 16
- source data objects (SDOs)
  - creating expressions in 23
  - creating filters for 28
  - defining 16
  - defining joins for 29
  - previewing results of 19
  - previewing SQL generated by 19
  - selecting for maps 50
  - specifying fields in 18

- understanding 15
- understanding expressions 20
- understanding filters for 27
- understanding joins for 29
- subject areas
  - defining 13
  - setting a default 14
  - understanding 12
- Subject Areas page 13
- Substring(String, StartPos, Length) 22
- Sum(Number) 22

## T

- tablespace name (installation option) 12
- target field default values
  - considering data type formats for 32
  - setting up 34
  - understanding 31
- temporary tables (installation option) 12
- TO\_CHAR(Number) 22
- TO\_NUM(String) 22
- transformation comments, entering 42
- Transformation Definition page - Transformation Wizard 38
- transformation definitions, creating 39
- transformation objects, defining 40
- transformation PeopleCode
  - understanding 44
  - using 45
- transformation wizard
  - creating message definitions 41
  - creating transformation definitions 39
  - defining look up conditions 43
  - defining look ups 40
  - entering comments 42
  - navigating through 37
  - setting source conditions 43
  - understanding 37
  - understanding transformations 33
- Transformation Wizard - Edit page 41
- Transformation Wizard - Look Up Condition page 43
- Transformation Wizard - Look Up page 40
- Transformation Wizard - Source Condition page 43
- Transformation Wizard - Transformation Definition page 39
- transforming data
  - See* extracting, transforming, and loading data (ETL)
- translation sets
  - entering values for 36
  - setting up 35
  - understanding 33
- Translation Sets page 35
- TrimSubStr(String, Start, Length) 23
- Truncate(Number, Factor) 23

## U

- UPPER(String) 23
- user profiles, roles, and permission lists
  - assigning roles to user profiles 72

- associating permission lists to roles 72
- understanding 69

## V

- View Query page 16

## Y

- YYMMDD(Date) 23

