



THE ENTERPRISE MIDDLEWARE SOLUTION

BEA TUXEDO

System Messages

LIBGWT Catalog

BEA TUXEDO Release 6.5
Document Edition 6.5
February 1999

Copyright

Copyright © 1999 BEA Systems, Inc. All Rights Reserved.

Restricted Rights Legend

This software and documentation is subject to and made available only pursuant to the terms of the BEA Systems License Agreement and may be used or copied only in accordance with the terms of that agreement. It is against the law to copy the software except as specifically allowed in the agreement. This document may not, in whole or in part, be copied photocopied, reproduced, translated, or reduced to any electronic medium or machine readable form without prior consent, in writing, from BEA Systems, Inc.

Use, duplication or disclosure by the U.S. Government is subject to restrictions set forth in the BEA Systems License Agreement and in subparagraph (c)(1) of the Commercial Computer Software-Restricted Rights Clause at FAR 52.227-19; subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.227-7013, subparagraph (d) of the Commercial Computer Software--Licensing clause at NASA FAR supplement 16-52.227-86; or their equivalent.

Information in this document is subject to change without notice and does not represent a commitment on the part of BEA Systems. THE SOFTWARE AND DOCUMENTATION ARE PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND INCLUDING WITHOUT LIMITATION, ANY WARRANTY OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. FURTHER, BEA Systems DOES NOT WARRANT, GUARANTEE, OR MAKE ANY REPRESENTATIONS REGARDING THE USE, OR THE RESULTS OF THE USE, OF THE SOFTWARE OR WRITTEN MATERIAL IN TERMS OF CORRECTNESS, ACCURACY, RELIABILITY, OR OTHERWISE.

Trademarks or Service Marks

BEA, ObjectBroker, TOP END, TUXEDO, and WebLogic are registered trademarks of BEA Systems, Inc. BEA Builder, BEA Connect, BEA Manager, BEA MessageQ, Jolt and M3 are trademarks of BEA Systems, Inc.

All other company names may be trademarks of the respective companies with which they are associated.

BEA TUXEDO System Messages LIBGWT Catalog

Document Edition	Date	Software Version
6.5	February 1999	BEA TUXEDO Release 6.5

Content

- 1. LIBGWT Messages 1000-1099**
- 2. LIBGWT Messages 1100-1199**
- 3. LIBGWT Messages 1200-1299**
- 4. LIBGWT Messages 1300-1399**



1 LIBGWT Messages

1000-1099

1000 ERROR: Remote domain link not set in action table

Description	Shared memory information on the remote domain is not available to establish a connection. Tables may have been changed since the service request came in and the remote domain is no longer configured.
--------------------	--

Action	Contact your BEA TUXEDO system Technical Support.
---------------	---

See Also	<code>dmconfig(5)</code>
-----------------	--------------------------

1001 ERROR: No free context structures available

Description	A free slot cannot be found in the context table. See surrounding messages for more information such as a memory allocation failure.
--------------------	--

Action	Contact your BEA TUXEDO system Technical Support.
---------------	---

1002 ERROR: No free fd structures available

Description	A free slot cannot be found in the file descriptor table. See surrounding messages for more information such as a memory allocation failure.
--------------------	--

Action	Contact your BEA TUXEDO system Technical Support.
---------------	---

1003	ERROR: No free context structures available
Description	A free slot cannot be found in the context table. See surrounding messages for more information such as a memory allocation failure.
Action	Contact your BEA TUXEDO system Technical Support.
1004	ERROR: Unable to obtain local tdomain address from shmем
Description	Shared memory information for the local domain is not available to get local device for connection establishment. Severe shared memory error.
Action	Contact your BEA TUXEDO system Technical Support.
See Also	dmconfig(5)
1005	ERROR: Unable to open device “<i>sub</i>”; network error code 0x<i>sub</i>
Description	The opening of the device specified in the “TDOM” section of the DMCONFIG for the local domain was not successful.
Action	Check the “NWDEVICE” value for the local domain as specified in the DM_TDOMAIN section of the DMCONFIG file. See the specified network error for more information, such as the permissions being incorrect on the device or the network not being up.
See Also	dmconfig(5)
1006	ERROR: Unable to obtain remote domain entry from shmем
Description	Shared memory information for the remote domain is not available to get needed information. An update to the configuration (DM_REMOTE_DOMAINS section) may have removed the domain information.
Action	Retry the request after all configuration information has been updated or contact your BEA TUXEDO system Technical Support.
See Also	dmconfig(5)

1007	ERROR: Unable to obtain remote tdomain address from shmem
Description	Shared memory information for the remote domain is not available to get the addressing information for connection establishment. An update to the configuration (DM_TDOMAINS section) may have removed the domain information.
Action	Retry the request after all configuration information has been updated.
See Also	dmconfig(5)

1008	ERROR: Unable to connect to remote domain <i>domain_name</i>; network error code 0xnumber
Description	The attempt to establish a connection to the remote domain <i>domain_name</i> failed with the network error of <i>number</i> .
Action	More details can be found from the definition of the error code for your particular network or contact your BEA TUXEDO system Technical Support.

1009	ERROR: Cannot associate with network transaction
Description	An attempt to mark the domain's shared memory record of the transaction that this action is beginning to send as part of the transaction failed. This was possibly due to the fact that the transaction has already begun rollback.
Action	Check the state of the transaction through tadmin(1) or contact your BEA TUXEDO system Technical Support.
See Also	tadmin(1)

1010	ERROR: Cannot change action into failure
Description	An internal error occurred during an attempt to begin processing a failure.
Action	Contact your BEA TUXEDO system Technical Support.

1011 ERROR: Unable to obtain local domain info from shmem	
Description	Shared memory information for the local domain is not available. Severe shared memory error.
Action	Contact your BEA TUXEDO system Technical Support.
See Also	dmconfig(5)
1013 ERROR: Unable to send service request “<i>servicename</i>”	
Description	The attempt to send the <i>servicename</i> service request to the remote domain failed. The file descriptor will be closed.
Action	Check the configuration of both the remote service (DM_REMOTE_SERVICES) and remote domain (DM_REMOTE_DOMAIN.)
See Also	dmconfig(5)
1014 ERROR: Cannot set remote domain for transaction	
Description	An attempt to set this remote domain as a participant in the transaction in the domain's shared memory record of the transaction failed. This was possibly due to the fact that the transaction has already begun rollback, or that the maximum number of remote domains participating in a transaction has been exceeded. See possible surrounding messages for more information.
Action	Check the MAXRDOM parameter in the DMCONFIG file for the configured maximum number of remote domains (MAXRDOM) that can participate in a single transaction.
See Also	dmconfig(5)
1015 ERROR: Cannot disassociate with network transaction	
Description	An attempt to mark the domain's shared memory record of the transaction that this action has completed its initial sending as part of the transaction failed. This was possibly due to the fact that the transaction has already begun rollback.
Action	Check the state of the transaction through tmadmin(1) or contact your BEA TUXEDO system Technical Support.
See Also	tmadmin(1)

1016	ERROR: Cannot change action into failure
Description	An internal error occurred during an attempt to begin processing a failure.
Action	Contact your BEA TUXEDO system Technical Support.
1017	ERROR: Unexpected action state <i>number</i>
Description	An internal error occurred in processing a service request.
Action	Contact your BEA TUXEDO system Technical Support.
1018	ERROR: Unable to obtain local domainid info from shm
Description	Shared memory information for the local domain is not available to get information associated with the domain id. Severe shared memory error.
Action	Contact your BEA TUXEDO system Technical Support.
See Also	dmconfig(5)
1019	ERROR: Message presend routine failed
Description	The call to the <code>_tmpresend()</code> routine to process the buffer before encoding and sending has failed. The routine is as defined in the <code>typeswitch</code> which can be defined by the specific BEA TUXEDO application.
Action	Contact your BEA TUXEDO system Technical Support.
See Also	typesw(5)
1020	ERROR: Invalid data length of 0, data not self describing
Description	The message buffer to be sent on the service call has an invalid length of 0 after calling the buffer type switch <code>_tmpresend()</code> routine.
Action	Contact your BEA TUXEDO system Technical Support.
See Also	typesw(5)

1021	ERROR: Encoding of message data failed
Description	The call to the <code>_tmencdec()</code> routine to encode the buffer failed. The routine is as defined in the typeswitch which can be defined by the specific BEA TUXEDO application.
Action	Contact your BEA TUXEDO system Technical Support.
See Also	<code>typesw(5)</code>
1022	ERROR: Improper action calling nw_snd
Description	An internal error occurred in processing a service request.
Action	Contact your BEA TUXEDO system Technical Support.
1023	ERROR: Improper action calling nw_snd
Description	An internal error occurred in processing a service request.
Action	Contact your BEA TUXEDO system Technical Support.
1024	ERROR: <code>_tprandkey()</code> failed <code>tperrno = number</code>, could not generate random encryption key
Description	The call to get a randomly generated encryption key for the security exchange when a connection is being set up from a remote domain returned with a failure with the specified <code>tperrno</code> .
Action	Contact your BEA TUXEDO system Technical Support.
1025	ERROR: Validation of ticket failed
Description	The ticket returned during the security check when a connection was being set up from a remote domain did not pass validation.
Action	Check the password entries configured on both the local and remote domains in the binary domains configuration file.
See Also	<code>dmconfig(5)</code>
1026	ERROR: Cannot change action into failure
Description	An internal error occurred during an attempt to begin processing a failure.
Action	Contact your BEA TUXEDO system Technical Support.

1027	ERROR: Action data incorrect - null context
Description	An internal error occurred in processing a service request - mandatory context information is missing for the action.
Action	Contact your BEA TUXEDO system Technical Support.
1028	ERROR: Failed security validation with remote domain (domainid=domainid)
Description	The challenge returned during the security check when connecting to the specified remote domain did not pass validation.
Action	Check the password entries configured on both the local and remote domains in the binary domains configuration file.
See Also	dmconfig(5)
1029	ERROR: Failed security validation with remote domain (domainid=domainid)
Description	When trying to set up a connection to the specified remote domain, the remote domain returned a failure for the security validation.
Action	Check the password entries configured on both the local and remote domains in the binary domains configuration file.
See Also	dmconfig(5)
1030	ERROR: Unable to set signals on file descriptor
Description	The attempt to set up signals on the file descriptor used for establishing a connection to a remote domain failed. The signals are used to notify of incoming data or a relief of a blocking condition. Although processing will continue, timely response to data may be jeopardized without signal functionality.
Action	Contact your BEA TUXEDO system Technical Support.
1031	ERROR: Unable to set signals on file descriptor
Description	The attempt to set up signals on the file descriptor used for listening for connections from a remote domain failed. The signals are used to notify of incoming data or a relief of a blocking condition. Although processing will continue, timely response to data may be jeopardized without signal functionality.
Action	Contact your BEA TUXEDO system Technical Support.

1032	ERROR: Unable to set signals on file descriptor
Description	The attempt to set up signals on the file descriptor used for accepting connections from a remote domain failed. The signals are used to notify of incoming data or a relief of a blocking condition. Although processing will continue, timely response to data may be jeopardized without signal functionality.
Action	Contact your BEA TUXEDO system Technical Support.
1033	ERROR: Action data incorrect - null fd index
Description	An internal error occurred in processing a service request - mandatory file descriptor index is missing for the action.
Action	Contact your BEA TUXEDO system Technical Support.
1034	ERROR: Action data incorrect - null fd
Description	An internal error occurred in processing a service request - mandatory file descriptor referenced by the index in the action is null.
Action	Contact your BEA TUXEDO system Technical Support.
1035	ERROR: Can't set the parent of initiator as itself
Description	An attempt to set the parent of the transaction to itself when it is the initiator failed.
Action	Contact your BEA TUXEDO system Technical Support.
1036	ERROR: Too many unrecoverable errors occurred - deleting action
Description	The calls to process error conditions on a single action occurred more than twice. The action will no longer be processed.
Action	Contact your BEA TUXEDO system Technical Support.
1037	ERROR: Unrecoverable error occurred on send of data - sending failure reply locally
Description	An error occurred when trying to send data across network. A local failure reply will be sent. See surrounding messages for more information.
Action	Contact your BEA TUXEDO system Technical Support.

1038	ERROR: Unrecoverable error occurred - sending disconnects
Description	An error occurred during a conversational exchange. A disconnect of the conversation will be started. See surrounding messages for more information.
Action	Contact your BEA TUXEDO system Technical Support.
1039	ERROR: Cannot create action to send remote disconnect
Description	During error processing, the action needed to send a disconnect across the network cannot be created. See surrounding messages for more information.
Action	Contact your BEA TUXEDO system Technical Support.
1040	ERROR: Cannot create action to send remote disconnect
Description	During error processing, the action needed to send a disconnect locally cannot be created. See surrounding messages for more information.
Action	Contact your BEA TUXEDO system Technical Support.
1041	ERROR: Unrecoverable error occurred on send of data - sending failure reply over network
Description	An error occurred when trying to send a reply or commitment protocol across network. A failure reply will be sent over the network. See surrounding messages for more information.
Action	Contact your BEA TUXEDO system Technical Support.
1042	ERROR: Unrecoverable error occurred - cannot detect received opcode - deleting action
Description	The opcode for the received data cannot be determined. No further processing will occur on the action. See surrounding messages for more information.
Action	Contact your BEA TUXEDO system Technical Support.

1043	ERROR: Unrecoverable error occurred on receipt of data - sending failure reply over network
Description	An error occurred during processing of data received over the network. A failure reply will be sent across network. See surrounding messages for more information.
Action	Contact your BEA TUXEDO system Technical Support.
1044	ERROR: Unrecoverable error occurred on receipt of data - sending disconnects
Description	An error occurred during processing of conversational data received over the network. A disconnect of the conversation will be started. See surrounding messages for more information.
Action	Contact your BEA TUXEDO system Technical Support.
1045	ERROR: Cannot create action to send remote disconnect
Description	During error processing, the action needed to send a disconnect across the network cannot be created. See surrounding messages for more information.
Action	Contact your BEA TUXEDO system Technical Support.
1046	ERROR: Cannot create action to send remote disconnect
Description	During error processing, the action needed to send a disconnect locally cannot be created. See surrounding messages for more information.
Action	Contact your BEA TUXEDO system Technical Support.
1047	ERROR: Unrecoverable error occurred on receipt of data - sending failure reply locally
Description	An error occurred during processing of data or commitment protocol received over the network. A failure reply will be sent locally. See surrounding messages for more information.
Action	Contact your BEA TUXEDO system Technical Support.

1048	ERROR: Unrecoverable error occurred - deleting action
Description	An error occurred during processing of data received over the network. No further processing will occur on the action. See surrounding messages for more information.
Action	Contact your BEA TUXEDO system Technical Support.
1049	ERROR: Unrecoverable error occurred - deleting action
Description	An error occurred during processing of data received over the network. No further processing will occur on the action. See surrounding messages for more information.
Action	Contact your BEA TUXEDO system Technical Support.
1050	ERROR: File descriptor closed while processing
Description	The file descriptor has been marked as closed when attempting to send data across the network. A local failure reply will be sent. See surrounding messages for more information.
Action	Contact your BEA TUXEDO system Technical Support.
1051	ERROR: Cannot change action into failure
Description	An internal error occurred during an attempt to begin processing a failure.
Action	Contact your BEA TUXEDO system Technical Support.
1052	ERROR: Unable to obtain remote service information from shared memory
Description	Shared memory information for the remote service is not available to get needed information. An update to the configuration (DM_REMOTE_SERVICES section) may have removed the service information.
Action	Retry the request after all configuration information has been updated or contact your BEA TUXEDO system Technical Support.
See Also	dmconfig(5)

1053 ERROR: System encryption failed	
Description	Initialization of encryption with the session key during the security phase of establishing a connection to a remote domain failed.
Action	Contact your BEA TUXEDO system Technical Support.
1054 ERROR: System encryption failed	
Description	Encryption of sending domain during the security phase of establishing a connection to a remote domain failed.
Action	Contact your BEA TUXEDO system Technical Support.
1055 ERROR: System encryption failed	
Description	The call to get a ticket for the security exchange when a connection is being set up from a remote domain returned with a failure. See possible surrounding messages for more information.
Action	Contact your BEA TUXEDO system Technical Support.
1056 ERROR: System encryption failed	
Description	Getting the session key or initialization of encryption with the session key for the security exchange when a connection is being set up from a remote domain failed.
Action	Contact your BEA TUXEDO system Technical Support.
1057 ERROR: System encryption failed	
Description	Encryption of ticket for the security exchange when a connection is being set up from a remote domain failed.
Action	Contact your BEA TUXEDO system Technical Support.
1058 ERROR: System encryption failed	
Description	Getting the session key or initialization of encryption with the session key for the security exchange when a connection is being set up from a remote domain failed.
Action	Contact your BEA TUXEDO system Technical Support.

1059	ERROR: System encryption failed
Description	Encryption of ticket for the security exchange when a connection is being set up from a remote domain failed.
Action	Contact your BEA TUXEDO system Technical Support.
1060	ERROR: Encoding of header failed
Description	The encoding of the header information to send across the network failed.
Action	Contact your BEA TUXEDO system Technical Support.
1061	ERROR: Action data incorrect - null action index
Description	An internal error occurred in processing receipt of data - mandatory action index is missing for the call.
Action	Contact your BEA TUXEDO system Technical Support.
1062	ERROR: Action data incorrect - null context index
Description	An internal error occurred in processing receipt of data - mandatory context information is missing for the action.
Action	Contact your BEA TUXEDO system Technical Support.
1063	ERROR: Action data incorrect - null fd index
Description	An internal error occurred in processing receipt of data - mandatory file descriptor index is missing for the action.
Action	Contact your BEA TUXEDO system Technical Support.
1064	WARN: File descriptor has been closed, cannot receive data
Description	The file descriptor has been marked as closed when attempting to receive data from the network. See possible surrounding messages for more information.
Action	Contact your BEA TUXEDO system Technical Support.

1066	WARN: Network returned error on receive from domain name, closing file descriptor
Description	An error was returned from an attempt to receive data (header information) over the network from the named remote domain. The file descriptor will be closed.
Action	Contact your BEA TUXEDO system Technical Support.
1068	ERROR: Network returned error on receive from <i>domain name</i>, closing file descriptor
Description	An error was returned from an attempt to receive data over the network from the named remote domain. The file descriptor will be closed.
Action	Contact your BEA TUXEDO system Technical Support.
1069	ERROR: Decoding of header failed
Description	The decoding of the header information received over the network failed.
Action	Contact your BEA TUXEDO system Technical Support.
1070	ERROR: Unable to obtain local service information from shared memory
Description	Shared memory information for the local service is not available to get needed information. An update to the configuration (DM_LOCAL_SERVICES section) may have removed the service information.
Action	Check configuration of both the local and remote machines to ensure the services offered are as required. Retry the request after all configuration information has been updated.
See Also	dmconfig(5)

1071	WARN: Access Control List check failed for local service <i>servicename</i>
Description	The configured Access Control List does not accept the remote domain as being allowed to access the specified local service.
Action	Check the configuration of the service's Access Control List to allow the remote domain to access the local service as required. Retry the request after all configuration information has been updated.
See Also	dmconfig(5)

1072	ERROR: Received unsupported opcode: <i>number</i>
Description	The opcode - description of action to be done with data - for the data received over the network is not valid.
Action	Contact your BEA TUXEDO system Technical Support.

1073	ERROR: Unable to obtain remote domain id (<i>domainid</i>) information from shared memory
Description	During processing of receipt of data, shared memory information for the specified remote domain is not available to get needed information.
Action	Check the configuration for proper listing of the specified remote domain.
See Also	dmconfig(5)

1074	ERROR: Unable to obtain remote domain name (<i>domainid</i>) information from shared memory
Description	During processing of receipt of data, shared memory information for the specified remote domain is not available to get needed information.
Action	Check the configuration for proper listing of the specified remote domain.
See Also	dmconfig(5)

1075 ERROR: Unable to create/find local txid from shared memory	
Description	A failure occurred when either trying to search shared memory for the network transaction id to determine the local transaction id, or trying to create a new local transaction id to associate with the network transaction id. See possible surrounding messages for more information.
Action	Contact your BEA TUXEDO system Technical Support.
See Also	<code>dmconfig(5)</code>
1076 WARN: Unable to find conversation context	
Description	The conversation id received from the network on the data on a disconnect or conversation reply cannot be associated with a local conversation context.
Action	Contact your BEA TUXEDO system Technical Support.
1077 WARN: Stale message found	
Description	A reply or security exchange reply was received from the network which is no longer associated with an outstanding request. The original request may have timed out internally. The message is considered stale and is deleted.
Action	No action required.
1078 ERROR: Memory allocation error	
Description	An attempt to dynamically reallocate memory from the operating system using <code>realloc()</code> failed while attempting to allocate space for more data structures to associate with file descriptors.
Action	Ensure that the operating system parameters are set correctly for the amount of memory on the machine and the amount of memory that can be used by a process. Reduce the memory usage on the machine or increase the amount of physical memory on the machine.

1079	ERROR: Memory allocation error
Description	An attempt to dynamically reallocate memory from the operating system using <code>realloc</code> failed while attempting to allocate space for more data structures for the action context.
Action	Ensure that the operating system parameters are set correctly for the amount of memory on the machine and the amount of memory that can be used by a process. Reduce the memory usage on the machine or increase the amount of physical memory on the machine.
1080	ERROR: Memory allocation error
Description	An attempt to dynamically allocate memory from the operating system using <code>malloc</code> failed while attempting to allocate space for buffers to hold data received from network.
Action	Ensure that the operating system parameters are set correctly for the amount of memory on the machine and the amount of memory that can be used by a process. Reduce the memory usage on the machine or increase the amount of physical memory on the machine.
1082	ERROR: Memory allocation error
Description	An attempt to dynamically allocate memory from the operating system using <code>malloc</code> failed while attempting to allocate space for buffers to hold data to send across network.
Action	Ensure that the operating system parameters are set correctly for the amount of memory on the machine and the amount of memory that can be used by a process. Reduce the memory usage on the machine or increase the amount of physical memory on the machine.
1084	WARN: Request id not found
Description	A request id was not found among actions waiting to be processed. See surrounding messages for more information.
Action	See surrounding messages for action needed.
1085	WARN: Conversation id not found
Description	A conversation id was not found among actions waiting to be processed. See surrounding messages for more information.
Action	See surrounding messages for action needed.

1086	ERROR: File descriptor closed while processing
Description	The file descriptor has been marked as closed when attempting to send commitment protocol across the network. See surrounding messages for more information.
Action	Contact your BEA TUXEDO system Technical Support.
1087	ERROR: Unable to obtain local domain addr from shared memory
Description	Shared memory information for the local domain is not available. Severe shared memory error.
Action	Contact your BEA TUXEDO system Technical Support.
1088	ERROR: Unable to obtain domainid entry from shared memory
Description	Shared memory information for the local domain is not available to get information associated with the domain id. Severe shared memory error.
Action	Contact your BEA TUXEDO system Technical Support.
1089	ERROR: Unable to obtain remote domainid entry from shared memory
Description	During processing of commitment protocol, shared memory information for the specified remote domain is not available to get needed information. An update to the configuration (DM_TDOMAINS section) may have removed the domain information.
Action	Check the configuration for proper listing of the specified remote domain. Retry the request after all configuration information has been updated.
1090	ERROR: Encoding of header failed
Description	The encoding of the header information to send commitment protocol across the network failed.
Action	Contact your BEA TUXEDO system Technical Support.
1091	ERROR: Network returned error on send, closing file descriptor
Description	The attempt to send the commitment protocol to the remote domain failed. The file descriptor will be closed.
Action	Contact your BEA TUXEDO system Technical Support.

1092	ERROR: Unable to set remote domain branch state in shared memory
Description	A failure occurred in an attempt to mark the domain's shared memory record of the transaction that the remote domain is in a new state of commitment.
Action	Contact your BEA TUXEDO system Technical Support.
1093	ERROR: System state error
Description	An internal error occurred in processing the sending of commitment protocol.
Action	Contact your BEA TUXEDO system Technical Support.
1094	ERROR: Unable to obtain transaction entry from shared memory (prepare)
Description	The transaction entry is not found in the domain's shared memory table when trying to send the first phase of commitment. This could be caused by an abort having been previously sent or received while the prepare was waiting to be processed by the gateway.
Action	Contact your BEA TUXEDO system Technical Support.
1095	ERROR: Unable to create action to prepare branch
Description	An attempt to create an action to send the first phase of commitment to a branch failed.
Action	Contact your BEA TUXEDO system Technical Support.
1096	ERROR: Unable to obtain transaction entry from shared memory (commit)
Description	The transaction entry is not found in the domain's shared memory table when trying to send the second phase of commitment. This could be caused by an abort having been previously sent or received while the commit was waiting to be processed by the gateway.
Action	Contact your BEA TUXEDO system Technical Support.
1097	ERROR: Unable to determine locality of transaction
Description	The check to determine if the local domain is the root of the transaction failed. See surrounding messages for more information.
Action	Contact your BEA TUXEDO system Technical Support.

1098 ERROR: Unable to obtain remote domainid entry from shared memory	
Description	During processing of commitment protocol, shared memory information for the specified remote domain is not available to get needed information. An update to the configuration (DM_TDOMAINS section) may have removed the domain information.
Action	Check the configuration for proper listing of the specified remote domain. Retry the request after all configuration information has been updated.
1099 ERROR: Unable to obtain remote domain entry from shared memory	
Description	During processing of commitment protocol, shared memory information for the specified remote domain is not available to get needed information. An update to the configuration (DM_REMOTE_DOMAINS section) may have removed the domain information.
Action	Check the configuration for proper listing of the specified remote domain. Retry the request after all configuration information has been updated.

2 LIBGWT Messages

1100-1199

1100	ERROR: Unable to obtain transaction entry from shared memory (sndcommit)
Description	The transaction entry is not found in the domain's shared memory table when trying to send the second phase of commitment. This could be caused by an abort having been previously sent or received while the commit was waiting to be processed by the gateway.
Action	Contact your BEA TUXEDO system Technical Support.
1101	ERROR: Unable to create action to commit branch
Description	An attempt to create an action to send the second phase of commitment to a branch failed.
Action	Contact your BEA TUXEDO system Technical Support.
1103	ERROR: Unable to obtain transaction entry from shared memory (done)
Description	The transaction entry is not found in the domain's shared memory table when trying to send the second phase of commitment. This could be caused by an abort having been previously sent or received while the done was waiting to be processed by the gateway.
Action	Contact your BEA TUXEDO system Technical Support.

1104	ERROR: Unable to determine locality of transaction
Description	The check to determine if the local domain is the root of the transaction failed. See surrounding messages for more information.
Action	Contact your BEA TUXEDO system Technical Support.
1105	ERROR: Unable to obtain remote domainid entry from shared memory
Description	During processing of commitment protocol, shared memory information for the specified remote domain is not available to get needed information. An update to the configuration (DM_TDOMAINS section) may have removed the domain information.
Action	Contact your BEA TUXEDO system Technical Support.
1106	ERROR: Unable to obtain remote domain entry from shared memory
Description	During processing of commitment protocol, shared memory information for the specified remote domain is not available to get needed information. An update to the configuration (DM_REMOTE_DOMAINS section) may have removed the domain information.
Action	Check the configuration for proper listing of the specified remote domain. Retry the request after all configuration information has been updated.
1107	ERROR: Unable to obtain transaction entry from shared memory (sndcommit)
Description	The transaction entry is not found in the domain's shared memory table when trying to send commitment rollback. This could be caused by an abort having been previously sent or received while the rollback was waiting to be processed by the gateway.
Action	Contact your BEA TUXEDO system Technical Support.
1108	ERROR: Unable to create action to rollback branch
Description	An attempt to create an action to send commitment rollback to a branch failed.
Action	Contact your BEA TUXEDO system Technical Support.

1109	ERROR: Unable to obtain transaction entry from shared memory (sndfailure)
Description	The transaction entry is not found in the domain's shared memory table when trying to send a failure reply/rollback. This could be caused by an abort having been previously sent or received while the failure was waiting to be processed by the gateway.
Action	Contact your BEA TUXEDO system Technical Support.
1110	ERROR: Unable to change nwstate in shared memory (sndfailure)
Description	A failure occurred in an attempt to mark the domain's shared memory record of the transaction that a failure has been sent on the transaction.
Action	Contact your BEA TUXEDO system Technical Support.
1111	ERROR: Unable to create action to send rollback
Description	An attempt to create an action to send commitment rollback to a branch failed.
Action	Contact your BEA TUXEDO system Technical Support.
1112	ERROR: Unable to set remote domain branch state in shared memory
Description	A failure occurred in an attempt to mark the domain's shared memory record of the transaction that the remote domain is in a new state of commitment.
Action	Contact your BEA TUXEDO system Technical Support.
1113	ERROR: Unable to obtain transaction entry from shared memory (prepare)
Description	The transaction entry is not found in the domain's shared memory table when trying to process the receipt of the first phase of commitment. This could be caused by an abort having been previously sent or received while the prepare was waiting to be processed by the gateway.
Action	Contact your BEA TUXEDO system Technical Support.

1115 ERROR: Unable to set remote domain branch state in shared memory	
Description	A failure occurred in an attempt to mark the domain's shared memory record of the transaction that the remote domain is in a new state of commitment.
Action	Contact your BEA TUXEDO system Technical Support.
1116 ERROR: Unable to set remote domain branch state in shared memory	
Description	A failure occurred in an attempt to mark the domain's shared memory record of the transaction that the remote domain is in a new state of commitment.
Action	Contact your BEA TUXEDO system Technical Support.
1118 ERROR: System state error	
Description	An internal error occurred in processing the receipt of commitment protocol.
Action	Contact your BEA TUXEDO system Technical Support.
1119 WARN: connections structure initialization failure	
Description	An error occurred during initialization of network connection structure. See surrounding messages for more information.
Action	Contact your BEA TUXEDO system Technical Support.
1120 ERROR: Memory allocation error	
Description	An attempt to dynamically allocate memory from the operating system using <code>malloc</code> failed while attempting to allocate space for data structures for network information.
Action	Ensure that the operating system parameters are set correctly for the amount of memory on the machine and the amount of memory that can be used by a process. Reduce the memory usage on the machine or increase the amount of physical memory on the machine.

1121	ERROR: Memory allocation error
Description	An attempt to dynamically allocate memory from the operating system using <code>malloc</code> failed while attempting to allocate space for data structures for file descriptor information, network data information, or context information.
Action	Ensure that the operating system parameters are set correctly for the amount of memory on the machine and the amount of memory that can be used by a process. Reduce the memory usage on the machine or increase the amount of physical memory on the machine.
1122	ERROR: Unable to allocate free fd structure
Description	An attempt to dynamically allocate memory from the operating system using <code>malloc</code> failed while attempting to allocate space for data structures for file descriptor information.
Action	Ensure that the operating system parameters are set correctly for the amount of memory on the machine and the amount of memory that can be used by a process. Reduce the memory usage on the machine or increase the amount of physical memory on the machine.
1123	ERROR: Unable to obtain local tdomain address from shmем
Description	Shared memory information for the local domain is not available to get local device for listening endpoint. Severe shared memory error.
Action	Contact your BEA TUXEDO system Technical Support.
See Also	<code>dmconfig(5)</code>
1124	ERROR: Unable to open listening endpoint
Description	The opening of the device specified in the “TDOM” section of the <code>DMCONFIG</code> for the local domain was not successful.
Action	Check the “NWDEVICE” value for the local domain as specified in the <code>DM_TDOMAIN</code> section of the <code>DMCONFIG</code> file. See the specified network error for more information, such as the permissions being incorrect on the device or the network not being up.
See Also	<code>dmconfig(5)</code>

1126	ERROR: Unable to obtain local domain info from shmem
Description	Shared memory information for the local domain is not available. Severe shared memory error.
Action	Contact your BEA TUXEDO system Technical Support.
See Also	dmconfig(5)
1127	ERROR: Memory allocation error
Description	An attempt to dynamically allocate memory from the operating system using <code>tpalloc(3c)</code> failed while attempting to allocate space for decoding of received data.
Action	Ensure that the operating system parameters are set correctly for the amount of memory on the machine and the amount of memory that can be used by a process. Reduce the memory usage on the machine or increase the amount of physical memory on the machine.
See Also	<code>tpalloc(3c)</code>
1128	WARN: Connection accepted from domain (domainid=<domainid>)
Description	The specified remote domain has made a network connection to the gateway. Security measures, if configured, have not yet been applied.
Action	No action required.
1129	WARN: Connection established with domain (domainid=<domainid>)
Description	The gateway has made a network connection to the specified remote domain. Security measures, if configured, have not yet been applied.
Action	No action required.
1130	WARN: Disconnected from domain (domainid=<domainid>)
Description	The network connection to the specified remote domain has been terminated. See surrounding messages for more information.
Action	No action required.

1131 ERROR: DOMAIN gateway could not close a NW connection	
Description	The attempt to close a network connection to a remote domain failed during shutdown processing.
Action	Contact your BEA TUXEDO system Technical Support.
See Also	tmshutdown(1)
1132 ERROR: Memory allocation failure for post receive	
Description	An attempt to dynamically reallocate memory from the operating system using <code>tprealloc</code> failed while attempting to allocate more space for the processing required for <code>buffer</code> .
Action	Ensure that the operating system parameters are set correctly for the amount of memory on the machine and the amount of memory that can be used by a process. Reduce the memory usage on the machine or increase the amount of physical memory on the machine.
See Also	<code>tprealloc(3c)</code> , <code>buffer(3c)</code>
1133 ERROR: Post receive operation on message failed	
Description	The call to the <code>buffer</code> routine to process the buffer after decoding received data has failed. The routine is as defined in the <code>typeswitch</code> which can be defined by the specific BEA TUXEDO application.
Action	Contact your BEA TUXEDO system Technical Support.
See Also	<code>buffer(3c)</code>
1134 ERROR: Memory allocation failure for post receive	
Description	An attempt to dynamically reallocate memory from the operating system using <code>tprealloc</code> failed while attempting to allocate more space for the processing required for <code>buffer</code> .
Action	Ensure that the operating system parameters are set correctly for the amount of memory on the machine and the amount of memory that can be used by a process. Reduce the memory usage on the machine or increase the amount of physical memory on the machine.
See Also	<code>tprealloc(3c)</code> , <code>buffer(3c)</code>

1135 ERROR: Post receive operation on message failed	
Description	The call to the <code>buffer(3c)_tmpostrecv()</code> routine to process the buffer of received data has failed. The routine is as defined in the typeswitch which can be defined by the specific BEA TUXEDO application.
Action	Contact your BEA TUXEDO system Technical Support.
See Also	<code>buffer(3c)</code>
1136 ERROR: Network initialization failure	
Description	An error occurred while initializing the network provider.
Action	Make sure that your network stack is correctly installed and configured. Use network administration tools to determine the cause of the initialization problem.

3 LIBGWT Messages

1200-1299

1200	WARN: Transaction received HEURISTIC MIX result from remote domain <i>val</i>
Description	The Domain gateway received a heuristic mix message indicating that part of the transaction committed and part of the transaction rolled back. This may cause an inconsistency in the application data.
Action	No action required.
1201	WARN: Transaction received HEURISTIC HAZARD result from remote domain <i>val</i>
Description	The Domain gateway received a heuristic hazard message indicating that the outcome of part of the transaction is uncertain. This may cause an inconsistency in the application data.
Action	No action required.
1202	ERROR: Bad message from <i>sub</i>. Closing file descriptor
Description	An invalid message was received in the Domain gateway. The gateway connection will be closed.
Action	Ensure that the TYPE values are set correctly if encoding is needed between domains.

1203 ERROR: Memory allocation failure for decompression	
Description	An attempt dynamically to allocate memory from the operating system failed while decompressing a received message.
Action	Make sure the operating system parameters are set correctly for the amount of memory on the machine and the amount of memory that can be used by a process. Reduce the memory usage on the machine or increase the amount of physical memory on the machine.
1204 ERROR: Memory allocation failure for decompression	
Description	An attempt dynamically to allocate memory from the operating system failed while decompressing a received message.
Action	Make sure the operating system parameters are set correctly for the amount of memory on the machine and the amount of memory that can be used by a process. Reduce the memory usage on the machine or increase the amount of physical memory on the machine.
1205 ERROR: Unable to obtain remote domain entry from shmem	
Description	While compressing a message, the entry for the remote domain could not be found (to determine the compression limit).
Action	This error should not occur. Contact BEA TUXEDO system Technical Support.
1206 ERROR: Memory allocation failure for compression	
Description	An attempt dynamically to allocate memory from the operating system failed while compressing a message.
Action	Make sure the operating system parameters are set correctly for the amount of memory on the machine and the amount of memory that can be used by a process. Reduce the memory usage on the machine or increase the amount of physical memory on the machine.
1207 ERROR: Unable to obtain remote domain entry from shmem	
Description	While compressing a message, the entry for the remote domain could not be found (to determine the compression limit).
Action	This error should not occur. Contact BEA TUXEDO system Technical Support.

1208 ERROR: Memory allocation failure for compression	
Description	An attempt dynamically to allocate memory from the operating system failed while compressing a message.
Action	Make sure the operating system parameters are set correctly for the amount of memory on the machine and the amount of memory that can be used by a process. Reduce the memory usage on the machine or increase the amount of physical memory on the machine.

1209 ERROR: Memory allocation failure for decompression	
Description	An attempt dynamically to allocate memory from the operating system failed while decompressing a message.
Action	Make sure the operating system parameters are set correctly for the amount of memory on the machine and the amount of memory that can be used by a process. Reduce the memory usage on the machine or increase the amount of physical memory on the machine.

1210 ERROR: decompression failed	
Description	An error occurred while decompressing a message.
Action	Check for other errors in the event log.

1211 ERROR: Failed to destroy inflate structure	
Description	An error occurred while decompressing a message.
Action	Check for other errors in the event log.

1212 WARN: Network connection closed by <i>rdom</i>, closing file descriptor	
Description	The gateway at the remote domain closed the network connection.
Action	No action required.

1213 WARN: Network connection closed by <i>rdom</i>, closing file descriptor	
Description	The gateway at the remote domain closed the network connection.
Action	No action required.

1214	WARN: Corrupted Communication Control data detected!
Description	An error occurred in the information associated with the domain connection.
Action	Contact BEA TUXEDO system Technical Support.
1215	WARN: Communication to remote domain <rdom> already disconnected
Description	A message was sent to a domain that has already disconnected from the local domain.
Action	Re-try the operation.
1216	WARN: Communication to remote domain <rdom> already disconnected
Description	A message was sent to a domain that has already disconnected from the local domain.
Action	Re-try the operation.
1217	ERROR: Decode function failed
Description	The call to the <code>buffer(3c)_tmencdec</code> routine to process the buffer of received data has failed. The routine is as defined in the <code>typeswitch</code> which can be defined by the specific BEA TUXEDO application.
Action	Contact your BEA TUXEDO system Technical Support.
See Also	<code>buffer(3c)</code>
1218	ERROR: memory allocation failed for compression
Description	The Domain Gateway library software detected an error while trying to compress a message. The process was unable to allocate enough virtual memory for the operation.
Action	Attempt to identify and stop any extraneous processes to free up virtual memory on your system.
See Also	<code>tpstrerror(3c)</code>

1219 ERROR: compression fails...continuing	
Description	The Domain Gateway library software detected an error while trying to compress a message. An internal function call returned a failure.
Action	This is an internal error with no associated user action. If the error persists, contact your BEA TUXEDO system Technical Support with the exact error message.
See Also	tpstrerror(3c)

1220 ERROR: memory allocation failure in decompression	
Description	The Domain Gateway library software detected an error while trying to decompress a message. The process was unable to allocate enough virtual memory for the operation.
Action	Attempt to identify and stop any extraneous processes to free up virtual memory on your system.
See Also	tpstrerror(3c)

1221 ERROR: decompression of message failed	
Description	The Domain Gateway library software detected an error while trying to decompress a message. An internal function call returned a failure.
Action	This is an internal error with no associated user action. If the error persists, contact your BEA TUXEDO system Technical Support with the exact error message.
See Also	tpstrerror(3c)

1222 ERROR: uncompressed message reallocation failed	
Description	The Domain Gateway library software detected an error while trying to decompress a message. The process was unable to allocate enough virtual memory for the operation.
Action	Attempt to identify and stop any extraneous processes to free up virtual memory on your system.
See Also	tpstrerror(3c)

1223	WARN: Reach system open max(<i>maximum</i>) limit
Description	The Domain Gateway library software detected an error while trying to get a free file descriptor entry. The BEA TUXEDO System maximum <i>maximum</i> for open files was reached.
Action	Attempt to identify and close any files which are open unnecessarily.
See Also	tpstrerror(3c)
1224	ERROR: Minimum encryption (<i>number of bits</i>) is larger than 0, but the link level package is not installed
Description	The Domain Gateway library software detected an error while trying to process a connect operation. The minimum number of encryption bits <i>number of bits</i> specified in the DM_TDOMAIN section of the domain configuration file is greater than zero; however, no link level security package is installed.
Action	Correct the configuration so that the minimum number of encryption bits is consistent with the link level security package in use.
See Also	dmconfig(5)
1225	ERROR: Minimum encryption (<i>number of bits</i>) is larger than 40, but only the 40-bit package is installed
Description	The Domain Gateway library software detected an error while trying to process a connect operation. The minimum number of encryption bits <i>number of bits</i> specified in the DM_TDOMAIN section of the domain configuration file is greater than forty; however, the forty-bit link level security package is installed.
Action	Correct the configuration so that the minimum number of encryption bits is consistent with the link level security package in use.
See Also	dmconfig(5)

1226	ERROR: Could not allocate encryption handle
Description	The Domain Gateway library software detected an error while trying to process a connect operation. The encryption handle could not be allocated. An internal function call returned a failure. A more descriptive error messages will be issued by the failing routine.
Action	Check the surrounding error messages for more descriptive error information.
See Also	tpstrerror(3c)

1227	ERROR: Could not get encryption settings
Description	The Domain Gateway library software detected an error while trying to receive a message. The process was unable to obtain from shared memory the *DM_TDOMAIN configuration section containing the encryption settings.
Action	This is an internal error with no associated user action. If the error persists, contact your BEA TUXEDO system Technical Support with the exact error message.
See Also	tpstrerror(3c)

1228	ERROR: Minimum encryption (<i>number of bits</i>) is larger than 40, but only the 40-bit package is installed
Description	The Domain Gateway library software detected an error while trying to receive a message. The minimum number of encryption bits <i>number of bits</i> specified in the DM_TDOMAIN section of the domain configuration file is greater than forty; however, the forty-bit link level security package is installed.
Action	Correct the configuration so that the minimum number of encryption bits is consistent with the link level security package in use.
See Also	dmconfig(5)

1229 ERROR: Encryption negotiation failure	
Description	The Domain Gateway library software detected an error while trying to receive a message. An error was detected in the encryption flag settings. The encryption flags are all zero.
Action	Ensure that the encryption bit settings in the DM_TDOMAIN sections of the <code>dmconfig</code> file are consistent for communicating domains.
See Also	<code>dmconfig(5)</code>
1230 ERROR: Unable to generate first diffie-hellman packet	
Description	The Domain Gateway library software detected an error while trying to send a message. An internal function call for encryption returned a failure. Additional error messages from the failing routine will be issued prior to this message.
Action	Check the messages from the failing routine for more specific information regarding the cause of this error.
See Also	<code>tpstrerror(3c)</code>
1231 ERROR: Could not allocate encryption handle	
Description	The Domain Gateway library software detected an error while trying to receive a message. An error was detected in the internal routine to allocate an encryption handle. A more specific message will be issued by the failing routine.
Action	Check the surrounding error messages for additional information.
See Also	<code>tpstrerror(3c)</code>
1232 ERROR: Memory allocation error	
Description	The Domain Gateway library software detected an error while trying to receive a message. The process was unable to allocate enough virtual memory for the operation.
Action	Attempt to identify and stop any extraneous processes to free up virtual memory on your system.
See Also	<code>tpstrerror(3c)</code>

1233	ERROR: Unable to generate second diffie-hellman packet
Description	The Domain Gateway library software detected an error while trying to send a message. An internal function call for encryption returned a failure. Additional error messages from the failing routine will be issued prior to this message.
Action	Check the messages from the failing routine for more specific information regarding the cause of this error.
See Also	tpstrerror(3c)
1234	ERROR: Unexpected link level encryption failure
Description	The Domain Gateway library software detected an error while trying to send a message. An internal function call for encryption returned a failure.
Action	This is an internal error with no associated user action. If the error persists, contact your BEA TUXEDO System technical support with the exact error message.
See Also	tpstrerror(3c)
1236	ERROR: Encryption negotiation failure
Description	The Domain Gateway library software detected an error while trying to receive a message. An error was detected in the encryption flag settings. The encryption flags are all zero.
Action	Ensure that the encryption bit settings in the DM_TDOMAIN sections of the dmconfig file are consistent for communicating domains.
See Also	dmconfig(5)
1237	ERROR: Invalid security level
Description	The Domain Gateway library software detected an error while trying to receive a message. An invalid encryption level was detected.
Action	This is an internal error with no associated user action. If the error persists, contact your BEA TUXEDO System technical support with the exact error message.
See Also	tpstrerror(3c)

1238	ERROR: Unexpected link level encryption failure
Description	The Domain Gateway library software detected an error while trying to receive a message. An internal function call for encryption returned a failure.
Action	This is an internal error with no associated user action. If the error persists, contact your BEA TUXEDO System technical support with the exact error message.
See Also	<code>tpstrerror(3c)</code>
1240	ERROR: Minimum encryption (<i>number of bits</i>) is larger than 0, but the link level package is not installed
Description	The Domain Gateway library software detected an error while trying to process a receive operation. The minimum number of encryption bits <i>number of bits</i> specified in the <code>DM_TDOMAIN</code> section of the domain configuration file is greater than zero; however, no link level security package is installed.
Action	Correct the configuration so that the minimum number of encryption bits is consistent with the link level security package in use.
See Also	<code>dmconfig(5)</code>
1241	ERROR: Invalid parameter, <code>tdom_link</code> is NULL
Description	GWTDOMAIN detects an internal error, or possible data corruption when it does a network open call.
Action	Contact your BEA TUXEDO system Technical Support.
1242	ERROR: Invalid parameter, <code>tdom_link</code> contains NULL pointer
Description	GWTDOMAIN detects an internal error, or possible data corruption when it does a network open call.
Action	Contact your BEA TUXEDO system Technical Support.

1243	WARN: Open <i>domain_name</i> address <i>ip_port</i> failed, Network error(0xerror_code)
Description	GWTDOMAIN tries to open a listening end point form domain <i>domain_name</i> using the port number and IP address as specified by <i>ip_address</i> failed with network error code specified. This can be caused by either the port is already been used, or the port just been release in some TCP/IP implementation.
Action	If the configuration contains multiple address entries for the specified domain, the GWTDOMAIN will continue with the next one. If all the address specified exhausted and still can't open the listening end point, GWTDOMAIN will exit. The user can try to restart it, or change configuration and restart it.
1244	WARN: No more NW address to try
Description	GWTDOMAIN already tries all the listening end points specified in the BDMCONFIG file, and still could not able to open any listening end point.
Action	The administrator should check whether the configuration is correct, and whether any other process already uses the port number.
1245	WARN: Try next one, device <i>device_name</i> address <i>ip_address</i>
Description	This is informational. It tells the user that GWTDOMAIN is going to try the next IP address and port number specified in the configuration.
Action	Nothing.
1246	ERROR: Invalid parameter, tdom_link is NULL
Description	GWTDOMAIN detects an internal error, or possible data corruption when it does a network connect call.
Action	Contact your BEA TUXEDO system Technical Support.
1247	ERROR: Invalid parameter, tdom_link contains NULL pointer
Description	GWTDOMAIN detects an internal error, or possible data corruption when it does a network connect call.
Action	Contact your BEA TUXEDO system Technical Support.

1248 ERROR: Invalid parameter, fd is -1	
Description	GWTDOMAIN detects an internal error, or possible data corruption when it does a network connect call.
Action	Contact your BEA TUXEDO system Technical Support.
1249 WARN: Connect to <i>domain_name</i> address <i>ip_addr</i> failed, Network error(0xerrno)	
Description	GWTDOMAIN tries to connect to a remote domain <i>domain_name</i> using the port number and IP address as specified by <i>ip_address</i> failed with network error code specified. This can be caused by network failure, wrong IP address or port number in the configuration, or the remote GWTDOMAIN not yet up and running, or the remote GWTDOMAIN has not yet able to open the listening end, or the remote GWTDOMAIN opened different end point then what specified in the local domain configuration file.
Action	Check the network, and check proper configuration. And also make sure the remote domain GWTDOMAIN is up and running and use the port and IP address specified in the configuration.
1250 WARN: No more remote domain NW address to try	
Description	GWTDOMAIN has exhausted all the address information specified in the configuration file, and still could not connect to remote GWTDOMAIN.
Action	Check the network, and check proper configuration. And also make sure the remote domain GWTDOMAIN is up and running and use the port and IP address specified in the configuration.
1251 WARN: Try next one, address <i>ip_address</i>	
Description	This is informational. It tells the user that GWTDOMAIN is going to try the next IP address and port number specified in the configuration to connect to remote GWTDOMAIN.
Action	No action required.

1252	ERROR: Unable to obtain transaction entry from shared memory (rollback)
Description	The /Domain transaction table entry for this transaction was not found in the /Domain shared memory tables when trying to process a transaction rollback. This could be caused if a stray message was received for a transaction that was already aborted.
Action	If the <code>dmadmin</code> subcommand <code>pt</code> indicates that the transaction has already been removed from the /Domain shared memory, no action is required. Otherwise, contact your BEA TUXEDO system Technical Support.
1253	ERROR: Unable to open device "<i>sub</i>"; network error code 0x<i>sub</i>
Description	The GWTDOMAIN process was unable to establish a connection to the remote domain using device <i><device name></i> . The error code <i><hex value></i> was returned from the network open routine.
Action	Ensure that the values specified for the <code>NWADDR</code> and <code>NWDEVICE</code> parameters in the <code>DM_TDOMAIN</code> section of the <code>dmconfig(5)</code> file are correct.
See Also	<code>dmconfig(5)</code>
1254	ERROR: Unable to determine locality of transaction
Description	The GWTDOMAIN process was unable to determine the locality (local or remote) of a transaction. This is an internal processing error.
Action	This is an internal error with no associated user action.
See Also	<code>tperrno(5)</code>
1255	WARN: Unable to create local txid in shared memory for transaction recovery
Description	The GWTDOMAIN process was unable to recover a transaction because the transaction table is full. The transaction will be rolled back.
Action	Modify the configuration to allow for more concurrent transactions.

1256 WARN: Unable to create local txid in shared memory for transaction recovery	
Description	The GWTDOMAIN process was unable to recover a transaction because the transaction table is full. The transaction will be rolled back.
Action	Modify the configuration to allow for more concurrent transactions.

4 LIBGWT Messages

1300-1399

1318 ERROR : Local security type (%s) does not match security type (%s) of remote domain (domainid=%s)

Description In order for two domains to communicate they must both have the same SECURITY types set in their dmconfig files. If the security levels do not match the connection will be refused.

Action Change the SECURITY value on one or both of the dmconfig files so that they match.

1319 ERROR : Unable to obtain local domain info from shmем

Description BEA TUXEDO was unable to obtain information about the local domain from the shared memory area.

Action Contact BEA TUXEDO System Technical Support.

1350 ERROR : Error occurred during security negotiation - closing connection

Description An error occurred during the security negotiation phase of setting up a connection. The connection is being closed. This error is on the initiator side of the connection during the sending phase of one of the protocol messages.

Action See other messages for more details, including the name of the remote domain to which the connection is being tried. Check that security parameters and passwords on both domains match.

1351	ERROR : Error occurred during security negotiation - closing connection
Description	An error occurred during the security negotiation phase of setting up a connection. The connection is being closed. This error is on the responder side of the connection during the receiving phase of one of the protocol messages.
Action	See other messages for more details, including the name of the domain that initiated the connection. Check that security parameters and passwords on both domains match.
1352	ERROR : Error occurred during security negotiation - closing connection
Description	An error occurred during the security negotiation phase of setting up a connection. The connection is being closed. This error is on the initiator side of the connection during the receiving phase of one of the protocol messages.
Action	See other messages for more details, including the name of the remote domain to which the connection is being tried. Check that security parameters and passwords on both domains match.
1353	ERROR : Error occurred during security negotiation - closing connection
Description	An error occurred during the security negotiation phase of setting up a connection. The connection is being closed. This error is on the responder side of the connection during the sending phase of one of the protocol messages.
Action	See other messages for more details, including the name of the domain that initiated the connection. Check that security parameters and passwords on both domains match.
1354	INFO: Retrying domain (domainid=<i>domainid</i>) every <i>retry_interval</i> seconds
Description	<p>The initial connection attempt to the remote domain has failed. The gateway is now retrying the connection to the remote domain periodically, as specified by <code>RETRY_INTERVAL</code> (default: 60 sec). The retry occurs only when the <code>CONNECTION_POLICY</code> is <code>ON_STARTUP</code>.</p> <p>The retry interval is rounded up to be a multiple of <code>SCANUNIT</code> (as specified in the <code>ubbconfig</code> file).</p>
Action	No action required.
1355	WARN: Message with <code>TPNOREPLY</code> to service <i>service</i> dropped - network down

Description	A client sent a message to the gateway with the <code>TPNOREPLY</code> flag set. The gateway was unable to deliver the message to the remote gateway because the network is down. Since the gateway cannot inform the client application, a userlog message is written.
Action	No action required.

1356 WARN: Message with TPNOREPLY to service <i>service</i> dropped - network down	
Description	A client sent a message to the gateway with the TPNOREPLY flag set. The gateway was unable to deliver the message to the remote gateway because the network is down. Since the gateway cannot inform the client application, a userlog message is written.
Action	No action required.
1357 WARN: Message with TPNOREPLY to service <i>service</i> dropped - network down	
Description	A client sent a message to the gateway with the TPNOREPLY flag set. The gateway was unable to deliver the message to the remote gateway because the network is down. Since the gateway cannot inform the client application, a userlog message is written.
Action	No action required.