

# Oracle Insurance IBRU SoftRater for Windows Reference Guide

Version 3.11

December 2008

# *Oracle Insurance Insbridge Rating and Underwriting SoftRater for Windows Reference Guide*

*Version 3.11*

*Part # formerly P01-713-12*

*December 2008*

Copyright © 2008, Oracle. All rights reserved.

*Primary Authors: Mary Elizabeth Wiger*

The Programs (which include both the software and documentation) contain proprietary information; they are provided under a license agreement containing restrictions on use and disclosure and are also protected by copyright, patent, and other intellectual and industrial property laws. Reverse engineering, disassembly, or decompilation of the Programs, except to the extent required to obtain interoperability with other independently created software or as specified by law, is prohibited.

The information contained in this document is subject to change without notice. If you find any problems in the documentation, please report them to us in writing. This document is not warranted to be error-free. Except as may be expressly permitted in your license agreement for these Programs, no part of these Programs may be reproduced or transmitted in any form or by any means, electronic or mechanical, for any purpose.

If the Programs are delivered to the United States Government or anyone licensing or using the Programs on behalf of the United States Government, the following notice is applicable:

## **U.S. GOVERNMENT RIGHTS**

Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the Programs, including documentation and technical data, shall be subject to the licensing restrictions set forth in the applicable Oracle license agreement, and, to the extent applicable, the additional rights set forth in FAR 52.227-19, Commercial Computer Software--Restricted Rights (June 1987). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

The Programs are not intended for use in any nuclear, aviation, mass transit, medical, or other inherently dangerous applications. It shall be the licensee's responsibility to take all appropriate fail-safe, backup, redundancy and other measures to ensure the safe use of such applications if the Programs are used for such purposes, and we disclaim liability for any damages caused by such use of the Programs.

The Programs may provide links to Web sites and access to content, products, and services from third parties. Oracle is not responsible for the availability of, or any content provided on, third-party Web sites. You bear all risks associated with the use of such content. If you choose to purchase any products or services from a third party, the relationship is directly between you and the third party. Oracle is not responsible for: (a) the quality of third-party products or services; or (b) fulfilling any of the terms of the agreement with the third party, including delivery of products or services and warranty obligations related to purchased products or services. Oracle is not responsible for any loss or damage of any sort that you may incur from dealing with any third party.

Oracle, JD Edwards, and PeopleSoft are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

# Contents

---

<b>CONTENTS</b> .....	<b>3</b>
<b>PREFACE</b> .....	<b>4</b>
<i>Audience</i> .....	4
<i>System Requirements</i> .....	4
<i>Manual History</i> .....	4
<b>CHAPTER 1</b> .....	<b>5</b>
CONCEPT DIAGRAM .....	5
<b>CHAPTER 2</b> .....	<b>6</b>
SOFTWARE INTEGRATION .....	6
<i>Visual Basic Example (Web Services – Lite Weight)</i> .....	7
<i>JavaScript (Web Services)</i> .....	7
<i>C# Example (Web Services)</i> .....	7
<b>CHAPTER 3</b> .....	<b>9</b>
RATING ARGUMENTS .....	9
<b>CHAPTER 4</b> .....	<b>10</b>
CUSTOM XML ARGUMENTS .....	10
<b>CHAPTER 5</b> .....	<b>11</b>
INSBRIDGE.XML .....	11
<i>Insbridge.XML Request Format</i> .....	11
<rate> Node .....	12
<heading> Node .....	12
<program> Node .....	13
<c> Node .....	13
<m> Node .....	14
<i>Insbridge.XML Result Format</i> .....	14
<result> Node .....	15
<program> Node .....	16
<m> Node .....	17
<input> Node .....	17
Input Overrides .....	17
<i>Examples</i> .....	18
Single Rate Request .....	18
Multiple Rate Requests in A Single XML Document .....	18
Multiple <rate> nodes .....	18
Multiple <program> nodes .....	19
Multi - State Request .....	19
Multi - Line of Business Request .....	20
<b>CHAPTER 6</b> .....	<b>21</b>
SUPPORT .....	21
<b>INDEX</b> .....	<b>22</b>

# Preface

---

Welcome to the *Oracle Insurance Insbridge Rating and Underwriting SoftRater for Windows User Guide*. This guide describes the concepts and requirements of SoftRater for Windows. It provides a reference for developers to properly interact with the SoftRater Engine either through SOAP, POST Web Services Interface (WSI) or Direct COM Interfacing.

## Audience

---

This guide is intended for SoftRater system administrators who are tasked with administering SoftRater. Readers of this guide should be familiar with XML, HTTP.

## System Requirements

---

System requirements for the Oracle Insurance Insbridge Rating and Underwriting system can be found in the Oracle Insurance Insbridge Rating and Underwriting Recommended Operating Environments for Hardware and Software Guide available from Oracle Insurance Support or Oracle Insurance Sales Representative.

## Manual History

---

New editions incorporate any updates issued since the previous edition.

Edition	Publication Number	Product Version	Publication Date	Comment
1 <sup>st</sup> Edition	P01-713-01	V 3.5	November 2005	
2 <sup>nd</sup> Edition	P01-713-02	V 3.5	April 2006	Update
3 <sup>rd</sup> Edition	P01-713-03	V 3.6	November 2006	Update
4 <sup>th</sup> Edition	P01-713-04	V 3.7	November 2006	Update
5 <sup>th</sup> Edition	P01-713-05	V 3.8	July 2007	Update
6 <sup>th</sup> Edition	P01-713-06	V 3.8.3	October 2007	Update
7 <sup>th</sup> Edition	P01-713-07	V 3.8.5	November 2007	Update
8 <sup>th</sup> Edition	P01-713-08	V 3.8.7	January 2008	Update
9 <sup>th</sup> Edition	P01-713-09	V 3.8.8	March 2008	Update
10 <sup>th</sup> Edition	P01-713-10	V 3.9	May 2008	Update
11 <sup>th</sup> Edition	P01-713-11	V 3.10	September 2008	Update
12 <sup>th</sup> Edition	P01-713-12	V 3.11	December 2008	Update

## Concept Diagram

The diagram below shows the high level interaction between the client application and the Oracle Insurance Insbridge Rating and Underwriting SoftRater (SoftRater) system. The SoftRater instance is responsible for all rating & underwriting processing. The basic functionality of the SoftRater system is demonstrated below. Input data is sent to the SoftRater instance, processed and output data is returned.




Figure 1 Concept Diagram

## Software Integration

The Web Service Interface (WSI) provides a platform, environment, and language neutral mechanism for business process interoperability using the two most common denominators of the Internet, XML & HTTP. The SoftRater WSI is supported through the use of Microsoft Internet Information Server (IIS) and ASP.NET.

Upon request, the URL configures an instance of the SoftRater Engine from those arguments and forwards the InsbridgeRate.XML (Input format) to the SoftRater Engine for processing. After the SoftRater Engine completes processing, the result, InsbridgeRate.XML (Output format), is forwarded through (HTTP) back to the requesting process.

1. HTTP SOAP Proxy – SoftRater Web Service – WSDL documents are included in the installation. From them proxy classes can be generated from a SOAP supported development environment to communicate with the installed SoftRater instance. The SoftRater Web Service WSDL should be located at the following URL.  
<http://<yourserver>/ibfa/connectors/sofrater.asmx?WSDL>

The SoftRater Web Service interface documentation should be located at the following URL.

<http://<yourserver>/ibfa/Connectors/sofrater.asmx?op=ProcessMessage>

Supported operations are SOAP, HTTP POST, and HTTP GET. In order to utilize the SoftRater rating arguments, the document must be a SOAP envelope.

2. HTTP POST – A lite-weight Web Service Interface. An ASPX page is provided as an interface for clients with only web form POST abilities without using a SOAP envelope message. CustomXml cannot be submitted from this interface.

The URL to the POST interface should be the following.

<http://<yourserver>/ibfa/Connectors/sofrater.aspx>

The Boolean rating arguments can be provided (optionally) as URL query string arguments. For example:

<http://<yourserver>/ibfa/Connectors/sofrater.aspx?addinputs=true&addroot=true;>

The lists of available URL arguments are the standard rating arguments provided through all SoftRater Interfaces. The doinXSL option will transform the contents of the input XML using the XSL processing-instruction element. The rating document name value pair “ibdoc” should be supplied as a form collection item.

```
addinputs=true
addroot=true
addheading=true
addresultdesc=true
addresultempty=true
doinXSL=true
```

```
<xsl:processing-instruction name='input' href='c:\location.xml'/>
```

## Visual Basic Example (Web Services – Lite Weight)

---

```
Dim MyResults
Dim MyXMLDoc
Dim AppURL
Dim objHTTP

MyXMLDoc = "ibDoc=<ibdoc><rate>.....</rate></ibdoc>"           '// Well formed InsbridgeRate.XML (Input)
AppURL = "http://yourserver/ibfa/Connectors/sofrater.aspx?AddRoot=TRUE" '// Web Services Request URL w/ Options

Set objHTTP = CreateObject("Msxml2.XMLHTTP")                     '// Microsoft HTTP Request Object

objHTTP.open "post", AppURL, false
objHTTP.setRequestHeader "Content-Type", "application/x-www-form-urlencoded"
objHTTP.send MyXMLDoc                                           '// INSBRIDGE.XML sent as the body.

MyResults=objHTTP.responseXML                                   '// returns XML response
MyResults=objHTTP.responseText                                 '// returns text response (Optional)
```

## JavaScript (Web Services)

---

```
var MyResults;
var MyXMLDoc;
var AppURL;
var objHTTP;

MyXMLDoc = "ibDoc=<ibdoc><rate>..... </rate></ibdoc>";           // Well formed InsbridgeRate.XML (Input)
                                                                    // or CustomXml
AppURL = "http://yourserver/ibfa/Connectors/sofrater.asmx/ProcessMessage" // Web Services Request URL

objHTTP = new ActiveXObject("Msxml2.XMLHTTP ");                  // Microsoft HTTP Request Object

objHTTP.open('post', AppURL, false);

objHTTP.setRequestHeader("SOAPAction", "http://insbridge.net/wsi/Connector/SoftRater/ProcessMessage"); //Set the SOAP action
objHTTP.setRequestHeader("Content-Type", "application/x-www-form-urlencoded");

objHTTP.send(MyXMLDoc);
MyResults=objHTTP.responseXML;                                   // returns XML response
MyResults=objHTTP.responseText;                                 // returns text response (Optional)
```

## C# Example (Web Services)

---

```
string rateXml = "<CustomXml/>";

//Or rateXml could simply be a valid InsbridgeXml document.
//rateXml = "<ibdoc><rate> </rate></ibdoc>";

//Get an instance
Insbridge.Net.RM.SRW.SI.SoftRater ibSoftRater = new Insbridge.Net.RM.SRW.SI.SoftRater();

//Only for rate operator exceptions
Insbridge.Net.RM.SoftRater.MappedRateOperators rateOper = new Insbridge.Net.RM.SoftRater.MappedRateOperators();

//Only for input and/or output transformations
Insbridge.Net.RM.SoftRater.MappedRateRequest rateRequest = Insbridge.Net.RM.SoftRater.MappedRateRequest();

rateOper.AddHeading = 0;
```

```
rateOper.AddRoot = 1;  
rateOper.AddInputs = 0;  
rateOper.AddResultDesc = 0;  
rateOper.AddResultEmpty = 0;  
rateOper.DebugRate = 0;  
rateOper.EnvRef = "dev";  
  
rateRequest.Subscriber = 100;  
rateRequest.Lob = 2;  
rateRequest.Program = 3;  
rateRequest.Version = 1;  
  
rateRequest.InputMappingIdentifier = agent_interface_v1;  
rateRequest.InputMappingGlobal = true;  
  
rateRequest.OutputMappingIdentifier = agent_interface_v1;  
rateRequest.OutputMappingGlobal = false;  
  
rateRequest.OutputMappingStateful = false;  
  
ibSoftRater.MappedRateOperatorsValue = rateOper;  
ibSoftRater.MappedRateRequestValue = rateRequest;  
  
string results = ibSoftRater.ProcessMessage(rateXml).OuterXml;
```



---

## Rating Arguments

The SoftRater engine rating arguments control the handling of XML data out of the system. Rating arguments are optional. For optimal performance, use the following arguments for your rating integration.

Add Root Node (Use default – False) – If submitting multiple rate request documents, this option is typically set to true to make the result document a valid XML document.

Add Inputs (Use default – False) – When set to true, the full request Insbridge.XML document is returned in the result Insbridge.XML document making the XML document much larger than normal.

Add Heading (Use default – False) – When set to true, the program name description information is returned in the result XML also.

Add Result Descriptions (Use default – False) – When set to true each result item includes the RateManager variable result name along with the result id and value. Making the result XML much larger.

Typically, most integration operates on the result IDs and descriptions are not needed when building an automated system.

Add Empty Results (Use default – False) – When set to true, a defined result item, whose value is empty (i.e. blank), is still created and returned blank in the resulting Insbridge.XML. If your program design requires a number of optional results, you could have blank results items in your XML.

Debug Output (Use default – False) – When set to false, no debug report will be issued. Set to true if you would like a debug report.

EnvRef (Use default – blank) – When left blank, the default environment defined in setup will be used. To specifically define an environment, enter in the environment name.

If no arguments are sent, the default values will be used. Default values are defined in setup. If using the SoftRater Server, see Submit Insbridge XML.

---

## Custom XML Arguments

The SoftRater WSI controls the processing (transformations) of XML data in and/or out of the system. Custom XML arguments are required only when you are submitting custom XML. If you are using Insbridge XML, custom XML arguments are not required. The information will be contained in the Insbridge XML.

Use the following MapRequest SOAP options below for your rating integration.

Lob – Identifier of the Line Of Business

Subscriber – Identifier of the Subscriber

Program – Identifier of the Program

Version – Identifier of the Program Version

InputMappingIdentifier – Name of the Custom Mapping Document

InputMappingType – Enum for the Custom Mapping Document

- NONE – No input mapping should be performed
- GLOBAL – Input mapping is global to the Line of Business
- LOCAL – Input mapping is unique to the program version
- CUSTOM – Input mapping of the customer that has been added into the workflow

OutputMappingIdentifier – Name of the Custom Mapping Document

OutputMappingType – Enum for the Custom Mapping Document

- NONE – No output mapping should be performed
- GLOBAL – Output mapping is global to the Line of Business
- LOCAL – Output mapping is unique to the program version
- CUSTOM – Output mapping of the customer that has been added into the workflow

OutputMappingStateful – The SoftRater WSI will add the contents of the rating results to the document that was submitted for rating.

OutputErrorXPathLoc – Location of any system errors that occurred during the WebService request that are not related to SoftRater for Windows. (By default, an error node is created at the root level.)

OutputSchema – Path of any schema that the WSI should validate against.

If you are using custom XML and do not define the custom XML arguments, any error message will be thrown.

## Insbridge.XML

XML is the primary data exchange mechanism used by Oracle Insurance Insbridge Rating and Underwriting system to import/export data and to communicate information electronically with external and internal software systems. XML provides a clean, readable, self-validating way to exchange data and is quickly becoming (or possibly already is) the data exchange standard.

Insbridge's rating request input XML is designed to be flexible and efficient. It allows for single or multiple rate requests to be submitted via one input XML document. The rate requests embedded in this single document can be targeted to multiple states and/or multiple lines of business. Multiple versions of a rating package also can be targeted in a single rate request document.

The rating request response XML is also streamlined to present all the results to the various request methods, described above, in a single output XML document.

### Insbridge.XML Request Format

The following is an example of an Insbridge rate request XML document:

```
<rate lob="2" tracking_attribute="" env_def="">
  <heading>
    <program parent_id="700" tiering_id="" program_id="24" program_ver="1"/>
  </heading>
  <c i="0" desc="Policy">
    <m i="1086" n="PackageDisclnd" v=""/>
    <m i="1094" n="RenewalRetentionCreditInd" v=""/>
    <m i="1157" n="CompanyCode" v=""/>
    <m i="1212" n="Eff_Date" v=""/>
    <m i="1214" n="PrimInsuredAge" v=""/>
    <m i="1215" n="SecInsuredAge" v=""/>
    <m i="1222" n="RenewalInd" v=""/>
  <c i="5" desc="Home">
    <m i="1083" n="TerritoryCode" v=""/>
    <m i="1084" n="ResidenceType" v=""/>
    <m i="1087" n="ProtectionClass" v=""/>
    <m i="1095" n="Wood/Tile/SlateRoofType" v=""/>
    <m i="1096" n="HomeDeductible" v=""/>
    <m i="1098" n="WindstormOrHailDeductible" v=""/>
    <m i="1100" n="CentralStationFireAlarmInd" v=""/>
    <m i="1101" n="CentralStationBurglarAlarmInd" v=""/>
  <c i="8" desc="Coverage">
    <m i="1204" n="CovCd" v=""/>
    <m i="1205" n="CovLimit" v=""/>
    <m i="1207" n="CovEff_Date" v=""/>
  </c>
</c>
```

```

        <c i="9" desc="Endorsement">
            <m i="1181" n="EndorCd" v=""/>
            <m i="1182" n="EndorRateInd" v=""/>
            <m i="1190" n="EndorEff_Date" v=""/>
            <m i="1191" n="Parm5" v=""/>
        </c>
    </c>
</c>
</rate>

```

## **<rate> Node**

The <rate> node marks the beginning of a rate request for a specific line of business. Accordingly, this node has the required attribute, “lob”, which identifies the “line of business” for the request. In the following example, the lob attribute is set to “2” which represents “Home” insurance according to the Insbridge standard line of business mappings (see Oracle Insurance Insbridge Rating and Underwriting RateManager User Guide). The rate node attributes are defined as follows:

lob - line of business indicator per Insbridge standard lob codes (Required)

env\_def - rating environment indicator per Insbridge Framework Administrator (Optional)

As an optional feature, all other attributes provided on the <rate> node are collected as tracking attributes to be returned in the result XML document as attributes in the <result> node. This allows the original rate request to be uniquely tracked with its result XML document by any identification elements available to the calling subsystem. In the example below, the “policyId=’A1206’ ” attribute value pair would be mirrored on the <result> node of the resulting output XML.

Example:

```
<rate lob="2" policyId="A1206">
```

This rate request may be targeted to one or more rating logic instances based on what is found in the <heading> node (described) next.

## **<heading> Node**

The <heading> node serves only as a container for <program> nodes and has no attributes. If multiple <program> nodes are found in the heading node, then rating is performed for each node, if possible, and appropriate results are generated in the output XML.

Example:

```

<heading>
    <program parent_id="700" tiering_id="" program_id="24"
        program_ver="1"/>
    <program parent_id="700" tiering_id="" program_id="22"
        program_ver="1"/>
</heading>

```

## <program> Node

The <program> node specifies a specific SoftRater Package (rating engine logic instance) to run this rate request against. A program typically represents rating logic for a particular State and line of business (e.g.: Texas Auto insurance, California Home insurance). The program node attributes are defined as follows:

- parent\_id - Insbridge identifier typically assigned to a carrier for database lookup purposes (Required)
- program\_id - Insbridge identifier assigned to a program (rating engine logic instance) which represent the rating rules necessary to generate a quote. (Optional)
- program\_ver - A particular version of a program. Each version may have different rating rules, inputs, outputs, etc. (Optional)
- tiering\_id - Insbridge identifier specifying which tier to use within a program. (Optional/Required)

### Attribute requirement rules:

1. If the [tiering\\_id](#) is provided then the [program\\_ver](#) value is required and is used to select a tiering program version to be processed against the source XML.  
Example: <program parent\_id="100" tiering\_id="20" ver="1"/>
2. If the [program\\_id](#) is provided then the version [program\\_ver](#) value is used to select a program version to be processed against the source XML.  
Example: <program parent\_id="100" program\_id="100" ver="3"/>
3. If the [program\\_id](#) is provided and the [program\\_ver](#) is not, the version selection rules for the program, identified by program\_id, are used to select the program version to be processed against the source XML.  
Example: <program parent\_id="100" program\_id="100" />

The <program> node allows mapped input overrides to be specified for a specific program in a multi-program (or multi-state) rate request. See Multiple Rate Requests below for more details.

## <c> Node

The <c> (category) node marks the beginning of input data for a specific category of information (i.e.: home, car, driver, policy, etc). It has the following attributes:

- i - identifier. Zero always indicates "Policy" level inputs, other categories are user definable. (Required)
- desc - description of category (Optional)

Example: <c i="0" desc="Policy">

The "Policy" category is always a direct child of the <rate> node, except for overrides in the <program> node (described later). It is also the top-level category node. The Policy category node typically has an ID of zero (i.e.: i="0"). Item level categories are nested under the Policy category node.

For example:

```
<c i="0" desc="Policy">
  <m i="1212" n="Eff_Date" v="" />
  <m i="1214" n="PrimInsuredAge" v="" />
  <m i="1215" n="SecInsuredAge" v="" />
  <c i="5" desc="Home">
    ....
    <c i="7" desc="Scheduled Property">
      ....
    </c>
  </c>
  <c i="5" desc="Home">
    ....
  </c>
</c>
```

### **<m> Node**

The <m> (map) node represents an individual attribute-value pair mapped for a specific SoftRater Package hosted by SoftRater. In the input case, it identifies an input attribute recognized by the SoftRater Package (or Packages) listed in the <heading> node, and its associated value. The <m> node's attributes are defined as follows:

- i - input identifier (Required)
- n - name, description of input (Optional)
- v - value of input (Required)

The <m> node is always a child of a <c> (category) node and is an attribute-value pair for that specific category instance (see the Policy category example above).

## **Insbridge.XML Result Format**

---

The following is an example of an Insbridge rate request result XML document. As you can see the result XML very similar to the input XML format.

```
<result lob="2" st="6" gen_date="2/19/2009 1:55:32 PM">
  <program parent_id="900" program_id="1" program_ver="1" status="PASS">
    <c i="5">
      <m i="Dwelling_1" v="640"/>
      <m i="Dwelling_3" v="0"/>
      <m i="Dwelling_5" v="0"/>
      <m i="replcc" v="0"/>
      <m i="COV Replacement Cost Contents" v="0"/>
      <m i="COV Mortgage Payment" v="0"/>
      <m i="Dwelling_10" v="0"/>
      <m i="Dwelling_11" v="34"/>
      <m i="COV Replacement Cost - Dwelling" v="0"/>
      <m i="Dwelling_13" v="0"/>
      <m i="Dwelling_13" v="674"/>
    </c>
  </program>
</result>
```

```

    <m i="COV Business Pursuits" v="0"/>
    <m i="COV Permitted Incidental Occupancies" v="0"/>
    <m i="COV Personal Injury" v="0"/>
    <m i="Dwelling_17" v="0.02"/>
    <m i="Dwelling_18" v="0"/>
    <m i="Dwelling_19" v="0"/>
    <m i="CREDIT Multi Policy Discount" v="0"/>
    <m i="CREDIT Neighborhood Watch" v="0"/>
    <m i="CREDIT New Home" v="0.20"/>
    <m i="CREDIT New Loan" v="0.10"/>
    <m i="CREDIT Protective Devices" v="0.020000000"/>
    <m i="Dwelling_25" v="0"/>
    <m i="SEC_I C. Personal Property" v="213500"/>
    <m i="SEC_I D. Loss of Use" v="122000"/>
    <m i="SEC_I A. Dwelling" v="305000"/>
    <m i="SEC_II Personal Liability Each Occurrence" v="500000"/>
    <m i="SEC_II Medical Payments Each Person" v="2000"/>
    <m i="SEC_I B. Other Structures" v="30500"/>
    <m i="Total Annual Premium" v="674"/>
    <m i="DED Standard Deductible" v="1000"/>
    <m i="COV Replacement Cost Comp" v="1"/>
    <m i="Total Earthquake Annual Prem" v="0"/>
    <m i="EQ Loss of Use" v="25000"/>
    <m i="EQ Personal Property" v="152500"/>
    <m i="EQ Dwelling Limit" v="305000"/>
    <m i="DED Earthquake Deductible" v="30500"/>
  </c>
  <c i="0">
    <m i="SELECTED_TEIR" v="SPECIAL"/>
    <m i="Total Policy Premium" v="674"/> </c>
</program>
</result>

```

The same nodes are present in the output XML as were found in the input XML; however their meanings are slightly different. The following sections describe how to interpret the output XML.

## <result> Node

The <result> node marks the beginning of a rate request result. There is a one-to-one correspondence between <rate> nodes in the request XML to <result> nodes in the response XML. The result node attributes are defined as follows:

lob - line of business indicator corresponding to the <rate> request nodes lob attribute.  
gen\_date - server creation timestamp indicating when this response was created.

As described previously, tracking attributes on the <rate> node are returned in the result XML document as attributes in the <result> node.

Example:

```
<rate lob="2" policyId="A1206" gen_date="2/9/2009 1:50:31 PM">
```

## **<program> Node**

The result <program> node provides an XML envelope containing all of the formatted data, setup in the RateManager application as output results for the program. There can be (1-N) <program> node groups based on (1-N) program node groups requested in the input <rate> XML document. If the original <rate> request contained a tiering selection, each program version located during tiering execution will generate a <program> node in the result data. The result XML program node attributes are defined as follows:

parent_id	- Parent or Insbridge Company Identifier	(available by default)
program_id	- Selected Program Identifier	(available by default)
ver	- Selected Program Version Identifier	(available by default)
Status	- Status of program rate request	(available by default)
company_nm	- Parent Corporate name	(with AddHeading request option)
program_nm	- Program name	(with AddHeading request option)
version_nm	- Version name	(with AddHeading request option)

Example base:

```
<program parent_id='500' program_id='3' ver='2' status='PASS'>
```

Example with "AddHeading" option requested:

```
<program parent_id='200' program_id='32' ver='4' company_nm='NewCo Mutual'  
program_nm='Texas 6 Month' ver_nm='Performance' rating='A++' logo='newco.jpg'  
site='www.newco.com' status='PASS'>
```

## **<c> Node**

The <c> (category) node marks the beginning of output data for a specific category of information (i.e.: home, car, driver, policy, etc). It has the following attributes:

- i - identifier. Zero always indicates "Policy" level inputs, other categories are user defined. (available by default)
- d - description of category (with AddResultDesc request option)

Example:

```
<c i="0" d="Policy">
```

The "Policy" category is always a direct child of the <program> node. It is also typically the top-level category node. The Policy category node typically has an ID of zero (i.e.: i="0"). Item level (user defined) categories are nested under the Policy category node.

For example

```
<c i="0">  
  <m i="SELECTED_TEIR" v="SPECIAL"/>  
  <m i="Total Policy Premium" v="674"/>
```



```

    <c i="5">
      <m i="Dwelling_1" v="640"/>
      <m i="Dwelling_3" v="0"/>
      <m i="Dwelling_5" v="0"/>
      <m i="SEC_II Personal Liability Each Occurrence" v="500000"/>
      <m i="SEC_II Medical Payments Each Person" v="2000"/>
    </c>
  </c>

```

## <m> Node

The <m> (map) node represents an individual attribute-value pair mapped for a specific SoftRater Package hosted by SoftRater. In the output case, it identifies an output attribute as defined in the SoftRater Package (represented by the <program> node) and its associated value. The <m> node's attributes are defined as follows:

- i - output identifier (available by default)
- n - (name) description of output (with AddResultDesc request option)
- v - value of output (available by default)

The <m> node is always a child of a <c> (category) node and is an attribute-value pair for that specific category instance (see the category example above).

## <input> Node

The <input> node is optional. When the rate request is issued with the "AddInputs" option, this node is returned in the result XML doc. It includes the full input rate request document that was used to generate the rate result document.

Example:

```

<result lob="1" policyId="ABC1234-AUTO" gen_date="7/9/2008 1:50:31 PM">
  <inputs>
    <rate policyId="ABC1234-AUTO">
      ....
    </rate>
  </inputs>
  ...
</result>

```

## Input Overrides

By specifying input values in the <program> node within the <header> section of the input XML, those values will be used for that program when it is processed by SoftRater, regardless of whether those values are present in the body of the XML request. This allows each program found in the <header> to use the common set of inputs provided in the rate request body, and either provide additional inputs that are relevant only to that program, or provide overriding inputs values to ones found in the body, for use during rating.

Example:

```
<rate lob="1">
  <heading>
    <program parent_id="2" program_id="1" program_ver="3.00">
      <c i="0" d="Policy">
        <m i="11" n="Policy Program Specific Something " v="1029"/>
        <m i="12" n="Custom Question 1" v="XYZ"/>

        <c i="3" d="driver">
          <m i="2" n="gender" v="Female"/>
          <m i="3" n="Custom Driver Question 1" v="ABC"/>
        </c>
      </c>
    </program>
    <program parent_id="2" program_id="7" program_ver="3.00">
  </heading>
  <c i="0" d="Policy">
    <m i="11" n="Policy Program Specific Something " v="5000"/>
    <c i="3" d="driver">
      <m i="3" n="Custom Driver Question 1" v="DEF"/>
    </c>
  </c>
  </rate>
```

## Examples

---

### Single Rate Request

See Insbridge.XML Request Format and Insbridge.XML Result Format above.

### Multiple Rate Requests in a Single XML Document

It is possible to request several rates from a single XML document. These can be rates on different lines of business, across different states, and/or different SoftRater Package versions.

This simple way to do this is to combine multiple <rate> request nodes in one single root node, and submit it for rating. The root node can be anything, however in the WSI call it is always <ibdoc>.

### Multiple <rate> nodes

This request XML:

```
<ibdoc>
  <rate> ... </rate>
  <rate> ... </rate>
</ibdoc>
```

...will produce this result XML:

```

<ibdoc>
  <result> ... </result>
  <result> ... </result>
</ibdoc>

```

The root node is not returned in the result XML automatically. It must be specified in the call using the "AddRoot" attribute.

### Multiple <program> nodes

This request XML:

```

<ibdoc>
  <rate>

    <heading>
      <program> ... </program>
      <program> ... </program>
    </heading>
    <c>...</c>
  </rate>
</ibdoc>

```

...will produce this result XML:

```

<ibdoc>
  <result>
    <program>
      <c>...</c>
    </program>
    <program>
      <c>...</c>
    </program>
  </result>
</ibdoc>

```

### Multi - State Request

To rate against multiple states using one request XML document, it is recommended to follow the "Multiple <program> nodes" request model. In the following example, we are targeting two Auto programs for rating. A program typically represents a State for a specific line of business. In this example we will assume CA="21" and TX="41". As discussed earlier in Input Overrides, each program entry can specify input values to be used for that particular program.

This rate request XML:

```

<ibdoc>
  <rate lob="1">
    <heading>
      <program parent_id="2" program_id="21"> ... </program>
      <program parent_id="2" program_id="41"> ... </program>
    </heading>
  </rate>
</ibdoc>

```

```

        <c>...</c>
    </rate>
</ibdoc>

```

... will produce this result XML:

```

<ibdoc>
  <result lob="1" gen_date="2/9/2009 1:50:31 PM">
    <program parent_id="2" program_id="21">
      <c>...</c>
    </program>
    <program parent_id="2" program_id="41">
      <c>...</c>
    </program>
  </result>
</ibdoc>

```

Results for CA

Results for TX

### Multi - Line of Business Request

To rate against multiple lines of business using one request XML document, it is recommended to follow the “Multiple <rate> nodes” request model. In the following example, we are targeting two lines of business for rating, Auto and Home. The “lob” attribute in the <rate> node signifies which line of business will be rated against.

This rate request XML:

```

<ibdoc>
  <rate lob="1" > ... </rate>
  <rate lob="2" > ... </rate>
</ibdoc>

```

...will produce this result XML:

```

<ibdoc>
  <result lob="1" gen_date="2/9/2009 1:50:31 PM"> ... </result>
  <result lob="2" gen_date="2/9/2009 1:50:45 PM"> ... </result>
</ibdoc>

```

Results for Auto

Results for Home

If during the installation or configuration of the Insbridge Rating and Underwriting Solution you receive an error or need a question answered, please contact Support at [support-skywire\\_ww@oracle.com](mailto:support-skywire_ww@oracle.com).

**Address any additional inquiries to:**

**Oracle Corporation**  
World Headquarters  
500 Oracle Parkway  
Redwood Shores, CA 94065  
U.S.A.

Worldwide Inquiries:  
Phone: +1.650.506.7000  
Fax: +1.650.506.7200  
[oracle.com](http://oracle.com)

# Index

---

(  
(1-N) <program> node Groups ..... 16

---

<  
<c> Node ..... 13, 16  
<heading> Node ..... 12  
<input> Node ..... 17  
<m> Node ..... 14, 17  
<program> Node ..... 13, 16  
    Specifying Input Values ..... 17  
<rate> Node ..... 12  
<result> Node ..... 15

---

## A

Add Empty Results  
    Options ..... 9  
Add Heading  
    Options ..... 9  
Add Inputs  
    Options ..... 9  
Add Result Descriptions  
    Options ..... 9  
Add Root Node  
    Options ..... 9  
AddInputs Option ..... 17  
AddRoot  
    Attribute ..... 19  
Applications  
    Supported by Insbridge ..... 5  
ASP.NET  
    SoftRater WSI ..... 6  
Attribute  
    Rules ..... 13  
Attributes  
    AddRoot ..... 19  
    c Node ..... 13, 16  
    company\_nm ..... 16  
    d 16  
    desc ..... 13  
    env\_def ..... 12  
    gen\_date ..... 15  
    i 13, 14, 16, 17  
    Line of Business ..... 12  
    lob ..... 12, 15  
    m Node ..... 14  
    n 14, 17

parent\_id ..... 13, 16  
Program Node ..... 13, 16  
program\_id ..... 13, 16  
program\_ver ..... 13  
Rate Node ..... 12  
Results Node ..... 15  
Status ..... 16  
tiering\_id ..... 13  
Tracking ..... 12  
v 14, 17  
ver ..... 16  
version\_nm ..... 16  
Attribute-value Pair ..... 14

---

## B

Boolean Rating Arguments  
    URL Query String Arguments ..... 6

---

## C

C# Example ..... 7  
Category Node  
    Example ..... 13, 16  
    Top Level ..... 13, 16  
Category Node Nested  
    Example ..... 14, 16  
Children  
    Category Node ..... 14, 17  
    Rate Node ..... 13, 16  
company\_nm  
    Attributes ..... 16  
Concept Diagram ..... 5  
CustomXml  
    Submitting ..... 6

---

## D

d  
    Attribute ..... 16  
Data  
    Handling Out of System ..... 9  
    SoftRater Interaction ..... 5  
desc  
    Attribute ..... 13  
Diagram  
    Concept ..... 5  
doInXSL Option ..... 6



---

**M**

Map Node	
Children .....	14, 17
Microsoft Internet Information Server	
SoftRater WSI .....	6
Microsoft SQL Server	
SoftRater .....	5
Multiple <rate> Nodes .....	20
Example .....	18
Multiple Line of Business Request	
Example .....	20
Multiple Program Nodes	
Example .....	19
Multiple Rate Request	
Example .....	18
Multiple State Request	
Example .....	19

---

**N**

n	
Attribute .....	14, 17
Node	
Category .....	13, 16
Heading .....	12
Input .....	17
Map .....	14, 17
Program .....	13, 16
Rate .....	12
Result .....	15

---

**O**

Options	
MapRequest SOAP .....	10
Rating Integration .....	9
Output Data	
Marking Beginning .....	16
Output Format	
InsbridgeRate.XML .....	6
Output XML Document .....	11
OutputErrorXPathLoc	
Identifier .....	10
OutputMappingIdentifier	
Identifier .....	10
OutputMappingStateful	
Identifier .....	10
OutputMappingType	
Identifier .....	10
OutputSchema	
Identifier .....	10

---

**P**

parent_id	
Attributes .....	13, 16
Policy Category	
Children .....	13, 16
Processing	
Data In and Out of System .....	10
SoftRater Engine .....	6
Program	
Identifier .....	10
Program Node	
Example .....	16
Program Node w/Heading Option Request	
Example .....	16
Program Nodes	
In Header .....	12
program_id	
Attributes .....	13, 16
Example .....	13
Rules .....	13
program_ver	
Attributes .....	13
Proxy Classes	
Generating .....	6

---

**R**

Rate Node	
Example .....	12
Rate Request	
Node to Mark Beginning .....	12
Rate Request Document .....	11
Rate Request Result	
Marking Beginning .....	15
Rating	
Multiple Lines of Business .....	20
Multiple States .....	19
Rating Arguments .....	9
Rating Integration	
Options .....	9
Rating Request Response XML .....	11
Request XML	
Result Nodes .....	15
Requirements	
Rate Node .....	12
Result Documents	
Setting Options .....	9, 10
Result Node	
Example .....	15
Output XML .....	12
Root Level	
Error Node Created .....	10
Rules	
Attribute .....	13



---

## *S*

Setting Options	
Result Documents.....	9, 10
Several Rates	
Requesting.....	18
Single Rate Request	
Example.....	18
SOAP	
Options.....	10
Supported Operations.....	6
SoftRater	
Basic Functionality.....	5
Engine Perform.....	5
Input Overrides.....	17
SoftRater Engine	
Processing.....	6
Rating Arguments.....	9
SoftRater Web Service.....	6
SoftRater WSI	
Processing XML Data.....	10
Software	
Integration.....	6
Status	
Attributes.....	16
Submitting	
Rate Requests via XML.....	11
Subscriber	
Identifier.....	10
Support.....	21
Supported Operations.....	6

---

## *T*

Tiering Selection.....	16
tiering_id	
Attributes.....	13
Rules.....	13
Tracking	
Attributes.....	12

---

## *U*

URL Arguments	
Available.....	6

---

## *V*

v	
Attribute.....	14, 17
ver	
Attributes.....	16
Version	
Identifier.....	10
version_nm	
Attributes.....	16
Visual Basic Example.....	7

---

## *W*

Web Service Interface.....	6
Web Service Interface ASP Page.....	6
Web Services.....	7
Web Services - LiteWeight.....	7
WSDL Documents.....	6
WSI.....	6

---

## *X*

XML	
Insbridge.....	11
Usage in SoftRater.....	11
Usage in SoftRater WSI.....	6
XML Data	
Out of System.....	9
XML Document	
Example.....	11
Multiple Rate Requests.....	18
XML Envelope.....	16