

Oracle Utilities Mobile Workforce Management

Installation Guide

Release 2.1.0 Service Pack 4

E26614-06

October 2012/ updated March 2013

E26614-06

Copyright © 2000, 2013, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS

Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle America, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third party content, products and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third party content, products or services.

Contents

Contents

Preface	i-i
Audience	i-i
Related Documents	i-i
Conventions	i-i
Chapter 1	
Overview	1-1
Installation Overview	1-1
Chapter 2	
Application Architecture Overview	2-1
Application Architecture	2-1
Tier 1: Desktop/Client, or Presentation Tier	2-1
Tier 2: Mobile Client Tier	2-1
Tier 3: Web Application / Business Application Server, or Business Logic Tier	2-1
Tier 4: Database, or Persistence Tier	2-1
Chapter 3	
Supported Platforms and Hardware Requirements	3-1
Software and Hardware Considerations	3-1
Requirements by Tier	3-2
Tier 1, Desktop: Software and Hardware Requirements	3-2
Tier 2, Mobile Client: Software and Hardware Requirements	3-3
Tier 3, Web/Business Application Server: Software and Hardware Requirements	3-3
Tier 4, Database Server: Software and Hardware Requirements	3-4
Supported Platforms	3-4
Operating Systems and Application Servers	3-4
Platform Changes	3-5
Oracle Database Servers	3-5
Application Dependencies for Oracle Business Intelligence for Utilities	3-5
Support for Software Patches and Upgrades	3-5
Chapter 4	
Planning the Installation	4-1
Installation and Configuration Overview	4-2
Before You Install	4-3
Before You Upgrade	4-3
Installation Checklist	4-3
Prerequisite Third-Party Software Overview	4-4
Application Framework Installation and Configuration Worksheets	4-4
Installation Menu Functionality Overview	4-4
Installation Menu Functionality Details	4-4
Third Party Software Configuration	4-5

Environment Installation Options	4-8
Environment Description.....	4-11
WebLogic Business Application Server Configuration.....	4-12
WebLogic Web Application Server Configuration.....	4-13
Database Configuration	4-17
General Configuration Options.....	4-20
Advanced Menu Options.....	4-22
Oracle Real-Time Scheduler Installation and Configuration Worksheets.....	4-31
JMS Configuration	4-32
ORS Environment Description.....	4-34
Geocode Data Source Configuration	4-35
Mapviewer Configuration.....	4-35
Security Configuration.....	4-36
Chapter 5	
Installing the Database	5-1
Chapter 6	
Installing Application Server Prerequisite Software.....	6-1
AIX 6.1 Application Server.....	6-2
Supported Application Servers	6-2
Web/Application Server Tier.....	6-2
Oracle Linux or Red Hat Linux Application Server	6-6
Supported Application Servers	6-6
Web/Application Server Tier.....	6-6
Solaris 10 Application Server.....	6-10
Supported Application Servers	6-10
Web/Application Server Tier.....	6-10
Windows 2008 Application Server	6-14
Supported Application Servers	6-14
Web/Application Server Tier.....	6-14
Chapter 7	
Installing the Application Server Component of Oracle Utilities Application Framework.....	7-1
Installation Overview.....	7-1
Preinstallation Tasks	7-2
Hardware and Software Version Prerequisites.....	7-2
Database Installation	7-2
Installation Prerequisites	7-2
System Architecture Overview	7-2
Copying and Decompressing Install Media	7-2
Set Permissions for the cistab File in UNIX	7-3
Installing Oracle Utilities Application Framework.....	7-3
Brief Description of the Installation Process	7-3
Detailed Description of the Installation Process	7-4
Installing Oracle Utilities Application Framework Service Pack1	7-7
Copying and Decompressing Install Media	7-7
Upgrade Installation	7-8
Chapter 8	
Installing the Application Server Component of Oracle Real-Time Scheduler.....	8-1
Preinstallation Tasks	8-1
Installing Prerequisite Patches	8-1
Copying Map files	8-1
Copying and Decompressing Install Media	8-2
Preparing for the Installation	8-2
Installing the Application	8-2

Security Considerations	8-5
Installing User Documentation	8-5
Installing Stand-Alone Online Help	8-5
Operating the Application	8-6
Postinstallation Tasks	8-6
Chapter 9	
Installing the Application Server Component of Oracle Utilities Mobile Workforce Management	9-1
Preinstallation Tasks	9-1
Installing Prerequisite Patches	9-1
Copying and Decompressing Install Media	9-1
Preparing for the Installation	9-2
Installing the Application	9-2
Security Considerations	9-3
Installing User Documentation	9-3
Installing Stand-Alone Online Help	9-3
Operating the Application	9-4
Upgrade Installation	9-4
Installing Service Packs and Patches	9-4
Chapter 10	
Installing the Mobile Client	10-1
Installing the Mobile Client on Windows	10-1
Installing on Windows XP or Windows 7	10-1
Installing on Windows Mobile	10-1
Mobile Device Registration	10-2
Uninstalling the Mobile Client	10-2
Installing the Mobile Client on Android	10-2
Overview of the Android MCP	10-3
Installing the Android MCP	10-3
Launching Android MCP	10-6
Launching Android MCP Tools	10-6
Uninstalling Android MCP	10-7
Chapter 11	
Additional Tasks	11-1
Configuring MapViewer	11-1
Configuring MapViewer Security	11-2
Oracle Location Services (eLocation)	11-3
Configuring the Environment for Oracle BPEL Server	11-4
Configuring the Scheduler	11-4
Building the wfullclient.jar File Using ANT	11-6
Configuring the Batch Scheduler for Different Servers	11-7
Configuring Business Service SDK	11-8
WebLogic Production Server Considerations	11-8
Configuring Identity and Trust	11-8
Building Javadoc Indexes	11-9
Configuring the Environment for Batch Processing	11-9
Customizing Configuration Files	11-9
Customizing the Logo	11-10
Generating the Application Viewer	11-10
Installation Verification Checklist	11-11
Accessing the Application	11-11
Appendix A	
Common Maintenance Activities	A-1

Appendix B

Application Framework Prerequisite Patches	B-1
---	------------

Appendix C

License and Copyright Notices	C-1
Third Party Products.....	C-1
Notice concerning usage of ANTLR and Classycle	C-1
Notice concerning usage of Apache Software.....	C-1
Notice concerning usage of ASM.....	C-4
Notice concerning usage of Concurrent	C-5
Notice concerning usage of dom4j	C-5
Notice concerning usage of International Components for Unicode (ICU4J)	C-6
Notice concerning usage of Jaxen	C-6
Notice concerning usage of JCIP Annotations	C-7
Notice concerning usage of XStream	C-10
Notice concerning usage of slf4j	C-11
Notice concerning usage of Perl.....	C-11
Notice concerning usage of Mime-Base64 Perl Module.....	C-13
Notice concerning usage of Mime-Lite Perl Module	C-13
Notice concerning usage of DBD::DB2 Perl Module	C-13
Notice concerning usage of DBI Perl Module.....	C-14

Preface

This guide describes how to install Oracle Utilities Mobile Workforce Management.

This preface contains these topics:

- **Audience**
- **Related Documents**
- **Conventions**

Audience

Oracle Utilities Mobile Workforce Management Installation Guide is intended for system administrators installing Oracle Utilities Mobile Workforce Management.

To complete this installation you should have:

- Experience installing and configuring application servers and other software
- Administrative privileges on the host where you are installing the software

Related Documents

For more information, see these Oracle documents:

- *Oracle Utilities Mobile Workforce Management Quick Install Guide*
- *Oracle Utilities Mobile Workforce Management Database Administrator's Guide*

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.

Convention	Meaning
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

Chapter 1

Overview

This chapter provides an overview of the installation of Oracle Utilities Mobile Workforce Management.

Note: This service pack is intended to be installed on top of an existing Oracle Utilities Mobile Workforce Management installation. Please refer to the **Readme.txt** file included with the release package for information about installing this service pack.

Installation Overview

Installing Oracle Utilities Mobile Workforce Management involves the following steps:

1. Review the different tiers of the application architecture as described in **Chapter 2: Application Architecture Overview**.
2. Understand the hardware requirements for installing the application and the supported platforms for the application and database servers as described in **Chapter 3: Supported Platforms and Hardware Requirements**.

Note: The installation and administration of the database server tier is described in detail in the document Oracle Utilities Mobile Workforce Management *Database Administrator's Guide*.

3. Plan your installation as described in **Chapter 4: Planning the Installation**.
4. Install the database as described in the document Oracle Utilities Mobile Workforce Management *Database Administrator's Guide*.
5. Install all required third-party software as described in **Chapter 6: Installing Application Server Prerequisite Software**. The required software is listed for each supported combination of operating system and application server.
6. Install the framework for the application as described in **Chapter 7: Installing the Application Server Component of Oracle Utilities Application Framework**.
7. Install Oracle Real-Time Scheduler as described in **Chapter 8: Installing the Application Server Component of Oracle Real-Time Scheduler**.
8. Install Oracle Utilities Mobile Workforce Management as described in **Chapter 9: Installing the Application Server Component of Oracle Utilities Mobile Workforce Management**.
9. Install the Mobile Client for Oracle Utilities Mobile Workforce Management on mobile devices as described in **Chapter 10: Installing the Mobile Client**.
10. Follow the installation guidelines described in **Chapter 11: Additional Tasks**.

Chapter 2

Application Architecture Overview

This section provides an overview of the Oracle Utilities Mobile Workforce Management application architecture.

Application Architecture

The Oracle Utilities Mobile Workforce Management application is deployed on multiple tiers.

Please see the Oracle Utilities Mobile Workforce Management *Server Administration Guide* for a more detailed description of the application architecture and individual tiers.

Tier 1: Desktop/Client, or Presentation Tier

This tier is implemented in a browser-based client. Users use a desktop client web browser to log in to and use the Oracle Utilities Mobile Workforce Management application. Note also that a desktop machine running Microsoft Windows and the Oracle client is required to perform some of the Oracle Utilities Mobile Workforce Management installation steps.

Tier 2: Mobile Client Tier

This tier is implemented on mobile computers such as laptops and handhelds. Users can install the mobile client software to use the mobile functionality of Oracle Utilities Mobile Workforce Management.

The current release of Oracle Utilities Mobile Workforce Management supports a mobile client for laptops running Windows XP or Windows 7, and mobile devices running Windows Mobile 6.5 Professional or Android Mobile 2.3.

Tier 3: Web Application / Business Application Server, or Business Logic Tier

This tier is implemented in a web application or business application server. The business application component can be installed as part of the web application server, or as a separate component. Except where explicitly noted, most of the Oracle Utilities Mobile Workforce Management installation documentation assumes that the web application and business application servers reside together.

Tier 4: Database, or Persistence Tier

This tier is implemented in a database server. The database server stores data maintained by the Oracle Utilities Mobile Workforce Management application. More specifically, the database tier contains the data server files and database executables that physically store the tables, indexes, and other database objects for your system.

Chapter 3

Supported Platforms and Hardware Requirements

This section gives an overview of the tiers on which the product is implemented, and shows each of the operating system/server combinations that the product is certified for. It includes:

- **Software and Hardware Considerations**
- **Requirements by Tier**
- **Supported Platforms**
- **Support for Software Patches and Upgrades**

Software and Hardware Considerations

There are many factors that can influence software and hardware decisions. For example, your system may have to satisfy specific performance, availability, or scalability requirements, or to support running in a language other than English. These business requirements, together with the chosen system architecture, should be used in initial software and hardware planning.

Some of the questions that you should answer before beginning the installation include:

- On which hardware platform and operating system will Oracle Utilities Mobile Workforce Management be deployed?
 - On which web server product will Oracle Utilities Mobile Workforce Management deploy?
 - On which database product will Oracle Utilities Mobile Workforce Management deploy?
 - Do you plan to deploy multiple Oracle Utilities Mobile Workforce Management instances on the same physical server?
 - How do you plan to deploy Oracle Utilities Mobile Workforce Management?
 - Web/application/database on the same physical server
 - Web/application on one server and database on separate server
 - Each component on its own server
- Note:** If you deploy the mobility application and web application on different servers, the log file path should be shared on the network.
- How do you plan to install and update the Oracle Utilities Mobile Workforce Management mobile client on the mobile computers or devices?
 - Use a device management software like Oracle Mobile Server for installation and updates.

- How do you plan to secure Oracle Utilities Mobile Workforce Management when communicating with devices over unsecured networks like the internet?

For detailed descriptions of various deployment architecture choices that may aid in planning, please see the document *Oracle Utilities Application Framework Architecture Guidelines*, available on My Oracle Support (Article ID 807068.1).

The final hardware and software decisions must comply with the specific requirements of Oracle Utilities Mobile Workforce Management, as described in the rest of this chapter.

Requirements by Tier

The application is deployed on multiple Tiers:

- Tier 1, Desktop
- Tier 2, Mobile Client
- Tier 3, Web/Business Application Server
- Tier 4, Database Server

Tier 1, Desktop: Software and Hardware Requirements

Configuration	Processor	Memory (RAM)	Monitor Display
Minimum	Pentium IV - 2.0 GHz	1024 MB	1024X768** 16-bit Color
Recommended*	Pentium IV - 3.0+ GHz, Or any Core 2 Duo Or any Athlon X2	2048 MB	1280X1024* 32-bit Color

* The Recommended configuration will support better performance of the client.

** To reduce the amount of scrolling required for pages that are longer than 768 or 1024 pixels, consider placing a monitor into vertical position (with narrow side on the bottom).

Web Browser Requirements

The following operating system / web browser software is supported:

- Windows XP SP3 or higher with Internet Explorer 7.x or 8.x
- Windows 7 (32-bit or 64-bit) with Internet Explorer 8.x
- Java plug-in 1.6.0 17

Tier 2, Mobile Client: Software and Hardware Requirements

The following hardware configuration is supported:

Configuration	Processor	Memory (RAM)
Minimum	Pentium IV - 2.0 GHz	1024 MB

The following Operating Systems are supported by the mobile client:

- Windows XP
- Windows 7 (64-bit)
- Windows Mobile 6.5 Professional
- Android 2.3

Note: This release of Oracle Utilities Mobile Workforce Management has been tested on a Motorola MC75 device running Windows Mobile 6.5 Professional, a Panasonic Toughbook 30 running Windows XP SP2, and an HTC Desire device running Android client Mobile 2.3.

Tier 3, Web/Business Application Server: Software and Hardware Requirements

Please consult the **Supported Platforms** on page 3-4 to determine which web application servers can be used with the operating system that will be hosting this tier.

The recommendations that follow are based on a standard installation with both the application and business servers on the same machine and the system running with the default values. The minimum resource requirements exclude third-party software installation requirements. Refer to the third-party vendors for specific requirements. The following sizing excludes the Oracle database server installation.

Memory Requirements

For each application server environment a minimum of 4 GB of real memory is required, plus 6 GB of swap space.

Disk Space Requirements

The approximate disk space requirements in a standard installation are as follows:

Location	Size	Usage
\$SPLEBASE	5 GB minimum	This location is where the application and Framework get installed. Startup, shutdown and other online log files are stored here. The size and space that is used should be monitored because various debugging options can significantly affect the size of log files.
\$SPLAPP	2 GB minimum	This location is used for storing batch log files and output from batch jobs. The size of this space should be influenced by which batches are run and how often, and the amount of debugging information that is collected.

Location	Size	Usage
Location of the application web work files on the web servers	1.5 GB minimum	This location is used by the various web server vendors to expand the application. It should be considered when installing these products. Refer to the individual web server documentation to determine the location of the temporary files.
Installation temporary area	4 GB	The application gets installed from this location. You need enough space to uncompress the files and install the application.
Oracle data area	4 GB minimum	This location is where the Oracle database data files are stored. The size of this space should be based on the requirements of the production environment. For an initial or demo database install 4 GB should be sufficient.

Tier 4, Database Server: Software and Hardware Requirements

See the section **Supported Platforms** on page 3-4 for supported database servers.

Supported Platforms

The installation has been tested and certified to operate on many operating system, application server, and database server combinations. For the software requirements for each of these combinations, see **Chapter 6: Installing Application Server Prerequisite Software** for more information.

Operating Systems and Application Servers

The following table details the operating system and application server combinations on which this version of Oracle Utilities Mobile Workforce Management has been tested and certified.

Operating System and Web Browser (Client)	Operating System (Server)	Chipset	Application Server	Database
Windows XP SP3 (IE 7.x, 8.x)	AIX 6.1 TL4 (64-bit)	POWER 64-bit	WebLogic 10.3.6	Oracle 11.2.0.1
	Oracle Linux 5.6, 5.8, or 6.2 (64-bit)	x86_64	WebLogic 10.3.6	Oracle 11.2.0.1
	Red Hat Enterprise Linux 5.6, 5.8, or 6.2 (64-bit)			
Windows 7 (IE 8.x)	Sun Solaris 10 Update 8 (64-bit)	SPARC	WebLogic 10.3.6	Oracle 11.2.0.1
	Windows Server 2008 R2 (64-bit)	x86_64	WebLogic 10.3.6	Oracle 11.2.0.1

Platform Changes

Oracle Utilities Mobile Workforce Management 2.1.0 no longer requires the Oracle Spatial database option to operate properly. While this release supports Oracle Spatial, additional installation steps have been added which allow the application to run against a database without this option, including Oracle Standard Edition.

Oracle Database Servers

This version of Oracle Utilities Mobile Workforce Management is supported with Oracle Database Server 11.2.0.1 on all of the operating systems listed above.

The Oracle 11.2.0.1 client is required for this version of the database server.

The following Oracle Database Server Editions are supported:

- Oracle Database Server Standard Edition
- Oracle Database Server Enterprise Edition

Application Dependencies for Oracle Business Intelligence for Utilities

When using Oracle Utilities Mobile Workforce Management version 2.1.0.4 with Oracle Business Intelligence for Utilities, you must upgrade to Oracle Utilities Advanced Spatial and Operational Analytics version 2.4.0 Service Pack 4. This release is not compatible with previous releases of Oracle Utilities Advanced Spatial and Operational Analytics. For more information, see the release notes and installation documentation for Oracle Utilities Advanced Spatial and Operational Analytics, version 2.4.0 Service Pack 4.

Support for Software Patches and Upgrades

Due to the ongoing nature of software improvement, vendors will issue patches and service packs for the operating systems, application servers and database servers on top of specific versions that Oracle Utilities Mobile Workforce Management has been tested with.

If it is necessary to apply an upgrade, please do so in a test environment that is running on the same platform as your production environment prior to updating the Oracle Utilities Mobile Workforce Management production environment.

The exception from this rule is Hibernate software version 3.3.2 ga. This version should not be upgraded.

Always contact Oracle Utilities Mobile Workforce Management support prior to applying vendor updates that do not guarantee backward compatibility.

Chapter 4


Planning the Installation

This chapter provides information for planning an Oracle Utilities Mobile Workforce Management installation, including:

- **Installation and Configuration Overview**
- **Before You Install**
- **Before You Upgrade**
- **Installation Checklist**
- **Prerequisite Third-Party Software Overview**
- **Application Framework Installation and Configuration Worksheets**
- **Oracle Real-Time Scheduler Installation and Configuration Worksheets**

Installation and Configuration Overview

The following diagram provides an overview of the steps that need to be taken to install and configure Oracle Utilities Mobile Workforce Management:



Before You Install

Refer to My Oracle Support for up-to-date additional information about installing Oracle Utilities Mobile Workforce Management.

For frequently asked questions and troubleshooting information during installation of the application and database components of Oracle Utilities Mobile Workforce Management, refer to articles 1475032.1 and 1475013.1 on My Oracle Support.

Before You Upgrade

The new MCP version control enhancement requires that a certain upgrade process be followed. This is to ensure that no data is lost and no incompatible version issues arise.

The upgrade process includes the following steps:

1. All mobile devices should end their shifts and log off.
2. Upgrade the server and all MDTs.
3. Regenerate all deployments.

For more information about this enhancement and upgrade considerations, see Chapter 11, “Deploying the Application to Mobile Devices,” in the *Oracle Utilities Mobile Workforce Management Configuration Guide*.

Installation Checklist

The following checklist will help guide you through the installation process of the application tier. The details for each step are presented in subsequent chapters.

Note: Please make sure that you follow the order listed below.

1. Create Group/User ID.
2. Install prerequisite software (see **Prerequisite Third-Party Software Overview** on page 4-4 for more information).
 - Oracle Client 11.2.0.1 (for connecting to Oracle database)
 - Java 6
 - Hibernate 3.3.2
 - JDeveloper 11g (11.1.1.4.0+)

Note: You can choose to install either JDeveloper or Oracle Application Developer Framework (ADF). Do **NOT** install JDeveloper if you plan to install and use Oracle ADF.

 - MapViewer 11.1.1.5.1
 - Map data
 - Oracle BPEL Process Manager 11g (optional)
3. Install application server.
 - Oracle WebLogic 11gR1 (10.3.4+)
 - wllfullclient.jar
4. Install Oracle Application Development Framework (ADF) 11g (11.1.1.4.0+). Ensure the version of Oracle ADF is compatible with the version of Weblogic installed.

Note: You can choose to install either JDeveloper or Oracle Application Developer Framework (ADF). Do **NOT** install Oracle ADF if JDeveloper is already installed.

5. Verify that all software is installed.
6. Set up environment variables.
7. Install Oracle Utilities Application Framework.
8. Install Oracle Real-Time Scheduler.
9. Install MapViewer 11.1.1.5.1.
10. Install Oracle Utilities Mobile Workforce Management.
11. Deploy the Oracle Utilities Mobile Workforce Management application.
12. Perform Post installation tasks.

Prerequisite Third-Party Software Overview

For complete details about installing and configuring the prerequisite third-party software for your specific platform, see **Chapter 6: Installing Application Server Prerequisite Software**.

Application Framework Installation and Configuration Worksheets

Installation Menu Functionality Overview

The main configuration menu is structured so that related variables and/or options are grouped together and are associated by a menu item number. To access a particular group of variables and options, enter the menu item number associated with that group. Each option within that group is displayed in turn on the screen, along with a prompt so that you can type the desired value for the option, if it is not the same as the default or current value.

When performing the initial installation you need to go through all menu options. The menu options may have a default value, a list of valid values and a validation check.

On each option prompt you can keep the current value by simply leaving the input line empty. In order to erase a variable value you need to enter one dot ("."). The leading spaces will be trimmed out on each values entered.

Note: When working with the menu you will see the following:

- **Valid Values: [ALFANUM].** This indicates you will need to enter an alphanumeric value in the prompt.
- **Valid Values: [NUM].** This indicates you will need to enter an numeric value in the prompt.

When all options are set, type <P> at the main menu prompt option. This will save the option values selected throughout the configuration.

During this processing the global variables are validated and the configuration file <SPLEBASE>/etc/ENVIRON.INI is created or updated. This file contains all the variables inputted and calculated. These are needed by the next part of the installation process.

To exit the configuration utility without saving any of the values entered, type <X> and 'Enter'

Installation Menu Functionality Details

The Environment Installation Utility requires that Oracle Client Home is set in the path for the user performing the installation.

Prior to running the installation utility you will need to review the supported platforms document to ensure you have all of the Third Party software installed.

In this menu if the variables are set prior to execution, that value will be defaulted by the installation utility when performing the installation.

When the installation has been completed successfully, the values will be written to an ENVIRON.INI file. When splenviron.sh / cmd is executed, it will read from the ENVIRON.INI file to set the environment variables.

In the worksheets there are three different types of values given:

- Default Values are the values that will be defaulted when running the installation utility.
- Security Values denote values that should be changed when in production.
- Example Values are values that can be used for a default installation.

Note: The production environment should not be run with default values. See the Oracle Utilities Mobile Workforce Management *Server Administration Guide* for additional information about configuring these values.

When you enter passwords you will not see the password characters on the screen because they are entered in silent mode. Passwords are encrypted when the values are entered.

Install the Oracle Client software specified in the section **Supported Platforms** prior to running any of the installation utilities.

The following prompt will appear when executing the installation utility:

Enter Oracle Client Home Directory (<ENTER> quit):

Note: If the environmental variable ORACLE_CLIENT_HOME is set, the install script will validate the variable. If it passes the validation you will not be prompted for it. This is needed in order to run Perl installation utilities.

Encryption Methods

When the application server choice is WebLogic, the Oracle Utilities Application Framework installation uses the Oracle WebLogic API to encrypt the User ID and password that perform admin functions for the WebLogic application servers. Please refer to the Oracle WebLogic documentation for further information about the encryption.

The Oracle Utilities Application Framework installation also uses industry standard cryptography to encrypt passwords that are prompted within the installation.

In each case these password are entered in the command line but the inputted values are not reflected on the screen when performing the installation.

Third Party Software Configuration

```
*****
* Environment Installation Options *
*****
1. Third Party Software Configuration
   Oracle Client Home Directory:
   Web Java Home Directory:
   Child JVM Home Directory:
   COBOL Home Directory:
   Hibernate JAR Directory:
   ONS JAR Directory:
   Database Home Directory:
   Web Application Server Home Directory:
   ADF Home Directory:
   OIM OAM Enabled Environment:
```

Menu Option	Name Used in Documentation	Usage	Customer Install Value
Oracle Client Home Directory	ORACLE_CLIENT_HOME***	The home directory of the Oracle Client. The application will use the Perl included under this Oracle Client. Example Location: /oracle/client/product/11.2.0.1	
Web Java Home Directory	JAVA_HOME***	Java home that will be used by the web application server. Example Location: /ouaf/java/jdk1.6.0_20	
Child JVM Home Directory	CHILD_JVM_JAVA_HOME	Java home that will be used by the child java process that handles COBOL related requests. Example Location: /ouaf/java/jdk1.6.0_20 Note: This value is optional for MWM 2.1.0 because it contains no COBOL components. Press Enter to skip this value.	
COBOL Home Directory	COBDIR	COBOL installation location directory. Example Location: /opt/SPLcobAS51WP6 Note: This value is optional for MWM 2.1.0. Press Enter to skip this value.	
Hibernate JAR Directory	HIBERNATE_JAR_DIR***	Location on the disk where the hibernate3.jar is installed. Example Location: Unix: /ouaf/Hibernate Install Dir Windows: C:\ouaf\Hibernate Install Dir\	
*ONS JAR Directory	ONS_JAR_DIR	Location on the disk where the ons-11.2.0.2.jar file is installed. **Required for Oracle RAC installation. See the Server Administration Guide for more information.	

Menu Option	Name Used in Documentation	Usage	Customer Install Value
Database Home Directory	DATABASE_HOME** *	Location on the disk where database client is installed for your particular installation. Example Location for Oracle Database: /oracle/client/product/11.2.0.1 Note: This value will be the same as the previously entered for Oracle.	
Web Application Server Home Directory	WEB_SERVER_HOME***	Location on the disk where the application server is installed. Example Location: WebLogic: /ouaf/middleware/ wlserver_10.3 To validate the home directory, check if the following jar files exist in the appropriate path: \$WEB_SERVER_HOME/server/lib/ weblogic.jar %WEB_SERVER_HOME%\server\lib\ weblogic.jar	
* ADF Home Directory	ADF_HOME***	Location on the disk where JDeveloper or ADF is installed. Example Location: /ouaf/jdev11_1_1_4 or /adf_location	
OIM OAM Enabled Environment	OPEN_SPML_ENABLED_ENV	Denotes if an environment will be integrating with Oracle Identity Manager for user propagation. Valid values: true false Defaulted value: false	

* Denotes optional Menu Options that may be required for the product installation and variables.

** In order to activate the RAC FCF, the application needs the external ons.jar file, version 11.2.0.2. This ons.jar is located under the Oracle Database Software 11.2.0.2, at the following path:

\$ORACLE_HOME/opmn/lib/ons.jar

The ons.jar should be copied to the Application Server. During the OUAF installation the relevant option should be populated with the folder location of the ons.jar.

*** Denotes mandatory field options that are required for the product installation.

Environment Installation Options

50. Environment Installation Options

Environment Mount Point:
 Log Files Mount Point:
 Environment Name:
 Database Type:
 Web Application Server Type:
 Install Application Viewer Module:

Menu Option	Name Used in Documentation	Usage	Customer Install Value
Environment Mount Point	<SPLDIR> ***	<p>The mount point into which the application is installed. For example: /ouaf for UNIX and C:\ouaf for Windows.</p> <p>This mount point MUST exist and the MWM administrator user ID MUST be able to write to this directory. (This is the user ID that is created specifically to administer the (MWM) environments; the default is cissys). The installation sets permissions on all subdirectories installed under this directory.</p> <p>See <SPLENVIRON> below for more information on how this mount point is used.</p>	
Log File Mount Point	<SPLDIROUT>***	<p>A mount point that will contain any application output or application logs. Example value is /ouaf/sploutput for UNIX installation or C:\ouaf\sploutput for Windows.</p> <p>This mount point MUST exist and the MWM administrator user ID MUST be able to write to this directory. (This is the user ID that is created specifically to administer the (MWM) environments; the default is cissys).</p> <p>For each environment initialized, the application logs will be written to the directory <SPLDIROUT>/<SPLENVIRON></p> <p>Note: Later in the installation the splenvron.sh (splenvron.cmd) script will set the \$SPLOUTPUT (%SPLOUTPUT%) environment variable to point to:<SPLDIROUT>/<SPLENVIRON></p>	

Menu Option	Name Used in Documentation	Usage	Customer Install Value
Environment Name	<SPLENVIRON>***	<p>A descriptive name to be used as both a directory name under the mount point <SPLDIR> and an environment descriptor. This value typically identifies the purpose of the environment. For example, DEV01 or CONV.</p> <p>On installation a directory <SPLDIR>/<SPLENVIRON> is created, under which the Oracle Utilities Application Framework and Oracle Utilities Mobile Workforce Management software resides.</p> <p>When multiple environments are set up on the machine you will typically have directories such as: /ouaf/DEV01/.... /ouaf/CONV/....</p> <p>Each of these contains a complete version of the Oracle Utilities Application Framework and Oracle Utilities Mobile Workforce Management.</p> <p>Note: Later in the installation process, the splenviron.sh (splenviron.cmd) script will set \$SPLEBASE (%SPLEBASE%) environment variable to point to <SPLDIR>/<SPLENVIRON></p>	
Database Type	<CMPDB>***	<p>Type of a database to connect an environment to.</p> <p>Valid values: oracle: Oracle</p> <p>Defaulted value: oracle</p> <p>Note: Not all database types are supported on all platforms; refer to the Supported Platforms section for details.</p>	oracle
Web Application Server Type	<SPLWAS>***	<p>A web application server for the environment to be used. The following value must be selected:</p> <p>Valid values: WLS: WebLogic WAS: WebSphere WASND: WebSphere ND</p> <p>Note: Not all web application servers are supported on all platforms; refer to Supported Platforms section for details.</p>	

Menu Option	Name Used in Documentation	Usage	Customer Install Value
Installation Application Viewer Module	<WEB_ISAPVIEWER>***	<p>Denotes if the Application Viewer Web Module will be installed in the environment. When this value is set to false the application viewer will not be accessible in the environment.</p> <p>Valid values:</p> <ul style="list-style-type: none">true: Application Viewer module will be installed.false: Application Viewer module will not be installed. <p>Defaulted value: true</p> <p>Note: When the value of false is selected, the Application Viewer will only be installed at a later date by a complete reinstall of the application.</p>	

Environment Description

1. Environment Description

Environment Description:

Menu Option	Name Used in Documentation	Usage	Customer Install Value
Environment Description	DESC***	This is a free form text field to describe the purpose of the environment.	

WebLogic Business Application Server Configuration

The WebLogic parameters below and in the worksheet are for a WebLogic installation.

2. Business Application Server Configuration

```

Business Server Host:                <machine_name>
WebLogic Server Name:                myserver
Business Server Application Name:    SPLService
MPL Admin Port Number:
MPL Automatic startup:                false
  
```

Menu Option	Name Used in Documentation	Usage	Customer Install Value
Business Server Host	BSN_WLHOST***	The host name on which business application server resides. Default value: <current server name>	
WebLogic Server Name	BSN_WLS_SVRNAME***	The name of the WebLogic server where the business application resides. Default value: myserver Note: If there is not a previously created WebLogic server, take the default value of “myserver”.	
Business Server Application Name	BSN_APP***	The name of the business application server. Default value: SPLService	
MPL Admin Port number	MPLADMINPORT	The port number for the Multi Purpose Listener (MPL) Admin Server. Example value: 6502	
MPL Automatic Startup	MPLSTART	Automatically starts the MPL Listener whenever environment starts. Default value: false	

WebLogic Web Application Server Configuration

The WebLogic parameters below and in the worksheet are for a WebLogic installation.

3. Web Application Server Configuration

```

Web Server Host:                                     <machine_name>
Web Server Port Number:
Web Context Root:
WebLogic JNDI User ID:
WebLogic JNDI Password:
WebLogic Admin System User ID:
WebLogic Admin System Password:
WebLogic Server Name:                               myserver
Web Server Application Name:                         SPLWeb
Application Admin User ID:
Application Admin Password:
Expanded Directories:                               true
Application Viewer Module:                           true
  
```

Menu Option	Name Used in Documentation	Usage	Customer Install Value
Web Server Host	WEB_WLHOST***	The host name on which the web application server resides. Default value: <current server name>	
Web Server Port Number	WEB_WLPORT***	A unique port number within the system that will be assigned to the HTTP port. This is the port number that is used as a part of the client URL request to connect to the host. Example value: 6500	
Web Context Root	WEB_CONTEXT_ROOT***	A context root name that allows customers to run multiple instances of web application on the same server. Default value: ouaf Once the application is up, you can access it using http://<host>:<port>/ouaf	
WebLogic JNDI User ID	WEB_WLSYSUSER***	The user ID the application uses to connect to the EJB component through JNDI. This is the EJB container user ID. Note: The required value for an initial installation is "system". This is a security value.	

Menu Option	Name Used in Documentation	Usage	Customer Install Value
WebLogic JNDI Password	WEB_WLSYSPASS***	<p>The password the application uses to connect to the EJB component through JNDI</p> <p>Note: The required value for an initial installation is “ouafadmin”. This value will be saved in encrypted format.</p> <p>This is a security value.</p>	
WebLogic Admin System User ID	WLS_WEB_WLSYSUSER***	<p>The user ID to log in to the Oracle WebLogic console and to administer Oracle WebLogic. The Oracle WebLogic startup and stop script also utilizes this user ID</p> <p>Note: The installation utility will prompt you to enter “Y” to encrypt. For an initial installation, enter Y/y and specify the required value “system”.</p> <p>This is a security value.</p>	
WebLogic Admin System Password	WLS_WEB_WLSYSPASS***	<p>The password to login to Oracle WebLogic console and to administer Oracle WebLogic. The Oracle WebLogic startup and stop script also utilize this password.</p> <p>Note: The installation utility will prompt you to enter “Y” to encrypt. For an initial installation, enter Y/y, and specify the required value “ouafadmin”.</p> <p>This is a security value.</p>	
WebLogic Server Name	WEB_WLS_SERVERNAME	<p>The name of the WebLogic server where the web application resides.</p> <p>Default value: myserver</p> <p>Note: For an initial installation, use the default value of “myserver”.</p> <p>.</p>	
Web Server Application Name	WEB_APP	<p>The name of the web application server.</p> <p>Default value: SPLWeb</p> <p>Note: For an initial installation, use the default value of “SPLWeb”.</p>	

Menu Option	Name Used in Documentation	Usage	Customer Install Value
Application Admin User ID	WEB_SPLUSER***	<p>This is the default user ID to login to the application through the browser.</p> <p>Example value: SYSUSER</p> <p>Note: The required value for an initial installation is “SYSUSER”. This value is also used in communication within the XAI application.</p> <p>This is a security value.</p>	
Application Admin Userid Password	WEB_SPLPASS***	<p>This is the password of the application admin user.</p> <p>Example value: sysuser00</p> <p>Note: The required value for an initial installation is “sysuser00”. This value will be saved in encrypted format</p> <p>This is a Security Value.</p>	
Expanded Directories	WEB_ISEXPANDED**	<p>When the value is “true” the web application will be deployed in exploded directory format (no WAR files).</p> <p>When the value is “false”, the web application will be deployed in ear file format.</p> <p>Valid values: true: Environment expanded (no WAR files) false: Environment with WAR/EAR files</p> <p>Default value: false</p>	

Menu Option	Name Used in Documentation	Usage	Customer Install Value
Application Viewer Module	WEB_ISAPPVIEWER**	<p>When the value is “true” the application viewer will be deployed to the web server. When the value is “false”, the application viewer will not be deployed to the web Server.</p> <p>Note: With either value the application viewer module will still be managed by the upgrade process.</p> <p>Note: When this value is set to false from the initial install menu you will not be able to change this value to true to re-enable the application viewer.</p> <p>Valid values: true: The application viewer module will be deployed to the web server false: The application viewer module will not be deployed to the web server</p> <p>Default value: true</p>	

Database Configuration

4. Database Configuration

Web Application Database User ID:
 Web Application Database Password:
 MPL Database User ID:
 MPL Database Password:
 XAI Database User ID:
 XAI Database Password:
 Batch Database User ID:
 Batch Database Password:
 Database Name
 Database Server:
 Database Port:
 ONS Server Configuration:
 Database Override Connection String:
 Oracle Client Character Set NLS_LANG: AMERICAN_AMERICA.AL32UTF8

Menu Option	Name Used in Documentation	Usage	Customer Install Value
Web Application Database User ID	DBUSER***	<p>The database user ID that has been configured on the database for the web application server connection.</p> <p>This is a security value.</p>	
Web Application Database Password	DBPASS***	<p>The database password that has been configured on the database for the web application connection.</p> <p>Note: This value will be saved in encrypted format.</p> <p>This is a security value.</p>	
MPL Database User ID	MPL_DBUSER***	<p>The database user ID that has been configured on the database for the MPL server connection.</p> <p>This is a security value.</p>	
MPL Database Password	MPL_DBPASS***	<p>The database password that has been configured on the database for the MPL server connection.</p> <p>Note: This value will be saved in encrypted format.</p> <p>This is a security value.</p>	
XAI Database User ID	XAI_DBUSER***	<p>The database user ID that has been configured on the database for the XAI server connection.</p> <p>This is a security value.</p>	

Menu Option	Name Used in Documentation	Usage	Customer Install Value
XAI Database Password	XAI_DBPASS***	<p>The database password that has been configured on the database for the XAI server connection.</p> <p>Note: This value will be saved in encrypted format.</p> <p>This is a security value.</p>	
Batch Database User ID	BATCH_DBUSER***	<p>The database user ID that has been configured on the database for the batch connection.</p> <p>This is a security value.</p>	
Batch Database Password	BATCH_DBPASS***	<p>The database password that has been configured on the database for the batch connection.</p> <p>Note: This value will be saved in encrypted format.</p> <p>This is a security value.</p>	
Database Name	DBNAME***	The name of the database instance that the application will be connecting to.	
Database Server	DBSERVER***	Host name of the server where database resides.	
Database Port	DBPORT***	Database port number on the database server used for connecting to the database	
ONS Server Configuration	ONSCONFIG	<p>ONS Server Configuration is required for Oracle RAC FCF.</p> <p>See the Server Administration Guide for more information.</p> <p>This is an optional value.</p>	

Menu Option	Name Used in Documentation	Usage	Customer Install Value
Database Override Connection String	DB_OVERRIDE_CONNECTION	<p>This connection string can be used to override the database information entered above for RAC installation.</p> <p>Set this string to override the standard database connection string, as entered above.</p> <p>Example: jdbc:oracle:thin:@(DESCRIPTION = (LOAD_BALANCE=on) (ADDRESS = (PROTOCOL = TCP)(HOST = dbhost1) (PORT = dbport1)) (ADDRESS = (PROTOCOL = TCP)(HOST = dbhost2) (PORT = dbport2)) (CONNECT_DATA = (SERVER = DEDICATED) (SERVICE_NAME = databasename)))</p> <p>See the Server Administration Guide for more information.</p> <p>This is an optional value.</p>	
Oracle Client Character Set NLS_LANG	NLS_LANG***	<p>The Oracle Database Character Set.</p> <p>Select the Language and Territory that are in use in your country.</p> <p>Default value: AMERICAN_AMERICA.AL32UTF8</p>	

General Configuration Options

Note: See the Oracle Utilities Mobile Workforce Management *Batch Server Administration Guide* for additional details on this configuration.

5. General Configuration Options

```
Batch RMI Port:
Batch Mode: CLUSTERED
Coherence Cluster Name:
Coherence Cluster Address:
Coherence Cluster Port:
Coherence Cluster Mode: dev
```

Menu Option	Name Used in Documentation	Usage	Customer Install Value
Batch RMI Port	BATCH_RMI_PORT** *	Unique port used by the Batch RMI. Make sure that this port is free to use.	
Batch Mode	BATCH_MODE***	Valid values: CLUSTERED or DISTRIBUTED DISTRIBUTED - allows numerous threads from numerous jobs to be execute by one or more JVMs. CLUSTERED - provides same facilities as DISTRIBUTED mode and uses the Named Cache and Work Manager facilities in Oracle Coherence. Default value: CLUSTERED Note: CLUSTERED is currently the only supported mode for production environments.	
Coherence Cluster Name	COHERENCE_CLUSTER_NAME***	Unique name for the batch CLUSTER Note: Value is required when batch mode is CLUSTERED.	
Coherence Cluster Address	COHERENCE_CLUSTER_ADDRESS***	Unique multicast address. Note: Value is required when batch mode is CLUSTERED.	
Coherence Cluster Port	COHERENCE_CLUSTER_PORT' ***	Unique port for the batch CLUSTER Make sure that this port is free to use. Note: Value is required when batch mode is CLUSTERED.	

Menu Option	Name Used in Documentation	Usage	Customer Install Value
Coherence Cluster Mode	COHERENCE_CLUSTER_MODE**	<p>Valid values: dev (Development) prod (Production)</p> <p>Default value: dev During non-production activities not involving a cluster, the mode should be set to dev For production and environments where clustering is required (for cluster testing) the mode should be set to prod</p>	

Advanced Menu Options

The advanced menu options are not available during installation. These options can be accessed after installation using the following commands:

Unix:

```
$SPLEBASE/bin/configureEnv.sh -a
```

Windows

```
%SPLEBASE%\bin\configureEnv.cmd -a
```

Advanced Environment Miscellaneous Configuration

50. Advanced Environment Miscellaneous Configuration

```
Online JVM Batch Server Enabled:           false
Online JVM Batch Number of Threads:        5
Online JVM Batch Scheduler Daemon Enabled:  false
JMX Enablement System User ID:
JMX Enablement System Password:
RMI Port number for JMX Business:
RMI Port number for JMX Web:
GIS Service Running on the same Web Server: true
GIS Service URL:
GIS WebLogic System User ID:
GIS WebLogic System Password:
Online Display Software Home:
```

Menu Option	Name Used in Documentation	Usage	Customer Value Install
WebSphere Deployment Manager Host Name	WASND_DMGR_HOST	WebSphere Deployment Manager Host name, this value is used for WebSphere ND, when connecting to the WebSphere Deployment Manager. Note: This value will only appear for WebSphere ND.	
Online JVM Batch Server Enabled	BATCHENABLED	When starting a web application server JVM, this property can be set to “true” to allow the on-line application server to also act as a batch worker in the grid. Default value: false Note: This functionality should only be used in low volume environments.	

Menu Option	Name Used in Documentation	Usage	Customer Value Install
Online JVM Batch Number of Threads	BATCHTHREADS	<p>The maximum number of batch processing threads to be executed within a worker JVM when no explicit Distributed Thread Pool is specified. The “DEFAULT” distributed thread pool is used by the batch-scheduling daemon when it initiates processing on batch jobs (typically added via the online system) where no thread pool is specified).</p> <p>Default value: 5</p> <p>Note: This will be only used and activated when BATCHEENABLED is set to true.</p>	
Online JVM Batch Scheduler Daemon Enabled	BATCHDAEMON	<p>In a distributed batch environment, this property can be set to “true” to allow a worker JVM to host the batch scheduling daemon. The daemon accepts online batch submissions requests and automatically submits the work for them.</p> <p>Valid values: true, false</p> <p>Default value: false</p> <p>Note: This will be only used and activated when BATCHEENABLED is set to true.</p>	
JMX Enablement System User ID	BSN_JMX_SYSUSER	<p>Example value: user</p> <p>This value is optional.</p>	
JMX Enablement System Password	BSN_JMX_SYSPASS	<p>Example value: admin</p> <p>Note: This value will be saved in encrypted format.</p> <p>This value is optional.</p>	
RMI Port number for JMX Business	BSN_JMX_RMI_POR T_PERFORMACE	<p>JMX Port for business application server monitoring.</p> <p>This needs to be set to an available port number on the machine.</p> <p>This value is optional.</p>	

Menu Option	Name Used in Documentation	Usage	Customer Value Install
RMI Port number for JMX Web	WEB_JMX_RMI_PORT_PERFORMANCE	<p>JMX Port for web application server monitoring</p> <p>This needs to be an available port number for the environment running on the machine.</p> <p>This value is optional.</p>	
GIS Service Running on the same Web Server	GIS	<p>Geographical information (GEOCODING) - GIS Service running on the same web application server</p> <p>Valid values: true, false</p> <p>This value is optional.</p>	
GIS Service URL	GIS_URL	<p>This is the URL of the external web server.</p> <p>Note: This value will be only be used when GIS is set to true.</p> <p>This value is optional.</p>	
GIS WebLogic System User ID	GIS_WLSYSUSER	<p>GIS WebLogic System User ID</p> <p>Note: This value will be only be used when GIS is set to true.</p> <p>This value is optional.</p>	
GIS WebLogic System Password	GIS_WLSYSPASS	<p>GIS WebLogic System Password.</p> <p>Note: This value will be only be used when GIS is set to true.</p> <p>This value is optional.</p>	
Online Display Software Home	ONLINE_DISPLAY_HOME	<p>The location of the Online Display Software installation directory.</p> <p>This value is optional.</p>	

Advanced Environment Memory Configuration

```

51. Advanced Environment Memory Configuration
    JVM Child Memory Allocation:                    512
    JVM Child Additional Options:
    Web Application Java Initial Heap Size:          1024
    Web Application Java Max Heap Size:              1024
    Web Application Java Max Perm Size:              700
    Web Application Additional Options:
    Ant Min Heap Size:                              200
    Ant Max Heap Size:                              800
    Ant Additional Options:
    Thread Pool Worker Java Min Heap Size:          512
    Thread Pool Worker Java Max Heap Size:          1024
    Thread Pool Worker Java Max Perm Size:          768
    Thread Pool Worker Additional Options:
    Additional Runtime Classpath:
    Release Cobol Thread Memory Options:
-Dspl.runtime.cobol.remote.releaseThreadMemoryAfterEachCall=...

```

Menu Option	Name Used in Documentation	Usage	Customer Install Value
JVM Child Memory Allocation	JVMMEMORYARG	<p>Heap size for the JVM Child.</p> <p>Default value: 512</p> <p>This option is not applicable to MWM.</p>	
JVM Child Additional Options	JVM_ADDITIONAL_OPT	<p>Additional JVM options that are passed to the Child JVM.</p> <p>Note: For WebLogic installation only.</p> <p>This option is not applicable to MWM.</p>	
Web Application Java Initial Heap Size	WEB_MEMORY_OPT_MIN***	<p>Minimum heap size for the application server.</p> <p>Default value: 1024</p> <p>Note: For WebLogic installation only. Recommended value is 2048.</p>	
Web Application Java Max Heap Size	WEB_MEMORY_OPT_MAX***	<p>Maximum heap size for the application server.</p> <p>Default value: 1024</p> <p>Note: For WebLogic installation only. Recommended value is 2048.</p>	

Menu Option	Name Used in Documentation	Usage	Customer Install Value
Web Application Java Max Perm Size	WEB_MEMORY_OPT _MAXPERMSIZE***	<p>Maximum Perm Size for the application server.</p> <p>Default value: 700MB (Linux, Solaris) 700MB (Windows)</p> <p>Note: For WebLogic installation only. Recommended value: 1024MB</p>	
Web Application Additional Options	WEB_ADDITIONAL_ OPT***	<p>Additional options that will be passed in to the web application server JVM.</p> <p>Note: For WebLogic installation only.</p> <p>Replace the value of SPLEBASE or %SPLEBASE% with the actual environment value.</p> <p>UNIX: -Xrs -XX:+ShowMessageBoxOnError - XX:+UseGCOverheadLimit - Doracle.security.jps.config=\$SPLEBASE/ splapp/config/jps-config.xml - Ddomain.home=\$SPLEBASE/splapp</p> <p>Windows: -Xrs -XX:+ShowMessageBoxOnError - XX:+UseGCOverheadLimit - Doracle.security.jps.config=%SPLEBASE %/splapp/config/jps-config.xml - Ddomain.home=%SPLEBASE%/splapp</p> <p>AIX: -Xrs -XX:+ShowMessageBoxOnError - XX:+UseGCOverheadLimit - Doracle.security.jps.config=\$SPLEBASE/ splapp/config/jps-config.xml - Ddomain.home=\$SPLEBASE/splapp - Djava.awt.headless=true</p>	
Ant Min Heap Size	ANT_OPT_MIN	<p>Minimum Heap Size passed to ANT JVM.</p> <p>Default value: 200</p>	
Ant Max Heap Size	ANT_OPT_MAX	<p>Maximum Heap Size passed to ANT JVM.</p> <p>Default value: 800</p>	
Ant Additional Options	ANT_ADDITIONAL_ OPT	Additional options that are passed into the ANT JVM.	

Menu Option	Name Used in Documentation	Usage	Customer Install Value
Thread Pool Worker Java Min Heap Size	BATCH_MEMORY_OPT_MIN	Minimum heap size passed to the Thread Pool Worker. Default value: 512 Recommended value is 1024.	
Thread Pool Worker Java Max Heap Size	BATCH_MEMORY_OPT_MAX	Maximum heap size passed to the Thread Pool Worker. Default value: 1024 Recommended value is 2048.	
Thread Pool Worker Java Max Perm Size	BATCH_MEMORY_OPT_MAXPERMSIZE	Maximum perm size passed to the Thread Pool Worker Default value: 768	
Thread Pool Worker Additional Options	BATCH_MEMORY_ADDITIONAL_OPT	Additional Memory Options passed into the Thread Pool Worker. This is an optional free form field.	
Additional Runtime Classpath	ADDITIONAL_RUNTIME_CLASSPATH***	Additional Classpath Options passed in when starting the WebLogic JVM Note: For WebLogic installation only. Replace the value of \$SPLEBASE or %SPLEBASE% with the actual value. Unix: \$SPLEBASE/splapp/standalone/lib/commons-cli-1.1.jar;\$SPLEBASE/splapp/standalone/lib/log4j-1.2.15.jar Windows: %SPLEBASE%/splapp/standalone/lib/commons-cli-1.1.jar;%SPLEBASE%/splapp/standalone/lib/log4j-1.2.15.jar	
Release Cobol Thread Memory Options	REL_CBL_THREAD_MEM	Allow for child JVMs to be optionally configured to release thread-bound memory when each thread is returned to its thread pool. This will increase the number of memory allocations and memory free calls performed by the Microfocus runtime. It will also lower the amount of C-heap memory consumed by child JVMs. Valid values: true, false Default value: false	

Advanced Web Application Configuration

52. Advanced Web Application Configuration

```

WebLogic SSL Port Number:
WebLogic Console Port Number:
WebLogic Additional Stop Arguments:
Strip HTML Comments: false
Authentication Login Page Type: FORM
Web Form Login Page: /loginPage.jsp
Web Form Login Error Page: /formLoginError.jsp
Web Security Role: cisusers
Web Principal Name: cisusers
This is a development environment: false
Preload All Pages on Startup: false
Maximum Age of a Cache Entry for Text: 28800
Maximum Age of a Cache Entry for Images: 28800
JSP Recompile Interval (s): 43200

```

Menu Option	Name Used in Documentation	Usage	Customer Install Value
WebLogic SSL Port Number:	WEB_WLSSPORT	<p>The port number assigned to WebLogic Secure Sockets connection. This is the port number that is used for Secure Sockets connecting to the WebLogic server.</p> <p>The Secure Sockets implementation is disabled in the default configuration.</p> <p>For Production additional actions are required. Do NOT run Production with Demo certificates Refer to the WLS installation guide - Configuring Identity and Trust When this value is populated http will be disabled.</p> <p>Example value: 6501</p> <p>Note: For WebLogic installation only. This value is optional. If you enable the SSL port, then the https port is enabled and http port is disabled by default.</p>	
WebLogic Console Port Number	WLS_ADMIN_PORT	<p>The port number assigned to WebLogic Console connection. This is the port number that is used for Secure Sockets connecting to the WebLogic Console server.</p> <p>Note: For WebLogic installation only.</p> <p>This value is optional.</p>	

Menu Option	Name Used in Documentation	Usage	Customer Install Value
WebLogic Additional Stop Arguments	ADDITIONAL_STOP_WEBLOGIC***	<p>WebLogic Additional Stop Arguments</p> <p>This value is required when running the WebLogic Console Port Number and the Application using SSL.</p> <p>Example values: -Dweblogic.security.TrustKeyStore=DemoTrust -Dweblogic.security.TrustKeystoreType=CustomTrust</p> <p>Note: For Production additional actions are required. Do NOT run Production with Demo certificates</p> <p>Refer to the WLS installation guide - Configuring Identity and Trust</p> <p>Note: For WebLogic installation only. This is an optional value.</p> <p>If you enable the WebLogic console port number using the Advanced Web Application Configuration menu, then you should specify the WebLogic additional stop argument.</p>	
StripHTMLComments: false	STRIP_HTML_COMMENTS	<p>Stripping HTML (and JavaScript) comments will increase the security of the system.</p> <p>Default value: false</p> <p>Valid values: true, false</p>	
Authentication Login Page Type	WEB_WLAUTHMETHOD	<p>Specifies which authentication mode should be used. To switch off OUA Login Page enter: BASIC</p> <p>Valid values: FORM, BASIC</p> <p>Default value: FORM</p>	
Web Form Login Page	WEB_FORM_LOGIN_PAGE	<p>Specify the jsp file used to login into the application.</p> <p>Default value: /loginPage.jsp</p>	
Web Form Login Error Page	WEB_FORM_LOGIN_ERROR_PAGE	<p>Specify the jsp file used when there is an error when logging into the application.</p> <p>Default value: /formLoginError.jsp</p>	

Menu Option	Name Used in Documentation	Usage	Customer Install Value
Web Security Role	WEB_PRINCIPAL_NAME	Specify the name of the security role. Default value: cisusers	
Web Principal Name	WEB_PRINCIPAL_NAME	Specify the name of a principal that is defined in the security realm. Default value: cisusers	
This is a development environment	WEB_ISDEVELOPMENT	<p>If the value is “true”, the web application may be used for application development, which will trigger certain generation processes. If the value is “false” the environment will be used as a runtime environment.</p> <p>When you choose “true” (development environment) the startup preload pages will be disabled, and the application security will be less strict. This value also controls the amount of logging information written to the application log files.</p> <p>Valid values: true, false</p> <p>Default value: false</p>	
Preload All Pages on Startup	WEB_PRELOADALL	<p>This controls if the pages should be pre-loaded during the startup of the application or not.</p> <p>Valid values: true, false</p> <p>Default value: false</p>	
Maximum Age of a Cache Entry for Text	WEB_MAXAGE	Default value: 28800	
Maximum Age of a Cache Entry for Images	WEB_MAXAGEI	Default value: 28800	
JSP Recompile Interval (s)	WEB_wlpageCheckSeconds	Default value: 43200	

Advanced Web Application Configuration

OIM Configuration Settings

```

53. OIM Configuration Settings
    SPML SOAP Trace Setting:                false
    SPML IDM Schema Name:                   F1-IDMUser
    SPML OIM Name Space:                    http://xmlns.oracle.com/OIM/provisioning
    SPML OIM Enclosing Element:             sOAPElement
  
```

Menu Option	Name Used in Documentation	Usage	Customer Install Value
SPML SOAP Trace Setting	OIM_SPML_SOAP_DEBUG_SETTING	Name of Oracle Identity Manager library for debug Default value: false Valid values: true, false	
SPML IDM Schema Name	OIM_SPML_UBER_SCHEMA_NAME	Name of Oracle Identity Manager library for schema Default value: F1-IDMUser	
SPML OIM Name Space	OIM_SPML_NAME_SPACE	Default Namespace for Oracle Identity Manager integration Default value: http://xmlns.oracle.com/OIM/provisioning	
SPML OIM Enclosing Element	OIM_SPML_SOAP_ELEMENT	Default top level SOAP Element name for Oracle Identity Manager integration Default value: sOAPElement	

Oracle Real-Time Scheduler Installation and Configuration Worksheets

During the installation and configuration of the application you will need to provide a variety of system values. These worksheets will assist you in providing that information. They should be completed before installing Oracle Real-Time Scheduler and Oracle Utilities Mobile Workforce Management, as described in **Chapter 8: Installing the Application Server Component of Oracle Real-Time Scheduler** and **Chapter 9: Installing the Application Server Component of Oracle Utilities Mobile Workforce Management**. No Customer Install Value fields should be left blank.

Note: Some web application server information will not be available until the software installation steps have been completed as described in **Chapter 6: Installing Application Server Prerequisite Software**.

JMS Configuration

8. JMS Configuration

```
Context Factory:          weblogic.jndi.WLInitialContextFactory
WebLogic Server URL:
Weblogic System User ID:
Weblogic System Password:
Time Out:                  120000
```

Menu Option	Name Used In Documentation	Usage	Customer Install Value
Context Factory	CONTEXTFACTORY* **	JNDI Name attribute field when the Connection Factory object is created. When the Connection Factory object is loaded, JNDI provides a path to the object. Default: weblogic.jndi.WLInitialContextFactory	
WebLogic Server URL	URL***	Specify weblogic server URL in below format: t3://<host>:<web server port no> NOTE: This is the port number that is used as a part of the client URL request to connect to the host. If you enable the WebLogic console port number using the Advanced Web Application Configuration menu, then specify WebLogic server URL in the following format: t3s://<host>:<weblogic console port number> Otherwise: t3://<host>:<web server port no>	
Weblogic System User ID	WLS_USERID***	User ID to login to Admin WebLogic console. Default user ID: system	

Menu Option	Name Used In Documentation	Usage	Customer Install Value
Weblogic System Password	WLS_PASSWORD***	On the configuration step of Oracle Utilities Mobile Workforce Management install process you have to provide the same password given during Oracle Utilities Application Framework installation. This should only be done if you have changed the password on an existing system following the Oracle WebLogic instructions.	
Time Out	TIMEOUT***	JMS Configuration Timeout, in milliseconds. Default:120000	

ORS Environment Description

9. ORS Environment Description

ORS Scheduler Map Files Location:

Schedule Manager Port Number:

Minimum Requests:

1

Maximum Time (seconds) Booking Requests:

5

Unique identifier for
the instance of the JVM:

Registry cleanse timing in seconds:

900

Scheduler connection timeout in milliseconds

300000

Menu Option	Name Used In Documentation	Usage	Customer Install Value
ORS Scheduler Map Files Location	MAPDIR***	Location for Map files from where scheduler will read the maps. For example: Unix: /ouaf/mapdir Windows: C:\ouaf\mapdir	
Schedule Manager Port Number	IPCSTARTPORT***	Specify the starting port number on which the application will communicate with the scheduler processes. The application will look for any available port above this number. Default: 9100	
Minimum Requests	MINREQUESTS***	Minimum request that scheduler can handle. Default: 1	
Maximum Time (seconds) Booking Requests	MAXPROCESSINGTIME***	Maximum request that scheduler can handle. Default: 5	
Unique identifier for the instance of the JVM	NODEID***	Unique id for JVM instance. For Example: Node1 Note: This has to be same as the Node ID configured in the Scheduler table in the Oracle Utilities Mobile Workforce Management application. This should be left empty if scheduler is going to be run from the standalone batch program.	
Registry cleanse timing in seconds	CLEANSE_INTERVAL***	This is the registry cleanse interval. Default: 900	
Scheduler connection timeout in milliseconds	SCHED_CONN_TIMEOUT***	Scheduler connection timeout in milliseconds. Default: 300000	

Geocode Data Source Configuration

10. Geocode Data Source Configuration
 JDBC URL for the
 Geocode database:
 Database User Name:
 Database Password:
 JNDI name for the
 Geocode datasource:

Menu Option	Name used in this Documentation	Usage	Customer Install Value
JDBC URL for Geocode Database	DBURL_GEOCODE* **	Geocode database information details. For example: jdbc:oracle:thin:@localhost:1521:GEODB	
Database User Name	DBUSER_GEOCODE ***	Geocode database user ID.	
Database Password	DBPASS_GEOCODE* **	Geocode database password.	
JNDI name for the Geocode datasource	JNDI_GEOCODE***	JNDI name for accessing the database. For example: GEOSAMPLE	

Mapviewer Configuration

11. Mapviewer Configuration
 Deploy mapviewer locally on this instance: true
 Location of mapviewer ear file:

Menu Option	Name used in this Documentation	Usage	Customer Install Value
Deploy mapviewer locally on this instance	MAPVIEWER_ISLOCAL***	Set this value to true for deploying mapviewer on the same WebLogic instance. Default: true	
Location of mapviewer ear file	MAPVIEWER_EAR** *	This needs to point to the location of the exploded mapviewer ear directory in case mapviewer is deployed locally on the same Weblogic instance. For example: /ouaf/mapviewer/mapviewer.ear	

Security Configuration

12. Security Configuration

Deploy only mobility web application: false

Menu Option	Name used in this Documentation	Usage	Customer Install Value
Deploy only mobility web application	MOBILITY_APP_ON LY***	Set this value to true to deploy only the mobility web application. This option can be used to expose just the mobility web application to the internet while the rest of the application runs inside a secured environment. Default: false	

Chapter 5

Installing the Database

Please review Chapter 1 of this guide and then follow the steps for installing the database as described in the Oracle Utilities Mobile Workforce Management *Database Administrator's Guide*.

Chapter 6

Installing Application Server Prerequisite Software

This chapter describes the software that needs to be installed for each of the supported operating system and application server combinations. The sections for this chapter are:

- **AIX 6.1 Application Server**
- **Oracle Linux or Red Hat Linux Application Server**
- **Solaris 10 Application Server**
- **Windows 2008 Application Server**

AIX 6.1 Application Server

This section describes the software requirements for operating the application using the AIX application server.

Supported Application Servers

Operating System	Chipsets	Application Server
AIX 6.1 (64-bit) TL4	POWER 64-bit	Oracle WebLogic 11gR1 (10.3.4) 64-bit version

Web/Application Server Tier

AIX 6.1 TL4 Operating System Running on Power5 and Power6 Architecture

UNIX Administrator User ID

The following user groups and accounts have to be created to install and administer the application:

Description	Default Value	Customer Defined Value
Oracle Utilities Mobile Workforce Management Administrator User ID	cissys	
Oracle Utilities Mobile Workforce Management User Group	cisusr	

Note: It is recommended that you change the default values for security reasons.

Throughout this document the administrator user id is often referred to as the "cissys" user id. You should substitute that with the customer defined user id when not using the default value. After the initial install, the software should always be managed using that user id.

By default, the cissys userid is the only one given access to the installed files.

1. Create a group called cisusr (user group).
2. Create a user called cissys. Primary group cisusr. Set the primary shell for the cissys user to Korn Shell.
3. Set the stack size limit to 50 MB or more in the user profile startup script for cissys user:

```
ulimit -s 51200
```
4. Set the desired hard/soft limit of the file handler for cissys user to 4096 or higher.

The shell scripts use the ">" to overwrite shell functionality. Your operating system may be configured to not allow this functionality by default in the users shell.

To avoid file access permission problems when executing scripts, consider placing the following command into cissys profile script:

```
set +o noclobber
```

Security Configuration

Various options exist to secure a system. In this application all files will be created with the minimum permissions required to ensure that group-readable, group-writable and group-executable files will have the correct user groups and to restrict the permissions available to legitimate users. In this way, a low privileged end user cannot directly edit configuration files and thereby bypass application security controls.

The following users and group categories must be defined to implement this security. For demonstration purposes the following users and groups will be used. These users must be created according to industry standards (including password policies). All users should be created with a default umask of 022 to ensure files created during normal operation have the correct permissions.

Please replace these users and groups for your installation defaults:

User	Group	Description
cissys	cisusr	This user will be used to install the application and to apply patches. This user will own all the application files. The same care should be taken with this user ID as if it is 'root'. This user will be able to add, delete and modify files within the application.
cisadm	cisusr	Administrative and Operation functions will be available to this user. This user will be able to stop and start the application and batch processes, but will not have access to modify any file other than generated log files
cisoper	-----	Low level operator. This user will only be able to read logs files and collect information for debugging and investigative purposes. Care should be taken in production to disable debugging as debugging information could contain potential sensitive data which this user should not have privy to.

Note: The Oracle Client and WebLogic should be installed as the user who will stop and start the application. For example, if you plan to run the application as the install user these components must belong to cissys.

Oracle Client 11.2.0.1 — Runtime Option

Install the Oracle Client as described in the Oracle Client installation documentation. Use the cissys account to install the Oracle Client. If another user installs the Oracle Client, make sure the cissys user ID has the proper execute permissions.

For the cissys user ID, ensure that the environment variable ORACLE_CLIENT_HOME is set up, and that ORACLE_CLIENT_HOME/perl/bin is the first Perl listed in the cissys account's PATH variable.

IBM Java Software Development Kit version 6.0 SR8 64-bit

Installation of Java is a prerequisite for using Oracle WebLogic as a web application server.

At the time of release, AIX Java packages could be obtained from:

<http://www.ibm.com/developerworks/java/jdk/aix/service.html>

The web server requires the 64-bit Java platform in order to function. The main prerequisite for the web server is the version of java mentioned above.

For the Administrator userid (cissys), ensure that the environment variable JAVA_HOME is set up, and that "java" can be found in cissys' PATH variable.

Hibernate 3.3.2

You must install Hibernate before installing Oracle Utilities Mobile Workforce Management.

Download the file hibernate-3.3.2.ga.zip (the zip file associated with the 3.3.2 GA release.) from the following link:

<http://sourceforge.net/projects/hibernate/files/hibernate3/3.3.2.GA/>

It is very important that you download the exact version, as the product has only been certified with this exact release.

You will need to create a permanent directory to place one of the files from hibernate-distribution-3.3.2.GA-dist.zip. (e.g., /opt/hibernate).

Extract the file hibernate3.jar into the newly created directory (e.g., /opt/hibernate) from the hibernate-distribution-3.3.2.GA-dist.zip file.

Oracle WebLogic 11gR1 (10.3.4+) 64-bit

Oracle WebLogic software can be downloaded from the Oracle web site. This application server will run as a 64-bit application.

- Download and install 64-bit Java (as documented above) before installing WebLogic.
- Download and install WebLogic Server 11gR1 (10.3.4+).

Note: For an easy and quick installation of Oracle Weblogic please use silent mode. For more information, refer to http://docs.oracle.com/cd/E13196_01/platform/docs81/install/silent.html#1044118

Oracle JDeveloper 11g (11.1.1.4.0+) Studio Edition

JDeveloper 11g (11.1.1.4.0) Studio Edition is supported on any platform that runs JDK 6. It requires Oracle Weblogic Server 10.3.4+. It must be installed prior to installing the Oracle Utilities Application Framework.

Oracle JDeveloper can be downloaded from following link:

<http://www.oracle.com/technology/software/products/jdev/index.html>

Note: For an easy and quick installation of Oracle JDeveloper, please use silent mode. For more information, refer to http://docs.oracle.com/cd/E16764_01/install.1111/e13666/ojdig.htm#CHDCDFEA

Oracle Application Developer Framework (ADF) 11g (11.1.1.4.0+)

Oracle ADF 11g (11.1.1.4.0+) requires Oracle Weblogic Server 10.3.4+ and it must be installed prior to installing ADF.

Oracle ADF can be downloaded from the following link:

<http://www.oracle.com/technetwork/developer-tools/adf/downloads/index.html>

Note: Make sure to only use the version of Oracle ADF certified with Weblogic server.

Oracle MapViewer 11g (11.1.1.5.1)

Oracle Fusion Middleware MapViewer 11g Release 1 (11.1.1.5.1) is a tool that renders maps showing different kinds of spatial data. It can be downloaded from the following link:

<http://www.oracle.com/technetwork/middleware/products/mapviewer/downloads/index-100641.html>

Download mapviewer.ear from this link.

Oracle BPEL Process Manager 11gR1

Oracle BPEL Process Manager is optional software and is required only for SMS dispatching functionality. Oracle BPEL Process Manager 11gR1 is a component of Oracle SOA Suite 11gR1. The Oracle BPEL Process Manager version is determined by your SMS gateway application. You can download SOA Suite 11gR1 from the SOA Suite download page at the following link:

<http://www.oracle.com/technology/products/soa/soasuite/collateral/downloads.html#11g>

GCC 4.2.4

GCC 4.2.4 libraries need to be installed for the scheduler functionality to work properly. The following GCC runtime libraries are required to be installed:

- `libgcc` : GCC compiler dynamic runtime library
- `libstdc++` : G++ compiler dynamic runtime library

After installing the GCC runtime libraries, copy the following libraries to `<INSTALL_DIR>/runtime` directory:

- `libstdc++.a`
- `libgcc_s.a`

Alternately, you can add these libraries to `LD_LIBRARY_PATH` environment variable.

wlfullclient.jar

Please refer to **Building the wlfullclient.jar File Using ANT** in Chapter **Additional Tasks** for more information.

Oracle Linux or Red Hat Linux Application Server

This section describes the software requirements for operating the application using the Oracle Linux or Red Hat Linux application server.

Supported Application Servers

Operating System	Chipsets	Application Server
Oracle Linux 5.6, 5.8, or 6.2 (64-bit) Red Hat Enterprise Linux 5.6 (64-bit)	x86_64	Oracle WebLogic 11gR1 (10.3.6) 64-bit version

Web/Application Server Tier

Oracle Linux 5.6 or Red Hat Enterprise Linux 5.6 Operating System Running on x86_64 64-bit Architecture

UNIX Administrator User ID

The following user groups and accounts have to be created to install and administer the application:

Description	Default Value	Customer Defined Value
Oracle Utilities Mobile Workforce Management Administrator User ID	cissys	
Oracle Utilities Mobile Workforce Management User Group	cisusr	

Note: It is recommended that you change the default values for security reasons.

Throughout this document the administrator user id is often referred to as the "cissys" user id. You should substitute that with the customer defined user id when not using the default value. After the initial install, the software should always be managed using that user id.

By default, the cissys userid is the only one given access to the files installed.

1. Create a group called cisusr (user group)
2. Create a user called cissys. Primary group cisusr. Set the primary shell for the cissys user to Korn Shell.
3. Set the stack size limit to 50 MB or more in the user profile startup script for cissys user:

```
ulimit -s 51200
```
4. Set the desired hard/soft limit of the file handler for cissys user to 4096 or higher.

The shell scripts use the ">" to overwrite shell functionality. Your operating system may be configured to not allow this functionality by default in the users shell.

To avoid file access permission problems when executing scripts, consider placing the following command into cissys profile script:

```
set +o noclobber
```

Security Configuration

Various options exist to secure a system. In this application all files will be created with the minimum permissions required to ensure that group-readable, group-writable and group-executable files will have the correct user groups and to restrict the permissions available to legitimate users. In this way, a low privileged end user cannot directly edit configuration files and thereby bypass application security controls.

The following users and group categories must be defined to implement this security. For demonstration purposes the following users and groups will be used. These users must be created according to industry standards (including password policies). All users should be created with a default umask of 022 to ensure files created during normal operation have the correct permissions.

Please replace these users and groups for your installation defaults:

User	Group	Description
cissys	cisusr	This user will be used to install the application and to apply patches. This user will own all the application files. The same care should be taken with this user ID as if it is 'root'. This user will be able to add, delete and modify files within the application.
cisadm	cisusr	Administrative and Operation functions will be available to this user. This user will be able to stop and start the application and batch processes, but will not have access to modify any file other than generated log files
cisoper	-----	Low level operator. This user will only be able to read logs files and collect information for debugging and investigative purposes. Care should be taken in production to disable debugging as debugging information could contain potential sensitive data which this user should not have privy to.

Note: The Oracle Client and WebLogic should be installed as the user who will stop and start the application. For example, if you plan to run the application as the install user these components must belong to cissys.

Oracle Client 11.2.0.1 — Runtime Option

Install the Oracle Client as described in the Oracle Client installation documentation. Use the cissys account to install the Oracle Client. If another user installs the Oracle Client, make sure the cissys user ID has the proper execute permissions.

For the cissys user ID, ensure that the environment variable ORACLE_CLIENT_HOME is set up, and that ORACLE_CLIENT_HOME/perl/bin is the first Perl listed in the cissys account's PATH variable.

Oracle Java Development Kit Version 6.0 Update 20 or Later, 64-bit

At time of release, Oracle Java packages could be obtained from:

<http://www.oracle.com/technetwork/java/archive-139210.html>

The Oracle WebLogic Server requires the 64-bit version. The main prerequisite for the web server is the version of java mentioned above.

For the userid cissys, ensure that the environment variable JAVA_HOME is setup, and that java_home/bin and java_home/lib can be found in cissys' PATH variable.

Hibernate 3.3.2

You must install Hibernate before installing Oracle Utilities Mobile Workforce Management.

Download the file hibernate-3.3.2.ga.zip (the zip file associated with the 3.3.2 GA release.) from the following link:

<http://sourceforge.net/projects/hibernate/files/hibernate3/3.3.2.GA/>

It is very important that you download the exact version, as the product has only been certified with this exact release.

You will need to create a permanent directory to place one of the files from hibernate-distribution-3.3.2.GA-dist.zip. (e.g., /opt/hibernate).

Extract the file hibernate3.jar into the newly created directory (e.g., /opt/hibernate) from the hibernate-distribution-3.3.2.GA-dist.zip file.

Oracle WebLogic 11gR1 (10.3.4+) 64-bit

Oracle WebLogic software can be downloaded from the Oracle web site. This application server will run as a 64-bit application.

- Download and install 64-bit Java (as documented above) before installing WebLogic.
- Download and install WebLogic Server 11gR1 (10.3.4+).

Note: For an easy and quick installation of Oracle Weblogic please use silent mode. For more information, refer to http://docs.oracle.com/cd/E13196_01/platform/docs81/install/silent.html#1044118

Oracle JDeveloper 11g (11.1.1.4.0+) Studio Edition

JDeveloper 11g (11.1.1.4.0) Studio Edition is supported on any platform that runs JDK 6. It requires Oracle Weblogic Server 10.3.4+. It must be installed prior to installing the Oracle Utilities Application Framework.

Oracle JDeveloper can be downloaded from following link:

<http://www.oracle.com/technology/software/products/jdev/index.html> Note: For an easy and quick installation of Oracle JDeveloper, please use silent mode. For more information, refer to http://docs.oracle.com/cd/E16764_01/install.1111/e13666/ojdig.htm#CHDCDFEA

Oracle Application Developer Framework (ADF) 11g (11.1.1.4.0+)

Oracle ADF 11g (11.1.1.4.0+) requires Oracle Weblogic Server 10.3.4+ and it must be installed prior to installing ADF.

Oracle ADF can be downloaded from the following link:

<http://www.oracle.com/technetwork/developer-tools/adf/downloads/index.html>

Note: Make sure to only use the version of Oracle ADF certified with Weblogic server.

Oracle MapViewer 11g (11.1.1.5.1)

Oracle Fusion Middleware MapViewer 11g Release 1 (11.1.1.5.1) is a tool that renders maps showing different kinds of spatial data. It can be downloaded from the following link:

<http://www.oracle.com/technetwork/middleware/products/mapviewer/downloads/index-100641.html>

Download mapviewer.ear from this link.

Oracle BPEL Process Manager 11gR1

Oracle BPEL Process Manager is optional software and is required only for SMS dispatching functionality. Oracle BPEL Process Manager 11gR1 is a component of Oracle SOA Suite 11gR1. The Oracle BPEL Process Manager version is determined by your SMS gateway application. You can download SOA Suite 11gR1 from the SOA Suite download page at the following link:

<http://www.oracle.com/technology/products/soa/soasuite/collateral/downloads.html#11g>

wlfullclient.jar

Please refer to **Building the wlfullclient.jar File Using ANT** in Chapter **Additional Tasks** for more information.

Solaris 10 Application Server

This section describes the software requirements for operating the application using the Sun Solaris 10 application server.

Supported Application Servers

Operating System	Chipsets	Application Server
Solaris 10 Update 8 (64-bit)	SPARC	Oracle WebLogic 11gR1 (10.3.4) 64-bit version

Web/Application Server Tier

Solaris 10 Operating System Running on SPARC-based 64-bit Architecture

UNIX Administrator User ID

The following user groups and accounts have to be created to install and administer the application:

Description	Default Value	Customer Defined Value
Oracle Utilities Mobile Workforce Management Administrator User ID	cissys	
Oracle Utilities Mobile Workforce Management User Group	cisusr	

Note: It is recommended that you change the default values for security reasons.

Throughout this document the administrator user id is often referred to as the "cissys" user id. You should substitute that with the customer defined user id when not using the default value. After the initial install, the software should always be managed using that user id.

By default, the cissys userid is the only one given access to the files installed.

1. Create a group called cisusr (user group)
2. Create a user called cissys. Primary group cisusr. Set the primary shell for the cissys user to Korn Shell.
3. Set the stack size limit to 50 MB or more in the user profile startup script for cissys user:

```
ulimit -s 51200
```
4. Set the desired hard/soft limit of the file handler for cissys user to 4096 or higher.

The shell scripts use the ">" to overwrite shell functionality. Your operating system may be configured to not allow this functionality by default in the users shell.

To avoid file access permission problems when executing scripts, consider placing the following command into cissys profile script:

```
set +o noclobber
```

Security Configuration

Various options exist to secure a system. In this application all files will be created with the minimum permissions required to ensure that group-readable, group-writable and group-executable files will have the correct user groups and to restrict the permissions available to legitimate users. In this way, a low privileged end user cannot directly edit configuration files and thereby bypass application security controls.

The following users and group categories must be defined to implement this security. For demonstration purposes the following users and groups will be used. These users must be created according to industry standards (including password policies). All users should be created with a default umask of 022 to ensure files created during normal operation have the correct permissions.

Please replace these users and groups for your installation defaults:

User	Group	Description
cissys	cisusr	This user will be used to install the application and to apply patches. This user will own all the application files. The same care should be taken with this user ID as if it is 'root'. This user will be able to add, delete and modify files within the application.
cisadm	cisusr	Administrative and Operation functions will be available to this user. This user will be able to stop and start the application and batch processes, but will not have access to modify any file other than generated log files
cisoper	-----	Low level operator. This user will only be able to read logs files and collect information for debugging and investigative purposes. Care should be taken in production to disable debugging as debugging information could contain potential sensitive data which this user should not have privy to.

Note: The Oracle Client and WebLogic should be installed as the user who will stop and start the application. For example, if you plan to run the application as the install user these components must belong to cissys.

Oracle Client 11.2.0.1 — Runtime Option

Install the Oracle Client as described in the Oracle Client installation documentation. Use the cissys account to install the Oracle Client. If another user installs the Oracle Client, make sure the cissys user ID has the proper execute permissions.

For the cissys user ID, ensure that the environment variable ORACLE_CLIENT_HOME is set up, and that ORACLE_CLIENT_HOME/perl/bin is the first Perl listed in the cissys account's PATH variable.

Oracle Java Development Kit Version 6.0 Update 20 or Later, 64-bit

This software is only required for Oracle WebLogic installations.

At the time of release, the Oracle Java packages used in the test cycle were downloaded from:

<http://www.oracle.com/technetwork/java/archive-139210.html>

The Oracle WebLogic Server requires the 64-bit version. The main prerequisite for the web server is the version of java mentioned above.

For the userid cissys, ensure that the environment variable JAVA_HOME is setup, and that java_home/bin and java_home/lib can be found in cissys' PATH variable.

Hibernate 3.3.2

You must install Hibernate before installing Oracle Utilities Mobile Workforce Management.

Download the file hibernate-3.3.2.ga.zip (the zip file associated with the 3.3.2 GA release.) from the following link:

<http://sourceforge.net/projects/hibernate/files/hibernate3/3.3.2.GA/>

It is very important that you download the exact version, as the product has only been certified with this exact release.

You will need to create a permanent directory to place one of the files from hibernate-distribution-3.3.2.GA-dist.zip. (e.g., /opt/hibernate).

Extract the file hibernate3.jar into the newly created directory (e.g., /opt/hibernate) from the hibernate-distribution-3.3.2.GA-dist.zip file.

Oracle WebLogic 11gR1 (10.3.4+) 64-bit

Oracle WebLogic software can be downloaded from the Oracle web site. This application server will run as a 64-bit application.

- Download and install 64-bit Java (as documented above) before installing WebLogic.
- Download and install WebLogic Server 11gR1 (10.3.4+).

Note: For an easy and quick installation of Oracle Weblogic please use silent mode. For more information, refer to http://docs.oracle.com/cd/E13196_01/platform/docs81/install/silent.html#1044118

Oracle JDeveloper 11g (11.1.1.4.0+) Studio Edition

JDeveloper 11g (11.1.1.4.0) Studio Edition is supported on any platform that runs JDK 6. It requires Oracle Weblogic Server 10.3.4+. It must be installed prior to installing the Oracle Utilities Application Framework.

Oracle JDeveloper can be downloaded from following link:

<http://www.oracle.com/technology/software/products/jdev/index.html> Note: For an easy and quick installation of Oracle JDeveloper, please use silent mode. For more information, refer to http://docs.oracle.com/cd/E16764_01/install.1111/e13666/ojdig.htm#CHDCDFEA

Oracle Application Developer Framework (ADF) 11g (11.1.1.4.0+)

Oracle ADF 11g (11.1.1.4.0+) requires Oracle Weblogic Server 10.3.4+ and it must be installed prior to installing ADF.

Oracle ADF can be downloaded from the following link:

<http://www.oracle.com/technetwork/developer-tools/adf/downloads/index.html>

Note: Make sure to only use the version of Oracle ADF certified with Weblogic server.

Oracle MapViewer 11g (11.1.1.5.1)

Oracle Fusion Middleware MapViewer 11g Release 1 (11.1.1.5.1) is a tool that renders maps showing different kinds of spatial data. It can be downloaded from the following link:

<http://www.oracle.com/technetwork/middleware/products/mapviewer/downloads/index-100641.html>

Download mapviewer.ear from this link.

Oracle BPEL Process Manager 11gR1

Oracle BPEL Process Manager is optional software and is required only for SMS dispatching functionality. Oracle BPEL Process Manager 11gR1 is a component of Oracle SOA Suite 11gR1. The Oracle BPEL Process Manager version is determined by your SMS gateway application. You can download SOA Suite 11gR1 from the SOA Suite download page at the following link:

<http://www.oracle.com/technology/products/soa/soasuite/collateral/downloads.html#11g>

wlfullclient.jar

Please refer to **Building the wlfullclient.jar File Using ANT** in Chapter **Additional Tasks** for more information.

Windows 2008 Application Server

This section describes the software requirements for operating the application using the Windows application server.

Supported Application Servers

Operating System	Chipsets	Application Server
Windows Server 2008 R2 (64-bit)	x86_64	Oracle WebLogic 11gR1 (10.3.4) 64-bit version

Web/Application Server Tier

Oracle Client 11.2.0.1 — Runtime Option

Install the Oracle Client as described in the Oracle Client installation documentation. Use the cissys account to install the Oracle Client. If another user installs the Oracle Client, make sure the cissys user ID has the proper execute permissions.

For the cissys user ID, ensure that the environment variable ORACLE_CLIENT_HOME is set up, and that ORACLE_CLIENT_HOME/perl/bin is the first Perl listed in the cissys account's PATH variable.

Oracle Java Development Kit version 6.0 Update 20 or Later, 64-bit

This software is required for the Oracle WebLogic Installation.

At time of release, Oracle Java packages could be obtained from:

<http://www.oracle.com/technetwork/java/archive-139210.html>

The Oracle WebLogic Server requires the 64-bit version. The main prerequisite for the web server is the version of java mentioned above.

For the userid cissys, ensure that the environment variable JAVA_HOME is setup, and that java_home/bin and java_home/lib can be found in cissys' PATH variable.

Hibernate 3.3.2

Hibernate must be installed prior to the installation of Oracle Utilities Mobile Workforce Management.

Please download the file hibernate-3.3.2.ga.zip from the following link:

<http://prdownloads.sourceforge.net/hibernate/>

or from the following link:

http://sourceforge.net/project/showfiles.php?group_id=40712&package_id=127784

It is very important that you download the exact version, as the product has only been certified with this exact release.

You will need to create a permanent directory to place one of the files from hibernate-3.3.2.ga.zip. (e.g. c:\opt\hibernate3.3.2).

Extract the file hibernate3.jar from hibernate-3.3.2.ga.zip.

Oracle WebLogic 11gR1 (10.3.4+) 64-bit

Oracle WebLogic software can be downloaded from the Oracle web site. This application server will run as a 64-bit application.

- Download and install 64-bit Java (as documented above) before installing WebLogic.
- Download and install WebLogic Server 11gR1 (10.3.4+).

Note: For an easy and quick installation of Oracle Weblogic please use silent mode. For more information, refer to http://docs.oracle.com/cd/E13196_01/platform/docs81/install/silent.html#1044118

Oracle JDeveloper 11g (11.1.1.4.0+) Studio Edition

JDeveloper 11g (11.1.1.4.0) Studio Edition is supported on any platform that runs JDK 6. It requires Oracle Weblogic Server 10.3.4+. It must be installed prior to installing the Oracle Utilities Application Framework.

Oracle JDeveloper can be downloaded from following link:

<http://www.oracle.com/technology/software/products/jdev/index.html> Note: For an easy and quick installation of Oracle JDeveloper, please use silent mode. For more information, refer to http://docs.oracle.com/cd/E16764_01/install.1111/e13666/ojdig.htm#CHDCDFEA

Oracle Application Developer Framework (ADF) 11g (11.1.1.4.0+)

Oracle ADF 11g (11.1.1.4.0+) requires Oracle Weblogic Server 10.3.4+ and it must be installed prior to installing ADF.

Oracle ADF can be downloaded from the following link:

<http://www.oracle.com/technetwork/developer-tools/adf/downloads/index.html>

Note: Make sure to only use the version of Oracle ADF certified with Weblogic server.

Oracle MapViewer 11g (11.1.1.5.1)

Oracle Fusion Middleware MapViewer 11g Release 1 (11.1.1.5.1) is a tool that renders maps showing different kinds of spatial data. It can be downloaded from the following link:

<http://www.oracle.com/technetwork/middleware/products/mapviewer/downloads/index-100641.html>

Download mapviewer.ear from this link.

Oracle BPEL Process Manager 11gR1

Oracle BPEL Process Manager is optional software and is required only for SMS dispatching functionality. Oracle BPEL Process Manager 11gR1 is a component of Oracle SOA Suite 11gR1. The Oracle BPEL Process Manager version is determined by your SMS gateway application. You can download SOA Suite 11gR1 from the SOA Suite download page at the following link:

<http://www.oracle.com/technology/products/soa/soasuite/collateral/downloads.html#11g>

wlfullclient.jar

Please refer to **Building the wlfullclient.jar File Using ANT** in Chapter **Additional Tasks** for more information.

Chapter 7

Installing the Application Server Component of Oracle Utilities Application Framework

Installing the Oracle Utilities Application Framework is the prerequisite and foundation for installing a framework-based application such as Oracle Utilities Mobile Workforce Management. This section describes the process for installing the Oracle Utilities Application Framework, including:

- **Installation Overview**
- **Preinstallation Tasks**
- **Installing Oracle Utilities Application Framework**
- **Installing Oracle Utilities Application Framework Service Pack1**

Installation Overview

This process replaces any previously delivered and installed version of the Oracle Utilities Application Framework Server. Before you proceed:

1. Make sure that you have installed all the required third-party software as described in **Chapter 6: Installing Application Server Prerequisite Software**.
2. Complete the database installation (refer to the Oracle Utilities Mobile Workforce Management *Database Administrator's Guide*).
3. If you plan to upgrade a previously installed application server make a backup before you start a new installation.

The application server installation process of Oracle Utilities Mobile Workforce Management consists of the following:

1. Installing Oracle Utilities Application Framework
2. Installing Oracle Real-Time Scheduler
3. Installing Oracle Utilities Mobile Workforce Management

As a first step of the application server installation, download and install the framework application server. The installation process creates and configures the application server environment.

Once the Oracle Utilities Application Framework installation is successfully completed and the framework application environment is created, Oracle Real-Time Scheduler and Oracle Utilities Mobile Workforce Management can be installed on top of the framework environment.

You can download the installation packages from the Oracle Software Delivery Cloud.

This section describes how to install a working Oracle Utilities Application Framework Server, which can then be further configured manually to allow for production performance levels.

Application server installation packages delivered for this version are multi-platform and are ready to install on any supported platform (as described in the section **Supported Platforms**). You must complete the database installation before installing the application server.

Preinstallation Tasks

Hardware and Software Version Prerequisites

The section **Supported Platforms** contains all of the available platforms that are required with this release of the product.

Database Installation

Verify that the database has been installed and is operational. See Oracle Utilities Mobile Workforce Management *Database Administrator's Guide* for more information.

Installation Prerequisites

Chapter 6: Installing Application Server Prerequisite Software describes all preparations that need to be done on the server prior to installing the application server. Please read carefully the server setup requirements and make sure that all prerequisite software is installed and that all required environment variables are set. Correct server setup and proper environment variable settings are an essential prerequisite for successful environment installation.

System Architecture Overview

Oracle Utilities Application Framework V4.1.0 is a decoupled system architecture involving a business service application tier and a web application tier. Typically both will run on the same server, but the design does allow each tier to be installed on separate servers.

The design implements a stateless session bean (EJB technology, under Java EE 6), to provide remote access to service invocations. The root web app, Mobility web app, and XAI web apps can be configured to access service processing locally (as in previous versions), or to make a remote EJB call to perform the service request. In the latter case, the served containers, effectively, run as very thin servlet wrappers around the remote call.

For all supported application servers except for WebLogic expanded configuration (SDK environment), the deployment is in the form of two Enterprise Archive (ear) Files: SPLService.ear and SPLWeb.ear. Web Archive (war) files are created during the installation process but are not deployed.

Copying and Decompressing Install Media

The Oracle Utilities Application Framework installation file is delivered in jar format for both UNIX and Windows platforms.

If you are planning to install multiple Oracle Utilities Framework environments operated by different Oracle Utilities Administrator user ids, you must complete each of the following installation steps for each Administrator userid.

1. Log in to the application server host as the Oracle Utilities Framework administrator user ID (default cissys).
2. Create a temporary directory such as c:\ouaf\temp or /ouaf/temp. (Referred to below as <TEMPDIR>.)

This directory must be located outside any current or other working Oracle Utilities application environment. All files that are placed in this directory as a part of the installation can be deleted after completing a successful installation.

3. Copy the file FW-V4.1.0-MultiPlatform.jar in the delivered package to a <TEMPDIR> on your host server. If you are using FTP to transfer this file, remember to use the BINARY option for the FTP transfer.

4. Decompress the file:

```
cd <TEMPDIR>
```

```
jar -xvf FW-V4.1.0-MultiPlatform.jar
```

Note: You will need to have Java JDK installed on the machine used to (un)jar the application server installation package. Please install the JDK that is supported for the install on your platform to be able to use the jar command. This is the location of Java packages:

<http://www.oracle.com/technetwork/java/archive-139210.html>

A sub-directory named “FW.V4.1.0” is created. It contains the installation software for the Oracle Utilities framework application server.

Set Permissions for the cistab File in UNIX

Every Oracle Utilities Application Framework environment installed on a server must be registered in the /etc/cistab file located on that server. On UNIX servers, generally only the root user ID has write permissions to the /etc directory. Since the installation process is run by the Oracle administrator user ID (cissys), this user ID may not be able to write to /etc/cistab table.

The install utility checks permissions and if it identifies a lack of the necessary permissions, it generates a script in the <TEMPDIR>/FW.V4.1.0 directory named cistab_<SPLENVIRON>.sh. Run the generated script using the root account before continuing with the installation process. The script initializes the cistab file in /etc directory (if it is the first Oracle Utilities Framework application environment on the server) and registers a new environment.

The generated script also changes the owner of /etc/cistab file to the Oracle Utilities Framework administrator user ID, so that the next time a new environment is created by the same Oracle Utilities Framework administrator user ID, you do not need to run the generated script with the root user ID. Instead the install utility itself proceeds with the registration.

If you are reinstalling an existing environment, only the validation of /etc/cistab entry is done by the install utility, no new registration occurs. The install utility interactively instructs you about every step that needs to occur in each specific case.

If you are planning to upgrade an existing environment it is your responsibility to take a backup prior to the installation process. The installation utility does not create a backup of existing environment.

Installing Oracle Utilities Application Framework

This section outlines the steps for installing the Application Framework.

Brief Description of the Installation Process

1. Log on as the Oracle Utilities Framework administrator (the default is cissys on UNIX) or as a user with Administrator privileges (on Windows).
2. Configure your application server and any third-party software required for your platform, as outlined in **Chapter 6: Installing Application Server Prerequisite Software**.

3. Change directory to the <TEMPDIR>/FW.V4.1.0 directory.
4. Set the ORACLE_CLIENT_HOME and path variables as Oracle client Perl is required to run the installer.

UNIX:

```
export ORACLE_CLIENT_HOME=<ORACLE CLIENT INSTALL LOCATION>
export PERL_HOME=${ORACLE_CLIENT_HOME}/perl
export PATH=${PERL_HOME}/bin:$PATH
export PERL5LIB=${PERL_HOME}/lib:${PERL_HOME}/lib/site_perl:<OUAF
Installer Decompressed location/bin/perl>
export PERLLIB=${PERL_HOME}/lib:${PERL_HOME}/lib/site_perl:<OUAF
Installer Decompressed location/bin/perl>
export LD_LIBRARY_PATH=${ORACLE_CLIENT_HOME}/lib:$LD_LIBRARY_PATH
```

Windows:

```
set ORACLE_CLIENT_HOME=<ORACLE CLIENT INSTALL LOCATION>
set PERL_HOME=%ORACLE_CLIENT_HOME%\perl
set PATH=%PERL_HOME%\bin;%PATH%
```

5. Start the application installation utility by executing the appropriate script:

UNIX: ksh ./install.sh

Windows: install.cmd

6. Follow the messages and instructions that are produced by the application installation utility. Use the completed worksheets in the section **Application Framework Installation and Configuration Worksheets** to assist you.
7. Installation of Oracle Utilities Framework Application Server is complete if no errors occurred during installation.

Detailed Description of the Installation Process

1. Log on to the host server as Oracle Utilities Application Framework administrator.
Logon as cissys (on UNIX) or as a user with Administrator privileges (on Windows).

2. Configure application server and third-party software.

Complete all steps outlined in **Chapter 6: Installing Application Server Prerequisite Software**. You will need to obtain specific information for the install.

3. Change directory to the <TEMPDIR>/FW.V4.1.0 directory and start the application installation utility by executing the appropriate script:

UNIX: ksh ./install.sh

Windows: install.cmd

4. On the Environment Installation Options menu, select item 1: Third Party Software Configuration.

Use the completed Third Party Software Configuration worksheet in **Application Framework Installation and Configuration Worksheets** to complete this step. Below are the mandatory lists of configurable items along with descriptions for a few items. Where you see <Mandatory>, enter values suitable to your environment. You can assign default values to the rest of the menu items.

```
1.Third Party Software Configuration
Oracle Client Home Directory: <Mandatory>
```

```

Web Java Home Directory: <Mandatory>
Child JVM Home Directory:
COBOL Home Directory:
Hibernate JAR Directory: <Mandatory>
ONS JAR Directory:
Database Home Directory:<Mandatory>
Web Application Server Home Directory: <Mandatory>
ADF Home Directory: <Mandatory>
OIM OAM Enabled Environment:

```

5. Select menu item 50: Environment Installation Options.

Use the completed Environment Installation Options Worksheet to complete this step. See **Application Framework Installation and Configuration Worksheets**.

Note: You must create the directory for output (the Log Mount Point). The installation process fails if this directory does not exist.

```

50. Environment Installation Options
Environment Mount Point: <Mandatory> - Install Location
Log Files Mount Point:<Mandatory> - ThreadPoolWorker Logs
Location
Environment Name:<Mandatory>
Database Type: Oracle
Web Application Server Type: WLS
Install Application Viewer Module: true

```

Each item in the above list should be configured for a successful install.

Choose option (1, 50, <P> Process, <X> Exit):

6. Once you enter 'P' after entering mandatory input values in the above menu, the system populates another configuration menu. See Application Framework Installation and Configuration Worksheets. During this step, the specification of a new environment is checked for validity against /etc/cistab and the permissions on mount points and directories. Below are the mandatory lists of configurable items along with descriptions for a few items.

```

*****
* Environment Configuration *
*****
1. Environment Description
Environment Description: <Mandatory>
2. Business Application Server Configuration
Business Server Host: <Mandatory> - Hostname on which
application being installed
WebLogic Server Name: myserver
Business Server Application Name: SPLService
MPL Admin Port Number: <Mandatory> - Multipurpose Listener
Port
MPL Automatic startup: false

3. Web Application Server Configuration
Web Server Host: <Mandatory>
Web Server Port Number: <Mandatory>
Web Context Root: ouaf
WebLogic JNDI User ID: <Mandatory>
WebLogic JNDI Password: <Mandatory>
WebLogic Admin System User ID: <Mandatory>
WebLogic Admin System Password: <Mandatory>
WebLogic Server Name: myserver
Web Server Application Name: SPLWeb
Application Admin User ID: <Mandatory>

```



```

Application Admin Password: <Mandatory>
Expanded Directories: false
Application Viewer Module: true

```

4. Database Configuration

```

Application Server Database User ID: <Mandatory>
Application Server Database Password: <Mandatory>
MPL Database User ID: <Mandatory>
MPL Database Password: <Mandatory>
XAI Database User ID: <Mandatory>
XAI Database Password: <Mandatory>
Batch Database User ID: <Mandatory>
Batch Database Password: <Mandatory>
Database Name: <Mandatory>
Database Server: <Mandatory>
Database Port: <Mandatory>
ONS Server Configuration:
Database Override Connection String:
Oracle Client Character Set NLS_LANG:

```

5. General Configuration Options

```

Batch RMI Port: <Mandatory> - RMI port for batch
Batch Mode: <Mandatory> - CLUSTERED or DISTRIBUTED
Coherence Cluster Name: <Mandatory> - Unique name for batch
Coherence Cluster Address: <Mandatory> - Unique multicast

```

address

```

Coherence Cluster Port: <Mandatory> - Unique port for batch

```

cluster

```

Coherence Cluster Mode: <Mandatory> - prod
Each item in the above list should be configured for a

```

successful install.

```

Choose option (1,2,3,4,5, <P> Process, <X> Exit):

```

7. When you are done with the parameter setup, proceed with the option P. The utility writes the configured parameters and their values into the configuration file \$ SPLEBASE/etc/ ENVIRON.INI. The application installation utility copies the installation media to a new environment.

- The installation utility copies the new version software from the temporary installation media directory to the new environment.
- If any manual or electronic interruption occurs during this step, you can rerun the install utility from the beginning and follow the interactive instructions. The application installation utility is able to recover from such a failure.
- The application installation utility generates environment configuration parameters:
- The application installation utility automatically executes the script initialSetup.sh (on UNIX) or initialSetup.cmd (on Windows), located in \$SPLEBASE/bin (%SPLEBASE%\bin on Windows) directory. This script populates different application template configuration files with the new environment variables values and completes the rest of the installation steps.

8. Once the install has finished, the installation log location appears on the screen. If the log does not list any error messages, the installation of the application component of Oracle Utilities Application Framework is complete.

9. Set up environment variables.

Once the ENVIRON.INI file is created and contains the correct environment parameters, the application installation utility starts a sub shell to the current process by executing the splenvron.sh (on UNIX) or splenvron.cmd (on Windows) script, located in \$SPLEBASE/bin (or %SPLEBSE%\etc for Windows) directory. This script sets up all the necessary environment variables and shell settings for the application server to function correctly.

From this point, a number of environment variables have been set up. Some key ones are:

- `$PATH` - an adjustment to `$PATH` is made so that all of the environment scripts and objects will be in the path.
- `$SPLEBASE (%SPLEBASE%)` - stands for `<SPLEDIR>/<SPLENVIRON>` directory
- `$SPLOUTPUT (%SPLOUTPUT%)` - stands for `<SPLEDIROUT>/<SPLENVIRON>` directory

Note: Make sure that this directory exists. Otherwise the installation script will fail.

- `$SPLENVIRON (%SPLENVIRON%)` - environment name

For future operations or any postinstallation steps, you need to first execute the following command to connect your session to the new environment:

UNIX: `$SPLEBASE/bin/splenvron.sh -e $SPLENVIRON`

Windows: `%SPLEBASE%\bin\splenvron.cmd -e %SPLENVIRON%`

You need to execute this script each time you want to be connected to the specific environment before performing manual operations such as shutdown, startup or performing an additional application product installation.

When you have finished the install process, your current online session will be connected to the new environment.

See the chapter **Planning the Installation** for settings and configuration.

Installing Oracle Utilities Application Framework Service Pack1

This section outlines the steps for installing the Application Framework Service Pack1

Copying and Decompressing Install Media

The installation file is delivered in jar format for both UNIX and Windows platforms.

Download the installation package and proceed as follows:

1. Log in to the host server as the Oracle Utilities Application Framework administrator user ID (default `cissys`). This is the same user ID that was used to install the Oracle Utilities Application Framework.
2. Create a `<TEMPDIR>` directory on the host server, which is independent of any current or other working Oracle Utilities Framework application environment. This can be the same `<TEMPDIR>` used during the installation of the Oracle Utilities Application Framework.
3. Copy the file `FW-V4.1.0.1.0-MultiPlatform.jar` in the delivered package to a `<TEMPDIR>` on your host server. If you are using FTP to transfer this file, remember to use the `BINARY` option for the FTP transfer.
4. Decompress the file:

```
cd <TEMPDIR>
jar -xvf FW-V4.1.0.1.0-MultiPlatform.jar
```

For Windows installations, include the location of the JDK in your path before you execute the jar command.

For both Unix and Windows platforms, a sub-directory named `FW/V4.1.0.1.0` is created. The contents of the installation directory are identical for both platforms. The directory contains the install software for the application.

Preparing for the Installation

1. Log on as Oracle Utilities Meter Data Framework Administrator (default cissys).
2. Initialize the Framework environment that you want to install the product into.

UNIX:

```
$SPLEBASE/bin/splenvron.sh -e $SPLENVIRON
```

Windows:

```
%SPLEBASE%\bin\splenvron.cmd -e %SPLENVIRON%
```

3. Stop the environment if running.

UNIX:

```
$SPLEBASE/bin/spl.sh stop
```

Windows:

```
%SPLEBASE%\bin\spl.cmd stop
```

Installing the Framework Service Pack1

1. Change to the <TEMPDIR>/FW.V4.1.0.1.0 directory.
2. Execute the script:

UNIX:

```
ksh ./installSP.sh
```

Windows:

```
installSP.cmd
```

Note: On UNIX, ensure that you have the proper execute permission on install.sh

Upgrade Installation

If you are upgrading from an earlier version of Oracle Utilities Application Framework the installation steps will be the same as for an initial installation. The upgrade installation process will upgrade the Oracle Utilities Application Framework version from V4.0.2 to V4.1.0.

There have been some changes in the application server prerequisite software required for this release compared to the previous versions. Before upgrading an existing installation please ensure that all the application server prerequisite software is installed. Also, a number of new configuration options have been added in this release. Please refer to **Application Framework Installation and Configuration Worksheets** on page 4-4.

If you are upgrading or installing into an existing environment that had customer modifications, the install utility will back up all your customer modifications in a temporary installation area and copy them back into the environment at the end of the upgrade process.

The configuration files of the existing environment are backed up in the directory \$SPLEBASE/etc on UNIX and %SPLEBASE%\etc on Windows during installation by the install scripts to preserve any customer changes.

The possible upgrade paths are the following:

- Existing 2.0.1 environment can be upgraded to 2.1.0 environment
- Existing 2.0.1.5 environment can be upgraded to 2.1.0 environment

Chapter 8

Installing the Application Server Component of Oracle Real-Time Scheduler

This section describes the procedure for installing Oracle Utilities Mobile Workforce Management on top of the previously created Oracle Utilities Application Framework environment. This section includes:

- **Preinstallation Tasks**
- **Installing the Application**
- **Security Considerations**
- **Installing User Documentation**
- **Operating the Application**
- **Postinstallation Tasks**

To proceed with the Oracle Utilities Mobile Workforce Management installation you need to be connected to the target framework application environment. See the detailed installation instructions in the following section.

You *must* initialize the Framework environment along with the required Patch Set prior to proceeding with Oracle Utilities Mobile Workforce Management Application product installation. For detailed instructions see **Preparing for the Installation** on page 8-2.

Preinstallation Tasks

This section describes the steps that should be taken before installing Oracle Utilities Mobile Workforce Management.

Installing Prerequisite Patches

Oracle Utilities Application Framework patches must be installed prior to installing Oracle Utilities Mobile Workforce Management 2.1.0. The patches are available as a convenience rollup, ORS-V2.1.0-FW-PREREQ-Multiplatform.zip, which is included in the downloaded Media Pack. Please refer to the instructions contained inside the rollup directory for steps to install the patches. For a list of the patches that are included in this rollup, see **Appendix B: Application Framework Prerequisite Patches**.

Copying Map files

Copy the Map file to the map file directory <MAPDIR>. For more information, see the Map Editor Installation Guide and Map Editor User's Guide.

Copying and Decompressing Install Media

The installation file is delivered in jar format for both UNIX and Windows platforms.

Oracle Utilities Mobile Workforce Management is delivered in a separate installation package for each supported Operating System. Please refer to the **Supported Platforms** on page 3-4 for version and installation details regarding the database and operating system versions. Also see **Chapter 7: Installing the Application Server Component of Oracle Utilities Application Framework** for prerequisite third-party software installation instructions.

Download the installation package for your operating system and proceed as follows:

1. Log in to the host server as the Oracle Utilities Application Framework administrator user ID (default cissys). This is the same user ID that was used to install the Oracle Utilities Application Framework.
2. Create a <TEMPDIR> directory on the host server, which is independent of any current or other working Oracle Utilities Mobile Workforce Management application environment. This can be the same <TEMPDIR> used during the installation of the Oracle Utilities Application Framework.
3. Copy the file ORS-V2.1.0-MultiPlatform.jar in the delivered package to a <TEMPDIR> on your host server. If you are using FTP to transfer this file, remember to use the BINARY option for the FTP transfer.
4. Decompress the file:

```
cd <TEMPDIR>
jar -xvf ORS-V2.1.0-MultiPlatform.jar
```

For Windows installations, include the location of the JDK in your path before you execute the jar command.

For both Unix and Windows platforms, a sub-directory named ORS.V2.1.0 is created. The contents of the installation directory are identical for both platforms. The directory contains the install software for the application product.

Preparing for the Installation

1. Log on as Oracle Utilities Mobile Workforce Management Administrator (default cissys).
2. Initialize the Framework environment that you want to install the product into.

UNIX:

```
$SPLEBASE/bin/splenvron.sh -e $SPLENVIRON
```

Windows:

```
%SPLEBASE%\bin\splenvron.cmd -e %SPLENVIRON%
```

3. Stop the environment if running.

UNIX:

```
$SPLEBASE/bin/spl.sh stop
```

Windows:

```
%SPLEBASE%\bin\spl.cmd stop
```

Installing the Application

1. Change to the <TEMPDIR>/ORS.V2.1.0 Directory.

2. Execute the script:

UNIX:

```
ksh ./install.sh
```

Windows:

```
install.cmd
```

Note: On UNIX, ensure that you have the proper execute permission on install.sh

3. The Oracle Utilities Mobile Workforce Management Application specific menu will appear.
4. Select the following menu items and enter mandatory fields. See **Oracle Real-Time Scheduler Installation and Configuration Worksheets** on page 4-31.
 8. JMS Configuration
 - Context Factory: <Mandatory>
 - WebLogic Server URL: <Mandatory>
 - Weblogic System User ID: <Mandatory>
 - Weblogic System Password: <Mandatory>
 - Time Out: <Mandatory>
 9. ORS Environment Description
 - ORS Scheduler Map Files Location: <Mandatory>
 - Schedule Manager Port Number: <Mandatory>
 - Minimum Requests: <Mandatory>
 - Maximum Time (seconds) Booking Requests: <Mandatory>
 - Unique identifier for the instance of the JVM: <Mandatory>
 - Registry cleanse timing in seconds: <Mandatory>
 - Scheduler connection timeout in milliseconds: <Mandatory>
 - Scheduler maintenance cycle time in seconds: <Mandatory>
 10. Geocode Data Source Configuration
 - JDBC URL for the Geocode database: <Mandatory>
 - Database User Name: <Mandatory>
 - Database Password: <Mandatory>
 - JNDI name for the Geocode datasource: <Mandatory>
 11. Mapviewer Configuration
 - Deploy mapviewer locally on this instance: <Mandatory>
 - Location of mapviewer ear file: <Mandatory>
 12. Security Configuration
 - Deploy only mobility web application: <Mandatory>
5. When you are done with the parameter setup, proceed with the option P. Write Configure file.
6. Once the install has finished successfully, initialize the environment and modify the Advanced Menu Option Values. For more information, refer to Appendix **Common Maintenance Activities**.
7. Select the menu item 51 for Advanced Memory Configuration.

Use the completed Advanced Memory Configuration Worksheet to complete this step. Specify the values for the Web Application Java Initial Heap Size, Web Application Java Max Heap Size, Web Application Java Max Perm Size and Web Application Additional Options. See **Oracle Real-Time Scheduler Installation and Configuration Worksheets** on page 4-31.

51. Advanced Environment Memory Configuration

```

JVM Child Memory Allocation:
JVM Child Additional Options:
Web Application Java Initial Heap Size:      <Mandatory>
Web Application Java Max Heap Size:          <Mandatory>
Web Application Java Max Perm Size:          <Mandatory>
Web Application Additional Options:          <Mandatory>
Ant Min Heap Size:
Ant Max Heap Size:
Ant Additional Options:
Thread Pool Worker Java Min Heap Size:
Thread Pool Worker Java Max Heap Size:
Thread Pool Worker Java Max Perm Size:
Thread Pool Worker Additional Options:
Additional Runtime Classpath:                <Mandatory>

```

8. Select the menu item 52 for Advanced Web Application Configuration.

Use the completed Advanced Web Application Configuration Worksheet to complete this step. See **Oracle Real-Time Scheduler Installation and Configuration Worksheets** on page 4-31.

52. Advanced Web Application Configuration

```

WebLogic SSL Port Number:
WebLogic Console Port Number:
WebLogic Additional Stop Arguments:          <Mandatory>
Strip HTML Comments:
Authentication Login Page Type:
Web Form Login Page:
Web Form Login Error Page:
Application Viewer Form Login Page:
Application Viewer Form Login Error Page:
Help Form Login Page:
Help Form Login Error Page:
Web Security Role:
Web Principal Name:
Application Viewer Security Role:
Application Viewer Principal Name:
This is a development environment:
Preload All Pages on Startup:
Maximum Age of a Cache Entry for Text:
Maximum Age of a Cache Entry for Images:
JSP Recompile Interval (s):

```

9. When you are done with the parameter setup, proceed with the option P. Write Configure file.
10. To apply the above changes to the environment, run initial setup script.

UNIX:

```

$ cd $SPLEBASE/bin
$ ksh ./initialSetup.sh

```

Windows:

```

C:\> cd %SPLEBASE%\bin
C:\> initialSetup.cmd

```

11. Once the installation has finished successfully, you will need to execute postinstallation steps as described in **Postinstallation Tasks** on page 8-6. Also, set security for your application according to the steps described in **Security Considerations** on page 8-5.

Security Considerations

It is critical to secure Oracle Utilities Mobile Workforce Management when communicating with mobile devices using unsecured networks like the internet. At a minimum, we recommend exposing only necessary resources for device communication to these networks and only permit communication using HTTPS. Also, it is recommended to insure that the WebLogic console and other web applications intended for intranet-only use are not exposed to the internet.

Whenever possible, HTTP access to the application should be disabled and only HTTPS access should be allowed. It is also advisable to allow access to the WebLogic admin console application through a separate HTTPS admin port that is different from the application port.

For a more secured configuration, only the mobility web application would be deployed on the public or exposed network while the rest of the application would be deployed behind an internal firewall.

Please refer to the Advanced Web Application Configuration options under **Oracle Real-Time Scheduler Installation and Configuration Worksheets** on page 4-31 for a list of the security options available when deploying the Oracle Utilities Mobile Workforce Management application in a public or exposed network such as a DMZ.

It is also recommended to deploy MapViewer on the same WebLogic server instance so that the user security credentials can be shared. Please refer to the Mapviewer Configuration options in the section **Oracle Real-Time Scheduler Installation and Configuration Worksheets** on page 4-31 for the options available for deploying MapViewer on the same WebLogic server instance. Also refer to **Configuring MapViewer** on page 11-1 for the configuration changes required in the MapViewer installation.

Refer to **Oracle Location Services (eLocation)** on page 11-3 for the configuration changes required in the application for eLocation.

Installing User Documentation

This section provides instructions for installing the Oracle Utilities Mobile Workforce Management user documentation that is supplied with the system. Oracle Utilities Mobile Workforce Management user documentation is provided in PDF format for printing.

The documentation is also provided in HTML format located inside the Oracle Utilities Mobile Workforce Management application server installation package. It is automatically installed and can be launched from the user interface. The files are under the applications directory packaged in the file named help.war. User documentation is provided in English (ENG). The documentation material is divided into the following subdirectories underneath the language directory:

- M1: Oracle Utilities Mobile Workforce Management User Guide
- F1: Oracle Utilities Application Framework Administration and Business Process Guides

Installing Stand-Alone Online Help

You can also use the Oracle Utilities Mobile Workforce Management online help in stand-alone mode (that is, you do not have to launch it from the Oracle Utilities Mobile Workforce Management application or access it on the application server).

To install the Oracle Utilities Mobile Workforce Management help for stand-alone operation, copy the help.war from the Oracle Utilities Mobile Workforce Management server (environment) or from the Oracle Utilities Mobile Workforce Management installation package to the server or machine on which you want to access the help. If you want to copy the file from any installed Oracle Utilities Mobile Workforce Management environment, you can locate the file in the \$SPLEBASE/splapp/applications directory on the server.

Unzip the help.war file to any directory on your machine. To launch the Oracle Utilities Mobile Workforce Management help in stand-alone mode, open the SPLHelp.html file (located inside the language directory that you wish to use).

Note: Do not change the subdirectory names. The documents use relative path names to link to other documents. Changing the subdirectory names will result in broken links.

Customizing Help for Stand-Alone Operation

You can customize the SPLHelp.html file to open to the file and topic that you most frequently use. To do so, edit the SPLHelp.html file and change the DEFAULT_BOOKMARK to the desired location. The default DEFAULT_BOOKMARK is 'helpHome.html'.

Installing Stand-Alone Help Under Web Server

You can also install Oracle Utilities Mobile Workforce Management online help as a stand-alone web application. You can use any web application server, such as WebLogic. Configure the configuration file for your web application server to use web application help.

For example,

- For WebLogic, configure config.xml file for deployed application Name="help" with URI="help.war" and set WebServer DefaultWebApp="help"

Access the documentation from the browser by the following URL :

`http://<host name>:<port name>/<WebContext>/<Lang>/SPLHelp.html`

where <hostname>:<portname> is the URL of the web server, <Web Context> is the root web context name specified during web application server configuration, <Lang> is the name of the language directory, for example, ENG.

Note: Standalone online help files are not automatically updated when changes are made to the help files on the application server. You will have to re-install the stand-alone online help files.

Operating the Application

At this point your installation and custom integration process is complete. Be sure to read the Server Administration Guide for more information on further configuring and operating the Oracle Utilities Mobile Workforce Management system.

Postinstallation Tasks

1. Run the postinstall script.

UNIX:

```
$cd $SPLEBASE/runtime
$ ksh ./ORS_postinstall.sh
```

If you get permission errors while running this script, run the following command to set the permissions, then repeat the above step.

```
chmod 755 ORS_postinstall.sh
```

Windows:

```
C:\> cd %SPLEBASE%\runtime
C:\> ORS_postinstall.cmd
```

Note: Whenever you run initialSetup.sh/cmd script to change any configuration (using the configureEnv.sh script), please execute the above script once the initialSetup.sh/cmd has completed successfully.

2. Start up the environment by running the following command:

UNIX: spl.sh start

Windows: spl.cmd start

Follow the messages on the screen along with the logs in \$SPLSYSTEMLOGS directory to ensure that the environment was started successfully.

If the startup failed, identify the problem by reviewing the log files. Resolve any issues before attempting to restart the environment.

You should postpone the startup process until you are done with postinstallation steps.

Use the following utility to stop the environment:

UNIX: spl.sh stop

Windows: spl.cmd stop

Chapter 9

Installing the Application Server Component of Oracle Utilities Mobile Workforce Management

This section describes the procedure for installing Oracle Utilities Mobile Workforce Management on top of the previously created Oracle Real-Time Scheduler environment. This section includes:

- **Preinstallation Tasks**
- **Installing the Application**
- **Security Considerations**
- **Installing User Documentation**
- **Operating the Application**
- **Upgrade Installation**
- **Installing Service Packs and Patches**

To proceed with the Oracle Utilities Mobile Workforce Management installation you need to be connected to the target Oracle Real-Time Scheduler application environment. See the detailed installation instructions in the following section.

You *must* initialize the Framework environment along with the required patch set prior to proceeding with Oracle Utilities Mobile Workforce Management Application product installation. For detailed instructions see **Preparing for the Installation** on page 9-2.

For frequently asked questions and troubleshooting information during installation of the application and database components of Oracle Utilities Mobile Workforce Management, refer to articles 1475032.1 and 1475013.1 on My Oracle Support.

Preinstallation Tasks

This section describes the steps that should be taken before installing Oracle Utilities Mobile Workforce Management.

Installing Prerequisite Patches

Oracle Real-Time Scheduler patches must be installed prior to installing Oracle Utilities Mobile Workforce Management. Go to My Oracle Support to check for the latest list of patches available for Oracle Real-Time Scheduler.

Copying and Decompressing Install Media

The installation file is delivered in jar format for both UNIX and Windows platforms.

Oracle Utilities Mobile Workforce Management is delivered in a separate installation package for each supported Operating System. Please refer to the **Supported Platforms** on page 3-4 for version and installation details regarding the database and operating system versions. Also see **Chapter 7: Installing the Application Server Component of Oracle Utilities Application Framework** for prerequisite third-party software installation instructions.

Download the installation package for your operating system and proceed as follows:

1. Log in to the host server as the Oracle Utilities Application Framework administrator user ID (default cissys). This is the same user ID that was used to install the Oracle Utilities Application Framework.
2. Create a <TEMPDIR> directory on the host server, which is independent of any current or other working Oracle Utilities Mobile Workforce Management application environment. This can be the same <TEMPDIR> used during the installation of the Oracle Utilities Application Framework.
3. Copy the file MWM-V2.1.0-MultiPlatform.jar in the delivered package to a <TEMPDIR> on your host server. If you are using FTP to transfer this file, remember to use the BINARY option for the FTP transfer.

4. Decompress the file:

```
cd <TEMPDIR>
jar -xvf MWM-V2.1.0-MultiPlatform.jar
```

For Windows installations, include the location of the JDK in your path before you execute the jar command.

For both Unix and Windows platforms, a sub-directory named MWM.V2.1.0 is created. The contents of the installation directory are identical for both platforms. The directory contains the install software for the application product.

Preparing for the Installation

1. Log on as Oracle Utilities Mobile Workforce Management Administrator (default cissys).
2. Initialize the Oracle Real-Time Scheduler environment that you want to install the product into.

UNIX:

```
$SPLEBASE/bin/splenvron.sh -e $SPLENVIRON
```

Windows:

```
%SPLEBASE%\bin\splenvron.cmd -e %SPLENVIRON%
```

3. Stop the environment if running.

UNIX:

```
$SPLEBASE/bin/spl.sh stop
```

Windows:

```
%SPLEBASE%\bin\spl.cmd stop
```

Installing the Application

1. Change to the <TEMPDIR>/MWM.V2.1.0 Directory.
2. Execute the script:

UNIX:

```
ksh ./install.sh
```

Windows:

```
install.cmd
```

Note: On UNIX, ensure that you have the proper execute permission on `install.sh`

See **Security Considerations** on page 9-3 for important information about configuring security.

Security Considerations

It is critical to secure Oracle Utilities Mobile Workforce Management when communicating with mobile devices using unsecured networks like the internet. At a minimum, we recommend exposing only necessary resources for device communication to these networks and only permit communication using HTTPS. Also, it is recommended to insure that the WebLogic console and other web applications intended for intranet-only use are not exposed to the internet.

Whenever possible, HTTP access to the application should be disabled and only HTTPS access should be allowed. It is also advisable to allow access to the WebLogic admin console application through a separate HTTPS admin port that is different from the application port.

For a more secured configuration, only the mobility web application would be deployed on the public or exposed network while the rest of the application would be deployed behind an internal firewall.

Please refer to the Advanced Web Application Configuration options under **Oracle Real-Time Scheduler Installation and Configuration Worksheets** on page 4-31 for a list of the security options available when deploying the Oracle Utilities Mobile Workforce Management application in a public or exposed network such as a DMZ.

It is also recommended to deploy MapViewer on the same WebLogic server instance so that the user security credentials can be shared. Please refer to the Mapviewer Configuration options in the section **Oracle Real-Time Scheduler Installation and Configuration Worksheets** on page 4-31 for the options available for deploying MapViewer on the same WebLogic server instance. Also refer to the section on **Configuring MapViewer** on page 11-1 for the configuration changes required in the MapViewer installation.

Installing User Documentation

This section provides instructions for installing the Oracle Utilities Mobile Workforce Management user documentation that is supplied with the system. Oracle Utilities Mobile Workforce Management user documentation is provided in PDF format for printing.

The documentation is also provided in HTML format located inside the Oracle Utilities Mobile Workforce Management application server installation package. It is automatically installed and can be launched from the user interface. The files are under the applications directory packaged in the file named `help.war`. User documentation is provided in English (ENG). The documentation material is divided into the following subdirectories underneath the language directory:

- M1: Oracle Utilities Mobile Workforce Management User Guide
- F1: Oracle Utilities Application Framework Administration and Business Process Guides

Installing Stand-Alone Online Help

You can also use the Oracle Utilities Mobile Workforce Management online help in stand-alone mode (that is, you do not have to launch it from the Oracle Utilities Mobile Workforce Management application or access it on the application server).

To install the Oracle Utilities Mobile Workforce Management help for stand-alone operation, copy the help.war from the Oracle Utilities Mobile Workforce Management server (environment) or from the Oracle Utilities Mobile Workforce Management installation package to the server or machine on which you want to access the help. If you want to copy the file from any installed Oracle Utilities Mobile Workforce Management environment, you can locate the file in the \$SPLEBASE/splapp/applications directory on the server.

Unzip the help.war file to any directory on your machine. To launch the Oracle Utilities Mobile Workforce Management help in stand-alone mode, open the SPLHelp.html file (located inside the language directory that you wish to use).

Note: Do not change the subdirectory names. The documents use relative path names to link to other documents. Changing the subdirectory names will result in broken links.

Customizing Help for Stand-Alone Operation

You can customize the SPLHelp.html file to open to the file and topic that you most frequently use. To do so, edit the SPLHelp.html file and change the DEFAULT_BOOKMARK to the desired location. The default DEFAULT_BOOKMARK is 'helpHome.html'.

Installing Stand-Alone Help Under Web Server

You can also install Oracle Utilities Mobile Workforce Management online help as a stand-alone web application. You can use any web application server, such as WebLogic. Configure the configuration file for your web application server to use web application help.

For example,

- For WebLogic, configure config.xml file for deployed application Name="help" with URI="help.war" and set WebServer DefaultWebApp="help"

Access the documentation from the browser by the following URL :

http://<host name>:<port name>/<WebContext>/<Lang>/SPLHelp.html, where <hostname>:<portname> is the URL of the web server, <Web Context> is the root web context name specified during web application server configuration, <Lang> is the name of the language directory, for example, ENG.

Note: Stand-alone online help files are not automatically updated when changes are made to the help files on the application server. You will have to re-install the stand-alone online help files.

Operating the Application

At this point your installation and custom integration process is complete. Be sure to read the Oracle Utilities Mobile Workforce Management *Server Administration Guide* for more information on further configuring and operating the Oracle Utilities Mobile Workforce Management system.

Upgrade Installation

At this time Oracle does not support an application upgrade and will only support a database upgrade from V2.0.1.5 to V2.1.0. Please refer the *Oracle Utilities Mobile Workforce Management Database Administrator's Guide* for more details about a database upgrade. You will need to do a fresh Oracle Utilities Mobile Workforce Management 2.1.0 installation over an Oracle Real-Time Scheduler 2.1.0 installation.

Installing Service Packs and Patches

Periodically, Oracle Utilities releases a service pack of single fixes for its products. A service pack is an update to an existing release that includes solutions to known problems and other product

enhancements. A service pack is not a replacement for an installation, but a pack consisting of a collection of changes and additions for it. The service pack may include changes to be applied to the application server, the database, or both. The service pack includes all files necessary for installing the collection of changes, including installation instructions.

Between services packs, Oracle Utilities releases patches to fix individual bugs. For information on installing patches, see knowledge base article ID 974985.1 on My Oracle Support.

Service packs and patches can be downloaded from My Oracle Support (<https://support.oracle.com/>).

Chapter 10

Installing the Mobile Client

This section describes how to install the Mobile Client for Oracle Utilities Mobile Workforce Management. It is intended for implementers and system administrators responsible for configuration and initial setup of the mobile application. This section includes:

- **Installing the Mobile Client on Windows**
- **Installing the Mobile Client on Android**

Installing the Mobile Client on Windows

This section describes how to install the Oracle Utilities Mobile Workforce Management Mobile Client Runtime on Windows Platforms. This section includes:

- **Installing on Windows XP or Windows 7**
- **Installing on Windows Mobile**
- **Mobile Device Registration**
- **Uninstalling the Mobile Client**

Installing on Windows XP or Windows 7

1. Extract OracleMWM.msi from ORS-V2.1.0-Mobile-Client-Win.zip and copy it to a temporary directory. Double click the OracleMWM.msi file to start the installation process.
2. Click **Next** to proceed with the installation of Oracle Mobile Workforce Management 2.1.0 Mobile Client on your machine.
3. Select a folder/hard drive location to install the application to.
4. Click **Next** to proceed with the installation.
5. Click **Close** after the installation is successful.

The mobile client application is now accessible from shortcuts created on the Desktop or Start Menu.

Installing on Windows Mobile

1. Extract OracleMWM.CAB from ORS-V2.1.0-Mobile-Client-WinMobile.zip and copy it to a temporary directory on the mobile device. Tap the OracleMWM.CAB file to start the installation process.
2. If prompted, select **Device** as the location to be installed.
3. Click **Close** after the installation is successful.

4. After completing the MCP installation, delete the CAB file (OracleMWM.CAB) and reboot the mobile device.

The mobile client application is now accessible from shortcuts created on the **Start > Programs** menu.

Mobile Device Registration

The mobile device needs to be registered with the Oracle Utilities Mobile Workforce Management application server before it can start using the application features. Ensure that the Oracle Utilities Mobile Workforce Management application is installed and running before registering the mobile device.

Please refer to the *Oracle Utilities Mobile Workforce Management Mobile Application User Guide* for the steps to register a device with the server.

Uninstalling the Mobile Client

Follow these procedures to remove the Mobile Client from Windows XP or Windows Mobile.

Uninstalling from Windows XP or Windows 7

1. Ensure that all the data is synchronized on the server.
2. Go to **Start Menu -> Control Panel**.
3. Open **Add or Remove Programs**.
4. Select Oracle Mobile Workforce Management 2.1.0 from the programs list and click **Remove**.
5. Click **Yes** to confirm the removal of the mobile client.
6. Click **Close** after the mobile client has been removed.

Uninstalling from Windows Mobile

1. Ensure that all the data is synchronized on the server.
2. Go to **Start Menu -> Settings -> System** tab
3. Open **Remove Programs**.
4. Select Oracle Mobile Workforce Management 2.1.0 from the programs list and click **Remove**.
5. Click **Yes** to confirm the removal of the mobile client.
6. Click **Close** after the mobile client has been removed.

Installing the Mobile Client on Android

This section describes how to install the Android Mobile Client Platform (Android MCP) for Oracle Utilities Mobile Workforce Management. It is intended for implementers and system administrators responsible for configuration and initial setup of the mobile application. This section includes:

- **Overview of the Android MCP**
- **Installing the Android MCP**
- **Launching Android MCP**
- **Launching Android MCP Tools**
- **Uninstalling Android MCP**

Overview of the Android MCP

Android MCP provides the same runtime functionality as the Windows Mobile and Windows XP MCP. This functionality includes:

- **RSI:** Communication between the device and the server
- **GPS:** GPS services such as location logging and transferring logs to the server
- **BO Processing:** Business Object Functionality
- **BS Processing:** Business Service Functionality
- **SS Processing:** Service Script Functionality
- **Authentication:** Login processing
- **UI Rendering:** User Interface Processing
- **Logging:** Log File Support

There may be differences in UI layout or JavaScript support due to the different browser component provided by the Android platform. There will also be normal differences in the user interface behavior that are specific to Android applications.

Installing the Android MCP

The Android MCP is delivered as a standard Android APK file. This APK will need to be installed to the Android device in one of the following ways.

- Using SD Card
- Downloading the file from a hosted web server
- Using device management software for Android
- Using Android SDK (Advanced only)

This document will describe the SD Card method only.


Note: You should uninstall previous versions of the Android MCP before installing a new version.

Installing the MCP Using the SD Card Method

To install Android MCP using the SD Card method


1. Extract OracleMWM.apk from the ORS-V2.1.0-Mobile-Client-Android.zip file and copy it to a temporary directory.

2. Connect the Android device to a desktop or laptop computer as a USB Drive.




3. Copy the OracleMWM.apk file to the removable disk (select **My Computer** for the drive letter).
4. Disconnect the device from the desktop or laptop, or choose the **Charge only** connection type.
5. Verify that non-Market applications can be installed.

Open **Settings, Applications** and select **Unknown sources**.



6. Use a file explorer on the device such as ASTRO or File Expert (which can be downloaded from Android Market) to locate the APK file on the SD card. Launch the file.




7. Confirm the installation by clicking **Install**.
8. The application will now be installed.
9. After the application is installed, click **Done**.

Launching Android MCP

To launch Android MCP on your device

1. Under All apps, locate the Oracle MWM icon.
2. Launch the application to register the device and download a deployment.

Note: Ensure that your device has data or WIFI connectivity.



Launching Android MCP Tools

The MCP Tools application provides functionality to import and export the MCP data folder to and from the SD card on the Android device. This can be very useful in debugging issues or for loading test data to the device.

To launch the Android MCP Tools Application on your device

1. Under All apps, locate the Oracle MWM Tools icon.
2. Launch the application to access import and export functionality.
 - **Export Data** exports the application's data folder to SD Card.
 - **Import Data** imports data from SD card's /MWMAApp/ folder into the application's data folder.

Uninstalling Android MCP

To uninstall the Android MCP

1. Open **Settings, Applications, Manage Applications** and click the Oracle MWM application.
2. Click **Uninstall** to remove Android MCP from your device. Do not select **Clear data**.

Chapter 11

Additional Tasks

This section describes tasks that should be completed after installing Oracle Utilities Mobile Workforce Management, including:

- **Configuring MapViewer**
- **Oracle Location Services (eLocation)**
- **Configuring the Environment for Oracle BPEL Server**
- **Configuring the Scheduler**
- **Building the wfullclient.jar File Using ANT**
- **Configuring Business Service SDK**
- **WebLogic Production Server Considerations**
- **Building Javadoc Indexes**
- **Configuring the Environment for Batch Processing**
- **Customizing Configuration Files**
- **Customizing the Logo**
- **Generating the Application Viewer**
- **Installation Verification Checklist**
- **Accessing the Application**

Configuring MapViewer

This section describes how to configure a MapViewer data source for Oracle Utilities Mobile Workforce Management.

Before you can configure a MapViewer data source you must:

- Install Oracle Fusion Middleware MapViewer 11.1.1.5.1.
- Create and configure the database.

To configure a MapViewer data source

1. Go to the MapViewer Application:

Example: `http://<host>:<port>/mapviewer`

Where <host> is the host name or IP address of the system where MapViewer is deployed. and <port> is the port of the WebLogic instance. If MapViewer is deployed on the same WebLogic instance then this is same as the application port.

2. Click the **Admin** button to log in as an administrator to MapViewer.
3. Click **Manage Map Viewer**, then **Configuration**.
4. Modify mapViewerConfig.xml using the Config text area.
 - a. Provide the data source details for the cisadm and NAVTEQ_UTIL data sources. The following code sample contains example data sources. Change the properties according to your data sources:

```
<!--(Sample datasource configuration)
  <map_data_source name="mvdemo"
    jdbc_host="db1.my_corp.com"
    jdbc_sid="orcl"
    jdbc_port="1521"
    jdbc_user="scott"
    jdbc_password="!tiger"
    jdbc_mode="thin"
    number_of_mappers="3"
    allow_jdbc_theme_based_foi="false"
  />
```

- b. If the secure protocol (HTTPS) is enabled for the MapViewer URL, add the following to the **Map Image Settings** section of mapViewerConfig.xml:

```
<save_images_at file_prefix="omsmap"
  url="https:// <host>:<port>/mapviewer/images"
  path="../../images"
  life="0"
  recycle_interval="480"
/>
```

Where <host> is the host name or IP address of the system where MapViewer is deployed and <port> is the port of the WebLogic instance.

5. Click **Save and Restart**.
6. To refresh the list of data sources, click **Manage Map Viewer**, then **Data sources**.
7. To confirm that the configuration is correct, click **Manage Map Tile Layers**.

Configuring MapViewer Security

When MapViewer is deployed on the same WebLogic instance as the application, follow these steps to configure MapViewer to share the security credentials of the application.

1. Add the following entry in the weblogic.xml file under <MAPVIEWER_EAR_DIR>/web.war/WEB-INF:


```
<security-role-assignment>
  <role-name>cisusers</role-name>
  <principal-name>cisusers</principal-name>
</security-role-assignment>

<session-descriptor>
  <cookie-path>/mapviewer</cookie-path>
</session-descriptor>
```
2. Add the following entry in the web.xml file under <MAPVIEWER_EAR_DIR>/web.war/WEB-INF:


```
<security-role>
  <description>MapView users</description>
  <role-name>cisusers</role-name>
</security-role>
```


Oracle Location Services (eLocation)

This section describes how to configure and deploy Oracle Location Services (eLocation) for use by Oracle Utilities Mobile Workforce Management. This is required if your implementation chooses to use eLocation for routing data instead of Oracle Real-Time Scheduler.

The installation of eLocation requires the following components

- eLocation Dispatcher Servlet (elocation.ear)
- Oracle RouteServer (routeserver.ear)
- Oracle Geocoder (geocoder.ear)

To configure eLocation

1. Download the elocation.ear file.

To download the latest elocation.ear, log on to My Oracle Support at support.oracle.com and download Patch 13446793, “SPATIAL elocation for Mobile Workforce Management Release 12.”

Oracle RouteServer and Oracle Geocoder are included with the Oracle 11g database in the following directory: ORACLE_HOME\md\jlib

2. When eLocation is deployed on the same WebLogic instance as the application, follow these steps to configure eLocation to share the security credentials of the application.

- a. Add the following entry in the weblogic.xml file, located under <ELOCATION_EAR_DIR>/web.war/WEB-INF:

```
<security-role-assignment>
<role-name>cisusers</role-name>
<principal-name>cisusers</principal-name>
</security-role-assignment>
```

- b. Add the following entry in the web.xml file, located under <ELOCATION_EAR_DIR>/web.war/ WEB-INF:

```
<security-role>
<description>SPL users</description>
<role-name>cisusers</role-name>
</security-role>
```

3. Deploy and configure the routing engine and the geocoding service as described in the Oracle Spatial Developer's Guide 11g.
4. Deploy the eLocation EAR manually using the WebLogic console. Open the eLocation URL at: http://<environment>:<port>/elocation/admin.jsp

The application will ask for login credentials because the web.xml and weblogic.xml files have changed. Once the login is successful, you will see the Oracle eLocation Administration page.

5. To modify the Mapper Cluster, click **Edit** on the component URL. Specify the following value:

```
<http://<environment>:<port>/mapviewer/omsserver>.
```

Make sure that MapViewer is also deployed in the environment.

6. To modify the Geocoder Cluster, click **Edit** on the component URL. Specify the following value:

```
< http://elocation.oracle.com/geocoder/gcserver>
```

7. To modify the Router Cluster, click **Edit** on the component URL. Specify the following value:

```
http://elocation.oracle.com/routeserver/servlet/RouteServerServlet
```

8. Click **Apply Changes**.

Configuring the Environment for Oracle BPEL Server

Oracle BPEL Process Manager is optional software that can be used by Oracle Utilities Mobile Workforce Management for sending SMS messages. Oracle Utilities Mobile Workforce Management can be configured to send SMS via different third party gateway/SMS providers. The ability to send SMS using the Oracle BPEL Server is already provided in the base application.

This section describes how to configure the Oracle Utilities Mobile Workforce Management to interact with Oracle BPEL Server.

Before configuring Oracle Utilities Mobile Workforce Management to interact with BPEL Server you must:

- Install Oracle BPEL Server.
- Configure Oracle Utilities Mobile Workforce Management with a process that receives phone numbers and messages deployed on the BPEL server.

Oracle Utilities Mobile Workforce Management uses the algorithm type F1-SMSSEND to connect to the Oracle BPEL server.

The following information will be required to set up the application to work with the BPEL server:

Option Type	Detail Description
Operation Name	The 'operation' or the method name of the SMS Web service
Password	The password for the Web service
Port Type	The 'port type' name of the SMS Web service
Server URL	The url of the BPEL/SMS gateway server
Service Name	The 'service' name of the SMS Server
User Name	The 'user name' for authentication to the Web service

Configuring the Scheduler

This section describes how to configure a scheduler as a standalone application on the TPW JVM.

After installing Oracle Real-Time Scheduler or Oracle Utilities Mobile Workforce Management V2.1.0, please verify that the below step1 and step 2 changes are available or not. If they are not available, follow the below steps:

1. Verify that the wlfullclient.jar file is in the following directory:

<Web Logic Home>/wlserver_10.3/server/lib

If the file is not there, generate the file by following the instructions in **Building the wlfullclient.jar File Using ANT** on page 11-6. Place the file in the above directory. The batch scheduler scripts use this jar in their classpath.

2. If you enabled the WebLogic Console Port Number, then the WebLogic console is accessed by https admin channel by default. Specify “t3s://<host>:<admin channel port>” as the WebLogic Server URL in menu item 8, JMS Configurations. Otherwise, specify “t3://<host>:<web server port>”.

See **Oracle Real-Time Scheduler Installation and Configuration Worksheets** on page 4-31 for more information.

3. Configure trust keystore as WebLogic Additional Stop Argument using menu item 52 Advanced Web Application Configuration. **Oracle Real-Time Scheduler Installation and Configuration Worksheets** on page 4-31 for more information.
4. Run the initialSetup script.

UNIX:

```
$ cd $SPLEBASE/bin
$ ksh ./initialSetup.sh
```

Windows:

```
cd %SPLEBASE%\bin
initialSetup.cmd
```

5. Run the standalone batch script. For example

UNIX:

```
$ cd $SPLEBASE/bin
$ nohup batchscheduler.sh <Node_ID> > /tmp/batchscheduler.log 2>&1
&
```

Windows:

```
cd %SPLEBASE%\bin
batchscheduler.cmd <Node_ID>
```

Notes:

- The application domain node ID must be unique value across the environment. This value is used for a scheduler running from Threadpoolworker.
- The scheduler should be disabled from the online application. The batch scheduler program invokes Threadpoolworker so there is no need to start Threadpoolworker separately.
- The NodeID is located in the threadpoolworker logs under \$SPLOUTPUT. You can locate this value by searching for “NODEID”.
- To locate the NodeID in the threadpoolworker process, search for the string “-Dspl.mwm.scheduler.nodeId=”

You will get multicast issues in an AIX environment if you start the batch scheduler and the multicast listener is not enabled. The workaround for this is to enable a unicast listener. See the Oracle Utilities Mobile Workforce Management *Batch Server Administration Guide* for more details.

To enable the unicast listener

1. Copy the file \$SPLEBASE/splapp/standalone/config/tangosol-coherence-override.xml to tangosol-coherence-override.xml.org
2. Remove the following code in the tangosol-coherence-override.xml file:

```
<multicast-listener>
-----
-----
</multicast-listener>
```

3. Add the following code after the </member-identity> tag in the tangosol-coherence-override.xml file:

```
<unicast-listener>
```

```

<well-known-addresses>
<socket-address id="0">
<address system-property=
"tangosol.coherence.wka">COHERENCE_CLUSTER_HOSTNAME</address>
<port system-property=
"tangosol.coherence.wka.port">COHERENCE_CLUSTER_PORT</port>
</socket-address>
</well-known-addresses>
<address system- property=
"tangosol.coherence.localhost">COHERENCE_CLUSTER_HOSTNAME
</address>
<port system-property=
"tangosol.coherence.localhost">COHERENCE_CLUSTER_PORT</port>
<port-auto-adjust system-property=
"tangosol.coherence.localhost.adjust">true</port-auto-adjust>
</unicast-listener>

```

4. Select the menu item 5 and General Configuration Options. Use the completed General Configuration Options Worksheet to complete this step. See **Oracle Real-Time Scheduler Installation and Configuration Worksheets** on page 4-31 for more information.
5. Run initialSetup and start the batch scheduler.

See Appendix **Common Maintenance Activities** for additional information on common batch scheduler tasks.

Building the wfullclient.jar File Using ANT

To build the wfullclient.jar file

1. Place the following build.xml file in WebLogic Installations Server/lib directory. (For example: /spl/Middleware/WLS_10.3.6/wlserver_10.3/server/lib.)

```

<project name="JarBuilder" default="run">
<property name="bea.home" value="/spl/Middleware/WLS_10.3.6"/>
<property name="wl.home" value="${bea.home}/wlserver_10.3"/>
<path id="main.class.path">
<pathelement path="${bea.home}/modules/
com.bea.core.utils_1.9.0.0.jar"/>
<pathelement path="${bea.home}/modules/
com.bea.core.jarbuilder_1.6.0.0.jar"/>
<pathelement path="${java.class.path}"/>
</path>
<target name="run">
<echo message="***ANT Script should run from inside the ${wl.home}/
server/lib ***" />
<echo message="***** ***** ***** *****" />
<java classname="com.bea.jarbuilder.JarBuilder">
<classpath refid="main.class.path"/>
<jvmarg value="-d ${wl.home}/server/lib -jar wljarbuilder.jar"/>
</java>
</target>
</project>

```

2. Modify the Properties defined in the ANT script according to your Installation directory:

```

<property name="bea.home" value="/spl/Middleware/WLS_10.3.6"/>
<property name="wl.home" value="${bea.home}/wlserver_10.3"/>

```

Note: Change the com.bea.core.utils_1.9.0.0.jar and com.bea.core.jarbuilder_1.6.0.0.jar file names, if there are any version conflicts.

3. Login to \$SPLEBASE and run the following command:

```
/spl/Middleware/WLS_10.3.6/wlserver_10.3/server/bin/ setWLSENV.sh
```

Unix:

```
cd $SPLEBASE
Run /spl/Middleware/WLS_10.3.6/wlserver_10.3/server/bin/
setWLSENV.sh
```

Windows:

```
cd %SPLEBASE%
Run C:\spl\Middleware\WLS_10.3.6\wlserver_10.3\server\bin\
setWLSENV.sh
```

4. Change the directory to "/spl/Middleware/WLS_10.3.6/wlserver_10.3/server/lib" folder :

```
#> cd /spl/Middleware/WLS_10.3.6/wlserver_10.3/server/lib
#>ant
```

5. When the ant script has executed successfully, the file wlfullclient.jar is generated in the following directory: /spl/Middleware/WLS_10.3.6/wlserver_10.3/server/lib

Note: For common Batch Scheduler start/stop tasks, please refer Appendix
Common Maintenance Activities.

Configuring the Batch Scheduler for Different Servers

This section describes how to configure the batch scheduler to point to a different application server, or “target server”. The target server has to be installed following the same steps as described for installing Oracle Real-Time Scheduler or Oracle Utilities Mobile Workforce Management. These steps can also be followed to run the batch scheduler(s) from a different box from the target server. In the following steps, substitute the appropriate values for the environment.

To configure the scheduler to point to a different target server

1. Install Oracle Real-Time Scheduler application.
2. Stop the environment if running.

UNIX:

```
$SPLEBASE/bin/spl.sh stop
```

Windows:

```
%SPLEBASE%\bin\spl.cmd stop
```

3. In the application menu, select the menu item 8 to configure JMS settings. Enter the menu items for the target server. Use the completed JMS Configuration Worksheet to assist you with this step. See **Oracle Real-Time Scheduler Installation and Configuration Worksheets** on page 4-31 for more information.
4. Select the menu item 9 to specify ORS environment description and enter the menu items for the target server. Use the completed ORS Environment Description Worksheet to complete this step. See **Oracle Real-Time Scheduler Installation and Configuration Worksheets** on page 4-31 for more information.
5. Verify that the wlfullclient.jar file is in the following directory: <Web Logic Home>/wlserver_10.3/server/lib. If it is not, generate the file by following the instructions in **Building the wlfullclient.jar File Using ANT** on page 11-6. The batch scheduler scripts use this jar in their classpath.

6. Enter the WebLogic Console Port Number for the target server using menu item 52 Advanced Web Application Configuration. See **Oracle Real-Time Scheduler Installation and Configuration Worksheets** on page 4-31 for more information.
7. Run the initialSetup script:
UNIX:

```
$SPLEBASE/initialSetup.sh
```

Windows:

```
%SPLEBASE%\initialSetup.cmd
```
8. Run the standalone batch scheduler script, which now points to the target server. See Appendix **Common Maintenance Activities** for details on how to start and stop the batch scheduler.

Configuring Business Service SDK

For details about configuring business service SDK, see the *Oracle Utilities Mobile Workforce Management Configuration Guide*.

WebLogic Production Server Considerations

By default, WebLogic Server is configured with two keystores, to be used for development only. These keystores should not be used in a production environment.

Configuring Identity and Trust

Private keys, digital certificates, and trusted certificate authority certificates establish and verify identity and trust in the WebLogic Server environment. WebLogic Server is configured with a default identity keystore DemoIdentity.jks and a default trust keystore DemoTrust.jks. In addition, WebLogic Server trusts the certificate authorities in the cacerts file in the JDK. This default keystore configuration is appropriate for testing and development purposes. However, these keystores should not be used in a production environment.

To configure identity and trust for a server:

1. Obtain digital certificates, private keys, and trusted CA certificates from the CertGen utility, Sun Microsystems's keytool utility, or a reputable vendor such as Entrust or Verisign. You can also use the digital certificates, private keys, and trusted CA certificates provided by the WebLogic Server kit. The demonstration digital certificates, private keys, and trusted CA certificates should be used in a development environment only.
2. Store the private keys, digital certificates, and trusted CA certificates. Private keys and trusted CA certificates are stored in a keystore.
3. Configure the identity and trust keystores for a WebLogic Server instance on the Configuration: Keystores page.

By default, WebLogic Server is configured with two keystores, to be used for development only.

- DemoIdentity.jks: Contains a demonstration private key for WebLogic Server. This keystore establishes an identity for WebLogic Server.
- DemoTrust.jks: Contains a list of certificate authorities trusted by WebLogic Server. This keystore establishes trust for WebLogic Server.

These keystores are located in the WL_HOME\server\lib directory and the JAVA_HOME\jre\lib\security directory. For testing and development purposes, the keystore configuration is complete. Use the steps in this section to configure identity and trust keystores for production use.

Refer to the WebLogic documentation to configure identity and trust keystores for production use (Secure servers and resources > Configure identity and trust/Set up SSL)

Note: Depending on your choice of implementation you may need to change some configuration files. These files are managed by templates and will be overwritten if the procedures documented in “Customizing Configuration Files” are not followed.

Building Javadoc Indexes

The following script rebuilds the Javadocs indexes in the application viewer java module. This is necessary after customer modifications (CM) have been applied to an environment. You need to run this script only if the customer modification includes Java code.)

Windows:

```
%SPLEBASE%\bin\buildJavadocsIndex.cmd
```

UNIX:

```
ksh $SPLEBASE/bin/buildJavadocsIndex.sh
```

Configuring the Environment for Batch Processing

See the Oracle Utilities Mobile Workforce Management *Batch Server Administration Guide* for information on configuring the environment for batch processing.

Customizing Configuration Files

You may wish to make customer modifications to various configuration files. To do so, you should locate the configuration file you want to customize and edit it manually.

Configuration files are generated from delivered templates in the Oracle Utilities installation and are populated by values entered by the installation utility during the configuration process. In future upgrades of Oracle Utilities application software versions, some templates may be changed to reflect new software version requirements. In this case, the upgrade process will back up your customized configuration file and will regenerate a configuration file based on a new template. You will need to review the new configuration file and apply your customized changes back if still applicable for the new version.

For configuration files that are located in a web application (for example, web.xml, hibernate.properties), of the web application during installation process, you will not be able to edit the configuration files directly.

You will need to follow the procedure:

- Locate the configuration file you want to customize in the directory \$SPLEBASE/etc/conf.
- Apply your changes.
- Update application war file with the latest changes by executing the following command:

Unix:

```
$SPLEBASE/bin/initialSetup.sh
```

Windows:

```
%SPLEBASE%\bin\initialSetup.cmd
```

Customizing the Logo

To replace the Oracle Utilities logo on the main menu with another image, put the new image<customer_logo_file>.gif file into the directory \$SPLEBASE/etc/conf/root/cm and create a new "External" Navigation Key called CM_logoImage. To do that, run the Oracle Utilities application from the browser with the parameters: http://<hostname>:<port>/<Web Context>/ cis.jsp?utilities=true&tools=true. From the Admin menu, select Navigation Key. Add the above Navigation Key with its corresponding URL Override path. The syntax for the URL path is:

Windows:

http://<host name>:<port>/<Web Context>/cm/<customer_logo_file>.gif

UNIX:

http://<host name>:<port>/<Web Context>/cm/<customer_logo_file>.gif.

The root directory may be deployed in war file format for runtime environment (SPLApp.war). Use provided utilities to incorporate your cm directory into SPLApp.war file.

Generating the Application Viewer

You may extend application viewer capabilities within an environment by generating additional items. The additional items that can be generated include algorithm type and related algorithm information, maintenance object information and data dictionary information.

To generate the additional items in the application viewer:

1. Shut down the environment.
2. Initialize a command shell:

The scripts that are provided with the system need to be run from a shell prompt on the machine that you installed the application on. Before such scripts can be run the shell must be “initialized” by running the splenvirion script provided with the system.

Unix:

You will need to logon to your UNIX box as the Oracle Utilities Administrator (default cissys) and open a shell prompt. In the following example you should replace the variables

\$SPLEBASE with the Full directory name that you installed the application into

and

\$SPLENVIRON with the name you gave to the environment at installation time.

To initialize the environment enter:

```
$SPLEBASE/bin/splenvirion.sh -e $SPLENVIRON
```

For example:

```
/ouaf/TEST_ENVIRON1/bin/splenvirion.sh -e TEST_ENVIRON1
```

Windows:

The command window should be opened on the Windows server that you installed the application on.

In the below example you should replace the following variables:

- %SPLEBASE% : The Full directory name that you installed the application into

- **%SPLENVIRON%:** The name you gave to the environment at installation time.

To initialize the environment type the following in your command prompt:

```
%SPLEBASE%\bin\splenviron.cmd -e %SPLENVIRON%
```

For example:

```
D:\ouaf\TEST_ENVIRON1\bin\splenviron.cmd -e TEST_ENVIRON1
```

3. Execute the following script to generate all information.

UNIX:

```
ksh $SPLEBASE/bin/genappvieweritems.sh
```

Windows:

```
%SPLEBASE%\bin\genappvieweritems.cmd
```

4. Restart your application

Installation Verification Checklist

After you complete the installation, verify the following:

1. Verify installation logs created under decompressed installer location for any errors.
2. Confirm installation logs do not contain any errors.
3. Confirm all the configurations are correct. Refer to Installation and Configuration Worksheets for details.
4. Confirm that the database is ready.
5. Start the application server. For instructions, refer to Appendix **Common Maintenance Activities**.
6. Verify Application deployment status.
 - a. Login to Weblogic Console.
 - b. Click on Deployment link
 - b. Verify the following application deployments are Active or not.
 - SPLService
 - "SPLWeb
 - "SPLAdf
 - "Mapviewer
3. Verify the Data Source Configuration.
4. To operate the application, refer to the next section.

Accessing the Application

1. Start up the environment by running the following command:

```
UNIX: spl.sh start
```

```
Windows: spl.cmd start
```

2. Follow the messages on the screen along with the logs in \$SPLSYSTEMLOGS directory to ensure that the environment was started successfully.
3. If the startup failed, identify the problem by reviewing the log files. Resolve any issues before attempting to restart the environment.
4. Once the application is up and running (can be viewed from logs file) then try to access the application via below URL

`http://<host name>:<port name>/<WebContext>`

Appendix A

Common Maintenance Activities

This appendix lists frequently-used commands that you use to perform common maintenance activities, such as starting and stopping the environment and thread pool worker, modifying the configuration items.

Run the following commands to perform these common tasks:

To Initialize the Environment

1. Go the directory <install_dir>/bin.
2. Run the following command:

UNIX:

```
./splenviron.sh -e <Env_Name>
```

Windows:

```
splenviron.cmd -e <Env_Name>
```

To Start the WebLogic Server

1. Initialize the environment.
2. Run the following command:

UNIX:

```
./spl.sh start
```

Windows:

```
spl.cmd start
```

To Stop the Batch Server

1. To Stop the BatchScheduler:

UNIX:

```
cd $SPLEBASE/bin  
batchscheduler.sh stop
```

Windows:

```
cd %SPLEBASE%\bin  
batchscheduler.cmd stop
```

To Start the Batch Scheduler

1. Run the following command:

UNIX:

```
cd $SPLEBASE/bin  
nohup batchscheduler.sh NodeID > /tmp/batchscheduler.log 2>&1 &
```

Windows:

```
cd %SPLEBASE%\bin  
batchscheduler.cmd NODEID
```

Note: The application domain node ID must be unique value across the environment. This value is used for a scheduler running from Threadpoolworker.

To Stop the Batch Scheduler

1. To stop the batch scheduler

UNIX:

```
cd $SPLEBASE/bin  
batchscheduler.sh stop
```

Windows:

```
cd %SPLEBASE%\bin  
batchscheduler.cmd stop
```

To Check Whether the BatchScheduler is running:

1. To check whether the batch scheduler is running

UNIX:

```
cd $SPLEBASE/bin  
batchscheduler.sh check
```

Windows:

```
cd %SPLEBASE%\bin  
batchscheduler.cmd check
```

To Modify the Configuration Values

1. Initialize the environment.
2. Run the following command:

UNIX:

```
ConfigureEnv.sh
```

Windows:

```
configureEnv.cmd
```

The configuration utility launches menu items. Select any Menu option.

3. Change the menu values.
4. After you change the menu values, press P to write the changes to the configuration file.
5. To apply the changes to the environment, run the initial setup script:

```
InitialSetup.sh,
```

To Modify the Advanced Menu Option Values

1. Initialize the environment.

The configuration utility launches menu items.

-
2. Run the following command:

UNIX:

```
ConfigureEnv.sh -a
```

Windows:

```
configureEnv.cmd -a
```

3. Select any menu option.
4. Change the menu values.
5. To apply the changes to the environment, run initial setup script:

```
InitialSetup.sh
```

Appendix B

Application Framework Prerequisite Patches

Oracle Utilities Application Framework patches must be installed prior to installing Oracle Real-Time Scheduler 2.1.0. The patches listed below are available as a convenience rollup, ORS-V2.1.0-FW-PREREQ-Multiplatform.zip, which is included in the downloaded Media Pack. Please refer to the instructions contained inside the rollup directory for steps to install the patches.

8503140	10357429	11061063	11802524	12355589
8901782	10357830	11065275	11805029	12357553
9042555	10359905	11065841	11810803	12358078
9382171	10360341	11066173	11812272	12369181
9387114	10360688	11068621	11825658	12369294
9411693	10363621	11068834	11825757	12375706
9455478	10363763	11070215	11825763	12377282
9527752	10366259	11071551	11826984	12380588
9540205	10367747	11074152	11827061	12388252
9564113	10367860	11077044	11828290	12388695
9569173	10368770	11078114	11829323	12390834
9618908	10371591	11659316	11831954	12394303
9682934	10374208	11659469	11831962	12396557
9704052	10374359	11671144	11836696	12397361
9712702	10374799	11673372	11837168	12398660
9728543	10375560	11675596	11838963	12401741
9803711	10375660	11676685	11838977	12404368
9808306	10375682	11677625	11840470	12412886
9822605	10376226	11684041	11844142	12415869
9943141	10376879	11684640	11844499	12417483
10014729	10380556	11686129	11846353	12417960

10073615	10382474	11686789	11848622	12428239
10133277	10383911	11687677	11849058	12432357
10179538	10385291	11688966	11865125	12432996
10189618	10387212	11689021	11870260	12536674
10215092	10390304	11689086	11870708	12537292
10222412	10391114	11689155	11875008	12539014
10235438	10391578	11689215	11875029	12546120
10235446	10393148	11690177	11880325	12546220
10235453	10397029	11691074	11881465	12548444
10235472	10399041	11691830	11882316	12548945
10240362	10399826	11691896	11882984	12556076
10263033	10400934	11694867	11886308	12558316
10271480	10401066	11698997	11886487	12560045
10281572	10403427	11699913	11888040	12561191
10281995	10407066	11700127	11888244	12564985
10283802	10411296	11700177	11890627	12564994
10289114	10411845	11703071	11893511	12565011
10289228	10412102	11706217	11894700	12567535
10296970	10413137	11708221	11896216	12574075
10297667	10413650	11709380	11897375	12578692
10301578	10413698	11711736	11900153	12584797
10304568	10416888	11712334	11900457	12593383
10306334	10419736	11713020	11903828	12632749
10311204	10419846	11714753	11904426	12680209
10312418	10420485	11714946	11930834	12703227
10314476	10422028	11718025	11935491	12774795
10314612	10424407	11718917	11935602	12844738
10316317	10428600	11724144	11937218	12874623
10316391	10428634	11725991	11937452	12875351
10316953	10435878	11729096	12327094	12932177
10318333	10623053	11731141	12327124	12938862
10321540	10624363	11735128	12329849	12958675
10321550	10625431	11735716	12337775	13089263
10322062	10625739	11738085	12338323	13089288

10324881	10631948	11739404	12340553	13337860
10325215	10632029	11742563	12344492	13341098
10326258	10636556	11742578	12344520	12824646
10327827	10638783	11744412	12354548	12833920
10329860	10639236	11785204	12355193	12861580
10330794	10639817	11790352	12355336	12877756
10334495	10640366	11791685	12355345	12975725
10334505	10647519	11793264	12355355	13399762
10335027	10649131	11800924	12355359	13339778
10356504	11055998	11800964	12355545	12888985
10356860	11056031	11802408	12355578	

Appendix C

License and Copyright Notices

License and Copyright notices for associated products:

Third Party Products

Notice concerning usage of ANTLR and Classycle

[The BSD License]

Copyright (c) 2010 Terence Parr

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

Neither the name of the author nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

\THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Notice concerning usage of Apache Software

The following are covered under the Apache 2.0 license.

1. bsf-2.4.0.jar

2. castor-1.3.1-core.jar
3. castor-1.3.1-xml.jar
4. castor-1.3.1-xml-schema.jar
5. cglib-2.2.jar
6. classycle.1.1.jar
7. commons-beanutils-core-1.8.1.jar
8. commons-cli-1.1.jar
9. commons-codec-1.4.jar
10. commons-collections-3.1.jar
11. commons-fileupload-1.2.1.jar
12. commons-httpclient-3.0.1.jar
13. commons-io-1.3.2.jar
14. commons-lang-2.2.jar
15. ehcache-1.2.3.jar
16. log4j-1.2.15.jar
17. qdox.1.6.1.jar
18. serializer-2.7.1.jar
19. stax2.jar
20. velocity.1.4.jar
21. wstx-asl-3.2.1.jar
22. xalan-mod-2.7.1.jar
23. xmlparserv2.jar

Apache License

Version 2.0, January 2004

<http://www.apache.org/licenses/>

TERMS AND CONDITIONS FOR USE, REPRODUCTION, AND DISTRIBUTION

1. Definitions.

"License" shall mean the terms and conditions for use, reproduction, and distribution as defined by Sections 1 through 9 of this document.

"Licensor" shall mean the copyright owner or entity authorized by the copyright owner that is granting the License.

"Legal Entity" shall mean the union of the acting entity and all other entities that control, are controlled by, or are under common control with that entity. For the purposes of this definition, "control" means (i) the power, direct or indirect, to cause the direction or management of such entity, whether by contract or otherwise, or (ii) ownership of fifty percent (50%) or more of the outstanding shares, or (iii) beneficial ownership of such entity.

"You" (or "Your") shall mean an individual or Legal Entity exercising permissions granted by this License.

"Source" form shall mean the preferred form for making modifications, including but not limited to software source code, documentation source, and configuration files.

"Object" form shall mean any form resulting from mechanical transformation or translation of a Source form, including but not limited to compiled object code, generated documentation, and conversions to other media types.

"Work" shall mean the work of authorship, whether in Source or Object form, made available under the License, as indicated by a copyright notice that is included in or attached to the work (an example is provided in the Appendix below).

"Derivative Works" shall mean any work, whether in Source or Object form, that is based on (or derived from) the Work and for which the editorial revisions, annotations, elaborations, or other modifications represent, as a whole, an original work of authorship. For the purposes of this License, Derivative Works shall not include works that remain separable from, or merely link (or bind by name) to the interfaces of, the Work and Derivative Works thereof.

"Contribution" shall mean any work of authorship, including the original version of the Work and any modifications or additions to that Work or Derivative Works thereof, that is intentionally submitted to Licensor for inclusion in the Work by the copyright owner or by an individual or Legal Entity authorized to submit on behalf of the copyright owner. For the purposes of this definition, "submitted" means any form of electronic, verbal, or written communication sent to the Licensor or its representatives, including but not limited to communication on electronic mailing lists, source code control systems, and issue tracking systems that are managed by, or on behalf of, the Licensor for the purpose of discussing and improving the Work, but excluding communication that is conspicuously marked or otherwise designated in writing by the copyright owner as "Not a Contribution."

"Contributor" shall mean Licensor and any individual or Legal Entity on behalf of whom a Contribution has been received by Licensor and subsequently incorporated within the Work.

2. Grant of Copyright License. Subject to the terms and conditions of this License, each Contributor hereby grants to You a perpetual, worldwide, non-exclusive, no-charge, royalty-free, irrevocable copyright license to reproduce, prepare Derivative Works of, publicly display, publicly perform, sublicense, and distribute the Work and such Derivative Works in Source or Object form.

3. Grant of Patent License. Subject to the terms and conditions of this License, each Contributor hereby grants to You a perpetual, worldwide, non-exclusive, no-charge, royalty-free, irrevocable (except as stated in this section) patent license to make, have made, use, offer to sell, sell, import, and otherwise transfer the Work, where such license applies only to those patent claims licensable by such Contributor that are necessarily infringed by their Contribution(s) alone or by combination of their Contribution(s) with the Work to which such Contribution(s) was submitted. If You institute patent litigation against any entity (including a cross-claim or counterclaim in a lawsuit) alleging that the Work or a Contribution incorporated within the Work constitutes direct or contributory patent infringement, then any patent licenses granted to You under this License for that Work shall terminate as of the date such litigation is filed.

4. Redistribution. You may reproduce and distribute copies of the Work or Derivative Works thereof in any medium, with or without modifications, and in Source or Object form, provided that You meet the following conditions:

You must give any other recipients of the Work or Derivative Works a copy of this License; and
You must cause any modified files to carry prominent notices stating that You changed the files; and

You must retain, in the Source form of any Derivative Works that You distribute, all copyright, patent, trademark, and attribution notices from the Source form of the Work, excluding those notices that do not pertain to any part of the Derivative Works; and

If the Work includes a "NOTICE" text file as part of its distribution, then any Derivative Works that You distribute must include a readable copy of the attribution notices contained within such

NOTICE file, excluding those notices that do not pertain to any part of the Derivative Works, in at least one of the following places: within a NOTICE text file distributed as part of the Derivative Works; within the Source form or documentation, if provided along with the Derivative Works; or, within a display generated by the Derivative Works, if and wherever such third-party notices normally appear. The contents of the NOTICE file are for informational purposes only and do not modify the License. You may add Your own attribution notices within Derivative Works that You distribute, alongside or as an addendum to the NOTICE text from the Work, provided that such additional attribution notices cannot be construed as modifying the License. You may add Your own copyright statement to Your modifications and may provide additional or different license terms and conditions for use, reproduction, or distribution of Your modifications, or for any such Derivative Works as a whole, provided Your use, reproduction, and distribution of the Work otherwise complies with the conditions stated in this License.

5. Submission of Contributions. Unless You explicitly state otherwise, any Contribution intentionally submitted for inclusion in the Work by You to the Licensor shall be under the terms and conditions of this License, without any additional terms or conditions. Notwithstanding the above, nothing herein shall supersede or modify the terms of any separate license agreement you may have executed with Licensor regarding such Contributions.

6. Trademarks. This License does not grant permission to use the trade names, trademarks, service marks, or product names of the Licensor, except as required for reasonable and customary use in describing the origin of the Work and reproducing the content of the NOTICE file.

7. Disclaimer of Warranty. Unless required by applicable law or agreed to in writing, Licensor provides the Work (and each Contributor provides its Contributions) on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied, including, without limitation, any warranties or conditions of TITLE, NON-INFRINGEMENT, MERCHANTABILITY, or FITNESS FOR A PARTICULAR PURPOSE. You are solely responsible for determining the appropriateness of using or redistributing the Work and assume any risks associated with Your exercise of permissions under this License.

8. Limitation of Liability. In no event and under no legal theory, whether in tort (including negligence), contract, or otherwise, unless required by applicable law (such as deliberate and grossly negligent acts) or agreed to in writing, shall any Contributor be liable to You for damages, including any direct, indirect, special, incidental, or consequential damages of any character arising as a result of this License or out of the use or inability to use the Work (including but not limited to damages for loss of goodwill, work stoppage, computer failure or malfunction, or any and all other commercial damages or losses), even if such Contributor has been advised of the possibility of such damages.

9. Accepting Warranty or Additional Liability. While redistributing the Work or Derivative Works thereof, You may choose to offer, and charge a fee for, acceptance of support, warranty, indemnity, or other liability obligations and/or rights consistent with this License. However, in accepting such obligations, You may act only on Your own behalf and on Your sole responsibility, not on behalf of any other Contributor, and only if You agree to indemnify, defend, and hold each Contributor harmless for any liability incurred by, or claims asserted against, such Contributor by reason of your accepting any such warranty or additional liability.

END OF TERMS AND CONDITIONS

Notice concerning usage of ASM

Copyright (c) 2000-2005 INRIA, France Telecom

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

3. Neither the name of the copyright holders nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE)

ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Notice concerning usage of Concurrent

All classes are released to the public domain and may be used for any purpose whatsoever without permission or acknowledgment. <http://g.oswego.edu/dl/classes/EDU/oswego/cs/dl/util/concurrent/intro.html>

Notice concerning usage of dom4j

Copyright 2001-2010 (C) MetaStuff, Ltd. All Rights Reserved.

Redistribution and use of this software and associated documentation ("Software"), with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain copyright statements and notices. Redistributions must also contain a copy of this document.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. The name "DOM4J" must not be used to endorse or promote products derived from this Software without prior written permission of MetaStuff, Ltd. For written permission, please contact dom4j-info@metastuff.com.
4. Products derived from this Software may not be called "DOM4J" nor may "DOM4J" appear in their names without prior written permission of MetaStuff, Ltd. DOM4J is a registered trademark of MetaStuff, Ltd.
5. Due credit should be given to the DOM4J Project - <http://dom4j.sourceforge.net>

THIS SOFTWARE IS PROVIDED BY METASTUFF, LTD. AND CONTRIBUTORS ``AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL METASTUFF, LTD. OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR

SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Notice concerning usage of International Components for Unicode (ICU4J)

COPYRIGHT AND PERMISSION NOTICE

Copyright (c) 1995-2010 International Business Machines Corporation and others

All rights reserved.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, provided that the above copyright notice(s) and this permission notice appear in all copies of the Software and that both the above copyright notice(s) and this permission notice appear in supporting documentation.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OF THIRD PARTY RIGHTS. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR HOLDERS INCLUDED IN THIS NOTICE BE LIABLE FOR ANY CLAIM, OR ANY SPECIAL INDIRECT OR CONSEQUENTIAL DAMAGES, OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

Except as contained in this notice, the name of a copyright holder shall not be used in advertising or otherwise to promote the sale, use or other dealings in this Software without prior written authorization of the copyright holder.

Notice concerning usage of Jaxen

/*

Copyright 2003-2006 The Werken Company. All Rights Reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- * Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

- * Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

- * Neither the name of the Jaxen Project nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR

CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

*/

Notice concerning usage of JCIP Annotations

Attribution 2.5

CREATIVE COMMONS CORPORATION IS NOT A LAW FIRM AND DOES NOT PROVIDE LEGAL SERVICES. DISTRIBUTION OF THIS LICENSE DOES NOT CREATE AN ATTORNEY-CLIENT RELATIONSHIP. CREATIVE COMMONS PROVIDES THIS INFORMATION ON AN "AS-IS" BASIS. CREATIVE COMMONS MAKES NO WARRANTIES REGARDING THE INFORMATION PROVIDED, AND DISCLAIMS LIABILITY FOR DAMAGES RESULTING FROM ITS USE.

License

THE WORK (AS DEFINED BELOW) IS PROVIDED UNDER THE TERMS OF THIS CREATIVE COMMONS PUBLIC LICENSE ("CCPL" OR "LICENSE"). THE WORK IS PROTECTED BY COPYRIGHT AND/OR OTHER APPLICABLE LAW. ANY USE OF THE WORK OTHER THAN AS AUTHORIZED UNDER THIS LICENSE OR COPYRIGHT LAW IS PROHIBITED.

BY EXERCISING ANY RIGHTS TO THE WORK PROVIDED HERE, YOU ACCEPT AND AGREE TO BE BOUND BY THE TERMS OF THIS LICENSE. THE LICENSOR GRANTS YOU THE RIGHTS CONTAINED HERE IN CONSIDERATION OF YOUR ACCEPTANCE OF SUCH TERMS AND CONDITIONS.

1. Definitions

1. "Collective Work" means a work, such as a periodical issue, anthology or encyclopedia, in which the Work in its entirety in unmodified form, along with a number of other contributions, constituting separate and independent works in themselves, are assembled into a collective whole. A work that constitutes a Collective Work will not be considered a Derivative Work (as defined below) for the purposes of this License.
2. "Derivative Work" means a work based upon the Work or upon the Work and other pre-existing works, such as a translation, musical arrangement, dramatization, fictionalization, motion picture version, sound recording, art reproduction, abridgment, condensation, or any other form in which the Work may be recast, transformed, or adapted, except that a work that constitutes a Collective Work will not be considered a Derivative Work for the purpose of this License. For the avoidance of doubt, where the Work is a musical composition or sound recording, the synchronization of the Work in timed-relation with a moving image ("synching") will be considered a Derivative Work for the purpose of this License.
3. "Licensor" means the individual or entity that offers the Work under the terms of this License.
4. "Original Author" means the individual or entity who created the Work.
5. "Work" means the copyrightable work of authorship offered under the terms of this License.
6. "You" means an individual or entity exercising rights under this License who has not previously violated the terms of this License with respect to the Work, or who has received express permission from the Licensor to exercise rights under this License despite a previous violation.

2. Fair Use Rights. Nothing in this license is intended to reduce, limit, or restrict any rights arising from fair use, first sale or other limitations on the exclusive rights of the copyright owner under copyright law or other applicable laws.

3. License Grant. Subject to the terms and conditions of this License, Licensor hereby grants You a worldwide, royalty-free, non-exclusive, perpetual (for the duration of the applicable copyright) license to exercise the rights in the Work as stated below:

1. to reproduce the Work, to incorporate the Work into one or more Collective Works, and to reproduce the Work as incorporated in the Collective Works;
2. to create and reproduce Derivative Works;
3. to distribute copies or phonorecords of, display publicly, perform publicly, and perform publicly by means of a digital audio transmission the Work including as incorporated in Collective Works;
4. to distribute copies or phonorecords of, display publicly, perform publicly, and perform publicly by means of a digital audio transmission Derivative Works.
- 5.

For the avoidance of doubt, where the work is a musical composition:

1. Performance Royalties Under Blanket Licenses. Licensor waives the exclusive right to collect, whether individually or via a performance rights society (e.g. ASCAP, BMI, SESAC), royalties for the public performance or public digital performance (e.g. webcast) of the Work.

2. Mechanical Rights and Statutory Royalties. Licensor waives the exclusive right to collect, whether individually or via a music rights agency or designated agent (e.g. Harry Fox Agency), royalties for any phonorecord You create from the Work ("cover version") and distribute, subject to the compulsory license created by 17 USC Section 115 of the US Copyright Act (or the equivalent in other jurisdictions).

6. Webcasting Rights and Statutory Royalties. For the avoidance of doubt, where the Work is a sound recording, Licensor waives the exclusive right to collect, whether individually or via a performance-rights society (e.g. SoundExchange), royalties for the public digital performance (e.g. webcast) of the Work, subject to the compulsory license created by 17 USC Section 114 of the US Copyright Act (or the equivalent in other jurisdictions).

The above rights may be exercised in all media and formats whether now known or hereafter devised. The above rights include the right to make such modifications as are technically necessary to exercise the rights in other media and formats. All rights not expressly granted by Licensor are hereby reserved.

4. Restrictions. The license granted in Section 3 above is expressly made subject to and limited by the following restrictions:

1. You may distribute, publicly display, publicly perform, or publicly digitally perform the Work only under the terms of this License, and You must include a copy of, or the Uniform Resource Identifier for, this License with every copy or phonorecord of the Work You distribute, publicly display, publicly perform, or publicly digitally perform. You may not offer or impose any terms on the Work that alter or restrict the terms of this License or the recipients' exercise of the rights granted hereunder. You may not sublicense the Work. You must keep intact all notices that refer to this License and to the disclaimer of warranties. You may not distribute, publicly display, publicly perform, or publicly digitally perform the Work with any technological measures that control access or use of the Work in a manner inconsistent with the terms of this License Agreement. The above applies to the Work as incorporated in a Collective Work, but this does not require the Collective Work apart from the Work itself to be made subject to the terms of this License. If You create a Collective Work, upon notice from any Licensor You must, to the extent practicable, remove from the Collective Work any credit as required by clause 4(b), as requested. If You create a Derivative

Work, upon notice from any Licensor You must, to the extent practicable, remove from the Derivative Work any credit as required by clause 4(b), as requested.

2. If you distribute, publicly display, publicly perform, or publicly digitally perform the Work or any Derivative Works or Collective Works, You must keep intact all copyright notices for the Work and provide, reasonable to the medium or means You are utilizing: (i) the name of the Original Author (or pseudonym, if applicable) if supplied, and/or (ii) if the Original Author and/or Licensor designate another party or parties (e.g. a sponsor institute, publishing entity, journal) for attribution in Licensor's copyright notice, terms of service or by other reasonable means, the name of such party or parties; the title of the Work if supplied; to the extent reasonably practicable, the Uniform Resource Identifier, if any, that Licensor specifies to be associated with the Work, unless such URI does not refer to the copyright notice or licensing information for the Work; and in the case of a Derivative Work, a credit identifying the use of the Work in the Derivative Work (e.g., "French translation of the Work by Original Author," or "Screenplay based on original Work by Original Author"). Such credit may be implemented in any reasonable manner; provided, however, that in the case of a Derivative Work or Collective Work, at a minimum such credit will appear where any other comparable authorship credit appears and in a manner at least as prominent as such other comparable authorship credit.

5. Representations, Warranties and Disclaimer

UNLESS OTHERWISE MUTUALLY AGREED TO BY THE PARTIES IN WRITING, LICENSOR OFFERS THE WORK AS-IS AND MAKES NO REPRESENTATIONS OR WARRANTIES OF ANY KIND CONCERNING THE WORK, EXPRESS, IMPLIED, STATUTORY OR OTHERWISE, INCLUDING, WITHOUT LIMITATION, WARRANTIES OF TITLE, MERCHANTIBILITY, FITNESS FOR A PARTICULAR PURPOSE, NONINFRINGEMENT, OR THE ABSENCE OF LATENT OR OTHER DEFECTS, ACCURACY, OR THE PRESENCE OF ABSENCE OF ERRORS, WHETHER OR NOT DISCOVERABLE. SOME JURISDICTIONS DO NOT ALLOW THE EXCLUSION OF IMPLIED WARRANTIES, SO SUCH EXCLUSION MAY NOT APPLY TO YOU.

6. Limitation on Liability. EXCEPT TO THE EXTENT REQUIRED BY APPLICABLE LAW, IN NO EVENT WILL LICENSOR BE LIABLE TO YOU ON ANY LEGAL THEORY FOR ANY SPECIAL, INCIDENTAL, CONSEQUENTIAL, PUNITIVE OR EXEMPLARY DAMAGES ARISING OUT OF THIS LICENSE OR THE USE OF THE WORK, EVEN IF LICENSOR HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

7. Termination

1. This License and the rights granted hereunder will terminate automatically upon any breach by You of the terms of this License. Individuals or entities who have received Derivative Works or Collective Works from You under this License, however, will not have their licenses terminated provided such individuals or entities remain in full compliance with those licenses. Sections 1, 2, 5, 6, 7, and 8 will survive any termination of this License.

2. Subject to the above terms and conditions, the license granted here is perpetual (for the duration of the applicable copyright in the Work). Notwithstanding the above, Licensor reserves the right to release the Work under different license terms or to stop distributing the Work at any time; provided, however that any such election will not serve to withdraw this License (or any other license that has been, or is required to be, granted under the terms of this License), and this License will continue in full force and effect unless terminated as stated above.

8. Miscellaneous

1. Each time You distribute or publicly digitally perform the Work or a Collective Work, the Licensor offers to the recipient a license to the Work on the same terms and conditions as the license granted to You under this License.

2. Each time You distribute or publicly digitally perform a Derivative Work, Licensor offers to the recipient a license to the original Work on the same terms and conditions as the license granted to You under this License.

3. If any provision of this License is invalid or unenforceable under applicable law, it shall not affect the validity or enforceability of the remainder of the terms of this License, and without further action by the parties to this agreement, such provision shall be reformed to the minimum extent necessary to make such provision valid and enforceable.

4. No term or provision of this License shall be deemed waived and no breach consented to unless such waiver or consent shall be in writing and signed by the party to be charged with such waiver or consent.

5. This License constitutes the entire agreement between the parties with respect to the Work licensed here. There are no understandings, agreements or representations with respect to the Work not specified here. Licensor shall not be bound by any additional provisions that may appear in any communication from You. This License may not be modified without the mutual written agreement of the Licensor and You.

Creative Commons is not a party to this License, and makes no warranty whatsoever in connection with the Work. Creative Commons will not be liable to You or any party on any legal theory for any damages whatsoever, including without limitation any general, special, incidental or consequential damages arising in connection to this license. Notwithstanding the foregoing two (2) sentences, if Creative Commons has expressly identified itself as the Licensor hereunder, it shall have all rights and obligations of Licensor.

Except for the limited purpose of indicating to the public that the Work is licensed under the CCPL, neither party will use the trademark "Creative Commons" or any related trademark or logo of Creative Commons without the prior written consent of Creative Commons. Any permitted use will be in compliance with Creative Commons' then-current trademark usage guidelines, as may be published on its website or otherwise made available upon request from time to time.

Creative Commons may be contacted at <http://creativecommons.org/>.

Notice concerning usage of XStream

Copyright (c) 2003-2006, Joe Walnes

Copyright (c) 2006-2007, XStream Committers

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

Neither the name of XStream nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY

THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Notice concerning usage of slf4j

SLF4J source code and binaries are distributed under the MIT license.

Copyright (c) 2004-2008 QOS.ch

All rights reserved.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Notice concerning usage of Perl

Perl Kit, Version 5

Copyright (C) 1993, 1994, 1995, 1996, 1997, 1998, 1999, 2000, 2001, by Larry Wall and others

All rights reserved.

This program is free software; it is being redistributed under the terms of the "Artistic License".

The Artistic License

Preamble

The intent of this document is to state the conditions under which a Package may be copied, such that the Copyright Holder maintains some semblance of artistic control over the development of the package, while giving the users of the package the right to use and distribute the Package in a more-or-less customary fashion, plus the right to make reasonable modifications.

Definitions:

"Package" refers to the collection of files distributed by the Copyright Holder, and derivatives of that collection of files created through textual modification.

"Standard Version" refers to such a Package if it has not been modified, or has been modified in accordance with the wishes of the Copyright Holder.

"Copyright Holder" is whoever is named in the copyright or copyrights for the package.

"You" is you, if you're thinking about copying or distributing this Package.

"Reasonable copying fee" is whatever you can justify on the basis of media cost, duplication charges, time of people involved, and so on. (You will not be required to justify it to the Copyright Holder, but only to the computing community at large as a market that must bear the fee.)

"Freely Available" means that no fee is charged for the item itself, though there may be fees involved in handling the item. It also means that recipients of the item may redistribute it under the same conditions they received it.

1.You may make and give away verbatim copies of the source form of the Standard Version of this Package without restriction, provided that you duplicate all of the original copyright notices and associated disclaimers.

2.You may apply bug fixes, portability fixes and other modifications derived from the Public Domain or from the Copyright Holder. A Package modified in such a way shall still be considered the Standard Version.

3.You may otherwise modify your copy of this Package in any way, provided that you insert a prominent notice in each changed file stating how and when you changed that file, and provided that you do at least ONE of the following:

- 1.place your modifications in the Public Domain or otherwise make them Freely Available, such as by posting said modifications to Usenet or an equivalent medium, or placing the modifications on a major archive site such as ftp.uu.net, or by allowing the Copyright Holder to include your modifications in the Standard Version of the Package.
- 2.use the modified Package only within your corporation or organization.
- 3.rename any non-standard executables so the names do not conflict with standard executables, which must also be provided, and provide a separate manual page for each non-standard executable that clearly documents how it differs from the Standard Version.
- 4.make other distribution arrangements with the Copyright Holder.

4.You may distribute the programs of this Package in object code or executable form, provided that you do at least ONE of the following:

- a)distribute a Standard Version of the executables and library files, together with instructions (in the manual page or equivalent) on where to get the Standard Version.
- b)accompany the distribution with the machine-readable source of the Package with your modifications.
- c)accompany any non-standard executables with their corresponding Standard Version executables, giving the non-standard executables non-standard names, and clearly documenting the differences in manual pages (or equivalent), together with instructions on where to get the Standard Version.
- d)make other distribution arrangements with the Copyright Holder.

5.You may charge a reasonable copying fee for any distribution of this Package. You may charge any fee you choose for support of this Package. You may not charge a fee for this Package itself. However, you may distribute this Package in aggregate with other (possibly commercial) programs as part of a larger (possibly commercial) software distribution provided that you do not advertise this Package as a product of your own.

6.The scripts and library files supplied as input to or produced as output from the programs of this Package do not automatically fall under the copyright of this Package, but belong to whomever generated them, and may be sold commercially, and may be aggregated with this Package.

7.C or perl subroutines supplied by you and linked into this Package shall not be considered part of this Package.

8.The name of the Copyright Holder may not be used to endorse or promote products derived from this software without specific prior written permission.

9.THIS PACKAGE IS PROVIDED "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, WITHOUT LIMITATION, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE.

The End

Notice concerning usage of Mime-Base64 Perl Module

Copyright 1995-1999,2001-2004 Gisle Aas <gisle@ActiveState.com>

This library is free software; you can redistribute it and/or modify it under the same terms as Perl itself.

The standard version of the package that is used can be obtained from <http://www.cpan.org>.

Specifically, the software can be obtained from the following link :

<http://search.cpan.org/search%3fmodule=MIME::Base64>

Notice concerning usage of Mime-Lite Perl Module

This is MIME::Lite 3.01 Maintenance release

TERMS AND CONDITIONS

Copyright (c) 1997 by Eryq.

Copyright (c) 1998 by ZeeGee Software Inc.

Copyright (c) 2003 Yves Orton. demerphq (at) hotmail.com.

All rights reserved. This program is free software; you can redistribute it and/or modify it under the same terms as Perl itself.

This software comes with NO WARRANTY of any kind. See the COPYING file in the distribution for details.

The standard version of the package that is used can be obtained from <http://www.cpan.org>.

Specifically, the software can be obtained from the following link :

<http://search.cpan.org/search%3fmodule=MIME::Lite>

Notice concerning usage of DBD::DB2 Perl Module

License Agreement for DBD::DB2

PLEASE READ THIS AGREEMENT CAREFULLY BEFORE INSTALLING OR USING THIS PROGRAM. IF YOU INSTALL OR USE THIS PROGRAM, YOU AGREE TO THESE TERMS.

1. This DBD::DB2 code "Program" is owned by International Business Machines Corporation or its subsidiaries (IBM) or IBM's suppliers, and is copyrighted and licensed, not sold. IBM retains title to the Program, and grants the user of the Program "You" an:

irrevocable, worldwide, nonexclusive, perpetual, royalty-free and fully paid-up license

- (i) to use, execute, display, perform, and reproduce the Program,
- (ii) to prepare derivative works based on the Program,
- (iii) to distribute copies of the Program and derivative works thereof, and
- (iv) to authorize others to do all of the above.

2. You must reproduce the copyright notice and any other legend of ownership on each copy or partial copy of the Program.

3. IBM would appreciate receiving a copy of derivative works of the Program that You create. You may provide to IBM such derivative works pursuant to the terms of this Agreement and the directions in the README file contained within the Program directory. You represent and warrant to IBM that You are the sole author of, and/or have full exclusive right, title and interest to any and all derivative works You provide to IBM. You further represent that You are under no obligation to assign your rights in such derivative works to any third-party, including without limitation, any current or former employer.

4. You agree that IBM may utilize all information, ideas, concepts, know-how or techniques furnished by You to IBM in connection with any derivative works You make or have made to the IBM Program, and that You provide to IBM and IBM may, but shall not be obligated to, include such derivative works in the IBM Program or in any IBM product without accounting to You.

5. With respect to any derivative works of the Program You provide to IBM, You grant to IBM an:

irrevocable, worldwide, non-exclusive, perpetual, royalty--free and fully paid-up license

(i) to use, execute, display, perform, and reproduce your derivative works,

(ii) to prepare derivative works based upon your derivative works,

(iii) to distribute copies of your derivative works, and

(iv) to authorize others to do all of the above.

6. YOU UNDERSTAND THAT THE PROGRAM IS BEING PROVIDED TO YOU "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY IMPLIED WARRANTIES OF MERCHANTABILITY, QUALITY, PERFORMANCE, INTELLECTUAL PROPERTY INFRINGEMENT OR FITNESS FOR ANY PARTICULAR PURPOSE. IBM has no obligation to provide service, defect correction, or any maintenance for the Program. IBM has no obligation to supply any Program updates or enhancements to You even if such are or later become available.

7. IBM accepts no liability for damages You may suffer as a result of your use of the Program. Under no circumstances is IBM liable for any of the following:

1. third-party claims against You for losses or damages;

3. loss of, or damage to, your records or data; or

4. direct damages, lost profits, lost savings, incidental, special, or indirect damages or consequential damages, even if IBM or its authorized supplier, has been advised of the possibility of such damages.

8. Some jurisdictions do not allow these limitations or exclusions, so they may not apply to You.

9. You are responsible for the payment of any taxes resulting from this license.

10. You agree not to bring a legal action more than two years after the cause of action arose.

11. This license will be governed by and interpreted in accordance with the laws of the State of New York.

12. This license is the only understanding and agreement IBM has for your use of the Program.

The standard version of the package that is used can be obtained from <http://www.cpan.org>.

Specifically, the software can be obtained from the following link :

<http://search.cpan.org/search%3fmodule=DBD::DB2>

Notice concerning usage of DBI Perl Module

DBI by Tim Bunce. This pod text by Tim Bunce, J. Douglas Dunlop,

Jonathan Leffler and others. Perl by Larry Wall and the perl5-porters.

COPYRIGHT

The DBI module is Copyright (c) 1994-2004 Tim Bunce. Ireland.

All rights reserved.

This is distributed under the terms of the Artistic License.

The standard version of the package that is used can be obtained from <http://www.cpan.org>.

Specifically, the software can be obtained from the following link :

<http://search.cpan.org/search%3fmodule=DBD::DB2>