

Name	disable-monitoring– disables monitoring for the server or for specific monitorable objects
Synopsis	disable-monitoring [--help] --modules <i>module-name</i> web-container,ejb-container
Description	<p>The disable-monitoring subcommand is used to turn off monitoring for Enterprise Server or for particular modules during runtime. Changes are dynamic, that is, server restart is not required.</p> <p>Running the disable-monitoring subcommand without the --module option disables the monitoring service by setting the monitoring-enabled attribute of the monitoring-service element is false. The individual modules retain their monitoring levels, but no monitoring data is generated because the entire monitoring service is disabled.</p> <p>This subcommand used with the --modules option disables monitoring for a module by setting the monitoring level to OFF. The status of the monitoring service is not affected. For a list of monitorable modules, see the --modules option in this help page.</p> <p>An alternative method for disabling monitoring is to use the set subcommand. In this case, the server must be restarted for changes to take effect.</p> <p>This subcommand is supported in remote mode only.</p>
Options	<p>--help Displays the help text for the subcommand.</p> <p>--modules <i>module-name</i> Disables the specified module or modules by setting the monitoring level to OFF. Multiple modules are separated by , (comma). Monitorable modules include connector-connection-pool, connector-service, ejb-container, http-service, jdbc-connection-pool, jersey, jpa, jms-service, jvm, security, thread-pool, transaction-service, web-container, and web-services-container. Additional modules can be listed by using the get subcommand.</p>
Examples	<p>EXAMPLE 1 Disabling the Monitoring Service for Enterprise Server</p> <p>This example disables monitoring for Enterprise Server in general by setting the enable-monitoring flag to false (default is true).</p> <pre>asadmin> disable-monitoring Command disable-monitoring executed successfully</pre> <p>EXAMPLE 2 Disabling Monitoring for the Web and EJB Containers</p> <p>This example disables monitoring for specific containers. Their monitoring levels are set to OFF.</p> <pre>asadmin> disable-monitoring --modules web-container,ejb-container Command disable-monitoring executed successfully</pre>
Exit Status	0 subcommand executed successfully

1 error in executing the subcommand

See Also enable-monitoring, list-monitoring-levels, [monitor\(1\)](#), [list\(1\)](#), [get\(1\)](#), [set\(1\)](#)
[monitoring\(5ASC\)](#)
[asadmin\(1M\)](#)

Chapter 8, “Administering the Monitoring Service,” in *Sun GlassFish Enterprise Server v3 Administration Guide*

