

**Name** create-domain – creates a domain

**Synopsis** create-domain create-domain [--help] --user *user-name*  
[--adminport 4848] [--instanceport 8080]  
[--portbase *portbase*]  
[--profile *profile-name*]  
[--template *template-name*]  
[--domaindir *domaindir*]  
[--savemasterpassword={false|true}]  
[--domainproperties (*name=value*)[:*name=value*]\*]  
[--keytooloptions (*name=value*)[:*name=value*]\*]  
[--savelogin={false|true}]  
[--checkports={true|false}]  
[--nopassword={false|false}]  
*domain\_name*

**Description** The create-domain subcommand creates the configuration of an administrative domain. A domain is an administrative namespace. Every domain has a configuration, which is stored in a set of files. Any number of domains, each of which has a distinct administrative identity, can be created in a given installation of Enterprise Server. A domain can exist independent of other domains. An Enterprise Server domain is a Java EE 6–compliant server.

Any user who has access to the asadmin utility on a given system can create a domain and store its configuration in a folder of choice. By default, the domain configuration is created in the default directory for domains. You can override this location to store the configuration elsewhere.

If domain customizers are found in domain.xml file when the create-domain subcommand is run, the customizers are processed.

This subcommand is supported in local mode only.

**Options** --help

-?

Displays the help text for the subcommand.

--user

User name of the domain administration server (DAS).

--adminport

The HTTP/S port for administration. This is the port to which you should point your browser (example, `http://localhost:this-port`) to manage the domain.

--instanceport

The domain provides services so that applications can run when deployed. This (HTTP) port specifies where the web application context roots are available for a web browser to connect to. This port is a positive integer and must be available at the time of domain creation.

**--portbase**

Determines the number with which the port assignment should start. A domain uses a certain number of ports that are statically assigned. The portbase value determines where the assignment should start. Choose this value carefully. The values for the ports are calculated as follows: Admin port: portbase + 48, HTTP listener port: portbase + 80, IIOP listener port: portbase + 37, JMX port: portbase + 86. See the output of this subcommand for a complete list of occupied ports, when **--portbase** option is specified.

**Note** – This subcommand uses some ports that are not required. This behavior is retained for compatibility with other releases.

**Note** – The **--portbase** option cannot be used with the **--adminport** or the **--instanceport** option.

**--profile**

Do not specify this option. This option is retained for compatibility with other releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and the option is silently ignored.

**--template**

Do not specify this option. This option is retained for compatibility with other releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and the option is silently ignored.

**--domaindir**

The directory where the domain is to be created. If specified, the path must be accessible in the filesystem. If not specified, the domain is created in the default domain directory, *install-dir/domains*.

**--savemasterpassword**

Setting this option to true allows the masterpassword to be written to the file system. Default is false.

A master password is really a password for the secure key store. A domain is designed to keep its own certificate (created at the time of domain creation) in a safe place in the configuration location. This certificate is called the domain's SSL server certificate. When the domain is contacted by a web browser over a secure channel (HTTPS), this certificate is presented by the domain. The master password is supposed to protect the store (a file) that contains this certificate. This file is called *keystore.jks* and is created in the configuration directory of the domain created. If however, this option is chosen, the master password is saved on the disk in the domain's configuration location. The master password is stored in a file called *master-password*, which is a Java JCEKS type keystore. The reason for using the **--savemasterpassword** option is for unattended system boots. In this case, the master password is not prompted for when the domain starts because the password will be extracted from this file.

It is best to create a master password when creating a domain, because the master password is used by the **start-domain** subcommand. For security purposes, the default setting

should be false, because saving the master password on the disk is an insecure practice, unless file system permissions are properly set. If the master password is saved, then `start-domain` does not prompt for it. The master password gives an extra level of security to the environment.

**--domainproperties**

Setting the optional name/value pairs overrides the default values for the properties of the domain to be created. The list must be separated by the : (colon) character. The following properties are available:

`jms.port`

Specifies the port number for JMS. Valid value is 7676.

`domain.jmxPort`

Specifies the port on which the JMX connector is initialized. The valid values are 1-65535.

`orb.listener.port`

Specifies the ORB listener port for IIOP connections on which `orb-listener-1` listens.

`http.ssl.port`

Specifies the port number for `http-listener-2`. Valid values are 1 to 65535. On UNIX, to create sockets that listen on ports 1–1024, you need superuser privileges.

`orb.ssl.port`

Specifies the ORB listener port for IIOP connections on which the IIOP listener called SSL listens.

`orb.mutualauth.port`

Specifies the ORB listener port for IIOP connections on which the IIOP listener called SSL\_MUTUALAUTH listens.

**--keytooloptions**

Specifies an optional list of name-value pairs of keytool options for a self-signed server certificate. The certificate is generated during the creation of the domain. Each pair in the list must be separated by the : (colon) character.

Allowed options are as follows:

**CN**

Specifies the common name of the host that is to be used for the self-signed certificate. This option name is case insensitive.

By default, the name is the fully-qualified name of the machine where the `create-domain` subcommand is run.

**--savelogin**

If set to true, this option saves the admin user name and password. Default value is false. The username and password are stored in the `.asadminpass` file in user's home directory. A domain can only be created locally. Therefore, when using the `--savelogin` option, the

host name saved in `.asadminpass` is always `localhost`. If the user has specified default admin port while creating the domain, there is no need to specify `--user`, `--passwordfile`, `--host`, or `--port` on any of the subsequent `asadmin` remote commands. These values will be obtained automatically.

**Note** – When the same user creates multiple domains having the same admin port number on the same or different machines (where the home directory is NFS mounted), the subcommand does not ask if the password should be overwritten. The password will always be overwritten.

`--checkports`

Specifies whether to check for the availability of the Admin, HTTP, JMS, JMX, and IIOP ports. Default value is true.

`--nopassword`

**Operands** *domain\_name*                      The name of the domain to be created.

**Examples** **EXAMPLE 1** Creating a Domain

This example creates a domain named `domain4`.

```
asadmin>create-domain --adminport 4848 domain4
Enter admin user name [Enter to accept default "admin" / no password]>
Using port 4848 for Admin.
Using default port 8080 for HTTP Instance.
Using default port 7676 for JMS.
Using default port 3700 for IIOP.
Using default port 8181 for HTTP_SSL.
Using default port 3820 for IIOP_SSL.
Using default port 3920 for IIOP_MUTUALAUTH.
Using default port 8686 for JMX_ADMIN.
Distinguished Name of the self-signed X.509 Server Certificate is:
[CN=srl-usca-22,OU=GlassFish,O=Sun Microsystems,L=Santa Clara,ST=California,C=US]
No domain initializers found, bypassing customization step
Domain domain4 created.
Domain domain4 admin port is 4848.
Domain domain4 allows admin login as user "admin" with no password.
Command create-domain executed successfully.
```

**EXAMPLE 2** Creating a Domain in an Alternate Directory

This example creates a domain named `sampleDomain` in the `/export/domains` directory.

```
asadmin> create-domain --domainindir /home/someuser/domains --adminport 7070
--instanceport 7071 sampleDomain
Enter admin user name [Enter to accept default "admin" / no password]>
Using port 7070 for Admin.
```

**EXAMPLE 2** Creating a Domain in an Alternate Directory *(Continued)*

```
Using port 7071 for HTTP Instance.
Using default port 7676 for JMS.
Using default port 3700 for IIOP.
Using default port 8181 for HTTP_SSL.
Using default port 3820 for IIOP_SSL.
Using default port 3920 for IIOP_MUTUALAUTH.
Using default port 8686 for JMX_ADMIN.
Distinguished Name of the self-signed X.509 Server Certificate is:
[CN=srl-usca-22,OU=GlassFish,O=Sun Microsystems,L=Santa Clara,ST=California,C=US]
No domain initializers found, bypassing customization step
Domain sampleDomain created.
Domain sampleDomain admin port is 7070.
Domain sampleDomain allows admin login as user "admin" with no password.
Command create-domain executed successfully.
```

**EXAMPLE 3** Creating a Domain and Saving the Admin Username and Password

This example creates a domain named myDomain and saves the administration username and password.

```
asadmin> create-domain --adminport 8282 --savelogin=true myDomain
Enter the admin password [Enter to accept default of no password]>
Enter the master password [Enter to accept default password "changeit"]>
Using port 8282 for Admin.
Using default port 8080 for HTTP Instance.
Using default port 7676 for JMS.
Using default port 3700 for IIOP.
Using default port 8181 for HTTP_SSL.
Using default port 3820 for IIOP_SSL.
Using default port 3920 for IIOP_MUTUALAUTH.
Using default port 8686 for JMX_ADMIN.
Distinguished Name of the self-signed X.509 Server Certificate is:
[CN=srl-usca-22,OU=GlassFish,O=Sun Microsystems,L=Santa Clara,ST=California,C=US]
Oct 16, 2009 1:41:25 PM com.sun.enterprise.module.impl.HK2Factory initialize
WARNING: Singleton already initialized as com.sun.enterprise.module.impl.
HK2Factory@2af8f5
No domain initializers found, bypassing customization step
Domain myDomain created.
Domain myDomain admin port is 8282.
Domain myDomain allows admin login as user "admin" with no password.
Login information relevant to admin user name [admin]
for this domain [myDomain] stored at
[/home/dixiep/.asadminpass] successfully.
Make sure that this file remains protected.
Information stored in this file will be used by
```

**EXAMPLE 3** Creating a Domain and Saving the Admin Username and Password *(Continued)*

asadmin commands to manage this domain.  
 Command create-domain executed successfully.

**EXAMPLE 4** Creating a Domain and Designating the Certificate Host

This example creates a domain named domain5. The common name of the host that is to be used for the self-signed certificate is trio.

```
asadmin> create-domain --adminport 9898 --keytooloptions CN=trio domain5
Enter the admin password [Enter to accept default of no password]>
Enter the master password [Enter to accept default password "changeit"]>
Using port 9898 for Admin.
Using default port 8080 for HTTP Instance.
Using default port 7676 for JMS.
Using default port 3700 for IIOP.
Using default port 8181 for HTTP_SSL.
Using default port 3820 for IIOP_SSL.
Using default port 3920 for IIOP_MUTUALAUTH.
Using default port 8686 for JMX_ADMIN.
Distinguished Name of the self-signed X.509 Server Certificate is:
[CN=trio,OU=GlassFish,O=Sun Microsystems,L=Santa Clara,ST=California,C=US]
Oct 16, 2009 1:52:25 PM com.sun.enterprise.module.impl.HK2Factory initialize
WARNING: Singleton already initialized as com.sun.enterprise.module.
impl.HK2Factory@bb05de
No domain initializers found, bypassing customization step
Domain domain5 created.
Domain domain5 admin port is 9898.
Domain domain5 allows admin login as user "admin" with no password.
Command create-domain executed successfully.
```

<b>Exit Status</b>	0	subcommand executed successfully
	1	error in executing the subcommand

**See Also** login(1), delete-domain(1), start-domain(1), stop-domain(1), list-domains(1)

[asadmin\(1M\)](#)

