



## Eigner 5.1

Defined error messages and error codes for possible errors  
in `edb_main`

## **Copyrights and Trademarks**

Copyright © 1995-2003 Agile Software Corporation. All rights reserved.

You shall not create any derivative works of this publication nor shall any part of this publication be copied, reproduced, distributed, published, licensed, sold, stored in a retrieval system or transmitted in any form or by any means: electronic, mechanical, photocopying, or otherwise, without the prior written consent of Agile Software Corporation, 6373 San Ignacio Avenue, San Jose, California 95119-1200 U.S.A.; Telephone 408.284.4000, Facsimile 408.284.4002, or <<http://www.agile.com/>>.

The material in this document is for information only and is subject to change without notice. While reasonable efforts have been made in the preparation of this document to ensure its accuracy, Agile Software Corporation assumes no liability resulting from errors or omissions in this document or from the use of the information contained herein. Agile Software Corporation reserves the right to make changes in the product design without reservation and without notification to its users.

Eigner PLM is a registered trademark. All other brands or product names are trademarks or registered trademarks of their respective holders.

Java and Solaris are registered trademarks of Sun Corporation.

Microsoft, Microsoft Windows, Microsoft Word, Microsoft Excel, Internet Explorer and SQL Server are registered trademarks of Microsoft Corporation.

Oracle and Oracle8i are registered trademarks of Oracle Corporation.

### **NOTICE OF RESTRICTED RIGHTS:**

The Software is a "commercial item," as that term is defined at 48 C.F.R. 2.101 (OCT 1995), consisting of "commercial computer software" and "commercial computer software documentation" as such terms are used in 48 C.F.R. 12.212 (SEPT 1995) and when provided to the U. S. Government, is provided (a) for acquisition by or on behalf of civilian agencies, consistent with the policy set forth in 48 C.F.R. 12.212; or (b) for acquisition by or on behalf of units of the Department of Defense, consistent with the policies set forth in 48 C.F.R. 227.7202-1 (JUN 1995) and 227.7202-4 (JUN 1995).

**July 29, 2004**

# CONTENTS

---

Chapter 1 Defined error messages and error codes edb\_main 1



# Chapter 1

## Defined error messages and error codes `edb_main`

This document contains a list of all defined error messages and error codes for possible errors in `edb_main`

**Note:** Error names, which are not found in `edb_main.c`, are highlighted in **RED** text.

Multiple messages are highlighted in **BLUE** text

Error Code Name	Error No	Error Message	Description	Solution
EDB_ERR_ILL_ARGUMENTS	1	Illegal arguments	Wrong arguments, axalant/plm expects the following arguments:  Usage of axalant/plm: axalant F:<conffile> <plm-usr> [-{ptkrwq}] <argument>  -p plm-user password (deprecated)  -t ECI protocol number  1 - tcpip -k hostname -r port number -w wildcards -q query mode	Correct parameters
EDB_ERR_CFG_MOD_UNSPECIFIED	10	Module administration failed with error code %d\n	Internal error at initialization of module management	Please contact agile support
EDB_ERR_CFG_MOD_SRC_NOT_FOUND	11	Config source '%s' does not exist or is empty  Module configuration '%s' does not exist or is empty	Configuration file is missing	Check configuration with administration tool

Error Code Name	Error No	Error Message	Description	Solution
EDB_ERR_CFG_MOD_ILL_FORMAT	12	Ignoring config parameter '%s' (illegal format) Unsupported module type %s	Invalid entries in configuration file	Check configuration with administration tool
EDB_ERR_CFG_MOD_OVERFLOW	13	Truncating config parameter '%s'	A value in configuration file exceeds 300 characters	Check configuration with administration tool
EDB_ERR_CFG_MOD_KEY_READ	14		No longer returned by axalant/plm	
EDB_ERR_CFG_MOD_ILLEGAL	15	"Could not start module %s\n"	Could not start module, module name or library missing in configuration file	Check configuration with administration tool
EDB_ERR_ENV_MOD_UNSPECIFIED	20		No longer returned by axalant/plm	
EDB_ERR_ENV_MOD_ROOT_UNKNOWN	21	EP_APP_ROOT" unknown "	Root directory unknown	Check installation (environment variable ep_root missing)
EDB_ERR_GET_OR_PUT_ENV	22	[Environment] (Reading/Setting environment entries)	Error while reading contents from the [Environment] section and export contents	Check configuration with administration tool
EDB_ERR_MOD_UNSPECIFIED	50	Module administration failed with error code %d	Error while initializing module administration	Check configuration with administration tool
EDB_ERR_MOD_ABORTED	51	Could not start module '%s' (err = %d)	Module unable to start, tolerated for non-core modules	Contact module provider
EDB_ERR_MOD_CONFLICT	52	Could not start module %s\n	Module ID already in use, two or more modules use the same module id	Check configuration with administration tool

Error Code Name	Error No	Error Message	Description	Solution
EDB_ERR_MOD_NOT_FOUND	53	Could not start module '%s' (err = %d)	Module library not found	Contact Agile support or module provider
EDB_ERR_MOD_IMPORT_CIRCULAR	54	Could not start module '%s' (err = %d)	Circular import dependencies	Contact Agile support or module provider
EDB_ERR_MOD_IMPORT_MISMATCH	55	Could not start module '%s' (err = %d)	One of the imported modules has an incorrect version	Contact Agile support or module provider
EDB_ERR_MOD_IMPORT_FAILED	56	Could not start module '%s' (err = %d)	One of the imported modules could not be initialized	Contact Agile support or module provider
EDB_ERR_PRT_INI_UNSPECIFIED	60	Privileges %d	Internal error in DataView privileges module	Contact Agile support
EDB_ERR_PRT_INI_NO_LIC	61	No License found	Unable to obtain DataView License	Check license number and expiration date
EDB_ERR_PRT_INI_UNKNOWN_USER	62	Unknown user. Insert user in dtv user list	Specified user does not exist in the database (table T_USER)	Check if correct user name was used
EDB_ERR_PRT_INI_UNKNOWN_GROUP	63	User has no group. Insert user in a group	User was not assigned to group. Dump error.	Check user definition
EDB_ERR_DFV_INI_UNSPECIFIED	64	Default-Module	Unable to initialize DataView Default module.	Contact Agile support
EDB_ERR_LNG_INI_UNSPECIFIED	65	Language-Module	Unable to initialize DataView Language module. Dump error.	Contact Agile support

Error Code Name	Error No	Error Message	Description	Solution
EDB_ERR_LNG_INI_NO_TABLE	66	Table T_LANGUAGE not found	Unable to initialize DataView Language module, missing table T_LANGUAGE. Dump error.	Contact Agile support
EDB_ERR_USX_INI_UNSPECIFIED	70	User-Exits	Unable to initialize DataView Userexit module	Contact Agile support
EDB_ERR_DTV_SUR_UNSPECIFIED	71	User-Interface	Unable to initialize DataView UI module. Dump error.	Contact Agile support
EDB_ERR_DTV_LCK_UNSPECIFIED	72	Lock-Module	Unable to initialize DataView Lock module.	Contact Agile support
EDB_ERR_IWF_INI_UNSPECIFIED	73	Entity-List	Unable to initialize DataView IWF module. Dump error.	Contact Agile support
EDB_ERR_ECI_MOD_UNSPECIFIED	74		No longer returned by axalant/plm	
EDB_ERR_BAS_MOD_UNSPECIFIED	75		No longer returned by axalant/plm	
EDB_ERR_ART_MOD_UNSPECIFIED	76		No longer returned by axalant/plm	
EDB_ERR_DOC_MOD_UNSP_ECIFIED	77		No longer returned by axalant/plm	
EDB_ERR_PRO_MOD_UNSPECIFIED	78		No longer returned by axalant/plm	
EDB_ERR_COR_MOD_UNSP_ECIFIED	79	Could not start the ECI module: err=%d  Static Core Modules	Unable to initialize the ECI or other core module	Contact Agile support
EDB_ERR_FMS_MOD_UNSPECIFIED	80		No longer returned by axalant/plm	
EDB_ERR_BAS_PASSWD	81	Foundation-Password (PLM-PDM)	Unable to obtain foundation license	Check license number and expiration date

Error Code Name	Error No	Error Message	Description	Solution
EDB_ERR_USX_EDB_INI_UNSPECIFIED	82		No longer returned by axalant/plm	
EDB_ERR_EDB_BATCH_UNSPECIFIED	83	EDB-Batch-Module	Batch call failed	Check the batch call
EDB_ERR_FMGT_PASSTWD_UNSPECIFIED	84	ECI server ECI connection password check failed: %d  ECI authentication failed: rc=%d	The ECI client (Java client, Web client or CAD interface) failed to authenticate.	Verify use of correct username and password
EDB_ERR_DTV_TCL_UNSPECIFIED	85	TCL: %d	Unable to initialize DataView TCL integration.	Contact Agile support
EDB_ERR_ECI_INIT_FAILED	86	ECI server  Unable to init ECI server on port %s: rc=%d, error %d: %s  ECI authentication failed: rc=%d  ECI connection password check failed	Unable to initialize Eci server (specified port already in use?), or wrong user password	Check ECI arguments or user/password combination
EDB_ERR_UNKNOWN_ERR	99	Basic initialization failed	Internal error	Contact Agile support
EDB_ERR_DTV_WIN_UNSPECIFIED	100	Window-Module	Unable to initialize DataView Window module	Contact Agile support
EDB_ERR_DTV_WIN_TERM	101	Window-Module  Error in reading variable DATAVIEW_TERM  Check, if DATAVIEW_TERM is set	While initializing DataView, there is an error in reading the variable DATAVIEW_TERM	Check installation

Error Code Name	Error No	Error Message	Description	Solution
EDB_ERR_DTV_WIN_SIZE	102	Window-Module Error in reading variable DATAVIEW_SIZE  Check, if DATAVIEW_SIZE is set	While initializing DataView, there is an error in reading the variable DATAVIEW_SIZE	Check installation
EDB_ERR_DTV_WIN_INP	103	Window-Module Error in reading variable DATAVIEW_INP  Check, if DATAVIEW_INP is set	While initializing DataView, there is an error in reading the variable DATAVIEW_INP	Check installation
EDB_ERR_DTV_WIN_INIT	104	Window-Module Error in reading variable DATAVIEW_INIT  Check, if DATAVIEW_INIT is set	While initializing DataView, there is an error in reading the variable DATAVIEW_INIT	Check installation
EDB_ERR_DTV_WIN_KEY	105	Window-Module Error in reading key file  Check, if file vt_key or ansi_key exist, check permissions of the files	While initializing DataView, there is an error in reading the variable DATAVIEW_INIT	Check installation
EDB_ERR_DTV_WIN_NRDE	106	Window-Module Error in reading variable DATAVIEW_NRD E  Check, if DATAVIEW_NRD E is set to correct value	While initializing dataView, there is an error in reading key file vt_key or ansi_key	Check installation
EDB_ERR_DTV_WIN_TCP_C RE	107	Window-Module Error in creating TCP-service	While initializing dataView, there is an error in creating TCP-service	Check installation

Error Code Name	Error No	Error Message	Description	Solution
EDB_ERR_DTV_WIN_TCP_REG	108	Window-Module Error in registering TCP-service	While initializing dataView, there is an error registering TCP-service	Check installation
EDB_ERR_DTV_WIN_LIC_READ	109	Window-Module Error in reading DataView License Check, if license server and agent are running.	While initializing dataView, there is an error in reading DataView License	Check installation
EDB_ERR_DTV_DBs_UNSPECIFIED	110	Database	Database unspecified. Connection to database failed	Check installation
EDB_ERR_DTV_DBs_ACC	111	Database Error in opening database database running? database user ok? database password ok? TNS_ADMIN set? Try sqlplus Access on DATAVIEW_TBS_P or DATAVIEW_IXSP denied?	There is an error in opening the database.	Please check – 1) Database is running 2) Database user and password are correct 3) TNS_ADMIN is set properly 4) Check the access rights.
EDB_ERR_DTV_DBs_TBSP	112	Database Error in reading variable DATAVIEW_TBS_P Check, if DATAVIEW_TBS_P is set	DataView is unable to read the variable DATAVIEW_TBS_P	Please check if DATAVIEW_TBS_P is set properly