

Agile Product Lifecycle Management

Getting Started Guide

Release 9.3.6

E71144-09

December 2022

Copyright © 2010,2022 Oracle and/or its affiliates. All rights reserved.

Primary Author: Oracle Corporation

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

Preface	xix
Audience.....	xix
Documentation Accessibility	xix
Related Documents	xix
Conventions.....	xix
 1 Introduction	
What is in this Manual	1-1
This Manual Precedes the Solution Manuals.....	1-1
Agile PLM Basics.....	1-1
Cross-Solution Utilities in Agile PLM	1-1
Overview of the Agile PLM Suite	1-2
What's New for the User Experience in Agile PLM 9.3.6	1-3
What's New for the User Experience in Agile PLM 9.3.5	1-4
What's New for the User Experience in Agile PLM 9.3.4	1-4
What's New for the User Experience in Agile PLM 9.3.3	1-5
What's New for the User Experience in Agile PLM 9.3.2	1-5
What's New for the User Experience in Agile PLM 9.3.1	1-5
What's New for the User Experience in Agile PLM 9.3	1-6
 2 Navigating in Agile Web Client	
Introducing Web Client	2-1
Logging In to Web Client	2-1
Bookmarking Web Client in Your Browser	2-2
Choosing Your Preferred Start Page.....	2-2
Logging Out of Web Client	2-3
Web Client Home Page	2-3
Exploring the Home Page	2-5
Quick Links.....	2-5
Inbox Tabs.....	2-6
Dashboard	2-6
Viewing the Dashboard	2-7
Dashboard Tabs	2-7
My Stuff Tab.....	2-7
Optional Tabs.....	2-8

Manipulating the Dashboard Widgets	2-8
Configuring Dashboard Tab Widgets	2-9
Notifications.....	2-9
Workflow Routings.....	2-11
Using the Workflow Routings Tab	2-12
My Assignments	2-14
My Assignments Table	2-14
My Assignments Tab Tools.....	2-15
Using the View Options to Sort your Assignment List	2-17
Editing Assignments	2-18
Accepting Assignments	2-18
Declining Assignments	2-18
Mark Assignments Complete.....	2-19
Printing the Assignment Table	2-19
Hiding and Unhiding Assignments.....	2-20
Flagging Assignments.....	2-20
Using the Quick View Dialog.....	2-21
Top Pane Main Toolbar.....	2-21
Navigation Pane.....	2-22
Showing and Hiding the Navigation Pane	2-23
Navigation Pane Toolbar	2-24
Web Client Session Timeouts.....	2-25
Navigation Pane Folders Drawer	2-26
Search Folders.....	2-26
Shortcuts	2-26
Using Online Help	2-27
Reports and Analytics Folders	2-27
Navigator Drawer.....	2-27
Navigating Workflow Routings.....	2-27
Navigating Search Results	2-28
Navigating Object Structures.....	2-29
Navigating the Project Tree	2-30
Changing Your User Settings.....	2-31
Changing Your User Profile	2-32
User Preferences	2-33
Persisted User Interface Settings	2-33
User Profile Tabs	2-34
Creating Personal Criteria.....	2-34
Changing Your Password.....	2-36
Signoff Authority Transfers	2-36
Working with Escalations in Web Client.....	2-37
Web Client Address Book: Users, User Groups, Functional Teams, and Supplier Groups	2-38
Address Book, Users Tab.....	2-38
Address Book, User Groups Tab	2-39
Creating Personal User Groups.....	2-39
Editing Personal User Groups.....	2-40
Deleting Personal User Groups.....	2-41

Undeleting Deleted Personal Groups.....	2-41
Creating a New Group Using Save As on a Deleted Personal Group	2-41
Address Book, Functional Teams Tab.....	2-41
Deleting Functional Teams	2-43
Creating a New Functional Team Using Save As on a Deleted Functional Team	2-43
Creating Personal Supplier Groups.....	2-44
Working with Web Client Tables	2-44
Viewing and Opening Table Objects	2-44
Selecting Rows in Tables	2-44
Table Views	2-45
Sort Order in Tables.....	2-45
Defining Table Views	2-46
Web Client Tab Content Indicator Icons	2-47
Adding Objects to Tables.....	2-49
Editing and Modifying Tables	2-50
Using and Organizing Bookmarks.....	2-50
Bookmarking.....	2-51
Using a Bookmark	2-51
Organizing Bookmarks	2-51
Buttons on the Web Client My Bookmarks Toolbar	2-51
The Organize Bookmarks Dialog	2-52
Deleting a Bookmark	2-52
Renaming a Bookmark or a Bookmark Folder	2-53
Using Folders to Organize Bookmarks	2-53
Creating a Bookmark Folder.....	2-53
Reordering the Contents of a Bookmark Folder.....	2-53
Removing a Bookmark Folder.....	2-54
Renaming a Bookmark or a Bookmark Folder	2-54
Moving Bookmarks and Folders.....	2-54
Using the Recently Visited List	2-55
User Properties Defined.....	2-55

3 Navigating in Agile Java Client

Navigating in Agile Java Client.....	3-1
Logging In and Out of Java Client.....	3-1
Java Client Windows, Menus, and Toolbars.....	3-3
Java Client Menus.....	3-3
Agile Scan Utility	3-4
Java Client Toolbars	3-4
Windows Bar	3-5
Hiding and Showing the Navigation Pane	3-6
Java Client Tables	3-6
Sort Order in Tables.....	3-7
Selecting Rows in Tables.....	3-7
Using the Inbox	3-8
Notifications.....	3-8
Workflow Routings.....	3-8

Using Bookmarks and the Recently Visited List	3-9
Bookmarking	3-9
Organizing Bookmarks.....	3-9
The Organize Bookmarks Window	3-9
Removing Bookmarks	3-10
Renaming Bookmarks	3-10
Recently Visited List	3-10
Changing Your User Settings	3-10
Changing Your User Profile	3-11
User Preferences	3-11
Changing Your Password	3-11
Persisted User Interface Settings	3-12
Working with Escalations in Java Client	3-12
Creating Personal Criteria.....	3-12
Editing Personal Criteria.....	3-14
Address Book in Java Client.....	3-14
Overview of the Address Book.....	3-15
Selecting Users and User Groups from the Address Book.....	3-15
User Groups	3-16
Creating User Groups	3-16
Completing or Editing User Groups	3-17
Deleting Personal User Groups.....	3-17
Creating Supplier Groups.....	3-18

4 Concepts and Terms in Agile PLM Solutions

Introducing Agile Objects	4-1
How Objects Appear.....	4-1
Agile Object Types	4-2
Installed Agile Classes, Base Classes, and Subclasses.....	4-4
Discovery and Read Privileges	4-10
Routable and Nonroutable Objects	4-10
Routing Managers.....	4-10
Other Important Concepts in Agile.....	4-11
Login Security and Passwords	4-11
Object Subscriptions, Relationships, and Sharing	4-11
File Folder Objects and Attachment Files.....	4-12
Searching for Data	4-12
Agile Packages.....	4-13
Exporting Data	4-13
Product Collaboration Process	4-13
Bills of Material	4-14
Approved Manufacturer Lists	4-14
Change Control Process	4-14
Objects and Change Control	4-14
Affected Items.....	4-14
Redlining BOMs, Manufacturers, and Attachment Files	4-14
Workflows	4-14

Change Control Process	4-15
A Typical Change Control Process.....	4-15
Product Portfolio Management Process.....	4-16
Common Terms in PPM	4-17
Product Quality Tracking Process.....	4-17
Common Terms in PQM.....	4-18
Product Cost Management Process	4-18
Common Terms in PCM.....	4-19
Product Governance and Compliance Process.....	4-19
Common Terms in PG&C.....	4-19
Engineering Collaboration Process	4-20

5 Working with Business Objects in Web Client

Creating Objects.....	5-1
Actions Menu.....	5-1
Creating Objects in Web Client Using the Create New Command	5-3
Creating an Object Using Save As.....	5-3
Site Change Order Save As Limitations	5-4
Design File Change Order (DFCO) Save As Limitations	5-4
Adding Objects to Tables.....	5-5
Adding Objects to Tables by Type-ahead Search.....	5-5
Adding Objects to Tables by Quick Search.....	5-5
Adding Objects to Tables by Create New	5-6
Adding Objects to Tables by Drag and Drop	5-6
Adding Objects to Tables by Copy and Paste.....	5-7
Adding Objects to Tables by Custom Search	5-7
Adding Objects to Tables from Excel by Copy and Paste.....	5-8
Editing and Modifying Tables	5-8
Editing Table Cells in Web Client	5-8
Using Fill-Up and Fill-Down in Web Client Tables.....	5-8
Modifying Date and Time Fields.....	5-9
Using the Calendar to Modify Date Fields	5-10
Manually Modifying Date and Time Fields.....	5-10
Selecting Users or User Groups to Modify a Field	5-11
Modifying List Fields	5-13
Viewing the Contents of LargeText Fields.....	5-13
Modifying LargeText Fields	5-14
LargeText Field HTML Editor	5-15
Modifying LargeText Journal Fields	5-21
Modifying LargeText Non-journal Fields.....	5-21
Comparing Historical LargeText Field Edits.....	5-21
Viewing LargeText Field Redline Edits	5-22
Printing Object Tabs.....	5-22
Emailing Objects	5-23
Smart URL Quick Access to Objects, Files, and Searches	5-23
Agile-Generated Quick Access Object Smart URLs	5-24
Using Quick Access Object Smart URLs	5-24

Formats for User-Generated Smart Object URLs.....	5-24
Smart Object URL Format.....	5-25
Examples of Quick Access Object Smart URLs	5-26
Discussion Objects	5-27
Creating and Viewing Discussions	5-27
Adding To and Editing Discussions.....	5-28
Sharing Objects with Other Users	5-28
Subscribing to Objects	5-29
Subscribing to an Item or Price Revision.....	5-29
Subscribing to Attachments by Using the File Folder	5-29
Subscribing to Objects	5-29
Subscription in Product Portfolio Management.....	5-30
Relationships and Dependencies Between Objects	5-31
What are Relationships?.....	5-31
What are Revision-Specific Relationships?	5-32
Relationships Tab.....	5-33
Relationships Tab Views	5-34
Relationship Tab Actions in Web Client	5-34
Using the Web Client Relationship Tab Views	5-35
Adding Relationships to Objects	5-35
Viewing Reference Objects	5-36
Selecting a Revision.....	5-36
Accepting or Rejecting a New Revision.....	5-36
Editing the Relationships Table	5-37
Removing Relationships	5-37
What is a Relationship Rule?	5-37
Relationship Rule Guidelines.....	5-38
Adding a Rule to a Relationship	5-39
Editing a Relationship Rule	5-40
Removing a Relationship Rule	5-40
Relationships in PQM	5-40
Deleting Objects	5-40

6 Working with Business Objects in Java Client

Interacting with Agile Objects: Actions and Tabs	6-1
More Menu.....	6-1
Object Tabs	6-2
Creating Objects	6-6
Creating Objects in Java Client Using the New Command.....	6-6
Creating an Object Using Save As.....	6-7
Site Change Order Save As Limitations	6-7
Adding Objects to Tables.....	6-8
Item Addition Rules.....	6-8
Modifying Date and Time Fields	6-8
Using the Calendar to Modify Date Fields	6-8
Manually Modifying Date and Time Fields.....	6-9
Modifying List Fields	6-9

Printing Object Tabs	6-10
Emailing Objects	6-10
Quick Access to Objects, Files, and Searches	6-11
Discussion Objects	6-11
Sharing Objects with Other Users	6-12
Subscribing to Objects	6-12
Subscribing to an Item or Price Revision.....	6-13
Subscribing to Attachments by Using the File Folder	6-13
Subscribing to Objects	6-13
Subscription in Product Portfolio Management.....	6-14
Relationships and Dependencies Between Objects	6-14
What are Relationships?.....	6-15
Relationships Tab.....	6-15
Relationships Tab Views	6-16
Relationship Tab Actions.....	6-16
Using the Table Filter	6-17
Adding Relationships to Objects.....	6-18
Editing the Relationships Table	6-18
Removing Relationships	6-18
What is a Relationship Rule?.....	6-19
Relationship Rule Guidelines	6-19
Adding a Rule to a Relationship.....	6-20
Editing a Relationship Rule	6-21
Removing a Relationship Rule	6-21
Relationships in PQM	6-21
Deleting Objects	6-22

7 Working with Agile Reports

About Reports	7-1
Types of Reports	7-1
How Your Roles and Privileges Affect Reports	7-2
General Info Tab	7-3
Layout Tab	7-4
Creating Standard Report Layouts	7-6
About Standard Report Layouts with Multiple Headers.....	7-6
Creating Custom Report Layouts.....	7-6
Creating a Standard Layout.....	7-7
Editing Standard Report Layouts	7-9
Editing Custom Report Layouts.....	7-9
Deleting Report Layouts	7-10
Schedule Tab	7-10
Historical Report Tab	7-11
Working with Standard Reports	7-12
Accessing Standard Reports.....	7-12
Working with Custom Reports	7-13
Creating a Custom Report.....	7-13
Creating a New Query.....	7-14

Conditions to Edit and Save a Query	7-15
Using a Saved Search.....	7-15
Executing Custom Reports.....	7-16
Deleting and Undeleting Custom Reports	7-16
Working with External Reports.....	7-17
Creating an External Report.....	7-17
Executing an External Report	7-18
The Report Output Window	7-18

8 Finding Agile Data with Searches

Overview of Search Tools	8-1
Types of Searches	8-1
Web Client, Types of Searches	8-1
Search Preferences	8-2
Java Client, Types of Searches	8-3
User Roles and Searchable Objects and Attributes.....	8-4
How Discovery Privileges Affect Searches.....	8-4
How Field-Level Read Privileges Affect Searches	8-4
Search Results	8-4
LargeText Fields in Search Results	8-6
Exporting Search Results.....	8-6
Saved Searches.....	8-7
Predefined System Searches	8-7
Running a Saved Search	8-8
Running Saved "Prompt at Runtime" Searches	8-9
Quick Searches	8-9
Quick Search Overview	8-9
Web Client Quick Search.....	8-10
Perform a Quick Search in Web Client	8-11
Web Client Name/Number/Description Field Searches	8-12
Java Client Quick Search	8-12
Perform a Quick Search in Java Client.....	8-13
Quick Searches and Wildcard Characters.....	8-14
Using Wildcard Characters	8-14
Special Characters as Part of Words.....	8-15
Full Text Search for Content in Attachment Files	8-17
Using Quick Search to Find Attachment File Content	8-17
"Stop" Words	8-18
Using Attachment Content Advanced Search Capabilities.....	8-18
Concept Search and Stem Search	8-19
Preconfigured Parametric Searches	8-20
Parametric Search Window.....	8-20
Parametric Search Window in Web Client	8-20
Running a Preconfigured Parametric Search in Web Client.....	8-22
Parametric Search Window in Java Client	8-23
Running a Preconfigured Parametric Search in Java Client	8-24
Saving a Search.....	8-25

Saving a Parametric Search as an Advanced Search	8-25
Using Save As to Save a Search	8-26
Advanced Searches	8-28
Overview of Advanced Searches	8-28
Basic Process to Create an Advanced Search	8-29
Some Caveats about Advanced Searches.....	8-29
Using Saved Searches to Create your Advanced Search	8-30
Complexity between Search Criteria and Output Display	8-30
Searching for Space Characters in Text Fields	8-30
Difference in Caching Search Attributes in Web Client and Java Client	8-31
Creating an Advanced Search in Web Client.....	8-31
A. Select the Search Type, Web Client	8-31
B. Define the Search Criteria, Web Client.....	8-32
C. Define a Custom Output Display, Web Client.....	8-34
D. Save and Run the Search, Web Client	8-34
Edit the Search After Running It, Web Client	8-35
Creating an Advanced Search in Java Client.....	8-35
A. Select the Search Type, Java Client	8-35
B. Define the Search Criteria, Java Client	8-35
C. Define a Custom Output Display, Java Client	8-37
D. Save and Run the Search, Java Client.....	8-37
Edit the Search After Running It, Java Client	8-38
Selecting Search Operators	8-38
Search Operators and Attribute Types.....	8-39
Searching with Date and Time Criteria	8-41
Limited Search Operators for Orphaned Item Search Criteria	8-41
Using And/Or Values in Advanced Searches	8-42
Using And/Or - An Example	8-42
Using Parentheses in Search Definitions	8-43
Where-Used Searches for Items	8-44
Searching on Rev-Specific Values.....	8-45
Where-Used Search Types.....	8-45
Where-Used - All Levels - Latest Released Revision Only	8-45
Where-Used - Top Level - Latest Released Revision Only.....	8-46
Where-Used - One Level - Latest Released Revision Only	8-47
Where-Used - One Level - All Released Revisions	8-47
Where-Used Set Operators.....	8-48
Union	8-48
Intersection.....	8-49
Minus	8-49
Creating a Where-Used Search in Web Client.....	8-50
Creating a Where-Used Search in Java Client	8-51
Where-used Searches for File Folders	8-53
Version-Specific Properties and File Folder Object Searches	8-54
Version-Specific Properties and File Folder Object Searches	8-55
Relationship Searches	8-55
Searching for Users and User Groups	8-56

Searching for Routable Objects with Workflow Attributes	8-57
Creating Workflow Searches	8-57
Creating Grouped Conditions for Workflow Searches	8-61
Tips and Guidelines for Grouped Conditions	8-63
Editing and Managing Searches and Search Folders	8-64
Buttons in the Web Client Searches Toolbar	8-64
Buttons and Right-click Menu Choices in the Java Client Search Toolbar	8-65
Organizing Searches	8-66
The Web Client Organize Searches Window	8-66
The Java Client Organize Searches Window	8-67
Editing Searches.....	8-67
Editing a Search in Web Client.....	8-68
Editing a Search in Java Client	8-68
Renaming a Search.....	8-69
Deleting a Search	8-69
Using Folders to Organize Bookmarks	8-70
Creating a Folder	8-70
Removing a Folder.....	8-71
Renaming a Folder.....	8-72
Moving Searches and Folders	8-72
Smart URL Quick Access to Searches	8-73
Formats for User-Generated Smart Object URLs for Searches	8-74
Smart Object Search URL Formats	8-74
Quick Search Smart Object URL Examples	8-75
Basic Search Smart Object URL Examples.....	8-75
Advanced Search Smart Object URL Examples	8-76
Saved Search Smart Object URL Examples	8-77

9 Routing Objects with Workflows

About Workflows	9-1
Status List	9-1
Show/Hide Workflows within a Class	9-3
Multiple Hold and Cancel Status	9-3
Default Workflows	9-4
Changes Base Class Default Workflows	9-4
Transfer Order Class Default Workflows	9-5
Product Service Request Class Default Workflows.....	9-5
Project Base Class Default Workflows	9-6
Default Packages Workflow	9-6
Default File Folders Workflow	9-6
Example of a Customized Workflow	9-6
Using Workflows in the Change Control Process	9-8
Selecting a Workflow.....	9-8
Working with Workflows	9-9
Switching a Routable Object from One Status to Another Status	9-10
Switching the Status of a Routable Object	9-10
Save Routing Slip Content when Advancing Change	9-11

Auditing Routable Objects.....	9-12
Status Audit, Conditions Audited	9-12
Release Audit, Conditions Audited	9-13
Modifying the Make/Buy Field on the Item Sites Tab	9-14
Performing a Status Audit.....	9-14
Performing an Audit Release	9-15
Autopromotion Failure.....	9-16
Redline Conflicts	9-16
Ability to Fail Autopromote More than Once within same Change Status	9-17
Demoting a Routable Object.....	9-17
Completing the Status Change.....	9-17
Completing the Status Change for a Review or Released Status	9-19
Discovery Privileges of Approvers, Acknowledgers, Observers, and Users to Notify	9-20
Handling Routed Changes	9-20
When to Add Approvers, Acknowledgers, and Observers	9-20
Adding and Removing Approvers, Acknowledgers, and Observers	9-21
Web Client, Adding and Removing Approvers, Acknowledgers, and Observers.....	9-21
Web Client, Resolve Duplicate Signoff Users.....	9-23
Java Client, Adding and Removing Approvers and Observers	9-24
Using Functional Teams with Routable Objects.....	9-25
Resolving Missing Users	9-26
Approving Routable Objects.....	9-27
Rejecting Routable Objects.....	9-30
Acknowledging Routable Objects	9-32
Reminder Period and Review Escalation Period	9-34
Designated Escalation Person	9-34
Transferring Signoff Authority	9-35
Routable Objects Affected During the Transfer Period.....	9-36
Modifying Signoff Authority Transfers.....	9-36
Deleting Signoff Authority Transfers	9-37
Defining Personal Criteria for Authority Transfers	9-38
Returning a Routable Object to the Originator	9-39
Canceling a Routable Object.....	9-40
Uncanceling a Routable Object.....	9-41
Putting a Routable Object on Hold	9-42
Releasing Routable Objects	9-42
Unreleasing Routable Objects.....	9-43
Multiple Released Status Types	9-44
Use Case of First Released Status.....	9-45
Adding Comments to the History Tab	9-45
Sending Comments to all Previous and Current CCB Members	9-45
Changing a Routable Object's Subclass	9-46
After a Routable Object is Released.....	9-47
Switching Routable Objects to Their Final Status.....	9-47
Redlining through ECOs, MCOs, PCOs and SCOs.....	9-48
Redlining through ECOs.....	9-48
Redlining through MCOs.....	9-49

Redlining Prices through PCOs	9-49
Redlining through SCOs	9-49
Deleting Routable Objects	9-49
Printing Routable Object's Data	9-49

10 Working with Attachments

What are Attachments?	10-1
Attachment Files and Agile File Folders: an Analogy to Papers, Desks, and Vaults	10-1
Agile Document Management: Even More Efficient than Doris	10-2
What are Attachment Versions?	10-3
Working with the Attachments Tab of Business Objects	10-4
Buttons on the Attachments Tab	10-5
Attachment Tab Buttons, Web Client	10-5
Attachment tab buttons, Java Client	10-7
Basic Procedures on the Attachments Tab	10-9
Getting Attachment Files	10-9
Getting Files in Web Client	10-9
Web Client, Get Files using Microsoft IE	10-10
Web Client, Get Files using Firefox	10-10
Web Client, Get files using Chrome:	10-11
Web Client, Get Files using Safari for Windows	10-11
Getting Structured Files in Web Client	10-12
Java Client, Getting Attachment Files	10-12
Java Client, Batch Get	10-12
Opening Attachment Files in their Native Applications	10-13
Printing Attachment Files	10-14
About Banners and Watermarks on the Printed Image	10-15
Accessing Different Versions of Attachments	10-15
Using the File Folder Version Browser	10-15
Adding and Removing Files by Using the Attachments Tab	10-17
Adding Attachment Files from your Local Disk or Network	10-17
Web Client File Uploader Tools	10-18
Web Client File Upload Selector	10-18
Web Client File Upload Manager	10-19
Java Client, Using the Java Upload/Download Tool	10-20
Add Files by Search Options	10-22
Add by Search for Existing File Folder	10-23
Adding a URL	10-23
Adding Files by using SaveAs to Create a New Business Object	10-24
Removing Attachments from the Attachments Tab	10-24
Editing the Attachments Table	10-25
Revising Attachment Files	10-26
Web Client, Checking Out Attachment Files	10-27
Java Client, Checking Out Attachment Files	10-27
Web Client, Checking in Revised Attachment Files	10-28
Java Client, Checking In Revised Attachment Files	10-28
Canceling Checkouts	10-29

Checksum File Validation.....	10-29
About Item Revisions and File Folder Versions	10-30
Revision and Version Defined for Agile PLM	10-30
Viewing a Different Revision	10-30
Introductory Revisions.....	10-31
How the Revision List Works.....	10-31
How Rev and Site Lists are Determined.....	10-32
Samples of Rev Lists with ECO, MCO, and SCO.....	10-32
Working with Pending Revisions	10-33
Attachments on Pending Revisions	10-33
Effects of CopyFilesToRev SmartRule.....	10-33
Availability of Attachment Operations	10-34
Viewing and Redlining Attachment Files in the AutoVue for Agile Viewer	10-35
Redlining or Marking Up Files in AutoVue for Agile.....	10-35
Marking Up or Redlining Attachment Files from an ECO.....	10-36
Marking Up or Redlining Attachment Files from an ECR.....	10-37
Configuring File Associations for Opening Files in Web Client.....	10-38
Smart URL Quick Access to Files	10-38
Generating Attachment Quick Access URLs.....	10-39
Agile-Generated Attachment Quick Access URLs.....	10-39
User-Generated Attachment Quick Access Smart URL Formats.....	10-40
Item Attachment Quick Access Smart URL Formats.....	10-40
Limitations for Item Object Attachment Quick Access Smart URLs	10-41
File Folders Quick Access Smart URL Formats	10-42
Program Content Quick Access Smart URL Formats	10-43
Accessing Attachment Files using Quick Access URLs	10-43
Scan Utility	10-44
Installing a Scanner.....	10-44
Using the Scan Utility	10-45

11 Working with File Folders

What are File Folders?	11-1
Why Use and Modify File Folders Directly?.....	11-1
Advantages of File Folders	11-2
Working with File Folders	11-2
File Folder Tabs, Buttons and Menus	11-2
File Folder Tabs	11-3
Where Used Tab, File Folder.....	11-4
Buttons on the Files Tab	11-4
Buttons on Files tab in Web Client.....	11-5
Buttons on Files tab in Java Client	11-6
Working with the Files Tab of File Folders.....	11-7
Fields on the Files Tab.....	11-8
Opening and Viewing Contents of File Folders.....	11-9
Web Client, Getting File Folder Files.....	11-9
Java Client, Getting File Folder Files	11-9
Java Client, Batch Get	11-10

Switching Between Versions	11-10
Routing and Reviewing File Folders	11-10
Printing Attachment Files	11-11
About Banners and Watermarks on the Printed Image.....	11-12
Creating File Folders	11-12
Revising File Folders	11-12
Adding Attachment Files and URLs to File Folders	11-13
Using the Java Upload/Download Tool	11-13
Adding URLs	11-15
Editing the Files Table	11-15
Deleting Attachment Files and URLs from File Folders	11-16
Purging Unused File Folder Versions	11-16
Why Purge Unused File Folder Versions?.....	11-17
Getting and Revising Attachment Files and File Folders	11-18
Getting Attachment Files or File Folders.....	11-18
Web Client, Getting Files	11-18
Java Client, Get Files	11-19
Java Client, Batch Get	11-19
Checkout and Checkin to Revise Attachment Files or File Folders	11-19
Canceling Checkouts	11-21
Ad Hoc Redlining or Marking Up of Attachment Files from the File Folder	11-21
Other File Folder Operations	11-22
Performing a Mass Update of a File Folder	11-22

12 Working with Design Objects

What are Design Objects?	12-1
Design object Actions Menu	12-1
View All Versions.....	12-2
Save As, Design Objects.....	12-3
Purge Version, Design Objects	12-3
Load to CAD, Design Objects	12-4
Mass Update, Design Object.....	12-4
Design Title Block Tab	12-5
Using the Design Object Navigator	12-6
Design Object Files Tab	12-6
Adding Files to the Design Object Files Tab.....	12-8
Structure Tab of Design Objects	12-8
Structure Tab Buttons	12-9
Using Structure Go To	12-10
Routing and Reviewing Design Objects	12-11
Relationships Tab, Design Object	12-11
Where Used Tab, Design Object	12-12
Where Used Query	12-13

13 Working with Design File Change Orders (DFCOs)

What are Design File Change Orders?	13-1
The Design File Change Order (DFCO) Object	13-1

The DFCO File Publishing Process	13-2
Creating DFCOs	13-3
Routing DFCOs for Approval.....	13-3
Deleting DFCOs.....	13-3
Working with the Affected Files Tab	13-4
The Affected Files Tab	13-4
Affected Files Tab Attributes	13-4
Change Sequence	13-5
Affected Files Tab Buttons and Actions.....	13-6
Adding File to the Affected Files Table	13-7
Removing Files from the Affected Files Table	13-8
Redline/Markup Table	13-9
Redline/Markup Table Attributes	13-9
Redline/Markup Table Buttons and Actions	13-9
Adding Redline/Markups.....	13-10
Associate Redlines – Consolidating Redlines	13-10
Removing Redlines.....	13-11
Title Block Version-Specific Attributes	13-11
Publishing the DFCO	13-12

14 Working with Thumbnails

What are Thumbnails?	14-1
Viewing Thumbnails in Search Results Tables	14-3
Viewing Thumbnails in Object Tab Tables	14-4
Viewing Thumbnails on Title Page and General Info Tabs	14-5
Using the Thumbnail Navigator.....	14-7
Viewing Thumbnails in the Quick View Palette.....	14-8
Thumbnail User Privileges	14-8

A Deleting Agile Objects

Soft Delete and Hard Delete Defined	A-1
Soft-Deleting an Object.....	A-2
Undeleting an Object	A-2
Hard-Deleting an Object	A-2
Notes about Deleting Specific Agile Object Types	A-3
Notes about Deleting Item Objects	A-3
Notes about Deleting Change Objects	A-4
Notes about Deleting Transfer Order Objects.....	A-4
Notes about Deleting PSR or QCR Objects.....	A-4
Notes about Deleting Sourcing Project, RFQ and RFQ Response Objects	A-5
Notes about Deleting Package Objects	A-6
Notes about Deleting Manufacturer Objects.....	A-6
Notes about Deleting Site Objects	A-6
Notes about Deleting User Objects.....	A-7
Notes about Deleting User Group Objects.....	A-7
Notes about Deleting PG&C Objects.....	A-8

Preface

Agile PLM is a comprehensive enterprise PLM solution for managing your product value chain..

Audience

This document is intended for administrators and users of the Agile PLM products.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit

<http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit

<http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Related Documents

Oracle's Agile PLM documentation set includes Adobe® Acrobat PDF files. The Oracle Technology Network (OTN) website

<http://www.oracle.com/technetwork/documentation/agile-085940.html> contains the latest versions of the Agile PLM PDF files. You can view or download these manuals from the website, or you can ask your Agile administrator if there is an Agile PLM Documentation folder available on your network from which you can access the Agile PLM documentation (PDF) files.

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.

Convention	Meaning
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

Introduction

This chapter provides an overview of Agile PLM main features and documentation.

What is in this Manual

This manual is an introduction to Agile Product Lifecycle Management (PLM) and its main features across the user solutions of the Agile PLM suite. Agile PLM is a comprehensive suite of enterprise business applications, and the information in this guide is both a starting point for learning Agile and also a "return-to" reference manual.

This Manual Precedes the Solution Manuals

Chapters 2-6 provide information about the two primary client applications and introduce basic terms, concepts, and features that are used in Agile PLM. Chapters 7-11 cover features and functionality in Agile PLM 9.3.x.x that all users will work with sooner or later.

Agile PLM Basics

Every new Agile user needs to have a good grasp of the material in either Chapters 2, 4, and 5, if primarily using Web Client, or Chapters 3, 4, and 6, if primarily using Java Client. Some solutions are accessed only through Web Client. Your Agile administrator has likely set up your Agile account with a "preferred client."

- ? [Chapter 2, "Navigating in Agile Web Client"](#) – Web Client user interface is fully described
- ? [Chapter 3, "Navigating in Agile Java Client"](#) – Java Client user interface is fully described
- ? [Chapter 4, "Concepts and Terms in Agile PLM Solutions"](#) – the basics in Agile PLM are surveyed
- ? [Chapter 5, "Working with Business Objects in Web Client"](#) – creating objects, printing, sending, relationships, subscriptions
- ? [Chapter 6, "Working with Business Objects in Java Client"](#) – creating objects, printing, sending, relationships, subscriptions

You can change many of your user settings to help you manage your Agile user experience. A complete list of the settings in your user object is found in ["User Properties Defined"](#) on page 2-55.

Cross-Solution Utilities in Agile PLM

The material in Chapters 7-13, within each chapter, tends to run from elementary to advanced. You will likely need to learn some things about reports, searches, workflows, and attachments in Agile early on; however, not everything in these chapters has to be—or can be—mastered at

once. For example, you could learn how to work with attachments ([Chapter 10](#)) but find that you do not have to work with file folders ([Chapter 11](#)).

- ? [Chapter 7, "Working with Agile Reports"](#) – using and customizing the many ready-to-use reports in Agile PLM
- ? [Chapter 8, "Finding Agile Data with Searches"](#) – locating data and information in the Agile database
- ? [Chapter 9, "Routing Objects with Workflows"](#) – routing business objects for approval and to gather other kinds of information
- ? [Chapter 10, "Working with Attachments"](#) – Agile business objects can "carry" additional data as attachments
- ? [Chapter 11, "Working with File Folders"](#) – more advanced capabilities with the Agile objects that hold attachment files and URLs
- ? [Chapter 12, "Working with Design Objects"](#) – Design objects are an additional type of File Folder object, intended for use with CAD models.
- ? [Chapter 14, "Working with Thumbnails"](#) – Thumbnails are small bitmap images or icons which represent attached files or URLs

The Agile end-user guides all assume that you have learned the basic information presented in this guide. For instance, although each PLM solution may have its own default workflows, saved searches, and predefined reports, the basic information in this manual precedes the more specific information in the various user guides.

Overview of the Agile PLM Suite

The Agile PLM suite of solutions covers five primary areas of product lifecycle management:

- ? **Agile Product Collaboration (PC)** – Management and collaboration of product record information throughout the product lifecycle, across internal organizations and the extended supply chain. Accessed through Web Client and Java Client.
- ? **Agile Product Governance & Compliance (PG&C)** – Management and tracking of all substances and materials contained by any item or manufacturer part, allowing companies to meet substance restrictions and reporting requirements, design recyclable products, minimize compliance costs, and eliminate noncompliance on future products. Accessed through Web Client.
- ? **Agile Product Portfolio Management (PPM, formerly Program Execution)** – Integration of program and product information, streamlining business processes across the product lifecycle and across a portfolio of programs. Accessed through Web Client.
- ? **Agile Product Quality Management (PQM, formerly Product Service & Improvement)** – Integration of customer, product, quality, and regulatory information with a closed-loop corrective action system. Accessed through Web Client and Java Client.
- ? **Agile Product Cost Management (PCM)** – Management of product costs across the product lifecycle and synchronization of product cost data and processes. Accessed through Web Client.
- ? **Agile Recipe & Material Workspace (RMW)** – Management of biotechnological and pharmaceutical products, and also improvement of business productivity, visibility, scientific outcomes, and proactive compliance during the product development lifecycle. Accessed through Web Client.

For further information see *Agile PLM Getting Started with Recipe & Material Workspace*.

Agile administrators use Agile Java Client to set up and maintain settings for these solutions.

A few administrative settings can also be done in Web client.

The Agile Application Server, the foundation of the Agile suite, manages data stored in the Agile database. All Agile data is contained or organized in business objects that are set up by the administrator, and specified and used by the enterprise's Agile users. For instance, the administrator configures the Parts class of objects, and users create and deploy specific instances of the kinds of Parts made available to them. "Business objects" is a general term that implies objects created from the classes available to the enterprise, but other entities in Agile are also objects, such as workflows, searches, reports, and so forth.

The following table shows relationships between the Agile functional components and the primary client applications (Agile Web Client and Java Client) that are used to manipulate the data in the Agile Application and Database Servers (the database where the data is stored).

Table 1–1 Agile PLM functional components

Agile functional components	Client applications	Notes
Administrative Settings	Java Client Web Client	Administrative settings are configured in both Java Client and Web Client. See <i>Agile PLM Administrator Guide</i> for details.
Product Collaboration	Web Client Java Client	Web Client provides access to Agile PC functions. Java Client access to Agile PC is available only if the Agile administrator has assigned the appropriate roles and privileges.
Product Quality Management	Web Client Java Client	Web Client provides access to Agile PQM functions. Java Client access to Agile PQM is available only if the Agile administrator has assigned the appropriate roles and privileges.
Product Cost Management	Web Client	Agile PCM functions are accessed in Web Client.
Product Portfolio Management	Web Client	Agile PPM functions are accessed in Web Client.
Product Governance & Compliance	Web Client	Agile PG&C functions are accessed in Web Client.
Recipe & Material Workplace	Web Client	Agile R&MW functions are accessed in Web Client.

What's New for the User Experience in Agile PLM 9.3.6

The user interface of Agile PLM Web Client has been updated and improved for Agile PLM 9.3.6.

- 7 Additional File Options have been added to the object subscription feature: Get File, View File and Open File. See ["Subscribing to Objects"](#) on page 5-29 (Web Client) and ["Subscribing to Objects"](#) on page 6-13 (Java Client).
- 7 **Edit search criteria** icon button in Web Client **Searches** folder list of searches. See ["Editing a Search in Web Client"](#) on page 8-68.
- 7 An expanded list of numeric formats is available for selection in the User Profile. See ["User Properties Defined"](#) on page 2-55.

- ? A new column has been added to the **Workflow Routings** tab for **Routed Date**. See ["Workflow Routings"](#) on page 2-11.
- ? The resolution of duplicate signoff users in multiple signoff roles (approver, acknowledger, and observer) has been improved. See ["Web Client, Resolve Duplicate Signoff Users"](#) on page 9-23.
- ? The **View files in separate Viewer windows** setting in the Tools and Settings menu lets you choose whether to display viewed files in separate Viewer windows. See ["Navigation Pane Toolbar"](#) on page 2-24.

What's New for the User Experience in Agile PLM 9.3.5

The user interface of Agile PLM Web Client has been updated and improved for Agile PLM 9.3.5:

- ? Release a set of Designs on a single change order with workflow capabilities (Agile Product Collaboration).

Prior to 9.3.5, Designs use a routing slip that lacks workflow capabilities. The routing slip approves only one Design, not a set of related Design objects. A set of Designs can be released on a single change order by using related Items.

The 9.3.5 release allows a set of Designs to be put on a change order using a new **Affected Files** tab (without having related items). Design files are added to the change order **Affected Files** tab, where they can be redlined and updated. This allows designers to route multiple designs for approval without having to first create items. Approvers can review the entire set of designs and approve using one signature.

For more information see ["Working with Design File Change Orders \(DFCOs\)"](#), and *Agile Administrator Guide*, chapter "Configuring Design File Change Orders (DFCOs).

- ? Improvements to the Gantt client in Project Portfolio Management (Agile PPM).

These improvements include managing Multiple Projects, adding Project Navigator in GANTT, adding Filtering in GANTT, verifying Modify Privileges, and improving the Task Assignment view.

For more information, see *Agile Product Portfolio Management User Guide*.

For information about new features and functions available in Agile PLM 9.3.5 see the Agile Product Lifecycle Management Documentation Library v9.3.5, which includes:

Agile PLM Readme v9.3.5

What's New in Agile Product Lifecycle Management, v.9.3.5

available on the Oracle Technology Network (OTN) website

<http://www.oracle.com/technetwork/documentation/agile-085940.html>.

What's New for the User Experience in Agile PLM 9.3.4

The user interface of Agile PLM Web Client has been updated and improved for Agile PLM 9.3.4.

- ? A new attribute type, LargeText fields, can contain HTML formatted text. The default maximum length for LargeText fields is 60,000 characters, however, the Agile administrator can set the maximum length higher or lower, as needed. For information about configuring LargeText fields, see *Agile PLM Administrator Guide*. For information about working with LargeText fields, see ["Viewing the Contents of LargeText Fields"](#) on page 5-13, and ["Modifying LargeText Fields"](#) on page 5-14.

- Agile PLM Product Portfolio Management now has the ability to create multiple work day management calendars. For more information, see *Product Portfolio Management User Guide*.

For information about new features and functions available in Agile PLM 9.3.4, see Agile PLM Readme v9.3.4, available on the Oracle Technology Network (OTN) website <http://www.oracle.com/technetwork/documentation/agile-085940.html>.

What's New for the User Experience in Agile PLM 9.3.3

The user interface of Agile PLM Web Client has been updated and improved for Agile PLM 9.3.3.

- Improved File Transfers – up to 16 GB file sizes are supported. In Web Client, new File Upload Selector, File Upload Manager, and web browser-based file download capabilities are introduced. The Advanced File Loader has been eliminated in Web Client. See ["Adding Attachment Files from your Local Disk or Network"](#) on page 10-17.
- ECR Redlining – Redlining is now enabled on ECR Attachments tab. This is similar to Ad-Hoc redlines that have previously been available on File Folders. ECR redlining allows users to specify potential changes to documentation as part of the standard ECR process. See ["Marking Up or Redlining Attachment Files from an ECR"](#) on page 10-37.
- Revision-Specific Relationships – This is an optional feature. When Revision-Specific relationships are enabled, Item relationships can be specific to a selected specific revision, All revisions, or the Latest revision. See ["Relationships and Dependencies Between Objects"](#) on page 5-31.

For information about new features and functions available in Agile PLM 9.3.3, see Agile PLM Readme v9.3.3, available on the Oracle Technology Network (OTN) website <http://www.oracle.com/technetwork/documentation/agile-085940.html>.

What's New for the User Experience in Agile PLM 9.3.2

The user interface of Agile PLM Web Client has been updated and improved for Agile PLM 9.3.2.

- Form tabs (for example, Title Block or Cover Page) can be configured as a one-column displays or two-column displays by setting the Multicolumn Display system preference. Attribute sizes are set to Short, Medium, or Long to accommodate the two-column display.
- The Navigator capability has been expanded to additional object tabs. Additionally, navigator capability has been expanded to additional object classes: Changes, PSR, QCR, Part Groups, Declarations, Specifications, and Sourcing Projects.
- Descriptions in Recently Visited: The links in the Recently Visited list now display the object description in addition to the object number or name.
- Descriptions in Bookmarks: Descriptions are included by default on new bookmarks.
- Audit Screen Improvements: Errors and Warnings are links that, when clicked, take the user to the field, table, or object where the problem can be resolved.

What's New for the User Experience in Agile PLM 9.3.1

The user interface of Agile PLM Web Client has been updated and improved for Agile PLM 9.3.1.

See [Chapter 10, "Working with Attachments"](#) and [Chapter 12, "Working with Design Objects."](#)

What's New for the User Experience in Agile PLM 9.3

The user interface of Agile PLM Web Client has been updated and improved for Agile PLM 9.3.

See [Chapter 2, "Navigating in Agile Web Client"](#) and [Chapter 5, "Working with Business Objects in Web Client."](#)

Navigating in Agile Web Client

This chapter introduces Agile PLM Web Client and discusses Web Client window features and actions that apply to all Agile PLM solutions.

Introducing Web Client

Agile PLM Web Client is opened using a browser. Web Client is the only client that supports the following Agile PLM solutions:

- ? Program Portfolio Management
- ? Product Governance & Compliance
- ? Product Cost Management

Both Web and Java clients support the following Agile PLM solutions:

- ? Product Collaboration
- ? Product Quality Management.

You can access Agile Reports (Reports and Analytics), Design Objects, and utilities such as Agile Import, Export, and File Load from Web Client or Java Client. When these objects are selected they open in Web Client. For example, in Java Client, choosing **Tools > Import** opens the Import utility in Web Client; Java Client remains open.

Logging In to Web Client

Agile PLM 9.3 has been installed on your company's system, and you are ready to work in Web Client. There may be a bookmark already on your browser, or perhaps your Agile administrator has given you a URL, along with username (User ID) and password.

If a URL is specified in the documentation or release notes, copy the upper- and lower-case characters exactly, including the full domain name specified.

Also, if a popup blocker is installed on your computer, the login may halt. You must disable the popup blocker and then click the **Retry** button, which will display the application in a new window.

To start Web Client:

1. Start your browser.
2. Click the Web Client bookmark, if one exists, or, in the address bar of the browser, type a URL that follows this pattern:

```
http://<webserver>.<domainname>:<port>/Agile/PLMServlet
```

The Login page appears.

3. Enter your username. Your username is not case-sensitive.

Your *username* is assigned by your Agile administrator and can be an abbreviation of your full name. For example, the name Michael Jones may be abbreviated to MICHAELJ or MJONES.

Note: If you are an LDAP user, your password cannot be reset in the Agile PLM database, neither by you nor by the Agile administrator. LDAP user passwords must be reset through LDAP.

4. Enter your password. Your password **is** case-sensitive.

Your password is initially assigned by your Agile administrator. If you have the appropriate privileges, you can change your password at any time. The administrator may require you to do so within a set number of sessions. See ["Changing Your Password"](#) on page 2-36.

5. Click the **Login** button. If you type an incorrect username or password, click **Clear** and retype your username and password.

The login process is complete, and the user Home page appears ("**Welcome, <Your Name>**").

You can choose an activity from the user Home page, the navigation pane on the left, or the main toolbar at the top. For more information, see ["Top Pane Main Toolbar"](#) on page 2-21 or ["Navigation Pane"](#) on page 2-22.

You can select a preferred start page; see ["Choosing Your Preferred Start Page"](#) on page 2-2.

Note: Although it is technically possible to log in and open multiple Web Client browser windows using the same username and password, Agile PLM does not support the use of multiple browser windows in the same session. Each Web Client browser window is a separate session and activities by the same user in different browser windows are not coordinated.

Therefore, if you perform conflicting edits in multiple Web Client browser windows, then Agile PLM resolves any edit conflicts in the same way that Agile PLM resolves edit conflicts between two different users editing an object at the same time. See also *Agile PLM Administrator Guide*, **Object Edit Conflicts** SmartRule.

Bookmarking Web Client in Your Browser

When the Web Client Login page opens in your browser, you can bookmark it in your browser to create a startup shortcut in your browser Favorites list or Bookmarks list.

When the Web Client login page is open in your browser window, right-click in the login page to create a shortcut on your desktop. You can click the desktop shortcut the next time you want to open Web Client.

Choosing Your Preferred Start Page

At any time you can change the start page that opens when you log in to Web Client. However, your administrator may restrict which user profile properties you are able to change in your user object.

To set or change your preferred start page:

1. Click the **My Settings** button in the left navigation pane.

Your "user object" appears. Your user object is the Agile database object that your administrator created to represent you.

2. Click the **Preferences** tab.
3. Click the **Edit** button. The properties on the page become editable.
4. Under Display Preferences, click the drop-down arrow for **Preferred Start Page**. Select the page you want: Workflow Routings, Notifications, My Assignments, or choose from the available Dashboard tabs.

The Preferred Start Page list includes all the dashboard tabs for which you have view privileges.

For more information about the Home page and these settings, see ["Exploring the Home Page"](#) on page 2-5.

5. When you have finished, click **Save** (at the top of the page). Your preferences have been saved and you will see your chosen start page the next time you log in to Web Client.

For more information about changing properties in your user object, see ["Changing Your User Profile"](#) on page 2-32.

6. The page that displays when you first open Web Client can be changed, as described in ["Choosing Your Preferred Start Page"](#) on page 2-2.

If you chose a Dashboard page as your Preferred Start Page, that Dashboard page is displayed each time you click the **Home** button in the main menu.

Logging Out of Web Client

To log out of Web Client:


1. From the courtesy controls in the left navigation pane, click the **Logout** button.
For information about the list of courtesy controls, see ["Web Client Home Page"](#) on page 2-3.
2. You are returned to the Login page. To exit, close the browser from the upper-right corner.

Web Client Home Page

When you log in, your user Home page appears (Welcome <Your Name>").


Your Preferred Start Page setting determines which tab is displayed in the content pane. The following illustration shows a typical Home page.

Figure 2–1 Web Client Home Page



The Web Client window is organized into three main areas, or panes:

- ? **Top Pane**
 - Navigation controls (**Back, Forward, Refresh, Home**)
 - Access to the File Upload Manager (**Display the progress of file uploads**)
 - **Create** menu
 - **Search** controls
- ? **Navigation Pane**
 - Branding area and Navigation pane Expand and Collapse controls
 - Courtesy Controls
 - * **My Settings**
 - * **Tools and Settings**, for example, Import, Export, Address Book, and Calendar.
 - * **Help**
 - * **Logout**
- ? **Navigation Drawers**
 - **FOLDERS** drawer: Saved Searches, **My Bookmarks**, and **Recently Visited**
 - **REPORTS** drawer: Reports and Analytics
 - **Navigator** drawer: object links from Workflow Routings, search results table, BOM tree, or Project tree
- ? **Content Pane**
 - Business objects tabular data is displayed in the content pane.
 - The Home page, at login and when the user clicks the **Home** button.

Figure 2–2 Web Client Navigation pane, Top pane, and Content pane

Exploring the Home Page

When you first start Agile Web Client, it is a good idea to view the information collected for you on the Home page.

Your Home page includes the following components:

- ? **"Quick Links"** on page 2-5.
- ? **"Inbox Tabs"** on page 2-6.

Quick Links

Quick Links, at the top of the Home page, is a list of up to ten links that you use frequently. You can define and edit your own Quick Links list. Your Quick Links list can include predefined Agile PLM system links, saved searches in your Personal Searches folder, or bookmarks in your **My Bookmarks** folder.

To edit your Quick Links list:

1. Click the **Edit** icon next to the **Quick Links:** heading at the top of the Home page. The Edit Quick Links dialog appears.
2. From the drop-down list choose the type of link you want to use.

The three types of available links are:

- ? **Links** – predefined Agile PLM system links including My User Profile and Change Password.
- ? **Bookmarks** – available values are all the bookmarks in your Bookmarks folders, listed individually.
- ? **Searches** – available values are all the searches in your Personal Searches folders, listed individually.

3. Use the **Display Selected Columns** button and the **Hide Selected Columns** button to move links from the Hidden Links list to the Quick Links list
Or, double-click to move links from one list to the other list.
4. You may include more than ten links in the Quick Links list, but only the first ten links are displayed in your **Quick Links** list.
5. Reorder the list by selecting one or more links and using the move up and move down arrow buttons to move them up or down in the list.
6. When you are finished, click the **Save** button.

Inbox Tabs

The specific Inbox tabs displayed on your home page are determined by your assigned roles and privileges. Agile PLM home page tabs include:

- ? **Dashboard** tab – provides personalized views of selected information, such as reports, project highlights, web pages that you need to access often, and so on.
- ? **Notifications** tab – informs you of some action or process that has taken place or a notification can let you know that you have a request to accept or decline ownership of an action item or activity. Delete notifications after you have read them.
- ? **Workflow Routings** tab – lists routable objects that require your review or action. Click the object number in the table to open it.
- ? **My Assignments** tab – lists project leaf node objects assigned to you which are not yet complete and action items assigned to you which are not yet complete.
- ? **Time Sheet** tab – Agile PPM feature used to record, administer, and analyze the number of hours worked on assigned tasks. For more information see *Product Portfolio Management User Guide*.

Once your preferred start page is displayed, you can click a different tab. For example, click the **My Assignments** tab, the **Notifications** tab, or the **Workflow Routings** tab to view information about your assignments, notifications, or workflow routings.

Note: The page that displays when you open Web Client can be changed, as described in "[Choosing Your Preferred Start Page](#)" on page 2-2. If you chose a Dashboard page as your Preferred Start Page, that Dashboard page is displayed each time you click the **Home** button in the main menu.

Dashboard

The Dashboard is a highly configurable set of views that enables users to track and manage the information available in the Agile PLM system.

You can create an unlimited number of dashboard tabs to categorize and display the content you want. Access to these tabs can be restricted through roles and privileges. The data that you want to view can be retrieved from different sources, and rendered in charts, tables, and other forms.

Dashboard tabs must be created and configured in Agile Java Client by an administrator. You can view and personalize the tabs that are made visible in Agile PLM Web Client for your use.

For details on configuring Dashboard views, see the *Agile PLM Administrator Guide*.

Viewing the Dashboard

The Dashboard tab appears on the Home page along with **Notifications**, **Workflow Routings**, and **My Assignments** tabs.

To view the Dashboard:

1. In the top pane of the Welcome page, click the **Home** button.
2. Click the **Dashboard** tab.

To make the Dashboard tab page your default start page when you log in to Web Client:

1. In the top pane of the Welcome page, click the **My Settings** button. The User Profile page appears.
2. Click the **Preferences** tab.
3. Click **Edit**.
4. Select the **Dashboard** list item in the **Preferred Start Page** drop-down list.
5. Click **Save**.

Dashboard Tabs

The Dashboard comprises:

- ⌘ **Default Tabs** that enable you to select the view: **My Stuff**, **Optional Tab 1**, and **Optional Tab 2**.
- ⌘ **User-configured tabs** that display customized information in tabular or chart formats, based on preferences set up by an administrator.

Note: To view user-configured tabs, you must have the Dashboard Tab View privilege assigned to you, and this privilege must be applied to these tabs within the Agile Java Client.

- ⌘ **Widgets** within each tab that present information relevant to that view. For example, in the **My Stuff** tab, the widgets can be named and configured to display the current user's project activities: **My Assignments**, **My Documents**, **My Action Items**, and so on.
- ⌘ The Dashboard Filter icon in every table enables you to filter data within the widgets to create customized views.

For information on how to configure optional dashboard tabs, see the *Agile PLM Administrator Guide*.

My Stuff Tab

The **My Stuff** tab displays the Documents, Discussions, and Action Items assigned to the logged in user. The widgets in this tab are:

- ⌘ **My Action Items** – Displays all your Action Items by **Status**, **Creator**, and **Due Date**. The name of the project or discussion to which the Action Item is associated appears as a link in the **Belongs To** column. Click the link to view the associated object. To view the Action Item, click the corresponding link in the **Subject** column.
- ⌘ **My Documents** – Lists all the project-related documents that you own with the name of the **Root Project**, **Project Name**, **Folder Number**, and the **File Name**. To open a file, click the folder number and then click the **Files** tab. Alternatively, you can click the file name to view the document.
- ⌘ **My Discussions** – Lists all the discussions you have created for the selected set of projects, showing the Subject, Most Recent Message, and the Date for each. You can click the **Subject** link to view and reply to a discussion.

Optional Tabs

You can configure Optional Tab1 and Optional Tab2 to display reports based on your customized queries in each table. If you have the privilege to configure these tabs, a **Configure** button appears in the middle of each table in the **Optional Tabs** page.

To configure a dashboard widget table:


1. Click **Configure**.
2. In the **Table Name** field, type a name relevant for the data you want to show in the table.
3. In the **Chart Type** field, select an option.
4. Click **Next**.
5. Select one of the following search options:
 - ? **Saved Search** – Use the search palette to select a saved search.
 - ? **Advanced Search** – Click **Define Query** to use the Agile PLM Advanced Search feature to retrieve the data you want.
6. Click **Next**.
7. Select the fields you want to display from the **Available Fields** column and move them to the **Selected Fields** column using the left and right arrows. You can also reorder the fields using the up and down arrows.
8. Specify sort order and click **Finish**.

The fields that are available for display are configured in Java Client by an administrator. For more information on configuring Optional tabs in Java Client, see the *Agile PLM Administrator Guide*.

Manipulating the Dashboard Widgets

The Dashboard widgets can be manipulated by the icons and menu entries described in the table below.

Table 2–1 Dashboard widget commands

Button	Description
 Dashboard Filter	Displays the dashboard category fields which you can use to filter the widget results. Edit these fields and click Save to obtain the narrowed down search results.
Remove Content From View	Closes the window. To reopen the window, refresh your browser view. Or select the content object from the Add Content drop-down list at the bottom of the page and click Add .
Export	Exports data in comma-separated value (.CSV) format for use in a spreadsheet (available in all tables).
Refresh	Refreshes the table view to show latest changes to content.
Gantt Chart	For Projects, launches the Gantt Chart. <i>See Agile Product Portfolio Management User Guide.</i>
Maximize/Restore Original Size	Expands the window to full size or reduces it to the size it was previously.

In the windows which display a widget, you can click column headings of most tables to change the sort order. If you have the necessary privileges, you can click data in most widgets to 'drill down' to a view of the individual object.

Configuring Dashboard Tab Widgets

The Dashboard Filter icon at the top of each widget enables you to filter the data in the widget to show only the information that is most relevant to you.

To filter the table display within a dashboard tab widget:

1. Click the Dashboard Filter icon in the table. The default filter values for the dashboard category fields appear.
2. Click **Edit**.
3. The default selection for all the dashboard categories is **All**. Choose the **Selected** option to enable the search palette next to each field.
4. Launch the search palette next to the dashboard category field which you want to filter, and search for defined attributes.
5. Select attributes for each category field, one by one.
6. Click **Save**.

The selected fields display in the widget.

Notifications

The Home page **Notifications** tab lists notifications that have been sent to you through the PLM notification system. Notifications inform you of some action or process that has taken place, such as the trigger of a field subscription and the generation of RFQs. A notification can also let you know that you have a request that requires your attention. Requests ask you to accept or decline ownership of an action item or activity.

Note: To accept or decline a request, use the **My Assignments** tab.

To view a notification:

1. Click the **Subject** link.

The notification details and links to associated data are displayed in the notification palette. The palette controls include:

- ⌵ Back – read the previous notification in the table.
- ⌵ Forward – read the next notification in the table.
- ⌵ Delete – delete the displayed notification.
- ⌵ Close – close the palette.

To delete notifications from the table:

1. Select the table rows you want to delete.
2. Click the **Delete** button or Press the **Delete** key.

To filter the Notifications by time ranges:







1. Use the **Pending** age of notifications drop-down list to select the age for the notifications that you want to see in the table: All, 30 days, 90 days, 180 days, 360 days.

For example, select 90 days to see notification that moved into your Notifications list within the last 90 days. The default is 90 days, but once you make a selection in the **Pending** age list, then that selection is retained the next time you log in.

The Notifications table displays the following information about each notification.

You can sort the Notifications table by clicking any of the table column headers described below.

Table 2–2 Notifications table columns

Notification table columns	Description
Notification icons	<p>Displays icons representing the type of notification and whether you have read the notification:</p> <ul style="list-style-type: none"> Unread notifications: <ul style="list-style-type: none">  Unread notification  High importance unread notification  Low importance unread notification. Read notifications: <ul style="list-style-type: none">  Read notification  High importance read notification  Low importance read notification
Subject	<p>A link that you can click.</p> <p>The title of the notification.</p> <p>Click this link to view and read the notification in the notification palette.</p>
object icon	<p>Icon for the object type related to the notification.</p> <p>Place your cursor over the icon to see the object name in the tool tip, for example, ECR or Audit.</p> <p>Click this column header to sort the notification table by object type.</p>
Regarding	<p>A link that you can click.</p> <p>The object for which the notification was sent, for example, a specific Discussion or ECR.</p> <p>Click this link to open the object in the content pane.</p> <p>Or, use the Quick View feature to view the object:</p> <ul style="list-style-type: none"> Place your cursor over the link. When the Quick View callout bubble appears, click Quick View to open the object in the Quick View palette, a separate pop-up window. <p>The Notifications table remains visible and accessible behind the Quick View palette.</p>
Received	<p>The date the notification was received.</p> <p>Click this column header to sort the notification table by date.</p>

Workflow Routings

The Home page **Workflow Routings** tab lists routable objects that require your review or action. For example, your **Workflow Routings** table may contain changes for which you are an approver. The workflow routings are a combination of base classes and actions that you need to perform, for example, approving or acknowledging a change.

Note: The searches selected in your User Profile **Searches** field also determine which workflow routings appear in your **Workflow Routings** tab. For example, if **Change Analyst Searches** is one of your assigned searches, you see Change class object workflow routings in the **Workflow Routings** tab. In a similar manner, if **Quality Searches** is one of your assigned searches, you see QCR and PSR workflow routings. For more information, see ["Changing Your User Profile"](#) on page 2-32 and ["User Properties Defined"](#) on page 2-55.

To open an object in the table, click its number. The **Print** button prints the entire table.

The types of routable objects that appear in the Workflow Routings table are:

- 7 **Change** base class, which includes the object classes:
 - Change Orders
 - Change Requests
 - Site Change Orders
 - Price Change Orders
 - Deviations
 - Stop Ships
- 7 **Quality Change Request (QCR)** base class, which includes the object classes:
 - Corrective and Preventative Actions (CAPA)
 - Audits
- 7 **Problem Service Request (PSR)** base class, which includes the object classes:
 - Non-Conformance Requests
 - Problem Reports
- 7 **Package** base class, which includes the object class:
 - Packages
- 7 **Project** base class, which includes the object classes:
 - Activities
 - Gates
- 7 **Transfer Order** base class, which includes the object classes:
 - Content Transfer Orders (CTO)
 - Automated Transfer Orders (ATO)
- 7 **Declaration** base class, which includes the object classes:
 - Substance Declarations
 - Part Declarations
 - Homogeneous Material Declarations
 - JGPSSI Declarations
 - Supplier Declarations of Conformance
 - IPC 1752-1 Declarations

- IPC 1752-2 Declarations
- ? **File Folders** base class, which includes the object classes:
 - Designs
 - File Folders
- ? Agile Product Cost Management base classes:
 - **Sourcing Projects**
 - **Requests for Quote**
 - **RFQ Responses**

Using the Workflow Routings Tab

The **Workflow Routings** tab includes features that allow you to review your routing objects quickly and efficiently. The Navigator feature enables the quick and efficient review of all objects in the routings list.

- ? **Navigator** – When you click the **Navigator** button, the routings list is displayed in the **NAVIGATOR** drawer in the left navigation pane.

Click the links in the **NAVIGATOR** on the left to display each object in the content pane. As you click through the list, the object appears in the content pane with the most recently viewed tab displayed.

For example, click a link in the **NAVIGATOR** and then click the **Affected Items** tab in the content pane. As you click each link in the **NAVIGATOR**, the object appears in the content pane with the **Affected Items** tab selected.

By using the **NAVIGATOR**, you can quickly review Affected Items table information for each Workflow Routings object.

Note: The **NAVIGATOR** displays a maximum of 500 object links.



- ? **Sort the table by any table column** – Click the table headers to sort the table by that attribute. You can use all the table columns to sort the table.
- ? **Pending** age of routings drop-down list – Select the age for the workflow routings you want to see in the table: All, 30 days, 90 days, 180 days, 360 days. For example, select 90 days to see routings that moved into your Workflow Routings list within the last 90 days. The default is 90 days, but once you make a selection in this list, that selection is retained the next time you log in.
- ? **Print** – Click the **Print** button to print a copy of the Workflow Routings table. Use the printed list as a reference as you work with your Workflow Routings list.

The **Workflow Routings** tab includes the following table attributes:

Table 2–3 Workflow Routing table columns

Workflow Routing table columns	Description
Object icons	This column displays the appropriate object icon for each table row, for example, for an ECO or for an ECR. Click this column header to sort the table by object type.

Table 2–3 (Cont.) Workflow Routing table columns

Workflow Routing table columns	Description
Number	<p>The object number is available as a link.</p> <p>Click this link to open the object in the content pane.</p> <p>Or, use the Quick View feature to view the object:</p> <ul style="list-style-type: none"> ▸ Place your cursor over the link. ▸ When the Quick View callout bubble appears, click Quick View to open the object in the Quick View palette, a separate pop-up window. <p>The Workflow Routings table remains visible and accessible behind the Quick View palette.</p>
	<p>Has Attachments indicator.</p> <p>A dot in this column indicates that the object in this row has attachments.</p> <p>Click this column header to sort the table by whether the objects have attachments or do not have attachments.</p>
	<p>Part indicator.</p> <p>A dot in this column indicates that the object in this row has parts on its affected items table.</p> <p>Click this column header to sort the table by whether objects have affected items or do not have affected items.</p>
Description	<p>The description of the object that appears in the Description field on the object's General Info or Cover Page tab.</p> <p>Click this column header to sort the table by the descriptions.</p>
Status	<p>The current status of the object, for example, CCB or Released.</p> <p>Click this column header to sort the table by workflow status.</p>
Action	<p>This column indicates the type of action the object requires. For example, Await Approval tells you that you need to approve the object.</p> <p>If you are a routing manager, this column tells you about the progress of the object through the workflow. For example, In Review tells you that the object is being reviewed by the approvers. Awaiting Release tells you that the approvers have signed off and the object is ready to release.</p> <p>Click this column to sort the table by the routings action.</p>
Workflow	<p>This column indicates the workflow assigned to each object.</p> <p>Click this column to sort the table by workflow.</p>
Routed Date	<p>This column indicates date the object was routed for review, signoff, or other action.</p> <p>Click this column to sort the table by routed date.</p> <p>See also "How the Routing Dates on the Workflow Routings Tab are Defined" on page 2-13.</p>

How the Routing Dates on the Workflow Routings Tab are Defined

The **Routed Date** is determined as follows:

- Routable objects with workflow statuses – the date the object status changed. The object base classes that use this date as their **Routed Date** are: Changes, Packages, Declarations, Change Quality Requests, Transfer Orders, Product Service Requests, Projects.
- File Folders – the date when a reviewer is added to the File Folder or Design. The Routed Date is updated whenever a reviewer is added.

- ? Sourcing Projects – the date when the Owner attribute is updated or when a closed sourcing project is re-opened.
- ? Requests for Quote (RFQ) – the date when the Owner attribute is updated or when a closed RFQ is re-opened or unlocked.
- ? RFQ Responses – the date the RFQ is opened, the date the Supplier RFQ Response Owner chooses Send Response to Suppliers, or the date the RFQ Response is forwarded to another supplier contact.

For more information about **Routed Date**, see *Agile PLM Administrator Guide*.

My Assignments

The Home page **My Assignments** tab lists Activities and Action Items for which you are responsible. The **My Assignments** tab provides a set of tools that allow you to efficiently work with your assignments. You can sort the assignments table rows, or select one or more assignment rows in the table, and then perform an action on the selected assignments. For example, you can accept or decline a project activity assignment, or flag an assignment for easier tracking.

The Home page **My Assignments** tab table includes:

- ? Activity objects where:
 - The activity is In Process. The workflow status type is *not* Complete or Canceled.
 - The activity's **Project State** attribute is set to Active. Proposed or Template activities are not included.
 - You are the owner of the activity and the **Delegated Owner** field is blank. If you have delegated ownership, the **Delegated Owner** field contains the name of the delegated owner until the activity is accepted or declined.
 - You are the delegated owner of the activity.
 - You are a resource on the **Team** tab of the activity and your allocation is greater than 0%.
- ? Action Items where:
 - The action item is assigned to you and it is *not* Complete or Canceled.
 - The action item is assigned to you and it has been accepted.
 - The action item is assigned to you and it has *not* been declined.
 - You are the creator of the action item and it has been declined by the assignee.

My Assignments Table

Your Agile administrator determines which columns appear in the **My Assignments** table. The displayed attributes can be enabled or disabled only through the **Admin > System Settings > My Assignments** node in Agile Java Client PLM Administrator. You can, however, rearrange or filter the defined columns as you want, using the **Personalize** option. If you have questions about the **My Assignments** tab, contact your Agile administrator.

By default, the **My Assignments** tab includes the following columns:

Table 2–4 My Assignments tab columns

Column name	Description
Flag	Flag icon which you can set to manage your assignments. For more information, see "Flagging Assignments" on page 2-20.

Table 2–4 (Cont.) My Assignments tab columns

Column name	Description
Activity Status	The current status of the activity. For example, if you have not yet accepted the assignment, a Pending Acceptance icon is displayed here.
Name	The name of the activity or action item. Click this link to open the activity or action item.
Status	Workflow status of the activity or action item. For example, an activity can be Not Started or In Process and an action item can be Not Accepted, Accepted, or In Progress. If you have the appropriate privileges, you can edit the Status column. For more information, see "Editing Assignments" on page 2-18.
Due Date	The date the activity or action item is due. You can sort the assignment list by due dates. For more information, see "Using the View Options to Sort your Assignment List" on page 2-17. If you have the appropriate privileges, you can edit the Due Date column. For more information, see "Editing Assignments" on page 2-18.
% Complete	For activities, the percentage of the task that has been completed. If you have the appropriate privileges, you can edit the % Complete column. For more information, see "Editing Assignments" on page 2-18.
Related To	For activities, the Related To column lists the parent activity and root parent activity. For action items, the Related To column lists the activity or discussion object to which the action item is associated. Click the links in this column to open the related activities or discussions.
Actual Hours	For activities, the number of hours expended on the activity. If you have the appropriate privileges, you can edit the Actual Hours column. For more information, see "Editing Assignments" on page 2-18.

My Assignments Tab Tools

The **My Assignments** tab tools include:



Table 2–5 My Assignments tab tools

Tool	Description
Views	Select a view from the drop-down list. Use the list to sort your assignments by pre-defined views, for example, pending requests, flagged assignments, due dates, action items, or activities where you are a resource. For more information, see "Using the View Options to Sort your Assignment List" on page 2-17.
Print	Prints the table. Lets you print the assignment table in the currently displayed sort order. For more information, see "Printing the Assignment Table" on page 2-19.

Table 2–5 (Cont.) My Assignments tab tools

Tool	Description
Accept	<p>Accept the selected activities, project activity assignments, or action items.</p> <p>For activities, accept the ownership when you are the designated owner.</p> <p>For project activity assignments, accept the assignment as a resource for the activity.</p> <p>For action items, accept the action item when you are the assignee and the action item has not yet been accepted.</p> <p>For more information, see "Accepting Assignments" on page 2-18.</p>
Decline	<p>Decline the selected activities, project activity assignments, or action items.</p> <p>For activities, decline the ownership when you are the designated owner.</p> <p>For project activity assignments, decline the assignment as a resource for the activity.</p> <p>For action items, decline the action item when you are the assignee and the action item has not yet been accepted.</p> <p>For more information, see "Declining Assignments" on page 2-18.</p>
Mark Complete	<p>Mark as complete the selected activities or action items.</p> <p>For activities, sets the Complete field to 100% and changes the workflow status to Complete.</p> <p>For action items, changes their status to complete and removes them from your assignment list.</p> <p>For more information, see "Mark Assignments Complete" on page 2-19.</p>
More > Add to Flagged View	<p>Sets the flag for all the selected table rows.</p> <p>Lets you flag multiple rows simultaneously.</p> <p>To display flagged rows, in the View drop-down list, choose Flagged.</p> <p>For more information, see "Flagging Assignments" on page 2-20.</p>
More > Add to Hidden Assignments View	<p>Lets you hide assignments.</p> <p>Hidden assignments do not appear in the assignments table.</p> <p>For more information, see "Hiding and Unhiding Assignments" on page 2-20.</p>
More > Remove From View	<p>Remove assignments from the Hidden view.</p> <p>When displaying the hidden assignment view, this menu lets you remove (unhide) the selected assignment rows.</p> <p>See also "Hiding and Unhiding Assignments" on page 2-20 and "Flagging Assignments" on page 2-20.</p>
More > Fill-down	Copy the value from a cell to the corresponding cells in all rows following the selection.
More > Fill-down (selected cells)	Copy the value from a cell to all the selected cells. The value of the first cell in the selection is copied into all the selected cells.
More > Fill-up	Copy the value from a cell to the corresponding cells in all rows preceding the selection.
More > Fill-up (selected cells)	Copy the value from a cell to all the selected cells. The value of the last cell in the selection is copied into all the selected cells.

Table 2–5 (Cont.) My Assignments tab tools

Tool	Description
 Flag not set  Flag set	<p>Flag icon appears in each row of the assignment table.</p> <p>Set or unset the flag by clicking it.</p> <p>The flag helps you to organize your assignments and mark the ones you want to track.</p> <p>For more information, see "Flagging Assignments" on page 2-20.</p>
Quick View	<p>The Quick View callout bubble appears when you place the mouse cursor over the name of the activity.</p> <p>Click this callout bubble to open a pop-up window that displays important details about the object and lets you edit, accept, or decline the object. The content of this window is configured in Java Client Administrator.</p> <p>For more information, see "Using the Quick View Dialog" on page 2-21.</p>

Using the View Options to Sort your Assignment List

Use the Home page **My Assignments** tab **Views** drop-down list to sort your assignments and quickly find the assignments with which you want to work. For example, you can sort for pending requests or for overdue assignments.

Agile PLM provides the following pre-defined view categories.

Table 2–6 My Assignments tab predefined Views

View	Description
Base View*	Displays all assignments, except hidden assignments.
Pending Requests	Displays only pending requests.
Flagged	<p>Displays only the flagged assignment rows.</p> <p>You set or clear flags to manage your assignments. This Views list choice displays only the rows that you have flagged.</p>
Due Today or Overdue Due this Week Due within 2 Weeks Due within 30 Days Due within 90 Days	These Views list choices display assignment table rows according to due dates.
Hidden Assignments	<p>Displays only hidden assignments.</p> <p>You decide which assignments you want to hide on your assignments list.</p> <p>For more information, see "Hiding and Unhiding Assignments" on page 2-20.</p>
Activities where I am a Resource	Displays activities where you have been assigned as a resource on the Team tab.
Action Items	<p>Displays action items assigned to you.</p> <p>Action items are generated and assigned from activities and discussions.</p>

Editing Assignments

You can edit the assignment attributes in the **My Assignments** tab table. You must have the appropriate Modify privileges for the editable fields.

For example, depending on your privileges, for an activity, you can edit the **Status**, **Percent Complete**, **Actual Hours**, and **Due Date**.

To edit My Assignment table rows:

1. Click the **Home** button to display the Home page.
2. Click the **My Assignments** tab to display your list of assignments.
3. Locate the row of the assignment you want to edit.
4. Within the row, double-click a table cell to make the field editable.
5. Make the desired modifications.

The editable fields are determined by which fields your Agile administrator has included in the assignments table and your modify privileges.

6. To duplicate an existing cell value across multiple cells:
 - a. Select the range of cells that you want to fill with the same value.
To deselect a cell within the range, press CTRL and click the cell.
 - b. From the **More** drop-down menu, choose **Fill Up** or **Fill Down** as appropriate.
 - c. When you are finished, click **Save**.

Accepting Assignments

You can use the Home page **My Assignments** tab **Accept** function to accept multiple activities or action items simultaneously. The accept action applies to:

- ? Activities where you are the delegated owner.
- ? Project activities assigned to you.
- ? Action items whose status is Not Accepted and you are the assignee.

To accept assignments on the My Assignment tab:

1. Click the **Home** button to display the Home page.
2. Click the **My Assignments** tab to display your list of assignments.
3. Select one or more rows in the table.
4. Click the **Accept** button.

The selected objects are accepted.

Declining Assignments

You can use the Home page **My Assignments** tab **Decline** function to decline multiple activities or action items simultaneously. The decline action applies to the:

- ? Activities where you are the delegated owner.
- ? Action items whose status is Not Accepted and you are the assignee.

Note: When you decline an activity, you must enter a reason.

To decline assignments on the My Assignment tab:

1. Click the **Home** button to display the Home page.
2. Click the **My Assignments** tab to display your list of assignments.
3. Select one or more rows in the table.
4. Click the **Decline** button.
5. If one or more of the selected rows are activities, you must enter a reason why you are declining the activities. Enter your reason in the pop-up dialog and click **Send**.

Mark Assignments Complete

You can use the Home page **My Assignments** tab **Mark Complete** function to mark as complete multiple activities or action items simultaneously.

Note: If you have not accepted an action item, you cannot mark it as complete. Accept the action item first and then mark it as complete.

When you mark an activity as complete, the **Percent Complete** field is automatically set to 100%.

To mark assignments as complete on the My Assignments tab:

1. Click the **Home** button to display the Home page.
2. Click the **My Assignments** tab to display your list of assignments.
3. Select one or more rows in the table.
4. Click the **Mark Complete** button.

The selected assignments are marked complete.

Printing the Assignment Table

You can use the **Print** function in the **My Assignments** tab of the Home page to print the currently displayed assignments table. Use the **View** drop-down list or the Filter to sort the table, and then print the displayed table rows.

To print the My Assignment table:

1. Click the **Home** button to display the Home page.
2. Click the **My Assignments** tab to display your list of assignments.
3. Use the **Views** drop-down list to sort the table to display the assignments you want.
4. Click the **Print** button.

A printable version of the table is displayed in a new browser window and the Print dialog appears.

5. Click **Print** in the Print dialog.
6. Close the new browser window when you are finished.

Hiding and Unhiding Assignments

On the **My Assignments** tab of the Home page, the **More > Add to Hidden Assignments View** command lets you hide assignment rows that you do not want to see. The assignments are still part of your assignment list, but they are displayed only when you choose **Hidden Assignments** in the **Views** drop-down list.

Hiding assignments can be a useful assignment management tool. For example, suppose you are assigned as a resource for an activity, but you are not the activity owner. You have completed your portion of the task, but other resources have not yet completed their portions of the task. Therefore, the assignment still appears on your **My Assignments** tab because it has not been marked as Complete. You can hide this assignment so it no longer appears on your assignments list. However, it will still appear on the assignment lists of other resources.

Hiding an assignment removes it from all your **My Assignments** tab views except your **Hidden Assignments** view. Your **Hidden Assignments** view has no effect on the assignment lists of other users. You can hide assignments (add them to your hidden view), display your hidden assignments, and unhide hidden assignments (remove them from your hidden view).

To add assignment rows to your Hidden View:

1. Click the **Home** button to display the Home page.
2. Click the **My Assignments** tab to display your list of assignments.
If desired, use the **Views** drop-down list or the filter to sort which assignment rows are displayed.
3. Select one or more rows in the table.
4. Choose **More > Add to Hidden Assignments View**.

To view your hidden assignments:

1. Click the **My Assignments** tab to display your list of assignments.
2. In the **Views** drop-down list, choose **Hidden Assignments**.

To remove assignment rows from your Hidden View:

1. Click the **My Assignments** tab to display your list of assignments.
2. In the **Views** drop-down list, choose **Hidden Assignments**.
3. In the hidden assignments view, select the rows you want.
4. Choose **More > Remove from View**.

Flagging Assignments

On the Home page **My Assignments** tab, the flag icon included in each row is a useful assignment management tool. Because you can sort assignments according to whether they are flagged, you can use the flag to indicate assignments that you want to track differently from other assignments. The flags on your assignment table appear only on your **My Assignments** tab, so you can decide how you want to use them.

To set or unset the flag in a single assignments table row:

1. Click the **Home** button to display the Home page.
2. Click the **My Assignments** tab to display your list of assignments.
3. Click the flag icon in the row you want.
 - If the flag is not set (white flag icon), clicking it toggles the flag to set (red flag icon).
 - If the flag is set (red flag icon), clicking it toggles the flag to not set (white flag icon).

To set the flags in multiple assignments table rows:

1. Click the **My Assignments** tab to display your list of assignments.
If desired, use the **Views** drop-down list or the filter to sort which assignment rows are displayed.

2. Select the rows you want to flag.
3. Choose **More > Add to Flagged View**.

To unset the flags in multiple assignments table rows in the flagged view:

1. Click the **My Assignments** tab to display your list of assignments.
2. In the **Views** drop-down list, choose **Flagged**.
3. In the flagged assignments view, select the rows you want.
4. Choose **More > Remove from View**.

Using the Quick View Dialog

On the Home page **My Assignments** tab, click the **Quick View** callout bubble (appears when you place the mouse cursor over the name of activity objects) to open a details dialog that displays additional information about the object and lets you perform some actions on that object, for example, edit and delete. In the details dialog, the attributes that you can view and the actions that you can perform are determined by the roles and privileges that are assigned to you for that object type.

Top Pane Main Toolbar

In Agile PLM Web Client, toolbars appear in the top pane, left navigation pane, and content pane.

If you have the appropriate roles and privileges, you can use the toolbar buttons on the top pane to perform the tasks described in the following table. Toolbars in content pane object windows contain buttons that pertain to the object.






Figure 2–3 Top Pane main toolbar



Table 2–7 Top Pane main toolbar buttons

Button	Name	Description
	Back	Takes you to the previous page you viewed in your browser. (It does not, however, undo any changes you entered in Agile PLM.)
	Forward	Takes you to the next page forward. It is disabled if you did not use the Back button to view the page currently in your browser.
	Refresh	<p>You can refresh (update) objects, the Recently Visited list, My Bookmarks list, and Search Results page by clicking the Refresh button.</p> <p>There is a Validate button on the Cover Page of change objects in Edit mode. The Validate button saves the changes, validates the workflow, and reloads the workflow list.</p>

Table 2–7 (Cont.) Top Pane main toolbar buttons

Button	Name	Description
	Home	Displays your home page in Web Client as defined by Preferred Start Page in your user properties. The Agile administrator selects your user properties and you can change them if you have the appropriate roles and privileges. See "Choosing Your Preferred Start Page" on page 2-2. Based on that setting, when you click the Home button, the main area displays your My Assignments , Workflow Routings , or Notifications . See "Exploring the Home Page" on page 2-5. Above the main area, the standard Home page has the live links that you have defined as your Quick Links list. See "Quick Links" on page 2-5.
	Displays the progress of file uploads	Opens the File Upload Manager dialog. In the File Upload Manager you can pause, resume, or cancel any file upload that is in progress. During a file upload, this button is an indicator of the file upload progress. See also: "Web Client File Uploader Tools" on page 10-18, "Web Client File Upload Manager" on page 10-19.
Create New menu	Create New	Lets you create objects in all the base classes and classes that your company has installed and to which you have privileges. See "Introducing Agile Objects" on page 4-1.
	All	Quick Search criteria text box. Use the drop-down list to limit your Quick Search to a specific base class. See "Installed Agile Classes, Base Classes, and Subclasses" on page 4-4. Enter the search criteria you want to use in the text box. See "Web Client Quick Search" on page 8-10. The icon for the selected object class appears in the text box. The Quick Search icon indicates All object classes will be searched. See "Full Text Search for Content in Attachment Files" on page 8-17.
	Execute a Quick Search	Searches for objects that match the criteria in the Quick Search text box. See "Quick Searches" on page 8-9.
	Custom Search	Opens the Custom Search page, which lets you run a custom search using the parameters configured by your Agile administrator. From the Custom Search page, you can choose to use an Advanced Search, which looks for objects with fields that match (multiple) conditions that you define. A Where Used search finds assemblies that contain parts that meet your search criteria; a Relationship search finds objects related to the objects that match your search criteria. See "Advanced Searches" on page 8-28.


Navigation Pane

The left pane, called the *navigation pane*, provides basic access to settings, searches, reports, and the Agile PLM Navigator feature:

- ✎ Logo area, which includes the navigation pane Collapse and Expand controls.
- ✎ Navigation Pane toolbar. See ["Navigation Pane Toolbar"](#) on page 2-24.
- ✎ Navigation pane drawers, which provide access to:

- FOLDERS – Search folder, My Bookmarks folder, Recently Visited list. See ["Navigation Pane Folders Drawer"](#) on page 2-26.
- REPORTS – Analytics, Standard Reports, Global Reports, Personal Reports. See [Chapter 7, "Working with Agile Reports."](#)
- NAVIGATOR – Workflow Routings, Search results, item BOM tree, or PPM Project tree. See ["Navigator Drawer"](#) on page 2-27.

Figure 2–4 Navigation Pane



Showing and Hiding the Navigation Pane

At times you may want to show the left navigation pane or view the content pane only (hide the navigation pane).

To hide the navigation pane:

- ? In the Navigation pane toolbar, click the **Collapse Left Navigation** button (which points left).

To show the navigation pane:

- ? At the upper-left margin of the Agile PLM browser window, click the **Expand Left Navigation** pointer (which points right).

To adjust the width of the navigation pane:

1. Hold the pointer on the boundary between the navigation and content panes. The pointer changes to a double-pointed arrow.
2. Drag until the pane is the desired width: it is limited to a maximum of about three quarters of the total screen width.

Navigation Pane Toolbar

There are toolbars in the left navigation pane, the top pane, above the Web Client content pane. In the content pane, toolbars appear in object windows, and in object tabs.

If you have the appropriate roles and privileges, you can use the toolbar buttons on the navigation pane toolbar to perform the tasks described in the following table. Toolbars in object windows contain buttons that pertain to the object.

Figure 2–5 *Navigation pane toolbar*



Table 2–8 *Navigation pane toolbar buttons*





Button	Name	Description
	My Settings	Displays your User Profile. Edit your user profile to modify your user settings and preferences.

Table 2–8 (Cont.) Navigation pane toolbar buttons

Button	Name	Description
	Tools and Settings	<p>The Tools and Settings drop-down menu includes the following commands:</p> <ul style="list-style-type: none"> ? Address Book lets you view and modify User Groups, Functional Teams, and Supplier Groups, depending on your assigned roles. See "Address Book, User Groups Tab" on page 2-39. If you have been assigned an Administrator role, opening the Address Book supplies administrative access to Users, User Groups, Functional Teams, and Supplier Groups. ? Import and Export menu commands provide access to the Agile PLM client utilities Import and Export. For more information, see <i>Agile PLM Import and Export Guide</i>. ? Calendar lets you create and modify workday calendars, depending on your assigned roles. For more information, see <i>Product Portfolio Management User Guide</i>. ? Recipe & Material Workspace lets you launch the Agile Recipe & Material Workspace application. ? Microsoft Project Publish is visible in the drop-down list if Product Portfolio Management is enabled in your Agile PLM system. ? Administration is visible in the drop-down list only if you have been assigned the Administrator privilege (or Administrator role). For more information, see <i>Agile PLM Administrator Guide</i>. ? View files in separate Viewer windows setting – when you view files, this setting determines whether a new AutoVue Viewer window is created for each file that you view (enabled) or whether one Viewer window is reused to view different files (disabled, the default). <p>To toggle this setting, select this menu item in the drop-down menu. The setting is enabled when a check mark is displayed next to this menu item.</p> <p>NOTE: When View files in separate Viewer windows is enabled for a user, then files viewed in Java Client are also displayed in separate Viewer windows.</p>
	Help	<p>The Help drop-down menu includes the following commands:</p> <ul style="list-style-type: none"> ? Help provides access to Agile PLM documentation and Oracle UPK (User Productivity Kit). ? About displays version information. ? Keyboard Controls opens a dialog box that lists the keyboard shortcuts available in Agile PLM. Use the Print button in the dialog to print a copy for reference. ? Quick Tours opens a dialog from which you can view several short videos about using Web Client features. <p>See "Using Online Help" on page 2-27.</p>
	Logout	Exits Web Client and ends your current session.

Web Client Session Timeouts

Web Client sessions are set to time out, or disconnect, after a session is idle for a specified time period.

Session timeout messages are displayed in the following sequence:

1. One minute before the session expires the Session Timeout Alert message appears.
 - ? Click **OK** to extend the session.
Any unsaved data is preserved, allowing you to save your work.
 - ? Click **Close** to log out.
Agile PLM prompts you to save unsaved data (if any) before logging out.
2. If you do not respond to the Session Timeout Alert above, when the session has expired, the Session Timed Out message appears. This indicates that Agile PLM has logged out of your session and any unsaved data has been discarded.
 - ? Click **OK**.

The login screen appears in the same browser window.

Once you log in again, Agile PLM displays the page you were viewing last, if possible. For example, if you were viewing the BOM tab of an item when the session timed out, and then you log in again, using the same browser window, Agile PLM displays the same BOM tab of the same Item.

If Agile PLM cannot display the last page you viewed, then Agile PLM displays the Home page.

Additionally, if you do not explicitly log out of Agile PLM, but you close the browser window, Agile PLM closes all dialogs and saves the **Recently Visited** list. Any unsaved data is discarded.

For information about setting the timeout (idle time) value for Web Client, see *Agile PLM Administrator Guide*.

Navigation Pane Folders Drawer

If the **FOLDERS** drawer is not already open in the navigation pane, click the **FOLDERS** drawer title in the navigation pane. The currently displayed drawer closes, and the **FOLDERS** drawer opens.

The **FOLDERS** drawer displays saved searches, bookmarks, and a list of recently visited objects.

Search Folders

The **Searches** section of the navigation pane **FOLDERS** drawer contains saved searches you can use whenever needed. It includes predefined system searches and searches you have created, stored in folders. Click a search to view the search results.

For more information about saved searches, see ["Saved Searches"](#) on page 8-7.

Shortcuts

Beneath the search folders are two shortcuts areas:

- ? **My Bookmarks** – Objects you have bookmarked for quick display later. To bookmark an object, choose **Actions > Bookmark** on an object's page. For more information about bookmarking, see ["Using and Organizing Bookmarks"](#) on page 2-50.
- ? **Recently Visited** – The last 10 objects you have viewed (or 25, 50, or 100, depending on how the Agile administrator has defined the Agile PLM system preferences); click a link to display it in the content pane. For more information about the **Recently Visited** list, see ["Using the Recently Visited List"](#) on page 2-55.

Using Online Help

The **Help** drop-down menu provides access to online Agile documentation set and online help tools:

- ? **Help** – Opens the Agile documentation web page, with a link to online Agile PLM manuals and a link to Oracle Agile UPK (User Productivity Kit).

The online Agile PLM documentation set contains detailed information about Oracle Agile PLM applications, concepts, procedures, and reference information.

Oracle Agile UPK is an interactive online help utility. If UPK is not installed on your company's Agile PLM system, no UPK link is displayed.

- ? **About** – Displays technical information about the current release of Agile PLM.
- ? **Keyboard Controls** – Opens a dialog box that lists the keyboard shortcuts available in Agile PLM. Use the Print button in the dialog to print a copy for reference.

Reports and Analytics Folders

The left navigation pane **REPORTS** drawer gives you access to the **Reports and Analytics** folders. You can access the types of reports for which you have privileges—and Analytics folders if that is part of your Agile installation. You can view, edit, and delete existing reports. You create reports from the **Create New** button; see ["Creating Objects"](#) on page 5-1.

Reports are documented later in this manual. See [Chapter 7, "Working with Agile Reports."](#)

Analytics requires separate licensing. Agile **PLM Analytics** folder may not appear in your view. There is a separate user guide for Analytics.

Navigator Drawer

When you click a **Navigator** button in the content pane, Agile PLM populates the **NAVIGATOR** drawer with a list of object links. As you click each link in the Navigator drawer, the object is displayed in the content pane. The list in the navigator drawer is not refreshed or updated as you click through the list.


Populate the navigator list by clicking the **Navigator** button in the following locations:

- ? **Workflow Routings** tab on the Home page, to navigate your workflow tasks.
See ["Navigating Workflow Routings"](#) on page 2-27.
- ? Search results table, to navigate the list of search results.
See ["Navigating Search Results"](#) on page 2-28.
- ? Content pane of Agile PLM objects: item, change, PSR, QCR, sourcing project, design, part group, declaration, specification.
See ["Navigating Object Structures"](#) on page 2-29.
- ? Project object, to navigate the Agile PPM project tree.
See ["Navigating the Project Tree"](#) on page 2-30.

Navigating Workflow Routings


When the **Workflow Routings** tab is displayed on the Home page, click the **Navigator** button on the **Workflow Routings** tab. The workflow routings list is displayed in the left navigation pane **NAVIGATOR** drawer.

Figure 2–6 Workflow routings list displayed in the Navigator drawer



When you click a link in the **NAVIGATOR** drawer, the object is displayed in the content pane. The navigator list remains visible in the **NAVIGATOR** drawer, allowing you to click and view any object in the navigator list.

Figure 2–7 Displaying a Navigator drawer workflow routing in the content pane




Navigating Search Results

When a search results table is displayed on the content page, click the **Navigator** button on the search results table. The list of search results is displayed in the left navigation pane **NAVIGATOR** drawer.

The **Navigator** button appears in Quick Search, Custom Search, and Advanced Search results tables.


Note: The **NAVIGATOR** drawer displays a maximum of 500 search results.

Figure 2–8 Search results displayed in Navigator drawer



When you click a link in the **NAVIGATOR** drawer, the object is displayed in the content pane. The navigator list remains visible in the **NAVIGATOR** drawer, allowing you to click and view any object in the navigator list.

Figure 2–9 Displaying a Navigator drawer search result object in the content pane



Navigating Object Structures

When the following objects are displayed in the content pane, click the **Navigator** button in the object window to display the object structure in the left navigation pane **NAVIGATOR** drawer.


- ? Item
- ? Design
- ? Part Group
- ? Project
- ? Change
- ? PSR
- ? QCR
- ? Sourcing Project
- ? Declaration
- ? Specification

Tabs that include a table are displayed in the left navigation pane **NAVIGATOR** drawer. The displayed tabs are the tabs that have been enabled for that object type. (For information about enabling object tabs, see *Agile PLM Administrator Guide*.)

The first tab is expanded to list the tab contents. To expand another tab, click the expand control (right arrow head) next to the tab name in the **NAVIGATOR** drawer. Click the collapse control (down arrow head) to collapse the tab in the **NAVIGATOR** drawer.


If you click the expand control for a tab that has no contents, then the tab is displayed in the content frame, and the tab name in the **NAVIGATOR** drawer is displayed without a collapse control.

For example, click the **Navigator** button in the content pane of a part to view the structure of the part:

Figure 2–10 Displaying the structure of a part in the Navigator drawer


Use the expand (right arrow head) and collapse (down arrow head) controls to view the contents of a tab in the **NAVIGATOR** drawer.

When you click a link in the **NAVIGATOR** drawer, the object is displayed in the content pane. The object structure remains visible in the **NAVIGATOR** drawer, allowing you to expand additional tabs as needed.

Figure 2–11 Displaying a Navigator drawer item structure object in the Content pane


Navigating the Project Tree

When a project object is displayed on the content pane, click the **Navigator** button in the Project window. The Project tree is displayed in the left navigation pane **NAVIGATOR** drawer.

Figure 2–12 *Displaying the project structure in the Navigation drawer*

Use the expand (right arrow head) and collapse (down arrow head) controls to view the Project tree structure in the **NAVIGATOR** drawer.

When you click a link in the **NAVIGATOR** drawer, the object is displayed in the content pane. The Project tree remains visible in the **NAVIGATOR** drawer, allowing you to click and view any object in the Project tree.

Figure 2–13 *Displaying a Navigator drawer project object in the Content pane*

Changing Your User Settings

View and edit your User Profile settings by clicking the **My Settings** button in the left navigation pane menu; your User Profile is displayed in the content pane.

Administrators or user administrators can access the profiles of other users by choosing **Tools and Settings > Address Book** or other User Settings. For more information about working with User Settings (for user administrators), see *Agile PLM Administrator Guide*.

The Agile administrator may have set values in Agile PLM that impact what you are able to modify. Most changes made by the administrator are automatically implemented systemwide; however, if the administrator makes changes in your role assignment, or to the roles and privilege masks themselves, these take effect for a user only after the user has logged out and logged back in to Web Client or Java Client.

To make changes to a setting:

1. Display your user profile by clicking the **My Settings** button in the left navigation pane. Your user profile object is displayed in the content pane.
2. Click the user profile tab you want to change.

3. The user profile window also includes the **Change Passwords** button, the **Transfer Authority** button, and the user profile **Actions** menu.

Here are the personal settings available on the User Profile object and where you can find more information about them in this manual.

Table 2–9 User settings on the My Settings page

User Settings available on the My Settings page	Topics in this manual describing the function
User Profile	"Changing Your User Profile" on page 2-32.. See also "Choosing Your Preferred Start Page" on page 2-2.
Change Passwords	"Changing Your Password" on page 2-36.
Transfer Authority	"Signoff Authority Transfers" on page 2-36.
Actions > Specify Personal Criteria	"Creating Personal Criteria" on page 2-34.

The following is a list of additional personal settings and features in Agile PLM Web Client, where to access these settings in Web Client, and the sections of this manual that explains the feature:

Table 2–10 Personal settings in Web Client

Additional personal settings	Where to access the function and topics in this manual describing the function
Organize Bookmarks	Navigation pane FOLDERS drawer, in the My Bookmarks section, click the Organize Bookmarks icon. "Organizing Bookmarks" on page 2-51.
Organize Searches	Navigation pane FOLDERS drawer, in the Searches section, click the Organize Searches icon. "Editing and Managing Searches and Search Folders" on page 8-64.
Organize Reports	Navigation pane REPORTS drawer, click the Organize Reports icon. Chapter 7, "Working with Agile Reports."
Personal Groups	Navigation pane select Address Book in the Tools and Settings menu. "Address Book, User Groups Tab" on page 2-39.
Personal Supplier Groups	Navigation pane, select Address Book in the Tools and Settings menu. "Creating Personal User Groups" on page 2-39.

Changing Your User Profile

Your User Profile is simply the settings entered by the Agile administrator when your "user object" was created. Your user profile is available for you to modify, within constraints set by the administrator. The data contained in the various tabs of your user profile is either purely information or it is data useful data to the Agile solutions:

- **General Information**, for example, your contact information;
- **User Preferences**, including:
 - **System Preferences**, for instance, your preferred client to receive email notifications;
 - **Format Preferences**, for instance, your Windows date and time preferences; and

- **Display Preferences**, for instance, whether you see icons or text in the toolbar (or both).
- ? Other tabs are for **Escalations**, **User Groups**, **Share**, **Subscription**, **Attachments**, and **History**, which you will learn about in other chapters of this manual.

To edit or add information to your user profile:

1. Open your user profile by clicking the **My Settings** button in the left navigation pane.
2. Click the tab on which you want to make changes. For example, click the **Preferences** tab.
3. Click the **Edit** button on that page. Use lists, palettes, and text boxes to enter the requested information.
4. When you have finished, click **Save**. To cancel your changes, click **Cancel**.

You may change settings on other tabs, but you must click **Save** for each page you alter the settings. If you click another tab after entering new values, you will be prompted to cancel the move operation so you can save the tab you are on.

To verify changes you make to your user profile, it is best to log out of Web Client and login again.

Note: If you will be working primarily in Web Client, check this setting in your user profile: **Preferences** tab, **System Preferences** section, **Preferred Client** setting; it should be set to Web Client. Also, **Receive Email Notifications** should be set to Yes. This will ensure that you receive email notifications in the same client you are working in. If there is a discrepancy and you are not able to change these properties, see your Agile administrator.

Important: Product Portfolio Management, Product Governance & Compliance, and Product Cost Management solutions operate only from Web Client. If one of these solutions is to be your primary area of work, your administrator has likely already set Preferred Client to **Web Client**. If you change this setting to **Java Client**, all your email notifications will include a link that opens Java Client; yet you cannot work with PPM, PG&C or PCM objects in Java Client, therefore, consider how you will use Agile PLM before you change this setting.

User Preferences

A full list of the user preferences and their descriptions are found in "[User Properties Defined](#)" on page 2-55.

Persisted User Interface Settings

For some user interface settings, the most recently used settings are persisted across sessions for each user.

Examples include:

- ? **Resizable table columns**
 - Resizable table column widths are persisted across sessions for each user.
 - Certain dialog sizes, for example, Create New dialog and Save As dialog.
 - Selections on the drop-down list on **Workflow Routings** tab on the **Home** page.

- The last-used custom search mode. That is, if you execute an advanced search, the next time you login and click the **Custom Search** button in top-pane, the advanced search is automatically displayed instead of the basic search.
- ? **Table Personalization** – See ["Defining Table Views"](#) on page 2-46.
- ? **Agile PPM** – Creation method selection in the Create Project from Template wizard.

User Profile Tabs

Your User Profile includes the following tabs. Your assigned roles and privileges determine which tabs and settings that you are allowed to modify.

Table 2–11 User Profile tabs

User Profile tab	Description
General Info	Information about you in Agile PLM. For details, see "Changing Your User Profile" on page 2-32 and "User Properties Defined" on page 2-55.
Preferences	Your preferences that determine how data is displayed for you in Agile PLM. For details, see "Changing Your User Settings" on page 2-31 and "User Properties Defined" on page 2-55.
Escalations	Your list of escalations. For more information about escalations, see "Working with Escalations in Web Client" on page 2-37.
User Groups / Functional Teams	The user groups and functional teams of which you are a member. Your personal user groups are listed and managed in the Address Book. See "Web Client Address Book: Users, User Groups, Functional Teams, and Supplier Groups" on page 2-38.
Share	List of objects that have been shared with you. On this tab, you can select and remove shares. For more information about sharing, see "Sharing Objects with Other Users" on page 6-12.
Subscription	List of objects to which you have subscribed. On this tab, you can select and remove subscriptions. For more information about subscriptions, see "Subscribing to Objects" on page 5-29.
Attachments	Files or URLs attached to your User Profile. See Chapter 10, "Working with Attachments."
History	Summary of actions and modifications made to the User Profile.

Creating Personal Criteria

A saved "personal criteria" is a reusable database query very similar to an advanced search, in that the attributes used to create personal criteria are similar to the attributes used to create advanced searches. (For more information, see ["Advanced Searches"](#) on page 8-28.) They may also be thought of as "filters" or "qualifying descriptions" of objects that you want to track.

You use personal criteria to define signoff authority transfers. If you have the appropriate privileges, you can temporarily transfer your signoff authority for routable objects to one or more Agile users. For more information about signoff authority transfers, see ["Transferring Signoff Authority"](#) on page 9-35. and ["Defining Personal Criteria for Authority Transfers"](#) on page 9-38.

Any criteria in Agile—personal or reusable—applies to one Agile class (and its children) or a particular subclass; therefore, you must create a separate criteria to apply to the objects of another class or another subclass.

To create a personal criteria:

1. Open your user profile by clicking the **My Settings** button in the left navigation pane.
2. Choose **Actions > Specify Personal Criteria**. The specify Personal Criteria window appears.
3. Click the **Add** button. The Create Criteria dialog appears.
4. Fill in the **Name** and **Description** fields.
5. In the first drop-down list, select the object base class. In the second drop-down list, select the object class or subclass (type) that your personal criteria will apply to.

The personal criteria name must be unique. If you specify a personal criteria name that is already used, a duplicate name error message is displayed.

6. Select the attribute you want from the **Attribute** drop-down list. The available values in the list change according to the Agile class or subclass you selected in the previous step.
7. The **Operator** field specifies the search operator. The values that appear depend on what you selected from the **Attribute** list. Select from the listed operators, which will be a subset of the following:

Contains, Does Not Contain
 Equal To, Not Equal To
 Greater Than, Greater Than Or Equal To
 Less Than, Less Than Or Equal To
 Is Null, Is Not Null
 Starts With, Does Not Start With
 Like, Not Like

8. In the **Value** field, select a value for the field you selected from the **Attribute** list.
9. If you are going to add additional conditions, select a value (And, Or) in the **Join** field.
 Alternately, you can click the plus button to add another search condition. Click the minus button to remove a search condition.
10. Repeat step 6 through step 8 until your personal criteria is complete.

Note: Changing the criteria in the **Object Type** field resets the entire personal criteria. A personal criteria applies to one class or subclass. You must create a separate global criteria to apply to another class or subclass.

11. If you want your criteria to be case-sensitive, select the **Match Case** check box. This can simplify how you define personal criteria:
 - ⌚ If you enter text in the Value field, the criteria will look for text that is an exact match, depending on the restraints of the **Operator** field's value.
 - ⌚ If you define a numeric value, selecting the **Match Case** check box allows the Agile PLM system to utilize internal database settings to find objects more quickly.

Using case-sensitive searches improves performance of the system and is recommended when possible.
12. When the criteria is complete, click **Save**.

13. Click **Close** to close the Specify Personal Criteria dialog.

The **Grouping** menu lets you group search conditions in parentheses or brackets. The **Add()** grouping option places parentheses around the specified condition or conditions, which changes the order in which the search conditions are evaluated. The **Add()** grouping option follows the standard algebraic order of operations. The grouped criteria within parentheses are resolved before any others. If you do not use parentheses when defining your personal criteria search, the search is processed row by row without any precedence of **Join** values (And, Or). The first line is combined with the second based on the first line's **Join** value. The result of the first two lines is then combined with the third line based on the second line's **Join** value, and so on.

Changing Your Password

These instructions describe how to change your login password. The process is similar for changing your approval password using the **Change Approval Password** option, which is enabled only if your Use Login Password for Approval user property is set to **No**.

Note: If you are an LDAP user, your password cannot be reset in the Agile PLM database, neither by you nor by the Agile administrator. LDAP user passwords must be reset through LDAP.

To change your login password:

1. Open your user profile by clicking the **My Settings** button in the left navigation pane.

Your user profile appears in the content pane.

2. Click the **Change Passwords** button.

The Change Passwords dialog appears.

3. Type your old login password in the **Login Password** field.

4. Type your new login password in the **New Login Password** and **Confirm Login Password** fields. (Passwords are case-sensitive.)

To change your approval password (and the Change Passwords dialog displays the **Change Approval Password** fields), fill in the fields as described above.

5. Click **Save**. If you have not followed the rules set by the Agile administrator for selecting passwords, you are prompted to correct your password.

Signoff Authority Transfers

The Agile administrator or user administrator can have signoff authority transferred from you to another user or from another user to you. This is useful when, for example, you are out of the office and unavailable to sign off on changes.

To view transfers that have been set up:

1. Open your user profile by clicking the **My Settings** button in the left navigation pane.

Your user profile appears in the content pane.

2. Click the **Transfer Authority** button.

3. The All Transfer Authority Details dialog appears.

If you have the appropriate privileges, you can add, remove, or edit a transfer authority. See ["Routing Objects with Workflows"](#) on page 9-1.

Working with Escalations in Web Client

If your administrator has granted you the necessary privileges, you can set up escalations for yourself. Escalations allow changes to be forwarded automatically to a designated user if you do not respond within a set amount of time. You can also create escalations for your personal user groups.

Your Agile administrator can add escalations to your user profile, and can edit existing escalations.

To manage escalations for yourself:

1. Display your user profile by clicking the **My Settings** button in the left navigation pane. Your user profile object is displayed in the content pane.

2. Click the **Escalations** tab.

3. To set up a new escalation, click the **Add** button. The Add Escalation dialog appears.

4. Select an escalation criteria.

5. Choose one or more users to be notified for that criteria.

6. When you are finished, click the **Add** button in the dialog.

7. You can select a different person for each criteria, if you want.

Click the **Add** button and repeat the process for each criteria for which you want to create an escalation.

8. To edit an escalation in the table:

- a. Double-click the cell you want to modify. For example, double-click the **Criteria** cell.
- b. Select a different criteria from the drop-down list. Press the Tab key to move to the **Notify Users** cell.
- c. Use the address palette to add or remove users from to **Notify Users** list.
- d. Click the **Save** button at the top right of the table.

9. To delete an escalation, select its row and click the **Remove** button.

To manage escalations for a personal user group:

1. Display your personal groups:

- a. In the left navigation pane **Tools and Settings** menu, choose **Address Book**. The Address Book appears in the content pane.
- b. Click the **User Groups** tab. By default, all the user groups to which you have access are displayed, both Global groups and Personal groups.
- c. In the **Views** list, choose **My Personal Groups**. The table is filtered to display only your personal groups.

2. Click the name link of the user group you want to modify. The user group appears in the content pane.

3. Click the **Escalations** tab.

4. To set up a new escalation, click the **Add** button. The Add Escalation dialog appears.

5. Select an escalation criteria.

6. Choose one or more users to be notified for that criteria.

7. Click the **Add** button in the dialog.

8. You can select a different person for each criteria, if you want.
9. Click the **Add** button and repeat the process for each criteria for which you want to create an escalation.
10. To edit an escalation in the table:
 - a. Double-click the cell you want to modify. For example, double-click the **Criteria** cell.
 - b. Select a different criteria from the drop-down list. Press the Tab key to move to the **Notify Users** cell.
 - c. Use the address palette to add or remove users from to **Notify Users** list.
 - d. Click the **Save** button at the top right of the table.
11. To delete an escalation, select its row and click the **Remove** button.

Web Client Address Book: Users, User Groups, Functional Teams, and Supplier Groups

The Agile Web Client Address Book is a multi-tab display in the content pane that lets you view or manage users, user groups, functional teams, and supplier groups, depending the roles and privileges assigned to you.

To open the Address Book, choose **Tools and Settings > Address Book > <Address Book tab>** in the left navigation pane menu.

The Address Book includes the following tabs:

- ? Users
- ? User Groups
- ? Functional Teams
- ? Supplier Groups

User groups cannot be modified (adding or deleting users) in the Address Book, instead, you must use the **Users** tab of the user group object. To modify a user group or delete a user group, use the **User Groups** tab on the Address Book display to view your user groups.

You can access the address book by choosing **Tools and Settings > Address Book** and selecting a tab. You can select individual users (**Users** tab) or user groups (**User Groups** tab). The address book lists all the individuals and global user groups that have been created in Agile PLM.

Your Agile administrator can use Discovery privileges to limit the users you see in the address book.

Address Book, Users Tab

Note: Your Agile administrator can use Discovery privileges to limit the users you see in the address book.

If you are assigned a role with privileges that allow you to create or modify user objects (for example, the User Administrator role), then you can perform these actions from the Web Client Address Book **Users** tab.

Refer to *Agile PLM Administrator Guide* for detailed information about creating and managing users, and for information about roles, job functions, and passwords.

To open the Address Book:

1. In the left navigation pane **Tools and Settings** menu, choose **Address Book** and then choose **Users**.
2. The **Add** button opens the Create New User dialog, which lets you create a new user object.

To use the remaining Users tab buttons:

1. Select one or more rows in the Users table, and then choose the action you want to perform.

Note: You must have the appropriate privileges to perform these actions. If you have questions about your roles and privileges, contact the Agile administrator.

The following table summarizes the remaining available **Users** tab actions:

Table 2–12 Address Book User tab actions

Address Book Users tab action	Description
Change Status	Change the status (Active, Inactive) of the selected users.
Add Users to Group menu: Add Users to Group	Add the selected users to an existing user group. In the Add Users To Group dialog, enter the name of the user group or perform a search for the user group you want.
Add Users to Group menu: Add Users to New Group	Add the selected users to a new users group. Opens the Create New dialog. Enter a name for the new user group. When you click Save , the user group is created and the selected users are added as members.
More menu: Assign Roles	Assign roles to the selected users. Lets you assign one or more roles to multiple users at the same time.
More menu: Assign Job Functions	Assign job functions to the selected users. Lets you assign one or more job functions to multiple users at the same time.
More menu: Change Password at Next Login	Forces the selected users to change passwords the next time the users log in.

Address Book, User Groups Tab

With the appropriate privileges, you can create personal user groups. You create user groups from the Address Book **User Groups** tab.

Creating Personal User Groups

With the appropriate privileges, you can create personal user groups. You create user groups from the Address Book **User Groups** tab.

To create a personal user group:

1. To open the Address Book, in the left navigation pane **Tools and Settings** menu, choose **Address Book** and then choose **User Groups**.
2. Click **Add**. The Create New User Groups dialog appears.
3. In the **Type** field, select the User Group subclass.
4. In the **Name** field, type the name of the new group.

5. In the **Global/Personal** field, choose **Personal** or **Global**.

Note: If you have the appropriate privileges, you can create a Global group. Global groups are available and visible to all Agile PLM users. Your personal groups are available and visible only to you.

6. Click **Save**.
7. The newly created user group is displayed in the content pane with the **General Info** tab in edit mode.
8. On the **General Info** tab, specify general information about the user group, including description, status (Active or Inactive), and whether you want this group to be a resource pool (part of the Product Portfolio Management solution), one or more owners, and maximum number of users.
9. Click **Save**.
10. To add users, click the **Users** tab.
11. Click the **Add** button to add users.
12. When you have selected all the users you want to include in the new group, press the Return key.

You may complete aspects of the user group by clicking the tabs and the **Edit** button. See ["Editing Personal User Groups"](#) on page 2-40.

Editing Personal User Groups

You can edit the groups you have created.

To edit a personal group in Web Client:

1. In the left navigation pane **Tools and Settings** menu, choose **Address Book** and then choose **User Groups**.

The Address Book appears in the content pane and displays the **User Groups** tab.

By default, all the user groups to which you have access are displayed, both Global groups and Personal groups.

2. In the **Views** list, choose **My Personal Groups**.
3. The table is filtered to display only your personal groups.
4. Click the name of the user group you want to edit.

The user group appears in the content pane.

5. On the **General Info** tab, you can click **Edit** to change the general information about the group.
6. You can click the **Users** tab to add or delete users.
 - ? To add users, click **Add**.
 - ? To remove users, select one or more user rows and click **Remove**.

7. To create or modify escalations, click the **Escalations** tab.
8. You can add or remove attachments on the **Attachments** tab.

For information about attachments, see [Chapter 10, "Working with Attachments."](#)

Deleting Personal User Groups

To delete a personal user group from the address book:

1. Choose **Tools and Settings > Address Book > User Groups** in the left navigation pane menu.

The Address Book appears in the content pane and displays the **User Groups** tab.

By default, all the user groups to which you have access are displayed, both Global groups and Personal groups.

2. In the **Views** list, choose **My Personal Groups**.

The table is filtered to display only your personal groups.

3. Click the name of the user group you want to delete.

The user group appears in the content pane.

4. Click **Remove**.

5. Respond to the prompt by clicking **OK**.

Note: If the personal group is involved with elements like workflow approval or escalation, you will be prompted and prevented from deleting the group. In this case, you can set the group to Inactive status, which keeps the group from being involved in new events, but does not impact events in which it is already involved.

Undeleting Deleted Personal Groups

A personal group may be "undeleted" if, for instance, a project team (group) is no longer needed after the project is completed, then the project is reinstated later, and the same people are on the project team. Once the group is undeleted, of course, the users in the group can be changed.

To undelete a personal user group:

1. From the Recycle Bin searches folder, execute the Deleted Personal User Groups search.
2. Open a deleted personal group by clicking its name.
3. In the **Actions** menu, choose **Undelete**. The selected group is undeleted and now appears in the Personal Groups table.

By undeleting the deleted user group, it appears again in the Address Book.

Creating a New Group Using Save As on a Deleted Personal Group

You can also create a new personal group from a deleted personal group. Once you have opened a deleted personal group, in the **Actions** menu, choose **Save As**. You will be prompted to give the deleted group a new name and save it. You can then modify it in the usual ways.

Address Book, Functional Teams Tab

Functional teams are a list of workplace job functions, and each job function is assigned one or more users. In the **Functional Team(s)** field of a routable object, one or more functional teams can be selected. Workflows are configured to assign Approvers, Acknowledgers, and Observers by job function. When the routable object enters a signoff status, Agile PLM automatically assigns users from the functional team as reviewers of the routable object according to job function. This ability to assign approvers by job function is referred to as the Approval Matrix feature.

Note: Functional Team objects are created in Agile PLM Web Client.

To create, modify, and manage functional team objects, you must have the appropriate role. If you have questions about your roles and privileges, contact the Agile administrator.

To create a functional team:

1. In the left navigation pane **Tools and Settings** menu, choose **Address Book** and then choose **Functional Teams**.

The Address Book opens with the **Functional Teams** tab displayed.

2. Click **Add**.
3. In the Create New dialog, select a value in the **Type** field, if necessary.
4. In the **Name** field, enter the name of the functional team.
5. Click **Save**.

The functional team object is displayed.

6. Modify the remaining fields on the **General Info** tab, if desired.

 ? Description – Enter a meaningful description.

 ? Status – Can be set to Active or Inactive.

 ? Owner – If desired, select a different user.

7. Click **Save**.

On the **Job Functions** tab, you specify the job functions that will be included in this functional team, and you select the user or user group that will perform each job function on this team.

To add select job functions and add team members:

1. Click the **Job Functions** tab.
2. Click the **Add** button. The Add Job Function to Functional Team dialog appears.
3. In the **Job Function** field, click the **Launch the Palette** button to open the selection palette.
4. Double-click to select a job function.

You can select only one job function for each job function table row. Each job function can be listed only once on the job function table.

5. Press Escape to close the palette.
6. Click the **Launch the Palette** button to open the Users/User Groups search palette.
7. Search for the user or user group you want to add.

The search is limited to users or user groups that have been assigned the job function that you selected in step 4. For example, if you select Developer as the job function, the search is limited to users or user groups that where Developer is included in their **Job Function(s)** attribute.

8. Double-click the users you want to add.
9. If desired, you can perform additional searches to find more users or user groups to add.

You can add as many users and user groups as needed.

10. When you are done, click **Add**.

The row is added to the job functions table.

To remove a job function from the Job Function table:

1. Select the row you want to remove.
2. Click **Remove**.

To edit a job function row:

Note: You can add or remove users or user groups in the **User/User Groups** cell of the Job Functions table.

1. In the table row you want to modify, double-click inside the **User/User Groups** cell. The search palette appears.
2. Click the small **x** button on each user or user group you want to remove.
3. Type the name of the user or user group you want to add separated by semicolons.

Or, click the **Launch the Palette** button to open the address book palette.

The search is limited to users or user groups that have been assigned the job function in that row.
4. Press Return to save your modifications to the cell.
5. When you are done, click **Save** on the job functions table.

Deleting Functional Teams

To soft-delete a functional team:

1. Select and open the functional team you want to delete.
2. In the Actions menu, choose **Delete**, and respond **OK** to the confirmation prompt.

The object is soft-deleted.

To undelete a soft-deleted functional team:

1. Run the Deleted Global User Groups search from the **Recycle Bin Searches** folder.
2. Open the deleted function team that you want to restore.
3. In the Actions menu, choose **Undelete**.

To hard-delete a soft-delete functional team object (if you have the appropriate privileges):

1. Run the appropriate Deleted Global User Groups search from the **Recycle Bin Searches** folder.
2. Open the functional team you want to delete.
3. In the Actions menu, choose **Delete**, and respond **OK** to the confirmation prompt.

Creating a New Functional Team Using Save As on a Deleted Functional Team

You can also create a new functional team from a deleted functional team. Once you have opened a deleted functional team, in the **Actions** menu, choose **Save As**. You will be prompted to give the deleted functional team a new name and save it. You can then modify it in the usual ways.

Creating Personal Supplier Groups

With the appropriate privileges, you can create personal supplier groups. You create personal supplier groups from the **Settings** page.

To create a personal supplier group:

1. In the left navigation pane **Tools and Settings** menu, choose **Address Book** and then choose **Supplier Groups**.
2. The Address Book appears in the content pane displaying the **Supplier Groups** tab.
3. Click **Add**. The Add Supplier Group dialog appears.
4. Type a name and a description of the new group, and select the supplier group type **Personal**.
5. In the Suppliers field, select the suppliers you want to include in the supplier group.
6. Click **Add**. The personal supplier group is created and appears on your Supplier Groups tab.

You may modify aspects of a supplier group by selecting the supplier group row and clicking the **Edit** button.

Working with Web Client Tables

Web Client displays many types of information in tables. For example, search results, BOMs, and RFQ information appear in tables. Often a table is what you see when you click a tab in an object, so as **BOM** tab displays the **BOM** table.

To open and view objects in a table:

1. Click the Number link of the object.

Web Client displays a tooltip (in both Read and Edit modes) that displays the object ID and object Description, which identifies the data in the row that has the focus.

Viewing and Opening Table Objects

To open and view objects in a table:

1. Click the Number link of the object.

Web Client displays a tooltip (in both Read and Edit modes) that displays the object ID and object Description, which identifies the data in the row that has the focus.

To Quick View the objects in a table:

1. Hover the cursor over the object link until the **Quick View** callout bubble appears.
2. Click the **Quick View** callout bubble. The object is displayed in the Quick View palette.

Selecting Rows in Tables

There are some Agile tables on which you can perform certain actions in Web Client. For example, on the **Affected Items** table, you can add items to the table or remove items from the table. These tables have a "handle" column at the left, as shown in the following figure. You can select rows by using any of the following methods:

1. You can select all the rows with the top handle, or you can use Windows commands (Shift-click and Ctrl-click) on the row handles to select the rows on which you want to perform the action.

- You can select a row by clicking in the row or you can use Windows commands (Shift-click and Ctrl-click) in the rows you want.

When you have selected the rows you want, the available actions are buttons in the menu bar above the table.

Figure 2–14 *Selecting rows in a table*




Table Views

Table Views allow you to customize the way you view tables. Global table views are available to all users. Your personal table views are available only to you. Multiple table views can be defined.

Sort Order in Tables

A table is initially sorted according to the Default View for that table. Agile PLM provides a Base View for each table. You can define additional personal views for each table, and select any view as your default view.

You can change the sort order of any Agile table, for example, the **Affected Items** table. To sort a table, click the column header of the column by which you want to sort. For example, to sort the **Affected Items** table by item description, click the **Item Description** column header. On a returned-search table, all columns can be sorted, that is, clicking the column header sorts the table one way, clicking again sorts the other way (ascending or descending order).







An indicator in the column header indicates how the table is currently sorted:

Table 2–13 *Column header sort order icons*

Column Sort Indicator	Sort Order
↑	Ascending. The table is sorted by the column attribute in ascending order.
↓	Descending. The table is sorted by the column attribute in descending order.

Table views can include up to three sort definitions: a primary sort, a secondary, and a tertiary sort. When more than one sort definition is applied to a table, the sort indicators appear in the column headers as follows:

Table 2–14 Column header multiple sort order icons

Column Sort Indicator	Sort Order
1 	Primary Sort, Ascending.
1 	Primary Sort, Descending.
2 	Secondary Sort, Ascending.
2 	Secondary Sort, Descending.
3 	Tertiary Sort, Ascending.
3 	Tertiary Sort, Descending.

Defining Table Views

To define a table view:

1. In the Views list, select a table view. You can select the Base View.
2. In the Personalize list, choose Save As.
3. In the Table Personalization palette, on the Properties tab:
 - ⌘ Enter a name and a description.
 - ⌘ In the Type list, choose a table view type: Global or Personal.
 - ⌘ In the Apply to list, choose whether to apply the table view to this object subclass or to the all objects in the class.

Tip: The subclass name appears in the top left corner of the object pane, under the object number.

4. To choose which attributes to display on the table, click the **Format** tab.
5. On the **Format** tab, in the Hidden Fields table, select field names you want and then use the right and left arrows to move field names to and from the Hidden Fields and Displayed Fields lists. Double-clicking a field name also moves it from one list to the other list.

The Displayed Fields list specifies the field names that will appear in the table. Use the up and down arrows to change the order of field names in the list, which reflects the order of the columns in the table.

Lock horizontal scrolling – Use the **Lock Selected Column** button to lock horizontal scrolling. Select and highlight an attribute in the Displayed Fields list. The slightly thicker vertical line appears to the right of the locked column in the search results table.

- ⌘ Click the **Lock Selected Column** button. A lock icon (locked padlock icon) appears in the Displayed Fields list next to the selected attribute. The locked column and all columns to the left of the locked columns will not scroll horizontally. For example, when you lock the number column, the object number is always visible when you scroll horizontally left or right.
- ⌘ To lock a different column, select the attribute you want in the Displayed Fields list and click the **Lock Selected Column** button. The lock is moved from one attribute to the other. Only one column can be locked at a time.

- 7. To remove the lock, select the locked column in the Displayed Fields list and click the **Unlock Selected Column** button. The column lock is removed and no columns remain locked.
- 6. Click the **Sort** tab.
- 7. To sort the table, on the Sort tab, in the Attribute column, use the drop-down list to select the field name by which you want to sort first and use the Sort Order drop-down list to choose Ascending or Descending. Select attributes and sort order for up to three attributes. The results are sorted by the first attribute, then by the second attribute and then by the third attribute.
- 8. Click **Apply** at any time to immediately apply your format settings to the table.
- 9. When you have finished specifying output fields and sort order, click **Close** in the Search Personalization palette.

Web Client Tab Content Indicator Icons

In Web Client, a gray dot icon appears on the tab, next to the tab name, to indicate:

- 7. The tab has contents. For example, content icon on a **BOM** tab indicates that the item has child items added to the **BOM** tab.
- 7. The tab has active contents. For example, a content icon appears on the **Changes** tab of an item only when the item has pending changes (active changes).

A red square icon appears on a tab to alert you that the tab has problematic content.

- 7. The red square icon is displayed on the **Compliance** tab if an item or manufacturer part has a specification that is non-compliant or is missing information.
- 7. A red square icon is displayed on the item **Changes** tab if the item has a released Deviation or Stop Ship.

Table 2–15 Tab indicator icons






Tab	Web Client Tab Indicator	Found in these classes of business objects
Attachments (and Files)	 (Gray Dot icon) = Object has attachments	All objects except file folders (which contain attachment content) and reports.
Changes	 (Gray Dot icon) = Item has pending changes  (Red Square icon) = Item has released Deviation or Stop Ship The Red Square icon also appears in the Pending Changes column on the Search Results, BOM, and Affected Items tables, if the items have pending and active Deviation or Stop Ship.	Items Published Prices File Folders Designs
BOM	 (Gray Dot icon) = Item has BOM items	Items.
Manufacturer	 (Gray Dot icon) = Item has manufacturer parts	Items & Sourcing Projects.

Table 2–15 (Cont.) Tab indicator icons















Tab	Web Client Tab Indicator	Found in these classes of business objects
Affected Items Affected Files (in DFCOs) Affected Prices (in PCOs)	 (Gray Dot icon) = Change has affected items	Changes, PSRs, QCRs.
Sites	 (Gray Dot icon) = Item has sites assigned	Items.
Prices	 (Gray Dot icon) = Object has prices	Items & Manufacturer Parts.
Suppliers	 (Gray Dot icon) = Object has suppliers	Items & Manufacturer Parts.
Quality	 (Gray Dot icon) = Item has active PSR or QCR	Items.
Compliance	 (Gray Dot icon) = Object has specifications  (Red Square icon) = Object has non-compliant or incomplete specifications	Items, Manufacturer Parts, & Part Groups.
Content	 (Gray Dot icon) = Program has object content (relationships)	<i>Agile PPM Program objects</i> <i>For Program classes, relationships are included on the Content tab and relationships with rules are named deliverables.</i>
Discussions	 (Gray Dot icon) = Program has discussions	Agile PPM Program objects.
Related PSR	 (Gray Dot icon) = PSR has related PSRs	Agile PQM Product Service Request (PSR) objects.
PSRs	 (Gray Dot icon) = Customer has active PSRs	Customers
First object tab "Page One" for example: Cover Page Title Block General Information General Info In Web Client, optional tabs: Page Two and Page Three	Not applicable Tab indicator icons are not used on these tabs.	All objects have a "Page One" that uses one of the names to the left. In Web Client, if Page Two and Page Three sections are enabled, they appear on the first object tab. Your Agile administrator may rename them.

Table 2–15 (Cont.) Tab indicator icons

Tab	Web Client Tab Indicator	Found in these classes of business objects
Relationships	 (Gray Dot icon) = Object has relationships  (Red Square icon) = Object has a revision-specific relationship and the revision-controlled item has a new revision	All classes (except Actions Items and Reports) (For Programs classes, relationships are included on the Content tab, which does have an indicator icon.)
Where Used	Not applicable Tab indicator icons are not used on this tab.	Items, Manufacturer Parts, Discussions, File Folders.
History	Not applicable Tab indicator icons are not used on this tab.	All.
Workflow (routable objects only)	 (Gray Dot icon) indicates that a workflow has been assigned	Changes, PSRs, QCRs, Packages, Transfer Orders, Programs
Escalations	Not applicable	Users and User Groups
Shares	Not applicable	Users and User Groups
Subscriptions	Not applicable	Users

Adding Objects to Tables

When adding rows to a table in Web Client, you can use any of the following methods to select the objects to add:

- ? Add by typing and type-ahead search
- ? Add by quick search
- ? Add by custom search
- ? Add by creating a new object
- ? Add by Drag and Drop
- ? Add by Copy and Paste

To add rows to a table in Web Client with the Add palette:

1. Click the object tab to display the table you want.
2. Click the **Add** button. The add object palette appears.
3. You can use any of these methods to select the objects to add to the table:
 - ? **Type-ahead Search:**
 - a. In the text entry field, begin typing the number or name of the object you want to add.
 - b. Agile PLM displays a list of objects that match the text typed so far.
 - c. Use the arrow up and arrow down keys to highlight the object you want.
 - d. Press the right arrow key to select the object.
 - e. Press the Enter key to add the object to the table and close the palette.

? **Quick Search:**

- a. Click the **Search to Add** button to open the Search palette.
- b. Enter the search string text in the text field, and click the **Launch Search** button. The search results are displayed in the palette table.
- c. Click, Ctrl-click or Shift-click to select the row or rows you want to add and then press Enter. The selected objects are added to the table.
- d. When you are done adding objects to the table, press Escape key to close the palette.

? **Custom Search:**

- a. Click the **Search to Add** button to open the Search palette.
- b. Click the **Custom Search** button to open the Custom Search palette. The Base Class appears by default according to the tab from which you invoke the Custom Search.

In the Custom Search palette, click **Advanced** to provide elaborate search criteria. Click **Basic** to revert to the simple search frame.

- c. Specify the Search criteria as required.
- d. Click **Search**. The search results conforming to the specific criteria appear in the Search results pane.
- e. Click, Ctrl-click or Shift-click to select the row or rows you want to add to the table.
- f. Use Copy/Paste or drag and drop method to add the selected results to the table.

Note: In the Custom Search palette, you can click the **Launch Saved Searches** button to view the list of Saved Searches. Double-click one of the saved searches. The results appear in the Search results pane.

? **Create a New Object:**

- a. Click the **Create to Add** button to open the Create New dialog.
- b. Select the object type.
- c. Complete the required fields.
- d. Click the **Add** button. The newly created object is added to the table.

Editing and Modifying Tables

Editing and modifying Web Client tables includes the following actions:

- ? Adding one or more rows to a table
See ["Adding Objects to Tables"](#) on page 5-5.
- ? Removing one or more rows from a table
- ? Editing table fields

Using and Organizing Bookmarks

If there are objects that you need to return to frequently, you can use Bookmarks and the **Recently Visited** list for quick access. For more information about the **Recently Visited** list, see ["Using the Recently Visited List"](#) on page 2-55.

Bookmarking

Bookmarking enables you to keep a list of objects that you return to frequently. You can click an object bookmark to quickly display that object.

You can also bookmark reports that you use frequently.

To bookmark an object in Web Client:

1. Open the object.
2. From the **Actions** menu, choose **Bookmark**.
3. The Add to Bookmarks dialog box appears.
4. Enter a name for the bookmark in the **Name** field.
By default, the **Name** field contains the object's number or name. You can edit or replace the bookmark name in this field now, or you can edit the bookmark name later.
5. Select a folder in which to store it.
6. To create a new folder, click the **New Folder** button. In the Add New Folder dialog, enter a folder name and click **Save**.
7. Click **Save** in the Add to Bookmarks dialog box to save the bookmark in the highlighted folder.

The bookmark is saved in the **My Bookmarks** list in the **FOLDERS** drawer on the left navigation pane.

Using a Bookmark

To open a bookmarked object in Web Client:

1. Click **FOLDERS** drawer in the navigation pane.
2. Expand the **My Bookmarks** list.
Or, click the **Expand All** icon in the navigation pane to display all bookmark subfolders and their contents.
3. Click the object link in the list of bookmarks.
The object opens in the content pane.




Organizing Bookmarks

You can organize bookmarks, including renaming them and organizing them into folders.

Buttons on the Web Client My Bookmarks Toolbar

The following table lists and describes the buttons on the **My Bookmarks** folder in the Web Client navigation pane.

Table 2–16 *My Bookmarks folder buttons*

Button	Description
 Expand All	Expands all the bookmark folders in the navigation pane to display all available bookmarks.
 Collapse All	Collapses all the bookmarks folders in the navigation pane.
 Organize Bookmarks	Opens the Organize Bookmarks dialog.

The Organize Bookmarks Dialog

Use the features in the Organize Bookmarks dialog to create or remove folders, rename or remove bookmarks, and organize and move folders and bookmarks.

Open the Organize Bookmarks dialog by clicking the pencil icon in the left navigation pane next to **My Bookmarks**. The Organize Bookmarks dialog appears.

Table 2–17 *Organize Bookmarks dialog actions*

Button or action	Description
Remove	Removes the selected bookmarks and bookmark folders. See "Deleting a Bookmark" on page 2-52.
(double-click a name)	Renames the selected bookmark or bookmark folder. See "Renaming a Bookmark or a Bookmark Folder" on page 2-54.
Create Folder	Adds a new bookmark folder within the current folder. See "Creating a Bookmark Folder" on page 2-53.
Order	Reorder the contents of the selected folder alphabetically, either A to Z or Z to A. See "Reordering the Contents of a Bookmark Folder" on page 2-53.
Expand All	Expands all the bookmark folders in the Organize Bookmark dialog to display all available bookmarks.
Collapse All	Collapses all the bookmarks folders in the Organize Bookmarks dialog.
(drag and drop)	Lets you reorder bookmarks and bookmark folders. See "Moving Bookmarks and Folders" on page 2-54.
Save	Save the modifications you made in the Organize Bookmarks dialog.
Cancel	Discards the modifications you made in the Organize Bookmarks dialog.
Close	Closes the Organize Bookmarks dialog.

Deleting a Bookmark

To delete a bookmark in Web Client:

1. Click the pencil icon in the left navigation pane next to **My Bookmarks**.
The Organize Bookmarks dialog appears.
2. In the Organize Bookmarks dialog navigate to the bookmark you want to remove and select it.
3. Click the **Remove** button.
4. To save your modifications, click **Save**.
5. When you are finished, click **Close**.

The Organize Bookmarks dialog closes.

Renaming a Bookmark or a Bookmark Folder

To rename a bookmark or a bookmark folder in Web Client:

1. Click the pencil icon in the left navigation pane next to **My Bookmarks**.
The Organize Bookmarks dialog appears.
2. In the Organize Bookmarks dialog navigate to the bookmark or to the bookmark folder you want.
3. Double-click the name of the bookmark or the bookmark folder.
An edit text box appears.
4. Type the name you want to use for the bookmark or folder and press the Return key.
5. To save your modifications, click **Save**.
6. When you are finished, click **Close**.
The Organize Bookmarks dialog closes.

Using Folders to Organize Bookmarks

You can organize your bookmarks in folders to make them easier to locate and manage. You can use the existing folders or create new ones.

Creating a Bookmark Folder

To create a bookmark folder in Web Client:

1. Click the pencil icon in the left navigation pane next to **My Bookmarks**.
The Organize Bookmarks dialog appears.
2. In the Organize Bookmarks dialog, if folders already exist, click a folder row within which you want to create a new folder.
3. Click the **Create Folder** button.
4. In the text field, enter a new name and press the Return key.
5. To save your modifications, click **Save**.
6. When you are finished, click **Close**.
The Organize Bookmarks dialog closes.

Reordering the Contents of a Bookmark Folder

To alphabetically reorder the contents of a bookmark folder in Web Client:

1. Click the pencil icon in the left navigation pane next to **My Bookmarks**.
The Organize Bookmarks dialog appears.
2. In the Organize Bookmarks window navigate to the bookmark or to the bookmark folder you want.
3. Select the folder you want to reorder alphabetically.
4. Click the **Order** button and select either **A to Z** or **Z to A**.
5. To save your modifications, click **Save**.

6. When you are finished, click **Close**.

The Organize Bookmarks dialog closes.

Removing a Bookmark Folder

You can remove or delete a folder, even if it is not empty.

To remove a bookmark folder in Web Client:

1. Click the pencil icon in the left navigation pane next to **My Bookmarks**.
The Organize Bookmarks dialog appears.
2. In the Organize Bookmarks window navigate to the folder you want to remove and select it.
3. Click the **Remove** button.
4. To save your modifications, click **Save**.
5. When you are finished, click **Close**.

The Organize Bookmarks dialog closes.

Renaming a Bookmark or a Bookmark Folder

To rename a bookmark or a bookmark folder in Web Client:

1. Click the pencil icon in the left navigation pane next to **My Bookmarks**.
The Organize Bookmarks dialog appears.
2. In the Organize Bookmarks dialog navigate to the bookmark or to the bookmark folder you want.
3. Double-click the name of the bookmark or the bookmark folder.
An edit text box appears.
4. Type the name you want to use for the bookmark or folder and press the Return key.
5. To save your modifications, click **Save**.
6. When you are finished, click **Close**.

The Organize Bookmarks dialog closes.

Moving Bookmarks and Folders

To move a bookmark or a bookmark folder into another folder or to a different location in the list in Web Client:

1. Click the pencil icon in the left navigation pane next to **My Bookmarks**.
The Organize Bookmarks dialog appears.
2. In the Organize Bookmarks window, navigate to the bookmark or folder that you want to move.
 - To expand a folder, click the **Expand** icon to the left of the closed folder icon.
 - To expand or collapse all the bookmark folders, use the **Expand All** and **Collapse All** buttons
3. Click and drag the folder or bookmark to its new location and drop it. The final location is indicated by highlight icons:

- 7. A blue arrow next to a folder indicates that the dropped bookmark will be inserted under the highlighted folder.
 - 7. A green arrow next to a bookmark or folder indicates that the dragged bookmark or folder will be inserted above or below the highlighted row.
4. To save your modifications, click **Save**.
 5. When you are finished, click **Close**.

The Organize Bookmarks dialog closes.

Using the Recently Visited List

When you view an object during a Web Client session, it is listed in the **Recently Visited** list. The **Recently Visited** list includes the last 10 objects viewed (or 25, 50, or 100 if the administrator re-set the Agile PLM systemwide Preference).

To open a recently visited object in Web Client:

1. Click the **FOLDERS** drawer in the navigation pane.
2. Expand the **Recently Visited** list.
3. Click the object link in the list of recently visited objects.

The object opens in the content pane.

User Properties Defined

The table below lists and describes the properties common to all users in the Agile PLM system. The **General Info**, **Preferences**, **Escalations**, and **User Groups** tabs are documented here. **Share**, **Subscription**, and **History** tabs are all automatically populated, and do not have editable fields or properties. To modify the **Attachments** tab, see ["Working with the Attachments Tab of Business Objects"](#) on page 10-4. If you are not able to set a field that you want, see the Agile administrator to go over your roles and privileges.

Preferences for users are found on the **Preferences** tab of any user object. There are three subcategories of user preferences: system-related, format-related, and display-related.

Note: For Administrator users – These user preferences should not be confused with the **Admin > Server Settings > Preferences** node in Agile Administrator in Java Client.

Table 2–18 *User properties, General Info tab*

Property	Notes	Description
User ID (username)	Required field	The user's Agile PLM login user identification or username.
First Name and Last Name	Required field	The user's public name.
Status	Required field	Indicates whether the user is enabled (Active) or disabled (Inactive). A disabled user cannot log in.
Email	Required field	The user's valid email address for change notification/routing. <i>Example: danny.design@agile.com.</i> Note: The user will not receive any email notifications if there is no valid address in the Email field.

Table 2–18 (Cont.) User properties, General Info tab

Property	Notes	Description
Status	Optional user information	Active or Inactive. (This is the same thing as Enabled or Disabled, respectively.)
Title	Optional user information	The user's title, for example, Senior Engineer.
Address fields	Optional user information	There are four address fields that are used for informational purposes only: Address (street), City , Postal/Zip Code , and Geography . The Geography field is a series of drop-down lists.
Phone number fields	Optional user information	The user's Business Phone , Home Phone , and Mobile Phone numbers (for informational purposes only).
Fax	Optional user information	The user's fax number (for informational purposes only).
Pager	Optional user information	The user's pager number (for informational purposes only).
Secondary Email	Optional user information	The Secondary Email is optional, but when the field is filled in, the user receives notifications at both email addresses.
Role(s)	Profile field	The user's role assignments. This property determines a user's access to the objects in Agile PLM from the point of discovery forward.
Job Function(s)	Profile field	The user's assigned job functions. This property determines which job functions the user can be associated with in a functional team.
Lists	Profile field	These lists link certain roles, like Change Analyst, to routable objects and their workflows, such as Changes.
Searches	Profile field	These lists control roles, searches folders, and queries. For example, Change Analyst Searches controls whether a user has, in Web Client, a Change Analyst Searches folder and, in Java Client, Change Analyst queries in the My Inbox Workflow Routings list.
User Category	Profile field	Named, Concurrent, or Restricted.
Use Login Password for Approval	Profile field	Each user has a login password and approval password (used to approve changes).
Allow Escalation Designation Approval	Profile field	If the user has identified one or more Designated Escalation Persons (DEPs), this setting determines when the DEPs can approve or reject a routable object.
Home Organization	Profile field	The name of the company profile (organization name) for all users created from the Java Client Users node or the Web Client Address Book Users tab. For supplier users, the supplier name and supplier number for all users added to the Contact Users tab of the supplier object.
Site(s) and Default Site	Profile field	Sites are used for distributed manufacturing, and indicate all of the company's locations where the user is involved; selecting from the drop-down list for this property populates the drop-down list for Default Site. Default Site is the user's main base of work.

Table 2–18 (Cont.) User properties, General Info tab

Property	Notes	Description
Ship-To address fields	Profile field	<p>Authorized Ship-To (called "Site" in earlier versions of PCM), used only by PCM, indicates all company locations where the user can initiate sourcing activity; selecting from the drop-down list for this property populates the drop-down list for Home Ship-To.</p> <p>Home Ship-To is the primary location where the user is responsible for sourcing activities.</p>
Program Manager for Partners	Profile field	The partners for which this user is program manager (which is the change analyst for Package objects).
Rate fields	Profile field	There are three Rates fields: Labor Rate , Overhead Rate , and Bill Rate . The drop-down lists in these fields show all currencies entered in the Currency Exchange Rates node. You can select a currency different from the user's Preferred Currency (see Preferences tab). Used by Agile PPM.
Comment	Profile field	The Agile PLM administrator may enter a comment regarding the user.
Project Type	Profile field	Types of Agile PPM projects the user can participate in.
Region	Profile field	Regions the user belongs to.
Division	Profile field	Divisions the user belongs to.
Product Line	Profile field	Product lines the user has access to.
Customer	Profile field	Customers the user is associated with.
Launch Year	Profile field	Product launch years the user is associated with.
Category 7 to Category 24	Profile field	Optional Product Portfolio Management Dashboard fields.
Project Type	Profile field	The Project types to which the user has access. For more information, see <i>Product Portfolio Management User Guide</i> .
Calendar	Profile field	The user's preferred calendar which defines work days and non-work days. For more information, see <i>Product Portfolio Management User Guide</i> .

Table 2–19 User Properties, Preferences Tab, System Preferences

System Preference Property	Description
Preferred Client	<p>This field controls the type of link provided in system notifications to the user. Select Web Client or Java Client.</p> <p>Agile's PCM, PG&C, and PPM solutions operate only in Web Client. Users who work primarily in those areas should have their Preferred Client set to Web Client.</p>
Preferred File Manager	Select from the list of file servers. For best performance, select a file server that is a local server for the user.
Receive Email Notification	Controls whether the user can receive automatically generated email notifications from the system. <i>Settings</i> = Yes or No

Table 2–20 User Properties, Preferences Tab, Format Preferences

Format Preference Property	Description
Language	English is available with all Agile PLM licenses. Agile PLM includes Italian, Korean, Portuguese, Russian, Spanish, Japanese, Traditional Chinese, Simplified Chinese, French, or German, per your license.
Workweek Settings	This setting is for future use only, and is not referenced in any Agile PLM solution. Note: This property is not applicable to any Agile PLM module including Product Portfolio Management and Microsoft Project schedules.
Preferred Date Format	The format in which dates are displayed to the user.
Time Zone	The time zone where the user is located.
Preferred Time Format	The format in which times are displayed to the user.
Preferred Currency	The currency in which prices/costs are displayed to the user.
Number Format	<p>The format in which numbers are displayed to the user when the Display Format property of the numeric attribute is set to User's Preferred Number Format.</p> <p>If the Display Format property of the numeric attribute is not set to User's Preferred Number Format, then the number is displayed in the format specified in the Display Format property of the numeric attribute, thus overriding the Number Format user preference when displaying that numeric attribute. For more information, refer to <i>Agile PLM Administrator Guide</i>.</p> <p>The administrator or user selects a type of number format preference. An example of each format is displayed in the drop-down list. The available number formats are:</p> <ul style="list-style-type: none"> 7 987,654,321.09 Comma as thousands separator. Period as decimal indicator. 7 987 654 321.09 Space as thousands separator. Comma as decimal indicator. 7 987.654.321,09 Period as thousands separator. Comma as decimal indicator. 7 987'654'321.09 Apostrophe as thousands separator. Period as decimal indicator. 7 987654321.09 No thousands separator. Period as decimal indicator. 7 987654321,09 No thousands separator. Comma as decimal indicator.

Table 2–21 User Profile, Preferences Tab, Display Preferences

Display Preferences Property	Description
Preferred Start Page	Select between My Assignments, Notifications, and Workflow Routings. If the user has privileges that allow them to view any dashboards, one of those dashboards can be selected as the Preferred Start Page.

Table 2–21 (Cont.) User Profile, Preferences Tab, Display Preferences

Display Preferences Property	Description
Response Edit Mode	The default response mode for RFQ Responses in Agile PCM. Choose between Basic, Advanced Table Edit, and Advanced Wizard Edit. The Basic setting brings the user—generally a "supplier" who does not work at the "buyer" company—to a simplified Web Client user interface. The two Advanced settings bring the user to the familiar Web Client UI.
Encode Type	Select from: Western European (ISO) , Japanese (Shift JIS) , Traditional Chinese (Big 5) , Japanese (EUC) , Simplified Chinese (GB2312) , Korean (MS949) , Russian (cp1251) , and Unicode (UTF-8)
Thumbnails	Turns thumbnail display Off or On. Requires the Agile PLM system preference Thumbnail Support to be enabled.
Table Display Mode	Determines whether Web Client tables will display Thumbnails in a separate column. Set to Standard or With Thumbnails
Search Display Mode	The three settings of this mode determine whether Web Client search results tables display Thumbnails. Set to Thumbnails, Standard, or Standard with Thumbnails
Show Time Sheet	Set to Yes to display Timesheet tab in your Agile PLM Home page. Requires the SmartRule Detailed Timesheet Entry to be enabled.

Table 2–22 User Profile, Escalation Tab

Escalation Tab Property	Description
Criteria and Notify Users	Set Criteria and Notify Users , which is an individual user or user group (personal or global) to be notified when a workflow status exceeds its escalation time period without a signoff by the user.

Table 2–23 User Profile, User Groups/Functional Teams Tab

Property	Description
Name and Status	The user's user group assignments. The user is a member of the listed groups.
Name, Job Function(s), Status	The user's functional team assignments. The user is a member of the listed functional teams. Job Function(s) indicates which job functions the user performs on that team.

Navigating in Agile Java Client

Agile Java Client is distributed using only a browser and Java Web Start. You can access the Product Collaboration solution and the Product Quality Management (PQM) solution with Java Client. Other Agile solutions are accessed with Web Client only.

While you might prefer to work in Java Client on a regular basis, some utilities on the **Tools** menu (Agile Import, Export, FileLoad) and Reports open only in Web Client. Some Product Collaboration features (Item Attribute Change Management features and viewing Designs attached to item objects) are available in Web Client only.

Navigating in Agile Java Client

Agile Java Client is distributed using only a browser and Java Web Start. You can access the Product Collaboration solution and the Product Quality Management (PQM) solution with Java Client. Other Agile solutions are accessed with Web Client only.

While you might prefer to work in Java Client on a regular basis, some utilities on the **Tools** menu (Agile Import, Export, FileLoad) and Reports open only in Web Client. Some Product Collaboration features (Item Attribute Change Management features and viewing Designs attached to item objects) are available in Web Client only.

Logging In and Out of Java Client

Agile PLM 9.3.4 has been installed on your company's system, and the Agile administrator has sent you a URL to connect to Java Client. You can also connect to the Java Client using application path on your Start Menu or a short cut icon on the desktop. If you do not have access to Java Client, see your administrator.

Complete details for installing the Java Client can be found in the manual *Windows Client Installation Guide for Agile e6.1.3.0*. To find Agile eSeries documentation, visit:

<http://www.oracle.com/technetwork/documentation/agile-eseries-098047.html>

To log in to Java Client:

1. Start the Web browser and type the following, per information from your administrator:
`http://<webserver_hostname>:portnumber/JavaClient/start.html`
2. You will receive a message about accessing the computer when you install and run Java Client. Click **Launch**. The Login window appears.
3. Enter your username. Your username is not case-sensitive.

Your *username* is assigned by your Agile administrator and can be an abbreviation of your full name. For example, the name Michael Jones may be abbreviated to MICHAELJ or MJONES.

4. Enter your password. Your password **is** case-sensitive.


Your password is initially assigned by your Agile administrator. If you have the appropriate privileges, you can change your password at any time. The administrator may require you to do so within a set number of sessions. (See "[Changing Your Password](#)" on page 3-11.)

Note: If you are an LDAP user, your password cannot be reset in the Agile PLM database, neither by you nor by the Agile administrator. LDAP user passwords must be reset through LDAP.

5. Click **OK**.

Note: If you do not have logon access to Java Client, an error message is displayed. If you have questions about your Java Client logon access, contact your Agile administrator

Figure 3–1 Java Client Window



The login process is complete. The Java Client window opens, as shown in the figure above.

The next time you start Java Client, you are prompted to create shortcuts on the desktop and in the Start menu. It is recommended that you choose Yes for either or both shortcut types.

You can also start Java Client using the Java Web Start icon on your desktop. Double-click the icon and you will see an option for Agile PLM.

Note: If you are having difficulty logging in to Java Client, one problem could be that your Java Web Start cache might be full. To clear the cache, open Java Web Start, choose **File > Preferences**, click the **Advanced** tab, and click **Clear Folder**. Then try launching Java Client. If you continue to have difficulty logging in, contact the Agile administrator.

You can search for Agile data using the Simple Search field and **Run Search** button. To create a Quick Search, use the Search Option drop-down list to select a specific object type. Or, use the **Advanced Search** button. You can choose an activity from the menu bar, main toolbar, or tab toolbar. For detailed instructions about searching, see, [Chapter 8, "Finding Agile Data with Searches."](#)

To close Java Client, click the **Exit** button.

Java Client Windows, Menus, and Toolbars

This section discusses some key user interface elements of Java Client.

Java Client Menus

You can use the following menus to perform various tasks based on your assigned roles and privileges:

- 7 **File** – Perform actions on Agile business objects, including **New** (Create), **Open**, **Close**, **Save**, **Save As**, **Send**, **Scan Files**, **Batch Print**, and **Exit** Java Client. Some Agile objects are items (parts and documents), changes (such as engineering change orders and price change orders), file folders (attachment objects), users, and suppliers. For more information about classes of Agile objects, see ["Introducing Agile Objects"](#) on page 4-1.

The Scan utility (**File > Scan Files**) is available in Java Client only. See ["Agile Scan Utility"](#) on page 3-4.

- 7 **Edit** – **Cut**, **Copy**, and **Paste** data. **Delete** and **Undelete** an object. Create a **Quick Search** or an **Advanced Search** and **Organize Searches** (delete). Add, organize, and delete **Bookmarks**.
- 7 **View** – View **Notifications**, **Workflow Routings**, and toggle the **Windows Bar** on or off: the Windows Bar shows all current open windows in Java Client.
- 7 **Tools** – Work with the **Address Book**; generate **Reports and Analytics**; access Agile Import, Export, and **FileLoad** (these are documented in the *Agile PLM Import/Export Guide*). **Process Extensions** appear on a drop-down menu, which depends on a developer at your company (or an Oracle Consulting - Agile Practice consultant) having created process extensions.
- 7 **Settings** – **Transfer Authority** for other users or user groups to sign off your workflows; create and modify **Personal Groups**, **Personal Supplier Groups**, and **Personal Criteria**; view **Deleted Personal Groups**; view and modify your **Current User** settings; **Change Password**.

Color Scheme and **Options** offer some standard Windows-based options.

- 7 **Window** – This is a standard menu that allows you switch to the **Previous Window** or the **Next Window**, and to arrange your open windows in **Cascade** or **Tile** schemes. The **Window** menu displays keyboard shortcuts for some commands.
- 7 **Help** – **Manuals** gives access to Agile PLM documentation and UPK (Oracle User Productivity Kit). UPK is available if it has been installed with your Agile system. **About Agile** displays information about the current release of Java Client.

Agile Scan Utility

From Java Client only, the Agile Scan utility runs a Windows utility that scans documents using a TWAIN interface. The user specifies valid file types. Scanned images are designated as one of those file types and they are added to the system as an attached file to a file folder object. For a description of Scan, see ["Scan Utility"](#) on page 10-44.

Java Client Toolbars

There are toolbars in the main Java Client window, in object windows, and in some object tabs.

Depending on your assigned roles and privileges, you can use the toolbar buttons on the main toolbar to perform the tasks described in the following table. Toolbars in object windows contain buttons that pertain to the object.

These are the buttons that appear on Java Client's main toolbar.

Table 3–1 *Java Client toolbar buttons*

















Button	Name	Description	For more information, see...
	Inbox	Displays Notifications or Workflow Routings . You can change this by clicking the View/Edit Current User main toolbar button.	"Using the Inbox" on page 3-8.
	New Object	Opens the New window, where you select which type of object you want to create, and assign a number to the object.	"Agile Object Types" on page 4-2.
	Open Selected Objects	Displays the tabbed window for the selected object(s).	n/a
	Cut	Removes selected information and places it on the Clipboard.	n/a
	Copy	Places a copy of the selected information on the Clipboard.	n/a
	Paste	Places a copy of the Clipboard contents into editable fields and tables.	n/a


Table 3–1 (Cont.) Java Client toolbar buttons

Button	Name	Description	For more information, see...
Quick Search Controls	These search controls consist of a selection list, a check box, and a text entry field.	 <p>Quick Search class selection list.</p> <p>Select a base class of objects that will limit the Quick Search. Default selection is All.</p>  <p>Search Attachment Contents</p> <p>Check this box to search attachment file contents.</p>  <p>Search Criteria Entry field</p> <p>Enter the search text in this field.</p>	<p>Base classes and other object types are presented in "Installed Agile Classes, Base Classes, and Subclasses" on page 4-4.</p> <p>"Full Text Search for Content in Attachment Files" on page 8-17.</p>
	Run Search	Searches for objects that match the criteria in the Simple Search text box.	"Quick Searches and Wildcard Characters" on page 8-14.
	Advanced Search	Searches for objects with fields that match (multiple) conditions of the search that you set up. A Where Used search finds assemblies that contain parts that meet your search criteria; a Relationship search finds objects related to the objects that match your search criteria.	"Advanced Searches" on page 8-28.
	Last Search Results	Displays results of the most recent search you performed.	n/a
	Address Book	Opens the Address Book window, where you can view, create, and modify user groups.	"Address Book in Java Client" on page 3-14.
	Process Extensions	Enables you to run/access custom actions that were defined by someone else.	For information about process extensions, see <i>Agile PLM Administrator Guide</i> , "Process Extensions."
	View/Edit Current User	Enables you to modify your Agile user profile.	"Changing Your User Settings" on page 3-10
	Exit	Logs out of Java Client.	n/a

Windows Bar

An optional windows bar appears below the main toolbar.

Figure 3–2 Optional Windows bar



The windows bar contains a button for each open Java Client window. Each button includes the title of the window and an icon reflecting the window's contents. The button representing the current window is highlighted. To move to a different window, click its button in the windows bar.

To close a window using the windows bar:

- ✧ Right-click the button representing the window you want to close, and choose **Close**.
- ✧ You can also use Shift-click and Ctrl-click to select multiple windows, right-click (over one of the selected windows), and choose **Close**.
- ✧ Finally, there is also a **Close All** option when you right-click in any window.

You can hide or show the windows bar, and you can move it to the top or bottom of the Java Client desktop.

To hide the windows bar:

- ✧ Right-click the window bar and choose **Hide Windows Bar**, or choose **View > Windows Bar**.

To show the windows bar:

- ✧ Choose **View > Windows Bar**.

To move the windows bar:

- ✧ Right-click the windows bar and choose **Move**.

Hiding and Showing the Navigation Pane

You may want to view the main window only (hide the navigation pane), and then show the navigation pane again when you need to use it.

To hide or show the navigation pane:

1. On the boundary between the navigation and content panes, click the small left arrow to hide the navigation pane and click the small right arrow to show the navigation pane.

To adjust the width of the navigation pane:

1. Hold the pointer on the boundary between the navigation and content panes. The pointer changes to a double-sided arrow.
2. Drag the arrow until the pane is the desired width: it is limited to a maximum of about one-fourth the total screen width.

Java Client Tables

Java Client displays many types of information in tables. For example, search results, BOMs, and AML information appear in tables.

Sort Order in Tables

You can change the sort order of some Agile tables, for example, the Affected Items table. To sort a table, click the column header of the column by which you want to sort. For example, to sort the **Affected Items** table by item description, click the **Item Description** column header. To change the width of the columns, select the line between column headers and drag.

Selecting Rows in Tables


There are some tables in Java Client on which you can perform certain actions. For example, on the **Affected Items** table, you can remove items. From the Search Results table, you can open an object and modify it or export it; you select the items on which you want to perform the action, and then click the action to perform it.

Tables on object tabs have a "handle" column at the left, as shown in the following figure. You can select rows by using any of the following methods:

- You can select all the rows with the top handle, or you can use Windows commands (Shift-click and Ctrl-click) on the row handles to select the rows on which you want to perform the action.
- You can select a row by clicking in the row or you can use Windows commands (Shift-click and Ctrl-click) in the rows you want.
- You can drag-select (mouse-down or mouse-up as you drag across multiple rows).

When you have selected the rows you want, the available actions are buttons in the menu bar above the table.

Figure 3–3 Selecting rows in Java Client tables



For editable tables, select the rows you want and click the **Edit** button, and the Edit mode popup appears. In this mode, make any changes or updates and click **OK**. The table refreshes to reflect the changes.

In Edit mode, Java Client displays the object ID and object Description, which identifies the data in the row that has the focus.

To open and view objects in a table, use one of these methods:

- To open one object, double-click the object's row in the table.
- To open an object with a specific tab on top:
 - a. Select the object's row in the table.
 - b. Right-click.
 - c. In the displayed menu, choose **Open** and the tab you want.
- To open multiple objects:
 - a. Select multiple rows in the table.
 - b. Press **Enter** on the keyboard or right-click the mouse and choose **Open**.

Using the Inbox

As information passes through the Agile system, users receive news of status changes, requests, and notifications. When you first start Java Client, it is a good idea to view your Inbox.

To view your Inbox in Java Client:

1. Click the arrow to the right of the **Inbox** icon on the main menu bar.
2. Click the Inbox section that you want to view, **Workflow Routings** or **Notifications**.

Notifications

The **Notifications** section of the Inbox lists Agile PLM notifications. Notifications inform you of some action or process that has taken place, such as subscriptions, RFQs, and project invitations. You also receive a notification when a program-related request is sent to your **My Assignments** tab. The **Accept** function does not apply to notifications.

You can view or delete a notification. To view a notification, double-click it. To delete a notification, select it and click **Delete**.

When configuring Agile PLM, the Agile administrator can choose whether notifications are sent to an email address, to the Agile PLM Inbox, or to both.

Workflow Routings

The **Workflow Routings** section of the Inbox lists routable objects that require your review or action. For example, your Inbox may contain changes for which you are an approver. The preconfigured workflow routings are a combination of base classes, and actions that define the kind of review:

- ? *routable objects* That Require My Approval
- ? *routable objects* That I Am An Observer Of
- ? *routable objects* That Were Returned To Me
- ? *routable objects* Transferred to Me
- ? *routable objects* Escalated to Me

Table 3–2 Routable objects listed in the Workflow Routings Inbox

Base class...	...includes routable objects from these classes...
Change	Change Orders, Change Requests, Site Change Orders, Price Change Orders, Deviations, and Stop Ships
Quality Change Request (QCR)	Corrective and Preventive Actions and Audits
Problem Service Request (PSR)	Non-Conformance Requests and Problem Reports
Package	Packages
Project	Activities and Gates
Transfer Order	Content Transfer Orders and Automated Transfer Orders
Declarations	Substance Declarations, Part Declarations, JGPSSI Declarations, Homogeneous Material Declarations, Supplier Declarations of Conformance, IPC 1752-1 Declarations, and IPC 1752-2 Declarations
File Folders	Designs and File folders

To open a workflow routing in the table, double-click its number.

To export objects to a text or PDX file (if you have privileges), select the row and choose **Tools > Export**.

The **Print** button prints the entire Inbox table.

Note: The searches selected in your User Profile **Searches** field also determine which workflow routings appear in your Inbox. For example, if **Change Analyst Searches** is one of your assigned searches, you see Change class object workflow routings in the **Workflow Routings** window. In a similar manner, if **Quality Searches** is one of your assigned searches, you see QCR and PSR workflow routings. For more information, see "[Changing Your User Settings](#)" on page 2-31 and "[User Properties Defined](#)" on page 2-55.

Using Bookmarks and the Recently Visited List

If there are objects that you need to return to frequently, you can use Bookmarks and the Recently Visited list for quick access.

Bookmarking

Bookmarking lets you keep a list of objects that you return to frequently. You can click an object bookmark to quickly display that object.

To bookmark an object in Java Client:

1. Open the object.
2. Choose **Edit > Add Bookmark**, or click the **Add Bookmark** button in the object's toolbar.

The Add Bookmark dialog appears.

3. Enter a name for the bookmark in the **Name** field.
4. Select a folder in which to store it.

You can always save a bookmark in the My Bookmarks folder.

5. To create a new folder, click the **New** button. In the Create New Folder dialog, enter a folder name and click **OK**.
6. Click **OK** in the Add Bookmark dialog to save the bookmark.

The object's number is saved in the **My Bookmarks** list on the **Searches** tab in the navigation pane.

To open a bookmarked object in Java Client:

1. Double-click the object's number in the **My Bookmarks** list on the **Searches** tab in the navigation pane. The object opens.

Organizing Bookmarks

You can arrange your bookmarks in folders using the Organize Bookmarks window (**Edit > Organize Bookmarks**).

To organize bookmarks in Java Client:

1. Choose **Edit > Organize Bookmarks**. The Organize Bookmarks window opens.

The Organize Bookmarks Window

Use the features in the Organize Bookmarks window to create or remove folders and rename or remove bookmarks.

Table 3–3 Organize Bookmark windows buttons

Button	Description
Remove	Removes the selected bookmark or folder.
Rename	Renames the selected bookmark or folder.
New	Adds a new bookmarks folder within the current folder. See "Bookmarking" on page 3-9 for more information.
Save	Saves the changes you made in the Organize Bookmarks window.
Cancel	Discards the changes you made in the Organize Bookmarks window and closes the window.

Removing Bookmarks

To remove a bookmark:

1. In the Organize Bookmarks window, select the bookmark or folder you want to remove.
2. Click the **Remove** button.
3. Click **Yes** to remove the bookmark or folder.
4. Removing a folder will also remove all of its children.
5. When you are finished, click **Save**.

Renaming Bookmarks

To rename a bookmark:

1. In the Organize Bookmarks window, select the bookmark or folder you want to rename.
2. Click the **Rename** button.
3. Edit the name of the bookmark in the **Enter Name** field.
4. Click **OK**.
5. When you are finished, click **Save**.

Recently Visited List

When you view an object during a work session, it is added to the Recently Visited list. The Recently Visited list includes the last 10 objects viewed (or 25, 50, or 100, depending on your administrator's setting of a Preference).

To open a recently visited object in Java Client:

1. Double-click the **Recently Visited** icon in the **Search** tab in the navigation pane.
2. Double-click the object's number in the list. The object opens.

Changing Your User Settings

This section includes information about creating or changing your User Profile, password, personal criteria, and escalations.

Note: The Agile administrator may have set values in Agile PLM that impact what you are able to modify. Most changes made by the administrator are automatically implemented systemwide; however, if the administrator makes changes in your role assignment, or to the roles and privilege masks, these take effect for a user only after the user has logged out and logged back in to Web Client or to Java Client.

Changing Your User Profile

Your user profile contains a variety of information about you, including your contact information, your Windows date and time preferences, and several Java Client on-screen display preferences. The Agile administrator determines whether you can edit your user profile.

To edit or add information to your user profile:

1. Select **Settings > Current User** in Java Client window, or click the **View/Edit Current User** button. The User Profile window opens with all the tabs.
2. Click the tab on which you want to make changes.

To make changes to the **General Info** tab, edit any field that is available. Use the lists, browse buttons, and text boxes to enter the requested information.

You can also make changes to the **Escalations** and **Attachments** tabs. For information about escalations, see ["Working with Escalations in Java Client"](#) on page 3-12. For information about working with the **Attachments** tab, see [Chapter 10, "Working with Attachments."](#)

Note: If you are working primarily in Java Client, check the System Preferences under the **Preferences** tab: Preferred Client should be set to Java Client and Receive Email Notifications should be set to Yes. This will ensure that you will receive email notifications in the same client you are working in. If there is a discrepancy and you are not able to change these properties, see the Agile administrator.

User Preferences

A full list of the user preferences and their descriptions are found in ["User Properties Defined"](#) on page 2-55.

Changing Your Password

These instructions describe how to change your login password, which you can do at any time. The **Change Approval Password** option is enabled only when your Use Login Password for Approval user property is set to No.

Note: If you are an LDAP user, your password cannot be reset in the Agile PLM database, neither by you nor by the Agile administrator. LDAP user passwords must be reset through LDAP.

To change your login password:

1. Choose **Settings > Change Password**. The Change Password dialog box appears.
2. Type your old login password in the **Old Password** field.
3. Type your new login password in the **New Password** and **Retype New Password** fields. (Passwords are case-sensitive.)

To change your approval password (and the Change Password dialog displays the **Change Approval Password** fields), fill in the fields as described above.

4. Click OK.

If you have not followed the rules defined in your Agile system for selecting passwords, you are prompted to correct your password.

Persisted User Interface Settings

For some user interface settings, the most recently used settings persist across sessions for each user.

Examples include:

- ? **Add method** – (Search, Type in Known Number(s), Create)
- ? **Edit Rows After Adding.**

Working with Escalations in Java Client

If your administrator has granted you the necessary privileges, you can set up escalations for yourself. Escalations allow changes to be forwarded automatically to a designated user, if you do not respond within a set amount of time. You can also create escalations for your personal user groups.

Your Agile administrator can add escalations to your user profile, and can edit existing escalations.

To manage escalations for yourself:

1. Choose **Settings > Current User** in Java Client window.
Or, click the **View/Edit Current User** button on the main toolbar.
2. Click the **Escalations** tab.
3. To set up a new escalation, click the **Add** button, and then select an escalation criteria and one or more users to be notified for that criteria. You can select a different person for each criteria, if you want.
4. To edit an escalation, select it on the **Escalations** tab and click the **Edit** button. Add users to, or remove them from, the **Notify Users** list.
5. To delete an escalation, select it and click the **Delete** button.

To manage escalations for a personal user group:

1. Choose **Settings > Personal Groups**.
2. Double-click the group.
3. When the user group window appears, click the **Escalations** tab.
4. To set up a new escalation, click the **Add** button, and then select an escalation criteria and one or more users to be notified for that criteria. You can select a different person for each criteria, if you want.
5. To edit an escalation, select it on the **Escalations** tab and click the **Edit** button. Add users to, or remove them from, the **Notify Users** list.
6. To delete an escalation, select it and click the **Delete** button.

Creating Personal Criteria

A saved 'personal criteria' is a reusable database query very similar to an advanced search, in that the attributes used to create personal criteria are similar to the attributes used to create

advanced searches. (For more information, see ["Advanced Searches"](#) on page 8-28.) They may also be thought of as "filters" or "qualifying descriptions" of objects that you are interested in tracking.

You use personal criteria to define signoff authority transfers. If you have the appropriate privileges, you can temporarily transfer your signoff authority for routable objects to one or more Agile users. For more information about signoff authority transfers, see ["Transferring Signoff Authority"](#) on page 9-35 and ["Defining Personal Criteria for Authority Transfers"](#) on page 9-38.

Any criteria in Agile—personal or reusable—applies to one Agile class (and its children) or a particular subclass; therefore, you must create a separate criteria to apply to the objects of another class or another subclass.

To create a personal criteria:

1. Choose **Settings > Personal Criteria**. The Personal Criteria window appears.
2. Click the **Create** button. The Create Criteria dialog box appears.
3. Fill in the **Name** and **Description** fields, and select the object type that your personal criteria will apply to. This list includes all the Agile classes and user-defined subclasses.

The personal criteria name must be unique. If you specify a personal criteria name that is already used, a duplicate name error message is displayed.
4. Select the attribute you want from the **Attribute** drop-down list. The values that are available change according to the Agile class or subclass you selected in the previous step. Click **OK** in the small dialog box.
5. The **Match If** field specifies the search operator. The values that appear depend on what you selected from the **Attribute** list. Select from the listed operators, which will be a subset of the following:

Contains, Does Not Contain
Equal To, Not Equal To
Greater Than, Greater Than Or Equal To
Less Than, Less Than Or Equal To
Is Null, Is Not Null
Starts With, Does Not Start With
Like, Not Like
6. In the **Value** field, select a value for the field you selected from the **Attribute** list. Click **OK** in the small dialog box.
7. To add additional conditions, select AND or OR in the **And/Or** field.
8. Repeat step 4 through step 7 until your personal criteria is complete.
9. When the criteria is complete, click **OK**.

Note: Changing the criteria in the **Object Type** field resets the entire personal criteria. A personal criteria applies to one class or subclass. You must create a separate global criteria to apply to another class or subclass.

If you want your criteria to be case-sensitive, select the **Case Sensitive** check box. This can simplify how you define personal criteria:

- If you enter text in the Value field, the criteria will look for text that is an exact match, depending on the restraints of the value of the **Match If** field.

- 7 If you define a numeric value, checking **Case Sensitive** allows the Agile system to utilize internal database settings to find objects more quickly.

Using case-sensitive searches improves performance of the system and is recommended when possible.

The **Add()** button places parentheses around the specified condition or conditions, which changes the order in which the search conditions are evaluated. The **Add()** button functions like a formula within parentheses in an algebraic equation, following the standard algebraic order of operations. The grouped criteria within parentheses are resolved before any others. If you do not use parentheses when defining your personal criteria search, the search is processed row by row without any precedence of And/Or values. The first line is combined with the second based on the first line's And/Or value. The result of the first two lines is then combined with the third line based on the second line's And/Or value, and so on.

Editing Personal Criteria

Use this dialog box to edit the conditions in your personal criteria object. Defining or modifying a personal criteria object is similar to defining or modifying an advanced search. For detailed information about searches, see [Chapter 8, "Finding Agile Data with Searches."](#)

You can perform the following modifications to your personal criteria object:

- 7 In the search condition table, use **Add**, **Insert** to add more **Search Condition** rows as needed, or **Delete** to delete rows you do not want.
- 7 Click a cell in the Search Condition table to display the search criteria selection list.

Working from left to right in the search condition row, click the drop-down list buttons to select the target **Attribute** (for example, CoverPage.Originator), the **Match If** search operator (for example, Equal To), and the **Value** (for example, John Smith).

Depending on the selection in the **Attribute** list, the **Value** field may contain a list that is relevant to the selection, a calendar button, or a field where you can enter text or numbers.

- 7 Click the **And/Or** field to select And or Or from the list. Use And if both conditions must be met. Use Or if either or both conditions can be met.
- 7 Use the **()** button to enclose selected rows in parentheses, which determines precedence in the way the search is performed.

If you do not use parentheses when defining your personal criteria search, the search is processed row by row without any precedence of And/Or values. The first line is combined with the second based on the first line's And/Or value. The result of the first two lines is then combined with the third line based on the second line's And/Or value, and so on.

- 7 Select **Case Sensitive** to perform a case-sensitive search where text capitalization matters.


Address Book in Java Client

The Address Book is a multi-list window that enables you to select users and user groups for various functions. The situations in which you use the address book can include:

- 7 When you send email notifications
- 7 When you select people or groups to sign off a workflow
- 7 When you share, or grant, one or more of your roles to another user or user group for specific objects

You can also create user groups in the Address Book.

Figure 3–4 Address Book dialog



Overview of the Address Book

You can access the Address Book by clicking the **Address Book** button on the main toolbar, or by choosing **Tools > Address Book**, or when you are performing actions that involve sending an object or a notification (for example, routing a change). You can select individual users or user groups. The Address Book lists all the individuals and user groups that use Java Client and Web Client.

The Agile administrator can use Discovery privileges to limit the users you see in the Address Book.

Selecting Users and User Groups from the Address Book

You can select recipients individually or in groups. When you select a group, all the members of the group receive the email message. You can sort users by Last Name or First Name by clicking one of the options.

To select users or user groups from the Address Book:

1. To display a list of names on the **Users** tab, click the **Check Names** button, which returns a list of all users.
2. Select a person on the **Users** tab, or select a user group on the **User Groups** tab.

To see more information about a user or user group, select it and click the **View** button.

3. To add names directly to the **Recipients** list, type a known value (for example, a last name) in the **Find Name** field, and then click the **Check Names** button or the keyboard shortcut **Ctrl+K**; the system finds the name and displays it in the **Users** tab list.

If more than one name matches the entered value, the names are displayed in the **Users** tab list.

4. Select one or more names and then click the **Add** button to move your selection into the **Recipients** list.

To select multiple names or user groups, use the Shift-click or Ctrl-click, and then the **Add** button.

To remove a name or multiple names, select using the same techniques and click the **Remove** button.

5. On the **User Groups** tab, if you select a user group and you want only the group name to appear in the **Recipients** list, use the **Add** button. If you do this when selecting approvers, only the group as a whole becomes an approver, and any single member of the group can approve.

If you select a user group, and you want to see **every name** in that group in the **Recipients** list, use the **Add all the users in the selected group** button (this button only appears on the **User Groups** tab). If you do this when selecting approvers for a routable object, each individual becomes an approver.

6. Continue selecting names and using the arrows until the **Recipients** list is correct.
7. Click **Save As** to create a new user group that includes every individual's name on the assembled list. This includes the individuals of any user group you included in the new group.
8. Click **Save** to save the list. Click **Close** to close the address book.

Note: When you add a user group to a group, and save it, when you open the modified user group, all the names of the members of the added user group are there.

User Groups

This section explains how to create both personal and global user groups, and how to modify and delete them. See also "[Creating Supplier Groups](#)" on page 3-18.

Your User Profile **User Group** tab lists the Global Groups of which you are a member. Your membership in the personal groups of individual users is not displayed on the **User Group** tab. See also "[Changing Your User Profile](#)" on page 3-11.

Creating User Groups

You can create personal user groups; with the appropriate privileges, you can create global user groups.

To create a personal user group in Java Client:

1. Choose **Settings > Personal Groups**. The Personal User Groups window appears.
2. Click the **New** button. The Create User Group dialog box opens.
3. Using the **Subclass** drop-down list, select a subclass of the User Groups class. User Groups will be the only subclass available if your administrator has not created another one in the User Groups class.
4. Fill in a name for the group in the **Name** field.
5. Click the button next to the **Users** field to open the address book. Then move users (from the **Users** list) or other user groups (from the **Groups** list) to the **Recipient** list.
6. Click **OK**. The new user group object appears, with applicable fields populated.
7. On the **General Info** tab, select or accept values from the drop-down lists. Enter a description and the maximum number of named users, if appropriate.
8. When you are finished, click **Save**.

9. Continue to select, enter, or accept values for properties under the **Users** and **Escalations** tabs.

To create a user group from the address book:

1. Open the address book by clicking the **Address Book** button on the main toolbar, or by choosing **Tools > Address Book**.
2. Select and move users (from the **Users** list) or other user groups (from the **User Groups** list) to the **Recipients** list.
3. Click **Save As Group**. The Save Group dialog box appears.
4. Under the Group Name heading, enter a name in the **New Group** field. Or you can select a group from the **Existing Group** field; the new version of the existing group will overwrite the original one.
5. Under the Save In heading, select **Personal Groups** or **Global Groups**.
6. The **Subclass** field contains only User Group. It will list other subclasses if the administrator has created new subclasses of the User Groups class.
7. Click **OK**. The new user group is saved in the Global or Personal Groups folder.

Completing or Editing User Groups

To complete additional information about your user group, or to edit an existing personal user group:

1. If the address book is still open, click **Refresh**. Otherwise, choose **Settings > Personal Groups**, or open the address book and then display the **Groups** tab.
2. Navigate to the group you created by expanding the appropriate group folder.
3. Select the group and click **View**. The group opens in a tabbed window.
4. On the **General Info** tab, specify general information about the user group.
5. You can click the **Users** tab to delete users. On the **Users** tab, select the name, and click the **Delete** button.
6. To add or modify escalations for the user group, click the **Escalations** tab. For information about escalations, see ["Working with Escalations in Java Client"](#) on page 3-12.
7. Add or remove any attachment references for the user group on the **Attachments** tab.
For information about attachments, see [Chapter 10, "Working with Attachments."](#)
8. Click **Close** to close the user group window.

Note: With User Group "synch" function enabled, you cannot remove or add users on a user group's **Users** tab that have been synchronized (that is, where users have been added to a user group through LDAP). This feature only applies to iPlanet server. Contact your Agile administrator if you have questions about your ability to delete users from the **Users** tab of a group object.

Deleting Personal User Groups

To delete a personal user group:

1. Choose **Settings > Personal Groups**.
2. Select the group and click the **Delete** button. The selected group is deleted.

To delete a personal user group from the address book:

1. Open the address book and display the **Groups** tab.
2. Select the group you want to delete. Click **View**.
3. Click the **Delete** button. The selected group is deleted.

Creating Supplier Groups

You can create personal supplier groups; you cannot create a global supplier group in Java Client. Suppliers are other companies who are using Agile PLM to work with your company.

Note: The Agile administrator creates global supplier groups, as noted below. For more information about creating global supplier groups see the *Agile PLM Administrator Guide*.

To create a personal supplier group:

1. Choose **Settings > Personal Supplier Groups**. The Personal Supplier Groups window appears.
2. Click the **New** button. The Create New Supplier Group dialog opens.
3. Fill in the **Name** and **Description** fields, and select Yes or No in the **Enabled** field.
4. The **Type** field is grayed, with the value of **Personal** entered. (Supplier groups that are created from the **Admin > User Settings > Supplier Groups** node are "global." You can create global supplier groups only if you have sufficient privileges. For more information about global supplier groups, see the *Agile PLM Administrator Guide*.)
5. For the Suppliers field, click the down-arrow. The Select Objects dialog appears.
 - a. In the Select Objects dialog, you can execute a quick search, define an advanced search, use a saved search, or select from your Bookmarks and Recently Visited list (Shortcuts).
 - b. Move suppliers from the Search Results table to the **Selected Objects** list.
6. Click **OK** and you are returned to the Create New Supplier Group dialog. Click **OK** again and the new supplier group object appears, with the applicable fields populated.

Concepts and Terms in Agile PLM Solutions

This chapter describes Agile objects and other important concepts in Agile PLM.

Introducing Agile Objects

In the Agile PLM system, you work with *objects*. Examples of objects are parts, documents, RFQs, and change orders.

The objects you can view and the actions you can perform are determined by the server components installed on the Agile PLM Application Server and the roles and privileges you are granted to access those components. Privileges can vary from field to field. If you have questions about your roles and privileges, contact your Agile administrator.

How Objects Appear

When you open an object, it appears with multiple tabs. Different types of objects have different tabs. Each tab contains fields that provide information about that object. For example, a part's **Title Block** tab includes **Number**, **Part Category**, and **Description** fields, and a change's **Cover Page** tab includes **Originator**, **Status**, and **Reason For Change** fields.

Some tabs have fields and tables where you enter data; some fields and tables are filled in automatically. Some objects and commonly found tabs are mentioned in the platform-specific discussions later in this chapter. For more information about objects and their tabs, see [Chapter 5, "Working with Business Objects in Web Client"](#) or [Chapter 6, "Working with Business Objects in Java Client."](#)

Below are a typical object page in Web Client and the same object window in Java Client.

Figure 4–1 Agile object page, Web Client

1000-12
1000-12
Part • COMPUTER

Production
Unincorporated

Site: ALL Rev: B C00017 Effective From: 05/25/2012 01:00:00 AM PDT to ...

Navigator Actions

Title Block Changes • BOM • Manufacturers Sites Prices Quality Compliance Suppliers Relationships Where Used Attachments • History

Page Two | Engineering Data | Sourcing Data

Number: 1000-12
Part Type: Part
Lifecycle Phase: Production
Description: COMPUTER
Part Category:
Size:
Product Line(s): Capricorn; Scorpio
Rev Incorp Date:
Rev Release Date: 03/07/2012 04:15:24 PM PST
Effectivity Date: 05/25/2012 01:00:00 AM PDT
Shippable Item: No
Exclude from Rollup: No
Compliance Calculated Date:
Part Family:
Mass:
Overall Compliance:
Item Group(s):
Base Model:

1 of 4

Page Two

Figure 4–2 Agile object window, Java Client

Part 1000-12 [COMPUTER]

Site: ALL Rev: B C00017

Production

Title Block Page Two Changes BOM Manufacturers Sites Prices Quality Relationships Where Used Attachments History

Number: 1000-12
Part Type: Part
Lifecycle Phase: Production
Description: COMPUTER
Part Category:
Size:
Product Line(s): Capricorn; Scorpio
Rev Incorp Date:
Rev Release Date: 03/07/2012 04:15:24 PM PST
Effectivity Date: 05/25/2012 01:00:00 AM PDT
Shippable Item: No
Exclude from Rollup: No
Compliance Calculated Date:
Part Family:
Mass: Gram
Overall Compliance:
Item Group(s):
Base Model:

Agile Object Types

Business objects that you create in Agile PLM are based on a framework of *object types*: **base class**, **class**, and **subclass**. The base class object type is a framework for classes; the class object type is a framework for subclasses. Each class has at least one default subclass; the subclass level is where you create specific objects. Every object created in Agile PLM (by users

or administrators) is an instance of an existing subclass. (Base classes and classes are never objects themselves.)

The Agile PLM provides some three dozen default classes of business objects. The default classes of objects that your company can avail depend on which Agile products and licenses have been purchased. The Agile administrator—that is, any user who has been assigned the Administrator privilege mask or role—can create subclasses according to the needs of the enterprise; the administrator can also rename the existing (preconfigured) base classes, classes, and subclasses. You may find that even a relatively new Agile PLM installation has objects that have been created with names that are not reflected in this manual, for example, in the next three tables that describe the object types.

The classes represent either a kind of action (business process) or kind of entity (business object). Everything that a user can create in Agile PLM—object or process—is treated as an object, and, again, each object is a specific instance of a subclass. The child subclass inherits the attribute settings of the parent class; where applicable, it inherits lifecycle phase and process extension. Tabs—tab names and tab visibility—are inherited from the parent class, but only if these are set at the class level; even preconfigured subclasses with the same parent class can differ slightly from their "siblings" because of tabs that the administrator has hidden or given different names.

This table summarizes Agile's hierarchy of object types. As an Agile user, you do not need to know much about base classes and classes, but it is helpful to have an idea of the hierarchy and naming behind the subclasses you will be working with. "Items" and "changes" are examples of frequently used base class names.

Table 4–1 Hierarchy of Agile object types

Object type	This type inherits...	Rename, Create, or Delete	Installed examples	Notes
Base Class	Does not inherit; is the highest level of object type that user sees (for example, in searches).	Administrator can rename base classes, but cannot create or delete any base class.	Users base class Items base class Changes base class Suppliers base class	n/a
Class	...general properties and process extensions of its parent base class.	Administrator can rename classes, but cannot create or delete any class.	Users class Parts class and Documents class Change Orders class, Change Requests class, Site Change Orders class, and so on Suppliers class	The class object type (sometimes called <i>main class</i>) is the primary level of organization in Agile PLM. Each class represents a specific process or kind of entity (see "Routable and Nonroutable Objects" on page 4-10).

Table 4–1 (Cont.) Hierarchy of Agile object types

Object type	This type inherits...	Rename, Create, or Delete	Installed examples	Notes
Subclass	...all components (tabs), properties, and attributes of its parent class. Subclasses arrange the information & data that describes the specific object in the Agile PLM.	Administrator can create and rename subclasses, and also delete any subclasses that have not been used by Agile users.	User Part, Document ECO, ECR, SCO, and so on Broker, Distributor, Component Mfr., Contract Mfr., and Mfr. Representative	When users create a new object in Agile, they specify one of the Agile-supplied subclasses or a subclass that the administrator has created (or renamed) per your company's requirements. Subclass names cannot be used more than once within an Agile PLM system. A few classes offer multiple preconfigured subclasses.

The object type plays a part in user access and permissions. For example, you can restrict a user's privilege to the Changes base class, the Change Orders class, or the ECO subclass (or another, user-defined subclass of Change Orders class).

Installed Agile Classes, Base Classes, and Subclasses

The following tables list all the possible installed object types in Agile PLM. Classes are grouped by being routable or nonroutable, which is discussed further on. This section also discusses the following topics:

- ✧ ["Discovery and Read Privileges"](#) on page 4-10.
- ✧ ["Routable and Nonroutable Objects"](#) on page 4-10.

The following tables list all the possible installed object types in Agile PLM, grouped by the routable and nonroutable distinction. Your company may have purchased server licenses to a subset of this list. A class appears grayed out in the administrator's list of classes if your company has not purchased its server license.

Your Agile administrator may have created or renamed subclasses. The Agile administrator defines new objects by creating subclass objects under each object class. For example, under the Deviations class, you could see new subclasses such as "MechDev," "SWDev," and "Part Switch" in addition to the default subclass, Deviation.

Installed Routable Object Types

The following tables list all the possible installed routable object types in Agile PLM.

Routable objects – the means to direct or recommend changes to nonroutable objects; these classes have a default workflow for changes to seek approval from other users; objects from these classes can be changed without approval.

Routable object base classes are:

- ✧ Changes
- ✧ Declarations
- ✧ Packages

- ? Product Service Requests
- ? Projects
- ? Quality Change Requests
- ? Transfer Orders

Table 4–2 Changes base class routable objects

Class	Subclass	Description
Change Orders	ECO	Directives to change an item; can advance the revision ("rev") of an item
Change Requests	ECR	Requests for a change to an item
Deviations	Deviation	Directives to temporarily substitute one item for another
Manufacturer Orders	MCO	Changes to AML data, such as information about manufacturers or manufacturer part numbers
Price Change Orders	PCO	Directives to change a published price; can advance the revision of a published price
Site Change Orders	SCO	Changes to BOM and AML information for a specific site
Stop Ships	Stop Ship	Directives to stop shipping/using an item

Table 4–3 Declaration base class routable objects

Class	Subclass	Description
Substance Declarations	Substance Declaration	Seeks compliance information for each substance within the specification
Part Declarations	Part Declaration	Seeks part-level compliance information and other composition header-level information (manufacturing parameters)
JGPSSI Declarations	JGPSSI Declaration	Seeks compliance information (weights) according to the JGP standard.
Homogeneous Material Declarations	Homogeneous Material Declaration	Seeks complete breakdown of parts on the Bill Of Substances and compliance information at the homogeneous material level
Supplier Declarations of Conformance	Supplier Declaration of Conformance	Seeks compliance with specifications from customers and government agencies
IPC 1752-1 Declarations	IPC 1752-1 Declaration	A Joint Industry Guide (JIG) material composition declaration for electronic products
IPC 1752-2 Declarations	IPC 1752-2 Declaration	A homogeneous material composition declaration for electronic products

Table 4–4 Packages base class routable objects

Class	Subclass	Description
packages	Package	Packages of data to share with partners

Table 4–5 Product Service Requests base class routable objects

Class	Subclass	Description
Problem Reports	Problem Report	Quality incidents with items or products
Non-Conformance Reports	NCR	Quality conformance issues with items or products

Table 4–6 Projects base class routable objects

Class	Subclass	Description
Activities	Phase; Program; Project; Task	Components of project planning in Product Portfolio Management; activities are time-based objects to which resources can be assigned
Gates	DG1, DG2, DG3, DG4, DG5, DG6; Gate; Milestone	Project management milestones in Product Portfolio Management; gates identify cross-PLM deliverables of the product development process to enable executive reviews of projects

Table 4–7 Quality Change Requests base class routable objects

Class	Subclass	Description
Corrective and Preventive Actions	CAPA	Requests for corrective actions and preventive actions
Audits	Audit	Proactive reviews of business processes

Table 4–8 Transfer Orders base class routable objects

Class	Subclass	Description
Automated Transfer Orders	ATO	Transfer or publication of a product record that is automatically triggered by a workflow
Content Transfer Orders	CTO	Transfer or publication of a product record that is manually triggered

Installed Nonroutable Object Types

The following tables list all the possible installed nonroutable object types in Agile PLM.

Nonroutable Objects – objects in these classes are not routed to Agile PLM users with workflows; objects from some of these classes, however, are changed by a user submitting a workflow (from routable classes) for approval from other users.

Nonroutable object base classes are:

- ? Customers
- ? Discussions
- ? File Folders
- ? Items
- ? Manufacturers
- ? Manufacturers Parts
- ? Part Groups
- ? Prices
- ? Reports

- ? Requests for Quote
- ? RFQ Responses
- ? Sites
- ? Sourcing Projects
- ? Specifications
- ? Substances
- ? Suppliers
- ? Users
- ? User Groups

Table 4–9 Customers base class nonroutable objects

Class	Subclass	Description
customers	Customer	Clients of the company

Table 4–10 Discussions base class nonroutable objects

Class	Subclass	Description
discussions	Discussion	Informal, threaded dialogue

Table 4–11 File Folders base class nonroutable objects

Class	Subclass	Description
File folders	File Folder Markup	Objects that include files or URLs; this class includes all file folder objects except historical report file folders
Designs	Design	Objects that permit building design structures in the CAD environment

Table 4–12 Items base class nonroutable objects

Class	Subclass	Description
Documents	Document	Specifications, blueprints, manufacturing data, and so forth
Parts	Materials Subclass Model Option Class Part Recipe	Parts manufactured within the company, or provided by manufacturers or suppliers and given internal part numbers Note: The Materials Subclass and Recipe subclasses are NOT available until the Recipe & Material Workspace product is installed.

Table 4–13 Manufacturers base class nonroutable objects

Class	Subclass	Description
manufacturers	Manufacturer	Qualified manufacturers

Table 4–14 Manufacturer Parts base class nonroutable objects

Class	Subclass	Description
Manufacturer parts	Manufacturer Part	Parts provided by manufacturers

Table 4–15 Part Groups base class nonroutable objects

Class	Subclass	Description
Part groups	Commodity Part Family Item Group	Containers of other parts (items or manufacturer parts) that share such properties as mass or composition information. Note: This object was named "Commodities" in previous releases of Agile PLM.

Table 4–16 Prices base class nonroutable objects

Class	Subclass	Description
Quote Histories	Quote History	Organizes bid prices from RFQ responses; cannot be revised by a PCO (see grouping of Changes in preceding table)
Published Prices	Published Price; Contract	Organizes prices of the company's products; can be revised by a PCO (see grouping of Changes in preceding table)

Table 4–17 Reports base class nonroutable objects

Class	Subclass	Description
Standard Reports	Administrator Report; Standard Report	The ready-to-use reports for administrators (Administrator Reports) and users (Standard Reports include Products, Sourcing, Quality, Process, Personal, and Global reports)
Custom Reports	Custom Report	Reports created and used within company
External Reports	External Report	Reports created outside Agile PLM

Table 4–18 Request For Quote base class nonroutable objects

Class	Subclass	Description
Requests for quote	RFQ	Requests for quote, which are assembled from sourcing projects and sent to suppliers for formal bids

Table 4–19 RFQ Responses base class nonroutable objects

Class	Subclass	Description
RFQ responses	RFQ Response	Bids, that is, responses from suppliers to your company's RFQs

Table 4–20 Sites base class nonroutable objects

Class	Subclass	Description
Sites	Site	Manufacturing locations within the company, or closely partnered with the company

Table 4–21 Sourcing Projects base class nonroutable objects

Class	Subclass	Description
Sourcing projects	Sourcing Project	Work preparatory to creating RFQs and capability for analysis across multiple RFQs

Table 4–22 Specifications base class nonroutable objects

Class	Subclass	Description
Specifications	Specification	Lists of banned substances (or substances of concern) and their threshold values

Table 4–23 Substances base class nonroutable objects

Class	Subclass	Description
Substances	Substance	A single chemical element used in composition of items, manufacturer parts, and part families
Materials	Material	A compound chemical, a substance consisting of multiple substances
Subparts	Subpart	A subunit of a component, used to get to the homogeneous material level to collect compliance information
Substance Groups	Substance Group	A group of multiple substances, with a base substance that is what legislation is interested in, for example, "Lead and Lead Compounds"

Table 4–24 Suppliers base class nonroutable objects

Class	Subclass	Description
Suppliers	Broker Component Mfr Contract Mfr Distributor Mfr. Representative	Qualified suppliers of manufacturer parts; used by PCM (which uses the ready-to-use subclasses) and PG&C solutions

Table 4–25 Users base class nonroutable objects

Class	Subclass	Description
Users	User	Individuals using the Agile PLM system

Table 4–26 User Groups base class nonroutable objects

Class	Subclass	Description
User groups	User Group	Groups of people using the Agile PLM system, that is, departments, teams, site-specific groups.
Functional Teams	Functional Team	Groups of people that comprise a functional team; each member is assigned a workplace job function.

Discovery and Read Privileges

Together, the Discovery privilege, the Read privilege, and the Enforce Field Level Read privilege determine which Agile objects you can find and open, and which object fields you can view.

The Discovery privilege lets you discover the existence of an object in the Agile database. If you do not have Discovery privilege for an object, you cannot view the object, and you cannot find, or discover, the object in the Agile database. This includes viewing users in the address book; there may be some users that you cannot view due to lack of privileges.

Once you have the privilege to discover an object, your Read and Enforce Field Level Read privileges for that object determine whether you can open and view it, and which individual fields you can view. You may be able to read an object, but you may not have Read privilege for every field of that object. So it is possible for you to open an object and, at the same time, be unable to view specific fields of that object. For more information about the Discovery and Read privileges, see the *Agile PLM Administrator Guide*.

Routable and Nonroutable Objects

Each class represents a specific process or kind of entity:

- 7 **Routable objects** are created from classes that represent *processes*, such as a change in the change control process, or a transfer order, or a product service request. These objects can be routed to Agile users for approval or other input through workflows (see "[Workflows](#)" on page 4-14.).
- 7 **Nonroutable objects** are created from classes that represent *entities* or things, such as parts, sites, RFQs, users, prices, or reports. These objects can be "flagged" for progress through lifecycle phases. Note, however, that nonroutable objects—especially parts and documents—can be changed by the process of information-gathering by using workflows, which are created through such routable objects as change orders or change requests.

Note: File folder objects have lifecycle phases and, as they represent the entity of "attachment wrapper," are not considered routable objects; however, the File Folders class has a default, non-editable workflow with a single Review status (and no other status), which provides a **Routing Slip** tab where approvers can sign off and comment.

Routing Managers

Any object that can be routed for approval is a routable object. The user who oversees the routing and approval process is the routing manager. The various routing managers (see the table below) are simply roles assigned to users by the administrator. Once a user has been assigned a role of, say, change analyst, their name appears on the Change Analyst List and can be selected manually by a Java Client or Web Client user with the appropriate Modify privilege. If the workflow specifies a Default Change Analyst, then the Change Analyst field is automatically populated by the workflow.

Routing managers evaluate and assign routable objects, and they receive email notifications pertaining to the objects to which they are assigned.

The following table lists routable objects and the corresponding default routing manager.

Table 4–27 Routable objects and corresponding routing managers

Routable Object (with base class)	Default Routing Manager
Changes base class: Change orders (ECOs), Change Requests (ECRs), Stop Ships, Deviations, Site Change Orders (SCOs)	Change analyst
Changes base class: Manufacturer Orders (MCOs)	Component Engineer
Changes base class: Price Change Orders (PCOs)	Price administrator
Declarations base class: Part Declarations, Substance Declarations, Homogeneous Material Declarations, JGPSSI Declarations, Supplier Declarations of Conformance	Compliance manager
Packages base class: Packages	Program manager
Product Service Requests base class (PSRs): Problem Reports and Non-Conformance Reports (NCRs)	Quality analyst
Programs base class: Activities and Gates	PE program manager
Quality Change Request base class (QCRs): Corrective and Preventive Actions (CAPAs) and Audits	Quality administrator
Transfer Orders base class: Content Transfer Orders (CTOs) and Automated Transfer Orders (ATOs)	Content manager

Other Important Concepts in Agile

Familiarity with the topics discussed in this section will help you use the full features of Agile.

Login Security and Passwords

Depending on how your Agile administrator has configured your password settings, you may have two separate passwords for login and approval, or you may have one password for both login and approval.

Your username and approval passwords are the same for both Java Client and Web Client.

For system security, your administrator may configure the Agile PLM system so that you are not allowed to log in after a specified number of password failures (entering the wrong password). The lockout applies to your login password only, not your approval password.

Depending on Agile PLM system settings, one of the following occurs:

- The login lockout lasts until a specified time has passed (for example, one minute).
After the specified time has passed, a small Login dialog box appears, telling you that there have been too many login failures. Click **OK** and continue.
- The login lockout lasts until your Agile administrator unlocks your account by changing your password. If you are locked out, Web Client does not accept further input for the time period specified by the Agile administrator (for example, one minute), before you can attempt to log in again.

If you are having difficulty logging in to Agile PLM, or had a failed logon and the lockout is lasting too long, see your Agile administrator.

Object Subscriptions, Relationships, and Sharing

"Sharing," "subscriptions," and "relationships" all describe operations with objects in Agile PLM that provide better collaboration and enhanced automation as they proceed through the

manufacturing process. These features are detailed in [Chapter 5, "Working with Business Objects in Web Client"](#) or [Chapter 6, "Working with Business Objects in Java Client."](#)

- ⌘ **Object sharing** – Lets you grant one or more of your roles to another Agile user for specific objects and specific classes listed in object tabs.
- ⌘ **Object subscription** – You can subscribe to objects so that you are notified when certain events happen to that object. For example, you can subscribe to a change to be notified whenever the change is promoted to a new status.
- ⌘ **Object-to-object relationships** – Lets you set up communication between Agile objects, and the actions resulting from (triggered by) that communication. For example, the implementation of an ECO could trigger the close of a related ECR.

File Folder Objects and Attachment Files

Attachments to objects may contain information about the object or a manufacturing process. You can attach files and URLs by referencing them in a *file folder* object. There are two primary types of File Folders, regular File folders and Designs. The file folder holds pertinent content, or attachments. Design objects contain objects used for CAD integration.

In previous versions of Agile, files and URLs that are attached—associated—to parts or other business objects are called *attachments*. In this version of Agile, attachment files and URLs may be referred to generally as attachments, but it is important to remember that what is really attached to Agile business objects are file folders.

You can still view, copy, delete, and print attachment files. With appropriate roles and privileges, you can markup or redline an attachment file in the Viewer. See ["Viewing and Redlining Attachment Files in the AutoVue for Agile Viewer"](#) on page 10-35.

The **Attachments** tab of an Agile object lists attached file folders. The **Files** tab of a file folder object lists the files and URLs that are referenced, and it is where you add and remove files and URLs in the file folder. A file folder's **Where Used** tab is populated automatically with any objects that have a link to the file folder. A single file folder object can be referenced from the **Attachments** tab of multiple objects.

For more information, see Working with Attachments. For details about searching attachment content, see ["Full Text Search for Content in Attachment Files"](#) on page 8-17. Also see the *Viewer Supplement*.

Searching for Data

When you want to find data in the Agile PLM system, you perform a search. Agile PLM provides several types of searches:

- ⌘ *Simple searches* find objects of all types that match the text you specify.
- ⌘ *Quick searches* find objects that match two basic conditions: the text and the object type that you specify. They also have the ability to search attachment file content.
- ⌘ *Advanced object searches* find all the objects with fields that match the conditions of the search. For example, you could search for parts where the **Description** field contains "Computer."
- ⌘ *Where-used searches* (a specific type of advanced search) find the assemblies in which the BOM contains the items that match the search criteria.
- ⌘ *Relationship searches* (a specific type of advanced search) find objects related to the objects that meet the search criteria. For example, you can search for the problem reports that appear on the **Relationships** tab of changes that meet search criteria.

- Attachment content searches find attachment objects that contain attachment files including the text specified in the search conditions.

For instructions about searching, see [Chapter 8, "Finding Agile Data with Searches."](#)

Agile Packages

Agile packages are sets of product information that can be created, viewed, and routed through Agile PLM to users up and down the supply chain.

For example, suppose an Electronic Manufacturer Service (EMS) provider must receive a certain set of documents to respond to a request for quotation from an Original Equipment Manufacturer (OEM). The EMS defines the required documents in Java Client or Web Client. OEM employees then log in to Web Client, where they create Agile packages and are prompted to attach the required files. The Agile packages are submitted to the program manager at the EMS.

The EMS is immediately notified when the OEM submits the packages. The EMS can review the packages and their contents. The packages pass through workflow stages in Agile PLM, where they are routed for review, accepted, or returned to the submitting partner if additional work is needed.

OEM personnel can monitor all this activity anytime they log in to Web Client for that EMS provider. The OEM can also use Agile Content Service (ACS) to automatically create and populate the Agile package in the Agile PLM system of the EMS.

Exporting Data

Users at Agile sites can export product definition data to a file. Export files can be comma-delimited text format (CSV) or Product Definition eXchange (PDX) format.

PDX is the Product Definition eXchange standard designed for the e-supply chain. The standard is based on XML because it provides a simple yet powerful and flexible way to encode structured data into a format that is both human- and computer-readable. The PDX standard provides a way to describe product content (BOMs, AMLs, drawings, and so on), ECRs, ECOs, and deviations in an XML format.

In a typical case, an OEM with Agile has a design to communicate to an EMS, also called contract electronics manufacturer (CEM), who builds the component or assembly. The product data might include items, BOMs, approved manufacturer lists, drawings, and so on. When a design changes, the manufacturer needs to communicate the changes to the EMS. The Export wizard can create a text file or PDX package of this information from the Agile database to be sent to the EMS.

At the receiving end, the EMS then views that data (in Agile eXpress, if the file is a PDX package) and prints it or extracts it as needed for use in spreadsheets or other applications. The EMS can use Agile Import to import the PDX package or text file into the Agile database.

Agile Import and Export are documented in the *Agile PLM Import/Export Guide*.

For more information about the PDX standard, visit the PDX organization website at <http://webstds.ipc.org/2571/2571.htm>.

Product Collaboration Process

The Agile Product Collaboration (PC) solution helps supply chain partners define, store, change, and manage product content information. The PC solution is central to Agile PLM, and most Agile users will need to be familiar with BOMs, AMLs, and the change control process.

Bills of Material

Bills of material (BOMs) show all the items (parts, documents) that comprise the current part or subassembly. (Documents may or may not have bills of material, depending on your Agile PLM system settings.) Items on a BOM can be a single item or an assembly of several items. The BOM for each part appears on its **BOM** tab.

Approved Manufacturer Lists

An approved manufacturers list (AML) is the list of manufacturers that have been approved to supply a particular item. The list identifies the manufacturer part for that item. The AML for a part, plus the manufacturer's part numbers and other information, appears on its **Manufacturers** tab.

Change Control Process

The change control process includes all procedures that manage changes or requests for change to any part, document, step, or instruction in your company's manufacturing process.

Objects and Change Control

Items are subject to change control, that is, modification by an approved and released change order. To modify an item's **BOM** or **Manufacturers** tab, you must create a change against the item.

The **Title Block** and **Sites** tabs of items are not under change control; this means, with the appropriate privileges, you can edit them at any time. Site objects and manufacturers are also not under change control.

Affected Items

The **Affected Items** tab of a change lists the items that are affected by the change. Users with sufficient privileges can use the **Affected Items** tab to:

- ? List the items affected by the change, and assign a pending revision (or *rev*) to the affected items of the ECO
- ? Open the affected items
- ? Work with BOM, manufacturer, and attachment redlines

Redlining BOMs, Manufacturers, and Attachment Files

When you redline a BOM, you change it in some ways. For example, you can add or delete parts and assemblies from the BOM or change quantities of existing parts. Likewise, when you redline an AML, you can change associated manufacturer parts information. When you redline an attachment file, you mark it up in the Viewer by adding new drawing lines, adding annotations, or adding measurements.

Redlining activities begin on the **Affected Items** tab of an ECO (for BOMs, AMLs, or attachment files), SCO (for BOMs or AMLs), or MCO (for AMLs).

Workflows

A workflow is a sequence of statuses that a routable object (such as a change) follows. Workflows automate many processes; for example, when a change is released, Agile users on the notification list receive automatic email with this information.

Agile provides default workflows for routable objects, and your Agile administrator can create workflows. For each workflow made available to Agile users, the administrator specifies workflow name, ID number, names of the statuses, and the properties that define each status.

Agile workflows are covered in detail in [Chapter 9, "Routing Objects with Workflows."](#)

Change Control Process

The change control process includes all procedures that manage changes or requests for change to any part, document, step, or instruction in your company's manufacturing process.

A Typical Change Control Process


Agile supports change control processes, including default and custom Agile workflows.

The following is an example of a typical change control process for a change using Agile workflows:

1. An Agile user creates a change (for example, an ECO or MCO), and then selects a workflow to route this change.
2. The user selects approvers (members of the change control board) and observers for the change and then submits it to the routing manager.
3. The routing manager switches the change to the next status, which routes the change to the specified approvers and observers.
4. The members of the change control board, or CCB, enter their approval or rejection on the **Workflow** tab of the change.
5. If all the approvers approve the change, it is automatically promoted to the next status (depending on the AutoPromote setting). If any approvers reject the change, the routing manager is notified. The routing manager may elect to do any of the following:
 - ? Cancel the change by switching the status to Canceled.
 - ? Return the change to the originator by switching the status to Pending.
 - ? Release the change despite the rejection.

The following figure illustrates this change control process. Agile packages and content transfer orders can follow a similar process.

Figure 4–3 Change control process diagram



Product Portfolio Management Process

Agile Product Portfolio Management (PPM) is a Web Client application for program management that lets you:

- ✎ Plan a program in terms of its schedules, resources, and deliverables
- ✎ Execute and manage multiple related programs and projects in a collaborative environment
- ✎ Associate product deliverables (such as Items, RFQs, ECOs, and CAPAs) to tasks on a project plan
- ✎ Establish project plan templates for rolling out best-practice processes
- ✎ Allocate work to users or resource pools and monitor capacity and future demand
- ✎ Establish executive dashboards for cross-program rollups and quick access to high risk activities

The program management process involves:

- ✎ Scheduling
- ✎ Task management
- ✎ Issue management
- ✎ Document management

- ? Phase/Gate management
- ? Resource management
- ? Deliverable management.

Common Terms in PPM

Listed below are some common terms used in PPM:

- ? Program: A set of related activities and gates that is created to monitor and manage progress on a specific project.
- ? Project: A set of phases, tasks, and gates that is created to monitor and manage progress of a specific planned activity.
- ? Phase: A segment of a program, also referred to as a stage. Phases are often used to define the activities required to create a set of deliverables.
- ? Gates: Indicates the completion of a set of related activities, such as a phase. A gate's status is closed until all its deliverables are complete, at which time it opens.
- ? Task: A segment of work that one or more resources can complete within a time period. Tasks may be embedded in programs, phases or other tasks.
- ? Deliverable: An Agile PLM object whose state change can trigger a state change in the program element that contains it. The statuses of deliverables control the status of gates.
- ? Gantt Chart: A program management tool that helps you to plan, administer, and track programs from start to finish.
- ? Content: Contains all program-related content including deliverables.
- ? Activity: A program, task or phase.

For more information on PPM, see *Agile Product Portfolio Management User Guide*.

Product Quality Tracking Process

The Agile Product Quality Management (PQM) solution consists of a comprehensive set of tools that allows companies to track and manage quality data across the enterprise. This includes customer complaints, field failures, product or manufacturing defects, and requests for enhancements or corrective and preventive actions. PQM unifies the company's organizations in customer service, field sales, manufacturing, and engineering, and links the organization to its customers and partners.

PQM features offer these benefits:

- ? Integration with external enterprise Customer Relations Management (CRM) systems – The ability to import customer complaints, manufacturing issues, and additional quality-related information from other enterprise applications streamlines the quality tracking process and offers a central repository for tracking product quality data.
- ? Improved product quality – Tracking defects, finding trends, and quickly determining the root causes of defects are the keys to effective defect reduction and improved product quality.
- ? Improved customer satisfaction – The ability to track problem reports and customer complaints lets you respond quickly to customers and resolve problems quickly.
- ? Lower production, repair costs, and warranty costs – Tracking and correcting defects can help reduce scrap, cycle time, and costs associated with rework and repair.
- ? New features enable compliance with ISO-9000, FDA, and other regulations.

The Agile PQM solution consists of Product Service Requests (PSRs) and Quality Change Request (QCRs). The two types of PSRs are Problem Reports and Non-Conformance Reports (NCRs). The two types of QCRs are Audits and Corrective and Preventive Actions (CAPAs). You can associate QCRs with problem reports.

Common Terms in PQM

Listed below are some common terms used in PQM:

- ? Product Service Request (PSR): You use a PSR to report a defect or a quality incident about a product. The PSR can be either a Problem Report or a Non-conformance Report.
 - Problem Report (PR): Contains a basic description of a problem, issue, or incident that occurred, from the customer's perspective.
 - Non-Conformance Report (NCR): Reports a basic material deviation from specifications or requirements in one or more products.
- ? Quality Change Request (QCR): Creates and manages quality records that aggregate problems related to products, documents, suppliers, and customers.
 - Audit: The pro-active process of verifying compliance with quality requirements.
 - Corrective and Preventive Action (CAPA): A formal process of addressing any quality problem and analyzing the root cause to implement corrective and preventive action.
- ? Related PSR: A list of all similar product service requests that are combined to form a single PSR.
- ? Affected Items: A list of items that are affected by the change in either a PSR or a QCR.
- ? Relationship tab: Creates a relationship with other Agile objects; the relationship is bi-directional.
- ? Relationship Rule: Specifying a rule for a relationship defines how the related Agile objects affect each other. Rules are optional; you can create a relationship between two objects without specifying a rule.
- ? Preview Pane: When you add a relationship to an object, the details of the Relationship are displayed in the Preview pane. It also displays the attributes and actions that can be performed on the relationship object.

For more information on PQM, see *Agile Product Quality Management User Guide*.

Product Cost Management Process

The Agile Product Cost Management (PCM) solution consists of the Product Sourcing and Price Management components. They allow you to integrate and leverage price and cost information within your company's business processes in the Agile Web Client.

A sourcing project holds the data you gather, such as items and assemblies, bills of material, and approved manufacturers lists. Using the project, multiple users can work as a team to complete sourcing and pricing activities, since the project lets multiple users view and modify the same components. Sourcing projects allow you to execute sourcing activities, including RFQs and analysis, on your Item Master content.

The Price Management solution provides you with a single controlled process for managing price and terms information that can be leveraged across organizations, business processes, and key analysis.

Common Terms in PCM

Listed below are some common terms used in PCM.

- 7 Approved Manufacturer's List (AML): Lists all the preferred or alternate manufacturer parts that correspond to an internal part.
- 7 Sourcing Projects: An entry point for sourcing and pricing. Tracks data required for sourcing and pricing, to perform analysis for effective pricing.
- 7 Item Master: The entire collection of Items - Parts, Documents, and other user-defined subclasses of the Items class maintained under change control in the Agile PCM system.
- 7 Project Items: Items added to a project. These can be items that exist in the Item Master, created within the project or imported into the project.
- 7 Project Data: Information about the supplier, item, manufacturer, manufacturer part number, revision, price information, RFQ response information of a project.
- 7 Subscriptions: Subscribing to an object sets you up to receive notification of events that happen to the object.
- 7 Target Price: The price you quote for an item with the standard cost in mind. Standard cost is the market cost per unit of the item or the manufacturer part.
- 7 Commodities: Lets you categorize parts for sourcing and analysis process. By associating each item with a commodity, you can distribute RFQs to suppliers based on the commodities they offer.
- 7 Request for Quotes (RFQs): Using RFQs, you request quotes for items involved in the project and suppliers respond to the Quote. RFQs can be sent to one or more suppliers.

For more information on PCM, see *Agile Product Cost Management User Guide*.

Product Governance and Compliance Process

Agile Product Governance and Compliance (PG&C) is designed to help OEM manufacturers audit the amount of regulated substances used in their products, and show that they responsibly dispose of, recycle, or reuse electronics containing those substances.

PG&C helps companies address the growing number of environmental specifications and policies that affect product definition, the import and export of products, and the disposal of restricted substances. It provides a solution that manages the entire product compliance process:

1. Collection of data from vendors through a Request For Information (RFI)
2. Determination of compliance by analyzing data and comparing it to established standards
3. Documentation of compliance by running reports

The RFI process is initiated by Compliance Manager, who creates a new declaration, or modifies an existing declaration, to specify the components for a parts assembly. An RFI consists of a Material Declaration, which lists the parts in a product assembly and shows the substances and materials that comprise those parts. It is linked to specifications which may restrict how much of a particular substance that product assembly may contain.

Common Terms in PG&C

Listed below are some terms used in PG&C.

- 7 Specification: Tracks the different legislations with which an assembly or part must comply. Environmental specifications are substance-based, and contain a list of banned substances or substances of concern and their threshold values. Agile uses specifications to

validate declarations and assess the compliance of parts by evaluating whether a given restricted substance in the composition of a part surpasses its specified threshold value.

- 7 Declaration: A structured way of bringing information concerning the environmental compliance of parts into Agile PLM. Each declaration is for a single supplier.
- 7 Composition: A composition represents the total collection of information contained in a completed declaration and is not a configurable "business object" in Agile PLM.
- 7 Substance: A substance is any chemical element or compound that is tracked within Agile PLM.
- 7 Bill of Substance (BOS): A way to manage compliance information-gathering regarding the parts and materials used in the manufacturing process.
- 7 Alias: Informs Agile PG&C of "substitute names" of substances. For example: When a supplier provides information about substances for a part, there is no guarantee that a substance with the same name exists in the buyer's system. Agile PG&C adds the invalid substance as an alias to the substance. Whenever the same invalid substance is imported, it automatically maps to the objects.
- 7 Supplier: A supplier is a company that provides compliance information about parts that are used in your company's manufacturing process.

For further information about PG&C, see *Agile Product Governance & Compliance User Guide*.

Engineering Collaboration Process

Engineering Collaboration (EC) is an application that provides data and process integration between CAD applications and Agile PLM. It allows CAD designers and engineers to capture and control the data representing a primary source of the product record.

See also [Chapter 13, "Working with Design File Change Orders \(DFCOs\)."](#)

Working with Business Objects in Web Client

This chapter describes working with business objects in Agile Web Client, including the actions of creating, modifying, printing, emailing, and deleting business objects.

Creating Objects

To create an object, you must be assigned the Create privilege for the kind of object that you want to create. See your Agile administrator.

In Web Client, you can create a business object in these ways:

- ? use the **Create New** menu to choose a base class and a class from the expanded lists.
- ? if you have an object open, use the **Actions > Save As** command.

You can also create some objects as you add them to an Agile table. For example, you can create an item to add it to the **BOM** tab of a parent item or to the **Affected Items** tab of a change.

There are some options to create objects from "within" another object. For example, from within an item, the **Actions** menu includes **Create Change**, **Create PSR**, **Create QCR**, and **Create Declaration**. From within a manufacturer, you can choose **Create Manufacturer Part**.

Once you create an object, that item exists until you delete it. If you create a new object and then you decide that you do not want to keep it, be sure to delete the object; otherwise, the new object is still in the database and the object's identifier (such as the item number) cannot be reused. See [Appendix A, "Deleting Agile Objects."](#)

Note: Although all characters are supported within Agile PLM, and should not create issues within Agile's clients, it is recommended that you avoid using the following characters when creating objects, due to issues that could potentially arise in integrations or custom applications written on the SDK.

, comma . period (dot) : colon ; semicolon = equal sign

Actions Menu

An important feature for working with objects in Web Client is the **Actions** menu (Web Client). Generally, objects in Web Client have an **Actions** button that opens a drop-down list of available actions.

Table 5–1 *Actions menu commands*

Command	Description
Save As	Creates a new object based on the current object.

Table 5–1 (Cont.) Actions menu commands

Command	Description
Delete	Deletes the object (a "soft delete"). For more information about deleting objects, see Chapter A, "Deleting Agile Objects."
Print	Choose either All Tabs or the tabs you want. The list of tabs changes with the current object's class.
Copy URL to Clipboard	In Web Client, copies the URL of the object to the clipboard, so it can be pasted elsewhere. For Internet Explorer: the URL is copied when you click the action; the prompt indicates it is copied. For Firefox: when you click the action, a popup displays the URL, manual Ctrl+C copies the URL.
Incorporate and Unincorporate	Available for items: incorporation locks the checkout and check-in capabilities of file folders on the Attachments tab of the item. This important capability is available only on the More menu. For more information about incorporating, see the <i>Product Collaboration User Guide</i> .
Bookmark or Add Bookmark	Saves a pointer to the object on your My Bookmarks folder (or "Favorites") list.
Send	Opens the address book and lets you select one or more users to send the object to, including a comment. A notification is then sent to the designated users with a link to the object.
Share or Sharing	Opens a page linked to the current object that lets you share the object or delete an existing share. For more information, see "Sharing Objects with Other Users" on page 5-28.
Subscribe or Subscriptions	Allows user to subscribe to receive a notification when certain attributes change. Offers a list of subscriptions for the current object: Lifecycle Phase Change or Status Change, Add File, Delete File, Checkin File, Checkout File, and Cancel Checkout File. See "Subscribing to Objects" on page 5-29. Note: Subscribe capabilities are not available for Report objects or for User Group objects.
Export	Opens the Export wizard in Web Client (even if you have activated it from Java Client).
Process Extensions	Offers a list of currently available process extensions, which have been created by your administrator.
Audit Status	Audits the remaining statuses in the object's workflow to test whether the workflow can advance through those statuses.
Audit Release	Audits the remaining statuses in the object's workflow to test whether the workflow can be released per the existing conditions in the statuses.
View Workflows	Shows eligible workflows for this (routable) object, in visual form. Offers drop-down list to select another workflow to view.
Create New	Creates a new change order with the open item (part or document) already added to the Affected Items tab. Select the change type from the list of available change subclasses.
Create Change Order	Creates a new Design File Change Order (DFCO) with the open file folder (Design or File Folder) already added to the Affected Files tab.
Create Product Service Report, Create Quality Change Request	Creates a new PSR or QCR with the open item already added to the Affected Items tab.

Table 5–1 (Cont.) Actions menu commands

Command	Description
Create Declaration	Create a new Declaration with the open item already added to the Affected Items tab.

Creating Objects in Web Client Using the Create New Command

The process for creating new business objects in Web Client involves two main steps: creating an empty object and then filling in the object tabs with information specific to the object.

To create and complete an object in Web Client:

1. Click the **Create New** button on the main toolbar.
Or, use the keyboard shortcut Ctrl + Shift + C to display the menu.
2. From the drop-down menu that opens, choose the base class for the business object you want to create. Any base class with two classes expands to offer choices in all possible child classes (thus, **Transfer Order** will offer Content Transfer Order but not Automated Transfer Order). The Create New dialog opens.
3. Follow the instructions on-screen to complete the creation process. The actions required may include:
 - a. Select the type (subclass) you want from the drop-down list. Depending on which type is selected, additional fields appear in the dialog.
 - b. The object number may be automatically selected for you. The autonumber format and sequence are determined by the Agile administrator. The administrator also determines whether using autonumbers is required or optional.
 - c. Complete any required fields. Required fields are indicated by an * asterisk. The Create New actions cannot be completed with any required fields empty.
 - d. Additional fields that are not required (not marked by an * asterisk) may also appear in the dialog. You can complete the additional fields now. If non-required fields are empty, the Create New action can be completed.
4. Click **Save**.
5. The newly created object appears in the content pane, with the first tab (**Cover Page**, **Title Block**, or **General Information** tab) showing. The tab is in edit mode and can be updated immediately.
6. Fill in information on the tab and click **Save**.
Fill in information on the item tabs, as necessary. Some tabs are completed automatically, such as the **Changes**, **Where Used**, and **History** tabs. You do not enter information on these tabs.

Creating an Object Using Save As

Using the Save As feature is a quick way to create an object that is similar to an existing object.

Note: In general, you should not use Save As to create an object in a different class or subclass from the original object. The different classes or subclasses may not have the same tabs or defined fields, and you may lose access to some data in the newly created object.

For example, parts generally have a **BOM** tab. By default, documents do not. When you save a part as a document, you cannot view the part's BOM in the resulting document unless your Agile administrator has configured your system to permit documents to have BOMs.

To create an object using Save As in Web Client:

1. Select and open an existing business object.
2. From the **Actions** menu, choose **Save As**. A dialog appears with the heading: "Save [object] [ID number] As..." with defaults naming the object and number.
3. The two fields in the dialog are Subclass and (Auto)Number. You can choose an available subclass from the drop-down list, and fill in an ID number manually if you want.
4. Depending on the selected object type, the Save As dialog may display additional required fields. Complete any required fields.
5. Click **Save**. The new object is created and opens automatically.
6. Make any appropriate modifications to the tabs.

If the Agile administrator has set the appropriate preferences, fields in the optional **Page Two** and **Page Three** sections are copied to the new object. For information about the behavior of **Page Two** and **Page Three** fields in your Agile system, see your Agile administrator.

Save As copies data from a field in the existing object to the same field in the new object. If a field or list value in the existing object is not available in the new object, then that field or list value is not copied to the new object.

Note: Because **Page Three** data applies to a specific subclass only, if you use Save As to create a new business object in a different subclass, the **Page Three** data is *not* copied to the new object.

Site Change Order Save As Limitations

You cannot initiate Save As from a non-Site Change Order (SCO) change object to create an SCO object, nor can you initiate Save As from an SCO object to create a non-SCO change object. Because Site Change Orders (SCOs) affect only site-specific information, and other types of changes are not limited to site-specific information (for example, ECOs and MCOs), SCOs can be Save-As-created only from another SCO. The Site Change Order's site-specific only usage makes it incompatible with other change types when using the Save As feature.

Design File Change Order (DFCO) Save As Limitations

A change order subclass can have the **Affected Items** tab enabled (example: ECO) or it can have the **Affected Files** tab enabled (example: DFCO), but it cannot have both tabs enabled in the same subclass. Therefore, when you Save As a change order subclass that has Affected Items, you cannot choose a different subclass that has Affected Files. Likewise, when you Save As a change order subclass that has Affected Files, you cannot choose a different subclass that has Affected Items.

Adding Objects to Tables

Agile PLM Web Client provides several methods of adding objects to a table:

- 7 Add button command on the table which lets you choose objects to add by:
 - Typing the object number, which also provides suggestions of objects that match what you have typed so far. ["Adding Objects to Tables by Type-ahead Search"](#) on page 5-5.
 - Performing a quick search to locate and select the objects you want. See ["Adding Objects to Tables by Quick Search"](#) on page 5-5.
 - Creating a new object. See ["Adding Objects to Tables by Create New"](#) on page 5-6.
- 7 Copy and Paste

Select objects in a similar table or the search results table, copy them (Ctrl-C) and then paste them (Ctrl-V) into the table.

See ["Adding Objects to Tables by Copy and Paste"](#) on page 5-7.
- 7 Drag and Drop

Select objects in the Navigation pane (**My Bookmarks, Recently Visited, NAVIGATOR** drawer), and then drag and drop them onto the table.

See ["Adding Objects to Tables by Drag and Drop"](#) on page 5-6.
- 7 Execute a search to find objects to add to a table.

See ["Adding Objects to Tables by Custom Search"](#) on page 5-7.

Adding Objects to Tables by Type-ahead Search

To add rows to a table in Web Client by type-ahead search:

1. Click the object tab to display the table you want.
2. Click the **Add** button. The add object palette appears.
3. In the text entry field, type the numbers or names of the objects you want to add, separated by semicolons. For example:
P00487; P00259; P00264
4. Or, you can also use the Web Client Type-Ahead search feature:
 - a. If you type a partial object number, Agile PLM displays a list of objects that match the text typed so far.
 - b. Use the arrow up and arrow down keys to highlight the object you want.
 - c. Press the right arrow key to select the object.

Repeat the steps above to select multiple objects to add.
5. Press the Enter key to add the objects to the table and close the palette.

Adding Objects to Tables by Quick Search

To add rows to a table in Web Client by Quick Search:

1. Click the object tab to display the table you want.
2. Click the **Add** button. The add object palette appears.
3. You can use any of these methods to select the objects to add to the table.
 - a. Click the **Search to Add** button to open the Search palette.

- b. Enter the search string text in the text field, and click the **Launch Search** button. The search results are displayed in the palette table.
 - c. Click, Ctrl-click, and Shift-click to select the row or rows you want to add and then press Enter. The selected objects are added to the table.
4. When you are done adding objects to the table, press the Escape key to close the palette.

Adding Objects to Tables by Create New

You can add to a table an object that has not been created yet.

Note: If the Create to Add option is not available for the table in which you are working, the **Create to Add** button does not appear in the object addition palette.

To add a non-existing object to a table in Web Client:

1. Click the tab to display the table you want in the content pane.
2. Click the **Add** button. The object addition palette appears.
3. Click the **Create to Add** button.
The Create New dialog appears.
4. In the Create New dialog, use the **Type** drop-down list to select the type (subclass) of object you want to create.
5. Complete any required fields.
6. Click **Add**.

The newly created object is added to the table.

Adding Objects to Tables by Drag and Drop

To add objects by drag and drop, you drag objects from the left navigation pane and drop them into an object table in the content pane. You can drag from:

- ? The **My Bookmarks** list in the **FOLDERS** drawer
- ? The **Recently Visited** list in the **FOLDERS** drawer
- ? The **NAVIGATOR** drawer – Click the **Navigator** button in any table, including search results tables, to populate the **NAVIGATOR** drawer.

To add rows to a table in Web Client by drag and drop:

1. In the content pane, click the object tab to display the table to which you want to add.
2. In the left navigation pane, click just to the left of an object link to select it.
3. Use Ctrl-click and Shift-click to select multiple objects in the navigation pane.
4. Drag the selected objects onto the table in the content pane.

The cursor becomes a box with a number, indicating the number of objects you are dragging.
5. When the cursor is over the table in the content pane, release the mouse button to drop the objects.
6. Respond to any warnings or errors.

The objects are added to the table.

Adding Objects to Tables by Copy and Paste

To add rows to a table in Web Client by using copy and paste:

You can copy objects to paste from the **My Bookmarks** or **Recently Visited** list in the left navigation pane, or you can copy objects to paste from any object tab table.

When you paste into a table, only the appropriate objects will be pasted into the table. For example, a BOM table includes only item objects. If you select and copy some item objects and change objects in a search results table, and paste the objects into the BOM table, only the items objects are successfully added to the table.

1. Copy the objects you want to paste:
 - ⌘ Search Results table – Execute a search. In the search results table, select the rows you want, and then choose **Copy** in the **More** menu.
 - ⌘ Object tab – In an object table tab (for example, the BOM table tab), select the rows you want to copy, and then choose **Copy** in the **More** menu.
2. In the content pane, open the object into which you want to paste.
3. Click the tab into which you want to paste.
4. In the tab **More** menu, choose **Paste**.

Adding Objects to Tables by Custom Search

In Web Client, you can use the search features to find objects that you want to add to a table.

- ⌘ From the top pane, execute a Quick Search or a Custom Search. In the search results table, select the rows you want and use the **More > Copy** command. Then, display the target table in the content pane and use **More > Paste** to add the selected objects to the table. See ["Adding Objects to Tables by Copy and Paste"](#) on page 5-7.
- ⌘ From the top pane, execute a Quick Search or a Custom Search. In the search results table, click the **Navigators** button to populate the **NAVIGATOR** drawer. Then, drag and drop objects from the **NAVIGATOR** drawer to the table in the content pane. See ["Adding Objects to Tables by Drag and Drop"](#) on page 5-6.

In addition, you can open a custom search palette, which lets you view the tab table in the content pane while you search for and select the objects you want to add to the table.

To open a Custom Search palette to find objects to add to a table:

1. In the content pane, click a tab to display the table to which you want to add.
2. On the keyboard, press Ctrl + Shift + X. The custom search palette appears. The tab table remains visible in the content pane behind the palette.
3. In the search palette, define a Basic search or an Advanced search. Execute the search. For more information about defining searches, see [Chapter 8, "Finding Agile Data with Searches."](#)

Note: In the upper left corner of the custom search palette, click the down arrow icon to collapse the entire palette; click the right arrow icon to expand the palette again.

4. Select one or more search results rows.
5. Click **More > Copy** in the search palette.
6. Put the focus in the content pane table by clicking in the content pane or by selecting a table row, and then choose **Paste** in the **More...** menu.

The objects are pasted into the content pane table.

7. You can execute multiple searches to find and select additional objects.
8. Press the Escape key on the keyboard to close the custom search palette.

Adding Objects to Tables from Excel by Copy and Paste

You can copy data from various cells in an Excel sheet and paste them into a table. This feature is functional in all tables where **Add** button opens a search box with **Search to Add** and **Create to Add** buttons.

To add rows from Excel to table by copy and paste:

1. In the Excel spreadsheet, select data that you want added to an object in Web Client.
2. In the Web Client, open the object into which you want to add the selected data.
3. Click the tab in which you want to add the data.
4. Click **Add**. The search box with **Create to Add** and **Search to Add** buttons is displayed.
5. Press Ctrl + V keys. The selected data from the Excel spreadsheet is pasted in the Search box.
6. Press the Enter key. The selected data with its complete records is added as rows in the table.

Editing and Modifying Tables

Editing and modifying Web Client tables includes the following actions:

- ? Adding one or more rows to a table
See "[Editing Table Cells in Web Client](#)" on page 5-8.
- ? Removing one or more rows from a table
- ? Editing table fields

Editing Table Cells in Web Client

To edit a table in Web Client:

1. Display the table you want to edit in the content pane.
2. To begin editing a table, double-click in any editable cell.

The table enters edit mode and the **Save** and **Cancel** buttons become active (not grayed).

Note: If the table is read-only, an error message is displayed in the table tab. If the cell you double-clicked is not editable, an error message to that effect appears in the table tab.

3. Make the required changes in each field. Navigate to other fields by clicking the field, pressing the Tab key, or using the arrow keys.
4. When you are finished, click **Save**.

Using Fill-Up and Fill-Down in Web Client Tables

From the tab **More** menu button, Web Client provides the following Fill-Up and Fill-Down table editing commands:

- ? Fill-down

- ? Fill-down (selected cells)
- ? Fill-up
- ? Fill-up (selected cells)

To Fill-down or Fill-up:

1. If the table is not already in edit mode, then enter table edit mode:

Double-click any editable cell of the table. The table enters edit mode and the **Save** and **Cancel** buttons become active. To navigate from one cell to another, press the Tab key to move to the next editable field, use the arrow keys, or click in a cell.

2. Select one cell in the column. The selected cell is highlighted.

- ? To fill-down, choose **More > Fill-down** in the tab menu or use the Ctrl + Shift + D keyboard shortcut.

The contents of the highlighted cell are copied down the column into all the cells below the highlighted cell.

- ? To fill-up, choose **More > Fill-up** in the tab menu or use the Ctrl + Shift + U keyboard shortcut.

The contents of the highlighted cell are copied up the column into all the cells above the highlighted cell.

Note: When using the shortcut for Fill-down (Ctrl + Shift + D) or Fill-up (Ctrl + Shift + U), the value for current cell must be entered. If the value is picked up from a drop-down list, the user must exit the selection mode to confirm the value is selected before using the shortcuts.

To Fill-down or Fill-up selected cells only:

1. If the table is not already in edit mode, then enter table edit mode:

Double-click any editable cell of the table. The table enters edit mode and the **Save** and **Cancel** buttons become active. To navigate from one cell to another, press the Tab key to move to the next editable field, use the arrow keys, or click in a cell.

2. Select two or more cells in the column. Use Shift-click to select contiguous cells. Use Ctrl-click to select non-contiguous cells. The selected cells are highlighted.

- ? To fill-down, choose **More > Fill-down (selected cells)** in the tab menu or use the Ctrl + Shift + D keyboard shortcut.

The content of the upper-most highlighted cell is copied down the column into only the highlighted cells below the up-most highlighted cell.

- ? To fill-up, choose **More > Fill-up (selected cells)** in the tab menu or use the Ctrl + Shift + U keyboard shortcut.

The content of the lower-most highlighted cell is copied up the column into only the highlighted cells above the lower-most highlighted cell.

Modifying Date and Time Fields

In Web Client, you can modify date fields by using the calendar tool, and also by typing in the field.

Using the Calendar to Modify Date Fields

To use the calendar tool in Web Client:

Note: The Agile administrator can configure Date fields to include both the date and the time or to include only the date. The time setting fields are not displayed in the calendar tool of a date field that is configured to include only the date.


1. In a date field, click the **Launch Calendar** icon to open the calendar (if it is enabled).
2. Double-clicking a date enters it directly into the field and closes the calendar.

By default, Agile PLM sets the time to 12:00:00 am.

The default time format is "12 hours" with am and pm.

3. To select a specific time:
 - ⌘ Enter the time in the Time: field, and choose AM or PM.
 - ⌘ Double-click the date you want. The date and time are entered in the field and the calendar closes.
4. To switch to a different month, click the **Previous Month** and **Next Month** buttons.
5. To switch to a different year, click the **Previous Year** and **Next Year** buttons.
6. Press Escape to close the calendar without selecting a date.

Figure 5–1 *Calendar tool*



Manually Modifying Date and Time Fields

To edit the date and time:

1. Select the date and time you want to change.
2. Enter the new date in the format specified in your user profile.
The default format is mm-dd-yyyy.
3. Press the Spacebar.
4. Enter the time in the format specified in your user profile. This step is optional; if you do not enter a time, by default the time displays midnight in the specified format.

Note: Web Client does not accept the new date without a space between the date and time.

5. Press the Tab key or the Enter key.

To edit just the time stamp:

1. Select the time you want to change.
2. Enter the new time in the hh:mm:ss format.
3. Press the Tab key or the Enter key.

Selecting Users or User Groups to Modify a Field

In Web Client, whenever you see the address book icon button, you can click that button to launch the address book palette. The address book palette lets you search for and select users or user groups to populate the field that you are currently modifying.

The available address book palette search methods are dependent on the properties of the specific field that you are modifying. For example, if a user group is not a valid entry for the field that you are modifying, the search for **User Groups** option is not available. You may be limited to selecting only one user or only one user group, depending on the properties of the field that you are modifying.

The address book palette provides the following search methods:

- ? Search for a user
- ? Search for a user in a specific user group

Note: The **Search within a User Group** option becomes available when the number of user groups in the Agile PLM system exceeds 200.

- ? Search for a user group

To search for users:

1. Click the address book icon button to open the address book palette.
2. Choose **Users** in the address book palette drop-down list.
3. Type the user object search criteria that you want to use.
4. Click the **Execute a Quick Search** button.
5. In the palette search results table, select the user row or rows you want to add:
 - ? Double-click a row.
 - ? Select one or more rows and drag them to the field that you are modifying.
6. Press the Escape key to close the address book palette.

To search for a user within a user group:

Note: The **Search within a User Group** option becomes available when the number of user groups in the Agile PLM system exceeds 200.

1. Click the address book icon button to open the address book palette.

2. Choose **Search within a user group** in the address book palette drop-down list.
3. In the **Select a user group to search within** popup, type the name of the user group you want or click the **Search** button to search for a group.
4. When you have selected a user group, click **OK** in the popup.

Note: Agile PLM adds the group name to the address book palette drop-down list. Agile PLM continues to add group names to the palette drop-down list until the number of groups equals twenty. As additional groups are added to the list, Agile PLM removes the oldest entries from the drop-down list. A maximum of twenty groups that you recently selected for the **Search within a user group** option remain on the drop-down list.

Alternately, you can use the address book palette drop-down list to select one of the user groups that you have selected recently.

5. Type the user object search criteria that you want to use.
6. Click the **Execute a Quick Search** button. The search is restricted to the members of the selected group.
7. In the palette search results table, select the user row or rows you want:
 - ? Double-click a row.
 - ? Select one or more rows and drag them to the field that you are modifying.
8. Press the Escape key to close the address book palette.

To search for a user group:

1. Click the address book icon button to open the address book palette.
2. Choose **User Groups** in the address book palette drop-down list.
3. Type the user group object search criteria that you want to use.
4. Click the **Execute a Quick Search** button.
5. In the palette search results table, select the user group row or rows you want:
 - ? Double-click a row.
 - ? Select one or more rows and drag them to the field that you are modifying.
6. Press the Escape key to close the address book palette.

To search for users or user groups by job function:

Note: The ability to search by job function is available in the address book only when selecting users or user groups as routable object reviewers.

1. Click the address book icon button to open the address book palette.
2. Choose a specific job function in the address book palette drop-down list.

Job functions appear in the drop-down list below the user groups.

Your search is limited to only those user objects and user group objects that include the selected job function in their **Job Function(s)** attribute.

3. Type the search criteria that you want to use.

4. Click the **Execute a Quick Search** button.
The search results include both users and user groups that have been assigned the selected job function.
5. In the palette search results table, select the row or rows you want to add:
 - ? Double-click a row.
 - ? Select one or more rows and drag them to the field that you are modifying.
6. Press the Escape key to close the address book palette.

Modifying List Fields

In Web Client, when you click the **Edit** button to edit a business object use one of these methods to modify a list field:

To modify a list field:

1. Click the drop-down list button to display the list entries.
2. Select an entry from the list.

To modify a MultiList field:

1. Click the MultiList select button to display the palette of list entries.
2. Select one or more list entries:
 - ? Double-click a row to add the entry to the list field.
 - ? Or, select a row, drag it to the list field, and drop it.
3. Press Escape to close the palette.

If the attribute for the list field includes a large number of list entries, the Agile administrator may choose to configure Agile PLM Web Client to display the editable list with search display.

To modify a search display list field:

1. Click the list field search button to display the search palette.
2. In the search palette, enter a search string and click the **Execute a Quick Search** button.
3. In the search results table, double-click a row to add the entry to the list field.
Or, select a row, drag it to the list field, and drop it.
4. Press Escape to close the palette.

Note: For list fields that contain more than 250 list entries, Web Client automatically displays the entries in search display.

For information about configuring list fields, see *Agile PLM Administrator Guide*.

Viewing the Contents of LargeText Fields

LargeText attributes are fields on the Page Two and Page Three tabs that can contain a large number of characters (between the minimum of 4000 and the maximum of 2,000,000) and HTML formatting. By default, the number of characters limit is set to 60,000. (By comparison, MultiText fields can contain a maximum of 4000 characters.)

For information about LargeText attribute property settings, see *Agile PLM Administrator Guide*.

On the Web Client **Title Block** tab or **Cover Page** tab, a LargeText field displays the first 4000 characters of the content.

- ✎ Use the scroll bar to view more content in the field.
- ✎ If there is additional content in a non-journal LargeText field, then the message
Select the expand icon to see the complete field content
is displayed at the bottom of the scroll area.
- ✎ If there is additional content in a journal LargeText field, then the message
Select the expand icon to see the complete field content. Only the most recent journal entry is shown.
is displayed at the bottom of the scroll area.

To view the LargeText field content:

1. Click the **Launch the Large Text Palette** button to the right of the LargeText field. The LargeText palette opens.
2. Use the scroll bar to view more content in the palette.
3. Use the palette window controls in the upper-right corner of the palette window to control how the palette is displayed:
 - ✎ Minimize
 - ✎ Maximize
 - ✎ Restore Original Size
 - ✎ Escape (small x) closes the palette, or press the Escape key on the keyboard.
4. If you have the appropriate privileges, you can click the **Edit** button or **Add** button on the palette to open the LargeText editor. See "[Modifying LargeText Fields](#)" on page 5-14.

Modifying LargeText Fields

LargeText fields can include HTML-formatted text and images. Agile PLM provides a WYSIWYG (What You See Is What You Get) editor that produces standards-compliant HTML code. With the HTML editor, you can enter text in the editing area and format that text in a few simple clicks of the toolbar buttons without knowing the details of HTML syntax.

When the LargeText field is saved, a content filter ensures that the correct enabled HTML tags are included.

LargeText fields can be configured two ways:

- ✎ Include Journal Entry property = No
When journal entry is disabled, the LargeText field is edited as a single document. Once you have entered content into the LargeText field, you can edit and revise that content, provided you have the necessary Read and Modify privileges.
- ✎ Include Journal Entry property = Yes
When journal entry is enabled, users can add successive content entries to the LargeText field. Each entry includes the name of the user who added it, and the date and time it was added. This allows you to create a running commentary or discussion. Journal entries cannot be edited.

LargeText journal fields display the journal entries in the order in which they were entered, either Youngest First (most recent) or Oldest First. Default is Youngest First.

See the following topics for detailed information about modifying LargeText fields:

- ? ["LargeText Field HTML Editor" on page 5-15](#)
- ? ["Modifying LargeText Journal Fields" on page 5-21](#)
- ? ["Modifying LargeText Non-journal Fields" on page 5-21](#)
- ? ["Comparing Historical LargeText Field Edits" on page 5-21](#)
- ? ["Viewing LargeText Field Redline Edits" on page 5-22](#)

LargeText Field HTML Editor

The following table describes all the available HTML editing functions. The Agile administrator can enable or disable each HTML editor toolbar button for each LargeText field. Disabled HTML editor button are inactive and appear greyed out.

Table 5–2 HTML Editor toolbar







Toolbar Buttons	Description
	Source View or edit the HTML source code of the LargeText field contents. To return to the WISYIWYG view, click the Source button again.
	? Cut Cut the selected text to the clipboard. ? Copy Copy the selected text to the clipboard. ? Paste Past the clipboard content, including formatting.
	Paste as plain text Paste the clipboard content without formatting.
	Paste from Word Paste clipboard content copied from Microsoft Word or similar applications, including formatting.
	Undo, Redo Undo the most recently performed action. Redo the most recent undo operation.
	Paragraph Format <ol style="list-style-type: none"> 1. Position the cursor in the paragraph you want to format. 2. Click the Paragraph Format button and choose a format from the drop-down list. Paragraph formats are predefined combinations of formatting options that provide a uniform text presentation.

Table 5–2 (Cont.) HTML Editor toolbar








Toolbar Buttons	Description
	<p>Font Name</p> <p>You can apply a font to the entire editable document, to a paragraph, or to a text fragment.</p> <ol style="list-style-type: none"> 1. Select the text to which the font will be applied. 2. Click the Font button and select a font from the drop-down list. 3. To change the font of the text you enter, select a font from the drop-down list and then begin typing.
	<p>Font Size</p> <p>You can apply a different font size to the selected text fragment.</p> <ol style="list-style-type: none"> 1. Select the text to which the font size will be applied. 2. Click the Font Size button and select a font size from the drop-down list. 3. To change the font size of the text you enter, select a font size from the drop-down list and then begin typing.
	<p>Text Color</p> <p>Change the color of the selected text.</p> <ol style="list-style-type: none"> 1. Select the text to which the text color will be applied. 2. Click the Text Color button and choose a color from the color palette. 3. For more color choices, click the More Colors link in the color palette and then select a color in the Select Color dialog. Click OK.
	<p>Background Color</p> <p>Change the background color of the selected text.</p> <ol style="list-style-type: none"> 1. Select the text to which the background color will be applied. 2. Click the Background Color button and choose a color from the color palette. 3. For more color choices, click the More Colors link in the color palette and then select a color in the Select Color dialog. Click OK.
	<p>Basic text formatting: Bold, Italic, Underline.</p> <ol style="list-style-type: none"> 1. Select the text to which the text format will be applied. 2. Click the appropriate button for each text format you wish to apply: Bold, Italic, and Underline.
	<p>Extended text formatting: Strike Through, Subscript, Superscript.</p> <ol style="list-style-type: none"> 1. Select the text to which the text format will be applied. 2. Click the appropriate button for each text format you wish to apply: Strike Through, Subscript, and Superscript.
	<p>Remove Format</p> <p>Remove all text formatting from the selected text.</p> <ol style="list-style-type: none"> 1. Select the text to which the text formats will be removed. 2. Click the Remove Format button. <p>The following text formats are removed: Font Name, Font Size, Text Color, Background Color, Bold, Italic, Underline, Strike Through, Subscript, and Superscript.</p>

Table 5–2 (Cont.) HTML Editor toolbar






Toolbar Buttons	Description
	<p>Insert/Remove Numbered List Insert/Remove Bulleted List</p> <ol style="list-style-type: none"> 1. To create a list, either select one or more paragraphs, or place the cursor in a paragraph. 2. Click a list button. The paragraphs become list items. 3. Press Enter to create another list item. 4. To remove a list, select one or more list items and click the list button. 5. To customize the list properties, right-click in the list to display the context menu, and choose List Properties.
	<p>Decrease Indent (outdent) Increase Indent (indent)</p> <p>Place the cursor in a paragraph. Click the indent or outdent button to increase or decrease the indent by one tab length.</p>
	<p>Block Quote</p> <p>Block quote is used for long quotations that are distinguished from the main text by both left and right indentation</p> <p>To add a block quotation, either select one or more paragraphs, or place the cursor in a paragraph, and then click the Block Quote button.</p>
	<p>Text Alignment: Place the cursor in the paragraph and click the alignment button. Click again to remove the alignment.</p> <p>Align Left: Aligns the paragraph text at the left margin.</p> <p>Center: Aligns the paragraph text symmetrically in the center between the two margins.</p> <p>Align Right: Aligns the paragraph text at the right margin.</p> <p>Justify: Aligns the paragraph text to both the left and right margins.</p>
	<p>URL Link and Unlink</p> <p>Link:</p> <ol style="list-style-type: none"> 1. Place the cursor where the URL is to be inserted. 2. Click the Link button to display the Link dialog. 3. Select a Link Type and Protocol, or accept the default settings. 4. In the URL field, enter the URL address. 5. Click OK. <p>Unlink:</p> <ol style="list-style-type: none"> 1. Place the cursor in the link text. 2. Click the Unlink button. The link is converted to plain text.

Table 5–2 (Cont.) HTML Editor toolbar





Toolbar Buttons	Description
	<p>Image</p> <p>To insert an image, click the Image button to display the Image Properties dialog.</p> <p>Image Info tab:</p> <ol style="list-style-type: none"> 1. In the URL field, enter the external address of the image, for example <code>http://example.com/image1.jpg</code>. 2. In the Alternate Text field, enter a brief text description of the image for use by applications such as screen readers. 3. Width: Image width in pixels. Default is the size of the original image. 4. Height: Image height in pixels. Default is the size of the original image. 5. Border: Specify an optional border around the image in pixels. 6. Hspace: Specify a horizontal space or margin in pixels between the image or image border and the surrounding document elements. 7. Vspace: Specify a vertical space or margin in pixels between the image or image border and the surrounding document elements. 8. Alignment: Select an optional alignment, either left or right. 9. The Preview pane displays a preliminary view of the image with the formatting options applied. <p>Link tab:</p> <p>Use the Link tab to assign a link to the image, thus converting the image into a clickable link.</p> <p>First, use the Image Info tab to insert an image into the document.</p> <p>Then, on the Link tab, enter a URL address.</p>
	<p>Table</p> <ol style="list-style-type: none"> 1. To create a table, click the Table button to display the Table Properties dialog, and then configure the table properties. 2. Rows: Enter the number of rows (required property). 3. Columns: Enter the number of columns (required property). 4. Width: Define the width of the table by pixels (example: 500) or by percentage of the editing area (example: 75%). 5. Height: the height of the table in pixels (optional). 6. Headers: You can apply header formats to First Row, First Column or Both (optional). 7. Border size: thickness of the table border in pixels. 8. Alignment: the alignment of the table on the page; Left, Center, or Right. 9. Cell spacing: in pixels, the space between individual cells and the space between cells and table borders. 10. Cell padding: in pixels, the space between the cell border and the cell contents. 11. Caption: the table title displayed above the table. 12. Summary: Enter a brief text description of the table for use by applications such as screen readers.

Table 5–2 (Cont.) HTML Editor toolbar

Toolbar Buttons	Description
Table context menu	<p>To modify properties of an existing table:</p> <ol style="list-style-type: none"> 1. Right-click in the table to display the table context menu and select a menu item: 2. Delete Table: Delete the entire table and its contents. 3. Table Properties: Displays the Table Properties dialog. With the exception of the rows and columns, you can modify the configuration options. 4. Row – Displays the row submenu: <ul style="list-style-type: none"> Insert Row Before: insert a new row before the row containing the cursor. Insert Row After: insert a new row after the row containing the cursor. Delete Rows: Delete the selected rows or the row containing the cursor. 5. Column – Displays the column submenu: <ul style="list-style-type: none"> Insert Column Before: insert a new column before the column containing the cursor. Insert Column After: insert a new column after the column containing the cursor. Delete Columns: Delete the selected columns or the column containing the cursor.

Table 5–2 (Cont.) HTML Editor toolbar

Toolbar Buttons	Description
Table context menu, Cell submenu	<p>To modify cell properties of an existing table, right-click in the table and choose Cell to display the cell submenu:</p> <p>Insert Cell Before: insert a new cell before the cell containing the cursor.</p> <p>Insert Cell After: insert a new cell after the cell containing the cursor.</p> <p>Delete Cells: Delete the selected rows or the row containing the cursor.</p> <p>Merge Cells: To merge multiple cells into one, select two or more cells and then choose the Merge Cells menu item.</p> <p>Merge Right: Merges the cell containing the cursor with the cell on its right. The contents of both cells are joined.</p> <p>Merge Down: Merges the cell containing the cursor with the cell below it. The contents of both cells are joined.</p> <p>Split Cell Horizontally: Split the cell containing the cursor into two cells, creating a new cell to the right. The cell content appears in the original cell on the left.</p> <p>Split Cell Vertically: Split the cell containing the cursor into two cells, creating a new cell below. The cell content appears in the original upper cell.</p> <p>Cell Properties: Opens the Cell Properties dialog.</p> <ul style="list-style-type: none"> ? Width: Enter a number for the width of the cell in pixels or percent. Choose pixels or percent from the drop-down list. ? Height: The height of the cells in pixels. ? Cell Type: From the drop-down list, choose Data cell or Header cell. ? Word Wrap: Disable (No) or Enable (Yes, default) word wrapping in the cell. ? Rows Span: Enter a numeric value to set the <code>rowspan</code> attribute. This setting stretches the row downward over several rows. ? Columns Span: Enter a numeric value to set the <code>colspan</code> attribute. This setting stretches the cell to the right over several columns. ? Horizontal Alignment: From the drop-down list, select the horizontal alignment of the cell contents: Left, Center, or Right. ? Vertical Alignment: From the drop-down list, select the vertical alignment of the cell contents: Top, Middle, Bottom, or Baseline. ? Background Color: The color of the cell background. Click Choose and select a color in the Select Color dialog. ? Border Color: The color of the cell border. Click Choose and select a color in the Select Color dialog.
	<p>Insert Horizontal Line</p> <p>Click the Insert Horizontal Line button to insert a horizontal line (also called a horizontal rule) into the document at the cursor location.</p>
	<p>Insert Special Character</p> <ol style="list-style-type: none"> Click the Insert Special Character button to open the Select Special Character dialog. Select a character by clicking it. Or, navigate to the character you want with the up, down, left, and right arrow keys, and then press Enter.

Modifying LargeText Journal Fields

When a LargeText field is configured to allow journal entries, and you have the appropriate privileges, then you can add a journal entry to the LargeText journal field. Once you have saved your entry, it cannot be edited.

To modify a LargeText journal field:

1. Click the **Launch the Large Text Palette** button to display the LargeText palette.
2. In the palette, click the **Add** button. The HTML editor buttons are displayed with the text entry field below.
3. Enter text and format the text as desired. Refer to "[LargeText Field HTML Editor](#)" on page 5-15 for more information about the HTML editor.
4. When you are done, click **Save**.

Note: The modification of a LargeText field is independent from the modification of the business object. A LargeText field can be modified at any time, regardless of whether the Title Block is in edit mode.

If the Title Block is in edit mode, and you modify a LargeText field and save those modifications, the LargeText field modifications are not discarded if you then cancel the Title Block edit session.

Modifying LargeText Non-journal Fields

When a LargeText field is configured to disallow journal entries, and you have the appropriate privileges, then you can edit and revise the LargeText field. Once you have saved your document, you can update or revise it, providing you have the appropriate privileges.

To modify a LargeText non-journal field:

1. Click the **Launch the Large Text Palette** button to display the LargeText palette.
2. In the palette, click the **Edit** button. The HTML editor buttons are displayed with the text entry field below.
3. Enter text and format the text as desired. Refer to "[LargeText Field HTML Editor](#)" on page 5-15 for more information about the HTML editor.
4. When you are done, click **Save**.

Note: The modification of a LargeText field is independent from the modification of the business object. A LargeText field can be modified at any time, regardless of whether the Title Block is in edit mode.

If the Title Block is in edit mode, and you modify a LargeText field and save those modifications, the LargeText field modifications are not discarded if you then cancel the Title Block edit session.

Comparing Historical LargeText Field Edits

You can view the difference between LargeText field edits on the business object **History** tab.

To compare LargeText field edits:

1. Open the business object and click the **History** tab.
2. In the History table **Details** column, click the **View** link to display the LargeText palette showing content saved for that modification.

3. In the History table **Details** column, click one of the Compare links to display the Difference Between Edits window.
 - ? **Incremental** – compares the content saved for that modification against the previously saved modification.
 - ? **Latest** – compares the content saved for that modification against the most current saved content.
4. Follow the instructions in the Difference Between Edits window to display descriptions of the differences:
 - ? Added text is shown in a green background.
 - ? Removed text is shown in red background.
 - ? Formatted text is shown with a blue underline and tooltip.
 - ? Click the changed text to see a detailed description.
 - ? Use the left and right arrow keys to review the edits sequentially.
 - ? Use the **First** and **Last** links in the Difference Between Edits window to go to the first change or to go to the last change.
5. When you are finished, close the window.

Viewing LargeText Field Redline Edits

If the LargeText non-journal field has been configured to be change controlled, you can view the redline edits on the ECO object Title Block redline tab. LargeText journal fields cannot be change controlled. For more information, see *Agile PLM Administrator Guide*.

1. Open the ECO object, and click the **Affected Items** tab to display it.
2. In the Affected Items table, select the affected item row.
3. In the redline pane below the Affected Items table, click the Title Block redline tab to display the Title Block redlines.
4. If the LargeText field has been redline edited, then the **Show Changes** button appears to the right of the LargeText field.

Click the **Show Changes** button. The Difference Between Edits window opens.

5. Follow the instructions in the Difference Between Edits window to display descriptions of the differences:
 - ? Added text is shown in a green background.
 - ? Removed text is shown in red background.
 - ? Formatted text is shown with a blue underline and tooltip.
 - ? Click the changed text to see a detailed description.
 - ? Use the left and right arrow keys to review the edits sequentially.
6. When you are finished, close the window.

For more information about change controlled attributes, see *Agile PLM Product Collaboration User Guide*.

Printing Object Tabs

You can print information from any tabbed object.

Attachments are printed from their native applications or the Viewer. For more information, see ["Printing Attachment Files"](#) on page 10-14.

To print an object in Web Client:

1. Open the object.
2. Choose **Print** from the **Actions** menu. The Print Options dialog appears.
3. Indicate whether you want to print all tabs or just the current tab.

If you choose **All tabs**, specify whether you want the printout to include all levels (for example, of the BOM).
4. Print the object by using one of the following options:
 - ⌘ Click the **Preview** button in the Print Options dialog to view a preview of the printout in a separate window. Click the **Print** button in the preview window to open the Print dialog. Click **Cancel** to close the preview window.
 - ⌘ Click **Print** in the Print Options dialog. A preview of the printout appears in a separate window and a Print dialog box opens.
5. In the Print dialog, make sure the appropriate print options are selected and click **Print**.

Note: The **Structure** tab of Design objects is not supported for printing.

LargeText fields are not supported for printing. See ["Viewing the Contents of LargeText Fields"](#) on page 5-13.

Emailing Objects

You can email any Agile object to another user listed in the Agile address book. Email is sent to the email address specified in the Agile user profile. The email contains a URL that links to the mailed object, and the recipient can click the URL to view the object in Agile PLM.

Note: The Agile administrator sets your user profile **Preferred Client** preference to determine whether you receive links to Web Client or Java Client.

To email an Agile object in Web Client:

1. Open the object.
2. Choose **Actions > Send**. The Send dialog appears.
3. Type the names you want, separated by a semicolon. Or, click the address book icon button to open the address book palette to search for the names you want.
4. Enter any comments in the **Comments** field.
5. Click **Send** to mail the object.

Smart URL Quick Access to Objects, Files, and Searches

You can generate quick access URLs that provide direct pointers to either Agile objects or to Agile attachment files.

These quick access URLs can be pasted into other applications or files such as spreadsheet files, word processing files, a company Intranet web page or WIKI page, or into an email.

For information about quick access to Agile objects using quick access URLs, see:

- ? ["Agile-Generated Quick Access Object Smart URLs"](#) on page 5-24.
- ? ["Using Quick Access Object Smart URLs"](#) on page 5-24.
- ? ["Formats for User-Generated Smart Object URLs"](#) on page 5-24.

For information about quick access to attachment files using attachment quick access URLs, see:

- ? ["Smart URL Quick Access to Files"](#) on page 10-38.

For information about quick access to searches using search quick access Smart URLs, see:

- ? ["Smart URL Quick Access to Searches"](#) on page 8-73

Agile-Generated Quick Access Object Smart URLs

From Web Client, you can generate Agile PLM object quick access URLs from the Web Client Actions menu.

To generate an Agile PLM object quick access URL:

1. Login to Agile PLM Web Client and open the desired object.
2. In the Actions menu, choose **Copy URL to Clipboard**.

The URL is copied to your clipboard. You can then paste it into another application or file, such as a word processing file, a spreadsheet file, or an email.

Using Quick Access Object Smart URLs

When a user clicks a Quick Access Smart Object URL, the user actions are the same whether the URL is an Agile-generated quick access URL or a user-generated Smart Object URL:

1. The user clicks the URL and the Agile PLM Web Client login screen is displayed in a browser window.
2. The user enters the respective login information.
3. Upon successful login, Agile PLM searches for the object specified in the link.

(If the object is not found, then Agile PLM displays an error and returns to the user's Home page.)

When the object is found, Agile PLM verifies that the user has the appropriate privileges to read the object and displays the first tab of the object, for example, the **Title Page**. If the Smart URL specifies a specific tab, then that tab is displayed.

See also ["Accessing Attachment Files using Quick Access URLs"](#) on page 10-43, and ["Formats for User-Generated Smart Object URLs for Searches"](#) on page 8-74.

Formats for User-Generated Smart Object URLs

The Agile Smart Object URL feature is designed to enable effective collaboration through email, spreadsheets, documents, WIKIs, and so forth. Users or automated tools can generate smart readable URLs that point to a specific object in Agile PLM, that open a specific attachment file, and that open a search page in Agile PLM.

Smart URLs can specify a specific tab, revision, or version to display when the object opens in Agile PLM.

By using the Smart URL formats, a user does not need to log into Agile PLM to generate the object URL. Automated tools can also use this format to generate object URLs.

Smart Object URLs can be used for objects available from Web Client.

Smart Object URL Format

You can generate Smart Object URLs by using the following formats:

```
http://server:port/<VirtualPath>/object/<ObjectType>/<ObjectName>
```

```
http://server:port/<VirtualPath>/object/<ObjectType>/<ObjectName>
[/tab/<TabName>]
```

```
http://server:port/<VirtualPath>/object/<ObjectType>/<ObjectName>
[/Rev/<RevChange>] [/tab/<TabName>]
```

```
http://server:port/<VirtualPath>/object/<ObjectType>/<ObjectName>
[/Version/<VerNum>] [/tab/<TabName>]
```

where the URL has the following representation:

Table 5–3 Smart Object URL parameters

Parameter	Description
server port VirtualPat	Server, port, and VirtualPath identify the Agile PLM instance
object	The text "object" indicates to Agile PLM that the URL is an object URL.
ObjectType	ObjectType refers to the subclass (type) of object, for example, ECO, Part, Manufacturer, File Folder, Project, Activity, or Discussion
ObjectName	<p>ObjectName refers to the unique identifier for the object. Depending on the object class, the unique identifier is either an object number or a name.</p> <p>Note: Manufacturer Parts are a special class of objects that are uniquely identified by two parameters: a Manufacturer Name and a Manufacturer Part Number. Therefore, a URL referring to a specific Manufacturer Part uses the following format:</p> <pre>http: //server:port/VirtualPath/object/ObjectType/ MfrName/MfrPart_Number</pre>
Rev	The text "Rev" indicates to Agile PLM that the URL opens a specific Rev (revision) of the object
RevChange	RevChange refers to the unique identifier (number) of the Change object that released the Rev you wish to display when the object opens in Agile PLM.
Version	The text "Version" indicates to Agile PLM that the URL opens a specific Version of the object.
VerNum	VerNum refers to the object version number (1, 2, 3, and so on) that you wish to display when the object opens in Agile PLM.
tab	The text "tab" indicates to Agile PLM that the URL opens the object and displays a specific object tab
TabName	<p>TabName refers to the name of the tab that is displayed when the object opens in Agile PLM.</p> <p>Note: TabNmae uses the API name. For information about API names, see <i>Agile PLM Administrator Guide</i>.</p>

Agile PLM identifies and handles special tags (such as %20) added to URLs to handle special characters (such as spaces and other special characters such as asterisk "*") in the unique identifier of an object. For example:

```
http://server:port/VirtualPath/object/Manufacturer/Philips%20Semiconductor
```

This URL resolves to the manufacturer "Philips Semiconductor".

Examples of Quick Access Object Smart URLs

Smart URLs for pointing to Agile objects use the following formats.

Open the latest revision or version of an object:

```
http://server:port/VirtualPath/object/ObjectType/ObjectName
```

Opens the latest revision or version of the object displaying the **Title Block** tab or the **General Info** tab.

```
http://server:port/VirtualPath/object/Part/P00348
```

```
http://server:port/VirtualPath/object/File Folder/F00045
```

```
http://server:port/VirtualPath/object/  
manufacturer part/Green%20Star/349-280
```

Open displaying a specific tab an object:

```
http: //server:port/VirtualPath/object/ObjectType/ObjectName/tab/TabName
```

Optionally, you can specify an object tab to display. Opens the latest revision or version of the object and displays the tab specified by TabName. If the tab TabName is disabled, or there is no such tab, then the object opens and displays the Title Block tab or the General Info tab instead.

```
http://server:port/VirtualPath/object/Part/P00243/tab/BOM
```

```
http://server:port/VirtualPath/object/File Folder/F00045/tab/Files
```

```
http://server:port/VirtualPath/object/manufacturer part/  
Green%20Star/349-280/tab/Where Used
```

Open a specific revision of an object:

Optionally, if the object has a Revision (Rev) or a Version, you can specify the specific Rev or Version to open:

```
http://server:port/VirtualPath/object/ObjectType/ObjectName/  
Rev/RevChange/tab/TabName
```

Opens the object displaying the revision created by the Change object RevChange. For example, item revisions are created by ECOs; Published Price revision are created by PCOs.

Example:

```
http://server:port/VirtualPath/object/Parts/P00243/Rev/C00548/tab/BOM
```

Opens Parts object number P00243 at the revision created by ECO C00548, and displays the BOM tab of that revision.

Open a specific version of an object:

```
http://server:port/VirtualPath/object/ObjectType/ObjectName/  
Version/VerNum/tab/TabName
```

Opens the object and displays the object version specified by VerNum.

Example:

```
http://server:port/VirtualPath/object/File Folder/
FOLDER00856/Version/3/tab/Files
```

Opens File Folder object number FOLDER00856 at version 3, and displays the Files tab of that version.

Discussion Objects

A Discussion can be created from the main toolbar **Create** menu, or from a business object's **Discussions** tab. Discussions are integrated into the Product Portfolio Management solution, and are also applicable to the Product Cost Management solution; however, discussions can be created and modified in the same manner as any Agile PLM object, and their utility can be applied to the other Agile PLM solutions, Product Collaboration, Product Governance & Compliance, and Product Quality Management.

Discussions are always created and viewed in Web Client. To access a discussion while using Java Client, you can search to locate an existing discussion and open the object, which will open the Web Client. Or you can simply open the Web Client and proceed from there, including creating discussions.

The following objects classes have a **Discussions** tab: Sourcing s, Request for Quote, RFQ Responses, Activities, and Gates. See *Product Portfolio Management User Guide* and *Product Cost Management User Guide* for information about using discussions in those solutions.

Creating and Viewing Discussions

To create a discussion:

1. Start at the **Create New** menu (see "[Creating Objects in Web Client Using the Create New Command](#)" on page 5-3).
2. In the Create New Discussion dialog, fill in the information.
3. Click **Save**. The new Discussion object appears in the Web Client content pane.

To manage your discussions, you can use Web Client features such as Search and Bookmark.

The discussion object includes:

? **Join** button, **Actions** menu.

The Join action adds the user to the Notify List.

? **Discussion** tab, which includes:

- Discussion object information - type information, such as the discussion's ID number, Subject, Status, Priority, Subject, and Notify List.
- **Message** table, which is a list of all the replies in the discussion.

? **Actions Items** tab of a discussion object includes:

- Action Items table, which lists action items that have been associated with the discussion.
- Action Item navigation button: **Add, Remove, Accept, Decline, Mark Complete**.

- Additional tabs, if the Agile administrator has enabled them, for example, **Attachments**, **Relationships**, **History**

Adding To and Editing Discussions

When the owner/creator opens the Discussion object, they can click **Edit** to modify the **Page One**-type information. (A user must have sufficient privileges to edit discussion information.)

Subsequent entries in the discussion are displayed in the **Messages** table with the most recent entry displayed in the first row of the **Messages** table.

To enter a reply:

1. Click the **Reply** button in the first row of the **Messages** table.
2. In the Reply to Discussion dialog, enter your reply in the **Message** field.
3. If you have sufficient privileges, you can add or remove users in the **Notify List**.
4. When you are finished, click **Send**.

Action Items can be created or deleted by users (on the Notify list) who have sufficient privileges.

Sharing Objects with Other Users

Sharing lets you grant one or more of your roles to another Agile user or user group for specific objects. The capability to share a given role requires being assigned the Grant privilege specific to that object. You can share only your assigned roles, that is, the roles that are listed in the **Roles** field on the **General Info** tab of your user profile, and the roles that are listed in the **Roles** field on the **General Info** tab of any groups of which you are a member.

You cannot share roles that have been shared with you by another user, and you cannot share roles that have been shared with a user group to which you belong.

When a role has been shared with a user (or members of a user group), each user can then perform actions permitted by the roles for that object only; a user does not "acquire" the role in any permanent or far-reaching way.

A user's or user group's **Share** tab lists those objects for which the user has been granted "shared roles" by a different user. Click the **Share** tab in your user profile to see objects being shared with you and what role(s) allow and define your interaction with each object. If you belong to a user group, you can see objects being shared with you through the user group by opening the group object and clicking the **Share** tab.

To share an object in Web Client:

1. Display the object.
2. In the **Actions** menu, choose **Sharing**. The Share with Users dialog appears.
3. Click **Add**. The Add Users dialog appears.
4. In the **Users** field, type the names of the users you want, separated by semicolons. Or, click the address book icon button to launch the address book palette and search for and select the users or user groups you want.
5. In the **Roles** field, type the name of the roles you want. Or click the **Launch the Palette** icon to launch the Roles palette to search for and select the roles you want.
6. Click **Save**. The Add Users dialog now lists the share you just defined.
7. To add more shares, click **Add** and repeat steps 4 through 6.

8. To remove a share, select its row and click **Remove**.
9. When you are finished, click **Close** in the Share with Users dialog.

When you view the original object and choose **Actions > Sharing**, it now shows you the complete list of users who have access to this object and the roles you specified.

To remove a shared object from the **Share** tab of your user profile, select the object and click **Remove**.

Subscribing to Objects

Subscribing to an object sets you up to receive notification of events that happen to that object. For example, you might subscribe to a change to be notified when the change is released, or you might subscribe to an attachment to be notified when the attachment is checked in. You can also be notified when specified fields are modified. You select the events about which to be notified. To be notified when certain fields change, you specify those fields.

You must have the Subscribe privilege for a specific object class to be able to subscribe to that class's objects. See your Agile administrator to be assigned additional privileges.

Note: Subscribe capabilities are not available for Report objects or for User Group objects.

On the **Subscription** tab of your user profile, you can view the objects to which you have subscribed. To cancel or remove a subscription, select the object, and click **Remove**.

Subscription events trigger two types of notifications: Email and Inbox. Email notifications are sent only if your Receive Email Notification preference is set to Yes; this field is on the **Preferences** tab of your User Profile. The ability to edit user information is determined by your privileges.

Subscribing to an Item or Price Revision

It is possible to subscribe to an item revision change and a price revision change. Since you cannot subscribe to a specific status change (for example, changed to Released) for a change that increments the revision of the Item (an ECO) or the Price object (a PCO), subscribing to the object itself (the part, document, or price) is the way you can be notified that the revision of the object has been modified by the release of an ECO or PCO.

Subscribing to Attachments by Using the File Folder

To be notified of changes to a file folder, subscribe to its "check-in" events. The version number of File Folder objects automatically increments every time they are checked in. However, it is not possible to subscribe to file folder versions, which work differently than item revisions. So, subscribing to a file folder's Check-ins is the way you can be notified that the file folder has been altered; file folders are not subject to changes (objects from the various change classes).

Subscribing to Objects

To subscribe to an object in Web Client:

1. Display the object.

Note: Subscribe capabilities are not available for Report objects or for User Group objects.

2. Choose **Actions > Subscribe**. The Define Subscriptions page appears.
3. Indicate whether you want to be notified when the subscribed object is modified by selecting the appropriate check boxes. You can select one or more:
 - ? Status Options:
 - Lifecycle Phase Change (or Status Change if it is a routable object)
 - ? Field Options:
 - Select from the displayed list of fields. The Agile administrator determines which fields are available for subscription.
 - Revision Change (items and prices)
 - ? File Options:
 - Select All
 - Delete File
 - Add File
 - Checkout File
 - Checkin File
 - Get File
Notifies when Get File action is performed in Web Client.
 - Cancel Checkout File
 - View File
Notifies when View File action is performed in Web Client.
 - Open File
Notifies when Open File action is performed in Web Client.
4. Click **Subscribe**.

Subscription in Product Portfolio Management

The events you can subscribe to vary per object. Product Portfolio Management has the following Activity-specific subscription events that do not apply to other objects. You can subscribe to actions related to:

- ? Discussions
- ? News
- ? Action Items
- ? Schedule
- ? Cost
- ? Health

The **Apply to all levels below** check box in activities and gates "pushes" a subscription to all subordinate objects. If you subscribe to an activity that has a schedule and select this check box, you will automatically subscribe to all of the activity's projects, phases, and tasks (that is, any object created in the preconfigured subclasses of Activities class). Because **Page Two** and **Page Three** fields can be defined differently for projects, phases, and tasks, any of the attributes that do not apply are ignored.

Relationships and Dependencies Between Objects

This section includes the following topics:

- ? ["What are Relationships?"](#) on page 5-31
- ? ["What are Revision-Specific Relationships?"](#) on page 5-32
 - ["Relationships Tab"](#) on page 5-33
 - ["Relationships Tab Views"](#) on page 5-34
 - ["Relationship Tab Actions in Web Client"](#) on page 5-34
- ? ["Adding Relationships to Objects"](#) on page 5-35
 - ["Selecting a Revision"](#) on page 5-36
 - ["Accepting or Rejecting a New Revision"](#) on page 5-36
- ? ["Editing the Relationships Table"](#) on page 5-37
- ? ["Removing Relationships"](#) on page 5-37
- ? ["What is a Relationship Rule?"](#) on page 5-37
 - ["Relationship Rule Guidelines"](#) on page 5-38
 - ["Adding a Rule to a Relationship"](#) on page 5-39
 - ["Editing a Relationship Rule"](#) on page 5-40
 - ["Removing a Relationship Rule"](#) on page 5-40
- ? ["Relationships in PQM"](#) on page 5-40

What are Relationships?

You can associate objects to each other by using the **Relationships** tab. A relationship between two Agile objects is bi-directional and is displayed on the **Relationships** tab of both objects.

Note: In Agile PPM, relationships are called *deliverables* and are managed on the PPM object **Contents** tab. For more information about the PPM **Contents** tab, see *Agile Product Portfolio Management User Guide*.

Specifying a rule for a relationship defines how the related Agile objects affect each other. For example, you can define a relationship rule so that ECO_100 affects ECR_250. When ECO 100 reaches the Implemented status, ECR_250 is promoted to the Complete status automatically.

Note: Rules are optional; you can create a relationship between two objects without specifying a rule.

A relationship is created when you add an object to a table in the **Relationships** tab of another object. The classes of objects that can reference each other on a **Relationships** tab are:

- ? All object classes, except Reports and Action Items.
- ? For Agile PPM Projects classes, relationships are named *deliverables* and are included on the **Content** tab.

The Agile administrator configures the Agile PLM system to enable the **Relationships** tab for each object class, making it visible. If you find that you want to create a relationship between objects and those tabs are not visible, see the Agile administrator.

Once you create relationships between objects, you can also create an advanced search for such relationships. See "[Relationship Searches](#)" on page 8-55.

A relationship without a rule is a simpler, less dynamic instance of object-to-object relationship; it simply lists references to other objects. It can be thought of as "bi-directional" information, because relationships without rules do not trigger events.

What are Revision-Specific Relationships?

Note: Revision-specific relationships are available to you only if the Agile administrator has configured Agile PLM to enable revision-specific relationship capabilities. The revision-specific columns on the **Relationships** tab (**Revision**, **Change**, **Track Impact**, and **Impacted**) must be visible, and you must have the appropriate privileges for those attributes. These revision-specific attributes can be enabled for specific object classes as needed, that is, some object classes may have revision-specific relationships enabled while the remaining object classes do not.



Revision-specific relationships allow you to select a specific revision for a Part object, Document object, or Published Price object in a relationship. The following conditions apply to revision-specific relationships:

- ⌚ Both objects in the relationship must be enabled for revision-specific relationships. For example, to create a revision-specific relationship between a Part object and an ECO, the Revision, Change, Track Impact and Impacted attributes must be enabled on the Relationships tables of both objects. This allows you to select a Part revision in the Relationships table of either the Part object or in the Relationships table of the ECO object.
- ⌚ Multiple revisions are allowed for the same revision-specific object, each revision with its own row in the Relationships table.
- ⌚ If a relationship is created between a revision-specific object that is configured for revision-specific relationships and any object that is not configured for revision-specific relationships, then the revision selected for the relationship is ALL by default. You cannot select a specific revision for this relationship.
- ⌚ Revision-specific relationships are available to you only if the Agile administrator has configured Agile PLM to enable revision-specific relationship capabilities. The revision-specific columns on the **Relationships** tab (**Revision**, **Change**, **Track Impact** and **Impacted**) must be visible, and you must have the appropriate privileges for those attributes. These revision-specific attributes can be enabled for specific object classes as needed, that is, some object classes may have revision-specific relationships enabled while the remaining object classes do not.
- ⌚ Revision-specific relationships allow you to select a specific revision for a Part object, Document object, or Published Price object in a relationship.

Relationships Tab

By default, the Relationships table for each object class displays the following columns. The Agile administrator may enable additional columns. If you have questions about the configuration of the **Relationships** tabs in your Agile system, see the Agile administrator.

Table 5–4 Relationships tab columns

Default attribute	Description
Criteria Met	<p>If the relationship has a rule, the Criteria Met icon in this column indicates that the criteria specified in the rule has been met.</p> <p>Web Client:</p> <p>?  – Criteria Met</p> <p>?  – Pending</p> <p>? (empty) - Rule not specified</p>
Name	The object name or object number that uniquely identifies the related object.
Description	The description that appears in the Description field of the related object.
Current Status	The current workflow status or lifecycle phase of the related object.
Rule	The rule defined for the relationship. If no rule is defined, this column is blank.
Type	The object type (or subclass) of the related object.

Note: For Design object relationships only, a Version-specific relationship can be created.

Table 5–5 Relationships tab revision-specific attribute columns

Revision-specific attribute	Description
Revision	<p>This attribute enables the association of the relationship with a specific object revision.</p> <p>When this attributes is enabled, the More menu selections Accept New Revisions and Reject New Revisions are enabled.</p>
Change	This read-only attribute shows the change (ECO, MCO, or PCO) associated with the selected revision in the Revision cell. Click the change number to navigate to the change object.
Impacted (icon)	<p>When Track Impact is set to Yes, then an icon appears in this column indicating that the Relationship target object has changed and has a new revision.</p> <p>If the selected revision is Latest, to clear this icon flag, then select the relationship table row and choose More > Accept New Revision or Reject New Revision.</p>
Track Impact	<p>Determines whether or not to track the impact of a new release of the revision-controlled target object.</p> <p>If you have the appropriate privileges, then you can edit the Track Impact cell.</p>

Relationships Tab Views

Use the **View** drop-down list to sort the relationships table rows. See also Using the Table Filter.

Table 5–6 Relationships tab views

View option	Description
Base View (Web Client) All Relationships (Java Client)	Displays all relationship table rows.
Complete	Displays relationships that have a rule specified and the criteria of the rule has been met.
Pending	Displays relationships that have a rule specified and the criteria of the rule has <i>not</i> been met.

Relationship Tab Actions in Web Client

In Web Client, buttons and actions on the **Relationships** tab allow you to add, edit, and remove relationships and relationship rules.

Table 5–7 Relationship tab buttons

Button	Description
Add	<p>Add a relationship to the table by searching for the object you want. See "Adding Relationships to Objects" on page 5-35.</p> <p>You can add a relationship by:</p> <ul style="list-style-type: none"> ▸ Add by search - Search for an object ▸ Add by create - Create a new object ▸ Add a Reference Object - Search an external application for an object and then create an Agile PLM Reference Object that provides access to the object in the external application from the Relationships tab. ▸ Copy and Paste ▸ Drag and Drop
Remove	Removes the selected relationship table rows. See "Removing Relationships" on page 5-37.
Edit Rule	<p>Opens the Relationship Rule edit dialog, which lets you add, edit, or remove a rule.</p> <p>See "Adding a Rule to a Relationship" on page 5-39.</p> <p>See "Editing a Relationship Rule" on page 5-40.</p> <p>See "Removing a Relationship Rule" on page 5-40.</p>
Views	<p>Lets you sort the table by multiple criteria. See "Relationships Tab Views" on page 5-34.</p> <p>As with nearly all Web Client tables, you can define and save your own personal views.</p>
Web Client table edit features	<p>Lets you edit the Relationships table. See "Editing the Relationships Table" on page 5-37.</p> <p>If the Agile administrator has enabled relationship table attributes in addition to the default attributes, you can edit the additional attributes if you have the appropriate privileges. Double-click in an editable cell to begin editing.</p> <p>If relationship table attributes for revision-specific relationships have been enabled, you can edit those attributes if you have the appropriate privileges. See "What are Revision-Specific Relationships?" on page 5-32.</p>

Using the Web Client Relationship Tab Views

The **Relationships** tab uses the Views feature that is available on all Web Client tables.

Agile PLM provides you with four standard preconfigured views; see "[Relationships Tab Views](#)" on page 5-34.

You can create and save personal table views. See "[Table Views](#)" on page 2-45.

Adding Relationships to Objects

You can add objects to the relationships table of any object. The relationship is listed on the **Relationships** tabs of both objects. You must have the appropriate modify privileges for both objects in the relationship: the object to which you are adding the relationship and the related object.

To add objects to the relationships table in Web Client:

1. Navigate to the **Relationships** tab of an object.
2. Click the **Add** menu button and choose one of the following options:
 - ⌵ Choose **By Search** to search for an object. Open the search palette. Execute a quick search to find the objects you want. Double-click to add an object. Press Escape to close the palette.
 - ⌵ Choose **By Create** to create a new object. Select an object type, fill in any required fields, and then click **Add**. The newly created object is added to the table.
 - ⌵ Choose **Reference Objects** to search for an object in an external application and add it as a reference in the relationships table.
 - a. In the Search palette that opens, search for the object and click the name of the object to view it in the corresponding application.
 - b. Click **OK** to add the reference object.

For details about configuring reference objects, see *Agile PLM Administrator Guide*.
3. By the Drag and Drop method:
 - ⌵ Select an object in the left navigation pane. Drag it onto the table and drop it. You can drag and drop from your **My Bookmarks**, **Recently Visited** list, and the **NAVIGATOR** drawer.
4. Copy and Paste
 - ⌵ Copy one or more objects from a table: search results table, BOM table, Where Used table, and so forth. Use **More > Copy** or Ctrl-C to copy the rows.
 - ⌵ Open the object to which you want to add a relationship. Click the **Relationships** tab to display it. Paste the rows by using **More > Paste** or Ctrl-V.

You can also add Problem Reports or Non-Conformance Reports to the **Relationships** tab of any other Agile objects.

Viewing Reference Objects

To view or access a reference object:

1. In the **Relationships** table, click the reference object link.
Reference object rows are indicated with the icon in the relationships table.
2. The external application opens in a new browser window.

Enter a username and password if prompted to do so.

3. The reference object appears in the external application browser window.

To see a quick view of the reference object:

1. Place the cursor over the reference object link.
2. When the **Quick View** callout bubble appears, click **Quick View** to open a quick view palette, a separate popup window.

Selecting a Revision

Note: You can select a specific part, document or price revision if the Agile administrator has enabled revision-specific relationship capabilities. See ["What are Revision-Specific Relationships?"](#) on page 5-32.

If revision-specific relationship capabilities are enabled for only one object in the relationship (for example, enabled for Part objects, but not for ECOs), then the relationship is added to the Relationships table, the Revision defaults to **All**.

If revision-specific relationship capabilities are enabled for both objects in the relationship, then the relationship is added, the default Revision is Latest. The default value is dynamic and will be bumped up whenever a new revision of the related object is released. For example, when the object with the relationship gets a new released revision 1.0, its value will be updated to "Latest-1.0". If you have the appropriate privileges you can select a different revision.

To select a revision for a relationship:

1. Double-click the **Revision** cell that you want to modify.
2. In the drop-down list, select a revision. You can select:
 - ⌵ A specific revision, for example, Introductory, A, B, or C.
 - ⌵ Latest – the relationship applies to the LATEST revision.
 - ⌵ All – the relationship applies to all revisions rather than a specific revision.
3. Click **Save** to save your modifications.

Accepting or Rejecting a New Revision

For revision-controlled objects (Parts, Documents, or Prices) on the **Relationships** tab, the **Impacted** icon is displayed in the relationships table row when **Track Impact** is set to Yes, and a new revision is released.

To accept or reject the new revision:

1. Select one or more table rows that display the **Impacted** icon.
2. In the **More** drop-down menu, choose either **Accept New Revision** or **Reject New Revision**.
3. Click **Save**.

Editing the Relationships Table

With the appropriate privileges, you can edit the nondefault attributes of the relationships table of any object. Default relationship table attributes cannot be edited. For a list of default

relationship table attributes, see ["Relationships Tab"](#) on page 5-33. If no nondefault attributes are enabled for the relationships table you are viewing, the **Edit** button may be disabled.

You cannot add, edit, or remove relationship rules with the relationship table edit feature. For more information about relationship rules, see ["Relationships and Dependencies Between Objects"](#) on page 5-31.

To edit a relationship in Web Client:

1. Open the object you want and click the **Relationships** tab.
2. Double-click in an editable cell.

The table enters edit mode and the table **Save** and **Cancel** buttons become active.

Note: If no nondefault attributes are enabled for the relationships table you are viewing, the table will not enter into edit mode.

3. Make the changes, and click **Save**.

Removing Relationships

When you remove a relationship, it is removed from the **Relationships** tab of the current object and from the **Relationships** tab of the related object. Any rules associated with the relationship are also removed.

To remove a relationship in Web Client:

1. In the table from which you want to remove objects, select the objects you want to remove.
2. Click the corresponding **Remove** button. The rows are removed.

To remove a reference object from the Relationships tab:

1. In the Relationships table, select the reference object rows you want to remove.
2. Click the **Remove** button. The rows are removed.

Note: If the reference object that was removed from the table does not appear on the Relationships tab of any other object, then the reference object is also deleted.

What is a Relationship Rule?

Specifying a rule for a relationship defines the manner in which one Agile object can affect the workflow status of another Agile object. A relationship rule includes a *Source Object*, an *Event*, a *Target Object*, and a *Result*. The format of a relationship rule is shown in the following sentence:

When <Source Object> is <Event>, set <Target Object> to <Result>.

That is, an *Event* in the *Source Object* triggers a *Result* in the *Target Object*.

- ⌘ A *Source Object* can be either a routable object with a workflow (for example, a change order or a project object) or a nonroutable object with a lifecycle phase (for example, a part or a document).
- ⌘ An *Event* is a change in the workflow status or a change in the lifecycle phase of the *Source Object*.
- ⌘ A *Target Object* is always a routable object with workflow statuses.

- ? A *Result* is always a change in the *Target Object's* workflow status.

Here are some examples of relationship rules:

When ECO_100 is Implemented, **set** ECR_334 **to** Closed.

When ECO_565 is Released, **set** NCR_009 **to** Closed.

When Part_945 is Production, **set** Task_Design_Assembly **to** In Process.

When Document_934 is Prototype, **set** ECO_3445 **to** Released.

When Part_D457 is Prototype, **set** Task_Promote_BOM_to_Prototype **to** Complete.

When FileFolder0098 is Concept, **set** Audit_0061 **to** Initiated.

The resulting change in the *Target Object's* workflow status also requires that all other conditions required for the workflow to advance have been met. For example, for a change order to be released, it must pass a release audit. If the relationship rule triggering event occurs, but the change order does not pass the release audit, its workflow status will not change. In a similar manner, if a change order passes its release audit, but the relationship rule triggering event has not occurred, the change order workflow status will not change. In both cases, when all the required criteria are fulfilled and the relationship rule triggering event has occurred, the *Target Object's* workflow status will change.

Note: You cannot define rules for reference objects.

Relationship Rule Guidelines

The following guidelines and restrictions apply to relationship rules:

- ? Rules for revision-specific relationships apply to ALL revisions.
- ? You cannot define a rule for a reference object.
- ? You cannot define a rule for a workflow object if no workflow has been selected for that object. Rules are based on workflow statuses and workflow statuses are defined by each workflow. If a routable object is Unassigned (it has no workflow assigned) then there is no identified list of statuses to select when defining a relationship rule.
- ? Only one rule can be defined for each relationship table row. However, you can add the same object to the relationship table in multiple rows and define a different rule for each row.
- ? If you want two objects to advance through their respective workflows simultaneously, you create relationship entries for each status.
- ? The **Criteria Met** column in the relationship tables indicates that the *Source Object's* triggering event has occurred. If the triggering event is that the *Source Object's* workflow status changes to Status_02, but the workflow status was manually changed to Status_03, skipping over Status_02, then the *Target Object's* event (workflow status change) will not occur. If you remove the relationship row or you remove the relationship rule, then the *Target Object's* event can occur.
- ? The **Criteria Met** field, once checked (the **Complete** icon appears) is not "unchecked" if an object is returned to an earlier status for other reasons.
- ? A relationship rule causes the *Target Object* only to advance in its workflow, never to return to a status it has already left.
- ? A nonroutable object with no workflow, for example, an item, can be a *Source Object* but it cannot be a *Target Object*. You can create a rule between a nonroutable object and a routable object only when the nonroutable object is the *Source Object*.

- 7 You can create a relationship without a rule between two nonroutable objects. Agile PLM will not allow you to create a rule between two nonroutable objects.
- 7 The relationship rule can be defined from the **Relationships** tab of either object.
- 7 You must have the appropriate "modify relationship" privilege for both objects to create a relationship without a rule between two objects. To create a rule between two related objects, you must, in addition, have the appropriate "modify rule" privilege for both objects.

The "modify rule" privilege allows you to specify a routable object as the *Target Object* in a rule. That is, it allows you to specify a rule that triggers a modification (*Result*) in the *Target Object*.

When both objects in a relationship are routable objects, if you do not have "modify rule" privilege for one of the objects in that relationship, then, in any rule you create, that object can be only the *Source Object* (because it will not be modified when the rule criteria is met); it cannot be the *Target Object*.

Note: If there are relationships with rules defined for multiple statuses of a single routable *Target Object*, Agile checks that related events that apply to earlier result statuses have been met before advancing the workflow. For example, for a specific *Target Object*, if there are events defined for both Submitted and Released statuses, and the events for the Released status are satisfied, Agile will not advance the *Target Object's* workflow to Released status until the events for the Submitted status are also satisfied.

Adding a Rule to a Relationship

To add a rule to a relationship in Web Client:

1. On the **Relationships** tab, select the table row of the related object to which you want to add a rule.
2. Click the **Edit Rule** button.

Note: If it is not possible to add a rule to the selected relationship because both objects are nonroutable objects, an error message is displayed on the tab.

3. In the Relationship Rule edit dialog, use the drop-down lists to define the rule.
4. When you are finished, click **Save**.

Editing a Relationship Rule

To edit a rule to a relationship in Web Client:

1. On the **Relationships** tab, select the table row of the related object to which you want to edit a rule.
2. Click the **Edit Rule** button.
3. In the Relationship Rule edit dialog, use the drop-down lists to edit the rule.
4. When you are finished, click **Save**.

Removing a Relationship Rule

To remove a rule to a relationship in Web Client:

1. On the **Relationships** tab, select the table row of the related object to which you want to remove a rule.
2. Click the **Edit Rule** button.
3. In the Relationship Rule edit dialog, click **Remove**.
The rule is removed from the selected relationship.

Relationships in PQM

This is some additional information about relationships as they are used in the PQM solution:

When relationships are created between PQM objects, a blank rule is created for the relationship. You must edit the blank rule to define how you want the PQM objects to affect each other.

- ⌚ When a QCR affects the PSR, that is, when a QCR and PSR are related and the relationship rule follows the format:

When *<QCR source object>* is *<event>*, set *<PSR target object>* to *<result>*

all items from the PSR **Affected Items** tab are displayed on the PSR Items table of the QCR. If the PSR was used to aggregate multiple PSRs, then the related PSRs' affected items are displayed.
- ⌚ When this QCR is affected by a PSR, that is, when the QCR and the PSR are related and the rule follows the format:

When *<PSR source object>* is *<event>*, set *<QCR target object>* to *<result>*.

all items from the PSR **Affected Items** tab and the related PSR's affected items are *not* displayed on the PSR Items table of the QCR.

Deleting Objects

For detailed information about deleting objects, see [Appendix A, "Deleting Agile Objects."](#)

Working with Business Objects in Java Client

This chapter describes working with business objects in Agile Java Client, including the actions of creating, modifying, printing, emailing, and deleting business objects.

Interacting with Agile Objects: Actions and Tabs

Finding and opening Agile objects is a straightforward process: the easiest way is to run a simple search. You can type a word in the **Quick Search** field-on the main toolbar of both clients-that describes the Agile content you are interested in. For example, typing **computer** will return a list of all objects with the word "computer" in their name or description. If you already know an object's ID number, typing it in the **Quick Search** field returns the object.

For more information about finding objects or data in Agile PLM, see [Chapter 8, "Finding Agile Data with Searches."](#)

Once you have found an object that you will want to refer to often, you can bookmark it to return to it easily.

The two main ways of interacting with Agile business objects with an object open are either by using the **Actions** menu, or through the fields and attributes on its various tabs.

More Menu

An important feature for working with Java Client is the **More** menu. In Java Client, right-click anywhere in the opened object to see a shortcut menu with the same commands found in the **More** menu.

On most tabs, if you right-click outside any table rows within the object, that object's main shortcut menu opens (except for the **Changes**, **Quality** and **Where Used** tab). However, on any tab with a table, you can also select a row in a displayed table and right-click, and a shortcut menu for the object referenced in that row opens.

Table 6–1 Java Client More menu

Command	Description
Save As	Creates a new object based on the current object.
Delete	Deletes the object (a "soft delete"). For more information about deleting objects, see Appendix A, "Deleting Agile Objects."
Print	Choose either All Tabs or the tabs you want. The list of tabs changes with the current object's class.
Incorporate and Unincorporate	Available for items: incorporation locks the checkout and check in capabilities of file folders on the Attachments tab of the item. This important capability is available only on the More menu. For more information about incorporating, see the <i>Product Collaboration User Guide</i> .

Table 6–1 (Cont.) Java Client More menu

Command	Description
Add Bookmark	Saves a pointer to the object on your My Bookmarks list.
Send	Opens the address book and lets you select one or more users to send the object to, including a comment. A notification is then sent to the designated users with a link to the object.
Sharing	Opens a page linked to the current object that lets you share the object or delete an existing share. For more information, see " Sharing Objects with Other Users " on page 6-12.
Subscribe or Subscriptions	Allows user to subscribe to receive a notification when certain attributes change. Offers a list of subscriptions for the current object: Lifecycle Phase Change or Status Change, Add File, Delete File, Checkin File, Checkout File, and Cancel Checkout File. See Subscribing to Objects . Note: Subscribe capabilities are not available for Report objects or for User Group objects.
Export	Opens the Export wizard in a browser window.
Process Extensions	Offers a list of currently available process extensions, which have been created by your administrator.
Audit Status	Audits the remaining statuses in the object's workflow to test whether the workflow can advance through those statuses.
Audit Release	Audits the remaining statuses in the object's workflow to test whether the workflow can be released per the existing conditions in the statuses.
View Workflows	Shows eligible workflows for this (routable) object, in visual form. Offers drop-down list to select another workflow to view.
Create Change	Creates a new change order with the open item (part or document) already added to the Affected Items tab.
Create Product Service Report, Create Quality Change Request	Creates a new PSR or QCR with the open item already added to the Affected Items tab.
Create Declaration	Creates a new Declaration with the open item already added to the Affected Items tab.

When you select a row in a table and right-click, the following actions are available:

Table 6–2 Table row right-click shortcut menu actions

Actions Available when Selecting a Table Row	Description
Open, Copy, or Paste	Select a row in a table, and then open the object on the selected tab, or copy the selected tab and paste it into another table.
Print	Select a row in a table and then print the object's selected tab or tabs.
Create Product Service Report, Create Quality Change Request	Creates a new PSR or QCR with the item in the selected row already added to the Affected Items tab.

Object Tabs

Tabs organize the content of Agile objects. A brief list of the most common tabs found in many objects across Agile PLM's solutions follows. The following table gives basic information about tabs that are elaborated on later in this manual and elsewhere in the Agile documentation

set, such as the platform-specific user guides. Some Agile solutions—such as Product Cost Management and Product Portfolio Management—have specialized tabs not listed below.

The *Agile PLM Administrator Guide* describes all the preconfigured business classes with all their default tabs.

Note: Remember that part of Agile PLM's flexibility includes the administrator's ability to rename business classes and subclasses, tabs within objects, and fields within tabs, so some tabs listed below may have a different name within all classes or within a particular class of object that your company works with.

Your ability to see or work with any object or any tab in Agile is governed in large part by your roles and privileges. If you are having trouble opening, seeing, or modifying an object, tab, or field, see the Agile administrator.

Table 6–3 Object tabs

Tab	Description: what information this tab collects	Found in these classes of business objects
"Page One"	<p>The Cover Page tab is the Page One for all routable objects—the Change, PSR, QCR, Transfer Order, Package, and Project base classes—and also RFQ and RFQ Response objects.</p> <p>The Title Block tab is the Page One for all Item and File Folder objects.</p> <p>The General Information tab is the Page One for all remaining (nonroutable) classes.</p> <p>Header links on the Page One of the objects enable the user to quickly navigate to the specific group and update the fields. The Page 2 and Page 3 attributes are also available as header links.</p>	All objects have a "Page One" that uses one of the names to the left.
Page Two and Page Three	Further information about the object. These are added by the administrator as extensions of "Page One." Page Two fields are the same for all objects in the same business object class. Page Three fields are the same for all objects in the same subclass. Both "Page Two" and "Page Three" can be replaced by more specific names.	Depends on how classes have been set up.
History	Summary of actions taken on this object. History is recorded for all objects in your Agile PLM system's database, and shows all actions by users and administrators. The History tab is populated automatically.	All.
Attachments (and Files)	<p>View, copy (get), or print attached files. Attach files and URLs to the current object by adding them to a file folder. Access Viewer to redline attached files (once the object is on an ECO, only from the Redline Attachment table on the Affected Items tab).</p> <p>Note: The Files tab lists all contents of file folder objects; so, an item's Attachments tab lists file folder objects, and file folder objects have a Files tab listing contents. (For more information, see Chapter 11, "Working with File Folders.")</p>	All classes except File Folders (which contain attachment content) and Reports.
Changes	<p>Information about change objects that involve the item object, published price object, file folder object or design object.</p> <p>Pending Changes and Change History tables are the two tables on the Changes tab.</p>	Items, Published Prices, File Folders, and Designs

Table 6–3 (Cont.) Object tabs

Tab	Description: what information this tab collects	Found in these classes of business objects
BOM	All the items that comprise the current part. (Documents may or may not have bills of material, depending on your system settings.) Items on a BOM can be a single item or an assembly of several items.	Items.
Manufacturer	Lists manufacturers that have been approved to supply a particular item. The list identifies the manufacturer part for the current item.	Items & Sourcing s.
Where Used	<p>Lists other objects where the current object is used. The Where Used tab is populated automatically. To open an object listed on the tab, click its Number or Name link; in Java Client, double-click the row.</p> <p>The type of objects that appear on the Where Used tab depends on the current object:</p> <p>Item – Assemblies and manufacturing sites that use the item.</p> <p>Manufacturer – (Item/MPN Where Used tab) Parts and assemblies that use manufacturer parts provided by the manufacturer.</p> <p>Manufacturer Part – Parts and assemblies that use the manufacturer part.</p> <p>File Folder – Objects with attachments contained in the file folder.</p> <p>Discussion – Objects that use the discussion, including RFQs, RFQ responses, activities, and gates.</p>	Items, Manufacturer Parts, Manufacturers, Discussions, File Folders, Declarations.
Affected Items (in PCOs: Affected Prices)	<p>Lists the items that are affected by the current change object. Users with sufficient privileges can use the Affected Items tab to:</p> <ul style="list-style-type: none"> 7 List the items affected by a change and give the affected items of an ECO a pending revision (or <i>rev</i>) 7 Open the affected items 7 Work with BOM, manufacturer, and attachment redlines 7 Affected Prices replaces Affected Items in PCOs. <p>Note: When you add an item to the Affected Items tab of a change, if the site you have selected during the "add" process is not associated with the item, you are prompted to add the site association to the item. That site association remains in effect for that item, even if the change is canceled or if you remove the item from the Affected Items table of the change.</p>	Changes, PSRs, QCRs
Affected Files (in DFCOs)	Lists the files and the design file folders that are affected by the current Design File Change Order (DFCO).	Changes
Workflow (routable objects only)	Shows where the routable object is in the assigned workflow (by using a flowchart), and lists present and past signoff information. Add or remove approvers and observers. Move the object to another status in the workflow.	Changes, PSRs, QCRs, Packages, Transfer Orders, Projects, Declarations
Sites	<p>Shows where each object is being produced at specified manufacturing locations within the company.</p> <p>See the Note for Affected Items in this table.</p>	Items

Table 6–3 (Cont.) Object tabs

Tab	Description: what information this tab collects	Found in these classes of business objects
Escalations	When a workflow status exceeds its escalation time period without a signoff, user groups or individual users can be notified. This tab shows whose escalations (other users) can be signed off by the current user (myself). Note: The settings in a user's Allow Escalation Designation Approval property (on the General Info tab) comes into play.	Users and User Groups
Shares	A user's or user group's Shares tab - it exists for these objects only - lists those objects for which the user/user group has been granted "shared roles" by a different user. The user (or members of the named user group) can then perform actions permitted by the roles for that object only. See "Sharing Objects with Other Users" on page 6-12.	Users and User Groups
Subscriptions	See "Subscribing to Objects" on page 6-12.	Users
Relationships (in projects: Content)	The relationships and dependencies between this object and other routable objects or nonroutable objects (with lifecycle phases). If the current object is a routable object, the Rule column displays the rule that defines how the workflow status or lifecycle phase of other objects affect the workflow progression of the current routable object, or how the workflow progression of the current routable object affects the workflow progression of the related objects. If the current object is a nonroutable object (with lifecycle phases) and the related object is a routable object, you can specify a rule for the relationship, thus creating a dependency between the current nonroutable object and the routable object. A relationship with a rule indicates a routable object whose workflow progression is affected by the lifecycle phase of the current nonroutable object. A relationship with no specified rule does not limit or affect the workflow progression of the related routable object. You can use non-rule relationships to record objects that are somehow related to the current object, but do not have any dependencies with the current object. You cannot specify a rule for a nonroutable object relationship with another nonroutable (lifecycle phase) object. See "Relationships and Dependencies Between Objects" on page 6-14. In Product Portfolio Management objects (Projects), relationships are included on the Content tab. All Project object Content table rows with rules are named <i>deliverables</i> .	All classes (except Actions Items and Reports) For Projects classes, relationships are included on the Content tab and relationships with rules are named <i>deliverables</i> .
Prices	Prices tab of an item includes information about price objects associated with the item, including "priceline" information. Prices tab of a manufacturer part includes information about price objects associated with the manufacturer part.	Items & Manufacturer Parts
Quality	Information regarding PSRs and QCRs created in relation to the item. Those objects have these cross-linked tabs: Related PSR tab for PSRs PSR Items tab for QCRs PSRs tab for Suppliers and Customers	Items

Creating Objects

To create an object, you must be assigned the Create privilege for the kind of object that you want to create. See your Agile administrator.

In Java Client, you can create a business object in these ways:

- ? use the main toolbar **New Object** button menu to choose a base class and a class from the expanded lists
- ? use the **File > New** command to choose a base class and a class from the expanded lists
- ? if you have an object open, use the **File > Save As** command

You can also create some objects as you add them to an Agile table. For example, you can create an item to add it to the **BOM** tab of a parent item or to the **Affected Items** tab of a change.

There are some options to create objects from "within" another object. For example, from within an item, the **Actions** menu includes **Create Change**, **Create PSR**, **Create QCR**, and **Create Declaration**. From within a manufacturer, you can choose **Create Manufacturer Part**.

Once you create an object, that item exists until you delete it. If you create a new object and then decide you do not want to keep it, be sure to delete the object; otherwise, the new object is still in the database and the object's identifier (such as the item number) cannot be reused. See [Appendix A, "Deleting Agile Objects."](#)

Note: Although all characters are supported within Agile PLM, and should not create issues within Agile's clients, it is recommended that you avoid using the following characters when creating objects, due to issues that could potentially arise in integrations or custom applications written on the SDK.

, comma . period (dot) : colon ; semicolon = equal sign

Creating Objects in Java Client Using the New Command

The process for creating new business objects in Java Client involves two main steps: creating an empty object and then filling in the object tabs with information specific to the object.

To create and complete an object in Java Client:

1. Choose **File > New** on the main menu bar or click the **New Object** button on the main toolbar.
2. From the drop-down menu that opens, choose the base class for the business object you want to create. Any base class with two classes expands to offer choices in all possible child classes (thus, **Transfer Order** will offer Content Transfer Order but not Automated Transfer Order). The New dialog box opens.
3. The New dialog specifies the object type and, for some objects, assigns an Autonumber.
The autonumber format and sequence are determined by the Agile administrator. The administrator also determines whether using autonumbers is required or optional.
4. Click **OK**. The new object appears with the **Cover Page**, **Title Block**, or **General Information** tab showing.

Fill in information on the object's tabs, as necessary. Some tabs are completed automatically, such as the **Changes**, **Where Used**, and **History** tabs. You do not enter information on these tabs.

Note: The object is created as of step 4 in the procedure. (In Web Client, objects are created through wizards.) All object-required fields are indicated by the field name displayed in bold type. If you attempt to close the object with any required fields empty, an error message will advise "**You have not completed all required fields. Please complete all fields in bold.**"

Creating an Object Using Save As

Using the Save As feature is a quick way to create an object that is similar to an existing object.

Note: In general, you should not use Save As to create an object in a different class or subclass from the original object. The different classes or subclasses may not have the same tabs or defined fields, and you may lose access to some data in the newly created object.

For example, parts generally have a **BOM** tab. By default, documents do not. When you save a part as a document, you cannot view the part's BOM in the resulting document unless your Agile administrator has configured your system to permit documents to have BOMs.

To create an object using Save As:

1. Select and open an existing business object.
2. Choose **File > Save As**. The Save As dialog appears.
3. The two fields in the Save As dialog box are (object) Type and (Auto)Number. Choose an available object type from the drop-down list, and click the **Autonumber** button for an autonumber or fill in an ID number manually.
4. Depending on the selected object type, the Save As dialog may display additional required fields. Complete any required fields.
5. Click **OK**. The new object is created and opens automatically.
6. Make any appropriate modifications on the tabs of your new object.

If the Agile administrator has set the appropriate preferences, fields in the optional **Page Two** and **Page Three** sections are copied to the new object. For information about the behavior of **Page Two** and **Page Three** fields in your Agile system, see your Agile administrator.

Save As copies data from a field in the existing object to the same field in the new object. If a field or list value in the existing object is not available in the new object, then that field or list value is not copied to the new object.

Note: Because **Page Three** data applies to a specific subclass only, if you use Save As to create a new business object in a different subclass, the **Page Three** data is *not* copied to the new object.

Site Change Order Save As Limitations

You cannot initiate Save As from a non-Site Change Order (SCO) change object to create an SCO object, nor can you initiate Save As from an SCO object to create a non-SCO change object. Because Site Change Orders (SCOs) affect only site-specific information, and other types of changes are not limited to site-specific information (for example, ECOs and MCOs), SCOs can be Save-As-created only from another SCO. The Site Change Order's site-specific only usage makes it incompatible with other change types when using the Save As feature.

Adding Objects to Tables

On Java Client table tabs where you can add objects to the table, the **Add** button presents one or more object choice methods that are appropriate for the type of objects that can be added to that table. For example, when adding users to a user group, clicking the **Add** button displays the address book.

When adding items to a BOM table, the add methods are:

- ? **Create** an item while adding it.
- ? **Search** for an existing item.
- ? **Type in Known Number(s)** of one or more existing objects.
- ? **Add a blank row** to the BOM table that can be filled in later.

Item Addition Rules

Whenever a user adds an item to a BOM or adds an affected item to a change, the user is prompted to respond to a warning message. If an item then happens to violate an "Item Addition Rule," the Agile PLM system knows how to handle it.

These are some item addition rules, that is, the question stemming from a potential violation of the rule:

- ? If there are duplicate items, would you still like to continue?
- ? Some items may not be associated with some sites; would you like to add the association?
- ? If one item does not exist, do you want to use it anyway?
- ? Do you want to add items, whose lifecycle phase is in the warning list, to the BOM?

Modifying Date and Time Fields

You can modify date fields by using the calendar tool, and also by typing in the field.

Using the Calendar to Modify Date Fields

To use the calendar tool:

1. In a date field, click the calendar icon to open the calendar (if it is enabled).
2. Select a date from the calendar and set a time if necessary.

The new date and time are set


Note: The default time format is "12 hours" with am and pm.

Double-clicking the date enters it directly to the field.

3. To switch to a different month or year, click the appropriate **Forward** or **Reverse** button.
4. Optional, with the **Today** button you can reset the date and time to the current date and time.
5. Close the calendar window.
 - ? With the red icon
Closes the calendar without storing the set date and time.
 - ? With the green icon

Closes the calendar and keeps the set date and time.

Figure 6-1 Calendar tool



Manually Modifying Date and Time Fields

To edit the date and time:

1. Select the date and time you want to change.
2. First, enter the new date in the format specified in your user profile (by default, mm/dd/yyyy).
3. Press the Spacebar.
4. Then enter the time in the format specified in your user profile.
This step is optional; if you do not enter a time, by default the time displays midnight in the specified format.
5. Press the Tab key or the Enter key.

To edit just the time stamp:

1. Select the time you want to change.
2. Enter the new time in the hh:mm:ss format.
3. Press the Tab key or the Enter key.

Modifying List Fields

To modify a list field:

1. Click the drop-down list button to display the list entries.
2. Select an entry from the list.

To modify a MultiList field:

1. Click the MultiList select button to display the palette of list entries.
2. Select one or more list entries:
 - Double-click a row to add the entry to the **Selected** list.

- Or, select a row, and use the arrow key to move the entry into the **Selected** list.
- 3. Press **OK** to close the palette.

If the attribute for the list field includes a large number of list entries, the Agile administrator may choose to configure Agile PLM to display the editable list with search display.

To modify a search display list field:

Note: The MultiList button also opens the Search palette.

1. Click the MultiList select button to display the search palette.
2. In the search palette, enter a search string and click the **Search** button.
3. In the search results table, double-click a row to add the entry to the **Selected** list.
Or, select a row, and use the arrow key to move the entry into the **Selected** list.
4. Press **OK** to close the palette.

Note: For list fields that contain more than 250 list entries, The Search palette is displayed.

Printing Object Tabs

You can print information from any tabbed object.

Attachments are printed from their native applications or the Viewer. For more information, see ["Printing Attachment Files"](#) on page 10-14.

To print an object:

1. Open the object.
2. To print all tabs, click the **Print** button in the object window. To print a single tab only, click the down arrow next to the **Print** button and select the appropriate option.

Note: If any of the tabs are blank, that is, containing no visible fields, you cannot print all tabs. Instead, select individual tabs to print.

3. If you select the BOM, the **BOM Printing Option** dialog box appears.
4. Select the levels to print, or select the **All depth** check box to print all levels.
5. Click **OK**.

A preview of the printout appears in a separate dialog box.

6. To print, click the **Print** button in the Print dialog box.

Emailing Objects

You can email any Agile object to another user listed in the Agile address book. Email is sent to the email address specified in the Agile user profile. The email contains a URL that links to the mailed object, and the recipient can click the URL to view the object in Agile PLM.

1. The Agile administrator sets your user profile **Preferred Client** preference to determine whether you receive links to Web Client or Java Client.

To email an Agile object:

1. Open the object.
2. Choose **File > Send**, or click the **Send** button.
3. In the **Send** dialog box that opens, click **To** to open the address book.
4. In the address book, use the right arrow to move names to the **Recipients** list, and click **OK**.

For information about using the address book, see ["Selecting Users and User Groups from the Address Book"](#) on page 3-15.

5. Enter any comments in the **Comment** field.
6. Click **Send** to mail the object.

Quick Access to Objects, Files, and Searches

You can generate quick access URLs that provide direct pointers to either Agile objects or to Agile attachment files.

These quick access URLs can be pasted into other applications or files such as spreadsheet files, word processing files, a company Intranet web page or WIKI page, or into an email.

For information about quick access to Agile objects using quick access URLs, see:

- ? ["Agile-Generated Quick Access Object Smart URLs"](#) on page 5-24
- ? ["Using Quick Access Object Smart URLs"](#) on page 5-24
- ? ["Formats for User-Generated Smart Object URLs"](#) on page 5-24

For information about quick access to attachment files using attachment quick access URLs, see:

- ? ["Smart URL Quick Access to Files"](#) on page 10-38

For information about quick access to searches using search quick access Smart URLs, see:

- ? ["Smart URL Quick Access to Searches"](#) on page 8-73

Discussion Objects

A Discussion can be created from the main toolbar **Create** menu, or from a business object's **Discussions** tab. Discussions are integrated into the Product Portfolio Management solution, and are also applicable to the Product Cost Management solution; however, discussions can be created and modified in the same manner as any Agile PLM object, and their utility can be applied to the other Agile PLM solutions, Product Collaboration, Product Governance & Compliance, and Product Quality Management.

Discussions are always created and viewed in Web Client. To access a discussion while using Java Client, you can search to locate an existing discussion and open the object, which will open the Web Client. Or you can simply open the Web Client and proceed from there, including creating discussions.

The following objects classes have a **Discussions** tab: Sourcing s, Request for Quote, RFQ Responses, Activities, and Gates. See *Product Portfolio Management User Guide* and *Product Cost Management User Guide* for information about using discussions in those solutions.

For more information about Discussions, refer to the section ["Discussion Objects"](#) on page 5-27.

Sharing Objects with Other Users

Sharing lets you grant one or more of your roles to another Agile user or user group for specific objects. The capability to share a given role requires being assigned the Grant privilege specific to that object. You can share only your assigned roles, that is, the roles that are listed in the **Roles** field on the **General Info** tab of your user profile, and the roles that are listed in the **Roles** field on the **General Info** tab of any groups of which you are a member.

You cannot share roles that have been shared with you by another user, and you cannot share roles that have been shared with a user group to which you belong.

When a role has been shared with a user (or members of a user group), each user can then perform actions permitted by the roles for that object only; a user does not "acquire" the role in any permanent or far-reaching way.

A user's or user group's **Share** tab lists those objects for which the user has been granted "shared roles" by a different user. Click the **Share** tab in your user profile to see objects being shared with you and what role(s) allow and define your interaction with each object. If you belong to a user group, you can see objects being shared with you through the user group by opening the group object and clicking the **Share** tab.

To share an object:

1. Display the object.
2. Right-click anywhere in the object and choose **Sharing**.
Or, use the **More** menu and choose **Sharing**.
The Share <named object> window appears.
3. Click the **Add** button. The Add Access Control Entry dialog box appears.
4. In the **Users** field, click the **Check Names** icon button; the Address book appears. Select the **Names** or **Groups** tab, and move those you want to the **Recipients** list.
5. Click **OK**. All users in the Selected Users list will appear in the Users field.
6. Now select an appropriate role or roles for your chosen users to have available for this object.
7. Click **OK**. The Share <named object> window appears again displaying the selected users and selected roles.
8. Click **Close**. This returns you to the original object. Click **Refresh**.

Note: When you right-click and choose **Sharing**, the Share window now shows you the complete list of users who have access to this object and the roles you specified.

Subscribing to Objects

Subscribing to an object sets you up to receive notification of events that happen to that object. For example, you might subscribe to a change to be notified when the change is released, or you might subscribe to an attachment to be notified when the attachment is checked in. You can also be notified when specified fields are modified. You select the events about which to be notified. To be notified when certain fields change, you specify those fields.

You must have the Subscribe privilege for a specific object class to be able to subscribe to that class's objects. See your Agile administrator to be assigned additional privileges.

Note: Subscribe capabilities are not available for Report objects or for User Group objects.

On the **Subscription** tab of your user profile, you can view the objects to which you have subscribed. To cancel or remove a subscription, select the object, and click **Remove**.

Subscription events trigger two types of notifications: Email and Inbox. Email notifications are sent only if your Receive Email Notification preference is set to Yes; this field is on the **Preferences** tab of your User Profile. The ability to edit user information is determined by your privileges.

Subscribing to an Item or Price Revision

It is possible to subscribe to an item revision change and a price revision change. Since you cannot subscribe to a specific status change (for example, changed to Released) for a change that increments the revision of the Item (an ECO) or the Price object (a PCO), subscribing to the object itself-the part, document, or price-is the way you can be notified that the revision of the object has been modified by the release of an ECO or PCO.

Subscribing to Attachments by Using the File Folder

To be notified of changes to a file folder, subscribe to its "check-in" events. The version number of File Folder objects automatically increments every time they are checked in. However, it is not possible to subscribe to file folder versions, which work differently than item revisions. So, subscribing to a file folder's Check-ins is the way you can be notified that the file folder has been altered; file folders are not subject to changes (objects from the various change classes).

Subscribing to Objects

To subscribe to an object:

1. Display the object.

Note: Subscribe capabilities are not available for Report objects or for User Group objects.

2. Right-click the object and choose **Subscribe**.

Or, use the **More** menu and choose **Subscribe**.

3. Indicate whether you want to be notified when the subscribed object is modified by selecting the appropriate **Subscriptions** check boxes. You can select one or more:

- ? Lifecycle Phase Change (or Status Change if it is a routable object)
- ? Field Change

Select from the displayed list of fields. Your Agile administrator determines which fields are available for subscription.

- ? Revision Change (items and prices)
- ? Add File
- ? Delete File
- ? Checkin File
- ? Checkout File

- ? Cancel Checkout File
 - ? Get File
Notifies when Get File action is performed in Web Client.
 - ? View File
Notifies when View File action is performed in Web Client.
 - ? Open File
Notifies when Open File action is performed in Web Client.
4. Click **Save**. A message indicates that your subscription was saved.

Subscription in Product Portfolio Management

The events you can subscribe to vary per object. Product Portfolio Management has the following Activity-specific subscription events that do not apply to other objects. You can subscribe to actions related to:

- ? Discussions
- ? News
- ? Action Items
- ? Schedule
- ? Cost
- ? Health

The **Apply to all levels below** check box in activities and gates "push" a subscription to all subordinate objects. If you subscribe to an activity that has a schedule and select this check box, you will automatically subscribe to all of the activity's projects, phases, and tasks (that is, any object created in the preconfigured subclasses of Activities class). Because **Page Two** and **Page Three** fields can be defined differently for projects, phases, and tasks, any of the attributes that do not apply are ignored.

Relationships and Dependencies Between Objects

This section includes the following topics:

- ? ["What are Relationships?"](#) on page 6-15
- ? ["Relationships Tab"](#) on page 6-15
 - ["Relationships Tab Views"](#) on page 6-16
 - ["Relationship Tab Actions"](#) on page 6-16
 - ["Using the Table Filter"](#) on page 6-17
- ? ["Adding Relationships to Objects"](#) on page 6-18
- ? ["Editing the Relationships Table"](#) on page 6-18
- ? ["Removing Relationships"](#) on page 6-18
- ? ["What is a Relationship Rule?"](#) on page 6-19
 - ["Relationship Rule Guidelines"](#) on page 6-19
 - ["Adding a Rule to a Relationship"](#) on page 6-20
 - ["Editing a Relationship Rule"](#) on page 6-21

- ["Removing a Relationship Rule"](#) on page 6-21
- ["Relationships in PQM"](#) on page 6-21

What are Relationships?

You can associate objects to each other by using the ["Relationships Tab"](#) on page 6-15

Relationships tab. A relationship between two Agile objects is bi-directional and is displayed on the **Relationships** tab of both objects.

Note: In Agile PPM, relationships are called *deliverables* and are managed on the PPM object **Contents** tab. For more information about the PPM **Contents** tab, see *Agile Product Portfolio Management User Guide*.

Specifying a rule for a relationship defines how the related Agile objects affect each other. For example, you can define a relationship rule so that ECO_100 affects ECR_250. When ECO 100 reaches the Implemented status, ECR_250 is promoted to the Complete status automatically.

Note: Rules are optional; you can create a relationship between two objects without specifying a rule.

A relationship is created when you add an object to a table in the **Relationships** tab of another object. The classes of objects that can reference each other on a **Relationships** tab are:

- All object classes, except Reports and Action Items.
- For Agile PPM Projects classes, relationships are named *deliverables* and are included on the **Content** tab.

The Agile administrator configures the Agile PLM system to enable the **Relationships** tab for each object class, making it visible. If you find that you want to create a relationship between objects and those tabs are not visible, see the Agile administrator.

Once you create relationships between objects, you can also create an advanced search for such relationships. See ["Relationship Searches"](#) on page 8-55.

A relationship without a rule is a simpler, less dynamic instance of object-to-object relationship; it simply lists references to other objects. It can be thought of as "bi-directional" information, because relationships without rules do not trigger events.

Relationships Tab

By default, the Relationships table for each object class displays the following columns. The Agile administrator may enable additional columns. If you have questions about the configuration of the **Relationships** tabs in your Agile system, see the Agile administrator.

Table 6–4 Relationships tab default attributes


Default attribute	Description
Criteria Met	<p>If the relationship has a rule, the Criteria Met icon in this column indicates that the criteria specified in the rule has been met.</p> <p>Java Client:</p> <p>–  – Criteria Met</p> <p>– (empty) – pending or rule not specified</p>

Table 6–4 (Cont.) Relationships tab default attributes

Default attribute	Description
Name	The object name or object number that uniquely identifies the related object.
Description	The description that appears in the Description field of the related object.
Current Status	The current workflow status or lifecycle phase of the related object.
Rule	The rule defined for the relationship. If no rule is defined, this column is blank.
Type	The object type (or subclass) of the related object.

Note: For Design object relationships only, a Version-specific relationship can be created.

Relationships Tab Views

Use the **View** drop-down list to sort the relationships table rows. See also Using the Table Filter.

Table 6–5 Relationship tab views

View option	Description
All Relationships	Displays all relationship table rows.
Complete	Displays relationships that have a rule specified and the criteria of the rule has been met.
Pending	Displays relationships that have a rule specified and the criteria of the rule has <i>not</i> been met.
Rule Not Specified	Displays relationships that do not have a rule specified.

Relationship Tab Actions

The buttons on the **Relationships** tab allow you to add, edit, and remove relationships and relationship rules.

Table 6–6 Relationship tab actions

Button	Description
Edit Relationship	Lets you edit the selected rows. See "Editing the Relationships Table" on page 6-18. If your Agile administrator has enabled relationship table attributes in addition to the default attributes, you can edit the additional attributes if you have the appropriate privileges.
Add > Search	Adds a relationship to the table by searching for the object you want. See "Adding Relationships to Objects" on page 6-18.
Add > Create	Adds a relationship to the table by creating a new object. See "Adding Relationships to Objects" on page 6-18.
Remove Relationship	Removes the selected relationship table rows. See "Removing Relationships" on page 6-18.
Edit Rule	Edits the rules in the selected relationship table rows. See "Editing a Relationship Rule" on page 6-21.

Table 6–6 (Cont.) Relationship tab actions

Button	Description
Add Rule	Adds a rule to the selected row by opening the Relationship Rule dialog for you to specify a rule. See "Adding a Rule to a Relationship" on page 6-20.
Remove Rule	Removes the rules from the selected relationship table rows. See "Removing a Relationship Rule" on page 6-21.
Show Filter Hide Filter	Opens the filter tool, which lets you sort the relationships table by multiple criteria. If the filter tool is presently displayed, clicking this button hides the filter tool. See "Using the Table Filter" on page 6-17.

Using the Table Filter

The **Relationships** tab includes a table filter.

The **Show Filter** and **Hide Filter** button toggles the display of the table filter. The table filter lets you define filter criteria based on any column in the table. You can define multiple filter criteria, which are combined in an AND search of the table rows.

For example, you can filter for relationships whose **Description** column includes the word **marketing** and the **Rule** column is **Not Null** (the relationship has a rule).

The format of each filter criteria row is similar to an Agile search criteria:

<attribute> is <Match If Operator> <value to match>

To use the Table filter:

1. On the **Relationships** tab, click **Show Filter** to display the **Filter:** criteria.
2. In the first filter drop-down list, labeled **--Select an Attribute--**, choose from a list of the columns in the assignments table.
3. In the next drop-down list, choose a Match If operator. The list of available Match If operators depends on the attribute type you chose as the **--Select an Attribute--** drop-down list.

For more information, see ["Search Operators and Attribute Types"](#) on page 8-39.

4. In the remaining field, enter the filter values.
 - ⌵ To add a filter criteria row, click the **Add Row** at the end of the row. A filter criteria row is added to the display.
 - ⌵ To delete a filter criteria row, click the **Delete Row** at the end of the row. The row is deleted.
5. Click **Apply** to filter the relationships table. Only relationships that match your filter criteria are displayed.
6. To define different set of filter criteria, click **Clear** to clear the criteria and begin again.

Adding Relationships to Objects

You can add objects to the relationships table of any object. The relationship is listed on the **Relationships** tabs of both objects. You must have the appropriate modify privileges for both objects in the relationship: the object to which you are adding the relationship and the related object.

To add a relationship to an object:

1. Go to the **Relationships** tab of the object.
2. To add by search, click the **Add** button drop-down list and select **Search**.
 - a. In the Add Relationship dialog, choose a search method:
 - * Enter the value to search for and click **Search** to perform a quick search.
 - * Define an advanced search.
 - * Run a saved search.
 - * Select a bookmarked or recently visited item (Shortcuts).
 - b. In the search results, select the objects you want and move them to the Select Related Objects list.
 - c. When you are finished, click **OK**. All the objects in the Selected Related Objects list are added to the relationships table.
3. To add by creating a new object, click the **Add** button drop-down list and select **Create**.
 - a. In the New dialog, select a type from the **Type** drop-down list.
 - b. If appropriate, enter an object number and complete any required fields.
 - c. Click **OK**. The new object is added to the relationships table.

Editing the Relationships Table

With the appropriate privileges, you can edit the nondefault attributes of the relationships table of any object. Default relationship table attributes cannot be edited. For a list of default relationship table attributes, see ["Relationships Tab"](#) on page 6-15. If no nondefault attributes are enabled for the relationships table you are viewing, the **Edit** button may be disabled.

Note: You cannot add, edit, or remove relationship rules with the relationship table edit feature. For more information about relationship rules, see ["Relationships and Dependencies Between Objects"](#) on page 6-14.

To edit a relationship:

1. Open the object you want and click the **Relationships** tab.
2. In the table, select the rows you want to edit.
3. Click the **Edit** button. The rows are in edit mode.
4. Make the changes, and click **Save**.

Removing Relationships

When you remove a relationship, it is removed from the **Relationships** tab of the current object and from the **Relationships** tab of the related object. Any rules associated with the relationship are also removed.

To remove a relationship:

1. In the table from which you want to remove objects, select the object that you want to remove.
2. Click the corresponding **Remove Relationships** button. You are prompted to confirm your choice.

What is a Relationship Rule?

Specifying a rule for a relationship defines the manner in which one Agile object can affect the workflow status of another Agile object. A relationship rule includes a *Source Object*, an *Event*, a *Target Object*, and a *Result*. The format of a relationship rule is shown in the following sentence:

When <Source Object> is <Event>, set <Target Object> to <Result>.

That is, an *Event* in the *Source Object* triggers a *Result* in the *Target Object*.

- 7 A *Source Object* can be either a routable object with a workflow (for example, a change order or a project object) or a nonroutable object with a lifecycle phase (for example, a part or a document).
- 7 An *Event* is a change in the workflow status or a change in the lifecycle phase of the *Source Object*.
- 7 A *Target Object* is always a routable object with workflow statuses.
- 7 A *Result* is always a change in the *Target Object's* workflow status.

Here are some examples of relationship rules:

When ECO_100 is Implemented, set ECR_334 to Closed.

When ECO_565 is Released, set NCR_009 to Closed.

When Part_945 is Production, set Task_Design_Assembly to In Process.

When Document_934 is Prototype, set ECO_3445 to Released.

When Part_D457 is Prototype, set Task_Promote_BOM_to_Prototype to Complete.

When FileFolder0098 is Concept, set Audit_0061 to Initiated.

The resulting change in the *Target Object's* workflow status also requires that all other conditions required for the workflow to advance have been met. For example, for a change order to be released, it must pass a release audit. If the relationship rule triggering event occurs, but the change order does not pass the release audit, its workflow status will not change. In a similar manner, if a change order passes its release audit, but the relationship rule triggering event has not occurred, the change order workflow status will not change. In both cases, when all the required criteria are fulfilled and the relationship rule triggering event has occurred, the *Target Object's* workflow status will change.

Note: You cannot define rules for reference objects.

Relationship Rule Guidelines

The following guidelines and restrictions apply to relationship rules:

- 7 You cannot define a rule for a reference object.
- 7 You cannot define a rule for a workflow object if no workflow has been selected for that object. Rules are based on workflow statuses and workflow statuses are defined by each workflow. If a routable object is Unassigned (it has no workflow assigned) then there is no identified list of statuses to select when defining a relationship rule.
- 7 Only one rule can be defined for each relationship table row. However, you can add the same object to the relationship table in multiple rows and define a different rule for each row.
- 7 If you want two objects to advance through their respective workflows simultaneously, you create relationship entries for each status.

- 7 The **Criteria Met** column in the relationship tables indicates that the *Source Object's* triggering event has occurred. If the triggering event is that the *Source Object's* workflow status changes to Status_02, but the workflow status was manually changed to Status_03, skipping over Status_02, the *Target Object's* event (workflow status change) will not occur. If you remove the relationship row or you remove the relationship rule, the *Target Object's* event can occur.
- 7 The **Criteria Met** field, once checked (the **Complete** icon appears) is not "unchecked" if an object is returned to an earlier status for other reasons.
- 7 A relationship rule causes the *Target Object* only to advance in its workflow, never to return to a status it has already left.
- 7 A nonroutable object with no workflow, for example, an item, can be a *Source Object* but it cannot be a *Target Object*. You can create a rule between a nonroutable object and a routable object only when the nonroutable object is the *Source Object*.
- 7 You can create a relationship without a rule between two nonroutable objects. Agile PLM will not allow you to create a rule between two nonroutable objects.
- 7 The relationship rule can be defined from the **Relationships** tab of either object.
- 7 You must have the appropriate "modify relationship" privilege for both objects to create a relationship without a rule between two objects. To create a rule between two related objects, you must, in addition, have the appropriate "modify rule" privilege for both objects.

The "modify rule" privilege allows you to specify a routable object as the *Target Object* in a rule. That is, it allows you to specify a rule that triggers a modification (*Result*) in the *Target Object*.

When both objects in a relationship are routable objects, if you do not have "modify rule" privilege for one of the objects in that relationship, in any rule you create, that object can be only the *Source Object* (because it will not be modified when the rule criteria is met); it cannot be the *Target Object*.

Note: If there are relationships with rules defined for multiple statuses of a single routable *Target Object*, the system checks that related events that apply to earlier result statuses have been met before advancing the workflow. For example, for a specific *Target Object*, if there are events defined for both Submitted and Released statuses, and the events for the Released status are satisfied, the system will not advance the *Target Object's* workflow to Released status until the events for the Submitted status are also satisfied.

Adding a Rule to a Relationship

To add a rule to a relationship:

1. On the **Relationships** tab, select the table row of the related object to which you want to add a rule.
2. Click the **Add Rule** button.

Note: If the **Add Rule** button is disabled, it is not possible to add a rule to the selected relationship because both objects are nonroutable objects.

3. In the Relationship Rule dialog, use the drop-down lists to define the rule.
4. When you are finished, click **OK**.

Editing a Relationship Rule

To edit a rule to a relationship:

1. On the **Relationships** tab, select the table row of the related object to which you want to edit a rule.
2. Click the **Edit Rule** button.
3. In the Relationship Rule dialog, use the drop-down lists to edit the rule.
4. When you are finished, click **OK**.

Removing a Relationship Rule

To remove a rule to a relationship:

1. On the **Relationships** tab, select the table row of the related object to which you want to remove a rule.
2. Click the **Remove Rule** button.
3. You are prompted to confirm your choice.

Relationships in PQM

This is some additional information about relationships as they are used in the PQM solution:

Important: When relationships are created between PQM objects, a blank rule is created for the relationship. You must edit the blank rule to define how you want the PQM objects to affect each other.

- ⌘ When a QCR affects the PSR, that is, when a QCR and PSR are related and the relationship rule follows the format:

When *<QCR source object>* is *<event>*, set *<PSR target object>* to *<result>*

all items from the PSR **Affected Items** tab are displayed on the PSR Items table of the QCR. If the PSR was used to aggregate multiple PSRs, then the related PSRs' affected items are displayed.

- ⌘ When this QCR is affected by a PSR, that is, when the QCR and the PSR are related and the rule follows the format:

When *<PSR source object>* is *<event>*, set *<QCR target object>* to *<result>*.

all items from the PSR **Affected Items** tab and the related PSR's affected items are *not* displayed on the PSR Items table of the QCR.

Deleting Objects

For detailed information about deleting objects, see [Appendix A, "Deleting Agile Objects."](#)

Working with Agile Reports

This chapter provides basic information about Agile Reports and how to use them. Refer to the appropriate Agile PLM solution user guide for information about specific reports for each solution. For a list of Agile PLM solutions, see ["Overview of the Agile PLM Suite"](#) on page 1-2.

About Reports

Reports provide you with the basic information you need to analyze your business processes. By accessing and summarizing this information in a meaningful way, reports provide an insight into your business processes and can help guide better-informed decisions. Agile PLM provides a robust reporting platform that lets you:

- Measure and monitor business performances using standard out-of-the-boxes reports. These standard reports capture the best practices in product lifecycle management business processes.
- Configure reports with Agile's custom reporting to obtain the specific information you need.
- Use a single point of access to all relevant reports—even those developed outside of the Agile PLM application—through Agile's external reporting capability.

Types of Reports

Agile PLM provides the following types of reports:

Table 7–1 *Agile PLM report types*

Report type	Descriptions
Standard Reports	<p>Standard reports provide you with the information you commonly need to analyze your business processes. You select predefined criteria and specify the results you want.</p> <p>Each solution has its own set of reports. The user guides describe specific reports.</p> <p>For more information, see "Working with Standard Reports" on page 7-12.</p>

Table 7–1 (Cont.) Agile PLM report types

Report type	Descriptions
Custom Reports	<p>You can create custom user—specific or company—specific reports directly within Agile. You define your query using the Query Definition feature, which is similar to an Advanced Search. The custom reports provide a high level of flexibility. You can select which objects to report on, define the filtering criteria, and specify report output.</p> <p>For more information, see "Working with Custom Reports" on page 7-13.</p>
External Reports	<p>You can create reports outside of Agile using any third-party solution, such as SDK or other tools. You can then create linked access directly within Agile to launch those external reports. This is accomplished through configuring process extensions in <i>Agile Administrator</i> and adding URLs.</p> <p>For more information, see "Working with External Reports" on page 7-17 and see <i>Agile PLM Administrator Guide</i>.</p>

How Your Roles and Privileges Affect Reports

The reports that you are allowed to manage or run, and the content of those reports, are affected by the privileges assigned to you, for both business objects and report objects.

You can create, view, edit and delete reports depending on the roles and privileges assigned to you. To run a report on a particular type of object, a user must be granted the following privileges:

- Business object privileges

If you do not have the Discovery privilege for a given business object, you cannot include that object in a report. Parts for which you do not have the Discovery privilege are displayed in the same way as they are displayed on BOMs.

All the Discovery privileges that are set up for your Agile content will be observed when you run a report with that content, including all Discovery-related SmartRule settings and warnings that the Agile administrator has specified. For more information about Discovery privilege and SmartRules, see *Agile PLM Administrator Guide*.

Attachment thumbnails are not support for reports.

- Report object privileges for standard reports

To run and view standard reports, you must have Run Report, Discover, and Read privileges for the standard report you want to run. Agile supplies some predefined roles that provide the ability to use specific types of business objects and to run standard reports relating to those business objects. For example, depending on your assigned roles, you may be able to run standard reports in the Products Reports folder, but not standard reports in the Quality Reports folder.

- Report object privileges for custom reports

In addition to Run Report, Discover, and Read privileges, custom reports require additional privileges: Create, Delete, Modify. The Undelete, SaveAs and Send privileges provide additional custom report capabilities.

- Report management privileges

To modify and delete report schedules and layouts, or to create and delete global reports folders, you need the Manage Report privilege.

To manage Static Template framework you need the Manage Report Templates privilege along with the Administrator and Manage Report privileges. In addition to performing the static template management you can also Create, Edit, Remove, Get, and Replace template files.

The Oracle Agile-provided predefined roles Report User and Report Manager contain the privileges you need to work with custom reports.

Note: In addition to assigning Oracle Agile-provided predefined roles, the Agile administrator can create customized roles for your company. Your assigned roles (either predefined roles or customized roles) determine which types of standard reports you can run and whether you are able to create and run custom reports.

For more information about the privileges that affect reports or about roles and predefined roles, see *Agile PLM Administrator Guide*. If you have questions about your assigned roles and privileges or about your ability to run reports, contact the Agile administrator.

General Info Tab

The **General Info** tab contains the general information about the reports. It has the following fields by default; the Agile administrator may have modified the fields:

- 7 **Name** – the name of the report.
- 7 **Report Type** – indicates the report type (subclass) for each class of reports.
 - **Standard Report Type** – indicates the standard report type, either Standard or Administrator.
 - **Custom Report Type** – indicates the custom report type (subclass). The default is **Custom Report**; your Agile administrator may define additional custom report types.
 - **External Report Type** – indicates the external report type (subclass). The default is **External Report**; your Agile administrator may define additional external report types.
- 7 **Description** – text that describes the report.
- 7 **Folder** – when the General Info tab is in edit mode, click the **Launch Palette** button to specify the report folder location. You can choose to share or not share the report folder location with users.
- 7 **Query Definition** – (Custom Reports only) lets you define criteria on which to base the search.
- 7 **Process Extension** – (External Reports only) a drop-down list of Process Extensions that are set by your administrator.
- 7 **Lifecycle Phase** – the lifecycle phase of the report: Active or Inactive.
 - Custom Report – the lifecycle phase is Inactive if the report cannot be executed because it does not have a query defined or a layout defined yet.
 - External Report – the lifecycle phase is Inactive if no Process Extension is defined, and the report cannot be executed.
- 7 **Create Date** – the date the report was created.
- 7 **Modified Date** – the date the report was last saved.

- ? **Create User** – the name of the user who created the report. This field is blank on standard reports.

This tab has the following buttons **standard**:

- ? **Edit** – appears when the **General Info** tab is not in edit mode. To edit the **General Info** tab, click **Edit**.

Custom reports include the following **General Info** tab edit variations:

- **Edit Information** – appears when the custom report **General Info** tab is not in edit mode and you place the pointer over the **Edit** button. To edit the **General Info** tab, click **Edit Information**.
- **Edit Query** – appears when the custom report **General Info** tab is not in edit mode. To edit the query, click **Edit Query**. Make any changes to the query on the Define Query dialog. To save changes that you made on the Define Query dialog, click **Save**.
- ? **Save** – appears when the **General Info** tab is in edit mode. To save the changes that you made to the tab while it was in edit mode, click **Save**.
- ? **Cancel** – appears when the **General Info** tab is in edit mode. To undo the changes that you made to the tab while it was in edit mode, click **Cancel**.

You can use the **Actions** menu on the **General Info** tab to perform various actions on the standard report. These commands are **Bookmark**, **Save As**, **Delete**, **Copy URL to Clipboard**, **Send**, and **Sharing**.

For more detailed information about bookmarking and other commonly used functions, see [Chapter 2, "Navigating in Agile Web Client."](#)

Layout Tab

Some standard reports do not include a **Layout** tab; the layout is predefined for you. For example, the IP Transfer does not include a **Layout** tab.

Use the **Layout** tab to add or modify a standard report or a customized report layout with the fields your business requires in the required order.

To create a layout, click **Add**.

To delete a layout, select the appropriate row, and click **Remove**.

To modify a layout, click the layout name link to open the layout definition palette.

To edit the information on the **Layout** tab, double-click an editable table cell and use the Web Client table editing features.

- ? Standard report layouts

Each standard report that includes a **Layout** tab which has a default layout. If you have the appropriate privileges, you can edit the default layout.

You can create layouts for standard reports that are available only to you (personal layouts), or you can make the layouts available to all users (global layouts).

To edit the layout fields, click the layout name link to open the layout definition palette. On the layout **Format** tab, you can select fields from the **Hidden Fields** list. Some standard report layouts allow you to select values for a main heading and an additional subordinate heading. For more information, see ["Editing Standard Report Layouts"](#) on page 7-9.

- ? Custom report layouts

You can use the custom report default layout to create a new custom report. You can create layouts for custom reports that are available only to you (personal layouts) or you can make layouts available to all users (global layouts).

To edit the layout fields, sorting and grouping, click the layout name link. On the layout definition **Format** tab, you can select fields from the **Hidden Fields** list. You can change the filter criteria on the layout definition Sort tab. For more information, see "[Creating Custom Report Layouts](#)" on page 7-6.

The **Layout** tab contains the following buttons:

- ? Web Client table editing features – lets you edit the attributes that appear in the Layout table: name, access, paper size, and orientation. Double-click any editable cell to begin editing.
- ? **Remove** – deletes the layouts you have selected.
- ? **Add** – lets you create a layout using the **Add Layout** palette.

The **Layout** tab has the following fields by default; your Agile administrator may have modified the fields:

- ? **Name** – the name of the given layout.
- ? **Access** – indicates whether the layout is available to all users (Global) or only to you (Personal).
- ? **Paper Size** – the size of the paper the report will be printed on, such as Legal or Letter.
- ? **Orientation** – the page orientation: Landscape or Portrait.
- ? **Owner** – the name of the user who created the report.

To edit the Layout tab table:

1. Display the **Layout** tab.
2. Double-click any editable cell. The table is edit mode.
3. In the Name, Access, Paper Size, and Orientation fields, make the desired modifications. You can use the Fill commands in the **More** menu.
4. Click **Save**.

Note: External reports do not have a **Layout** tab. The third-party solution that generates the report also defines the report layout. If you have questions about external reports on your Agile PLM system, contact your Agile administrator.

Note: When attributes from Title Block, BOM, Manufacturers, and Attachments tabs for either Parts or Documents class are enabled, they are treated as enabled for either Parts or Documents. To make sure they are disabled, users must disable for both Parts and Documents. For example, enabling Parts.BOM's itemList11 enables it for Documents.BOM's itemList11. To disable itemList11, it must be disabled for both Parts.BOM and Documents.BOM.

This is not the same for Page Two and Page Three attributes, as they are treated differently and will display separately on the layout's Format tab.

Creating Standard Report Layouts

Use the **Layout** tab **Add** command to create a new layout for a standard report.

About Standard Report Layouts with Multiple Headers

Some standard report layouts include two headings in both the **Hidden Fields** list and in the **Displayed Fields** list. The values under the first header are field attributes of the object the report is intended to locate. The values under the second header are field attributes of objects that are subordinate to the report object. For example, in layouts for the Change Activity report, the values under **Main Header Attributes** are fields of the change objects upon which Agile PLM is reporting. The values under the **Affected Items** header are fields of the affected items of each change that appears in the report.

When you run the Change Activity report, each change is listed in its own row. Under each change row are rows with a different background color that list each of the affected items of the change; these affected items appear on the **Affected Items** tab of the change object. In a similar manner, the Item Manufacturers report has a header for item field attributes and a subordinate header for field attributes of the manufacturer parts that are listed on the item's **Manufacturers** tab.

When you create a standard report layout with multiple headers, keep these tips in mind:

- 7 You can sort each header section independently. For example, you can sort the attributes under the main header without affecting the order of the attributes under the subordinate header.
- 7 The **Hidden Fields** list is also organized by headers. You must select values under the appropriate **Hidden Fields** header to add it under the corresponding **Displayed Fields** header.
- 7 Attributes under one header cannot be moved to be under a different header, although you can select as many attributes as you want under each header.
- 7 You are not required to specify any attributes under the subordinate header. For example, in a Change Activity report, if there are no values under the Affected Items header in the **Displayed Fields** list, then no affected items will be listed on the report; only a list of changes will appear on the report.
- 7 The Change Package report, which assembles all the information about a change in an easy-to-read, printable format, includes more than two headers in the **Hidden Fields** and **Displayed Fields** lists. Each tab of the change object has a header (for example, Cover Page, Affected Items, or Workflow). In addition, depending on which type of change you select in the **Layout Type** drop-down list, additional headers may also be available. For example, under Affected Items.BOM you can select field attributes of the items that appear on the **BOM** tabs of the affected items listed on the change's **Affected Items** tab. For example, you might select Items.BOM.Qty and Items.BOM.Find Num.

Creating Custom Report Layouts

Use the **Add** command on the **Layout** tab to create a new layout for a custom report.

To create a custom report layout:

1. In the navigation pane, select the report you want customize. Click the **Layout** tab, and then click **Add**. The **Add Layout** palette appears.
2. On the layout palette **Properties** tab:
 - a. Type a name for the layout.

- b. In the **Access** list, select the location for the layout. Your report layout can be Global—available to all—or Personal—available only to you.
 - c. Select the paper size and orientation from the corresponding drop-down lists.
3. On the layout palette **Format** tab, select the fields you want in the report.
 - ⌵ To add values to the **Displayed Fields** list, select them in the **Hidden Fields** list, and double-click (or click the right arrow button).
 - ⌵ To remove values from **Displayed Fields** list, select them and double-click (or click the left arrow button).
 - ⌵ To change the order of fields, select a field and use the up arrow or down arrow button to move it.

Note: Because LargeText fields cannot be included in reports they do not appear in the **Displayed Fields** list nor in the **Hidden Fields** list.

4. On the layout palette **Sort** tab, you can specify how you want the report data to be sorted. Select an attribute, and then choose **Ascending** or **Descending** to specify the sort order. You can also select the **Group** check boxes to further organize the report data.
 - ⌵ The first level **Attribute** sort setting is applied to all the report rows.
 - ⌵ The second level **Attribute** sort setting is applied if there are any ties in the first level of sorting.
 - ⌵ The third level **Attribute** sort setting is applied if there are any ties in the second level of sorting.
 - ⌵ **Group** organizes the report by grouping the results according the value selected in the sort-by list.

Note: Because LargeText fields cannot be included in reports they do not appear in the **Sort** tab **Attributes** lists.

5. Click **Save**.

Important: Avoid using special characters in reports using BI Publisher, as they tend to fail.

Creating a Standard Layout

To create a standard report layout:

1. In the navigation pane, select the report you want customize. Click the **Layout** tab, and then click **Add**. The **Add Layout** palette appears.
2. Type a name for the layout.
3. Select a format for the generated report from the **Output Format** list. Choose from a list of formats – PDF, WORD, EXCEL, HTML, and STANDARD.

Note: The **Output Format** list appears only on specific reports. If you do not see the **Output Format** list, ignore this step.

4. On the layout palette **Properties** tab:
 - a. Type a name for the layout.
 - b. In the **Access** list, select the location for the layout. Your report layout can be Global—available to all—or Personal—available only to you.
 - c. Select the paper size and orientation from the corresponding drop-down lists.
 - d. If there is a **Layout Type** list, choose a layout type from the list. For example, the Change Activity report lets you create layouts for change orders and price change orders.

Note: The **Layout Type** list appears on only a few specific report layouts. If you do not see a **Layout Type** list, ignore this step.

5. On the layout palette **Format** tab, select the fields you want in the report.
 - ⌵ To add values to the **Displayed Fields** list, select them in the **Hidden Fields** list, and double-click (or click the right arrow button).
 - ⌵ To remove values from **Displayed Fields** list, select them and double-click (or click the left arrow button).
 - ⌵ To change the order of fields, select a field and use the up arrow or down arrow button to move it.

Note: Because LargeText fields cannot be included in reports they do not appear in the **Displayed Fields** list nor in the **Hidden Fields** list.

6. On the layout palette **Sort** tab, you can specify how you want the report data to be sorted. Select an attribute, and then choose **Ascending** or **Descending** to specify the sort order. You can also select the **Group** check boxes to further organize the report data.
 - ⌵ The first level **Attribute** sort setting is applied to all the report rows.
 - ⌵ The second level **Attribute** sort setting is applied if there are any ties in the first level of sorting.
 - ⌵ The third level **Attribute** sort setting is applied if there are any ties in the second level of sorting.

Note: Because LargeText fields cannot be included in reports they do not appear in the **Sort** tab **Attributes** lists.

7. **Group** organizes the report by grouping the results according the value selected in the sort-by list.
8. If there are multiple headers in the **Hidden Fields** and **Displayed Fields** lists, select the appropriate values under each header and arrange them in the order you want. For more information, see ["About Standard Report Layouts with Multiple Headers"](#) on page 7-6.

Note: Multiple headers do not appear on all standard report layouts. If you see only one header (for example, Main Header Attributes) in the **Selected Values** list, ignore this step.

9. When you are finished, click **Save**.

Editing Standard Report Layouts

You edit a report layout in the layout definition palette. For information about how to change the information in the fields on the **Layout** tab, see ["Layout Tab"](#) on page 7-4.

To edit a standard report layout:

1. Display the layout definition palette in one of the following ways:
 - ? In the navigation pane, select the report you want customize. Click the **Layout** tab, and then click the name link for the layout you want to edit. The layout definition palette appears.
 - ? Select the report you want to customize. Click the **Execute** button. On the Select Layout and Configuration page of most Report wizards, click the **Edit** button to the right of the **Layout** field. The layout definition palette for the selected layout appears.
2. Change the fields you want the report to include, as necessary. On the layout palette **Format** tab:
 - ? To add values to the **Displayed Fields** list, select them in the **Hidden Fields** list, and double-click (or click the right arrow button).
 - ? To remove values from the **Displayed Fields** list, select them and double-click (or click the left arrow button).
 - ? To change the order of fields, select a field and use the up arrow or down arrow button to move it.

Note: Because LargeText fields cannot be included in reports they do not appear in the **Displayed Fields** list nor in the **Hidden Fields** list.

3. If there are multiple headers in the **Hidden Fields** and **Displayed Fields** lists, select the appropriate values under each header and arrange them in the order you want. For more information, see ["About Standard Report Layouts with Multiple Headers"](#) on page 7-6.
4. Click **Save** to save your changes to the layout.

Editing Custom Report Layouts

You edit a report layout in the layout definition palette.

To edit a report layout:

1. Display the layout definition palette in one of the following ways:
 - ? In the navigation pane, select the report you want customize. Click the **Layout** tab, and then click the name link for the layout you want to edit. The layout definition palette appears.
 - ? Select the report you want to customize. Click the **Execute** button. On the Select Layout and Configuration page of most Report wizards, click the **Edit** button to the right of the **Layout** field. The layout definition palette for the selected layout appears.
2. Change the fields you want the report to include, as necessary. On the layout palette **Format** tab:
 - ? To add values to the **Displayed Fields** list, select them in the **Hidden Fields** list, and double-click (or click the right arrow button).

- ⌘ To remove values from the **Displayed Fields** list, select them and double-click (or click the left arrow button).
- ⌘ To change the order of fields, select a field and use the up arrow or down arrow button to move it.

Note: Because LargeText fields cannot be included in reports they do not appear in the **Displayed Fields** list nor in the **Hidden Fields** list.

3. On the layout palette **Sort** tab, change the sort order and select or clear the **Group** check box as necessary.

Note: Because LargeText fields cannot be included in reports they do not appear in the **Sort** tab **Attributes** lists.

4. Click **Save** to save your changes to the layout.

Deleting Report Layouts

You can delete report layouts that are no longer used.

To delete a report layout:

1. Display the **Layout** tab.
2. Select the layouts you want to delete, and then click **Remove**.

The selected layouts are deleted.

Note: You must retain at least one layout.

Schedule Tab

Use the **Schedule** tab when you want a report to run based on a specific schedule or on a specific date and time. You can add, edit, or delete the schedules.

You must have the appropriate privileges to work with the **Schedule** tab.

This tab has the following actions and buttons:

- ⌘ Web Client table editing features – lets you edit the schedule attributes that appear in the Schedule tab table.
- ⌘ **Remove** – deletes the schedules you have selected.
- ⌘ **Add** – lets you add a new schedule frequency (Run Once, Every Day, Weekdays, Mondays, Tuesdays, Wednesdays, Thursdays, Fridays, Saturdays, Sundays, First Day of the Month, and Last Day of the Month) to the report schedule using the Report wizard.
- ⌘ View Details – click to view the schedule details of the selected schedule table row.

The **Schedule** tab has the following fields by default; your Agile administrator may have modified the fields:

- ⌘ **Enable** – double-click to edit; select **Yes** to activate the schedule and run reports automatically, or select **No** to disable the automatic schedule.

- 7 **Schedule Frequency** – a drop-down list with the following options: Run Once, Every Day, Weekdays, Mondays, Tuesdays, Wednesdays, Thursdays, Fridays, Saturdays, Sundays, First Day of the Month, or Last Day of the Month.
- 7 **Schedule Time** – the date and time when the report should run. You specify the date only if the **Schedule Frequency** option is set to Run Once. For any other schedule, you specify only the time.
- 7 **Share W/Users** – list of users who will be notified when the report is generated (based on the schedule) and who will have access to the reports generated from the schedule.
- 7 **Owner** – the name of the user who created the schedule.

To create a schedule:

1. Display the **Schedule** tab for the report.
2. Click **Add**. The Add Schedule wizard appears.
3. Follow each step in the wizard to define and specify your report. These are the same wizard steps you use when you click the **Execute** button to run the report. For details about running specific reports, see the appropriate user guide.

The last wizard step in the Add Schedule wizard is the Define Schedule step.

4. On the Define Schedule page, in the **Schedule** drop-down list, select Run Once, or select the recurring day you want the report to run.
5. If you select Run Once, click the calendar button and select a date. Specify the time you want the report to run. The default time is 12:00 a.m. To enter a time to run the report, use the time format hh:mm:ss and select the appropriate option (**AM** or **PM**). For example, to run the report at 8 p.m., enter 08:00 and click the **PM** option.
6. If you select a recurring day you want the report to run, you can specify a time to run the report. The default time is 12:00 a.m. Use the time format hh:mm:ss and select the appropriate option (**AM** or **PM**). For example, to run the report at 8 p.m. enter 08:00 and click the **PM** option.
7. Click the **Open Palette** icon next to the **Users** field to select the names of users or user groups who will have access to this report.
8. Click **Finish**.

Note: External reports do not have a **Schedule** tab. If there is a schedule, the third-party solution that generates the report also defines the report schedule. If you have questions about external reports on your Agile PLM system, contact the Agile administrator.

Historical Report Tab

After you run a report, you can save the report results. The **Historical Report** tab displays all previously saved report instances with a date and time stamp and the name of the user who executed the report. To share a report, select the appropriate check box and click **Sharing**. To delete or view a report, select the appropriate check box, and click **Delete** or **View**.

To save the generated report as a historical report, click the **Save** button in the Report Output window. If you do not save a report, once you close the report results window, you cannot access that instance of the report again.

If a historical report is generated according to a schedule, then the Type field in the report displays Schedule Generated.

This tab contains the following buttons:

- ? **Sharing** – lets you specify other users who can view the selected report instance.
- ? **Remove** – deletes the selected report instance.
- ? **View** – lets you view the generated Report Output window of the selected report.
- ? **More** – table edit Fill commands.

The **Historical Report** tab has the following fields:

- ? **Create Date** – indicates the date and time the report was generated.
- ? **Type** – indicates if the historical report is saved by the user or generated by a schedule.
- ? **Share W/Users** – users who can view this report instance. Edit this field to modify (add or remove) users who can view the selected report instance.
- ? **Owner** – the name of the user who created the report.

External reports do not have an **Historical Reports** tab. If you have questions about external reports on your Agile PLM system, contact the Agile administrator.

Working with Standard Reports

Standard reports provide you with the information you commonly need to analyze your business processes. You select predefined criteria and specify the results you want. These preconfigured reports are applicable in most situations. You can run them as they are, modify the default layouts, or create your own layouts. You can run Agile reports from Agile Web Client or Java Client.

When you run standard reports from Java Client, Agile PLM opens a Web Client window with the selected report displayed.

Accessing Standard Reports

In the **REPORTS** drawer in the left navigation pane, click the **Expand** icon next to the **Reports and Analytics** folder to view the top-level folders such as **Products Reports** and **Process Reports**. You can access reports from these folders. (Click the **Expand All** icon to expand all the reports folders.)

To execute a standard report, open the report, click the **Execute** button and follow the wizard steps. If the standard report does not have any wizard steps, the report is generated immediately after you click the **Execute** button.

- ? For information about standard report layouts, see ["Creating a Standard Layout"](#) on page 7-7 and ["Editing Standard Report Layouts"](#) on page 7-9.
- ? For information about scheduling standard reports, see ["Schedule Tab"](#) on page 7-10.
- ? For information about standard reports **Historical Reports** tab, see ["Historical Report Tab"](#) on page 7-11.
- ? For information about running standard reports, refer to the appropriate user guide, listed in the following table.

The **Standard Reports** folder contains the predefined folders as listed in the following table.

Table 7–2 Standard Reports subfolders

Report folder	Description and location to find more information about specific reports
Product Reports	Contains the standard Product Collaboration (PC) reports. For more information about these reports, see <i>Product Collaboration Guide</i> .
Administrator Reports	Contains all administrator user reports. For more information about these reports, see <i>Agile PLM Administrator Guide</i> .
Sourcing Reports	Contains the standard Product Cost Management (PCM) reports. For more information about these reports, see <i>Product Cost Management User Guide</i> .
Quality Reports	Contains the standard Product Quality Management (PQM) reports. For more information about these reports, see <i>Product Quality Management User Guide</i> .
Process Reports	Contains reports for changes and transfer orders. For more information about these reports, see <i>Product Collaboration Guide</i> . For more information about the IP Transfer Report, see <i>Agile Content Service User Guide</i> .
Program & Portfolio Reports	Contains standard reports for Product Portfolio Management (PPM) solutions. Sub folders include End User Reports, Portfolio Reports, Program Reports, and Resource Pool Reports. For more information about these reports, see <i>Agile Product Portfolio Management User Guide</i> . If your company has installed Portfolio Analytics, then the Portfolio Analytics reports appear in the Analytics folder under the Program & Portfolio Reports folder. For more information, see <i>Portfolio Analytics User Guide</i> .
Compliance Reports	Contains the standard Product Governance & Compliance (PG&C) reports. For more information about these reports, see <i>Agile Product Governance and Compliance User Guide</i> .

Working with Custom Reports

You can create user-specific or company-specific reports directly within Agile PLM. When you define your query on the Define Query step of the Create Custom Reports wizard, the search looks for objects with fields that match the search conditions that you set up.

You can customize reports in the following ways:

- ? Change the way each report looks by editing the report layout.
- ? Specify a schedule (date and time) when you want a report to be executed.
- ? Save and view report instances.
- ? See what actions have been taken on the report.

Creating a Custom Report

If you have the appropriate roles and privileges, you can create any user-specific or company-specific custom report by using the **Create New** command on the main toolbar.

To create a custom report:

1. Choose **Create New > Report > Custom Reports**.
2. The Create Custom Reports wizard appears. Select the subclass, and type a name for the report.
3. Click **Next**.
4. The Define Query step appears. In this step, click the appropriate option to create a new query or to select an existing query (saved search), complete the remaining fields, and click **Next**.

For information about the options for defining a query, see ["Creating a New Query"](#) on page 7-14.

5. The Select Output Fields page appears. In this wizard step, specify which fields to include in the report and how to sort the results table. To include a field, move it to the **Displayed Fields** list. In the **Attribute** sort lists, select the attributes for sorting and specify how you want the report data to be sorted. Select **Ascending** or **Descending** to specify the sort order. You can also select the **Group** check boxes to further organize the report data.

Note: Because LargeText fields cannot be included in reports they do not appear in **Displayed Fields** list nor in the **Attribute** sort lists.

The settings specified in this step are saved as the Default Layout for the report. For more information about custom report layouts, see ["Creating Custom Report Layouts"](#) on page 7-6.

6. Click **Finish** when you have completed the last step.
7. View general information about the newly created report on the **General Info** tab.
Click **Edit Information** to modify the **General Info** tab.
8. On the **General Info** tab, enter a description. Click the **Launch Palette** icon next to the **Folder** field to select a folder in which to store the report. The Folder palette appears. All the available report folders are listed; expand the folders to find the one you want. Double-click a folder to select it. Select one or more folder locations. Press Escape to close the palette.
9. When you have finished editing the **General Info** tab, click **Save**.

Creating a New Query

To create your own query, select the **Create New** option on the Define Query step of the Create Custom Report wizard. For a new query, complete the **Search Type** and **Search For** fields, and specify at least one search condition. Click **Next**.

The search type options include the following drop-down lists:

- ⌵ *Base Class* list – the broad definition of the type of object that you want to search for; for example, Items, Changes, or Manufacturer Parts.
- ⌵ *Class or Subclass* list – the type of object (class or subclass) that you want to search for; for example, ECO, document, or manufacturer part.
- ⌵ *Search Type* list – the type of search that you are creating. An Object search finds Agile objects that match the search conditions. A Where-used search finds the assemblies that use the items defined by your search criteria. The assemblies in which the defined items are used appear in the search results.

- ⌘ *Related Content* list – when you choose a Relationships search type, this additional list lets you select the related content for the search.

The search criteria options include:

- ⌘ **Match Case** – if checked, the search will be case-sensitive; that is, it will find uppercase or lowercase values exactly the way that you enter them.
- ⌘ **Clear button** – clears the information on this page.
- ⌘ **Attribute** – the field on which you want to search. The contents of this list depend on the class or subclass you have chosen for the query.
- ⌘ **Operator** – a search operator, such as Equal To or Contains. The contents of this list depend on the value specified in the **Attribute** field.
- ⌘ The **Prompt** field – select this box to prompt the report user to fill in the value when the custom report is executed. If you select the check box, the Value field is disabled and you do not enter a value now as you create the custom report query; however, when you execute the custom report, you will be prompted to enter a value in a wizard step. See also ["Executing Custom Reports"](#) on page 7-16.
- ⌘ **Value** – the value for which you want to search. Click the field to specify a value.
- ⌘ **Join** – used to specify multiple search conditions. If you want both conditions to be met, select And. If only one condition must be met, select Or.
- ⌘ **Grouping** menu list – Choose **Add ()**, **Add []**, **Remove []** and **Remove ()** options to tell Agile PLM to group or ungroup conditions. In most searches, use parentheses to group conditions. Use brackets to group conditions in workflow searches.

For more information about defining a query, see [Chapter 8, "Finding Agile Data with Searches."](#)

Note: Delete invalid data for queries as the Use Report subclass tends to hang if the data submitted is large.

Conditions to Edit and Save a Query

To edit a Query:

1. Click **Edit Query** on the General Info.
2. In the Define Query wizard, edit the necessary fields.

Note: Layout settings can be affected when you edit a query. If you edit the values in the Base Class, Subclass, Search Type, or Related Content lists, custom layout settings are reset to default layout settings. If you edit only the fields in the search criteria conditions, custom layout settings are retained.

3. Click **Save**.

The **General Info** tab is then displayed with the latest details that have been entered in the Define Query wizard.

Using a Saved Search

If you select the **Use Saved Search** button on the Define Query page:

1. Click the **Launch Palette** icon to select an existing search to customize.

2. In the displayed palette, locate the saved search you want to use.
3. Double-click the search to select it. Press Escape to close the palette.

On the Define Query wizard step, all the search criteria are copied from the saved search.

You can modify the criteria to suit your needs. Default Layout output fields are copied from the output display of the saved search.

Executing Custom Reports

You must have sufficient privileges to execute a report. For more information about roles and privileges, see the *Agile PLM Administrator Guide*. The report outputs are displayed only in Web Client.

To run a custom report:

1. Select the report that you want to execute, and click the **Execute** button.
2. In the report wizard, select a layout, or:
 - ? Click the **Edit** button to edit the selected layout.
 - ? Click the **Create** button to create a new layout.

For more information, see "[Creating Custom Report Layouts](#)" on page 7-6.

When you are done with this step, click **Finish**. If the **Finish** button is disabled, click **Next**.

3. Select an Output Format. Choices include: Standard, PDF, Word, Excel, and HTML.
4. Click **Finish**.
5. If there are any parametric fields in the report, the Enter Parameter values dialog appears. Fill in the required information. Click **OK**.

If there are no parametric fields in the report, this wizard step is omitted.

6. If you selected the Standard report output, once the output appears, use buttons at the top of the Report Output window to save, export, or print the report.
 - ? Click the **Print** button to print the generated custom report.
 - ? Click the **Export** button to export the report as delimited text files (.CSV) or as Microsoft Excel Workbook files.
 - ? Click the **Save** button to save the report instance.

For more information, see "[Historical Report Tab](#)" on page 7-11.

You can also use buttons to move from page to page in the report and to change the magnification.

7. If you selected the PDF, Word, Excel, or HTML output format, you are prompted to download the output file in the format you selected. You can use the features of the selected application (for example, Save As) to save the output file on your local drive.

Note: When a scheduled custom report fails, a custom report failure notification is sent to all the Users with Administrator privileges.

Deleting and Undeleting Custom Reports

When you no longer need a report, you can delete it from the report folder.

To delete a custom report:

1. Select the report you want to delete.
2. From **Actions** menu, choose **Delete**. A warning message appears asking you to confirm that you want to delete this report. Click **OK**.

To undelete a custom report:

1. Under Searches in the navigation pane, select **Deleted Reports** from the **Recycle Bin Searches** folder.
2. Open the deleted report you want to undelete.
3. From **Actions** menu, choose **Undelete**.

Note: Although the report users can run reports and do analysis on assigned projects, including those to which they do not have direct access, they cannot delete reports that they do not own. Only the report manager can delete reports that belong to other users.

Working with External Reports

You can create reports and generate them from an external report engine. Process extension provides a URL address that can be initiated from within Agile PLM reports and that will launch the specified Web address. The Agile administrator sets the Process Extensions based on your requirements. If you have any questions or comments about the Process Extension settings, contact the Agile administrator.

Creating an External Report

If you have the appropriate roles and privileges, you can create an external report from the **Create New** command on the main toolbar. In Agile Web Client, you can connect to an external resource or URL to generate an external report. Before you create an external report, you must add the URL associated with the report to the Process Extension Library. For more information about Process Extensions, see the *Agile PLM Administrator Guide*.

To create reports in Agile Web Client, you must have the Create Reports privilege.

To create an external report:

1. Log in to Agile Web Client.

Note: You cannot create external reports in Agile Java Client.

2. Click **Create New > Reports > External Reports**.
3. In the Create New dialog, select a subclass, and type a name for the report.
4. Click **Save**.

The newly created External Report object appears in the content pane with the **General Info** tab displayed. The tab is in edit mode.

5. Enter the following general information:
 - ⌵ **Description** – Enter a brief description of the report.
 - ⌵ **Process Extension** – Select a Process Extension. The Process Extension you select is associated with a URL, such as the location of Web-based report. The only Process Extensions that appear in this list are those that are designated as "Initiate From: External Reports" in the Process Extension Library.

- 7. **Folder** – Select a folder in which to store the report.
- 6. Click **Save**.

Executing an External Report

You must have sufficient privileges to execute a report; see ["How Your Roles and Privileges Affect Reports"](#) on page 7-2. For more detailed information about roles and privileges, see the *Agile PLM Administrator Guide*.

To run the newly created external report, click the **Execute** button. The Process Extension that references a URL is invoked, and you see the Web page in a new browser window.

The Report Output Window

When you execute a report in the Standard output format, you see the report displayed in a new browser window. Once the report output appears, you can use buttons at the top of the Report Output window to save, export, or print the report.

- 7. Click the **Print** button to print the generated custom report.
Follow the on-screen instructions to print the report.
- 7. Click the **Export** button to export the report. Follow the on-screen instructions.

The report can be exported in one of three formats:

- File type CSV (comma delimited text file)
- File type Microsoft Excel Workbook.
- File type HTML

CSV and Microsoft Excel Workbook file types can then be opened in Microsoft Excel. CSV files can also be opened with any application that uses the CSV file type. HTML file types can be opened using a browser.

Note: Exporting in Microsoft Excel Workbook with more than 256 columns is currently not supported. To export with more than 256 columns, the user may opt to export in CSV or HTML file type instead.

- 7. To move from page to page, use the **Page** drop-down list and the **Next Page**, and **Previous Page** buttons.
- 7. To change magnification, use the **Zoom In** and **Zoom Out** buttons.
- 7. Click the **Save** button to save the report instance. The saved report instance appears on the **Historical Report** tab.

For more information, see ["Historical Report Tab"](#) on page 7-11.

- 7. Click the browser **Close** button to close the report window.

Finding Agile Data with Searches

When you want to find specific Agile objects, content found in documents or attachments, or other kinds of information contained in the database, you perform a search.

Overview of Search Tools

The main Searches folder has subfolders of saved searches:

- In the Web Client left navigation pane, if the **FOLDERS** drawer is not already displayed, click **FOLDERS** to display the search folders, bookmarks, and recently visited list. In the Searches section, click the **Expand All** icon to display all the searches. Or, for a specific folder, click the **Expand** icon to display the searches in that folder.
- In Java Client, to display the search window, click the **Search** tab in the left navigation pane. Select the top Search folder and click the **Expand All** icon to display all the searches. Or, for a specific folder, click the + icon to display the searches in that folder.

For more information about the predefined searches in Agile PLM, see ["Saved Searches"](#) on page 8-7.

For more information about organizing, editing, and deleting your personal searches, see ["Editing and Managing Searches and Search Folders"](#) on page 8-64.

Types of Searches

Several types of searches are available from the toolbar of both Web Client and Java Client.

Web Client, Types of Searches

Several types of searches are available in Agile PLM Web Client.

- **Quick Search**-Searches for objects whose name, number, or description matches the criteria in the top pane toolbar **Search** text box. See ["Quick Searches and Wildcard Characters"](#) on page 8-14.

A Quick Search can search across all objects or can be filtered for a specific object base class. By default, the Search object class drop-down list is set to All, and Agile PLM performs a Quick Search to search all objects in the database. Narrow your Quick Search by selecting a base class in the drop-down list that limits the search to any object with that base class as its "ancestor."

You can also extend the Quick Search to attachment files. To enable attachment text searching, at the bottom of the base class drop-down list, click the last selection (Include Attachments Text). A check mark on this list selection indicates that attachment searching is enabled. (See ["Quick Searches"](#) on page 8-9.)

Note: When the object class drop-down list is set to All, then attachment text searching is disabled.

- 7 **Custom Search** – In the quick search results display or from the top pane search menu, click **Custom Search** to display the Search Criteria dialog. You can narrow your search by filtering the search results and defining additional search criteria. Agile PLM displays the last custom search you used:
 - **Basic Search** – A preconfigured parametric search the Agile administrator has configured. Your Agile administrator configures Agile PLM to present the most commonly used search attributes for that class or type.

From the drop-down list, you can select a base class that limits the search to any object with that base class as its "ancestor" similar to a Quick Search.

Click the + to expand and display the parametric search the Agile administrator has configured. Your Agile administrator configures Agile PLM to present the most commonly used search attributes for that class or type. Select the search operator and search value for one or more of the displayed attributes. See ["Preconfigured Parametric Searches"](#) on page 8-20.
 - **Advanced Searches** – For greater precision, you can perform an advanced search, which lets you use more specific search conditions and multiple conditions which have not been preconfigured in the parametric search. See ["Advanced Searches"](#) on page 8-28.
- 7 **Attachment content search** – You can use a quick, parametric, or advanced search to find specified content in attachment files. See ["Full Text Search for Content in Attachment Files"](#) on page 8-17.
- 7 **Where-used Searches** – An option in Advanced Search, it searches specific levels of the BOM and revisions, such as "All Levels Latest Released Revision Only." See ["Where-Used Searches for Items"](#) on page 8-44 and ["Where-used Searches for File Folders"](#) on page 8-53.
- 7 **Relationship searches** – An option in Advanced Search, it finds objects that are related to the object that meets the search conditions. See ["Relationship Searches"](#) on page 8-55.

Note: The Rev column from Title Block tab on the search result always shows the latest revision of the item. If Attachment attributes are added in Search Format (e.g. Filename), attachments of all revisions are displayed, but Rev column still shows the latest revision and clicking the item on the search result also navigates to latest revision of the item. If users want to get each attachment's linked revision, they can output Rev from Change History tab in Search Format to display the information (Introductory revision is excluded).

Search Preferences

Note: To be able to change the search preference, add **users.Preference.Include Inactive List Values** to the **Modify My User** and **Read My User** privilege. Contact your Agile administrator.

The **Preferences** tab of the **My Settings** page allows to define a search preference (**Include Inactive List Values**) for Basic or Advanced searches. By default, this option is set to **Yes**, thus

the search result for these searches contains active and inactive list values. To hide inactive list values, this option has to be set to **No**.

This setting applies to:

- ? Lists on the **Search Criteria** page
- ? Lists on the **Filter** tab of the **Table Personalization** mask

To modify your search preference:

1. In Web Client, select **My Settings** to display the My Settings page.
2. Click the **Preferences** tab.
3. Click **Edit**.
4. In the Display Preferences section, open the **Include Inactive List Values** drop-down list.
5. Select **No**.
6. Click **Save**.

Java Client, Types of Searches

Several types of searches are available from the toolbar of both Java Client and Web Client.

- ? **Simple Search** – Searches for objects whose name, number, or description matches the criteria in the main toolbar **Search** text box. See ["Quick Searches and Wildcard Characters"](#) on page 8-14. In a Simple Search, the object class drop-down list is set to All and a wildcard character is used in the main toolbar **Search** text box.

When the object class drop-down list is set to All, the **Search Attachments Context** check box is inactive and not available.

- ? **Quick Search** – Searches for objects whose name, number, or description matches the criteria in the main toolbar **Search** text box. See ["Quick Searches and Wildcard Characters"](#) on page 8-14.

By default, the Search object class drop-down list is set to All, and Agile performs a Simple Search to search all objects in the database. Narrow your Quick Search by selecting a base class in the drop-down list that limits the search to any object with that base class as its "ancestor."

You can also extend the Quick Search to attachment files. See ["Quick Searches"](#) on page 8-9

- ? **Preconfigured Parametric Search** – From the **Search...** button drop-down list, select a base class that limits the search to any object with that base class as its "ancestor" similar to a Quick Search. Click the + to expand and display the parametric search your Agile administrator has configured. Your Agile administrator configures Agile PLM to present the most commonly used search attributes for that class or type. Select the search operator and search value for one or more of the displayed attributes. See ["Preconfigured Parametric Searches"](#) on page 8-20
- ? **Last Search Results** – Return to the results of the last search that you ran.
- ? **Attachment content search** – You can use a quick, parametric, or advanced search to find specified content in attachment files. See ["Full Text Search for Content in Attachment Files"](#) on page 8-17
- ? **Advanced Searches** – For greater precision, you can perform an advanced search, which allow you to use more specific search conditions and multiple conditions which have not been preconfigured in the parametric search. See ["Advanced Searches"](#) on page 8-28.

- 7 **Where-used Searches** – An option in Advanced Search, it searches specific levels of the BOM and revisions, such as "All Levels Latest Released Revision Only." See ["Where-Used Searches for Items"](#) on page 8-44 and ["Where-used Searches for File Folders"](#) on page 8-53.
- 7 **Relationship searches** – An option in Advanced Search, it finds objects that are related to the object that meets the search conditions. See ["Relationship Searches"](#) on page 8-55.

User Roles and Searchable Objects and Attributes

A user's assigned roles determine which Agile objects they can search for and which object attributes they can use for search criteria.

How Discovery Privileges Affect Searches

For Parametric Search and Advanced Search, the base classes, classes and subclasses that appear **Search for:** drop-down lists are determined by the user's Discovery privilege masks.

Discovery privilege masks can be based on criteria for a specific subclass, class, or base class. If the user has a Discovery privilege mask based on a criteria for a specific class, then the user sees and can select any of the subclasses of that class in the **Search for:** drop-down list. Similarly, if a user has a Discovery privilege mask based on a base class, then all classes and subclasses in the specified base class appear in the **Search for:** drop-down list. However, if a user's Discovery privilege masks are limited only to specified subclasses, then the user sees the associated base class and class, but only those specified subclasses appear in the **Search for:** drop-down lists. The user may select the base class, class or subclass; however, if their discovery privileges are limited to specific subclasses, only objects of the specified subclasses appear in the search results.

How Field-Level Read Privileges Affect Searches

The business object fields a user can view and select as search criteria in Parametric Searches and Advanced Searches is determined by the user's field-level Read privileges.

In Advanced Searches, the searchable attributes appear in the **Field** drop-down list of each search condition. In Parametric Searches, the Agile administrator configures which attributes are displayed for selection in the parametric search display. In addition, the user must have the appropriate field-level read privilege masks. If the user does not have read privilege for a specific field, that field does not appear in the Parametric Search display, and that field does not appear in the search condition **Field** drop-down list in Advanced Search.

Search Results

- 7 In Web Client, when you run a search, the results appear in the right content pane.
- 7 In Java Client, when you run a search, the results appear in a search results window. The window title bar displays the name of the search. The search result icon appears in the left corner of the window title bar.

The maximum number of search results that can be displayed is based on the **Maximum Query Results Displayed** property in Agile Administrator under **Admin > Server Settings > Preferences**. If the system found more than the setting **Maximum Query Results Displayed** allows, a message informs you that the returned results were more than allowed. Refine your search criteria as needed.

The maximum number of search results that can be displayed for an external search is based on the **Maximum Database Records to Process for Searches** property in Agile Administrator under **Admin > Server Settings > Preferences**. If the system found more results than defined in the setting **Maximum Database Records to Process for Searches**, a message informs you

that you either do not have sufficient user privileges, or that you need to refine your search criteria.

For Quick Search, the search results are sorted when the number of search results displayed is less than or equal to 5,000.

Note: If you do not have Discovery or Read privilege for an object, it does not appear in search results. Depending on Agile Administrator SmartRule settings, you may see a warning that rows are missing due to insufficient privileges. For more information, see your Agile administrator.

When you search for items (part or document objects), the items displayed are the latest released revision or the most recent pending revision (which was created when the item was added to the **Affected Items** tab of an ECO or an MCO). See also "[Searching on Rev-Specific Values](#)" on page 8-45.

Important: The Specify Output Column privilege is removed from Agile PLM; therefore, all users can potentially specify output attributes in advanced searches. However, if you find that you cannot do so, you have probably been assigned the Enforce Field Level Read privilege by your administrator.

To open and view objects in the results table in Web Client:

1. Click the Number link of the object.

To open and view objects in the results table in Java Client, use one of these methods:

- ? To open one object, double-click the object's row in the search results table.
- ? To open an object with a specific tab on top:
 - a. Select the object's row in the search results table.
 - b. Right-click.
 - c. In the displayed menu, select **Open > tab**.
- ? To open multiple objects:
 - a. Select multiple rows in the search results table.
 - b. Either press **Enter** on the keyboard or click the **Open** button in the main toolbar.

To print a list of objects found by the search:

- ? In Web Client, click the **Print** button on the Search Results page.
- ? In Java Client, click the **Print** button in the search results toolbar.

To view the results of the last search you performed:

- ? In Web Client, if you have opened an item on the Search Results table, you can click the Search Results link at the top of the content pane.
- ? In Java Client, click the **Last Search Results** button.

LargeText Fields in Search Results

When LargeText fields are included in the Search Results table format (see "[C. Define a Custom Output Display, Web Client](#)" on page 8-34.), then the contents of LargeText fields are represented by a **Has Content** icon.

To view the contents of a LargeText field from the Search Results table:

1. Click the **Has Content** icon in the table cell.

The LargeText palette opens.

2. To close the palette, press Escape.

If the LargeText field has no content, then the corresponding cell in the Search Results table is empty.

Exporting Search Results

In both Web Client and Java Client, you can export some or all results of a search (Advanced Search or saved search) to a CSV (comma separated value) file for use in another application, for instance, Microsoft Excel or Microsoft Word. You can also export the search results in Microsoft Excel '.

To export search results in Web Client:

1. Run a search.
2. In the search results table, click the **More** drop-down button and choose a format (.csv or Microsoft Excel):
 - ⌵ **Export (csv)**

The content of LargeText attributes are not exported.
 - ⌵ **Export (xls)**

Then content of LargeText attributes are not exported.
 - ⌵ **Export Objects**

When exported by choosing the XML format, then the content of LargeText attributes are included.
3. When you choose either Export (csv) or Export (xls), the File Download dialog opens.
4. Click **Open** to view the exported file in the chosen format, or **Save** to save the file to your local drive.

Note: For information about **Export Objects**, see *Agile PLM Import/Export User Guide*.

To export search results in Java Client:

1. Run a search.
2. In the search results table, click the Export drop-down button and choose a file format: .CSV or Microsoft Excel.
3. In the File Download dialog that opens, click **Open** to view the exported file in the chosen format, or **Save** to save the file to your local drive.

Saved Searches

Saved searches are advanced searches that have been saved for future use. They include the predefined searches shipped with Agile, global searches that your Agile administrator created, or personal searches you created yourself.

Global searches are seen by all Agile users with appropriate Discovery and Read privileges. Personal searches are seen only by the user who created the search. Although personal searches are created on a local computer, they are stored on the server. Because your personal searches are stored on the server, you can log in to any computer that runs your usual client and see the personal searches you have created, even if those searches were created on a different computer. Only you can see them, under your own login.

Predefined System Searches

Agile PLM comes with a set of predefined searches. You can use them as they are, or you can use them as a template to modify and save as your own custom searches.

Which searches you see depends on your company's licenses and your user profile settings, roles, and privileges. If you have the Global Search privilege, you can edit or delete the predefined system searches. If you do not have the Global Search privilege, you can still view the system searches.

Note: Some predefined system searches cannot be edited, viewed or saved because they are defined internally and are not based on an advanced search. For example, the Recycle Bin searches for soft-deleted objects are not editable.

The search Save As feature lets you create a shortcut (link) to a non-editable system search, but does not allow you to make a copy of that search in your personal searches folder. For more information, see ["Using Save As to Save a Search"](#) on page 8-26.

You also need to have the Searches property in your user profile include the kind of searches you want to see. The Agile administrator may have already set that up when your profile was created as an object in the Agile database; if not, follow this sequence:

To add the capability to see a folder of searches:

1. Display your user profile:
 - In Web Client, choose **My Settings** in the navigation pane toolbar. Your user profile is displayed.
 - In Java Client, click the **View/Edit Current User** button in the main toolbar.
2. This step is only necessary in the Web Client! Click **Edit** to begin modifying your user profile.
3. On the **General Info** tab, scroll down to the Profile section.
4. Modify the **Searches** field to select the Searches you want access to. You may select multiple searches.
5. When you have finished modifying your user profile, click **Save**.

If you have questions about your ability to discover, read, or edit searches, see the Agile administrator.

The **Global Searches** folder has a subfolder named **Workflow Searches** with additional predefined searches.

The following table lists all Searches you can have access to.

Table 8–1 *Predefined system search folders*

Name of folder	Purpose of searches
Compliance Searches	Searches that find product governance and compliance data.
Global Searches > Workflow Search	Searches that use workflow attributes to find routable objects. See "Searching for Routable Objects with Workflow Attributes" on page 8-57.
Change Analyst Searches	Searches that find changes, items, and redlined attachment files.
Component Engineer Searches	Searches that find manufacturers and manufacturer parts.
Workflow Routings	Searches that find workflows, as described in "Workflow Routings" on page 2-11. Also see "Searching for Routable Objects with Workflow Attributes" on page 8-57.
Content Manager Searches	Searches that find content transfer orders and packages.
Price Searches	Searches that find prices.
Project Searches	Searches that find projects.
Quality Searches	Searches that find product service requests and quality change requests.
Sourcing Searches	Searches that find requests for quote and sourcing projects.
Supplier RFQ Searches	Searches that find supplier RFQ requests.
Recycle Bin Searches	Searches that find deleted objects in every base class in Agile PLM.
Personal Searches	Searches that you have created.

Running a Saved Search

- ⌘ In Web Client, when you run a saved search, the found objects are listed in the right pane, below the name of the search.
- ⌘ In Java Client, when you run a saved search, the found objects are listed in the search results window with the name of the search in the window title bar.

In Web Client, to use searches predefined in Agile PLM, created by your Agile administrator, or saved by you:

1. In the **FOLDERS** drawer in the navigation pane, navigate to the search you want to edit.
 - ⌘ Click the **Expand** icon next to a search folder to display the list of saved searches in that folder.
 - ⌘ Or, click the **Expand All** icon in the Searches navigation pane to display all search subfolders and their contents.
2. Click the search name link to execute the search. Results appear in the right content pane.
 - ⌘ At the top of the search results table, click the **Expand** icon to view the search control pane.
 - ⌘ Click the **Collapse** icon at the bottom of the search control pane to collapse and hide the search control pane.
 - ⌘ Click the **Navigator** button in any table, including search results tables, to populate the **NAVIGATOR** drawer.

In Java Client, to use searches predefined in Agile PLM, created by your Agile administrator, or saved by you:

1. If the folders of saved searches are not displayed in the **Searches** folder on the Search tab of the left navigation pane, double-click the **Searches** folder.
Or, highlight the **Searches** folder and click the **Expand All** icon in the Searches toolbar to display all search subfolders and their contents.
2. Double-click the name of the folder that you want to open.
3. Double-click the name of a search in that folder to run it. Results appear in a search results window.

Running Saved "Prompt at Runtime" Searches

You can create and save searches that prompt you to fill in the values for which you want to search. Each time you run the saved search, you can specify different search values.

When you run a saved "Prompt at Runtime" search, a dialog appears that lets you fill in search values.

Fill in the fields provided and then click **Run**.

To create and save a "Prompt at Runtime" search, see ["Creating an Advanced Search in Web Client"](#) on page 8-31 or ["Creating an Advanced Search in Java Client"](#) on page 8-35

Quick Searches

Use the main toolbar quick search features in both clients to run quick searches. Quick searches let you quickly locate objects in the Agile PLM database. The quick search returns a list of all Agile objects whose name, number (ID), or description contains the search criteria that you specified.

Quick Search Overview

In a default quick search (main toolbar class drop-down list set to **All**, also referred to as a simple search) Agile searches all classes to find any object in the database that matches the criteria. When you choose a base class in the drop-down list, Agile limits the search to any object with that base class as its "ancestor." You can also extend the search to attachment files; see ["Full Text Search for Content in Attachment Files"](#) on page 8-17.

Quick searches behave like **Contains** searches for text strings. The search criteria is treated as a single string and Agile PLM searches for names or descriptions that contain the search criteria string. In the case of ID numbers, Agile PLM searches for an exact match, however, you may use wildcard characters to specify part of an ID number as a search criteria.

The columns included in the search results table depend on the type of objects for which you searched.

["Using Wildcard Characters"](#) on page 8-14 gives some examples of values for quick searches and the returned results that can be expected.

For detailed information about using quick searches, see:

- ["Web Client Quick Search"](#) on page 8-10
- ["Java Client Quick Search"](#) on page 8-12
- ["Using Wildcard Characters"](#) on page 8-14
- ["Using Quick Search to Find Attachment File Content"](#) on page 8-17

Web Client Quick Search




The Web Client Quick Search interface appears in the top pane main toolbar in Web Client. See also ["Top Pane Main Toolbar"](#) on page 2-21.

Figure 8–1 Quick search interface, Web Client






The following table describes the actions associated with the Quick Search buttons and fields in Web Client.

Table 8–2 Quick Search controls, Web Client

Button or field	Description
	<p>Base Class drop-down list</p> <p>Use to select a specific base class. Agile limits the search to any object with that base class as its "ancestor."</p> <p>All (default when is displayed) – searches all object classes in the database.</p> <p>See "Perform a Quick Search in Web Client" on page 8-11 for more information.</p>
Search Criteria field	<p>The search criteria text is not case-sensitive. You can enter as search criteria:</p> <ul style="list-style-type: none"> ? a product ID number ? an entire word ? multiple words ? partial numbers or partial words, using the * and ? wildcards. <p>See "Quick Searches and Wildcard Characters" on page 8-14 for more information.</p>
	<p>Execute a Quick Search button</p> <p>Runs the search you specify and displays the results in the Search Results window.</p> <p>See "Search Results" on page 8-4 for more information.</p>
	<p>Custom Search (Ctrl + Shift + Q)</p> <p>Opens a Search Criteria definition pane to create either a basic (parametric) search or an advanced search. The last Search Criteria you used (basic or advanced) is displayed. See "Preconfigured Parametric Searches" on page 8-20 and "Advanced Searches" on page 8-28.</p> <p>Runs a Quick Search. See "Quick Searches and Wildcard Characters" on page 8-14 and "Quick Searches" on page 8-9.</p>

Additional Web Client Quick Search features appear in the Base Class drop-down list.

Figure 8–2 Quick Search drop-down list, Web Client**Table 8–3 Quick Search drop-down list features, Web Client**

Drop-down list icon	Description
	Active menu entry indicator In addition to the base class icon in the search criteria field, the active menu entry icon appears in the drop-down list to indicate which class has been selected.
	Include Attachment Text list entry check mark icon Click to toggle this menu entry selection. To include the content of attachment files in your search, the Include Attachment Text entry must be checked. Scroll to the bottom of the list and click this menu entry to enable this option; the check mark appears on the list. To disable this option, click the menu entry again; the check mark is removed. For more information see "Full Text Search for Content in Attachment Files" on page 8-17.

Perform a Quick Search in Web Client

To perform a Quick Search in Web Client:

1. Use the object type drop-down list to select the type of object you want to search for. Select a base class to limit the search to any object with that base class as its "ancestor."
When you select All, Agile searches across all classes.
2. To include the content of attachment files in your search, scroll to the bottom of the drop-down list and click the Include Attachment Text entry to enable it; the menu selection checkmark icon appears when this option is selected. Click the entry again to deselect it; the icon is removed. See ["Full Text Search for Content in Attachment Files"](#) on page 8-17 for more information.
3. Enter the search characters in the search criteria field.

4. Click the **Execute Quick Search** button. The search returns all objects in the specified base class where the ID number matches or a word in the description contains the search characters.
5. To open a returned object, click its link in the search results table.

Web Client Name/Number/Description Field Searches

In Agile PLM Web Client, when you specify a search criteria for a Quick Search or for the **Name/Number/Desc** search criteria attribute, Web Client executes the search using an internally appended asterisk (*) wildcard at the end of your search criteria. (See also ["Quick Searches and Wildcard Characters"](#) on page 8-14.)

For example, if you execute a quick search (that is, a **Name/Number/Desc** search) for 1000, the search results will include items with the following numbers and descriptions.

Table 8–4 *Name/Number/Desc search results for 1000*

Number	Description
1000-01	Computer, Model 1.0
1000-021	Computer, Model 2.1
403-1009-02	DIODE, REC 1A 1000V

All Web Client quick searches are **Name/Number/Desc** searches. In addition to executing a quick search from the Web Client top pane menu, the **Add by Search** palettes and the search palettes that allow you search for an object field value are also quick searches.

The Basic custom search includes a **Name/Number/Desc** search criteria field. When you define an Advanced Search, **Name/Number/Desc** can be selected in the **Attribute** column of the search criteria.

Java Client Quick Search

The Java Client Quick Search interface appears in the main Java Client window toolbar. See also ["Java Client Toolbars"](#) on page 3-4.

Figure 8–3 *Quick search interface, Java Client*







The following table describes the actions associated with the Quick Search buttons and fields in Java Client.

Table 8–5 *Quick Search controls, Java Client*

Button or field	Description
Base Class drop-down list	Use the drop-down list button to select a specific base class. Agile limits the search to any object with that base class as its "ancestor." All (default) – searches all object classes in the database. For more information see "Perform a Quick Search in Java Client" on page 8-13.

Table 8–5 (Cont.) Quick Search controls, Java Client

Button or field	Description
Search Attachment Text check box	<p>When you select a base class in the Base Class drop-down list, then this check box is enabled.</p> <p>To include the content of attachment files in your search, click the check box to select this option.</p> <p>For more information, see "Full Text Search for Content in Attachment Files" on page 8-17.</p>
Search Criteria field	<p>The search criteria text is not case-sensitive. You can enter as search criteria:</p> <ul style="list-style-type: none"> ? an object ID number ? an entire word ? multiple words ? partial numbers or partial words, using the * and ? wildcards. <p>See "Quick Searches and Wildcard Characters" on page 8-14 for more information.</p>
 Run Search button	<p>Click to run the Simple Search or Quick Search that you have specified. The search results are displayed in the Search Results window.</p> <p>See also:</p> <p>"Search Results" on page 8-4.</p> <p>"Quick Searches and Wildcard Characters" on page 8-14.</p> <p>"Quick Searches" on page 8-9.</p>
 Advanced Search button	<p>Opens the Advanced Search dialog to create an advanced search.</p> <p>See "Advanced Searches" on page 8-28.</p>
 Search drop-down list	<p>Click the drop-down arrow to display a list of base classes to select for a preconfigured parametric search.</p> <p>See "Preconfigured Parametric Searches" on page 8-20.</p>
 Last Search Results button	<p>Display the results of the last search that you performed.</p>

Perform a Quick Search in Java Client

To perform a quick search in Java Client:

1. Enter the search characters in the **Search Text** field in the main toolbar.
2. Use the **Object Type** drop-down list to select the type of object you want to search for. Select a base class to limit the search to any object with that base class as its "ancestor."

When you select All, Agile performs a Simple Search and searches across all classes. The **Search Attachment Text** check box is disabled for Simple Searches.
3. When you select an object type, the **Search Attachment Text** check box is enabled. To include the content of attachment files in your search, select the check box. See ["Full Text Search for Content in Attachment Files"](#) on page 8-17 for more information.
4. Click the **Run Search** button. The search returns all objects in the specified base class where the ID number matches or a word in the description contains the search characters.
5. To open an object in the search results table, double-click its row.

Quick Searches and Wildcard Characters

You can use wildcard characters when you perform a quick search in Web Client ("[Web Client Quick Search](#)" on page 8-10) or Java Client ("[Java Client Quick Search](#)" on page 8-12).

Using Wildcard Characters

Agile accepts two wildcards: the asterisk (*) and the question mark (?), and they can be used in any of the searches.

- ? The question mark ?
Finds matches with any other single character.
- * The asterisk *
Finds matches with more than one character.

Note: For systems on SQL Server, there are some limitations on searches that depend on the available resources of the database server. On SQL Server, the newly created or renamed object cannot be searched on immediately. There is a delay of 10-15 seconds.

Also, on SQL Server, the wildcard search "**value***" is supported. The following searches are not supported:

-
- ? "**value?**"
 - ? "***value**"
 - ? "**?value**"
 - ? "**value*value**"
 - ? "**value?value**"
-

Web Client internally appends an asterisk (*) to the Quick Search criteria you enter to make quick searching more efficient. Here are some examples, using each of the wildcards and no wildcards in Web Client:

Table 8–6 Wildcard search examples, Web Client

Search criteria	will be returned	will not be returned
Hello World	Java output hello world	Hello Dolly
at	Item is at Phoenix site	bat, atlas
?at	bat, cat (and so on)	splat
*at	bat, cat, splat, big hat batter, catfood, hatpin	—
1001-0?2	1001-002, 1001-012, 1001-0A2 Also: 1001-0029	—
1001-0*2	1001-012, 1001-0A2, 1001-0A12, 1001-03742 (and so on) Also: 1001-0129	—
Semi	ABC Semi Haulers Also: ABC Semiconductor	—

Table 8–6 (Cont.) Wildcard search examples, Web Client

Search criteria	will be returned	will not be returned
Semi*	ABC Semi Haulers, ABC Semiconductor Also: ABC Nonsemi Haulers	—

Here are some examples, using each of the wildcards and no wildcards, in Java Client:

Table 8–7 Wildcard search example, Java Client

Search criteria	will be returned	will not be returned
Hello World	Java output hello world	Hello Dolly
at	Item is at Phoenix site	bat, atlas
?at	bat, cat (and so on)	splat
*at	bat, cat, splat, big hat	batter, catfood, hatpin
1001-0?2	1001-002, 1001-012, 1001-0A2	1001-0029
1001-0*2	1001-012, 1001-0A2, 1001-0A12, 1001-03742 (and so on)	1001-0129
Semi	ABC Semi Haulers	ABC Semiconductor
Semi*	ABC Semi Haulers, ABC Semiconductor	ABC Nonsemi Haulers

Note: The only *advanced search* operator that allows wildcard characters is the Like operator. The Like operator is located in the **Match If** list. (See ["Advanced Searches"](#) on page 8-28.)

To search for objects that contain "*", type the backslash character (\) in front of the * wildcard (so, "*") to indicate that you mean the * character, not the * wildcard. For example, to search for "10*18", type **10*18**.

Note: You cannot search for the "?" character, that is, you cannot enter the string "\?". Nor can you search for the backslash character by entering the string "\\".

Special Characters as Part of Words

The following characters are considered to be *part of* the word or number in which they are found:

Table 8–8 Special characters considered to be part of a word or number

Character	Description
_	underscore
-	hyphen
~	tilde
*	asterisk
'	apostrophe
@	at sign

Table 8–8 (Cont.) Special characters considered to be part of a word or number

Character	Description
#	number sign
%	percent
"	quotation mark
^	caret
&	ampersand
.	period (fullstop)
(open parenthesis
)	close parenthesis
+	plus sign
=	equal sign
:	colon
;	semicolon

For instance, if an item's number is 10#40, the search treats it as a single word; "10" and "40" would not be found. So, if you use the * wildcard character, 1* would find 10#40 but 4* would not.

Important: Do not use wildcards to create searches that match too many rows in the database, for example, a search for "P*". When you run a search with a wildcard, the criteria must be matched against all words in the index (formed by combining autonumbers, descriptions, and text in attachments), which can run into several million rows on a large database. It is a good idea to further refine such a search so performance of the database is not compromised.

If your wildcard search matches too many rows in the database, you may see an error message telling you that your wildcard query resulted in too many results, refine your criteria and try again. In this case, enter a more specific search string and try again. The more clues you can provide, the more specific your search will be. For example, "Resistor*" is more specific than "R*" and "MOSFET Transistor" is more specific than "Transistor".

Wildcard searches that specify only one or two characters, including the space character and punctuation characters, may return this error. Whether a specific wildcard search matches too many rows in the database also depends on the size and complexity of your database.

If you enter "*" without any criteria, Agile PLM does not attempt to match all the words in the index.

Note: For multi-byte language Agile installations (Japanese, Chinese, and Korean), simple searches and quick searches, that use wildcard characters to search for text strings that include the following special characters, produce inconsistent results or do not return the correct search results.

tilde ~ grave accent ` exclamation point ! at sign @ number sign # dollar sign \$ per cent sign % caret ^ ampersand & asterisk * open parenthesis (close parenthesis) hyphen - underscore _ equal sign = plus sign + backslash \ vertical bar | open bracket [open brace { close brace } close bracket] semicolon ; colon : apostrophe ' quotation mark " comma , less than sign < period . greater than sign > slash / question mark ?

Instead, use an *advanced search* to use wildcard characters to search for text strings that include these special characters. Specify **Like** as the search operator. The Like search operator lets you use wildcard characters in advanced searches. When you have defined the advanced search, you can save it for later use. See "[Advanced Searches](#)" on page 8-28.

Full Text Search for Content in Attachment Files

You can search attachment files to find a particular word or phrase. You can use Quick Search or Advanced Search to find attachment file content.

Note: FTS in the content of attached files with multi-language characters and wildcard characters may not be fully successful in Simple Search, Quick Search, and Parametric Search.

Full Text Search (FTS) for multi-language characters and wildcard characters may not be fully successful for a Simple Search, Quick Search, and Parametric Search.

We recommend that you use the Advanced Search for multi-language characters and wildcard characters. For more information see "[Advanced Searches](#)" on page 8-28.

When you search for attachment file content, the search results list each object that contains files matching the search criteria. Only the latest versions of attachments are listed.

Note: If an object contains multiple files, even if only one of the files contains the search text, the entire object is returned. The file that contains the text is not indicated, and you may need to look through all attachment files to find the appropriate one.

For non-English text in documents, Full Text Search is not supported for Stem search or Concept search. Moreover, attachment files that can be returned by a full text search must be created and saved in Microsoft Word (.DOC) or Excel (.XLS). Non-English-text attachment files created in .RTF or .TXT formats are not returned (although .TXT files may work if the encoding type is Unicode UTF-8).

Using Quick Search to Find Attachment File Content

To include attachment file content in a quick search:

- ? Web Client – In the quick search drop-down list, click the **Include Attachment Text** entry at the bottom of the list to enable it. The icon appears when the entry is enabled. Click again to disable.
- ? Java Client – Select the **Search Attachment Text** check box.

For detailed information about running quick searches, see ["Web Client Quick Search"](#) on page 8-10 and ["Java Client Quick Search"](#) on page 8-12.

"Stop" Words

The following words are called "stop" words and are ignored by the system in searching against attachment files. So, a search for "the mouse" will return all matches for "mouse", which includes attachment content with the sequence "the mouse" because the stop word "the" is ignored. (To contrast, a simple search of objects—not attachments—for "mouse" would *not* return "the mouse".

Note: On SQL Server, the query string cannot contain any stop words. For example, you would not be able to input "the mouse" as a query string.

"Stop" Words List

- ? a, about, after, all, also, an, and, any, are, as, at
- ? be, because, been, but, by
- ? can, co, Corp, corp, could
- ? for, from
- ? had, has, have, he, her, his
- ? if, in, inc, into, is, it, its
- ? last
- ? more, most, Mr, mr, Mrs, mrs, Ms, ms, Mz, mz
- ? no, not
- ? of, on, one, only, or, other, out, over
- ? s, says, she, so, some, such
- ? than, that, the, their, there, they, this, to
- ? up
- ? was, we, were, when, which, who, will, with, would

Using Attachment Content Advanced Search Capabilities

You can search for attachment files in which the file content matches the text criteria you specify. The following list shows an example of an advanced search in Web Client that will find attachment files that contain the words "PCB" and "Layout." (For general instructions about creating advanced searches, see ["Advanced Searches"](#) on page 8-28.)

Table 8–9 *Example: Attachment content search*

Search definition field:	Criteria selected or entered:
Base Class drop-down list	Items
Search Type drop-down list	Object Search

Table 8–9 (Cont.) Example: Attachment content search

Search definition field:	Criteria selected or entered:
Search Attribute drop-down list	Attachments tab, File Document Text
Search Operator drop-down list	Contains all Words
Search Value field	PCM Layout

To search for attachment file content, use the attribute Attachments.File Document Text.

The following tables describe the attachment content search options available when Attachments.File Document Text is the selected search attribute.

Table 8–10 File Document Text search operators

Search Attribute Setting	Finds	Example
Contains All Words	Attachment files that contain all the words that you specify, in any order	Search text: PCB layout Search results may include: ? PCB layout ? PCB design layout ? Layout of PCB
Contains Any Word or Words	Attachment files that contain at least one of the words that you specify	Search text: PCB layout Search results may include: ? PCB layout ? PCB design layout ? Layout of PCB ? PCB design ? Circuit board layout
Contains Phrase	Attachment files that contain all the words that you specify, in the order specified	Search text: PCB layout Search results include only: ? PCB layout
Does Not Contain (or Contains None Of)	Attachments that do not contain the specified text	Search text: PCB layout Search results never include: ? "PCB" or "layout"
About (for concept searching)	Searches for words that are about the same concept as the specified word.	Search text: sports Search results may include "basketball"

Concept Search and Stem Search

This table describes two specialized search settings, stem searching and concept searching.

Note: SQL Server systems do not support concept searching.

Table 8–11 Concept Search and Stem Search

Feature	Description	Examples
Concept searching	Searches for words that are about the same concept as the specified word.	Search text: sports Search results may contain: basketball, baseball
Stem searching	Searches for the root of the specified word and find all attachments that contain the root.	Search text: index Search results may contain: indexing, indices Search text: run Search results may contain: running, ran

Preconfigured Parametric Searches

In an advanced search, you can choose from a complete list of the available search attributes. By contrast, in a preconfigured parametric search, a list of the most useful or commonly used search attributes is automatically displayed for you in the search window. For each parametric search attribute, you can select a **Match If** operator and a value for which to search. You define search values for only the attributes you want to use in your search. You can leave the remaining parametric search attributes blank.

Your Agile administrator defines the parametric search for all Agile PLM users in Agile Administrator. Each object class or type can have a different set of preconfigured search attributes. Contact your Agile administrator if you have questions about preconfigured search attributes in your Agile system.

After you have defined your parametric search, you can save it in your Personal Searches folder for reuse. For more information about saving a parametric search, see ["Saving a Search"](#) on page 8-25.

Parametric Search Window

The search features in the parametric search pane or window are similar to the quick search.

Important: To display the preconfigured search attributes in the parametric search window, you must select an object type in the second drop-down list. This displays the preconfigured parametric search attributes. Then, select Match If operators and search values for the parametric search attributes you want to use, and click **Search** or **Run**.

Each search condition you define is added to the search (creating an AND search), including the quick search condition at the top of the page.

Parametric Search Window in Web Client

The following figure illustrates the Web Client parametric search window.

Figure 8–4 Parametric search window example, Web Client

The following search control fields, buttons, and menus appear in the Web Client parametric search pane:

Table 8–12 Parametric search pane controls, Web Client

Button, field, or menu	Description
Base Class drop-down list	In this list, select a specific base class. Agile limits the search to any object with that base class as its "ancestor." See "Perform a Quick Search in Web Client" on page 8-11.
Object Type drop-down list	In this list, select a specific object class or a specific object subclass (object type) to further limit the search. The available choices in this list are defined by the Base Class list selection. Note: Selecting an object type in this list automatically displays any preconfigured search attributes.
Search attributes	The search attributes that are displayed in the parametric search are preconfigured by the Agile administrator.
Search Operator drop-down lists	The available search operators depend on the attribute type, for example, list, date, or text. "Search Operators and Attribute Types" on page 8-39.
Search Criteria fields	The search criteria text is not case-sensitive. You can enter as search criteria: <ul style="list-style-type: none"> ? a product ID number ? an entire word ? multiple words ? partial number or partial words, using the * and ? wildcards The available criteria entry methods depend on the attribute type, for example, list, date, or text. "Quick Searches and Wildcard Characters" on page 8-14.

Table 8–12 (Cont.) Parametric search pane controls, Web Client

Button, field, or menu	Description
Include Attachment Text check box	When you select an Object Type, then this check box is enabled. To include the content of attachment file in your search, click to select the check box. "Full Text Search for Content in Attachment Files" on page 8-17.
Advanced button	Displays the Advanced Search criteria definition pane. The parametric search criteria you defined in the parametric search are pre-defined in the Advanced Search pane. See "Saving a Parametric Search as an Advanced Search" on page 8-25.
Format button	The Search Personalization palette lets you select which attribute columns appear in the search results table and the order in which you want them to appear. See "C. Define a Custom Output Display, Web Client" on page 8-34.
Save button	Use to save the displayed search. See "Saving a Search" on page 8-25.
Search button	Runs the search you specify and displays the results in the Search Results table. See "Search Results" on page 8-4 for more information.
Clear button	Clears the displayed search criteria in the Search window.

Running a Preconfigured Parametric Search in Web Client

To define and run a preconfigured parametric search:

1. In the main menu, click the **Custom Search** button. The custom search pane appears. If the advanced search pane is displayed, click the **Basic** button to display the parametric search pane.

Note: Agile PLM displays the last type of search you used, either Advanced or Basic (parametric).

2. In the first drop-down list, select the base class you want to use.
3. To display the preconfigured search attributes, select an object type in the second drop-down list.

The preconfigured search attributes for the selected object type are displayed in the search criteria pane.
4. For each attribute you want to include in your search, select a search operator.
5. For each search attribute you want to include in your search, enter a search value.

If you leave a search value blank, that attribute search criteria will not be used in your search.
6. Click **Search**.

The results are displayed in the search table below the parametric search definition.

The parametric search is an AND search. Each search condition is included in the search with an AND operator.

Parametric Search Window in Java Client

The following figure illustrates the Java Client parametric search window.

Figure 8–5 Parametric search window example, Java Client

The following search control fields, buttons, and menus appear in the Java Client parametric search pane:

Table 8–13 Parametric search window controls, Java Client

Button, field, or menu	Description
Base Class drop-down list	Use the drop-down list to select a specific base class. Agile limits the search to any object with that base class as its "ancestor." Selecting All in this list disables the Object Type list. Agile searches all object classes in the database. See "Perform a Quick Search in Java Client" on page 8-13.
Object Type drop-down list	Use the drop-down list to select a specific object class or a specific object subclass (object type) to further limit the search. The available choices in this list are defined by the Base Class list selection. Note: Selecting an object type in this list, automatically displays any preconfigured search attributes.
Search Attachment Text check box	When you select an Object Type, this check box is enabled. To include the content of attachment files in your search, click to select the check box. See "Full Text Search for Content in Attachment Files" on page 8-17.
Search Criteria field	The search criteria text is not case-sensitive. You can enter the following as search criteria: <ul style="list-style-type: none">? a product ID number? an entire word? multiple words? partial number or partial words, using the * and ? wildcards See "Quick Searches and Wildcard Characters" on page 8-14.
Run Search button	Runs the search you specify and displays the results in the Search Results window.

Table 8–13 (Cont.) Parametric search window controls, Java Client

Button, field, or menu	Description
Search attributes	The search attributes that are displayed in the parametric search are preconfigured by the Agile administrator.
Attribute Match if drop-down lists	The available search operators depend on the attribute type, for example, list, date, or text. "Search Operators and Attribute Types" on page 8-39.
Attribute search value criteria fields	The available criteria entry methods depend on the attribute type, for example, list, date, or text. "Quick Searches and Wildcard Characters" on page 8-14.
Run button	Runs the search with the displayed criteria.
Save button	Save the displayed search as an Advanced Search. The Save in Folder dialog appears. See "Saving a Search" on page 8-25.
Reset button	Clears the displayed search criteria in the Search window.
More...	The More drop-down list displays additional actions.
More... Customize Output Display	The Customize Output Display dialog lets you select which attribute columns appear in the search results table and the order in which you want to appear. See "C. Define a Custom Output Display, Java Client" on page 8-37.
More... Convert to Advanced Search	Displays the Advanced Search dialog. The parametric search criteria you defined in the parametric search are pre-defined in the Advanced Search dialog. See "Saving a Parametric Search as an Advanced Search" on page 8-25.

Running a Preconfigured Parametric Search in Java Client

To define and run a preconfigured parametric search:

1. In the main menu **Search** button drop-down list, select the object class you want for your search.
2. The parametric search window opens with no preconfigured search attributes displayed.
See ["Parametric Search Window in Java Client"](#) on page 8-23.
3. You can use the collapsed parametric search display to run a quick search. (See ["Quick Search Overview"](#) on page 8-9.)
4. To display the preconfigured search attributes, select an object type in the second drop-down list.

The preconfigured search attributes for the selected object type are displayed in the search window.

Use the - or + to the left of the **Search For** field to collapse or expand the list of preconfigured search attributes.
5. For each attribute you want to include in your search, select a Match If operator.
6. For each search attribute you want to include in your search, enter a search value.

If you leave a search value blank, that attribute search criteria will not be used in your search.
7. Click **Run**.

The results are displayed in the search window below the parametric search definition.

The parametric search is an AND search. Each search condition is included in the search with an AND operator.

Saving a Search

You can save both parametric searches and advanced searches using a similar save process or save as processes. A saved parametric search returns search results in the parametric search window, and a saved advanced search returns the search results in the advanced search results table.

- When you run a saved parametric search, the search results are displayed in the parametric search window. You can expand the list of preconfigured attributes to modify or refine your search. If you want, you can save the search with the modifications you made.
- When you run a saved advanced search, the search results are displayed in the advanced search results window. To modify the advanced search, use the Edit button in the search results table.

To save a parametric or advanced search in Web Client:

1. Define the search conditions; click the **Save** menu button and choose **Save**.
The Save Search As dialog box appears.
2. Enter a name for the search in the **Search Name** field.
3. Then select a folder in which to store it.
If you do not have sufficient privileges to save a search in the selected folder, you can select another. You can always save a search in the Personal Searches folder.
4. To create a new folder, click the **New Folder** button. In the Create a Folder dialog, enter a folder name and click **Save**.
5. Click **Save** in the Save Search As dialog box to save the search.

To save a parametric or advanced search in Java Client:

1. Define the search conditions and click **Save**.
The Save in Folder dialog box appears.
2. Enter a name for the search in the **Search Name** field.
3. Select a folder in which to store it.
If you do not have sufficient privileges to save a search in the selected folder, you can select another. You can always save a search in the Personal Searches folder.
4. To create a new folder, click the **New** button. In the Create New Folder dialog, enter a folder name and click **OK**.
5. Click **OK** in the Save in Folder dialog box to save the search.
6. Click **Save** in the Save Search As dialog box to save the search.

Saving a Parametric Search as an Advanced Search

When the parametric search window is open, you can convert the parametric search to a new advanced search. The advanced search is created with all the parametric search conditions predefined in the advanced search. This lets you define additional search criteria not available in a parametric search and save the advanced search for reuse.

To save a parametric search as an advanced search in Web Client:

1. With a parametric search window open, click the **Advanced** button.
You can either define a parametric search and convert it, or you can run a previously saved parametric search and convert it.
2. The Advanced Search pane appears. Define the advanced search.
For more information about defining advanced searches, see ["Creating an Advanced Search in Web Client"](#) on page 8-31.
3. When you are finished, in the Advanced Search pane, click the **Save** menu button and choose **Save**.
The Save Search As dialog box appears.
4. Enter a name for the search in the **Search Name** field.
5. Then select a folder in which to store it.
If you do not have sufficient privileges to save a search in the selected folder, you can select another. You can always save a search in the Personal Searches folder.
6. To create a new folder, click the **New Folder** button. In the Create a Folder dialog, enter a folder name and click **Save**.
7. Click **Save** in the Save Search As dialog box to save the search.

To save a parametric search as an advanced search in Java Client:

1. With a parametric search window open, in the **More** button drop-down list, choose **Convert to Advanced Search...**
You can either define a parametric search and convert it, or you can run a previously saved parametric search and convert it.
2. The Advanced Search dialog appears. Define the advanced search.
For more information about defining advanced searches, see ["Creating an Advanced Search in Java Client"](#) on page 8-35.
3. When you are finished, in the Advanced Search dialog, click **Save**.
The Save in Folder dialog box appears.
4. Enter a name for the search in the **Search Name** field.
5. Select a folder in which to store it.
If you do not have sufficient privileges to save a search in the selected folder, you can select another. You can always save a search in the Personal Searches folder.
6. To create a new folder, click the **New** button. In the Create New Folder dialog, enter a folder name and click **OK**.
7. Click **OK** in the Save in Folder dialog box to save the search.

Using Save As to Save a Search

You can use **Save As** to:

- Create a new copy of a previously saved search.
- Create a shortcut (link) to a predefined system search in a system folder, for example, the Global Searches folder, in your personal searches folder.

If the Agile administrator updates or modifies a global search, when you run the search from the shortcut in your personal searches folder, Agile runs the most recent updated search.

- ? Create a shortcut (link) to a non-editable system search.

Note: When you use Save As and select a non-editable system search, creating a shortcut is the default action.

- ? Create a shortcut to a saved search in a different personal searches folder.

To use Save As to save a search in Web Client:

1. In the left navigation pane, navigate to the search you want to edit. Click the search to execute it.
2. In the search results pane, click the **Expand** icon at the top of the pane to show the search controls.
3. Modify the search definition in the search control pane.
4. Click the **Save** menu button and choose **Save As**.
5. The Save Search As dialog appears. To create a shortcut or link to the search, select the check box for **Create shortcut (a reference to the exiting search)**. To create a copy of the search, ensure that the check box is deselected.

Note: If you have selected a non-editable predefined system search, the **Save** menu button is unavailable. Instead, use the **Save as Shortcut** button. The **Create shortcut (a reference to the exiting search)** check box is preselected for you and cannot be deselected. You are not allowed to create a copy of a non-editable system search using Save As. For more information, see "[Predefined System Searches](#)" on page 8-7.

6. Select the folder you want for the saved search or shortcut.
7. To create a new folder, click the **New Folder** button. In the Create a Folder dialog, enter a folder name and click **Save**.
8. Click **Save** in the Save Search As dialog box to save the search.

To use Save As to save a search in Java Client:

1. Select the search you want to copy or link to, and then initiate the save as process:
 - ? In the Search folder, select the search you want, right-click and choose **Save As**.
 - ? In the Search folder, select the search you want, right-click and choose **Edit**. In the **More** button drop-down list, choose **Save As**.
 - ? Run the search, and then choose edit from the search results table:
 - In a parametric search window, use the **More** button drop-down list, choose **Save As**.
 - In an advanced search results table, click the **Edit** button. In the advanced search dialog, use the **More** button drop-down list and choose **Save As**.
2. The Move to Folder dialog appears. The **Create ShortCut** check box is selected by default. To create a copy of the search, deselect the check box.

Note: If you have selected a non-editable predefined system search, then the **Create ShortCut** check box is preselected for you and cannot be deselected. You are not allowed to create a copy of a non-editable system search using Save As. For more information, see ["Predefined System Searches"](#) on page 8-7.

3. Select the folder you want for the saved search or shortcut.
4. To create a new folder, click the **New** button. In the Create New Folder dialog, enter a folder name and click **OK**.
5. Click **OK** in the Move to Folder dialog box to save the search.

Advanced Searches

This section provides the details on using the advanced search capability.

For information specific to searching for attachment file content, see ["Full Text Search for Content in Attachment Files"](#) on page 8-17.

For information about where-used searches, see ["Where-Used Searches for Items"](#) on page 8-44. Where-used searches find assemblies that contain items that match the search criteria.

For information about relationship searches, see ["Relationship Searches"](#) on page 8-55. Relationship searches find objects that are related to objects that match the search criteria.

These are the topics in this section about advanced searches:

- ? ["Overview of Advanced Searches"](#) on page 8-28
- ? ["Basic Process to Create an Advanced Search"](#) on page 8-29
- ? ["Some Caveats about Advanced Searches"](#) on page 8-29
- ? ["Creating an Advanced Search in Web Client"](#) on page 8-31
- ? ["Creating a Where-Used Search in Java Client"](#) on page 8-51
- ? ["Selecting Search Operators"](#) on page 8-38
- ? ["Using And/Or Values in Advanced Searches"](#) on page 8-42
- ? ["Using Parentheses in Search Definitions"](#) on page 8-43

Overview of Advanced Searches

Advanced searches look for all the objects with fields that match the conditions of the search. The object fields and attributes that you can use for advanced searches depend on whether you are searching for an object base class, class, or subclass. (For information about classes, see ["Introducing Agile Objects"](#) on page 4-1.)

Important: Your company may need to examine the benefits of indexing specific columns in your database. If the enterprise has an extremely large database, and users discover that advanced searches are taking a long time (longer than 2 or 3 minutes), it is likely that the searching operation is going through every single column in the database. By indexing specific database columns, or setting a "search order" of database columns, the searching capability can run faster for all users. See your Agile administrator if you suspect this is a problem.

For example, Agile can search for the fields on the **Title Block** tab of items, the **Cover Page** tab of changes, and the **General Info** tab of manufacturing objects, and also the fields on the **Manufacturers** tab of items. In both Web Client and Java Client, if your company uses custom **Page Two** or **Page Three** fields (which appear on the **Title Block** or **Cover Page** tab in Web Client), they may be referred to by a different name on your system. Agile can also search those fields.

Note: When searching for Discussions, Agile lets you do a relationship search if a Discussion exists for the object.

You can only search for Discussions if you have the respective privileges assigned to you. Contact your administrator.

When searching for changes, Agile can search for workflow attributes and statuses on changes.

Once you create and save a search, you can:

- Run it by clicking it (Web Client), or double-clicking it (Java Client), in the navigation pane.
- Edit it as described in ["Editing and Managing Searches and Search Folders"](#) on page 8-64.

Basic Process to Create an Advanced Search

For detailed instructions for creating an advanced search in Web Client and in Java Client, see ["Creating an Advanced Search in Web Client"](#) on page 8-31, and ["Creating an Advanced Search in Java Client"](#) on page 8-35.

The general procedure to creating an advanced search is as follows:

1. Open the Advanced Search definition window from the button in the menu.
2. Define the Search Criteria: the type of object, the kind of search (for example, an object search, a where-used search, or a relationship search), field names, conditions, and values you want to search for.
3. Define search results options: specify the output fields you want displayed in the search results table, and the order in which you want to display them.
4. Save the search (name and folder), run the search, and print the search results.

Also see the sections immediately following the "create search" tasks: ["Using And/Or Values in Advanced Searches"](#) on page 8-42 and ["Using Parentheses in Search Definitions"](#) on page 8-43.

Some Caveats about Advanced Searches

The following topics discuss important ideas about advanced searches:

- ["Using Saved Searches to Create your Advanced Search"](#) on page 8-30.

- 7 ["Complexity between Search Criteria and Output Display"](#) on page 8-30.
- 7 ["Searching for Space Characters in Text Fields"](#) on page 8-30.
- 7 ["Difference in Caching Search Attributes in Web Client and Java Client"](#) on page 8-31.

Using Saved Searches to Create your Advanced Search

Creating a successful advanced search can be challenging. Consider using a saved search that has some elements of the search you want to create.

- 7 In Web Client, you can execute the search you want to begin with and then use the Save As command to save a duplicate copy. Develop your new search by modifying the copy of the old search.
- 7 In Java Client, when you start to create an advanced search, there is an option to Use a Saved Search; you browse to the search and it "prepopulates" the search dialog box or wizard. Or you may prefer, with a search selected in Java Client, to click the **View/Edit** button, save the opened search with another name (and directory as needed), and develop your new search by modifying the old search.

Complexity between Search Criteria and Output Display

There is potential for ambiguity between the search criteria and the search results output display settings. The search criteria that you define (including the object type coupled with the object attributes) determine which objects the search finds. The output display attributes determine how the found objects are listed in the search results table. The output display attributes do not alter the results of the search; they determine only the manner in which those results are displayed.

When you search for objects by defining criteria that uses data found on related tables, and select similar criteria to display in the output, you may find unexpected results. It is recommended that, whenever possible, you set up your search against the parent object and not its associated data.

More specifically, if you search an object using an attribute of a related object (data that is pulled from other objects, such as BOM, Affected Items, Related PSRs, Changes, and so forth) as a search criteria, and for your output you choose to display attributes of the related object in your output, *all* the related objects will be listed, not just those that meet the search criteria. You will see the searched-for objects listed multiple times in the search results, once for each related object.

Note: When using a Relationships Search, you may add the Description attribute of the Relationships tab in the Format to avoid seeing all the related objects and display only those that meet the Search Criteria. Make sure to check that the attribute has the API Name Description on Java Client.

For example, if you choose "PSR" for object type and search against Affected Items (which is associated data) for some criteria such as "quantity > 5," and you display the affected item number and quantity, you may expect that only affected items with quantity > 5 will appear on the search results table; however, *all* the affected items of the found PSRs will be listed, resulting in the PSR itself being listed multiple times.

Searching for Space Characters in Text Fields

A space character by itself is not a valid search value. Agile PLM will return an error if one or more space characters are the only characters specified in the search condition **Value** field.

However, you can specify a search value that includes a space character with other characters. For example, you can search for "blue box" to find the text string "blue<space>box".

Note: To search for text strings that begin with a space, you can use the Like search operator in the **Match If** field and include a wildcard character in the **Value** field.

When you use a wildcard in the search **Value** field, you must use the Like operator. The only *advanced search* operator that allows wildcard characters is the Like operator.

For more information about wildcard characters, see ["Using Wildcard Characters"](#) on page 8-14.

Difference in Caching Search Attributes in Web Client and Java Client

You may encounter a situation where a field on Page Three of a business object is available for search in Web Client, but is not available in Java Client. This can happen when the administrator hides a field (changes Visible property to No), but has not yet logged out on their system, so the change has not gone into effect for Java Client users, while the change is immediately in effect for Web Client users.

Creating an Advanced Search in Web Client

To create an advanced search in Web Client:

A. Select the Search Type, Web Client

1. Display the Advanced Search **Search Criteria** pane.

Click the **Custom Search** button in the main toolbar to open the **Search Criteria** pane. Click the **Advanced** button if the Advanced Search criteria pane is not already displayed.

2. There are three drop-down lists at the top of the **Search Criteria** pane. In the first two lists, select the following:
 - ⌵ Base Class – This list specifies a broad object definition for the search, for example, Items or Changes.
 - ⌵ Class or Subclass – This list selection narrows your search. If you selected Items in the first list, select a class (Parts or Documents), or select a specific subclass (Resistors or Diodes). If you leave this list blank, Agile PLM searches all object subclasses included in the specified base class.
3. In the Search Type drop-down list, make sure Object Search is selected.

Note: When you make a selection in the Class or Subclass list (the list is not left blank), additional search types become available in the Search Type list. If you select a search type other than Object Search, a fourth drop-down list may be displayed. The fourth list lets you select the Related Content for the search. For more information, see ["Where-Used Searches for Items"](#) on page 8-44, ["Where-used Searches for File Folders"](#) on page 8-53, and ["Relationship Searches"](#) on page 8-55.

B. Define the Search Criteria, Web Client

1. By default, the search condition table contains one row. (In Web Client, you can add as many rows as you need by making a selection in the **Join** drop-down list (select And or Or from the list) or by clicking the plus sign button at the end of the row. See step 2e below.)
2. Define a set of search criteria, or conditions:

- a. In the **Attribute** column, use the drop-down list to select a target search attribute from the list. For example, under the **Title Block** heading in the list, choose **Number**, which represents the **Number** field on the **Title Block** tab of a part or document.

The **Attribute** list varies depending on the object selected in the search definition lists above the search criteria table. For example, if you search for assembly drawings (a part) the **Attribute** list includes the Lifecycle Phase attribute on the Title Block tab. If you search for ECOs (a change) the **Attribute** list includes the Status attribute on the Cover Page tab.

Note: If you are using Microsoft IE browser, long names in the **Attribute** drop-down list may be truncated. To view the full attribute name, hold the cursor over a list entry in the **Attribute** drop-down list and the full attribute name is displayed in a tooltip.

- b. Click the second drop-down list to select a search operator from the list. For more information, see ["Selecting Search Operators"](#) on page 8-38.
- c. The **Prompt** field is enabled if appropriate, and the check box is deselected by default. If you leave the check box deselected, the **Value** field is enabled (see next step). If you select the check box, you are not going to fill in the **Value** field now, and, when you run the saved search, you will be prompted to enter a value.
- d. Click the **Value** field, and enter or select the value or values you want to search for; press Enter when you are finished.

The value entry selection method depends on the kind of attribute you selected (for example, text, list, or date). In the Search Criteria value selection, Web Client uses the same attribute entry and modification methods used elsewhere in Web Client.

In general, begin to type the value you want to search for and a list of matching entries is displayed in the palette. Double-click an entry to select it. Click the **Search to Add** button in the palette to open a Quick Search dialog. For date values, you can click the **Calendar** button.

The **Value** field specifies the content or setting of the field selected from the field list. Depending on the selection in the field list, the value field may allow you select from a list that is relevant to the selection, a calendar button, or a field where you can enter text or numbers. For example, if **Attribute** is set to Title Block, Lifecycle Phase, then the **Attribute** field lists the different lifecycle phases when you click the **Search to Add** button. If **Attribute** is set to Title Block, Description, then you can enter text or numbers in the **Value** field.

If you select Like as a search operator, or if you are searching for attachment file content, you can use wildcard characters when entering a value. For information about using wildcards to search for objects, see ["Using Wildcard Characters"](#) on page 8-14. For information about searching for attachment file content, see ["Full Text Search for Content in Attachment Files"](#) on page 8-17.

- e. To add an operator setting of "And" or "Or," click the **Join** field and select And or Or from the list.

Use **And** if both conditions must be met.

Use **Or** if either or both conditions can be met.

A second line for your search is added as soon as you select **And** or **Or**.

If you have selected **And** or **Or** but want to remove the operator, click the **Join** field and select the empty space, which will depopulate the field of either operator.

The added line does not disappear. You can still set values for that row, and re-select **And** or **Or**. You can also delete the row using the minus sign button to the right.

If you do not use parentheses when defining your search, the search is processed giving precedence to **And** values, that is, it processes all rows that end with **And** before processing rows that end with **Or**. In other words, the first line is combined with the second and process order is based on the first line's **And/Or** value.

For more information, see ["Using And/Or Values in Advanced Searches"](#) on page 8-42.

- f. To add parentheses, click the appropriate options to locate both an open and close parenthesis. Then click the **Grouping** menu button and choose **Add ()**. The proper parenthesis appears to the left of the first row and right of the second row.

To remove parentheses, click the appropriate options for the two rows grouped by parentheses, and click the **Grouping** menu button and choose **Remove ()**.

For more information about using parentheses, see ["Using Parentheses in Search Definitions"](#) on page 8-43.

3. To add another row of search conditions, click the **And/Or** field and select **And** or **Or**. A new row is added at the bottom of the table. You can add as many rows as you like before populating them with criteria.
4. To insert a search condition row, click the **Add** button. The new row is inserted below the row where you clicked the button. To delete a search condition row, click the button for that row.
5. To perform a case-sensitive search where text capitalization matters, select the **Match Case** check box.

To perform a search where text capitalization does *not* matter, click to deselect **Match Case**.

Selecting the **Match Case** check box can help your search run more quickly. If you enter text in the **Value** field, the search looks for text that is an exact match (uppercase and lowercase letters). If you select a value from a list (such as for **Product Line**), checking **Match Case** allows the system to use internal database settings to find objects more quickly.

6. When you have finished adding search conditions, you can use the buttons at the bottom of the dialog to:
 - ? **Search** – execute the search.
 - ? **Save** – save the search.

If you choose **Save**, skip to ["D. Save and Run the Search, Web Client"](#) on page 8-34 to save the search. Saving the search now, before you define the search results format (see ["C. Define a Custom Output Display, Web Client"](#) on page 8-34), gives you the opportunity to name the Search Criteria you have defined, and to use that search with different output displays later.

C. Define a Custom Output Display, Web Client

1. When you have finished adding search conditions, click the **Format** button. The Search Personalization palette appears for you to specify which fields to include in the search results. The Sort tab is displayed.
2. To sort the search results, on the Sort tab, in the Attribute column, use the drop-down list to select the field name by which you want to sort first and use the Sort Order drop-down list to choose Ascending or Descending. Select attributes and sort order for up to three attributes. The results are sorted by the first attribute, then by the second attribute, and then by the third attribute.

Note: List and MultiList fields, such as Product Lines, cannot be sorted alphabetically.

3. To format the search results table, click the Search Personalization Format tab.
4. On the Format tab, in the Hidden Fields table, select field names you want and then use the right and left arrows to move field names to and from the Hidden Fields and Displayed Fields lists. Double-clicking a field name also moves it from one list to the other list.

The Displayed Fields list specifies the field names that will appear in the search results table. Use the up and down arrows to change the order of field names in the list, which reflects the order of the columns in the search results.

Lock horizontal scrolling - Use the **Lock Selected Column** button to lock horizontal scrolling. Select and highlight an attribute in the Displayed Fields list. The slightly thicker vertical line appears to the right of the locked column in the search results table.

- ⌘ Click the **Lock Selected Column** button. A lock icon appears in the Displayed Fields list next to the selected attribute. The locked column and all columns to the left of the locked columns will not scroll horizontally. For example, when you lock the number column, the object number is always visible when you scroll horizontally left or right.
 - ⌘ To lock a different column, select the attribute you want in the Displayed Fields list and click the **Lock Selected Column** button. The lock is moved from one attribute to the other. Only one column can be locked at a time.
 - ⌘ To remove the lock, select the locked column in the Displayed Fields list and click the **Unlock Selected Column** button. The column lock is removed and no columns remain locked.
5. Click **Apply** at any time to immediately apply your format settings to the Search Results table.
 6. When you have finished specifying output fields and sort order, click **Close** in the Search Personalization palette.

D. Save and Run the Search, Web Client

1. You may choose to click the **Save** menu button and choose **Save** to save the search, or click **Search** to execute the search.
 - a. If you chose **Save**, the Save Search As dialog box appears.
 - b. Enter a name for the search.
 - c. Then select a folder in which to store it. If you do not have sufficient privileges to save a search in the selected folder, you can select another. You can always save a search in the Personal Searches folder.
 - d. Click **Save** in the dialog box to save the search.

2. When you are ready to run the search, click **Search** in the Search Criteria pane.
The Search Results table shows all the objects that match the search criteria.
3. To print the list of search results, click the **More** button menu, and then choose **Print**.

Edit the Search After Running It, Web Client

To edit the search after running it in Web Client:

Open the Search Criteria pane at the top of the Search Results table and edit the search.

- ? If the Search Criteria pane is not already displayed, click the **Expand** icon at the top of the pane to show the search controls.
- ? Click **Collapse** icon to hide the search controls.

Creating an Advanced Search in Java Client

To create an advanced search in Java Client:

A. Select the Search Type, Java Client

1. Click the **Advanced Search** button in the toolbar.
The Advanced Search dialog appears, ready for you to define the search criteria. The name **Advanced Search** appears in the title bar at the upper left of the dialog box.
2. To create a completely new search, select the **Create New** check box.
You can also start with a saved search: select the **Use a Saved Search** check box, click the button next to the **Select a Search** field, and select the search you want to start with.
3. In the **Object Type** drop-down list, select the type of object to find. You can specify a base class, class, or subclass object.
4. In the **Search Type** drop-down list, make sure Object Search is selected.

Note: If you select a search type other than Object Search, you must also select an object type in the **With Related Content** drop-down list. For more information, see ["Where-Used Searches for Items"](#) on page 8-44, ["Where-used Searches for File Folders"](#) on page 8-53, and ["Relationship Searches"](#) on page 8-55.

B. Define the Search Criteria, Java Client

1. By default, the search condition table contains one row. (You can add as many rows as you need by clicking **Add** in the search builder window.)
Click the row to enable the search criteria selection lists.
2. Define a set of search criteria, or conditions:
 - a. Click the first drop-down list to select a target **Field** from the list. For example, Title Block.Number represents the **Number** field on the **Title Block** tab of a part or document.

The **Field** list varies depending on the object selected in the **Object Type** field. For example, if you search for assembly drawings (a part) the Field list includes Title Block.Lifecycle Phase. If you search for ECOs (a change) the **Field** list includes Cover Page.Status.

- b. Click the second drop-down list to select a **Match If** search operator from the list. For more information, see ["Selecting Search Operators"](#) on page 8-38.
- c. The **Prompt?** field is enabled if appropriate, and the check box is deselected by default. If you leave the check box deselected, the Value field is enabled (see next step). If you select the check box, you are not going to fill in the Value field, and, when you run the saved search, you will be prompted to enter a value.
- d. In the **Value** field, select a value from the drop-down list and click **OK**. The value you selected populates the field.

The **Value** field specifies the content or setting of the field selected from the field list. Depending on the selection in the field list, the value field may contain a list that is relevant to the selection, a calendar button, or a field where you can enter text or numbers. For example, if **Field** is set to Title Block.Lifecycle Phase, then the **Value** field lists the different lifecycle phases. If **Field** is set to Title Block.Description, then you can type text or numbers in the **Value** field.

If you select Like as a **Match If** search operator, or if you are searching for attachment file content, you can use wildcard characters when entering a value. For information about using wildcards to search for objects, see [s For information about searching for attachment file content](#), see ["Full Text Search for Content in Attachment Files"](#) on page 8-17.

- e. To add an operator setting of "AND" or "OR," click the **And/...** field and select AND or OR from the list.

Use AND if both conditions must be met.

Use OR if either or both conditions can be met.

If you have selected AND or OR but want to remove the operator, click the **And/...** field and select the empty space, which will depopulate the field of either operator.

If you do not use parentheses when defining your search, the search is processed giving precedence to AND values, that is, it processes all rows that end with AND before processing rows that end with OR. In other words, the first line is combined with the second and process order is based on the first line's AND/OR value.

- f. For more information, see ["Using And/Or Values in Advanced Searches"](#) on page 8-42. To add parentheses, select two adjacent rows using Shift-click. When you select two adjacent rows, then the () button is enabled. Click it and the proper parenthesis appears to the left of the first row and right of the second row.

To remove parentheses, select two rows grouped by parentheses, and click the enabled **Remove ()** button.

For more information about using parentheses, see ["Using Parentheses in Search Definitions"](#) on page 8-43.

- 3. To add another row of search conditions, click **Add**. A new row is added at the bottom of the table. The AND/OR field at the end of the previous row is set to [blank] by default.
- 4. To insert a search condition row, select a row and click the **Insert** button. The new row is inserted above the selected row. To delete a search condition row, select one or more rows and click **Delete**. The selected rows are deleted.
- 5. To perform a case-sensitive search where text capitalization matters, select the **Match Case** check box.

To perform a search where text capitalization does *not* matter, click to deselect **Match Case**.

Selecting the **Match Case** check box can help your search run more quickly. If you enter text in the Value field, the search looks for text that is an exact match (uppercase and lowercase letters). If you select a value from a list (such as for Product Line), checking **Match Case** allows the system to use internal database settings to find objects more quickly.

6. When you have finished adding search conditions, you can **Save** the search, or click **Run** to run the search without saving it.

If you click **Save**, skip to ["D. Save and Run the Search, Java Client"](#) on page 8-37 and follow step a through step d to save the search. Saving the search now, before you define the Custom Output Display (see ["C. Define a Custom Output Display, Java Client"](#) on page 8-37), gives you the opportunity to name the Search Criteria you have defined, and to use that search with different output displays later.

If you click **Run** without saving the search, the results are displayed in the search results window. To further edit the search or to save the search, click the **View/Edit** button.

C. Define a Custom Output Display, Java Client

1. When you have finished adding search conditions, select **Custom Output Display...** in the **More..** button drop-down list. The Custom Output Display dialog appears for you to specify which fields to include in the search results. The Available Fields and Selected Fields tables are displayed.
2. In the Custom Output Display dialog, in the Available Fields table, select the field names you want and use the right and left arrows to move field names to and from the Available Fields and Selected Fields lists. Double-clicking a field name also moves it from one list to the other list.

The Selected Fields list specifies the field names that will appear in the search results table. Select one or more rows and use the up and down arrows to change the order of field names in the list, which reflects the order of the columns in the search results.

3. To sort the search results, in the Selected Fields list, click in the **Sort** column for the field name by which you want to sort, and select a number from the drop-down list (for example, 1 means sort by this field name first). You can sort by multiple field names; select a number in the **Sort** column for the each of the field names you want to use to sort. Click in the **Direction** column and select Ascending or Descending order.

Note: List and MultiList fields, such as Product Lines, cannot be sorted alphabetically.

4. When you have finished specifying output display fields and sort order, click **OK** in the dialog box.

D. Save and Run the Search, Java Client

1. You may choose to click **Save** to save the search, or click **Run** to run the search without saving it first.
 - a. If you click **Save**, the Save in Folder dialog box appears.
 - b. Enter a name for the search.
 - c. Then select a folder in which to store it. If you do not have sufficient privileges to save a search in the selected folder, you can select another. You can always save a search in the Personal Searches folder.
 - d. Click **OK** in the dialog box to save the search.

- e. When you are ready to run the search, click **Run** in the search dialog box.

The Search Results window shows all the objects that match the search criteria.

2. To print the list of search results, click the **Print** button.

Edit the Search After Running It, Java Client

To edit the search after running it, do one of the following:

- 7 If the search results window is open, click the **View/Edit** button.
- 7 If you saved the search and closed it, in the **Searches** tab of the navigation pane, select the search and run it. Then click the **View/Edit Search** button in the search results window, and edit the search.

Selecting Search Operators

Search operators are specified in the **Match If** field. Available operators vary depending on the **Field** list selection. For example, if the **Field** setting is Title Block.Description, the **Match If** field includes the Contains operator along with several others; if the **Field** is set to Title Block.Lifecycle Phase, the only operators are In, Not In, Is Null, and Is Not Null.

Table 8–14 Search Operators

Operator	Description
Contains	Finds any value that includes the contents of the Value field. For example, if you are searching for objects that contain the value "cap" in their description, the search would find objects described as capacitor, High Capacity Drive, CAP plug, and so on.
Equal To	Finds only an exact match with the contents of the Value field.
Like	Allows wildcard searches that match any single character.
Not Like	Allows wildcard searches that exclude any single character.
Starts With	Finds values that begin with the characters in the Value field.
Does Not Contain	Finds any value that does not include the contents of the Value field.
Not Equal To	Finds any value other than an exact match with the contents of the Value field.
Does Not Start With	Finds values that do not begin with the characters in the Value field.
Is Null	Finds objects where the field selected from the Field list contains no value.
Is Not Null	Finds objects where the field selected from the Field list contains any value.
Greater Than	Finds dates later than, or duration (in hours) longer than, the contents of the Value field. Finds numbers larger than the contents of the Value field. Finds currency amounts larger than the contents of the Value field.
Greater Than Or Equal To	Finds dates that match or are later than, or duration (in hours) that matches or is longer than, the contents of the Value field. Finds numbers that match or are larger than the contents of the Value field. Finds currency amounts that match or are larger than the contents of the Value field.

Table 8–14 (Cont.) Search Operators

Operator	Description
Less Than	Finds dates earlier than, or duration (in hours) less than, the contents of the Value field. Finds numbers less than the contents of the Value field. Finds currency amounts less than the contents of the Value field.
Less Than Or Equal To	Finds dates that match or are earlier than, or duration (in hours) that matches or is less than, the contents of the Value field. Finds numbers that match or are less than the contents of the Value field. Finds currency amounts that match or are less than the contents of the Value field.
Between	Finds dates that match or are between the beginning date and ending date specified in the Value field. Finds numbers that match or are between the high number and low number specified in the Value field. Finds currency amounts that match or are between the high amount and low amount specified in the Value field.
Not Between	Finds dates that do not match or are not between the beginning date and ending date specified in the Value field. Finds numbers that do not match or are not between the high number and low number specified in the Value field. Finds currency amounts that do not match or are not between the high amount and low amount specified in the Value field.
In	Finds a list attribute that matches one of the list values specified in the Value field.
Not In	Finds a list attribute that does not match any of the list values specified in the Value field.
Contains Any	Finds a MultiList attribute that matches any (at least one) of the MultiList values specified in the Value field.
Contains All	Finds a MultiList attribute that contains all of the MultiList values specified in the Value field. Note: To find an exact match, use the Equal To operator. To find a MultiList attribute that is not empty, use the Is Not Null operator.
Contains None	Finds a MultiList attribute that contains none of the MultiList values specified in the Value field. Note: To find an empty MultiList attribute, use the Is Null operator.

Search Operators and Attribute Types

The following table lists the search operators used for each attribute type and explains how to recognize different attribute types by the manner in which you enter data into the field.

The Agile PLM administrator can set default values (such as the current date, or current user) to automatically appear in a field when new objects are created. For more information, see *Agile PLM Administrator Guide*.

Table 8–15 Attribute types

Type	What to Enter in the Field
Date	Enter date and time, enter the variable \$TODAY to use today's date, or select date and time from a pop-up calendar.
List	Select one item from a list. Select one item from a cascading list.
MultiList	Select one or more items from a multiple-selection list. The list can be a cascading list. Note: There is now no limit to the number of list entries in a multi-list field; in previous service packs, multi-lists could only save and populate 31 list entries.
Text	Enter a single line of text; the allowable length varies, but generally it is up to 50 characters.
MultiText	Enter a block of text (up to 4,000 characters) that wraps across multiple lines.
Numeric	Enter a numeric value.
Money	Enter a monetary amount.
LargeText	If the attribute is configured to allow journal entries, you can add a new time-stamped journal entry. Use the HTML editor features to format the entry. If the attribute does not allow journal entries, you can enter new text or edit existing text. Use the HTML editor features to format the text. Default maximum length is 60,000 characters, including HTML format characters. The Agile administrator can increase the maximum length if needed. See <i>Agile PLM Administrator Guide</i> .

The following table lists the search operators that apply to each attribute type.

Table 8–16 Search operators that apply to each attribute type

Attribute types	Search operators that apply
List	In Not In Is Null Is Not Null
MultiList	Equal To Not Equal To Contains Any Contains All Contains None Is Null Is Not Null
Date Number Money	Between Equal To Less Than Less Than or Equal To Greater Than Greater Than or Equal To Not Equal To Not Between Is Null Is Not Null

Table 8–16 (Cont.) Search operators that apply to each attribute type

Attribute types	Search operators that apply
Text MultiText	Equal To Like Contains Starts With Not Equal To Not Like Does Not Contain Does Not Start With Is Null Is Not Null
LargeText	Contains Phrase Contains All Words Contains Any Word Contains None Of

Searching with Date and Time Criteria

- 7 When the time stamp for the date is 12:00:00 AM, Agile PLM assumes the entire day (12:00:00 AM to 11:59:59 PM) for the search.
- 7 If you enter a specific time, Agile PLM uses the exact time in the search. For example, between 08/20/2007 8:00:00 AM PST and 08/21/2007 5:00:00 PM PST.
- 7 In Advanced Searches, you may also use the search wildcard \$TODAY by typing the wildcard into the search value field (as opposed to clicking the calendar button to display the calendar tool).
- 7 \$TODAY evaluates true for today's date, all times from 12:00:00 AM to 11:59:59 PM. Date and time are determined by your Time Zone as defined in your user profile.
- 7 Use \$TODAY-<integer> or \$TODAY+<integer> to include the number of days before or after today. The integers refer to whole days, not hours. For example, use the \$TODAY wildcard to search for:
 - Items with a Release Date >= \$TODAY-7, that is, all items released in the last week.
 - Changes with a Date Originated Between \$TODAY-10 and \$TODAY, that is, all changes created in the last 10 days.

Limited Search Operators for Orphaned Item Search Criteria

An orphaned item is an item that is not used in any BOM tree, therefore, the orphaned item does not have any parents. In the hierarchy of a BOM tree structure, there are parent items and children items. When an item no longer has any parents, it is referred to as an orphan. On the **Where Used** tab of an orphaned item, the Where Used table is empty.

In an object search for item objects, in the search criteria attribute list, you can select the Where Used table Item Number text attribute as shown below. For this specific item search attribute, the search operators are limited to **Is Null** and **Is Not Null**.

Table 8–17 Orphaned item object search criteria

Item object search criteria attribute	Description	Available Operators
Where Used Item Number	Specifies the latest released revision of the item object.	Is Null Is Not Null

Table 8–17 (Cont.) Orphaned item object search criteria

Item object search criteria attribute	Description	Available Operators
Where Used	Specifies all the revisions of the item object.	Is Null
Item Number All Revisions		Is Not Null

This orphaned item search attribute can be combined with other search attributes to define a narrow search for specific orphaned items. For example, the following search finds all parts without parents for the latest released revision where the product line is Gemini, and the specified date is later than May 1, 2013.

```

Item Number          Is Null          And
Product Lines(s)     Equal To          Gemini          And
Page Two Date 01     Greater Than      May 1, 2013

```

Using And/Or Values in Advanced Searches

When you have two or more conditions defined in a search, the relationship between them is defined as either *AND* or *OR*.

- ✧ **AND** narrows the search by requiring that both conditions are met. Each item in the results must match both conditions.
- ✧ **OR** broadens the search by including any object that meets either condition. Each item in the results table needs to match only one of the conditions, but may match both.

When you define a search with "Equal to" and AND, both parts of the definition must be true. For example, the following search results in zero objects found.

```

Title Block.Product Line(s)  Equal To  Taurus  AND
Title Block.Product Line(s)  Equal To  Scorpio

```

This is because if the first part of the definition is true (that is, the object belongs only to the product line Taurus), then the second part of the definition cannot also be true (that is, the object cannot belong only to the product line Scorpio).

In the example above, if you wanted to search for objects that belong to more than one product line, you could use Contains Any with And. The following search would find all the objects that belong to both the Taurus *and* Scorpio product lines because both sides of the definition could be true:

```

Title Block.Product Line(s)  Contains Any  Taurus  AND
Title Block.Product Line(s)  Contains Any  Scorpio

```

Alternately, the Contains Any operator lets you specify the search as follows:

```

Title Block.Product Line(s)  Contains Any  Taurus, Scorpio

```

Using And/Or - An Example

Knowing when you want to use AND versus OR in constructing your search criteria can help you get the most accurate results from your search and save you valuable time. For example, the following figure shows a search that looks for parts that have *both* a part category equal to Electrical *and* a lifecycle phase equal to Inactive.

Title Block.Part Category	In	Electrical	AND
Title Block.Part Category	In	Inactive	

If you replace And with Or, the search locates all parts with *either* a part category of Electrical *or* a lifecycle phase of Inactive. Depending on your database, this latter search might locate a very large number of parts.

Using Parentheses in Search Definitions

If you do not use parentheses when defining your search, the search is processed giving precedence to AND values, that is, it processes all rows that end with AND before processing rows that end with OR.

In this case, shown in the following figure, Agile looks for objects with *both* a lifecycle phase equal to Production *and* a product line equal to Scorpio. Then, Agile searches the *rest of the database* for objects with a **Description** field that contains "computer." Found objects must have a lifecycle phase equal to Production and a product line equal to Scorpio *or* the word "computer" in their **Description** field because the rows are processed in order.

Title Block.Lifecycle Phase	Equal To	Production	AND
Title Block.Product Line(s)	Equal To	Scorpio	OR
Title Block.Description	Contains	computer	

Parentheses let you group search conditions to determine how the search is performed.

To place parentheses around search conditions in Web Client:

1. In the row where you want to place an open parenthesis, select the option in the open parenthesis column.
2. In the row where you want to place a close parenthesis, select the option in the close parenthesis column.
3. Click the **Add ()** button. The parentheses are placed in the first and last rows selected.

To place parentheses around search conditions in Java Client:

1. Select the rows that you want to enclose in parentheses.
2. Click a row to select it. The row is highlighted.
3. Use Shift-click or Ctrl-click to select one or more additional rows.
4. Click the parentheses () button. The parentheses are placed in the first and last rows selected.

To remove parentheses from search conditions in Web Client:

1. Deselect the open and close parentheses options in the rows from which you want to remove parentheses.
2. Click the **Remove ()** button. The parentheses are removed.

To remove parentheses from search conditions in Java Client:

1. Select the rows with the open parenthesis and close parenthesis.
2. Use Shift-click or Ctrl-click to select one or more additional rows.
3. Click a row to select it. The row is highlighted.
4. Click the **Remove ()** button. The parentheses are removed.

For example, in the search conditions shown in the following table, the second and third conditions are enclosed in parentheses. Agile first looks for objects with a lifecycle phase equal to Production, then searches *that group* for objects with *either* the specified product line **or** description. All found objects *must have* a lifecycle phase equal to Production, but they can have *either* a product line equal to Scorpio *or* a **Description** field that contains "computer."

Title Block.Lifecycle Phase	Equal To	Production	AND
(Title Block.Product Line(s)	Equal To	Scorpio	OR
Title Block.Description	Contains	computer)

If the parentheses are placed around different conditions, a different search occurs. For example, in the search conditions shown in the following table, the parentheses are around the first and second conditions. Found objects will either have lifecycle phase equal to Production and product line equal to Scorpio, *or* the Description will contain "computer" without regard to lifecycle phase or product line.

(Title Block.Lifecycle Phase	Equal To	Production	AND
Title Block.Product Line(s)	Equal To	Scorpio) OR
Title Block.Description	Contains	computer	

Where-Used Searches for Items

Where-used searches are specialized searches that find assemblies that include items that meet the search criteria.

In an object search, the search conditions define the objects you want to find; the objects that meet those search conditions appear in the search results table. In a where-used search, the search conditions specify items that appear on the BOM(s) of the object(s) that you want to find. Therefore, a where-used search finds any assembly that uses the specified items. The assemblies that use the defined items appear in the search results table.

For example, the intent of an object search is

Create a list of items whose **Description** field contains Computer.

The intent of a where-used search with the same search condition is

Create a list of assemblies where the BOM contains items whose **Description** field contains Computer.

These are the subsections of "Where-Used Searches for Items":

- ? ["Searching on Rev-Specific Values"](#) on page 8-45
- ? ["Where-Used Search Types"](#) on page 8-45
- ? ["Where-Used Set Operators"](#) on page 8-48
- ? ["Creating a Where-Used Search in Web Client"](#) on page 8-50
- ? ["Creating a Where-Used Search in Java Client"](#) on page 8-51

Note: Page Three attributes for where-used searches are not fully supported. It is only valid that the header and content are same if the child and the parent have the same subclasses.

Searching on Rev-Specific Values

When you set up a Where Used search, you may well be seeking information about specific revisions of a part or other object. A revision, or "rev", explicitly means that the part has been modified by a change order. (These ideas are covered in *Product Collaboration User Guide*.)

You may use or create criteria that includes revision-specific attributes, such as Rev, Lifecycle Phase, Rev. Release Date, Rev. Incorporate Date, and also fields on the **Manufacturers** tab of the object.

In general, Agile reviews only the latest revision of each item object. The "latest rev" is the most recent revision of the object. If the object has been released (through a change order), this can be called a "released rev." Because an object might be released, *unreleased*, and released again (there can be multiple releases), you may want information about the "latest released rev" – presumably the part or assembly that is closest to being finished.

The latest revision can be any of the following, but only one case at a time (see Note below):

1. The **latest released revision** of the item: the item has been released, it has a revision number, and there are no change orders or MCOs pending against the item. A released revision occurs when the change (Change Order or Manufacturer Order) that created the revision is in its workflow at Released or Implemented status types. This is indicated by the revision letter showing in parentheses.
2. The **latest pending revision** of the item: the item is on the **Affected Items** tab of one or more unreleased change orders or MCOs. A Pending revision occurs when the change that created the revision is in its workflow at one of these status types: Unassigned, Pending, Submit, Review, or Hold. This is indicated by the revision letter showing in parentheses.
3. An **Introductory rev** with *no* pending changes: this Introductory item has no revision number or pending revision number. It has never been released and it is not on the **Affected Items** tab of a change order or an MCO.

Note: These revision types are listed in hierarchical order: if there is an instance of case 1, that is the latest rev. If there is no released rev but there is an instance of case 2, the system sees that as the latest rev. If there is no released or pending rev but there is an instance of case 3, Agile takes the Introductory rev as the latest rev. Note also that the Introductory rev is considered to be a released revision, so items at Intro rev are expected to be included in Where Used search results.

Where-Used Search Types

There are four types of "where-used" searches, which are defined and described in the following sections. "Level" refers to the BOM.

- ? ["Where-Used - All Levels - Latest Released Revision Only"](#) on page 8-45
- ? ["Where-Used - Top Level - Latest Released Revision Only"](#) on page 8-46
- ? ["Where-Used - One Level - Latest Released Revision Only"](#) on page 8-47
- ? ["Where-Used - One Level - All Released Revisions"](#) on page 8-47

Where-Used - All Levels - Latest Released Revision Only

This where-used search type returns a list of the latest released revision of assemblies that contain the named object (that is, assemblies *where* that object is *used*). The following rules apply:

- ⌚ Pending revisions are *not* included. For items/assemblies with pending change order, the Where Used search result will return the item/assembly labeled Introductory (Intro) revision.
- ⌚ Introductory revisions are included, and they are treated as if they were released revisions.


The object described by the search conditions is contained, directly or indirectly (defined below), on the BOMs of the returned assemblies. This search returns assemblies that contain the described object at any BOM level.

Refer to the figure below. In Assembly 999, Part 222 is contained *directly* on the BOM of Assembly 999. Also, Assembly 999 includes Subassemblies 777 and 888.

Part 333 is on Subassembly 777; therefore, Part 333 is *indirectly* contained on the BOM of Assembly 999.

A **Where-Used-All Levels-Latest Released Revision Only** search for Part 333 returns both Assembly 999 (where it is indirectly contained) and Subassembly 777 (where it is directly contained).

Figure 8–6 Where-Used - All Levels - Latest Released Revision Only search for 333 returns 999 and 777



Where-Used - Top Level - Latest Released Revision Only


This where-used search type returns a list of top-level assemblies, latest released revision only. The following rules apply:

- ⌚ Pending revisions are *not* included. For items/assemblies with pending change order, the Where Used search result will return the item/assembly labeled Introductory (Intro) revision.
- ⌚ Introductory revisions are included, and they are treated as if they were released revisions.

The object described by the search conditions is contained, directly or indirectly, on the BOMs of the returned assemblies.

For example, in the figure below, a **Where-Used-Top Level-Latest Released Revision Only** search for Part 333 returns only Assembly 999, the top-level assembly.

Figure 8–7 Where-Used - Top Level - Latest Released Revision Only search for 333 returns 999



Where-Used - One Level - Latest Released Revision Only

This where-used search type returns a list of latest released revision assemblies that directly contain the named object. The following rules apply:

- Pending revisions are *not* included. For items/assemblies with pending change order, the Where Used search result will return the item/assembly labeled Introductory (Intro) revision.
- Introductory revisions are included, and they are treated as if they were released revisions.

The object described by the search conditions is contained directly on the BOMs of the returned assemblies.

Refer to the figure below. Assembly 999 has been released five times, named by Revs **A**, **B**, **C**, **D**, and **E**; there is a pending rev, named by Rev **(F)**.

A **Where-Used-One Level-Latest Released Revision Only** search for Part 111 returns Assembly 999 Rev E only, since Part 111 is directly contained on the BOM of the latest released revision - Rev **E** - of Assembly 999; previously released revisions of Assembly 999 also contain Part 111, but they are not included in the search results because they are not the latest released revision.

Rev **(F)** also contains Part 111, but it is not included in the search results because it is a pending revision.

Figure 8–8 Where-Used - One Level - Latest Revision Only search for 111 returns 999 E

Assembly 999 Rev A	Assembly 999 Rev B	Assembly 999 Rev C
Part 111	Part 111	Part 111
Part 222	Part 333	Part 222
Assembly 999 Rev D	Assembly 999 Rev E	Assembly 999 Rev (F)
Part 111	Part 111	Part 111
Part 444	Part 444	Part 222

Where-Used - One Level - All Released Revisions

This where-used search type returns a list of all the released revision assemblies that directly contain the named object. The following rules apply:

- Pending revisions are *not* included. For items/assemblies with pending change order, the Where Used search result will return the item/assembly labeled Introductory (Intro) revision.
- Introductory revisions are included, and they are treated as if they were released revisions.

The object described in the search conditions is contained directly on the BOM of the released revision of the assembly, even if it is not the latest released revision.

For example, in the figure below, a **Where-Used-One Level-All Released Revisions** search for Part 222 returns Assembly 999 Rev A and Rev C. Assembly 999 Rev B and Rev D are both released revisions, but they do not directly contain Part 222. Revision (F) does directly contain Part 222, but it is not included in the search results because it is a pending revision.

Figure 8–9 Where-Used - One Level - All Released Revisions search for 222 returns 999 A and 999 C

Assembly 999 Rev A Part 111 Part 222	Assembly 999 Rev B Part 111 Part 333	Assembly 999 Rev C Part 111 Part 222
Assembly 999 Rev D Part 111 Part 444	Assembly 999 Rev E Part 111 Part 444	Assembly 999 Rev (F) Part 111 Part 222


Where-Used Set Operators

Where-used set operators allow you to further define relationships between grouped search conditions.

Union

This operator is the equivalent of Or. For example, this lets you find assemblies that contain only part 111, assemblies that contain only part 222 and assemblies that contain both parts 111 and 222. The search results are the union of these two sets of assemblies.


Figure 8–10 Where-Used Set Operator, Union



Intersection

This operator is the equivalent of And. For example, this lets you find assemblies that contain *both* part 222 and part 333, but not assemblies with *only* part 222 or part 333. The search results are the intersection of these two sets of assemblies.


Figure 8–11 Where-Used Set Operator, Intersection



Minus

This operator is the equivalent of Not. For example, this operator lets you find assemblies that contain part 333, but not part 444. The search results are the assemblies that contain part 333, *except for* the assemblies that contain *both* part 333 and 444, nor the assemblies that contain only part 444.

Figure 8–12 Where-Used Set Operator, Minus



The following table illustrates how the set operators can be used. This search locates all assemblies that contain (part 111, part 222, or both) *and* part 333, but *not* part 444.

Title Block.Number	Equal To	111	Union
Title Block.Number	Equal To	222	Intersection
Title Block.Number	Equal To	333	Minus
Title Block.Number	Equal To	444	

This where-used search first finds assemblies that contain either part 111 or part 222 (or both). Next, in the resulting list of assemblies, the search then finds assemblies that also contain part 333. In that resulting list of assemblies, the search now subtracts any assemblies that contain part 444.

Creating a Where-Used Search in Web Client

To create a where-used search in Web Client:

1. Display the Advanced Search, Search Criteria pane.

Click **Custom Search** to open the Search Criteria pane. Click the **Advanced** button if the Advanced search criteria pane is not already displayed.
2. In the Search For list, select the type of object on which to base the where-used search.

The object must be an item or a part or document.

Optionally, you can further narrow your search by selecting a subclass in the second Search For list.
3. In the Search Type list, select the type of where-used search to perform.
4. Select **Match Case** to perform a case-sensitive search where capitalization matters.

Selecting the **Match Case** check box can help your search run more quickly. If you enter text in the **Value** field, the search looks for text that is an exact match (uppercase and lowercase letters). If you selected a value from a list (such as for Product Line), checking **Match Case** allows Agile PLM to use internal database settings to find objects more quickly.
5. Define a set of search criteria, or conditions:
 - a. Select a target attribute from the **Attribute** example, Title Block.Number represents the **Number** field on the **Title Block** tab of a part or document.
 - b. Select a search operator from the **Operator** list. For more information, see ["Selecting Search Operators"](#) on page 8-38..
 - c. If you select the **Prompt** check box, the value field is disabled and you do not enter a value for which to search. Instead, when you run the saved search, you are prompted to enter a value.
 - d. Enter a value in the **Value** field.

Value specifies the content or setting of the field selected from the **Attribute** list. Depending on the selection in the **Attribute** list, the **Value** field may contain a list that is relevant to the selection, a calendar button, or a field where you can enter text or numbers. For example, if **Attribute** is set to Title Block.Size, then **Value** lists different sizes. If **Attribute** is set to Title Block.Description, then you can type text or numbers in the **Value** field.

If you select Like as a Match If search operator, you can use wildcard characters when entering a value. For information about using wildcards to search for objects, see ["Using Wildcard Characters"](#) on page 8-14.
 - e. To add another row of search conditions, use the **Join** field:

Set the **Join** field to And, Or, or none (empty field) to show whether the search conditions for either or both rows must be met. Use And if both conditions must be met. Use Or if either or both conditions can be met. If you do not use parentheses when defining your search, the search is processed giving precedence to And values, that is, it processes all rows that end with And before processing rows that end with Or. In other words, the first line is combined with the second and process order is based on the first line's Join value.

For more information, see ["Using And/Or Values in Advanced Searches"](#) on page 8-42.

6. When you have finished adding search conditions, you can continue with any of the following actions:
 - ⌘ Run the search. Click the **Search** button. The Search Results appear in a table below the Search Criteria pane.
 - ⌘ Define search results formatting. Click the **Format** button to display the Search Personalization palette. See "[C. Define a Custom Output Display, Web Client](#)" on page 8-34.
 - ⌘ Save the search. In the **Save** button drop-down list, choose either Save or Save As. See "[D. Save and Run the Search, Web Client](#)" on page 8-34.
7. To print the list of search results, click the **More** menu button and choose **Print**.

Creating a Where-Used Search in Java Client

The process for creating a where-used search is similar to the process for creating an object search.

To create a where-used search in Java Client:

1. Click the **Advanced Search** button in the toolbar.
The Advanced Search dialog box appears with the **Search** tab displayed.
2. In the **Object Type** list, select the type of object on which to base the where-used search.
The object must be an item, a part, or a document.
3. In the **Search Type** list, select the type of where-used search to perform.
4. By default, the search condition table contains one row. (You can add as many rows as you need by clicking **Add** in the Advanced Search dialog box.)
Click the row to display the search criteria selection lists.
Click each drop-down list button, from left to right, to define the target Field, the Match If search operator, and the value.
5. Define a set of search criteria, or conditions:
 - a. Click the first drop-down list to select a target Field from the list. For example, Title Block.Number represents the **Number** field on the **Title Block** tab of a part or document.
The Field list varies depending on the object selected in the **Object Type** field.
 - b. Click the second drop-down list to select a Match If search operator from the list. For more information, see "[Selecting Search Operators](#)" on page 8-38.
 - c. If you select the **Prompt ?** check box, the value field is disabled and you do not enter a value for which to search. Instead, when you run the saved search, you are prompted to enter a value.
 - d. In the last field, enter a value.
The last search condition field, the **Value** field, specifies the content or setting of the field selected from the Field list. Depending on the selection in the Field list, the **Value** field may contain a list that is relevant to the selection, a calendar button, or a field where you can enter text or numbers. For example, if the first field is set to Title Block.Size, then **Value** lists different sizes. If the first field is set to Title Block.Description, then you can type text or numbers in the field.

If you select Like as a **Match If** search operator, you can use wildcard characters when entering a value. For information about using wildcards to search for objects, see ["Using Wildcard Characters"](#) on page 8-14.

- e. To add another row of search conditions, click **Add**.

A new row is added at the bottom of the table. The And/Or field at the end of the row is set to [blank] by default.

- f. To modify the And/Or or Union/Intersection/Minus setting, click the And/Or field to select AND or OR from the list. Use AND if both conditions must be met. Use OR if either or both conditions can be met. For more information, see ["Using And/Or Values in Advanced Searches"](#) on page 8-42.

- g. To insert a search condition row, select a row and click **Insert**.

The new row is inserted above the selected row.

- h. To delete a search condition row, select one or more rows and click **Delete**.

The selected rows are deleted.

If you do not use parentheses when defining your search, the search is processed giving precedence to AND values, that is, it processes all rows that end with AND before processing rows that end with OR. In other words, the first line is combined with the second and process order is based on the first line's AND/OR value.

For more information, see ["Using And/Or Values in Advanced Searches"](#) on page 8-42.

- 6. Choose **Custom Output Display...** in the **More..** button drop-down list to specify which fields to include in the search results and save the search, or click **Run** to run the search without saving it.

If you click **Run**, the search results window shows all the objects that match the search criteria.

If you choose **Custom Output Display...** in the **More..** button drop-down list, the Display Fields, Results Range and Case Sensitive settings are displayed.

Note: In these setup steps, **Case Sensitive** is selected by default.

- 7. Under Display Fields, select fields and use the right and left arrows to move fields to and from the **Available Fields** and **Selected Fields** lists. Double-clicking a field name also moves it from one list to the other list.

The **Selected Fields** list specifies the fields that will appear in the search results table. Use the up and down arrows to change the order of fields in the list, which reflects the order of the columns in the search results.

- 8. To sort the search results, in the **Selected Fields** list, click in the **Sort** column for the field by which you want to sort, and select a number from the drop-down list (for example, 1 means sort by this field first). You can sort by multiple fields; select a number in the **Sort** column for the each of the fields you want to use to sort. Click in the **Direction** column and select Ascending or Descending order.

- 9. To perform a case-sensitive search where text capitalization matters, make sure **Case Sensitive** is selected.

To perform a search where text capitalization does *not* matter, click to deselect **Case Sensitive**.

Selecting the **Case Sensitive** check box can help your search run more quickly. If you enter text in the Value field, the search looks for text that is an exact match (uppercase and lowercase letters). If you selected a value from a list (such as for Product Line), checking **Case Sensitive** allows Agile to use internal database settings to find objects more quickly.

10. When you have finished specifying output fields and sort order, click **Run** to run the search, or click **Save** to save it.

If you click **Save**, the Save in Folder dialog box appears.

11. Enter a name for the search. Then select a folder in which to store it. If you do not have sufficient privileges to save a search in the selected folder, you can select another. You can always save a search in the Personal Searches folder.

12. Click **OK** in the Save in Folder dialog box to save the search.

13. When you are ready to run the search, click **Run** in the search dialog box.

The search results window shows all the objects that match the search criteria. If there is more than one page, click the right arrow at the top of the window to display the next page.

14. To print the list of search results, click the **Print** button.

To edit the search after running it, do one of the following:

- If you saved the search, on the Searches tab of the navigation pane, select the search, and click the **View/Edit** button.
- If the Search Results window is open, click the **View/Edit** button in the Search Results window.

Where-used Searches for File Folders

Where-used searches for file folders are specialized searches similar to "[Relationship Searches](#)" on page 8-55 that find file folders that appear on the **Attachments** tabs of the objects defined in the search criteria.

In a file folder *object* search, the search conditions specify object attributes of the file folders you want to find; the file folder objects that match those search conditions are returned in the search results.

For example, the following search returns file folders that Mary Smith has checked out:

Table 8–18 Example: Object Search for File Folders

Search setting	Specified as:
Search for Object:	File Folder
Search Type:	Object Search
Search Condition:	Title Block.Checkout User Equal to Mary Smith

In a file folder *where-used* search, you select the object where the file folder is used, for example, Changes. This lets you specify search conditions that include change object attributes, in addition to search criteria that specify file folder attributes.

For example, the following search returns file folders that Mary Smith has checked out that appear on the **Attachments** tab of changes assigned to the Virgo product line.

Table 8–19 Example: Where-Used search for File Folders

Search setting	Specified as:
Search for Object:	File Folder
Search Type:	Where Used Search
With Related Content:	Changes
Search Condition:	Title Block.Checkout User Equal to Mary Smith And Where Used.Changes.Cover Page.Product Line(s) Equal to Virgo

For detailed information about defining searches, see "[Advanced Searches](#)" on page 8-28.

Version-Specific Properties and File Folder Object Searches

Note: For file folder object searches, the latest checked-in file folder version that meets the search criteria is included in the search results table. For file folder searches that include search conditions based on version-specific properties, the search results table will include only checked-in versions of the file folder where the search condition is true.

When a file folder is checked out, the pending version is enclosed in brackets in the **Version** list, for example [3]. Pending version [3] becomes a valid version only when the file folder is checked in.

File folder objects (File Folder class objects and Design class objects) have multiple versions. When you create a file folder object search that include search conditions based on version-specific properties, the search results table will include a row for each version of a file folder object where the search condition is true. Therefore, the file folder search results table may list the same file folder object multiple times.

The following table lists the version-specific properties that automatically cause the search results to list a file folder object multiple times, regardless of whether the version-specific field appears in the search results table, as defined in the advanced search output display.

Note: These attributes are visible on the **Title Block** tab only if the Agile administrator has enabled them. They are typically enabled for Design objects.

Table 8–20 File Folder object version-specific fields

Version-specific file folder Title Block field	Description
Label	A design object version-specific text field which indicates a label identifier for the version. Users with the appropriate privileges can modify this field on any checked in or checked out version.
Revision	Version-specific text field which indicates the targeted Revision for the Design Version.
Revision Date	Version-specific date field which indicates a revision date for the Design Version.
Version	The version number.

The search results table can also display an object multiple times depending on the Output Display as defined in an advanced search. For more information about the Output Display, see ["C. Define a Custom Output Display, Web Client"](#) on page 8-34 and ["C. Define a Custom Output Display, Java Client"](#) on page 8-37.

See also [Chapter 12, "Working with Design Objects."](#)

Version-Specific Properties and File Folder Object Searches

When you create a file folder search based on the file folder **Lifecycle Phase** attribute, the search results will include the latest checked-in file folder version where the search condition is true.

To display all checked-in versions where the Lifecycle Phase search condition is true:

1. Modify the output format to include the Title Page **Version** attribute.

For more information about the Output Display, see ["C. Define a Custom Output Display, Web Client"](#) on page 8-34 and ["C. Define a Custom Output Display, Java Client"](#) on page 8-37.

The search results will include all checked-in versions that meet the search criteria.

Note: For file folder object searches, the latest checked-in file folder version that meets the search criteria is included in the search results table. For file folder searches that include search conditions based on version-specific properties, the search results table will include only checked-in versions of the file folder where the search condition is true.

When a file folder is checked out, the pending version is enclosed in brackets in the **Version** list, for example [3]. Pending version [3] becomes a valid version only when the file folder is checked in.

Relationship Searches

Relationship searches are available for any class that has a **Relationships** tab, that is, all object classes except Action Items and Reports.

In a relationship search you select the related object type, for example, Changes. This lets you specify search conditions that include change object attributes, in addition to search criteria that specify the attributes of the searched-for object.

If the **Relationships** tab is visible for the searched-for object, you will be able to select this search type in the search definition dialog.

For example, the following search returns Non-Conformance Report (NCR) objects where the **Severity** field on the **Cover Page** tab of the NCR equals "Minor" and the NCR **Relationships** tab, Affected By table includes change order objects whose **Cover Page** tab, **Change Analyst** field lists Larry Jones as the change analyst.

Table 8–21 Example: Relationship search

Search setting	Specified as:
Search for Object:	Non-Conformance Reports
Search Type:	Relationships
With Related Content:	Changes

Table 8–21 (Cont.) Example: Relationship search

Search setting	Specified as:
Search Condition:	Cover Page. Severity Equal to Minor And Relationships.Change Orders.Cover Page.Change Analyst Equal to Larry Jones

You set up an advanced search to find objects in relationship with each other that fit the criteria you specify in the search. See ["Advanced Searches"](#) on page 8-28.

Relationship searches allow you to include attributes from the objects on the **Relationships** tab in your search criteria and to search by Relationship tab attributes including, but not limited to:

- ? Rule – Null or Not Null – Determine if there is a rule
- ? Criteria Met – Yes or No – Determine if the criteria defined in the rule has been met
- ? Relationship Type – Affects, Affected By, Reference

You can select from the following relationship searches:

Table 8–22 Available relationship searches by object type

For object classes:	Available relationship searches
All object classes <i>except</i> Reports and Action Items.	Relationships Search
Programs (Agile PPM)	Content Search
File Folders	Relationships Search Where Used Search (See "Where-used Searches for File Folders" on page 8-53.)
Transfer Orders	Relationships Search Selected Content Search

- ? **Relationships Search** lets you include attributes from the objects on the **Relationships** tab in your search criteria, including search criteria about rules and the relationship type> (Affected By, Affects, or Reference).
- ? **Selected Content Search** lets you include attributes from the objects on the **Selected Content** tab in your search criteria.
- ? **Content Search** lets you include Relationships Search attributes and additional Agile PPM content attributes in your search criteria.

For detailed information about defining searches, see ["Advanced Searches"](#) on page 8-28.

Searching for Users and User Groups

You can search on Users and User Groups. In Quick Search, you can select **Users** or **User Groups** as the base class guiding the system per the search-text. You can define a preconfigured parametric search for users and user groups. In Advanced Search, when you select **Users** or **User Groups** as the object to search for, the drop-down list in the Attribute (Web Client) or Field (Java Client) drop-down list is populated with object-specific attributes.

As always, your roles and privileges govern what types of objects you can search for and also which objects you can open.

For more information about constructing advanced searches, see ["Advanced Searches"](#) on page 8-28.

Searching for Routable Objects with Workflow Attributes

["Workflow Routings"](#) on page 3-8 introduced and described the workflow-based sample searches. This section elaborates on this area.

Agile comes with a large array of predefined search samples based on workflow attributes. These are designed to complete the majority of tasks for change analysts, observers, and approvers, but they can be used by any users if they are assigned the appropriate privileges.

Note: Your ability to use workflow attributes to create searches may be limited depending on the Agile Server licenses at your site, and which roles and privileges you have been granted. For more information, see your Agile administrator.

These predefined workflow searches are also modifiable for use as templates. Building a search with workflow attributes is the same as building standard searches. However, you need to follow some special rules to build a successful search. For more information about building a search, begin with ["Advanced Searches"](#) on page 8-28. For information about using workflow attributes in searches, see ["Creating Grouped Conditions for Workflow Searches"](#) on page 8-61.

It is highly recommended that you save the predefined searches with a new name before you modify them. This way you will always have a template to work from if you need to start over.

Creating Workflow Searches

You can search for changes by various attributes relating to the workflow in use for those changes. You can combine some workflow attributes with other workflow attributes in brackets to create a grouped condition, which further refines the way the workflow attributes work together.

In general, you can use the workflow attributes with other non-workflow attributes; however, not all the workflow attributes work together in a search with other workflow attributes, or with non-workflow attributes. If you have selected search attributes that cannot be used together, an error message is displayed. For information about creating grouped conditions, see ["Creating Grouped Conditions for Workflow Searches"](#) on page 8-61.

The following tables display each workflow attribute, its operators, and the expected results of using it in a search. Use these tables to verify that the attributes you want to search will deliver the information you require. A table is included for each of the following workflow attributes:

- ? Cover Page.Status
- ? Workflow.Workflow Status
- ? Workflow.Next Status
- ? Workflow.Approver
- ? Workflow.Observer
- ? Workflow.Notify Users
- ? Workflow.Signoff User

- ? Workflow.Status Changed By
- ? Workflow.Duration
- ? Workflow.Approver Action or Workflow.Observer Action

Note: \$CurrentStatus limits searches on workflow activities to the change's current workflow status. \$User limits searches on users or user actions to the current user, that is, the user running the search.

Cover Page.Status

Table 8–23 *Cover Page.Status workflow attribute search results*

Match If operator	Value	The change found has these attributes
In	Any workflow status; any status type; Unassigned	The specified status matches the current status on the Cover Page.
Not In	Any workflow status; any status type; Unassigned	The specified status does not match the current status on the Cover Page.
Is Null	(None)	The Cover Page.Status field is empty.
Is Not Null	(None)	The Cover Page.Status field is not empty.

Workflow.Workflow Status

Table 8–24 *Workflow.Workflow Status workflow attribute search results*

Match If operator	Value	The change found has these attributes
Equal To	Any workflow status; any status type \$CurrentStatus	The specified status matches the current status of the change.
Not Equal To	Any workflow status; any status type \$CurrentStatus	The specified status does not match the current status of the change.

Workflow.Next Status

Table 8–25 *Workflow.Next Status workflow attribute search results*

Match If operator	Value	The change found has these attributes
Equal To	Any workflow status; any status type	The specified status matches the next status of the change.
Not Equal To	Any workflow status; any status type	The specified status does not match the next status of the change.

Workflow.Approver

Table 8–26 *Workflow.Approver workflow attribute search results*

Match If operator	Value	The change found has these attributes
Contains	One or more users or user groups from the address book; \$User	The specified user or user group is included in the list of approvers.

Table 8–26 (Cont.) Workflow.Approver workflow attribute search results

Match If operator	Value	The change found has these attributes
Does Not Contain	One or more users or user groups from the address book; \$User	Specified user or user group is not included in the list of approvers.
Is Null	(None)	The approver list is empty.
Is Not Null	(None)	The approver list is not empty; there is at least one user, department, or group on the list.

Workflow.Observer**Table 8–27 Workflow.Observer workflow attribute search results**

Match If operator	Value	The change found has these attributes
Contains	One or more users or user groups from the address book; \$User	The specified user or user group is included in the list of observers.
Does Not Contain	One or more users or user groups from the address book; \$User	The specified user or user group is not included in the list of observers.
Is Null	(None)	The observer list is empty.
Is Not Null	(None)	The observer list is not empty; there is at least one user, department, or group on the list.

Workflow.Notify Users**Table 8–28 Workflow.Notify Users workflow attribute search results**

Match If operator	Value	The change found has these attributes
Contains	One or more users or user groups from the address book; \$User	The specified user or user group is included in the list of persons to notify.
Does Not Contain	One or more users or user groups from the address book; \$User	The specified user or user group is not included in the list of persons to notify.
Is Null	(None)	The Notify list is empty.
Is Not Null	(None)	The Notify list is not empty; there is at least one user, department, or group on the list.

Workflow.Signoff User**Table 8–29 Workflow.Notify User workflow attribute search results**

Match If operator	Value	The change found has these attributes
Contains	One or more usernames from the address book; \$User	The specified user performed the signoff action.
Does Not Contain	One or more usernames from the address book; \$User	The specified user did not perform any signoff action.
Is Null	(None)	No users have performed any signoff actions.

Table 8–29 (Cont.) Workflow.Notify User workflow attribute search results

Match If operator	Value	The change found has these attributes
Is Not Null	(None)	At least one user has performed a signoff action.

Workflow.Status Changed By**Table 8–30 Workflow.Status Changed By workflow attribute search results**

Match If operator	Value	The change found has these attributes
In	One username from the address book; \$User	The specified user caused the change to be moved out of this status.
Not In	One username from the address book; \$User	The specified user did not cause the change to be moved out of this status.
Is Null	(None)	The change was autopromoted.
Is Not Null	(None)	The change was manually promoted.

Workflow.Duration

Workflow.Duration must be used with Cover Page.Status.

Workflow.Duration cannot be used with Cancel or Hold status types.

Table 8–31 Workflow.Duration workflow attribute search results

Match If operator	Value	The change found has these attributes
Number of hours. Any positive number; decimal point allowed.	All numeric comparison operators: >, <, >=, <=, =, <>	The change was moved to the specified status within the number of hours specified. Cannot be used with Cancel or Hold status types.

Workflow.Approver Action or Workflow.Observer Action

When either Workflow.Approver Action or Workflow.Observer Action is used in a grouped condition with Workflow.Approver or Workflow.Observer, then the Workflow.Approve Action or Workflow.Observer Action attribute represents the action of the particular user specified by Workflow.Approver or Workflow.Observer.

When Workflow.Approver Action or Workflow.Observer Action are not used in a grouped condition, then these attributes represent the actions taken by all the approvers and observers.

Table 8–32 Workflow.Approver Action and Workflow.Observer Action workflow attributes search results

Match If operator	Value	The change found has these attributes
Contains	Awaiting Approval	One or more approvers/observers have not signed off.
Contains	Approved	One or more approvers/observers have approved.
Contains	Rejected	One or more approvers/observers have rejected.

Table 8–32 (Cont.) Workflow.Approver Action and Workflow.Observer Action workflow attributes search results

Match If operator	Value	The change found has these attributes
Contains	Returned	One or more approvers/observers' signoff request has been returned.
Does Not Contain	Awaiting Approval	All approvers/observers have signed off.
Does Not Contain	Approved	No approvers/observers have approved.
Does Not Contain	Rejected	No approvers/observers have rejected.
Does Not Contain	Returned	No approvers/observers' signoff request has been returned.
Equal To	Awaiting Approval	All selected approvers/observers have not signed off.
Equal To	Approved	All selected approvers/observers have approved.
Equal To	Rejected	All selected approvers/observers have rejected.
Equal To	Returned	All selected approvers/observers' signoff requests have been returned.
Not Equal To	Awaiting Approval	Some selected approvers/observers have signed off.
Not Equal To	Approved	Not all selected approvers/observers have approved.
Not Equal To	Rejected	Not all selected approvers/observers have rejected.
Not Equal To	Returned	Not all selected approvers/observers' signoff requests have been returned.

Creating Grouped Conditions for Workflow Searches

One of the powerful functions that you can use for a workflow search is grouped conditions. This option lets you build powerful search conditions based on certain pairs of workflow attributes. Grouped conditions are enclosed in brackets [].

For example, consider the following grouped condition:

```
[ Workflow.Workflow Status Equal To Status Type.Implemented OR
  Workflow.Workflow Status Equal To Status Type.Released ] AND
Workflow.Status Changed In Sharon
```

This grouped condition finds all changes where the status type is either Implemented or Released and Sharon is the person who changed the status.

Use a grouped condition to refine a search based on workflow attributes. These three rules must be followed to create a grouped condition:

- Two workflow attributes are used within a set of brackets.
- The operator is set to And.
- There are no non-workflow attributes used within the brackets.

To group two or more workflow attributes in Web Client:

1. In the row where you want to place an open bracket, select the option in the open parenthesis column.
2. In the row where you want to place a close bracket, select the option in the close parenthesis column.
3. Click the **Grouping** button and choose **Add []** from the menu.
Brackets [] are placed around the group of workflow attributes.

To group two or more workflow attributes in Java Client:

1. Select the rows that you want to group in brackets.
 - a. Click a row to select it. The row is highlighted.
 - b. Use shift-click or Ctrl-click to select the last row of the group.
2. Click the **[Group]** button.
The brackets are placed around the rows selected.

To ungroup two or more workflow attributes in Web Client:

1. In the row where you want to remove an open bracket, select the option in the open parenthesis column.
2. In the row where you want to remove a close bracket, select the option in the close parenthesis column.
3. Click the **Grouping** button and choose **Remove []** from the menu.

To ungroup two or more workflow attributes in Java Client:

1. Select the rows enclosed in brackets.
2. Click a row to select it. The row is highlighted.
3. Use Shift-click or Ctrl-click to select the second row.
4. Click the **Remove ()** button.
The brackets are removed.

The following fields qualify for grouped condition searches:

- ? **Cover Page.Status**
- ? **Workflow.Duration**
- ? **Workflow.Workflow Status**
- ? **Workflow.Next Status**
- ? **Workflow.Signoff User**
- ? **Workflow.Approver** when it is set to a valid user's name, and Workflow.Approver Action is set to Equal To or Not Equal To a specific action, and there are no non-workflow attributes within the brackets.
- ? **Workflow.Observer** when it is set to a valid user's name and Workflow.Observer Action is set to Equal To or Not Equal To a specific action, and there are no non-workflow attributes within the brackets.

When used in a grouped condition, the workflow attribute that pertains to observers or approvers is set to Contains and the operator for the second workflow attribute is set to either Equal To or Not Equal To, the grouped condition is evaluated in respect to only that specific approver or observer.

If one of the workflow attributes in a grouped condition pertains to a status, and specifies a specific status, then the remaining workflow attributes in the grouped condition are evaluated in respect to only that specific status. For example:

Search 1:

Find all changes where Cathy is an approver and she has approved that change. The approval action applies specifically to Cathy. The use of brackets makes this a grouped condition:

```
[ Workflow.Approver           Contains  Cathy Agile   AND
  Workflow.Approver Action    Equal To  Approved     ]
```

Search 2:

Find all changes where Cathy is an approver and all approvers have approved that change. The approval action applies generally to all the approvers.

Note: This specific search does not work and it should be taken as a sample for this discussion.

There are no brackets; this is not a grouped condition:

```
Workflow.Approver           Contains  Cathy Agile   AND
Workflow.Approver Action    Equal To  Approved
```

In Web Client, grouping is available whenever the open parenthesis and close parenthesis options have been selected to enclose multiple search conditions. Click the **Grouping** button and choose **Add []** from the menu to enclose the selected search conditions in brackets []. If the selected search conditions constitute a valid grouped condition, Web Client adds brackets. If the selected search conditions do not constitute a valid grouped condition, the **Grouping** button **Add []** menu selection is disabled (grayed).

In Java Client, grouping is available whenever multiple search conditions are selected. If the **Group** button is disabled (grayed) the selected search conditions do not constitute a valid grouped condition. Click the **Group** button to enclose the selected search conditions in brackets []. If the selected search conditions enclosed in brackets do not constitute a valid grouped condition, you see an error message when you run or save the search.

Workflow attributes grouped within a set of brackets can be used with other search conditions within a single search.

When non-workflow attributes appear in parentheses along with workflow attributes, parentheses are considered precedences rather than a grouped condition. For example:

```
( Workflow.Signoff User           Contains  Ann Agile           AND
  Cover Page.Change Category      Equal To  Quick Phase-In ) OR
  Cover Page.Product Line(s)      Contains  Scorpio
```

Tips and Guidelines for Grouped Conditions

In Web Client, when you attempt to save searches with illegal grouped conditions, Web Client disables the **Add []** Grouping option.

In Java Client, when you attempt to define searches with illegal grouped conditions, Java Client disables the **Group** button.

In some cases, when you attempt to save a search, you may see an error message. If you do, edit your search to correct the error and then save the search again.

Additional restrictions apply to the use of workflow attributes:

- 7 Nested brackets are not supported. You may not include a grouped condition inside the brackets of another grouped condition. (You can, however, use a bracketed grouped condition inside a set of parentheses with other non-workflow search conditions.)
- 7 Each workflow attribute can be used only once within a grouped condition within a set of brackets. For instance, you may not use **Workflow.Signoff User** twice in the same set of brackets.
- 7 **Workflow.Approver**, **Workflow.Observer**, **Workflow.Notify Users** and **Workflow.Signoff User** may not be used in the same grouped condition.
- 7 **Workflow.Approver Action** and **Workflow.Observer Action** may not be used in the same grouped condition.
- 7 **Workflow.Duration** can be used only in a grouped condition within a set of brackets that contains only **CoverPage.Status** with an operator of Equal To.
- 7 **Workflow.Workflow Status** can be used only along with another workflow attribute within a grouped condition.
- 7 **Workflow.Status Changed By** can be used only with **Workflow.Workflow Status** within a grouped condition.
- 7 Non-workflow attributes cannot be used in a grouped condition, although they may be used with workflow attributes when enclosed in parentheses.
- 7 The Match If logical operator Or cannot be used in a grouped condition.
- 7 If **Workflow.Approver Action** or **Workflow.Observer Action** is used in a grouped condition with **Workflow.Signoff User**, then the Match If operator for **Workflow.Approver Action** or **Workflow.Observer Action** must be Equal To or Not Equal To, and the Match If operator for **Workflow.Signoff User** must be Contains.
- 7 When you search for a specific user for **Workflow.Approver**, **Workflow.Observer**, or **Workflow.Notify Users**, if that user is the member of a group or department, the search also returns changes where the group or department is an approver, observer, or user to notify. For example, if Mary is a member of the Libra Project group, searching for changes where Mary is an approver also returns changes that list the Libra Project group as an approver.

Editing and Managing Searches and Search Folders

If you have sufficient privileges, you can rename, delete, and rearrange both searches and the folders, even some default system searches.

Buttons in the Web Client Searches Toolbar

The following table lists and describes the buttons in the **Searches** section of the **FOLDERS** drawer in the navigation pane.

Table 8–33 Searches toolbar buttons, Web Client






Button	Description
 Expand All	Expands all the search folders in the navigation pane to display all available searches.

Table 8–33 (Cont.) Searches toolbar buttons, Web Client

Button	Description
 Collapse All	Collapses all the search folders in the navigation pane.
 Organize Searches	Opens the Organize Searches window.

In addition, the name of each search in the **Searches** section of the **FOLDERS** drawer in the navigation pane is preceded by two icon buttons.

Table 8–34 Search list icon buttons, Web Client

Button	Description
 Search	Runs the search and displays the search results in the content pane. You can also run the search by clicking the name of the search in the Searches section of the FOLDERS drawer in the navigation pane.
 Edit search criteria	Opens the search control panel in the content pane without running the search. You can now edit the search criteria. See "Editing a Search in Web Client" on page 8-68.

Buttons and Right-click Menu Choices in the Java Client Search Toolbar

When you select a search in Java Client, most of the buttons on the Search toolbar in the left pane are enabled; additional functions are enabled on the right-click menu.

The following table lists and describes the buttons used in the Search toolbar in Java Client.

Table 8–35 Search toolbar buttons, Java Client











Button	Name	Description
	New	Adds a new search folder <i>within</i> the current folder (you can select another folder in the Save In Folder dialog). Available in both Search toolbar and right-click menu.
	Edit Search Right-click menu only	Opens the selected search in edit mode. Available in Right-click menu only.
	Save As Right-click menu only	Saves the selected search, with standard Save As dialog box that prompts for a file name and directory. Available in right-click menu only.
	Rename	Lets you rename the selected search (all searches) or the selected user-defined subfolder. Available in both Search toolbar and Right-click menu.
	Move To Folder	Moves the selected search or subfolder to the folder you specify. Available in both Search toolbar and right-click menu.

Table 8–35 (Cont.) Search toolbar buttons, Java Client

Button	Name	Description
	Delete	Removes the selected user-created search or user-created subfolder. Available in both Search toolbar and Right-click menu.
	Organize Search Right-click menu only when the top Search folder is selected.	Opens the Organize Search dialog which lets you <ul style="list-style-type: none"> ⌵ Create, rename, or remove folders. ⌵ Rename or remove searches. ⌵ Reorder folders and searches depending on your privileges. Available in right-click menu only.
	Expand All Available only when the top Search folder is selected.	When the Searches folder is highlighted, expands all the subfolders. Available in both Search toolbar and Right-click menu
	Collapse All Available only when the top Search folder is selected.	When the Searches folder is highlighted, collapses all the subfolders. Available in both Search toolbar and right-click menu
	Refresh Left Panel Tree	Refreshes the navigation pane of Java Client's user interface

Organizing Searches

Searches can be organized in the Organize Searches window.

To open the Organize Searches window in Web Client:

1. In the **FOLDERS** drawer in the navigation pane, click the **Organize Searches** icon.
The Organize Searches window opens.

To open the Organize Search window in Java Client:

1. Select the Searches folder at the top of the Search tab in the left navigation pane.
2. Right-click and choose **Organize Search** in the menu.
The Organize Search window opens.




The Web Client Organize Searches Window

Use the features in the Web Client Organize Searches window to create or remove folders, rename or remove searches, and sort and move folders and searches.

Table 8–36 Web Client Organize Searches window actions and buttons

Web Client Button	Description
Create Folder	Adds a new search folder within the selected folder.
Remove	Removes the selected searches and search folders. See "Deleting a Search" on page 8-69 or "Removing a Folder" on page 8-71
Order	Alphabetically reorder the searches in the selected folder. Menu choice are A to Z and Z to A .

Table 8–36 (Cont.) Web Client Organize Searches window actions and buttons

Web Client Button	Description
Expand All	Expands all folders, sub-folders and searches.
Collapse All	Collapses all folders, sub-folders and searches.
(double-click to edit name)	Opens a text box to rename the selected search or search folder. See "Renaming a Search" on page 8-69 or "Renaming a Folder" on page 8-72.
(drag and drop)	Lets you reorder searches and search folders. As you drag the search or folder, the displayed icon indicates the drop action:  Drop above the indicated folder.  Drop into the indicated folder.  Drop below the indicated folder See "Moving Searches and Folders" on page 8-72.
Save	Save the modifications you made in the Organize Searches window.
Cancel	Discards the modifications you made in the Organize Searches window and closes the window.
Close	Closes the Organize Searches window.

The Java Client Organize Searches Window

Use the features in the Java Client Organize Searches window to create or remove folders, rename or remove searches, and sort and move folders and searches.

Table 8–37 Java Client Organize Searches window, actions and buttons

Java Client Button	Description
Remove	Removes the selected searches and search folders. See "Deleting a Search" on page 8-69 or "Renaming a Folder" on page 8-72.
Rename	Renames the selected search or search folder. See "Renaming a Search" on page 8-69 or "Renaming a Folder" on page 8-72.
Add New Folder	Adds a new search folder within the current folder.
(drag and drop)	Lets you reorder searches and search folders. See "Moving Searches and Folders" on page 8-72.
Save	Saves the modifications you made in the Organize Searches window.
Cancel	Discards the modifications you made in the Organize Searches window and closes the window.

Editing Searches

When you edit a search, you are changing the combination of conditions Agile PLM looks for. You might want to edit a search to either broaden or narrow the scope of the search or change the output fields.

Whether a search is editable depends on your privileges.

When editing a search you can:

- ⌵ Alter the values of search criteria
- ⌵ Add conditions to the search condition table
- ⌵ Insert conditions into the interior of the search condition table
- ⌵ Delete conditions from the search conditions table
- ⌵ Substitute an And for an Or and vice versa
- ⌵ Add or remove output columns in search results
- ⌵ Modify the sort order of search results

Editing a Search in Web Client

To edit a search in Web Client:

1. In the **FOLDERS** drawer in the navigation pane, navigate to the search you want to edit.
2. Click the **Edit search criteria** icon button to the left of the name of the search you want to edit.

The search control pane is displayed in the content pane. The search is not executed, therefore the Search Results table is empty.

3. To edit the output columns or the sort order, from the **Format** button to display and modify the Sort and Format settings palette. Modify the setting and click **Apply**. Click **Close** to close the palette.
4. To edit search conditions, follow the steps in ["Advanced Searches"](#) on page 8-28 or ["Where-Used Searches for Items"](#) on page 8-44 to edit the search.

For a Basic search, modify the Match If search operators and value fields. Click **Advanced** to convert the search to an Advanced search.

For an Advanced search, to add a search condition, click the **Add** icon at the end of the row. To remove a search condition, click **Remove** icon at the end of the row.

5. When you are finished, use the **Save** button menu and choose **Save**. The search is saved and Agile PLM runs the search and displays the search results below the search control pane.

Or, use the **Save** button menu and choose **Save As**. You are prompted to enter a search name and specify a folder in which to save it. The search is saved and Agile PLM runs the search and displays the search results in the content pane. At the top of the search results table, click the **Expand** icon to view the search control pane. Click the **Collapse** icon to collapse and hide the search control pane.

Editing a Search in Java Client

To edit a search in Java Client:

1. In the Search folder, navigate to the search you want to edit.
2. Select the search, right-click and choose **Edit Search** in the menu.
3. To edit search conditions, click the row you want to edit. To edit the search, follow the steps in ["Creating an Advanced Search in Java Client"](#) on page 8-35, or ["Where-Used Searches for Items"](#) on page 8-44.

To delete a condition, select the row you want to delete, and click **Delete**.

4. When you are finished, click **Save**.

Note: If the search results window is open, click the **View/Edit** button in the search results window, and edit the search.

Renaming a Search

You can rename a saved search to better indicate the type of objects the search is designed to locate.

To rename a search in Web Client:

1. In the **FOLDERS** drawer in the navigation pane, click the **Organize Searches** icon.
2. In the Organize Searches window navigate to the search you want to rename.

Note: Your assigned roles and privileges control which searches and folders you can rename. You can always rename searches and folders in your Personal Searches folder.

3. Double-click the search name to edit it.
4. In the text field, enter a new name and press the Return key.
5. When you are finished, click **Save**.

To rename a search in Java Client Search tab:

1. In the Search tab, select the search you want to rename.
2. Right-click and select **Rename** in the menu.
3. In the dialog, enter a name for the folder and click **OK**.

To rename a search in Java Client Organize Searches window:

1. Select the Searches folder, right-click and choose **Organize Search** in the menu.
2. In the Organize Search window navigate to the search you want to rename and select it.

Note: Your assigned roles and privileges control which searches and folders you can rename. You can always rename searches and folders in your Personal Searches folder.

3. Click the **Rename** button.
4. Edit the name of the search in the **Enter Name** field.
5. Click **OK**.
6. When you are finished, click **Save**.

Deleting a Search

In Web Client, you can delete a search from the Organize Searches page.

In Java Client, you can delete a search on the Searches tab if you have the appropriate privileges for that search.

To remove a search in Web Client:

1. In the **FOLDERS** drawer in the navigation pane, click the **Organize Searches** icon.

2. In the Organize Searches window navigate to the search you want to remove and select it.

Note: Your assigned roles and privileges control which searches you can remove. You can always remove searches and folders in your Personal Searches folder.

3. Click the **Remove** button.

To remove a search in Java Client Search tab:

1. In the Search tab, select the search you want to delete.
2. Right-click and select **Delete** in the menu.
3. When the confirmation prompt appears, click **Yes**.

The search is deleted.

To remove a search in Java Client Organize Search window:

1. Select the Searches folder, right-click and choose **Organize Search** in the menu.
2. In the Organize Search window navigate to the search you want to remove and select it.

Note: Your assigned roles and privileges control which searches and folders you can remove. You can always remove searches and folders in your Personal Searches folder.

3. Click the **Remove** button.
4. When you are finished, click **Save**.

Using Folders to Organize Bookmarks

You can organize your bookmarks in folders to make them easier to locate and manage. You can use the existing folders or create new ones.

Creating a Folder

To create a search folder in Web Client:

1. In the **FOLDERS** drawer in the navigation pane, click the **Organize Searches** icon.
2. In the Organize Searches window navigate to the folder in which you want to create a new folder.

Note: Your assigned roles and privileges control the folders in which you can create new subfolders. You can always add folders in your Personal Searches folder.

3. Click the **Create Folder** button.
4. In the text field, enter a new name and press the Return key.
5. When you are finished, click **Save**.
6. To close the Organize Searches window, click **Close**.

To create a search folder in Java Client Search tab:

1. In the Search tab, select the folder in which you want to create a new folder.
2. Right-click and choose **New Folder** in the menu.
3. In the **Folder Name** field, enter a name for the folder and click **OK**.

To create a search folder in Java Client in the Organize Search window:

1. Select the Searches folder, right-click and choose **Organize Search** in the menu.
2. In the Organize Search window navigate to the folder in which you want to create a new folder.

Note: Your assigned roles and privileges control the folders in which you can create new subfolders. You can always add folders in your Personal Searches folder.

3. In the **Folder Name** field, enter a new name.
4. Click **OK**.
5. When you are finished, click **Save**.

Removing a Folder

You can remove or delete a folder, even if it is not empty.

To remove a search or folder in Web Client:

1. In the **FOLDERS** drawer in the navigation pane, click the **Organize Searches** icon.
2. In the Organize Searches window navigate to the folder you want to remove and select it.

Note: Your assigned roles and privileges control which folders you can remove. You can always remove searches and folders in your Personal Searches folder.

3. Click the **Remove** button.
4. When you are finished, click **Save**.
5. To close the Organize Searches window, click **Close**.

To remove a folder in Java Client Search tab:

1. In the Search tab, select the folder you want to delete.
2. Right-click and choose **Delete** in the menu.
3. When the confirmation prompt appears, click **Yes**.

The folder and its contents are deleted.

To remove a folder in Java Client Organize Search window:

1. Select the Searches folder, right-click and choose **Organize Search** in the menu.
2. In the Organize Search window, navigate to the folder you want to remove and select it.

Note: Your assigned roles and privileges control which folders you can remove. You can always remove searches and folders in your Personal Searches folder.

3. Click the **Remove** button.
4. When you are finished, click **Save**.

Renaming a Folder

To rename a search in Web Client:

1. In the **FOLDERS** drawer in the navigation pane, click the **Organize Searches** icon.
2. In the Organize Searches window navigate to the search you want to rename.

Note: Your assigned roles and privileges control which folders you can rename. You can always rename searches and folders in your Personal Searches folder.

3. Double-click the search name.
4. In the text field, enter a new name and press the Return key.
5. When you are finished, click **Save**.
6. To close the Organize Searches window, click **Close**

To rename a folder in Java Client Search tab:

1. In the Search tab, select the folder you want to rename.
2. Right-click and select **Rename** in the menu.
3. In the **Enter Name** field, enter a name for the folder.
4. Click **OK**.

To rename a search in Java Client Organize Searches window:

1. Select the Searches folder, right-click and choose **Organize Search** in the menu.
2. In the Organize Search window navigate to the search you want to rename and select it.

Note: Your assigned roles and privileges control which searches and folders you can rename. You can always rename searches and folders in your Personal Searches folder.

3. Click the **Rename** button.
4. In the **Enter Name** field, enter a name for the folder.
5. Click **OK**.
6. When you are finished, click **Save**.

Moving Searches and Folders

To move a search or a search folder into another folder in Web Client:

1. In the **FOLDERS** drawer in the navigation pane, click the **Organize Searches** icon.
2. In the Organize Searches window, navigate to the search or folder that you want to move.
To expand a folder, click its Expand icon.
3. Click the folder or search to select it.
4. Drag the folder or search to its new location and drop it onto a folder or a search.

As shown in "[The Web Client Organize Searches Window](#)" on page 8-66, the green arrow icons indicate the drop location for the dropped search or folder:

- ? Above the indicated folder.
- ? Into the indicated folder.
- ? Below the indicated folder

5. When you are finished, click **Save**.

6. To close the Organize Searches window, click **Close**.

To use the Search window buttons to move a search or a search folder into another folder in Java Client:

1. Select the Searches folder, right-click and choose **Organize Search** in the menu.
2. In the Organize Search window, navigate to the folder or search you want to move.
3. Click the folder or search to select it.
4. Drag the folder or search to its new location and drop it onto:
 - ? Highlighted folder – the dropped folder or search is moved into the highlighted folder.
 - ? Gray line between two names in the list of searches and folders – the dropped folder or search is moved to that location in the list.
5. When you are finished, click **Save**.

Smart URL Quick Access to Searches

You can generate quick access URLs that provide direct pointers to either Agile objects or to Agile attachment files.

These quick access URLs can be pasted into other applications or files such as spreadsheet files, word processing files, a company Intranet web page or WIKI page, or into an email.

For information about quick access to searches using search quick access Smart URLs, see:

- ? ["Formats for User-Generated Smart Object URLs for Searches"](#) on page 8-74
 - ["Smart Object Search URL Formats"](#) on page 8-74
 - ["Quick Search Smart Object URL Examples"](#) on page 8-75
 - ["Basic Search Smart Object URL Examples"](#) on page 8-75
 - ["Advanced Search Smart Object URL Examples"](#) on page 8-76
 - ["Saved Search Smart Object URL Examples"](#) on page 8-77

For information about quick access to Agile objects using quick access URLs, see:

- ? ["Agile-Generated Quick Access Object Smart URLs"](#) on page 5-24.
- ? ["Using Quick Access Object Smart URLs"](#) on page 5-24.
- ? ["Formats for User-Generated Smart Object URLs"](#) on page 5-24.

For information about quick access to attachment files using attachment quick access URLs, see:

- ? ["Smart URL Quick Access to Files"](#) on page 10-38.

Formats for User-Generated Smart Object URLs for Searches

The Agile Smart Object URL feature is designed to enable effective collaboration through email, spreadsheets, documents, WIKIs, and so forth. Users or automated tools can generate smart readable URLs that point to a specific object or attachment file in Agile PLM. See ["Formats for User-Generated Smart Object URLs"](#) on page 5-24 and ["Smart URL Quick Access to Files"](#) on page 10-38.

In addition, you can use the Smart Object URL feature to directly open a search dialog in Agile PLM Web Client. You can define a Smart URL for searches that can:

- Run a Quick search and display the quick search results in Agile PLM. See ["Quick Search Smart Object URL Examples"](#) on page 8-75.
- Open a Basic (or Parametric) search dialog that specifies the object type for the search. When the basic search dialog is displayed, then you can begin defining the search conditions. See ["Basic Search Smart Object URL Examples"](#) on page 8-75.
- Open an Advanced search dialog that specifies the object type for the search. When the advanced search dialog is displayed, then you can begin defining the search conditions. See ["Advanced Search Smart Object URL Examples"](#) on page 8-76.
- Run a Saved search and display the search results. You can specify either a global saved search or a personal saved search. See ["Saved Search Smart Object URL Examples"](#) on page 8-77.

Automated tools can also use this format to generate object URLs.

Smart Object Search URLs open search dialogs in Agile PLM Web Client.

Smart Object Search URL Formats

Smart object search URLs use the following formats

```
http://server:port/VirtualPath/object/search/<SearchType>/
[<BaseClass>]/[<ObjectType>]/[<search-condition>]
```

```
http://server:port/VirtualPath/object/search/<SearchType>/
[<BaseClass>]/[<ObjectType>]/
```

```
http://server:port/VirtualPath/object/search/<SearchType>/
<SearchFolder>/<SavedSearch>
```

where the URL has the following representation:

Table 8–38 Smart Object Search URL parameters

Parameter	Description
server port VirtualPat	Server, port, and VirtualPath identify the Agile PLM instance
object	The text "object" indicates to Agile PLM that the URL is an object URL.
search	The text "search" indicates to Agile PLM that the Smart URL opens a search.
SearchType	Specifies the trype of search to open. Choices are: quick, basic, advanced, or saved.
BaseClass	The base class you wish to specify for the Smart URL search.
ObjectType	The class or subclass you wish to specify for the Smart URL search. If you specify an ObjectType, then you must also specify a BaseClass.

Table 8–38 (Cont.) Smart Object Search URL parameters

Parameter	Description
search condition	For Smart URL Quick search only: Enter the text string to use in the quick search.
SearchFolder	For Smart URL Saved Search only: Enter the name of the folder that contains the saved search to be opened.
SearchName	For Smart URL Saved search only: Enter the name of the saved search to be opened.

Quick Search Smart Object URL Examples

```
http://server:port/VirtualPath/object/search/quick/<BaseClass>/
<ObjectType>/search_condition_text
```

Opens a browser window, displaying the quick search results. To display search results, you must specify the base class, the object type, and a search condition text string. If you omit parameters the search condition, object type or base class in the URL, Agile PLM displays Web Client with the quick search field selected and highlighted. You can immediately begin to type the search condition text.

Examples:

```
http://server:port/VirtualPath/object/search/quick/Items/Parts/green
```

Searches for part objects with the search condition green, and displays the search results in the Web Client search results page.

```
http://server:port/VirtualPath/object/search/quick/Items/Parts/
```

Displays Web Client content pane with quick search field selected and highlighted. Enter the search condition text. The search is limited to the object type specified in the URL, in this example, Parts.

```
http://server:port/VirtualPath/object/search/quick/Items/Parts/green
```

Displays Web Client content pane with quick search field selected and highlighted. Enter the search condition text. The search is limited to the base class specified in the URL, in this example, Items.

```
http://server:port/VirtualPath/object/search/quick/
```

Displays Web Client window with quick search field selected and highlighted. Enter the search condition text. A quick search of All object types is performed.

Basic Search Smart Object URL Examples

```
http://server:port/VirtualPath/object/search/basic/
<BaseClass>/<ObjectType>/
```

Displays the Basic search window. The specified base class and object type are preselected in the search pane. Begin to define any parametric search attributes.

Note: The Agile administrator determines which attributes appear in the list of parametric criteria in the basic search window. For more information, see *Agile PLM Administrator Guide*.

Examples:

```
http://server:port/VirtualPath/object/search/basic/  
<BaseClass>/<ObjectType>/
```

Displays the Basic search window. The specified base class and object are preselected in the search pane. Define the desired parametric search attributes.

```
http: //server:port/VirtualPath/object/search/basic/<BaseClass>/
```

Displays the Basic search window. The specified base class is preselected in the search pane. If needed, select an object type. Define the desired parametric search attributes.

```
http: //server:port/VirtualPath/object/search/basic/
```

Displays the Basic search window. The default base class is selected in the search pane. If needed, select a base class and object type. Define the desired parametric search attributes.

Advanced Search Smart Object URL Examples

```
http://server:port/VirtualPath/object/search/advanced/  
<BaseClass>/<ObjectType>/
```

Displays the Basic search window. The specified base class and object type are preselected in the search pane. Begin to define any parametric search attributes.

Examples:

```
http: //server:port/VirtualPath/object/search/advanced/  
<BaseClass>/<ObjectType>/
```

Displays the Advanced search window. The specified base class and object are preselected in the search pane. Define the desired search criteria.

```
http: //server:port/VirtualPath/object/search/advanced/<BaseClass>/
```

Displays the Advanced search window. The specified base class is preselected in the search pane. If needed, select an object type. Define the desired search criteria.

```
http: //server:port/VirtualPath/object/search/advanced/
```

Displays the Advanced search window. The default base class is selected in the search pane. If needed, select a base class and object type. Define the desired search criteria.

Saved Search Smart Object URL Examples

```
http://server:port/VirtualPath/object/search/saved/
<SearchFolder>/<SavedSearch>
```

Displays the specified saved search and the search results in the search window. You can specify either a global saved search, or a personal saved search.

You must specify both the search folder name and the saved search name. These two parameters (folder name and search name) comprise the unique identifier for the saved search.

Note: In the case where one or more saved searches in the Agile PLM database have the same unique identifier (the same folder name and the same saved search name), then Agile PLM uses the saved search that was created first. Folder and search names are case-sensitive.

For example, Bob has organized his personal saved searches in several subfolders in his Personal Searches folder. Bob collaborates with Sally by sending her a Smart Object URL for one of his personal searches:

```
http://server:port/VirtualPath/object/search/saved/
Taurus Project/Taurus Mechanical Parts/
```

When Sally clicks the Smart URL, the search results of Bob's saved search is displayed in Sally's Agile PLM window.

Examples:

```
http: //server:port/VirtualPath/object/search/saved//Workflow Searches/
Changes that I am as Approver of/
```

Displays the search results window of the specified global search.

```
http: //server:port/VirtualPath/object/search/saved/
Sally Personal Searches/Sally Saved Search/
```

Displays the search results window of the specified personal search.

Routing Objects with Workflows

Workflows provide an automated process for routing, approving, and releasing changes and other routable objects.

About Workflows

Workflows automate the change control process by performing or completing tasks that you previously performed manually. For example:

- When you create a routable object, you can select the appropriate workflow from the list of available workflows for that routable object.
- When the routable object moves into a Review or Released status type, the lists of approvers and observers can be automatically selected.
- When all the approvers have signed off for a Review or Released status type, and all the required fields have been completed, the routable object can be automatically promoted to the next status with the AutoPromote feature.
- By defining a workflow with multiple Review or Released status types, you can sequentially route an object to different lists of approvers and observers.
- When all required fields have been filled in on a routable object, it can be autopromoted to the next status.
- When an approver does not respond within the specified reminder period set by the Agile administrator, a reminder email will be sent automatically.
- If the approver does not respond within the specified escalation period set by the Agile administrator, the routable object will be sent to that user's designated escalation person. The designated escalation person can then approve or reject the routable object in place of the original approver.
- You can transfer your authority to approve the routable object to another user for a specified time period. If you have the appropriate privileges, you can transfer signoff authority for other users.

Status List

At its most basic level, a workflow consists of:

- A unique name
- A list of matching criteria
- A list of statuses

The status list defines the ordered list of statuses (or steps) that the routable object must go through during the change control process. The Agile administrator can define each workflow to have as many statuses as required. Each status is of a particular status type. Some status types may be used only once in a workflow, while others may be used multiple times.

The following section lists and defines the different status types.

Status Types and Definitions

Before a workflow is selected for a routable object:

- ⌚ **Unassigned** – Unassigned is a placeholder, that is, the default initial status name before a routable object has been matched with a workflow.

Basic Status Types (Active):

- ⌚ **Pending** – An originator is developing the routable object. A workflow must begin with a Pending status type. It is the first status in every workflow and is used only once in each workflow.
- ⌚ **Submit** – The Submit status type sends the routable object to the specified routing manager, who determines whether to promote the routable object to the next status.
- ⌚ **Review** – The Review status type routes the routable object to CCB members (approvers, acknowledgers, and observers). When all approvers and acknowledgers have signed off, and required fields have been completed, the routable object is automatically promoted to next status in the status list if AutoPromote is enabled. If Autopromote is not enabled, the routable object is manually moved to the next status by the routing manager.
- ⌚ **Released** – When a routable object enters the first Released type status, Agile PLM performs a series of checks; it also creates new revisions of the affected items (ECOs) with the new BOM, incorporates redlines into a new "rev," or updates the manufacturer part information (MCOs).

Like the Review status type, the Released status type may have approvers, acknowledgers, and observers and be routed for signoff and may be autopromoted.

Only the first Released status actually releases the routable object. Subsequent Released status types—given distinguishing status names—provide additional review/approval cycles for the released routable object.

Returning a released routable object to any of the first three status types (Unassigned, Pending, Submit) unreleases the routable object and removes approvals that were gathered. A Deviation can be unreleased if it does not have affected items.

- ⌚ **Complete** – If Complete status type is used, it must be the last active status in the workflow, and it may be used only once.

Special Status Types (Inactive)

- ⌚ **Hold** – The Hold status type provides a way to temporarily remove a routable object from the workflow and reinsert it later. It is added to the end of the status list as it is never part of the active sequence of statuses.

Hold unreleases a routable object.

Given appropriate privileges, you can manually move a routable object to Hold from any other status in the workflow (assuming it is listed as a valid next status under the Manual Valid Next Status property). It stays there until you manually move it back into the workflow. These moves require proper Change Status privileges.

- ⌚ **Cancel** – The Cancel status provides a way to remove a routable object from the workflow. Cancel unreleases a routable object.

Cancel resets the workflow.

When a routable object is canceled, any redlines associated with the routable object are discarded.

Given appropriate privileges, you can manually move a routable object to Cancel from any other status in the workflow (assuming it is listed as a valid next status under the Manual Valid Next Status property).

Show/Hide Workflows within a Class

When you open the **Workflow** tab of a routable object, the tab displays a graphical chart of the workflow and a workflow signoff history table.

To hide the workflow chart:

- Web Client: the Expand icon and Collapse icon controls to the left of the Summary (*Workflow Name*) heading. Click these controls to show a hidden workflow summary or to hide the workflow summary.
- Java Client: The **Hide/View workflow chart** button controls the display of the workflow chart on the **Workflows** tab. Toggle this button to Hide or View the workflow chart.

If the workflow is not visible and you click the button or control icon, the ECO's workflow appears, and the same is true for the workflow of any ECO you open at this point. If you click the Expand/Collapse icon or the **Show/Hide Workflow** button again, the workflows are hidden in all ECOs. The switch controls the View/Hide mode for all objects in that Agile class (for example, ECOs, PCOs, or Problem Reports). This is on a "per computer" basis, that is, it is not dependent on which user is logged on or other factors.

Multiple Hold and Cancel Status

Your Agile administrator may define custom workflows that include multiple Hold and Cancel statuses.

The Next Status button on the Cover page also lets you move the routable object to any of the permissible order of statuses available in the workflow. The drop down menu on the Next Status button lists additional statuses: Hold and Cancel.

- The **Hold** status appears from the status from which it is initiated.


Example: The general routing of a business object (PSR) is as given below:

Unassigned, Pending, Submitted, Review, Released, Closed. Once you reach the Submitted status, additional workflow statuses Hold and Cancel are available on the Workflow chart.

- You can initiate single Hold and Cancel status or multiple Hold statuses.

Example: While moving from one status to another you can initiate Hold status at any point:

- (Hold_info) – gather more information
- (Hold_test) – to test

Figure 9–1 Example workflow with multiple Hold statuses

You can click either of the above for a single Hold.

To gather more info *and* test then you need to initiate Multiple Holds. Naming the Hold indicates the purpose of the Hold status. You can have multiple hold statuses with unique names.

Significant points:

- 7 You can move to Hold or Cancel status from any of the existing statuses.
Example: If you are in the **Implemented** status you can move to **Hold** and then either come back to **Implemented** or move to **Review** status.
- 7 When you move back from Hold, existing Approvers and Observers of a workflow do not change.
- 7 A Hold or Cancel will display in the workflow diagram if it is a valid status change.
- 7 Active hyperlinks indicate valid status of the workflow.
- 7 The Hold status displays in the workflow for the duration of the current cycle. If the status changes to **Pending** or **Submitted**, the **Hold** status does not display on the workflow.
- 7 **Hold** Status for current and previous statuses will appear on the workflow for the duration of the current cycle.
- 7 Cancel signals the end of the workflow.

When you return from a Cancel status, the workflow is reset. Cancel does not appear on the workflow.

Default Workflows

Agile PLM includes default workflows for each routable object type. Default workflows provide the same change control process as previous Agile releases.

Changes Base Class Default Workflows

Note: The Hold and Canceled statuses are optional, and are not part of the sequential status list.

Table 9–1 *Changes objects default workflows*

Default Workflow Name	1st Status	2nd Status	3rd Status	4th Status	Final	Optional
Default Change Orders	Pending	Submitted	CCB	Released	Implemented	Hold Canceled
Default Site Change Orders	Pending	Submitted	CCB	Released	Implemented	Hold Canceled
Default Change Requests	Pending	Submitted	CCB	Released	Closed	Hold Canceled
Default Deviations	Pending	Submitted	CCB	Released	Expired	Hold Canceled
Default Stop Ship	Pending	Submitted	CCB	Released	Resumed	Hold Canceled
Default Manufacturer Orders	Pending	Submitted	CCB	Released	First Article Complete	Hold Canceled

Transfer Order Class Default Workflows

Table 9–2 *ATO (Automatic Transfer Order) default workflow*

Default Workflow Name	1st Status	2nd Status	Final
Default ATOs	Pending	Released	Complete

The Default ATOs workflow is read-only.

Table 9–3 *CTO (Content Transfer Order) default workflow*

Default Workflow Name	1st Status	2nd Status	3rd Status	Final
Default CTOs	Pending	Review	Released	Complete

Product Service Request Class Default Workflows

Note: The Hold and Canceled statuses are optional, and are not part of the sequential status list.

Table 9–4 *Problem Report object and Non-Conformance Reports default workflows*

Default Workflow Name	1st Status	2nd Status	3rd Status	4th Status	Final	Optional
Default Problem Reports	Pending	Submitted	Review	Released	Closed	Hold Canceled
Default Non-Conformance Reports	Pending	Submitted	CCB	Released	Closed	Hold Canceled

Table 9–5 CAPAs object default workflow

Default Workflow Name	1st Status	2nd Status	3rd Status	4th Status	5th Status	Final	Optional
Default CAPAs	Identified	Acknowledged	Investigated	Implemented	Validated	Closed	Hold Canceled

Table 9–6 Audit object default workflow

Default Workflow Name	1st Status	2nd Status	3rd Status	4th Status	5th Status	6th Status	Final	Optional
Default Audits	Preparation	Initiation	Analysis	Issued	Correction	Validated	Closed	Hold Canceled

Project Base Class Default Workflows

Note: The Canceled status is optional, and is not part of the sequential status list.

Table 9–7 Projects base class default workflows

Default Workflow Name	1st Status	2nd Status	3rd Status	Final	Optional
Default Activities	Not Started	In Process	Review	Complete	Canceled
Default Gates	Closed	In Review	Open	Closed	Canceled

Default Packages Workflow

Note: The Hold and Canceled statuses are optional, and are not part of the sequential status list.

Table 9–8 Packages object default workflow

Default Workflow Name	1st Status	2nd Status	3rd Status	4th Status	Final	Optional
Default Audits	Pending	Submitted	Review	Accepted	Closed	Hold Canceled

Default File Folders Workflow

The Default File Folders workflow has one status, Review. The Default File Folders workflow and the Default ATOs workflow are read-only.


Example of a Customized Workflow

The following figure shows an example of a customized workflow. Notice that this workflow has three different Review status types and two different Released status types. A routable object using this workflow is:

- 7 Routed through an approval cycle (Review status type) before it is submitted to the change analyst.
- 7 Routed through two approval cycles (Review status type) before it is released, with a different group of approvers for each approval cycle.
- 7 Released when it moves into the first Released status type.
- 7 Moved into the second Released status type after the required fields have been filled in and, at this status, routed for approval a final time before moving into the Complete status type.

Customized Agile workflows allow great flexibility in defining change control processes to meet your company's needs.

Figure 9–2 Example custom workflow diagram



Using Workflows in the Change Control Process

When a routable object is first created, it has no workflow assigned to it; therefore, it has no workflow status. Until you select a workflow for the routable object, it remains unassigned, and the Unassigned status stamp is displayed in the upper right corner of the **Cover Page** tab.

You can edit an unassigned routable object the same way you edit a routable object in a Pending status type: fill in fields, add items to the **Affected Items** tab, add files to the **Attachments** tab, and so on.

When you have finished editing an Unassigned routable object, or a routable object in the Pending status type, and you are ready to start the routable object moving through the change control process, use the **Next Status** button.

While promoting workflows (of Changes, PSRs, QCRs and Declarations) to the **Next Status**, if no Change Analyst is assigned, a default Change Analyst is automatically populated to the field. The system assigns the default Change Analyst even if the user does not have the Modify privilege for the Change Analyst field.

Selecting a Workflow

Until you select a workflow for a routable object, the routable object remains unassigned, and the Unassigned status stamp is displayed in the upper right corner.

To select a workflow for an unassigned routable object in Web Client:

1. Open the routable object to which you want to assign a workflow.
2. When working with an unassigned routable object, you can use either of these methods to select a workflow:
 - ⌘ On the **Cover Page** tab, click the **Edit** button.
 - a. Select a workflow from **Workflow** drop-down list.
 - b. Click **Save**.

The status of the routable object switches to the first status in the selected workflow which is always a Pending status type.
 - ⌘ Or, click the **Next Status** button above the tabs.
 - a. If there is no workflow assigned, you are prompted to select one.
 - b. Complete any required fields, for example, select a Change Analyst.

If the workflow specifies a Default Change Analyst, then the Change Analyst field is automatically populated by the workflow, even if you do not have the Modify privilege for the Change Analyst field.
 - c. Click **Continue**. Agile PLM routes the object to the first non-pending status in the workflow, usually a Submitted status type.
 - d. Choose any users you want to notify.
 - e. Enter any comments you want to send.
 - f. Click **Finish**.

All the workflows that match the routable object are shown in the drop-down list. The drop-down list may vary depending on whether the Agile administrator has created any custom workflows.

Note: As long as the routable object is in the Pending status type, you can select a different workflow. You can also select the blank field in the **Workflow** drop-down list, which switches the routable object to the Unassigned status and cancels the previous workflow selection.

To select a different workflow for a routable object that is not in either the Unassigned status or the Pending status type, you must switch the status to the Pending status type first. (See ["Returning a Routable Object to the Originator"](#) on page 9-39.).

To select a workflow for an unassigned routable object in Java Client:

1. Open the routable object that you want to assign a workflow to.
2. When working with an unassigned routable object, you can use either of these methods to select a workflow:
 - ? On the **Cover Page** tab, select a workflow from **Workflow** drop-down list.
 - a. Click **Save** in the object window.

The status of the routable object switches to the first status in the selected workflow, which is always a Pending status type.
 - ? Or, click the **Next Status** button above the tabs.
 - a. If there is no workflow assigned, you are prompted to select one in the Select Required Fields dialog drop-down list.
 - b. Complete any required fields, for example, select a Change Analyst.
 - c. Click **OK**. Agile PLM routes the object to the first non-pending status in the workflow, usually a Submitted status type.
 - d. Choose any users you want to notify.
 - e. Enter any comments you want to send.
 - f. Click **Submit**.

All the workflows that match the routable object are shown in the drop-down list. The drop-down list may vary depending on whether the Agile administrator has created any custom workflows.

Note: As long as the routable object is in the Pending status type, you can select a different workflow.

To select a different workflow for a routable object that is not in either the Unassigned status or the Pending status type, you must switch the status to the Pending status type first. (See ["Returning a Routable Object to the Originator"](#) on page 9-39.).

Working with Workflows

This section includes the following topics:

- ? ["Auditing Routable Objects"](#) on page 9-12
- ? ["Switching a Routable Object from One Status to Another Status"](#) on page 9-10
- ? ["Demoting a Routable Object"](#) on page 9-17

- ? ["Completing the Status Change"](#) on page 9-17
- ? ["Handling Routed Changes"](#) on page 9-20
- ? ["Approving Ratable Objects"](#) on page 9-27
- ? ["Rejecting Ratable Objects"](#) on page 9-30
- ? ["Reminder Period and Review Escalation Period"](#) on page 9-34
- ? ["Designated Escalation Person"](#) on page 9-34
- ? ["Transferring Signoff Authority"](#) on page 9-35
- ? ["Defining Personal Criteria for Authority Transfers"](#) on page 9-38
- ? ["Returning a Ratable Object to the Originator"](#) on page 9-39
- ? ["Canceling a Ratable Object"](#) on page 9-40
- ? ["Uncanceling a Ratable Object"](#) on page 9-41
- ? ["Putting a Ratable Object on Hold"](#) on page 9-42
- ? ["Releasing Ratable Objects"](#) on page 9-42
- ? ["Unreleasing Ratable Objects"](#) on page 9-43
- ? ["Multiple Released Status Types"](#) on page 9-44
- ? ["Adding Comments to the History Tab"](#) on page 9-45
- ? ["Changing a Ratable Object's Subclass"](#) on page 9-46

Switching a Ratable Object from One Status to Another Status

Ratable objects move through the change control process by moving through the statuses in the workflow status list. Ratable objects make the transition from one status to another status in two ways:

- ? The ratable object is autopromoted from its current status to the next status in the workflow status list.
- ? An Agile user switches the ratable object from one status to another status manually.

For details about switching a ratable object from the Unassigned status, see ["Selecting a Workflow"](#) on page 9-8.

A ratable object is manually switched from one status to another in one of the following ways:

- ? The **Next Status** button switches the ratable object from the current status to the next sequential status in the workflow status list. Click this button, and the appropriate change status dialog is displayed.
- ? The **Workflow** tab lets you switch the ratable object from the current status to any status allowed by the settings in the workflow (*manual valid next status*). The status need not be the next status in the workflow status list. For example, you might switch a ratable object from a Submit status type to a Hold status type.

Whether you use the **Next Status** button or the **Workflow** tab, you must have the appropriate privileges to switch a ratable object from one status to another status. See the Agile administrator if you have questions about your privileges.

Switching the Status of a Ratable Object

You can use the **Workflow** tab or the **Next Status** button to switch the status of a ratable object to any valid next status.

To switch a routable object to any valid next status in Web Client:

1. Open the routable object.
2. Audit the routable object to ensure that there are no errors that prevent switching to another status. If any errors are found, fix them. See ["Auditing Rutable Objects"](#) on page 9-12.
3. Click the **Workflow** tab.

Note: The valid next statuses that appear in the Workflow Summary are determined by workflow property settings and your privileges. To review the entire status list, choose **Actions > View Workflows**. Click **Close** to close the View Workflow dialog.

4. Select one of the valid next statuses from the chart on the **Workflow** tab, or click the **Next Status** button to accept the default next status in the sequence.
5. When the Change Status dialog appears, add the appropriate approvers, observers, users to notify, and comments. See ["Auditing Rutable Objects"](#) on page 9-12.
6. Click **Finish**.

The routable object moves to the selected status, which is the orange status on the **Workflow** tab.

To switch a routable object to any valid next status in Java Client:

1. Open the routable object.
2. Audit the routable object to ensure that there are no errors that prevent switching to another status. If any errors are found, fix them. See ["Auditing Rutable Objects"](#) on page 9-12.
3. Click the **Workflow** tab.

Note: The valid next statuses (underlined statuses) that appear on the **Workflow** tab are determined by workflow property settings and your privileges. To review the entire status list, click the **View Workflows** button in the toolbar. Click **Close** to close the View Workflows dialog box.

4. Click one of the valid next statuses from the chart on the **Workflow** tab, or click the default next status (underlined). Or click the **Next Status** button above the tabs to accept the default next status in the sequence.
5. When the Change Status dialog box appears, add the appropriate approvers, observers, users to notify, and comments. See ["Adding and Removing Approvers, Acknowledgers, and Observers"](#) on page 9-21.
6. Click the dialog button that completes the status change, for example, **Submit**, **Route**, or **Release**.

The routable object moves to the selected status, which is the yellow status on the **Workflow** tab.

Save Routing Slip Content when Advancing Change

When you manually advance a workflow to the next status, the routing slip is filled in. This contains approvers, observers, "notify" users, and comments. In Web Client, the routing slip also includes acknowledgers. You may spend several minutes completing the slip. When you click **Route** or **Finish**, Agile performs an automatic workflow status audit.

• Web Client

The change status dialog is displayed again, with an error message that lists the errors and the actions taken. The remainder of your user lists and comments are preserved.

• Java Client

An error message dialog is displayed, listing the errors and actions taken. Click **OK** to acknowledge the error message. The change status dialog is displayed again. The remainder of your user lists and comments are preserved.

At this time, you can continue filling out the change status routing slip information and route the change status again.

Alternately, you can copy the routing slip data and paste it to a temporary location, such as a word processor file. This lets you save the work you have done so far.

Auditing Routable Objects

You can audit a routable object at any status in the workflow. Before switching the routable object to a different status, always audit the object to detect any errors that may prevent switching to a different status.

With appropriate privileges, you can perform two types of audits: a status audit and a release audit.

Note: When a routable object moves from the current status (including the Pending status type, the first status in the workflow) to the next status in the workflow, the system automatically performs a release audit depending on the workflow Pass Release Audit property settings for the current status.

In Web Client, the audit results dialog remains open until you close it, allowing you to refer to the audit results as you modify the routable object. You can use the **Print** button in the results dialog to print the audit results for your reference. Clicking each audit issue navigates you to the error. If you have the appropriate privileges, you can modify the highlighted field to correct the issue.

In Java Client, the audit results box remains open until you close it. This lets you refer to the audit results as you modify the routable object.

Note: Your Discovery and Read privileges determine which objects and which fields you can see in the audit results box. If you do not have the appropriate privileges, you may see the words "No Privilege" displayed.

See also ["Switching a Routable Object from One Status to Another Status"](#) on page 9-10.

Status Audit, Conditions Audited

The **status audit** is performed automatically when you use the Change Status function or the workflow attempts to autopromote to the next status. You can perform a status audit at any time by using the **Audit Status** button or menu selections. It performs the following checks:

- Makes sure the Exit Required Fields for the current status are filled in.
- If the current status is a Review status type or a Released status type, makes sure that all approvers have approved.

- Checks the workflow settings of the Pass Release Audit property for the current status. If Pass Release Audit is set to either Yes or Warning, Agile PLM also performs a release audit.

Release Audit, Conditions Audited

Agile PLM performs a release audit automatically when the routable object is promoted to the first Released type status in the workflow. You can perform a release audit at any time by using the **Audit Release** button or menu selections.

The release audit performs the status audit for both the current status and the release status.

It performs the following additional checks:

- For ECOs, checks if the proposed new revision number on the **Affected Items** tab already exists.
- For ECOs, SCOs, PCOs and MCOs, checks if there are manufacturer redlines that will be lost after the routable object is released.
- For ECOs and SCOs, checks if there are BOM redlines that will be lost after the routable object is released.
- For ECOs, SCOs, PCOs and MCOs, checks if there are conflicts due to another ECO, SCO, or MCO being released first.
- For ECOs, SCOs, and MCOs, if the BOM Multi-level Recursive SmartRule is set to Disallow, checks for recursive BOM structures, that is, when a subassembly includes one of its parent items from an upper level of the BOM tree structure on its own BOM. (A recursive BOM structure, if carried to its logical conclusion, would repeat indefinitely).

The BOM tree is evaluated from top to bottom. The Audit Release error message indicates, for each affected item with a recursive BOM, the first item found in the BOM tree whose first-level BOM table includes an item that appears at a higher level in the BOM tree, thus causing a recursive BOM structure. Although there may be multiple instances of recursive BOM structure in an affected item BOM tree, only the first found instance is displayed in the audit results.

- For ECOs, SCOs, and PCOs, depending on SmartRule settings, checks for duplicate items, duplicate find numbers and duplicate reference designators caused by a change rebased. (When there are multiple pending changes for the same item, when one change is released, the remaining pending changes are rebased on the latest released change.)
- For ECOs, SCOs, and MCOs, checks for duplication of the same manufacturer part on an item. (MultipleItemsPerManufPart is set to Warning or Disallow.)

(Duplication of the same manufacturer part on an item occurs when an item has multiple pending changes which associate the same manufacturer part to that item and one change is released. The remaining pending changes are rebased on the latest released change. The remaining pending changes now include manufacturer part redline modifications to add a manufacturer part that already exists on the released item's Manufacturers table.)

- For ECOs, SCOs, and MCOs, checks for the use of the same manufacturer part on multiple items. (MultipleItemsPerManufPart is set to Warning or Disallow.)

(Duplication of the same manufacturer part on multiple items occurs when multiple changes add the same manufacturer part to two or more items' Manufacturers tables, either by redline addition or redline replacement. When one of the changes is released, the manufacturer part's Where Used table is rebased to refer to the newly released item. The remaining pending changes now include manufacturer part redline modifications that would allow a single manufacturer part to be used by multiple items.)

- ⌚ For ECOs, SCOs, and PCOs, if the Item Release First SmartRule is set to Disallow or Warning, then the routable object is checked to see if the child components have been released.
- ⌚ Checks if any of the attachments of the routable object remain checked out.
- ⌚ For every affected item, checks if any of the attachments remain checked out.
- ⌚ Checks the Effectivity Date Order and Effectivity Gap SmartRule settings.
- ⌚ Checks if items on the **Affected Items** tab have any other pending routable objects.
- ⌚ For ECOs, validates the affected item's **Sites** tab **Make/Buy** setting with the site's **Site AML Allowed** and **AML Required on Buy** settings. For more information, see *Product Collaboration User Guide*.

Modifying the Make/Buy Field on the Item Sites Tab

If you have the appropriate modify privileges, then you can modify the **Make/Buy** field in the Sites table of an item, even if the item has been released. However, the Make/Buy setting is not revision-specific. When you modify the Make/Buy setting on any item revision, it is also modified for all revisions. The following restrictions apply when modifying the **Make/Buy** setting:

- ⌚ When the item is included on the affected items table of a change order, the release audit validates the **Site AML Allowed** and **AML Required on Buy** settings of the site with the item **Sites** tab **Make/Buy** setting for that revision. Past revisions are not audited. (A release audit is performed automatically when the change order is released.)
- ⌚ Because the **Make/Buy** setting is not revision-specific and can be changed without using a change order, any validation violations caused by a modification to **Make/Buy** remain on the latest released revision of the item and may not be detected until the next time the item is added to a change order and the change order is release audited.

Performing a Status Audit

To audit the current status of a routable object in Web Client:

1. Open the routable object you want to audit.
You may audit a routable object from any tab.
2. Choose **Actions > Audit Status**.
The Audit Status Results dialog appears.
 - ⌚ Click the **Print** button to print the audit results.
 - ⌚ Click **Close** to close the Audit Status Results dialog.
3. Click an error message. Agile PLM navigates to the appropriate tab where the error exists and indicates the field, table row, or table cell where the error exists.
Depending on the error, Agile PLM may navigate to a field on the routable object, or to a field on an affected item.
4. If you have the appropriate privileges, you can modify the field to resolve the error.
The audit window remains open while you resolve the audit issues.
5. At any time, you can click the **Audit** button in the Audit Status Results dialog to perform the audit again.

To audit the current status of a routable object in Java Client:

1. Open the routable object you want to audit.

You may audit a routable object from any tab.

2. Click the **Audit Status** button above the tabs. Or right-click in the Agile Java Client window; in the menu that appears, choose **Audit Status**.

The Audit Results for Audit Status dialog box appears.

If there are errors, correct them and audit again.

3. To close the Audit Results dialog box, click **OK**.

Performing an Audit Release

To audit the routable object for release in Web Client:

1. Open the routable object you want to audit for release.

You may audit a change from any tab.

2. Choose **Actions > Audit Release**.

The Audit Status Results dialog appears.

? Click the **Print** button to print the audit results.

? Click **Close** to close the Audit Status Results dialog.

3. Click an error message. Agile PLM navigates to the appropriate tab where the error exists and indicates the field, table row, or table cell where the error exists.

Depending on the error, Agile PLM may navigate to a field on the routable object, or to a field on an affected item.

4. If you have the appropriate privileges, you can modify the field to resolve the error.

The audit window remains open while you resolve the audit issues.

5. At any time, you can click the **Audit** button in the Audit Status Results dialog to perform the audit again.

6. For ECOs, SCOs, and PCOs, if the Item Release First SmartRule is set to Warning or Disallow and there are unreleased children:

- a. Click the error link to navigate to the **Affected Items** tab.

The unreleased children are automatically added to the affected items table.

7. For ECOs, SCOs, and MCOs, if the BOM Multi-Level Recursive Smart Rule is set to Warning or Disallow, and there is a recursive BOM:

- a. Click the error link to navigate to the first item found in the BOM tree whose first-level BOM table includes an item that appears at a higher level in the BOM tree, thus causing a recursive BOM structure.

The BOM tree is evaluated from top to bottom. Although there may be multiple instances of recursive BOM structure in the affected item BOM tree, only the first instance is displayed in the Audit Status Results dialog.

- b. Correct the recursive BOM error.

- c. Click the **Audit** button in the Audit Status Results dialog to perform the audit again. The next recursive BOM error in the BOM tree is displayed in the audit results, if such an error exists.

- d. Repeat steps b and c until all the recursive BOM errors have been corrected.

8. At any time, you can click the **Audit** button in the Audit Status Results dialog to perform the audit again.

To audit the routable object for release in Java Client:

1. Open the routable object you want to audit for release.
You may audit a change from any tab.
2. Click the **Audit Release** button above the tabs. Or right-click in the Agile Java Client window; in the menu that appears, choose **Audit Release**.
The Audit Results for Audit Release dialog box appears.
If there are errors, correct them and audit again.
3. To close the Audit Results dialog box, click **OK**.

Autopromotion Failure

When all the approvers have signed off for a Review or Released status type, and all the required fields have been completed, the routable object can be automatically promoted to the next status with the AutoPromote feature.

If autopromotion fails, the routing manager receives a notification. The routing manager should investigate why autopromotion failed and take the necessary action to move the routable object forward in the workflow.

Autopromotion may fail for one or more of the following reasons:

- ? An attachment on the routable object, for example, a change order, remains checked out.
Either check-in the attachment or cancel the checkout, and then use **Next Status** to move the routable object to the next status in the workflow. See "[Switching the Status of a Routable Object](#)" on page 9-10.
- ? For one or more affected items of the routable object, an attachment remains checked out.
Either check in the attachment or cancel the checkout, and then use **Next Status** to move the routable object to the next status in the workflow. See "[Switching the Status of a Routable Object](#)" on page 9-10.

Redline Conflicts

If an affected item has two or more unreleased changes and each of those changes includes redlines to the item. The redlines are in conflict, for example, both ECOs include redlines to the quantity of the same BOM item.

Or an affected item has two or more unreleased changes with redlines and there are no redline conflicts while both changes are unreleased. However, if the current change is released, it will cause the other change to have redline conflicts with the most recently released revision of the item.

The change analyst can determine how to resolve the conflict:

- ? Examine the pending changes and decide which redlines you want to keep. You can remove redlines or you may decide to remove the item from the Affected Items table of one of the changes. Advance the status manually.
- ? Or, manually advance the status of one of the changes. A warning appears that tells you that releasing the change will cause another change to lose redlines. Ignore the warning and release the change; the redlines are removed from the remaining change.

Ability to Fail Autopromote More than Once within same Change Status

This feature notifies whoever is specified in the status's If Autopromote Fails, Notify setting each time a change order fails to autopromote if new approvers were added since the last autopromote failure. Additionally, History is updated if Autopromote fails when a new approver is added but does not complete all workflow-required fields.

Demoting a Routable Object

You promote a routable object by moving it through the sequential list of statuses in the workflow. If the workflow allows it, and if you have the appropriate privileges, you can also use the **Workflow** tab to demote a routable object by moving the routable object to a previous status in the workflow status list. From that previous status, the routable object then moves through the workflow again. For an example, see ["Returning a Routable Object to the Originator"](#) on page 9-39.

If the routable object has entered the first Released status type, moving the routable object to a previous status in the workflow status list unreleases the routable object, and may have undesirable consequences. For more information, see ["Releasing Routable Objects"](#) on page 9-42.

Agile administrative settings determine what happens when a routable object again moves through a status with approvers and observers (Review status type or Released status type) after status demotion. Depending on the settings, the following rules apply:

- Demotion Approvers Removal SmartRule:
 - **Remove:** any ad hoc approvers and observers added during the first time through the Review status type or Released status type are removed for the second Review status type or Released status cycle.
 - **Retain:** ad hoc approvers and observers added during the first time through the Review status type or Released status type are kept on the approvers and observers lists for the second Review status type or Released status type cycle.
- Demotion Signoff Removal SmartRule:
 - **Remove:** When a routable object enters the Review status type or Released status type the second time, all approvals and rejections from the first routing cycle are removed, and the approvers and observers must sign off again. (The approvals and rejections from the first routing cycle are still shown on the **Workflow** tab.)
 - **Retain:** When a routable object enters the Review status type or Released status type the second time, all the approvals and rejections from the first routing cycle are retained in the second routing status cycle and displayed in the signoff summary table. The approvers and observers who have already signed off do not need to sign off again.

Completing the Status Change

Whenever you switch a routable object from one status to another, you must complete the Change Status dialog. The Change Status dialog for all status types includes a list of people to notify (the **To:** field in Web Client and the **Notify** field in Java Client) and a **Comments** field. For the Review status type and Released status type, additional fields for approvers, acknowledgers, and observers are included.

By default, you can switch a routable object to a Submit status type only if you are the originator, or if you have the appropriate privileges. Typically, the routing manager has the appropriate privileges to submit routable objects.

Note: If the routing manager field (for example, the **Change Analyst** field) on the Cover Page of the routable object is left blank, and if the workflow is defined to notify the default routing manager, then when you switch to a Submit status type, the routable object is submitted to every user on the routing manager drop-down list.

You must include at least one change analyst in the Notify users list of the Change Status dialog.

Only the originator and users with the appropriate privileges can submit a routable object.

You cannot submit a routable object to a routing manager who does not have Discovery and Read privileges for that routable object. (See the *Agile PLM Administrator Guide* for details.)

By default, you can switch a routable object to a Submit status type only if you are the originator, or if you have the appropriate privileges. Typically, the change analyst or component engineer has the appropriate privileges to submit routable object.

To complete the Change Status page in Web Client:

1. Select a new status by using either the **Next Status** button or the **Workflow** tab. See ["Switching a Routable Object from One Status to Another Status"](#) on page 9-10.

The Change Status dialog appears.

The Notify **To:** field may already contain a list of names, as specified in the workflow, or the **To:** field may be blank. In either case, you can add names to the **To:** field if you choose to do so.

2. To add names to the **To:** list, type the names of the users to be notified.

Or, click the icon to launch the address book palette.

You may select individual usernames or user groups. See ["Adding and Removing Approvers, Acknowledgers, and Observers"](#) on page 9-21.

3. Add any comments in the **Comments** field.
4. Click **Finish**.

To complete the Change Status dialog box in Java Client:

1. Select a new status by using either the **Next Status** button or the **Workflow** tab. See ["Switching the Status of a Routable Object"](#) on page 9-10.

The Change Status dialog box appears.

The **Notify** field may already contain a list of names, as specified in the workflow, or the **Notify** field may be blank. In either case, you can add names to the **Notify** field if you choose to do so.

2. To add names to the **Notify** list, type the names of the users to be notified (with semicolons separating the names).

Or click the **Notify** button to open the address book.

You may select individual usernames or user groups. See ["Adding and Removing Approvers, Acknowledgers, and Observers"](#) on page 9-21.

Note: In Java Client, you can select approvers and observers, but you cannot select acknowledgers for the routable object.

3. Add any comments in the **Comments** field.
4. Click the dialog button that completes the status change, for example, **Submit**, **Route**, or **Release**.

Completing the Status Change for a Review or Released Status

When you switch a routable object to a Review status type or a Released status type, you are routing it for signoff review to a list of approvers, acknowledgers, and observers. This list of approvers may also be called the CCB, or change control board.

When the Change Status dialog box (Java Client) or page (Web Client) appears, workflow property settings may have already assigned a list of users as approvers, acknowledgers, observers, and users to notify. If you choose, you may add to this list. If these fields are blank, complete them. When the routable object is routed, it is attached to an email message and sent to all the approvers, acknowledgers, observers, and users to notify. The email message contains an icon representing the change; double-clicking the icon opens the routable object. Approvers are required to either accept or reject the routable object. Acknowledgers are required to acknowledge the routable object. Observers may also accept or reject the routable object, but their response is not required. Users who are notified are not required to take any action.

To complete the Change Status to Review or Released page in Web Client:

1. Select the Review status type or the Released status type by using either the **Next Status** button or the **Workflow** tab. See ["Switching the Status of a Routable Object"](#) on page 9-10.

The Change Status page appears.

2. Complete the **Approvers**, **Acknowledgers**, **Observers**, and **To:** fields. These fields may already contain names as defined by the workflow; with appropriate privileges, you may add names.

To add names to a Notify list, type the names of the users you want (with semicolons separating the names).

Or, click the icon to launch the address book palette.

You may select individual users, usernames, or user groups. See ["Adding and Removing Approvers, Acknowledgers, and Observers"](#) on page 9-21.

Add any comments in the **Comments** field.

3. If appropriate, select the **Send notifications as urgent** check box. This adds "URGENT" to the subject of the email (if users are using Microsoft Outlook).
4. Click **Finish**.

The routable object is routed to all the approvers, acknowledgers, and observers, and their names are placed on the **Workflow** tab. All users in the Notify **To:** field receive email informing them of the new status of the routable object.

To complete the Change Status to Review or Released dialog box in Java Client:

1. Select the Review status type or the Released status type by using either the **Next Status** button or the **Workflow** tab. See ["Switching the Status of a Routable Object"](#) on page 9-10.

The Change Status dialog box appears.

2. Complete the **Approvers**, **Observers**, and **Notify** fields. These fields may already contain names as defined by the workflow; with appropriate privileges, you may add names. Type the names, separated by semicolons.

Or click the **Approvers**, **Observers**, or **Notify** buttons to open the address book for each field.

From the **Users** or **Groups** tab, you may select individual usernames or user groups. See ["Adding and Removing Approvers, Acknowledgers, and Observers"](#) on page 9-21.

Note: In Java Client, you can select approvers and observers, but you cannot select acknowledgers for the routable object.

3. Add any comments in the **Comments** field.
4. If appropriate, select the **Urgent** check box. This adds "URGENT" to the subject of the email (if users are using Microsoft Outlook).
5. Click the dialog button that completes the status change, for example, **Route** or **Release**.

The routable object is routed to all the approvers, acknowledgers, and observers, and their names are placed on the **Workflow** tab. All users in the **Notify** field receive email informing them of the new status of the routable object.

Discovery Privileges of Approvers, Acknowledgers, Observers, and Users to Notify

If any of the users you select as approvers, acknowledgers, observers, or users to notify do not have the appropriate Discovery or Read privileges for the routable object, an error message appears when you attempt to route or release the routable object. The error message lists the users that do not have the appropriate privileges and informs you that their names have been automatically removed from the distribution list.

For more information about Discovery and Read privileges, see the *Agile PLM Administrator Guide*.

Handling Routed Changes

The following sections describe procedures you perform when routing changes:

- ["When to Add Approvers, Acknowledgers, and Observers"](#) on page 9-20
- ["Adding and Removing Approvers, Acknowledgers, and Observers"](#) on page 9-21

When to Add Approvers, Acknowledgers, and Observers

Routing managers may want to monitor routable objects assigned to them to ensure that the list of approvers, acknowledgers, and observers is complete. Workflows may assign approvers, acknowledgers, and observers according to the attributes of the affected items of a routable object; you can add approvers, acknowledgers, and observers that were not automatically assigned by the workflow.

For example, at Acme Incorporated, each product line has several projects in development simultaneously. Acme uses a field to identify which project or projects each item (part or document) belongs to. The Libra Product Line workflow looks at the project assigned to the affected items on an ECO to determine which default approvers, acknowledgers, and observers to assign.

Mary Green creates ECO 333. She adds six Orion project objects to the **Affected Items** tab: three parts and three documents. Mary finishes preparing ECO 333 and switches it to the next status, where the routable object (ECO 333) is submitted to Bob Smith, the default change analyst.

To select approvers for the Orion project, the Libra Product Line workflow examines each item on the affected items table to determine if the field contains Orion. If *all* the items on the

affected items table belong to the Orion project, then the list of Orion approvers, as defined in the workflow, is automatically added to the **Workflow** tab when ECO 333 is submitted to Bob.

However, in the case where some objects on the affected items table are documents, Acme requires that Orion team members in the Publications department (a user group) must also sign off the routable object. Since not all ECOs include documents to sign off, the Libra Product Line workflow does not automatically add to every ECO approvers from the Publications department.

Bob Smith, the change analyst, examines the ECO 333 and notices that some affected items are documents. Bob clicks **Add Reviewers** on the ECO 333 page and adds all the members of the Orion Publications group as approvers. Bob can add approvers, acknowledgers, or observers to any future Review or Released status type; the ECO does not need to be in the Review or Released status type to add approvers, acknowledgers, or observers.

See ["Adding and Removing Approvers, Acknowledgers, and Observers"](#) on page 9-21 for detailed instructions for adding approvers, acknowledgers, and observers.

Adding and Removing Approvers, Acknowledgers, and Observers

After a routable object has been routed for approval and enters a Review or Released status type, it may be necessary to either add or remove reviewers (approvers, acknowledgers, or observers). This requires both of the following:

- 7 The Ad Hoc Reviewers property in the workflow is set to Yes.
- 7 You have the appropriate privilege granted to you by the Agile administrator.

Note: You cannot add a user as a reviewer if that user does not have Discovery and Read privileges for that routable object.

Ad hoc reviewers (approvers, acknowledgers, or observers) can be added to or removed from the routable object only when it is in a Submitted, Review, or Released type status. Ad hoc reviewers cannot be added to or removed from the routable object when it is in the Pending type status.

You cannot add the same user to multiple reviewer lists (the Approvers, Acknowledgers, or Observers lists). If you attempt to add the same names to more than one list, Agile PLM warns you that the names are duplicated in more than one list. Before you can complete the add reviewers action, you must remove the duplicates so that each name appears in only one list.

In Web Client, you can also remove duplicate signoff users by using the **Resolve Duplicates** button in the Change Status dialog and in the Add Approvers, Acknowledgers and Observers dialog.

Web Client, Adding and Removing Approvers, Acknowledgers, and Observers

To add an approver, acknowledger, or observer in Web Client:

1. Select and open the routable object. Click the **Workflow** tab.
2. Click the **Add Reviewers** button.
The Add Approvers, Acknowledgers and Observers dialog appears.
3. Select the status you want the additional people to approve.
4. Complete the **Approvers**, **Acknowledgers**, and **Observers** fields. Type the names of the approvers, acknowledgers, or observers to add to the list (with semicolons separating the names).

Or click the icon to open the address book palette.

You may select individual usernames or user groups. For more information about using the address book palette, see ["Selecting Users or User Groups to Modify a Field"](#) on page 5-11

5. To add an entire user group as an approver:
 - a. In the address book palette, select User Groups in the drop-down list and execute a quick search to find the user groups you want.
 - b. Select a group by double-clicking it. The Group Sign-off Criteria dialog appears.
 - c. Select the appropriate check box and click **Apply**. The check box choices are:
 - * Only one group member must approve
 - * All group members must approve.
6. To select individual users or user groups according to their assigned job functions:
 - a. In the address book palette, select a specific job function in the drop-down list and execute a quick search to find a user or user group. Only users or user groups with that job function appear in the search results.

For example, if you select Lead Developer in the address book palette drop-down list, your search is limited to only users or user groups that include the Lead Developer job function in their **Job Function(s)** attribute.
 - b. Select the users or user groups that you want.
7. Add any comments.
8. When you have completed the Add Approvers, Acknowledgers and Observers dialog, click **Add**.

If one or more users or user groups are selected for duplicate signoff lists (Approver, Acknowledger, and Observer), then an error message appears indicating the users and their duplicate signoff roles.

To resolve the duplicates, you can either: You can remove users or groups by clicking the small **x** button on each approver, acknowledger, or observer name you want to remove. Or, click the **Resolve Duplicates** button; see ["Web Client, Resolve Duplicate Signoff Users"](#) on page 9-23.

7. Click the small **x** button on each approver, acknowledger, or observer name you want to remove.
7. Click the **Resolve Duplicates** button to resolve the duplicate names; see ["Web Client, Resolve Duplicate Signoff Users"](#) on page 9-23.

When the duplicate names are resolved, then click **Add**.

Note: When you add a user group as an approver such that only one member of the group needs to signoff (*UserGroupName* - Any), escalation behavior is determined by the user group's profile settings for **Allow Escalation Designation Approval** (After Escalation or Always) and the user group's assigned escalation persons. However, when you add a user group as an approver such that all members of the group must signoff (*UserGroupName* - All), Agile PLM automatically adds each member of the group as an individual approver and, therefore, escalation behavior depends on the user profile settings and assigned escalation persons of each individual user.

You must select a global user group to add a user group as an approver such that only one member of the group needs to signoff. If you select a personal user group and also choose the **Only one group member must approve** Group Sign-off Criteria, then a warning is displayed when you click **Add** in step 8.

To remove an approver, acknowledger, or observer in Web Client:

1. Select and open the routable object.
2. Click the **Remove Reviewers** button.
The Remove Approvers, Acknowledgers and Observers dialog appears.
3. Select the status for which you want to remove approvers, acknowledgers, or observers.
4. In the **Remaining Approvers**, **Remaining Acknowledgers**, and **Remaining Observers** fields, click the small **x** button on each approver, acknowledger, or observer name you want to remove.
5. Enter any comments.
6. If desired, select the **Send notification as urgent** check box.
7. Click **Save**.

Note: You can remove an approver, acknowledger, or observer only if that reviewer has not yet approved, acknowledged, or rejected the routable object.

Web Client, Resolve Duplicate Signoff Users

In Agile Web Client, you add signoff users (approvers, acknowledgers, or observers) in the following dialogs:

- Change Status to Review-type status or Released-type status. See ["Completing the Status Change for a Review or Released Status"](#) on page 9-19.
- Add Approvers, Acknowledger,s or Observers; see ["Web Client, Adding and Removing Approvers, Acknowledgers, and Observers"](#) on page 9-21.

When you are done selecting the users or user groups in the dialog, you click **Finish** or **Add**.

If one or more users or user groups are selected for duplicate signoff lists (Approver, Acknowledger, and Observer), then an error message appears indicating the users and their duplicate signoff roles. The **Resolve Duplicates** button becomes active.

To resolve duplicate signoff users manually:

You can click the small **x** button on each approver, acknowledger, or observer name you want to remove.

To quickly resolve all the duplicate signoff uses at one time:

1. Click the **Resolve Duplicates** button.

The Resolve Duplicate Users dialog appears, including the error message listing the users and their duplicate signoff roles.

2. Select the order in which the duplicate users are to be resolved. The signoff roles take precedence in the order listed and each duplicate user is assigned only one role.

For example, if you select **Approver, Acknowledger, Observer**, then:

- ⌘ If the user name is in all three lists, then the user name remains on the Approver list, and the user name is removed from the Acknowledger and Observer lists.
- ⌘ If the user name is on the Approver and Acknowledger lists, then the user name remains on the Approver list and the user name is removed from the Acknowledger list.
- ⌘ If the user name is on the Approver and Observer lists, then the user name remains on the Approver list and the user name is removed from the Observer list.
- ⌘ If the user name is on the Acknowledger and Observer lists, then the user name remains on the Acknowledger list and the user name is removed from the Observer list.

The resolution orders you can choose are:

- ⌘ Approver, Acknowledger, Observer (default)
- ⌘ Approver, Observer, Acknowledger
- ⌘ Acknowledger, Approver, Observer
- ⌘ Acknowledger, Observer, Approver
- ⌘ Observer, Approver, Acknowledger
- ⌘ Observer, Acknowledger, Approver

3. Click **Save**.

Focus returns to the Change Status dialog (then click **Finish**) or to the Add Approvers, Acknowledgers or Observers dialog (then click **Add**).

Java Client, Adding and Removing Approvers and Observers

To add an approver or observer in Java Client:

1. Select and open the routable object.
2. On the **Workflow** tab, select the status you want the additional people to approve.
3. Click the **Add Approver/Observer** button.
4. The Add Approvers and Observers dialog box appears.
5. Complete the **Approvers** and **Observers** fields. Type the names of the approvers or observers to add to the list (with semicolons separating the names).

Or click the **Approvers** or **Observers** button to open the address book for each field.

From the **Users** or **Groups** tab, you may select individual usernames or user groups.
6. To add an entire user group as an approver, you can either add the group itself or the members of the group. This determines whether only one member or all members of the group must sign off.
 - a. Click the **Group** tab in the address book.

- b. Select one or more group names.

(To select user names, expand a group by clicking the plus sign +.)

- c. To add the group name to the recipient list, click the **Add** button. The group name is added to the recipients list. Only one user in the group needs to sign off.

Note: Personal user groups cannot be added as an approver or an observer. If you select a personal user group, then the **Add** button is disabled. Only a global user group can be added as an approver or an observer.

- d. To add the members of the group to the recipient list, click the **Add all the users in the selected group** button. The usernames of the members of the group are added to the recipient list. Each user in the group must sign off.

The **Add all the users in the selected group** button can be used both with global user groups and with personal user groups.

7. Add any comments.

8. Click **OK**.

To remove an approver or observer in Java Client:

1. Select and open the routable object.
2. On the **Workflow** tab, under the appropriate status, select the approvers or observers you want to remove from the list.
3. Click the **Remove Approver/Observer** button.
4. When prompted to confirm the removal action, click **Yes**.

Note: You can remove an approver only if that approver has not yet approved or rejected the routable object.

Using Functional Teams with Routable Objects

When Agile PLM has been configured to use the Approval Matrix feature and the Approval Matrix Manager has created the necessary functional teams, then end users can use functional teams in the workflow process.

To use functional teams in the workflow process:

1. Create a routable object, for example, an ECO.
2. On the **Cover Page** tab, the two attributes that control the Approval Matrix feature are:
 - ? **Workflow** – Select the appropriate workflow for your routable object.
 - ? **Functional Team(s)** – Select one or more functional teams.
3. When the routable object enters a signoff status (review-type status or released-type status), Agile PLM matches the job functions in the workflow definition to the job functions in the functional teams, and populates the routable object **Workflow** tab with Approvers, Acknowledgers, Observers. That is:

- ? A functional team matches one or more users with a job function. For example:

Mary Jones – Developer

John Smith – Product Manager

Bob White – QA Lead

- 7 The Agile administrator configures a workflow to associate a workflow action with a job function, for example:

Approver – Developer

Acknowledger – Product Manager

Observer – QA Lead

- 7 On the routable object **Cover Page** or **General Info** tab, one or more functional teams are selected in the **Functional Team(s)** attribute. When the routable object enters a signoff status, the job functions configured in the workflow are matched to the job functions in the functional teams. Agile PLM then populates the Workflow table with the appropriate users. From the examples above:

Approver – *Developer* – Mary Jones

Acknowledger – *Product Manager* – John Smith

Observer – *QA Lead* – Bob White

Resolving Missing Users

The **Missing User** icon is displayed in the **Reviewer** column of routable object workflow table when:

- 7 A job function has been defined as a reviewer for the routable object.




And

- 7 There is no identified user or user group to assign as a reviewer.

This occurs when, in the selected functional team, no user or user group is defined for that job function or the job function does not appear in the Job Functions table.

For example, the workflow requires that a user with the Product Strategy job function must approve the routable object. The functional team that was selected in the routable object **Functional Team(s)** attribute does not include the Product Strategy job function. When the routable object enters the CCB status, the missing user is indicated by the **Missing User** icon.

Figure 9–3 Workflow table with missing user

Status Code	Workflow Status	Reviewer	Action	Req'd	Reviewer Job Function
	Implemented				
	Released				
	CCB				
		 Analyst, Analyst12	Awaiting Approval	Yes	Developer
			Awaiting Approval	Yes	Product Strategy

To resolve a missing user on the routable object workflow table:

Note: You must have the appropriate modify privileges to edit the workflow table **Reviewer** field.

1. Double-click inside the table cell where the **Missing User** icon appears. A small search dialog appears.

Note: Only users and user groups that have the specified job function included in their **Job Function(s)** attribute appear in the search results. For example, when you resolve a missing user for a Product Strategy reviewer job function, then the search results are limited to Product Strategy users and user groups.

2. Enter text to find a reviewer:
 - a. Begin typing a name and Agile PLM displays a name that matches in the search results field.
 - b. Click the name in the search results field to select it.
 - c. Press **Enter** to populate the Reviewer cell and to close the search dialog.
3. Or, click the icon to launch the address book palette.
 - a. Execute a search.
 - b. Double-click to select the search result row you want.
 - c. Press **Escape** to close the address book palette.
 - d. Press **Enter** to populate the Reviewer cell and to close the search dialog.
4. When you are done, click **Save** on the workflow table to save your edits.

Approving Routable Objects

When you approve a routable object, the approval and any comments are shown on the **Workflow** tab.

To approve a routable object in Web Client:

1. Open the routable object.
2. Click the **Approve** button to open the Approve dialog. The **Approve** and **Reject** buttons appear after the routable object is moved to a certain status, for example, a problem report moves from the Submitted to the Review status.
3. Depending on the Agile PLM system settings and workflow definitions, and the conditions under which you are signing off, the signoff area of the Approve dialog may include multiple users, job functions, or groups for whom you can approve.

In the Signoff area of the Approve dialog, ensure that the check boxes of users, job functions, or groups for whom you are approving are selected. Possible choices include:

- ? Yourself
- ? Groups – the approver groups of which you are a member.
- ? Job Function – your job functions in the functional teams of which you are a member.
- ? Transfers – transfer authorities for approver users or groups for which you are the Transfer To person.
- ? Escalations – escalations for approver users or groups for which you are the Designated Escalation Person.

Note: When presented with multiple signoff possibilities (job functions, escalations, transfers, groups, or self) you must select at least one group, job function, or person for whom you are approving.

4. In the Signoff area of the dialog, depending on Agile PLM system settings, you may be required to enter dual types of identification.
 - ? The first identification type is your approval password. Enter your approval password in the **Password** field.
 - ? The second identification type depends on Agile PLM system settings and may be either your userID (username) or your login password.

Note: The **Password** field appears in the Approve window depending on the **Password Required** property setting for the current workflow status. For more information about workflow properties, see *Agile PLM Administrator Guide*.

5. Enter any comments in the Comments field.

Completing the **Comments** field may be either required or optional, depending on workflow settings.
6. In the Notify area of the approval dialog, select any of these check boxes to notify these people: **Change Analyst**, **Originator**, **Reviewers**. When notifying reviewers, you can select a workflow status other than the Current Status.
7. To select additional people to notify, launch the Address Book palette by clicking the **Launch Palette** icon.
8. Click **Approve**.

Note: For Design and File Folder objects, when you (Approvers/Observers/Reviewers) click the workflow approval link of a routing slip, the system takes you to the specific version to be approved.

When all the approvers have approved and all the acknowledgers have acknowledged, then the routable object is ready to move to the next status in the status list.

- ? If the AutoPromote property for the status is set to Yes, and the required fields are filled in, then the routable object is automatically promoted to the next status in the status list.
- ? If the AutoPromote property for the status is set to No, then an email message notifies the change analyst, component engineer, or other routing manager that all the approvers have approved the routable object and all the acknowledgers have acknowledged the routable object.

To approve a routable object in Java Client:

1. Open the routable object.
2. Click the **Approve** button to open the Approve dialog box.
3. Enter any comments in the **Comments** field.

Completing the **Comments** field may be either required or optional, depending on workflow settings.

4. Select any of these check boxes to notify these people: **Notify Change Analyst**, **Notify Originator**, or **Notify Reviewers**. If you select **Notify Reviewers**, you can use the drop-down list to choose a different workflow status.

- Note:** When presented with multiple signoff possibilities (escalations, transfers, groups, or self) you must select at least one group or person for whom you are approving.

6. Click **Approve**.

Note: For File Folder objects, when you (Approvers/Observers/Reviewers) click the workflow approval link of a routing slip, the system takes you to the specific version to be approved.

Rejecting Routable Objects

When you reject a routable object, the rejection and any comments appear on the **Workflow** tab, and the specified users receive an email message. Usually, this is the change analyst or component engineer. The email message states that you have rejected the routable object.

If a routable object is first rejected but is then later approved, the **Workflow** tab shows only the approval and not the rejection. However, the **History** tab shows both actions.

To reject a routable object in Web Client:

1. Open the routable object.
2. Click the **Reject** button to open the Reject dialog. The **Approve** and **Reject** buttons appear after the routable object is moved to a certain status, for example, a problem report moves from the Submitted to the Review status.
3. Depending on the Agile PLM system settings and workflow definitions, and the conditions under which you are signing off, the signoff area of the Reject dialog may include multiple users, job functions, or groups for whom you can reject.

In the Signoff area of the Reject dialog, ensure that the check boxes of users, job functions, or groups for whom you are rejecting are selected. Possible choices include:

- ? Yourself
- ? Groups – the approver groups of which you are a member.
- ? Job Function – your job functions in the functional teams of which you are a member.
- ? Transfers – transfer authorities for approver users or groups for which you are the Transfer To person.
- ? Escalations – escalations for approver users or groups for which you are the Designated Escalation Person.

Note: When presented with multiple signoff possibilities (job functions, escalations, transfers, groups, or self) you must select at least one group, job function, or person for whom you are approving.

4. In the Signoff area of the dialog, depending on Agile PLM system settings, you may be required to enter dual types of identification.
 - ? The first identification type is your approval password. Enter your approval password in the **Password** field.
 - ? The second identification type depends on Agile PLM system settings and may be either your userID (username) or your login password.

Note: The **Password** field appears in the Reject window depending on the **Password Required** property setting for the current workflow status. For more information about workflow properties, see *Agile PLM Administrator Guide*.

5. Enter any comments in the **Comments** field.

Completing the **Comments** field may be either required or optional, depending on workflow settings.

6. In the Notify area of the approval dialog, select any of these check boxes to notify these people: **Change Analyst**, **Originator**, **Reviewers**. When notifying reviewers, you can select a workflow status other than the Current Status.
7. To select additional people to notify, click the **Launch Palette** icon button to launch the Address Book palette.
8. Click **Reject**.

To reject a routable object in Java Client:

1. Open the routable object.

2. Click the **Reject** button to open the Reject dialog box.

3. Enter any comments in the **Comments** field.

Completing the **Comments** field may be either required or optional, depending on workflow settings.

4. Depending on the Agile PLM system settings and workflow definitions, and the conditions under which you are signing off, the Reject dialog may include the following fields or lists that you must fill in:

- ? **Escalated From:** A list of escalations for approver users or groups for which you are the Designated Escalation Person.
 - a. Click the down arrow next to the **Escalated From** field.
 - b. To select the users or groups for which you want to reject, in the dialog box that appears, select a user or group in the Choices list or the Selected list and click the right or left arrows to move the your selections from one list to the other. If you do not want to reject for any escalations, leave the Selected list blank.
 - c. Click **OK**.
- ? **Transferred From:** A list of transfer authorities for approver users or groups for which you are the Transfer To person.
 - a. Click the down arrow next to the **Transfer From** field.
 - b. To select the users or groups for which you want to reject, in the dialog box that appears, select a user or group in the Choices list or the Selected list and click the right or left arrows to move the your selections from one list to the other. If you do not want to reject for any transfers, leave the Selected list blank.
 - c. Click **OK**.
- ? **Approval Group(s):** A list of the approver groups of which you are a member.
 - a. Click the down arrow next to the **Approving for Group(s)** field.
 - b. To select the users or groups for which you want to reject, in the dialog box that appears, select a user or group in the Choices list or the Selected list and click the right or left arrows to move the your selections from one list to the other. If you do not want to reject for any groups, leave the Selected list blank.
 - c. Click **OK**.
- ? **Signoff for Self:** When you are also an individual approver, a check box is displayed next to your name.

- a. Select the check box to indicate that you are rejecting for yourself, in addition to any group, escalation, or transfer rejections. If you do not want to reject for yourself, deselect the check box.
- 7 **Dual Identification:** Depending on Agile PLM system settings, you may be required to enter dual types of identification.
 - a. The first identification type is your approval password. Enter your approval password in the **Password** field.
 - b. The second identification type depends on Agile PLM system settings and may be either your userID (username) or your login password.

Note: The **Password** field appears in the Reject window depending on the **Password Required** property setting for the current workflow status. For more information about workflow properties, see *Agile PLM Administrator Guide*.

When presented with multiple signoff possibilities (escalations, transfers, groups, or self) you must select at least one group or person for whom you are rejecting.

- 5. Click the **Notify** button to add any users to be notified.
- 6. Click **Reject**.

When at least one approver has rejected a routable object, the following actions occur, as specified in the workflow property settings:

- 7 The users specified in the workflow properties are notified that the routable object has been rejected.
- 7 If the AutoPromote property is set to Yes, then the routable object is not promoted to the next status in the status list.
- 7 Depending on the workflow property settings, the object may switch to a specified status when it has been rejected.

Acknowledging Routable Objects

Note: You must use Web Client to acknowledge a routable object. The workflow acknowledge action is not available in Java Client.

When you acknowledge a routable object, the acknowledgment and any comments are shown on the **Workflow** tab.

By acknowledging the routable object, the acknowledger verifies that they have reviewed the routable object or that they have performed an expected action when the object is routed.

Note: An acknowledgment is not an approval, however, similar to an approval, it is a required workflow action that must be completed in order for the routable object to be released.

To acknowledge a routable object in Web Client:

- 1. Open the routable object.

2. Click the **Acknowledge** button to open the Acknowledge dialog. The **Acknowledge** button appears after the routable object is moved to a certain status, for example, a problem report moves from the Submitted to the Review status.
3. Depending on the Agile PLM system settings and workflow definitions, and the conditions under which you are acknowledging, the signoff area of the Acknowledge dialog may include multiple users, job functions, or groups for whom you can acknowledge.

In the Signoff area of the Acknowledge dialog, ensure that the check boxes of users, job functions, or groups for whom you are approving are selected. Possible choices include:

- ? Yourself
- ? Groups – the acknowledger groups of which you are a member.
- ? Job Function – your job functions in the functional teams of which you are a member.

Note: When presented with multiple signoff possibilities (job functions, groups, or self) you must select at least one job function, group or person for whom you are acknowledging.

4. In the Signoff area of the dialog, depending on Agile PLM system settings, you may be required to enter dual types of identification.
 - ? The first identification type is your approval password. Enter your approval password in the **Password** field.
 - ? The second identification type depends on Agile PLM system settings and may be either your userID (username) or your login password.

Note: The **Password** field appears in the Acknowledge window depending on the **Password Required** property setting for the current workflow status. For more information about workflow properties, see *Agile PLM Administrator Guide*.

5. Enter any comments in the Comments field.
Completing the **Comments** field may be either required or optional, depending on workflow settings.
6. In the Notify area of the approval dialog, select any of these check boxes to notify these people: **Change Analyst**, **Originator**, **Reviewers**. When notifying reviewers, you can select a workflow status other than the Current Status.
7. To select additional people to notify, launch the Address Book palette by clicking the **Launch Palette** icon.
8. Click **Acknowledge**.

When all the approvers have approved and all the acknowledgers have acknowledged, then the routable object is ready to move to the next status in the status list.

- ? If the AutoPromote property for the status is set to Yes, and the required fields are filled in, then the routable object is automatically promoted to the next status in the status list.
- ? If the AutoPromote property for the status is set to No, then an email message notifies the change analyst, component engineer, or other routing manager that all the approvers have approved the routable object and all the acknowledgers have acknowledged the routable object.

Reminder Period and Review Escalation Period

The reminder period and the review escalation period are periods of time defined for each Review or Released status type in each workflow. For example, the reminder period for the CCB status in the Default Change Orders workflow is 48 hours, and the review escalation period is 96 hours. The reminder period and the review escalation period begin when the routable object enters a Review or Released status type. The reminder period is shorter than the escalation period so the approvers have time to respond before the escalation period elapses.

Note: If your user profile **Receive Email Notifications** preference is set to Yes, Agile PLM will also send an email notification to your user profile email address. See also "[User Properties Defined](#)" on page 2-55

Each Review or Released status type has its own reminder period and review escalation period. If a workflow has several Review or Released status types, each one may have a different length of time for both its reminder period and review escalation period.

When the reminder period elapses, if an approver has not approved or rejected the routable object, or an acknowledger has not acknowledged the routable object, then a reminder notification is sent to the approver or acknowledger. The change analyst or component engineer receives a similar notification.

When the escalation period elapses, if an approver has not approved or rejected the routable object or an acknowledger has not acknowledged a routable object, then a notification is sent to the appropriate designated escalation person. A similar notification notifies the change analyst or component engineer that the routable object has been escalated to the specified designated escalation person. The designated escalation person may approve or reject the routable object in the place of the original approver or acknowledge the routable object in the place of the original acknowledger.

When reminder and escalation notifications are sent, the actions are recorded on the **History** tab.

Designated Escalation Person

Each user or user group may have multiple designated escalation persons. A designated escalation person can be an individual user or user group.

The Agile administrator determines whether your designated escalation persons are able to sign off a routable object for you at any time, or only after the escalation period has elapsed. See the Agile administrator if you have questions about your designated escalation persons.

For information about defining escalations, see "[Working with Escalations in Web Client](#)" on page 2-37 or "[Working with Escalations in Java Client](#)" on page 3-12.

Note: If your user profile **Receive Email Notifications** preference is set to Yes, Agile PLM will also send an email notification to your user profile email address. See also "[User Properties Defined](#)" on page 2-55.

If the review escalation period elapses, the reviewer's designated escalation persons are notified that the approver or the acknowledger has not responded. Now the designated escalation persons may approve or reject the routable object in the place of the original approver or acknowledge the routable object in the place of the original acknowledger. If the designated escalation person approves, rejects, or acknowledges the routable object, then the name is recorded on the **Workflow** tab and the **History** tab as the Signoff user.

Note: If the designated escalation person is a user group, only one member of the group needs to sign off the routable object. When the routable object has been signed off, the routable object no longer appears in the Inbox of the other members of the group.

Transferring Signoff Authority

If you have the appropriate privileges, you can temporarily transfer your signoff authority for the routable object to one or more Agile users. For example, if you know you will be on vacation for a week, you can give other users the authority to sign off routable objects for you while you are gone. You can specify which routable objects to transfer to which user.

In addition, if you have the appropriate privileges, you can also transfer signoff authority for other users. For example, if Mary will be on vacation, you can give Bob the authority to sign off routable objects for Mary while she is gone.

Signoff authority is transferred for users who are assigned approvers or acknowledgers on a routable object. Signoff authority is not transferred for observers.

To transfer signoff authority for yourself or others in Web Client:

1. Click the **My Settings** button in the left navigation pane. Your user profile is displayed in the content pane.
2. Click the **Transfer Authority** button. The All Transfer Authority Details dialog appears.
3. Click the **Add** button. The Create Transfer Authority dialog appears.
4. Select yourself or another user to transfer authority from and then select the user who is receiving signoff authority.

Users who are receiving the authority must have the appropriate privileges to sign off the routable objects transferred to them. If you have questions about privileges, see the Agile administrator.

5. In the **Criteria** list, click to select the type of information to transfer.

The list of criteria is quite extensive. If you have questions about which criteria would best suit your needs, contact the Agile administrator, who manages all global criteria.

Alternatively, consider defining a *personal* criteria that you can then use for transferring authority: choose **Actions > Specify Personal Criteria** in the Actions menu of your user profile. See ["Defining Personal Criteria for Authority Transfers"](#) on page 9-38 for information about creating personal criteria.

6. Specify a start date and an end date.
7. In the **Affected Changes** list, specify whether you want all routable objects in your Inbox to be transferred, or only routable objects that arrive in your Inbox within the date range you specified.
8. Click **Save** to complete the transfer.

To transfer signoff authority for yourself or others in Java Client:

1. Choose **Settings > Transfer Authority** in the main menu bar. The Transfer Authority dialog box appears which lists the transfer authority definitions you have the ability to modify or delete.
2. Click the **New** button. The New Transfer Authority dialog box appears.
3. Select yourself or another user to transfer authority from and then select the user who is receiving signoff authority.

Users who are receiving the authority must have the appropriate privileges to sign off the routable objects transferred to them. If you have questions about privileges, see the Agile administrator.

4. In the **Select Criteria** list, click to select the type of information to transfer.

To view the filter conditions for the selected criteria, click the **View** button in the Criteria pane. The criteria is displayed, much like a search definition, in a read-only dialog box. You can verify whether the selected transfer criteria will find the routable objects you want to transfer. Click **Cancel** to close the dialog box.

The list of criteria is quite extensive. If you have questions about which criteria would best suit your needs, contact the Agile administrator, who manages all global criteria.

Alternatively, consider defining a *personal* criteria that you can then use for transferring authority. See ["Defining Personal Criteria for Authority Transfers"](#) on page 9-38 for information about creating personal criteria.

5. Specify a start date and an end date.
6. Under **Affected Changes**, specify whether you want all routable objects in your Inbox to be transferred, or only routable objects that arrive in your Inbox within the date range you specified.
7. Click **OK** to complete the transfer.

The new transfer authority definition appears in the Transfer Authority dialog box.

8. Click **Close**.

Routable Objects Affected During the Transfer Period

- ? If the Transfer Authority **Affected Changes** property is set to **All Changes During Time Period**, the following conditions define the routable objects are transferred:
 - The routable object meets the criteria defined in the transfer authority.
 - The routable object enters a workflow status that has a list of approvers or acknowledgers (a Review-type status or a Released-type status) during the time period defined in the Transfer Authority.
 - The From user is an approver or acknowledger for that workflow status.
- ? If the Transfer Authority **Affected Changes** property is set to **All Changes**, the following conditions define the routable objects are transferred:
 - The conditions listed above for **All Changes During Time Period**.
 - In addition, all criteria-defined routable objects that were awaiting signoff by the From user at the time the Transfer Authority was created (in a Review-type status or a Released-type status).
- ? Routable objects that are created during the Transfer Authority time period that do not also enter a Review-type or Released-type status during the time period are not transferred to the To user.

The Start and End dates are time specific. If you enter today's date as the start date, and the time component of the date is in the past, Agile PLM creates the Transfer Authority with the current date and time.

Modifying Signoff Authority Transfers

With the appropriate privileges, you can modify or delete signoff authority transfers at any time. For each authority transfer, you can modify the person who receives signoff authority, the

start and end dates, and whether to transfer routable objects already in the Transfer To user's Inbox.

You can also modify and reuse any expired authority transfer at a future date.

Your Transfer Authority privileges determine which authority transfers you can modify:

- If you have privileges to create only your own authority transfers, you can modify only your own authority transfers.
- If you have privileges to create authority transfers for other users, you can modify any authority transfers created by any user.

To modify signoff authority in Web Client:

1. Click the **My Settings** button in the left navigation pane. Your user profile is displayed in the content pane.
2. Click the **Transfer Authority** button. The All Transfer Authority Details dialog appears.
3. Select the row you want to modify and then click the **Edit** button.
4. Change the settings as needed.

Note: Users who are receiving the authority must have the appropriate privileges to sign off the routable objects transferred to them. If you have questions about privileges, see the Agile administrator.

5. Click **Save**.

To modify signoff authority in Java Client:

1. Choose **Settings > Transfer Authority** in the main menu bar. The Transfer Authority dialog box appears which lists the transfer authority definitions you have the ability to modify or delete.
2. Click to select the transfer authority definition you want to change and then click the **Modify** button. The Modify Transfer Authority dialog box appears.
3. Change the settings as needed.

Note: Users who are receiving the authority must have the appropriate privileges to sign off the routable objects transferred to them. If you have questions about privileges, see the Agile administrator.

4. Click **OK** to complete the transfer.

The modified transfer authority definition appears in the Transfer Authority dialog box.

5. Click **Close**.

Deleting Signoff Authority Transfers

To delete one or more transfers of signoff authority in Web Client:

1. Click the **My Settings** button in the left navigation pane. Your user profile is displayed in the content pane.
2. Click the **Transfer Authority** button. The All Transfer Authority Details dialog appears.
3. Select the rows you want to delete and then click the **Remove** button.

To delete one or more transfers of signoff authority in Java Client:

1. Choose **Settings > Transfer Authority** in the main menu bar. The Transfer Authority dialog box appears which lists the transfer authority definitions you have the ability to modify or delete.
2. Click to select the transfer authority definition you want to change and then click the **Delete** button.
3. When prompted, click **Yes**.
4. Click **Close** to close the Transfer Authority dialog box.

Defining Personal Criteria for Authority Transfers

A criteria is similar to an advanced search. The attributes used to create criteria are similar to the fields used to create advanced searches. For escalations and authority transfers, criteria can also be thought of as "filters" or "qualifying descriptions" of the changes that will be escalated or transferred.

For example, you could create a personal criteria for all ECOs that affect a specified product line.

To create a personal criteria in Web Client:

1. Click the **My Settings** button in the left navigation pane. Your user profile is displayed in the content pane.
2. Click the **Transfer Authority** button. The All Transfer Authority Details dialog appears.
3. In your user profile **Actions** menu, choose **Specify Personal Criteria**.
4. Click the **Add** button. The Create Criteria dialog appears.
5. Enter a name for the criteria.

Note: The personal criteria that you create appears in the Transfer Authority criteria list preceded by your name, making it easier to locate. For example, if Bob Jones enters "All Leo Projects," the criteria appears in the transfer authority **Criteria** list as "Bob Jones.All Leo Projects."

6. Enter a description for the criteria.
Using the sample name above, the description might be "All changes in the Leo product line."
7. You define criteria in the Create Criteria dialog the same way that you define search conditions in an Advanced Search. Fill in the fields. For more information about searching, see [Chapter 8, "Finding Agile Data with Searches."](#)
8. Click **Save**.

The new criteria appears in the **Criteria** drop-down list. You can now select this criteria when defining a transfer authority (**Tools > My Settings > Transfer Authority**).

To create a personal criteria in Java Client:

1. Choose **Settings > Transfer Authority** in the main menu bar. The Transfer Authority dialog box appears which lists the transfer authority definitions you have the ability to modify or delete.
2. Either click the **New** button or select a row and click the **Modify** button. The New or Modify Transfer Authority dialog box appears.
3. In the Criteria pane, click the **New** button to display the New Personal Criteria dialog box.

4. Enter a name for the criteria.

Note: The personal criteria that you create appear in the Transfer Authority criteria list preceded by your name, making them easier to locate. For example, if Bob Jones enters "All Leo Projects," the criteria appears in the Transfer Authority criteria list as "Bob Jones.All Leo Projects."

5. Enter a description for the criteria.

Using the sample name above, the description might be "All changes in the Leo product line."

6. You define criteria in the New Personal Criteria dialog box the same way that you define search conditions in the Advanced Search wizard. Fill in the fields. For more information about searching, see [Chapter 8, "Finding Agile Data with Searches."](#)
7. Click **OK**.

The new criteria appears in the Criteria pane in the Transfer Authority dialog box. You can now select this criteria when defining or modifying a transfer authority.

Returning a Routable Object to the Originator

You return a routable object to the originator by switching the status to the Pending status type. Before you can switch a routable object back to the Pending status type, you need the appropriate privileges. Usually, the change analyst and component engineer have these privileges. If you need them and do not have them, see the Agile administrator.

When a change analyst or component engineer switches a routable object from a workflow status (not from the Unassigned status) to the Pending status type (the first status in the workflow status list), the originator is notified. The originator is now able to edit the routable object, including editing items on the **Affected Items** tab and selecting a different workflow.

When the originator completes edits to the returned routable object and then switches it to the next status in the workflow status list, the routable object moves through the workflow status list and enters the Review status type or Released status type cycle a second time. For details about what happens when the routable object enters the Review status type or Released status type cycle again, see ["Demoting a Routable Object"](#) on page 9-17.

To return a routable object to the originator in Web Client:

1. Open the routable object.
2. On the **Workflow** tab, click Pending (or a status of type Pending) in the chart on the **Workflow** tab.

When the Change Status dialog appears, complete the Notify **To:** field and add comments.

3. Click **Finish**.

The status of the routable object switches to the Pending status type.

Note: Approvals and rejections from previous routing cycles appear on the **Workflow** tab, but they are not active. Only approvals and rejections for the latest routing cycle on the **Workflow** tab are allowed. The **History** tab also shows the actions of the earlier routing cycles.

You cannot return a routable object to an originator who does not have Discovery and Read privileges for that object. (See the *Agile PLM Administrator Guide* for details.)

To return a routable object to the originator in Java Client:

1. Open the routable object.
2. On the **Workflow** tab, click Pending (or a status of type Pending) in the chart on the **Workflow** tab.

See ["Switching a Routable Object from One Status to Another Status"](#) on page 9-10.

When the Change Status dialog box appears, complete the **Notify** field and add comments.

3. Click **OK**.

The status of the routable object switches to the Pending status type.

Note: Approvals and rejections from previous routing cycles appear on the **Workflow** tab, but they are not active. Only approvals and rejections for the latest routing cycle on the **Workflow** tab are allowed. The **History** tab also shows the actions of the earlier routing cycles.

You cannot return a routable object to an originator who does not have Discovery and Read privileges for that object. (See the *Agile PLM Administrator Guide* for details.)

Canceling a Routable Object

You can use the **Workflow** tab to cancel a routable object by switching the status to the Cancel status type if both of the following are true:

- The Cancel status type has been defined in the workflow as one of the valid next statuses.
- You have the appropriate privileges. (See the Agile administrator if you have questions about your privileges.)

For example, you create an ECO to modify an assembly and route it through workflow, but later decided not to modify it. You can cancel the routable object itself. The reasons the ECO is canceled would be recorded in the comments of the canceled ECO. The canceled ECO can still remain in Agile database.

Note: If you cancel a released routable object, the revision is removed from the item revision list of the affected items. A routable object with affected items that has been canceled cannot be uncanceled (moved to a different status in the workflow). The canceled routable object appears on the Change History table of the item's **Changes** tab. If there are redline edits associated with the routable object, redlines are dropped (discarded) and you cannot access the redline table of a canceled routable object. This differs from a routable object on hold; see ["Putting a Routable Object on Hold"](#) on page 9-42.

Canceling a routable object is different than deleting it. A routable object can be canceled due to a fundamental flaw or rejection by several approvers, but it remains in the database. See also [Appendix A, "Deleting Agile Objects."](#)

When a routable object is canceled, it no longer has the current status, and the remaining statuses on the status list are skipped. All the remaining statuses on the status list show the name of the person who moved the routable object to Canceled under the Status Changed By column on the **Workflow** tab.

To cancel a routable object in Web Client:

1. Open the routable object.
2. On the **Workflow** tab, click Cancel in the Summary workflow chart.
When the Change Status dialog appears, complete the Notify **To:** field, and add comments.
3. Click **Finish**.

The status of the routable object switches to the Cancel status type.

To cancel a routable object in Java Client:

1. Open the routable object.
2. On the **Workflow** tab, click Cancel in the chart.
When the Change Status dialog box appears, complete the **Notify** field, and add comments.
3. Click **OK**.

The status of the routable object switches to the Cancel status type.

Uncanceling a Routable Object

You uncancel a routable object by using the **Workflow** tab to switch the status. You can switch to any status if:

- ? The status has been defined in the workflow as one of the valid next statuses.
- ? You have the appropriate privileges. (See the Agile administrator if you have questions about your privileges.)
- ? There are no items on the **Affected Items** tab of the routable object.

Note: If you cancel a released routable object, the revision is removed from the item revision list of the affected items. A routable object with affected items that has been canceled cannot be uncanceled (moved to a different status in the workflow). This differs from a routable object on hold; see also ["Putting a Routable Object on Hold"](#) on page 9-42.

To uncancel a routable object status change in Web Client:

1. Open the routable object.
2. On the **Workflow** tab, select a status in the Summary workflow chart.
When the Change Status dialog appears, complete the Notify **To:** field, add approvers, acknowledgers, and observers if appropriate, and add comments.
3. Click **Finish**.

The status of the routable object switches to the selected status.

To uncancel a routable object in Java Client:

1. Open the routable object.
2. On the **Workflow** tab, select a status in the chart.
When the Change Status dialog box appears, complete the **Notify** field, add approvers and observers if appropriate, and then add comments.
3. Click **OK**.

The status of the routable object switches to the selected status.

Putting a Routable Object on Hold

The process of switching a routable object to the Hold status type is similar to the process of canceling an object. See ["Canceling a Routable Object"](#) on page 9-40 for detailed instructions.

When you put a routable object on hold, select the Hold status type instead of the Cancel status type.

For information about taking a routable object off hold, follow the directions described in ["Uncanceling a Routable Object"](#) on page 9-41.

Note: A routable object with affected items that has been put on hold can be switched from a Hold status type to another status in the workflow. If you put a released routable object on hold, the revision remains on the item revision list of the affected items. This is a substantial difference between Cancel and Hold.

The routable object on hold appears in the Pending Changes table on the item's **Changes** tab.

Releasing Routable Objects

You can release routable objects by using the **Next Status** button on the **Workflow** tab. See ["Switching a Routable Object from One Status to Another Status"](#) on page 9-10.

If the AutoPromote property of the preceding Review status type is set to Yes, then the routable object is automatically released when all required fields are filled in, and all approvers have approved the change, and all acknowledgers have acknowledged the change.

Before a routable object can be released, the system checks for the following:

- ⌚ The Category field and all other required fields are filled in. (The Agile administrator determines which fields are required in the workflow property settings.)
- ⌚ The routable object passes the release audit.

In addition, when a routable object releases an item, the system checks to see which sites the item is being released for, as indicated on the **Affected Items** tab of the routable object. The system then checks the following:

- ⌚ The value in the **Make/Buy** field on the items' **Sites** tabs, to determine if any of the sites are specified as Buy. A warning is displayed when an AML is required for a Buy item.
- ⌚ The **Site-Specific AML** field of the sites, to determine if any of the sites are required or allowed to have a site-specific AML.

You can use the **Audit Release** button (Java Client) or the **Audit Release** command on the **Actions** menu (Web Client) to verify that the routable object passes the release audit and that all required fields have been completed. For details, including the conditions a release audit checks, see ["Auditing Routable Objects"](#) on page 9-12.

Note: If you do not have Discovery and Read privileges for an item on the **Affected Items** tab of the routable object, you cannot release that routable object.

To release a routable object in Web Client:

1. Open the routable object.
2. If you want, audit the routable object (choose **Actions** > **Audit Release**).

3. On the **Workflow** tab, select the Released status type from the workflow status chart.
4. Complete the **Notify** field and enter any comments in the **Comments** field.
Complete the **Approvers**, **Acknowledgers**, and **Observers** fields if you want an additional signoff cycle after the routable object has been released. Otherwise, leave these fields blank.

See ["Completing the Status Change"](#) on page 9-17.

5. Click **OK**.

If not all the required fields have been completed, you are prompted to complete them. Otherwise, the status of the routable object switches to Released.

To release a routable object in Java Client:

1. Open the routable object.
2. If you want, audit the routable object (click the **Audit Release** button, or right-click and choose **Audit Release**).
3. On the **Workflow** tab, select the Released status type from the workflow status chart.
Or click the **Next Status** button.
4. Complete the **Notify** field, and enter any comments in the **Comments** field.
Complete the **Approvers** and **Observers** fields if you want an additional signoff cycle after the routable object has been released. Otherwise, leave these fields blank.

See ["Completing the Status Change"](#) on page 9-17.

5. Click **Release**.

For information about multiple Released status types, see ["Multiple Released Status Types"](#) on page 9-44.

Unreleasing Routable Objects

You can use the **Workflow** tab to unrelease a routable object by switching the routable object from a Released or Complete status type to a Pending, Submit, Review, Cancel, or Hold status type.

Routable objects can be interrelated in complex ways, for example, by their release order or by being listed on the **Relationships** tab one or more additional routable objects. Unreleasing any routable object can have unforeseen consequences.

Caution: Unreleasing a routable object is **not** a recommended practice. Use **extreme caution** when unreleasing routable objects if you are using Agile Content Service (ACS) or ChangeCAST. After you have released a routable object and it's been passed to your ERP system, unreleasing the routable object has no effect on the information in the ERP system. ACS and ChangeCAST do not pass the updated information about unreleasing a routable object to the ERP system, and any audit trails, records of tasks, or dependencies between objects are **not** restored.

You can unrelease a routable object, if:

- The workflow assigned to the routable object has been configured by the Agile administrator to allow you to switch a Released or Complete routable object to another status type. (The default workflows do not allow this procedure.)

- ? You have the appropriate privileges.
- ? No other changes have been made and released against the same items.

For example, when you are working with items and changes, if other changes have been created and released against the same items, you must first unrelease those later changes. Unrelease those changes in the reverse order in which they were created.

If you do not have Discovery and Read privileges for an item on the **Affected Items** tab of the routable object, you cannot unrelease that routable object.

To unrelease a routable object in Web Client:

1. Open the routable object.
2. On the **Workflow** tab, select a status from the chart. Do *not* select a Released or Complete status type.
3. Selecting the Pending status type lets you edit the unreleased routable object, including selecting a different workflow.
4. Complete the **Notify** field, and enter any comments in the **Comments** field. If appropriate, add approvers, acknowledgers, and observers.
5. Click **OK**.

To unrelease a routable object in Java Client:

1. Open the routable object.
2. On the **Workflow** tab, select a status from the chart. Do *not* select a Released or Complete status type.

Note: Selecting the Pending status type lets you edit the unreleased routable object, including selecting a different workflow.

3. Complete the **Notify** field, and enter any comments in the **Comments** field. If appropriate, add approvers and observers.

See ["Completing the Status Change"](#) on page 9-17.

4. Click **OK**.

Multiple Released Status Types

A workflow can have multiple Released status types. When the routable object enters the first Released status type, all the release checks are performed (described in ["Auditing Routable Objects"](#) on page 9-12), and any BOM or manufacturer data redlines data goes into effect in the affected items. The routable object is now released.

For subsequent Released status types, no additional checks or release actions are performed; the routable object remains released. However, the released routable object may be routed for additional approval cycles. This allows for individual approval cycles after release but before the routable object moves to the Complete status type. The routable object remains released if it moves from a Released status type to either another Released status type or to a Complete status type.

Note: Moving a routable object from a Released status type to a Pending, Submit, Review, Hold, or Cancel status type unrelaxes the routable object.

Use Case of First Released Status

This use case explains how the system refers to multiple Released statuses. The "first Released status" does release the workflow. The other Released statuses provide for additional review signoffs; they can also have Entry Required fields.

Let there be a workflow with multiple Released statuses (call them R1, R2, and R3) and there are Entry Required fields set for each Release status. Also, a "non-first Released status" (in this case, R2 or R3) has been permitted to be a Valid Manual Next Status from one of the pre-Released statuses (that is, you can skip the first Released status, the one that actually releases the workflow). Then, when you select that workflow and it moves from Pending status to R3 status, the system checks the Entry Required fields of the first Released status, R1.

It works this way because the workflow should not be released without checking the first Released status's Entry Required fields, because that's where objects are changed in the database because of the released Change. For example, when an item's lifecycle is changed, its revision (rev) should be incremented, and even if you are attempting to leapfrog over R1, R1's requirements are important; if R1's Entry Required fields are ignored, you could end up with an improperly released item.

Adding Comments to the History Tab

If you have the appropriate privilege and the routable object has a Comment button, you can add a comment to the routable object's History tab and send that comment to the users you select.

To add a History tab comment in Web Client:

1. Open the routable object and click its **Comment** button.
2. In the displayed dialog, enter your comments in the **Comment** field.
3. Use the check boxes to select default users to notify, such as the change analyst or the list of reviewers. Each type of routable object includes a selection of default users appropriate for that type of object.
4. Use the **To:** field to specify additional users to notify. Type user names or click the **Launch Palette** icon to launch the address book palette.
5. If desired, check the **Send notification as urgent** check box.
6. When you are finished, click **Send**.

To add a History tab comment in Java Client:

1. Open the routable object and click its **Comment** button.
2. In the displayed dialog, enter your comments in the **Comment** field.
3. Use the check boxes to select default users to notify, such as the change analyst or the list of reviewers. Each type of routable object includes a selection of default users appropriate for that type of object.
4. Use the **Notify** field to specify additional users to notify.
5. When you are finished, click **Comment**.

Sending Comments to all Previous and Current CCB Members

When sending comments (by using the **Comment** button) from a Review or Released type status in a change, you can specify whether the comments are to be sent to only the *current* review or released status reviewers (that is, for the workflow's current status) or if comments are to be sent to all reviewers in both current and previous Review and Released statuses. In the Comment dialog (Java Client) and the Comment wizard (Web Client), a drop-down box (after

the "Notify Reviewers for" check box) contains **Current Status** and **Current and Previous Statuses** for selection.

Changing a Routable Object's Subclass

The Agile administrator can create new subclasses of routable objects. If you have the appropriate privileges, and the routable object is still in the Pending status type, you can change the subclass of a routable object to another subclass in the same class. For example, if your administrator has created the ECN (engineering change notice) subclass, you can change the subclass of a routable object in the Change Orders class from ECO to ECN.

Note: When you change the subclass of a routable object, some of its data fields may change, and all previous information about the Page Three section is cleared.

To change the subclass of a routable object in Web Client:

1. On the **Cover Page** tab of the change, click **Edit**, and select a new subclass from the **Object Type** drop-down list. For example, for **Change Type**, you can select ECO or ECN (engineering change notice).
2. If the Page Three section (on the **Cover Page** tab) is visible and has data, a warning message appears, alerting you that all Page Three data is cleared.
 - ⌵ Select **Continue** to continue changing the subclass and to allow Page Three data to be cleared.
 - ⌵ Select **Cancel** to cancel the change subclass process. No changes are made to the object.
 - ⌵ Click **Finish**.
3. If the new subclass has an autonumbering scheme assigned by the Agile administrator, Agile Web Client asks you whether to select a new autonumber for the new subclass (unless your Agile system is configured to require autonumbering, in which case you see a different warning message).
 - ⌵ Select **Continue** to continue the process of changing the number.
 - ⌵ Select **Cancel** to cancel the change subclass process. No changes are made to the object.
 - ⌵ Click **Finish**.
4. Agile PLM automatically numbers the change and displays the new number in the **Number** field, and the event is entered on the **History** tab of the routable object.

To change the subclass of a routable object in Java Client:

1. On the **Cover Page** tab of the routable object, select a new subclass *from the* **Object Type** drop-down list. For example, for **Change Type**, you can select ECO or ECN.

If the **Page Three** tab is visible, a warning message appears, alerting you that all Page Three data is cleared.

 - ⌵ Click **Yes** to continue changing the subclass and to allow Page Three data to be cleared.
 - ⌵ Click **No** to cancel the change subclass process. No changes are made to the object.
2. If the new subclass has an autonumbering scheme assigned by the Agile administrator, Agile asks you whether to continue using the same object number.

- ? Click **Yes** to change the subclass but retain the existing number.
- ? Click **No** to change the subclass and assign a new autonumber. If more than one autonumbering scheme applies, you are prompted to select the autonumbering scheme you want.

If the new subclass does not have an autonumbering scheme assigned by the Agile administrator, the process is completed with the subclass being changed but the number not being changed.

Note: When you click the **AutoNumber** button, the number changes automatically. The autonumbering scheme assigned to the subclass you selected is used, or you are prompted to select one (if multiple schemes have been designated).

3. Agile PLM automatically numbers the routable object and displays the new number in the **Number** field, and the event is entered on the **History** tab of the routable object.

After a Routable Object is Released

Releasing a routable object affects the appearance and behavior of the routable object's tabs, and also the BOM of any items affected by the routable object that were included on the affected items list of that routable object.

On the **Cover Page** tab of the routable object:

- ? The status stamp reflects the new status.
- ? The **Status** field reads Released.

On the **Affected Items** tab, the **Add** and **Remove** buttons are disabled.

Note: If the workflow has more than one Released status type, the appearance and behavior of the routable object are altered only when the routable object enters the first Released status type. For more information, see "[Multiple Released Status Types](#)" on page 9-44

Switching Routable Objects to Their Final Status

A routable object's workflow defines its final status. If the workflow has a status of type Complete, it is always the last status in the status list, before any Hold or Cancel status types.

Note: Depending on the assigned workflow, a routable object may not have a Complete status type. A Complete status type is not required in a workflow.

To examine the status lists of the workflows in use at your company, in Java Client, click the **View Workflows** button in the toolbar. In Web Client, choose **Actions > View Workflows**.

If the Released status type is set to autopromote and it immediately precedes the Complete status type, then the routable object automatically switches to the Complete status type when all the required fields for the Released status type are filled in, any approvers have approved the routable object, and any acknowledgers have acknowledged the routable object.

You must have the appropriate privileges to switch a routable object to its Complete status type. See the Agile administrator if you have questions about your privileges.

After a routable object has been switched to its final status, you cannot delete it unless you unrelease it first. See [Appendix A, "Deleting Agile Objects."](#)

To switch a routable object to its final status in Web Client:

1. Open the routable object.
2. If you want, audit the routable object.
3. Select the Complete status type by using either the **Next Status** button or the **Workflow** tab.

The Change Status to *Complete status type name* page appears.

4. Complete the **To:** field.
5. Enter any comments in the **Comments** field.
6. Click **Finish**.

The routable object is switched to its final status.

To switch a routable object to its final status in Java Client:

1. Open the routable object.
2. If you want, audit the routable object.
3. Select the Complete status type by using either the **Next Status** button or the **Workflow** tab.

The Change Status dialog box appears.

4. Complete the **Notify** field.
5. Enter any comments in the **Comments** field.
6. Click **OK**.

The routable object is switched to its final status.

Redlining through ECOs, MCOs, PCOs and SCOs

Redlining highlights, in red, changes made to an object. Only ECOs, MCOs, PCOs, and SCOs have redlining functions. Use these changes when you need to modify a released item. For information about the functions of these types of changes, see the *Product Collaboration User Guide*.

Depending on your company policy, when you redline manufacturing data, use an ECO when you want to advance the revision of an item, or use an MCO when you *do not* want to advance the revision of an item.

For information about redlining a BOM, AML, and attachments, see [Chapter 4, "Concepts and Terms in Agile PLM Solutions."](#)

Redlining through ECOs

You can redline BOM and AML data and attachments using an ECO.

Depending on Agile PLM system configuration, you may be able to perform change-controlled modifications to item Title Block attributes using an ECO in Web Client. See *Product Collaboration User Guide*.

ECO changes let you release new items and modify previously released items. When you create an ECO, a preliminary revision is created for any items modified by the change (the ones listed

on the **Affected Items** tab). When the ECO is released, the preliminary revision is converted to a released revision for each modified item.

Redlining through MCOs

You can redline AML data using an MCO.

Depending on Agile PLM system configuration, you may be able to perform change-controlled modifications to item Title Block attributes using an MCO in Web Client. See *Product Collaboration User Guide*.

MCOs are similar in appearance and function to an ECO. However, MCOs do not change the revision of an item, unlike an ECO. Instead, the MCO number is displayed alongside the corresponding revision number in the **Rev** drop-down list. For example, if there is a pending MCO #M12345 against Rev B of an item, then, on the **Rev** drop-down list, that revision is listed as (B) M12345.

Redlining Prices through PCOs

You can redline prices using a PCO. Using the redlining feature, you can publish the price to your customers. For example, if you have renegotiated the price of a particular item with your supplier and you want to publish the new price, you can redline the price and route it through a PCO.

For detailed information about using PCOs, see *Product Cost Management User Guide*.

Redlining through SCOs

You can redline site-specific BOM and AML data using an SCO.

SCOs are similar in appearance and function to ECOs. However, SCOs do not change the revision of an item, unlike ECOs. Instead, the SCO number is displayed next to the corresponding revision number in the **Rev** drop-down list. For example, if there is a pending SCO S12345 against revision B of an item, then, on the **Rev** drop-down list, that revision is listed as (B) S12345.

Deleting Routable Objects

For details about deleting routable objects, see [Appendix A, "Deleting Agile Objects."](#)

Printing Routable Object's Data

You can print routable objects and other data. With the routable object open, click the **Print** button (Java Client), or choose **Actions > Print** (Web Client). You can print the current tab or all tabs.

Attachments are printed from their native applications or from the AutoVue for Agile viewer.

Working with Attachments

This chapter explains how File Folder objects and attachments are associated.

What are Attachments?

Attachments to Agile business objects contain pertinent information about the object in addition to the information recorded on the object tabs. Examples of attachment files are:

- ⌚ Drawing files such as CAD drawings or scanned image files in viewable formats
- ⌚ Web-based information in the form of URLs
- ⌚ Specifications and other documents
- ⌚ Non-viewable files, compressed files, and so on

Use the business object's **Attachments** tab to manage and access attachments. **Attachments** tab actions allow you to add, remove, open, view (in the Viewer), or get a copy of an attachment file. You can also check out and check in an attachment file to modify or update it. For more information about **Attachments** tab actions, see ["Working with the Attachments Tab of Business Objects"](#) on page 10-4.

Attachment file storage and retrieval is managed automatically by your Agile PLM system. Attachment files are stored in the Agile File Vault and each attachment file in the vault is associated with a numbered Agile file folder object. The concept is similar to the way in which you would file and store paper documents: sort the documents into file folders, label or number the file folders, and store them in a filing cabinet.

Attachment Files and Agile File Folders: an Analogy to Papers, Desks, and Vaults

Using numbered file folder objects and a locked Agile File Vault to store attachment files is similar in concept to the way you might manage paper documents that you must work with every day. The scenario that follows describes a typical office system, which will make the rules that govern Agile attachment files and file folders easier to follow.

Bob is an engineering manager, and managers at his company have to coordinate the designs of their products. Bob has a file cabinet, but he is afraid of losing track of his drawings so he keeps stacks of paper drawings on his desk and he never files them. The drawings are associated with various projects that Bob manages. When Carl wants to see a particular drawing, he must ask Bob, who then searches through the piles on his desk. Bob often has several versions of a drawing, and it is difficult for him to locate the specific version that Carl remembers seeing. Of course, this sorting process is time-consuming and inefficient.

Bob decides to get organized, so he sorts the drawings and puts them into manila file folders, and he even puts a label on each folder with an identifying name or number. Bob puts all the

versions of the same drawing in one file folder, newest version in front and the oldest version in back. He then files the manila folders into his filing cabinet. He can lock the cabinet to keep the drawings secure. Now when Carl asks for a drawing by project name, folder number, and version—for example, the Acme project-Bob locates the Acme drawing that Carl needs.

However, six months later, Bob's archive of drawings has continued to grow. His naming of folders is somewhat inconsistent, and occasionally he cannot find what he wants. He spends too much time fielding requests from his staff, and he hands out various versions of drawings but then forgets who has what. When changes are made to a product, there is no control over which version of drawing plan to use. Bob needs someone to help him manage the drawings, and other engineers in the company have the same problem.

Doris is tasked to create and manage the company's document control vault. Bob and his colleagues give all their drawings and file folders to Doris, who files them in a locked vault. Doris uses a document system that ensures she will always locate the correct file folder and correct version of a drawing. Now when Carl needs a drawing, he requests it from Doris, she locates it in the vault and makes a copy of it. She gives the copy to Carl, but the original drawing stays locked in the vault. Doris also marks the file folder as **Checked Out**. When a file folder is checked out, Doris does not allow any other person to update the drawings in that file folder.

When Carl brings Doris the updated drawing, she puts it in the file folder, records the new version number on the file folder and marks the file folder as **Checked In**. Now when Bob asks Doris for the Acme folder, he can see the progress of work done on the product by Carl and the other engineers.

If Bob happens to know the file folder number of the Acme drawing he wants to update, he can ask Doris to check out that file folder by its number. But he does not have to know the file folder number because Doris keeps track of the relationships between each project, the names and version numbers of the drawings for that project, and the file folder numbers where the drawings are stored.

Agile Document Management: Even More Efficient than Doris

The scenario above illustrates some problems that companies have as designs, data, and information accumulate on projects, and also solutions that have been developed to manage and control the information. Agile PLM manages and controls the product record in electronic form, and Agile users have to become familiar with an arena in which design drawings or data are attachment files, manila folders are file folder objects, and the venerable file cabinet is accessed through the **Attachments** tab of any Agile business object, or from the **Files** tab of a file folder object. There is nobody named Doris controlling the file vault in Agile PLM, but you should recognize the same kind of business rules that have been incorporated into Agile's system of file security and management.

Files and URLs that are attached to—associated with—parts or other business objects have always been called *attachments* in Agile. A file folder is simply a numbered container or "wrapper" for attachment content. By referencing the same file folder number and version on their **Attachments** tabs, multiple business objects can use the same file attachment (for example, a single datasheet attached to multiple manufacturer parts). This ensures that the attachment content is always synchronized with the business objects. Reuse of attachment files prevents the proliferation of multiple copies of the same file in the file vault.

The diagram below illustrates the relationships between business object **Attachments** tabs, file folders, and the file vault. One file in a file folder can be attached to one business object, and another file in the *same* file folder can be attached to another business object.

Attachments to business objects are managed through the **Attachments** tab; use the **Attachments** tab features to add, remove, get, view, and update attachments. In addition, if your company's business processes require it, file folders can be managed and updated

independently of other objects in the database. All attachment files are stored in the file vault, part of Agile File Manager (AFM). For more information about file folders, see [Chapter 11, "Working with File Folders."](#)

It is generally a best practice to limit each file folder to a single, attachable file or URL; however, file folders can contain any number of files and URLs. For example, a file folder might contain the same file under different formats, such as a CAD drawing that is saved in its native CAD format and also in PDF format. Also, items or other Agile objects can have any number of file folders attached. In this way, every file, drawing, or URL that contributes to describing any part, product, or process at the enterprise can be referenced by multiple objects in Agile PLM.

The following diagram illustrates the relationship between business objects with file folders attached, file folder objects, and attachment file content. Once files are added to a file folder, other Agile objects can have any combination of those files attached by referencing the file folder. The following diagram illustrates a few cases.

Figure 10–1 Relationship between business objects and attachments


Multiple Agile objects (Parts, documents, changes, and son on) can reference a single file folder.

Any object in Agile can be associated with:

- a file folder that contains a single attachment file or several files or a single URL
- or several URLs or any combination of these, or
- multiple file folders.

Items (or other Agile objects) with attached file folders.

Note that a business object can point to a specific file contained in a file folder.



What are Attachment Versions?

The version of a file folder is important to understand when you work with attachments. This is a brief introduction to versions. For more information about versions (of attachments) and revisions (of items), see ["About Item Revisions and File Folder Versions"](#) on page 10-30.

- On the **Attachments** tab of business objects, the Folder Version field in each row reports the version of the file folder that is attached to the object. The file folder version represents the version of the attached file.

- ⌚ When you use the **Add > Files** feature of the **Attachments** tab to add business object attachment files from your local disk or network, Agile automatically creates a new file folder container for each of the added files and sets the version of each file folder to 1.
- ⌚ Each time you modify the attachment file, (by checking out the file, editing the file, and then checking in the file) the file folder version number is incremented by one.
- ⌚ A business object revision can attach (that is, point to) only one version of a file folder; you select this version when you add the attachment.
- ⌚ By editing the attachment row, you can select a different version of the file you want to attach or reference from the **Attachments** tab. For example, if an attachment has file folder versions 1, 2, and 3, you can select any one of those versions in the attachment row, or you can select LATEST.
- ⌚ "Latest-x" represents the dynamic "latest version of a file folder," where x is the highest numbered version up to this point. For example, Latest-x is seen as **Latest-3** on the business object's **Attachments** tab. When you select LATEST as the version number, the attachment row always refers to the latest version of the file, no matter how many times it has been updated (checked out and checked in).
- ⌚ When you point to the latest version (that is, either Latest-x or x), you can check out and check in attachment files from the object's **Attachments** tab. You can checkout only the most recent version of the attachment. In this example, the version number must be either Folder Version Latest-3 or Folder Version 3. In the Web Client, if the attachment row refers to a non-latest version (in this example, 1 or 2), the checkout button is enabled, but the checkout operation displays an error message because the file folder version is not the latest.
- ⌚ If you have the appropriate privileges, you can open the file folder object by clicking its number on the **Attachments** tab. For more information about file management activities you can perform from the file folder object, see [Chapter 11, "Working with File Folders."](#)

To access earlier versions of the attachment files, use the Show Versions or View Version feature on the **Attachments** tab to display and select a previous version of the file, as described below.

Working with the Attachments Tab of Business Objects

All business objects in Agile have an **Attachments** tab. Items-parts or documents-and manufacturer parts may reference attachment files more often than the other classes in Agile because those classes represent physical entities that often require supportive information; however, users will likely encounter objects from classes across Agile PLM solutions that have attachments. This section describes operations performed from the **Attachments** tab of any business object.

For more information about items and manufacturer parts, see the *Product Collaboration User Guide*.

You can use the **Attachments** tab to:

- ⌚ Get a copy of an attachment file and place it in a location of your choice
- ⌚ View an attachment file in the Viewer
- ⌚ Open an attachment file in its native application
- ⌚ View previous versions of an attachment file
- ⌚ Print attached files
- ⌚ Add and remove attachments

- 7 Check file folders out, modify them, and check file folders in

Buttons on the Attachments Tab

You need the appropriate privileges to perform any attachment file operation on the **Attachments** tab. The buttons on the **Attachments** tab are enabled or disabled, depending on your privileges and administrative settings. File Validation (Handle File Checksum) addresses some of these dependencies.

The buttons in the following table are available to users with the required privileges. To view a file using Viewer, double-click its File Name (Java Client) or click its File Name link (Web Client). If the file format is included on the list of valid viewer file types in Agile Administrator, the file opens in the Agile viewer. Otherwise, the file opens in its native application, provided the application is installed on your computer.

Note: You cannot make changes to the **Attachments** tab of incorporated items. Once an item rev is incorporated, its attachments cannot be checked out from the item rev without a change. However, you can still check out or check in the associated file folder, and the folder version still increments upon checkin.

Attachment Tab Buttons, Web Client

Table 10–1 Attachment tab buttons and actions, Web Client

Name	Description
Action: Open file in its native application	Click the File Name link. If the file format is included on the list of valid viewer file types in Agile Administrator, the file opens in the Agile viewer. Otherwise, the file opens in its native application, provided the application is installed on your computer.
Remove	Removes all selected files from the Attachments tab. The Remove button is disabled if the item is incorporated.
Add	Click the Add button to open the File Uploader. Or, click the Add button's drop-down arrow and select from the menu: Files – displays the File Upload Selector dialog, which lets you drag and drop the files you want to attach. You can also click Browse for Files button to browse your computer or network for the files you want. To add multiple files as a single file folder, click the Add all files to a single file folder button. If you select the UnZip all zipped files after upload check box, the ZIP file is unzipped and the contents are added as individual files. For more information about the Web Client File Upload Selector, see "Web Client File Uploader Tools" on page 10-18.. URLs – brings up the Add URLs dialog By Search – brings up the Add Files by Search dialog The Add button is disabled if the item is incorporated.

Table 10–1 (Cont.) Attachment tab buttons and actions, Web Client

Name	Description
View	<p>Click the View Files button to view the selected files in the Viewer.</p> <p>Or, click the View Files button's drop-down arrow and select from the menu:</p> <p>View – view the files in the Viewer.</p> <p>Compare – compares the selected files and presents a comparison summary.</p> <p>Compare By Search – find other files in the system without having to select two files from the same Attachments tab; that is, you could search and select one attached file from Part 234 and another attached file from Part 765.</p> <p>Overlay – lets you lay other files over the current active file. (For more information, see <i>Viewer Supplement</i>.)</p>
Get	<p>Click the Get button to place a copy of the selected files in the folder or location of your choice. These copies are in native application formats.</p> <p>Click the corner of the table on the Attachments tab to select all files in the table. Click the Get button to copy all files.</p> <p>See "Getting Files in Web Client" on page 10-9.</p>
Open	<p>Click the Open button to open the files in file folders on the Attachments tab as a unit. In the case of multi-file file folders, you can choose an individual referenced file to open.</p>
Check Out	<p>The Check Out button checks a single attachment file or multiple attachment files out of the file vault. From the business object, the checkout prompts you to get the file or files. You can download and edit the file. If you cancel the procedure, the attachment is checked out, but the file is not downloaded. When a folder is checked out, a Has been Checked Out icon appears in front of it on the Attachments tab row.</p> <p>Check Out is disabled when the item is incorporated.</p>
Check In	<p>Click the Check In button to return file(s) to the file vault. The file folder version number is advanced. Previous versions are accessible by using the View Versions feature.</p> <p>Check In is disabled when the item is incorporate</p>
Cancel Checkout	<p>Click the Cancel Checkout button to cancel a checkout. It re-locks the selected file folder, so it is available to be checked out again. A user who has Cancel Checkout privilege can cancel the checkout.</p> <p>Cancel Checkout is disabled when the item is incorporated</p>
More	<p>Click the More button's drop-down arrow and select from the menu:</p> <p>Get Shortcut – Copies a URL to your clipboard, which you can paste into another software application, such as an email, document, or spreadsheet.</p> <p>View Versions – Lets you to switch between versions of the file.</p> <p>Print – With a file or files selected, prints the corresponding files.</p>

Attachment tab buttons, Java Client

Table 10–2 Attachment tab buttons, Java Client











Button	Name	Description
	Get Files	<p>Select the rows you want and then click the Get Files from Selected Attachments button to place a copy of the selected files in the folder or location of your choice. These copies are in native application formats.</p> <p>Or</p> <p>Click the button and select Batch Get All Files from this Object to place a copy of all the object's attached files in the folder or location of your choice. These copies are in native application formats.</p> <p>If you selected a row with multiple files (indicated by a file folder icon in the row), the Select Files dialog appears, allowing you to select which files you want to get.</p>
	Open Files	Click the Open Files button to open the files in file folders on the Attachments tab as a unit. In the case of multi-file file folders, you can choose an individual referenced file to open.
	Show Versions	Click the Show Versions button to open a table of all versions of selected attachment file. From this dialog you can view, get, open, and print a selected version.
	View Files	<p>Click the View Files button to view the selected files in the Viewer.</p> <p>Or, click the View Files button's drop-down arrow and select from the menu:</p> <p>View - view the files in the Viewer.</p> <p> Cross Probe - cross probe between PCB and schematic files in two windows.</p> <p> Compare - compares the selected files and presents a comparison summary.</p> <p> Overlay - lets you lay the selected files over each other.</p> <p> By Search - find other files in the system, which you may want to (select from menu) cross probe, compare, or overlay (see above), without having to select two files from the same Attachments tab; that is, you could search and select one attached file from Part 234 and another attached file from Part 765.</p> <p>(For more information about Cross Probe, Compare, and Overlay, see <i>Viewer Supplement</i>.)</p>
	View Redline	For item objects, the View Redline button shows whether a file has been redlined by the Viewer. Click the button to view the file and its redlines in the Viewer.
	Print Files	Click the Print Files button to print the corresponding attachment file. The Viewer is started in a separate browser window and begins the printing process.

Table 10–2 (Cont.) Attachment tab buttons, Java Client















Button	Name	Description
	Edit	Click the Edit button to edit the Version, File Description, and Folder Description of the selected file that you want to attach, and also any other editable, custom fields that your administrator has defined. The Add button is disabled if the item is incorporated
   	Add Files	Click the Add button to open the File Uploader. Or, click the Add button's drop-down arrow and select from the menu:  Files - displays the File Uploader dialog, which lets you drag and drop the files you want to attach. You can also click Browse for Files button to browse your computer or network for the files you want. To add multiple files as a single file folder, click the Add all files to a single file folder button. If you select the UnZip all zipped files upon upload check box, the ZIP file is unzipped and the contents are added as individual files. Note: Selecting the UnZip check box is not recommended for very large files.  URLs - brings up the Add URLs dialog  By Search - brings up the Add Files by Search dialog  By Scan - permit direct access to a file you want to scan. See "Scan Utility" on page 10-44. The Add button is disabled if the item is incorporated.
	Remove Files	The Remove Files button removes the selected attachment references from the Attachments tab. The file remains linked to the file folder object, and is not removed from the Agile File Management Server. The Remove Files button is disabled if the item is incorporated.
	Check Out	The Check Out button checks a single attachment file or multiple attachment files out of the file vault. From the business object, the checkout prompts you to get the file or files. You can download and edit the file. If you cancel the procedure, the attachment is checked out, but the file is not downloaded. When a folder is checked out, a appears in front of it on the Attachments tab. Check Out is disabled when the item is incorporated.
	Check In	Click the Check In button to return file(s) to the file vault. The file folder version number is advanced. Previous versions are accessible by using the Show Versions feature. Check In is disabled when the item is incorporated.
	Cancel Checkout	Click the Cancel Checkout button to cancel a checkout. It re-locks the selected file folder, so it is available to be checked out again. A user who has Cancel Checkout privilege can cancel the checkout. Cancel Checkout is disabled when the item is incorporated.
(no icon)	Incorporate or Un-incorporated	The information regarding whether the part is Incorporated or Unincorporated is automatically filled in.

Table 10-2 (Cont.) Attachment tab buttons, Java Client

Button	Name	Description
	Has Checksum Error	The Has Checksum Error field is checked if the file has been modified directly in the file server vault. For more information, see "Checksum File Validation" on page 10-29.

Basic Procedures on the Attachments Tab

On the **Attachments** tab of any business object, you can perform all the actions needed to add, view, manage, and update your attachment files.

Note: Your ability to use **Attachments** tab features is determined by your assigned roles and privileges. Contact your Agile administrator if you have questions about your **Attachments** tab privileges.

Getting Attachment Files

You can copy attachment files to the directory of your choice. This is called *getting* a file. You can get as many copies as you like. To revise an attachment file and make the version public, you must check the file out, make changes, and check it back in. This is covered in ["Web Client, Checking Out Attachment Files"](#) on page 10-27 and ["Java Client, Checking Out Attachment Files"](#) on page 10-27.

Several users can get the same attachment files simultaneously. You can get files that are checked out. Also, you can get a file even though the application used to create that file is not installed on your computer.

You must have the appropriate privileges to get a copy of the file. If you have questions about your privileges, contact your Agile administrator.

Note: When you get an attachment file, the date and time stamps on your copy of the file reflects the date and time that you got the file, not the date that the file was attached or saved.

For more information, see:

- ["Getting Files in Web Client"](#) on page 10-9
- ["Java Client, Getting Attachment Files"](#) on page 10-12
- ["Java Client, Batch Get"](#) on page 10-12

Getting Files in Web Client

In Web Client, to get files from the business object **Attachments** tab or from the file folder object **Files** tab, follow the same procedure:

1. Display the **Attachments** tab of a business object.
Or, display the **Files** tab of a file folder object.
2. Click the table row of the file you want.
3. Click the **Get** button.

The download behavior varies depending on which browser you are using.

- ["Web Client, Get Files using Microsoft IE"](#) on page 10-10

- ? ["Web Client, Get Files using Firefox"](#) on page 10-10
- ? ["Web Client, Get files using Chrome:"](#) on page 10-11
- ? ["Web Client, Get Files using Safari for Windows"](#) on page 10-11

Web Client, Get Files using Microsoft IE

To get copies of attachment files from a business object in Web Client when using Microsoft IE:

1. Display the **Attachments** tab of a business object.
Or, display the **Files** tab of a file folder object.
2. Click the table row of the file you want.
3. Click the **Get** button.
The File Download dialog opens. Continue with the next step.
If you selected multiple files, a ZIP file is downloaded.
4. Based on your web browser settings, you may have the option to open or to save the file.
 - ? If you choose to open, select the appropriate application with which you can open the file.
 - ? If you choose to save, the Save As dialog appears. Save the files to disk, specifying the directory where you want to place the files. Web Client copies the files to the selected directory. If you get copies of multiple files, they are placed in a ZIP file.
5. Click **OK**. The files (or ZIP file) are copied to the specified directory.

Web Client, Get Files using Firefox

To get copies of attachment files from a business object in Web Client when using Firefox:

1. Display the **Attachments** tab of a business object.
Or, display the **Files** tab of a file folder object.
2. Click the table row of the file you want.
3. Click the **Get** button.
Depending on the browser settings, the **Downloads** window appears. You can use the **Downloads** window controls to pause, resume, or cancel the download.
4. Based on your web browser settings, you may have the option to open or to save the file.
 - ? If you choose to open, select the appropriate application with which you can open the file.
 - ? If you choose to save, the **Enter name of file to save to...** dialog appears. Save the files to disk, specifying a file name, if desired, and selecting the directory where you want to place the files. Web Client copies the files to the selected directory. If you get copies of multiple files, they are placed in a ZIP file.
5. Click **Save**. The files (or ZIP file) are copied to the specified directory.
6. To view the Firefox download history information at any time, click the Firefox menu and choose **Downloads**.
For more information, choose **Help** in the Firefox menu.

To configure Firefox download behavior:

1. Click the Firefox menu button, and choose **Options > Options**.

2. On the **General** tab, in the **Downloads** section, you can:
 - ⌵ Change the default download location.
 - ⌵ Select the option **Always ask me where to save files**.
 - ⌵ Choose to show the **Downloads** window when downloading a file.

Web Client, Get files using Chrome:

To get copies of attachment files from a business object in Web Client when using Google Chrome:

1. Display the **Attachments** tab of a business object.
Or, display the **Files** tab of a file folder object.
2. Click the table row of the file you want.
3. Click the **Get** button.
4. Based on your web browser settings, you may have the option to open or to save the file.
 - ⌵ A download indicator appears at the bottom of the screen. Click the menu button on this indicator to pause and resume the download, or choose additional actions.
 - ⌵ If the **Save As** dialog appears, then specify the directory where you want to place the files. and click Save. Web Client copies the files to the selected directory. If you get copies of multiple files, they are placed in a ZIP file.
 - ⌵ If the **Save As** dialog does not appear, then the files are copied to the Chrome default download location.
5. To view the Chrome download history information at any time, click the Chrome menu button and choose **Downloads** from the drop-down menu, or use the menu.
For more information, choose **Help** in the Chrome menu.

To configure Google Chrome download behavior:

1. In the Chrome browser window, click the Chrome menu button, and choose **Settings** from the drop-down menu.
2. On the **Settings** page, click the **Show advanced settings** link.
3. In the **Downloads** section, you can:
 - ⌵ Change the default download location.
 - ⌵ Select the option **Ask where to save each file before downloading**.

Web Client, Get Files using Safari for Windows

To get copies of attachment files from a business object in Web Client when using Safari:

1. Display the **Attachments** tab of a business object.
Or, display the **Files** tab of a file folder object.
2. Click the table row of the file you want.
3. Click the **Get** button.
4. Based on your web browser settings, you may have the option to open or to save the file.
 - ⌵ The **Downloads** window opens and you are prompted to either open or save the file.
 - ⌵ If you choose to save the file, the file is listed in the **Downloads** window. You can use the **Downloads** window controls to pause, resume, or cancel the download.

5. To view the **Downloads** window at any time, click the **Settings** menu button and choose **Downloads** from the drop-down menu.

For more information, choose **Help** in the Safari **Settings** menu.

To configure Safari download behavior:

1. Click the **Settings** button, and choose **Preferences** from the drop-down menu.
2. On the settings dialog **General** tab, you can:
 - ? Change or set the default download folder.
 - ? Choose whether to be prompted before downloading.
 - ? Set how to remove download list items.

Getting Structured Files in Web Client

If the file selected for Get has a structure, the Get function lets you extract all files in that structure (CAD assembly). A zip file is created that contains all files in the structure. The name of the zip file is the original file name (plus .zip), which helps to identify the top-level assembly file inside the zip file. This capability is available in two cases from an **Attachments** tab:

- ? From the **Attachments** tab of a Part object with attached Designs.
- ? From the **Attachments** tab of a Document object with attached File Folders (that is, the older DocuBOM-style CAD structures created by Agile EC).

See also [Chapter 12, "Working with Design Objects."](#)

Java Client, Getting Attachment Files

To get copies of one or more attachment files from a business object in Java Client:

1. Display the **Attachments** tab of an object.
2. Select the rows of the files that you want to get.
3. Click the **Get Files** button.
 - ? If you selected a row with multiple files (indicated by a file folder icon in the row), the Select Files dialog opens.
Select the files you want and click **OK**. The Select Directory dialog opens. Continue with the next step.
 - ? If you selected one or more rows that consist of a single attached file, the Select Directory dialog opens. Continue with the next step.
4. In the Select Directory dialog, specify the directory where you want to store the copies.
To get the files together in one ZIP file, click **Download the files in one ZIP file**. Specify a **ZIP file name**.
5. Click **OK**. The files (or ZIP file) are copied to the specified directory.
You will be prompted whether you want to open the file or files.

Java Client, Batch Get

To batch get copies of all the attachment files of a business object in Java Client:

1. Display the **Attachments** tab of an object.
2. Click the button drop-down menu for **Get Files** and select **Batch Get All Files from this Object**.

- ⌚ If the attachments table includes a row with multiple files (indicated by a file folder icon in the row), the Select Files dialog opens.
Select the files you want and click **OK**. The Select Directory dialog opens. Continue with the next step.
- 3. In the Select Directory dialog, specify the directory where you want to store the copies.
To get the files together in one ZIP file, click **Download the files in one ZIP file**. Specify a **ZIP file name**.
- 4. Click **OK**. The files (or ZIP file) are copied to the specified directory.
You will be prompted whether you want to open the file or files.

Opening Attachment Files in their Native Applications

To open an attachment file from a business object in Web Client:

1. Display the **Attachments** tab of an object.
2. Use one of these methods to open the attachment file:
 - ⌚ Click the file name link.
 - ⌚ Click the **Open** button.

Note: When the Agile system preference **Allow Download of Productivity Components** is set to No, then the Web Client file Open action is the same as the file Get action. For more information, refer to *Agile PLM Administrator Guide*.

- ⌚ Select the row, click the **Get** button, and choose to open the file.

The file opens in its native application providing the following conditions are both true:

- ⌚ The file is not in a format that is listed as a valid Viewer file type. (Viewer valid file types are set by your Agile administrator.)
- ⌚ The native application is installed on your computer.

Note: If the attachment is a URL, clicking the file name link launches the URL in a web browser.

The cells in the **Filename** column do not scroll. Adjust the size of the **Filename** column to see and click individual file name links.

To open an attachment file from a business object in Java Client:

1. Display the **Attachments** tab of an object.
2. Select the rows of the files that you want to open.
3. Click the **Open Files** button. The files will open in their native application.
 - ⌚ If you selected a row with a URL attachment, the URL is launched in a web browser.
 - ⌚ If you selected a row with multiple files (indicated by a file folder icon in the row), the Select Files dialog opens.
Select the files you want and click **Finish**.

If a file's native application is not installed on your computer, then the Viewer will open and display the file.

You can also select a file and then click the **View** button; in this case, the Viewer opens the files for viewing.

Printing Attachment Files

You must have the appropriate privileges to print an attachment file. If you have questions about your privileges, contact your Agile administrator.

Note: A "batch print" is simply printing the contents of a file folder that has multiple files. You still click the **Print** button and follow the sequence in Viewer.

To print a file on the Attachments tab using the Viewer in Web Client:

1. With the **Attachments** tab displayed, select the row to print.
2. Choose **More > Print** from the tab menu.
3. Click the file name link to open the file in the Viewer. In this case you would start the viewer print functions manually.
4. If the file type is supported by the Viewer, the viewer opens and begins the printing process. Follow the instructions in the displayed dialog boxes to complete the printing process. When the printing process is complete, the Viewer automatically closes.

Otherwise, Web Client starts the file's native application and opens the file so you can print it using that application's printing commands. Choose the **Print** command for that application.

Note: When you print from within the Viewer, watermarks and banners can appear in addition to the contents of the attached file. For more information, see ["About Banners and Watermarks on the Printed Image"](#) on page 10-15.

It is also possible to get a copy of the file, open it in its native application, and use the native application's print functions to print the file. The native application must be installed on your computer before you can print the file. Follow the usual printing procedures according to the application's documentation.

To print a file on the Attachments tab using the Viewer in Java Client:

1. With the **Attachments** tab displayed, select one or more attachment rows to print.
2. Click the **Print** button.

You can also select a file and click the **View** button; in this case you would start the viewer print functions manually.

3. If the file type is supported by the Viewer, the viewer opens and begins the printing process. Follow the instructions in the displayed dialog boxes to complete the printing process. When the printing process is complete, the Viewer automatically closes.

Note: When you print from within the Viewer, watermarks and banners can appear in addition to the contents of the attached file. For more information, see ["About Banners and Watermarks on the Printed Image"](#) on page 10-15.

About Banners and Watermarks on the Printed Image

When printed through the AutoVue for Agile viewer, the printed image has a banner above and below the image. The banner has six fields: top left, top center, top right, bottom left, bottom center, and bottom right.

The banner labels and contents for each object class are set by the Agile administrator.

In addition, the Agile administrator can choose to include a printed watermark on the printed image.

Accessing Different Versions of Attachments

You can get, open, view, and print any version of an attachment file from the **Attachments** tab of the business object.

You can easily access history without clicking through to the File Folder object. This is useful when a single file is being modified and accessed by multiple people/different functions. For instance, user can easily trace and identify in which versions another user made their edits - this is identified from version create date and checkout user.

The Versions dialog displays, for each version, the Version Creation Date (date the version was created), whether that version has redlines (indicated by the **Has Been Redlined** icon), and the Checkout User (user who created that version). This lets you easily see the history of an attachment from the **Attachments** tab, including who modified the file, and when it was modified.

To switch between versions of file folders from an object's Attachments tab in Web Client:

1. On the **Attachments** tab, select the attachment row you want.
2. In the tab menu, choose **More > View Versions**. The Versions dialog appears.
3. In the Versions dialog, select the row you want, and choose the appropriate dialog menu button (**Get**, **View**, or **Print**).
4. Optionally, select two version rows, and then choose **Compare** or **Overlay** in the **View** action button drop-down menu.

To switch between versions of file folders from an object's Attachments tab in Java Client:

1. On the Attachments tab, select one attachment row that you want to access.
2. Click the **Show Versions** button. The Versions dialog appears.
3. Select the version row or rows that you want to access.
4. Click the appropriate action button (**Get**, **Open**, **View**, or **Print**).
5. Optionally, click the **Has Been Redlined** icon to open the AutoVue for Agile and display the redlines.
6. Optionally, select two version rows, and then choose **Compare** or **Overlay** in the **View** action button drop-down menu.

Using the File Folder Version Browser

When a File Folder object is open, you can view information about all versions of the File Folder in the Version Browser.

When a Design object is open, you can view information about all versions/revisions of the Design by using the **Actions** menu **View All Versions** command.

A version or revision can be selected from the version drop-down list on File Folder objects. Revisions (if set) are indicated to the right of the version.

To switch between versions of a Design object in Web Client:

From the **Version** drop-down list at the top of the Design object, select the version/revision you want to view.

Note: A version number in brackets, for example [4], indicates a version that has not yet been checked in. In this example, when version 3 was checked out, a pending version [4] was created. Selecting [4] in the version drop-down list lets you view and work with the pending version.

To open the Versions palette:

1. In the **Actions** menu, choose **View All Versions**. The Versions palette opens.

Note: The **View All Versions** action is available only in Web Client. Java Client does not support Design objects.

The Version palette displays the following information about each version:

Table 10–3 File Folder Version palette columns

Versions Column	Description
Column 1	Displays the approval status of the file folder version. Note: The approval status is displayed only if there are approvers on the Routing Slip.
Version	The version number.
Checkin Date Checkin User	The date the version was checked in and the user who performed the checkin. When the version is checked out, these fields are blank.
Change Info	Indicates how the version was modified before it was checked in. Files indicate that the object's files were modified; for example, files were replaced, added, or deleted. For Design objects, Structure indicates that the Design's Structure tab was modified.
Label, Revision, Revision Date	These are version-specific editable fields used primarily with Design data model objects.

Actions you can initiate in the Versions palette:

- **View:** Click the **View** drop-down menu to choose one of the options.
 - **View:** Select any version row and click **View** to view the file or files in AutoVue for Agile.
 - **Compare:** For single-file versions, select two version rows, and choose **Compare** in the **View** button drop-down list. AutoVue for Agile compares the selected files.

The Design object Version palette includes the following additional actions:

- **Comparison Report:** (Design objects only) Click the Comparison Report drop-down menu to choose one of the options.

- **Compare:** Select any two version rows and click **Compare** to compare the Designs in the Comparison Report drop-down menu. A Design Comparison Chart displays a comparison report.
- **Comparison by Search:** Select a version row and click **Compare by Search** in the Comparison report drop-down list. A Compare by Search palette opens. In the drop-down list select either Latest Version or All Versions. Enter a search string (enter * to search for any design object) and execute a quick search. Choose from a list of Designs to compare with the original Design object. The Design Comparison Chart displays a comparison report.
- **Design Comparison Chart**

The Design Comparison Chart displays reports of the compared Design objects.

The plus sign expands the Design object to display a list of child objects attached to it. You can collapse the object using the minus sign. Click the gray dot icon to see more details about Attributes and Files. Colors indicate the state of the Design object. For example, Blue - Added, Orange - Modified, Red - Deleted.
- **Purge Version:** Design objects store large CAD files, which are updated regularly. The **Purge Version** action lets you remove unwanted Design versions and help optimize file storage. To begin the process, the Design object must be in the checked in state. Purging starts at the original version and continues down the **Structure** tab, and goes through all the versions, including the child objects. The process stops if you cannot purge a child object.

Adding and Removing Files by Using the Attachments Tab

This section includes the following topics:

- ["Adding Attachment Files from your Local Disk or Network"](#) on page 10-17
- ["Add Files by Search Options"](#) on page 10-22
- ["Adding a URL"](#) on page 10-23
- ["Adding Files by using SaveAs to Create a New Business Object"](#) on page 10-24
- ["Removing Attachments from the Attachments Tab"](#) on page 10-24
- ["Editing the Attachments Table"](#) on page 10-25

Adding Attachment Files from your Local Disk or Network

In Web Client, when adding files to a business object Attachments tab, the Web Client File Uploader provides full control over file transfers and a File Upload Manager where you can view your recent file uploads. The File Upload Selector allows you to drag and drop the files you want from your desktop or from an open directory window to the file uploader window. The File Upload Selector also has a Browse button so you can find the files you want in that manner.

Note: Internet Explorer (IE) does not support selecting multiple files for drag-and-drop. IE users must select one file at a time to add to the File Upload Selector screen.

For information about using the File Upload Manager, see ["Web Client File Uploader Tools"](#) on page 10-18.

Java Client uses a different file uploader and downloader tool than Web Client. For details, see ["Java Client, Using the Java Upload/Download Tool"](#) on page 10-20.

Web Client File Uploader Tools

The Web Client file uploader is comprised of two file upload dialogs:

? File Upload Selector

When you choose **Add > Files** on the Attachments tab, the File Upload Selector dialog appears. Select files by drag-and-drop or by browsing.

See ["Web Client File Upload Selector"](#) on page 10-18.

? File Upload Manager

The File Upload Manager dialog appears when the file upload process begins or when you click the **Display the progress of file upload button** in the top pane main toolbar. In the File Upload Manager you can pause, resume, or cancel and file upload that is in progress.

See ["Web Client File Upload Manager"](#) on page 10-19.

Web Client File Upload Selector

To add attachment files in Web Client:

1. Click **Add > Files**.

The File Upload Selector dialog appears

2. Open a directory window (for example, Microsoft Explorer) and size the window so that you can see both the File Upload Selector dialog and the directory window on your screen.

3. Navigate to the directory you want.

4. Select one or more file you want and drag it to the File Upload Selector dialog and drop it. The file name appears in the File Upload Selector list.

5. You can also click the **Browse for files** button in the File Upload Selector dialog and browse for the file you want. When using the browse function:

? Double-clicking on folder will open the folder's contents.

? Select one or more files and then click **Open** to add the files to the File Upload Selector list.

? You can select up to 100 files from your computer to upload in one browsing session. Browsing again will add more files to the File Upload Selector list for upload.

? You can open additional directory windows if you choose.

6. When you have selected the files you want, you can make the following choices:

? **Type** – select the file folder type (subclass) you want to create.

? **Unzip all files after upload** – unzips ZIP files so that they are stored in their native format.

If this option is unchecked, a ZIP file is stored in its ZIP format.

? **Add all files to a single File Folder** – adds all the selected files to a single file folder. You may enter a Folder Description.

If this option is unchecked, each file in the list is assigned its own unique file folder, one attachment file to one file folder. By default, Agile assigns attachments to the File Folder type (subclass).

7. When you are done, click **Upload**.

The File Upload Manager dialog appears. See ["Web Client File Upload Manager"](#) on page 10-19.

Web Client File Upload Manager


When you initiate a file upload, the File Upload Manager dialog appears. See ["Web Client File Upload Selector"](#) on page 10-18.

The Web Client File Upload Manager provides a common dialog that enables you to:

- Monitor and observe the progress of file uploads as they occur.
- Pause, resume, or cancel a file upload in progress.
- View the historical list of completed file uploads.




The File Upload Manager controls and features are described in the following table.

Table 10–4 File Upload Manager features

File Upload Manager feature or action	Description
 <p>Display the progress of file uploads button</p> <p>Displays the File Upload Manager.</p>	<p>This button appears in the Web Client Top Pane toolbar. Click this button at any time to display the File Upload Manager dialog. The appearance of this button changes to indicate:</p> <ul style="list-style-type: none"> • The progress of the current file upload indicated by percentage. • A file upload has been paused, indicated by a progress indicator. • The file upload has completed, indicated by a green button.
Auto Hide option	Select this option in the File Upload Manager to hide the File Upload Manager when
Progress indicator display	<p>The progress indicator display appears at the top of the File Upload Manager dialog during a file upload.</p> <p>The indicator graphically displays the progress of the file upload. In addition, details of the file upload are displayed below the graphic:</p> <ul style="list-style-type: none"> • Speed of the file upload in bits per second • Time left until transfer is complete • Percentage of progress • Transferred amount of total to be transferred, for example, 45.00 KB/100.00 KB
Clear All button	<p>Click Clear All to clear the upload history list.</p> <p>By default, a maximum 250 file uploads are displayed in the list. When the number of file transfers exceeds 250, the oldest transfers are removed from the list.</p> <p>For more information, see <i>Agile PLM Administrator Guide</i>.</p>
Table of file uploads	A table of current and historical file uploads appears in the File Upload Manager. See Table 10–5, "File upload list table" .

The list of current and historical file uploads is displayed in a table that includes the following information and controls for each file upload row.

Table 10–5 File upload list table

Column or control	Description
Object number	<p>The unique identifier of the Agile object to which the file was uploaded and attached.</p> <p>Click the object number link to display the object in the Web Client content pane.</p> <p>Product Cost Management attachments are displayed as follows:</p> <ul style="list-style-type: none"> • When a file is uploaded as an attachment to an item within a sourcing project, the sourcing project link is displayed with the item number in parenthesis. Click the sourcing project link to display the Items tab within the sourcing project. • When a file is uploaded as an attachment to an MPN within a sourcing project, the sourcing project link is displayed with the Item number and MPN number. Click the sourcing project link to display the MPN tab within the sourcing project.
File name	The name of the upload file follows the object number.
File size	The size of the upload file.
Date	The date the file was uploaded.
Progress indicator	While the file upload is in progress, a progress indicator graphic is displayed for each file upload.
Status	<p>The status of the file upload. Statuses include:</p> <ul style="list-style-type: none"> • In Progress • Paused • Completed • Not Completed • Cancelled
File upload control buttons	<p>The buttons displayed in this column depend upon whether the file upload is in progress, paused, or completed.</p> <ul style="list-style-type: none"> •  Pause a file upload in progress. •  Remove the file upload from the list. You can remove a file upload row when the file upload is completed, failed, or paused. •  Resume a paused file upload.

For detailed information about Agile Administrator settings related to file upload, see *Agile PLM Administrator Guide*.

Java Client, Using the Java Upload/Download Tool

You can add as many files at one time as you like. There are two checkboxes; when selected, one will **Unzip all zipped files upon upload**, and the other will **Add all files to a single File Folder**. When you are ready, click **Upload**.

When the upload is completed, depending on Agile PLM system settings, you may be prompted “Would you like to delete the uploaded files from your local disk?” which is useful if you have loaded a file onto your machine only to attach it to an Agile object. When you uploaded the file, Agile File Manager created a copy of the file that is always stored in the file vault.

At any time before clicking **Upload**, you can **Cancel** the upload. Click **Close** to close the uploader dialog.

To add attachment files using Advanced File Loader in Java Client:

1. Click Add > Files.

The blank File Uploader window is displayed. The instruction "Drag Files Here" appears in the window.

2. Open a directory window (for example, Microsoft Explorer) and size the window so that you can see both the File Uploader window and the directory window on your screen.

3. Navigate to the directory you want.

4. Select the file you want and drag it to the File Uploader window and drop it. The file name appears in the File Uploader window.

- ? If you drag and drop a folder, all the files in the folder are added to the list in the File Uploader.
- ? You can also click the **Browse** button in the File Uploader window and browse for the file you want. When using the browse function:
 - Double-clicking on folder will open the folder's contents.
 - Single clicking on folder and then clicking **Open** will add all contents of that folder (files and also contents of subfolders within that folder)

5. Continue locating and dragging as many files as you want. You can open additional directory windows if you choose.

To remove any file from the download dialog box (for example, if you made a mistake and selected a file erroneously), simply click the file and press the Delete key on your keyboard.

6. When you have selected the files you want, if desired, click the Options button to make additional choices:

- ? **Type** – select the file folder type (subclass) you want to create.
- ? **Unzip all zipped files upon upload** – unzips ZIP files so that they are stored in their native format.

If this option is deselected, a ZIP file is stored in its ZIP format.

- ? **Add all files to a single File Folder** – adds all the selected files to a single file folder. You may enter a Folder Description.

If this option is deselected, each file in the list is assigned its own unique file folder, one attachment file to one file folder. By default, Agile assigns attachments to the File Folder type (subclass).

- ? **Edit rows after adding** – presents an edit dialog which lets you edit the newly added attachment table rows.

7. When you are done, click Upload.

The files are added to the business object **Attachment** stab. The File Uploader window displays progress messages for each file as it is uploaded.

Note: Agile automatically creates a new file folder container for each of the uploaded files and sets the version of each file folder to 1. If you selected **Add all files to a single File Folder**, only one file folder container is created and the version is set to 1.

8. When the files are uploaded, you are asked whether to delete the uploaded file from your local disk.

- ⌘ **Yes** (default) – removes the copy of the file from the directory from which you selected it. This ensures that the correct version of the file is maintained in the Agile file vault and you do not have any out-of-date copies on your local disk. To view or update the file, use the Agile **Attachments** tab.

Note: The copy of the file on your local disk is removed; it is **not** moved to your desktop recycle bin.

- ⌘ **No** – the copy of the file that you selected to add to the **Attachments** tab remains on your local disk.

Add Files by Search Options

To reuse existing attachments and file folders, use the **Add > By Search** function. This option lets you reuse existing attachments when needed.

To Add attachments by search:

1. Open the object to which you want to add an attachment, and click the **Attachments** tab.
2. Select **Add > By Search**. The Add Files by Search dialog appears.

Add > By Search (button or menu choice) in Java Client opens a dialog with three Search tabs.

This dialog lets you search for any business object (for example, items or manufacturer parts) and select the attachments of those objects to add to the current object.

- ⌘ **Search** tab lets you create a simple search or an advanced search. You can check to search attachment contents, too.
- ⌘ **Saved Searches** tab opens to your navigation pane where you can browse in search folders, select a search, and run it. Again, returned results may be moved to the Selected Items table, and click **OK**.
- ⌘ **Shortcuts** tab opens to your navigation pane where you can select objects from **My Bookmarks** or **Recently Visited**. The system displays shortcuts to only those objects that are appropriate to the operation you are performing.

Note: Only business objects with attached files appear in the search results table. For example, a business object that you viewed recently will not appear on the Recently Visited list of the Shortcuts tab if it has no attachments.

3. When the results of your search are returned, select a row in the Results table, and the related files for that object appear in the Related Files table.
4. In the Related Files table, select and move attachments to the Selected Files table.
 - ⌘ If the object is an item, the Related Files table displays only the attachments on the latest Released Revision of the item (not pending or older revisions).
 - ⌘ For any other (non-item) object, the Related Files table displays only attachments currently on that **Attachments** tab (not previously associated files).

Note: In the Related Files table in the Web Client, double-click to move attachments to the Attachments table.

5. You can continue to run multiple searches or shortcuts until you are finished selecting the attachments you want.
6. To edit the attachment table rows after you add the attachments, check **Edit rows after adding**. (Java Client only)
7. Click **OK**.

The current business object now references (or points to) the existing attachments and file folders you selected.

Add by Search for Existing File Folder

If you have the appropriate privileges, you can use the Add by Search feature ("[Add Files by Search Options](#)" on page 10-22) and select File Folders as the object type for your search.

To add by searching for existing file folders in Web Client:

1. Select File Folders as the object type.
2. Enter the search criteria in the Add Files by Search dialog.
3. In the results table, select the folder you want.
4. Select the file folder version number you want to use. By default, the latest version is selected.
5. Double-click to move your file selections to the Attachments table.
6. You can continue to run searches and select files to add by repeating the above steps.
7. When you are finished, close the Add Files by Search dialog.

To add by searching for existing file folders in Java Client:

1. Select File Folders as the object type.
2. Use one of the available search methods: simple search, advanced search, saved search or shortcuts.
3. In the results table, select the file folder you want.
4. In the Related Files table, select the file folder version number you want to use. By default, the latest version is selected.
5. Move your file selections to the Selected Files table.
6. You can continue to run searches and select files to add by repeating the above steps.
7. When you are finished, if desired, check **Edit rows after adding**, and then click **OK**.

Adding a URL

To add a URL to the Attachments tab in both Java Client and Web Client:

1. Open the object to which you want to add a URL, and click the **Attachments** tab.
2. Select **Add > URL**. The add URL dialog appears.
3. Enter a URL and description. URLs must include the http syntax.

The URL field is prepopulated with the text string **http://** to streamline this process.

4. To verify that you have typed the correct URL, click **Preview**. A new browser window opens using the URL you have entered.

If desired, check the option **Add All URLs to a Single File Folder**. You can enter a Folder Description.

If you leave this option deselected, a separate file folder will be created for each URL.

5. Click **OK** or **Add**. The URL is added to the **Attachments** tab.

Note: If a URL is added to a single file folder (there are no other files or URLs in that file folder) and the file folder version remains at Version 1, you can select the URL row on the **Attachments** tab, click **Edit**, and then edit (modify) the URL. All the business objects that include the URL on their **Attachments** tab will display the newly edited URL.

Adding Files by using SaveAs to Create a New Business Object

When you use Save As to create a new business object (object B), if the object from which you are performing the Save As function (object A) has one or more attachments, an Agile system preference determines how object B's attachments are created.

If your Agile administrator has selected Prompt for this system preference, you will be prompted to choose between the following two options. If you are not prompted, the new object is automatically created using the specified system preference setting.

- ? **Create new copy of file(s)** means that as object A is being replicated to create new object B, the system creates a new copy of the attachment file and also a new (referenced) file folder. Object A references FF-1, ver. 5, now version 5 of the file has been copied but, in new file folder FF-2 referenced by object B, the file is at version 1.
- ? **Reference existing file(s)** means that as the object is being replicated to create a new object, the system will use the existing file folder and create a new reference to it. In this case, object A references FF-1, ver. 5, and object B also references FF-1, ver. 5; the object was replicated but no file folder nor copy of attachment file was created.
- ? **Do not copy file(s)** means that as object A is being replicated to create new object B, the system creates object B with no attachment files. Object B's attachment table is empty.
- ? **Prompt** means that the system will always prompt the user who performs a Save As whether they want to create a new copy of the attachment, simply reference existing file and folder, or create the new object with no attachments. This prompt does not display if object A does not have an attachment.

Removing Attachments from the Attachments Tab

You can modify the **Attachments** tab by removing attachment table rows.

Note: Removing an attachment table row removes only the reference to the attached file's file folder object. The file folder object and its contents are not deleted.

To remove attachments from the Attachments tab:

1. Open the object and click the **Attachments** tab.
2. Select the rows you want to remove.
3. Click the **Remove** button.

Note: You cannot remove an incorporated item's attachments. For more information about incorporated items and attachments, see ["About Item Revisions and File Folder Versions"](#) on page 10-30.

Editing the Attachments Table

You can edit the File Description and Version of the selected attached file and also any other editable fields and custom fields that your administrator has defined.

Note: Your ability to use **Attachments** tab features is determined by your assigned roles and privileges. Contact your Agile administrator if you have questions about your **Attachments** tab privileges.

The following attachment row fields can be edited as described below:

Table 10–6 Attachment table fields edit methods

Field	Edit method
Filename	If the selected row refers to a file folder that contains multiple files, you can use the drop-down list to select a different file. You can select All Files.
File Description	<p>Edit the description for this version of the attached file.</p> <ul style="list-style-type: none"> ⌘ File Description is Folder Version specific. For example, if you modify the File Description for version 3, the File Description for version 1 remains unchanged. Each attachment version can have a different File Description, if needed. ⌘ If the selected row refers to a file folder that contains multiple files and one specific file is selected in the Filename field, you can edit the File Description field. The File Description field on the file folder objects Files tab is updated with the new file description. ⌘ If the select row refers to a file folder that contains multiple files and All Files is selected in the Filename field, the File Description field is editable depending on your roles and privileges pertaining to the referenced file folder. ⌘ If the selected version is incorporated to an item (which may not be the current business object that you are editing), the File Description field is not editable.
Folder Description	<p>Edit the description of the file folder which contains the referenced file.</p> <ul style="list-style-type: none"> ⌘ If the file folder is referenced by multiple business objects, you must have the appropriate modify privileges to edit this field. ⌘ If the file folder is referenced by multiple business objects and you have the appropriate privileges to modify this field, the new Folder Description appears on all the business object Attachments tabs that reference this file folder.
Folder Version	<p>Select the attachment version (file folder version) you want.</p> <ul style="list-style-type: none"> ⌘ If the selected row refers to a file folder that contains multiple files, if you select Latest-x as the version, the Filename field is automatically set to All Files. ⌘ You can select any version in the list. If you select a non-latest version, you will not be able to checkout this attachment row. For more information about latest and non-latest versions, see "What are Attachment Versions?" on page 10-3.

Table 10–6 (Cont.) Attachment table fields edit methods

Field	Edit method
Other editable fields	Your Agile administrator may have defined other custom fields. If you have the appropriate privileges, you can modify these additional fields. Contact your Agile administrator if you have questions about your Attachments tab privileges

To edit attachment table rows in Web Client:

Double-click the fields in the row you want to edit and make the modifications, and then click the **Save** button.

To edit attachment table rows in Java Client:

1. Open the object and click the **Attachments** tab.
2. Select the rows you want to edit.
3. Click the **Edit** button.
4. Make the modifications you want.
5. Click **OK** (Java Client).

Revising Attachment Files

When you need to update or revise the attached file, Agile PLM uses **Check Out** and **Check In** functions to ensure that only one user at a time can revise the file.

This section includes the topics:

- ? ["Web Client, Checking Out Attachment Files"](#) on page 10-27
- ? ["Java Client, Checking Out Attachment Files"](#) on page 10-27
- ? ["Web Client, Checking in Revised Attachment Files"](#) on page 10-28
- ? ["Java Client, Checking In Revised Attachment Files"](#) on page 10-28
- ? ["Canceling Checkouts"](#) on page 10-29
- ? ["Checksum File Validation"](#) on page 10-29

The examples of Bob and Carl, engineers, and Doris, the document control manager in the following story illustrate the concepts of the **Check Out** and **Check In** features. See ["Attachment Files and Agile File Folders: an Analogy to Papers, Desks, and Vaults"](#) on page 10-1.

Doris keeps all the company's documents locked in a document vault. Each document is filed in a labeled file folder. When Bob or Carl needs a copy of a document, Doris makes a copy and gives it to them. See ["Getting Attachment Files"](#) on page 10-9.

However, when Carl wants to revise a document, Doris gives him a copy of the latest version, and she marks the file folder as **Checked Out**. When a file folder is checked out, Doris does not allow any other person to update the drawings in that file folder, although anyone can still request a copy of the drawings.

When Carl brings Doris the updated drawing, she puts it in the file folder, records the new version number on the file folder and marks the file folder as **Checked In**.

In Agile PLM, **Check Out** and **Check In** features provide the following safeguards:

- 7 When an attachment is **Checked In**, no one is allowed to revise the attachment. The attachment file is locked in the vault; however, any user with the appropriate privileges can check it out. The attachment is locked for all users.
- 7 When an attachment is **Checked Out** only the checkout user can revise the attachment. The attachment file remains locked in the vault, and it is not available for checkout by any other user. The attachment is unlocked for revision *only* by the checkout user.

Web Client, Checking Out Attachment Files

Note: To checkout an attachment file on a business object **Attachments** tab, the Folder Version for that row must specify the latest revision, either the latest revision number (for example, **3**) or the dynamic Latest-x revision (for example, **Latest-3**). For more information, see "[What are Attachment Versions?](#)" on page 10-3.

Checkout is disabled for URL attachments

To check out an attachment row of an object for revision, Web Client:

1. Display the **Attachments** tab of the object.
2. Select one or more attachment rows.
3. Click the **Check Out** button.
If you have selected a row that cannot be checked out, an error message is displayed telling you which rows cannot be checked out and why (for example, non-latest version or already checked out).
4. If you have selected an attachment row that includes multiple files (a folder icon appears in the Filename field), or you have selected multiple Attachment table rows, then the Select Files dialog appears. Select the files you want, and click **OK**.
If you select all the rows in the Select Files dialog, then the files are downloaded in a single ZIP file.
5. Depending on the browser you are using and the settings you have selected for the browser, the files are saved to the browser default download location or you are prompted to select a download location. See "[Getting Attachment Files](#)" on page 10-9 for more information about downloading files in each supported browser.

Java Client, Checking Out Attachment Files

Note: To checkout an attachment file on a business object **Attachments** tab, the Folder Version for that row must specify the latest revision, either the latest revision number (for example, **3**) or the dynamic Latest-x revision (for example, **Latest-3**). For more information, see "[What are Attachment Versions?](#)" on page 10-3.

Checkout is disabled for URL attachments.

To check out an attachment row of an object for revision, Java Client:

1. Display the **Attachments** tab of the object.
2. Select one or more attachment rows.

3. Click the **Check Out** button.

If you have selected a row that cannot be checked out, an error message is displayed telling you which rows cannot be checked out and why (for example, non-latest version or already checked out).

4. If you have selected an attachment row that includes multiple files (a folder icon appears in the Filename field), the Select Files dialog appears. By default, all files are selected. Select the files you want, and click **OK**.
5. The Select directory dialog appears. Navigate to the directory where you want to save copies of the checked out files.

To save the files in a ZIP file, select the **Download the files in one ZIP file** option and enter a ZIP file name.

The checkout location is recorded on the **Attachments** tab Checkout Location field; it is also logged on the **History** tab.
6. Click **OK**.
7. The Open Files dialog appears. To open the checked out files, click **Yes**.

Web Client, Checking in Revised Attachment Files

When you check in attachment files, Agile PLM verifies that the file has been modified.

In the check in process you select the replacement file, and Agile replaces the checked out version of the file. The Folder Version is advanced by 1. For example, if you checked out version 6, when you perform a checkin, the version will be 7. Note that version 6 is still stored in the Agile file vault. If you wish to view it, use the Show Versions feature. See ["Accessing Different Versions of Attachments"](#) on page 10-15.

To check in attachment files in Web Client:

1. Select the checked out row that you want to check in.
2. Click the **Check In** button. The File Replace Selector dialog appears.
3. Add the file to the File Replace Selector list by one of these methods:
 - Drag-and-drop the file onto the File Replace Selector list.
 - Click the **Browse for file** button and select the replacement file from the appropriate directory.
4. When you are done, click **Replace**.

Java Client, Checking In Revised Attachment Files

When you check in attachment files, Agile PLM verifies that the file has been modified.

The check in process retrieves the revised file from the Checkout Location recorded on the **Attachments** tab, and replaces the checked out version of the file. The Folder Version is advanced by 1. For example, if you checked out version 6, when you perform a checkin, the version will be 7. Version 6 is still stored in the Agile file vault. To view it, use the Show Versions feature. See ["Accessing Different Versions of Attachments"](#) on page 10-15.

If the revised file has been moved from the checkout location, or you have changed its name, you are prompted to browse for the replacement file.

When the checkin process is finished, you are prompted to delete the checked-in files from your local disk.

To check in attachment files, Java Client:

1. Select the checked out rows that you want to check in.
2. Click the **Check In** button.
3. Agile PLM automatically checks in the revised files from the Checkout Location recorded on the **Attachments** tab when the files were checked out.
4. If any of the revised replacement files are not in the recorded Checkout Location where they were originally checked out, the Check In Files dialog appears.

Note: If you have moved the checked out file or changed its name, then the Check In Files dialog appears so you can specify the check in replacement files.

Use the **Browse** button to locate each replacement file.

5. When you are done, click **OK**.
6. When the check in process is complete, you are asked whether to delete the checked-in files from your local disk. The default response is **Yes**.
 - ⌚ Click **Yes** to delete the copy of the checked-in files from the checkout location.
 - ⌚ Click **No** to leave the copy of the checked-in files in the checkout location.

Canceling Checkouts

When you want to discard edits to attachment files that you checked out, you can cancel the checkout.

A checkout can be canceled only by the user who checked out the attachment, or by a user with necessary privileges. If you have questions about your privileges, contact your Agile administrator.

When you cancel a checkout, copies of the attachment files remain in the checkout location you selected, but the original files are once more available to be checked out from the **Attachments** tab. Any edits you make to the remaining copies of the files do *not* appear in the public versions of the file (the versions of the file stored in the file vault).

To cancel a checkout from an object's Attachments tab in Web Client:

1. Display the **Attachments** tab on an object page.
2. Select the checked-out row or rows for which you want to cancel the checkout.
3. Click the **Cancel Checkout** button at the top of the table.

To cancel a checkout from an object's Attachments tab in Java Client:

1. Display the **Attachments** tab of an object.
2. Select the checked-out row or rows for which you want to cancel the checkout.
3. Click the **Cancel Checkout** button.

Checksum File Validation

To enhance the security of file access and to inform the end-user or administrator of any illegal modification or corruption of a file, the Agile system performs file validation on attachment files with a utility called Handle File **Checksum**. The validation reveals when a file in the file server vault has been modified directly, that is, bypassing the Agile system. So when you try to view, get, check out, check in, or add a file that has been improperly modified, an error message appears and access to the file is prevented until the error is resolved.

In the Java Client, the **Attachments** tab of business objects and the **Files** tab of file folders have a field called **Has Checksum Error**. When a file on an attachment row has a checksum error, the Has Checksum Error field displays the same symbol. (If the administrator has disabled the Checksum Computation systemwide preference, however, this field will not display any errors. If you suspect there are security problems with files and this field is never populated, see your Agile administrator.)

You can resolve a checksum error only if you have been assigned the Reset File Checksum privilege mask. If you click the Checksum icon that appears on an attachment row and get a warning, you cannot resolve the problem; however, the system sends notification to the administrator and other designated users. The **History** tab of the file folder (with the offending attachment file) identifies users who have been notified, either during the validation process or during the "handle checksum" process.

Assuming you have been assigned the Reset File Checksum privilege (along with appropriate file folder privileges), clicking the **Has Checksum Error** icon in the row of the offending file brings up a dialog that offers several options to resolve the problem. Because this privilege is usually assigned to Agile administrators or user administrators, more information about resolving checksum errors is found in *Agile PLM Administrator Guide*. See "Administering Attachments and Files."

About Item Revisions and File Folder Versions

This section distinguishes revisions to items (or other business objects) and versions of file folders (referencing attachment files), and also other background information about the Introductory revision, the "Rev" list on items, change orders (ECO, MCO, SCO) regarding items, and pending revisions. See *Product Collaboration User Guide* for more information about items, revisions, and the change control process.

Revision and Version Defined for Agile PLM

The words "revision" and "version" can be similar or synonymous in a variety of manufacturing contexts; here is what they mean in Agile PLM:

Revision – an item's state at a point in time; also, a BOM's structure at a point in time. Revisions are advanced in the change control process. (Items and change control are documented in *Product Collaboration User Guide*.)

Version – A file folder's state at a point in time; also, an attachment file's state as it is attached to an item or other business object. This latter definition was the only use in Agile 8.5 and earlier. With the introduction of file folders in Agile PLM, version primarily refers to how a file folder changes through file addition, deletion, and replacement.

Viewing a Different Revision

To view a different revision:

1. To see a revision that pertains to a specific manufacturing site, then select that site from the **Site** drop-down list.

Note: When you select ALL from the **Site** drop-down list, the default value in the **Rev** list is the latest released change for that item.

2. Select a revision from the **Rev** drop-down list above the tabs. When you select a revision, the corresponding effectivity date is displayed.

When you select a different revision, *all* the tabs display information from the selected revision. For example, if the **BOM** tab is displayed, and you switch from revision C to revision B, then the other tabs also show revision B.

Note: Not all tabs are revision-specific, for example, the **Where Used** tab and the **History** tab are not revision-specific. When you view tabs that are not revision-specific, the **Rev** drop-down list is disabled.

Introductory Revisions

The initial revision of an item—that is, the revision of a newly created, unreleased item—is called *Introductory*. Introductory revisions have no changes against them, the only rev on the list that is not associated with a change. It is never assigned a revision letter, for when an item is in the Introductory stage, it is not under change control and can therefore be modified directly.

Introductory revisions are treated the same as released revisions; they are considered to be the base revision by Where-used and Object searches, the **Where Used** tab, changes, and the Save As feature. All revision-specific rules that apply to ECO-created revisions also apply to the Introductory revision of an item.

Introductory appears at the bottom of the **Rev** drop-down list because it is the earliest revision. The user can select the Introductory rev and control all the attributes seen on every tab of the object (including **Attachments** tab). Even after pending revisions and released revisions are created, the Introductory rev remains a "baseline" with a single record of data about the item before any changes took effect.

How the Revision List Works

As stated above, a revision labeled **Introductory** in the **Rev** list indicates the initial revision of the object, with no pending changes. Once the object is listed on a change, a letter sequence of revisions is started.

For released revisions, the number of the releasing ECO is displayed next to its corresponding revision. (Remember, an item can be revised only by an ECO.) For example, for a part, if ECO E54321 resulted in the release of revision C, then revision C in the **Rev** drop-down list reads

C E54321

A revision number or letter inside parentheses indicates that the revision is pending, not yet released:

(A) C00004

You may see revisions in the list that are not Introductory and that do not have an assigned revision letter. These are referred to as *blank revisions*.

Blank revisions occur when an MCO is released against an item before an ECO releases the item. That releasing MCO creates a blank revision, as do any subsequent changes that occur before a new ECO revision is created. The **Rev** list displays the number of the MCO instead of a revision letter:

M00001

MCOs and SCOs are based on item revisions, but neither can create a new revision of a part, and, therefore, neither has attachment capabilities. MCO and SCO modifications, which you can select in the **Rev** drop-down list, inherit the attachments of the ECO-created revision or the Introductory revision upon which they are based.

The MCO or SCO number is displayed next to the corresponding revision on the **Rev** drop-down list. For example, if there is a pending MCO M12345 against Rev B of a part, then on the **Rev** drop-down list, that revision is listed as "(B) M12345."

How Rev and Site Lists are Determined

All revisions are shown to all users regardless of their default site or site access. However, when you open an item, the **Rev** drop-down list is set to the last change for your default site.

The default revision of an item that is shown is based on your default site. Even if you select a different site from the **Site** drop-down list, then the default revision still reflects what you see from your default site.

Samples of Rev Lists with ECO, MCO, and SCO

Given the following list of revisions on the **Rev** drop-down list of an item that was initially released as an ECO, the second column describes the attachment capability of each revision.

Table 10–7 *Rev list example, item released by ECO, and attachment capabilities*

Rev list entry	Attachment capabilities
(c) ECO -356	Yes, has attachment capabilities, because it is a pending ECO-created Rev.
B SCO-444	No attachment capabilities; it is based on Rev B and inherits Rev B's attachments.
B ECO-233	Yes, has attachment capabilities, because it is an ECO-created Rev.
A MCO-888	No attachment capabilities; it is based on Rev A and inherits Rev A's attachments.
A ECO-222	Yes, has attachment capabilities, because it is an ECO-created Rev.
INTRODUCTORY	Yes, has attachment capabilities, because it is an introductory revision. Introductory revisions have the same features as an ECO-created revision.

In the case of an item initially released by an MCO to create a blank revision:

Table 10–8 *Rev list example, item released by MCO, and attachment capabilities*

Rev list entry	Attachment capabilities
(B) MCO-934	No attachment capabilities; pending MCO based on Rev B and inherits Rev B's attachments.
B ECO-572	Has attachment capabilities, because it is an ECO-created Rev.
A SCO-444	No attachment capabilities; it is based on Rev A and inherits Rev A's attachments.
A MCO-788	No attachment capabilities; it is based on Rev A and inherits Rev A's attachments.
A ECO-333	Has attachment capabilities, because it is an ECO-created Rev.
MCO-766	No attachment capabilities; it is based on the Introductory revision and inherits the Introductory revision's attachments.
INTRODUCTORY	Has attachment capabilities, because it is an introductory revision. Introductory revisions have the same features as an ECO-created revision.

Working with Pending Revisions

You can create a pending revision of an item. When you create an ECO against an item, the ECO creates a pending revision of that item. Pending revisions let you incorporate (lock) attached files into the item. When the preliminary ECO affecting the item is released, the attached files stay with the new revision of the item and are incorporated (unless your Agile administrator has opted to alter this behavior).

A pending revision is identified by parentheses around the revision number in the **Rev** field, for example, (A).

The pending revision is always based on the latest released revision of the item. If there is an existing pending revision -the item is already on the **Affected Items** tab of an unreleased change order-and you choose to add the item anyway, the pending revision associated with your change order is based on the latest released revision, not the existing pending revision. Thus, if ECO-1 has an existing pending rev on Part 123, and ECO2 is created by SaveAs of ECO-1, then ECO-2 pending rev does *not* reflect any ECO-1 pending rev BOM redlines, manufacturer redlines, attachment redlines, or attachment additions/deletions made to ECO-1 pending rev.

Attachments on Pending Revisions

By default, when a pending revision is created, it inherits whatever files are attached to the current default revision. If any files are then either added to or removed from the current default revision, those modifications are not reflected on the **Attachments** tab of the pending revision.

The administrator sets your system to either allow or disallow attachments to be copied to a new pending revision.

Effects of CopyFilesToRev SmartRule

The **CopyFilesToRev (Copy Files to Rev)** SmartRule setting determines how pending revision item attachments are created or referenced. The Agile administrator sets the Agile PLM system to either copy, copy with warning, reference, reference with warning or disallow the list of attachments to be copied to a new pending revision. There are two "Copy File to Rev" SmartRules, one for File folders class and the other for Designs class, which have different options and which can be set independently.

When you add an item to the Affected Items table of a pending ECO, you create a pending revision of an item. Depending on the Agile PLM **Copy Files to Rev** SmartRule setting, pending revision attachments are processed as followed:

- ⌘ **Copy** (available for File folders only) – For the item's new pending revision, Agile PLM creates a new file folder and creates a new copy of the attachment file, which is placed in the new file folder.
- ⌘ **Reference** – Agile PLM uses the existing file folder and creates a new reference to it on the item's new pending revision **Attachments** tab.
- ⌘ **Disallow** – The new item pending revision is created with no attachments.
- ⌘ **Copy with Warning** (available for File folders class only) – The same as the **Copy** setting, with the option of choosing no attachments for the new pending revision.

When you add items to the pending ECO, you are presented with a warning dialog that includes a row for each item you are adding.

- ⌘ To add the item and to copy the attachments, select both the **Add** check box and the **Attachments** check box.
- ⌘ To add the item with no attachments, select only the **Add** check box.

- ? **Reference with Warning** – The same as the **Reference** setting, with the option of choosing no attachments for the new pending revision.

When you add items to the pending ECO, you are presented with a warning dialog that includes a row for each item you are adding.

- To add the item and to reference the existing attachments, select both the **Add** check box and the **Attachments** check box.
- To add the item with no attachments, select only the **Add** check box.

When this SmartRule is set to **Reference** or **Reference with Warning**, if there are multiple versions of any attachment file, then only the reference to the latest version is used for the new reference on the pending revision.

For example, if you create an ECO against Part 456, Rev C (thus creating a pending Rev D), then all the attachment files that are attached to Rev C are also attached to pending Rev D. (The file and file folder references on the **Attachments** tab of released Rev C are duplicated on the **Attachments** tab of pending Rev D.) Any attachment files that are added to the **Attachments** tab of Rev C, or any other Rev C **Attachments** tab modifications (for example, modifying the file folder version numbers) after the creation of the ECO are *not* copied to pending Rev D.

Note: Attachment files that are added to the Introductory revision after the object is associated with a change (that will result in released Rev A) will not be copied to subsequent revs. This SmartRule does not affect MCO or SCO revisions because MCOs and SCOs do not create separate new revisions.

Availability of Attachment Operations

Certain situations affect access to attachment operations. If operations are disabled, check for the following:

- ? Are you looking at the desired version of the attachment? Always check the number in the **Version** column to ensure you are looking at the latest version, or other specific version you may want to revise.
- ? Are you viewing an item MCO revision? Attachment operations are not available on MCO revisions.

For more information about item revisions and attachment capabilities, see ["Samples of Rev Lists with ECO, MCO, and SCO"](#) on page 10-32.

- ? Have you been granted sufficient privileges? Check with your Agile administrator. You may be granted certain privileges for some files but not for others.
- ? Is the item released? Your privileges may allow you to modify the attachments of an unreleased item; however, you may not have sufficient privileges to modify the attachments of a released item. Check with your Agile administrator.
- ? Is the item revision incorporated? You cannot modify the attachments of an incorporated revision.

More specifically, once an item revision is incorporated, that revision's attachments cannot be checked out from the item **Attachments** tab. (If you select an unincorporated revision of the item, including pending revisions, you can check out from the item **Attachments** tab.) However, you can still check out or check in the associated attachment files in the file folder. Modifications to the file folder (adding, removing, or editing the attachment file) will not affect the incorporated item revision's attachment, since the version of folder (holding the attachment) is fixed when the item's revision is incorporated; while modifications to the file folder will bring about a new version number upon checkin.

For more information about items, incorporation, and changes (for example, ECOs and MCOs), see the *Agile PLM Product Collaboration User Guide*.

See also: "[Adding Files by using SaveAs to Create a New Business Object](#)" on page 10-24.

Viewing and Redlining Attachment Files in the AutoVue for Agile Viewer

With appropriate privileges, you can view attachment files in AutoVue for Agile, redline them, and print them with timestamps, timestamps, and other banner and watermark information.

For more information about working with AutoVue for Agile, see *Viewer Supplement*.

To view a file using AutoVue for Agile in Web Client:

1. Display the **Attachments** tab of the object.
2. Click the name of a file or select the row of the file, and then click **View > View**.

When you click the file name link, the results are as follows:

- ⌵ If the file folder holds a single file, and the file is viewable with AutoVue for Agile, the attachment file opens in the viewer.
- ⌵ If the file folder holds a single file, and the file is *not* viewable with AutoVue for Agile, the attachment file opens in the native application, if it is installed on your computer.

Note: When the Agile system preference **Allow Download of Productivity Components** is set to No, then the Web Client file Open action is the same as the file Get action. For more information, refer to *Agile PLM Administrator Guide*.

- ⌵ If the file folder holds multiple files, and the files are viewable with AutoVue for Agile, the first file in the folder opens in the viewer.
- ⌵ If the file folder holds multiple files, and *none* of the files are viewable with AutoVue for Agile, the file name is not a link. Click the **Get** button to get a copy of the file.

To view a file using AutoVue for Agile, starting from Java Client:

1. Display the **Attachments** tab of the object.
2. Select one or more rows in the files or attachments table.
3. Click the **View** button. The attachment file opens in AutoVue for Agile.

Redlining or Marking Up Files in AutoVue for Agile

With the Viewer, you can add redline layers or "markup files" to attachment files that are referenced by Agile items. To redline or markup attachment files associated with an item, that item must be on the **Affected Items** tab of an ECO. From the ECO, click the **Redline Attachments** tab, open the attachment files and markup or redline using the Viewer.

Note: For more information about ECO redlining and ad hoc file folder redlining, see *Viewer Supplement*.

Attachment files can be redlined in two ways:

- ⌚ Use an engineering change order (ECO) or use an engineering change request (ECR). You cannot use the other routable objects to redline files.
 - ECO markups are saved against and associated with the pending revision of the item.
See ["Marking Up or Redlining Attachment Files from an ECO"](#) on page 10-36.
 - ECR redlining allows you to add the attachments of the ECR affected items to the **Attachments** tab of an ECR and then create redline markups for those files. ECR redline markups are associated with the file folder that holds the file.
See ["Marking Up or Redlining Attachment Files from an ECR"](#) on page 10-37.
- ⌚ "Ad hoc redlining" can be done from the **Files** tab of a file folder that holds the object.
See ["Ad Hoc Redlining or Marking Up of Attachment Files from the File Folder"](#) on page 11-21.

Attachment-file redlines follow these rules:

- ⌚ You must have appropriate privileges to redline attachment files.
- ⌚ Only the file folders referenced by parts and documents can be ECO-redlined or ECR-redlined.
- ⌚ Multiple users may redline a file at the same time. If that happens, Agile saves the redlines from the first user and closes the file. When the other users attempt to save their redlines, they see a warning message and can save the redlines to a different location.
- ⌚ Each user can redline in a different color.
- ⌚ For a specific file, for example, FILEA.txt, ECO-created redlines, ECR redlines, and ad hoc file folder redlines are separate from each other. To view ECO-created redlines, you must open the ECO object or the affected item object; ad hoc file folder redlines are not visible via the ECO. To view ad hoc file folder redlines, you must open the file folder object; ECO-created redlines are not visible via the file folder object.

Marking Up or Redlining Attachment Files from an ECO

One method to mark up or redline an attachment file is to create a change order for an item with an attachment, and approach the attachment through the **Redline Attachments** tab of the change.

Note: When redlining an attachment through an ECO, the pending revision attachment Folder Version must be set to a specific version number; if the Folder Version is set to **LATEST-x**, you will not be able to create redline markups. However, you can edit the Folder Version on the **Attachments** tab of the pending revision so that it refers to a specific Folder Version.

For example, if the pending revision of the item refers to Folder Version **LATEST-7** of the file folder, select that row on the **Attachments** tab, click the **Edit** button and use the **Folder Version** drop-down list in the Edit dialog box to select **7**. Click **OK** to complete the edit process. You will now be able to create redline markups for that attachment. Select the added item on the **Affected Items** tab of the ECO.

To mark up or redline an attachment file from an ECO in Web Client:

1. If you have not already done so, add an item with an attachment to the **Affected Items** tab of an unreleased ECO. The item now has a pending revision associated with the unreleased ECO.
2. On the **Affected Items** tab, select the item.

3. If the item has already been redlined, the **Has Redlines** icon will be displayed in the same column. Click the **Has Redlines** icon to access the Redlines page.
4. On the **Redline Attachments** tab, select the row you want to redline.
5. Click the **Redlines** button on the row of the file you want to redline.
6. Use the tools described in the viewer online Help to redline the attachment. To view online Help, choose **Help > Content** in the menu bar.

Note: ECO markups are saved against and associated with the pending revision of the item.

For information about redlining 3D files from a change order, and about viewing change order redlines on the Pending revision of the item's **Attachments** tab, see *Viewer Supplement*.

To mark up or redline an attachment file from an ECO in Java Client:

1. If you have not already done so, add an item with an attachment to the **Affected Items** tab of an unreleased ECO. The item now has a pending revision associated with the unreleased ECO.
2. Select the added item on the **Affected Items** tab of the ECO.
3. On the **Redline Attachments** tab, select the row containing the file you want to redline.
4. Click the **Redline** button.
5. When the Viewer appears, click the **Markup** button. (This button is available only when markups are allowed.)
6. Use the tools described in the viewer online Help to redline the attachment. To view online Help, choose **Help > Content** in the menu bar.

Note: ECO markups are saved against and associated with the pending revision of the item.

Marking Up or Redlining Attachment Files from an ECR

You can create redline markups for the ECR Affected Item attachments by adding those attachments to the ECR **Attachments** tab. Then, use the ECR **Attachments** tab **Redline** button to open the file in AutoVue and create redline markups. These markups are associated with the file folder version of the attached file, similar to ad hoc file folder redline markups. See ["Ad Hoc Redlining or Marking Up of Attachment Files from the File Folder"](#) on page 11-21.

To mark up or redline an attachment file from an ECR affected item Web Client:

1. If you have not already done so, add one or more items with an attachment to the **Affected Items** tab of an unreleased ECR.
2. On the ECR **Attachments** tab, add the affected item attachment to the ECR attachments table:
 - a. Click the **Add** drop-down menu and choose **From Affected Item**. The Affected Items palette for the ECR appears.
 - b. Select the table row for the affected item that you want. The attached files for that are listed in the lower pane.
 - c. Double-click the desired file. It is added to the ECR Attachments table.
 - d. Press Escape to close the palette.

3. On the ECR Attachments tab, select the row of the attachment you want to redline.
4. Click the **Redline** button. AutoVue for Agile opens and displays the selected file.
5. Use the tools described in the viewer online Help to redline the attachment. To view online Help, choose **Help > Content** in the menu bar.

Note: ECR attachment markups are saved against version of the file folder that contains the file.

Configuring File Associations for Opening Files in Web Client

When you are using Web Client, you can open attachment files in your browser. This feature works for those file formats for which you have the corresponding applications installed, and when the file association is set up for your browser between those applications and file formats. Web Client relies on the file format associations, which are set up in your operating system, to open the appropriate application with which to open a file.

Your system administrator can help you determine the file format associations that need to be set up in your system to handle the file formats you are working with.

Some examples of common file formats and their associations are shown in the following table:

Table 10–9 *File associations for opening files in Web Client*

File format	File extension	Application often associated
Microsoft Word document	DOC	Microsoft Word for Windows
Microsoft Excel file	XLS	Microsoft Excel for Windows
JPEG graphic	JPEG, JPG	Default browser
GIF graphic	GIF	Default browser
HTML	HTML, HTM	Default browser
PDF	PDF	Adobe Acrobat Reader

For UNIX users, Web Client attempts to display the file within a new instance of the browser window. The file types that can be displayed depend on various factors, including the UNIX vendor and the version of Netscape Communicator that has been installed. If you have questions, see your system administrator for assistance.

If you cannot view the file, you can get a copy instead (using the **Get** button), and view it in the file's associated application.

Smart URL Quick Access to Files

You can generate quick access URLs that provide direct pointers to Agile objects, to Agile attachment files, or to Agile searches.

These quick access URLs can be pasted into other applications or files such as spreadsheet files, word processing files, a company Intranet web page or WIKI page, or into an email. When a user clicks the Smart URL, an Agile PLM Web Client window opens and displays the object, attachment file or search window.

For information about quick access to attachment files using attachment quick access Smart URLs, see:

- ["Generating Attachment Quick Access URLs"](#) on page 10-39

- ? ["Agile-Generated Attachment Quick Access URLs"](#) on page 10-39
- ? ["User-Generated Attachment Quick Access Smart URL Formats"](#) on page 10-40
- ? ["Accessing Attachment Files using Quick Access URLs"](#) on page 10-43

For information about quick access to Agile objects using quick access URLs, see:

- ? ["Agile-Generated Quick Access Object Smart URLs"](#) on page 5-24
- ? ["Using Quick Access Object Smart URLs"](#) on page 5-24
- ? ["Formats for User-Generated Smart Object URLs"](#) on page 5-24

For information about quick access to searches using search quick access Smart URLs, see:

- ? ["Smart URL Quick Access to Searches"](#) on page 8-73

Generating Attachment Quick Access URLs

Attachment URLs allow you to do the following:

- ? Generate a URL for an attachment on item objects.
- ? Generate a URL for a file on file folder objects.
- ? Generate a URL for a file on the **Content** tab of Program objects.
- ? Paste URLs from Agile PLM to another application
- ? Externally open files outside of the Agile PLM application.

You can generate attachment URLs from Items, Activities, and File Folders by two methods:

- ? Using Agile PLM commands to copy a URL to your clipboard:
["Agile-Generated Attachment Quick Access URLs"](#) on page 10-39
- ? Manually typing an Attachment Smart URL in an easy-to-understand format:
["User-Generated Attachment Quick Access Smart URL Formats"](#) on page 10-40

The URL format enables you to identify which object and files are being referenced. Because of the easy-to-understand format, you can generate your own URLs to point to specific file attachments without logging into the Agile PLM system, if you know where the files are located.

See also ["Accessing Attachment Files using Quick Access URLs"](#) on page 10-43.

Agile-Generated Attachment Quick Access URLs

From Web Client, you can only generate Attachment Quick Access URLs from the **Attachments** tab of any object, the **Content** tab of Activities, and **Files** tab File Folders by clicking **Get Shortcut** after performing one of the following scenarios:

- ? Selecting **only** one row from the **Attachments**, **Content**, or **Files** tab to generate a URL that points to the folder corresponding to the file on that row.
- ? Selecting all the rows on the **Attachments**, **Content**, or **Files** tab to generate a URL that points to the collection of files on the tab.

Note: You must have Read privileges for an object to generate a URL for the object.

If you select more than one row, but not all rows, on the **Attachments**, **Content**, or **Files** tab, then the Get Shortcut link is disabled.

The URL is copied to your clip board. You can then paste it into another application or file, such as a word processing file, a spreadsheet file, or an email.

User-Generated Attachment Quick Access Smart URL Formats

With the easy-to-understand Smart URL format, you can generate your own URLs to point to specific file attachments without logging into the Agile PLM system, if you know where the files are located.

The formats of user-generated attachment Smart URLs depend on the object type, and fall into three main categories:

- ? ["Item Attachment Quick Access Smart URL Formats"](#) on page 10-40
- ? ["File Folders Quick Access Smart URL Formats"](#) on page 10-42
- ? ["Program Content Quick Access Smart URL Formats"](#) on page 10-43

Item Attachment Quick Access Smart URL Formats

You can generate Smart URLs for item attachments in the following format:

```
http://<server:port>/<VirtualPath>viewer<ObjectType>/<ObjectNumber>
[/Revision/ChangeNumber]/files/Folder/<FolderNumber>[/<FileAction>]
```

or

```
http://<server:port>/<VirtualPath>viewer<ObjectType>/<ObjectNumber>
[/Revision/ChangeNumber]/files/<FileName>[/<FileAction>]
```

where the URL has the following representation:

Table 10–10 Item Attachment Smart URL formats

URL format component	Represents
<Server:Port>/<Virtual Path> element	Identifies the Agile instance
ObjectType	Refers to the subclass of the Item, File Folder, or Program/Activity.
ObjectNumber	Refers to the actual object number for the object type.
Revision	Identifies an item revision by specifying the change number corresponding to that revision.
ChangeNumber	Identifies a unique revision (Released or Pending) of the item. If the number is not specified, the latest released revision is attached. If the number is not specified and the item does not have a released change, the Introductory revision is attached.
Folder	Indicates that the object is a file folder, not the actual file.
FolderNumber	Identifies the file folder related to the selected row. The version of the file retrieved is the most current version, based on the specific revision of the item.
FileName	Refers to the name of the specific file attached to the specified revision of the item.

Table 10–10 (Cont.) Item Attachment Smart URL formats

URL format component	Represents
FileAction	<p>Determines the action performed with the retrieved files. Values are GET, VIEW, OPEN, or MARKUP. If FileAction is not specified, a GET is performed.</p> <p>If the parameters specified in the URL point to a single file, the file is retrieved in its native format. If the parameters specified in the URL point to a collection of files, then all the files are returned as a zipped file called "Download.zip".</p> <p>OPEN performs the same action as clicking on the file name in the Web Client. MARKUP opens the file in the Viewer with markup being active.</p>

If the specific revision of an item has multiple files contained in the same folder on the Attachments tab, but is referenced from different versions of the folder, then a Folder-based URL may not reflect the actual set of attachments from the item revision's Attachments tab.

Examples of user-generated URLs for item attachments:

```
http://myappserver/mycompany/viewer/Document/DOC0001/files/Folder/Folder001
```

Returns a zipped file containing all files from Folder001 that are attached to the latest released revisions of DOC0001.

```
http://myappserver/mycompany/viewer/Document/DOC0001/files/Folder/Folder001/VIEW
```

Opens all files from FOLDER001 that are attached to the latest released revision of DOC0001 in AutoVue for Agile.

Limitations for Item Object Attachment Quick Access Smart URLs

The following limitations apply to retrieving the attached files of item objects:

- In the case where a specific revision of an item has multiple files on its **Attachments** tab that belong to the same folder, but are referenced from different versions of the folder, a folder-based URL may not reflect the true set of attachments from that item+revision's **Attachments** tab. For example, consider an item P0001, whose revision A has two attachments: P0001_3dmodel.dwg and P0001_specs.pdf, both in Folder1. Assume that the DWG file is from version 2 of the file folder, and the PDF file is from version 5 of the file folder. In this case, the following URL:

```
http://server:port/<VirtualPath>/viewer/Part/P0001/Revision/C0001/files/Folder/Folder1
```

returns all the files contained in either version 5 or version 2 (results are not predictable) of Folder1.

However, the following URL:

```
http://server:port/<VirtualPath>/viewer/Part/P0001/Revision/C0001/files/ALL
```

returns the complete set of files belonging to revision A of the item, including P0001_3dmodel.dwg from version 2 of Folder1 and P0001_specs.pdf from version 5 of Folder1.

- You cannot generate an item-based URL that will return a file from a historical version of a file folder referenced on an item's attachments tab. The user can, however, generate a folder-based URL to achieve this.

- 7 In case of the following format example,

```
http://server:port/<VirtualPath>/viewer/ObjectType/  
ObjectNumber[/Rev/ChangeNumber]/files/FileName[/FileAction]
```

If two files of the same name (file name + file extension) exist on the attachments table, and a user generate a URL using file name, only the first encountered file is retrieved. If you use the ALL option to access files from the **Attachments** tab of an item where there are multiple files by the same name on the attachments table, or if a URL is generated to return all the files of a file folder where there are more than one file with the same name, an error is displayed indicating that there are multiple files by the same name and therefore a valid zip archive of files cannot be generated.

- 7 If you use the ALL option to access files from a Program's **Content** tab where multiple files with the same name exist, an error is displayed indicating that there are multiple files by the same name and therefore a valid zip archive of files cannot be generated.

File Folders Quick Access Smart URL Formats

You can generate Smart URLs for file folders in the following format:

```
http://<server:port>/<VirtualPath>/viewer/<ObjectType>/<ObjectNumber>/  
files/<FileName>[/</version>[/<FileAction>]
```

where the URL has the following representation:

Table 10–11 File Folder smart URL format

URL format component	Represents
<Server:Port>/<Virtual Path> element	Identifies the Agile instance
version	Identifies the specific version of the file folder. The value can be a number, or the string, LATEST (default).
FileName	<p>Refers to the name of the specific file from the folder or string ALL which attaches all the files in the specified version of the folder.</p> <p>If more than one file of the same name exists in a specific version of a folder and a URL is generated based on file name, only the first version of the file is attached. You cannot use the ALL value to access files from a folder where more than one file of the same name exists.</p>
FileAction	<p>Determines the action performed with the retrieved files. Values are GET, VIEW, OPEN, or MARKUP. If fileaction is not specified, a GET is performed.</p> <p>If the parameters specified in the URL point to a single file, the file is retrieved in its native format. If the parameters specified in the URL point to a collection of files, then all the files are returned as a zipped file called "Download.zip".</p> <p>OPEN performs the same action as clicking on the file name in the Web Client. MARKUP opens the file in the Viewer with markup being active.</p>

Examples of user-generated URLs for file folder attachments:

```
http://myappserver/mycompany/viewer/FileFolder/Folder0001/files/abc.txt/1
```

Gets the abc.txt file from version 1 of Folder0001.

```
http://myappserver/mycompany/viewer/FileFolder/Folder0001/files/ALL/VIEW
```

Opens all files from the latest version of FOLDER001 in AutoVue for Agile.

Program Content Quick Access Smart URL Formats

You can generate Smart URLs for files on the **Content** tab of Programs and Activities. The **Content** tab allows specification of any object as valid content and allows the addition of external files, just like the **Attachments** tab. However, the **Content** tab stores the folder object related to an attached file as valid content. So, when retrieving, you must attach the entire folder.

The Smart URL for files on the **Content** tab is generated in the following format:

```
http://<server:port>/<VirtualPath>/viewer/<ObjectType>/<ObjectNumber>/content/Folder/<FolderNumber>[/<FileAction>]
```

where the URL has the following representation:

Table 10–12 Program Content smart URL format

URL format component	Represents
ObjectType	Represents the subclass of the Program object.
ObjectNumber	Represents the identifier of the Program object.
Content	Indicates the Content tab.
Folder	Indicates that a specific folder is being retrieved.
FolderNumber	Refers to the number of the folder being retrieved from the Content tab. The most current version of the folder is always retrieved.
FileAction	Determines the action performed with the retrieved files. Values are GET or VIEW. If FileAction is not specified, a GET is performed. If the parameters specified in the URL point to a single file, the file is retrieved in its native format. If the parameters specified in the URL point to a collection of files, then all the files are returned as a zipped file called "Download.zip".

Accessing Attachment Files using Quick Access URLs

After clicking or opening an Attachment Quick Access URL, Agile PLM validates that you have the appropriate privileges to get or view the file or set of files specified in the URL. The attachments are viewable in all supported browsers, in AutoVue for Agile, or in the native application.

For example:

1. In an email, the user clicks the Attachment Quick Access URL and an Agile PLM Web Client login popup appears.
2. The user enters their login information

Agile PLM verifies that the user has the appropriate privileges to read and view the file.

Note: If the URL returns a collection of files and the user does not have the appropriate Get or View privilege for one or more files, those files are excluded from the returned collection. However, a collection of files is returned to the user containing the rest of the files for which they do have the appropriate Get or View privileges.

Scan Utility

Note: The Scan Utility is available only in Java Client.

The Scan utility lets you scan drawings and documents for use in Agile. After the scanned image file is created, it is referenced by a file folder, which can be attached to a business object. The name and description that you give the image appears on the **Attachments** tab of any object that points to that file folder. To access the Scan utility, choose **File > Scan Files** or select **Add > By Scan** on either the business object's **Attachments** tab or the **Files** tab of file folders.

Agile PLM uses the application TWAINER (twainer.exe) installed on an appropriate scanner to perform its scan function. Scan runs smoothly with or without a Kofax driver installed. You must install a Twain-driver-driven scanner, such as CanoScan N650U/N656U. Agile's TWAINER reads data from a standard TWAIN data source.

Kofax VRS is an electronic checkpoint for scanned images, working with its certified scanners and connection interfaces. If Kofax VRS is associated with such a scanner, like CanoScan N650U/N656U with TWAIN driver installed and USB connection, then it's a candidate for TWAINER's data source.

Scan supports all objects that can be created in Agile PLM. Scan does not require any roles or privileges. However, your Discover, Read, and Modify privileges may affect Scan.

Installing a Scanner

To install a scanner on your computer:

1. Connect the scanner to the computer and install the scanner.
2. Install Kofax driver.
3. Go to **Start > Settings > Control Panel > Scanners and Cameras**.
4. Double-click **KSM (32-bit)** to start the Kofax Source Manager wizard.
5. Click **Next**. Remove all configured sources.
6. **Create** a new source. In Source Properties dialog, define Source Name and Source Type as follows:

Source Name: Canon
Source Type: TWAIN scanning
7. In Select TWAIN Source dialog, select Canon CanoScan N650U/N656U.
8. Click **Finish**.

Using the Scan Utility

Note: The Scan Utility is available only in Java Client.

The following is a general sequence for using the Scan utility.

1. From an object's **Attachments** tab, select **Add > By Scan**.
2. You can also select **File > Scan File** in the Java Client main menu.
3. Java Client creates the twainer.exe file in %USERPROFILE%\AgileCM\twainer.exe.
Java Client is suspended while twainer.exe completes its execution.
4. Twainer.exe retrieves a list of the TWAIN supporting devices on the client computer and displays the Select Source dialog showing available TWAIN devices.
5. Select one of the devices and twainer.exe displays the TWAIN user interface for that device.
6. You can scan your images or documents and exit the user interface. Any scanned files are stored by twainer.exe in a temp directory.
7. Twainer.exe writes status and scan information to its standard output stream and terminates. Java Client is reactivated and reads the status information.
8. Java Client converts images from the TWAIN standard BMP format to PNG and adds the scanned files as an attachment file to the file folder. If an error occurred, Java Client displays an appropriate error message.
9. Java Client deletes all temporary scanned files and also deletes the twainer.exe program after logging off Java Client.

Working with File Folders

Attachment file storage and retrieval is managed automatically by your Agile PLM system.

What are File Folders?

Attachment files are stored in the Agile File Vault and each attachment file in the vault is associated with a numbered Agile file folder object. The concept is similar to the way in which you would file and store paper documents: sort the documents into file folders, label or number the file folders, and store them in a filing cabinet. There are two primary types of File Folders, regular File folders and Designs.

The relationships between attachments files, file folders, and business objects is explained in detail in:

- ? ["Attachment Files and Agile File Folders: an Analogy to Papers, Desks, and Vaults"](#) on page 10-1.
- ? ["Agile Document Management: Even More Efficient than Doris"](#) on page 10-2.

Why Use and Modify File Folders Directly?

If you have the appropriate privileges, you can perform file maintenance actions on file folder objects directly. Updating and maintaining documents from the file folder object is useful when those documents are attached to many different business objects.

For example, you can update and maintain a document that describes a company-wide procedure by checking out and checking in the associated file folder object. The procedure document (and its associated file folder) may appear on the attachments table on the **Attachments** tabs of many Agile business objects, but you do not need to open each of those business objects to update the procedure attachment.

File folders can be managed and updated independently of other objects in the database. All attachment files are stored in the file vault, part of Agile File Manager.

Examples of file folder content are:

- ? Drawing files such as CAD drawings or scanned image files in viewable formats
- ? Web-based information in the form of URLs
- ? Specifications and other documents
- ? Non-viewable files, compressed (ZIP) files, and so on

It is generally a best practice to limit each file folder to a single, attachable file or URL; however, file folders can contain any number of files and URLs.

Advantages of File Folders

The file folder object was developed to manage documents and URLs that support your company's manufacturing, production, or specification processes. These are some specific advantages of file folder objects:

- ? You can create, modify, or delete file folders. Like any other object in Agile, you can search for file folders and bookmark them.
- ? You can view, redline, and print files from the file folder.
- ? You can search for file folders by file folder attributes, including Filename or File Type, regardless of what business objects the file folders may be attached to.

For more information about searching for attachment content, see ["Full Text Search for Content in Attachment Files"](#) on page 8-17.

- ? File folders can be sent to reviewers for approval without using the change control process. You can track who has received, reviewed, and accepted or rejected file folder content files.
- ? Files that are referenced in a file folder are subject to version control. On the **Attachments** tab, in the Folder Version field, if you edit the row and select **Latest Version**, the object always references the latest version of the file folder, even when the item's revision changes.
- ? File folders can be created by users manually and can also be created automatically. A file folder is created automatically when you attach a file or URL to an object; the file folder is generated, and it is already associated with the object. Now that the file folder exists, it can be associated with other objects.

It may be useful to create a file folder object manually, for instance, when specifications and related design and drawing files are brought together before the part objects (that they describe) have been created in the Agile system. These are later associated with any object in Agile on each object's **Attachments** tab.

- ? With appropriate roles and privileges, files (2D and 3D) can be redlined from the **Files** tab of file folder object.

See ["Viewing and Redlining Attachment Files in the AutoVue for Agile Viewer"](#) on page 10-35. There is additional information about marking up and redlining attachment files in the *Viewer Supplement*.

Working with File Folders

The next sections describe tabs, buttons, actions, fields, and other user-interface elements that you encounter in your work with file folders.

- ? A file folder's **Files** tab lists files and URLs, and you can add and remove files and URLs in the file folder. You can check out and check in file folders from here and then get and edit single attachment files. See ["Working with the Files Tab of File Folders"](#) on page 11-7.
- ? A file folder's **Where Used** tab is populated automatically with a link to any business object that references the file folder on the object's **Attachments** tab.

File Folder Tabs, Buttons and Menus

File folders are listed in a window (Java Client) or page (Web Client) with the following elements:

- 7 **Tabs** on file folder objects include **Title Block**, **Files**, **Routing Slip**, **Relationships**, **Where Used**, and **History**. For information about the contents and operations of the **Files** tab, see ["Working with the Files Tab of File Folders"](#) on page 11-7.

For information about the contents and operations of the **Attachments** tab of objects that reference file folders, see ["Working with the Attachments Tab of Business Objects"](#) on page 10-4..

- 7 **Buttons** on the main toolbar of file folder objects in both clients are **CheckOut**, **CheckIn**, **Cancel CheckOut**, and **Comment**.

- Java Client buttons also include **Approve** and **Reject**.

Additional **buttons** in Java Client are **Send**, **Print**, **Delete**, and **Add Bookmark**. A final button, **More**, is a drop-down menu offering these functions: **Subscribe**, **SaveAs**, **Sharing**, **Process Extensions**, **Mass Update**, and **Get All Files**.

- For Web Client, the **Approve** and **Reject** buttons are visible when you are listed as an approver or observer of the selected version.

For information about Checkout, Checkin, and Cancel Checkout, see ["Getting and Revising Attachment Files and File Folders"](#) on page 11-18.

For information about Approve, Reject, and Comment, see in ["Routing and Reviewing File Folders"](#) on page 11-10.

Subscription and sharing are discussed in [Chapter 5, "Working with Business Objects in Web Client,"](#) and [Chapter 6, "Working with Business Objects in Java Client."](#)

Mass update is covered in ["Performing a Mass Update of a File Folder"](#) on page 11-22.

- 7 Drop-down **menus** include:

- The **Version** list shows the number of times a file has been checked out and checked back in, unless it was modified. By default, the most recent version is shown, but you can select an earlier version. Each time an attachment file is checked out and modified, a new version is created.

If the most recent version is a checked out version, the version number is enclosed in brackets, for example, [4].

- The **Actions** drop-down menu in Web Client offers these actions to perform on the object: **Bookmark**, **Subscribe**, **Save As**, **Delete**, **Print**, **Purge Version**, **Version Browser**, **Copy URL to Clipboard**, **Mass Update**, **Print**, **Send**, **Sharing**, or **View All Versions**. Any existing process extensions are also listed.

The **Actions** shortcut menu in Java Client opens when you right-click anywhere on the file folder object. It offers these actions to perform on the attachment: **Cut**, **Copy**, **Paste**, **Add Bookmark**, **Subscribe**, **Save As**, **Delete**, **Print**, **Send**, **Sharing**, **Process Extensions**, **Mass Update**, **Get All Files**, **Check Out**, **Check In**, and **Cancel Check Out**.

File Folder Tabs

File folders include the following tabs. Some tabs may not be visible in your Agile system, depending on how your Agile administrator has configured Agile PLM.

This table lists the tabs found on all file folder objects, with file folder-specific definitions.

Table 11–1 File Folder object tabs

Tab	Description
Title Block	Provides general information about the file folder, such as a description, the object number, approval status, and the date the file folder was last modified. Your administrator may have added Page Two and Page Three sections (which may be named differently) that contain additional information: class-specific and subclass-specific, respectively.
Files	Lists all the contents of the file folder object, and it is where you add and remove files and URLs in the file folder. For details about the Files tab, see "Working with the Files Tab of File Folders" on page 11-7.
Changes	Optional tab that is enabled when using Design File Change Orders (DFCOs) in Web Client. See Chapter 13, "Working with Design File Change Orders (DFCOs)." The File Folder object Changes tab displays a list of changes related to the File Folder that you are viewing. The changes are displayed in two tables. The information on this tab is filled in automatically. The upper table, Pending Changes, shows pending changes, including changes on hold. The lower table, Change History, shows published (released) and canceled changes.
Routing Slip	Lets you route the file folder for approval, and shows a signoff summary for the file folder; a record of which users have viewed and signed off on it. You can add or remove approvers and observers for the file folder object on this tab.
Where Used	Populated automatically with any business object that references the file folder on the object's Attachments tab. To open an object listed on the tab, click its Number link or Name link.
History	The History tab is a record of actions taken on the file folder and the users who performed those actions. The History tab is populated automatically.

Where Used Tab, File Folder

Note: The File Folder object **Where Used** tab is version-specific and displays the where-used status of the currently selected version.

When you select a different version in the **Version** drop-down list, the Where Used table displays information about the selected version only.

The Attachments table lists all the Agile business objects where the currently selected version of the File Folder object is attached, that is, all the Agile business objects that have the current version of the File Folder object listed on their **Attachments** tab.

Buttons on the Files Tab

You need the appropriate privileges to add or remove files on the **Files** tab. The buttons on the **Files** tab are enabled or disabled, depending on your privileges and administrative settings. File Validation (Handle File Checksum) addresses some of these dependencies. If you have questions about your privileges, contact your Agile administrator.

The buttons described in the following tables are available to users with the required privileges on Agile object pages. Many of the operations in this and subsequent tables are elaborated on later in this chapter.

Buttons on Files tab in Web Client

Table 11–2 Web Client Files tab buttons

Button	Description
Get	<p>The Get button places copies of the selected, referenced files in a location of your choice.</p> <p>These copies are in native application formats. If you select more than one file, a ZIP file containing the selected files is created and placed in the folder or location of your choice.</p>
Open	With a file or files selected, opens the file(s) in its native application, if possible.
View	<p>Click the View Files button to view the selected files in the Viewer.</p> <p>Or, click the View Files button's drop-down arrow and select from the menu:</p> <ul style="list-style-type: none"> 7 View – view the files in the Viewer. 7 Compare – visually compare two files in a third compare viewer window. 7 Overlay – lets you lay other files over the current active file. (For more information, see <i>Viewer Supplement</i>.) 7 Compare By Search – find other files in the system, which you may want to (select from menu) cross probe, compare, or overlay (see above), without having to select two files from the same folder; that is, you could search and select one file in file-folder A and another file in file-folder B
Print	With a file or files selected, prints the corresponding files. The Viewer is started in a separate browser window and begins the printing process.
Remove	Removes all selected files from the Files tab (the file folder object must be checked out). The Remove button is disabled if the file folder is checked in.
Add	<p>Click the Add drop-down button to add a folder reference to the object. It can be a file or a URL. This button is disabled when the file folder is checked in.</p> <p>Click the Add button to open the File Upload Selector dialog.</p> <p>Or, click the Add button's drop-down arrow and select from the menu:</p> <ul style="list-style-type: none"> 7 Files – displays the File Upload Selector dialog, which lets you drag and drop the files you want to attach. You can also click Browse for Files button to browse your computer or network for the files you want. To add multiple files as a single file folder, click the Add all files to a single file folder button. If you select the UnZip all zipped files after upload check box, the ZIP file is unzipped and the contents are added as individual files. <p>For more information about the Web Client File Uploader Selector, see "Web Client File Uploader Tools" on page 10-18..</p> <ul style="list-style-type: none"> 7 URLs – brings up the Add URLs dialog

Buttons on Files tab in Java Client

Table 11–3 Java Client Files tab buttons

















Button	Name	Description
	Get Files	<p>Places copies of the files in the location of your choice. Click the drop-down arrow and select Get files from selected attachments or Batch Get all files from this object. These copies are in native application formats.</p> <p>Select the rows you want and then click the Get Files from Selected Attachments button to place a copy of the selected files in the directory folder or location of your choice. These copies are in native application formats.</p> <p>Or</p> <p>Click the button and select Batch Get All Files from this Object to place a copy of all the file folder's files in the folder or location of your choice. These copies are in native application formats.</p> <ul style="list-style-type: none"> ? If you selected more than one file, you are prompted to choose whether a ZIP file containing the selected files is created and placed in the folder or location of your choice. ? If you choose to create a ZIP file, you can fill in a ZIP file name; if you choose no ZIP file, the individual files are placed in the specified location.
	Open Files	With a file or files selected, opens the file(s) in its native application, if possible.
	Print Files	With a file or files selected, prints the corresponding files. The Viewer is started in a separate browser window and begins the printing process.
	View Files	<p>Click the View Files button to view the selected files in the Viewer.</p> <p>Or, click the View Files button's drop-down arrow and select from the menu:</p> <ul style="list-style-type: none"> ?  View – view the files in the Viewer. ?  Cross Probe – cross probe between PCB and layout ECAD files. (For more information, see <i>Viewer Supplement</i>.) ?  Compare – visually compare two files in a third compare viewer window. ?  Overlay – lets you lay other files over the current active file. (For more information, see <i>Viewer Supplement</i>.) ?  By Search – find other files in the system, which you may want to (select from menu) cross probe, compare, or overlay (see above) without having to select two files from the same folder; that is, you could search and select one file in file-folder A and another file in file-folder B. You can search for file folder objects or for any other object type with attachments.
	Edit	Modify the File Description field of the selected file or files, and any other editable, custom fields that your administrator has defined. The Edit button is disabled if the file folder is checked in.

Table 11-3 (Cont.) Java Client Files tab buttons

Button	Name	Description
	Add Files	Click the Add drop-down menu button to add to the Files tab. It can be a file, URL, or you can scan a document to create an attachment.
	Add URL	Click the Add button to open the File Uploader. Or, click the Add button's drop-down arrow and select from the menu:
	Add Scan	<ul style="list-style-type: none"> ? Files – displays the File Uploader dialog, which lets you drag and drop the files you want to attach. You can also click Browse for Files button to browse your computer or network for the files you want. To add multiple files as a single file folder, click the Add all files to a single file folder button. If you select the UnZip all zipped files upon upload check box, the ZIP file is unzipped and the contents are added as individual files. Note: Selecting the UnZip check box is not recommended for very large files. ? URLs – brings up the Add URLs dialog ? By Scan – permit direct access to a file you want to scan. (Windows only, Java Client only) Runs a Windows application that scans documents using a TWAIN interface. The resulting images are added as file types that are specified by the user using Agile Scan; see "Scan Utility" on page 10-44.
	Replace Files	Replaces a file that has been revised (the file folder object must be checked out). Click Replace to remove the file and add a new version of the file, and then check the folder in.
	Remove	Removes all selected files from the Files tab (the file folder object must be checked out). The Remove button is disabled if the file folder is checked in.
	Handle File Checksum Error	Shows whether files have been modified directly in the file server vault. For more information, see " Checksum File Validation " on page 10-29 (Handle File Checksum).

Working with the Files Tab of File Folders

You can use the **Files** tab of file folders to:

- ? Add files and URLs to the file folder
- ? Delete files or URLs from the file folder
- ? "Get" a copy of an attachment file (but not revise it)
- ? With the file folder checked out, get a file for revision, and then replace the version of the file
- ? Print files
- ? View and redline an attachment file
- ? Open a file without being prompted to download it (Java Client only).

To display the Files tab of a file folder:

1. Open a file folder. (You may want to use a Quick Search for **FOLDER***.)
 - ? In Web Client, click the folder number in the **Attachments** tab to open the folder object.
 - ? In Java Client, double-click the folder number on the **Attachments** tab to open the folder object.
2. Click the **Files** tab to display the contents of the file folder.

To open a file or files in a file folder in Web Client:

1. On the **Files** tab of the folder, click the file name of the file or files you want to open.
2. If the file is a supported file format (see *Agile PLM Administrator Guide* for a list of supported file formats), the file opens in the Viewer. With the appropriate privileges, you can use all Viewer features, as described in ["Viewing and Redlining Attachment Files in the AutoVue for Agile Viewer"](#) on page 10-35.

If the file is not a supported file format, the attachment file opens in its native application, if possible.

To open a file or files in a file folder in Java Client:

1. On the **Files** tab of the folder, select the file or files you want to open.
2. Click the **Open Files** button. The attachment file opens in its native application, if possible.

Fields on the Files Tab

The following table lists fields on the **Files** tab.

Table 11–4 Fields on the Files tab






Field	Description
 (Java Client)	If a file has been modified directly in the file server vault, this icon appears in the field to indicate that the file Has checksum error . Click the icon to get information about the checksum error. See "Checksum File Validation" on page 10-29 (Handle File Checksum). (Java Client only)
 (Web Client)	Replace File The Replace icon is visible in Web Client only when the file folder is checked out. To replace a file, click the Replace icon in a file row to remove the file and replace it with the latest version of that file or another file. You are prompted to browse for the replacement file. Note: The checkin files must have the same file extension as the checkout files.
 (Java Client) or  (Web Client)	This icon appears in the field if the file Has been redlined . The Do Redlining icon will appear here from the file folder level for any file type that is listed in the Supported File Types and Valid Model File Type settings in Agile Administrator. Both of these cases allow ad-hoc viewing and redlining.
File Name	The name of the file. ? In Java Client, the files table row must be selected to print, open, get, or view the file. ? In Web Client, click the file name to view the file in the Viewer.
File Path	Can be manually set.
File Type	The format of the file.
File Size	The size of the file, in bytes.
Last Viewed Date	Date when the file was last viewed. (The History tab records detailed information about file viewing.)

Table 11–4 (Cont.) Fields on the Files tab

Field	Description
Checkout Location	Records where checked out files were placed during the check out procedure. If you are using the Java Client, then Agile uses Checkout Location to automatically locate and checkin the checked-out files.
File Description	Description of the file.
Document Text	If needed, this field will be filled in automatically by the Agile system.
 Master Thumbnail (Web Client)	Only visible if Thumbnails are enabled.

Opening and Viewing Contents of File Folders

This section includes the topics:

- ? ["Web Client, Getting File Folder Files"](#) on page 11-9
- ? ["Java Client, Getting File Folder Files"](#) on page 11-9
- ? ["Java Client, Batch Get"](#) on page 11-10

Web Client, Getting File Folder Files

In Web Client, the process to get files from the file folder **Files** tab is the same process used to get files from a business object **Attachment** tab.

The process is described in:

- ? ["Getting Files in Web Client"](#) on page 10-9
 - ["Web Client, Get Files using Microsoft IE"](#) on page 10-10
 - ["Web Client, Get Files using Firefox"](#) on page 10-10
 - ["Web Client, Get files using Chrome:"](#) on page 10-11
 - ["Web Client, Get Files using Safari for Windows"](#) on page 10-11

Java Client, Getting File Folder Files

To get copies of files from a file folder in Java Client:

1. Display the **Files** tab of the file folder.
2. Select the rows of the files that you want to get.
3. Click the **Get Files** button.
The Select Directory dialog opens.
4. In the Select Directory dialog, specify the directory where you want to store the copies.
If you selected more than one row, and you want to get the files together in one ZIP file, click **Download the files in one ZIP file**. Specify a **ZIP file name**.
5. Click **OK**. The files (or ZIP file) are copied to the specified directory.
You will be prompted whether you want to open the file or files.

Java Client, Batch Get

To batch get copies of all the files from a file folder in Java Client:

1. Display the **Files** tab of the file folder.
2. Click the button drop-down menu for **Get Files** and select **Batch Get All Files from this Object**.
3. In the Select Directory dialog, specify the directory where you want to store the copies.
To get the files together in one ZIP file, click **Download the files in one ZIP file**. Specify a **ZIP file name**.
4. Click **OK**. The files (or ZIP file) are copied to the specified directory.
You will be prompted whether you want to open the file or files.

Switching Between Versions

A version or revision can be selected from the version drop-down list on File Folder objects. Revisions (if set) are indicated to the right of the version.

To switch between versions of a file folder from within the file folder in Web Client:

1. From the **Version** drop-down list at the top of the folder object, select the version/revision you want to view.

To switch between versions of a file folder from within the file folder in Java Client:

1. From the **Version** drop-down list at the top of the folder object, select the version/revision you want to view.

Note: A version number in brackets, for example [4], indicates a version that has not yet been checked in. In this example, when version 3 was checked out, a pending version [4] was created. Selecting [4] in the version drop-down list lets you view and work with the pending version.

Routing and Reviewing File Folders

The Default File Folders Workflow applies to all file folder objects that users create in the File Folders base class, which includes both the *File folders class* and the *Designs class*. This workflow has a read-only privilege along with a single Review status—a simple review-and-signoff—although the signoff can still be an approval or a rejection.

Each Design object version has its own Routing Slip. Each version can have a different set of approvers and observers.

To add Approvers or Observers:

1. Open the Design object.
2. Select the **Routing Slip** tab.
3. In the **Version** drop-down list, select a version.

Note: Ensure that the selected version is check in. You cannot add Approvers to a version which is not yet checked in.

Click the **Check In** button. The Add Reviewers /Remove Reviewers button is active once you check in the Design object.

4. Click the Add Reviewers button. The Add Approvers and Observers dialog box opens.
5. Select the approvers and observers you want to add. Enter a comment, if desired.
6. If urgent, select the **Send notification as urgent** option.
7. Click **OK**.

Similarly, use the Remove Reviewers button to remove reviewers from a Design object.

Approving or Rejecting a Design object:

Approving or rejecting a Design object uses the same process as approving or rejecting any routable object. For detailed information, see:

- ["Approving Routable Objects"](#) on page 9-27.
- ["Rejecting Routable Objects"](#) on page 9-30.

Important: Approvals and rejections are version-specific. Your approval or rejection applies only to the selected version of the Design object.

Printing Attachment Files

You must have the appropriate privileges to print an attachment file. If you have questions about your privileges, contact your Agile administrator.

Note: A "batch print" is simply printing the contents of a file folder that has multiple files. You still click the **Print** button and follow the sequence in Viewer.

To print a file on the Attachments tab using the Viewer in Web Client:

1. With the **Attachments** tab displayed, select the row to print.
2. Choose **More > Print** from the tab menu.
3. Click the file name link to open the file in the Viewer. In this case you would start the viewer print functions manually.
4. If the file type is supported by the Viewer, the viewer opens and begins the printing process. Follow the instructions in the displayed dialog boxes to complete the printing process. When the printing process is complete, the Viewer automatically closes.

Otherwise, Web Client starts the file's native application and opens the file so you can print it using that application's printing commands. Choose the **Print** command for that application.

Note: When you print from within the Viewer, watermarks and banners can appear in addition to the contents of the attached file. For more information, see ["About Banners and Watermarks on the Printed Image"](#) on page 11-12.

It is also possible to get a copy of the file, open it in its native application, and use the native application's print functions to print the file. The native application must be installed on your computer before you can print the file. Follow the usual printing procedures according to the application's documentation.

To print a file on the Attachments tab using the Viewer in Java Client:

1. With the **Attachments** tab displayed, select one or more attachment rows to print.
2. Click the **Print** button.

You can also select a file and click the **View** button; in this case you would start the viewer print functions manually.
3. If the file type is supported by the Viewer, the viewer opens and begins the printing process. Follow the instructions in the displayed dialog boxes to complete the printing process. When the printing process is complete, the Viewer automatically closes.

Note: When you print from within the Viewer, watermarks and banners can appear in addition to the contents of the attached file. For more information, see ["About Banners and Watermarks on the Printed Image"](#) on page 11-12.

About Banners and Watermarks on the Printed Image

When printed through the AutoVue for Agile viewer, the printed image has a banner above and below the image. The banner has six fields: top left, top center, top right, bottom left, bottom center, and bottom right.

The banner labels and contents for each object class are set by the Agile administrator.

In addition, the Agile administrator can choose to include a printed watermark on the printed image.

Creating File Folders

There are two ways to create a file folder: automatically, when you attach a file or URL to a business object in the **Attachments** tab of the object, and manually, using the create object functions of Java Client and Web Client.

To create a file folder manually:

1. Create the file folder using the **Create New** button in Web Client or the **New** button in Java Client.
2. The file folder that you have created is an empty container, that is, it has no files in it. To add files to the file folder, see ["Adding Attachment Files and URLs to File Folders"](#) on page 11-13..

For more information on creating business objects, see ["Creating Objects"](#) on page 5-1.

Revising File Folders

Revising or editing a file folder object requires the appropriate modify privileges, just as editing any Agile object requires the appropriate modify privileges. In addition, you must also have privileges that allow you to check out and check in a file folder.

To revise the **Files** tab, or the content of the file folder, you must check out the file folder, modify files, add files or remove files, and then check in the file folder. For details, see:

- 7 ["Adding Attachment Files and URLs to File Folders"](#) on page 11-13.
- 7 ["Deleting Attachment Files and URLs from File Folders"](#) on page 11-16.
- 7 ["Getting and Revising Attachment Files and File Folders"](#) on page 11-18.

Adding Attachment Files and URLs to File Folders

You must have the appropriate privileges to add attachment files to file folders. If you have questions about your privileges, contact your Agile administrator.

Each time you add a file to the Agile system, it is copied into the Agile File Manager vault as an independent file with a unique numeric vault file name.

You can also include a URL (Internet address) in a file folder. URL attachments point to Internet sites; they are not, themselves, documents on the Agile File Manager file server.

Note: When you check out a file folder, the **Version** field increments by 1, however, other users are still able to view the current version. When you check the file folder in, and it has been changed, the new version number holds. The system will not let an unchanged file folder be checked in. If you did not make a change to the file folder, complete the action by clicking **Cancel Checkout**, and the version number reverts to the previous numeral.

Web Client – When adding files to a file folder **Files** tab in Web Client, Agile PLM provides the Web Client file uploader tools, which are described in the following topics:

- ["Web Client File Uploader Tools"](#) on page 10-18
- ["Web Client File Upload Selector"](#) on page 10-18
- ["Web Client File Upload Manager"](#) on page 10-19

Java Client – When adding files to a file folder **Files** tab in Java Client, Agile provides a simple and easy-to-use file uploader. The Java Upload/Download tool lets you drag and drop the files you want from your desktop or from an open directory window to the file uploader window. The tool also has a **Browse** button so you can find the files you want in that manner.

Deleting attachment files is covered in ["Deleting Attachment Files and URLs from File Folders"](#) on page 11-16.

Using the Java Upload/Download Tool

Note: The Java Upload/Download tool is used in Java Client only.

You can simultaneously add as many files as you like. When adding to the **Files** tab, the Java Upload/Download tool includes one check box; when selected, it will **Unzip all zipped files upon upload**. When you are ready, click **Upload**.

When the upload is completed, depending on Agile PLM system settings, you may be prompted "Would you like to delete the uploaded files from your local disk?" which is useful if you have loaded a file onto your computer only to attach it to an Agile object. When you uploaded the file, Agile File Manager created a copy of the file that is always stored in the file vault.

At any time before clicking **Upload**, you can **Cancel** the upload. Click **Close** to close the dialog.

To add attachment files to the file folder **Files tab using the Java Upload/Download Tool in Java Client:**

1. Open the file folder you want and, if it is not already checked out, click the **Check Out** button.

2. On the **Files** tab, select **Add > Files**.

The blank File Uploader window is displayed. The instruction "Drag Files Here" appears in the window.

3. Open a directory window (for example, Microsoft Explorer) and size the window so that you can see both the File Uploader window and the directory window on your screen.
4. Navigate to the directory you want.
5. Select the file you want and drag it to the File Uploader window and drop it. The file name appears in the File Uploader window.
 - ? If you drag and drop a folder, all the files in the folder are added to the list in the File Uploader.
 - ? You can also click the **Browse** button in the File Uploader window and browse for the file you want. When using the browse function:
 - Double-clicking on folder will open the folder's contents.
 - Single clicking on folder and then clicking Open will add all contents of that folder (files and also contents of subfolders within that folder)
6. Continue locating and dragging as many files as you want. You can open additional directory windows if you choose.

Note: To remove any file from the download dialog box (for example, if you made a mistake and selected a file erroneously), click the file and press the Delete key on your keyboard.

7. When you have selected the files you want, if desired, select the optional check box.
8. **Unzip all zipped files upon upload** — unzips ZIP files so that they are stored in their native format.

If this option is deselected, a ZIP file is stored in its ZIP format.
9. When you are done, click **Upload**.

The files are added to the file folder's **Files** tab. The File Uploader window displays progress messages for each file as it is uploaded.
10. When the files are uploaded, you are asked whether to delete the uploaded file from your local disk.
 - ? **Yes** (default) – removes the copy of the file from the directory from which you selected it. This ensures that the correct version of the file is maintained in the Agile file vault and you do not have any out-of-date copies on your local disk. To view or update the file, use the Agile **Files** tab.
 - ? **No** – the copy of the file that you selected to add to the **Files** tab remains on your local disk.
11. When you are finished, remember to check in the file folder by clicking the **Check In** button.

Adding URLs

Note: If a URL is added to a single file folder (there are no other files or URLs in that file folder) and the file folder version remains at Version 1, you can select the URL row on the **Files** tab, click **Edit**, and then edit (modify) the URL. All the business objects that include the URL on their **Attachments** tab will display the newly edited URL.

To add a URL to the Files tab in both Java Client and Web Client:

1. Open a file folder, and click the **Check Out** button to check out the file folder.
2. Click the **Files** tab to display its contents.
3. Select **Add > URLs**. The URL dialog appears with rows for up to five URLs.
4. Enter a URL and description. URLs must include the http syntax.

Note: The URL field is prepopulated with the text string **http://** to streamline this process.

5. To verify that you have typed the correct URL, click **Preview**. A new browser window opens using the URL you have entered.
6. Click **OK** in Java Client or **Add** in Web Client. The URL is added to the **Files** tab.
7. Click **Check In** to check in the file folder.

Editing the Files Table

When a file folder is checked out, you can modify the editable fields on the **Files** tab.

To edit the files table in Java Client:

1. Open the file folder you want and, if it is not already checked out, click the **Check Out** button.
2. Click the **Files** tab to display it.
3. Select the rows you want to edit, and click the **Edit** button.
The Edit dialog appears.
4. Make the desired modifications and click **OK**.

Note: If a URL is added to a single file folder (there are no other files or URLs in that file folder) and the file folder version remains at Version 1, you can select the URL row on the **Files** tab, click **Edit**, and then edit (modify) the URL. All the business objects that include the URL on their **Attachments** tab will display the newly edited URL.

If there are multiple files or URLs on the **Files** tab, or the file folder has been advanced from Version 1, you will not be able to edit the URL. However, if the file folder is checked out, you can delete the URL row from the table and use **Add > URLs** to add a new URL row.

Note: In the Web Client, the Files tab is displayed in edit mode. Make the desired modifications and click **Save**.

Deleting Attachment Files and URLs from File Folders

When you delete a referenced attachment file, Agile removes the file from the File Management vault. The outside file at its original location is untouched; only the Agile copy in the vault is deleted.

Each time you use an outside file to create a referenced attachment file, it is copied into the File Management vault as an independent file with a unique numeric vault file name. This is true even if you add the same outside file to several different file folders. You can delete the file from one file folder without affecting any of the copies.

You must have the appropriate privileges to delete files and URLs from the **Files** tab. If you have questions about your privileges, contact your Agile administrator.

Note: If the file you want to delete has been checked out from the **Attachments** tab of the business object that references it, (unless you have sufficient privileges) you cannot delete it from the file folder until it has been checked back in on the **Attachments** tab.

To delete files and URLs from a file folder in Web Client:

1. On the **Files** tab of the checked-out file folder, select the files and URLs that you want to delete.
2. Click the **Remove** button or press the **Delete** key.

Note: Be sure to use the **Remove** button on the **Files** tab. *Do not* use the **Delete** command on the **Actions** menu. This deletes the *entire object you are working with*, not just the attachment.

To delete files and URLs from a file folder in Java Client:

1. On the **Files** tab of the checked-out file folder, select the files and URLs that you want to delete.
2. Click the **Delete** button.

Note: Be sure to use the **Delete Attachments** button on the **Files** tab. *Do not* use the **Delete** command on the **File** menu and *do not* use the **Delete Object** button in the object window toolbar. This deletes the *entire object you are working with*, not just the attachment.

Purging Unused File Folder Versions

If you have the appropriate privileges, you can purge checked-in file folder versions that are not referenced by any Agile object. Purging a file folder version removes from the File Management vault all the files checked in for that version. The version number is also removed from the file folder drop-down list.

Purging a file folder version and deleting attachment files have similar results because both actions remove files from the Agile file vault. These actions differ in the following ways:

- 7 When deleting files or URLs from a file folder, the file folder must be checked out. While the file folder is checked out you can selectively delete or replace files and URLs in that checked-out file folder version. When you check in the file folder version, any files or URLs you deleted are removed from the File Management vault. For more information, see ["Deleting Attachment Files and URLs from File Folders"](#) on page 11-16.
- 7 Purging an unused file folder version action can be performed only to a checked-in file folder version. The checked-in file folder version cannot be referenced by any Agile object and it cannot contain any redlined files. Purging a file folder version removes all the files and URLs in that version from the Agile File Management vault.

Why Purge Unused File Folder Versions?

Mary has checked out the Version 5 file attachment from an Item object **Attachments** tab. Mary works on her local copy of the file, and then checks in the Version 6 file attachment for the Item object. After she has checked in, Mary realizes that the file she checked in is incorrect. She checks out the attachment again, replaces it with the correct file and checks in Version 7. The incorrect file in file folder Version 6 remains in the file vault. Even though Version 6 can be considered only an historical document, and the Item attachment table no longer points to Version 6, Mary would like to remove Version 6 completely because it is incorrect.

To remove an unused file folder version:

1. Before you begin, you can verify that the file folder version you want to purge is not referenced by any other Agile object, on an **Attachments** tab or a **Content** tab.
 - a. Navigate to the file folder object and click the **Where Used** tab.
 - b. In the **Version** drop-down list, select the version you want to purge.

If the Where Used table for the selected version is empty, the file folder version is not in use.
 - c. If the Where Used table for the selected version lists one or more objects, if you have the appropriate privileges, you can modify those objects so they use a different file folder version:

Navigate to each object and edit the **Attachments** tab or the **Content** tab of the object to select a version of the file folder other than the version you want to purge. You can choose an earlier version, a more recent version, or the latest version (providing the version you want to purge is not the latest version).
2. With the file folder object open, from the **Version** drop-down list, select the version you want to purge.
3. From the Web Client **Actions** menu or the Java Client **More...** menu, select **Purge Version**.
4. Confirm the prompt.

Agile PLM checks whether the selected file folder version meets the requirements that allow it to be purged:

 - 7 If the selected file folder version is in use (on an Agile object **Attachments** tab or **Content** tab, or on the **Affected Files** tab of a DFCO) or if the file folder version has been incorporated to an item object, then Agile PLM displays a warning message and the file folder version is not purged.

For information about the **Affected Files** tab, see [Chapter 13, "Working with Design File Change Orders \(DFCOs\)."](#)
 - 7 If the selected file folder version contains redlined files, then Agile PLM displays a warning message and the file folder version is not purged.

- ⌚ If the selected file folder version is checked out, then Agile PLM displays a warning message and the file folder version is not purged.

If the file folder version meets the requirements, it is purged. All files and URLs are removed from the Agile File Management vault and the version number is removed from the file folder's **Version** drop-down list.

The Purge Version menu selection is disabled if:

- ⌚ The user does not have the Purge Version privilege.
- ⌚ The latest version of the file folder is zero (0).

Getting and Revising Attachment Files and File Folders

If you have searched and found an attachment file that you are interested in, then you may want to read it, revise it, or print it, among other possibilities. To print the file, see ["Printing Attachment Files"](#) on page 10-14.

To read the file without revising it (or, to revise the file as you want without other people being able to access your revised version through Agile), or to review the contents of a file folder without revising it, then you will just perform a "Get" procedure, as described below.

You must have the appropriate privileges to check out and check in a file folder and to cancel a checkout, whether you are performing the operation at the file folder itself or from the Attachments tab of a business object. If you have questions about your privileges, contact your Agile administrator. If you are going to work with file folders often, it may be appropriate that you be assigned the File Folder Administrator or File Folder Manager role.

Getting Attachment Files or File Folders

You can copy files on the **Files** tab of a File Folder object or a Design object to the directory of your choice. This is called *getting* a file. You can get as many copies as you like. To revise an attached file and make the version public, you must check the File Folder object out, make changes, and check it back in. This is covered in ["Checkout and Checkin to Revise Attachment Files or File Folders"](#) on page 11-19.

Several users can get the same attachment files simultaneously. You can get files that are checked out. Also, you can get a file even though the application used to create that file is not installed on your computer.

You must have the appropriate privileges to get a copy of the file. If you have questions about your privileges, contact your Agile administrator.

Note: When you get an attached file, the date stamp on your copy of the file reflects the date that you got the file, not the date that the file was attached or saved.

Web Client, Getting Files

In Web Client, the process to get files from the file folder **Files** tab is the same process used to get files from a business object **Attachment** tab.

The process is described in:

- ⌚ ["Getting Files in Web Client"](#) on page 10-9
 - ["Web Client, Get Files using Microsoft IE"](#) on page 10-10
 - ["Web Client, Get Files using Firefox"](#) on page 10-10

- ["Web Client, Get files using Chrome:"](#) on page 10-11
- ["Web Client, Get Files using Safari for Windows"](#) on page 10-11

Java Client, Get Files

To get copies of attachment files from a file folder object in Java Client:

1. Display the **Files** tab of the file folder.
2. Select the rows of the files that you want to get.
3. Click the **Get Files** button.

In the Select Directory dialog, specify the directory where you want to store the copies.

If you selected more than one file, and you want to get the files together in one ZIP file, click **Download the files in one ZIP file**. Specify a **ZIP file name**.

4. Click **OK**. The files (or ZIP file) are copied to the specified directory.

You will be prompted whether you want to open the file or files.

Java Client, Batch Get

To batch get copies of all the files from a file folder in Java Client:

1. Display the **Files** tab of the file folder.
2. Click the button drop-down menu for **Get Files** and select **Batch Get All Files from this Object**.
3. In the Select Directory dialog, specify the directory where you want to store the copies.

To get the files together in one ZIP file, click **Download the files in one ZIP file**. Specify a **ZIP file name**.

4. Click **OK**. The files (or ZIP file) are copied to the specified directory.

You will be prompted whether you want to open the file or files.

Checkout and Checkin to Revise Attachment Files or File Folders

There are several factors that determine how you check out an attachment file for modification and check it back in, and how you check out a file folder for revision and check it back in. To revise an attachment file means, of course, to alter the contents of the file itself. To revise a file folder means making structural changes to the file folder's contents, such as adding a file, deleting a file, replacing one file with another, or editing the File Description.

Note: When you download a file for revision, you simply get a copy of the file, make your revisions, and replace the original file when you are checking it back in.

A file folder can contain one file or multiple files. All the files are stored in the file vault, part of Agile File Manager, each file identified with its file folder. To modify a file in the file vault, you must first check out its file folder.

When you check out a file folder, Agile PLM makes the attachment files available for modification by the Checkout User only—unlocks them—and renders the file folder inaccessible for modification by others. You can download and edit the file(s), which no one else can do until you either check in the folder or cancel the checkout.

Important: To many people in manufacturing industries, to "check out a file" means a one-step operation in which the checked-out file is automatically downloaded to the user's computer and, in Agile PLM, when you check out a file from an Agile business object Attachments tab, the checked-out file is automatically download to the user's computer. However, in Agile PLM File Folders, think of **CheckOut** as synonymous with *unlocking* a file, making it available to only the file folder Checkout User for modification. After modifying and replacing the referenced file(s), **CheckIn** is synonymous with *locking* the file in the file vault.

Once you have modified an attachment file and checked a containing folder back in, every user who views objects that reference that file, from the same or another file folder object, will see the modified version of the file, provided the user accesses the Latest Version of the folder object.

The ability for users to check out File Folders can be controlled by privileges associated to criteria based on attributes of the File Folder. For example, the "Approval Status" attribute can be used for controlling check out, when Routing Slip approvals on File Folders are used. See *Agile PLM Administrator's Guide* for more details on defining criteria and privilege masks.

By default, only you or a user with "file folder administration" privileges can check in a file folder that you checked out, or cancel a checkout.

The following procedure works from a file folder's **Files** tab. For information about checking out from a business object Attachments tab, see ["Web Client, Checking Out Attachment Files"](#) on page 10-27 and ["Java Client, Checking Out Attachment Files"](#) on page 10-27.

To check out a file folder and get attachment files for modification:

1. Open a file folder.
2. Click the **Check Out** button.

In Java Client and Web Client, "[Checked out]" appears at the upper-right portion of the object page.

The **Version** number of the folder is advanced, from the latest previous version to the next number. If the checkout is canceled, the version number will revert.

On the **Title Block** tab of the file folder, the checkout information is filled in, for example, Checkout User and Checkout Date.

3. Click the **Files** tab. The files in the file folder are listed (URLs are listed too).
4. To change the file folder itself, click the **Add > Files** or **Add > URLs** button.
To change the contents of attachment file(s), having checked the folder out, now select the files you want and click the **Get** button.
5. Revise and save the files.
6. Return to the checked-out file folder from which you got the attachment file you have modified.
7. Replace the file on the Files tab with the file you modified, using the appropriate instructions below for either Java Client or Web Client.

When you have completed all your modifications (Replace, Add, Delete, and Edit) click the **Check In** button. The file folder is checked in, and the version increments.

Web Client, replace files:

1. In the file row you want to replace, click the **Replace** button.

2. The Browse to Replace File dialog appears.
3. Click the **Browse** button to navigate to the directory you want and select the file.
4. When you are done, click **Replace**.

Java Client, replace files:

1. Select the row to enable the **Replace File** button.
2. Click the **Replace File** button.
3. The Select File dialog appears.
4. Select the modified file or navigate to the directory you want and select the file.
5. Click **Open** to complete the replacement process.

Note: From the **Files** tab of the file folder, you can choose to replace a file at any time the file folder is checked out.

The modified file writes over the previous version of the file.

Checking in a file folder increases the version number of the attachment.

When you check out a file folder and get an attachment file, a copy of the attachment file is stored in a specified directory. When you check the file folder in, the files remain in the directory until you delete them manually.

If you placed the file on the network or in a shared drive or directory (during the Get operation), you can check in the file from any computer that provides access to that drive or directory. If you place the file into a directory that is not a shared directory, it must be checked in from that same computer. See your Microsoft documentation for more information about shared directories.

Canceling Checkouts

When you want to discard edits to files on a file folder that you checked out, you can cancel the checkout.

A checkout can be canceled only by the user who checked out the attachment, or by a user with necessary "file folder administration" privileges. If you have questions about your privileges, contact your Agile administrator.

When you cancel a checkout, copies of the attachment files remain in the checkout directory you selected, but the original files are once more available to be checked out from the **Files** tab. Any edits you make to the remaining copies of the files do *not* appear in the public versions of the file (the versions of the file stored in the file vault).

To cancel a file folder object checkout:

1. Display the file folder object.
2. Click the **Cancel Checkout** button.

Ad Hoc Redlining or Marking Up of Attachment Files from the File Folder

The other method to mark up or redline an attachment file is called "ad hoc redlining" in which the attachment is approached through the **Files** tab of the file folder.

To ad hoc redline or mark up an attachment file from a File Folder object in the Web Client:

1. On the **Files** tab of a file folder object, click the **Redline** button (or **Has Been Redlined** button) on the row of the file you want to redline. (This button is available only when the file folder is checked in.)
2. Use the tools described in the viewer online Help to redline the attachment. To view online Help, choose **Help > Content** in the menu bar.

Note: Ad hoc markups are saved against and associated with the version of the file folder object.

To ad hoc redline or mark up an attachment file from a file folder object in the Java Client:

1. On the **Files** tab of the file folder object, select a file you want to redline.
2. Click the **Do Redlining** button.
3. When the Viewer opens in redline mode, click the **Markup** button. (This button is available only when markups are allowed.)
4. Use the tools described in the viewer online Help to redline the attachment. To view online Help, choose **Help > Content** in the menu bar.

Note: Ad hoc markups are saved against and associated with the version of the file folder object in the Agile system.

For more information about the Viewer, see *Viewer Supplement*.

Other File Folder Operations

You can perform a mass update of a file folder in both Web Client and Java Client.

Performing a Mass Update of a File Folder

You can remove or replace a file-folder attached to multiple objects simultaneously. For example, if File Folder 2 is created, and File Folder 1 becomes obsolete, you can replace the attachment of File Folder 1 with File Folder 2 on all of the objects that include a reference to File Folder 1.

- ⌘ Remove a file folder reference from all objects or from some objects that reference the file folder.
- ⌘ Replace a file folder reference in all objects or in some objects that reference the file folder.
- ⌘ Add a file folder to the **Attachments** tab of multiple specified objects.

To perform a bulk file folder operation in Web Client:

1. Open the file folder that you want to remove, replace, or add.
2. Choose **Actions > Mass Update**.
3. Specify whether you want to add file, remove file, replace file, or replace version, and click **Continue**.
4. Select the version of the file folder on which you want to perform the bulk operation.

5. Using the wizard search tools, find and select the objects you want to be affected by this bulk operation.
6. Select the attachment files you want to include in the operation, and click **Save**.

To perform a bulk file folder operation in Java Client:

1. Open the file folder that you want to remove, replace, or add.
2. Right-click and choose **Mass Update**.
3. Select the version of the file folder on which you want to perform the bulk operation.
4. Select the attachment files you want to include in the operation, and click **Next**.
5. Specify whether you want to add, remove, replace the file folder or replace the version of the file folder, and click **Next**.
6. Depending on which function you selected in step 5 above, use the wizard search tools to find and select the objects you want to be affected by this bulk operation or, select the objects you want to be affected from the displayed list.
7. Click **Finish**.

Working with Design Objects

A Design object is an container object intended for use with CAD models.

What are Design Objects?

Design objects are an additional type of File Folder object. The File Folder base class includes two classes of objects:

- ? File folders
- ? Designs

A Design object is another type of file container object intended for use with CAD models. Design objects have all the capabilities of file folder objects described in [Chapter 11, "Working with File Folders."](#)

Design objects have additional features that allow you to create a parent-child structure of related design objects, and to record and modify the version of each design object in the model structure.

Typically, Design objects are used with an Agile PLM Engineering Collaboration (EC) CAD integration. The integration application manages most of the tasks related to the creation, modification, and maintenance of CAD data model structures associated with Agile Design objects. Although you can create and modify Design object, just like any other Agile object, an Agile PLM EC CAD integration will perform many of these tasks automatically.

Note: Design objects are available in your Agile PLM system only if your Agile administrator has enabled them for use. Design objects are not available through the Java Client.

Contact your Agile administrator if you have questions about how Design objects are used at your company. For additional information about Design objects, see *Agile PLM Administrator Guide*.

Design object Actions Menu

For information about the Web Client Actions menu, see ["Actions Menu"](#) on page 5-1.

For information about Design object actions, see:

- ? ["View All Versions"](#) on page 12-2
- ? ["Save As, Design Objects"](#) on page 12-3

View All Versions

When a Design object is open, you can view information about all versions/revisions of the Design by using the **Actions** menu **View All Versions** command.

A version or revision can be selected from the version drop-down list on File Folder objects. Revisions (if set) are indicated to the right of the version.

To switch between versions of a Design object in Web Client:

From the **Version** drop-down list at the top of the Design object, select the version/revision you want to view.

Note: A version number in brackets, for example [4], indicates a version that has not yet been checked in. In this example, when version 3 was checked out, a pending version [4] was created. Selecting [4] in the version drop-down list lets you view and work with the pending version.

To open the Versions palette:

1. In the **Actions** menu, choose **View All Versions**. The Versions palette opens.

Note: The **View All Versions** action is available only in Web Client. Java Client does not support Design objects.

The Version palette displays the following information about each version:

Table 12–1 Design object Version palette information

Versions Column	Description
Column 1	Displays the approval status of the file folder version. Note: The approval status is displayed only if there are approvers on the Routing Slip.
Version	The version number.
Checkin Date Checkin User	The date the version was checked in and the user who performed the checkin. When the version is checked out, these fields are blank.
Change Info	Indicates how the version was modified before it was checked in. Files indicate that the object's files were modified; for example, files were replaced, added, or deleted. For Design objects, Structure indicates that the Design's Structure tab was modified.
Change Sequence, Change Order, Change Publish Date, Lifecycle Phase	These fields are associated with Design File Change Orders (DFCOs). Change Sequence: See " Change Sequence " on page 13-5. Change Order: The number of the DFCO. Change Publish Date: The date the DFCO was published (released). Lifecycle Phase: The Design folder Lifecycle Phase specified by the DFCO.
Label, Revision, Revision Date	These are version-specific editable fields used primarily with Design data model objects.

Actions you can initiate in the Versions palette:

- ? **View:** Click the **View** drop-down menu to choose one of the options.
 - **View:** Select any version row and click **View** to view the file or files in AutoVue for Agile.
 - **Compare:** For single-file versions, select two version rows, and choose **Compare** in the **View** button drop-down list. AutoVue for Agile compares the selected files.

The Design object Version palette includes the following additional actions:

- ? **Comparison Report:** (Design objects only) Click the Comparison Report drop-down menu to choose one of the options.
 - **Compare:** Select any two version rows and click **Compare** to compare the Designs in the Comparison Report drop-down menu. A Design Comparison Chart displays a comparison report.
 - **Comparison by Search:** Select a version row and click **Compare by Search** in the Comparison report drop-down list. A Compare by Search palette opens. In the drop-down list select either Latest Version or All Versions. Enter a search string (enter * to search for any design object) and execute a quick search. Choose from a list of Designs to compare with the original Design object. The Design Comparison Chart displays a comparison report.

- **Design Comparison Chart**

The Design Comparison Chart displays reports of the compared Design objects.

The plus sign expands the Design object to display a list of child objects attached to it. You can collapse the object using the minus sign. Click the gray dot icon to see more details about Attributes and Files. Colors indicate the state of the Design object. For example, Blue - Added, Orange - Modified, Red - Deleted.

- ? **Purge Version:** Design objects store large CAD files, which are updated regularly. The **Purge Version** action lets you remove unwanted Design versions and help optimize file storage. To begin the process, the Design object must be in the checked in state. Purging starts at the original version and continues down the **Structure** tab, and goes through all the versions, including the child objects. The process stops if you cannot purge a child object.

Save As, Design Objects

When you use **Save As** in the Design object **Actions** menu to create a new Design object, Save As additionally copies the **Structure** tab of the latest checked-in version of the Design object.

Purge Version, Design Objects

Design objects store large CAD files, which are updated regularly. The **Purge Version** action lets you remove unwanted Design versions and help optimize file storage. To begin the process, the Design object must be in the checked in state. Purging starts at the original version and continues down the Structure tab, and goes through all the versions, including the child objects. The process stops if you cannot purge a child object.

A Design object version cannot be purged if the version is checked out, redlined or in use.

- ? If the selected Design version is in use on an Agile object **Attachments** tab, **Relationships** tab, or **Content** tab, or on the **Affected Files** tab of a DFCO, then Agile PLM displays a warning message and the Design version is not purged.

See also [Chapter 13, "Working with Design File Change Orders \(DFCOs\)."](#)

- ? If the selected Design version contains redlined files, then Agile PLM displays a warning message and the Design version is not purged.
- ? If the selected Design version is checked out, then Agile PLM displays a warning message and the Design version is not purged.

For details on how to use the **Purge Version** action, see ["Purging Unused File Folder Versions"](#) on page 11-16.

Load to CAD, Design Objects

The **Load to CAD** option on the **Actions** menu of the Design objects lets you load Design objects into a CAD system, when used along with Agile EC CAD connectors. The data in XML format includes the object base class, number, and specific version or revision, which will help in accessing more details using SDK or EC connection to Agile PLM. You can access data from both the Design object page and the Search results page. You can select and load single or multiple Design objects from the Search Results page. The Design object page loads the current version of the selected Design object.

To enable the Load to CAD feature in Java Client go to **Admin > Server Settings > Preferences > Load to CAD**.

The following objects also support Load to CAD:

- ? File Folders
- ? Item
- ? Changes
- ? Customers
- ? Manufacturer Parts
- ? Manufacturers
- ? Programs
- ? User Groups
- ? Users
- ? Suppliers

Mass Update, Design Object

The **Mass Update** option on the **Actions** menu lets you update the files on a bulk scale. You can **Attach Files**, **Replace Attached Files**, **Replace Attached Versions**, and **Remove as Attachment** from the **Actions** menu.

To perform a Mass Update action on a Design object in Web Client:

1. Open the Design object that you want to remove, replace, or add.
2. Choose **Actions > Mass Update**.
3. Specify whether you want to add file, remove file, replace file, or replace version, and click **Next**.
4. Select the version of the Design object on which you want to perform the bulk operation.
5. Select the attachment files you want to include in the operation, and click **Next**.
6. Using the wizard search tools, find, and select the objects you want to be affected by this bulk operation. The wizard takes you through 3 frames: Select Files to Replace, Select Objects to Replace File and Select Replacement Files.

7. Click Finish.

Design Title Block Tab

By default, the Design object **Title Block** tab contains the fields listed in the following table. Agile administrators determine which fields are enabled and visible on the **Title Block** tab.

In Web Client, the **Title Block** can contain two additional sections, called **Page Two** and **Page Three** by default. (Design objects are not supported in Java Client). Agile administrators can add custom class fields to Page Two section and custom subclass fields to the Page Three section. The Agile administrator determines enabling, and naming these sections.

The following table describes each Title Block tab field and how it is completed.

Table 12–2 *Design object Title Block tab fields*

Field	Description
Number	The Design object's number, completed when the file object is created.
Type	The subclass of this Design object. Depending on Agile system settings, this field is automatically completed when the Design object is created.
Lifecycle Phase	Current lifecycle; selected from a list. For example, Concept or Maintenance .
Description	Text describing the Design object
Version	Indicates the version and the revision of the Design object.
Last Modified Date	Date the Design object was last modified. Completed automatically.
Checkout Status	Indicates whether the Design object is currently checked out or checked in. Completed automatically.
Checkout User	When the Design object is checked out, displays the user who checked out the object. Completed automatically.
Checkout Date	When the Design object is checked out, displays the checkout date. Completed automatically.
Checkout Location	In Java Client, the checkout location is automatically filled in.
Checkin Date	When the Design object is checked in, displays the checkin date. Completed automatically.
Create Date	The date the Design object was created.
Label	Version-specific text field which indicates a label identifier for the version. Users with the appropriate privileges can modify this field on any checked in or checked out version.
Component Type	List field which indicates the type of component represented by the Design object.
Revision	Version-specific text field which indicates the Revision for the Design version.
Revision Date	Version-specific date field which indicates a revision date for the Design version.
Checkin User	Indicates the user who checked in the currently selected version; completed automatically.
Approval Status	The "Approval Status" attribute gives the overall status from the Routing Slip, per version.

Table 12–2 (Cont.) Design object Title Block tab fields

Field	Description
Item Change Status	The "Item Change Status" attribute is a non-editable version-specific text attribute that can be used instead of, or in combination with, the "Approval Status" attribute to control privileges on the Design.

Using the Design Object Navigator


Note: To view Design Object in Agile PLM Web Client, the Design Object feature must be enabled in your Agile PLM system and your user profile **Design Object** preference must be set to **On**. If you have questions about your ability to view Design Objects, contact the Agile administrator.

To open the Design Object Navigator:

1. Click the **Navigator** button in the header area of the Design Object.

A Navigator pane appear to the left of the main pane, displaying the structure and the Relationships of the Design Object.

Figure 12–1 Design object Navigator pane



Design Object Files Tab

The following table lists fields on the **Files** tab of Design objects.

Table 12–3 Design object Files tab fields




Field	Description
	Replaces a file. Click Replace button to remove the file and add the latest version of the file or another file. Check-out the file to be replaced. Note: The checked-in files must have the same file extension as the checked-out file.

Table 12–3 (Cont.) Design object Files tab fields

Field	Description
	This icon appears in the field if the file Has been redlined . The Do Redlining icon will appear here from the file folder level for any file type that is listed in the Supported File Types and Valid Model File Type settings in Agile Administrator. Both of these cases allow ad-hoc viewing and redlining.
File Name	The name of the file. In Web Client, click the file name to view the file in the Viewer.
File Description	Description of the File object.
File Path	Can be manually set.
File Type	The format of the file.
File Size	The size of the file, in bytes
Last Viewed Date	Date when the file was last viewed. (The History tab records detailed information about file viewing.)
Checkout Location	In Java Client, records where checked out files were placed during the check out procedure.
File Category	Category selected from a list.
Document Text	If needed, this field will be filled in automatically by the Agile system.
 Master Thumbnail	Only visible if Thumbnails are enabled.

You can perform the following actions using buttons on the Files tab in the Designs object.

Table 12–4 Design object Files tab buttons

Buttons	Description
Add	Lets you add Files or URLs to the Design object.
Remove	Lets you remove the Files or URLs, provided they are not reflected on any other object.
Get	Lets you extract files and save it in a folder or location of your choice. In addition, if the file has a structure, the "Get" function lets you extract all files from the structured file (for example, a CAD assembly). A zip file will be created that contains all CAD files in a Design Structure. The name of the zip file is the original file name (plus zip), which helps to identify the "top level" assembly file inside the zip file. Note: All files with the same value of "File Category" as the initial file will be extracted!
Open	Opens a copy of the selected file in the native application of the file. Note: This is for single files only, not for CAD design structures!

Table 12–4 (Cont.) Design object Files tab buttons

Buttons	Description
View	Lets you select from a list of views. View: Lets you view the selected files in the Viewer. Compare: Lets you compare versions of two Design objects Compare by Search: Lets you compare the original Design object with other Design objects you obtain by Search. Overlay: Lets you lay other files over the current active file. (For more information, see <i>Viewer Supplement</i> .)
Print	Prints selected Design objects.
Get Shortcut	Opens the URL directly in a browser.
More	Displays more actions you can perform.

Adding Files to the Design Object Files Tab

The Files tab of the Design class object has the same functions as the Files tab of the File Folder class object.

For information about working on the Files tab, see ["Adding Attachment Files and URLs to File Folders"](#) on page 11-13.

Design objects are available in Web Client only. Any instructions related to Java Client do not apply to Design objects.

Structure Tab of Design Objects

Each row in the structure table includes information about the child Design object in each structure table row.

- ? Structure rows can reference checked in or checked out versions of child objects.
- ? You can check in a parent while using a checked out version of a child.
- ? You cannot Cancel Checkout a version that is in use; an error message is displayed.

The following table describes the fields included in the Structure table.

Table 12–5 Design object Structure tab fields











Structure Table Field	Description
	Icon indicates that the Design data model has a file attached to its Files tab.
	Icon indicates that the Design data model is linked to an Agile business object; that is, whether the Design object appears on the Attachments tab of an Agile object, for example, the Attachments tab of an item object.
	Icon indicates that the Design object is currently checked out.
Design Type	The type of the Design object

Table 12–5 (Cont.) Design object Structure tab fields

Structure Table Field	Description
Number  	<p>The number of the Design object.</p> <p> – Indicates a Design object with no children, that is, a leaf node.</p> <p> – Indicates a Design object with structure, that is, a Design object with children design objects listed on its Structure tab.</p> <p>Click the number to open the Design object.</p>
Description	The description of the Design object.
Lifecycle Phase	List field which indicates the current phase of the Design object.
Version 	<p>The version of the Design object included in the structure. The version included in the structure can be any version of the Design data model.</p> <p> – A Not Latest icon indicates that the specified Design object version is not the latest version.</p>
Label	Version-specific text field which indicates a label identifier for the version.
Component Type	List field which indicates the type of component represented by the Design object.
Last Modified Date	Date the Design object was last modified.
Checkout Status	Indicates whether the Design object is currently checked out or checked in.
Checkout User	When the specified version of the Design object is checked out, displays the user who checked out the object.
Checkout Date	When the specified version of the Design object is checked out, displays the checkout date.
Checkin Date	Date the specified version was checked in.
Create Date	Date the Design object was created.
Checkout Location	In Java Client, when the Design object is checked out and, the checkout location is automatically completed.
 Master Thumbnail	Only visible if Thumbnails are enabled.

Structure Tab Buttons

The following table explains the Structure tab buttons and the actions you can perform on the Structure tab.

You must select a checked out Design object version to Add or Remove rows, or to Edit rows. Checkout all checked in versions of the object before adding, removing, or editing Structure table rows.

Table 12–6 Design object Structure tab buttons

Button	Description
Edit	<p>Note: You must select a checked-out version to edit Structure table rows.</p> <p>The edit button on the right hand side of the page lets you edit Structure row details by displaying the selected rows on an Edit page. The editable fields are in the form of text boxes, list boxes, and so on.</p>
Remove	<p>Note: You must select a checked-out version to remove Structure table rows.</p> <p>Removes the selected rows from the Structure table.</p>
Add	<p>Note: You must select a checked-out version to add Structure table rows.</p> <p>Add – Adds a Design object to the Structure table. Depending on which option you choose, you can:</p> <p>Search for an existing Design object using the Search palette.</p> <p>Create a Design object using the Create to add palette.</p>
Multi-level... Expand Collapse	<p>Multi-level > Expand expands all the sub-structures in the Structure table. All levels of the Structure are displayed.</p> <p>Multi-level > Collapse collapses all expanded structure levels. Displays only the top level of the structure.</p>
Go To	<p>Takes you to a specific Design object based on the criteria you enter in the Go To dialog box.</p> <p>The Go To search can be limited to a particular Design data model column and to the specified number of levels. For example, specifying level 3 searches through levels 1, 2, and 3.</p>
More...	<p>Lists more actions that you can perform from the Structure tab.</p> <p>Copy – lets you copy an object from the Structure table and paste it in another Design object.</p> <p>Paste – lets you paste an object from another Design object.</p>

Using Structure Go To

The Structure Go To feature lets you search for a specific Design object in the parent/child design structure.

To use the Go To Design in Structure feature in Web Client:

- On the **Structure** tab, click the **Go To** button.
- In the Go To Design in Structure dialog box, define your search:
 - Enter the text you want to find. The Go To search finds any Design object that includes (contains) the specified text in its attribute fields. You can use any type of character, including numerals and punctuation.
 - In the drop-down list, choose which Structure table column you want to search. You can choose all columns or one specific column.
 - Check **Match Case** to perform a case-sensitive search where text capitalization matters.
 - Choose how many Structure levels you want to search: Enter a number or check **All levels**.
- To start the search, click **Find Next**. The Structure table highlights the first Design object that matches the search criteria.

4. Use the **Find Next** and **Find Previous** buttons to scroll up and down the Structure table, highlighting Design objects that match the search criteria.
5. When you have found the Design object you want, click **Close** in the Go To Design in Structure dialog box. The last Design object you highlighted in the Structure table remains highlighted.

Routing and Reviewing Design Objects

The Default File Folders Workflow applies to all file folder objects that users create in the File Folders base class, which includes both the *File folders class* and the *Designs class*. This workflow has a read-only privilege along with a single Review status—a simple review-and-signoff—although the signoff can still be an approval or a rejection.

Each Design object version has its own Routing Slip. Each version can have a different set of approvers and observers.

To add Approvers or Observers:

1. Open the Design object.
2. Select the **Routing Slip** tab.
3. In the **Version** drop-down list, select a version.

Note: Ensure to check in the selected version. You cannot add Approvers to a version, which is not yet checked in.

Click the **CheckIn** button. The Add Reviewers /Remove Reviewers button is active once you check in the Design object.

4. Click the Add Reviewers button. The Add Approvers and Observers dialog box opens.
5. Select the approvers and observers you want to add. Enter a comment, if desired.
6. If urgent, select the **Send notification as urgent** option.
7. Click **OK**.

Similarly, use the Remove Reviewers button to remove reviewers from a Design object.

Approving or Rejecting a Design object:

Approving or rejecting a Design object uses the same process as approving or rejecting any routable object. For detailed information, see:

- 7 ["Approving Routable Objects"](#) on page 9-27
- 7 ["Rejecting Routable Objects"](#) on page 9-30

Note: Approvals and rejections are version-specific. Your approval or rejection applies only to the selected version of the Design object.

Relationships Tab, Design Object

The Relationships tab of the Design object has the same functions as other routable objects in Agile PLM. Relationships between two Design objects are now version-specific. Storage of certain data causes circular reference and hence version-specific relationships between objects are required to support storage of data. Other relationships involved with Design objects will not be version-specific.

The table below lists the default fields on the Relationships tab.

Table 12–7 Design object, Relationships tab fields

Field	Description
Name	Name of the added object. For example, C10970
Description	The description of the object you add with the number.
Current Status	The current status of the object. For example, Pending
Rule	The Rule associated with the object.
Type	The type of the object you add.
Version	By default the latest version of the related Design object is displayed. If the check box "Display all versions" is selected, then all versions are displayed. In this case, the Not Latest icon indicates that the specified Design object version is not the latest version.

For more information on Relationships, see ["Relationships and Dependencies Between Objects"](#) on page 5-31.

Where Used Tab, Design Object


















A Display all version check box enables you to toggle on or off the display of all versions. When the check box is deselected (default), only the latest version is displayed.

Figure 12–2 Design object Where Used tab

Design

☒ Display all versions

More ▾

Design Ty	Number	Description	Life Cycle Phase	Version			
Design	DESIGN00008.SLDASM	uLearn Assembly		2 			
Design	DESIGN00008.SLDASM	uLearn Assembly		3 			
Design	DESIGN00008.SLDASM	uLearn Assembly		4			
Design	DESIGN00011.SLDASM	uLearn Assembly - Next Gen		1 			
Design	DESIGN00011.SLDASM	uLearn Assembly - Next Gen		2			

When you select a different version in the Version drop-down list, then the Where Used tables display information about the selected version only.

? Attachments

The Attachments table lists all the Agile business objects where the currently selected version of the Design object is attached, that is, all the Agile business objects that have the current version of the Design object listed on their **Attachments** tab.

? Design

The Design table lists all the Design objects that are structure parent objects for the currently selected Design object version. That is, the selected version of the Design object appears on the **Structure** tab of the listed Design objects as a child object.

Note: The Design table lists only direct (on-level) parents of the current version of the Design object.

Where Used Query

The Where-Used query locates version-specific relationships of the Design objects. You can search, any or all checked in versions of a Design object used in another Design object in Advanced Search.

Search results for Advanced Search criteria like Where-Used in Structure One Level All Checked In versions or Where-Used in Structure One Level Latest Version Only now returns all the checked in versions or the latest checked in version of the Design object.

Working with Design File Change Orders (DFCOs)

The Design File Change Order (DFCO) is a Change Order subclass with the **Affected Files** tab enabled by the Agile administrator. DFCOs use the Agile PLM workflow process to publish Design and File Folder objects, similar to the way ECOs are used to release item objects. Agile workflows provide a sign-off approval process. DFCOs are supported in Web Client only.

What are Design File Change Orders?

Design File Change Orders (DFCOs) are available in Agile PLM only if your Agile administrator has enabled and configured DFCOs and the roles and privileges you need to use DFCOs.

Features of DFCOs include:

- Use the Agile workflow process to submit, update, approve, and publish designs files that you add to the DFCO **Affected Files** tab.

When you use the Affected Files table to publish design file folders, you do not use item object attachments to define the design file folder you wish to release.

- Consolidate AdHoc, ECO, and ECR redline markups associated with the Design file folder on the DFCO Redline/Markup Files table on the **Affected Files** tab.
- Add local files as markup files to the Redline/Markup Files table on the Affected Files tab.
- Typically, DFCOs and the Design file publishing process is used in conjunction with Agile Engineering Collaboration (Agile EC), which is an MCAD Connector for Agile PLM that is operated from within your CAD system environment.

For more information, refer to Agile EC documentation at

<http://www.oracle.com/technetwork/documentation/agile-085940.html#ec>

?

The Design File Change Order (DFCO) Object

The Design File Change Order (DFCO) is a Change subclass, similar to an ECO. The ECO object has the **Affected Items** tab enabled. In comparison, the DFCO object has the **Affected Files** tab enabled.


Note: A Change Order subclass can be configured with either the **Affected Items** tab enabled (ECO), or with the **Affected Files** tab enabled (DFCO), but both tabs cannot be enabled for the same change order subclass.

For detailed information about Change Order objects, see *Product Collaboration User Guide*, "Changes" chapter.

The DFCO File Publishing Process

DFCOs allow you to use the Agile workflow process to submit, update, approve, and publish design files.

Figure 13–1 Example design development and DFCO publication process



1. Dan Designer creates a new design in the CAD system and saves it to Agile PLM through EC.
2. Dan continues to work on the design in CAD. They perform several updates in through EC. Each time they update the design and saves it, the Design folder version number in Agile PLM increments by 1.
Temporary Change Sequence numbers are assigned to each Design file folder on the Affected Files table. See also "[Change Sequence](#)" on page 13-5.
3. Through EC, Dan creates a DFCO in Agile PLM for the design. The design is added to the Affected Files table of the DFCO.
4. When Dan Designer determines that his design is ready for approval, then Dan submits the DFCO to Mike Manager for review.
5. Mike Manger reviews the DFCO and Dan's design. Mike can add markups to the **Redline/Markup Files** tab by several methods:
 - ⌘ View the affected file in the AutoVue viewer and then add redline markups in AutoVue, which are added to the markup table.
 - ⌘ On the **Redline/Markup Files** tab, use **Add** button to browse for local files to add to the markup table.
 - ⌘ On the **Redline/Markup Files** tab, use the **Associate Redlines** button to find redlines and add them to the markup table. Redlines to associate are file folder Ad Hoc redlines, ECO redlines, or ECR redlines.

6. Mike Manager returns the DFCO to Dan Designer.
7. Dan reviews the markups. Dan checks out the design in EC, and makes the changes in the design as specified in the markups. Dan checks in the design.
8. Dan submits the DFCO to Mike Manager. Mike compares the design and the redlines. When they are satisfied, Mike Manager moves the DFCO to the CCB workflow status, where the reviewers approve the DFCO.
9. The DFCO is released and Dan's design is published. The Title Block of the Design object is updated with the data from the DFCO:
 - ? **Lifecycle Phase**
The New Lifecycle Phase as defined on the **Affected Files** tab of the publishing DFCO.
 - ? **Version**
The file folder version published by the DFCO.
 - ? **Change Sequence**
The temporary Change Sequence numbers are locked and assigned to the file folder version number and to the publishing DFCO.
 - ? **Change Publish Date**
The date the DFCO is published.
 - ? **Published Change Order**
Then number of the DFCO that published the design.

Creating DFCOs

In Agile PLM, you create DFCOs in the same ways that any change object is created:

- ? Use the top pane **Create New** menu to choose the Changes base class and then choose the Change Orders class from the expanded lists. In the Create New dialog, choose DFCO in the Type drop-down list.
- ? If you have a published DFCO object open, you can use the **Actions > Save As** command.

Note: Designs can be included on the Affected Files table of only one pending DFCO at a time.

- ? With a file folder object open, use the **Actions** menu and choose **Create Change Order**.

Routing DFCOs for Approval

DFCOs are a Change Order subclass. The workflow process for approval and publication is the same process as used for any Change Order. For more information, see:

- ? [Chapter 9, "Routing Objects with Workflows"](#)
- ? *Agile PLM Administrator Guide*, chapter "Administering Approval Matrix"

Deleting DFCOs

See [Appendix A, "Deleting Agile Objects."](#)

Working with the Affected Files Tab

The **Affected Files** tab of a DFCO is similar to the **Affected Items** tab of an ECO.

On the Affected Files tab, you can add and remove files, add redline markups, edit the Affected File attributes, and add or modify Version Specific Properties.

See ["Affected Files Tab Buttons and Actions"](#) on page 13-6.

The Affected Files Tab

The DFCO **Affected Files** tab lists the file folders to be published, and identifies the specific files.

Affected Files Tab Attributes

The following table describes the columns on the Affected Files table.

If you have the appropriate privileges, then you can edit the editable cells in the table. Click **Save** to save your edits. See ["Editing Table Cells in Web Client"](#) on page 5-8.

Table 13–1 Columns of the Affected Files table




Attribute column	Description
Is Checked Out (icon) 	When icon is displayed, indicates that the file folder in this row is checked out.
Incorporated (icon) 	When icon is displayed, indicates that the file folder is incorporated. Files cannot be checked out or edited when the file folder is incorporated.
Has Been Redlined (icon) 	When icon is displayed, indicates that the file in this row has been redlined.
Type (icon)	The icon of the Design or File Folder object subclass.
Type	The Design or File Folder object subclass name.
Folder Number	The number of the Design or File Folder.
Folder Description	The folder description that appears on the Title Block tab of the folder. If you have the appropriate privileges, you can edit this attribute on the Affected Files table.
Filename	The name of the file. Each row lists one file. If there are multiple files in one affected file folder, then each file appears on a separate Affected Files table row.
File Description	The description of the file that appears on the Files table of the file folder object. If you have the appropriate privileges, you can edit this attribute on the Affected Files table.
Folder Version	The current version of the affected file folder. If the folder is checked out, then the pending version is displayed in brackets, for example [3].
Folder Owner	The person who is responsible for editing the affected file to incorporate the associated redline comments and corrections. If you have the appropriate privileges, you can edit this attribute on the Affected Files table.
New Change Sequence	When a design file folder is added to the Affected Files table, a new Change Sequence number is assigned. Each Change Sequence number is associated with a specific design file folder version number.

Table 13–1 (Cont.) Columns of the Affected Files table

Attribute column	Description
Old Folder Lifecycle Phase	The current Lifecycle Phase of the affected file folder.
Folder Lifecycle Phase	The proposed Lifecycle Phase of the affected file folder when the DFCO is published. If you have the appropriate privileges, you can edit this attribute on the Affected Files table.
Checkout User	The name of the person who checked out the folder. If the folder is not checked out, then this attribute is empty.
Last Modified	The date and time the affected file folder was last modified and checked in.
Checkout Date	The date and time the affected file folder was checked out.
Checkin Date	The date the of the most recent file folder checkin.
Create Date	The date the affected file folder was created.
Label	A version-specific text field.
Component Type	The Component Type that appears on the Title Page tab of the affected file folder object.
Change Date	The Date the DFCO was published.
Checkin User	The name of the person who performed the most recent checkin.
File Type	The file type of the affected file.

Change Sequence

Change Sequence numbers define the order in which each DFCO is published for each Design or File Folder.

Each Change Sequence number is associated with one specific file folder version number. Before the DFCO is published, the affected files can be checked out and checked in multiple times, as many times as necessary. Each checkin increments the file folder version number. When a DFCO is published, the current file folder version is then associated with the DFCO and Change Sequence number.

The following table shows an example of how Change Sequence numbers, DFCOs, and file folder version numbers are associated with one another.

Table 13–2 Change Sequence Number example

DFCO number	Design file folder version number	Change Sequence number	Notes
DFCO-00254	4	001	Version 4 of the Design is checked in when the Design is published for the first time. Version 4 is associated with Change Sequence Number 001.
DFCO-00481	12	002	The Design is checked out and checked in as many times as needed. When the DFCO is published, then version 12 is associated with Change Sequence Number 002.
DFCO-00538	25	003	Version 25 is associated with Change Sequence Number 003.

Change Sequence numbers are a series of three-digit numbers (001 through 099) that define the order in which DFCOs have been published for a specific Design or File Folder. Each Change Sequence number is associated with one specific DFCO and with the file folder version number in use when the DFCO is published.

File Folder Change Sequence numbers are similar to the concept of Items and Revision numbers. (See ["About Item Revisions and File Folder Versions"](#) on page 10-30.)

When a Design file folder is added to the **Affected Files** tab of a DFCO, a Change Sequence number is assigned. If the Design has never been published before, then the Change Sequence number 001 is assigned. On the file folder object, the Change Sequence Number is displayed on the **Changes** tab.

If the file folder has been published before, then the next number in the sequence is assigned. For example, if the current Change Sequence Number is 013, and the file folder is added to the Affected Files table, then 014 is assigned.

Affected Files Tab Buttons and Actions

The following table describes the actions available on the **Affected Files** tab.

Table 13–3 Affected Files tab buttons

Button or Action	Description
Add > To Change Order To Selected File Folder By Search	Add files to the Affected Files table. Choose the add option: ? To Change Order Browse to select a file to add a row to the change order. ? To Selected File Folder Add a file to a file folder on the Affected Files table. ? By Search Search the Agile PLM database for files to add to the Affected Files table.
Remove > From Change Order From File Folder	Remove selected file. Choose the remove option: ? From Change Order Remove the selected file from the DFCO. ? From Selected File Folder Remove the selected file from the file folder; the file folder remains on the DFCO.
Get	Get a copy of the selected file. See "Getting Files in Web Client" on page 10-9.
Open	Open a copy of the selected file in its native application. See "Opening Attachment Files in their Native Applications" on page 10-13.

Table 13–3 (Cont.) Affected Files tab buttons

Button or Action	Description
View/Redline > View Compare by Search	<p>Opens the selected file in the AutoVue viewer. Choose the view option:</p> <ul style="list-style-type: none"> ? View Opens the selected file in the viewer. You can now add AutoVue redline markups to the file. The redline markups appear on the lower Redline/Markup table on the Affected Files tab. ? Compare by Search Choose files in the selected file folder, and then search for other files in the Agile PLM system for comparison.
Checkout	<p>Checkout the selected file.</p> <p>See "Web Client, Checking Out Attachment Files" on page 10-27.</p>
Cancel Checkout	See "Canceling Checkouts" on page 10-29.
Checkin	See "Web Client, Checking in Revised Attachment Files" on page 10-28.
More menu	<p>The More menu includes:</p> <ul style="list-style-type: none"> ? Fill-down Fill-down (selected cells) Fill-up Fill-up (selected cells) See "Using Fill-Up and Fill-Down in Web Client Tables" on page 5-8. ? Full Display Mode ? Incorporate ? Unincorporate

Adding File to the Affected Files Table

When adding files to the Affected Files table, you can choose from the following add methods:

- ? **Add File to Change Order** – browse for a file to add to the DFCO. A new Design or File Folder is created when the file is added.
 1. Click the **Add** button and choose **To Change Order**.
The File Upload Selector dialog appears.
 2. Browse for one or more files to add. See ["Web Client File Upload Selector"](#) on page 10-18.
 3. Choose a folder **Type**, either Design or File Folder.
 4. When you are finished, click **Upload** to begin uploading the files.
- ? **Add File to Selected File Folder** – browse for a file to add to the selected file folder.
 1. In the Affected Files table, select the row of the file folder to which a file will be added.
The file folder must be checked out.
 2. Click the **Add** button and choose **To Selected File Folder**.
The File Upload Selector dialog appears.

3. Browse for one or more files to add. See ["Web Client File Upload Selector"](#) on page 10-18.
 4. When you are finished, click **Upload** to begin uploading the files.
- ?
- Add File by Search** – search for Design and File Folder objects, and then select a file to add. Or, search Design Structures to find a file to add.
1. Click the **Add** button and choose **By Search**.
The Add Files search dialog appears.
 2. Choose a search type (Object Search or Design Structure), and then choose an object. Define your search criteria and click **Search**.
You can choose to display files that are on Active Changes and Published Change Orders. However, a file can be included on the Affected Files tab of only one DFCO at a time.
 3. In the Search Results table, select one or more rows, and press Return.
The files are added to the Affected Files table.

Removing Files from the Affected Files Table

Note: When you remove a file folder from the Affected Files table, then the associated Change Sequence Number is released. For example, if the Change Sequence Number of the selected file folder is [004], when the file folder is removed, then 003 becomes the current Change Sequence Number.

If the file folder is later added to a different DFCO, then the Change Sequence Number [004] is associated with the new DFCO.

To remove files from the Change Order:

1. Select one or more rows in the Affected Files table.
2. Click the **Remove** button and choose a **From Change Order**.
The selected file is removed from the DFCO, but it is not removed from the Design or File Folder object. Removing the file means that it is no longer part of the change process.
Only the selected file is removed from the Affected Files table. If a Design or File Folder has multiple files, you remove from the DFCO only the file you selected to remove.

To remove files from the Selected File Folder:

1. The file folders must be checked out. Check out the file folders if they are not already checked out.
2. Select an Affected Files table file row.
3. Click the **Remove** button and choose a **From Selected File Folder**.
The file is removed from the checked out version of the Design or File Folder.
If the selected file to remove is the last file in the file folder, then an error message is displayed.

Redline/Markup Table

When you select a row in the Affected Files table, then you are able to view, add, and remove redline markups.

Redline/Markup Table Attributes

The Redline/Markup Files tab appears at the bottom of the Affected Files tab when you have selected a single Affected Files table row.

The redline markups added or associated with the selected file are displayed in the Redline/Markup table, against all versions (for all files) of the selected file's Design or File Folder object.

If you have the appropriate privileges, you can edit the editable table cells. Click **Save** to save your edits. See ["Editing Table Cells in Web Client"](#) on page 5-8.

Table 13-4 Columns of the Redline/Markup table

Attribute column	Description
Markup Name	The name assigned to the markup (editable).
Markup Number	The number assigned to the markup.
Markup Description	Description of the markup (editable).
Folder Version	The folder version to which the markup is associated.
Redline Process	Process used to create the redline. The redline process is the change number of ECO, ECR or DFCO in which the redline was created. For File Folder or Design Ad Hoc redlines, the redline process is the File Folder number or the Design number.
Redline User	User who created the redline in the upper Affected Files table.
Last Modified	Most recent modify date.
File Size	File size
File Name	Name of the affected file.
File Type	File type
Create Date	Date the file was created.
File Name	Name of the file

Redline/Markup Table Buttons and Actions

The following table describes the **Redline/Markup** tab buttons.

Table 13-5 Redline/Markup tab buttons

Button or Action	Description
Add	Add markup files to the Redline/Markup table. Opens the File Upload Selector. Browse for files to upload to the Redline/Markup table. See "Web Client File Upload Selector" on page 10-18.
Associate Redlines	Opens the Associate Redlines dialog. See "Associate Redlines – Consolidating Redlines" on page 13-10.
Remove	Remove redlines from the table.

Table 13–5 (Cont.) Redline/Markup tab buttons

Button or Action	Description
Get	Get a copy of the redline file.
Open	Open the redline file.
View/Redline	Opens the selected file in the viewer. You can now add AutoVue redline markups to the file. The redline markups appear on the lower Redline/Markup table on the Affected Files tab.
More	Includes the Full Display Mode menu option.

Adding Redline/Markups

If you have the appropriate privileges, then you can add local files as new markup files.

- 7 In order to add markups, the selected Affected File must be checked in.
- 7 Markups can be added regardless of the incorporation status of the selected Affected File.
- 7 The files can be of any file type that the Agile administrator has configured as a valid markup file type.
- 7 When you add a local file as a markup, then a new markup file folder is created.
- 7 The Redline Process is the current DFCO.
- 7 Clicking the markup file name in the Redline/Markup Files table opens the markup file in its native application.

To add Redline/Markups:

1. Select a row in the Affected Files table.
2. In the lower **Redline/Markup Files** tab, click the **Add** button.
The File Upload Selector dialog appears.
See "[Web Client File Upload Selector](#)" on page 10-18.
3. Browse to locate and select the file you want.
4. Click the **Upload** button.

Associate Redlines – Consolidating Redlines

The Associate Redlines action provides a method to consolidate all the redline markups for a specific file on the DFCO **Affected Files** tab Redline/Markup table.

For the selected Affected Files table row file folder, you can select markup files from any object with redline markup files (ECO Affected Item Attachment Redlines, ECR Attachment Redlines, DFCO Redline/Markups and File Folder/Design Files Ad hoc Redlines). The markup is against the selected Affected File's File Folder.

4.63.2The redline process is the change number for ECO, ECR and DFCO. For File Folder/Design redlines, the redline process is the file folder/design number.

Redline markups can be associated with a specific file by several methods:

- 7 Ad Hoc redline markups are created on the **Files** tab of a Design or File Folder object.
See "[Ad Hoc Redlining or Marking Up of Attachment Files from the File Folder](#)" on page 11-21.
- 7 ECO redline markups of item attachment files are created on a change order for an item with an attachment, and approaching the attachment through the **Redline Attachments** tab of the ECO.

See ["Marking Up or Redlining Attachment Files from an ECO"](#) on page 10-36.

- 7 ECR redline markups are created for the ECR Affected Item attachments by adding those attachments to the ECR **Attachments** tab. Then, use the ECR **Attachments** tab **Redline** button to open the file in AutoVue and create redline markups.

See ["Marking Up or Redlining Attachment Files from an ECR"](#) on page 10-37.

- 7 DFCO Redline/Markup redlines are created on the **Redline/Markup Files** lower tab on the **DFCO Affected Files** tab.

See ["Adding Redline/Markups"](#) on page 13-10.

To consolidate redlines, use the Associate Redlines button:

1. In the Affected Files table, select the file row you want.
The Redline/Markup table to the selected affected file is displayed in the lower tab.
2. In the lower **Redline/Markup Files** tab, click the **Associate Redlines** button.
The Associate Redlines dialog appears.
The Associate Redlines search returns all redlines against all versions (for all files) of the selected file's file folder.
3. Select the option **Include Markups on Affected Files** to include redlines from other DFCOs.
4. Select one or more rows in the Associate Redlines dialog table.
5. Click **Associate**.

Removing Redlines

Only redline rows with the Redline Process equal to the current DFCO can be removed.

You can remove redlines as long as the DFCO has not yet been released.

To remove redlines:

1. In the Redline/Markups table, select the redline row you want to remove.
2. Click **Remove**.

Title Block Version-Specific Attributes

The Affected Files **Title Block** tab is similar to the ECO Affected Items **Title Block Redlines** tab.

(For more information about the Affected Items Title Block Redlines tab, see *Agile PLM Product Collaboration User Guide*, Appendix B.)

The Agile administrator determines which attributes are version-specific. Attributes that can be defined as version-specific are some title block attributes and some Page two attributes.

If an attribute has been defined as version-specific, then it can only be modified on the DFCO Affected Files **Title Block** tab.

To modify a version-specific attribute:

1. Select a rows in the Affected Files table.
2. Click the lower **Title Block** tab to display it.

Attributes defined as version-specific are displayed on the **Title Block** tab.

3. On the Title Block tab, click **Edit**.
4. Edit the version-specific attributes.
5. Click **Save**.

Publishing the DFCO

DFCOs are routed for review and signoff in the same manner as any Change Order or routable object. See [Chapter 9, "Routing Objects with Workflows."](#)

Before a DFCO can be published (released), the release audit checks the following:

- ⌚ All affected files must be checked in.
- ⌚ The affected files are incorporated if the Publish Change Order with Unincorporated Files SmartRule is set to either Disallow or Warning.
- ⌚ Release audit checks for unreleased Design structure children.
- ⌚ Release audit checks for unincorporated file folders according to the setting of the SmartRule Publish Change Order with Unincorporated Affected File Rows.
- ⌚ Release audit checks that affected file Design structure recursive components are included on the Affected Files table of the same DFCO.

See also ["Release Audit, Conditions Audited"](#) on page 9-13.

Once a DFCO is released, then.:

- ⌚ The released DFCO cannot be moved to a pre-release status in the workflow. That is, the DFCO cannot be unreleased.
- ⌚ The released DFCO cannot be canceled after it is released or implemented.
- ⌚ The released DFCO cannot be moved to a Hold-type status from the released-type status or from the implemented-type status.

If a DFCO is canceled, then:

- ⌚ The Change Sequence Number and DFCO number are not shown in the file folder Version dropdown list.
- ⌚ The Design or File Folder versions that were created through the DFCO remain visible on the Design or File Folder object, but the reline markup files remain on the canceled DFCO.
- ⌚ The Design or File Folder objects listed on the **Affected Files** tab of the canceled DFCO can be checked out and checked in from the **Files** tab of the Design or File Folder once the DFCO is canceled.
- ⌚ If there are affected files on the canceled DFCO, then the canceled DFCO cannot be moved to any another workflow status.

Working with Thumbnails

Thumbnails are displayed in Web Client; thumbnails are not displayed in Java Client.

What are Thumbnails?

In Agile PLM Web Client, thumbnails are small bitmap images or icons which represent attached files or URLs.

If the Thumbnails capability is enabled on your Agile PLM system, you have the appropriate privileges, and your user profile settings are set to allow you to view thumbnails, you will be able to view thumbnails on the following tables and object tabs.

Table 14–1 *Thumbnail availability by table and object tab*

Thumbnails available from:	Details
Search Results tables	Thumbnails are available in search results tables when you run a search for objects that display Thumbnails: Items, Manufacturer Parts, and File Folders.
Item objects	Title Block tab BOM tab Where Used tab Attachments tab
Manufacturer Part objects	General Info tab Attachments tab
File Folder objects	Title Block tab Where Used tab
Design objects	Title Block tab Structure tab Where Used tab, includes both Attachments table and Design table.
Quick View palette	The Quick View palette of valid thumbnail objects also displays thumbnails.






The AutoVue view server generates Thumbnails. Thumbnails are automatically generated according to the Agile Administrator settings in the Viewer and Files node.

Note: If the Structure or BOM changes after the thumbnails have been generated, use the **Regenerate** function to generate the newly added structure or BOM items. See ["Using the Thumbnail Navigator"](#) on page 14-7.

For valid image file types, the thumbnail is generated immediately when the file is attached in Agile PLM. Thumbnails are scaled directly from image files.

Standard file type icons are used for files where images are not useful. Some examples are listed below:

Table 14–2 Standard file type thumbnail icons

Thumbnails	Details
	This icon represents all URLs.
	.txt file
	Microsoft Excel file
	Microsoft Word file
	Visual media file

Special icons provide additional information about the thumbnail attachment. Some examples are listed below:

Table 14–3 Special thumbnail icons





Thumbnails	Details
	<p>Either the file type is not supported for viewing, or the file type is supported for viewing but not supported for thumbnail generation in "Viewer and File Association" node, or not listed in the standard Icon settings.</p> <p>The file count underneath the title block thumbnail also includes the files with N/A icons because they are valid files even though there are no valid thumbnails for those files.</p>
	<p>The object has no attachments.</p> <p>A blank thumbnail icon or a N/A thumbnail icon is displayed in the search results table when the only checked-in version of the file folder is Version 0</p>


Table 14–3 (Cont.) Special thumbnail icons

Thumbnails	Details
	The thumbnail is in the process of being generated by the view server.
	An error condition exists, for example, the thumbnail generation AutoVue or primary file server is down.

Viewing Thumbnails in Search Results Tables

Note: To view thumbnails in Agile PLM Web Client, the Thumbnails feature must be enabled in your Agile PLM system and your user profile **Thumbnails** preference must be set to **On**. If you have questions about your ability to view thumbnails, contact the Agile administrator.

When you run a search for objects that can include thumbnails, the search results table includes buttons that allow you to choose how you want to view thumbnails in the search results. The thumbnail view buttons appear at the top of the search results table:

Figure 14–1 Thumbnail view buttons, search results table**Table 14–4 Thumbnail View buttons**





Search results table Thumbnail View buttons	Description
	Standard View No thumbnails are displayed in the search results table.
	Thumbnail View Thumbnails are displayed in the Thumbnails column in the search results table. Available actions: <ul style="list-style-type: none"> ▸ To open the Thumbnail Navigator, click a thumbnail. ▸ To open an attachment file in the AutoVue for Agile, hover the cursor over a thumbnail and then click the file name button in the lower left corner of the thumbnail. The file opens in the viewer. URLs open in a new browser window.
	Thumbnails column header icon in search results table.

Table 14–4 (Cont.) Thumbnail View buttons

Search results table Thumbnail View buttons	Description
	<p>Only Thumbnail View</p> <p>Only thumbnails are displayed, allowing you to quickly identify the image you want.</p> <p>Available actions:</p> <ul style="list-style-type: none"> • To open the Thumbnail Navigator, click a thumbnail. • To open an attachment file in AutoVue for Agile, hover the cursor over a thumbnail and then click the file name button in the lower left corner of the thumbnail. The file opens in the viewer. URLs open in a new browser window. • To open the associated Agile object, click the number or description link below the thumbnail. The object opens in the content pane.

Your default search results table thumbnail view mode is determined by your user profile **Search Display Mode** preference setting: Standard, With Thumbnail, or Only Thumbnail. To change your default Search Display Mode, click the **My Settings** button in the left navigation pane menu to edit your **Preferences** tab.

Click the thumbnail – opens Thumbnail Navigator (Item and Manufacturer Part objects only)

Click the file name button (on hover) – use "Open" action (viewer or MIME type)

Note: A blank thumbnail icon or a N/A thumbnail icon is displayed in the search results table when the only checked-in version of the file folder is Version 0. Any files associated with pending Version [1] become available to create a thumbnail only when Version [1] is checked-in. See also ["Version-Specific Properties and File Folder Object Searches"](#) on page 8-55.

Viewing Thumbnails in Object Tab Tables

Note: To view thumbnails in Agile PLM Web Client, the Thumbnails feature must be enabled in your Agile PLM system and your user profile **Thumbnails** preference must be set to **On**. If you have questions about your ability to view thumbnails, contact the Agile administrator.


Thumbnails can be viewed in the tables of the following tabs:

- Items – **BOM** tab, **Where Used** tab, **Attachments** tab.
- Manufacturer Parts – **Attachments** tab
- File Folders – **Where Used** tab
- Designs – **Structure** tab and **Where Used** tab (which includes two tables: Attachments and Design)

To toggle the tab table thumbnail view mode:

- In the table **More** menu, choose **Thumbnail View** to display the table row object thumbnails in the Thumbnails column.
- In the table **More** menu, choose **Standard View** to hide the Thumbnails column. No thumbnails are displayed in Standard View.

Table 14–5 Thumbnail tab icons

Thumbnail tab icon	Description
	Thumbnail column header icon appears in the object tabs where thumbnails are displayed.

To open an attachment file in the AutoVue for Agile:

1. Hover the cursor over the thumbnail and then click the file name button in the lower left corner of the thumbnail. The file opens in the viewer. URLs open in a new browser window.

To open the Thumbnail Navigator (Item and Manufacturer Part objects only):

1. Click the thumbnail.

Your default tab table thumbnail view mode is determined by your user profile **Table Display Mode** preference setting: Standard or With Thumbnail. To change your default Table Display Mode, click the **My Settings** button in the left navigation pane menu to edit your **Preferences** tab.

Viewing Thumbnails on Title Page and General Info Tabs

Note: To view thumbnails in Agile PLM Web Client, the Thumbnails feature must be enabled in your Agile PLM system and your user profile **Thumbnails** preference must be set to **On**. If you have questions about your ability to view thumbnails, contact the Agile administrator.

On the item **Title Block** tab and the manufacturer part **General Info** tab, you can view the thumbnails for the object attachments.

To view additional thumbnails:

1. Click the **Next** and **Previous** buttons under the thumbnail.


To open an attachment file in the AutoVue for Agile:

1. Hover the cursor over the thumbnail and then click the file name button in the lower left corner of the thumbnail. URLs open in a new browser window.

To open the Thumbnail Navigator:

1. Click the thumbnail.

Figure 14–2 *Thumbnails on Title Page or General Info tabs*



Although a File Folder or a Design object may have multiple files added to the **Files** tab, on the **Title Block** tab, only the Master Thumbnail is displayed on the **Title Block** tab. By default, the Master Thumbnail is the first file added to the **Files** tab.

To change the Master Thumbnail:

1. Click the **Files** tab to display it.
2. In the Files table, select the file row you want.
3. In the table **More** menu, choose **Set Master Thumbnail**.




The Master Thumbnail icon in the Master Thumbnail row indicates the Master Thumbnail for the file folder or design object.

Note: Only one thumbnail is displayed on the **Title Block** tab of each File Folder or Design object. No Thumbnail Navigator is available on the File Folder **Title Block** tab.

On the File Folder or Design **Title Block** tab, you can:

- ⌘ Replace a file – Select a file to use to create a new thumbnail, replacing the current thumbnail.
- ⌘ Regenerate thumbnails.

Table 14–6 *File Folder object Thumbnail controls and icons*

File Folder buttons and icons	Description
	Master Thumbnail icon. Appears on the file folder object Files tab Master Thumbnail column to indicate the Master Thumbnail file for that file folder object.
	Replace file button. Appears on the Title Block tab of File Folder objects and Design objects.
	Regenerate thumbnails button. Appears on the Title Block tab of File Folder and Design objects.

Using the Thumbnail Navigator

Note: To view thumbnails in Agile PLM Web Client, the Thumbnails feature must be enabled in your Agile PLM system and your user profile **Thumbnails** preference must be set to **On**. If you have questions about your ability to view thumbnails, contact the Agile administrator.

On the item **Title Block** tab and the manufacturer part **General Info** tab, you can view the thumbnails for the object attachments. The Thumbnail Navigator serves as a *graphical Attachments tab*, performing the common operations typically done on the **Attachments** tab in a simpler, graphical way.


The Thumbnail Navigator can also be opened from the item **BOM** and **Where Used** tabs, and **Where Used** tab of the File Folder and Design object.

To open the Thumbnail Navigator:

1. Click the thumbnail.

The Thumbnail Navigator dialog appears.






Figure 14–3 Thumbnail Navigator dialog



Note: If the item or manufacturer part has no attachments, the blank thumbnail icon is visible on the Title Block (item) or General Info (manufacturer part) tab. Click the blank thumbnail icon to add an attachment file.

You can perform the following actions in the Thumbnail Navigator:

Table 14–7 Thumbnail Navigator buttons and actions

Button or action	Description
Set as default check box	Choose the default thumbnail. Select the Set as default option for the file you want. Only one file can be set as the default.
	Add Add a new attachment. The add process generates a thumbnail from the attachments, displays that thumbnail, and adds it to the end of the vertical list.
	Remove Thumbnail/File Click to remove the attachment corresponding to the current thumbnail.
	Replace Select a file to use to create a new thumbnail, replacing the current thumbnail. Replace can be performed only with file types that are listed in the Directly Use These Thumbnail Image Types property of the Viewers and Files system settings in Agile Administrator. For more information, see <i>Agile PLM Administrator Guide</i>
	Reload Resets the setting modifications in the currently opened Thumbnail Navigator. For example, modifications to Set as Default setting will be revert to original setting.
	Regenerate Forces Agile PLM system of perform the action of re-generating the thumbnail image, according to the method defined by Agile Administrator. Also provides an undo action for the Replace action.
Drag and Drop	Drag and drop the thumbnails in the Thumbnail Navigator right pane to sort them into the desired order.
Display thumbnail in large view panel	Click small thumbnail image in vertical list in the right pane to display that thumbnail in the view panel in the left pane.
Open file in AutoVue for Agile	In the view panel, click the file name hyperlink below the thumbnail to launch AutoVue for Agile. The file opens in the viewer. URLs open in a new browser window.
X Close Thumbnail Navigator	Click the X in the upper-right corner to close the Thumbnail Navigator and save the current thumbnail sequence order.

Viewing Thumbnails in the Quick View Palette

When you open an object in the Quick View palette, the default thumbnail is displayed in the palette.

No thumbnail actions are available in the Quick View palette.

Thumbnail User Privileges

The following list describes the user privileges necessary to view and modify thumbnails. The Agile administrator defines and assigns user roles and privileges. If you have questions about your ability to view and modify thumbnails, contact the Agile administrator.

View Thumbnails

Requires Read privilege with Applied To property set to include the Thumbnail attribute on tabs where thumbnails appear, for example, Items.Title Block.Thumbnails.

7 Add, Remove, Replace, or Regenerate Thumbnails

Requires Modify privilege with Applied To property set to include the Thumbnail attribute on tabs where thumbnails appear, for example, File Folders.Files.Thumbnail and Parts.Attachments.Thumbnail.

Note: When defining privilege masks, the Thumbnail attribute is not considered a visible attribute. When selecting Applied To properties for Thumbnail attributes, deselect the **Show visible attributes only** check box. For detailed information about Agile roles and privileges, see *Agile PLM Administrator Guide*.

Deleting Agile Objects

Agile PLM objects can be soft-deleted, and then hard-deleted. The following topics are discussed:

- ? ["Soft Delete and Hard Delete Defined"](#) on page A-1
- ? ["Soft-Deleting an Object"](#) on page A-2
- ? ["Undeleting an Object"](#) on page A-2
- ? ["Hard-Deleting an Object"](#) on page A-2
- ? ["Notes about Deleting Specific Agile Object Types"](#) on page A-3

Soft Delete and Hard Delete Defined

Java Client and Web Client support "soft" and "hard" deletes for many Agile object classes. When you soft-delete an object in the database, it is not permanently deleted. A soft-deleted object is marked "Deleted" in the database, and its object number or name is reserved. You cannot create another object with the same type and number or name as a soft-deleted object.

When you run a search, soft-deleted objects do not appear in the search results table. To locate soft-deleted objects, you must run the predefined deleted object searches in the **Recycle Bin Searches** folder.

Note: You have access to the **Recycle Bin Searches** folder if **Recycle Bin Searches** is included in the **Searches** field of your user profile. If you have the appropriate privileges, then you can edit your user profile and add **Recycle Bin Searches** to the list of searches in the **Searches** field. If you do not have the appropriate privileges to modify the **Searches** field in your user profile, then ask the Agile administrator to modify your user profile.

A hard-deleted object is permanently removed from the database.

Caution: You *cannot* undelete a hard-deleted object.

To soft-delete, hard-delete or undelete an Agile object:

- ? You must have the appropriate Delete or Undelete privileges for that object.
- ? All relationships and subscriptions must be removed.
- ? The object must meet any additional conditions that determine whether it can be deleted or undeleted.

In general, if deleting or undeleting an object would cause the compromise of data integrity, the delete or undelete action is disabled.

For detailed information about deleting specific object types, see ["Notes about Deleting Specific Agile Object Types"](#) on page A-3.

Soft-Deleting an Object

When an object is soft-deleted, it is no longer available for use. However, until it is hard-deleted, its number or name is reserved in the Agile PLM database and cannot be reused.

To soft-delete an object in Web Client:

1. Select and open the object you want to delete.
2. Choose **Actions > Delete**, and respond **OK** to the confirmation prompt.

The object is soft-deleted.

To soft-delete an object in Java Client:

1. Select and open the object you want to delete.
2. Click the **Delete** button, and respond **Yes** to the confirmation prompt.

The object is soft-deleted.

See also: ["Soft Delete and Hard Delete Defined"](#) on page A-1, ["Undeleting an Object"](#) on page A-2, and ["Hard-Deleting an Object"](#) on page A-2.

Undeleting an Object

If you have the appropriate privileges, then you can undelete soft-deleted objects.

To undelete an object in Web Client:

1. Run the appropriate Deleted *<objects>* search from the **Recycle Bin Searches** folder.
2. Open the deleted object you want to restore.
3. Choose **Actions > Undelete**.

Note: You can click the **Navigator** button in the search results table to display the search result object links in the left pane **NAVIGATOR** drawer.

To undelete an object in Java Client:

1. Run the appropriate Deleted *<objects>* search from the **Recycle Bin Searches** folder.
2. Open the deleted object you want to restore.
3. Click the **Undelete** button.

See also: ["Soft Delete and Hard Delete Defined"](#) on page A-1, ["Soft-Deleting an Object"](#) on page A-2, and ["Hard-Deleting an Object"](#) on page A-2,

Hard-Deleting an Object

Soft-deleted objects still exist in the database. To remove an object permanently, you must hard-delete it. While an object is still only soft-deleted, you can undelete it. Run the appropriate Deleted *object* search from the **Recycle Bin Searches** folder.

To hard-delete a soft-delete object (if you have the appropriate privileges) in Web Client:

1. Run the appropriate Deleted *<objects>* search from the **Recycle Bin Searches** folder.
2. Select the one or more object rows in the search results table.
3. Click the **Delete** button.
4. In response to the warning prompt, choose **Continue** and then click **Finish**.
5. Or, you can hard-delete one object at a time:
 - ? Open the object.
 - ? Choose **Actions > Delete**, and respond **OK** to the confirmation prompt.

Note: You can click the **Navigator** button in the search results table to display the search results object links in the left pane **NAVIGATOR** drawer.

To hard-delete a soft-deleted object (if you have the appropriate privileges) in Java Client:

1. Run the appropriate Deleted *<objects>* search from the **Recycle Bin Searches** folder.
2. Open the object.
3. Click the **Delete Object** button, and respond **Yes** to the confirmation prompt.

See also: ["Soft Delete and Hard Delete Defined"](#) on page A-1, ["Undeleting an Object"](#) on page A-2, and ["Soft-Deleting an Object"](#) on page A-2,.

Notes about Deleting Specific Agile Object Types

The following topics provide notes about required conditions for deleting each Agile PLM object type.

Notes about Deleting Item Objects

Before you can delete an item object, it must meet the conditions described below.

- ? The Agile administrator has assigned to you a role that has the appropriate Delete privileges.
- ? All relationships and subscriptions have been removed.
- ? The item has no released changes against it.
- ? The item is not listed on the **Affected Items** tab of any pending changes.

You must first remove the item from the **Affected Items** tab of each pending change before you can delete the item.

- ? The item has not been added to PSR.
- ? The item has not been added to QCR.
- ? The item has not been added to Material Declaration.
- ? The item has not been added to Price.
- ? The item has no content on its **BOM** tab for the current revision or any pending revisions.
- ? The item has no content on its **Manufacturers** tab for the current revision or any pending revisions.

- ? The item is not used on the Bill of Materials of any other item, that is, the item to be deleted is not a child item on the BOM tab of a parent item revision, including the latest released revision, past released revisions, or pending revisions of the parent item.
- ? The item is not associated with a Part Family, that is, the item does not appear on the **Parts** tab of a Part Family object. On the **Title Page** of the item to be deleted, the Part Family field must be empty. If the **Part Family** field is populated, then the **Actions > Delete** command is disabled.

Notes about Deleting Change Objects

Before you can delete a change object, it must meet the conditions described below.

- ? The Agile administrator has assigned to you a role that has the appropriate Delete privileges. For example, you are the change analyst or component engineer, and the Agile administrator has given change analysts or component engineers the appropriate privileges to delete a change.
- ? All relationships and subscriptions have been removed.
- ? The change is at the Pending status type or the Unassigned status.
- ? You have Discovery and Read privileges for any items on the Affected Items table, otherwise, you cannot delete the change.

Note: To delete a change that has already been released, you must first unrelease the change. You need the appropriate privileges to unrelease a change by using the Workflow tab to switch it to a different status.

- ? When you soft-delete a change that has items on the Affected Items tab, all redlines associated with that change are discarded. To preserve data integrity, a soft-deleted change with items on the Affected Items tab cannot be undeleted. That is, a soft-deleted change can be undeleted only if there are no items on the Affected Items tab.

Note: If you think you might want to undelete a soft-deleted routable object in the future, then be sure to clear its **Affected Items** tab before you delete it. You can undelete only routable objects with no entries on the **Affected Items** tab. To keep a record of affected items when you delete the change object, then use the **Save As** command to copy it under another change object number before deleting it.

Notes about Deleting Transfer Order Objects

Before you can delete a Transfer Order object, it must meet the conditions described below.

- ? The Agile administrator has assigned to you a role that has the appropriate Delete privileges.
- ? All relationships and subscriptions have been removed.
- ? The transfer order is at the Pending status type or the Unassigned status.

Notes about Deleting PSR or QCR Objects

Before you can delete a Product Service Request (PSR) or Quality Change Request (QCR) object, it must meet the conditions described below.

- ? The Agile administrator has assigned to you a role that has the appropriate Delete privileges.
- ? All relationships and subscriptions have been removed.
- ? The PSR or QCR is at the Pending status type or the Unassigned status.
- ? You have Discovery and Read privileges for any items on the Affected Items table; otherwise, you cannot delete the PSR or QCR.

Note: To delete a PSR or QCR that has already been released, you must first unrelease it. You need the appropriate privileges to unrelease a PSR or QCR by using the **Workflow** tab to switch it to a different status.

You *cannot* delete a **PSR** if:

- ? It appears on the **Relationships** tab of a QCR.
- ? It is currently part of a corrective action process. Remove the PSR from the QCR and then delete the PSR.
- ? It appears in the Related PSR tab of another PSR.
- ? It is currently part of a larger problem. Remove this PSR from the parent PSR and then delete it.
- ? It appears on the Related PSR tab.
- ? It is being used to aggregate multiple problems. Remove the related PSRs and then delete it.

You *cannot* delete a **QCR** if:

- ? It has any PSRs on the **Relationships** tab.
- ? If the corrective action process contains Problem Reports. Remove the PSR from the QCR and then delete the QCR.
- ? It has any Changes on its **Relationships** tab.
- ? If the corrective action process is already routed through engineering changes. Remove the Changes from the QCR and then delete the QCR.

Notes about Deleting Sourcing Project, RFQ and RFQ Response Objects

Agile Product Cost Management (PCM) objects include: Sourcing Project, RFQ, and RFQ Response. Before you can delete any Agile PCM object it must meet the conditions described below.

- ? The Agile administrator has assigned to you a role that has the appropriate Delete privileges.
- ? All relationships and subscriptions have been removed.
- ? Sourcing Project
 - The sourcing project has no RFQs.
 - If the sourcing project has RFQs, the RFQs are in the closed state.

Note: Sourcing project objects can be soft deleted, but soft-deleted sourcing project objects cannot be undeleted or hard deleted.

- ⌚ RFQ
 - The RFQ has no released changes against it.

Note: RFQ objects can be soft deleted, but soft-deleted RFQ objects cannot be undeleted or hard deleted.

- ⌚ RFQ Response
 - The delete action is not supported for RFQ response objects.

Notes about Deleting Package Objects

Before you can delete a Package object, it must meet the conditions described below.

- ⌚ The Agile administrator has assigned to you a role that has the appropriate Delete privileges.
- ⌚ All relationships and subscriptions have been removed.
- ⌚ The package is at the Pending status type or the Unassigned status.

Notes about Deleting Manufacturer Objects

Before you can delete a manufacturer object, it must meet the conditions described below.

- ⌚ The Agile administrator has assigned to you a role that has the appropriate Delete privileges.
- ⌚ All relationships and subscriptions have been removed.
- ⌚ It is not listed on the Manufacturers tab of an item. (Check the Where Used tab of the manufacturing object.)
- ⌚ If the object is a manufacturer, no manufacturer parts are associated with it.

Note: If all manufacturer parts associated with a manufacturer have been deleted, then the manufacturer can be deleted as well. However, you will not be allowed to undelete the soft-deleted manufacturer parts until the soft-deleted manufacturer object is undeleted.

Notes about Deleting Site Objects

Before you can delete a Site object, it must meet the conditions described below.

Note: Site objects can be soft deleted, but soft-deleted sites cannot be undeleted or hard deleted. If you are no longer using a site, then Agile recommends that you disable it.

- ⌚ The Agile administrator has assigned to you a role that has the appropriate Delete privileges.
- ⌚ All relationships and subscriptions have been removed.

- ? The site does not appear on any item's **Sites** tab.
- ? The site is not associated with any other Agile object.
- ? The site has a lifecycle of Disabled.

Note: If it meets the conditions listed above, then a disabled site can be soft-deleted even when it is listed in the Sites or Default Site field of user profiles. The deleted site is automatically removed from the Sites list in any user profile where it is listed.

Once the site has been associated with an item, you can change its status to Disabled, but you cannot delete it.

Notes about Deleting User Objects

Before you can delete a User object, it must meet the conditions described below.

- ? The Agile administrator has assigned to you a role that has the appropriate Delete privileges.
- ? All relationships and subscriptions have been removed.

Note: User objects *cannot* be hard-deleted.

User access to Agile PLM can also be controlled by using the user profile Status property. For example, if someone leaves the company, or will no longer be using Agile PLM, or you need to prevent a user from logging in to the Agile PLM system, then disable the user object by setting the Status property to Inactive. The user remains listed on the Java Client Administrator **Users** node and on the Web Client Address Book **Users** tab, and the name still appears on existing workflows, escalations, and so forth, but the user will no longer appear in the Address Book for other users to select. You can reset the user to Active status at any time.

In Java Client Administrator, to display the list of deleted users, you can use either the **Deleted Users** node or the Recycle Bin search **Deleted Users**. In Agile Web Client, to display the list of deleted users, use the Recycle Bin search **Deleted Users**.

For detailed information about managing Agile PLM users, see *Agile PLM Administrator Guide*.

Notes about Deleting User Group Objects

You can delete a user group that is no longer needed.

Before you can delete a user group object, it must meet the conditions described below.

- ? The Agile administrator has assigned to you a role that has the appropriate Delete privileges.
- ? All relationships and subscriptions have been removed.

Note: If you set a user group Status to Inactive, then the inactive group appears in the search results table. In contrast, a soft-deleted user group does not appear in the search results table.

If you delete a user group to which users have been assigned, then you can do so without removing the users who were in the user group:

- ⌚ Global User Groups – when you soft-delete a global user group, the group is listed in the group members' user profile **Groups** tabs as an inactive group. When you hard-delete a global user group, the user assignments to that global user group are also deleted and do not appear on the user profile **Groups** tab.
- ⌚ Personal User Groups – For personal user groups, whether active or inactive, assignments are not listed on the group members' user profile **Groups** tabs.'

When you delete a user group, it is removed from the Agile PLM address book. You cannot delete a user group if it is in use in these cases:

- ⌚ It is on any routable object signoff list on the routable object **Workflow** tab.
- ⌚ It is listed in any workflow definition Notify properties.
- ⌚ It is used as a designated escalation person for any users, user groups, and partners.

In Java Client Administrator, to display the list of deleted user groups, you can use either the **Deleted User Groups** node or the Recycle Bin search **Deleted User Groups**. In Agile Web Client, to display the list of deleted users, use the Recycle Bin search **Deleted User Groups**.

Notes about Deleting PG&C Objects

Agile Product Governance & Compliance (PG&C) objects include: Declarations, Specifications, Substances, and Part Groups. Before you can delete any Agile PG&C object it must meet the conditions described below.

- ⌚ The Agile administrator has assigned to you a role that has the appropriate Delete privileges.
- ⌚ All relationships and subscriptions have been removed.
- ⌚ Substances, Specifications, and Part Groups
 - If the substance, specification or part group object is in use, then it cannot be deleted.
- ⌚ Declaration
 - The Declaration is at the Pending status type or the Unassigned status.

Glossary

Activity

A project activity in Agile Product Portfolio Management, such as a program, task, or phase.

Affected Files

Similar to Affected Items, these objects are EC files that are Design Release Candidates.

Agile Configuration Propagation (ACP)

Propagating existing configuration of PLM to the newly installed version of PLM.

Agile Content Service (ACS)

ACS is an event-driven XML-based publishing service that makes the product record available to a wide variety of business applications and users, internally and across the global manufacturing network

Agile Destination

A package created by an Agile PLM system in the target PLM using Web Services to import from the Attachments tab of the package in the target system.

Agile Integration Services (AIS)

A collection of predefined Web Services in the Agile Integration Framework that enable communication between the Agile Application Server and disparate systems

Agile Product Portfolio Management

The Agile PLM project management solution that is integrated with the product information in PLM.

AI

Affected Items tab on Change objects in Agile.

Approved Manufacturer Parts List (AML)

List of approved manufacturer parts associated with an item.

Application Programming Interface (API)

A set of routines, protocols, and tools for building software applications. An API expresses a software component in terms of its operations, inputs, outputs, and underlying types.

Assembly

A product assembly lists the parts in a product and shows the substances and materials that comprise those parts. It is linked to specifications that can restrict how much of a particular substance that product assembly may contain

Automated Transfer Orders (ATO)

Content published by Agile PLM users in real time with a content transfer order (CTO) or set up subscribers to automatically create automated transfer orders (ATO) based on a schedule or triggered by a workflow status change.

Baseline

A snapshot of a project, usually in its initial stage, used as a reference for future comparison in Agile Product Portfolio Management.

Bill of Material (BOM)

A hierarchical representation of a product that is made up of other products.

Bill of Substances (BOS)

A hierarchical list of substances that are contained in the parts and assemblies that make up a BOM.

Change Sequence

A series of three-digit numbers (001 through 099) that define the order in which DFCOs (Design File Change Orders) have been published for a specific Design or File Folder. Each Change Sequence number is associated with one specific DFCO and with the specific file folder version number in use when the DFCO is published.

Commodity

A class of goods that is in demand, that is supplied without qualitative differentiation regardless of supplier.

Computer-aided Design (CAD)

The use of computer systems to assist in the creation, modification, analysis, or optimization of a design. CAD software is used to increase the productivity of the designer, improve the quality of design, improve communications through documentation, and to create a database for manufacturing. CAD output is often in the form of electronic files for print, machining, or other manufacturing operations.

Contract (Price)

This is a subclass of the Published Prices class. Contract prices are prices provided by the supplier for a specific item or manufacturer part. This price information applies only for the specified duration and can apply to any project.

Co-Sourcing

The process of leveraging product cost across suppliers.

Deliverable

A unit of work required for a project's success, usually fulfilled by generating a digital file. (Word processing documents, spreadsheet documents, PDFs, presentation documents, and so on.) Deliverables can also be Agile PLM objects and processes. Also called 'content' in Agile Product Portfolio Management.

Design Change Order (DCO)

A Change Order subclass that is available when the effected File Tab is enabled and provides access to all Agile PLM Workflow functions.

Design File Folder

An EC file folder that is integrated with CAD and PLM files, providing full access to PLM Workflow function.

EC Client

A Java-based UI to access, administer and operated the EC solution.

Engineering Collaboration (EC)

An application that provides data and process integration between CAD applications and Agile PLM. It allows CAD designers and engineers to capture and control the data representing a primary source of the product record.

Engineering Collaboration Order (ECO)

An object that carries with it all the proposed changes to a product and/or its BOM. When approved and implemented, the proposed changes become effective.

Extensible Markup Language (XML)

A markup language that defines a set of rules for encoding documents in a format that is both human-readable and machine-readable

File Manager

The File Manager manages files in a repository or vault in the file system and provides a place to store and retrieve files locally or remotely. You can install it on the same server as the Agile Application Server or on a separate one. You can also install the File in a redundant configuration and/or distributed across geographic regions.

File Transfer Protocol (FTP)

A standard network protocol used to transfer computer files from one host to another host over a TCP-based network, such as the Internet.

Fully Qualified File Name

The exact name of a file on a computer that is completely specified such that it is unambiguous and cannot be mistaken for any other file on that system.

Fully Qualified Path Name (FQPN)

The full path of a resource, directory or file, stored in a computer. It is composed by the full path to the resource and its syntax depends on the operating system.

Gantt Chart

A project management tool that shows project activities and schedule as a bar chart. The chart lists project activities in sequence, and presents critical information such as the start and end dates of each activity, as well as interdependencies between activities.

Item Master

The product record. It is the entire collection of Items - Parts, Documents, and any other user-defined subclasses of the Items class maintained under change control in the Agile system.

Java Message Service (JMS)

The Java Message Service (JMS) API is a Java Message Oriented Middleware (MOM) API for sending messages between two or more clients.

Lifecycle Phase

Current state in an object's workflow.

LRR

Latest Released Rev - concerning a Part or Document.

Non Cancelable Non Returnable (NCNR)

Applies to an item. NCNR can be a Yes or No, depending on the supplier. You can ask for the NCNR information in the supplier response. This is one of the critical factors in finding the best deal among the supplier responses.

PDX

See [Product Definition eXchange \(PDX\)](#).

PLM

See [Product Lifecycle Management \(PLM\)](#).

Percent allocation or % allocation

The percentage of a resource's time allocated to a specific task or tasks in Agile Product Portfolio Management..

Percent complete or % complete

Amount of time and effort expended on a project measured as a percentage of the time and effort required to complete the whole project. Used in Agile Product Portfolio Management.

Product Definition eXchange (PDX)

A standard designed for the e-supply chain. This standard is based on the XML format because it provides a simple yet powerful and flexible way to encode structured data into a format that is both human- and computer-readable. In PLM, PDX packages contain product content, such as items.

Product Lifecycle Management (PLM)

The process of taking parts/documents from inception to production to phase-out, and all the stages in between.

Protocol

A system of digital rules or agreed-upon format for data exchange within or between devices. It determines the type of error checking and data compression used.

Published Price

This is a subclass of the Published Prices class. Published prices are prices provided by the suppliers in response to an RFQ and published from the project. The published price information can also be used in other projects.

Price

An object that carries with it all the proposed changes to a product and/or its BOM. It can be approved and implemented to make the proposed changes effective.

Price Change Order

It is an object that carries with it all the proposed changes to a price. It can be approved and implemented to make the proposed changes effective.

Quote History

A subclass of the Quote Histories class. Quote history prices are the stored prices from supplier responses that you can use. Any change in the response line of an RFQ is stored in the historical response and is usable at any time.

Request for Information (RFI)

A material declaration that lists the parts in a product assembly and shows the substances and materials contained in the part.

Request for Quote (RFQ)

A standard business process whose purpose is to invite suppliers into a bidding process to bid on specific products or services.

Request for Proposal (RFP)

A solicitation, often made through a bidding process, by an agency or company interested in procuring a commodity, service or valuable asset, to potential suppliers.

Response Line

A response line has information about only one item. The negotiation of price and terms for items is dealt with in a response line.

Resource Pool

A group of users who can be bulk assigned as resources for a particular project or task in Agile Product Portfolio Management.

RFQ Response

A medium of communication between the user and the supplier. One response from a supplier can contain multiple response lines for different items. Price data is added to the project automatically when the supplier submits the response.

Schedule Editor

The scheduling engine that handles updates to the project schedule in Agile Product Portfolio Management.

Schema

In computer programming, a schema is the organization or structure for a database. The activity of data modeling leads to a schema.

Software Development Kit (SDK or "devkit")

A set of software development tools that allows the creation of applications for a certain software package, software framework, hardware platform, computer system, video game console, operating system, or similar development platform.

Sourcing Project

The entry point of sourcing and product pricing. A sourcing project tracks data required for sourcing and pricing, to perform data analysis for effective pricing.

Standard Cost

Applies to an item. This is the market cost of the item. It is site-specific. The standard cost is for a unit.

Supplier

A supplier of one or several commodities.

Target Cost

Applies to item. This is the expected cost of the item by you or the supplier. This can be a percentage of the standard cost. Target cost is for a unit.

Timesheet

The time entry system in Agile Product Portfolio Management, used to track actual hours spent by resources on project activities and to calculate corresponding labor cost.

Top Level Assembly (TLA)

The level in a BOM that indicates the ultimate product being manufactured.

Transfer order

Every time Agile Content Service (ACS) publishes product content, it produces a transfer order that keeps track of what, where, and when product content is transferred.

User Productivity Kit (UPK)

The Oracle online help system used in some Oracle products.

Web Service Extensions (WSX)

A Web service engine that enables communication between Agile Product Lifecycle Management system and disparate internal and external systems.

XML

See [Extensible Markup Language \(XML\)](#).

XML Schema

Description of a type of XML document, typically expressed in terms of constraints on the structure and content of documents of that type, above and beyond the basic syntactical constraints imposed by XML rules.