

Name create-jdbc-connection-pool– registers a JDBC connection pool

Synopsis create-jdbc-connection-pool [--help]
--datasourceclassname=*datasourceclassname*
[--restype=*resourcetype*]
[--steadypoolsize=*poolsize*]
[--maxpoolsize=*maxpoolsize*]
[--maxwait=*maxwaittime*]
[--poolresize=*poolresizelimit*]
[--idletimeout=*idletimeout*]
[--initsql=*initsqlstring*]
[--isolationlevel=*isolationlevel*]
[--isisolationguaranteed={true|false}]
[--isconnectvalidatereq={false|true}]
[--validationmethod=*validationmethod*]
[--validationtable=*validationtable*]
[--failconnection={false|true}]
[--allownoncomponentcallers={false|true}]
[--nontransactionalconnections={false|true}]
[--validateatmostonceperiod=*validationinterval*]
[--leaktimeout=*leaktimeout*]
[--leakreclaim={false|true}]
[--creationretryattempts=*creationretryattempts*]
[--creationretryinterval=*creationretryinterval*]
[--sqltracelisteners=*sqltracelisteners* [*sqltracelisteners*]
[--statementtimeout=*statementtimeout*]
[--lazyconnectionenlistment={false|true}]
[--lazyconnectionassociation={false|true}]
[--associatewiththread={false|true}]
[--associatewiththreadconnectionscount=*associatewiththreadcount*]
[--driverclassname=*jdbcdriverclassname*]
[--matchconnections={false|true}]
[--maxconnectionusagecount=*maxconnectionusagecount*]
[--ping={false|true}]
[--pooling={false|true}]
[--statementcachesize=*statementcachesize*]
[--validationclassname=*validationclassname*]
[--wrapjdbcobjects={false|true}]
[--description *description*]
[property *name=value*][:*name=value*]*]
[--target=*target*]
connectionpoolid

Description The create-jdbc-connection-pool subcommand registers a new Java™ Database Connectivity (“JDBC™”) software connection pool with the specified JDBC connection pool name.

A JDBC connection pool with authentication can be created either by using a `--property` option to specify user, password, or other connection information, or by specifying the connection information in the XML descriptor file.

This subcommand is supported in remote mode only.

Options

`--help`

`--?`

Displays the help text for the subcommand.

`--datasourceclassname`

The name of the vendor-supplied JDBC datasource resource manager.

`--restype`

The interface that the datasource class implements. Must be one of `javax.sql.DataSource`, `javax.sql.ConnectionPoolDataSource` or `javax.sql.XADataSource`. It leads to an error when this option has a legal value and the indicated interface is not implemented by the datasource class. This option has no default value.

`--steadypoolsize`

The minimum and initial number of connections maintained in the pool. The default value is 8.

`--maxpoolsize`

The maximum number of connections that can be created. The default value is 32.

`--maxwait`

The amount of time, in milliseconds, that a caller will wait before a connection timeout is sent. The default is 60000 (60 seconds). A value of 0 forces the caller to wait indefinitely.

`--poolresize`

Quantity by which the pool will scale-up or scale-down the number of connections. Scale up: When the pool has no free connections, pool will scale up by this quantity. Scale down: All the invalid and idle connections are removed, sometimes resulting in removing connections of quantity greater than this value. Steadypoolsize will be ensured. Possible values are from 0 to `MAX_INTEGER`. The default value is 2.

`--idletimeout`

The maximum time, in seconds, that a connection can remain idle in the pool. After this time, the implementation can close this connection. This timeout value must be kept shorter than the server side timeout value to prevent the accumulation of unusable connections in the application. The default value is 300.

`--initsql`

An SQL string that is executed whenever a connection is created from the pool. If an existing connection is reused, this string is not executed. This option has no default value.

--isolationlevel

The transaction-isolation-level on the pooled database connections. This option does not have a default value. If not specified, the pool operates with the default isolation level that the JDBC driver provides. You can set a desired isolation level using one of the standard transaction isolation levels: read-uncommitted, read-committed, repeatable-read, serializable. Applications that change the isolation level on a pooled connection programmatically risk polluting the pool. This could lead to program errors.

--isolationguaranteed

This is applicable only when a particular isolation level is specified for transaction-isolation-level. The default value is true.

This option assures that every time a connection is obtained from the pool, isolation level is set to the desired value. This could have some performance impact on some JDBC drivers. Administrators can set this to false when the application does not change

--isolationlevel before returning the connection.

--isconnectvalidatereq

If set to true, connections are validated or checked to see if they are usable before giving out to the application. The default value is false.

--validationmethod

The name of the validation table used to perform a query to validate a connection. Valid settings are: auto-commit, meta-data, table, or custom-validation. The default value is auto-commit.

--validationtable

The name of the validation table used to perform a query to validate a connection.

--failconnection

If set to true, all connections in the pool must be closed when a single validation check fails. The default value is false. One attempt is made to reestablish failed connections.

--allownoncomponentcallers

A pool with this property set to true can be used by non-Java EE components, that is, components other than EJBs or Servlets. The returned connection is enlisted automatically with the transaction context obtained from the transaction manager.

--nontransactionalconnections

A pool with this property set to true returns non-transactional connections. This connection does not get automatically enlisted with the transaction manager.

--validateatmostonceperiod

Specifies the time interval in seconds between successive request to validate a connection at most once. Setting this attribute to an appropriate value minimizes the number of validation requests by a connection. The default value is 0, which specifies that the connection is never validated.

--leaktimeout

Specifies the amount of time, in seconds, for which connection leaks in a connection pool are to be traced.

If connection leak tracing is enabled, you can use the Administration Console to enable monitoring of the JDBC connection pool to get statistics on the number of connection leaks. The default value is 0, which disables connection leak tracing.

--leakreclaim

Specifies whether leaked connections are restored to the connection pool after leak connection tracing is complete. Possible values are as follows:

false

Leaked connections are *not* restored to the connection pool (default).

true

Leaked connections are restored to the connection pool.

--creationretryattempts

Specifies the maximum number of times that Enterprise Server retries to create a connection if the initial attempt fails. The default value is 0, which specifies that Enterprise Server does not retry to create the connection.

--creationretryinterval

Specifies the interval, in seconds, between successive attempts to create a connection.

If **--creationretryattempts** is 0, the **--creationretryinterval** option is ignored. The default value is 10.

--sqltracelisteners

A list of one or more custom modules that provide custom logging of database activities. Each module must implement the `org.glassfish.api.jdbc.SQLTraceListener` public interface. This option has no default value.

--statementtimeout

Specifies the length of time in seconds after which a query that is not completed is terminated.

A query that remains incomplete for a long period of time might cause the application that submitted the query to hang. To prevent this occurrence, use this option set a timeout for all statements that will be created from the connection pool that you are creating. When creating a statement, Enterprise Server sets the `QueryTimeout` property on the statement to the length of time that is specified. The default value is -1, which specifies that incomplete queries are never terminated.

--lazyconnectionenlistment

Specifies whether a resource to a transaction is enlisted only when a method actually uses the resource. Possible values are as follows:

false

Resources to a transaction are always enlisted and *not* only when a method actually uses the resource (default).

true

Resources to a transaction are enlisted *only* when a method actually uses the resource.

--lazyconnectionassociation

Specifies whether a physical connection should be associated with the logical connection only when the physical connection is used, and disassociated when the transaction is completed. Such association and dissociation enable the reuse of physical connections. Possible values are as follows:

false

A physical connection is associated with the logical connection even before the physical connection is used, and is *not* disassociated when the transaction is completed (default).

true

A physical connection is associated with the logical connection only when the physical connection is used, and disassociated when the transaction is completed. The --lazyconnectionenlistment option must also be set to true.

--associatewiththread

Specifies whether a connection is associated with the thread to enable the thread to reuse the connection. If a connection is not associated with the thread, the thread must obtain a connection from the pool each time that the thread requires a connection. Possible values are as follows:

false

A connection is *not* associated with the thread (default).

true

A connection is associated with the thread.

--associatewiththreadconnectionscount

The maximum number of connections to associate with a thread. This value is used only if associatewiththread is true. The default value of this option is 1.

--driverclassname

The name of the vendor-supplied JDBC driver class. This driver should implement the `java.sql.Driver` interface.

--matchconnections

Specifies whether a connection that is selected from the pool should be matched with the resource adaptor. If all connections in the pool are identical, matching between connections and resource adaptors is not required. Possible values are as follows:

false

A connection should *not* be matched with the resource adaptor (default).

true

A connection should be matched with the resource adaptor.

--maxconnectionusagecount

Specifies the maximum number of times that a connection can be reused. When this limit is reached, the connection is closed. By limiting the maximum number of times that a connection can be reused, you can avoid statement leaks.

The default value is 0, which specifies no limit on the number of times that a connection can be reused.

--ping

Specifies if the pool is pinged during pool creation or reconfiguration to identify and warn of any erroneous values for its attributes. Default value is false.

--pooling

Specifies if connection pooling is enabled for the pool. The default value is true.

--statementcachesize

The number of SQL statements to be cached using the default caching mechanism (Least Recently Used). The default value is 0, which indicates that statement caching is not enabled.

--validationclassname

The name of the class that provides custom validation when the value of validationmethod is custom-validation. This class must implement the org.glassfish.api.jdbc.ConnectionValidation interface, and it must be accessible to the application server.

--wrapjdbcobjects

Specifies whether the pooling infrastructure provides wrapped JDBC objects to applications.

By providing wrapped JDBC objects, the pooling infrastructure prevents connection leaks by ensuring that applications use logical connections from the connection pool, not physical connections. The use of logical connections ensures that the connections are returned to the connection pool when they are closed. However, the provision of wrapped JDBC objects can impair the performance of applications.

The pooling infrastructure provides wrapped objects for implementations of the following interfaces in the JDBC API:

- java.sql.CallableStatement
- java.sql.DatabaseMetaData
- java.sql.PreparedStatement
- java.sql.ResultSet
- java.sql.Statement

Possible values of --wrapjdbcobjects are as follows:

false

The pooling infrastructure does *not* provide wrapped JDBC objects to applications. (default).

true

The pooling infrastructure provides wrapped JDBC objects to applications.

--description

Text providing details about the specified JDBC connection pool.

--property

Optional attribute name/value pairs for configuring the pool. The following properties are available:

user

Specifies the user name for connecting to the database.

password

Specifies the password for connecting to the database.

databaseName

Specifies the database for this connection pool.

serverName

Specifies the database server for this connection pool.

port

Specifies the port on which the database server listens for requests.

networkProtocol

Specifies the communication protocol.

roleName

Specifies the initial SQL role name.

datasourceName

Specifies an underlying XADataSource, or a ConnectionPoolDataSource if connection pooling is done.

description

Specifies a text description.

url

Specifies the URL for this connection pool. Although this is not a standard property, it is commonly used.

LazyConnectionEnlistment

Deprecated. Use the equivalent attribute. The default value is false.

LazyConnectionAssociation

Deprecated. Use the equivalent attribute. The default value is false.

AssociateWithThread

Deprecated. Use the equivalent attribute. The default value is false.

MatchConnections

Deprecated. Use the equivalent attribute. The default value is true.

Note – If an attribute name or attribute value contains a colon, the backslash (\) must be used to escape the colon in the name or value. Other characters might also require an escape character. For more information about escape characters in command options, see the [asadmin\(1M\)](#) man page.

--target

Do not specify this option. This option is retained for compatibility with other releases. If you specify this option, a syntax error does not occur. Instead, the subcommand runs successfully and the option is silently ignored.

Operands *connectionpoolid*

The name of the JDBC connection pool to be created.

Examples **EXAMPLE 1** Creating a JDBC Connection Pool

This example creates a JDBC connection pool named `sample_derby_pool`.

```
asadmin> create-jdbc-connection-pool
--host localhost --port 7070
--datasourceclassname org.apache.derby.jdbc.ClientDataSource
--restype javax.sql.XADataSource
--property portNumber=1527:password=APP:user=APP:serverName=
localhost:databaseName=sun-appserv-samples:connectionAttributes=\;
create\\=true sample_derby_pool
Command create-jdbc-connection-pool executed successfully
```

The escape character backslash (\) is used in the `--property` option to distinguish the semicolon (;). Two backslashes (\\) are used to distinguish the equal sign (=).

Exit Status	0	subcommand executed successfully
	1	error in executing the subcommand

See Also `delete-jdbc-connection-pool(1)`, `list-jdbc-connection-pools(1)`

[asadmin\(1M\)](#)

