Oracle® Clusterware

Installation Guide 11*g* Release 1 (11.1) for AIX Based Systems **B28258-07**

August 2010



Oracle Clusterware Installation Guide, 11g Release 1 (11.1) for AIX Based Systems

B28258-07

Copyright © 2007, 2010, Oracle and/or its affiliates. All rights reserved.

Primary Author: Douglas Williams

Contributing Authors: Mark Bauer, Namrata Bhakthavatsalam, Jonathan Creighton, Barb Lundhild, Saar Maoz, Sundar Matpadi, Markus Michalewicz, Hanlin Qian, Dipak Saggi, Ara Shakian

Contributors: David Austin, Tanya Bagerman, Aimee Cai, Sumanta Chatterjee, Tracy Chen, Larry Clarke, Sudip Datta, Dave Diamond, Richard Frank, Luann Ho, Julie Hu, Priyesh Jaiswal, Rajiv Jayaraman, Sameer Joshi, Sana Karam, Roland Knapp, George Kotsovolos, Raj Kumar, Ranjith Kundapur, Seshasai Koduru, Vivekananda Kolla, Ram Kumar, Sergio Leunissen, Karen Li, Rich Long, Allen Lui, Venkat Maddali, Arnab Maity, Ofir Manor, Sundar Matpadi, Louise Morin, Anil Nair, Shoko Nishijima, Matthew McKerley, Philip Newlan, Goran Olsson, Balaji Pagadala, Soma Prasad, Srinivas Poovala, Sandesh Rao, Sudheendra Sampath, Ghassan Salem, Arun Saral, Vishal Saxena, Sanjay Sharma, David Schreiner, Vivian Schupmann, Janelle Simmons, Khethavath P. Singh, Duane Smith, Malai Stalin, Janet Stern, Jason Straub, Eri Suzuki, Madhu Velukur, Nitin Vengurlekar, Sumana Vijayagopal, Ajesh Viswambharan, Rache Wang, Pierre Wagner, Sergiusz Wolicki, Bin Yan, Jun Yang, Sivakumar Yarlagadda, Gary Young, Shi Zhao, Ricky Zhu

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure the safe use of this software. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software in dangerous applications.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

This software and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Contents

WI	hat's New in Oracle Clusterware Installation and Configuration?	xii
1	Summary List: Installing Oracle Clusterware	
	Verify System Requirements	
	Check Network Requirements	
	Check Operating System Packages	
	Set Kernel Parameters	
	Configure Groups and Users	
	Create Directories	
	Configure Oracle Installation Owner Shell Limits	
	Configure SSH	
	Check Existing SSH Configuration on the System	
	Configure SSH on Cluster Member Nodes	
	Enable SSH User Equivalency on Cluster Member Nodes	
	Create Storage	
	Create Disk Partitions for ASM Disks, OCR Disks, and Voting Disks	
	Verify Oracle Clusterware Requirements with CVU	
	Install Oracle Clusterware Software	
	Prepare the System for Oracle RAC and ASM	1-8
2	Oracle Clusterware Preinstallation Tasks	
	Reviewing Upgrade Best Practices	2-1
	Logging In to a Remote System as root Using X Terminal	2-2
	Overview of Groups and Users for Oracle Clusterware Installations	2-3
	Creating Groups and Users for Oracle Clusterware	
	Understanding the Oracle Inventory Group	2-3
	Understanding the Oracle Inventory Directory	2-4
	Determining If the Oracle Inventory and Oracle Inventory Group Exists	
	Creating the Oracle Inventory Group If an Oracle Inventory Does Not Exist	2-5
	Creating the Oracle Clusterware User	2-5
	Example of Creating Users and Groups	
	Checking the Hardware Requirements	
	Checking the Network Requirements	

	IP Address Requirements	. 2-11
	Node Time Requirements	. 2-11
	Configuring the Network Requirements	. 2-12
	Checking the Software Requirements	. 2-12
	Tuning AIX System Environment	. 2-16
	Tuning Virtual Memory Manager (VMM)	. 2-16
	Increasing System Block Size Allocation	. 2-17
	Configuring Shell Limits	. 2-17
	Configuring User Process Parameters	. 2-18
	Configuring Network Tuning Parameters	. 2-18
	Configuring SSH on All Cluster Nodes	. 2-20
	Checking Existing SSH Configuration on the System	. 2-20
	Downloading and Installing SSH Filesets	. 2-20
	Configuring SSH on Cluster Member Nodes	. 2-21
	Enabling SSH User Equivalency on Cluster Member Nodes	. 2-23
	Setting Display and X11 Forwarding Configuration	. 2-25
	Preventing Oracle Clusterware Installation Errors Caused by stty Commands	
	Configuring Software Owner User Environments	
	Procedure for Configuring Oracle Software Owner Environments	
	Running the rootpre.sh Script	
	Requirements for Creating an Oracle Clusterware Home Directory	
	Understanding and Using Cluster Verification Utility	
	Entering Cluster Verification Utility Commands	
	Using CVU to Determine if Installation Prerequisites are Complete	
	Using the Cluster Verification Utility Help	
	Using Cluster Verification Utility with Oracle Database 10g Release 1 or 2	
	Verbose Mode and "Unknown" Output	
	Checking Oracle Clusterware Installation Readiness with CVU	
3	Oracle Real Application Clusters Preinstallation Tasks	
	Creating Standard Configuration Operating System Groups and Users	3-1
	Overview of Groups and Users for Oracle Database Installations	
	Creating Standard Operating System Groups and Users	
	Creating Custom Configuration Groups and Users for Job Roles	
	Overview of Creating Operating System Group and User Options Based on Job Roles	
	Creating Database Operating System Groups and Users with Job Role Separation	
	Understanding the Oracle Base Directory Path	
	Overview of the Oracle Base directory	
	Understanding Oracle Base and Oracle Clusterware Directories	
	Creating the Oracle Base Directory Path	
	Environment Requirements for Oracle Database and Oracle ASM Owners	
	Environment Requirements for Oracle Database and Oracle ASM Owners	. 5-11
4	Configuring Oracle Clusterware Storage	
	Reviewing Storage Options for Oracle Clusterware Files	4-1
	Overview of Storage Options	
	Checking for Available Shared Storage with CVU	
	Configuring Storage for Oracle Clusterware Files on a Supported Shared File System	

Requirements for Using a File System for Oracle Clusterware Files	4-
Checking NFS Mount and Buffer Size Parameters for Oracle Clusterware	4-
Creating Required Directories for Oracle Clusterware Files on Shared File	Systems 4-
Configuring Storage for Oracle Clusterware Files on Raw Devices	4-
Identifying Required Raw Partitions for Clusterware Files	4-
Configuring Raw Disk Devices for Oracle Clusterware Without HACMP of	or GPFS 4-
Configuring HACMP Multinode Disk Heartbeat (MNDHB) for Oracle Clu	
Configuring Raw Logical Volumes for Oracle Clusterware	4-1
Creating a Volume Group for Oracle Clusterware	4-1
Configuring Raw Logical Volumes in the New Oracle Clusterware Volume	
Importing the Volume Group on the Other Cluster Nodes	4-1
Activating the Volume Group in Concurrent Mode on All Cluster Nodes	4-1
Configuring Oracle Real Application Clusters Storage	
Reviewing Storage Options for Oracle Database and Recovery Files	
Overview of Oracle Database and Recovery File Options	
General Storage Considerations for Oracle RAC	
After You Have Selected Disk Storage Options	
Checking for Available Shared Storage with CVU	
Choosing a Storage Option for Oracle Database Files	
Configuring Storage for Oracle Database Files on a Supported Shared File S	ystem 5
Requirements for Using a File System for Oracle Database Files	
Deciding to Use NFS for Data Files	
Deciding to Use Direct NFS for Datafiles	
Enabling Direct NFS Client Oracle Disk Manager Control of NFS	5-
Disabling Direct NFS Client Oracle Disk Management Control of NFS	
Checking NFS Mount Buffer Size Parameters for Oracle RAC	5-
Creating Required Directories for Oracle Database Files on Shared File Sys	
Configuring Storage for Oracle Database Files on Shared Storage Devices	5-1
Planning Your Shared Storage Device Creation Strategy	
Identifying Required Shared Partitions for Database Files	5-1
Configuring Disks for Automatic Storage Management	5-1
Identifying Storage Requirements for Automatic Storage Management	5-1
Using an Existing Automatic Storage Management Disk Group	5-1
Configuring Database File Storage for Automatic Storage Management and	d Raw Devices 5-1
Configuring Database File Storage on Raw Devices	5-1
Identifying Required Raw Partitions for Database Files	5-2
Configuring Raw Disk Devices for Database File Storage Without HACMF	P or GPFS 5-2
Configuring Raw Logical Volumes for Database File Storage	
Creating a Volume Group for Database Files	
Creating Database File Raw Logical Volumes in the New Volume Group	
Importing the Database File Volume Group on the Other Cluster Nodes	
Activating the Database File Volume Group in Concurrent Mode on All Cl	
Desupport of the Database Configuration Assistant Raw Device Mapping Fi	
Checking the System Setup with CVU	

6	Installing Oracle Clusterware	
	Verifying Oracle Clusterware Requirements with CVU	. 6-1
	Interpreting CVU Messages About Oracle Clusterware Setup	. 6-2
	Preparing to Install Oracle Clusterware with OUI	. 6-4
	Installing Oracle Clusterware with OUI	. 6-7
	Running OUI to Install Oracle Clusterware	. 6-7
	Installing Oracle Clusterware Using a Cluster Configuration File	. 6-8
	Troubleshooting OUI Error Messages for Oracle Clusterware	
	Confirming Oracle Clusterware Function	. 6-9
7	Oracle Clusterware Postinstallation Procedures	
	Required Postinstallation Tasks	. 7-1
	Back Up the Voting Disk After Installation	
	Download and Install Patch Updates	. 7-1
	Recommended Postinstallation Tasks	. 7-2
	Back Up the root.sh Script	. 7-2
	Run CVU Postinstallation Check	. 7-2
8	Deinstallation of Oracle Clusterware	
	Deciding When to Deinstall Oracle Clusterware	. 8-1
	Relocating Single-instance ASM to a Single-Instance Database Home	. 8-1
	Removing Oracle Clusterware	. 8-2
	About the rootdelete.sh Script	. 8-2
	Example of the rootdelete.sh Parameter File	. 8-2
	About the rootdeinstall.sh Script	. 8-3
	Removing Oracle Clusterware	. 8-3
Α	Troubleshooting the Oracle Clusterware Installation Process	
	Install OS Watcher and RACDDT	A-1
	General Installation Issues	A-2
	Performing Cluster Diagnostics During Oracle Clusterware Installations	A-3
	Interconnect Errors	A-4
В	How to Perform Oracle Clusterware Rolling Upgrades	
	Back Up the Oracle Software Before Upgrades	B-1
	Restrictions for Clusterware Upgrades to Oracle Clusterware 11g	
	Verify System Readiness for Patchset and Release Upgrades	
	Installing a Patch Set On a Subset of Nodes	B-3
	Installing an Upgrade On a Subset of Nodes	B-4

Index

List of Tables

2–1 AIX Operating System Kernel Requirements	2-12
2–2 AIX APAR and Other Operating System Fixes	
2–3 Recommended Values for Virtual Memory Manager	
4–1 Supported Storage Options for Oracle Clusterware Files	
4–2 Shared File System Volume Size Requirements	
4–3 Raw Partitions Required for Oracle Clusterware Files on AIX	
5–1 Supported Storage Options for Oracle Database and Recovery Files	
5–2 Shared File System Volume Size Requirements	5-6
5–3 Shared Devices or Logical Volumes Required for Database Files on	AIX 5-11
5–4 Raw Partitions Required for Database Files on AIX	5-20
5–5 Raw Logical Volumes Required for Database Files	5-28
B–1 Minimum Oracle Clusterware Patch Levels Required for Rolling U	

Preface

Oracle Clusterware Installation Guide for AIX Based Systems explains how to install and configure Oracle Clusterware, and how to configure a server and storage in preparation for an Oracle Real Application Clusters installation.

This preface contains the following topics:

- Intended Audience
- Documentation Accessibility
- Related Documents
- Conventions

Intended Audience

Oracle Clusterware Installation Guide for AIX Based Systems provides configuration information for network and system administrators, and database installation information for database administrators (DBAs) who install and configure Oracle Clusterware.

For customers with specialized system roles who intend to install Oracle Real Application Clusters (Oracle RAC), this book is intended to be used by system administrators, network administrators, or storage administrators to complete the process of configuring a system in preparation for an Oracle Clusterware installation, and complete all configuration tasks that require operating system root privileges. When configuration and installation of Oracle Clusterware is completed successfully, a system administrator should only need to provide configuration information and to grant access to the database administrator to run scripts as root during Oracle RAC installation.

This guide assumes that you are familiar with Oracle database concepts. For additional information, refer to books in the Related Documents list.

Documentation Accessibility

Our goal is to make Oracle products, services, and supporting documentation accessible to all users, including users that are disabled. To that end, our documentation includes features that make information available to users of assistive technology. This documentation is available in HTML format, and contains markup to facilitate access by the disabled community. Accessibility standards will continue to evolve over time, and Oracle is actively engaged with other market-leading technology vendors to address technical obstacles so that our documentation can be

accessible to all of our customers. For more information, visit the Oracle Accessibility Program Web site at http://www.oracle.com/accessibility/.

Accessibility of Code Examples in Documentation

Screen readers may not always correctly read the code examples in this document. The conventions for writing code require that closing braces should appear on an otherwise empty line; however, some screen readers may not always read a line of text that consists solely of a bracket or brace.

Accessibility of Links to External Web Sites in Documentation

This documentation may contain links to Web sites of other companies or organizations that Oracle does not own or control. Oracle neither evaluates nor makes any representations regarding the accessibility of these Web sites.

Access to Oracle Support

Oracle customers have access to electronic support through My Oracle Support. For information, visit http://www.oracle.com/support/contact.html or visit http://www.oracle.com/accessibility/support.html if you are hearing impaired.

Related Documents

For more information, refer to the following Oracle resources:

Oracle Clusterware and Oracle Real Application Clusters Documentation

Most Oracle error message documentation is only available in HTML format. If you only have access to the Oracle Documentation media, then browse the error messages by range. When you find a range, use your browser's "find in page" feature to locate a specific message. When connected to the Internet, you can search for a specific error message using the error message search feature of the Oracle online documentation. However, error messages for Oracle Clusterware and Oracle RAC tools are included in *Oracle Clusterware Administration and Deployment Guide*, or *Oracle Real Application Clusters Administration and Deployment Guide*.

This installation guide reviews steps required to complete an Oracle Clusterware installation, and to perform preinstallation steps for Oracle RAC. If you intend to install Oracle Database or Oracle RAC, then review those installation guides for additional information.

Installation Guides

- Oracle Diagnostics Pack Installation Guide
- Oracle Database Installation Guide for AIX Based Systems
- Oracle Real Application Clusters Installation Guide for Linux and UNIX

Operating System-Specific Administrative Guides

- Oracle Clusterware Administration and Deployment Guide
- Oracle Database Administrator's Reference, 11g Release 1 (11.1) for UNIX Systems
- Oracle Database Platform Guide for Microsoft Windows

Oracle Real Application Clusters Management

Oracle Real Application Clusters Administration and Deployment Guide

- Oracle Database 2 Day + Real Application Clusters Guide
- Oracle Database 2 Day DBA
- Getting Started with the Oracle Diagnostics Pack

Generic Documentation

- Oracle Database New Features Guide
- Oracle Database Net Services Administrator's Guide
- Oracle Database Concepts
- Oracle Database Reference

Printed documentation is available for sale in the Oracle Store at the following Web site:

http://oraclestore.oracle.com/

To download free release notes, installation documentation, white papers, or other collateral, please visit the Oracle Technology Network (OTN). You must register online before using OTN; registration is free and can be done at the following Web site:

http://otn.oracle.com/membership/

If you already have a username and password for OTN, then you can go directly to the documentation section of the OTN Web site at the following Web site:

http://otn.oracle.com/documentation/

Oracle error message documentation is available only in HTML. You can browse the error messages by range in the Documentation directory of the installation media. When you find a range, use your browser's "find in page" feature to locate a specific message. When connected to the Internet, you can search for a specific error message using the error message search feature of the Oracle online documentation.

If you already have a username and password for OTN, then you can go directly to the documentation section of the OTN Web Site:

http://otn.oracle.com/documentation/

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
italic	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

What's New in Oracle Clusterware Installation and Configuration?

This section describes Oracle Database 11g release 1 (11.1) features as they pertain to the installation and configuration of Oracle Clusterware and Oracle Real Application Clusters (Oracle RAC) The topics in this section are:

- Changes in Installation Documentation
- Enhancements and New Features for Installation

Changes in Installation Documentation

With Oracle Database 11g release 1, Oracle Clusterware can be installed or configured as an independent product, and additional documentation is provided on storage administration. For installation planning, note the following documentation:

Oracle Database 2 Day + Real Application Clusters Guide

This book provides an overview and examples of the procedures to install and configure a two-node Oracle Clusterware and Oracle RAC environment.

Oracle Clusterware Installation Guide

This book (the guide that you are reading) provides procedures either to install Oracle Clusterware as a standalone product, or to install Oracle Clusterware with either Oracle Database, or Oracle RAC. It contains system configuration instructions that require system administrator privileges.

Oracle Real Application Clusters Installation Guide

This platform-specific book provides procedures to install Oracle RAC after you have completed successfully an Oracle Clusterware installation. It contains database configuration instructions for database administrators.

Oracle Database Storage Administrator's Guide

This book provides information for database and storage administrators who administer and manage storage, or who configure and administer Automatic Storage Management (ASM).

Oracle Clusterware Administration and Deployment Guide

This is the administrator's reference for Oracle Clusterware. It contains information about administrative tasks, including those that involve changes to operating system configurations and cloning Oracle Clusterware.

Oracle Real Application Clusters Administration and Deployment Guide

This is the administrator's reference for Oracle RAC. It contains information about administrative tasks. These tasks include database cloning, node addition and deletion, Oracle Cluster Registry (OCR) administration, use of SRVCTL and other database administration utilities, and tuning changes to operating system configurations.

Enhancements and New Features for Installation

The following is a list of enhancements and new features for Oracle Database 11*g* release 1 (11.1):

Oracle HTTP Server Update

To install Oracle HTTP Server, use the "Oracle Fusion Middleware Web Tier Utilities 11g (11.1.1.2.0)" media or download.

New SYSASM Privilege and OSASM operating system group for ASM Administration

This feature introduces a new SYSASM privilege that is specifically intended for performing ASM administration tasks. Using the SYSASM privilege instead of the SYSDBA privilege provides a clearer division of responsibility between ASM administration and database administration.

OSASM is a new operating system group that is used exclusively for ASM. Members of the OSASM group can connect as SYSASM using operating system authentication and have full access to ASM.

Summary List: Installing Oracle Clusterware

The following is a summary list of installation configuration requirements and commands. This summary is intended to provide an overview of the installation process.

In addition to providing a summary of the Oracle Clusterware installation process, this list also contains configuration information for preparing a system for Automatic Storage Management (ASM) and Oracle Real Application Clusters (Oracle RAC) installation.

1.1 Verify System Requirements

For more information, review Section 2.5, "Checking the Hardware Requirements."

Enter the following commands to check available memory:

```
# /usr/sbin/lsattr -E -l sys0 -a realmem
# /usr/sbin/lsps -a
```

The minimum required RAM is 1 GB, and the minimum required swap space is 1 GB. Oracle recommends that you set swap space to twice the amount of RAM for systems with 2 GB of RAM or less. For systems with 2 GB to 8 GB RAM, use swap space equal to RAM. For systems with over 8 GB RAM, use .75 times the size of RAM.

Verify the space available for Oracle Clusterware files using one of the following commands, depending on where you intend to place Oracle Clusterware files:

GPFS:

df -k

Raw Logical Volumes in Concurrent VG (HACMP); in the following example, the variable 1v_name is the name of the raw logical volume whose space you want to verify:

```
lslv lv_name
```

Raw hard disks; in the following example, the variable rhdisk# is the raw hard disk number that you want to verify, and the variable size_mb is the size in megabytes of the partition that you want to verify:

```
lsattr -El rhdisk# -a size_mb
```

If you use standard redundancy for Oracle Clusterware files, which is 2 Oracle Cluster Registry (OCR) partitions and 3 voting disk partitions, then you should have at least 1 GB of disk space available on separate physical disks reserved for Oracle Clusterware files. Each partition for the Oracle Clusterware files should be 256 MB in size.

The Oracle Clusterware home requires 2.6 GB of disk space.

df -k /tmp

Ensure that you have at least 400 MB of disk space in /tmp. If this space is not available, then increase the partition size, or delete unnecessary files in /tmp.

1.2 Check Network Requirements

For more information, review Section 2.6, "Checking the Network Requirements."

The following is a list of address requirements that you must configure on a domain name server (DNS), or configure in the /etc/hosts file for each cluster node:

- You must have three network addresses for each node:
 - A public IP address
 - A virtual IP address, which is used by applications for failover in the event of node failure
 - A private IP address, which is used by Oracle Clusterware and Oracle RAC for internode communication

- The virtual IP address has the following requirements:
 - The IP address and host name are currently unused (it can be registered in a DNS, but should not be accessible by a ping command)
 - The virtual IP address is on the same subnet as your public interface
- The private IP address has the following requirements:
 - It should be on a subnet reserved for private networks, such as 10.0.0.0 or 192.168.0.0
 - It should use dedicated switches or a physically separate, private network, reachable only by the cluster member nodes, preferably using high-speed **NICs**
 - It must use the same private interfaces for both Oracle Clusterware and Oracle RAC private IP addresses
 - It cannot be registered on the same subnet that is registered to a public IP address

After you obtain the IP addresses from a network administrator, you can use the utility system-config-network to assign the public and private IP addresses to NICs, or you can configure them manually using ifconfig. Do not assign the VIP address.

Ping all IP addresses. The public and private IP addresses should respond to ping commands. The VIP addresses should not respond.

1.3 Check Operating System Packages

Refer to the tables listed in Section 2.7, "Checking the Software Requirements" for details.

1.4 Set Kernel Parameters

For more information, review Section 2.8, "Tuning AIX System Environment."

1.5 Configure Groups and Users

the following sections in Chapter 2:

For more information, review Section 2.3, "Overview of Groups and Users for Oracle Clusterware Installations."

For information about creating Oracle Database homes, review the following sections in Chapter 3:

Section 3.1, "Creating Standard Configuration Operating System Groups and Users"

Section 3.2, "Creating Custom Configuration Groups and Users for Job Roles"

Section 3.5, "Environment Requirements for Oracle Database and Oracle ASM Owners"

For purposes of evaluation, we will assume that you have one Oracle installation owner, and that this oracle installation software owner name is oracle. You must create an Oracle installation owner group (oinstall) for Oracle Clusterware. If you intend to install Oracle Database, then you must create an OSDBA group (dba). Use the id oracle command to confirm the correct group and user configuration. Then use smit to create the oracle user, or enter commands similar to the following:

```
# mkgroup oinstall
```

mkgroup dba

mkuser pgrp=oinstall groups=dba,oinstall oracle

Ensure that the Oracle Clusterware oracle user has the capabilities CAP_NUMA_ ATTACH, CAP_BYPASS_RAC_VMM, and CAP_PROPAGATE.

To check existing capabilities, enter the following command as root; in this example, the Oracle Clusterware oracle user is crs:

```
# lsuser -a capabilities crs
```

To add capabilities, enter a command similar to the following:

```
# chuser capabilities=CAP_NUMA_ATTACH CAP_BYPASS_RAC_VMM CAP_PROPAGATE crs
```

Set the password on the oracle account:

```
passwd oracle
```

Repeat this process for each cluster member node.

1.6 Create Directories

For more information, review Section 2.12, "Requirements for Creating an Oracle Clusterware Home Directory"

For information about creating Oracle Database homes, review the following sections in Chapter 3:

Section 3.3, "Understanding the Oracle Base Directory Path"

Section 3.4, "Creating the Oracle Base Directory Path"

For installations with Oracle Clusterware only, Oracle recommends that you let Oracle Universal Installer (OUI) create the Oracle Clusterware and Oracle Central Inventory (oraInventory) directories for you. However, as root, you must create a path compliant with Oracle Optimal Flexible Architecture (OFA) guidelines, so that OUI

can select that directory during installation. For OUI to recognize the path as an Oracle software path, it must be in the form u0[1-9]/app.

For example:

```
mkdir -p /u01/app
chown -R oracle:oinstall /u01/app
```

1.7 Configure Oracle Installation Owner Shell Limits

For information, review the following section in Chapter 2:

Section 2.10, "Configuring Software Owner User Environments"

1.8 Configure SSH

the following section in Chapter 2:

For information, review Section 2.9, "Configuring SSH on All Cluster Nodes"

OUI uses the ssh and scp commands during installation to run remote commands on and copy files to the other cluster nodes. If SSH is not available, then OUI falls back to rsh and rcp commands. If you want to use SSH for increased security during installation, then you must configure SSH so that the ssh and scp commands used during installation do not prompt for a password.

To configure SSH, complete the following tasks:

1.8.1 Check Existing SSH Configuration on the System

To determine if SSH is running, enter the following command:

```
$ ps -ef | grep sshd
```

If SSH is running, then the response to this command is one or more process ID numbers. In the home directory of the software owner that you want to use for the installation (crs, oracle), use the command 1s -al to ensure that the .ssh directory is owned and writable only by the user.

1.8.2 Configure SSH on Cluster Member Nodes

Complete the following tasks on each node. You must configure SSH separately for each Oracle software installation owner that you intend to use for installation.

- Create .ssh, and create either RSA or DSA keys on each node
- Add all keys to a common authorized_keys file

1.8.3 Enable SSH User Equivalency on Cluster Member Nodes

After you have copied the authorized_keys file that contains all keys to each node in the cluster, start SSH on the node, and load SSH keys into memory. Note that you must either use this terminal session for installation, or reload SSH keys into memory for the terminal session from which you run the installation.

1.9 Create Storage

The following outlines the procedure for creating OCR and voting disk partitions, and creating ASM disks.

For information, review the following sections in Chapter 4:

Section 4.2, "Configuring Storage for Oracle Clusterware Files on a Supported Shared File System"

Section 4.3, "Configuring Storage for Oracle Clusterware Files on Raw Devices"

1.9.1 Create Disk Partitions for ASM Disks, OCR Disks, and Voting Disks

Create partitions as needed. For OCR and voting disks, create 280MB partitions for new installations, or use existing partition sizes for upgrades. To create partitions:

> **Note:** Every server running one or more database instances that use ASM for storage has an ASM instance. In an Oracle RAC environment, there is one ASM instance for each node, and the ASM instances communicate with each other on a peer-to-peer basis.

Only one ASM instance is permitted for each node regardless of the number of database instances on the node.

If you are upgrading an existing installation, then shut down ASM instances before starting installation, unless otherwise instructed in the upgrade procedure for your platform.

Identify or configure the required disk devices.

The disk devices must be shared on all of the cluster nodes.

As the root user, enter the following command on any node to identify the device names for the disk devices that you want to use:

```
# lspv | grep -i none
```

This command displays information similar to the following for each disk device that is not configured in a volume group:

```
hdisk17
                 0009005fb9c23648
                                                       None
```

In this example, hdisk17 is the device name of the disk and 0009005fb9c23648 is the physical volume ID (PVID).

If a disk device that you want to use does not have a PVID, then enter a command similar to the following to assign one to it:

```
# chdev -1 hdiskn -a pv=yes
```

Note: If you have an existing PVID, then chdev will overwrite the existing PVID, which will cause applications depending on the previous PVID to fail.

On each of the other nodes, enter a command similar to the following to identify the device name associated with each PVID on that node:

```
# lspv | grep -i "0009005fb9c23648"
```

The output from this command should be similar to the following:

hdisk18 0009005fb9c23648

In this example, the device name associated with the disk device (hdisk18) is different on this node.

- 5. If the device names are the same on all nodes, then enter commands similar to the following on all nodes to change the owner, group, and permissions on the character raw device files for the disk devices:
 - OCR device:

```
# chown root:oinstall /dev/rhdiskn
# chmod 640 /dev/rhdiskn
```

- Other devices:
 - # chown oracle:dba /dev/rhdiskn # chmod 660 /dev/rhdiskn
- **6.** If the device name associated with the PVID for a disk that you want to use is different on any node, then you must create a new device file for the disk on each of the nodes using a common unused name.

For the new device files, choose an alternative device file name that identifies the purpose of the disk device. The previous table suggests alternative device file names for each file. For database files, replace dbname in the alternative device file name with the name that you chose for the database in step 1.

Note: Alternatively, you could choose a name that contains a number that will never be used on any of the nodes, for example hdisk99.

To create a new common device file for a disk device on all nodes, perform these steps on each node:

a. Enter the following command to determine the device major and minor numbers that identify the disk device, where *n* is the disk number for the disk device on this node:

```
# ls -alF /dev/*hdiskn
```

The output from this command is similar to the following:

```
brw----- 1 root system
                         24,8192 Dec 05 2001 /dev/hdiskn
crw----- 1 root system 24,8192 Dec 05 2001 /dev/rhdiskn
```

In this example, the device file /dev/rhdiskn represents the character raw device, 24 is the device major number, and 8192 is the device minor number.

b. Enter a command similar to the following to create the new device file, specifying the new device file name and the device major and minor numbers that you identified in the previous step:

Note: In the following example, you must specify the character c to create a character raw device file.

```
# mknod /dev/ora_ocr_raw_256m c 24 8192
```

- **c.** Enter commands similar to the following to change the owner, group, and permissions on the character raw device file for the disk:
 - OCR:

```
# chown root:oinstall /dev/ora_ocr_raw_256m
# chmod 640 /dev/ora_ocr_raw_256m
```

Oracle Clusterware voting disk:

```
# chown oracle:dba /dev/ora_vote_raw_256m
# chmod 660 /dev/ora_vote_raw_256m
```

d. Enter a command similar to the following to verify that you have created the new device file successfully:

```
# ls -alF /dev | grep "24,8192"
```

The output should be similar to the following:

```
brw----- 1 root system 24,8192 Dec 05 2001 /dev/hdiskn
crw----- 1 root system 24,8192 Dec 05 2001 /dev/rhdiskn
```

To enable simultaneous access to a disk device from multiple nodes, you must set the appropriate Object Data Manager (ODM) attribute, depending on the type of reserve attribute used by your disks. The following section describes how to perform this task using hdisk logical names. Refer to your operating system documentation to find logical device names.

To determine the reserve setting your disks use, enter the following command, where *n* is the hdisk device number:

```
# lsattr -E -l hdiskn | grep reserve_
```

The response is either a reserve_lock setting, or a reserve_policy setting. If the attribute is reserve_lock, then ensure that the setting is reserve_lock = no. If the attribute is reserve policy, then ensure that the setting is reserve policy = no reserve.

If necessary, change the setting with the chdev command using the following syntax, where *n* is the hdisk device number:

```
chdev -l hdiskn -a [reserve_lock=no | reserve_policy=no_reserve]
```

For example, to change a setting for the device hdisk4 from reserve_lock=yes to reserve_lock=no, enter the following command:

```
# chdev -l hdisk4 -a reserve_lock=no
```

To verify that the setting is correct on all disk devices, enter the following command:

```
# lsattr -El hdiskn | grep reserve
```

8. Enter commands similar to the following on any node to clear the PVID from each disk device that you want to use:

```
# chdev -1 hdiskn -a pv=clear
```

When you are installing Oracle Clusterware, you must enter the paths to the appropriate device files when prompted for the path of the OCR and Oracle Clusterware voting disk, for example:

/dev/rhdisk10

1.10 Verify Oracle Clusterware Requirements with CVU

For information, review Section 6.1, "Verifying Oracle Clusterware Requirements with CVU."

Using the following command syntax, log in as the installation owner user (oracle or crs), and start Cluster Verification Utility (CVU) to check system requirements for installing Oracle Clusterware. In the following syntax example, replace the variable *mountpoint* with the installation media mountpoint, and replace the variable *node*_ *list* with the names of the nodes in your cluster, separated by commas:

/mountpoint/runcluvfy.sh stage -pre crsinst -n node_list

1.11 Install Oracle Clusterware Software

For information, review the following sections in Chapter 6:

Section 6.2, "Preparing to Install Oracle Clusterware with OUI"

Section 6.3, "Installing Oracle Clusterware with OUI"

- 1. Ensure SSH keys are loaded into memory for the terminal session from which you rn the Oracle Universal Installer (OUI).
- **2.** Navigate to the installation media, and start OUI. For example:

```
$ cd /Disk1
./runInstaller
```

3. Select Install Oracle Clusterware, and enter the configuration information as prompted.

1.12 Prepare the System for Oracle RAC and ASM

For information, review Section 5.6, "Configuring Disks for Automatic Storage Management."

If you intend to install Oracle RAC, as well as Oracle Clusterware, then Oracle recommends that you use ASM for database file management.

Oracle Clusterware Preinstallation Tasks

This chapter describes the system configuration tasks that you must complete before you start Oracle Universal Installer (OUI) to install Oracle Clusterware.

This chapter contains the following topics:

- **Reviewing Upgrade Best Practices**
- Logging In to a Remote System as root Using X Terminal
- Overview of Groups and Users for Oracle Clusterware Installations
- Creating Groups and Users for Oracle Clusterware
- Checking the Hardware Requirements
- Checking the Network Requirements
- Checking the Software Requirements
- Tuning AIX System Environment
- Configuring SSH on All Cluster Nodes
- Configuring Software Owner User Environments
- Running the rootpre.sh Script
- Requirements for Creating an Oracle Clusterware Home Directory
- Understanding and Using Cluster Verification Utility
- Checking Oracle Clusterware Installation Readiness with CVU

2.1 Reviewing Upgrade Best Practices

If you have an existing Oracle installation, then document version numbers, patches, and other configuration information, and review upgrade procedures for your existing installation. Review Oracle upgrade documentation before proceeding with installation, to decide how you want to proceed.

For late-breaking updates and best practices about preupgrade, post-upgrade, compatibility, and interoperability discussions, refer to "Oracle Upgrade Companion." "Oracle Upgrade Companion" is available through Note 466181.1 on OracleMetaLink:

https://metalink.oracle.com

2.2 Logging In to a Remote System as root Using X Terminal

Before you install the Oracle software, you must complete several tasks as the root user on the system where you install Oracle software. To complete tasks as the root user on a remote server, you need to enable remote display as root.

Note: If you log in as another user (for example, oracle), then you need to repeat this procedure for that user as well.

To enable remote display, complete one of the following procedures:

- If you are installing the software from an X Window System workstation or X terminal, then:
 - 1. Start a local terminal session, for example, an X terminal (xterm).
 - **2.** If you are not installing the software on the local system, then enter a command using the following syntax to enable remote hosts to display X applications on the local X server:

```
$ xhost + remote_host
```

where remote_host is the fully qualified remote hostname. For example:

```
$ xhost + somehost.example.com
somehost.example.com being added to the access control list
```

3. If you are not installing the software on the local system, then use the ssh, command to connect to the system where you want to install the software:

```
$ ssh remote_host
```

where remote_host is the fully qualified remote hostname. For example:

```
$ ssh somehost.example.com
```

4. If you are not logged in as the root user, then enter the following command to switch the user to root:

```
$ su - root
password:
```

If you are installing the software from a PC or other system with X server software installed, then:

Note: If necessary, refer to your X server documentation for more information about completing this procedure. Depending on the X server software that you are using, you may need to complete the tasks in a different order.

- **1.** Start the X server software.
- **2.** Configure the security settings of the X server software to permit remote hosts to display X applications on the local system.
- Connect to the remote system where you want to install the software and start a terminal session on that system, for example, an X terminal (xterm).

4. If you are not logged in as the root user on the remote system, then enter the following command to switch user to root:

```
$ su - root
password:
```

2.3 Overview of Groups and Users for Oracle Clusterware Installations

You must create the following group and user to install Oracle Clusterware:

The Oracle Inventory group (typically, oinstall)

You must create this group the first time that you install Oracle software on the system. In Oracle documentation, this group is referred to as oinstall.

Note: If Oracle software is already installed on the system, then the existing Oracle Inventory group must be the primary group of the operating system user (oracle or crs) that you use to install Oracle Clusterware. Refer to Section 2.4.5.1, "Determining if an Oracle Software Owner User Exists" to identify an existing Oracle Inventory group.

Oracle clusterware software owner user (typically, oracle, if you intend to create a single software owner user for all Oracle software, or crs, if you intend to create separate Oracle software owners.)

You must create at least one software owner the first time you install Oracle software on the system. This user owns the Oracle binaries of the Oracle Clusterware software, and you can also make this user the owner of the binaries of Automatic Storage Management and Oracle Database or Oracle RAC.

See Also: Oracle Database Administrator's Reference for UNIX Systems and Oracle Database Administrator's Guide for more information about the OSDBA and OSOPER groups and the SYSDBA, SYSASM and SYSOPER privileges

2.4 Creating Groups and Users for Oracle Clusterware

Log in as root, and use the following instructions to locate or create the Oracle Inventory group and a software owner for Oracle Clusterware:

- Understanding the Oracle Inventory Group
- Understanding the Oracle Inventory Directory
- Determining If the Oracle Inventory and Oracle Inventory Group Exists
- Creating the Oracle Inventory Group If an Oracle Inventory Does Not Exist
- Creating the Oracle Clusterware User
- **Example of Creating Users and Groups**

2.4.1 Understanding the Oracle Inventory Group

You must have a group whose members are given access to write to the Oracle Central Inventory (oraInventory). The Central Inventory contains the following:

- A registry of the Oracle home directories (Oracle Clusterware, Oracle Database, and Automatic Storage Management) on the system
- Installation logs and trace files from installations of Oracle software. These files are also copied to the respective Oracle homes for future reference.

Other metadata inventory information regarding Oracle installations are stored in the individual Oracle home inventory directories, and are separate from the Central Inventory.

2.4.2 Understanding the Oracle Inventory Directory

The first time you install Oracle software on a system, Oracle Universal Installer checks to see if you have created an Optimal Flexible Architecture (OFA) compliant path in the format u[01-09]/app, such as /u01/app, and that the user running the installation has permissions to write to that path. If this is true, then Oracle Universal Installer creates the Oracle Inventory directory in the path /u[01-09]/app/oraInventory. For example:

/u01/app/oraInventory

If you have set the environment variable \$ORACLE_BASE for the user performing the Oracle Clusterware installation, then OUI creates the Oracle Inventory directory in the path \$ORACLE_BASE/../oraInventory. For example, if \$ORACLE_BASE is set to opt/oracle/11, then the Oracle Inventory directory is created in the path /opt/oracle/oraInventory.

If you have created neither an OFA-compliant path nor set \$ORACLE_BASE, then the Oracle Inventory directory is placed in the home directory of the user that is performing the installation. For example:

/home/oracle/oraInventory

As this placement can cause permission errors during subsequent installations with multiple Oracle software owners, Oracle recommends that you either create an OFA-compliant installation path, or set an \$ORACLE_BASE environment path.

For new installations, Oracle recommends that you allow OUI to create the Central Inventory directory. By default, if you create an Oracle path in compliance with OFA structure, such as /u01/app, that is owned by an Oracle software owner, then the Central Inventory is created in the path u01/app/oraInventory using correct permissions to allow all Oracle installation owners to write to this directory.

2.4.3 Determining If the Oracle Inventory and Oracle Inventory Group Exists

When you install Oracle software on the system for the first time, OUI creates the oraInst.loc file. This file identifies the name of the Oracle Inventory group (typically, oinstall), and the path of the Oracle Central Inventory directory. An oraInst.loc file has contents similar to the following:

inventory_loc=central_inventory_location inst_group=group

In the preceding example, central_inventory_location is the location of the Oracle Central Inventory (oraInventory), and group is the name of the group that has permissions to write to the central inventory.

If you have an existing Oracle Inventory, then ensure that you use the same Oracle Inventory for all Oracle software installations, and ensure that all Oracle software users you intend to use for installation have permissions to write to this directory.

To determine if you have an Oracle Inventory on your system:

Enter the following command:

```
# more /etc/oraInst.loc
```

If the oraInst.loc file exists, then the output from this command is similar to the following:

```
inventory_loc=/u01/app/oracle/oraInventory
inst_group=oinstall
```

In the previous output example:

- The inventory_loc group shows the location of the Oracle Inventory
- The inst_group parameter shows the name of the Oracle Inventory group (in this example, oinstall).

2.4.4 Creating the Oracle Inventory Group If an Oracle Inventory Does Not Exist

If the oraInst.loc file does not exist, then create the Oracle Inventory group by entering a command similar to the following:

```
# mkgroup id=501 oinstall
```

The preceding command creates the group oinstall, with the group ID number 501.

2.4.5 Creating the Oracle Clusterware User

You must create a software owner for Oracle Clusterware in the following circumstances:

- If an Oracle software owner user does not exist; for example, if this is the first installation of Oracle software on the system
- If an Oracle software owner user exists, but you want to use a different operating system user, such as crs, with different group membership, to give separate clusterware and database administrative privileges to those groups in a new Oracle Clusterware and Oracle Database installation.

In Oracle documentation, a user created to own only Oracle Clusterware software installations is called the crs user. A user created to own either all Oracle installations, or only Oracle database installations, is called the oracle user.

Note: If you intend to use multiple Oracle software owners for different Oracle Database homes, then Oracle recommends that you create a separate Oracle software owner for Oracle Clusterware, and install Oracle Clusterware using the Oracle Clusterware software owner.

If you want to create separate Oracle software owners (oracle, crs, asm) to create separate users and separate operating system privileges groups for different Oracle software installations, then note that each of these users must have the oinstall group as their primary group, and each user must share the same Oracle Central Inventory, to prevent corruption of the Central Inventory. Refer to "Creating Custom Configuration Groups and Users for Job Roles" on page 3-3.

2.4.5.1 Determining if an Oracle Software Owner User Exists

To determine whether an Oracle software owner user named oracle or crs exists, enter a command similar to the following (in this case, to determine if oracle exists):

id oracle

If the user exists, then the output from this command is similar to the following:

```
uid=501(oracle) gid=501(oinstall) groups=502(dba),503(oper)
```

Determine whether you want to use the existing user, or create another user.

If you want to use the existing user, then ensure that the user's primary group is the Oracle Inventory group (oinstall).

2.4.5.2 Creating a Software Owner User for Oracle Clusterware

If the Oracle software owner (oracle, crs) user does not exist, or if you require a new Oracle software owner user, then create it. The following procedure uses crs as the name of the Oracle software owner.

1. Enter the following command:

```
# smit security
```

- **2.** On the **Security & Users** menu, select **Users**.
- 3. On the Users menu, select Add a User.
- 4. Choose the appropriate menu items to create the Oracle Clusterware user (crs or oracle). In the **Primary GROUP** field, specify the Oracle Inventory group. Make a note of the information you provide in the entry fields, so that you can provide the same value on other nodes.

Note: The UID and GID for the Oracle Clusterware user must be less than 65536.

- **5.** Press F10 to exit.
- **6.** Set the password of the Oracle Clusterware oracle user. For example:

```
# passwd crs
```

7. Ensure that the Oracle Clusterware oracle user has the capabilities CAP_ NUMA_ATTACH, CAP_BYPASS_RAC_VMM, and CAP_PROPAGATE.

To check existing capabilities, enter the following command as root; in this example, the Oracle Clusterware oracle user is crs:

```
# /usr/bin/lsuser -a capabilities crs
```

To add capabilities, enter a command similar to the following:

```
# /usr/bin/chuser
capabilities=CAP_NUMA_ATTACH, CAP_BYPASS_RAC_VMM, CAP_PROPAGATE crs
```

8. Repeat this procedure on all of the other nodes in the cluster.

2.4.5.3 Modifying an Existing Software Owner User

If the user account you want to use for Oracle Clusterware exists, but its primary group is not oinstall, then use the following procedure to modify the user to add groups:

1. Enter the following command:

```
# smit security
```

- **2.** Choose the appropriate menu items to modify the oracle user.
- 3. In the **Primary GROUP** field, specify the Oracle Inventory group, for example oinstall.
- **4.** Press F10 to exit.
- Repeat this procedure on all of the other nodes in the cluster.

2.4.6 Example of Creating Users and Groups

The following is an example of how to create the Oracle Clusterware software owner (in this case, crs), and a path compliant with OFA structure with correct permissions for the oral nventory directory. This example also shows how to create separate Oracle Database and Oracle ASM homes with correct ownership and permissions, and how to create separate operating system groups for Oracle ASM, Oracle Clusterware, and Oracle Database system privileges:

```
# groupadd -g 1000 oinstall
# groupadd -g 1100 asmadmin
# groupadd -g 1200 dba
# groupadd -g 1300 asmdba
# groupadd -g 1301 asmoper
# useradd -u 1100 -g oinstall -G asmadmin,asmdba,asmoper crs
# useradd -u 1101 -g oinstall -G dba,asmdba oracle
# useradd -u 1102 -g oinstall -G asmadmin,asmdba,asmoper asm
# mkdir -p /u01/app/crs
# chown -R crs:oinstall /u01
# mkdir -p /u01/app/oracle
# chown oracle:oinstall /u01/app/oracle
# chmod -R 775 /u01
# mkdir /u01/app/asm
# chown asm:oinstall /u01/app/asm
```

At the end of this procedure, you will have the following:

- /u01 owned by root.
- /u01/app owned by crs:oinstall with 775 permissions. This ownership and permissions enables OUI to create the oralnventory directory, in the path /u01/app/oraInventory.
- /u01/app/crs owned by crs:oinstall with 775 permissions. These permissions are required for installation, and are changed during the installation process.
- /u01/app/oracle owned by oracle:oinstall with 775 permissions.
- /u01/app/asm owned by asm: oinstall with 775 permissions.

2.5 Checking the Hardware Requirements

Each system must meet the following minimum hardware requirements:

- At least 1 GB of physical RAM
- Swap space equivalent to the multiple of the available RAM, using the following table as a guideline:

Available RAM	Swap Space Required
Between 1 GB and 2 GB	1.5 times the size of RAM
Between 2 GB and 8 GB	Equal to the size of RAM
More than 8 GB	.75 times the size of RAM

On AIX systems with 1 GB or more of memory, Oracle recommends that you set the paging space to an initial setting of half the size of RAM plus 4 GB, with an upper limit of 32 GB. During installation, to optimize paging, monitor the paging space use in a separate window. Use the command 1sps -a to increase or decrease the paging space size. The output of lsps -a should indicate paging space use of less than 25 percent on a healthy system. Refer to Oracle Database Administrator's Reference for AIX for more information about configuring paging space.

- 400 MB of disk space in the /tmp directory
- 2 GB of disk space for Oracle Clusterware files, in partitions on separate physical disks, assuming standard redundancy (2 Oracle Cluster Registry partitions and 3 voting disks)
- 2.6 GB of disk space for the Oracle Clusterware home and log files
- 7.5 GB of disk space for the Oracle Database files (Oracle base)
- 2 GB of disk space for a preconfigured database that uses file system storage (optional)

Note: The disk space requirement for databases that use Automatic Storage Management or raw device storage is described in Chapter 4.

Additional disk space, either on a file system or in an Automatic Storage Management disk group, is required for the Fast recovery area if you choose to configure automated backups.

To ensure that each system meets these requirements, follow these steps:

1. To determine the physical RAM size, enter the following command:

```
# /usr/sbin/lsattr -E -l sys0 -a realmem
```

If the size of the physical RAM installed in the system is less than the required size, then you must install more memory before continuing.

2. To determine the available RAM and swap space, enter the following command:

```
# /usr/sbin/lsps -s
```

3. To determine the size of the configured swap space, enter the following command:

```
# /usr/sbin/lsps -a
```

If necessary, refer to your operating system documentation for information about how to configure additional swap space.

To determine the amount of disk space available in the /tmp directory, enter the following command:

```
# df -k /tmp
```

If there is less than 400 MB of disk space available in the /tmp directory, then complete one of the following steps:

- Delete unnecessary files from the /tmp directory to make available the disk space required.
- Set the TEMP and TMPDIR environment variables when setting the oracle user's environment (described later).
- Extend the file system that contains the /tmp directory. If necessary, contact your system administrator for information about extending file systems.
- To determine the amount of free disk space on the system, use one of the following commands, depending on where you intend to place Oracle Clusterware files:

GPFS:

```
# df -k
```

Raw Logical Volumes in Concurrent VG (HACMP); in the following example, the variable 1v_name is the name of the raw logical volume whose space you want to verify:

```
# lslv lv_name
```

Raw hard disks; in the following example, the variable rhdisk# is the raw hard disk number that you want to verify, and the variable size_mb is the size in megabytes of the partition that you want to verify:

```
# lsattr -El rhdisk# -a size_mb
```

The following table shows the approximate disk space requirements for software files for each installation type:

Installation Type	Requirement for Software Files (GB)
Enterprise Edition	4 GB
Standard Edition	4 GB
Custom (maximum)	4 GB

To determine if the system architecture can run the software, enter the following command:

```
# getconf HARDWARE_BITMODE
```

Note: The expected output of this command is 64. If you do not see the expected output, then you cannot install the software on this system.

7. To determine if the system is started in 64-bit mode, enter the following command:

bootinfo -K

The result of this command should be 64, indicating that the 64-bit kernel is

2.6 Checking the Network Requirements

Check that you have the networking hardware and internet protocol (IP) addresses required for an Oracle Real Application Clusters installation.

Note: For the most up-to-date information about supported network protocols and hardware for Oracle Clusterware installations, refer to the Certify pages on the Oracle MetaLink Web site at

https://metalink.oracle.com

Network Hardware Requirements

Each node in the cluster must meet the following requirements:

- Each node must have at least two network adapters: one for the public network interface, and one for the private network interface (the interconnect).
- The public interface names associated with the network adapters for each network must be the same on all nodes, and the private interface names associated with the network adaptors should be the same on all nodes.
 - For example: With a two-node cluster, you cannot configure network adapters on node1 with en0 as the public interface, but on node2 have en1 as the public interface. Public interface names must be the same, so you must configure en0 as public on both nodes. You should configure the private interfaces on the same network adapters as well. If en1 is the private interface for node 1, then en1 should be the private interface for node 2.
- For increased reliability, configure redundant public and private network adapters for each node.
- For the public network, each network adapter must support TCP/IP.
- For the private network, the interconnect must support the user datagram protocol (UDP) using high-speed network adapters and switches that support TCP/IP (Gigabit Ethernet or better recommended).

Note: UDP is the default interconnect protocol for Oracle RAC, and TCP is the interconnect protocol for Oracle Clusterware.

Token-Ring is not supported for the interconnect.

For the private network, the endpoints of all designated interconnect interfaces must be completely reachable on the network. There should be no node that is not connected to every private network. You can test whether an interconnect interface is reachable using a ping command.

2.6.1 IP Address Requirements

Before starting the installation, you must have the following IP addresses available for each node:

- An IP address with an associated network name registered in the domain name service (DNS) for the public interface. If you do not have an available DNS, then record the network name and IP address in the system hosts file, /etc/hosts.
- One virtual IP (VIP) address with an associated network name registered in DNS. If you do not have an available DNS, then record the network name and VIP address in the system hosts file, /etc/hosts. Select an address for your VIP that meets the following requirements:
 - The IP address and network name are currently unused
 - The VIP is on the same subnet as your public interface

Before installation, check that the default gateway can be accessed by a ping command. During installation, OUI uses the ping command to ensure that the VIP is reachable. To find the default gateway, use the route command, as described in your operating system's help utility. After installation, configure clients to use either the VIP address, or the network name associated with the VIP. If a node fails, then the node's virtual IP address fails over to another node.

A private IP address with a host name for each private interface

Oracle recommends that you use private network IP addresses for these interfaces (for example: 10.*.*.* or 192.168.*.*). Use the /etc/hosts file on each node to associate private network names with private IP addresses.

For example, with a two node cluster where each node has one public and one private interface, you might have the configuration shown in the following table for your network interfaces, where the hosts file is /etc/hosts:

Node	Interface Name	Туре	IP Address	Registered In
rac1	rac1	Public	143.46.43.100	DNS (if available, else the hosts file)
rac1	rac1-vip	Virtual	143.46.43.104	DNS (if available, else the hosts file)
rac1	rac1-priv	Private	10.0.0.1	Hosts file
rac2	rac2	Public	143.46.43.101	DNS (if available, else the hosts file)
rac2	rac2-vip	Virtual	143.46.43.105	DNS (if available, else the hosts file)
rac2	rac2-priv	Private	10.0.0.2	Hosts file

To enable VIP failover, the configuration shown in the preceding table defines the public and VIP addresses of both nodes on the same subnet, 143.46.43. When a node or interconnect fails, then the associated VIP is relocated to the surviving instance, enabling fast notification of the failure to the clients connecting through that VIP. If the application and client are configured with transparent application failover options, then the client is reconnected to the surviving instance.

2.6.2 Node Time Requirements

Before starting the installation, ensure that each member node of the cluster is set as closely as possible to the same date and time. Oracle strongly recommends using the Network Time Protocol feature of most operating systems for this purpose, with all nodes using the same reference Network Time Protocol server.

2.6.3 Configuring the Network Requirements

To verify that each node meets the requirements, follow these steps:

- If necessary, install the network adapters for the public and private networks and configure them with either public or private IP addresses.
- Register the host names and IP addresses for the public network interfaces in DNS.
- For each node, register one virtual host name and IP address in DNS.
- For each private interface on every node, add a line similar to the following to the /etc/hosts file on all nodes, specifying the private IP address and associated private host name:

```
10.0.0.1
             rac1-priv1
```

5. To identify the interface name and associated IP address for every network adapter, enter the following command:

```
# netstat -i
```

From the output, identify the interface name and IP address for all network adapters that you want to specify as public or private network interfaces.

Note: When you install Oracle Clusterware and RAC, you will require this information.

2.7 Checking the Software Requirements

Depending on the products that you intend to install, verify that the following software is installed on the system. The procedure following the table describes how to verify whether these requirements are addressed.

Note: Oracle Universal Installer performs checks on your system to verify that it meets the listed requirements. Check Oracle Certify for the most recent updates at the following URL:

https://metalink.oracle.com

Table 2–1 AIX Operating System Kernel Requirements

Item	Requirement
Operating systems	AIX 6L version 6.1 (64-bit), TL01-SP01 (NOTE: AIX6.1-TL0-SP04 is not supported, due to an operating system bug)
	AIX 5L version 5.3 (64-bit) TL 05, Service Pack 06 or later

Table 2–1 (Cont.) AIX Operating System Kernel Requirements

Item

Requirement

AIX 6L operating system filesets

The following operating system filesets are required:

bos.adt.lib bos.adt.libm

bos.perf.libperfstat bos.perf.perfstat bos.perf.proctools rsct.basic.rte

rsct.compat.clients.rte

xlC.aix61.rte:9.0.0.1 (or later) xlC.rte:9.0.0.1 (or later)

You must have the xIC C/C++ runtime filesets for installation, but you do not require the C/C++ compilers. You do not require a license for the xlC runtime filesets

AIX 5L operating system filesets

The following operating system filesets are required:

bos.adt.base bos.adt.lib bos.adt.libm

bos.perf.libperfstat bos.perf.perfstat bos.perf.proctools rsct.basic.rte

rsct.compat.clients.rte xlC.aix50.rte 8.0.0.7 (or later)

xlC.rte 8.0.0.7 (or later)

You must have the xlC C/C++ runtime filesets for installation, but you do not require the C/C++ compilers. You do not require a license for the xlC runtime filesets

Obtaining C/C++ Compilers

To obtain the XLC runtime filesets, Oracle Database users who do not install the IBM XL C/C++ Enterprise Edition V8.0 or V9.0 compiler should install the IBM XL C/C++ Enterprise Edition V8.0 for AIX Runtime Environment Component. For AIX5L, this contains xLC.aix.rte 8.0.0.8 and xlC.rte 8.0.0.8.

Download the C/C++ compiler from the following Web site:

http://www-1.ibm.com/support/docview.wss?uid=swg 24015075

Download the C runtime environment file sets, with no license requirement, from the following Web site:

http://www-1.ibm.com/support/docview.wss?uid=swg 24015077

Table 2-1 (Cont.) AIX Operating System Kernel Requirements

Item	Requirement				
Oracle RAC	High Availability Cluster Multi-Processing (HACMP) v5.4.1 (with AIX 6.1)				
	High Availability Cluster Multi-Processing (HACMP) v5.3 (with AIX 5L				
	Note: HACMP is required only if you want to use raw logical volumes for Oracle Clusterware or database file storage. However, it is supported for all installations. Review patch sets to ensure that you have required patches. Changes in the fileset packaging of HACMP 5.4, including 5.4.1, require updates to the Oracle rootpre.sh script. Download and install patch 6718715 before installing Oracle Clusterware.				
	General Parallel File System (GPFS) v3.1.0.10 or later.				
	Note: GPFS is required only if you want to use a cluster file system for Oracle Clusterware or database files.				
ADA	OC Systems PowerAda 5.4d				
JDK	IBM JDK 1.5 is installed with this release.				
Pro*FORTRAN	IBM XL Fortran v. 10.1 for AIX				
Pro*C/C++, Oracle Call Interface, Oracle C++ Call Interface,	Note: If you do not install the $C/C++$ compilers, then you require the $C/C++$ runtime filesets for installation as described in the "Operating system filesets" row in this table.				
Oracle XML Developer's Kit (XDK), GNU Compiler Collection (GCC)	■ February 2007 XL C/C++ Enterprise Edition V8.0 for AIX PTF 8.0:				
concenen (ecc)	You can download the PTF from the following link:				
	http://www-1.ibm.com/support/docview.wss?uid=swg24015075				
	Download the C++ runtime environment file sets, with no license requirement, from the following Web site:				
	<pre>http://www-1.ibm.com/support/docview.wss?uid= swg24015077</pre>				
	■ gcc 3.45				
Pro*COBOL	■ AcuCobol 6.1				
	■ Micro Focus Server Express 5.0 (Both 32-bit and 64-bit)				
Oracle Messaging Gateway	IBM WebSphere MQ V6.0, client and server:				
	mqm.Client.Bnd mqm.Server.Bnd				

To ensure that the system meets these requirements:

1. To determine the version of AIX installed, enter the following command:

```
# oslevel -r
```

If the operating system version is lower than AIX 5.3, then upgrade your operating system to at least this maintenance level. AIX 5L version 5.3 maintenance packages are available from the following Web site:

```
http://www-912.ibm.com/eserver/support/fixes/
```

2. To determine whether the required filesets are installed and committed, enter a command similar to the following:

```
# lslpp -1 bos.adt.base bos.adt.lib bos.adt.libm bos.perf.perfstat \
```

bos.perf.libperfstat bos.perf.proctools rsct.basic.rte

If a fileset is not installed and committed, then install it. Refer to your operating system or software documentation for information about installing filesets.

Verify that the following patches are installed on the system. The procedure following the table describes how to check these requirements

Note: There may be more recent versions of the patches listed installed on your system. If a listed patch is not installed, then determine if you have a more recent patch installed that includes the listed patch before you install the patch version listed.

Table 2–2 AIX APAR and Other Operating System Fixes

Installation Type or Product	Requirement	
All AIX 5L v5.3 installations	All AIX 5L v. 5.3 installations Authorized Problem Analysis Reports (APARs) for AIX 5L v. 5.3 ML06, and the following AIX fixes:	
	IY89080 IY92037 IY94343 IZ01060, or efix for IZ01060 IZ03260, or efix for IZ03260	
Oracle ODBC Drivers	You do not require ODBC drivers for Oracle Clusterware or Oracle Database.	
	To use ODBC with Oracle Database, you must also install gcc 3.4.5 or later.	
	Oracle ODBC driver on AIX is certified with ODBC Driver Manager 2.2.12. You can download and install the Driver Manager from the following link:	
	http://www.unixodbc.org	
Oracle JDBC/OCI Drivers AIX 5L v5.3	Note: These APARs are required only if you are using the associated JDK version.	
	APAR required for JDK 1.4.2 (64-bit):	
	■ IY63533: JDK 1.4.2 64-bit SR1 caix64142-20040917	
	APARs required for JDK 1.3.1.16 (32-bit):	
	■ IY58350: SDK 1.3.1 32-Bit SR7P: CA131IFX-20040721A	
	■ IY65305: JAVA142 32-bit PTF: CA142IFX-20041203	
RAC AIX 5L v5.3	If you use HACMP, then note the following additional requirements:	
THAT VOL.	■ AIX: AIX 5.3 TL06 or newer (bosrte.lvm must be at least 5.3.0.60)	
	 HACMP: Ensure the following versions are installed: 	
	* HACMP v. 5.3 with PTFS (APAR:IY94307) and cluster.es.clvm installed	
	* HACMP APAR: IZ01809	
	■ RSCT (component of AIX): RSCT (rsct.basic.rte) version 2.4.7.3	
	APARs required for GPFS v3.1.0.10:	
	None.	

To ensure that the system meets these requirements:

1. To determine if required APARs are installed, enter a command similar to the following:

```
# instfix -i -k "IY92312 IY97156 IY76252 IY94335 IY94334"
```

If an APAR is not installed, then download it from the following Web site and install it:

http://www-03.ibm.com/servers/eserver/support/pseries/aixfixes.html

2. To determine whether a PTF is installed, enter a command similar to the following:

```
# lslpp -1 -B U489726 U485561 ...
```

If a PTF is not installed, then download it from the following Web site and install

http://www-03.ibm.com/servers/eserver/support/pseries/aixfixes.html

3. If you require a CSD for WebSphere MQ, then refer to the following Web site for download and installation information:

http://www-306.ibm.com/software/

2.8 Tuning AIX System Environment

Perform the following system tuning and configuration all cluster nodes.

- Tuning Virtual Memory Manager (VMM)
- Increasing System Block Size Allocation
- Configuring Shell Limits
- Configuring User Process Parameters
- Configuring Network Tuning Parameters

Note: The parameter and shell limit values shown in this section are recommended values only. For production database systems, Oracle recommends that you tune these values to optimize the performance of the system. See your operating system documentation for more information about tuning kernel parameters.

2.8.1 Tuning Virtual Memory Manager (VMM)

Oracle recommends that you use the vmo command to tune virtual memory using the following values:

Table 2–3 Recommended Values for Virtual Memory Manager

Parameter	Value	
minperm%	3 (default is 20)	
maxperm%	90 (default is 80)	
maxclient% = 90	90 (default is 80)	

Table 2-3 (Cont.) Recommended Values for Virtual Memory Manager

Parameter	Value	
lru_file_repage	0 (default is 1)	
strict_maxclient	1 (default is 1)	
strict_maxperm	0 (default is 0)	

For example:

```
vmo -p -o minperm%=3
vmo -p -o maxperm%=90
vmo -p -o maxclient%=90
vmo -p -o lru_file_repage=0
vmo -p -o strict_maxclient=1
vmo -p -o strict_maxperm=0
```

You must restart the system for these changes to take effect.

2.8.2 Increasing System Block Size Allocation

Oracle recommends that you increase the space allocated for ARG/ENV list to 128. The size is specified by number of 4K blocks.

For example:

```
chdev -1 sys0 -a ncargs='128'
```

2.8.3 Configuring Shell Limits

To improve the performance of the software, you must increase the following shell limits for all Oracle software installation owners (oracle, crs) and for the root user (root):

Shell Limit	Item in limits.conf	Hard Limit
Maximum number of open file descriptors	nofile	65536
Maximum number of processes available to a single user	maxuproc	16384

To increase the shell limits:

1. Add the following lines to the /etc/security/limits file:

```
default:
        fsize = -1
        core = -1
        cpu = -1
        data = 512000
        rss = 512000
        stack = 512000
        nofiles = 2000
```

2. Enter the following command to list the current setting for the maximum number of process allowed by the Oracle software user:

```
/etc/lsattr -E -l sys0 -a maxuproc
```

If necessary, change the maxuproc setting using the following command:

/etc/chdev -1 sys0 -a maxuproc = 16384

3. Repeat this procedure on all other nodes in the cluster.

2.8.4 Configuring User Process Parameters

Verify that the maximum number of processes allowed for each user is set to 2048 or greater:

Note: For production systems, this value should be at least 128 plus the sum of the PROCESSES and PARALLEL_MAX_SERVERS initialization parameters for each database running on the system.

1. Enter the following command:

smit chgsys

2. Verify that the value shown for Maximum number of PROCESSES allowed for each user is greater than or equal to 2048.

If necessary, edit the existing value.

3. When you have finished making changes, press F10 to exit.

2.8.5 Configuring Network Tuning Parameters

Verify that the network tuning parameters shown in the following table are set to the values shown or higher values. The procedure following the table describes how to verify and set the values.

Network Tuning Parameter	Recommended Value	
ipqmaxlen	512	
	312	
rfc1323	1	
sb_max	2*65536	
tcp_recvspace	65536	
tcp_sendspace	65536	
udp_recvspace	655360	
	Note: The recommended value of this parameter is 10 times the value of the udp_sendspace parameter. The value must be less than the value of the sb_max parameter.	
udp_sendspace	ice 65536	
	Note: This value is suitable for a default database installation. For production databases, the minimum value for this parameter is 4 KB plus the value of the database DB_BLOCK_SIZE initialization parameter multiplied by the value of the DB_MULTIBLOCK_READ_COUNT initialization parameter:	
	(DB_BLOCK_SIZE * DB_MULTIBLOCK_READ_COUNT) + 4 KB	

To view the current value specified for these parameters, and to change them if necessary:

1. To check the current values of the network tuning parameters, enter commands similar to the following:

```
# no -a | more
```

2. If you must change the value of any parameter, then enter the following command to determine whether the system is running in compatibility mode:

```
# lsattr -E -l sys0 -a pre520tune
```

If the system is running in compatibility mode, then the output is similar to the following, showing that the value of the pre520tune attribute is enable:

```
pre520tune enable Pre-520 tuning compatibility mode True
```

- If the system is running in compatibility mode, then follow these steps to change the parameter values:
 - **a.** Enter commands similar to the following to change the value of each parameter:

```
# no -o parameter_name=value
```

For example:

```
# no -o udp_recvspace=655360
```

b. Add entries similar to the following to the /etc/rc.net file for each parameter that you changed in the previous step:

```
if [ -f /usr/sbin/no ] ; then
  /usr/sbin/no -o udp sendspace=65536
  /usr/sbin/no -o udp_recvspace=655360
  /usr/sbin/no -o tcp_sendspace=65536
  /usr/sbin/no -o tcp_recvspace=65536
  /usr/sbin/no -o rfc1323=1
  /usr/sbin/no -o sb_max=2*655360
  /usr/sbin/no -o ipqmaxlen=512
fi
```

By adding these lines to the /etc/rc.net file, the values persist when the system restarts.

- If the system is not running in compatibility mode, then enter commands similar to the following to change the parameter values:
 - ipqmaxlen parameter:

```
no -r -o ipqmaxlen=512
```

Other parameter:

```
no -p -o parameter=value
```

Note: If you modify the ipqmaxlen parameter, then you must restart the system.

These commands modify the /etc/tunables/nextboot file, causing the attribute values to persist when the system restarts.

2.9 Configuring SSH on All Cluster Nodes

Before you install and use Oracle Clusterware, you must configure secure shell (SSH) on all cluster nodes for the user that you plan to use to install Oracle Clusterware. In the examples that follow, the Oracle software owner listed is the crs user.

If you intend to install Oracle RAC or other Oracle software, then you should configure SSH for each of the other users (oracle, asm or other software owner) that you plan to use to install software, and either do not use a passphrase, or ensure that you and other installation users load SSH keys into memory before running the installation. As you perform this procedure, replace the example with the user name for which you are configuring SSH.

OUI uses the ssh and scp commands during installation to run remote commands on and copy files to the other cluster nodes. If SSH is not available, then OUI falls back to rsh and rcp commands. If you want to use SSH for increased security during installation, then you must configure SSH so that the ssh and scp commands used during installation do not prompt for a password. The SSH configuration procedure in this section describes how to configure SSH using SSH1.

This section contains the following sections:

- Checking Existing SSH Configuration on the System
- Downloading and Installing SSH Filesets
- Configuring SSH on Cluster Member Nodes
- Enabling SSH User Equivalency on Cluster Member Nodes
- Setting Display and X11 Forwarding Configuration
- Preventing Oracle Clusterware Installation Errors Caused by stty Commands

2.9.1 Checking Existing SSH Configuration on the System

To determine if SSH is running, enter the following command:

```
$ ps -ef | grep sshd
```

If SSH is running, then the response to this command is one or more process ID numbers. In the home directory of the software owner that you want to use for the installation (crs, oracle), use the command 1s -al to ensure that the .ssh directory is owned and writable only by the user.

You need either an RSA or a DSA key for the SSH protocol. RSA is used with the SSH 1.5 protocol, while DSA is the default for the SSH 2.0 protocol. With OpenSSH, you can use either RSA or DSA. The instructions that follow are for SSH1. If you have an SSH2 installation, and you cannot use SSH1, then refer to your SSH distribution documentation to configure SSH1 compatibility or to configure SSH2 with DSA.

2.9.2 Downloading and Installing SSH Filesets

Install the OpenSSL package in the AIX bonus package installation disks, or download OpenSSL from the following URL:

```
http://www-306.ibm.com/software/
```

You require an IBM ID or Partner World ID to access this site.

- Install the following file sets from the AIX Base installation media:
 - openssh.base

- openssh.license
- openssh.msg.en_US
- openssh.man.en US

You can also obtain filesets from the following URL:

http://sourceforge.net/projects/openssh-aix

3. Start the sshd daemon by running the following command:

```
/usr/bin/startsrc -s sshd
```

Note: If the AIX server on which OpenSSH is installed also has GSA installed, then the SSH daemon will not start. This is a known problem.

To resolve this issue, check to see if the sshd user exists on the system. If not, then create it using the following commands:

```
mkuser -a pgrp=sshd login=false home=/var/empty gecos="OpenSSH\
privilege separation" account_locked=true sshd
```

2.9.3 Configuring SSH on Cluster Member Nodes

To configure SSH, you must first create RSA or DSA keys on each cluster node, and then copy all the keys generated on all cluster node members into an authorized keys file that is identical on each node. Note that the SSH files must be readable only by root and by the software installation user (oracle, crs, asm), as SSH ignores a private key file if it is accessible by others. When this is done, then start the SSH agent to load keys into memory. In the examples that follow, the RSA key is used.

You must configure SSH separately for each Oracle software installation owner that you intend to use for installation.

To configure SSH, complete the following:

2.9.3.1 Create .SSH, and Create RSA Keys On Each Node

Complete the following steps on each node:

- Log in as the software owner (in this example, the crs user).
- To ensure that you are logged in as the Oracle user, and that the user ID matches the expected user ID you have assigned to the Oracle user, enter the commands id and id oracle. Ensure that Oracle user group and user and the terminal window process group and user IDs are identical. For example:

```
uid=502(crs) gid=501(oinstall) groups=501(oinstall),502(crs)
$ id crs
uid=502(crs) gid=501(oinstall) groups=501(oinstall),502(crs)
```

3. If necessary, create the .ssh directory in the crs user's home directory, and set permissions on it to ensure that only the oracle user has read and write permissions:

```
$ mkdir ~/.ssh
$ chmod 700 ~/.ssh
```

4. Enter the following command:

```
$ /usr/bin/ssh-keygen -t rsa
```

At the prompts:

- Accept the default location for the key file (press **Enter**).
- Enter and confirm a pass phrase unique for this installation user.

This command writes the RSA public key to the ~/.ssh/id_rsa.pub file and the private key to the ~/.ssh/id_rsa file.

Never distribute the private key to anyone not authorized to perform Oracle software installations.

5. Repeat steps 1 through 4 on each node that you intend to make a member of the cluster.

2.9.3.2 Add All Keys to a Common authorized_keys File

Complete the following steps:

1. On the local node, change directories to the .ssh directory in the Oracle Clusterware owner's home directory (typically, either crs or oracle).

Then, add the RSA key to the authorized_keys file using the following commands:

```
$ cat id_rsa.pub >> authorized_keys
```

In the .ssh directory, you should see the id_rsa.pub keys that you have created, and the file authorized_keys.

2. On the local node, use SCP (Secure Copy) or SFTP (Secure FTP) to copy the authorized_keys file to the oracle user .ssh directory on a remote node. The following example is with SCP, on a node called node2, with the Oracle Clusterware owner crs, where the crs user path is /home/crs:

```
[crs@node1 .ssh]$ scp authorized_keys node2:/home/crs/.ssh/
```

You are prompted to accept an RSA key. Enter Yes, and you see that the node you are copying to is added to the known_hosts file.

When prompted, provide the password for the crs user, which should be the same on all nodes in the cluster. The authorized_keys file is copied to the remote node.

Your output should be similar to the following, where xxx represents parts of a valid IP address:

```
[crs@node1 .ssh]$ scp authorized keys node2:/home/crs/.ssh/
The authenticity of host 'node2 (xxx.xxx.173.152) can't be established.
RSA key fingerprint is 7e:60:60:ae:40:40:d1:a6:f7:4e:zz:me:a7:48:ae:f6:7e.
Are you sure you want to continue connecting (yes/no)? yes
Warning: Permanently added 'node1,xxx.xxx.173.152' (RSA) to the list
of known hosts
crs@node2's password:
authorized_keys 100% 828 7.5MB/s
                                                00:00
```

Using SSH, log in to the node where you copied the authorized_keys file, using the pass phrase you created. Then change to the .ssh directory, and using the cat command, add the RSA keys for the second node to the authorized_ keys file:

```
[crs@node1 .ssh]$ ssh node2
The authenticity of host node2 (xxx.xxx.100.102) can't be established. RSA key
fingerprint is z3:z3:33:z3:z3:z3:z3:z3.
Are you sure you want to continue connecting? (yes/no)? yes
Enter passphrase for key '/home/oracle/.ssh/id_rsa':
[crs@node2 crs]$ cd .ssh
[crs@node2 ssh]$ cat id_rsa.pub >> authorized_keys
```

Repeat steps 2 and 3 from each node to each other member node in the cluster.

When you have added keys from each cluster node member to the authorized keys file on the last node you want to have as a cluster node member, then use scp to copy the authorized keys file with the keys from all nodes back to each cluster node member, overwriting the existing version on the other nodes.

If you want to confirm that you have all nodes in the authorized_keys file, enter the command more authorized keys, and check to see that there is an RSA key for each member node. The file lists the type of key (ssh-rsa), followed by the key, and then followed by the user and server. For example:

```
ssh-rsa AAAABBBB . . . = crs@node1
```

Note: The crs user's /.ssh/authorized_keys file on every node must contain the contents from all of the /.ssh/id_rsa.pub files that you generated on all cluster nodes.

2.9.4 Enabling SSH User Equivalency on Cluster Member Nodes

After you have copied the authorized_keys file that contains all keys to each node in the cluster, complete the following procedure, in the order listed. In this example, the Oracle Clusterware software owner is named crs:

- On the system where you want to run OUI, log in as the crs user.
- Use the following command syntax, where hostname1, hostname2, and so on, are the public hostnames (alias and fully qualified domain name) of nodes in the cluster to run SSH from the local node to each node, including from the local node to itself, and from each node to each other node:

```
[crs@nodename]$ ssh hostname1 date
[crs@nodename]$ ssh hostname2 date
```

For example:

```
[crs@node1 crs]$ ssh node1 date
The authenticity of host 'node1 (xxx.xxx.100.101)' can't be established.
RSA key fingerprint is 7z:60:60:zz:48:48:z1:a0:f7:4e.
Are you sure you want to continue connecting (yes/no)? yes
Warning: Permanently added 'node1,xxx.xxx.100.101' (RSA) to the list of
known hosts.
Enter passphrase for key '/home/crs/.ssh/id_rsa':
Mon Dec 4 11:08:13 PST 2006
[crs@node1 crs]$ ssh node1.example.com date
The authenticity of host 'nodel.example.com (xxx.xxx.100.101)' can't be
established.
```

```
RSA key fingerprint is 7z:60:60:zz:48:48:z1:a0:f7:4e.
Are you sure you want to continue connecting (yes/no)? yes
Warning: Permanently added 'node1.example.com, xxx.xxx.100.101' (RSA) to the
list of known hosts.
Enter passphrase for key '/home/crs/.ssh/id_rsa':
Mon Dec 4 11:08:13 PST 2006
[crs@node1 crs]$ ssh node2 date
Enter passphrase for key '/home/crs/.ssh/id_rsa':
Mon Dec 4 11:08:35 PST 2006
```

At the end of this process, the public hostname for each member node should be registered in the known_hosts file for all other cluster member nodes.

If you are using a remote client to connect to the local node, and you see a message similar to "Warning: No xauth data; using fake authentication data for X11 forwarding," then this means that your authorized keys file is configured correctly, but your ssh configuration has X11 forwarding enabled. To correct this issue, proceed to Section 2.9.5, "Setting Display and X11 Forwarding Configuration."

- Repeat step 2 on each cluster node member.
- **4.** On each node, enter the following commands to start the SSH agent, and to load the SSH keys into memory:

```
$ exec /usr/bin/ssh-agent $SHELL
$ /usr/bin/ssh-add
```

At the prompt, enter the pass phrase for each key that you generated.

For example:

```
[crs@node1 .ssh]$ exec /usr/bin/ssh-agent $SHELL
[crs@node1 .ssh]$ ssh-add
Enter passphrase for /home/crs/.ssh/id_rsa
Identity added: /home/crs/.ssh/id_rsa (/home/crs/.ssh/id_rsa)
```

These commands start the ssh-agent on the node, and load the RSA keys into memory so that you are not prompted to use pass phrases when issuing SSH commands

If you have configured SSH correctly, then you can now use the ssh or scp commands without being prompted for a password or a pass phrase. For example:

```
[crs@node1 ~|$ ssh node2 date
Mon Feb 26 23:34:42 UTC 2007
[crs@node1 ~]$ ssh node1 date
Mon Feb 26 23:34:48 UTC 2007
[crs@node1 ~]$ ssh node2
```

If any node prompts for a password or pass phrase, then verify that the ~/.ssh/authorized keys file on that node contains the correct public keys, and that you have created an Oracle software owner with identical group membership and IDs.

Note: You must run OUI from this session, or make a note of your SSH pass phrase, and remember to repeat step 4 before you start OUI from a different terminal session.

2.9.5 Setting Display and X11 Forwarding Configuration

If you are on a remote terminal, and the local node has only one visual (which is typical), then use the following syntax to set the DISPLAY environment variable:

Bourne and Korn shells

```
$ export DISPLAY=hostname:0
C shell:
```

\$ setenv DISPLAY hostname:0

For example, if you are using the Bourne shell, and if your hostname is node1, then enter the following command:

```
$ export DISPLAY=node1:0
```

- To ensure that X11 forwarding will not cause the installation to fail, create a user-level SSH client configuration file for the Oracle software owner user, as follows:
 - Using any text editor, edit or create the software installation owner's ~/.ssh/config file.
 - **b.** Make sure that the ForwardX11 attribute is set to no. For example:

```
Host. *
      ForwardX11 no
```

2.9.6 Preventing Oracle Clusterware Installation Errors Caused by stty Commands

During an Oracle Clusterware installation, OUI uses SSH to run commands and copy files to the other nodes. During the installation, hidden files on the system (for example, .cshrc) will cause makefile and other installation errors if they contain stty commands.

To avoid this problem, you must modify these files in each Oracle installation owner user home directory to suppress all output on STDERR, as in the following examples:

Bourne or Korn shell:

```
if [ -t 0 ]; then
   stty intr ^C
fi
```

C shell:

```
test -t 0
if ($status == 0) then
  stty intr ^C
endif
```

Note: When SSH is not available, the Installer uses the rsh and rcp commands instead of ssh and scp.

If there are hidden files that contain stty commands that are loaded by the remote shell, then OUI indicates an error and stops the installation.

2.10 Configuring Software Owner User Environments

You run OUI from the user account that you want to own the Oracle Clusterware installation (oracle or crs). However, before you start OUI you must configure the environment of the user performing the Oracle Clusterware installation. In addition, create other required Oracle software owners, if needed.

2.10.1 Procedure for Configuring Oracle Software Owner Environments

To set the Oracle software owners' environments, follow these steps, for each software owner (crs, oracle, asm):

- **1.** Start a new terminal session; for example, start an X terminal (xterm).
- 2. Enter the following command to ensure that X Window applications can display on this system:

```
$ xhost + hostname
```

The *hostname* is the name of the local host.

- 3. If you are not already logged in to the system where you want to install the software, then log in to that system as the software owner user.
- **4.** If you are not logged in as the user, then switch to the software owner user you are configuring. For example, with the crs user:

```
$ su - crs
```

5. To determine the default shell for the user, enter the following command:

```
$ echo $SHELL
```

- **6.** Open the user's shell startup file in any text editor:
 - Bourne shell (sh) or Korn shell (ksh):

```
$ vi .profile
```

C shell (csh or tcsh):

```
% vi .login
```

7. Enter or edit the following line, specifying a value of 022 for the default file mode creation mask:

```
umask 022
```

- 8. If the ORACLE_SID, ORACLE_HOME, or ORACLE_BASE environment variable is set in the file, then remove the appropriate lines from the file.
- **9.** Save the file, and exit from the text editor.
- **10.** To run the shell startup script, enter one of the following commands:
 - Bourne or Korn shell:

```
$ . ./.profile
```

C shell:

```
% source ./.login
```

11. If you are not installing the software on the local system, then enter a command similar to the following to direct X applications to display on the local system:

Bourne or Korn shell:

```
$ DISPLAY=local_host:0.0 ; export DISPLAY
```

C shell:

```
% setenv DISPLAY local_host:0.0
```

In this example, <code>local_host</code> is the host name or IP address of the system that you want to use to display OUI (your workstation or PC).

12. If you determined that the /tmp directory has less than 400 MB of free disk space, then identify a file system with at least 400 MB of free space and set the TEMP and TMPDIR environment variables to specify a temporary directory on this file system:

Note: You cannot use a shared file system as the location of the temporary file directory (typically /tmp) for Oracle RAC installation. If you place / tmp on a shared file system, then the installation fails.

- Use the df -k command to identify a suitable file system with sufficient free space.
- **b.** If necessary, enter commands similar to the following to create a temporary directory on the file system that you identified, and set the appropriate permissions on the directory:

```
$ su - root
# mkdir /mount_point/tmp
# chmod 775 /mount_point/tmp
# exit
```

- Enter commands similar to the following to set the TEMP and TMPDIR environment variables:
 - Bourne or Korn shell:

```
$ TEMP=/mount_point/tmp
$ TMPDIR=/mount_point/tmp
$ export TEMP TMPDIR
```

C shell:

```
% setenv TEMP /mount_point/tmp
% setenv TMPDIR /mount_point/tmp
```

13. To verify that the environment has been set correctly, enter the following commands:

```
$ umask
$ env | more
```

Verify that the umask command displays a value of 22, 022, or 0022 and that the environment variables you set in this section have the correct values.

2.11 Running the rootpre.sh Script

Note: Do not run the rootpre. sh script if you have a later release of the Oracle Database software already installed on this system.

Run the rootpre.sh script:

1. Switch user to root:

```
$ su - root
```

2. Complete one of the following steps, depending on the location of the installation

If the installation files are on disc, enter a command similar to the following, where *directory_path* is the disc mount point directory or the path of the database directory on the DVD:

```
# /directory_path/rootpre.sh
```

If the installation files are on the hard disk, change directory to the Disk1 directory and enter the following command:

```
# ./rootpre.sh
```

3. Exit from the root account:

exit

Repeat steps 1 through 3 on all nodes of the cluster.

Note: Do not run the rootpre.sh script if you have a later release of Oracle Database software already installed on this system.

2.12 Requirements for Creating an Oracle Clusterware Home Directory

During installation, you are prompted to provide a path to a home directory to store Oracle Clusterware binaries. Ensure that the directory path you provide meets the following requirements:

- It should be created in a path separate from existing Oracle homes.
- It should not be located in a user home directory.
- It should be created either as a subdirectory in a path where all files can be owned by root, or in a unique path.
- Before installation, it should be owned by the installation owner of Oracle Clusterware (typically oracle for a single installation owner for all Oracle software, or crs for role-based Oracle installation owners), and set to 750 permissions

For installations with Oracle Clusterware only, Oracle recommends that you create a path compliant with Oracle Optimal Flexible Architecture (OFA) guidelines, so that Oracle Universal Installer (OUI) can select that directory during installation. For OUI to recognize the path as an Oracle software path, it must be in the form u0[1-9]/app.

When OUI finds an OFA-compliant path, it creates the Oracle Clusterware and Oracle Central Inventory (oralnventory) directories for you.

Create an Oracle Clusterware path. For example:

```
# mkdir -p /u01/app
# chown -R crs:oinstall /u01
```

Alternatively, if you later intend to install Oracle Database software, then create an Oracle base path. OUI automatically creates an OFA-compliant path for Oracle Clusterware derived from the Oracle base path. The Optimal Flexible Architecture path for the Oracle Base is /u01/app/user, where user is the name of the user account that you want to own the Oracle Database software. For example:

```
# mkdir -p /u01/app/oracle
# chown -R oracle:oinstall /u01/app/oracle
# chmod -R 775 /u01/app/oracle
```

Note: If you choose to create an Oracle Clusterware home manually, then do not create the Oracle Clusterware home under Oracle base. Creating an Oracle Clusterware installation in an Oracle base directory will cause succeeding Oracle installations to fail.

See Also: "Creating Standard Configuration Operating System Groups and Users" on page 3-1, and "Creating Custom Configuration" Groups and Users for Job Roles" on page 3-3 for information about creating groups, users, and software homes for additional Oracle software installations

2.13 Understanding and Using Cluster Verification Utility

Cluster Verification Utility (CVU) is a tool that performs system checks. This guide provides Cluster Verification Utility commands to assist you with confirming that your system is properly configured for Oracle Clusterware and Oracle RAC installation.

This section describes the following topics:

- **Entering Cluster Verification Utility Commands**
- Using CVU to Determine if Installation Prerequisites are Complete
- Using the Cluster Verification Utility Help
- Using Cluster Verification Utility with Oracle Database 10g Release 1 or 2
- Verbose Mode and "Unknown" Output

2.13.1 Entering Cluster Verification Utility Commands

Cluster Verification Utility is provided with two scripts: runcluvfy.sh, which is designed to be used before installation, and cluvfy, which is in the path CRS_ home/bin. The script runcluvfy. sh contains temporary variable definitions which enable it to be run before installing Oracle Clusterware or Oracle Database. After you install Oracle Clusterware, use the command cluvfy to check prerequisites and perform other system readiness checks.

Before Oracle software is installed, to enter a Cluster Verification Utility command, change directories and start runcluvfy.sh using the following syntax:

```
cd /mountpoint
./runcluvfy.sh options
```

In the preceding example, the variable *mountpoint* represents the mountpoint path for the installation media and the variable options represents the Cluster Verification Utility command options that you select. For example:

```
$ cd /mnt/dvdrom
$ ./runcluvfy.sh comp nodereach -n node1,node2 -verbose
```

By default, when you enter a Cluster Verification Utility command, Cluster Verification Utility provides a summary of the test. During preinstallation, Oracle recommends that you obtain detailed output by using the -verbose argument with the Cluster Verification Utility command. The -verbose argument produces detailed output of individual checks. Where applicable, it shows results for each node in a tabular layout.

2.13.2 Using CVU to Determine if Installation Prerequisites are Complete

You can use Cluster Verification Utility to determine which system prerequisites for installation are already completed. Use this option if you are installing Oracle 11g release 1 (11.1) on a system with a pre-existing Oracle software installation. In using this option, note the following:

- You must complete the prerequisites for using Cluster Verification Utility, notably configuring SSH between all nodes in the cluster, before you can complete a clusterwide status check.
- Cluster Verification Utility can assist you by finding preinstallation steps that need to be completed, but it cannot perform preinstallation tasks

Use the following syntax to determine what preinstallation steps are completed, and what preinstallation steps must be performed

```
$ ./runcluvfy.sh stage -pre crsinst -n node_list
```

In the preceding syntax example, replace the variable *node_list* with the names of the nodes in your cluster, separated by commas.

For example, for a cluster with mountpoint /mnt/dvdrom/, and with nodes node1, node2, and node3, enter the following command:

```
$ cd /mnt/dvdrom/
$ ./runcluvfy.sh stage -pre crsinst -n node1,node2,node3
```

Review the Cluster Verification Utility report, and proceed to the sections of the preinstallation chapter to complete additional steps as needed.

2.13.3 Using the Cluster Verification Utility Help

The cluvfy commands have context-sensitive help that shows correct syntax usage based on the command line arguments that you enter.

If you enter an invalid Cluster Verification Utility command, then Cluster Verification Utility shows the correct usage for that command. For example, if you type runcluvfy.sh stage -pre dbinst, then Cluster Verification Utility shows the correct syntax for the database preinstallation checks that Cluster Verification Utility performs with the dbinst stage option. The following is a list of context help commands.

cluvfy -help —Cluster Verification Utility displays detailed command information.

- cluvfy comp -list—Cluster Verification Utility displays a list of components that can be checked, and brief descriptions of how each component is checked.
- cluvfy comp -help—Cluster Verification Utility displays detailed syntax for each of the valid component checks.
- cluvfy stage -list—Cluster Verification Utility displays a list of valid stages.
- cluvfy stage -help—Cluster Verification Utility displays detailed syntax for each of the valid stage checks.

2.13.4 Using Cluster Verification Utility with Oracle Database 10g Release 1 or 2

You can use Cluster Verification Utility on the Oracle Database 11g release 1 (11.1) media to check system requirements for Oracle Database 10g release 1 (10.1) and later installations. To use Cluster Verification Utility to check 10. 2 installations, append the command flag -r 10gR2 to the standard Cluster Verification Utility system check commands.

For example, to perform a verification check for a Cluster Ready Services 10. 2 installation, on a system where the media mountpoint is /mnt/dvdrom, and the cluster nodes are node1, node2, and node3, enter the following command:

```
$ cd /mnt/dvdrom
$ ./runcluvfy.sh stage -pre crsinst -n node1, node2, node3 -r 10gR2
```

Note: If you do not specify a release version to check, then Cluster Verification Utility checks for 11g release 1 (11.1) requirements.

2.13.5 Verbose Mode and "Unknown" Output

If you run Cluster Verification Utility using the -verbose argument, and the command responds with UNKNOWN for a particular node, then this is because Cluster Verification Utility cannot determine if a check passed or failed. The following is a list of possible causes for an "Unknown" response:

- The node is down
- Executables required by Cluster Verification Utility are missing in the /bin directory in the Oracle Clusterware home or Oracle home directory
- The user account starting Cluster Verification Utility does not have privileges to run common operating system executables on the node
- The node is missing an operating system patch, or a required package
- The node has exceeded the maximum number of processes or maximum number of open files, or there is a problem with IPC segments, such as shared memory or semaphores

2.14 Checking Oracle Clusterware Installation Readiness with CVU

Use the Cluster Verification Utility (CVU) to check your servers for their readiness to install Oracle Clusterware:

As the installation owner user (oracle or crs), ensure that you have ssh keys loaded into memory, and enter a command using the following syntax to verify that your cluster is properly configured for Oracle Clusterware installation:

/mountpoint/runcluvfy.sh stage -pre crsinst -n node_list [-verbose]

In the preceding syntax example, the variable node_list is a comma-delimited list of nodes in your cluster. This command checks node reachability, user and group equivalence on each node, node connectivity, and basic system requirements, including kernel versions and packages.

Select the option -verbose to receive progress updates as Cluster Verification Utility performs its system checks, and detailed reporting of the test results.

For example, to verify system readiness on a two-node cluster with nodes node1 and node2, with the mountpoint /mnt/dvdrom, and with updates and a summary of the verification checks Cluster Verification Utility performs, enter the following command:

\$ /mnt/dvdrom/runcluvfy.sh stage -pre crsinst -n node1,node2 -verbose

Oracle Real Application Clusters Preinstallation Tasks

This chapter describes the system configuration tasks that are generally completed by the system administrator if you plan to install Oracle Database or Oracle Database with Oracle Real Application Clusters (Oracle RAC). These tasks include creating additional groups and users for the database and for Automatic Storage Management (ASM).

You must complete these tasks before you or a database administrator start Oracle Universal Installer to install Oracle RAC. If you do not plan on installing Oracle Database on this cluster, then you can continue to the next chapter.

This chapter contains the following topics:

- Creating Standard Configuration Operating System Groups and Users
- Creating Custom Configuration Groups and Users for Job Roles
- Understanding the Oracle Base Directory Path
- Creating the Oracle Base Directory Path
- Environment Requirements for Oracle Database and Oracle ASM Owners

Note: Any task required for Oracle Database is also required for Oracle RAC, unless otherwise stated.

3.1 Creating Standard Configuration Operating System Groups and **Users**

A standard configuration is a configuration with the default groups and users that Oracle Universal Installer (OUI) displays by default during Oracle database installation, which are not created already for Oracle Clusterware installation.

The following sections describe how to create the required operating system user and groups for Oracle Database or Oracle Database with Oracle RAC and ASM installations:

To allocate separate operating system user privileges to different administrative users, refer to "Creating Custom Configuration Groups and Users for Job Roles" on page 3-3.

- Overview of Groups and Users for Oracle Database Installations
- Creating Standard Operating System Groups and Users

3.1.1 Overview of Groups and Users for Oracle Database Installations

The following operating system groups and user are required if you plan to install Oracle Database:

The OSDBA group (typically, dba)

You must create this group the first time you install Oracle Database software on the system. In a standard installation, you are prompted to one group to grant the following privileges to its members:

- Database Administrator (OSDBA)
- Database Operator (OSOPER)
- ASM Administrator (OSASM)

In addition, members of this group are granted database write access to ASM (OSDBA for ASM).

The default name for this group is dba.

An unprivileged user

Verify that the unprivileged user nobody exists on the system. The nobody user must own the external jobs (extjob) executable after the installation.

3.1.2 Creating Standard Operating System Groups and Users

The following sections describe how to create required and optional operating system user and groups:.

- Verifying That the User nobody Exists
- Creating the OSDBA Group

3.1.2.1 Verifying That the User nobody Exists

If you intend to install Oracle Database or Oracle RAC, then complete the following procedure to verify that the user nobody exists on the system:

1. To determine if the user exists, enter the following command:

```
# id nobody
```

If this command displays information about the nobody user, then you do not have to create that user.

2. If you need to create a nobody user, then enter the following command:

```
# smit security
```

- 3. Select Users, then Add a User.
- 4. On the Add a User form, specify the appropriate options to create an unprivileged nobody user, and make a note of the user ID.
- **5.** Press F10 to exit.
- Repeat this process on each node in the cluster, ensuring that the user ID for each nobody user is identical on each cluster node.

3.1.2.2 Creating the OSDBA Group

To create the OSDBA group, complete the following procedure:

1. Enter the following command:

smit security

- **2.** Select **Groups**, then **Add a Group**.
- **3.** On the **Add a Group** form, specify the appropriate options to create an OSDBA group, with a group ID that can be identical on all nodes in the cluster. Make a note of the group ID.
- **4.** Press F10 to exit.
- **5.** Repeat this process on each node in the cluster, ensuring that the group ID for OSDBA is identical on each cluster node.

3.2 Creating Custom Configuration Groups and Users for Job Roles

A Custom configuration is a configuration with groups and users that divide access privileges granted by membership in separate operating system groups and users.

Note: This configuration is optional, to restrict user access to Oracle software by responsibility areas for different administrator users.

To allocate operating system user privileges to a minimum number of groups and users, refer to Creating Standard Configuration Operating System Groups and Users on page 3-1.

- Overview of Creating Operating System Group and User Options Based on Job
- Creating Database Operating System Groups and Users with Job Role Separation

Note: If you want to use a directory service, such as Network Information Services (NIS), refer to your operating system documentation for further information.

3.2.1 Overview of Creating Operating System Group and User Options Based on Job **Roles**

This section provides an overview of how to create users and groups to divide access privileges by job roles. Log in as root to create these groups and users.

- Users for Oracle Installations with Job Role Separation
- Database Groups for Job Role Installations
- ASM Groups for Job Role Installations

3.2.1.1 Users for Oracle Installations with Job Role Separation

Oracle recommends that you create the following operating system group and users for all installations where you create separate software installation owners:

One software owner to own each Oracle software product (typically, oracle, for the database software owner user, crs for Oracle Clusterware, and asm for Oracle ASM.

You must create at least one software owner the first time you install Oracle software on the system. This user owns the Oracle binaries of the Oracle

Clusterware software, and you can also make this user the owner of the binaries of Automatic Storage Management and Oracle Database or Oracle RAC.

Oracle software owners must have the Oracle Inventory group as their primary group, so that each Oracle software installation owner can write to the Central Inventory, and so that OCR and Oracle Clusterware resource permissions are set correctly. The Database software owner must also have the OSDBA group and (if you create it) the OSOPER group as secondary groups. In Oracle documentation, when Oracle software owner users are referred to, they are called oracle users.

Oracle recommends that you create separate software owner users to own each Oracle software installation. Oracle particularly recommends that you do this if you intend to install more than one database on the system.

In Oracle documentation, a user created to own the Oracle Clusterware binaries is called the crs user.

If you intend to use Automatic Storage Management (ASM), then Oracle recommends that you create a separate user to own ASM files. In Oracle documentation, that user is referred to as asm.

See Also: Oracle Database Administrator's Reference for UNIX Systems and Oracle Database Administrator's Guide for more information about the OSDBA, OSASM and OSOPER groups and the SYSDBA, SYSASM and SYSOPER privileges

An unprivileged user

Verify that the unprivileged user nobody exists on the system. The nobody user must own the external jobs (extjob) executable after the installation.

3.2.1.2 Database Groups for Job Role Installations

The following operating system groups and user are required if you are installing Oracle Database:

The OSDBA group (typically, dba)

You must create this group the first time you install Oracle Database software on the system. This group identifies operating system user accounts that have database administrative privileges (the SYSDBA privilege). If you do not create separate OSDBA, OSOPER and OSASM groups for the ASM instance, then operating system user accounts that have the SYSOPER and SYSASM privileges must be members of this group. The name used for this group in Oracle code examples is dba. If you do not designate a separate group as the OSASM group, then the OSDBA group you define is also by default the OSASM group.

If you want to specify a group name other than the default dba group, then you must choose the Custom installation type to install the software or start Oracle Universal Installer (OUI) as a user that is not a member of this group. In this case, OUI prompts you to specify the name of this group.

On Automatic Storage Manager (ASM) instances, members of the OSDBA group are given privileges to perform all administrative privileges granted to the SYSASM privileges, including mounting and dismounting disk groups. This privileges grant is deprecated, and will be removed in a future release.

The OSOPER group for Oracle Database (typically, oper)

This is an optional group. Create this group if you want a separate group of operating system users to have a limited set of database administrative privileges (the SYSOPER privilege). By default, members of the OSDBA group also have all privileges granted by the SYSOPER privilege.

If you want to use the OSOPER group to create a database administrator group with fewer privileges than the default dba group, then you must choose the Custom installation type to install the software or start OUI as a user that is not a member of the dba group. In this case, OUI prompts you to specify the name of this group. The usual name chosen for this group is oper.

3.2.1.3 ASM Groups for Job Role Installations

SYSASM is a new system privilege that enables the separation of the ASM storage administration privilege from SYSDBA. Members of the database OSDBA group are granted SYSASM privileges, but this privilege is deprecated, and may be removed in a future release.

Use the Custom Installation option to designate separate operating system groups as the operating system authentication groups for privileges on ASM. Before you start OUI, create the following groups and users for ASM

The Oracle Automatic Storage Management Group (typically asm)

SYSASM privileges for ASM files provide administrator privileges for storage file equivalent to SYSDBA privileges for the database. In Oracle documentation, the operating system group whose members are granted SYSASM privileges is called the OSASM group, and in command lines, is referred to as asm.

If you have more than one database on your system, then you must create a separate OSASM group, and a separate ASM user. ASM can support multiple databases.

Members of the OSASM group can use SQL to connect to an ASM instance as SYSASM using operating system authentication. The SYSASM privileges permit mounting and dismounting disk groups, and other storage administration tasks. SYSASM privileges provide no access privileges on an RDBMS instance. In this release of Oracle Clusterware and Oracle Database, SYSASM privileges and SYSDBA privileges are equivalent, but using SYSDBA privileges to perform ASM management tasks on ASM instances is deprecated. SYSDBA privileges may be limited on ASM instances in a future release.

The OSDBA group for ASM (typically asmdba)

Members of the OSDBA group for ASM are granted read and write access to files managed by ASM. The Oracle database software owner (typically oracle) must be a member of this group, and all users with OSDBA membership on databases that you want to have access to the files managed by ASM should be members of the OSDBA group for ASM

3.2.2 Creating Database Operating System Groups and Users with Job Role Separation

The following sections describe how to create the required operating system user and groups:.

- Creating the OSDBA Group for Custom Installations
- Creating an OSOPER Group
- Creating the Oracle Software Owner User
- Creating Identical Database Users and Groups on Other Cluster Nodes

3.2.2.1 Creating the OSDBA Group for Custom Installations

You must create an OSDBA group in the following circumstances:

- An OSDBA group does not exist, for example, if this is the first installation of Oracle Database software on the system
- An OSDBA group exists, but you want to give a different group of operating system users database administrative privileges for a new Oracle Database installation

If the OSDBA group does not exist or if you require a new OSDBA group, then create it as follows. In the following procedure, use the group name dba unless a group with that name already exists:

1. Enter the following command:

```
# smit security
```

- 2. Select Groups, then Add a Group.
- **3.** On the **Add a Group** form, specify the appropriate options to create an OSDBA group, with a group ID that can be identical on all nodes in the cluster. Make a note of the group ID.
- **4.** Press F10 to exit.
- Repeat this process on each node in the cluster, ensuring that the group ID for OSDBA is identical on each cluster node.

3.2.2.2 Creating an OSOPER Group

Create an OSOPER group only if you want to identify a group of operating system users with a limited set of database administrative privileges (SYSOPER operator privileges). For most installations, it is sufficient to create only the OSDBA group. If you want to use an OSOPER group, then you must create it in the following circumstances:

- If an OSOPER group does not exist; for example, if this is the first installation of Oracle Database software on the system
- If an OSOPER group exists, but you want to give a different group of operating system users database operator privileges in a new Oracle installation

If you require a new OSOPER group, then create it as follows. In the following, use the group name oper unless a group with that name already exists.

1. Enter the following command:

```
# smit security
```

- 2. Select Groups, then Add a Group.
- On the **Add a Group** form, specify the appropriate options to create an OSOPER group, with a group ID that can be identical on all nodes in the cluster. Make a note of the group ID.
- **4.** Press F10 to exit.
- Repeat this process on each node in the cluster, ensuring that the group ID for OSOPER is identical on each cluster node.

3.2.2.3 Creating the OSASM Group

If the OSASM group does not exist or if you require a new OSASM group, then create it as follows. In the following procedure, use the group name asm unless a group with that name already exists:

1. Enter the following command:

```
# smit security
```

- **2.** Select **Groups**, then **Add a Group**.
- **3.** On the **Add a Group** form, specify the appropriate options to create an OSASM group, with a group ID that can be identical on all nodes in the cluster. Make a note of the group ID.
- Press F10 to exit.
- Repeat this process on each node in the cluster, ensuring that the group ID for OSASM is identical on each cluster node.

3.2.2.4 Creating the OSDBA Group for ASM

You must create an OSDBA group for ASM to provide access to the ASM instance. This is necessary if OSASM and OSDBA are different groups.

If the OSDBA group for ASM does not exist or if you require a new OSDBA group for ASM, then create it as follows. In the following procedure, use the group name asmdba unless a group with that name already exists:

Enter the following command:

```
# smit security
```

- **2.** Select **Groups**, then **Add a Group**.
- **3.** On the **Add a Group** form, specify the appropriate options to create an ASMDBA group, with a group ID that can be identical on all nodes in the cluster. Make a note of the group ID.
- **4.** Press F10 to exit.
- Repeat this process on each node in the cluster, ensuring that the group ID for ASMDBA is identical on each cluster node.

3.2.2.5 Creating the Oracle Software Owner User

You must create an Oracle software owner user in the following circumstances:

- If an Oracle software owner user exists, but you want to use a different operating system user, with different group membership, to give database administrative privileges to those groups in a new Oracle Database installation
- If you have created an Oracle software owner for Oracle Clusterware, such as crs, and you want to create a separate Oracle software owner for Oracle Database software, such as dba.

3.2.2.5.1 Determining if an Oracle Software Owner User Exists To determine whether an Oracle software owner user named oracle or crs exists, enter a command similar to the following (in this case, to determine if oracle exists):

```
# id oracle
```

If the user exists, then the output from this command is similar to the following:

```
uid=501(oracle) gid=501(oinstall) groups=502(dba),503(oper)
```

Determine whether you want to use the existing user, or create another user. If you want to use the existing user, then ensure that the user's primary group is the Oracle Inventory group and that it is a member of the appropriate OSDBA and OSOPER groups. Refer to one of the following sections for more information:

Note: If necessary, contact your system administrator before using or modifying an existing user.

- To modify an existing user, refer to the "Modifying an Existing Oracle Software Owner User" section on page 3-8.
- To create a user, refer to the following section.

3.2.2.5.2 Creating an Oracle Software Owner User If the Oracle software owner user does not exist, or if you require a new Oracle software owner user, then create it as follows. In the following procedure, use the user name oracle unless a user with that name already exists.

1. Enter the following command:

```
# smit security
```

- **2.** Select **Users**, then **Add a User**.
- On the Add a User form, specify the appropriate options to create the oracle user. These include the following:
 - User NAME: The oracle user account name. For example: oracle.
 - User ID: The user ID of the oracle account.
 - PRIMARY Group: The primary group ID for the oracle user. For example: oinstall.
 - Group SET: The primary and secondary groups for the oracle user. For example: oinstall, dba, oper, hagsuser
- Press F10 to exit.
- Repeat this procedure on all of the other nodes in the cluster.

3.2.2.5.3 Modifying an Existing Oracle Software Owner User If the oracle user exists, but its primary group is not oinstall, or it is not a member of the appropriate OSDBA or OSOPER groups, then modify the user group configuration:

1. Enter the following command:

```
# smit security
```

- 2. From the Security and Users menu, select Users, then Change/Show Characteristics of a User.
- Enter the oracle user name, and press Enter.
- In the Change/Show Characteristics of a User menu, update the entry fields as necessary. When you are finished, press the **Enter** key to save changes and exit.

3.2.2.6 Creating a Separate ASM Owner

1. Enter the following command:

- # smit security
- **2.** Select **Users**, then **Add a User**.
- **3.** On the **Create User** form, specify the appropriate options to create the asm user. These include the following:
 - User NAME: The oracle user account name. For example: asm.
 - User ID: The user ID of the asm account.
 - PRIMARY Group: The primary group ID for the asm user. For example: oinstall.
 - Group SET: The primary and secondary groups for the asm user. For example: oinstall, asmdba.
- **4.** Press F10 to exit.
- Repeat this procedure on all of the other nodes in the cluster.

3.2.2.7 Creating Identical Database Users and Groups on Other Cluster Nodes

Note: You must complete the following procedures only if you are using local users and groups. If you are using users and groups defined in a directory service such as NIS, then they are already identical on each cluster node.

Oracle software owner users and the Oracle Inventory, OSDBA, and OSOPER groups must exist and be identical on all cluster nodes. To create these identical users and groups, you must identify the user ID and group IDs assigned them on the node where you created them, and then create the user and groups with the same name and ID on the other cluster nodes.

Identifying Existing User and Group IDs

To determine the user ID (UID) of the crs, oracle, or asm users, and the group IDs (GID) of the Oracle Inventory, OSDBA, and OSOPER groups, follow these steps:

1. Enter a command similar to the following (in this case, to determine a user ID for the oracle user):

id oracle

The output from this command is similar to the following:

```
uid=502(oracle) gid=501(oinstall) groups=502(dba),503(oper),506(asmdba)
```

2. From the output, identify the user ID (UID) for the user and the group identities (GIDs) for the groups to which it belongs. Ensure that these ID numbers are identical on each node of the cluster.

Creating Users and Groups on the Other Cluster Nodes

To create users and groups on the other cluster nodes, repeat the following procedure on each node:

1. Log in to the next cluster node as root.

2. Use smit, or enter commands similar to the following to create the oinstall and dba groups, and if required, the oper and asm groups. Use the -g option to specify the correct GID for each group.

```
# mkgroup id=501 oinstall
# mkgroup id=502 crs
# mkgroup id=503 dba
# mkgroup id=505 oper
# mkgroup id=504 asm
# mkgroup id=506 asmdba
# mkuser id=502 pgrp=oinstall groups=dba,oracle gecos="RDBMS owner" oracle
passwd db2inst1
```

Note: If the group already exists, then use the groupmod command to modify it if necessary. If you cannot use the same group ID for a particular group on this node, then view the /etc/group file on all nodes to identify a group ID that is available on every node. You must then change the group ID on all nodes to the same group ID.

3. To create the oracle or asm user, enter a command similar to the following (in this example, to create the oracle user):

```
# mkuser id='502' pgrp='oinstall' groups='dba','oper' oracle
```

In the preceding command:

- The id option specifies the user ID, which must be the user ID that you identified in the previous subsection
- The pgrp option specifies the primary group, which must be the Oracle Inventory group, for example oinstall
- The groups option specifies the secondary groups, which must include the OSDBA group and if required, the OSOPER group. For example: dba or dba, oper

Note: You must specify a user ID that *is* available on every node. You must then specify that ID for the user on all of the nodes.

4. Set the password of the user. For example:

```
# passwd oracle
```

- **5.** Complete SSH configuration for each user as described in the section Section 2.9, "Configuring SSH on All Cluster Nodes."
- 6. Complete user environment configuration tasks for each user as described in the section Section 2.10, "Configuring Software Owner User Environments."

3.3 Understanding the Oracle Base Directory Path

This section contains information about preparing an Oracle base directory.

3.3.1 Overview of the Oracle Base directory

During installation, you are prompted to specify an Oracle base location, which is owned by the user performing the installation. You can choose a location with an existing Oracle home, or choose another directory location that does not have the structure for an Oracle base directory. However, setting an Oracle base directory may become mandatory in a future release.

Using the Oracle base directory path helps to facilitate the organization of Oracle installations, and helps to ensure that installations of multiple databases maintain an Optimal Flexible Architecture (OFA) configuration.

3.3.2 Understanding Oracle Base and Oracle Clusterware Directories

Even if you do not use the same software owner to install Oracle Clusterware and Oracle Database, be aware that the root.sh script in the clusterware installation changes ownership of the Oracle Clusterware home directory to root. For this reason, the Oracle Clusterware home cannot be in the same location as other Oracle software.

3.4 Creating the Oracle Base Directory Path

If you have created a path for the Oracle Clusterware home that is compliant with Oracle Optimal Flexible Architecture (OFA) guidelines for Oracle software paths, then you do not need to create an Oracle base directory. When OUI finds an OFA-compliant path, it creates the Oracle base directory in that path.

For OUI to recognize the path as an Oracle software path, it must be in the form u0[1-9]/app, and it must be writable by any member of the oinstall group.

Oracle recommends that you create an Oracle base path manually. The Optimal Flexible Architecture path for the Oracle Base is /u01/app/user, where user is the name of the user account that you want to own the Oracle Database software. Use smit, or enter shell commands. For example:

```
# mkdir /u01/app/oracle
# chown oracle:oinstall /u01/app/oracle
# chmod -R 775 /u01/app/oracle
```

3.5 Environment Requirements for Oracle Database and Oracle ASM **Owners**

If you create separate Oracle installation owner accounts for the database or ASM, then complete the following tasks for the Oracle Database software owner (oracle) and Oracle ASM software owner (asm).

- If you create an Oracle base path, as described in the preceding section, then set the path to the Oracle base directory as an environment variable for the Oracle database owner. For example:
 - # ORACLE_BASE=/u01/app/oracle; export ORACLE_BASE
- Set the installation software owner user (asm, oracle) default file mode creation mask (umask) to 022 in the shell startup file. Setting the mask to 022 ensures that the user performing the software installation creates files with 644 permissions.
- Set ulimit settings for file descriptors and processes for the installation software owner (asm, oracle)

Set the software owners' environment variable DISPLAY environment variables in preparation for the ASM or Oracle Database installation

Configuring Oracle Clusterware Storage

This chapter describes the storage configuration tasks that you must complete before you start Oracle Universal Installer. It includes information about the following tasks:

- Reviewing Storage Options for Oracle Clusterware Files
- Configuring Storage for Oracle Clusterware Files on a Supported Shared File
- Configuring Storage for Oracle Clusterware Files on Raw Devices

4.1 Reviewing Storage Options for Oracle Clusterware Files

This section describes supported options for storing Oracle Clusterware files. It includes the following sections:

- Overview of Storage Options
- Checking for Available Shared Storage with CVU

4.1.1 Overview of Storage Options

Use the information in this overview to help you select your storage option.

See Also: The Oracle Certify site for a list of supported vendors for Network Attached Storage options:

http://www.oracle.com/technology/support/metalink/

Refer also to the Certify site on Oracle Metalink for the most current information about certified storage options:

https://metalink.oracle.com/

4.1.1.1 Overview of Oracle Clusterware Storage Options

There are two ways of storing Oracle Clusterware files:

- A supported shared file system: The supported file system includes:
 - General Parallel File System (GPFS): A cluster file system for AIX that provides concurrent file access
 - **Network File System (NFS)**: A file-level protocol that enables access and sharing of files

See Also: The Certify page on Oracle *Metalink* for supported Network Attached Storage (NAS) devices. Note that Direct NFS is not supported for Oracle Clusterware files.

Raw partitions: Raw partitions are raw disks that are accessed either through a logical volume manager (LVM), or through non-LVM file systems.

4.1.1.2 General Storage Considerations

For all installations, you must choose the storage option that you want to use for Oracle Clusterware files and Oracle Database files. If you want to enable automated backups during the installation, then you must also choose the storage option that you want to use for recovery files (the Fast recovery area). You do not have to use the same storage option for each file type.

Oracle Clusterware files include voting disks, used to monitor cluster node status, and Oracle Cluster Registry (OCR) which contains configuration information about the cluster. The voting disks and OCR are shared file in a cluster file system environment. If you do not use a cluster file system, then you must place these files on a shared raw device. Oracle Universal Installer (OUI) automatically initializes the OCR during the Oracle Clusterware installation.

For voting disk file placement, ensure that each voting disk is configured so that it does not share any hardware device or disk, or other single point of failure. An absolute majority of voting disks configured (more than half) must be available and responsive at all times for Oracle Clusterware to operate.

For single-instance Oracle Database installations using Oracle Clusterware for failover, you must use GPFS or shared raw disks if you do not want the failover processing to include dismounting and remounting disks.

The following table shows the storage options supported for storing Oracle Clusterware files. Oracle Clusterware files include the Oracle Cluster Registry (OCR), a mirrored OCR file (optional), the Oracle Clusterware voting disk, and additional voting disk files (optional).

Note: For the most up-to-date information about supported storage options for Oracle Clusterware installations, refer to the Certify pages on the OracleMetaLink Web site:

https://metalink.oracle.com

Supported Storage Options for Oracle Clusterware Files

Storage Option	OCR and Voting Disks	Oracle Software
Automatic Storage Management	No	No
General Parallel File System (GPFS)	Yes	Yes
 Note: Oracle does not recommend the use of GPFS for voting disks if HACMP is used. 		
Local storage	No	Yes

Table 4–1 (Cont.) Supported Storage Options for Oracle Clusterware Files

Storage Option	OCR and Voting Disks	Oracle Software
NFS file system	Yes	Yes
 Note: Requires a certified NAS device. Oracle does not recommend the use of NFS for voting disks if HACMP is used. 		
Raw Logical Volumes Managed by HACMP	Yes	No
 Note: If HACMP is used, then voting disks can only be placed on raw devices or logical volumes. 		

Use the following guidelines when choosing the storage options that you want to use for each file type:

- You can choose any combination of the supported storage options for each file type, provided that you satisfy all requirements listed for the chosen storage options.
- You cannot use Automatic Storage Management to store Oracle Clusterware files, because these files must be accessible before any Automatic Storage Management instance starts.
- If you do not have a storage option that provides external file redundancy, then you must configure at least three voting disk areas to provide voting disk redundancy.

4.1.1.3 Quorum Disk Location Restriction with Existing 9.2 Clusterware Installations

When upgrading your Oracle9i release 9.2 Oracle RAC environment to Oracle Database 11g Release 1 (11.1), you are prompted to specify one or more voting disks during the Oracle Clusterware installation. You must specify a new location for the voting disk in Oracle Database 11g Release 1 (11.1). You cannot reuse the old Oracle9i release 9.2 quorum disk for this purpose.

4.1.1.4 After You Have Selected Disk Storage Options

When you have determined your disk storage options, you must perform the following tasks in the order listed:

1: Check for available shared storage with CVU

Refer to Checking for Available Shared Storage with CVU on page 4-4

2: Configure shared storage for Oracle Clusterware files

- To use a file system (local or GPFS) for Oracle Clusterware files, refer to Configuring Storage for Oracle Clusterware Files on a Supported Shared File System on page 4-4
- To use raw devices (partitions) for Oracle Clusterware files, refer to "Configuring Storage for Oracle Clusterware Files on Raw Devices" on page 4-7

3: Configure storage for Oracle Database files and recovery files

To use a file system for database or recovery file storage, refer to Section 4.2, "Configuring Storage for Oracle Clusterware Files on a Supported Shared File System" on page 4-4, and ensure that in addition to the volumes you create for Oracle Clusterware files, you also create additional volumes with sizes sufficient to store database files.

See Also: Section 5.4, "Configuring Storage for Oracle Database Files on a Supported Shared File System"

4.1.2 Checking for Available Shared Storage with CVU

To check for all shared file systems available across all nodes on the cluster with GPFS, use the following command:

/mountpoint/runcluvfy.sh comp ssa -n node_list

If you want to check the shared accessibility of a specific shared storage type to specific nodes in your cluster, then use the following command syntax:

/mountpoint/runcluvfy.sh comp ssa -n node_list -s storageID_list

In the preceding syntax examples, the variable mountpoint is the mountpoint path of the installation media, the variable node_list is the list of nodes you want to check, separated by commas, and the variable storage ID list is the list of storage device IDs for the storage devices managed by the file system type that you want to check.

For example, if you want to check the shared accessibility from node1 and node2 of storage devices /dev/rhdisk8 and /dev/rhdisk9, and your mountpoint is /dev/dvdrom/, then enter the following command:

/dev/dvdrom/runcluvfy.sh comp ssa -n node1, node2 -s /dev/rhdisk8, /dev/rhdisk9

If you do not specify specific storage device IDs in the command, then the command searches for all available storage devices connected to the nodes on the list.

4.2 Configuring Storage for Oracle Clusterware Files on a Supported **Shared File System**

Oracle Universal Installer (OUI) does not suggest a default location for the Oracle Cluster Registry (OCR) or the Oracle Clusterware voting disk. If you choose to create these files on a file system, then review the following sections to complete storage requirements for Oracle Clusterware files:

- Requirements for Using a File System for Oracle Clusterware Files
- Checking NFS Mount and Buffer Size Parameters for Oracle Clusterware
- Creating Required Directories for Oracle Clusterware Files on Shared File Systems

Note: Database Configuration Assistant uses the OCR for storing the configurations for the cluster databases that it creates. The OCR is a shared file in a cluster file system environment. If you do not use a cluster file system, then you must make this file a shared raw device. Oracle Universal Installer (OUI) automatically initializes the OCR during the Oracle Clusterware installation.

4.2.1 Requirements for Using a File System for Oracle Clusterware Files

To use a file system for Oracle Clusterware files, the file system must comply with the following requirements.

- To use a cluster file system on AIX, you must use GPFS.
- If you choose to place your Oracle Cluster Registry (OCR) files on a shared file system, then one of the following must be true:
 - The disks used for the file system are on a highly available storage device, (for example, a RAID device that implements file redundancy),
 - At least two file systems are mounted, and use the features of Oracle Database 11g Release 1 (11.1) to provide redundancy for the OCR.
- If you intend to use a shared file system to store database files, then use at least two independent file systems, with the database files on one file system, and the recovery files on a different file system.
- The Oracle Clusterware owner (-, oracle) must have write permissions to create the files in the path that you specify.

Note: If you are upgrading from Oracle9*i* release 2, then you can continue to use the raw device or shared file that you used for the SRVM configuration repository instead of creating a new file for the OCR.

If you are upgrading Oracle Clusterware, and your existing cluster uses 100 MB OCR and 20 MB voting disk partitions, then you can continue to use those partition sizes.

Use Table 4–2 to determine the partition size for shared file systems.

Table 4–2 Shared File System Volume Size Requirements

File Types Stored	Number of Volumes	Volume Size
Oracle Clusterware files (OCR and voting disks) with external redundancy	1	At least 280 MB for each volume
Oracle Clusterware files (OCR and voting disks) with redundancy provided by Oracle software	1	At least 280 MB for each volume
Redundant Oracle Clusterware files with redundancy provided by Oracle software (mirrored OCR and two additional voting disks)	1	At least 280 MB of free space for each OCR location, if the OCR is configured on a file system or
		At least 280 MB available for each OCR location if the OCR is configured on raw devices.
		and
		At least 280 MB for each voting disk location, with a minimum of three disks.

In Table 4–2, the total required volume size is cumulative. For example, to store all Oracle Clusterware files on the shared file system with normal redundancy, you

should have at least 1.3 GB of storage available over a minimum of three volumes (two separate volume locations for the OCR and OCR mirror, and one voting disk on each volume).

4.2.2 Checking NFS Mount and Buffer Size Parameters for Oracle Clusterware

If you are using NFS, then you must set the values for the NFS buffer size parameters rsize and wsize to 32768. The NFS mount options are:

```
cio, rw, bg, hard, intr, rsize=32768, wsize=32768, tcp, noac, vers=3, timeo=600
```

Update the /etc/fstab file on each node with an entry similar to the following:

```
nfs server:/vol/CWfiles /u01/oracle/cwfiles nfs \
cio, rw, bg, hard, intr, rsize=32768, wsize=32768, tcp, noac, vers=3, timeo=600
```

Note that mount point options are different for Oracle software binaries, Oracle Clusterware files (OCR and voting disks), and data files.

If you want to create a mount point for binaries only, then enter the following line for a binaries mount point:

```
nfs_server:/vol/crshome /u01/oracle/crs nfs -yes
rw, bg, hard, nointr, rsize=32768, wsize=32768, proto=tcp, vers=3, timeo=600
```

See Also: Oracle *MetaLink* bulletin 359515.1, "Mount Options for Oracle Files When Used with NAS Devices" for the most current information about mount options, available from the following URL:

```
http://metalink.oracle.com
```

Note: Refer to your storage vendor documentation for additional information about mount options.

4.2.3 Creating Required Directories for Oracle Clusterware Files on Shared File **Systems**

Use the following instructions to create directories for Oracle Clusterware files. You can also configure shared file systems for the Oracle Database and recovery files.

Note: For GPFS storage, you must complete this procedure only if you want to place the Oracle Clusterware files on a separate file system to the Oracle base directory.

To create directories for the Oracle Clusterware files on separate file systems from the Oracle base directory, follow these steps:

If necessary, configure the shared file systems that you want to use and mount them on each node.

Note: The mount point that you use for the file system must be identical on each node. Make sure that the file systems are configured to mount automatically when a node restarts.

- 2. Use the df -k command to determine the free disk space on each mounted file system.
- **3.** From the display, identify the file systems that you want to use:

File Type File System Requirements	
Oracle Clusterware files	Choose a file system with at least 560 MB of free disk space (one OCR and one voting disk, with external redundancy).

If you are using the same file system for more than one type of file, then add the disk space requirements for each type to determine the total disk space requirement.

- **4.** Note the names of the mount point directories for the file systems that you identified.
- 5. If the user performing installation has permissions to create directories on the disks where you plan to install Oracle Clusterware, then OUI creates the Oracle Clusterware file directory.

If the user performing installation does not have write access, then you must create these directories manually using commands similar to the following to create the recommended subdirectories in each of the mount point directories and set the appropriate owner, group, and permissions on them:

- Oracle Clusterware file directory:
 - # mkdir /mount_point/oracrs
 - # chown oracle:oinstall /mount_point/oracrs
 - # chmod 750 /mount_point/oracrs

Note: After installation, directories in the installation path for the Oracle Cluster Registry (OCR) files should be owned by root, and not writable by any account other than root.

When you have completed creating subdirectories in each of the mount point directories, and set the appropriate owner, group, and permissions, you have completed GPFS configuration.

4.3 Configuring Storage for Oracle Clusterware Files on Raw Devices

The following subsections describe how to configure Oracle Clusterware files on raw partitions.

- Identifying Required Raw Partitions for Clusterware Files
- Configuring Raw Disk Devices for Oracle Clusterware Without HACMP or GPFS
- Configuring HACMP Multinode Disk Heartbeat (MNDHB) for Oracle Clusterware
- Configuring Raw Logical Volumes for Oracle Clusterware
- Creating a Volume Group for Oracle Clusterware
- Configuring Raw Logical Volumes in the New Oracle Clusterware Volume Group

- Importing the Volume Group on the Other Cluster Nodes
- Activating the Volume Group in Concurrent Mode on All Cluster Nodes

4.3.1 Identifying Required Raw Partitions for Clusterware Files

Table 4–3 lists the number and size of the raw partitions that you must configure for Oracle Clusterware files.

Note: Because each file requires exclusive use of a complete disk device, Oracle recommends that, if possible, you use disk devices with sizes that closely match the size requirements of the files that they will store. You cannot use the disks that you choose for these files for any other purpose.

Table 4–3 Raw Partitions Required for Oracle Clusterware Files on AIX

Number	Size for Each Partition (MB)	Purpose
2	256	Oracle Cluster Registry
(or 1, if you have external redundancy		Note: Create these raw partitions only once on the cluster. If you create more than one database on the cluster, then they all share the same Oracle Cluster Registry (OCR).
support for this file)		You should create two partitions: One for the OCR, and one for a mirrored OCR.
uno me		If you are upgrading from Oracle9 <i>i</i> release 2, then you can continue to use the raw device that you used for the SRVM configuration repository instead of creating this new raw device.
3	256	Oracle Clusterware voting disks
(or 1, if you have external redundancy		Note: Create these raw partitions only once on the cluster. If you create more than one database on the cluster, then they all share the same Oracle Clusterware voting disk.
support for this file)		You should create three partitions: One for the voting disk, and two for additional voting disks.

4.3.2 Configuring Raw Disk Devices for Oracle Clusterware Without HACMP or GPFS

If you are installing Oracle RAC on an AIX cluster without HACMP or GPFS, then you must use shared raw disk devices for the Oracle Clusterware files. You can also use shared raw disk devices for database file storage. However, Oracle recommends that you use Automatic Storage Management to store database files in this situation.

This section describes how to configure the shared raw disk devices for Oracle Clusterware files (Oracle Cluster Registry and Oracle Clusterware voting disk). It also describes how to configure shared raw devices for Oracle ASM and for Database files, if you intend to install Oracle Database, and you need to create new disk devices.

Note: In the following procedure, you are directed to set physical volume IDs (PVIDs) to confirm that all devices appear under the same name on all nodes. Oracle recommends that you complete the entire procedure, even if you are certain that you do not have PVIDs configured on your system, to prevent the possibility of configuration issues.

To configure shared raw disk devices for Oracle Clusterware files:

1. Identify or configure the required disk devices.

The disk devices must be shared on all of the cluster nodes.

As the root user, enter the following command on any node to identify the device names for the disk devices that you want to use:

```
# /usr/sbin/lspv | grep -i none
```

This command displays information similar to the following for each disk device that is not configured in a volume group:

```
hdisk17
                0009005fb9c23648
                                                      None
```

In this example, hdisk17 is the device name of the disk and 0009005fb9c23648 is the physical volume ID (PVID).

If a disk device that you want to use does not have a PVID, then enter a command similar to the following to assign one to it:

```
# chdev -1 hdiskn -a pv=yes
```

Note: If you have an existing PVID, then chdev will overwrite the existing PVID, which will cause applications depending on the previous PVID to fail.

On each of the other nodes, enter a command similar to the following to identify the device name associated with each PVID on that node:

```
# /usr/sbin/lspv | grep -i "0009005fb9c23648"
```

The output from this command should be similar to the following:

```
hdisk18
                0009005fb9c23648
```

In this example, the device name associated with the disk device (hdisk18) is different on this node.

- If the device names are the same on all nodes, then enter commands similar to the following on all nodes to change the owner, group, and permissions on the character raw device files for the disk devices:
 - OCR device:

```
# chown root:oinstall /dev/rhdiskn
```

- # chmod 640 /dev/rhdiskn
- Other devices:

```
# chown oracle:dba /dev/rhdiskn
```

- # chmod 660 /dev/rhdiskn
- **6.** If the device name associated with the PVID for a disk that you want to use is different on any node, then you must create a new device file for the disk on each of the nodes using a common unused name.

For the new device files, choose an alternative device file name that identifies the purpose of the disk device. The previous table suggests alternative device file

names for each file. For database files, replace dbname in the alternative device file name with the name that you chose for the database in step 1.

Note: Alternatively, you could choose a name that contains a number that will never be used on any of the nodes, for example hdisk99.

To create a new common device file for a disk device on all nodes, perform these steps on each node:

a. Enter the following command to determine the device major and minor numbers that identify the disk device, where *n* is the disk number for the disk device on this node:

```
# ls -alF /dev/*hdiskn
```

The output from this command is similar to the following:

```
brw----- 1 root system
                         24,8192 Dec 05 2001 /dev/hdiskn
crw----- 1 root system 24,8192 Dec 05 2001 /dev/rhdiskn
```

In this example, the device file /dev/rhdiskn represents the character raw device, 24 is the device major number, and 8192 is the device minor number.

b. Enter a command similar to the following to create the new device file, specifying the new device file name and the device major and minor numbers that you identified in the previous step:

Note: In the following example, you must specify the c flag to create a character raw device file.

```
# mknod /dev/ora_ocr_raw_256m c 24 8192
```

- **c.** Enter commands similar to the following to change the owner, group, and permissions on the character raw device file for the disk:
 - OCR:

```
# chown root:oinstall /dev/ora_ocr_raw_256m
# chmod 640 /dev/ora_ocr_raw_256m
```

Oracle Clusterware voting disk:

```
# chown oracle:dba /dev/ora_vote_raw_256m
# chmod 660 /dev/ora_vote_raw_256m
```

d. Enter a command similar to the following to verify that you have created the new device file successfully:

```
# ls -alF /dev | grep "24,8192"
```

The output should be similar to the following:

```
brw----- 1 root system 24,8192 Dec 05 2001 /dev/hdiskn
crw-r---- 1 root     oinstall 24,8192 Dec 05 2001 /dev/ora_ocr_raw_256m
crw----- 1 root system 24,8192 Dec 05 2001 /dev/rhdiskn
```

7. To enable simultaneous access to a disk device from multiple nodes, you must set the appropriate Object Data Manager (ODM) attribute, depending on the type of reserve attribute used by your disks. The following section describes how to

perform this task using hdisk logical names. Refer to your operating system documentation to find logical device names.

To determine the reserve setting your disks use, enter the following command, where *n* is the hdisk device number:

```
# lsattr -E -l hdiskn | grep reserve_
```

The response is either a reserve_lock setting, or a reserve_policy setting. If the attribute is reserve lock, then ensure that the setting is reserve lock = no. If the attribute is reserve_policy, then ensure that the setting is reserve_ policy = no_reserve.

If necessary, change the setting with the chdev command using the following syntax, where *n* is the hdisk device number:

```
chdev -l hdiskn -a [ reserve_lock=no | reserve_policy=no_reserve ]
```

For example, to change a setting for the device hdisk4 from reserve_lock=yes to reserve_lock=no, enter the following command:

```
# chdev -l hdisk4 -a reserve_lock=no
```

To verify that the setting is correct on all disk devices, enter the following command:

```
# lsattr -El hdiskn | grep reserve
```

8. Enter commands similar to the following on any node to clear the PVID from each disk device that you want to use:

```
# /usr/sbin/chdev -l hdiskn -a pv=clear
```

When you are installing Oracle Clusterware, you must enter the paths to the appropriate device files when prompted for the path of the OCR and Oracle Clusterware voting disk, for example:

/dev/rhdisk10

4.3.3 Configuring HACMP Multinode Disk Heartbeat (MNDHB) for Oracle Clusterware

This section contains the following topics:

- Overview of Requirements for Using HACMP with Oracle Clusterware
- Deploying HACMP and MDNDHB for Oracle Clusterware
- Upgrading an Existing Oracle Clusterware and HACMP Installation

4.3.3.1 Overview of Requirements for Using HACMP with Oracle Clusterware

You must define one Multi-node Disk Heartbeat (MNDHB) network for each Oracle Clusterware voting disk. Each MNDHB and voting disk pair must be located on a single hard disk, separate from the other pairs. You must also configure MNDHB so that the node is halted if access is lost to a quorum of the MNDHB networks in the enhanced concurrent volume group.

To reduce the likelihood of a cluster partition, IBM recommends that HACMP is deployed with multiple IP networks and at least one non-IP network. The non-IP networks can be implemented using RS232 or disk heart-beating. For systems using Oracle RAC and HACMP enhanced concurrent resources (enhanced concurrent logical volumes) for database storage, you must configure MNDHB networks.

Install, configure and have HACMP running before installing Oracle Clusterware. For an Oracle RAC configuration, do not use HACMP for IP failovers on the Oracle RAC network interfaces (public, VIP or private). These network interfaces should not be configured to use HACMP IP failover, as Oracle Clusterware manages VIP failovers for Oracle RAC. The RAC network interfaces are bound to individual nodes and RAC instances. Problems can occur with Oracle Clusterware if HACMP reconfigures IP addresses over different interfaces, or fails over addresses across nodes. You only can use HACMP for failover of IP address on Oracle RAC nodes if Oracle RAC does not use these addresses.

4.3.3.2 Deploying HACMP and MDNDHB for Oracle Clusterware

Complete the following tasks, replacing each term in italics with the appropriate response for your system, or carrying out the action described and entering the appropriate response for your image:

- **1.** Start HACMP.
- 2. Enter the following command to ensure that the HACMP clcomdES daemon is running:

```
# lssrc -s clcomdES
```

If the daemon is not running, then start it using the following command:

```
# startsrc -s clcomdES
```

- 3. Ensure that your versions of HACMP and AIX meet the system requirements listed in Section 2.7, "Checking the Software Requirements".
- **4.** Create HACMP cluster and add the Oracle Clusterware nodes. For example:

```
# smitty cm_add_change_show_an_hacmp_cluster.dialog
* Cluster Name [mycluster]
```

5. Create an HACMP cluster node for each Oracle Clusterware node. For example:

```
# smitty cm_add_a_node_to_the_hacmp_cluster_dialog
* Node Name [mycluster_node1]
Communication Path to Node []
```

6. Create HACMP Ethernet heartbeat networks. The HACMP configuration requires network definitions. Select NO for the IP address takeover for these networks, since they are used by Oracle Clusterware.

Create at least two network definitions: one for the Oracle public interface and a second one for the Oracle private (cluster interconnect) network. Additional Ethernet heartbeat networks can be added if desired.

For example:

```
# smitty cm_add_a_network_to_the_hacmp_cluster_select
- select ether network
* Network Name [my_network_name]
* Network Type ether
* Netmask [my.network.netmask.here]
* Enable IP Address Takeover via IP Aliases [No]
IP Address Offset for Heart beating over IP Aliases []
```

7. For each of the networks added in the previous step, define all of the IP names for each Oracle Clusterware node associated with that network, including the public, private and VIP names for each Oracle Clusterware node. For example:

```
# smitty cm add communication interfaces devices.select
- select: Add Pre-defined Communication Interfaces and Devices / Communication
Interfaces / desired network
* IP Label/Address [node_ip_address]
* Network Type ether
* Network Name some network name
* Node Name [my_node_name]
Network Interface []
```

8. Create an HACMP resource group for the enhanced concurrent volume group resource with the following options:

```
# smitty config_resource_group.dialog.custom
* Resource Group Name [my_resource_group_name]
* Participating Nodes (Default Node Priority) [mynode1, mynode2, mynode3]
Startup Policy Online On All Available Nodes
Fallover Policy Bring Offline (On Error Node Only)
Fallback Policy Never Fallback
```

9. Create an AIX enhanced concurrent volume group (Big VG, or Scalable VG) using either the command smitty mkvg, or using command lines. The VG must contain at least one hard disk for each voting disk. You must configure at least three voting disks.

In the following example, where you see *default*, accept the default response:

```
# smitty _mksvg
VOLUME GROUP name [my_vg_name] PP SIZE in MB
* PHYSICAL VOLUME names [mydisk1, mydisk2, mydisk3]
Force the creation of a volume group? no
Activate volume group AUTOMATICALLY no at system restart?
Volume Group MAJOR NUMBER []
Create VG Concurrent Capable? enhanced concurrent
Max PPs per VG in kilobytes default
Max Logical Volumes default
```

10. Under "Change/Show Resources for a Resource Group (standard)", add the concurrent volume group to the resource group added in the preceding steps.

For example:

```
# smitty cm_change_show_resources_std_resource_group_menu_dmn.select
- select_resource_group_from_step_6
Resource Group Name shared_storage
Participating Nodes (Default Node Priority) mynode1, mynode2, mynode3
Startup Policy Online On All Available Nodes
Fallover Policy Bring Offline (On Error Node Only)
Fallback Policy Never Fallback
Concurrent Volume Groups [enter_VG_from_step_7]
Use forced varyon of volume groups, if necessary false
Application Servers []
```

11. Using the following command, ensure that one MNDHB network is defined for each Oracle Clusterware voting disk. Each MNDHB and voting disk pair must be collocated on a single hard disk, separate from the other pairs. The MNDHB network and Voting Disks exist on shared logical volumes in an enhanced concurrent logical volume managed by HACMP as an enhanced concurrent resource. For each of the hard disks in the VG created in step 6 on which you want to place a voting disk logical volume (LV), create a MNDHB LV.

```
# smitty cl_add_mndhb_lv
```

```
- select_resource_group_defined_in_step_6
* Physical Volume name enter F4, then select a hard disk
Logical Volume Name []
Logical Volume Label []
Volume Group name ccvg
Resource Group Name shared storage
Network Name [n]
```

Note: When you define the LVs for the Oracle Clusterware voting disks, they should be defined on the same disks: one for each disk, as used in this step for the MNDHB LVs.

12. Configure MNDHB so that the node is halted if access is lost to a quorum of the MNDHB networks in the enhanced concurrent volume group. For example:

```
# smitty cl set mndhb response
- select_the_VG_created_in_step_7
On loss of access Halt the node
Optional notification method []
Volume Group ccvq
```

13. Verify and Synchronize HACMP configuration. For example:

```
# smitty cm_initialization_and_standard_config_menu_dmn
- select "Verify and Synchronize HACMP Configuration"
```

Enter Yes if prompted: "Would you like to import shared VG: ccvg, in resource group my_resource_group onto node: mynode to node: racha702 [Yes / No]:"

14. Add the Add the HACMP cluster node IP names to the file /usr/es/sbin/cluster/etc/rhosts.

4.3.3.3 Upgrading an Existing Oracle Clusterware and HACMP Installation

Complete the following procedure:

- 1. Back up all databases, and back up the Oracle Cluster Registry (OCR)
- Shut down on all nodes all Oracle RAC databases, all node applications, and Oracle Clusterware.
- **3.** Enter the following command to disable Oracle Clusterware from starting when nodes are restarted:

```
# crsctl disable crs
```

- 4. Shut down HACMP on all nodes.
- Install HACMP APAR IZ01809, following the directions in the README included with that APAR.
- 6. Determine if the existing voting disk LVs are already on separate hard disks, and if each of these disks have sufficient space (at least 256 MB for the MNDHB LVs. If this is true, then create a MNDHB LV on each of the hard disks. If this is not true, then create new MNDHB LVs and new voting disk LVs, located on separate hard disks using the following command, responding to the sections in italics with the appropriate information for your system:

```
# smitty cl_add_mndhb_lv
```

⁻ Select_resource_group

^{*} Physical Volume name Enter F4, then select disk for the MNDHB and Voting Disk

```
pair
Logical Volume Name []
Logical Volume Label []
Volume Group name ccvg
Resource Group Name shared_storage
Network Name [net_diskhbmulti_01]
```

- **7.** Verify and Synchronize HACMP configuration.
- Start HACMP on all nodes.
- 9. If you added new LVs for voting disks in step 5, then replace each of the existing voting disks with the new ones.
- **10.** Enter the following command to re-enable Oracle Clusterware:

```
# crsctl enable CRS
```

11. Start Oracle Clusterware on all nodes, and verify that all resources start correctly.

4.3.4 Configuring Raw Logical Volumes for Oracle Clusterware

Note: To use raw logical volumes for Oracle Clusterware, HACMP must be installed and configured on all cluster nodes.

This section describes how to configure raw logical volumes for Oracle Clusterware and database file storage. The procedures in this section describe how to create a new volume group that contains the logical volumes required for both types of files.

Before you continue, review the following guidelines which contain important information about using volume groups with this release of Oracle RAC:

- You must use concurrent-capable volume groups for Oracle Clusterware.
- The Oracle Clusterware files require less than 560 MB of disk space, with external redundancy. To make efficient use of the disk space in a volume group, Oracle recommends that you use the same volume group for the logical volumes for both the Oracle Clusterware files and the database files.
- If you are upgrading an existing Oracle9i release 2 Oracle RAC installation that uses raw logical volumes, then you can use the existing SRVM configuration repository logical volume for the OCR and create a new logical volume in the same volume group for the Oracle Clusterware voting disk. However, you must remove this volume group from the HACMP concurrent resource group that activates it before you install Oracle Clusterware.

See Also: The HACMP documentation for information about removing a volume group from a concurrent resource group.

Note: If you are upgrading a database, then you must also create a new logical volume for the SYSAUX tablespace. Refer to the "Configuring Raw Logical Volumes in the New Oracle Clusterware Volume Group" section on page 4-18 for more information about the requirements for the Oracle Clusterware voting disk and SYSAUX logical volumes.

You must use a HACMP concurrent resource group to activate new or existing volume groups that contain only database files (not Oracle Clusterware files).

See Also: The HACMP documentation for information about adding a volume group to a new or existing concurrent resource group.

- All volume groups that you intend to use for Oracle Clusterware must be activated in concurrent mode before you start the installation.
- The procedures in this section describe how to create basic volumes groups and volumes. If you want to configure more complex volumes, (using mirroring, for example), then use this section in conjunction with the HACMP documentation.

4.3.5 Creating a Volume Group for Oracle Clusterware

To create a volume group for the Oracle Clusterware files:

- If necessary, install the shared disks that you intend to use.
- To ensure that the disks are available, enter the following command on every node:

```
# /usr/sbin/lsdev -Cc disk
```

The output from this command is similar to the following:

```
hdiskO Available 1A-09-00-8,0 16 Bit LVD SCSI Disk Drive
hdisk1 Available 1A-09-00-9,0 16 Bit LVD SCSI Disk Drive
hdisk2 Available 17-08-L SSA Logical Disk Drive
```

- **3.** If a disk is not listed as available on any node, then enter the following command to configure the new disks:
 - # /usr/sbin/cfgmgr
- Enter the following command on any node to identify the device names and any associated volume group for each disk:

```
# /usr/sbin/lspv
```

The output from this command is similar to the following:

```
hdisk0
         0000078752249812 rootvg
hdisk1
         none
hdisk4
         00034b6fd4ac1d71 ccvq1
```

For each disk, this command shows:

- The disk device name
- Either the 16 character physical volume identifier (PVID) if the disk has one, or none
- Either the volume group to which the disk belongs, or none

The disks that you want to use may have a PVID, but they must not belong to existing volume groups.

- If a disk that you want to use for the volume group does not have a PVID, then enter a command similar to the following to assign one to it:
 - # /usr/sbin/chdev -l hdiskn -a pv=yes

To identify used device major numbers, enter the following command on each node of the cluster:

```
# ls -la /dev | more
```

This command displays information about all configured devices, similar to the following:

```
crw-rw---- 1 root
                               45, 0 Jul 19 11:56 vg1
                      system
```

In this example, 45 is the major number of the vg1 volume group device.

- **7.** Identify an appropriate major number that is unused on all nodes in the cluster.
- To create a volume group, enter a command similar to the following, or use SMIT (smit mkvg):

```
# /usr/sbin/mkvg -y VGname -B -s PPsize -V majornum -n \
-C PhysicalVolumes
```

The following table describes the options and variables used in this example. Refer to the mkvg man page for more information about these options.

Command Option	SMIT Field	Sample Value and Description
-y VGname	VOLUME GROUP name	oracle_vg1
		Specify the name for the volume group. The name that you specify could be a generic name, as shown, or it could specify the name of the database that you intend to create.
-y VGname	VOLUME GROUP name	oracle_vg1
		Specify the name for the volume group. The name that you specify could be a generic name, as shown, or for a database volume group, it could specify the name of the database that you intend to create.
-В	Create a big VG format Volume Group	Specify this option to create a big VG format volume group.
		Note: If you are using SMIT, then choose yes for this field.
-s PPsize	Physical partition SIZE in megabytes	32
		Specify the size of the physical partitions for the database. The sample value shown enables you to include a disk up to 32 GB in size (32 MB * 1016).
-V Majornum	Volume Group MAJOR NUMBER	46
		Specify the device major number for the volume group that you identified in Step 7.

Command Option	SMIT Field	Sample Value and Description
-n	Activate volume group AUTOMATICALLY at system restart	Specify this option to prevent the volume group from being activated at system restart.
		Note: If you are using SMIT, then choose no for this field.
-C	Create VG Concurrent Capable	Specify this option to create a concurrent capable volume group.
		Note: If you are using SMIT, then choose yes for this field.
PhysicalVolumes	PHYSICAL VOLUME names	hdisk3 hdisk4
		Specify the device names of the disks that you want to add to the volume group.

^{10.} Enter a command similar to the following to vary on the volume group that you created:

4.3.6 Configuring Raw Logical Volumes in the New Oracle Clusterware Volume Group

To create the required raw logical volumes in the new Oracle Clusterware volume group:

- **1.** Identify the logical volumes that you must create.
- 2. If you prefer, you can also use the command smit mklv to create raw logical volumes.

The following example shows the command used to create a logical volume for the ocr volume group in the SYSAUX tablespace with a physical partition size of 114 MB (1792/7 = 256):

```
# /usr/sbin/mklv -y test_sysaux_raw_1792m -T O -w n -s n -r n ocr 7
```

3. Change the owner, group, and permissions on the character device files associated with the logical volumes that you created, as follows:

Note: The device file associated with the Oracle Cluster Registry must be owned by root. All other device files must be owned by the Oracle software owner user (oracle).

```
# chown oracle:dba /dev/rora_vote_raw_256m
# chmod 660 /dev/rora_vote_raw_256m
# chown root:oinstall /dev/rora_ocr_raw_256m
# chmod 640 /dev/rora_ocr_raw_256m
```

4.3.7 Importing the Volume Group on the Other Cluster Nodes

To make the volume group available to all nodes in the cluster, you must import it on each node, as follows:

Because the physical volume names may be different on the other nodes, enter the following command to determine the PVID of the physical volumes used by the volume group:

^{# /}usr/sbin/varyonvg VGname

- # /usr/sbin/lspv
- **2.** Note the PVIDs of the physical devices used by the volume group.
- 3. To vary off the volume group that you want to use, enter a command similar to the following on the node where you created it:
 - # /usr/sbin/varyoffvg VGname
- On each cluster node, complete the following steps:
 - Enter the following command to determine the physical volume names associated with the PVIDs you noted previously:
 - # /usr/sbin/lspv
 - **b.** On each node of the cluster, enter commands similar to the following to import the volume group definitions:
 - # /usr/sbin/importvg -y VGname -V MajorNumber PhysicalVolume

In this example, MajorNumber is the device major number for the volume group and Physical Volume is the name of one of the physical volumes in the volume group.

For example, to import the definition of the oracle_vg1 volume group with device major number 45 on the hdisk3 and hdisk4 physical volumes, enter the following command:

- # /usr/sbin/importvg -y oracle_vg1 -V 45 hdisk3
- **c.** Change the owner, group, and permissions on the character device files associated with the logical volumes you created, as follows:

```
# chown oracle:dba /dev/rora_vote_raw_256m
# chmod 660 /dev/rora_vote_raw_256m
# chown root:oinstall /dev/rora_ocr_raw_256m
```

- # chmod 640 /dev/rora_ocr_raw_256m
- **d.** Enter the following command to ensure that the volume group will not be activated by the operating system when the node starts:
 - # /usr/sbin/chvg -a n VGname

4.3.8 Activating the Volume Group in Concurrent Mode on All Cluster Nodes

To activate the volume group in concurrent mode on all cluster nodes, enter the following command on each node:

/usr/sbin/varyonvg -c VGname

Configuring Oracle Real Application Clusters Storage

This chapter includes storage administration tasks that you should complete if you intend to use Oracle Clusterware with Oracle Real Application Clusters (Oracle RAC).

This chapter contains the following topics:

- Reviewing Storage Options for Oracle Database and Recovery Files
- Checking for Available Shared Storage with CVU
- Choosing a Storage Option for Oracle Database Files
- Configuring Storage for Oracle Database Files on a Supported Shared File System
- Configuring Storage for Oracle Database Files on Shared Storage Devices
- Configuring Disks for Automatic Storage Management
- Configuring Database File Storage on Raw Devices
- Desupport of the Database Configuration Assistant Raw Device Mapping File
- Checking the System Setup with CVU

5.1 Reviewing Storage Options for Oracle Database and Recovery Files

This section describes supported options for storing Oracle Database files, and data files.

See Also: The Oracle Certify site for a list of supported vendors for Network Attached Storage options:

http://www.oracle.com/technology/support/metalink/

Refer also to the Certify site on Oracle Metalink for the most current information about certified storage options:

https://metalink.oracle.com/

5.1.1 Overview of Oracle Database and Recovery File Options

There are three ways of storing Oracle Database and recovery files:

Automatic Storage Management: Automatic Storage Management (ASM) is an integrated, high-performance database file system and disk manager for Oracle Database files. It performs striping and mirroring of database files automatically. **Note:** For Standard Edition Oracle Database installations using Oracle RAC, ASM is the only supported storage option.

Only one ASM instance is permitted for each node regardless of the number of database instances on the node.

- A supported shared file system: Supported file systems include the following:
 - General Parallel File System (GPFS): Note that if you intend to use GPFS for your data files, then you should create partitions large enough for the database files when you create partitions for Oracle Clusterware. If you intend to store Oracle Clusterware files on GPFS, then you must ensure that GPFS volume sizes are at least 500 MB each.
 - NAS Network File System (NFS) listed on Oracle Certify: Note that if you intend to use NFS for your data files, then you should create partitions large enough for the database files when you create partitions for Oracle Clusterware.

See Also: The Certify page on Oracle *Metalink* for supported Network Attached Storage (NAS) devices, and supported cluster file systems

Raw Devices: A partition is required for each database file. If you do not use ASM, then for new installations on raw devices, you must use a custom installation.

5.1.2 General Storage Considerations for Oracle RAC

For all installations, you must choose the storage option that you want to use for Oracle Database files, or for Oracle Clusterware with Oracle RAC. If you want to enable automated backups during the installation, then you must also choose the storage option that you want to use for recovery files (the Fast recovery area). You do not have to use the same storage option for each file type.

For single-instance Oracle Database installations using Oracle Clusterware for failover, you must use ASM, or shared raw disks, if you do not want the failover processing to include dismounting and remounting of local file systems.

The following table shows the storage options supported for storing Oracle Database files and Oracle Database recovery files. Oracle Database files include data files, control files, redo log files, the server parameter file, and the password file.

Note: For the most up-to-date information about supported storage options for Oracle RAC installations, refer to the Certify pages on the Oracle*MetaLink* Web site:

https://metalink.oracle.com

Table 5–1 Supported Storage Options for Oracle Database and Recovery Files

Storage Option	File Types Supported		
	Database	Recovery	
Automatic Storage Management	Yes	Yes	

Table 5–1 (Cont.) Supported Storage Options for Oracle Database and Recovery Files

Storage Option	File Types Supported		
	Database	Recovery	
General Parallel File System (GPFS)	Yes	Yes	
■ Note: You cannot place ASM files on GPFS.			
Local storage	No	No	
NFS file system	Yes	Yes	
 Note: Requires a certified NAS device 			
Raw Logical Volumes Managed by HACMP	Yes	Yes	

Use the following guidelines when choosing the storage options that you want to use for each file type:

- You can choose any combination of the supported storage options for each file type provided that you satisfy all requirements listed for the chosen storage options.
- Oracle recommends that you choose Automatic Storage Management (ASM) as the storage option for database and recovery files.
- For Standard Edition Oracle RAC installations, ASM is the only supported storage option for database or recovery files.
- If you intend to use ASM with Oracle RAC, and you are configuring a new ASM instance, then your system must meet the following conditions:
 - All nodes on the cluster have the 11*g* release 1 (11.1) version of Oracle Clusterware installed.
 - Any existing ASM instance on any node in the cluster is shut down.
- If you intend to upgrade an existing Oracle RAC database, or an Oracle RAC database with ASM instances, then you must ensure that your system meets the following conditions:
 - Oracle Universal Installer (OUI) and Database Configuration Assistant (DBCA) are run on the node where the Oracle RAC database or Oracle RAC database with ASM instance is located.
 - The Oracle RAC database or Oracle RAC database with an ASM instance is running on the same nodes that you intend to make members of the new cluster installation. For example, if you have an existing Oracle RAC database running on a three-node cluster, then you must install the upgrade on all three nodes. You cannot upgrade only 2 nodes of the cluster, removing the third instance in the upgrade.

See Also: *Oracle Database Upgrade Guide* for information about how to prepare for upgrading an existing database

If you do not have a storage option that provides external file redundancy, then you must configure at least three voting disk areas to provide voting disk redundancy.

5.1.3 After You Have Selected Disk Storage Options

After you have installed and configured Oracle Clusterware storage, and after you have reviewed your disk storage options for Oracle Database files, you must perform the following tasks in the order listed:

1: Check for available shared storage with CVU

Refer to Section 5.2, "Checking for Available Shared Storage with CVU."

2: Configure storage for Oracle Database files and recovery files

- To use a shared file system for database or recovery file storage, refer to Section 5.4, "Configuring Storage for Oracle Database Files on a Supported Shared File System," and ensure that in addition to the volumes you create for Oracle Clusterware files, you also create additional volumes with sizes sufficient to store database files.
- To use Automatic Storage Management for database or recovery file storage, refer to Section 5.6, "Configuring Disks for Automatic Storage Management."
- To use shared devices for database file storage, refer to Section 5.5, "Configuring Storage for Oracle Database Files on Shared Storage Devices."

Note: If you choose to configure database files on raw devices, note that you must complete database software installation first, and then configure storage after installation.

You cannot use OUI to configure a database that uses raw devices for storage.

5.2 Checking for Available Shared Storage with CVU

To check for all shared file systems available across all nodes on the cluster on a supported shared file system, log in as the installation owner user (oracle or crs), and use the following syntax:

```
/mountpoint/runcluvfy.sh comp ssa -n node_list
```

If you want to check the shared accessibility of a specific shared storage type to specific nodes in your cluster, then use the following command syntax:

```
/mountpoint/runcluvfy.sh comp ssa -n node_list -s storageID_list
```

In the preceding syntax examples, the variable mountpoint is the mountpoint path of the installation media, the variable node_list is the list of nodes you want to check, separated by commas, and the variable *storageID_list* is the list of storage device IDs for the storage devices managed by the file system type that you want to check.

For example, if you want to check the shared accessibility from node1 and node2 of storage devices /dev/rhdisk6 and /dev/rhdisk7, and your mountpoint is /dev/dvdrom/, then enter the following command:

```
$ /mnt/dvdrom/runcluvfy.sh comp ssa -n node1,node2 -s /dev/rhdisk6,/dev/rhdisk7
```

If you do not specify storage device IDs in the command, then the command searches for all available storage devices connected to the nodes on the list.

5.3 Choosing a Storage Option for Oracle Database Files

Database files consist of the files that make up the database, and the recovery area files. There are five options for storing database files:

- General Parallel File System (GPFS)
- Network File System (NFS)
- Automatic Storage Management (ASM)
- Raw devices managed by HACMP

During configuration of Oracle Clusterware, if you selected GPFS or NFS, and the volumes that you created are large enough to hold the database files and recovery files, then you have completed required preinstallation steps. You can proceed to Chapter 6, "Installing Oracle Clusterware."

If you want to place your database files on ASM, then proceed to Section 5.6, "Configuring Disks for Automatic Storage Management."

If you want to place your database files on raw devices, and manually provide storage management for your database and recovery files, then proceed to Section 5.7, "Configuring Database File Storage on Raw Devices."

Note: Databases can consist of a mixture of ASM files and non-ASM files. Refer to Oracle Database Administrator's Guide for additional information about ASM.

5.4 Configuring Storage for Oracle Database Files on a Supported Shared File System

Review the following sections to complete storage requirements for Oracle Database files:

- Requirements for Using a File System for Oracle Database Files
- Deciding to Use NFS for Data Files
- Deciding to Use Direct NFS for Datafiles
- Enabling Direct NFS Client Oracle Disk Manager Control of NFS
- Disabling Direct NFS Client Oracle Disk Management Control of NFS
- Checking NFS Mount Buffer Size Parameters for Oracle RAC
- Creating Required Directories for Oracle Database Files on Shared File Systems

5.4.1 Requirements for Using a File System for Oracle Database Files

To use a file system for Oracle Database files, the file system must comply with the following requirements:

- To use an NFS file system, it must be on a certified NAS device.
- If you choose to place your database files on a shared file system, then one of the following must be true:
 - The disks used for the file system are on a highly available storage device, (for example, a RAID device that implements file redundancy).

- The file systems consist of at least two independent file systems, with the database files on one file system, and the recovery files on a different file system.
- The oracle user must have write permissions to create the files in the path that you specify.

Use Table 5–2 to determine the partition size for shared file systems.

Table 5–2 Shared File System Volume Size Requirements

File Types Stored	Number of Volumes	Volume Size
Oracle Database files	1	At least 1.5 GB for each volume
Recovery files	1	At least 2 GB for each volume
Note : Recovery files must be on a different volume than database files		

In Table 5–2, the total required volume size is cumulative. For example, to store all database files on the shared file system, you should have at least 3.4 GB of storage available over a minimum of two volumes.

5.4.2 Deciding to Use NFS for Data Files

Network-attached storage (NAS) systems use NFS to access data. You can store data files on a supported NFS system.

NFS file systems must be mounted and available over NFS mounts before you start installation. Refer to your vendor documentation to complete NFS configuration and mounting.

5.4.3 Deciding to Use Direct NFS for Datafiles

This section contains the following information about Direct NFS:

- About Direct NFS Storage
- Using the Oranfstab File with Direct NFS
- Mounting NFS Storage Devices with Direct NFS
- Specifying Network Paths with the Oranfstab File

5.4.3.1 About Direct NFS Storage

With Oracle Database 11g release 1 (11.1), instead of using the operating system kernel NFS client, you can configure Oracle Database to access NFS V3 servers directly using an Oracle internal Direct NFS client.

To enable Oracle Database to use Direct NFS, the NFS file systems must be mounted and available over regular NFS mounts before you start installation. The mount options used in mounting the file systems are not relevant, as Direct NFS manages settings after installation. Refer to your vendor documentation to complete NFS configuration and mounting.

Some NFS file servers require NFS clients to connect using reserved ports. If your filer is running with reserved port checking, then you must disable it for Direct NFS to operate. To disable reserved port checking, consult your NFS file server documentation.

5.4.3.2 Using the Oranfstab File with Direct NFS

If you use Direct NFS, then you can choose to use a new file specific for Oracle datafile management, oranfstab, to specify additional options specific for Oracle Database to Direct NFS. For example, you can use oranfstab to specify additional paths for a mount point. You can add the oranfstab file either to /etc or to \$ORACLE_ HOME/dbs. The oranfstab file is not required to use NFS or Direct NFS.

With Oracle RAC installations, if you want to use Direct NFS, then you must replicate the file /etc/oranfstab on all nodes, and keep each /etc/oranfstab file synchronized on all nodes.

When the oranfstab file is placed in \$ORACLE_HOME/dbs, the entries in the file are specific to a single database. In this case, all nodes running an Oracle RAC database use the same \$ORACLE_HOME/dbs/oranfstab file.

When the oranfstab file is placed in /etc, then it is globally available to all Oracle databases, and can contain mount points used by all Oracle databases running on nodes in the cluster, including single-instance databases. However, on Oracle RAC systems, if the oranfstab file is placed in /etc, then you must replicate the file /etc/oranfstab file on all nodes, and keep each /etc/oranfstab file synchronized on all nodes, just as you must with the /etc/fstab file.

In all cases, mount points must be mounted by the kernel NFS system, even when they are being served using Direct NFS.

5.4.3.3 Mounting NFS Storage Devices with Direct NFS

Direct NFS determines mount point settings to NFS storage devices based on the configurations in /etc/filesystems.

Direct NFS searches for mount entries in the following order:

- \$ORACLE HOME/dbs/oranfstab
- 2. /etc/oranfstab
- /etc/filesystems

Direct NFS uses the first matching entry found.

Note: You can have only one active Direct NFS implementation for each instance. Using Direct NFS on an instance will prevent another Direct NFS implementation.

If Oracle Database uses Direct NFS mount points configured using oranfstab, then it first verifies kernel NFS mounts by cross-checking entries in oranfstab with operating system NFS mount points. If a mismatch exists, then Direct NFS logs an informational message, and does not serve the NFS server.

If Oracle Database is unable to open an NFS server using Direct NFS, then Oracle Database uses the platform operating system kernel NFS client. In this case, the kernel NFS mount options must be set up as defined in Section 5.4.6, "Checking NFS Mount Buffer Size Parameters for Oracle RAC." Additionally, an informational message will be logged into the Oracle alert and trace files indicating that Direct NFS could not be established.

The Oracle files resident on the NFS server that are served by the Direct NFS Client are also accessible through the operating system kernel NFS client. The usual considerations for maintaining integrity of the Oracle files apply in this situation.

5.4.3.4 Specifying Network Paths with the Oranfstab File

Direct NFS can use up to four network paths defined in the oranfstab file for an NFS server. The Direct NFS client performs load balancing across all specified paths. If a specified path fails, then Direct NFS reissues I/O commands over any remaining paths.

Use the following views for Direct NFS management:

- **v\$dnfs_servers**: Shows a table of servers accessed using Direct NFS.
- v\$dnfs_files: Shows a table of files currently open using Direct NFS.
- v\$dnfs_channels: Shows a table of open network paths (or channels) to servers for which Direct NFS is providing files.
- **v\$dnfs_stats**: Shows a table of performance statistics for Direct NFS.

5.4.4 Enabling Direct NFS Client Oracle Disk Manager Control of NFS

Complete the following procedure to enable Direct NFS:

- 1. Create an oranfstab file with the following attributes for each NFS server to be accessed using Direct NFS:
 - **Server**: The NFS server name.
 - Path: Up to four network paths to the NFS server, specified either by IP address, or by name, as displayed using the ifconfig command.
 - **Export**: The exported path from the NFS server.
 - **Mount**: The local mount point for the NFS server.

Note: On Linux and UNIX platforms, the location of the oranfstab file is \$ORACLE_HOME/dbs.

The following is an example of an oranfstab file with two NFS server entries:

```
server: MyDataServer1
path: 132.34.35.12
path: 132.34.35.13
export: /vol/oradata1 mount: /mnt/oradata1
server: MyDataServer2
path: NfsPath1
path: NfsPath2
path: NfsPath3
path: NfsPath4
export: /vol/oradata2 mount: /mnt/oradata2
export: /vol/oradata3 mount: /mnt/oradata3
export: /vol/oradata4 mount: /mnt/oradata4
export: /vol/oradata5 mount: /mnt/oradata5
```

- 2. Oracle Database uses an ODM library, libnfsodm10.so, to enable Direct NFS. To replace the standard ODM library, \$ORACLE_HOME/lib/libodm10.so, with the ODM NFS library, libnfsodm10.so, complete the following steps:
 - Change directory to \$ORACLE_HOME/lib.
 - **b.** Enter the following commands:

```
cp libodm10.so libodm10.so_stub
ln -s libnfsodm10.so libodm10.so
```

5.4.5 Disabling Direct NFS Client Oracle Disk Management Control of NFS

Use one of the following methods to disable the Direct NFS client:

- Remove the oranfstab file.
- Restore the stub libodm10. so file by reversing the process you completed in step 2b in Section 5.4.4, "Enabling Direct NFS Client Oracle Disk Manager Control of NFS."
- Remove the specific NFS server or export paths in the oranfstab file.

Note: If you remove an NFS path that Oracle Database is using, then you must restart the database for the change to be effective.

5.4.6 Checking NFS Mount Buffer Size Parameters for Oracle RAC

If you are using NFS, then you must set the values for the NFS buffer size parameters rsize and wsize to 32768.

If you are using Direct NFS, then you must set write size values (wtmax) to at least 32768.

Update the /etc/fstab file on each node with an entry similar to the following:

```
nfs_server:/vol/DATA/oradata /u02/oradata
cio,rw,bg,hard,intr,rsize=32768,wsize=32768,tcp,noac,vers=3,timeo=600
```

Note: Refer to your storage vendor documentation for additional information about mount options.

5.4.7 Creating Required Directories for Oracle Database Files on Shared File Systems

Use the following instructions to create directories for shared file systems for Oracle Database and recovery files (for example, for a RAC database).

If necessary, configure the shared file systems that you want to use and mount them on each node.

Note: The mount point that you use for the file system must be identical on each node. Ensure that the file systems are configured to mount automatically when a node restarts.

- **2.** Use the df -k command to determine the free disk space on each mounted file system.
- **3.** From the display, identify the file systems that you want to use:

File Type	File System Requirements	
Database files	Choose either:	
	 A single file system with at least 1.5 GB of free disk space. 	
	■ Two or more file systems with at least 1.5 GB of free disk space in total.	
Recovery files	Choose a file system with at least 2 GB of free disk space.	

If you are using the same file system for more than one type of file, then add the disk space requirements for each type to determine the total disk space requirement.

- **4.** Note the names of the mount point directories for the file systems that you identified.
- If the user performing installation (typically, oracle) has permissions to create directories on the disks where you plan to install Oracle Database, then DBCA creates the Oracle Database file directory, and the Recovery file directory.

If the user performing installation does not have write access, then you must create these directories manually using commands similar to the following to create the recommended subdirectories in each of the mount point directories and set the appropriate owner, group, and permissions on them:

- Database file directory:
 - # mkdir /mount_point/oradata
 - # chown oracle:oinstall /mount_point/oradata
 - # chmod 775 /mount_point/oradata
- Recovery file directory (Fast recovery area):
 - # mkdir /mount_point/Fast_recovery_area
 - # chown oracle:oinstall /mount_point/Fast_recovery_area
 - # chmod 775 /mount_point/Fast_recovery_area

By making the oracle user the owner of these directories, this permits them to be read by multiple Oracle homes, including those with different OSDBA groups.

When you have completed creating subdirectories in each of the mount point directories, and set the appropriate owner, group, and permissions, you have completed NFS configuration for Oracle Database shared storage.

5.5 Configuring Storage for Oracle Database Files on Shared Storage **Devices**

The following subsections describe how to configure Oracle Clusterware files on raw devices.

- Planning Your Shared Storage Device Creation Strategy
- Identifying Required Shared Partitions for Database Files

5.5.1 Planning Your Shared Storage Device Creation Strategy

Before installing the Oracle Database 11g release 1 (11.1) software with Oracle RAC, create enough partitions of specific sizes to support your database, and also leave a few spare partitions of the same size for future expansion. For example, if you have space on your shared disk array, then select a limited set of standard partition sizes for your entire database. Partition sizes of 50 MB, 100 MB, 500 MB, and 1 GB are suitable for most databases. Also, create a few very small and a few very large spare partitions that are (for example) 1 MB and perhaps 5 GB or greater in size. Based on your plans for using each partition, determine the placement of these spare partitions by combining different sizes on one disk, or by segmenting each disk into same-sized partitions.

Note: Be aware that each instance has its own redo log files, but all instances in a cluster share the control files and data files. In addition, each instance's online redo log files must be readable by all other instances to enable recovery.

In addition to the minimum required number of partitions, you should configure spare partitions. Doing this enables you to perform emergency file relocations or additions if a tablespace data file becomes full.

5.5.2 Identifying Required Shared Partitions for Database Files

Note: For new installations, Oracle recommends that you do not use raw devices for database files.

Table 5–3 lists the number and size of the shared partitions that you must configure for database files.

Table 5–3 Shared Devices or Logical Volumes Required for Database Files on AIX

Number	Partition Size (MB)	Purpose
1	800	SYSTEM tablespace
1	400 + (Number of instances * 250)	SYSAUX tablespace
Number of instances	500	UNDOTBSn tablespace (One tablespace for each instance)
1	250	TEMP tablespace
1	160	EXAMPLE tablespace
1	120	USERS tablespace
2 * number of instances	120	Two online redo log files for each instance
2	110	First and second control files
1	5	Server parameter file (SPFILE)
1	5	Password file

Note: If you prefer to use manual undo management, instead of automatic undo management, then, instead of the UNDOTBSn shared storage devices, you must create a single rollback segment tablespace (RBS) on a shared storage device partition that is at least 500 MB in size.

5.6 Configuring Disks for Automatic Storage Management

This section describes how to configure disks for use with Automatic Storage Management. Before you configure the disks, you must determine the number of disks and the amount of free disk space that you require. The following sections describe how to identify the requirements and configure the disks:

- Identifying Storage Requirements for Automatic Storage Management
- Using an Existing Automatic Storage Management Disk Group
- Configuring Database File Storage for Automatic Storage Management and Raw Devices

Note: Although this section refers to disks, you can also use zero-padded files on a certified NAS storage device in an Automatic Storage Management disk group. Refer to *Oracle* Database Installation Guide for AIX 5L Based Systems (64-Bit) for information about creating and configuring NAS-based files for use in an Automatic Storage Management disk group.

If you intend to use Hitachi HDLM (dmlf devices) for storage, then ASM instances do not automatically discover the physical disks, but instead discover only the logical volume manager (LVM) disks. This is because the physical disks can only be opened by programs running as root.

Physical disk paths have path names similar to the following:

/dev/rdlmfdrv8 /dev/rdlmfdrv9

5.6.1 Identifying Storage Requirements for Automatic Storage Management

To identify the storage requirements for using Automatic Storage Management, you must determine how many devices and the amount of free disk space that you require. To complete this task, follow these steps:

Determine whether you want to use Automatic Storage Management for Oracle Database files, recovery files, or both.

Note: You do not have to use the same storage mechanism for database files and recovery files. You can use the file system for one file type and Automatic Storage Management for the other.

For Oracle RAC installations, if you choose to enable automated backups and you do not have a shared file system available, you must choose Automatic Storage Management for recovery file storage.

If you enable automated backups during the installation, you can choose Automatic Storage Management as the storage mechanism for recovery files by specifying an Automatic Storage Management disk group for the Fast recovery area. Depending on how you choose to create a database during the installation, you have the following options:

If you select an installation method that runs Database Configuration Assistant in interactive mode (for example, by choosing the Advanced database configuration option), then you can decide whether you want to use the same Automatic Storage Management disk group for database files and recovery files, or use different disk groups for each file type.

The same choice is available to you if you use Database Configuration Assistant after the installation to create a database.

- If you select an installation method that runs Database Configuration Assistant in non-interactive mode, you must use the same Automatic Storage Management disk group for database files and recovery files.
- 2. Choose the Automatic Storage Management redundancy level that you want to use for the Automatic Storage Management disk group.

The redundancy level that you choose for the Automatic Storage Management disk group determines how Automatic Storage Management mirrors files in the disk group and determines the number of disks and amount of disk space that you require, as follows:

External redundancy

An external redundancy disk group requires a minimum of one disk device. The effective disk space in an external redundancy disk group is the sum of the disk space in all of its devices.

Because Automatic Storage Management does not mirror data in an external redundancy disk group, Oracle recommends that you use only RAID or similar devices that provide their own data protection mechanisms as disk devices in this type of disk group.

Normal redundancy

In a normal redundancy disk group, Automatic Storage Management uses two-way mirroring by default, to increase performance and reliability. A normal redundancy disk group requires a minimum of two disk devices (or two failure groups). The effective disk space in a normal redundancy disk group is *half* the sum of the disk space in all of its devices.

For most installations, Oracle recommends that you use normal redundancy disk groups.

High redundancy

In a high redundancy disk group, Automatic Storage Management uses three-way mirroring to increase performance and provide the highest level of reliability. A high redundancy disk group requires a minimum of three disk devices (or three failure groups). The effective disk space in a high redundancy disk group is *one-third* the sum of the disk space in all of its devices.

While high redundancy disk groups do provide a high level of data protection, you should consider the greater cost of additional storage devices before deciding to select high redundancy disk groups.

Determine the total amount of disk space that you require for the database files and recovery files.

Use the following table to determine the minimum number of disks and the minimum disk space requirements for installing the starter database:

Redundancy Level	Minimum Number of Disks	Database Files	Recovery Files	Both File Types
External	1	1.15 GB	2.3 GB	3.45 GB
Normal	2	2.3 GB	4.6 GB	6.9 GB
High	3	3.45 GB	6.9 GB	10.35 GB

For Oracle RAC installations, you must also add additional disk space for the Automatic Storage Management metadata. You can use the following formula to calculate the additional disk space requirements (in MB):

15 + (2 * number_of_disks) + (126 * number_of_Automatic_Storage_Management_ instances)

For example, for a four-node Oracle RAC installation, using three disks in a high redundancy disk group, you require an additional 525 MB of disk space:

$$15 + (2 * 3) + (126 * 4) = 525$$

If an Automatic Storage Management instance is already running on the system, then you can use an existing disk group to meet these storage requirements. If necessary, you can add disks to an existing disk group during the installation.

The following section describes how to identify existing disk groups and determine the free disk space that they contain.

4. Optionally, identify failure groups for the Automatic Storage Management disk group devices.

Note: Complete this step only if you intend to use an installation method that runs Database Configuration Assistant in interactive mode, for example, if you intend to choose the Custom installation type or the Advanced database configuration option. Other installation types do not enable you to specify failure groups.

If you intend to use a normal or high redundancy disk group, then you can further protect your database against hardware failure by associating a set of disk devices in a custom failure group. By default, each device comprises its own failure group. However, if two disk devices in a normal redundancy disk group are attached to the same SCSI controller, then the disk group becomes unavailable if the controller fails. The controller in this example is a single point of failure.

To protect against failures of this type, you could use two SCSI controllers, each with two disks, and define a failure group for the disks attached to each controller. This configuration would enable the disk group to tolerate the failure of one SCSI controller.

Note: If you define custom failure groups, you must specify a minimum of two failure groups for normal redundancy disk groups and three failure groups for high redundancy disk groups.

- 5. If you are sure that a suitable disk group does not exist on the system, then install or identify appropriate disk devices to add to a new disk group. Use the following guidelines when identifying appropriate disk devices:
 - All of the devices in an Automatic Storage Management disk group should be the same size and have the same performance characteristics.
 - Do not specify more than one partition on a single physical disk as a disk group device. Automatic Storage Management expects each disk group device to be on a separate physical disk.
 - Although you can specify a logical volume as a device in an Automatic Storage Management disk group, Oracle does not recommend their use. Logical volume managers can hide the physical disk architecture, preventing Automatic Storage Management from optimizing I/O across the physical devices.

For information about completing this task, refer to section Section 5.6.3, "Configuring Database File Storage for Automatic Storage Management and Raw Devices."

5.6.2 Using an Existing Automatic Storage Management Disk Group

If you want to store either database or recovery files in an existing Automatic Storage Management disk group, then you have the following choices, depending on the installation method that you select:

- If you select an installation method that runs Database Configuration Assistant in interactive mode (for example, by choosing the Advanced database configuration option), then you can decide whether you want to create a disk group, or to use an existing one.
 - The same choice is available to you if you use Database Configuration Assistant after the installation to create a database.
- If you select an installation method that runs Database Configuration Assistant in noninteractive mode, then you must choose an existing disk group for the new database; you cannot create a disk group. However, you can add disk devices to an existing disk group if it has insufficient free space for your requirements.

Note: The Automatic Storage Management instance that manages the existing disk group can be running in a different Oracle home directory.

To determine if an existing Automatic Storage Management disk group exists, or to determine if there is sufficient disk space in a disk group, you can use Oracle

Enterprise Manager Grid Control or Database Control. Alternatively, you can use the following procedure:

 View the contents of the oratab file to determine whether an Automatic Storage Management instance is configured on the system:

```
$ more /etc/oratab
```

If an Automatic Storage Management instance is configured on the system, the oratab file should contain a line similar to the following:

```
+ASM2:oracle_home_path:N
```

In this example, +ASM2 is the system identifier (SID) of the Automatic Storage Management instance, with node number appended, and oracle_home_path is the Oracle home directory where it is installed. By convention, the SID for an Automatic Storage Management instance begins with a plus sign.

- 2. Set the ORACLE_SID and ORACLE_HOME environment variables to specify the appropriate values for the Automatic Storage Management instance that you want to use.
- **3.** Connect to the Automatic Storage Management instance as the SYS user with SYSDBA privilege and start the instance if necessary:

```
$ $ORACLE_HOME/bin/sqlplus "SYS/SYS_password as SYSDBA"
SQL> STARTUP
```

4. Enter the following command to view the existing disk groups, their redundancy level, and the amount of free disk space in each one:

```
SQL> SELECT NAME, TYPE, TOTAL_MB, FREE_MB FROM V$ASM_DISKGROUP;
```

- **5.** From the output, identify a disk group with the appropriate redundancy level and note the free space that it contains.
- 6. If necessary, install or identify the additional disk devices required to meet the storage requirements listed in the previous section.

Note: If you are adding devices to an existing disk group, Oracle recommends that you use devices that have the same size and performance characteristics as the existing devices in that disk group.

5.6.3 Configuring Database File Storage for Automatic Storage Management and Raw **Devices**

To configure disks for use with Automatic Storage Management on AIX, follow these steps:

- 1. On AIX-based systems, you must apply Program Technical Fix (PTF) U496549 or higher to your system before you use ASM.
- 2. If necessary, install the shared disks that you intend to use for the Automatic Storage Management disk group and restart the system.
- **3.** To make sure that the disks are available, enter the following command on every node:

```
# /usr/sbin/lsdev -Cc disk
```

The output from this command is similar to the following:

```
hdiskO Available 1A-09-00-8,0 16 Bit LVD SCSI Disk Drive
hdisk1 Available 1A-09-00-9,0 16 Bit LVD SCSI Disk Drive
hdisk2 Available 17-08-L SSA Logical Disk Drive
```

- If a disk is not listed as available on any node, then enter the following command to configure the new disks:
 - # /usr/sbin/cfgmgr
- Enter the following command on any node to identify the device names for the physical disks that you want to use:

```
# /usr/sbin/lspv | grep -i none
```

This command displays information similar to the following for each disk that is not configured in a volume group:

```
0000078752249812
hdisk2
```

In this example, hdisk2 is the device name of the disk and 0000078752249812 is the physical volume ID (PVID). The disks that you want to use might have a PVID, but they must not belong to a volume group.

- Enter commands similar to the following to clear the PVID from each disk device that you want to use:
 - # /usr/sbin/chdev -l hdiskn -a pv=clear

Note: If the disk device has a PVID, then ASM will fail to mount the diskgroup created on the disk device.

7. On each of the other nodes, enter a command similar to the following to identify the device name associated with each PVID on that node:

```
# /usr/sbin/lspv | grep -i 0000078752249812
```

The output from this command should be similar to the following:

```
hdisk18
               0000078752249812
                                       None
```

Depending on how each node is configured, the device names may differ between nodes. Note that you will clear PVIDs later in this procedure.

- If the device names are the same on all nodes, then enter commands similar to the following on all nodes to change the owner, group, and permissions on the character raw device files for the disk devices you want to use with ASM datafiles:
 - # chown oracle:dba /dev/rhdiskn # chmod 660 /dev/rhdiskn
- If PVIDs are configured, and the device name associated with the PVID for a disk that you want to use is different on any node, then you must create a new device file for the disk on each of the nodes using a common unused name.

For the new device files, choose an alternative device file name that identifies the purpose of the disk device. Table 5-4 suggests alternative device file names for each file. For database files, replace dbname in the alternative device file name with the name that you chose for the database in step 1.

Note: Alternatively, you can choose a name that contains a number that will never be used on any of the nodes, for example hdisk99.

To create a new common device file for a disk device on all nodes, follow these steps on each node:

a. Enter the following command to determine the device major and minor numbers that identify the disk device, where *n* is the disk number for the disk device on this node:

```
# ls -alF /dev/*hdiskn
```

The output from this command is similar to the following:

```
brw----- 1 root system
                         24,8192 Dec 05 2001 /dev/hdiskn
crw----- 1 root system 24,8192 Dec 05 2001 /dev/rhdiskn
```

In this example, the device file /dev/rhdiskn represents the character raw device, 24 is the device major number, and 8192 is the device minor number.

b. Enter a command similar to the following to create the new device file, specifying the new device file name and the device major and minor numbers that you identified in the previous step:

Note: In the following example, you must specify the character c to create a character raw device file.

```
# mknod /dev/ora_ocr_raw_256m c 24 8192
```

- **c.** Enter commands similar to the following to change the owner, group, and permissions on the character raw device file for the disk:
 - OCR:

```
# chown root:oinstall /dev/ora_ocr_raw_256m
# chmod 640 /dev/ora_ocr_raw_256m
```

Voting disk or database files:

```
# chown oracle:dba /dev/ora_vote_raw_256m
# chmod 660 /dev/ora_vote_raw_256m
```

d. Enter a command similar to the following to verify that you have created the new device file successfully:

```
# ls -alF /dev | grep "24,8192"
```

The output should be similar to the following:

```
brw----- 1 root system 24,8192 Dec 05 2001 /dev/hdiskn
crw-r---- 1 root     oinstall 24,8192 Dec 05 2001 /dev/ora_ocr_raw_256m
crw----- 1 root system 24,8192 Dec 05 2001 /dev/rhdiskn
```

10. To enable simultaneous access to a disk device from multiple nodes, you must set the appropriate Object Data Manager (ODM) attribute listed in the following table to the value shown, depending on the disk type:

Disk Type	Attribute	Value
SSA or FAStT disks	reserve_lock	no
ESS, EMC, HDS, CLARiiON, or MPIO-capable disks	reserve_policy	no_reserve

To determine whether the attribute has the correct value, enter a command similar to the following on all cluster nodes for each disk device that you want to use:

```
# /usr/sbin/lsattr -E -l hdiskn
```

If the required attribute is not set to the correct value on any node, enter a command similar to one of the following on that node:

- SSA and FAStT devices:
 - # /usr/sbin/chdev -l hdiskn -a reserve_lock=no
- ESS, EMC, HDS, CLARiiON, and MPIO-capable devices:
 - # /usr/sbin/chdev -l hdiskn -a reserve_policy=no_reserve
- 11. Enter commands similar to the following on any node to clear the PVID from each disk device that you want to use:
 - # /usr/sbin/chdev -l hdiskn -a pv=clear
- **12.** Enter commands similar to the following on every node to change the owner, group, and permissions on the character raw device file for each disk that you want to add to the disk group:
 - # chown oracle:dba /dev/rhdiskn
 - # chmod 660 /dev/rhdiskn

Note: If you are using a multi-pathing disk driver with ASM, then ensure that you set the permissions only on the correct logical device name for the disk.

The device name associated with a disk may be different on other nodes. Ensure that you specify the correct device name on each node.

When you are installing Oracle Clusterware Services, you must enter the paths to the appropriate device files when prompted for the path of the OCR and voting disk. For example:

/dev/rhdisk10

When you have completed creating and configuring Automatic Storage Management with raw partitions, proceed to Chapter 6, "Installing Oracle Clusterware."

5.7 Configuring Database File Storage on Raw Devices

The following subsections describe how to configure raw partitions for database files.

- Identifying Required Raw Partitions for Database Files
- Configuring Raw Disk Devices for Database File Storage Without HACMP or **GPFS**

- Configuring Raw Logical Volumes for Database File Storage
- Creating a Volume Group for Database Files
- Creating Database File Raw Logical Volumes in the New Volume Group
- Importing the Database File Volume Group on the Other Cluster Nodes
- Activating the Database File Volume Group in Concurrent Mode on All Cluster **Nodes**

5.7.1 Identifying Required Raw Partitions for Database Files

Table 5–4 lists the number and size of the raw partitions that you must configure for database files.

Note: Because each file requires exclusive use of a complete disk device, Oracle recommends that, if possible, you use disk devices with sizes that closely match the size requirements of the files that they will store. You cannot use the disks that you choose for these files for any other purpose.

Table 5–4 Raw Partitions Required for Database Files on AIX

Number	Partition Size (MB)	Purpose and Sample Alternative Device File Name
1	800	SYSTEM tablespace:
		dbname_system_raw_800m
1	400 + (Number of	SYSAUX tablespace:
	instances * 250)	dbname_sysaux_raw_900m
Number of instances	500	UNDOTBS n tablespace (One tablespace for each instance, where n is the number of the instance):
		dbname_undotbsn_raw_500m
1	250	TEMP tablespace:
		dbname_temp_raw_250m
1	160	EXAMPLE tablespace:
		<pre>dbname_example_raw_160m</pre>
1	120	USERS tablespace:
		dbname_users_raw_120m
2 * number of instances	120	Two online redo log files for each instance (where n is the number of the instance and m is the log number, 1 or 2):
		dbname_redon_m_raw_120m
2	110	First and second control files:
		$dbname_control\{1 2\}_raw_110m$
1	5	Server parameter file (SPFILE):
		dbname_spfile_raw_5m
1	5	Password file:
		dbname_pwdfile_raw_5m

Note: If you prefer to use manual undo management, instead of automatic undo management, then, instead of the UNDOTBSn raw devices, you must create a single rollback segment tablespace (RBS) raw device that is at least 500 MB in size.

5.7.2 Configuring Raw Disk Devices for Database File Storage Without HACMP or GPFS

If you are installing Oracle RAC on an AIX cluster without HACMP or GPFS, you can use shared raw disk devices for database file storage. However, Oracle recommends that you use Automatic Storage Management to store database files in this situation. This section describes how to configure the shared raw disk devices for database files.

To configure shared raw disk devices for Oracle Clusterware files, database files, or both:

If you intend to use raw disk devices for database file storage, then specify a name for the database that you want to create.

The name that you specify must start with a letter and have no more than four characters. For example: orcl.

Identify or configure the required disk devices.

The disk devices must be shared on all of the cluster nodes.

As the root user, enter the following command on any node to identify the device names for the disk devices that you want to use:

```
# /usr/sbin/lspv | grep -i none
```

This command displays information similar to the following for each disk device that is not configured in a volume group:

```
hdisk17
                0009005fb9c23648
                                                       None
```

In this example, hdisk17 is the device name of the disk and 0009005fb9c23648 is the physical volume ID (PVID).

If a disk device that you want to use does not have a PVID, then enter a command similar to the following to assign one to it:

```
# /usr/sbin/chdev -l hdiskn -a pv=yes
```

On each of the other nodes, enter a command similar to the following to identify the device name associated with each PVID on that node:

```
# /usr/sbin/lspv | grep -i "0009005fb9c23648"
```

The output from this command should be similar to the following:

```
hdisk18
                0009005fb9c23648
```

In this example, the device name associated with the disk device (hdisk18) is different on this node.

If the device names are the same on all nodes, then enter commands similar to the following on all nodes to change the owner, group, and permissions on the character raw device files for the disk devices you want to use for database files:

```
# chown oracle:dba /dev/rhdiskn
```

[#] chmod 660 /dev/rhdiskn

7. If the device name associated with the PVID for a disk that you want to use is different on any node, then you must create a new device file for the disk on each of the nodes using a common unused name.

For the new device files, choose an alternative device file name that identifies the purpose of the disk device. Table 5–3 suggests alternative device file names for each file. For database files, replace dbname in the alternative device file name with the name that you chose for the database in step 1.

Note: Alternatively, you could choose a name that contains a number that will never be used on any of the nodes, for example hdisk99.

To create a new common device file for a disk device on all nodes, perform these steps on each node:

Enter the following command to determine the device major and minor numbers that identify the disk device, where *n* is the disk number for the disk device on this node:

```
# ls -alF /dev/*hdiskn
```

The output from this command is similar to the following:

```
brw----- 1 root system 24,8192 Dec 05 2001 /dev/hdiskn
crw----- 1 root system 24,8192 Dec 05 2001 /dev/rhdiskn
```

In this example, the device file /dev/rhdiskn represents the character raw device, 24 is the device major number, and 8192 is the device minor number.

b. Enter a command similar to the following to create the new device file, specifying the new device file name (in this example, using an alternative device file name from Table 5–3) and the device major and minor numbers that you identified in the previous step:

Note: As the following example illustrates, you must specify the character c to create a character raw device file.

```
# mknod dbname example raw 160m c 24 8192
```

c. Enter a command similar to the following to verify that you have created the new device file successfully:

```
# ls -alF /dev | grep "24,8192"
```

The output should be similar to the following:

```
brw----- 1 root system 24,8192 Dec 05 2001 /dev/hdiskn
crw-r---- 1 root     oinstall 24,8192 Dec 05 2001 /dev/ora_ocr_raw_256m
crw----- 1 root system 24,8192 Dec 05 2001 /dev/rhdiskn
```

To enable simultaneous access to a disk device from multiple nodes, you must set the appropriate Object Data Manager (ODM) attribute listed in the following table to the value shown, depending on the disk type:

Disk Type	Attribute	Value	
SSA, FAStT, or non-MPIO-capable disks	reserve_lock	no	

Disk Type	Attribute	Value
ESS, EMC, HDS, CLARiiON, or MPIO-capable disks	reserve_policy	no_reserve

To determine whether the attribute has the correct value, enter a command similar to the following on all cluster nodes for each disk device that you want to use:

```
# /usr/sbin/lsattr -E -l hdiskn
```

If the required attribute is not set to the correct value on any node, then enter a command similar to one of the following on that node:

- SSA and FAStT devices
 - # /usr/sbin/chdev -l hdiskn -a reserve_lock=no
- ESS, EMC, HDS, CLARiiON, and MPIO-capable devices
 - # /usr/sbin/chdev -l hdiskn -a reserve_policy=no_reserve
- **9.** Enter commands similar to the following on any node to clear the PVID from each disk device that you want to use:
 - # /usr/sbin/chdev -l hdiskn -a pv=clear
- 10. If you are using raw disk devices for database files, then follow these steps to create the Database Configuration Assistant raw device mapping file:

Note: You must complete this procedure only if you are using raw devices for database files. The Database Configuration Assistant raw device mapping file enables Database Configuration Assistant to identify the appropriate raw disk device for each database file. You do not specify the raw devices for the Oracle Clusterware files in the Database Configuration Assistant raw device mapping file.

- Set the ORACLE_BASE environment variable to specify the Oracle base directory that you identified or created previously:
 - Bourne or Korn shell:
 - \$ ORACLE_BASE=/u01/app/oracle ; export ORACLE_BASE
 - C shell:
 - % setenv ORACLE_BASE /u01/app/oracle
- **b.** Create a database file subdirectory under the Oracle base directory and set the appropriate owner, group, and permissions on it:

```
# mkdir -p $ORACLE_BASE/oradata/dbname
# chown -R oracle:oinstall $ORACLE_BASE/oradata
# chmod -R 775 $ORACLE BASE/oradata
```

In this example, dbname is the name of the database that you chose previously.

- **c.** Change directory to the \$ORACLE_BASE/oradata/dbname directory.
- **d.** Using any text editor, create a text file similar to the following that identifies the disk device file name associated with each database file.

Oracle recommends that you use a file name similar to dbname_raw.conf for this file.

Note: The following example shows a sample mapping file for a two-instance Oracle RAC cluster. Some of the devices use alternative disk device file names. Ensure that the device file name that you specify identifies the same disk device on all nodes.

```
system=/dev/rhdisk11
sysaux=/dev/rhdisk12
example=/dev/rhdisk13
users=/dev/rhdisk14
temp=/dev/rhdisk15
undotbs1=/dev/rhdisk16
undotbs2=/dev/rhdisk17
redo1_1=/dev/rhdisk18
redo1_2=/dev/rhdisk19
redo2_1=/dev/rhdisk20
redo2_2=/dev/rhdisk22
control1=/dev/rhdisk23
control2=/dev/rhdisk24
spfile=/dev/dbname_spfile_raw_5m
pwdfile=/dev/dbname_pwdfile_raw_5m
```

In this example, *dbname* is the name of the database.

Use the following guidelines when creating or editing this file:

Each line in the file must have the following format:

```
database_object_identifier=device_file_name
```

The alternative device file names suggested in Table 5–4 include the database object identifier that you must use in this mapping file. For example, in the following alternative disk device name, redo1_1 is the database object identifier:

```
/dev/rac redo1 1 raw 120m
```

- For an Oracle RAC database, the file must specify one automatic undo tablespace datafile (undotbsn) and two redo log files (redon_1, redon_ 2) for each instance.
- Specify at least two control files (control1, control2).
- To use manual instead of automatic undo management, specify a single RBS tablespace datafile (rbs) instead of the automatic undo management tablespace data files.
- **e.** Save the file and note the file name that you specified.
- When you are configuring the oracle user's environment later in this chapter, set the DBCA_RAW_CONFIG environment variable to specify the full path to this file.
- 11. When you are installing Oracle Clusterware, you must enter the paths to the appropriate device files when prompted for the path of the OCR and Oracle Clusterware voting disk, for example:

```
/dev/rhdisk10
```

5.7.3 Configuring Raw Logical Volumes for Database File Storage

Note: To use raw logical volumes for database file storage, HACMP must be installed and configured on all cluster nodes.

This section describes how to configure raw logical volumes for database file storage. The procedures in this section describe how to create a new volume group that contains the logical volumes required for both types of files.

Before you continue, review the following guidelines which contain important information about using volume groups with this release of Oracle RAC:

- You must use concurrent-capable volume groups for database files.
- Oracle Clusterware files require less than 560 MB of disk space, with external redundancy. To make efficient use of the disk space in a volume group, Oracle recommends that you use the same volume group for the logical volumes for both the Oracle Clusterware files and the database files.
- If you are upgrading a database, then you must also create a new logical volume for the SYSAUX tablespace. Refer to Section 5.7.3, "Configuring Raw Logical Volumes for Database File Storage" for more information about the requirements for the SYSAUX logical volumes.

See Also: The HACMP documentation for information about removing a volume group from a concurrent resource group.

You must use a HACMP concurrent resource group to activate new or existing volume groups that contain only database files (not Oracle Clusterware files).

See Also: The HACMP documentation for information about adding a volume group to a new or existing concurrent resource group.

- All volume groups that you intend to use for database files must be activated in concurrent mode before you start the installation.
- The procedures in this section describe how to create basic volumes groups and volumes. If you want to configure more complex volumes (for example, using mirroring), then use this section in conjunction with the HACMP documentation.

5.7.4 Creating a Volume Group for Database Files

To create a volume group for the Oracle Database files:

- If necessary, install the shared disks that you intend to use.
- To ensure that the disks are available, enter the following command on every node:

```
# /usr/sbin/lsdev -Cc disk
```

The output from this command is similar to the following:

```
hdiskO Available 1A-09-00-8,0 16 Bit LVD SCSI Disk Drive
hdisk1 Available 1A-09-00-9,0 16 Bit LVD SCSI Disk Drive
hdisk2 Available 17-08-L SSA Logical Disk Drive
```

3. If a disk is not listed as available on any node, then enter the following command to configure the new disks:

```
# /usr/sbin/cfgmgr
```

4. Enter the following command on any node to identify the device names and any associated volume group for each disk:

```
# /usr/sbin/lspv
```

The output from this command is similar to the following:

```
hdisk0
         0000078752249812 rootvg
hdisk1 none
hdisk4 00034b6fd4ac1d71 ccvg1
```

For each disk, this command shows:

- The disk device name
- Either the 16 character physical volume identifier (PVID) if the disk has one, or none
- Either the volume group to which the disk belongs, or none

The disks that you want to use may have a PVID, but they must not belong to existing volume groups.

5. If a disk that you want to use for the volume group does not have a PVID, then enter a command similar to the following to assign one to it:

```
# /usr/sbin/chdev -l hdiskn -a pv=yes
```

6. To identify used device major numbers, enter the following command on each node of the cluster:

```
# 1s -la /dev | more
```

This command displays information about all configured devices, similar to the following:

```
crw-rw---- 1 root
                      system
                                45, 0 Jul 19 11:56 vg1
```

In this example, 45 is the major number of the vg1 volume group device.

- 7. Identify an appropriate major number that is unused on all nodes in the cluster.
- **8.** To create a volume group, enter a command similar to the following, or use SMIT (smit mkvg):

```
# /usr/sbin/mkvg -y VGname -B -s PPsize -V majornum -n \
-C PhysicalVolumes
```

The following table describes the options and variables used in this example. Refer to the mkvg man page for more information about these options.

Command Option	SMIT Field	Sample Value an	d Description
-y VGname	VOLUME GROUP	oracle_vg1	
			Specify the name for the volume group. The name that you specify could be a generic name, as shown, or it could specify the name of the database that you intend to create.
-y VGname	VOLUME GROUP	oracle_vg1	
			Specify the name for the volume group. The name that you specify could be a generic name, as shown, or for a database volume group, it could specify the name of the database that you intend to create.
-В	Create a big VG format Volume Group	Specify this option format volume gro	
		Note: If you are us yes for this field.	sing SMIT, then choose
-s PPsize	Physical partition SIZE in megabytes	32	
			Specify the size of the physical partitions for the database. The sample value shown enables you to include a disk up to 32 GB in size (32 MB * 1016).
-V Majornum	Volume Group MAJOR NUMBER	46	
			Specify the device major number for the volume group that you identified in Step 7.

Command Option	SMIT Field	Sample Value and Description
-n	Activate volume group AUTOMATICALLY at system restart	Specify this option to prevent the volume group from being activated at system restart.
		Note: If you are using SMIT, then choose no for this field.
-C	Create VG Concurrent Capable	Specify this option to create a concurrent capable volume group.
		Note: If you are using SMIT, then choose yes for this field.
PhysicalVolumes	PHYSICAL VOLUME names	hdisk3 hdisk4
		Specify the device names of the disks that you want to add to the volume group.

^{10.} Enter a command similar to the following to vary on the volume group that you created:

5.7.5 Creating Database File Raw Logical Volumes in the New Volume Group

To create the required raw logical volumes in the new volume group:

- 1. Choose a name for the database that you want to create.
 - The name that you choose must start with a letter and have no more than four characters, for example, orcl.
- **2.** Identify the logical volumes that you must create.

Table 5–5 lists the number and size of the logical volumes that you must create for database files.

Table 5–5 Raw Logical Volumes Required for Database Files

Number	Size (MB)	Purpose and Sample Logical Volume Name
1	800	SYSTEM tablespace:
		dbname_system_raw_800m
1	400 +	SYSAUX tablespace:
	(Number of instances * 250)	dbname_sysaux_raw_900m
1	500	UNDOTBS1 tablespace:
		dbname_undotbs1_raw_500m
Number of	500	UNDOTBS n tablespace (One tablespace for each instance, where n is the number of the instance):
instances		dbname_undotbsn_raw_500m
1	250	TEMP tablespace:
		dbname_temp_raw_250m
1	160	EXAMPLE tablespace:
		dbname_example_raw_160m

^{# /}usr/sbin/varyonvg VGname

Number Size (MB) Purpose and Sample Logical Volume Name 1 120 **USERS** tablespace: dbname_users_raw_120m 2 120 Two online redo log files (where *m* is the log number, 1 or 2): dbname_redo1_m_raw_120m 2 * 120 Two online redo log files for each instance (where n is the number number of of the instance and m is the log number, 1 or 2): instances dbname_redon_m_raw_120m 110 First and second control files: dbname_control{1|2}_raw_110m 1 5 Server parameter file (SPFILE): dbname_spfile_raw_5m 1 5 Password file: dbname_pwdfile_raw_5m

Table 5–5 (Cont.) Raw Logical Volumes Required for Database Files

To create each required logical volume for data files, Oracle recommends that you use a command similar to the following to create logical volumes with a zero offset:

/usr/sbin/mklv -y LVname -T O -w n -s n -r n VGname NumPPs

In this example:

- LVname is the name of the logical volume that you want to create
- The -T O option specifies that the device subtype should be z, which causes Oracle to use a zero offset when accessing this raw logical volume
- VGname is the name of the volume group where you want to create the logical volume
- NumPPs is the number of physical partitions to use

To determine the value to use for NumPPs, divide the required size of the logical volume by the size of the physical partition and round the value up to an integer. For example, if the size of the physical partition is 32 MB and you want to create a 500 MB logical volume, then you should specify 16 for the NumPPs (500/32 = 15.625).

Using a zero offset improves database performance and fixes the issues described in Oracle bug 2620053.

Note: On raw logical volumes, if you create tablespaces in datafiles that are not created in this way, a message is recorded in the alert.log file.

If you prefer, you can also use the command smit mklv to create raw logical volumes.

The following example shows the command used to create a logical volume for the SYSAUX tablespace of the test database in the oracle_vg1 volume group with a physical partition size of 32 MB (800/32 = 25):

```
# /usr/sbin/mklv -y test_sysaux_raw_900m -T 0 -w n -s n -r n oracle_vq1 25
```

4. Change the owner, group, and permissions on the character device files associated with the logical volumes that you created, as follows:

Note: The device file associated with the Oracle Cluster Registry must be owned by root. All other device files must be owned by the Oracle software owner user (oracle).

```
# chown oracle:dba /dev/rdbname*
```

5.7.6 Importing the Database File Volume Group on the Other Cluster Nodes

To make the database file volume group available to all nodes in the cluster, you must import it on each node, as follows:

- 1. Because the physical volume names may be different on the other nodes, enter the following command to determine the PVID of the physical volumes used by the volume group:
 - # /usr/sbin/lspv
- **2.** Note the PVIDs of the physical devices used by the volume group.
- To vary off the volume group that you want to use, enter a command similar to the following on the node where you created it:
 - # /usr/sbin/varyoffvg VGname
- On each cluster node, complete the following steps:
 - Enter the following command to determine the physical volume names associated with the PVIDs you noted previously:
 - # /usr/sbin/lspv
 - **b.** On each node of the cluster, enter commands similar to the following to import the volume group definitions:

```
# /usr/sbin/importvg -y VGname -V MajorNumber PhysicalVolume
```

In this example, <code>MajorNumber</code> is the device major number for the volume group and Physical Volume is the name of one of the physical volumes in the volume group.

For example, to import the definition of the oracle_vg1 volume group with device major number 45 on the hdisk3 and hdisk4 physical volumes, enter the following command:

```
# /usr/sbin/importvg -y oracle_vg1 -V 45 hdisk3
```

- **c.** Change the owner, group, and permissions on the character device files associated with the logical volumes you created, as follows:
 - # chown oracle:dba /dev/rdbname*
 - # chmod 660 /dev/rdbname*

[#] chmod 660 /dev/rdbname*

d. Enter the following command to ensure that the volume group will not be activated by the operating system when the node starts:

/usr/sbin/chvg -a n VGname

5.7.7 Activating the Database File Volume Group in Concurrent Mode on All Cluster **Nodes**

To activate the volume group in concurrent mode on all cluster nodes, enter the following command on each node:

/usr/sbin/varyonvg -c VGname

5.8 Desupport of the Database Configuration Assistant Raw Device Mapping File

With the release of Oracle Database 11g and Oracle RAC release 11g, configuring raw devices using Database Configuration Assistant is not supported.

5.9 Checking the System Setup with CVU

As the oracle user, use the following command syntax to start Cluster Verification Utility (CVU) stage verification to check hardware, operating system, and storage setup:

/mountpoint/runcluvfy.sh stage -post hwos -n node_list [-verbose]

In the preceding syntax example, replace the variable *node_list* with the names of the nodes in your cluster, separated by commas. For example, to check the hardware and operating system of a two-node cluster with nodes node1 and node2, with the mountpoint /mnt/dvdrom/ and with the option to limit the output to the test results, enter the following command:

\$ /mnt/dvdrom/runcluvfy.sh stage -post hwos -n node1,node2

Select the option -verbose to receive detailed reports of the test results, and progress updates about the system checks performed by Cluster Verification Utility.

Installing Oracle Clusterware

This chapter describes the procedures for installing Oracle Clusterware for AIX Based Systems. If you are installing Oracle Database with Oracle Real Application Clusters (Oracle RAC), then this is phase one of a two-phase installation.

This chapter contains the following topics:

- Verifying Oracle Clusterware Requirements with CVU
- Preparing to Install Oracle Clusterware with OUI
- Installing Oracle Clusterware with OUI
- **Confirming Oracle Clusterware Function**

6.1 Verifying Oracle Clusterware Requirements with CVU

Using the following command syntax, log in as the installation owner user (oracle or crs), and start Cluster Verification Utility (CVU) to check system requirements for installing Oracle Clusterware:

```
/mountpoint/runcluvfy.sh stage -pre crsinst -n node_list
```

In the preceding syntax example, replace the variable mountpoint with the installation media mountpoint, and replace the variable node 1ist with the names of the nodes in your cluster, separated by commas.

For example, for a cluster with mountpoint /mnt/dvdrom/, and with nodes node1, node2, and node3, enter the following command:

```
$ /mnt/dvdrom/runcluvfy.sh stage -pre crsinst -n node1,node2,node3
```

The Cluster Verification Utility Oracle Clusterware preinstallation stage check verifies the following:

- **Node Reachability**: All of the specified nodes are reachable from the local node.
- **User Equivalence**: Required user equivalence exists on all of the specified nodes.
- **Node Connectivity:** Connectivity exists between all the specified nodes through the public and private network interconnections, and at least one subnet exists that connects each node and contains public network interfaces that are suitable for use as virtual IPs (VIPs).
- Administrative Privileges: The oracle user has proper administrative privileges to install Oracle Clusterware on the specified nodes.
- **Shared Storage Accessibility**: If specified, the OCR device and voting disk are shared across all the specified nodes.

- **System Requirements**: All system requirements are met for installing Oracle Clusterware software, including kernel version, kernel parameters, memory, swap directory space, temporary directory space, and required users and groups.
- **Kernel Packages**: All required operating system software packages are installed.
- Node Applications: The virtual IP (VIP), Oracle Notification Service (ONS) and Global Service Daemon (GSD) node applications are functioning on each node.

Note: Avoid changing host names after you complete the Oracle Clusterware installation, including adding or deleting domain qualifications. Nodes with changed host names must be deleted from the cluster and added back with the new name.

6.1.1 Interpreting CVU Messages About Oracle Clusterware Setup

If the Cluster Verification Utility (CVU) report indicates that your system fails to meet the requirements for Oracle Clusterware installation, then use the topics in this section to correct the problem or problems indicated in the report, and run the Cluster Verification Utility command again.

User Equivalence Check Failed

Cause: Failure to establish user equivalency across all nodes. This can be due to not creating the required users, or failing to complete secure shell (SSH) configuration properly.

Action: Cluster Verification Utility provides a list of nodes on which user equivalence failed. For each node listed as a failure node, review the oracle user configuration to ensure that the user configuration is properly completed, and that SSH configuration is properly completed.

See Also: Section 3.1, "Creating Standard Configuration Operating System Groups and Users" and Section 2.9, "Configuring SSH on All Cluster Nodes" for user equivalency configuration instructions

Use the command su - oracle and check user equivalence manually by running the ssh command on the local node with the date command argument using the following syntax:

```
$ ssh node_name date
```

The output from this command should be the timestamp of the remote node identified by the value that you use for node_name. If ssh is in the default location, the /usr/bin directory, then use ssh to configure user equivalence. You can also use rsh to confirm user equivalence.

If you have not attempted to use SSH to connect to the host node before running, then Cluster Verification Utility indicates a user equivalence error. If you see a message similar to the following when entering the date command with SSH, then this is the probable cause of the user equivalence error:

```
The authenticity of host 'node1 (140.87.152.153)' can't be established.
RSA key fingerprint is 7z:ez:e7:f6:f4:f2:4f:8f:9z:79:85:62:20:90:92:z9.
Are you sure you want to continue connecting (yes/no)?
```

Enter yes, and then run Cluster Verification Utility again to determine if the user equivalency error is resolved.

If ssh is in a location other than the default, /usr/bin, then Cluster Verification Utility reports a user equivalence check failure. To avoid this error, navigate to the directory \$CV_HOME/cv/admin, open the file cvu_config with a text editor, and add or update the key ORACLE SRVM REMOTESHELL to indicate the ssh path location on your system. For example:

```
# Locations for ssh and scp commands
ORACLE_SRVM_REMOTESHELL=/usr/local/bin/ssh
ORACLE_SRVM_REMOTECOPY=/usr/local/bin/scp
```

Note the following rules for modifying the cvu_config file:

- Key entries have the syntax name=value
- Each key entry and the value assigned to the key defines one property only
- Lines beginning with the number sign (#) are comment lines, and are ignored
- Lines that do not follow the syntax name=value are ignored

When you have changed the path configuration, run the Cluster Verification Utility check again. If ssh is in another location than the default, you also need to start OUI with additional arguments to specify a different location for the remote shell and remote copy commands. Enter runInstaller -help to obtain information about how to use these arguments.

Note: When you or OUI run ssh or rsh commands, including any login or other shell scripts they start, you may see errors about invalid arguments or standard input if the scripts generate any output. You should correct the cause of these errors.

To stop the errors, remove all commands from the oracle user's login scripts that generate output when you run ssh or rsh commands.

If you see messages about X11 forwarding, then complete the task Section 2.9.5, "Setting Display and X11 Forwarding Configuration" to resolve this issue.

If you see errors similar to the following:

```
stty: standard input: Invalid argument
stty: standard input: Invalid argument
```

These errors are produced if hidden files on the system (for example, .bashrc or .cshrc) contain stty commands. If you see these errors, then refer to Section 2.9.6, "Preventing Oracle Clusterware Installation Errors Caused by stty Commands" to correct the cause of these errors.

Node Reachability Check or Node Connectivity Check Failed

Cause: One or more nodes in the cluster cannot be reached using TCP/IP protocol, through either the public or private interconnects.

Action: Use the command /usr/sbin/ping address to check each node address. When you find an address that cannot be reached, check your list of public and private addresses to make sure that you have them correctly configured. If you use third-party vendor clusterware, then refer to the vendor documentation for assistance. Ensure that the public and private network interfaces have the same interface names on each node of your cluster.

User Existence Check or User-Group Relationship Check Failed

Cause: The administrative privileges for users and groups required for installation are missing or incorrect.

Action: Use the id command on each node to confirm that the oracle user is created with the correct group membership. Ensure that you have created the required groups, and create or modify the user account on affected nodes to establish required group membership.

See Also: Section 3.1, "Creating Standard Configuration Operating System Groups and Users" for instructions about how to create required groups, and how to configure the oracle user

6.2 Preparing to Install Oracle Clusterware with OUI

Before you install Oracle Clusterware with Oracle Universal Installer (OUI), use the following checklist to ensure that you have all the information you will need during installation, and to ensure that you have completed all tasks that must be done before starting to install Oracle Clusterware. Mark the box for each task as you complete it, and write down the information needed, so that you can provide it during installation.

☐ Shut Down Running Oracle Processes

If you are installing Oracle Clusterware on a node that already has a single-instance Oracle Database 11g release 1 (11.1) installation, then stop the existing ASM instances. After Oracle Clusterware is installed, start up the ASM instances again. When you restart the single-instance Oracle database, the ASM instances use the Cluster Synchronization Services (CSSD) Daemon from Oracle Clusterware instead of the CSSDdaemon for the single-instance Oracle database.

You can upgrade some or all nodes of an existing Cluster Ready Services installation. For example, if you have a six-node cluster, then you can upgrade two nodes each in three upgrading sessions. Base the number of nodes that you upgrade in each session on the load the remaining nodes can handle. This is called a "rolling upgrade."

If a Global Services Daemon (GSD) from Oracle9i Release 9.2 or earlier is running, then stop it before installing Oracle Database 11g release 1 (11.1) Oracle Clusterware by running the following command:

\$ Oracle_home/bin/gsdctl stop

where Oracle_home is the Oracle Database home that is running the GSD.

Caution: If you have an existing Oracle9*i* release 2 (9.2) Oracle Cluster Manager (Oracle CM) installation, then *do not* shut down the Oracle CM service. Shutting down the Oracle CM service prevents the Oracle Clusterware 11g release 1 (11.1) software from detecting the Oracle9i release 2 nodelist, and causes failure of the Oracle Clusterware installation.

Note: If you receive a warning to stop all Oracle services after starting OUI, then run the command

Oracle_home/bin/localconfig delete where *Oracle_home* is the home that is running CSS.

Prepare for Clusterware Upgrade If You Have Existing Oracle Cluster Ready **Services Software**

During an Oracle Clusterware installation, if OUI detects an existing Oracle Database 10g release 1 (10.1) Cluster Ready Services (CRS), then you are given the option to perform a rolling upgrade by installing Oracle Database 11g release 1 (11.1) Oracle Clusterware on a subset of cluster member nodes.

If you intend to perform a rolling upgrade, then you should shut down the CRS stack on the nodes you intend to upgrade, and unlock the Oracle Clusterware home using the script mountpoint/clusterware/upgrade/preupdate.sh, which is available on the 11g release 1 (11.1) installation media.

If you intend to perform a standard upgrade, then shut down the CRS stack on all nodes, and unlock the Oracle Clusterware home using the script mountpoint/clusterware/upgrade/preupdate.sh.

When you run OUI and select the option to install Oracle Clusterware on a subset of nodes, OUI installs Oracle Database 11g release 1 (11.1) Oracle Clusterware software into the existing Oracle Clusterware home on the local and remote node subset. When you run the root script, it starts the Oracle Clusterware 11g release 1 (11.1) stack on the subset cluster nodes, but lists it as an inactive version.

When all member nodes of the cluster are running Oracle Clusterware 11g release 1 (11.1), then the new clusterware becomes the active version.

If you intend to install Oracle RAC, then you must first complete the upgrade to Oracle Clusterware 11g release 1 (11.1) on all cluster member nodes before you install the Oracle Database 11g release 1 (11.1) version of Oracle RAC.

Determine the Oracle Inventory location

If you have already installed Oracle software on your system, then OUI detects the existing Oracle Inventory directory from the /etc/oraInst.loc file, and uses this location.

If you are installing Oracle software for the first time on your system, and your system does not have an Oracle inventory, then you are asked to provide a path for the Oracle inventory, and you are also asked the name of the Oracle Inventory group (typically, oinstall).

See Also: Chapter 2 for information about creating the Oracle Inventory, and completing required system configuration

Obtain root account access

During installation, you are asked to run configuration scripts as the root user. You must run these scripts as root, or be prepared to have your system administrator run them for you. Note that these scripts must be run in sequence. If you attempt to run scripts simultaneously, then the installation will fail.

☐ Decide if you want to install other languages

During installation, you are asked if you want translation of user interface text into languages other than the default, which is English.

Note: If the language set for the operating system is not supported by Oracle Universal Installer, then Oracle Universal Installer, by default, runs in the English language.

See Also: Oracle Database Globalization Support Guide for detailed information on character sets and language configuration

☐ Determine your cluster name, public node names, private node names, and virtual node names for each node in the cluster

If you install the clusterware during installation, and are not using third-party vendor clusterware, then you are asked to provide a public node name and a private node name for each node. If you use vendor clusterware, then use your vendor documentation to complete setup of your public and private domain addresses.

When you enter the public node name, use the primary host name of each node. In other words, use the name displayed by the hostname command. This node name can be either the permanent or the virtual host name.

In addition, ensure that the following are true:

- Determine a cluster name with the following characteristics:
 - It must be globally unique throughout your host domain.
 - It must be at least one character long and less than 15 characters long.
 - It must consist of the same character set used for host names: underscores (_), hyphens (-), and single-byte alphanumeric characters (a to z, A to Z, and 0 to 9). If you use third-party vendor clusterware, then Oracle recommends that you use the vendor cluster name.
- Determine a private node name or private IP address for each node. The private IP address is an address that is accessible only by the other nodes in this cluster. Oracle Database uses private IP addresses for internode, or instance-to-instance Cache Fusion traffic. Oracle recommends that you provide a name in the format *public_hostname*-priv. For example: myclstr2-priv.
- Determine a virtual host name for each node. A virtual host name is a public node name that is used to reroute client requests sent to the node if the node is down. Oracle Database uses VIPs for client-to-database connections, so the VIP address must be publicly accessible. Oracle recommends that you provide a name in the format *public_hostname*-vip. For example: myclstr2-vip.

Note: The following is a list of additional information about node IP addresses:

- For the local node only, OUI automatically fills in public, private, and VIP fields. If your system uses vendor clusterware, then OUI may fill additional fields.
- Host names, private names, and virtual host names are not domain-qualified. If you provide a domain in the address field during installation, then OUI removes the domain from the address.
- Private IP addresses should not be accessible as public interfaces. Using public interfaces for Cache Fusion can cause performance problems.

☐ Identify shared storage for Oracle Clusterware files and prepare disk partitions if necessary

During installation, you are asked to provide paths for two files that must be shared across all nodes of the cluster, either on a shared raw device, or a shared file system file:

- The voting disk is a partition that Oracle Clusterware uses to verify cluster node membership and status.
 - The voting disk must be owned by the user performing the installation (oracle or crs), and must have permissions set to 640.
- The Oracle Cluster Registry (OCR) contains cluster and database configuration information for the Oracle RAC database and for Oracle Clusterware, including the node list, and other information about cluster configuration and profiles.

The OCR disk must be owned by the user performing the installation (crs or oracle. That installation user must have oinstall as its primary group. The OCR disk partitions must have permissions set to 640, though permissions files used with system restarts should have ownership set to root: oinstall. During installation, OUI changes ownership of the OCR disk partitions to root. Provide at least 280 MB disk space for the OCR partitions.

If your disks do not have external storage redundancy, then Oracle recommends that you provide one additional location for the OCR disk, and two additional locations for the voting disk, for a total of five partitions (two for OCR, and three for voting disks). Creating redundant storage locations protects the OCR and voting disk in the event of a disk failure on the partitions you choose for the OCR and the voting disk.

See Also: Chapter 4, "Configuring Oracle Clusterware Storage"

6.3 Installing Oracle Clusterware with OUI

This section provides you with information about how to use Oracle Universal Installer (OUI) to install Oracle Clusterware. It contains the following sections:

- Running OUI to Install Oracle Clusterware
- Installing Oracle Clusterware Using a Cluster Configuration File
- Troubleshooting OUI Error Messages for Oracle Clusterware

6.3.1 Running OUI to Install Oracle Clusterware

Complete the following steps to install Oracle Clusterware on your cluster. At any time during installation, if you have a question about what you are being asked to do, click the **Help** button on the OUI page.

Unless you have the same terminal window open that you used to set up SSH, enter the following commands:

```
$ exec /usr/bin/ssh-agent $SHELL
$ /usr/bin/ssh-add
```

2. Start the runInstaller command from the /Disk1 directory on the Oracle Database 11g release 1 (11.1) installation media.

3. Provide information or run scripts as root when prompted by OUI. If you need assistance during installation, click **Help**.

Note: You must run root . sh scripts one at a time. Do not run root.sh scripts simultaneously.

4. After you run root.sh on all the nodes, OUI runs the Oracle Notification Server Configuration Assistant, Oracle Private Interconnect Configuration Assistant, and Cluster Verification Utility. These programs run without user intervention.

When you have verified that your Oracle Clusterware installation is completed successfully, you can either use it to maintain high availability for other applications, or you can install an Oracle database.

If you intend to install Oracle Database 11g release 1 (11.1) with Oracle RAC, then refer to Oracle Real Application Clusters Installation Guide for AIX Based Systems. If you intend to use Oracle Clusterware by itself, then refer to the single-instance Oracle Database installation guide.

See Also: Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide for information about using cloning and node addition procedures, and Oracle Clusterware Administration and Deployment Guide for cloning Oracle Clusterware

6.3.2 Installing Oracle Clusterware Using a Cluster Configuration File

During installation of Oracle Clusterware, on the Specify Cluster Configuration page, you are given the option either of providing cluster configuration information manually, or of using a cluster configuration file. A cluster configuration file is a text file that you can create before starting OUI, which provides OUI with information about the cluster name and node names that it requires to configure the cluster.

Oracle suggests that you consider using a cluster configuration file if you intend to perform repeated installations on a test cluster, or if you intend to perform an installation on many nodes.

To create a cluster configuration file:

- On the installation media, navigate to the directory Disk1/response.
- Using a text editor, open the response file crs.rsp, and find the section CLUSTER_CONFIGURATION_FILE.
- **3.** Follow the directions in that section for creating a cluster configuration file.

6.3.3 Troubleshooting OUI Error Messages for Oracle Clusterware

The following is a list of some common Oracle Clusterware installation issues, and how to resolve them.

PRKC-1044 Failed to check remote command execution

Cause: SSH keys need to be loaded into memory, or there is a user equivalence error.

Action: Run the following commands to load SSH keys into memory:

- \$ exec /usr/bin/ssh-agent \$SHELL
- \$ /usr/bin/ssh-add

Note that you must have the passphrase used to set up SSH. If you are not the person who set up SSH, then obtain the passphrase. Note also that the .ssh folder in the user home that is performing the installation must be set with 600 permissions.

In addition, confirm group membership by entering the id command, and entering ID username. For example:

```
$ id
$ id oracle
```

Incorrect permissions on partitions used for OCR or Voting Disks

Cause: The user account performing the installation (oracle or crs) does not have permission to write to these partitions

Action: Make the partitions writable by the user performing installation. For example, use the command chown *user* to make the selected partitions writable by the user (oracle or crs) performing the installation. During installation, these permissions are changed to root ownership.

6.4 Confirming Oracle Clusterware Function

After installation, log in as root, and use the following command syntax to confirm that your Oracle Clusterware installation is installed and running correctly:

```
CRS_home/bin/crs_stat -t -v
```

For example:

[root@node1	/]:/u01/app/crs	/bin/cr	rs_stat	-t -v		
Name	a Type	R/RA	F/FT	Target	State	Host
crsac3.	gsd application	0/5	0/0	Online	Online	node1
crsac3.	ons application	0/5	0/0	Online	Online	node1
crsac3.	vip application	0/5	0/0	Online	Online	node1
crsac3.	gsd application	0/5	0/0	Online	Online	node2
crsac3.	ons application	0/5	0/0	Online	Online	node2
crsac3.	vip application	0/5	0/0	Online	Online	node2

You can also use the command crsctl check crs for a less detailed system check. for example:

```
[root@node1 bin] $ ./crsctl check crs
Cluster Synchronization Services appears healthy
Cluster Ready Services appears healthy
Event Manager appears healthy
```

Caution: After installation is complete, do not remove manually or run cron jobs that remove /tmp/.oracle or /var/tmp/.oracle or its files while Oracle Clusterware is up. If you remove these files, then Oracle Clusterware could encounter intermittent hangs, and you will encounter error CRS-0184: Cannot communicate with the CRS daemon.

Oracle Clusterware Postinstallation Procedures

This chapter describes how to complete the postinstallation tasks after you have installed the Oracle Clusterware software. It contains the following sections:

- Required Postinstallation Tasks
- Recommended Postinstallation Tasks

7.1 Required Postinstallation Tasks

You must perform the following tasks after completing your installation:

- Back Up the Voting Disk After Installation
- Download and Install Patch Updates

7.1.1 Back Up the Voting Disk After Installation

After your Oracle Clusterware installation is complete, and after you are sure that your system is functioning properly, make a backup of the contents of the voting disk. Use the dd.exe utility.

Also, make a backup copy of the voting disk contents after you complete any node additions or node deletions, and after running any deinstallation procedures.

7.1.2 Download and Install Patch Updates

Refer to the Oracle MetaLink Web site for required patch updates for your installation. To download required patch updates:

Use a Web browser to view the Oracle MetaLink Web site:

https://metalink.oracle.com

2. Log in to Oracle*MetaLink*.

Note: If you are not an Oracle *MetaLink* registered user, then click Register for MetaLink and register.

- **3.** On the main Oracle*MetaLink* page, click **Patches**.
- On the Select a Patch Search Area page, click **New MetaLink Patch Search**.
- On the Simple Search page, click **Advanced**.

- **6.** On the Advanced Search page, click the search icon next to the Product or Product Family field.
- 7. In the Search and Select: Product Family field, enter RDBMS Server in the For field, and click **Go**.
- **8.** Select **RDBMS Server** under the Results heading, and click **Select**.
 - RDBMS Server appears in the Product or Product Family field. The current release appears in the Release field.
- **9.** Select your platform from the list in the Platform field, and click **Go**.
- **10.** Any available patch updates appear under the Results heading.
- **11.** Click the number of the patch that you want to download.
- **12.** On the Patch Set page, click **View README** and read the page that appears. The README page contains information about the patch set and how to apply the patches to your installation.
- **13.** Return to the Patch Set page, click **Download**, and save the file on your system.
- **14.** Use the unzip utility provided with Oracle Database 10g to uncompress the Oracle patch updates that you downloaded from OracleMetaLink. The unzip utility is located in the \$ORACLE_HOME/bin directory.

7.2 Recommended Postinstallation Tasks

Oracle recommends that you complete the following tasks after installing Oracle Clusterware:

- Back Up the root.sh Script
- Run CVU Postinstallation Check

7.2.1 Back Up the root.sh Script

Oracle recommends that you back up the root. sh script after you complete an installation. If you install other products in the same Oracle home directory, then the Oracle Universal Installer (OUI) updates the contents of the existing root.sh script during the installation. If you require information contained in the original root.sh script, then you can recover it from the root. sh file copy.

7.2.2 Run CVU Postinstallation Check

After installing Oracle Clusterware, check the status of your Oracle Clusterware installation with the command cluvfy stage -post crsinst, using the following syntax:

cluvfy stage -post crsinst -n node_list [-verbose]

Deinstallation of Oracle Clusterware

This chapter describes how to remove Oracle Clusterware.

This chapter contains the following topics:

- Deciding When to Deinstall Oracle Clusterware
- Relocating Single-instance ASM to a Single-Instance Database Home
- Removing Oracle Clusterware

See Also: Product-specific documentation for requirements and restrictions, if you want to remove an individual product

8.1 Deciding When to Deinstall Oracle Clusterware

Remove installed components in the following situations:

- You have encountered errors during or after installing or upgrading Oracle Clusterware, and you want to re-attempt an installation.
- Your installation or upgrade stopped because of a hardware or operating system failure.
- You are advised by Oracle Support to reinstall Oracle Clusterware.
- You have successfully installed Oracle Clusterware, and you want to remove the Clusterware installation, either in an educational environment, or a test environment.
- You have successfully installed Oracle Clusterware, but you want to downgrade to a previous release.

8.2 Relocating Single-instance ASM to a Single-Instance Database Home

If you have a single-instance Oracle Database on Oracle Clusterware, and you want to remove Oracle Clusterware, then use the following syntax to add the local CSS configuration to the ASM home:

ASM_home/bin/localconfig add

For example:

\$ cd /u01/app/asm/bin/ \$./localconfig add

8.3 Removing Oracle Clusterware

The scripts rootdelete.sh and rootdeinstall.sh remove Oracle Clusterware from your system. After running these scripts, run Oracle Universal Installer to remove the Oracle Clusterware home. The following sections describe the scripts, and later, provide exact procedure to the removal of the Oracle Clusterware software.

8.3.1 About the rootdelete.sh Script

The rootdelete.sh script should be run from the Oracle Clusterware home on each node. It stops the Oracle Clusterware stack, removes inittab entries, and deletes some of the Oracle Clusterware files. It can also be used to downgrade the Oracle Cluster Registry from the existing release to a previous release. The script uses the following syntax:

rootdelete.sh options

Options:

- paramfile: Use a parameter file containing configuration information for the rootdelete. sh command. Provide the path and name of the parameter file. For example: -paramfile /usr/oracle/cwdeletepar.
- local | remote: Use local if you are running rootdelete. sh on the local node, and use **remote** if you are running the script on one of the other nodes. The local node is the one from which you run OUI (in other words, the last surviving node), and on which you run rootdeinstall.sh.
- **nosharedvar** | **sharedvar**: Use **nosharedvar** if the directory path for ocr.loc (in /etc/oracle or /var/opt/oracle) is not on a shared file system. Use sharedvar if the directory path for ocr.loc is in a shared location. The default is nosharedvar.
- **sharedhome** | **nosharedhome**: Use **sharedhome** if the Oracle Clusterware home is shared across the nodes. Otherwise, use **nosharedhome**. The default is
- **downgrade**: Use this option if the Oracle Clusterware is downgraded to a previous Oracle Clusterware version. The **-downgrade** option takes the following
 - **-version**: Use this option to specify the version to which you want to downgrade. The default is 10.2.
 - **-force**: Use this option to force cleanup of root configuration

For example, to run the rootdelete. sh script from an Oracle Clusterware home in the path /u01/app/crs, where you are running the script on a remote node, and the ocr.loc file is in /etc/oracle on each node, enter the following command:

```
# cd /u01/app/crs/install/
# ./rootdelete.sh remote nosharedvar
```

8.3.2 Example of the rootdelete.sh Parameter File

You can create a parameter file for rootdelete. sh to repeat deinstallation steps. You may want to do this if you intend to perform repeated reinstallations, as in a test environment. The following is an example of a parameter file for rootdelete.sh; terms that change relative to system configuration are indicated with italics:

```
CLUSTER_NODES=mynode1, mynode2
INVENTORY_LOCATION=u01/app/oracle/oraInventory
```

CRS HOME=true ORA_CRS_HOME=/u01/app/crs ORACLE_OWNER=oracle DBA_GROUP=oinstall

8.3.3 About the rootdeinstall.sh Script

The rootdeinstall.sh script should be run on the local node only, after rootdelete.sh has been run on all nodes of the cluster. Use this command either to remove the Oracle Clusterware OCR file, or to downgrade your existing installation. The rootdeinstall.sh script has the following command options:

- paramfile: A parameter file containing configuration information for the rootdelete.sh command
- **downgrade**: Use this option if the database is downgraded to a previous Oracle Clusterware version. Use the **-version** flag to specify the version to which you want to downgrade. The default is 10.2.

8.3.4 Removing Oracle Clusterware

Complete the following procedure to remove Oracle Clusterware:

 Log in as the oracle user, and shut down any existing Oracle Database instances on each node, with normal or immediate priority. For example:

```
$ Oracle_home/bin/srvctl stop database -d db_name
$ Oracle_home/bin/srvctl stop asm -n node
$ Oracle_home/bin/srvctl stop nodeapps -n node
```

- 2. Use Database Configuration Assistant and NETCA to remove listeners, Automatic Storage Management instances, and databases from the system. This removes the Oracle Clusterware resources associated with the listeners, Automatic Storage Management instances, and databases on the cluster.
- **3.** On each remote node, log in as the root user, change directory to the Oracle Clusterware home, and run the rootdelete script with the options remote nosharedvar nosharedhome. For example:

```
[root@node2 /] # cd /u01/app/crs/install
[root@node2 /install] # ./rootdelete.sh remote nosharedvar nosharedhome
```

4. On the local node (the last cluster member node), log in as the root user, change directory to the Oracle Clusterware home, and run the rootdelete script with the options local nosharedvar nosharedhome. For example:

```
[root@node1 /] # cd /u01/app/crs/install
[root@node1 /install] # ./rootdelete.sh local nosharedvar nosharedhome
```

5. On the local node, run the script rootdeinstall. For example:

```
[root@node1 install]# ./rootdeinstall.sh
```

6. Log in as the oracle user, and run Oracle Universal Installer to remove the Oracle Clusterware home. For example

```
$ cd /u01/app/crs/oui/bin
$ ./runInstaller -deinstall -removeallfiles
```

Troubleshooting the Oracle Clusterware Installation Process

This appendix provides troubleshooting information for installing Oracle Clusterware.

See Also: The Oracle Database 11g Oracle RAC documentation set included with the installation media in the Documentation directory:

- Oracle Clusterware Administration and Deployment Guide
- Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide

This appendix contains the following topics:

- Install OS Watcher and RACDDT
- General Installation Issues
- Performing Cluster Diagnostics During Oracle Clusterware Installations
- **Interconnect Errors**

A.1 Install OS Watcher and RACDDT

To address troubleshooting issues, Oracle recommends that you install OS Watcher, and if you intend to install an Oracle RAC database, RACDDT. You must have access to OracleMetaLink to download OS Watcher and RACDDT.

OS Watcher (OSW) is a collection of UNIX/Linux shell scripts that collect and archive operating system and network metrics to aid Oracle Support in diagnosing various issues related to system and performance. OSW operates as a set of background processes on the server and gathers operating system data on a regular basis. The scripts use common utilities such as vmstat, netstat and iostat.

RACDDT is a data collection tool designed and configured specifically for gathering diagnostic data related to Oracle RAC technology. RACDDT is a set of scripts and configuration files that is run on one or more nodes of an Oracle RAC cluster. The main script is written in Perl, while a number of proxy scripts are written using Korn shell. RACDDT will run on all supported UNIX and Linux platforms, but is not supported on any Windows platforms.

OSW is also included in the RACDDT script file, but is not installed by RACDDT. OSW must be installed on each node where data is to be collected.

To download binaries for OS Watcher and RACDDT, go to the following URL:

https://metalink.oracle.com

Download OSW by searching for OS Watcher, and downloading the binaries from the User Guide bulletin. Installation instructions for OSW are provided in the user guide. Download RACDDT by searching for RACDDT, and downloading the binaries from the RACDDT User Guide bulletin.

A.2 General Installation Issues

The following is a list of examples of types of errors that can occur during installation. It contains the following issues:

- An error occurred while trying to get the disks
- Failed to connect to server, Connection refused by server, or Can't open display
- Nodes unavailable for selection from the OUI Node Selection screen
- Node nodename is unreachable
- PROT-8: Failed to import data from specified file to the cluster registry
- Time stamp is in the future
- YPBINDPROC_DOMAIN: Domain not bound

An error occurred while trying to get the disks

Cause: There is an entry in /etc/oratab pointing to a non-existent Oracle home. The OUI error file should show the following error: "java.io.IOException: /home/oracle/OraHome//bin/kfod: not found" (OracleMetalink bulletin 276454.1)

Action: Remove the entry in /etc/oratab pointing to a non-existing Oracle home.

Failed to connect to server, Connection refused by server, or Can't open display

Cause: These are typical of X Window display errors on Windows or UNIX systems, where xhost is not properly configured.

Action: In a local terminal window, log in as the user that started the X Window session, and enter the following command:

\$ xhost fully_qualified_remote_host_name

For example:

```
$ xhost somehost.example.com
```

Then, enter the following commands, where workstation_name is the host name or IP address of your workstation.

Bourne or Korn shell:

```
$ DISPLAY=workstation_name:0.0
$ export DISPLAY
```

To determine whether X Window applications display correctly on the local system, enter the following command:

```
$ xclock
```

The X clock should appear on your monitor.

If the X clock appears, then close the X clock and start Oracle Universal Installer again.

Nodes unavailable for selection from the OUI Node Selection screen

Cause: Oracle Clusterware is either not installed, or the Oracle Clusterware services are not up and running.

Action: Install Oracle Clusterware, or review the status of your Oracle Clusterware. Consider restarting the nodes, as doing so may resolve the problem.

Node nodename is unreachable

Cause: Unavailable IP host **Action:** Attempt the following:

- 1. Run the shell command if config -a. Compare the output of this command with the contents of the /etc/hosts file to ensure that the node IP is listed.
- **2.** Run the shell command nslookup to see if the host is reachable.
- As the oracle user, attempt to connect to the node with ssh or rsh. If you are prompted for a password, then user equivalence is not set up properly. Review Section 2.9, "Configuring SSH on All Cluster Nodes."

PROT-8: Failed to import data from specified file to the cluster registry

Cause: Insufficient space in an existing Oracle Cluster Registry device partition, which causes a migration failure while running rootupgrade.sh. To confirm, look for the error "utopen:12:Not enough space in the backing store" in the log file \$ORA CRS HOME/log/hostname/client/ocrconfig pid.log.

Action: Identify a storage device that has 280 MB or more available space. Locate the existing raw device name from /var/opt/oracle/srvConfig.loc, and copy the contents of this raw device to the new device using the command dd.

Time stamp is in the future

Cause: One or more nodes has a different clock time than the local node. If this is the case, then you may see output similar to the following:

time stamp 2005-04-04 14:49:49 is 106 s in the future

Action: Ensure that all member nodes of the cluster have the same clock time.

YPBINDPROC DOMAIN: Domain not bound

Cause: This error can occur during postinstallation testing when a node public network interconnect is pulled out, and the VIP does not fail over. Instead, the node hangs, and users are unable to log in to the system. This error occurs when the Oracle home, listener.ora, Oracle log files, or any action scripts are located on an NAS device or NFS mount, and the name service cache daemon nscd has not been activated.

Action: Enter the following command on all nodes in the cluster to start the nscd service:

/sbin/service nscd start

A.3 Performing Cluster Diagnostics During Oracle Clusterware Installations

If Oracle Universal Installer (OUI) does not display the Node Selection page, then perform clusterware diagnostics by running the olsnodes -v command from the binary directory in your Oracle Clusterware home (CRS home/bin on Linux and UNIX-based systems, and CRS_home\BIN on Windows-based systems) and analyzing its output. Refer to your clusterware documentation if the detailed output indicates that your clusterware is not running.

In addition, use the following command syntax to check the integrity of the Cluster Manager:

```
cluvfy comp clumgr -n node_list -verbose
```

In the preceding syntax example, the variable node_list is the list of nodes in your cluster, separated by commas.

A.4 Interconnect Errors

If you use more than one NIC for the interconnect, then you must use NIC bonding, or the interconnect will fail.

If you install Oracle Clusterware and Oracle RAC, then they must use the same NIC or bonded NIC cards for the interconnect.

If you use bonded NIC cards, then they must be on the same subnet.

How to Perform Oracle Clusterware Rolling Upgrades

This appendix describes how to perform Oracle Clusterware rolling upgrades. Because you must stop database processes on the nodes you intend to upgrade when you perform an Oracle Clusterware upgrade, it includes information about how to stop processes in Oracle Real Application Clusters (Oracle RAC) databases.

The instructions in this section specify a single node, and assume that you are upgrading one node at a time. To upgrade a subset of nodes together, you can specify a list of nodes (the subset), where the example commands specify a single node. For example, instead of -n node, specify -n node1, node2, node3.

This appendix contains the following topics:

Note: You can use the procedures in this chapter to perform rolling upgrades of Oracle Clusterware from any Oracle Clusterware 10g or Oracle Clusterware 11g installation to the latest patchset update. For example, you can use these procedures to prepare to upgrade from Oracle Clusterware 10.2.0.1 to 10.2.0.3.

- Back Up the Oracle Software Before Upgrades
- Restrictions for Clusterware Upgrades to Oracle Clusterware 11g
- Verify System Readiness for Patchset and Release Upgrades
- Installing a Patch Set On a Subset of Nodes
- Installing an Upgrade On a Subset of Nodes

B.1 Back Up the Oracle Software Before Upgrades

Before you make any changes to the Oracle software, whether you intend to upgrade or patch part of the database or clusterware, or all of your cluster installation, Oracle recommends that you create a backup of the Oracle software.

B.2 Restrictions for Clusterware Upgrades to Oracle Clusterware 11*g*

To upgrade existing Oracle Clusterware and Cluster Ready Services installations to Oracle Clusterware 11g, you must first upgrade the existing installations to a minimum patch level. The minimum patch level is listed in the following table:

Table B–1 Minimum Oracle Clusterware Patch Levels Required for Rolling Upgrades to 11g

Oracle Clusterware Release	Minimum Patch Level Required
10g Release 2	10.2.0.3, or 10.2.0.2 with CRS bundle # 2 (Patch 526865)
10g Release 1	10.1.0.3

To upgrade your Oracle Clusterware installation to the minimum patch level using a rolling upgrade, follow the directions in the Patch Readme file.

Note: You can use the procedures in this chapter to prepare to perform rolling upgrades of Oracle Clusterware from any Oracle Clusterware 10g release 10.2 or Oracle Clusterware 11g installation to the latest patchset update. For example, you can use these procedures to prepare to upgrade from Oracle Clusterware 10.2.0.1 to 10.2.0.3.

See Also: Oracle Database Upgrade Guide for additional information about upgrades, and check the following site on the Oracle Technology Network for relevant information about rolling upgrades:

http://www.oracle.com/technology/deploy/availability

My Oracle Support also has an Upgrade Companion for each release that provide additional upgrade information. It is available at the following URL:

https://metalink.oracle.com/

B.3 Verify System Readiness for Patchset and Release Upgrades

If you are completing a patchset update of your database or clusterware, then after you download the patch software, and before you start to patch or upgrade your database, review the Patch Set Release Notes that accompany the patch to determine if your system meets the system requirements for the operating system and the hardware platform.

Use the following Cluster Verification Utility (CVU) command to assist you with system checks in preparation for starting a database patch or upgrade, where node is the node, or comma-delimited subset of nodes, that you want to check, and *inventory*_ *group* is the name of the Oracle Inventory group:

cluvfy stage -pre crsinst -n node -orainv inventory_group

For example, to perform a system check on nodes node1, node2 and node3, and where the Oracle Inventory group is oinstall, enter the following command:

\$ cluvfy stage -pre crsinst -n node1, node2, node3 -orainv oinstall

Note: Before you start an upgrade, Oracle recommends that you download the latest Cluster Verification Utility version from Oracle Technology Network at the following URL:

http://otn.oracle.com

B.4 Installing a Patch Set On a Subset of Nodes

To patch Oracle Clusterware, review the instructions in the Patch Set README document for additional instructions specific to the patchset.

Before you shut down any processes that are monitored by Enterprise Manager Grid Control, set a blackout in Grid Control for the processes that you intend to shut down. This is necessary so that the availability records for these processes indicate that the shutdown was planned downtime, rather than an unplanned system outage.

To patch a subset of nodes, complete the following steps:

Note: You must perform these steps in the order listed.

1. Change directory to the Oracle Clusterware home. As root, run the preupdate. sh script on the local node, and on all other nodes in the subset that you intend to upgrade. Use the following command syntax, where *clusterware*_ home is the path to the existing Oracle Clusterware home, and installation_owner is the Oracle Clusterware installation owner:

./preupdate.sh -crshome clusterware_home -crsuser installation_owner

For example:

```
# cd $ORACLE HOME/install
# ./preupdate.sh -crshome /opt/crs -crsuser oracle
```

The script output should be similar to the following:

```
Shutting down Oracle Cluster Ready Services (CRS):
Stopping resources. This could take several minutes.
Successfully stopped CRS resources.
Stopping CSSD.
Shutting down CSS daemon.
Shutdown request successfully issued.
Shutdown has begun. The daemons should exit soon.
Checking to see if Oracle CRS stack is down...
Oracle CRS stack is down now.
```

Confirm that you are logged in as the Oracle Clusterware installation owner, and start Oracle Universal Installer to install the software.

For example:

```
$ whoami
$ cd /cdrom/clusterware/
./runInstaller
```

Provide information as prompted by the Installer.

Note: You cannot change the owner of the Oracle Clusterware home.

3. During an Oracle Clusterware installation, if Oracle Universal Installer detects an existing Oracle Clusterware 10g release 1 or release 2 installation, then you are given the option to perform a rolling upgrade by installing the patch on a subset of cluster member nodes.

You can patch the entire cluster, and then run the root. sh patch script in a rolling fashion to make the patch update active.

4. After you select the nodes you want to upgrade, the Installer installs the patch software in the existing Oracle Clusterware home on the local and the remote subset of nodes you have selected.

OUI prompts you to run the appropriate root script for the patchset. The script starts the Oracle Clusterware stack on the upgraded subset of nodes. However, it lists it as an inactive version.

5. After you upgrade the initial node or subset of nodes, repeat steps 1 through 4 for each remaining node or subset of nodes until all nodes in the cluster have been patched, and the new version is the active version.

When all member nodes of the cluster are running the new Oracle Clusterware release, then the new clusterware becomes the active version. Otherwise, the older Oracle Clusterware release is still used.

To list the version of Oracle Clusterware that is installed on a node, enter the following command, where CRShome is the Oracle Clusterware home, and nodename is the name of the node:

CRShome/bin/crsctl query crs softwareversion [nodename]

To list the Oracle Clusterware software version that is running on a node, enter the following command, where *CRShome* is the Oracle Clusterware home:

CRShome/bin/crsctl query crs activeversion

If you intend to install or upgrade Oracle RAC, then you must first complete the upgrade to Oracle Clusterware 11g release 1 (11.1) on all cluster member nodes before you install the Oracle Database 11g release 1 (11.1) version of Oracle RAC.

6. Check with Oracle Support to confirm you have installed any recommended patchsets, bundle patches or critical patches.

To check for the latest recommended patches for Oracle Clusterware and Oracle Real Application Clusters, log on to the following site:

https://metalink2.oracle.com

Click Patches & Updates, and click Oracle Database from the Recommended Patches list. Provide information as prompted.

B.5 Installing an Upgrade On a Subset of Nodes

To upgrade an Oracle Clusterware release, you must shut down all Oracle Database instances on the subset of nodes you want to upgrade before modifying the Oracle software. Review the instructions in the release upgrade README document for additional instructions specific to the upgrade.

Before you shut down any processes that are monitored by Enterprise Manager Grid Control, set a blackout in Grid Control for the processes that you intend to shut down. This is necessary so that the availability records for these processes indicate that the shutdown was planned downtime, rather than an unplanned system outage.

To shut down Oracle processes and upgrade a subset of nodes, complete the following steps:

Note: You must perform these steps in the order listed.

- 1. Shut down any processes that may be accessing a database on each node you intend to upgrade. For example, shut down Oracle Enterprise Manager Database Control.
- 2. Shut down all Oracle RAC instances on the nodes you intend to upgrade. To shut down an Oracle RAC instance for a database, enter the following command db name is the name of the database and *inst* name is the database instance:

```
$ Oracle_home/bin/srvctl stop instance -d db_name -i inst_name
```

3. Shut down all ASM instances on all nodes you intend to upgrade. To shut down an ASM instance, enter the following command, where ASM_home is the ASM home location, and node is the name of the node where the ASM instance is running:

```
$ ASM home/bin/srvctl stop asm -n node
```

Note: If you shut down ASM instances, then you must first shut down all database instances on the nodes you intend to upgrade that use ASM, even if these databases run from different Oracle homes.

4. Stop all listeners on the node. To shut down listeners on the node, enter the following command, where nodename is the name of the node, and the listener is running from the ASM home:

```
$ ASM_home/bin/srvctl stop listener -n node_name
```

Stop all node applications on all nodes. To stop node applications running on a node, enter the following command, where *node* is the name of the node where the applications are running

```
$ Oracle_home/bin/srvctl stop nodeapps -n node
```

6. Change directory to the Oracle Clusterware home. As root, run the preupdate.sh script on the local node, and on all other nodes in the subset that you intend to upgrade. Use the following command syntax, where *clusterware*_ home is the path to the existing Oracle Clusterware or Cluster Ready Services home, and *installation_owner* is the Oracle Clusterware installation owner:

./preupdate.sh -crshome *clusterware_home* -crsuser *installation_owner*

For example:

```
# cd $ORACLE_HOME/install
# ./preupdate.sh -crshome /opt/crs -crsuser oracle
```

The script output should be similar to the following:

```
Shutting down Oracle Cluster Ready Services (CRS):
Stopping resources. This could take several minutes.
Successfully stopped CRS resources.
Stopping CSSD.
Shutting down CSS daemon.
Shutdown request successfully issued.
Shutdown has begun. The daemons should exit soon.
```

```
Checking to see if Oracle CRS stack is down...
Oracle CRS stack is down now.
```

7. Confirm that you are logged in as the Oracle Clusterware installation owner, and start Oracle Universal Installer to install the software.

For example:

```
$ whoami
crs
$ cd /cdrom/clusterware/
./runInstaller
```

Provide information as prompted by the Installer.

Note: You cannot change the owner of the Oracle Clusterware home.

8. During an Oracle Clusterware installation, if Oracle Universal Installer detects an existing Oracle Clusterware 10g release 1 or release 2 installation, then you are given the option to perform a rolling upgrade by installing Oracle Clusterware 11g release 1 on a subset of cluster member nodes.

By default, all the cluster member nodes are checked for upgrade. To perform a rolling upgrade of a subset of nodes, uncheck the cluster member nodes you do not want to upgrade on the Specify Hardware Cluster Installation Mode installation screen.

After you select the nodes you want to upgrade, the Installer installs the Oracle Clusterware 11g release 1 software in the existing Oracle Clusterware home on the local and the remote subset of nodes you have selected.

OUI prompts you to run the appropriate root script for the release or patchset. The script starts the Oracle Clusterware 11g release 1 stack on the upgraded subset of nodes. However, it lists it as an inactive version.

10. After you upgrade the initial node or subset of nodes, repeat steps 1 through 10 for each remaining node or subset of nodes until all nodes in the cluster have been upgraded and the new version is the active version.

When all member nodes of the cluster are running the new Oracle Clusterware release, then the new clusterware becomes the active version. Otherwise, the older Oracle Clusterware release is still used.

To list the version of Oracle Clusterware that is installed on a node, enter the following command, where CRShome is the Oracle Clusterware home, and nodename is the name of the node:

```
# CRShome/bin/crsctl query crs softwareversion [nodename]
```

To list the Oracle Clusterware software version that is running on a node, enter the following command, where CRShome is the Oracle Clusterware home:

```
# CRShome/bin/crsctl query crs activeversion
```

If you intend to install or upgrade Oracle RAC, then you must first complete the upgrade to Oracle Clusterware 11g release 1 (11.1) on all cluster member nodes before you install the Oracle Database 11g release 1 (11.1) version of Oracle RAC.

11. Check with Oracle Support, and apply any recommended patchsets, bundle patches or critical patches.

To check for the latest recommended patches for Oracle Clusterware and Oracle Real Application Clusters, log on to the following site:

https://metalink2.oracle.com

Click Patches & Updates, and click Oracle Database from the Recommended Patches list. Provide information as prompted.

Index

A	storage option for data files, 4-2
activating volume groups, 4-19, 5-31 AIX	В
character raw device names, 5-19	
checking disk availability for ASM, 5-16	Bourne shell
configuring disks for ASM, 5-16	default user startup file, 2-26
configuring new disks, 5-17	
identifying disks for ASM, 5-17	C
identifying LVM disks, 5-17	C compiler
initializing disks for LVM, 5-17	*
raw device sizes, 4-8	requirement, 2-14 See also Pro*C/C++
tuning virtual memory manager, 2-16	C shell
APAR	
download location, 2-16	default user startup file, 2-26
APAR download location, 2-16	Central Inventory, 3-3 about, 2-3
architecture	See also oraInventory
checking system architecture, 2-9	cfgmgr command, 4-16, 5-17, 5-26
ASM	changing host names, 6-2
and multiple databases, 3-5	character raw device
changing owner and permissions of disks	device name on AIX, 5-19
on AIX, 5-19	chdev command, 4-16, 5-17, 5-26
character raw device names on AIX, 5-19	checking disk availability for raw devices, 4-16, 5-25
characteristics of failure groups, 5-14	checking existence of the nobody user, 3-2
checking disk availability on AIX, 5-16	checking maintenance level, 2-14
configuring disks	checking version, 2-14
on AIX, 5-16	chmod command, 4-7, 5-10, 5-19
creating the asmdba group, 3-7	chown command, 4-7, 5-10, 5-19
disk groups, 5-13	cluster configuration file, 6-8
failure groups, 5-13	cluster file system
examples, 5-14	single-instance storage option for data files, 4-2
identifying, 5-14	storage option for data files, 4-2, 5-2
files not supported on GPFS, 5-3	cluster name
identifying available disks on AIX, 5-17	requirements for, 6-6
identifying disks on AIX, 5-17	cluster nodes
number of instances on each node, 1-5, 5-2	activating volume groups, 4-19, 5-31
OSDBA group for ASM, 3-5	importing raw device disk group, 4-18, 5-30
recommendations for disk groups, 5-13	private node names, 6-6
restrictions on use for OCR or voting disk, 5-12	public node names, 6-6
space required for preconfigured database, 5-14	specifying uids and gids, 3-9
storage option for data files, 5-2	virtual node names, 6-6
asm group	Cluster Ready Services
creating, 3-7	upgrading, 6-4
asmdba group	Cluster Synchronization Services, 6-4
creating, 3-7	Cluster Verification Utility
Automatic Storage Management	difference between runchingly shand chingly 2-20

hardware and operating system setup stage	creating on other nodes, 3-9
verification, 5-31	description, 3-2, 3-4
Oracle Clusterware configuration check, 6-1	raw device group, 4-18, 4-19, 5-30
shared storage area check, 4-4, 5-4	DBCA_RAW_CONFIG environment variable, 5-24
user equivalency troubleshooting, 6-2	default file mode creation mask
clusterware diagnostics, A-3	setting, 3-11
commands	deinstallation
chmod, 5-10	local and remote nodes, 8-2
chown, 5-10	device names
cluvfy, 2-30	on AIX, 5-19
groupadd, 3-10	device numbers
id, 3-2, 3-9	identifying major numbers, 4-17, 5-26
mkdir, 5-10	df command, 2-27
mkuser, 3-10	diagnostics, A-3
passwd, 3-10	Direct NFS
runcluvfy.sh, 2-29	disabling, 5-9
umask, 3-11	enabling, 5-8
usermod, 3-8	for datafiles, 5-6
xhost, 2-2	directory
xterm, 2-2	creating separate data file directories, 4-6, 5-9
configuring new disks, 4-16, 5-26	permission for data file directories, 4-7, 5-10
control files	disk group
raw devices for, 5-11, 5-20, 5-29	ASM, 5-13
creating a volume group, 4-16, 5-25	recommendations for ASM disk groups, 5-13
creating logical volumes, 5-29	disk space
	checking, 2-9
creating raw logical volumes, 4-18, 5-28	e e e e e e e e e e e e e e e e e e e
creating volume groups, 4-17, 5-26	requirements for preconfigured database in
CRS	ASM, 5-14
OCR restriction, 5-12	disks
raw device for OCR on AIX, 4-8	changing permissions and owner for ASM
voting disk restriction, 5-12	on AIX, 5-19
CSD	checking availability for ASM on AIX, 5-16
download location for WebSphere MQ, 2-16	checking availability for raw devices, 4-16, 5-25
CSS, 6-4	configuring for ASM on AIX, 5-16
OCCSD, 6-4	configuring new disks, 4-16, 5-17, 5-26
custom database	enabling simultaneous access of, 4-10
failure groups for ASM, 5-14	identifying LVM disks, 4-16, 5-26
requirements when using ASM, 5-14	identifying LVM disks on AIX, 5-17
Custom installation type	raw voting disk on AIX, 4-8
7.1	DISPLAY environment variable
reasons for choosing, 3-4	
CVU. See Cluster Verification Utility	setting, 2-26
D	E
data files	emulator
creating separate directories for, 4-6, 5-9	installing from X emulator, 2-2
setting permissions on data file directories, 4-7,	env command, 2-27
5-10	environment
single-instance database storage options, 4-2	checking settings, 2-27
storage options, 4-2, 5-2	configuring for oracle user, 2-26
data loss	environment variables
minimizing with ASM, 5-14	DBCA_RAW_CONFIG, 5-24
database files	DISPLAY, 2-26
supported storage options, 5-2	removing from shell startup file, 2-26
databases	SHELL, 2-26
ASM requirements, 5-14	TEMP and TMPDIR, 2-9, 2-27
dba group	errors
and ASM disks on AIX, 5-19	due to permissions, 2-4
and SYSDBA privilege, 3-2, 3-4	due to stty commands, 2-25
creating, 3-6, 3-7	
CIEALITY, 3-0, 3-/	Oracle Universal Installer error messages, 6-8

stty, 6-3	specifying on other nodes, 3-9
user equivalence, 6-2	globalization
X11 forwarding, 2-24, 2-25	support for, 6-5
x11 forwarding, 6-3	GPFS, 4-1
/etc/security/limits.so file, 2-17	and best practices with HACMP, 4-2
EXAMPLE tablespace	database file storage on, 5-3, 5-5
raw device for, 5-20, 5-28	Oracle Clusterware file storage on, 4-2
raw devices for, 5-11	Partition recommendations for, 5-2
examples	group IDs
ASM failure groups, 5-14	identifying existing, 3-9
external jobs	specifying, 3-9
UNIX user required for, 3-2, 3-4	specifying on other nodes, 3-9
extjob executable	groups
UNIX user required for, 3-2, 3-4	checking for existing oinstall group, 2-4 creating identical groups on other nodes, 3-9
F	creating the asm group, 3-7
<u> </u>	creating the asmdba group, 3-7
failover	creating the dba group, 3-6
of single-instance databases using Oracle	creating the oinstall group, 2-3
Clusterware, 4-2	creating the oper group, 3-6
failure group	specifying when creating users, 3-9
ASM, 5-13	UNIX OSDBA group (dba), 3-2, 3-4
characteristics of ASM failure group, 5-14	UNIX OSOPER group (oper), 3-4
examples of ASM failure groups, 5-14	using NIS, 3-1, 3-3, 3-9
file mode creation mask	
setting, 3-11	
file system	Н
storage option for data files, 4-2, 5-2	HACMP, 4-11
storage option for single instance data files, 4-2	clusterware storage on, 4-3
files	database storage on, 5-3
\$ORACLE_HOME/lib/libnfsodm10.so, 5-8	deploying, 4-12
\$ORACLE_HOME/lib/libodm10.so, 5-8	not required for Oracle Clusterware, 2-14
control files	requirements for, 2-15
raw devices for, 5-20, 5-29	supported versions, 2-14
editing shell startup file, 2-26	upgrading, 4-14
/etc/security/limits.so, 2-17	verifying free disk space on, 2-9
login, 2-26	hardware requirements, 2-7
oraInst.loc, 2-5	hdisk
password file	reserve setting for, 4-10
raw device for, 5-20, 5-29	hdiskpower
.profile, 2-26	reserve setting for, 4-10
redo log files	host names
raw devices for, 5-11, 5-20, 5-29	changing, 6-2
server parameter file	Changing, 02
raw devices for, 5-20, 5-29	
SPFILE	
raw device for, 5-20, 5-29	IBM WebSphere MQ
SPFILE file	requirement, 2-14
raw devices for, 5-11	id command, 3-2, 3-9
filesets, 2-12	identifying disks for LVM, 4-16, 5-25
	identifying LVM disks, 4-16, 5-26
checking, 2-14	importing raw device disk group, 4-18, 5-30
	importing raw device disk group, 110,000 importing raw device disk group, 110,000
G	initializing disks for LVM, 4-16, 5-26
Gateway	installation
See Oracle Messaging Gateway	and globalization, 6-5
General Parallel File System. See GPFS	using cluster configuration file, 6-8
	installation types
gid identifying existing 3-9	and ASM requirements, 5-14
identifying existing, 3-9	<u>*</u>
specifying, 3-9	instfix command, 2-16

intermittent hangs	N
and socket files, 6-9	NAS, 4-3, 5-3
	network attached storage
J	for database files, 4-3, 5-3
JDK requirements, 2-12	Network Information Services See NIS
К	NFS, 4-3, 4-6, 5-3, 5-9 and data files, 5-6
Korn shell	and Oracle Clusterware files, 5-5
default user startup file, 2-26	buffer size parameters for, 4-6, 5-9 Direct NFS, 5-6
L	for datafiles, 5-6
	rsize, 4-6, 5-9
libnfsodm10.so, 5-8	NIS
libodm10.so, 5-8 limits.so file, 2-17	alternative to local users and groups, 3-1, 3-2, 3-3, 3-5
local node	
defined, 8-2	nobody user
logical volumes	checking existence of, 3-2 description, 3-2, 3-4
creating, 5-29	nofile
login file, 2-26	shell limit, 2-17
lsdev command, 4-16, 5-16, 5-25	nproc
Islpp command, 2-14, 2-16	shell limit, 2-17
lspv command, 4-16, 4-18, 4-19, 5-17, 5-26, 5-30	Sich mitt, 2 17
LVM	
creating a volume group, 4-16, 5-25	0
creating raw logical volumes, 4-18, 5-28	Object Data Manager, 4-10
creating volume groups, 4-17, 5-26	enabling simultaneous disk access for, 5-18
identifying available disks, 4-16, 5-25	OCCSD, 6-4
identifying major device numbers, 4-17, 5-26	OCR
identifying volume group devices, 4-16, 5-26	mirroring, 4-5
identifying volume group devices on AIX, 5-17	raw device for
initializing disks, 4-16, 5-26	on AIX, 4-8
initializing disks on AIX, 5-17	restriction on using ASM for, 5-12
recommendations for ASM, 5-13	OCR. See Oracle Cluster Registry
recommendations for ASWI, 5-15	ODM, 4-10
	oinstall
M	and oraInst.loc, 2-4
maintenance level	oinstall group
checking, 2-14	checking for existing, 2-4
major device numbers	creating, 2-3
identifying, 4-17, 5-26	creating on other nodes, 3-9
mask	description, 2-3
setting default file mode creation mask, 3-11	olsnodes command, A-3
memory requirements, 2-7	oper group
Messaging Gateway	and SYSOPER privilege, 3-4
See Oracle Messaging Gateway	creating, 3-6
MetaLink	creating on other nodes, 3-9
Oracle patches, 7-1	description, 3-4
mkdir command, 4-7, 5-10	operating system
mkly command, 5-29	checking version, 2-14
mkuser command, 3-10	operating system requirements, 2-12
mkvg command, 4-17, 5-26	Oracle base directory
mode	about, 3-10
setting default file mode creation mask, 3-11	minimum disk size for, 2-8
<u> </u>	
multiple databases	Oracle Cluster Registry
and ASM, 3-5	configuration of, 6-7
multiple oracle homes, 2-5, 5-10	mirroring, 5-5
	partition sizes, 4-5 See OCR
	000 0 011

Oracle Clusterware	ORACLE_HOME environment variable
and single-instance databases, 4-2	removing from shell startup file, 2-26
and upgrading ASM instances, 1-5, 5-2	ORACLE_SID environment variable
installing, 6-1	removing from shell startup file, 2-26
installing with Oracle Universal Installer, 6-7	OracleMetaLink, 7-1
raw device for voting disk on AIX, 4-8	oraInst.loc
rolling upgrade of, 6-5	and Central Inventory, 2-4
upgrading, 4-5	contents of, 2-4
Oracle Database	oraInst.loc file
creating data file directories, 4-6, 5-9	location, 2-5
data file storage options, 4-2, 5-2	location of, 2-5
privileged groups, 3-2, 3-4	oraInventory, 3-3
requirements with ASM, 5-14	creating, 2-5
single instance data file storage options, 4-2	oraInventory directory
supported storage options for, 5-1	and Oracle Inventory Group, 2-3
Oracle Disk Manager	OSASM
and Direct NFS, 5-8	and multiple databases, 3-5
Oracle Inventory	and SYSASM, 3-5
pointer file, 2-5	OSASM group
Oracle Inventory Group	creating, 3-7
and Central Inventory (oraInventory), 2-3	OSDBA group
Oracle Inventory group	and ASM disks on AIX, 5-19
checking for existing, 2-4	and SYSDBA privilege, 3-2, 3-4
creating, 2-3, 2-5	creating, 3-6
creating on other nodes, 3-9	creating on other nodes, 3-9
description, 2-3	description, 3-2, 3-4
Oracle Messaging Gateway	for ASM, 3-5
requirements, 2-14	raw device group, 4-18, 4-19, 5-30
Oracle Notification Server Configuration	OSDBA group for ASM
Assistant, 6-8	creating, 3-7
Oracle Private Interconnect Configuration	oslevel command, 2-14
Assistant, 6-8	OSOPER group
Oracle RAC	and SYSOPER privilege, 3-4
configuring disks for raw devices, 5-11	
	creating, 3-6
Oracle Real Application Clusters	creating on other nodes, 3-9
shared storage device setup, 5-10	description, 3-4
Oracle Software Owner user	OUI
and ASM disks, 5-19	see Oracle Universal Installer
configuring environment for, 2-26	
creating, 2-5, 2-6, 3-7	P
creating on other nodes, 3-9	
description, 2-3, 3-3	partition 5.12
determining default shell, 2-26	using with ASM, 5-13
raw device owner, 4-18, 4-19, 5-30	partitions
required group membership, 2-3, 3-3	creating, 5-11
Oracle Universal Installer	creating raw partitions, 4-8, 5-20
and Oracle Clusterware, 6-7	required sizes for raw devices on AIX, 4-8
error messages, 6-8	passwd command, 2-6, 3-10
Oracle Upgrade Companion, 2-1	password file
oracle user	raw device for, 5-20, 5-29
and ASM disks, 5-19	raw devices for, 5-11
configuring environment for, 2-26	patches
creating, 2-5, 2-6, 3-7, 3-8	download, 7-1
creating on other nodes, 3-9	download location, 2-16
description, 2-3, 3-3	install, 7-1
determining default shell, 2-26	OracleMetaLink, 7-1
	PC X server
raw device owner, 4-18, 4-19, 5-30	installing from, 2-2
required group membership, 2-3, 3-3	permission errors, 2-4
ORACLE_BASE environment variable	permissions
removing from shell startup file. 2-26	PETITIOSIONS

for data file directories, 4-7, 5-10	for SYSAUX tablespace, 5-11, 5-20, 5-28
physical RAM requirements, 2-7	for SYSTEM tablespace, 5-11, 5-20, 5-28
postinstallation	for TEMP tablespace, 5-11, 5-20, 5-28
patch download and install, 7-1	for UNDOTBS tablespace, 5-11, 5-20, 5-28
root.sh back up, 7-2	for USER tablespace, 5-11, 5-20, 5-29
Precompilers	identifying disks, 4-16, 5-25
requirements, 2-14	importing on disk group on cluster nodes, 4-18,
preconfigured database	5-30
ASM disk space requirements, 5-14	initializing disks for LVM, 4-16, 5-26
requirements when using ASM, 5-14	initializing disks for LVM on AIX, 5-17
preinstallation	required sizes, 4-18, 5-28
shared storage device creation, 5-10	on AIX, 4-8
privileged groups	specifying owner and permissions, 4-18, 4-19,
for Oracle Database, 3-2, 3-4	5-30
Pro*C/C++	storage option for data files, 4-2, 5-2
requirements, 2-14	value for DBCA_RAW_CONFIG environment
processor	variable, 5-24
checking system architecture, 2-9	recovery files
.profile file, 2-26	supported storage options, 5-2
PTF	redo log files
checking, 2-16	raw devices for, 5-11, 5-20, 5-29
download location, 2-16	redundancy level
PTF download location, 2-16	and space requirements for preconfigured
PVID	database, 5-14
clearing from disk device, 5-17	remote node
	defined, 8-2
R	removing Oracle software
	local and remote nodes, 8-2
RAC	requirements
configuring disks for raw devices on AIX, 5-20	hardware, 2-7
configuring raw logical volumes, 4-16, 5-25	management and the second seco
	reserve setting, 4-10
preferred datafile storage mechanisms, 5-12	rolling upgrade
preferred datafile storage mechanisms, 5-12 RAID	
preferred datafile storage mechanisms, 5-12 RAID and mirroring OCR and voting disk, 4-5	rolling upgrade
preferred datafile storage mechanisms, 5-12 RAID and mirroring OCR and voting disk, 4-5 and mirroring Oracle Cluster Registry and voting	rolling upgrade Oracle Clusterware, 6-5
preferred datafile storage mechanisms, 5-12 RAID and mirroring OCR and voting disk, 4-5 and mirroring Oracle Cluster Registry and voting disk, 5-5	rolling upgrade Oracle Clusterware, 6-5 root user
preferred datafile storage mechanisms, 5-12 RAID and mirroring OCR and voting disk, 4-5 and mirroring Oracle Cluster Registry and voting disk, 5-5 recommended ASM redundancy level, 5-13	rolling upgrade Oracle Clusterware, 6-5 root user logging in as, 2-2
preferred datafile storage mechanisms, 5-12 RAID and mirroring OCR and voting disk, 4-5 and mirroring Oracle Cluster Registry and voting disk, 5-5 recommended ASM redundancy level, 5-13 RAM requirements, 2-7	rolling upgrade Oracle Clusterware, 6-5 root user logging in as, 2-2 root.sh, 6-8
preferred datafile storage mechanisms, 5-12 RAID and mirroring OCR and voting disk, 4-5 and mirroring Oracle Cluster Registry and voting disk, 5-5 recommended ASM redundancy level, 5-13 RAM requirements, 2-7 raw device	rolling upgrade Oracle Clusterware, 6-5 root user logging in as, 2-2 root.sh, 6-8 back up, 7-2
preferred datafile storage mechanisms, 5-12 RAID and mirroring OCR and voting disk, 4-5 and mirroring Oracle Cluster Registry and voting disk, 5-5 recommended ASM redundancy level, 5-13 RAM requirements, 2-7 raw device for OCR	rolling upgrade Oracle Clusterware, 6-5 root user logging in as, 2-2 root.sh, 6-8 back up, 7-2 running, 6-5
preferred datafile storage mechanisms, 5-12 RAID and mirroring OCR and voting disk, 4-5 and mirroring Oracle Cluster Registry and voting disk, 5-5 recommended ASM redundancy level, 5-13 RAM requirements, 2-7 raw device for OCR on AIX, 4-8	rolling upgrade Oracle Clusterware, 6-5 root user logging in as, 2-2 root.sh, 6-8 back up, 7-2 running, 6-5 rsize parameter, 4-6, 5-9
preferred datafile storage mechanisms, 5-12 RAID and mirroring OCR and voting disk, 4-5 and mirroring Oracle Cluster Registry and voting disk, 5-5 recommended ASM redundancy level, 5-13 RAM requirements, 2-7 raw device for OCR on AIX, 4-8 for password file, 5-20, 5-29	rolling upgrade Oracle Clusterware, 6-5 root user logging in as, 2-2 root.sh, 6-8 back up, 7-2 running, 6-5 rsize parameter, 4-6, 5-9
preferred datafile storage mechanisms, 5-12 RAID and mirroring OCR and voting disk, 4-5 and mirroring Oracle Cluster Registry and voting disk, 5-5 recommended ASM redundancy level, 5-13 RAM requirements, 2-7 raw device for OCR on AIX, 4-8 for password file, 5-20, 5-29 for server parameter file, 5-20, 5-29	rolling upgrade Oracle Clusterware, 6-5 root user logging in as, 2-2 root.sh, 6-8 back up, 7-2 running, 6-5 rsize parameter, 4-6, 5-9 S scripts
preferred datafile storage mechanisms, 5-12 RAID and mirroring OCR and voting disk, 4-5 and mirroring Oracle Cluster Registry and voting disk, 5-5 recommended ASM redundancy level, 5-13 RAM requirements, 2-7 raw device for OCR on AIX, 4-8 for password file, 5-20, 5-29 for server parameter file, 5-20, 5-29 for SPFILE, 5-11, 5-20, 5-29	rolling upgrade Oracle Clusterware, 6-5 root user logging in as, 2-2 root.sh, 6-8 back up, 7-2 running, 6-5 rsize parameter, 4-6, 5-9 S scripts root.sh, 6-5
preferred datafile storage mechanisms, 5-12 RAID and mirroring OCR and voting disk, 4-5 and mirroring Oracle Cluster Registry and voting disk, 5-5 recommended ASM redundancy level, 5-13 RAM requirements, 2-7 raw device for OCR on AIX, 4-8 for password file, 5-20, 5-29 for server parameter file, 5-20, 5-29 for SPFILE, 5-11, 5-20, 5-29 for SPFILE file, 5-11	rolling upgrade Oracle Clusterware, 6-5 root user logging in as, 2-2 root.sh, 6-8 back up, 7-2 running, 6-5 rsize parameter, 4-6, 5-9 S scripts root.sh, 6-5 security
preferred datafile storage mechanisms, 5-12 RAID and mirroring OCR and voting disk, 4-5 and mirroring Oracle Cluster Registry and voting disk, 5-5 recommended ASM redundancy level, 5-13 RAM requirements, 2-7 raw device for OCR on AIX, 4-8 for password file, 5-20, 5-29 for server parameter file, 5-20, 5-29 for SPFILE, 5-11, 5-20, 5-29 for SPFILE file, 5-11 for voting disk	rolling upgrade Oracle Clusterware, 6-5 root user logging in as, 2-2 root.sh, 6-8 back up, 7-2 running, 6-5 rsize parameter, 4-6, 5-9 S scripts root.sh, 6-5 security dividing ownership of Oracle software, 3-3
preferred datafile storage mechanisms, 5-12 RAID and mirroring OCR and voting disk, 4-5 and mirroring Oracle Cluster Registry and voting disk, 5-5 recommended ASM redundancy level, 5-13 RAM requirements, 2-7 raw device for OCR on AIX, 4-8 for password file, 5-20, 5-29 for server parameter file, 5-20, 5-29 for SPFILE, 5-11, 5-20, 5-29 for SPFILE file, 5-11 for voting disk on AIX, 4-8	rolling upgrade Oracle Clusterware, 6-5 root user logging in as, 2-2 root.sh, 6-8 back up, 7-2 running, 6-5 rsize parameter, 4-6, 5-9 S scripts root.sh, 6-5 security dividing ownership of Oracle software, 3-3 server parameter file
preferred datafile storage mechanisms, 5-12 RAID and mirroring OCR and voting disk, 4-5 and mirroring Oracle Cluster Registry and voting disk, 5-5 recommended ASM redundancy level, 5-13 RAM requirements, 2-7 raw device for OCR on AIX, 4-8 for password file, 5-20, 5-29 for server parameter file, 5-20, 5-29 for SPFILE, 5-11, 5-20, 5-29 for SPFILE file, 5-11 for voting disk on AIX, 4-8 raw device sizes, 4-18, 5-28	rolling upgrade Oracle Clusterware, 6-5 root user logging in as, 2-2 root.sh, 6-8 back up, 7-2 running, 6-5 rsize parameter, 4-6, 5-9 S scripts root.sh, 6-5 security dividing ownership of Oracle software, 3-3 server parameter file raw device for, 5-20, 5-29
preferred datafile storage mechanisms, 5-12 RAID and mirroring OCR and voting disk, 4-5 and mirroring Oracle Cluster Registry and voting disk, 5-5 recommended ASM redundancy level, 5-13 RAM requirements, 2-7 raw device for OCR on AIX, 4-8 for password file, 5-20, 5-29 for server parameter file, 5-20, 5-29 for SPFILE, 5-11, 5-20, 5-29 for SPFILE file, 5-11 for voting disk on AIX, 4-8 raw devices raw devices	rolling upgrade Oracle Clusterware, 6-5 root user logging in as, 2-2 root.sh, 6-8 back up, 7-2 running, 6-5 rsize parameter, 4-6, 5-9 S scripts root.sh, 6-5 security dividing ownership of Oracle software, 3-3 server parameter file raw device for, 5-20, 5-29 setting shell limits, 2-17
preferred datafile storage mechanisms, 5-12 RAID and mirroring OCR and voting disk, 4-5 and mirroring Oracle Cluster Registry and voting disk, 5-5 recommended ASM redundancy level, 5-13 RAM requirements, 2-7 raw device for OCR on AIX, 4-8 for password file, 5-20, 5-29 for server parameter file, 5-20, 5-29 for SPFILE, 5-11, 5-20, 5-29 for SPFILE file, 5-11 for voting disk on AIX, 4-8 raw devices sizes, 4-18, 5-28 raw devices activating volume group on cluster nodes, 4-19,	rolling upgrade Oracle Clusterware, 6-5 root user logging in as, 2-2 root.sh, 6-8 back up, 7-2 running, 6-5 rsize parameter, 4-6, 5-9 S scripts root.sh, 6-5 security dividing ownership of Oracle software, 3-3 server parameter file raw device for, 5-20, 5-29 setting shell limits, 2-17 shared storage devices
preferred datafile storage mechanisms, 5-12 RAID and mirroring OCR and voting disk, 4-5 and mirroring Oracle Cluster Registry and voting disk, 5-5 recommended ASM redundancy level, 5-13 RAM requirements, 2-7 raw device for OCR on AIX, 4-8 for password file, 5-20, 5-29 for server parameter file, 5-20, 5-29 for SPFILE, 5-11, 5-20, 5-29 for SPFILE file, 5-11 for voting disk on AIX, 4-8 raw devices sizes, 4-18, 5-28 raw devices activating volume group on cluster nodes, 4-19, 5-31	rolling upgrade Oracle Clusterware, 6-5 root user logging in as, 2-2 root.sh, 6-8 back up, 7-2 running, 6-5 rsize parameter, 4-6, 5-9 S scripts root.sh, 6-5 security dividing ownership of Oracle software, 3-3 server parameter file raw device for, 5-20, 5-29 setting shell limits, 2-17 shared storage devices configuring for datafiles, 5-10
preferred datafile storage mechanisms, 5-12 RAID and mirroring OCR and voting disk, 4-5 and mirroring Oracle Cluster Registry and voting disk, 5-5 recommended ASM redundancy level, 5-13 RAM requirements, 2-7 raw device for OCR on AIX, 4-8 for password file, 5-20, 5-29 for server parameter file, 5-20, 5-29 for SPFILE, 5-11, 5-20, 5-29 for SPFILE file, 5-11 for voting disk on AIX, 4-8 raw devices activating volume group on cluster nodes, 4-19, 5-31 checking availability of disks, 4-16, 5-25	rolling upgrade Oracle Clusterware, 6-5 root user logging in as, 2-2 root.sh, 6-8 back up, 7-2 running, 6-5 rsize parameter, 4-6, 5-9 S scripts root.sh, 6-5 security dividing ownership of Oracle software, 3-3 server parameter file raw device for, 5-20, 5-29 setting shell limits, 2-17 shared storage devices configuring for datafiles, 5-10 shell
preferred datafile storage mechanisms, 5-12 RAID and mirroring OCR and voting disk, 4-5 and mirroring Oracle Cluster Registry and voting disk, 5-5 recommended ASM redundancy level, 5-13 RAM requirements, 2-7 raw device for OCR on AIX, 4-8 for password file, 5-20, 5-29 for server parameter file, 5-20, 5-29 for SPFILE, 5-11, 5-20, 5-29 for SPFILE file, 5-11 for voting disk on AIX, 4-8 raw devices sizes, 4-18, 5-28 raw devices activating volume group on cluster nodes, 4-19, 5-31 checking availability of disks, 4-16, 5-25 creating logical volumes, 5-29	rolling upgrade Oracle Clusterware, 6-5 root user logging in as, 2-2 root.sh, 6-8 back up, 7-2 running, 6-5 rsize parameter, 4-6, 5-9 S scripts root.sh, 6-5 security dividing ownership of Oracle software, 3-3 server parameter file raw device for, 5-20, 5-29 setting shell limits, 2-17 shared storage devices configuring for datafiles, 5-10 shell determining default shell for oracle user, 2-26
preferred datafile storage mechanisms, 5-12 RAID and mirroring OCR and voting disk, 4-5 and mirroring Oracle Cluster Registry and voting disk, 5-5 recommended ASM redundancy level, 5-13 RAM requirements, 2-7 raw device for OCR on AIX, 4-8 for password file, 5-20, 5-29 for server parameter file, 5-20, 5-29 for SPFILE, 5-11, 5-20, 5-29 for SPFILE file, 5-11 for voting disk on AIX, 4-8 raw devices sizes, 4-18, 5-28 raw devices activating volume group on cluster nodes, 4-19, 5-31 checking availability of disks, 4-16, 5-25 creating logical volumes, 5-29 creating partitions on, 5-11	rolling upgrade Oracle Clusterware, 6-5 root user logging in as, 2-2 root.sh, 6-8 back up, 7-2 running, 6-5 rsize parameter, 4-6, 5-9 S scripts root.sh, 6-5 security dividing ownership of Oracle software, 3-3 server parameter file raw device for, 5-20, 5-29 setting shell limits, 2-17 shared storage devices configuring for datafiles, 5-10 shell determining default shell for oracle user, 2-26 SHELL environment variable
preferred datafile storage mechanisms, 5-12 RAID and mirroring OCR and voting disk, 4-5 and mirroring Oracle Cluster Registry and voting disk, 5-5 recommended ASM redundancy level, 5-13 RAM requirements, 2-7 raw device for OCR on AIX, 4-8 for password file, 5-20, 5-29 for server parameter file, 5-20, 5-29 for SPFILE, 5-11, 5-20, 5-29 for SPFILE file, 5-11 for voting disk on AIX, 4-8 raw device sizes, 4-18, 5-28 raw devices activating volume group on cluster nodes, 4-19, 5-31 checking availability of disks, 4-16, 5-25 creating logical volumes, 5-29 creating partitions on, 5-11 creating raw logical volumes, 4-18, 5-28	rolling upgrade Oracle Clusterware, 6-5 root user logging in as, 2-2 root.sh, 6-8 back up, 7-2 running, 6-5 rsize parameter, 4-6, 5-9 S scripts root.sh, 6-5 security dividing ownership of Oracle software, 3-3 server parameter file raw device for, 5-20, 5-29 setting shell limits, 2-17 shared storage devices configuring for datafiles, 5-10 shell determining default shell for oracle user, 2-26 SHELL environment variable checking value of, 2-26
preferred datafile storage mechanisms, 5-12 RAID and mirroring OCR and voting disk, 4-5 and mirroring Oracle Cluster Registry and voting disk, 5-5 recommended ASM redundancy level, 5-13 RAM requirements, 2-7 raw device for OCR on AIX, 4-8 for password file, 5-20, 5-29 for server parameter file, 5-20, 5-29 for SPFILE, 5-11, 5-20, 5-29 for SPFILE file, 5-11 for voting disk on AIX, 4-8 raw device sizes, 4-18, 5-28 raw devices activating volume group on cluster nodes, 4-19, 5-31 checking availability of disks, 4-16, 5-25 creating logical volumes, 5-29 creating partitions on, 5-11 creating raw logical volumes, 4-18, 5-28 creating raw partitions, 4-8, 5-20	rolling upgrade Oracle Clusterware, 6-5 root user logging in as, 2-2 root.sh, 6-8 back up, 7-2 running, 6-5 rsize parameter, 4-6, 5-9 S scripts root.sh, 6-5 security dividing ownership of Oracle software, 3-3 server parameter file raw device for, 5-20, 5-29 setting shell limits, 2-17 shared storage devices configuring for datafiles, 5-10 shell determining default shell for oracle user, 2-26 SHELL environment variable checking value of, 2-26 shell limits, 2-17
preferred datafile storage mechanisms, 5-12 RAID and mirroring OCR and voting disk, 4-5 and mirroring Oracle Cluster Registry and voting disk, 5-5 recommended ASM redundancy level, 5-13 RAM requirements, 2-7 raw device for OCR on AIX, 4-8 for password file, 5-20, 5-29 for server parameter file, 5-20, 5-29 for SPFILE, 5-11, 5-20, 5-29 for SPFILE file, 5-11 for voting disk on AIX, 4-8 raw device sizes, 4-18, 5-28 raw devices activating volume group on cluster nodes, 4-19, 5-31 checking availability of disks, 4-16, 5-25 creating logical volumes, 5-29 creating partitions on, 5-11 creating raw logical volumes, 4-18, 5-28 creating raw partitions, 4-8, 5-20 for control files, 5-11, 5-20, 5-29	rolling upgrade Oracle Clusterware, 6-5 root user logging in as, 2-2 root.sh, 6-8 back up, 7-2 running, 6-5 rsize parameter, 4-6, 5-9 S scripts root.sh, 6-5 security dividing ownership of Oracle software, 3-3 server parameter file raw device for, 5-20, 5-29 setting shell limits, 2-17 shared storage devices configuring for datafiles, 5-10 shell determining default shell for oracle user, 2-26 SHELL environment variable checking value of, 2-26 shell limits, 2-17 shell startup file
preferred datafile storage mechanisms, 5-12 RAID and mirroring OCR and voting disk, 4-5 and mirroring Oracle Cluster Registry and voting disk, 5-5 recommended ASM redundancy level, 5-13 RAM requirements, 2-7 raw device for OCR on AIX, 4-8 for password file, 5-20, 5-29 for server parameter file, 5-20, 5-29 for SPFILE, 5-11, 5-20, 5-29 for SPFILE file, 5-11 for voting disk on AIX, 4-8 raw device sizes, 4-18, 5-28 raw devices activating volume group on cluster nodes, 4-19, 5-31 checking availability of disks, 4-16, 5-25 creating logical volumes, 5-29 creating partitions on, 5-11 creating raw logical volumes, 4-18, 5-28 creating raw partitions, 4-8, 5-20 for control files, 5-11, 5-20, 5-29 for EXAMPLE tablespace, 5-11, 5-20, 5-28	rolling upgrade Oracle Clusterware, 6-5 root user logging in as, 2-2 root.sh, 6-8 back up, 7-2 running, 6-5 rsize parameter, 4-6, 5-9 S scripts root.sh, 6-5 security dividing ownership of Oracle software, 3-3 server parameter file raw device for, 5-20, 5-29 setting shell limits, 2-17 shared storage devices configuring for datafiles, 5-10 shell determining default shell for oracle user, 2-26 SHELL environment variable checking value of, 2-26 shell limits, 2-17 shell startup file editing, 2-26
preferred datafile storage mechanisms, 5-12 RAID and mirroring OCR and voting disk, 4-5 and mirroring Oracle Cluster Registry and voting disk, 5-5 recommended ASM redundancy level, 5-13 RAM requirements, 2-7 raw device for OCR on AIX, 4-8 for password file, 5-20, 5-29 for server parameter file, 5-20, 5-29 for SPFILE, 5-11, 5-20, 5-29 for SPFILE file, 5-11 for voting disk on AIX, 4-8 raw device sizes, 4-18, 5-28 raw devices activating volume group on cluster nodes, 4-19, 5-31 checking availability of disks, 4-16, 5-25 creating logical volumes, 5-29 creating partitions on, 5-11 creating raw logical volumes, 4-18, 5-28 creating raw partitions, 4-8, 5-20 for control files, 5-11, 5-20, 5-29	rolling upgrade Oracle Clusterware, 6-5 root user logging in as, 2-2 root.sh, 6-8 back up, 7-2 running, 6-5 rsize parameter, 4-6, 5-9 S scripts root.sh, 6-5 security dividing ownership of Oracle software, 3-3 server parameter file raw device for, 5-20, 5-29 setting shell limits, 2-17 shared storage devices configuring for datafiles, 5-10 shell determining default shell for oracle user, 2-26 SHELL environment variable checking value of, 2-26 shell limits, 2-17 shell startup file

software requirements, 2-12	setting, 2-27
checking software requirements, 2-14	troubleshooting
specifying owner and permissions of raw	ASM failure to mount disk group, 5-17
devices, 4-18, 4-19, 5-30	intermittent hangs, 6-9
SPFILE	ssh, 2-20
raw device for, 5-20, 5-29	user equivalency, 2-20, 6-2
raw deviceS for, 5-11	
raw devices for, 5-11	U
ssh	
and X11 Forwarding, 2-25	uid
loading keys into memory before	identifying existing, 3-9
installation, 2-24	specifying, 3-9
Standard Edition Oracle Database	specifying on other nodes, 3-9
supported storage options for, 5-2	umask, 2-27
startup file	umask command, 2-27, 3-11
for shell, 2-26	UNDOTBS tablespace
storage	raw device for, 5-20, 5-28
for database files, 4-3, 5-3	raw devices for, 5-11
GPFS, 4-2, 5-5	UNIX commands, 2-27
ASM files not supported on, 5-3	cfgmgr, 4-16, 5-17, 5-26
HACMP, 4-3, 5-3	chdev, 4-16, 5-17, 5-26
storage options	chmod, 4-7, 5-19
for Enterprise Edition installations, 5-1	chown, 4-7, 5-19
for Standard Edition installations, 5-1	env, 2-27
supported storage options, 5-2	importvg, 4-19, 5-30
swap space	instfix, 2-16
requirements, 2-7	lsdev, 4-16, 5-16, 5-25
SYSASM	lslpp, 2-14, 2-16
and OSASM, 3-5	lspv, 4-16, 4-18, 4-19, 5-17, 5-26, 5-30
SYSAUX tablespace	mkdir, 4-7
raw device for, 5-20, 5-28	mklv, 5-29
raw devices for, 5-11	mkvg, 4-17, 5-26
SYSDBA	oslevel, 2-14
using database SYSDBA on ASM deprecated, 3-5	passwd, 2-6
SYSDBA privilege	smit, 2-6, 3-2, 3-3
associated UNIX group, 3-2, 3-4	swap, 2-9
SYSOPER privilege	swapon, 2-9
associated UNIX group, 3-4	varyoffvg, 4-19, 5-30
system architecture	varyonvg, 4-18, 5-28
checking, 2-9	xterm, 2-2
SYSTEM tablespace	UNIX groups
raw device for, 5-20, 5-28	oinstall, 2-3
raw devices for, 5-11	OSDBA (dba), 3-2, 3-4
	OSOPER (oper), 3-4
T	required for oracle user, 2-3, 3-3
	using NIS, 3-2, 3-5
TEMP environment variable, 2-9	UNIX users
setting, 2-27	nobody, 3-2, 3-4
TEMP tablespace	oracle, 2-3, 3-3
raw device for, 5-20, 5-28	required for external jobs, 3-2, 3-4
raw devices for, 5-11	unprivileged user, 3-2, 3-4
temporary directory, 2-9	using NIS, 3-2, 3-5
temporary disk space	unprivileged user
checking, 2-9	nobody user, 3-2, 3-4
freeing, 2-9	upgrade
requirements, 2-7	of Cluster Ready Services, 6-4
/tmp directory	of Oracle Clusterware, 6-5
checking space in, 2-9	upgrades, 2-1
freeing space in, 2-9	upgrading
TMPDIR environment variable, 2-9	and existing ASM instances, 1-5, 5-2

and OCR partition sizes, 4-5 and voting disk partition sizes, 4-5 user equivalence testing, 6-2 user equivalence error, 6-2 user IDs identifying existing, 3-9 specifying, 3-9 specifying on other nodes, 3-9 USER tablespace raw device for, 5-20, 5-29 raw devices for, 5-11 users checking existence of the nobody user, 3-2 creating identical users on other nodes, 3-9 creating the oracle user, 2-5, 2-6, 3-7 Oracle Software Owner user (oracle), 2-3, 3-3 specifying groups when creating, 3-9 UNIX nobody user, 3-2, 3-4 using NIS, 3-1, 3-3, 3-9 ٧ varyoffvg command, 4-19, 5-30 varyonvg command, 4-18, 5-28 virtual memory manager tuning, 2-16 volume group creating, 4-16, 5-25 volume groups creating, 4-17, 5-26 volumes creating logical volumes, 5-29 voting disk configuration of, 6-7 mirroring, 4-5, 5-5 raw device for on AIX, 4-8 restriction on using ASM for, 5-12 voting disks, 4-2 partition sizes, 4-5 requirement of absolute majority of, 4-2 WebSphere MQ CSD download location, 2-16 requirement, 2-14 workstation installing from, 2-2 wsize, 4-6, 5-9 wsize parameter, 4-6, 5-9 X X emulator installing from, 2-2 X window system enabling remote hosts, 2-2 X11 forwarding

X11 forwarding errors, 2-24 xhost command, 2-2 xterm command, 2-2

errors, 2-25