



Agile Product Lifecycle Management

Administrator Guide

v9.3.0.2

Part No. E17298-01

June 2010

Oracle Copyright

Copyright © 1995, 2010, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS

Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy and other measures to ensure the safe use of this software. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software in dangerous applications.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

This software and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third party content, products and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third party content, products or services.

CONTENTS

Oracle Copyright.....	ii
Chapter 1 Introduction	1
Welcome to Agile PLM Administrator	1
How to Find Documentation for Agile PLM.....	1
Documentation for the PLM Administrator.....	1
Agile Configuration Propagation (ACP) Guide	1
Getting Started with Agile PLM.....	1
PLM Solution-Specific User Guides	2
Agile Product Lifecycle Management Solutions	2
What's New in Administrator	3
Features and Enhancements added in Rel. 9.3	3
Installation Test Notice	3
Chapter 2 Getting Started in Administrator.....	5
Overview.....	5
Logging in to Agile Clients as an Administrator.....	5
Creating New Administrator Users	6
Dates and Times in Agile PLM	8
...at the Server Level	8
...at the Client Level.....	8
Example.....	8
Administrator User Interfaces	8
Filtering Data in Java Client.....	9
Administrator Nodes in Java Client	9
Administrative Capabilities	12
Example Nodes in Java Client.....	13
Administration in Web Client	14
Agile PLM Variables	15
Default Value Variables	15
\$CURRENTREV Criteria Logic	15
Privilege Mask Criteria Variables.....	16
Workflow Assignment and Status Type Variables.....	17
Routing Manager Variables	18
Chapter 3 Administrator Functions in Java Client	19
API Name	19
API Name field in Java Client	19
Administrator Reports.....	20

Utilities on Admin Toolbar	22
Sending Email to Users	22
Global Replace	22
Global Replace Properties.....	23
History Tracking.....	24
Object History and Administrative Object History	24
Administrator History	25
Purging Administrator History	26
History of Deleted Objects.....	26
Deleting Objects in Agile	26
Administrator Import and Export.....	28
Encoding Types.....	28
Administrator Export.....	29
Administrator Import	29
Process Extensions Library	30
Multiple Language Support	30
Administrator Data that is Supported for Multi-Language Capability.....	31
Supported Administrator Nodes	31
Supported Predefined System Objects	33
Administrator Data that is Not Supported for Multi-Language Capability	33
User Settings	33
System Settings.....	33
Any values/strings input by user.....	33
Attribute names with "01", "02", "03", etc appended	33
Configuring a System for Multi-Languages	34
Chapter 4 Administrator Functions in Web Client	37
Overview to Administrator in Web Client.....	37
Configuring the Dashboard	38
Visual Themes.....	38
Selecting Theme Options	38
Replacing the Oracle Logo	39
Modifying Style Schemes	40
Specifying Colors in Hexidecimal Format.....	41
Report Templates.....	42
Manage Report Template (AppliedTo Choice)	42
Dynamic and Static Templates	42
Creating Report Templates	43
Reports Unsupported by BI Publisher	43
Logging Configuration	44
– For use by Agile Support ONLY! –	44
Cache Health Monitor.....	45

How the Cache Health Monitor Works	45
Automatic Synchronization using Java Client Administrator	46
Logging and Debugging Errors.....	47
Manual Triggering:.....	48
Automatic Triggering:	48
Deleting Objects in Agile	49
Chapter 5 Classes.....	51
Configuring Business Objects with Agile PLM Classes	51
Agile PLM Class Structure	52
Routable and Non-Routable Objects.....	53
Object Types in Agile PLM	53
Viewing Agile PLM Classes.....	53
Agile PLM's Installed Object Types	54
Agile PLM's Installed Nonroutable Object Types	55
Disabling Object Types.....	57
Customizing Lifecycle Phases.....	58
Modifying a Lifecycle Phase	58
Adding a Lifecycle Phase	59
Removing a Lifecycle Phase	59
Configuring Subclasses.....	60
Before You Begin	61
Viewing Subclass Properties	61
Changing the AutoNumber Source Property	61
Preventing Manual Number Assignment	62
Changing a Subclass Name or Description	62
Changing the Site-Specific BOM Property	63
Creating a New Subclass	63
Deleting a Subclass.....	64
Configuring Tabs	65
About Page Two Tabs	65
About Page Three Tabs	65
Showing, Hiding, or Renaming a Tab.....	66
Modifying the Format of Tabs.....	66
Modifying Attribute Order on a Form Tab.....	67
Modifying Attribute Order on a Table Tab	68
Designing a Page Two or Page Three Tab	68
About the Page Two Create User Attribute	68
Guidelines for Designing Page Two and Page Three Tabs	69

Stage I: Preparing Page Two or Page Three Attributes	69
Before You Begin	70
Stage II: Setting Up the Tab	71
Using Heading Attributes	71
Removing a Page Two or Page Three Tab	72
About Attributes, Flex Fields, and Read-Through Fields	73
User-Defined Flex Fields	73
Where User-Defined Flex Fields can be Used	74
Where user-defined flex fields are fully supported:	74
Where user-defined flex fields are partially supported:	75
Where User-Defined Flex Fields cannot be Used	75
Read-Through Fields	75
Read-Through Fields Made Consistent in Items and Changes	76
Read-Through Fields on the BOM and Manufacturers Tabs	76
Defining Attributes	77
Recognizing Attribute Types	78
Defining Attribute Properties	79
An Exception Involving Required Fields in Object Modification	83
Image Attributes	84
Configuring Attributes	84
Modifying Attributes	84
Matching the Properties of Attributes Common to Several Tabs	85
Setting Default Values	85
Showing or Hiding an Attribute on a Tab	86
Editing a Field Label or Table Column Name	86
Using Custom Icons for Subclasses	86
Quick Access to Objects and Files	87
Agile-Generated Quick Access Object URLs	87
Formats for User-Generated Smart Object URLs	88
Using Quick Access Object URLs	89
Chapter 6 Character Sets	91
Available Character Sets	91
Creating a Character Set	92
Modifying a Character Set	93
Chapter 7 Lists	95
Overview	95
Routing Manager Lists	95
Creating Custom Lists and Adding to Lists	96
More Kinds of Lists	97
SingleList Lists	98
MultiList Lists	98

Cascading Lists	99
Dynamic Lists	99
Configuring Lists.....	99
Setting Default Values for Lists	101
Display Type for Lists in Web Client_93.....	102
Failure Mode Lists	102
Creating Cascading Lists	102
Chapter 8 Process Extensions	105
Overview to Process Extensions	105
Using the Process Extension Library	106
Assigning Process Extensions to Classes	108
Assigning Process Extensions to Workflow Statuses	108
Chapter 9 Autonumbers	111
How Autonumbers Are Used	111
Modifying an Autonumber Source	111
About Autonumber Sources	112
Configuring Autonumber Sources	114
Changing an Autonumber's Prefix or Suffix.....	115
Changing Where an Autonumber Source Is Used	116
Custom Autonumbers	116
Timeout.....	116
Creating a New Autonumber Source.....	116
Before You Begin	117
Deleting an Autonumber Source	118
Chapter 10 Criteria.....	119
About Reusable Criteria	119
Exploring Reusable Criteria.....	120
Viewing a Reusable Criteria	120
Criteria Windows and Tabs	121
Creating a New Criteria	121
Modifying an Existing Reusable Criteria.....	123
Using Affected Items Tab Fields in Reusable Criteria.....	123
How Changes Are Matched When Reusable Criteria Specify Affected Items Tab Fields.....	123
Difference Between "Item" and "Part" in Affected Items Names.....	124
More about Affected Items: Adding Approvers and Observers	124
Using \$CURRENTREV and \$LATESTREV in Criteria for Items	125
About TitleBlock.Rev	125

Rules for Using the \$CURRENTREV Variable	126
Rules for Using the \$LATESTREV Variable	127
Item Relationship Creation Using \$CURRENTREV and \$LATESTREV Criteria	128
Chapter 11 Workflows	129
How Workflows Automate the Change Control Process	129
Modifying a Workflow	130
Workflow Basics	130
Routing Managers	130
Other Workflow Basics	131
Keep It Simple!	132
Default Status-Based Workflows	133
Status Types Defined	133
Creating New Workflows with Save As	135
General Workflow Properties	136
General Information Tab	136
About Workflow name	137
Workflow Criteria Matching Type	137
Status Criteria Matching Type	138
Creating and Using Custom Workflows	139
Before You Begin	140
Custom Workflow Example	140
Guidelines for Creating Workflows	141
Creating a New Workflow	142
When a New Workflow is Enabled	144
Routing to a User Group	144
Status Properties Defined	145
If No Criteria Apply At Exit, Notify	145
Manual Valid Next Status	145
Save Routing Slip Content when Advancing Change	146
Send Workflow Status Comments and Notifications to all Previous and Current CCB Members	146
AutoPromote	146
If AutoPromote Fails, Notify	147
Ability to Fail Autopromote More than Once within same Change Status	148
Ad Hoc Approvers/Observers	148
If Rejected, Set Status To	148
If Rejected, Notify	149
Reminder Period	149
Review Escalation Period	150

Designated Escalation Person	150
Comments for Approval	151
Comments for Rejection	151
Criteria-Specific Properties Defined	151
Approvers and Observers	151
Criteria Usage	152
Default Change Analyst / Component Engineer	152
Notify Upon Entry	153
Pass Release Audit	153
Two Levels of Audit	154
Status Audit, or Audit Current Status for Conditions to Advance	154
Release Audit, or Audit Current Status for Conditions to Release	154
Exit Required Fields	156
Workflow Functionality Testing	156
Areas of Workflow Validation	156
Quick Tips on Testing	157
Migrating Workflows to Production	158
Quick Tip on Migrating Workflows	158
Workflow Migration Process	158
Changing Active Workflows	158
Modifying Properties in an Enabled Workflow	159
When You Can Disable, Modify, and Re-enable a Workflow	159
What You Can Modify If a Workflow Has Any Routable Objects Applied	159
What You Cannot Modify If a Workflow Has Any Routable Objects Applied	160
Disabling, Changing, and Reactivating Workflows	160
Chapter 12 Account Policy	163
Before You Begin	163
Configuring the Account Policy	163
Administrator Reset of Locked Out Account	165
Chapter 13 Users	167
Adding New Users	167
Before You Begin	168
About Usernames	169
About Passwords	169
Change Internal User Password	170
LDAP as a Node in Administrator	171
Modifying User Properties	171
Changing a User's Password	171
Changing a User's Role Assignments	172
User Properties Defined	172

Chapter 14 User Groups	179
Creating a New User Group	179
User Group Properties	181
Modifying a User Group	182
Assigning Escalation Persons to User Groups	182
Adding User Groups as Approvers of a Change	183
Setting Up User Groups as Partners	184
Chapter 15 Supplier Groups	187
Overview	187
Properties	187
Available actions	187
Chapter 16 Roles	189
Overview of Roles and Privileges in Agile PLM	189
What is a Privilege Mask?	189
Getting Familiar with Roles	190
Viewing the Roles Window	191
Viewing a Role	191
Guidelines for Working with Roles	192
Default Agile PLM Roles	192
Administrator roles	193
General-function Agile PLM roles	193
Engineering Collaboration role	194
Product Collaboration roles	195
Product Quality Management roles	195
Product Cost Management roles	196
Product Portfolio Management roles	196
Reports roles	197
Agile Content Services role	197
Product Governance & Compliance roles	197
Agile Configuration Propagation roles	198
Example Roles	198
Restricted Roles	198
Role-based Enhancements	199
User Administrator Enhancement	199
Advanced Search Security	199
Securing and Maintaining Roles and Privilege Masks	199
Using Agile Configuration Propagation to Restore Admin Settings	200
Recommended Security and Maintenance Plan	200
Database Backup Procedures	201

Exporting Agile PLM Administrative Settings	201
Running Reports.....	201
Working with Roles.....	202
Modifying a Role.....	202
Building and Testing Attributes, Read/Modify Privileges, and Roles	204
Creating a New Role	205
Before You Begin	205
Creating a New Role Using Save As.....	205
Creating a New Role from Scratch.....	206
Using the Example Roles	207
Example Privilege Masks in Example Roles	207
Creating a New Role from an Example Role Using Save As	208
Deleting a Role	208
Chapter 17 Privileges and Privilege Masks	211
About Privileges and Privilege Masks	211
Getting Familiar with Privileges and Privilege Masks.....	211
Viewing Privilege Masks.....	212
Viewing Privilege Mask Properties	212
Tasks Performed from the Privileges Window.....	214
Removing a Privilege Mask from a Role	214
Adding a Privilege Mask to a Role	215
Default Agile PLM Privileges	215
Further Discussion of Specific Privileges	220
More Information about Selected Privileges.....	221
Add Approver/Observer and Remove Approver/Observer.....	221
Change Status	221
Export	222
Full Search Display.....	222
Grant.....	222
Override.....	223
Purge Folder Version Privilege.....	224
Transfer Authority for Self.....	224
Transfer Authority for Others	225
Site Change Order Save As Limitations	225
Subscribe.....	225
Privilege Mask Components.....	225
All Privilege Masks have a Privilege, an Object Type, and a Criteria.....	226
A Few Privileges are the Basis to Privilege Masks with AppliedTo.....	226
Diagramming Privilege Masks	227
Naming Privilege Masks	227
Privilege Mask Component 1: Privileges	227
Privilege Mask Component 2: Object Type	229
Privilege Mask Component 3: Criteria	230
Privilege Mask Component 4: Attributes	230
Enabling a Privilege Mask	231

Modifying Privilege Masks	232
Modifying Privilege Mask Criteria	232
AppliedTo Property in Select Privileges	232
Administrator Privilege and the AppliedTo Capability	233
Specialized Administrator Privilege Masks	234
Dashboard Management	236
Project Summary Page Configuration	237
Creating New Privilege Masks	237
Before You Begin	237
Copying a Privilege Mask Using Save As	238
Creating a New Privilege Mask from Scratch	238
Combining Options in Criteria and AppliedTo Attributes	239
Discovery and Read Privileges	241
Discovery Privilege	241
Discovery Privilege and Sites	242
Discovery Privilege and Life Cycle Phases	242
Related SmartRules	242
Discovery Privilege and Reports	242
Relationships among Discovery and Read Privileges	243
Field-Level Read Privilege	243
Modifying the AppliedTo Fields of Read Privilege Masks	244
Enforce Field-Level Read Privilege	244
Display on Tables Due to Enforce Field-level Read	245
Modify Privilege	246
Some 'Modify' Basics and Rules	246
Controlling the Ability to Modify Items at Introductory Revision with \$CURRENTREV	247
Applicable Item Attributes	247
\$CURRENTREV Criteria Logic	247
Building Criteria for Specific Use Cases	248
Applying Create User Criteria	250
Using Privilege Mask Criteria Variables	251
Chapter 18 Other User Settings	253
User Monitor	253
Refreshing the User Monitor Window	253
Terminating a User Session	253
Deleting and Undeleting Users	254
Deleting a User Group	254
Hard-Deleting a User Group	255
Undeleting a User Group	255
Chapter 19 SmartRules	257
Modifying SmartRules Settings	257
SmartRules Defined	258

Allow Deletion of Attachments	258
Auto-Installs from PPM	258
Auto Publish Quote History	258
BOM Multi-Level Recursion	258
Change Status Approver Rejected Change	259
Change Status No Response Change	259
Change Status Observer Rejected Change	259
Check In Attachment With Different File Extension	259
Copy Files to Rev	260
Demotion Approvers Removal	260
Demotion Signoff Removal	261
Detailed TimeSheet Entry	261
Discovery Object Tables	261
Discovery Results Table	261
Display BOM Tables	262
Display Structure Tables	262
Duplicate Find Numbers	262
Duplicate Ref Des	263
Effectivity Date Order	263
Effectivity Gap	263
Effectivity Overlap	264
Enable Addition of Activities and Gates to Completed Activities	264
Enable Comments for Deleting, Archiving & Delegating	264
Force Commodity and Part Family to be Identical	264
Items Released First	264
Many Items per PSR	264
Many QCR per PSR	265
Multiple Items Per Manuf Part	265
Negative Value For Material Price Adder Fields	265
Negative Value For Material Price Fields	265
Negative Value For Non-Material Price Fields	265
Notify Resource Pool Owner for Proposed Programs	265
Overlap Price Line Effectivity Periods	265
PSR Contains Items and Related PSRs	265
Redline Attributes	266
Redline Manufacturers On Change Order	266
Release QCR With Un-resolved Items	266
Released Rev Required	266
Unrelease Change Order	266

Unrelease Change Request	267
Unrelease Deviation	267
Unrelease Manufacturing Order	267
Unrelease Stop Ship.....	267
Workflow Matching Criteria Attribute Modification	267
Zero Value For Material Price Fields	267
Zero Value For Material Price Adder Fields	268
Zero Value For Non-Material Price Fields	268
Chapter 20 Viewer and Files	269
Introduction	269
Viewer & Files Properties	269
Options for Purging and Retaining Files	270
AutoPurge Enabled	270
File Version Keep	271
Purge Redlined Files	271
Directly Use These Thumbnail Image Types.....	271
Thumbnail generation options	272
CAD Revision BOM Attribute.....	272
File Association tab	273
Specifying Supported File Types for AutoVue for Agile.....	273
Printing Banners and Watermarks	275
Banner and Watermark Properties	277
Specifying Banner Text and Location	278
Chapter 21 Notifications	279
Overview of Notifications	279
Preliminary Admin Settings for Notifications.....	279
Default Notifications.....	280
Attributes of Default Notifications	280
Event-based Notifications.....	281
Attributes of Event-based Notifications.....	282
Working with Events-based Notifications	283
Creating a Notification	283
Deleting a Notification.....	284
Invoking Notifications Programmatically.....	284
Working with Default and Event-based Notifications	285
Editing a Notification	285
Entering Subject and Body Text	285
Creating a Notification using SaveAs	286

Chapter 22 Full Text Search.....	287
Full Text Search Limitations	287
Full Text Search Properties	288
Indexing Attachment Files	289
Using FileLoad and Indexing New Files	289
Index Attachment Button	289
"Stop" Words	289
Chapter 23 My Assignments	291
Overview.....	291
Columns	291
Chapter 24 Unit of Measure (UOM).....	293
Creating Categories of Measure and Units of Measure	293
Chapter 25 Other System Settings.....	295
Company Profile	295
Currency Exchange Rates	295
Chapter 26 Dashboard Management	297
View Dashboard Tabs	297
Adding Dashboard Tabs.....	297
Deleting Dashboard Tabs.....	297
Adding Tables to Optional Tabs	298
Adding Data to Tables	298
Adding Charts to Optional Tabs	299
Adding Advanced Search to Optional Tabs	300
Configure Table for Advanced Search	300
Adding Custom (URL) Process Extensions for Optional Tables	301
Reordering Table Rows in a Tab.....	301
Displaying Optional Tabs	301
Chapter 27 Solution-specific Administration	303
Documentation	303
Configurable solutions for Administrator	303
Chapter 28 Event Management.....	305
Introduction to Event Management	305
Preliminary Configuration	305

Access to the Event Management nodes	305
Global Event control	306
Systemwide Preferences that pertain to Events.....	306
Event Management Node Folder.....	306
About Process Extensions and Notifications Nodes	307
Anatomy of Event Subscriptions	307
Event Subscription Components are Interconnected	310
Event Subscribers Tab on All Object Types	311
Handler Types	312
Process Extension-based Handler Types.....	312
Java Process Extensions	312
Script Process Extensions.....	313
Notification-based Handler Type	313
Notification Masks	313
Notes on Event Handler Types Node	313
Event Types.....	313
Default Event Types	314
Multiple Triggers from Single Action.....	316
User \$AGILEUSER	317
Working in Events Node	317
Attributes of Event Masks.....	318
Checklist for Creating an Event Mask	319
Creating an Event Mask	320
Working in Event Handlers Node	320
Attributes of Handler Masks	321
Roles in Handler Masks.....	321
Checklist for Creating a Handler Mask.....	322
Creating a Handler Mask.....	322
Working in Event Subscribers Node.....	323
Filtering in Dialogs during Create Subscriber	323
Attributes of Subscriber Masks.....	324
Trigger Type: Pre and Post	326
Execution Mode: Synchronous or Asynchronous.....	326
Checklist for Creating a Subscriber Mask	327
Creating a Subscriber Mask	327
Sample Event Subscriptions	328
Monitoring Events.....	329
Event Handler Monitor.....	329
Attributes of Event Handler Monitor	329
Event Log File.....	330
Object History Tab.....	331
Control of Event Components	331

Global Event Control	331
When an Event Type is Disabled	332
When a Handler Type is Disabled	332
When an Event Mask is Disabled	332
When a Handler Mask is Disabled	332
When a Subscriber Mask is Disabled	333
More about Selected Event Types	333
More about Selected Global Event Types	333
Extend Tools Menu	333
Scheduled Event	333
More about Selected Generic Object-based Event Types	333
Extend Actions Menu	333
Create Object	334
Delete Object	334
Get File	334
Update Relationship	335
Update Table	335
Update Title Block	336
More about Selected Specific Object-based Event Types	336
Change Status for Sourcing Object	336
More about Workflow-based Event Types	336
Approve for Workflow	337
Audit for Workflow	337
Change Approvers or Observers for Workflow	337
Change Status for Workflow	337
Comment for Workflow	338
Escalation for Workflow	338
Promotion Failure for Workflow	338
Reject for Workflow	338
Reminder for Workflow	339
Chapter 29 Scripting and Sample Event Subscriptions.....	341
Overview to Scripting in Agile PLM	341
Using Groovy Scripting Language	342
Choosing Script-based Handlers	342
Steps to Develop or Update Handler Masks	342
Editing Scripts in the Handler Mask	343
Logging of Scripts	343
Checklist for Specifying Script-based Event Subscriptions	344
Sample Event Subscriptions with Scripts	345
Update Item Description	345
Event mask: [Update Title Block Items]	345
Handler mask: [Update Item Description]	345
Subscriber mask: [Update Title Block Items Update Item Description]	346
Notify Create User when Item is Incorporated	346

Event mask: [Incorporate Item]	347
Handler mask: [Incorporated Item]	347
Subscriber mask: [Incorporate Item Incorporated Item]	347
Set Change Analyst.....	347
Event mask: [Change Analyst for Workflow]	348
Handler mask: [Set Change Analyst]	348
Subscriber mask: [Change Analyst for Workflow Set Change Analyst]	349
Add Document to New Part.....	349
Event mask: [Create Parts]	349
Handler mask: [Add Doc to New Part]	350
Subscriber mask:	351
Notify when Affected Items Table is Updated.....	351
Event mask: [Update Table ECO]	352
Notification mask: [Notify ECO AffItem Change]	352
Subscriber mask: [Update Table ECO Notify Item ECO AffItem Change].	352
Chapter 30 Locations and File Management.....	355
Configuring Web Client Notification.....	355
Configuring Java Client Notification	356
File Management in Agile PLM	356
Agile File Management Server	356
File Vault	357
Using FileLoad and Indexing New Files	357
Distributed File Management.....	357
Optimized Replication Systemwide Preference	357
Using the AutoVue for Agile Server in a Distributed Environment	357
How Distributed File Manager Works.....	357
File Management Security.....	358
Server Security	358
Client Access Security	358
Handle File Checksum	358
Configuring a File Manager	360
Creating a Custom File Vault.....	362
Modifying a File Manager Definition	363
Deleting a File Manager Definition or Removing a File Server	363
Setting the Preferred File Manager for a User.....	363
Purging Older Versions of Files.....	364
Use Case for Attachment Purging Task	364
Chapter 31 Database.....	365
Configuration of Database Settings.....	365
Database Properties.....	365
Chapter 32 LDAP	367
Configuring WebLogic Server for LDAP with Agile PLM.....	367
Configuring WebLogic with Oracle Internet Directory.....	368

Configuring WebLogic with Sun Java System Directory Server	369
Configuring WebLogic with Microsoft Active Directory Server	371
Creating Users in an LDAP Directory	372
Configuring Multiple LDAP User Repositories	373
Enhanced LDAP	373
Synchronizing LDAP and Agile PLM	374
LDAP-controlled User Properties	374
Agile LDAP Configuration	375
Directory Service Connection Parameters	375
Configuration Parameters Defined	375
Multiple Directory Server Support	377
Configuration Scripts	377
Synchronizing Users and User Groups	377
Chapter 33 Systemwide Preferences	379
Modifying Preferences	379
Default Systemwide Preferences	379
Details of Selected Preferences	385
Agile Drive	385
Allow Download of Productivity Components	385
Allow Password Reset	385
Copy Values along with Tabs	386
Content Service Wait Time	386
Content Service Maximum Retries	386
Reference Designators Allow Range Expand Collapse	386
Signoff User Dual Identification	387
Languages tab	387
Chapter 34 Licenses	389
General Info Tab	389
Modules Tab	390
Chapter 35 Task Monitor and Task Configuration	391
Task Monitor	391
Task Configuration	392
Chapter 36 Administering Attachments	395
Evaluating Your Company's Needs with Attachments or Designs	395
Administrator Settings Related to Attachments	395
File Management in Agile PLM	395
How SmartRules affect Attachments	396

Copy Files To Rev	396
Check In Attachment With Different File Extension	397
How Preferences affect Attachments	397
Filename Prefix.....	397
Optimized Replication.....	397
Save As Attachments	397
Allow Download of Productivity Components	399
File Productivity User Preference in the User Profile	399
Assign Roles and Privileges for Attachments	400
Attachment Privileges.....	400
Attachment Capability Privileges in a Role.....	401
Modify Privilege and Attachments	402
Markup Subclass	404
Markup Promotion	404
Redline Markup Default Roles and Privileges	405
Redline Markup Privilege Guidelines	406
Document Management Enhancements.....	406
View All Versions.....	406
Limit Attachment Size.....	407
Identify Checkin User	407
URLs can be up to 255 characters.....	407
Generating Attachment Quick Access URLs	407
Agile-Generated Attachment Quick Access URLs	408
User-Generated Attachment Quick Access Smart URL Formats.....	408
Item Attachment Quick Access Smart URL Formats	408
File Folders Quick Access Smart URL Formats.....	410
Program Content Quick Access Smart URL Formats	411
Accessing Attachment Files using Quick Access URLs	412
Chapter 37 Administering Designs	413
Evaluating Your Company's Needs with Designs	413
Purpose of Design Data Model	413
Benefits of Designing Structures using the Designs Class.....	414
Designs Class Overview	414
View All Versions.....	415
Designs Class Tabs.....	415
Title Block Tab.....	415
Files Tab.....	416
Structure Tab.....	417
Routing Slip Tab	417
Where Used Tab	417
Administrator Settings Related to Designs.....	418
Display Structure Tables SmartRule	418

Design-specific Role & Privilege.....	418
Chapter 38 Administering Agile Drive.....	419
Overview.....	419
File Management.....	419
Enabling Agile Drive	420
Appendix A Configuring Single Sign-On.....	421
Overview of Single Sign-On in PLM.....	421
Configuring and Deploying SSO with Windows NTLM	422
SSO NTLM Authentication	422
Configure SSO for Windows NTLM.....	422
Configure IIS Proxy	422
Configure PLM for NTLM.....	423
Deploy NTLM.....	424
With Secure Proxy	424
With Transparent Proxy or No Proxy.....	424

Preface

The Agile PLM documentation set includes Adobe® Acrobat PDF files. The [Oracle Technology Network \(OTN\) Web site](http://www.oracle.com/technology/documentation/agile.html) <http://www.oracle.com/technology/documentation/agile.html> contains the latest versions of the Agile PLM PDF files. You can view or download these manuals from the Web site, or you can ask your Agile administrator if there is an Agile PLM Documentation folder available on your network from which you can access the Agile PLM documentation (PDF) files.

Note To read the PDF files, you must use the free Adobe Acrobat Reader version 7.0 or later. This program can be downloaded from the [Adobe Web site](http://www.adobe.com) <http://www.adobe.com>.

The [Oracle Technology Network \(OTN\) Web site](http://www.oracle.com/technology/documentation/agile.html) <http://www.oracle.com/technology/documentation/agile.html> can be accessed through **Help > Manuals** in both Agile Web Client and Agile Java Client. If you need additional assistance or information, please contact My Oracle Support (<https://support.oracle.com>) for assistance.

Note Before calling Oracle Support about a problem with an Agile PLM manual, please have the full part number, which is located on the title page.

TTY Access to Oracle Support Services

Oracle provides dedicated Text Telephone (TTY) access to Oracle Support Services within the United States of America 24 hours a day, 7 days a week. For TTY support, call 800.446.2398. Outside the United States, call +1.407.458.2479.

Readme

Any last-minute information about Agile PLM can be found in the Readme file on the [Oracle Technology Network \(OTN\) Web site](http://www.oracle.com/technology/documentation/agile.html) <http://www.oracle.com/technology/documentation/agile.html>

Agile Training Aids

Go to the [Oracle University Web page](http://www.oracle.com/education/chooser/selectcountry_new.html) http://www.oracle.com/education/chooser/selectcountry_new.html for more information on Agile Training offerings.

Accessibility of Code Examples in Documentation

Screen readers may not always correctly read the code examples in this document. The conventions for writing code require that closing braces should appear on an otherwise empty line; however, some screen readers may not always read a line of text that consists solely of a bracket or brace.

This documentation may contain links to Web sites of other companies or organizations that Oracle does not own or control. Oracle neither evaluates nor makes any representations regarding the accessibility of these Web sites.

Introduction

This chapter includes the following:

- Welcome to Agile PLM Administrator 1
- What's New in Administrator 3

Welcome to Agile PLM Administrator

Welcome to Oracle's *Agile PLM Administrator Guide* for Agile Product Lifecycle Management (Agile PLM, or PLM).

How to Find Documentation for Agile PLM

The Agile PLM documentation set is found at this Web site:
<http://www.oracle.com/technology/documentation/agile.html>.

Documentation for the PLM Administrator

This manual is the primary handbook for Agile PLM administrators. It is a comprehensive reference for setting up users and business objects in PLM. The *Agile PLM Administrator Guide* documents most of the nodes in the Administrator user interfaces ("Admin" UI specifics are discussed in the next chapter).

However, the administrator must access other manuals in the Agile PLM documentation set for many situations, as listed below.

Agile Configuration Propagation (ACP) Guide

ACP is a separate utility that enables the administrator to propagate changed Administrator settings from a Test system to the Production system. The ACP utility has its own manual, *Agile Configuration Propagation Guide*, which covers installation and use by the Agile administrator.

Getting Started with Agile PLM

Getting Started with Agile PLM is more than a "primer" for the PLM end-user, as it contains in-depth information about features and functions that are common to all PLM solutions. The Agile administrator will find the *Getting Started* guide to be an indispensable reference of many features in PLM, including:

- Terminology and concepts used in the Agile PLM solutions;
- General features such as:
 - Searches,

- Workflows,
 - Reports,
 - Attachments and File Management;
- The user interfaces and operation of Java Client and Web Client:
- PLM administrators generally use Java Client to set up and manage the Agile system; therefore, before starting on the present manual ('*Admin Guide*'), please examine Chapter 2, "Navigating in Agile Java Client" in *Getting Started*;
 - Most PLM users work in Web Client; some administration tasks can be done in Web Client, for example, creating users; Chapter 3, "Navigating in Agile Web Client" in *Getting Started* is recommended.

PLM Solution-Specific User Guides

Most user guides for the PLM solutions contain a chapter (or appendix) for the administrator. These chapters deal with specific settings and configurations for each solution, and are mandatory reading for each solution purchased by your company.

For instance, every installation of PLM includes the solution called Product Collaboration. In the *Agile PLM Product Collaboration User Guide*, there is a chapter dedicated to the Agile administrator, not the end-user. The main solutions in PLM are listed in the next section.

The Agile administrator should also become familiar with the end-user documentation of PLM solutions. The manuals for end-users contain valuable information that assist the Agile administrator in grasping what the solution is all about and what the user experience incorporates.

Agile Product Lifecycle Management Solutions

The Agile Product Lifecycle Management (PLM) suite provides the following product solutions that are accessed through Java Client and/or Web Client:

- **Agile Product Collaboration (PC)** — Management and collaboration of product record information throughout the product lifecycle, across internal organizations and the extended supply chain.
- **Agile Product Portfolio Management (PPM)** — Integration of project and product information in the context of overall product development in order to streamline business processes across the product portfolio and lifecycle.
- **Agile Product Quality Management (PQM)** — Management of customer, supplier and product quality issues, tied to the product design via a closed loop corrective action process.
- **Agile Product Cost Management (PCM)** — Management of product costs across the product lifecycle and synchronization of product cost and cost processes with both internal and external participants.
- **Agile Product Governance & Compliance (PG&C)** — Management and tracking of all substances and materials contained by any item or manufacturer part, allowing companies to meet substance restrictions and reporting requirements, design recyclable products, minimize compliance costs, and eliminate noncompliance on future products.
- **Agile Engineering Collaboration (EC)** — Management of CAD design data from the engineer's desktop directly in a central PLM product record, automating both the design and product BOM change processes and supporting IP reuse.

- **Agile Enterprise Visualization** — Visualization, markup, and analysis of native documents (office, image, drawing, and CAD) through the Web across the extended enterprise, without the need for the original authoring tool or conversion to a neutral format.

Again, there are separate user guides for each product solution listed above, and all (except *PQM User Guide*) contain a chapter for the Agile administrator.

What's New in Administrator

Features and Enhancements added in Rel. 9.3

- The major feature enhancement in administrator is the Events framework for automated process extensions, script process extensions, and flexible notifications. The **Event Management** node folder has been added to **System Settings**, containing six new nodes. For more information, see [Event Management](#) on page 305 and [Notifications](#) on page 279.
- Web Client Administrator has many new features and has undergone a significant User Interface redesign. For more information, see [Administrator Functions in Web Client](#) on page 37.
- Please see [Viewers & Files](#) on page 269 for information regarding **Auto Generating Thumbnails** and thumbnail display options in Agile PLM.
- Several new roles have been added. For a list of available roles, see [Roles](#) on page 189.
- There are eight new preferences available including **Agile Drive** and **Thumbnail Support**. For more information, see [Preferences](#) on page 379.
- The Programs base class has been changed to Projects to be more consistent with industry standards.
- **API Name:** see [API Name](#) on page 19 in the Introduction chapter.
- Locations now has an **Online Help Manuals URL** field to access Online Help Manuals and User Productivity Kit (UPK) content. For more information, see [Locations](#) on page 355.

Important Portals is no longer supported in Agile PLM 9.3 and the Portals tab has been removed from Locations.

Installation Test Notice

Install and test this release on a designated development server before installing it on your production environment. Your development environment should mirror your production environment as closely as possible to provide accurate testing results. It is important to validate the installation of this release, and confirm your integrations are working correctly as part of your minimum due diligence. Any problems or questions noted during your development system testing should be resolved before installing this release on your production environment.

Getting Started in Administrator

This chapter includes the following:

▪ Overview	5
▪ Logging in to Agile Clients as an Administrator	5
▪ Creating New Administrator Users	6
▪ Dates and Times in Agile PLM	8
▪ Administrator User Interfaces	8
▪ Agile PLM Variables	14

Overview

This chapter collects information for the Agile administrator that is either basic or pertains to capabilities that are not found or specified by the node on the Administrator user interface.

The primary client for administering Agile PLM is Agile's Java Client.

To use Java Client, you must install it on your computer first. Java Client uses Java WebStart technology to download the software and keep it updated. For information about installing Java Client, see the *Agile PLM Installation Guide* for your application server.

Web Client is a Web-based application. You can use your browsers, as documented in the *Agile PLM Capacity Planning* guide, to run Web Client.

To see administrative features in Agile PLM clients, users must be assigned the Administrator privilege mask. The “admin” user account is pre-configured to see Administrator nodes and settings. You can use the admin account to create new users and assign the Administrator role to them. For more information, see [Creating New Administrator Users](#) on page 6.

Important Please examine the information in [Administrator Privilege and the AppliedTo Capability](#) on page 233. It provides information about the AppliedTo property that is a crucial part of all Administrator-related privilege masks. You do not need to grasp everything described on that page at this point, but it is crucial to know about the AppliedTo property.

Logging in to Agile Clients as an Administrator

For security reasons, you can change the password for the admin account to something only you would know. For more information, see [Changing a User's Password](#) on page 171.

To start Agile Java Client and log in as an administrator:

1. Double-click the Agile icon on your desktop, or choose **Start > Agile 9.3**, or launch Agile from the

URL provided by the system administrator. The Login dialog box appears.

2. Enter the username *admin* (or *administrator*) and the password *agile*. The username is not case-sensitive, but the password is case-sensitive.
3. Click **OK**. The login process is complete. The Java Client window opens, as shown in the following figure, usually with the **Search** tab displayed in the navigation pane.
4. Click the **Admin** tab in the navigation pane (on the left) to display the administrative nodes.

A user who has not been assigned the Administrator privilege mask (or role) will not see the **Admin** tab, only the **Search** and **Analytics and Reports** tabs will be visible.

Note The **Search** and **Analytics and Reports** tabs in Java Client are documented in the chapter “Navigating in Java Client” in *Getting Started with Agile PLM*.

To start Agile Web Client and log in as an administrator:


1. Start your browser.
2. Click the Agile Web Client bookmark, if one exists, or type the URL, for example,
<http://webserver.domainname.com/Agile/PLMServlet>

Note Make sure you enter the full domain name for your web server. The Web Client URL is case-sensitive.

The Login page appears.

3. Enter the username *admin* and the password *agile*. The username is not case-sensitive, but the password is.
4. Click the **Log In** button. If you make a mistake, click **Clear** and retype your username and password.

The login process is complete.

5. The first time you log in, the User Profile page appears. Enter the requested information. When you have finished, click **Save**.
6. After you complete this information, the Agile Web Client opens.
7. To open the administrative functions of Web Client, choose **Tools and Settings**  in the menu bar and select **Administration** and then select the appropriate administrative actions from the supplied menu options.

Creating New Administrator Users

Agile PLM uses Roles and Privileges to assign access to PLM solutions and other capabilities. The Agile administrator generally has access to the entire PLM system.

In addition, users can be given tailored privileges that enable them to administer a subset or portions of the Agile PLM system. These lesser PLM administrators are often referred to categorically as user administrators, but other names are perfectly useful, such as assistant administrator, roles administrator, or workflows administrator.

Note In this section, as well as in most of this manual, we are addressing users who have the Administrator or User Administrator Privilege Mask. These are powerful, system-impacting roles. They should not be confused with some other solution-specific roles in PLM that contain the word Administrator, for example, Discussion Administrator or Program Administrator. See the organization of roles in [Default Agile PLM Roles](#) on page 192.

Whether or not your company requires more than one Agile PLM administrator, it is recommended that you assign at least one user as backup PLM administrator in case the primary administrator is not available.


This section describes how to assign Administrator privileges to a new user using Java Client or Web Client. For more detailed information about how to create Agile PLM users and set user properties, see [Users](#) on page 167.

Important The **AppliedTo** property – found in the Administrator-related privilege masks, among others – is important to understand, as it controls what nodes an administrator user sees in the **Java Client > Admin** tree. The following Administrator-specific privilege masks make significant use of the **AppliedTo** property: Administrator (privilege mask); Admin Access for User Admin (privilege mask); and User Administrator (privilege mask). See [Administrator Privilege and the AppliedTo Capability](#) on page 233 and [Options for Building Administrator Assistants](#) on page 235.

To create a new Administrator user in Java Client:

1. Start Java Client and log in as “admin”.
2. Under **User Settings**, double-click **Users**. The Users window appears.
3. Click the **New** button. The Create User dialog box opens.
4. Type the **UserID**, **First Name**, **Last Name**, **Email**, and **Password**. Repeat the password in the **Retype Login Password** field.
5. Click **OK**. The setup window for the new user appears.
6. Click the **Role(s)** list, choose the Administrator role, and Click **OK**.
7. Fill out other user properties as needed, and then click **Save**.

To create a new Administrator user in Web Client:

1. In a browser, go to the Web Client URL and log in as `admin`.
2. Click **Tools and Settings > Address Book > Users**. The Users page appears.
3. Click **Add**.
4. Type the **Username** and **Login Password**. Repeat the password in the **Retype Login Password** field.
5. Then enter values for **First Name**, **Last Name**, and **Email**.
6. The General Information page appears.
7. Under the Profile heading open the **Role(s)** list, click the **Launch the Palette**  button to the right of the field.

8. Choose the Administrator role and click **OK**.
9. Fill out other user properties as needed, and then click **Save**.

Dates and Times in Agile PLM

...at the Server Level

The format of dates and times for object-related events (recorded by the Agile Application Server, or AAS) conforms to international standards.

The standard date format is Year [4 digits] / Month / Day, or **yyyy/MM/dd**.

The standard time format is Hour [converted to the 24-hour clock in GMT] : Minute : Second, or **hh:mm:ss**.

...at the Client Level

However, the format of dates and times in Agile PLM clients depends primarily on the user profile settings for **Preferred Time Format**, **Preferred Date Format**, and **Time Zone**. See [User Properties Defined](#) on page 172 for details. The settings that the user specifies do not affect how the dates are stored.

Example

Agile PLM records object-related events based on when they occur at the AAS. However, in **History** tabs of objects, you see the local client time that an event occurred—that is, the time matches that recorded by Agile PLM clients.

For example, Jerry creates an Agile object at 5:00 PM in San Jose, California. The server that the object is created on is in San Jose, so the server records the object's creation time as 5:00 PM. Jerry's Time Zone user preference is set to "New York (EST)". This means that on his machine, the **History** tab of this object will indicate that it was created at 8:00 PM, the time it was in New York.

Note The administrator sets Time Zone for all users, but users can change this setting. Users should set their time zone correctly, otherwise **History** in business objects will report misleading times.

Administrator User Interfaces

This manual documents most of the Administrator nodes in Java Client. However, as stated in Chapter 1, documentation of the solution-specific nodes – PC, PCM, PPM, ACS, and PG&C – has been moved to the respective user guides.

Filtering Data in Java Client

You can use a filter bar (sometimes called “table search”) to search for objects in the following nodes: **Lists**, **Criteria**, **Users**, **Roles**, **Privileges**, **Notifications**, **Event Management** and **Commodities**, as well as the **Admin History** window (available from the **Admin** tab toolbar).

To use the filter bar in Java Client:

1. In the filter bar's **Filter By** dropdown list, select a value.
The Filter By list depends on the type of object being filtered. For example, if you are searching for users, you can select First Name, Last Name, User ID, Business Phone, or Email.
2. Select an operator from the **Match If** dropdown list, such as Contains, Starts With, or Show All.
3. Type the value you want to search for in the text box.
4. Click **Apply**.

Administrator Nodes in Java Client

The following table lists Agile PLM Administrator nodes found in Java Client.

Administration functions that are available only in Web Client are detailed in [Administrator Functions in Web Client](#) on page 37 .

Your company may not have purchased all the business solutions contained in Agile PLM; in that case, some nodes are not visible.

Node	Description
<i>Data Settings</i>	
Classes	Define and manage business objects and their attributes, flex fields, and other properties
Character Sets	Configure lists of valid characters that are used to manage the text attributes
Lists	Manage lists that are used across multiple classes; also contains dynamic lists of objects such as users and items
Process Extensions	Extends the functionality of the Agile PLM system by defining custom actions to create user-driven and workflow-triggered custom actions, custom tools accessible through Agile PLM clients, custom autonumbering, and custom reports.
Autonumbers	Configure the number sources used in the automatic numbering of objects in Agile PLM
Criteria	Define criteria objects that are used in search conditions, privilege masks, and workflow settings

Node	Description
Workflow Settings	
Workflows	Configure, modify, and create workflows to track the progress of changes in your change control process
User Settings	
Account Policy	Set up systemwide rules for password age, length, and uniqueness
Users	Add new Agile PLM users to the system and modify properties for existing users, such as passwords, usernames, role and user group assignments, and more
User Groups	Define user groups and assign users to them
Supplier Groups	Select suppliers during the RFQ process; the administrator sets up global supplier groups that can be leveraged by users with appropriate roles
Roles	Define default and custom roles that control which actions groups and individual users can perform in Agile PLM
Privileges	Define privileges and privilege masks, which are assembled into user roles
User Monitor	View which users are presently logged in and terminate user sessions
Deleted Users	If needed, undelete a deleted user; the list of deleted users is maintained to provide a complete audit trail
Deleted User Groups	If needed, undelete a deleted user group; the list of deleted user groups is maintained to provide a complete audit trail
System Settings	
SmartRules	Manage the rules that make your change control process consistent
Viewers and Files	Define preferences for files attached to Agile PLM objects, and define viewer settings and banners and watermarks for redlines and attachments
Notifications	Customize templates for notification addressing and content
Full Text Search	Manage the indexing of attachment files
My Assignments	Configures what your users see when they click the My Assignments tab in Web Client's home page
UOM	Manage the units of measure
Company Profile	Stores useful information about the company
Currency Exchange Rates	Manage the Currency Exchange Rates table for in-system currency conversion
Dashboard Management	Enable or disable and rename the tabs of the Dashboard
Product Cost Management — PCM nodes are documented in <i>Product Cost Management User Guide</i>	

Node	Description
Ship-to Locations	Data that is factored in defining prices in RFQs
RFQ Terms and Conditions	Limit suppliers' access to an RFQ until they electronically agree to RFQ terms and conditions
Product Portfolio Management — PPM nodes are documented in <i>Product Portfolio Management User Guide</i>	
Status Nodes: Cost, Quality, Resource, Schedule	Reports whether a project's targets in the areas of cost, quality, resources, and schedule are currently being met, currently not being met, or are seriously off target
Default Role	Specifies which roles are assigned automatically to users when a task is delegated to them or when a Microsoft Project, along with its users and roles, is published to Agile PLM.
UI Configuration Data	Configures the pop-up windows on the Project Summary page and Content tab.
Agile Content Service — ACS nodes are documented in <i>Agile Content Service User Guide</i>	
Subscribers	Create profiles specifying all details of transfer orders
Destinations	Define where the output files of transfer orders will be sent
Events	Define when transfer orders are to be triggered
Filters	Define what content is included in a transfer order
Package Services	Configure the target Agile PLM system for Web services to facilitate Agile-to-Agile communication; these filters are also used for the Agile PLM Export process.
Response Services	An acknowledgment from the remote recipient of data
Product Governance and Compliance — PG&C nodes are documented in <i>Product Governance & Compliance User Guide</i>	
Signoff Message	Define message that the information supplier must agree to and sign off when submitting the declaration back to the buyer/customer
Compliance Rollup Scheduling	Define how often the system runs a scheduled rollup, and start time
Compliance Rollup Rule Setting	Control elements of suppliers' responses on declarations as they potentially impact the results of compliance rollups
Supplier Declaration Process Extensions	Set which process extensions are visible in each type of declaration request that your information suppliers receive. Note The process extensions themselves are not defined in this node folder.
Specification Mapping	Set up a mapping between specifications and PageTwo fields that display Result Compliance for the part-spec combination.
Event Management — Event Management nodes are documented in Event Management on page 305	
Events	Create and manage Event masks.

Node	Description
Event Handlers	Create and manage Handler masks based on "Java PX" and "Script PX" handler types. Notifications, the third handler type, are created and managed in Notifications node.
Event Subscribers	Create and manage Subscriber masks.
Event Types	Library of preconfigured event types, upon which event masks are based.
Event Handler Types	Library of event handler types: Java PX, Script PX, and Notification.
Event Handler Monitor	Review event handler transactions, including start and execution of event handlers.
<i>Server Settings</i>	
Locations	Define Agile Application Server, File Manager, and Portal locations
Database	Set systemwide preferences for the database
LDAP	Configure a Lightweight Directory Access Protocol system and dedicated LDAP server to create user accounts
Preferences	Set systemwide preferences for your Agile PLM system
Licenses	Server licenses pertain to products; user licenses pertain to individual users of Java and Web Clients
Task Monitor	Manage and track the progress of certain scheduled tasks
Task Configuration	Manage various scheduled activities such as reports and full text search indexing
<i>Example Nodes</i>	
Example Roles	Read-only copies of all default roles
Example Privileges	Read-only copies of all default privileges
Example Criteria	Read-only copies of all default criteria

Administrative Capabilities

The features in Agile Administrator help you configure and adapt Agile PLM to fit the way you already do business. Administrator nodes let you manage users and tailor aspects of Agile PLM to meet your company's requirements.

- Users, user groups, roles and privileges are all "reusable objects," enabling you to easily manage user accounts, such as in the following tasks:
 - Add and remove users, or set users as inactive
 - Assign users to user groups, which consolidates previous use of departments and groups

- Assign users to roles, and customize roles for individual users
- Enable users to grant temporary privilege access to specified objects for other users
- Create one or more user administrators to assist in managing user accounts
- Establish a systemwide account policy for password aging, length, rules, lockout, and uniqueness
- Configure systemwide business rules that govern how the Agile PLM system responds to certain user actions
- Configure and assign AutoNumber sources
- Create workflows to route changes, each with their own set of statuses and settings, and each status with its own set of approvers, observers, and required fields
- Create subclasses of existing Agile PLM classes to create new types of objects
- Create tabs with new fields—including numeric fields and money fields—for Agile PLM classes and subclasses
- Generate reports of Agile PLM users, objects, and administrative data.

Guidelines for Implementing Agile PLM

If you are setting up a new Agile PLM system, you may configure PLM by following the sequence of Administrator nodes in the previous tables. You won't necessarily set up *everything* in each node in this order, and it is useful to become familiar with all the nodes in Administrator before beginning to configure your company's business objects, users, and systemwide settings.

The tree of node folders and nodes is only a suggested starting point, not a comprehensive or certified sequence. Should you begin to configure Agile PLM for your company and find that the process is more extensive than first understood, please contact Oracle Consulting – Agile Practice or your Oracle Agile PLM sales representative.

Thorough testing before going live with Agile PLM is strongly recommended. It can take one to several weeks to configure Agile PLM to be production-ready depending on the following:

- how many Agile solutions to configure (there are several solution-specific nodes under **System Settings**, but configuring the solutions for users is a process that goes beyond the settings),
- how many Agile Users to be created, including their Roles and Privileges, and
- how complex your company's processes are (reflected in such nodes as **Classes**, **AutoNumbers**, **Workflows**, **Locations**).

You can enlist Oracle Consulting – Agile Practice to install and set up Agile PLM for your company.

Example Nodes in Java Client

Example nodes are read-only nodes that provide a backup of default Agile PLM roles, privilege masks, and reusable criteria. The examples cannot be enabled, but they can be used to restore default functionality to the system. For example, if you modified one of the default roles and find that it is not functioning properly, you can restore the original role by saving the example.

To save an example node as an active node:

1. Under **Examples**, double-click **Example Roles**, **Example Privileges**, or **Example Criteria**.
2. Use the filter bar to display the example you want to save.
3. Double-click an example to open it.
4. Click the **Save As** button. The Save As dialog box opens.
5. Type the new name, and click **OK**.

To export an example node:

1. Under **Examples**, double-click **Example Roles**, **Example Privileges**, or **Example Criteria**.
2. Use the filter bar to display the example you want to export.
3. Select an example and click the **Export** button.
4. Type the name of the file, and click **Save**.

Note You can import the exported file into another Agile PLM system. When you import the example, it becomes an active role, privilege mask, or reusable criteria. For more information about importing administrative data, see [Administrator Import](#) on page 29.

Administration in Web Client

If a user has been assigned the Administrator or User Administrator privileges, they can perform certain administrator actions in Web Client.

Click **Tools and Settings > Address Book** for user administration tasks under the **Users**, **User Groups**, and **Supplier Groups** tabs. The capabilities are documented as follows:

- **Users** – see [Users](#) on page 167
- **User Groups** – see [User Groups](#) on page 179
- **Supplier Groups** – see [Supplier Groups](#) on page 187

Click **Tools and Settings > Administration** and choose from the flyout list. The capabilities are documented as follows:

- **Dashboard Configuration** – see [Dashboard Management](#) on page 38
- **Visual Themes** – see [Visual Themes](#) on page 38
- **Report Templates** – see [Report Template](#) on page 42
- **Logging Configuration** – see [Logging Configuration](#) on page 44
- **Cache Health Monitor** – see [Cache Health Monitor](#) on page 45

Agile PLM Variables

This section lists Agile PLM variables you can use when you configure the system.

Default Value Variables

The following variables are used for setting default values for attribute properties.

Variable	Description
\$TODAY (must be uppercase)	The current date \$TODAY is not supported in Text type attributes. If you set \$TODAY as the default value for a Text type attribute, the time is displayed in GMT.
\$NOW (must be uppercase)	The current date and time \$NOW is not supported in Text type attributes. If you set \$NOW as the default value for a Text type attribute, the time is displayed in GMT.
\$LATESTREV (uppercase)	Defines whether or not the latest revision of an item has been released or not. The only values possible are \$LATESTREV = Is Introductory \$LATESTREV = Is Released. For more information, see Using \$CURRENTREV and \$LATESTREV on page 125.
\$CURRENTREV (uppercase)	The current revision of the object. For more information about \$CURRENTREV, see next topic and Using \$CURRENTREV and \$LATESTREV on page 125, and Controlling the Ability to Modify Items at Introductory Revision with \$CURRENTREV on page 247.

\$CURRENTREV Criteria Logic

Using \$CURRENTREV in an item criteria allows the administrator to build in privilege control based on the displayed revision. Using combinations of multiple \$CURRENTREV criteria conditions allows the administrator to narrowly define which items a user is allowed to modify.

A \$CURRENTREV criteria condition can be set to be **Equal To** or **Not Equal To** the following values:

- \$LATEST (the latest released revision of the item)
- Status type variables, for example, \$STATUSTYPE.RELEASED.
- Workflow statuses pertaining to specific workflows, for example, Default Change

Orders.Pending.

- Special values for evaluating Introductory revisions:
 - \$INTRODUCTORY_NOCHANGE
 - \$INTRODUCTORY_PENDINGCHANGE
 - \$INTRODUCTORY_RELEASEDCHANGE

For detailed information about \$CURRENTREV criteria values, see [Using \\$CURRENTREV and \\$LATESTREV](#) on page 125.

Privilege Mask Criteria Variables

You may select the following variables when establishing privilege mask criteria.

Variable	Description
\$AFFECTEDITEMTYPE	Inserts the type (subclass) of object that is listed in the Affected Items tab or field.
\$ATTRIBUTENAME	Inserts the name of the attribute that is selected in the Attribute Watermark field (see Banner and Watermark Properties on page 277).
\$APPROVER	Inserts the name(s) of the approver(s) of the workflow
\$CHECKOUTUSER	The user who checked out the object.
\$CREATEUSER	The user who created the object.
\$CURRENTREV	The current revision of an object you have selected from the rev list, or the revision of an object you are currently viewing. (See previous topic.)
\$DEFAULTSITE	Specifies if an item's manufacturing site contains the user's default site.
\$LATEST	<p>The latest revision of an object; more specifically, the latest released revision for a released item, or the latest pending revision for an unreleased item (with pending changes). \$LATEST is meaningful only in the Read and Modify privileges.</p> <p>\$LATEST goes on the right side of the equation. Valid use is:</p> <p>\$CURRENTREV (equal, not equal) \$LATEST.</p> <p>More information about \$LATEST is in Item Relationship Creation Using \$CURRENTREV and \$LATEST Criteria on page 128.</p>
\$LATESTFILEVERSION	The latest file folder version.
\$MAINORG	Supplier users can read and discover all users in the buyer organization as well as in their own organization (which, alone, is handled by \$USERORG variable). Supplier users are prevented from reading and discovering users from other supplier organizations.
\$NOTIFY	A default list of users selected to be receive a notification(s)
\$OBSERVER	Inserts the name(s) of the observer(s) of the workflow

Variable	Description
\$USER	Inserts the name(s) of PLM users. A criteria such as "\$USER Equal to \$APPROVER" can be used with certain privileges, for example, Modify.
\$USERGROUP	Inserts the name(s) of PLM user groups, based on a given user's User Group property being populated with a value, that is, a Group name. So, If a field is tied to the Admin list for User Groups, criteria can match a user to a user group; this criteria can be used with Read and Discover privileges to grant object access and control to a group or team.
\$USERORG	Used to create criteria based on the relationship between an attribute (organization or supplier) that specifies an organization, and the organization of the logged-in user.
\$USERSITE	Used to create criteria based on the relationship between an attribute (site) and sites assigned to the logged-in user.

Workflow Assignment and Status Type Variables

You may select the following variables when establishing workflow assignment:

Variable	Description
\$APPROVER	The approver(s) of the workflow.
\$OBSERVER	The observer(s) of the workflow.
\$ORIGINATOR	The originator of the routable object.

You may select the following "status type" variables under the **Criteria** column when setting up workflows:

Variable	Description
\$UNASSIGNED	Unassigned status type.
\$CURRENTSTATUS	The current status type.
\$STATUSTYPE.PENDING	Pending status type.
\$STATUSTYPE.SUBMIT	Submitted status type.
\$STATUSTYPE.REVIEW	Review status type.
\$STATUSTYPE.RELEASED	Released status type
\$STATUSTYPE.COMPLETE	Completed status type.
\$STATUSTYPE.CANCEL	Canceled status type.
\$STATUSTYPE.HOLD	Hold status type.

Routing Manager Variables

Routing manager variables facilitate management of routable objects. These variables represent the user selected from the Change Analyst, Compliance Manager, Component Engineer, Program Manager, Quality Administrator, Quality Analyst, and Price Administrator lists.

Variable	Description	Related routable objects
\$CHANGEANALYST	User selected from the Change Analyst list	Engineering change orders (ECOs), engineering change requests (ECRs), manufacturer change orders (MCOs), deviations, stop ships
\$COMPLIANCEMANAGER	User selected from the Compliance Manager list	All declarations
\$COMPONENTENGINEER	User selected from the Component Engineer list	Manufacturer change orders (MCOs)
\$PROGRAMMANAGER	User selected from the Program Manager list	Packages
\$QUALITYADMINISTRATOR	User selected from the Quality Administrator list	Product service requests: Problem Reports & NCRs
\$QUALITYANALYST	User selected from the Quality Analyst list	Quality change requests: CAPAs & Audits
\$PRICEADMINISTRATOR	User selected from the Price Administrator list	Price change orders (PCOs)

Administrator Functions in Java Client

This chapter includes the following:

▪ API Name	19
▪ Administrator Reports	20
▪ Utilities on Admin Toolbar	22
▪ History Tracking	24
▪ Administrator Import and Export	28
▪ Process Extensions Library	30
▪ Multiple Language Support	30

API Name

The **API Name** field is present on many Administrator objects and PLM business objects. When it is present, API Name is a required field. It is a unique systemwide identifier for objects and can be autogenerated. You can specify an API name, but internal consistency is enhanced by accepting the system-generated name. The API Name works as a system-identifying key because it tends not to change, while the Name attribute is much more likely to change.

See the *Accessing PLM Metadata with API Name Field* chapter in *SDK Developer Guide* for more information.

API Name field in Java Client

The following is a list of where you see the **API Name** field for objects in Agile PLM:

- **Classes** > Base Classes > Classes, Subclasses, Tabs, Tables, Attributes
- **Character Sets**
- **Lists** > List Values
- **Criteria**
- **Autonumbers**
- **Roles**
- **Privileges**
- **Workflows** > Workflow Statuses
- **Notifications**
- **UOM**
- **Dashboard Management**

- **Agile Content Service** > Subscribers, Destinations, Events, Filters, Package Services, Response Services
- **Event Management** > Events, Event Handlers, Event Subscribers, Event Types, Event Handler Types
- **Examples** > All nodes

Administrator Reports

You can generate Administrator reports to show the current settings for the Administrator nodes. These reports are available in the navigation pane's **Analytics and Reports** tab > **Standard Reports** folder > **Administrator Reports** subfolder. These reports are especially useful when you are planning to reconfigure an Agile PLM component.

The following table lists Agile PLM administrator reports.

Report	Description
Agile Classes report	Lists current and default attribute settings for all Agile PLM classes; this is a valuable tool for Agile systems engineers when performing upgrades to the Agile PLM system
Criteria Library Configuration report	Lists existing reusable criteria and where they are used
Events Configuration Report	<p>Lists existing event-specific objects as follows:</p> <p>Events: list of existing Event Masks; each row in this section begins with chosen Event Type, then Name of the event mask, followed by all other "event"-object attributes.</p> <p>Event Handlers: list of existing Handler Masks; each row in this section begins with chosen Handler Type, then Name of the handler mask, followed by all "handler"-object attributes.</p> <p>Note Handlers for Notifications are not listed.</p> <p>Event Subscribers: list of existing Subscriber Masks; each row in this section begins with Name of the subscriber mask, followed by all "subscriber"-object attributes.</p>
Login Failure report	Captures failed attempts for system login and workflow signoff, and the reason for each failure.
Preferences Configuration report	Lists the current attribute and property settings of the Preferences and Viewer and Files nodes.
Privilege Mask Detail report	Lists each privilege mask by name and description, whether or not it is enabled, roles where it is used; provides Object Type, Applied To, and Criteria values
Roles and Privilege Summary report	Lists each role by name, description, and whether or not the role is enabled; lists users assigned to each role; lists the name and description of privilege masks in each role

Report	Description
SmartRules Configuration report	Lists the current setting of each SmartRule
Subclass in Use report	Lists all subclasses and where they are used: global searches, reusable criteria, workflows, privileges, and roles
User Group Configuration report	Lists all user groups, users assigned, and pertinent user properties for each user; also includes a second table that indicates each group's escalation person and criteria for escalation
User Share Lists for Granted ACL report	Lists the objects and associated roles to which users have been granted access
User Subscriptions Lists report	Lists the class attributes and actions about which users have subscribed to receive notifications
User Usage report	For each active user, lists usage over a period of time, from the start date you select to the present; includes number of logins and total online login time in minutes
Users Configuration report	Lists all users and their properties, except passwords
Workflows Configuration report	Lists all existing workflows and the properties (status properties, criteria-specific properties) of each workflow's status list

You can save these reports for before-and-after comparisons when making changes to your database. For example, if you are going to be upgrading your Agile PLM system, you might want to first generate an updated Agile Classes report to keep a record of your current Classes configuration. Then compare it with one generated afterward.

To generate Administrator reports:


1. Select the **Analytics and Reports** tab and expand the **Administrator Reports** node folder.
2. Double-click the report you want. Agile Web Client opens to the specific report page, for instance, the Administrator Report: User Usage Report page.
3. Click **Execute**. The Specify Parameters dialog box opens. The User Usage report requires a From and To time range and the users you are requesting information about.
4. When you have populated the fields, click **Finish**. A message appears: "Server is generating the report. Please wait."
5. Select the encoding type—the default encoding type is Unicode (UTF-8). If you need to use a different encoding type, select it in the dropdown list. When you are ready, click **Continue**.
6. Follow the directions in the Save As dialog boxes to save the file to disk and choose a location to save it.
7. Modify the filename to include the report date and time. For example, **User_usage072604_3PM.csv**.
8. When the download is complete, click **Close** in the dialog box.

Utilities on Admin Toolbar


In Java Client when you click the **Admin** tab, there is a toolbar of buttons that either perform a single function or open to a utility or tool.

- **Disable System Access** – this button will close off user calls to the Agile Application Server (AAS). If you need to do this, use **Email To Users** button to let users know when and for how long they should not use the system. When you click **Disable System Access**, it changes appearance and becomes **Enable System Access**.
- **Synchronize Admin data across cluster** – this button performs a "synchronize" data routine across multiple AAS servers in a cluster; if your PLM setup uses one AAS server, this button is not enabled. An Oracle Consulting – Agile Solutions representative can provide you with more in-depth information about deploying and maintaining clustered servers.
- **Email To Users** – see [Sending Email to Users](#) on page 22
- **Global Replace** – see [Global Replace](#) on page 22
- **Admin History** – see [Administrator History](#) on page 25
- **Disable Triggering Events** – see [Enable/Disable All Event Triggers](#) on page 331

Sending Email to Users


Use the **Email To Users** button  to email a message to all active (enabled) users, all logged-in users, or to specific users that you select.

When you click the **Email To Users** button, the Email to Users window appears. You can send email to the following groups of recipients:

- **All active users** – Email all enabled users a message that they will receive the next time they log in to Agile PLM. For example, you may want to inform all enabled users that a new class or subclass or workflow is now available for their use.
- **All logged-in users** – Email all logged-in users a message that you want them to receive immediately. For example, you may want to inform all logged-in users that the Agile PLM system will be down in 10 minutes.
- **Other users** – Email a message to selected users. After you select the radio button, open the address book by clicking , from which you choose the users for your message.

Enter the message in the **Content** field, then click **Send**.

Global Replace

The **Global Replace** button  lets you replace one user with another in workflows, escalations, and transfer authority assignments. You can use this capability in a variety of situations, for instance, when an employee leaves the company or moves to another assignment. Global Replace can accomplish the following:

- Replace a user as an approver, observer, or routing manager in a single workflow or all existing workflows; however, this does not replace the user in the actual changes he is currently


working on, which must be done manually.


- Change the designated escalation person for single or multiple users and user groups.
- Change the transfer authority person for single or multiple users and user groups. You can replace To users but not From users.

The “users” in the **From** and **Replace With** drop-down lists include all existing user groups. See Users and User Groups.

Global Replace Properties

To define or change the settings in the Global Replace window:

1. Click **Global Replace**  in the Admin tab toolbar. The Global Replace window appears.



You can specify the following values in the Global Replace window:

Property	Description
Replace user or user group	The “Replace” person is the user or user group you are replacing. Select a user or user group from the drop-down list.
With user or user group	The “With” person is the user or user group who will replace the “From” person. Select a user or user group from the drop-down list.
Workflows	Select a specific workflow from the drop-down list. You can use Ctrl-shift or Shift-click to select all the workflows if you want to change every instance of the “Replace” person to the same “With” person in all workflows. With the checkbox selected, the “Replace” person is replaced with the “With” person in approver, observer, and change analyst (routing manager) capacities in the designated workflow.

Property	Description
Designated Escalation Person	Replaces the “Replace” person with the “With” person as the designated escalation person. (See Designated Escalation Person.)
Transfer Authority	Replaces the “Replace” person with the “With” person as the person who has the authority to approve or reject the “Replace” person’s changes. (See Transfer Authority for Self on page 224.)

If you have selected more than one workflow in the **Workflows** field, when you click **Save** you see this confirmation message: “Are you sure you want to replace <Replace person> with <With person> for all Workflows?”

If the “Replace” person is a routing manager, and the “With” person is not, a warning appears. If you answer the prompt with **Yes** (to continue), when the “Replace” person is used in any default routing manager property (for example, Default Change Analyst), this function will be filled by a non-routing manager. If that is an unwanted result, you should instead answer the prompt with **No** and select a more appropriate “With” person.

For more information about routing managers, see [Routing Managers](#) on page 130.

History Tracking

The Agile PLM system tracks several kinds of “history,” some available only to the administrator and some available to all users. These topics are considered in the following sections:

- **Object History and Administrative Object History** – the object history shows only the history of that object, which includes all actions performed by users and administrator users; those actions that involved an administrator also are listed in the Administrator History window.
- **Administrator History** – records administrative actions on all objects in Agile PLM. Administrator History also records history of deleted objects and settings.
- **History of Deleted Objects** – when an object is deleted, its history is preserved. This type of history is also accessed in Administrator History.
- **Previous Administrator Histories** – displays object history that took place in previous releases of Agile PLM. This kind of history is in Previous Administrator Histories. This will only have content for customers upgrading from Agile 8.5 or Agile Advantage.

Object History and Administrative Object History

Every object in Agile PLM has a **History** tab, on which all individual actions performed are recorded, for example, Create, Modify, and Delete. Different data is recorded on the **History** tab depending on the object type. The history of actions performed by an Agile PLM administrator appears also in Administrator History (see [Administrator History](#) on page 25).

All objects have a record of the information listed in the following table on their **History** tabs. Many kinds of Agile objects have additional fields on their **History** tab.

Property	Description
Action	The action that was performed, for example, create, modify, delete.
User	The user who performed the action.
Local Client Time	The date and time the action was performed.
Details	Details of the object, property, or action after the modification.

When a modification is made to an administrative object on a node that records the assignment or reference of one object to another object, history is logged on the object that “owns” the reference or assignment. See the table below. For example, if you assign a role (object) to a user (object), the user object owns the referenced role object, and the **History** tab of the user object is updated.

Owner (history logged on this object)		Reference or assignment object
Role	owns	Privilege
Privilege	owns	Criteria
Subclass	owns	AutoNumber
Workflow criteria nodes (matching criteria, exit criteria)	own	Criteria
User	owns	Role

Administrator History

When a modification is made to an administrative object, the action is recorded and displayed in the Administrator History window. Administrator History also records history of deleted objects and settings.

Note Administrator History does not include User history or User Group history.

The following table describes the fields in the Administrator History window. These fields are similar to the history table fields for Agile PLM administrative objects.



Field	Description
Action	The action that was performed, for example, create, modify, delete.
Object	The name of the object on which the action was performed, for example, the name of a workflow, privilege mask, or criteria.
Username	The user who performed the action. The username is an active link; click it to open the user's tabbed page.
Local Client Time	The date and time the action was performed.
Details	Details of the object, property, or action after the modification.

Purging Administrator History

The Administrator History can be cleared or purged.

Caution The familiar “Delete” button implies different behavior in this context. You cannot delete selected lines from the Administrator History window; this works as a true “purge” capability. Purge also removes the records in the Previous Administrator History window.

To purge Administrator History:

1. On the **Admin** tab toolbar, click the **Admin History** button .
2. On the Administrator History window toolbar, click the **Purge** button .
3. You are prompted with three options to answer the question, **Would you like to export the existing history?**
 - a. **If Yes, purge all history records with an export file:** If you click **Yes**, all records in Administrator History are purged, and an export file is created with all the data. This is a recommended course if your company was ever audited and these archives are required.
 - b. **If No, purge all history records without an export file:** If you click **No**, all records in Administrator History are purged, and an export file is not created.
 - c. **If Cancel, cancel purge action:** If you click **Cancel**, the operation is not executed.
4. If you click **Yes** or **No**, all records in Administrator History are instantly purged. They cannot be retrieved.

History of Deleted Objects

When an object or setting is deleted, the history of the object or setting is maintained in Administrator History. However, the data is no longer maintained on the object or setting **History** tab.

For example, if you delete an object, such as a workflow, its history entries, including the delete action, are maintained in Administrator History. However, there is no longer a **History** tab for the workflow object (the object does not exist anymore), so there is no individual object history for that workflow.

If you remove one object from another—for instance, removing a privilege from a role—the removal of the privilege is recorded in **Admin History** with reference to the role.

Deleting Objects in Agile

Java Client and Web Client support “soft” and “hard” deletes. When you soft-delete an object in the database, it is not permanently deleted. A soft-deleted object is marked “Deleted” in the database, and its object number or name is reserved. You cannot create another object with the same type and number or name as a soft-deleted object.

Note You *can* undelete a soft-deleted object, if you have the appropriate privileges set by the Agile administrator.

When you run a search, soft-deleted objects do not appear in the search results table. To locate soft-deleted objects, you must run the predefined deleted object searches in the **Recycle Bin Searches** folder.

Note You have access to the **Recycle Bin Searches** folder if **Recycle Bin Searches** is included in the **Searches** field of your user profile. If you have the appropriate privileges, you can edit your user profile and add **Recycle Bin Searches** to the list of searches in the **Searches** field.

A hard-deleted object is permanently removed from the database.

<p>Caution You <i>cannot</i> undelete a hard-deleted object.</p>


To soft-delete, hard-delete or undelete an Agile object:

- You must have the appropriate Delete or Undelete privileges for that object.
 - The object must meet the conditions that allow it to be deleted or undeleted.
- In general, if deleting or undeleting an object would cause the compromise of data integrity, the delete or undelete action is disabled.

You cannot delete an object unless all of its relationships and subscriptions are removed.


For detailed information about deleting specific *object* types see the *Deleting Agile Objects* section of *Getting Started with Agile PLM*.

To soft-delete an object in Java Client:


1. Select and open the object you want to delete.
2. Click the **Delete** button , and respond **Yes** to the confirmation prompt.

The object is soft-deleted.

To undelete an object in Java Client:

1. Run the appropriate Deleted <objects> search from the **Recycle Bin Searches** folder.
2. Open the deleted object you want to restore.
3. Click the **Undelete** button .

To hard-delete a soft-deleted object (if you have the appropriate privileges) in Java Client:

1. Run the appropriate Deleted <objects> search from the **Recycle Bin Searches** folder.
2. Open the object.
3. Click the **Delete Object** button , and respond **Yes** to the confirmation prompt.

Administrator Import and Export

In several nodes of Administrator, exporting and importing functions are available.

- **Data Settings**
 - **Criteria**
- **Workflow Settings**
 - **Workflows**
- **User Settings**
 - **Roles**
 - **Privileges**

You can export Agile PLM-object definition data to a file. You can import an Agile PLM-object definition data file to create a new object. Example objects (such as example roles) cannot be imported or exported.

Note On the **Tools** menu of Agile PLM clients, **Import** and **Export** utilities can be used to import and export product data, not Agile PLM system metadata. The Import and Export utilities are documented in the *Agile PLM Import and Export Guide*.

Important When you import Administrator data from a test system to a production system, verify the imported data as completely as is possible immediately.

Encoding Types

When you import or export workflow data, you must select the encoding type. The following table lists available encoding types.

Value	Note
Western European (ISO)	ISO-8859-1
Japanese (Shift JIS)	SJIS
Traditional Chinese (Big 5)	BIG5
Japanese (EUC)	EUC-JP
Simplified Chinese (GB2312)	GB2312
Unicode (UTF-8)	UTF8

Administrator Export

The Administrator Export function exports the necessary data to create the object. Not all properties are exported. For example, exporting a privilege mask does not export the Where Used information. You can examine the exported text file to determine which properties are exported for each type of object.

To export Administrator data:

1. Open the node you want to work with: **Workflows**, **Criteria**, **Roles**, or **Privileges**.
2. Select the objects you want to export. You can export one object, or all objects in the table; the Workflows, Criteria, and Privileges windows have an **Export All** button.

Note In windows with a filter bar (see [Filtering Data](#) on page 8), to display all the objects in the node, Select Show All in the **Match If** dropdown list, and click **Apply**.

3. Click the **Export** button  in the window toolbar.

For *workflow exports only*, the Encoding Type dialog box opens. See the table above. The encoding type generally used is Western European (ISO). If you need to use a different encoding type, select it in the dropdown list, and click **OK**.

Note You must specify the same encoding type when you import the file later.

4. Follow normal Save As procedures to give the file a name and select a location to save it to disk. Modify the filename to make it easy to identify. You might include the object exported, the date, and the encoding type. For example, **ChangeOrderWorkflow072602_ISO.txt**.
5. When you are ready, click **Save**. Verify the data in the file you exported.

Administrator Import


You can import an exported text file to create an object in the Agile PLM system.

You cannot create two objects with the same name. For example, you cannot import an object data file for a workflow named ABC if there is already a workflow named ABC in your Agile PLM system. You have the option of overriding the existing named object; in that case, the imported object replaces the existing object in the Agile PLM system.

Note that some properties—for example, user assignments—are not exported. When you import the object data text file, you will create a new object without those properties (for example, with no user assignments).

Note Before you import it, open the text file you want to import to verify which object properties were exported.


To import Administrator data:

1. Open the node you want to work with: **Workflows**, **Criteria**, **Roles**, or **Privileges**.
2. Click the **Import** button  in the window toolbar. The Import File dialog opens.


For workflow imports only, the Import File dialog includes an Encoding Type field. Make sure

the encoding type matches the exported file of workflow(s).

Caution You must select the same encoding type you used when you exported the object. Import results are not reliable if you do not use the same encoding type.

3. Next to the Files to be Imported field, click the **Browse** button  to locate and select the file you want to import. Click **Open**.
4. Click **OK**. The import operation takes place. Verify the data in the imported file.

Process Extensions Library

In Java Client, use **Tools > Process Extensions** or the **Process Extensions** button  or **Admin tab > Data Settings > Process Extensions** to access the library of Custom Process Extensions (that is, those PXs that preceded Events-based PXs).

If there are no Custom PXs deployed on your Agile PLM system, that item is unavailable on the **Tools** menu, and “Empty” appears below the button when you click it.

For details about configuring custom process extensions, see [Process Extensions](#) on page 105. For technical information on how to develop custom process extensions for your Agile PLM system, see the *Agile PLM SDK Developer Guide*.

Note With the introduction of Event Management, it is possible to have more flexibility with PXs, through Java PX handlers and Script PX handlers. The previously existing Process Extensions capabilities remain intact, but Events Management allows PXs to be triggered through normal user and system actions. See [Event Management](#) on page 305. For technical information on developing the new PX handlers, see the *Agile PLM SDK Developer Guide*.

Multiple Language Support

Agile PLM is an internationalized application that permits companies to enter non-English label data, and for users to see their client user interface in their preferred language. English is included with all licenses. Agile PLM is certified for French, German, Japanese, Korean, Russian, Simplified Chinese, and Traditional Chinese.


Important This list of supported languages is current as of May, 2010 and is subject to change. Please see the **Languages** tab found in the **Preferences** node for your current installation supported languages.

Note For the Product Governance & Compliance solution, there is a fully supported Japanese version of the Rollup in Excel template. Localized versions of the Rollup in Excel template are supported in Chinese, French, and German. Additionally, there is a fully supported Japanese version of the JGPSSI template for creating JGPSSI Declarations.

Every user has a language preference (<user object> > **Preferences** > **Format Preferences** (heading only) > **Language**) that you will likely set during configuration of your company's business objects (which includes, of course, Agile users).

If the company has purchased a localized language as part of PLM, that language will appear in the dropdown list for the Language property.

To set the Language preference for a user:

1. Open the user profile. (This will likely be set when you create your company's Agile users. This task instructs for an already-created user object.)
2. Click the **Preferences** tab.
3. Under **Format Preferences**, click  for the **Language** field.
The dropdown list shows English and any other languages your company has licensed.
4. Select a language, and click **Save**. That user will see supported elements of Agile in that language.

If you change any user's Language preference, that user (if logged in) must log out and log back in to see changes in their user interface.

Users can switch their own Language preference (again, non-English languages that the company has a license for). In Java Client, the user clicks **Current User...** from the **Settings** dropdown menu of the main toolbar and follows the previous instructions.

In Web Client, the user's path to the Language setting is **My Settings** > **User Profile** > **Preferences** > **Edit** > **Language** (under **Format Preferences**).

For more information about Agile PLM Language settings, see the [Systemwide Preferences](#) on page 387 chapter.

Administrator Data that is Supported for Multi-Language Capability

We use the term "multi-language capability" to refer both to those "Administrator-editable" objects that can hold different licensed languages inputs separately, and those non-editable objects that can be displayed in different languages according to any end-user's Language preference setting.

The following list includes those Administrator nodes whose objects are supported by the multi-language capability. If the node is listed as supported, it does not matter whether the object is created by the administrator or by a user. (As always, the ability for users to create an object in Agile is defined by their roles and privileges.) Names and Descriptions of these objects are supported for multi-languages unless otherwise noted.

Supported Administrator Nodes

Administrator-editable items can hold names in any enabled language. The administrator can configure these items into a different language for users by setting the Language user preference. For instance, Company A has a localized version of Agile PLM with Japanese enabled (and, by default, English). The administrator creates a list; he can name the list differently for English users and Japanese users. Users with language preference set to Japanese will see the list named in Japanese as the administrator configured.

Multi-language support is provided for the following kinds of objects:

Data Settings

- Classes
- Character Sets
- Lists
- Process Extensions
- Autonumbers
- Criteria

Workflow Settings

- Workflows

User Settings

- Roles
- Privileges

System Settings

- Notifications (Name, Description, Subject, Body)
- Full Text Search is supported for attachment files in Japanese, Traditional Chinese, Simplified Chinese, German, and French localized versions
- Dashboard Management
- Product Portfolio Management:
 - Schedule Status
 - Cost Status
 - Quality Status
 - Resource Status
 - Default Role
- Agile Content Service:
 - Subscribers
 - Destinations
 - Events
 - Filters
 - Package services
 - Response services
- Product Governance & Compliance:
 - Signoff Message

- Compliance Rollup Scheduling
 - Compliance Rollup Rule Setting
 - Supplier Declaration Process Extension
 - Specification Mapping
- Event Management

Supported Predefined System Objects

Objects that are predefined in Agile—that is, are not editable in Administrator, for example, an Example Role—are fully supported by multi-language capability. For instance, a user whose Language preference is English who logs in will see the “Example–Administrator” role in English; when the same user logs in with the Language preference set to Japanese, he will see a translation of “Example–Administrator” as configured by the Japanese user administrator.

Administrator Data that is Not Supported for Multi-Language Capability

While most types of Administrator data are supported for multi-language capability, the following types of Admin data are not supported for multi-languages, but only in localized user interfaces.

User Settings

- Users
- User Groups
- Supplier Groups

System Settings

- Viewers & Files
- Company Profiles
- PCM Ship-To Location

Any values/strings input by user

Attribute names with "01", "02", "03", etc appended

- As an example, let's say Company B has a localized version of Agile PLM with Simplified Chinese enabled (as well as English). The administrator, who has a language preference of English, creates a user group and names it UserGroup_1. Then, another Agile administrator for Company B, whose language preference is set to Simplified Chinese, changes the name of UserGroup_1 into a Chinese name with Chinese characters. Now the name of the user group appears to *everyone* as the Chinese name in Chinese characters, even those users whose language preference is English.

Note Full Text Search is supported for attachment files in Japanese, Traditional Chinese, Simplified Chinese, German, and French localized versions.

Configuring a System for Multi-Languages

When you set up fields in any language, you have to be logged in with your own Language preference set to that language. If you make changes in Japanese with your Language preference set to Japanese, and then you want to make changes in English, you must change your Language preference to English, log out, log back in, and proceed. Or you can log out and log back in as a different administrator user whose Language preference is English.

To give an example of how the Language setting for individuals is handled by the multi-language capability in Agile, let Jim and Jan be two users:

- **Case 1:** Company C has an English version of Agile only. Everyone in Company C sees Agile user interface and business objects in English; no user can change their Language user preference to another language.
- **Case 2:** Company D has a localized version of Agile with Japanese enabled (and, by default, an English license). You have configured the company so all users' Language preference is Japanese. Jim sets his Language user preference to English. After logging back in, Jim now sees his user interface and the objects he creates in English. Jan is a typical user whose Language preference has remained Japanese: the objects that Jim created appear to Jan in Japanese.

- **Case 3:** Company E has a localized version of Agile, with Simplified Chinese enabled. The administrator has configured the users at the Hong Kong office so their Language user preference is Chinese. Other people in Company E working outside Hong Kong still keep English as their language preference. Now the administrator creates a subclass of the Parts class, and names it "Modules". Objects from this subclass appear to everyone in Company E with the name Modules, no matter which Language is set in the user preference.

Later on, the administrator decides that the Modules subclass should be renamed in Chinese for the Hong Kong users. He sets his own Language preference to Simplified Chinese, and renames the Modules subclass as a translated name in Chinese characters. Now the Modules subclass name appears in Chinese characters to all Hong Kong users with Language user preference set to Chinese. But the English users still see the subclass name Modules in English.

- **Case 4:** Company F has a localized version of Agile, with Simplified Chinese enabled. The administrator has configured the users at the Hong Kong office so their Language user preference is Chinese. Everyone there adds information (for instance, in creating objects) in Chinese. When a user in Hong Kong creates a business object, it appears in Chinese to everyone in Company F, no matter which Language they have set in the user preference.

If you create a new subclass, its name can enter the system in localized (translated) form; however, if you rename the newly created subclass, or any subclass, it is renamed in the same language you are logged in with (Language user preference).

For Java Client to show non-English characters (in the user interface and user-entered text), it must be running on an operating system that supports a particular language. If it is not, some anomalies can appear, for example, "blank squares" instead of proper non-English characters. This is often the case for double-byte character sets such as Japanese and Chinese.

For instance, Jan is using a machine with a Japanese OS. She enters Japanese text into an ECO's **Description** field. Then Jim launches Java Client on an English OS machine; when he views this ECO, Japanese text that was entered into the **Description** field may appear corrupted (having "blank

squares”): the English OS may not support Japanese characters (Windows English version requires installing the Asian Language Pack to support Japanese characters).

Administrator Functions in Web Client

This chapter includes the following:

▪ Overview to Administrator in Web Client	37
▪ Configuring the Dashboard	38
▪ Visual Themes	38
▪ Report Templates	42
▪ Logging Configuration	44
▪ Cache Health Monitor	45
▪ Deleting Objects in Agile	49

Overview to Administrator in Web Client

Agile Web Client contains certain Administrator capabilities, accessible only to users who have been assigned the Administrator or User Administrator role, or more specifically the Administrator or User Administrator privilege.

The "user" and "group" administrator capabilities are accessed via Web Client's **Tools and Settings > Address Book**. Other administrative capabilities are found in Web Client's **Tools and Settings > Administration** flyout menu.

This chapter documents utilities for the Agile administrator that are unique to Web Client. The table offers brief definitions of all Web Client Admin nodes, as well as cross-references to the applicable documentation.

Node	Description
<i>Users and Groups</i>	
– accessed in Web Client via Tools and Settings > Address Book	
Users	Add new Agile PLM users to the system and modify properties for existing users, such as passwords, usernames, role and user group assignments, and more
User Groups	Define user groups and assign users to them
Supplier Groups	Select suppliers during the RFQ process; the administrator sets up global supplier groups that can be leveraged by users with appropriate roles
Web Client Administration	
– accessed in Web Client via Tools and Settings > Administration	
Dashboard Configuration	Configure the PLM Dashboard – see Configuring the Dashboard on page 38.

Node	Description
Visual Themes	Configure the display of the Web Client user interface for all users, including the definition of colors, font style and size – see Visual Themes on page 38
Report Templates	Create and manage report templates – see Report Template on page 42
Logging Configuration	View and configure the loggers within Application – see Logging Configuration on page 44
Cache Health Monitor	Ensure that all changes to Administrator data is properly replicated across the cluster – see Cache Health Monitor on page 45

Configuring the Dashboard

Each Dashboard tab contains a set of configurable widgets that display information in tables and charts. You can configure which of these widgets should display in each tab and where they should appear.

To configure each Dashboard tab:

1. In Agile Web Client **Tools and Settings > Administration** menu, choose **Dashboard Configuration**.
2. In the **Configure Tab** field, select the tab you wish to configure. The widgets available for the selected tab are displayed in the **Available Content** column.
3. Move the widgets you want displayed to the **Row** columns.
4. Use the direction arrows to reorder the widgets as desired.
5. When you finish configuring all the tabs, click **Save**.
6. To exit the configuration window, click **Close**.
7. Refresh the Dashboard to see your changes.

Visual Themes

Visual Themes lets the administrator define a visual look, or style, that the PLM users will see across the enterprise. This allows the configuration of Web Client to be consistent with other deployed applications or with corporate colors.

Selecting Theme Options

Styles are defined and modified by choosing **Tools and Settings > Administration > Visual Themes**. The Select Theme Options page appears, with three fields.

Branding Logo

There are some default Oracle branding logos in the dropdown list. To use your company's branding logo, a graphic file will have to be added to the web.xml file. For instructions on this procedure, see [Replacing the Oracle Logo](#) on page 39. Once another logo is added, it appears in

this dropdown list.

Icon Motif

These are Agile's "Mechanical", "Electrical", and "High Tech" symbols that appear on this page.

Color Palette

On the Select Theme Options page, the **Color Palette** list box lists all available style schemes. Those with an asterisk (*) are the out-of-box System Styles, which cannot be modified or deleted.

You can select a visual style theme from the dropdown list and begin modifying it with one of the following actions:

- New themes can be developed using **Save As**. Clicking the **Save As** button brings up the Specify Palette Colors page.

At first, you must enter a new name in the Name field. If you alter the elements of a System Style without assigning a new name, the system does not save your new scheme; as soon as you enter a distinguishing name (regardless of whether you have altered any of the fields), the system can save it.

This is the way you can "create" a new style scheme from the default System Styles (and the only way to create a new scheme at first, while there are no non-default color-palette Styles).

For more details, see [Modifying Styles](#) on page 40.

- Click the **Delete** button to delete a selected style scheme.

Note that this button is disabled when a System Style is in the field. You cannot delete a System Style (denoted by the "*" in the name).

- Click the **Edit** button to modify a selected style scheme.

Clicking the **Edit** button brings up the Specify Palette Colors page.

For more details, see [Modifying Styles](#) on page 40.

Note The button is disabled when a System Style is in the field. As noted, you cannot modify the System Styles, except by working through the SaveAs feature.

Replacing the Oracle Logo

If you want your company's logo (or any other co-branding image) to appear in place of Oracle's logo, or to alter its height or width, the easiest way is to alter the file **web.xml**.

To replace the default company logo with a custom logo:

1. Log in to server side.
2. Find **web.xml** in the Oracle home directory.
3. The bullet-items below give some samples of changing specific parameters:
 - These lines of code in web.xml allow you to enter the filename of your custom logo file:

```
<context-param>  
  <param-name>cobranding.image</param-name>
```

```
<param-value>logo.gif</param-value>
</context-param>
```

Change the filename (including extension) where “logo.gif” appears.

- These lines of code in web.xml allow you to change the height of the logo:

```
<context-param>
  <param-name>cobranding.image.height</param-name>
  <param-value>25</param-value>
</context-param>
```

Change the parameter value "25" to another value.

- These lines of code in web.xml allow you to change the width of the logo:

```
<context-param>
  <param-name>cobranding.image.width</param-name>
  <param-value>114</param-value>
</context-param>
```

Change the parameter value "114" to another value.

- These lines of code allow you to change the title of the Oracle Agile window or page:

```
<context-param>
  <param-name>application.window.title</param-name>
  <param-value>Product Lifecycle Solution</param-value>
</context-param>
```

Change the parameter value "Product Lifecycle Solution" to another value.

- The next few lines of code in web.xml allow you to update the tooltip by changing the text:

```
<context-param>
  <param-name>cobranding.image.altext</param-name>
  <param-value>Oracle|Agile</param-value>
</context-param>
```

Insert the new text where "Oracle|Agile" appears in the example.

4. Restart the application server.
5. Log into Web Client to verify or evaluate your change(s).

Modifying Style Schemes

Once you have modified a style theme, you can use these buttons for further actions:

- Click **Preview** to preview the modified style scheme. This displays the Web Client interface in the selected scheme on your machine only. (All other users still see the user interface in the currently applied scheme.)

Note The Preview button displays only when the user creates a new theme.

- If you want to save the current scheme, click **Save**. This does nothing more than simply save the settings under the name in the Name field, as well as add that scheme to the list in the Color Palette field. (Clicking **Save** does not propagate the scheme to your Web Client users.)

Whether or not you have saved it, if you wish to make further modifications to the scheme you are modifying, you may do so. You can save over the scheme you saved, or enter a new name and thereby save a new scheme.

- To cancel the preview of the selected scheme, click **Cancel**. You are returned to the Select Theme Options page.
- With a named color-palette scheme selected, when you click the **Apply** button, the selected scheme becomes current throughout your system. This changed scheme is seen by active users as soon as their screen is refreshed, or when a user next logs in to Web Client.
- If you don't want to keep the new style in the Style Theme list, you can simply **Delete** it.

The following table lists the fields on the Specify Palette Colors page, with descriptions of what each property modifies in the Web Client user interface (UI).

Field	Area or Element in UI
Name	Name of specified style scheme. The name of each scheme that is saved appears in the Color Palette dropdown list.
Gradient	"Gradient" or "Flat" applies a filter to certain areas of the UI, so the chosen color has no shading (Flat) or appears to have a light-to-dark quality (Gradient).
[Background column]	"Hex" value that specifies the main color of the field
[Text Color column]	"Light" results in white text lettering, or "Dark" results in black text lettering.
[Sample column]	This color swatch displays how the color you specified in Background and the Text Color value will look together.
Global Toolbar	Toolbar along the top of the Web Client UI
Dialog Bars	Top and bottom color bars in action dialogs
Widget Title Bar	On the Dashboard, background color where the widget's name is displayed
Selected Controls	Areas like tabs (in objects) or the drawers (on the Navigation Pane) when selected
Non-Selected Controls	Same elements named in "Selected Controls," only when they are not selected
Control Highlight	Drawer (in Navigation Pane) & Dropdown list item when mouse-over; Table Row when selected
Message Area	Shading in the Information line (near top of an object)
Backgrounds	Various backgrounds not assigned by above fields
Slider Separator	Small band of "outline" to give the slider bars definition

Specifying Colors in Hexidecimal Format

The PLM application has provided a few default style schemes, but it is likely that your company will prefer that Web Client have a corporate "look and feel." You have probably noted that most of the fields in the Specify Palette Colors page are in Hexidecimal format. Web designers use a variety of tools to specify colors for elements of web documents, such as RGB triplets expressed in hexidecimal (a "hex triplet").

While the Specify Palette Colors page can accept any color in hex format, you will need to access such color tools to generate coordinated color schemes and their corresponding "Hex" format values. For example, the Adobe web site <http://kuler.adobe.com/#themes/rating?time=30> can be useful for this purpose.

Report Templates

Agile PLM integrates existing Standard Reports with Custom Reports, which are modifiable through Oracle BI Publisher.

There is not a separate installation of Oracle BI Publisher required because Agile PLM includes a BI Publisher in order to:

- Run a standard Agile report
- Modify a standard Agile report layout, including adding flex fields
- Create new reports
- Get data through Agile PLM SDK and generate reports using Agile Java PX

Note The version that is bundled with Oracle Agile PLM is a restricted use version only.

Further information and documentation about the BI Publisher tool is located at the following web site: <http://xdo.us.oracle.com/?tab=doc> (<http://xdo.us.oracle.com/?tab=doc>).

End-user documentation is found in the chapter on Reports in *Getting Started with Agile PLM*.

This section details how the administrator prepares the layout template for the end-user reports that are available through the BI Publisher interface.

Manage Report Template (AppliedTo Choice)

"Manage Report Templates" is a choice in the Administrator-specific AppliedTo property (that is, found in **Administrator** and **Admin Access for User Admin** privilege masks).

When it is moved to the Selected table, Manage Report Templates enables you or an assistant administrator to upload templates for reports in the PLM Report Template utility. Choose **Web Client > Tools and Settings > Administration > Report Template** to bring up the Manage Report Template page.

Users see these templates, per assigned privileges, when they use the Reports function in Web Client.

Dynamic and Static Templates

There are two template modes: Static Template or Dynamic Template.

Static Template

The only two reports that support **Static Template** and generate files in RTF are the BOM Explosion Report and the Manufacturer BOM Report. This is accessed when the user selects both "Use BI Publisher" and "Use Template For Layout" options. The Static Template is the only mode that

supports XML format.

Dynamic Template

All custom reports and most of the standard reports use the **Dynamic Template** to define and generate reports in multiple output formats such as PDF, HTML, Excel, and Word.

Creating Report Templates

The administrator can define layouts by creating RTF templates in addition to the out-of-box layout already provided.

In Java Client, select **Admin > Server Settings > Preferences**. **Enable BI Publisher for Reports** has two values of Yes or No. When preference is set to No, reports are generated using the existing reporting layout. When preference is set to Yes, reports can be generated in multiple output formats using BI Publisher. For information on the system preference **Enable BI Publisher for Reports** see [Preferences](#) on page 379.

Note If the file server is down, templates will not generate reports as they are stored in the file server.

1. In Web Client, navigate to **Tools and Settings > Administration > Report Template**.
2. Click **Create** and the Create Report Template window appears.
3. Choose a name and enter a description for the template.
4. Browse to the location of your template RTF files.
5. Then click **OK** and your template is added to the list of options for templates. You can **Get** the template file and now modify it. You have the option to use Microsoft Office (Word) or Adobe Acrobat to design the layout of the report. There is also the option to use BI Publisher's Template Builder plug-in for Microsoft Word to employ drag-and-drop designing.

Reports Unsupported by BI Publisher

The following reports are not supported with the BI Publisher framework template:

- Change Package Report
- Change Metrics
- Change Backlog
- Change Cycle Time
- Quality Metrics
- Quality Backlog
- Quality Cycle Time
- Failure Trend
- RFQ Export
- IP Transfer

- Project Actual vs Budgeted Cost Report
- Baseline Comparison Report
- Portfolio Cost Report
- Resource Pool Consumption Report
- All PCM Reports

Logging Configuration

– For use by Agile Support ONLY! –

The **Logging Configuration** monitor has been added to permit Agile Support to perform quick changes to the logging configuration without stopping and restarting your company's Agile Application Server (AAS).

Important	Because the Logging Configuration utility is intended for use by Agile personnel in troubleshooting a customer's system, and is not intended for "self-treatment" of any problem, the various configuration scripts and Level menu choices are not documented herein.
------------------	---

Caution	You should never change the logging configuration without first receiving a recommendation from Agile Support.
----------------	--

Use of the Logging Configuration node:

1. When you, the PLM customer, encounter a problem and call Agile Support, you provide a URL for Web Client access to your PLM system. This "window" to your system permits data gathering.
2. If the Support person can identify the problem and a quick remedy, he will enter the logging change, attempt to reproduce the problem, and turn off Logging Configuration. The monitor enables resetting your "Log4J logging level" dynamically without stopping and restarting your system's AAS.
 - Use the Quick Search field at the bottom of the page. The debugging information appears in a console window.
 - After collecting the debugging information, Support can exit the **Logging Configuration** page without altering the PLM system being examined.
 - Click the **Refresh** button to update the view of logging data at any time.
 - In the Level column, modify the configuration by selecting from the dropdown list for appropriate classes.
 - Click the **Update Logger** button to commit the configuration change without stopping the system's AAS.
3. If Support does not find a remedy or workaround, the problem can be escalated to Agile Development.
 - "Agile Development" may ask Support to request that the customer turn on certain logs,

- based on which area of PLM the problem is originating from.
- The customer can turn on logs without restarting AAS, the information can be retrieved by Support, and the logs can be turned off without restarting AAS.
4. When "Agile Development" has debugged the problem, Support can:
- return to the customer's system to put the change into effect; or,
 - communicate the proposed fix to the customer.

Cache Health Monitor

Agile PLM caches in memory all data related to application configuration in each and every clustered server. This is called the Admin Cache. Any change to the Admin Cache data – on any server in the cluster – triggers a message to be delivered to all the cluster servers, to update the Cache for the data item that changed. Agile PLM uses Java Messaging Service (JMS) to broadcast this message.

It has been found that some changes are not propagated across all servers in the cluster. This happens randomly, that is, the occurrence of non-propagation is not possible to predict. Once it occurs, the solution is to restart all the servers in the cluster. An additional solution to this issue is the utility called **Cache Health Monitor**.

Note Cache Health Monitor utility is designed as a backup system. The current method of using the JMS server remains as the primary data synchronization mechanism.

The Cache Health Monitor performs the following actions:

- Lists all modified Administrator nodes and the current synchronization state;
- Commences the synchronization manually or automatically (see [Automatic Synchronization using Java Client Administrator](#) on page 46);
- Turns logging of cache synchronization operations on or off;
- Views the log file containing cache synchronization operation messages;
- Purges old entries.

How the Cache Health Monitor Works

All Administrator (configuration-related) changes are entered to a new database table. At the server startup time, Cache Health Monitor logs the server time as "last update time" (LUT) and monitors all changes made from LUT onwards. If a manual or automatic triggering is initiated, all changes made from the LUT are synchronized (if not already synchronized) and the LUT is updated to the current time.

To access the servers in the cluster, the administrator must log in to each application server directly, using the application server name and port. For example, suppose there is a cluster with three servers:

- app1.abc.com
- app2.abc.com

- app3.abc.com

To monitor and synchronize manually, the administrator would log in to each server using these URLs:

- <http://app1.abc.com:7777/Agile/PLMServlet>
- <http://app2.abc.com:7777/Agile/PLMServlet>
- <http://app3.abc.com:7777/Agile/PLMServlet>

The default Oracle Application HTTP port-"7777"-is shown in the examples; you are advised to change this as appropriate.

Buttons on Cache Health Monitor Page

The specific application server name is listed on the **Cache Health Monitor** page. This helps identify the server that the user is connected to, especially when the user may want to have one browser session for each server in the cluster.

The buttons on the **Cache Health Monitor** page activate specific events as follows:

Synchronize – Synchronizes the data on that particular application server; use when one or more objects are reported as "Not synchronized" in the **Status** column. After the Synchronize button is clicked, synchronization is triggered and the status changes to "Synchronized."

Refresh – Refreshes the data on that page.

Purge – Purges old entries in the CACHE_SYNC_LOG table in database; the time interval to select entries to purge is configured through the property cache.syncevent.obsoletetime (in minutes) in the file `agile_home/agileDomain /config/agile.properties`. The default value is 144000 minutes, or 100 days. Changing this property requires server restart.

Purge removes all entries in the table that are older than the Purge value. In above case, all entries older than 144000 minutes will be removed.

Turn Log on / Turn Log off – Enables or disables logging, works as a toggle switch.

View Log – Displays current synchronization log; this log contains information about synchronization process, objects that have been synchronized and failures, if any.

Automatic Synchronization using Java Client Administrator

To configure automatic cache synchronization, you must enable a background task called "Admin Cache Synchronization Task." This task is configured in **Java Client > Admin > Server Settings > Task Configuration**; it is documented in [Task Configuration](#) on page 392.

When you double-click a task in the Task Configuration page, the Task Configuration **General Info** window for that task appears. Admin Cache Synchronization Task has the following properties, including the defaults specific to Cache Health Monitor.

Property	Description
Name	Name of the task being configured.

Property	Description
Task Interval	Periodic time interval in minutes after which the server updates the status of the task. Default is 5, meaning all enabled tasks in the node run every 5 minutes.
Task Delay Time	How many minutes the event is delayed before it starts to run. Default = 0.
Task Lookback Window	How far back in minutes the task manager is to look to retrieve the events that can be run now. Default = 0.
Task Max Event Number	How many events can be running at the same time on one server. Default = 1.
Task Restart Upon Failure	Indicates whether the event should be restarted after it failed. Yes or No. Default = No.
Task Load Across Server	Indicates whether the event can be executed at the same time in different servers of a cluster. Yes or No. Default = No.
Task Disabled	Indicates whether the task is disabled (Yes) or enabled (No). Note that you may want to set this property to Yes while you are configuring and testing it; when you are ready to enable the task, you must re-set this property to No. Default = No.

If you do not make frequent changes in Administrator, or if Admin changes are updated on a specific or scheduled time, manual synchronization of the cluster will likely meet your needs. If, however, you frequently change settings in Administrator, and these are entered at many intervals throughout the day, this automatic Admin Cache Synchronization Task is a more structured backup should synchronization fail. In the event of synchronization failure, use Cache Health Monitor (either manual or automatic) until you are able to restart the cluster's servers.

Logging and Debugging Errors

To provide a mechanism to track the events related to Admin Cache synchronization, logging can be enabled to log all debugging messages. When logging is turned off, only errors and synchronization issues seen by the Cache Health Monitor are logged.

When an Administrator object or a business object is modified on any server in the cluster, a JMS server receives the event details and is triggered to broadcast the message to the other servers.

Note While the Cache Health Monitor monitors and synchronizes Administrator objects exclusively (for example, Changes Base Class or Change Orders Class), the logging mechanism logs events related both to Administrator objects and to user-modified business objects (for example, a modified change order). This is helpful for tracking the propagation of changes to business objects across the servers.

The following two messages (each message starts with a time stamp) will be recorded in the log file (when log is turned on).

```
2006-09-20 18:14:08,881 HttpRequestHandler-3096409 <Messenger:DEBUG> Sending
message <class:com.agile.pc.cmserver.event.CMBatchEvent, content:Batch events:
event class: com.agile.pc.cmserver.event.CMObjectEvent, content: object: class: 10000
```

```
subclass:10141 id:6010147 version:1 action: 4
event class: com.agile.pc.cmserver.event.CMFTSSyncEvent, content: FTS sync object: class:
10000 subclass:10141 id:6010147 version:0
event class: com.agile.pc.cmserver.event.CMObjectEvent, content: object: class: 10000
subclass:10141 id:6010147 version:1 action: 1
> to <topic:sync_topic> with property <name=APP_SRV_ID, value=6010141>
2006-09-20 18:14:10,222 HttpRequestHandler-3096409 <Messenger:DEBUG> Message was
delivered to JMS topic:sync_topic
```

The first message captures the details of the object modified; the second message indicates that the JMS server received the message. JMS then propagates this message and the following three messages are recorded on all servers other than the originating server.

```
2006-09-20 18:14:27,257 ApplicationServerThread-2 <SyncMDBean:DEBUG> Received
message from JMS server.
2006-09-20 18:14:27,257 ApplicationServerThread-2 <SyncMDBean:DEBUG> Message was
sent by server with ID: 6010141, current server id is: 6010121
2006-09-20 18:14:27,257 ApplicationServerThread-2 <SyncMDBean:DEBUG> Process event:
class name --> com.agile.pc.cmserver.event.CMBatchEvent, type --> 1, content --> Batch
events:
event class: com.agile.pc.cmserver.event.CMObjectEvent, content: object: class: 10000
subclass:10141 id:6010147 version:1 action: 4
event class: com.agile.pc.cmserver.event.CMFTSSyncEvent, content: FTS sync object: class:
10000 subclass:10141 id:6010147 version:0
event class: com.agile.pc.cmserver.event.CMObjectEvent, content: object: class: 10000
subclass:10141 id:6010147 version:1 action: 1
```

Using the above log messages, any unsynchronized data could be traced out.

When manual / automatic (background thread) triggering occurs, even with logging turned off, the following messages are displayed for all Administrator nodes being synchronized.

Manual Triggering:

```
2006-09-20 13:17:39,512 HttpRequestHandler-394365 <ADictionary:INFO> Admin cache sync >
invalidate node: admin objid: 7000 class id: -1 version: -1
```

Automatic Triggering:

```
2006-09-20 13:17:39,512 ApplicationServerThread-149 <ADictionary:INFO> Admin cache sync >
invalidate node: admin objid: 7000 class id: -1 version: -1
```

Note that the difference in the two messages is the source of triggering, in the manual case since we are sending a HTTP request the source is displayed as `HttpRequestHandler`, in the second case, the source is application itself (background thread) therefore the source is displayed as `ApplicationServerThread`.

Logging is configured through the log.xml file in agile_home/agileDomain/config directory.

The following element configures the log for Cache Synchronization.

```
<appender name="CacheSyncLog" class="org.apache.log4j.RollingFile
Appender">
    <param name="File" value="${agile.log.dir}/cachesync.log" />
    <param name="Append" value="true" />
    <param name="MaxFileSize" value="1MB"/>
    <param name="MaxBackupIndex" value="10"/>
    <layout class="org.apache.log4j.PatternLayout">
        <param name="ConversionPattern" value="%d\t\t\t\t\t;
%c{1}:%p>\t\t\t\t\t"/>
    </layout>
</appender>
```

Parameter	Description
File	Name and path of the log file
Append	Append or overwrite to existing file at server startup
MaxFileSize	Maximum file size after the current file is archived and new file is created
MaxBackupIndex	Maximum number of files that would be archived

Deleting Objects in Agile

Java Client and Web Client support “soft” and “hard” deletes. When you soft-delete an object in the database, it is not permanently deleted. A soft-deleted object is marked “Deleted” in the database, and its object number or name is reserved. You cannot create another object with the same type and number or name as a soft-deleted object.

Note You *can* undelete a soft-deleted object, if you have the appropriate privileges set by the Agile administrator.

When you run a search, soft-deleted objects do not appear in the search results table. To locate soft-deleted objects, you must run the predefined deleted object searches in the **Recycle Bin Searches** folder.

Note You have access to the **Recycle Bin Searches** folder if **Recycle Bin Searches** is included in the **Searches** field of your user profile. If you have the appropriate privileges, you can edit your user profile and add **Recycle Bin Searches** to the list of searches in the **Searches** field.

A hard-deleted object is permanently removed from the database.

Caution You *cannot* undelete a hard-deleted object.

To soft-delete, hard-delete or undelete an Agile object:

- You must have the appropriate Delete or Undelete privileges for that object.
- The object must meet the conditions that allow it to be deleted or undeleted.

In general, if deleting or undeleting an object would cause the compromise of data integrity, the delete or undelete action is disabled.

You cannot delete an object unless all of its relationships and subscriptions are removed.

For detailed information about deleting specific *object* types see the *Deleting Agile Objects* section of *Getting Started with Agile PLM*.


To soft-delete an object in Web Client:

1. Select and open the object you want to delete.
2. Choose **Actions > Delete**, and respond **OK** to the confirmation prompt.

The object is soft-deleted.


To hard-delete a soft-deleted object (if you have the appropriate privileges) in Web Client:

1. Run the appropriate Deleted <objects> search from the **Recycle Bin Searches** folder.
2. Select the one or more object rows in the search results table.
3. Click the **Delete** button.
4. In response to the warning prompt, choose **Continue**, then click **Finish**.
5. Or, you can hard-delete one object at a time:
 - Open the object.
 - Choose **Actions > Delete**, and respond **OK** to the confirmation prompt.

Note You can click the **Navigator** button in the search results table to display the search results object links in the left pane  **NAVIGATOR** drawer.

To undelete an object in Web Client:

1. Run the appropriate Deleted <objects> search from the **Recycle Bin Searches** folder.
2. Open the deleted object you want to restore.
3. Choose **Actions > Undelete**.

Note You can click the **Navigator** button in the search results table to display the search result object links in the left pane  **NAVIGATOR** drawer.

This chapter includes the following:

▪ Configuring Business Objects with Agile PLM Classes	51
▪ Agile PLM Class Structure	52
▪ Agile PLM's Installed Object Types	54
▪ Agile PLM's Installed Nonroutable Object Types	55
▪ Customizing Lifecycle Phases	58
▪ Configuring Subclasses	60
▪ Configuring Tabs	65
▪ Modifying the Format of Tabs	66
▪ About Attributes, Flex Fields, and Read-Through Fields	72
▪ Defining Attributes	77
▪ Configuring Attributes	84
▪ Using Custom Icons for Subclasses	86
▪ Quick Access to Objects and Files	87

This chapter describes the predefined business classes delivered with Agile PLM, and how to create subclasses, assign autonumber sources, and tailor the arrangement of tabbed windows and formatted fields for your product data.

Configuring Business Objects with Agile PLM Classes

The **Classes** node provides a framework for classifying objects in Agile PLM. Everything that an Agile PLM user creates is an object. As administrator, you can define new types of business objects, or modify the default classes and subclasses.

Note The default classes that are available in Agile PLM depend on which licenses your company purchased. Unavailable classes appear in red type on the Classes page.

Each class represents a kind of action (business process) or kind of entity (business object). Every class has at least one default subclass. Every object created in Agile PLM is an instance of a subclass.

Before you start configuring Agile PLM, you should consider what types of business objects are required by your company. You can then tailor Agile PLM to your requirements. For example, you might want to create several new subclasses in the Parts class to organize the kinds of parts that your company manufactures or purchases.


The Agile PLM object framework is ready to use out-of-box, or you can tailor it as follows:

- Create additional subclasses
- Modify classes and subclasses as needed
- Create new attributes for classes (Page Two) and subclasses (Page Three) as needed

- Modify the properties of attributes
- Display or hide attributes or tabs
- Reorder table columns or fields

Agile PLM Class Structure

Agile PLM classes have the following three levels:



- **Base Class** — The highest level object. Base class is the parent object of classes. You cannot create or delete base classes, but you can rename them. Examples of provided base classes are Users, Items, and Changes.
- **Class** — The primary level of organization in Agile PLM. Also called *main class*. Inherits the general properties and process extensions of its base class. Classes are the organizing framework for the creation of subclasses. You cannot create or delete classes, but you can rename or disable them. Examples of provided classes are Parts, Change Orders, and Change Requests classes.
- **Subclass** — Inherits all properties and attributes of its parent class. Subclasses arrange the information and data that describes a specific business object in Agile PLM. You can rename subclasses. You can also create a subclass in any class except Users, Automated Transfer Orders, Requests For Quote, RFQ Responses, and Standard Reports. You can delete or disable any subclass except those descended from Items, Changes, and File Folders base classes. Examples of provided subclasses are User, Part, Document, ECO, and ECR.

Caution	Before renaming any classes, particularly the base classes, make sure you become familiar with the default classes provided with Agile PLM. Class names must be unique.
----------------	---

Routable and Non-Routable Objects

Each class represents a specific process or kind of entity:

- **Routable objects** are created from classes that represent *processes*, such as a change in the change control process, or a transfer order, or a product service request. These objects can be routed to Agile PLM users for approval or other input via workflows (see [Workflows](#) on page 129).
- **Non-routable objects** are created from classes that represent *entities* or things, such as parts, sites, RFQs, users, prices, or reports. These objects can be “flagged” for progress via lifecycle phases (see [Customizing Lifecycle Phases](#) on page 58). Note, however, that non-routable objects—especially parts and documents—can be changed by the process of information-gathering via workflows, which are created through such routable objects as change orders or change requests.

Note The File Folders class has a default, non-editable workflow with a single Review status and no other statuses. This provides file folder objects with a **Routing Slip** tab, which allows approvers to sign off and comment on a file folder. However, file folder objects also have lifecycle phases and are considered non-routable.

Object Types in Agile PLM

In PLM, Object Types are each and every one of the rows in the **Classes** node. Object types are organized by the hierarchy of Base Class (a kind of template), Class (more detailed, generally specific to a PLM solution), and Subclass (most specific organizing group).

So, for example, let `ECO987` be an individual business object: it is a single instance of the object type *ECO* (a subclass), which is derived from the object type *Change Orders* (a class), which in turn is derived from the object type *Changes* (a base class).

Therefore, each new subclass that you create is also an object type. So, *Items*, *Parts*, and *Part* are each an object type, and if you add subclasses called *Capacitor* and *Resistor*, each of these are also object types.

"Object Type" is a significant field in such areas of PLM administration as **Criteria**, **Privileges**, **Notifications**, and **Event Management**. For these and many other functions, it is a crucial element to inform the PLM system precisely what kind of object is to be accessed and subject to user actions.

Viewing Agile PLM Classes

To view an Agile PLM class or subclass:

1. On the Admin tab, under **Data Settings**, double-click **Classes**. The Classes window appears.
2. Double-click the class or subclass you want to view.
3. Now click the **User Interface Tabs** tab. Double-click any row to bring up that tab's information:

The **General Information** tab displays the name and description of the UI tab and whether it is visible.

Once you have opened one tab, a dropdown list allows you to switch to any of the other tabs

for that object.

Agile PLM's Installed Object Types

Your company may be licensed to a subset of the list of object types in **Classes** node.

The following tables list all the possible installed object types in Agile PLM. The first table lists the routable objects, the second table lists the non-routable objects.

Base class	Class	Subclass	Description
Routable objects: the means to direct or recommend changes to non-routable objects. These classes have a default workflow for changes to seek approval from other users. Objects from these classes can be changed without approval.			
Changes	Change Orders	ECO	Directives to change an item; can advance the revision ("rev") of an item
	Change Requests	ECR	Requests for a change to an item
	Deviations	Deviation	Directives to temporarily substitute one item for another
	Manufacturer Orders	MCO	Changes to AML data, such as information about manufacturers or manufacturer part numbers
	Price Change Orders	PCO	Directives to change a published price; can advance the revision of a published price
	Site Change Orders	SCO	Changes to BOM and AML information for a specific site
	Stop Ships	Stop Ship	Directives to stop shipping/using an item
Declarations	Substance Declarations	Substance Declaration	Seeks compliance information for each substance within the specification
	Part Declarations	Part Declaration	Seeks part-level compliance information and other composition header-level information (manufacturing parameters)
	JGPSSI Declarations	JGPSSI Declaration	Seeks compliance information (weights) according to the JGP standard.
	Homogeneous Material Declarations	Homogeneous Material Declaration	Seeks complete breakdown of parts on the Bill Of Substances and compliance information at the homogeneous material level

Base class	Class	Subclass	Description
	Supplier Declarations of Conformance	Supplier Declaration of Conformance	Seeks compliance with specifications from customers and government agencies
	IPC 1752-1 Declarations	IPC 1752-1 Declaration	A Joint Industry Guide (JIG) material composition declaration for electronic products
	IPC 1752-2 Declarations	IPC 1752-2 Declaration	A homogeneous material composition declaration for electronic products
Packages	packages	Package	Packages of data to share with partners
Product Service Requests	Problem Reports	Problem Report	Quality incidents with items or products
	Non-Conformance Reports	NCR	Quality conformance issues with items or products
Projects	Activities	Phase; Program; Project; Task	Components of project planning in Product Portfolio Management; activities are time-based objects to which resources can be assigned
	Gates	DG1, DG2, DG3, DG4, DG5, DG6; Gate; Milestone	Project management milestones in Product Portfolio Management; gates identify cross-PLM deliverables of the product development process to enable executive reviews of projects
Quality Change Requests	Corrective and Preventive Actions	CAPA	Requests for corrective actions and preventive actions
	Audits	Audit	Proactive reviews of business processes
Transfer Orders	Automated Transfer Orders	ATO	Transfer or publication of a product record that is automatically triggered by a workflow
	Content Transfer Orders	CTO	Transfer or publication of a product record that is manually triggered

Agile PLM's Installed Nonroutable Object Types

Base class	Class	Subclass	Description
Non-Routable Objects: objects in these classes are not routed to Agile PLM users with workflows; objects from some of these classes, however, are changed by a user submitting a workflow (from routable classes) for approval from other users.			

Base class	Class	Subclass	Description
Customers	customers	Customer	Clients of the company
Discussions	discussions	Discussion	Informal, threaded dialogue
File Folders	File folders	File Folder Markup	Objects that include files or URLs; this class includes all file folder objects except historical report file folders
	Designs	Design	Objects that permit building design structures in the CAD environment
Items	Documents	Document	Specifications, blueprints, manufacturing data, and so forth
	Parts	Part	Parts manufactured within the company, or provided by manufacturers or suppliers and given internal part numbers
Manufacturers	manufacturers	Manufacturer	Qualified manufacturers
Manufacturer Parts	Manufacturer parts	Manufacturer Part	Parts provided by manufacturers
Part Groups	Part groups	Commodity Part Family Item Group	Containers of other parts (items or manufacturer parts) that share such properties as mass or composition information. Note This object was named "Commodities" in previous releases of Agile PLM.
Prices	Quote Histories	Quote History	Organizes bid prices from RFQ responses; cannot be revised by a PCO (see grouping of Changes in preceding table)
	Published Prices	Published Price; Contract	Organizes prices of the company's products; can be revised by a PCO (see grouping of Changes in preceding table)
Reports	Standard Reports	Administrator Report; Standard Report	The out-of-box reports for administrators (Administrator Reports) and users (Standard Reports include Products, Sourcing, Quality, Process, Personal, and Global reports)
	Custom Reports	Custom Report	Reports created and used within company
	External Reports	External Report	Reports created outside Agile PLM

Base class	Class	Subclass	Description
Requests For Quote	Requests for quote	RFQ	Requests for quote, which are assembled from sourcing projects and sent to suppliers for formal bids
RFQ Responses	RFQ responses	RFQ Response	Bids, that is, responses from suppliers to your company's RFQs
Sites	sites	Site	Manufacturing locations within the company, or closely partnered with the company
Sourcing Projects	Sourcing projects	Sourcing Project	Work preparatory to creating RFQs and capability for analysis across multiple RFQs
Specifications	specifications	Specification	Lists of banned substances (or substances of concern) and their threshold values
Substances	substances	Substance	A single chemical element used in composition of items, manufacturer parts, and part families
	Materials	Material	A compound chemical, a substance consisting of multiple substances
	Subparts	Subpart	A subunit of a component, used to get to the homogeneous material level to collect compliance information
	Substance Groups	Substance Group	A group of multiple substances, with a base substance that is what legislation is interested in, for example, "Lead and Lead Compounds"
Suppliers	suppliers	Broker; Distributor; Component Mfr.; Contract Mfr.; Mfr. Representative	Qualified suppliers of manufacturer parts; used by PCM (which uses the out-of-box subclasses) and PG&C solutions
Users	users	User	Individuals using the Agile PLM system
User Groups	User groups	User Group	Groups of people using the Agile PLM system, e.g., departments, teams, site-specific groups

Disabling Object Types

When a base class is disabled, the child classes and subclasses are automatically disabled. When a class is disabled, the child subclasses are disabled. When a base class, class, or subclass is disabled, it is "grayed out" in the user interface for Java Client or Web Client. Examples of where the disabled class would be unavailable are the **Create** menu and search options. Existing searches

and criteria are not deleted or modified if a class is disabled; existing objects of disabled object types remain in the Agile PLM database.

The following base classes cannot be disabled, nor can their child classes or out-of-box subclasses:

- Items
- Changes
- Users
- File Folders

Customizing Lifecycle Phases

Lifecycle phases describe the valid phases for classes whose objects are non-routable, that is, they do not follow workflows. Items, sites, manufacturers, manufacturer parts, prices, sourcing projects, RFQs, RFQ responses, suppliers, customers, prices, commodities, specifications, substances, and file folders all have lifecycle phases.

Lifecycle phases at the base class level are inherited by classes and subclasses. The lifecycle stamp is automatically created for you using the name and color you specified for each lifecycle phase.

Modifying a Lifecycle Phase

You can modify lifecycle phases for the following base classes:

- Commodities
- Customers
- File Folders
- Items
- Manufacturer Parts
- Manufacturers
- Prices
- Specifications
- Substances
- Suppliers

Note You cannot delete or rename the Preliminary lifecycle phase for items. Objects in the Sites, Sourcing Projects, Requests for Quote, and RFQ Responses classes have read-only lifecycle phases that cannot be renamed or deleted.

To modify lifecycle phase **settings**:

1. Select the base class you want to work with, and select the **Lifecycle Phases** tab. The Lifecycle Phases window appears.

2. Double-click the lifecycle phase you want to modify.
3. In any editable field, enter a new value or select from the dropdown list.
4. When you have finished, click **Save**.

Adding a Lifecycle Phase

You can add lifecycle phases to base classes, classes, or subclasses.

To add a lifecycle phase:

1. Select the class you want to work with, and select the **Lifecycle Phases** tab. The Lifecycle Phases window appears.
2. Click the **New** button. The Define Lifecycle Phase dialog box appears.
3. Enter a name, API name and description for the lifecycle phase. The name can be up to 29 characters.
4. In the **Enable** field, select Yes or No from the dropdown list.
5. For items, there is an additional field, **AddLifecyclePhaseOnBomRule**. Select Allow, Disallow, or Warning (the default).

If you select Disallow, users will be prevented from adding items currently in this lifecycle phase to an item's BOM table.

6. When you are done, click **OK**.

Note To select a different color for the lifecycle phase, modify it on the appropriate lifecycle phases tab.

Removing a Lifecycle Phase

You can remove a lifecycle phase only from the level in which it was created. When you remove a lifecycle phase from a class, it is also removed from all subclasses that inherit from the class. For example, if you create a new lifecycle phase in the Items base class, you can open the Items base class later to remove it. The lifecycle phase is also removed from the Parts and Documents classes, and the Part and Document subclasses.

To remove a lifecycle phase:

1. Select the class you want to work with, and select the **Lifecycle Phases** tab. The Lifecycle Phases window appears.
2. Select the lifecycle phase you want to delete.
3. Click the **Delete** button.
4. Click **OK** in the confirmation message to delete the lifecycle phase.

The lifecycle phase is deleted and is no longer available as a selection in Agile PLM.

If you delete a lifecycle phase that has already been used to release an item in Agile PLM, it still indicates that phase, but users cannot assign that phase in the future.

Note You cannot delete the Preliminary lifecycle phase for items.

Configuring Subclasses

When users create an object in Agile PLM, they first specify its subclass, such as ECO, Part, Capacitor, and so on. These subclasses are created and defined in the **Classes** node. The defined Agile PLM classes are each equipped with at least one subclass. You can create more subclasses in any class. For example, the Parts class can have subclasses called Capacitors, Resistors, Diodes, and so on.

You can decide to use just the default subclasses, define new subclasses, or rename subclasses.

You can delete a subclass as long as it has not been used to create any of these objects from the administrative nodes:

- Search criteria
- An object in Java Client or Web Client
- A privilege mask

Note You cannot create new subclasses for the following classes:

- Users class
- Automated Transfer Orders class
- Requests For Quote class
- RFQ Responses class
- Standard Reports class

Important Setting up new subclasses in Agile PLM requires a lot of planning. If you set up new subclasses without an overall plan, you may find in a few weeks that you want to “start over,” only now new subclasses are in use and will not be easy to remove from the system. It is better to become proficient with Agile PLM objects using the out-of-box classes and subclasses while you develop an overall plan that covers your company’s needs.

Before You Begin

Consider the following details before creating a new subclass:

- For which Agile PLM class will you create a subclass?
- What name will you give the new subclass? Remember that a subclass name must be unique, and cannot be used more than once in the same Agile PLM system.
- Do you need to track product data specific to this subclass? If so, you may also want to set up a **Page Three** tab for this subclass.
- If you plan to create a Page Three for the new subclass, you will need to adjust some users' roles and privileges to allow Page Three modification.

For new subclasses that have autonumbering, you should consider the following:

- Will you permit users to assign numbers manually for the new subclass?
- Will you be creating new autonumber sources for the subclass, or will you use existing autonumber sources?
- If you plan to use existing autonumber sources, which ones?

Viewing Subclass Properties

You can see how a subclass is configured by viewing its properties. For example, to see what number sources are assigned to a Change Orders subclass, you can view the subclass properties in Administrator.

To view the properties of a subclass:

1. Under **Data Settings**, double-click **Classes**. The Classes window appears.
2. Double-click the name of the subclass you want to view.

The properties of the subclass are listed on the **General Info** tab.


Changing the AutoNumber Source Property

Subclasses that can be autonumbered have an AutoNumber Source property. Since subclasses in the Manufacturers, Manufacturer Parts, and Sites classes do not use autonumbering, they do not have an AutoNumber Source property.

The Agile PLM administrator can change the AutoNumber Source property for a subclass to do the following:

- Require automatic number assignment for the subclass, so that manual number assignment is prevented.
- Assign one or more different autonumber sources for the subclass.
- Remove autonumber source assignments from the subclass.

To change the autonumber sources used for a subclass:

1. Under **Data Settings**, double-click **Classes**. The Classes window appears.
2. Double-click the name of the subclass you want. The subclass properties window appears.
3. Next to the **AutoNumber Source** field, click . The List Chooser dialog box appears.
4. To move a number source from the **Choices** list to the **Selected** list, select it, and click the right arrow. You can also move the number source by double-clicking it.

You can select more than one number source.

5. Click **OK** to close the dialog box.
6. If you want to create a new autonumber—more customized than those offered by the automatic sequencing of autonumbers—click the **New AutoNumber** button and follow the instructions in the dialog box. For more information, see [Creating a New Autonumber Source](#) on page 116.
7. If you want to prevent users from entering an object number manually, select No in the **Autonumber Required** dropdown list. For more information, see the next section.
8. Select Yes or No in the **AutoGenerate** dropdown list.
9. Click **Save**.

Preventing Manual Number Assignment

If you decide to require autonumbering for a specific subclass, you can prevent users from entering numbers manually. You can require autonumbering for any subclass that can be autonumbered.

Note	Several Agile PLM subclasses, such as Manufacturer and User, do not allow autonumbering.
-------------	--

To prevent manual number assignment for a specific subclass:

1. Under **Data Settings**, double-click **Classes**. The Classes window appears.
2. Double-click the name of the subclass you want. The subclass properties window appears.
3. In the **Autonumber Required** dropdown list, select Yes.
4. Click **Save**.

Changing a Subclass Name or Description

You can change the name of any subclass. If you change the name of a subclass that has already been used to create objects in Agile PLM clients, the subclass name for the existing objects is changed to reflect the new name. You can also enter a different description for the subclass; a description is optional.

Caution	Although all characters are supported within Agile PLM, and should not create issues within Agile's clients, it is recommended that you avoid using the following characters when renaming or creating subclasses, due to issues that could potentially arise in integrations or custom applications written on the SDK.
----------------	--

, comma . period (dot) : colon ; semicolon = equal sign

To change the name of a subclass:

1. Under **Data Settings**, double-click **Classes**. The Classes window appears.
2. Double-click the name of the subclass you want. The subclass properties window appears.
3. Enter a new name and description in the **Name** and **Description** fields.
4. Click **Save**.

The subclass name is changed for all objects in the subclass. The new name appears as a selection in the **Type** dropdown list in the New Object dialog box in Java Client, and the new name appears as a selection in the **Type** dropdown list in the Create New Change Order window in Web Client.

Changing the Site-Specific BOM Property

On the subclass properties window, there is a property called **Site-Specific BOM**. The value for the property is either **Allow** or **Disallow**.

- **Allow** – The subclass may be added to a site-specific portion of a BOM.
- **Disallow** – The subclass may not be added to a site-specific portion of a BOM.

This property determines whether a Parts or Documents subclass may be part of a site-specific BOM.

For example, let the Manufacturing Item subclass have the Site-Specific BOM property set to Allow, and subclass Part have it set to Disallow. A user at the Singapore site can add any manufacturing item to the site-specific section of the BOM for Singapore, but not add a part to the site-specific section of the BOM for Singapore. A Global user can add either a manufacturing item or a part to the Global section of the BOM.

The default value for all newly created Parts and Documents subclasses is Allow.

To change the Site-Specific BOM property of a subclass:


1. Under **Data Settings**, double-click **Classes**. The Classes window appears.
2. Double-click the name of the subclass you want. The subclass properties window appears.
3. In the **Site-Specific BOM** field, select Allow or Disallow. Click **Save**.

Creating a New Subclass

This is the procedure for creating a new subclass. Please review the points in [Before You Begin](#) on page 61. Remember you can keep a subclass disabled while you run some tests before releasing it to your users.

To create a new subclass:

1. Under **Data Settings**, double-click **Classes**. The Classes window appears.
2. Click the **New Subclass** button. The New Subclass dialog box appears.
3. Select a class from the dropdown list.

4. Fill in the **Name**, **API Name** and **Description** fields, and select Yes or No in the **Enabled** list. You must use a unique subclass name.
5. Next to the **AutoNumber Source** field, click . The selection dialog box appears.
6. To move a number source from the **Choices** list to the **Selected** list, select it, and click the right arrow. You can also move the number source by double-clicking it.

You can select more than one number source.
7. Click **OK** to close the dialog box.
8. If you want to create a new autonumber—more customized than those offered by the automatic sequencing of autonumbers—click the **New AutoNumber** button and follow the instructions in the dialog box. (This task is detailed in [Creating a New AutoNumber Source](#) on page 116.)
9. If you want to prevent users from entering an object number manually, select No in the **Autonumber Required** dropdown list. (For more information, see [Preventing Manual Number Assignment](#) on page 62.)
10. Select Yes or No in the **AutoGenerate** dropdown list.
11. If you selected the Parts or Documents class in step 3 above, set **Site-specific BOM** to Allow or Disallow. (For more information, see [Changing the Site-Specific BOM Property](#) on page 63.)
12. When you have specified all the settings, click **OK**.

The new subclass appears under the class name in the Classes window.

Note Number sources are created and configured in the **AutoNumbers** node. For instructions, see About Autonumber Sources.

Deleting a Subclass

You can delete any subclass that has not been used to create a saved search, an object, or a reusable criteria.

To delete a subclass:

1. Under **Data Settings**, double-click **Classes**. The Classes window appears.
2. Double-click the subclass you want to delete. The subclass properties window appears.
3. Click the **Delete** button.
4. In the confirmation dialog box, click **OK**.

The subclass no longer appears under the class name on the Classes window.

Note If you attempt to delete a subclass that has already been used to create a search, an object, or a reusable criteria, an error message states that the object is already in use.

You can also delete a subclass by displaying it, then choose **Delete** from the Actions menu.

Configuring Tabs

When users open an object in Agile PLM clients, they see a tabbed page, or window of tabs. From the **Classes** node, you can enable (make visible) or disable (hide) most object tabs. You can also rename any object tab. You configure optional **Page Two** and **Page Three** tabs by enabling the tabs to make them visible.

Although you can hide most object tabs, you cannot disable or hide the following tabs:

- The first tab of any object, specifically:
 - **Cover Page** tab of any change, package, PSR, QCR, transfer order, or project
 - **General Info** tab of any manufacturer, manufacturer part, user, user group, site, customer, discussion, price, or report
 - **Title Block** of any item or file folder
- **Affected Items** tab of any change and the **Affected Prices** tab of PCOs
- **Action Items** tab of discussions
- **Selected Content** tab and **Where Sent** tab of any transfer order—in fact, no tab of ATOs can be disabled or hidden
- **Files** tab of file folders (not historical report file folders)
- **Response List** tab of RFQs and RFQ responses
- **Replies** tab of discussions
- **Team** tab and **Workflows** tab of projects

If you want to configure the attributes that appear on a tab, you must go to the setup window for that tab. See [Defining Attributes](#) on page 77.

About Page Two Tabs

If you need to document additional information for change orders, for example, you can enable an extra tab called a **Page Two** tab by default. This tab then appears next to the **Cover Page** tab for all subclasses in the Change Orders class. You can use the default name **Page Two** for this tab, or you can give it a more specific name.

Note In Web Client, Page Two attributes are displayed on the **Cover Page** tab, under the heading **Page Two** (any custom tab name is not displayed). The user can scroll down to see the additional “Page Two” information.

About Page Three Tabs

If you need to record additional information that is specific to a subclass, you can enable an extra tab called a **Page Three** tab by default. For example, you can set up a **Page Three** tab for the subclass Capacitors and create a field called Insulation (or multiple fields as needed), where users record information about insulation for each capacitor object created. You can use the default name **Page**

Three, or you can give the tab a more specific name.

Note In Web Client, Page Three attributes are displayed on the **Cover Page** tab, below the Page Two attributes, under the heading **Page Three** (any custom tab name is not displayed). The user can scroll down to see the additional “Page Three” information.

Showing, Hiding, or Renaming a Tab

You can customize the Agile PLM client user interface by showing, hiding, or renaming the tabs in classes.

Note If you hide the **BOM** tab or the **Manufacturers** tab, the buttons under the **Redline BOM** and the **Redline Manufacturer** tabs are disabled.

The name and visibility of any tab depends on the settings at the *subclass* level. For example, in the Change Orders class, if you set **Page Two** tab to Name = P2, Visible = No, and in ECO subclass, if you set **Page Two** tab to Name = P2 of ECO, Visible = Yes, then in Java Client or Web Client, the **Page Two** tab will be visible and appear as **P2 of ECO**.

To show, hide, or rename a tab:

1. In the Classes window, locate the tab you want and double-click it to display the setup window for that tab.

For example, click **Change Orders Class**, display the **User Interface Tabs** tab, then double-click **Workflow** to display the setup window for the change order **Workflow** tab.

2. If you want, on the **General Information** setup tab, enter a new name for the tab.

The tab, with its new name, appears in Java Client. In Web Client, the tab data appears on the first object tab, for example, the **Cover Page** tab.

Note When you change the name of **Page Three** tabs for Content Transfer Order (CTO) subclasses, the modified **Page Three** tab name does not appear in the Content Service filters. The name **Page Three** always appears in the filters.

3. In the **Visible** drop-down list, select Yes to make the tab visible in Agile PLM clients.
4. When you have finished your modifications, click **Save**.

Note If you hide a **Page Two** or **Page Three** tab, any attributes configured for the tab are still visible as search selections in Java Client or Web Client unless you also hide them. See [Removing a Page Two or Page Three Tab](#) on page 72.

Modifying the Format of Tabs

Each object tab uses one of two different formats to display data in Agile PLM clients:


- **Form format** — Attributes appear on the tab in rows and columns, according to the attribute order, lowest number first, left to right, then top to bottom. Each attribute field is labeled. Web Client has two columns. In Java Client, the number of columns varies depending on the size of the object window.

- **Table format** — Attributes appear on the tab in a table. The attribute names appear as column headings in the table.

You can modify the order in which object attributes appear on object tabs in both forms and tables.

Modifying Attribute Order on a Form Tab

In Web Client, on a form type tab, the attributes appear in one column. You can determine the order in which they appear. Starting with the lowest numbered attribute, the attributes appear from top to bottom. MultiText attributes span the width of the tab. Header attributes, which appear on **Page Two** and **Page Three** tabs only, also span the width of the tab. The following figure shows an example of how attributes appear on a form tab in Web Client.



In Java Client, attributes appear on the tab in rows and columns, according to the attribute order, lowest number first, left to right, then top to bottom. The number of columns changes as the user resizes the object window. No matter how many columns are in an object window, the attributes are always displayed by attribute order. Header attributes (Page Two and Page Three) span the width of the object window.

To modify the order of attributes on a form tab:

1. On the **User Interface Tabs** tab of the setup window for the class, locate the tab you want, and double-click it to display the setup window for that tab.
For example, double-click **Change Orders**, then double-click **Cover Page** to display the setup window for the change order **Cover Page** tab.
2. Click the **Attributes** tab.

3. Click the **Order visible attributes** button. The Define Attribute Order dialog box appears. All the object tab attributes with Visible property set to Yes appear in the list of attributes.
4. Click an attribute name to highlight it.
5. Click the up arrow to move the highlighted attribute up one position in the list. Click the down arrow to move the highlighted attribute down one position in the list.
6. Continue highlighting attributes and moving them up or down in the list until they are in the order you want.
7. When you are finished, click **Save**.

The attributes appear on the **Attributes** setup tab in the order you specified.

To verify that the order was changed, open an object in Java Client or Web Client where the tab appears. Click the tab to view the form or table and confirm the change.

Modifying Attribute Order on a Table Tab

In both Web and Java Clients, on a table-type tab, the attributes appear in a table; the attribute names are table headings for each column. You modify the order of attributes on a table tab the same way you do on a form tab.

Designing a Page Two or Page Three Tab

You can create extra tabs for Java Client. When enabled, these tabs are always displayed behind the first or second tab, and are named Page Two or Page Three by default. You can change these tab names to something more specific if necessary.

Note In Web Client, Page Two and Page Three information is displayed below the Cover Page information on the Cover Page tab. Users scroll down to see this information.

While Page Two tabs record supplemental information for an entire class of objects, such as the Change Orders class, Page Three tabs record information specific to individual subclasses, such as ECOs or Capacitors.

The Page Two tab's built-in Create User feature is described next.

About the Page Two Create User Attribute

Each **Page Two** tab has a Create User attribute that allows users with a Create privilege, but not a Read privilege, to create an object. Users with their name in the Create User list can then also open and read any pending or preliminary objects they have created.

To activate the Create User feature for a class of objects, such as Change Orders, you must first make the Create User attribute visible on the **Page Two** tab for that class. Then the attribute can be used both to display the name of the Create User on the tab, and to create criteria in the **Criteria** node.

For example, if you set the subclass criteria for a read privilege to Create User Equal To \$USER, then the privilege mask will be enabled when the current user is also the user who created the object. For more information about Create User criteria, see [Applying Create User Criteria](#) on page 250.

Guidelines for Designing Page Two and Page Three Tabs

There are two stages for designing a **Page Two** or **Page Three** tab. This section outlines the process for these two stages, and then gives you detailed instructions for each step in the process. Also, see [Before You Begin](#) on page 117.

The following is a summary of the two stages in designing a **Page Two** or **Page Three** tab.

Stage I: Preparing Page Two or Page Three Attributes

1. Make the tab visible and name the tab.
2. Make the attributes visible, and name them.
3. Assign length properties to text attributes.
4. Assign other attribute properties, such as drop-down lists or defaults.

Stage II: Setting Up the Tab

Set the attribute order.

The following sections provide detailed instructions for creating a **Page Two** or **Page Three** tab.

Stage I: Preparing Page Two or Page Three Attributes

The first stage in designing a **Page Two** or **Page Three** tab is to:

- Make the tab visible and name the tab. This work is done from the **Page Two** or **Page Three General Information** setup tab. For instructions, see [Showing, Hiding, or Renaming a Tab](#) on page 66.
- Select the attributes that you want to appear on the tab, make them visible, and give them names that describe the fields and their use. This work is done from **Page Two** or **Page Three Attributes** setup tab.

Note	Attribute names are the criteria for Java Client or Web Client searches. By making attribute names both specific and unique, you increase the efficiency of Agile PLM client searches. If you modify the name of an attribute once a system is in production, you may affect existing searches.
-------------	---

Before You Begin

Consider the following details before designing a new tab.

- Do you want to create an extra tab for an entire Agile PLM class (**Page Two**), or a tab that's specific to a particular subclass (**Page Three**)?
If you are creating a **Page Three** tab, remember that you also need to create privilege masks that enable users to modify attributes for the specific subclass.
- Do you plan to use Agile ChangeCAST to transfer information to an ERP system? If so, the information must be on a **Page Two** tab. Page Three data cannot be transferred using ChangeCAST.
- What do you want to name the tab?
- Which attributes will appear on the tab?
- What are the properties for each attribute, including name, drop-down list values, default values, the format for text fields, and so on. See [Defining Attribute Properties](#) on page 79.
- Where will each field be placed (located under a heading) on the tab in Web Client?
- What are the length requirements (in characters) for each text field?
- What will the tab order be, that is, the sequence in which fields are activated when a user presses the Tab key? (This is determined by the attribute order.)

For more information about attributes, see [Recognizing Attribute Types](#) on page 78.

To make the tab visible, and configure the attributes you want to use:

1. Make the tab visible and name the tab. For instructions, see [Showing, Hiding, or Renaming a Tab](#) on page 66.
2. Locate the attributes you want, and double-click them to open the setup window.
For detailed instructions, see [Modifying Attributes](#) on page 84. For **Page Two** tab attributes, double-click the class, for example, Change Orders. For **Page Three** tab attributes, double-click the subclass, for example, ECO.
3. Enter a new name for each attribute.
4. Make the attributes visible; select Yes in the **Visible** drop-down list.
5. Set the appropriate properties for each attribute type (see [Defining Attribute Properties](#) on page 79).
 - For List and MultiList attributes, define the list selections (see [Configuring Lists](#) on page 99).
 - For Text and MultiText attributes, set the **MaxLength** and **Include Characters** properties.
 - For Numeric attributes, set the **MinValue**, **MaxValue**, and **Scale** properties.
 - For Heading attributes, enter a heading **Name** (note: headings are used in Web Client only).
 - For Date attributes, set the **Default Value** date using the calendar utility.
 - For Money attributes, set the **Default Value**.

6. If appropriate, set a default value for each attribute. (See [Setting Default Values](#) on page 85.)
7. When you are finished configuring the attributes, click **Save**.

Once you have completely defined the attributes for your **Page Two** or **Page Three** tab on the **Attributes** tab, you define the attribute order to set up the physical appearance of the tab.

Stage II: Setting Up the Tab

After selecting the attributes that will appear on the **Page Two** or **Page Three** tab and establishing their properties, you need to arrange the fields on the tab. You do this by using the **Order visible attributes** button on the **Attributes** setup tab.

Note For detailed information about setting attribute order, see [Modifying Attribute Order on a Form Tab](#) on page 67.

To set up the order the attributes appear on the tab:

1. Click the **Order visible attributes** button. The Define Attribute Order dialog box appears.
2. Click an attribute name to highlight it.
3. Click the up arrow to move the highlighted attribute up one position in the list. Click the down arrow to move the highlighted attribute down one position in the list.
4. Continue highlighting attributes and moving them up or down in the list until they are in the order you want.
5. When you are finished, click **Save**.

Field Tab Order

The *tab order* refers to the sequence in which the fields in an Agile PLM client **Page Two** or **Page Three** tab is activated when a user presses the Tab key.

The field tab order is determined by the attribute order, as described above.

Using Heading Attributes

Java Client displays actual tabs for **Page Two** and **Page Three** tabs. However, Web Client displays the Page Two and Page Three information on the first object tab (for example, **Cover Page**, **Title Block**, or **General Info** tab). When viewing an object with Page Two and Page Three information, the user scrolls down to see that information. For example, the Page Two information is displayed below the Cover Page information. The Page Three information is displayed below the Page Two information.


To make the additional information on the first tab easier to understand in Web Client, each Page Two and Page Three tab has 10 Heading attributes. Make Heading attributes visible and give them a meaningful name. Then, position them on the attribute order list so they describe the group of attributes that follow them.

For example, a Page Two attribute order list might be set as follows:

Attribute order list	Type of attribute
Page Two	Heading01

Attribute order list	Type of attribute
Create User	CreateUser
Date Created	Date01
Component Properties	Heading02
Resistance	Text01
Material	List01
Notes	Multitext10

The attributes appear in Web Client, following the Cover Page information, in the format shown in the figure below. In Java Client, the Page Two and Page Three attributes (including Heading attributes) are displayed on the **Page Two** and **Page Three** tabs.



Removing a Page Two or Page Three Tab

You may effectively remove a **Page Two** or **Page Three** tab from Java Client or Web Client by changing its Visible property to No. You must make this change in the **Tabs** node as well as in each of the Page Two attributes that were defined for the tab. If you do not change an attribute's Visible property to No, it continues to appear in Java Client or Web Client Search folders.

About Attributes, Flex Fields, and Read-Through Fields

If you have been reading this chapter sequentially, the term “attributes” is already familiar. Before going into the detailed discussion of [Defining Attributes](#) on page 77, this section introduces two special kinds of attributes: user-defined flex fields and read-through attributes.

When users open an object in Agile PLM clients, they see a tabbed window with fields. These fields are called attributes. From the **Classes** node, you define how these attributes appear for each Agile PLM class.

The individual fields that you define for each Agile PLM class appear on the tabs for all subclasses within that class. For example, the part categories that you define for the Parts class become the part categories for its subclasses, such as Capacitors, Resistors, and Diodes. In addition, if you enable an extra tab called a **Page Two** tab for an Agile PLM class, the tab and its attributes also appear for each subclass within the class.

Each subclass also has its own setup window for the **Page Three** tab where you can define the fields that are specific to the subclass, and will appear only on the **Page Three** tab for that subclass.

User-Defined Flex Fields

You can create an infinite number of attributes in any class or subclass. These are called “user-defined flex fields.” They are distinct from the predefined flex fields installed with Agile PLM.

User-defined flex fields can be created only on **Page Two** and **Page Three** tabs. As such, any user-defined flex field is specific to a class (**Page Two**) or to a subclass (**Page Three**).

Note User-defined flex fields are specific to a class and therefore require class-specific privileges. Base class privileges (such as Read Items or Modify Preliminary Items) don't apply to class attributes. The subject of roles and privileges in Agile PLM is broad, but you may want to refer to a small tutorial, [Building and Testing Attributes, Read/Modify Privileges, and Roles](#) on page 204.

To create a user-defined flex field in a class:

1. Under **Data Settings**, double-click **Classes**. The Classes window appears.
2. As an example, double-click the **Change Orders** class, then click the **User Interface Tabs** tab.
3. Double-click Page Two, then click the **Attributes: Page Two** tab.
4. Click the **New** icon. The New Attribute dialog appears.
5. Type in a name and API name for the new attribute. Also select an attribute type from the dropdown list. Click **OK**.

Note An attribute name cannot contain a colon (:), a semicolon (;), or an equal sign (=).

6. The new attribute object appears. This user-defined flex field will be present in all objects created in the **Change Orders** class, for this example.

You may now fill in the various supporting fields, such as Description, Visible, Default Value,

Required, and Available for Subscribe.

To create a user-defined flex field in a subclass:

1. Under **Data Settings**, double-click **Classes**. The Classes window appears.
2. As an example, double-click the **ECO** subclass, then click the **User Interface Tabs** tab.
3. Double-click Page Three, then click the **Attributes: Page Three** tab.
4. Click the **New** icon. The New Attribute dialog appears.
5. Type in a name and API name for the new attribute. Also select an attribute type from the dropdown list. Click **OK**.

Note An attribute name cannot contain a colon (:), a semicolon (;), or an equal sign (=).

6. The new attribute object appears. This user-defined flex field will be present in all objects created in the **ECO** subclass, for this example.

You may now fill in the various supporting fields, such as Description, Visible, Default Value, Required, and Available for Subscribe.

Where User-Defined Flex Fields can be Used

User-defined flex fields are more limited than predefined flex fields. They are supported in the following places in Agile PLM:

Where user-defined flex fields are fully supported:

- **Advanced Search**
 - User-defined flex fields can be used as a query condition
 - ... can be used in display/output of search results
 - ... can be used as an attribute for sorting of search results
- **Roles and Privileges**
 - User-defined flex fields can be used as an AppliedTo attribute in Read privilege
 - ... can be used as an AppliedTo attribute in Modify privilege
- **Workflow**
 - User-defined flex fields can be used in entry required fields
 - ... can be used in exit required fields
- **Subscription**
 - User-defined flex fields can be made available for subscription when this field changes or is updated
- **Out-of-box Standard Reports**
 - For reports where user can optionally select **Page Two** attributes to display in report results, user-defined flex fields can also be selected.
- **Custom Reports**

- User-defined flex fields can be used as a query condition in building a custom report
- ... can be used in display/output of report results
- ... can be used as an attribute for sorting and grouping of report results
- **Agile Integration Service**
 - User-defined flex fields can be used as part of AIS
- **Agile Content Service**
 - User-defined flex fields can be used as part of CTO.
- **Export**
 - User-defined flex fields can be exported into supported output formats

Where user-defined flex fields are partially supported:

- **SDK**
 - User-defined flex fields supports Set (update) the property and Get (retrieve) the property, but does not support Create.

Where User-Defined Flex Fields cannot be Used

User-defined flex fields are not supported in the following places within the Agile system:

- **Criteria**
 - User-defined flex fields cannot be used as a value in defining Criteria
- **DataLoad**
 - User-defined flex fields cannot be loaded via DataLoad
- **Notification**
 - User-defined flex fields cannot be used as a data tag that can be sent in subject or body of the notification
- **ACS**
 - User-defined flex fields cannot be used for ATO, since they are autogenerated and modification is not allowed in class settings

Read-Through Fields

Some fields on some tabs are able to display pertinent information about a related object. These fields are referred to as “read-through” fields. The data that is displayed in a read-through field is a read-only copy of attribute data from a different object that is related to the currently viewed object. If a tab has read-through fields, you can enable or disable them as needed.

Some tabs with read-through fields are not editable (for example, the item object **Changes** tab). However, a few editable tabs include both types of attributes: editable and read-through (for example, the item object **Manufacturers** tab). Read-through fields cannot be edited on the tab because they are read-only copies. However, if the original attribute is modified, the read-only copy in a read-through field will reflect those modifications.

In Administrator, on the <Tab Name>:Attributes tab of the setup window of object tabs that include both editable fields and read-through fields, read-through fields include the name of the related object in their names. For example, on the item object **Manufacturers** tab, attributes with names that begin with “Mfr” or “Mfr. Part” are read-through fields from the Manufacturer and Manufacturer Parts objects, for example, Mfr. Name and Mfr. Part Notes.

Read-Through Fields Made Consistent in Items and Changes

Oracle Agile PLM makes it also possible for the administrator to consistently define **Page One** and **Page Two** fields as read-through fields, as follows:

- All Item **P1 / P2** fields can be defined as read-through fields on the **Item > BOM** table (excluding **Page Two** heading fields)
- All Item **P1 / P2** fields can be defined as read-through fields on the **Item > Where Used** table (excluding **Page Two** heading fields)
- Most Item **P1 / P2** fields can be defined as read-through fields on the associated **Change > Affected Items** table (excluding **Page Two** heading fields and these special handling of Rev-related fields: REV.COMPLIANCY_CALC_DATE [only on ECO and MCO], REV.COMPLIANCY [already on ECO and MCO], and REV.INCORP_DATE [ECO only for the future revision, MCO for the revision it applies to]).
- This does *not* include any new (user-generated) **P2** multilist fields.

Read-Through Fields on the BOM and Manufacturers Tabs

The Item **BOM** tab and the Item **Manufacturers** tab include both editable fields and read-through fields.

Editable fields on an item’s **BOM** tab describe the relationship between it and the items on its BOM, for example, Quantity, Find Number, Reference Designators. Read-through fields on the **BOM** tab allow you to display additional information about the items listed on the **BOM** tab, for example, Page Two data of the BOM items.

Editable fields on an item’s **Manufacturers** tab define the relationship between it and its manufacturer parts, for example, Preferred Status and Reference Notes. Read-through fields on the **Manufacturers** tab allow you to display additional information about the Manufacturer (for example, the manufacturer’s address), or the Manufacturer Part (for example, Page Two data of the Manufacturer Parts).

Important Like all read-through fields, the read-through fields on the **BOM** tab and the **Manufacturers** tab cannot be edited on those tables. Because these read-through cannot be edited on the **BOM** tab and **Manufacturers** tab, they also cannot be redlined from the **Redline BOM** tab or the **Redline Manufacturers** tab.

For your reference, the item object **BOM** tab and item object **Manufacturers** tab attributes which can be edited and, therefore, redlined are listed in the table below.

Note A user’s assigned roles and privileges also determine which specific fields he can edit or redline.

Item object BOM table fields which can be edited or redlined	Item object Manufacturers table fields which can be edited or redlined
BOM Date01 – BOM Date05 BOM Description BOM List01 – BOM List05 BOM MultiText30, BOM MultiText31 BOM Notes BOM Numeric01 – BOM Numeric05 BOM Text01 – BOM Text05 Find Num Item Number Qty Ref Des	AML Split (%) Mfr. Name Mfr. Part Number Mfr. Tab Date01 – Mfr. Tab Date05 Mfr. Tab List01 – Mfr. Tab List05 Mfr. Tab MultiList01 – Mfr. Tab MultiList03 Mfr. Tab MultiText30, Mfr. Tab MultiText31 Mfr. Tab Numeric01 – Mfr. Tab Numeric05 Mfr. Tab Text01 – Mfr. Tab Text05 Preferred Status Reference Notes

Defining Attributes

Attributes are the fields that appear on Agile PLM client tabs. You can define these attributes by configuring their properties.

Each object tab has its own setup window. To display the tab setup window you want, use the guidelines in the following table.

Type of attribute or property	Setup activity	Do this
Class-specific attribute (all tabs except Page Three)	Define attributes for: Cover Page Title Block General Information Page Two Affected Items Workflow Relationships Attachments History Changes BOM Manufacturers Where Used Sites Escalations Selected Objects Where Sent	In the Classes window: <ul style="list-style-type: none"> ▫ Double-click a class name. ▫ Click User Interface Tabs. ▫ Double-click the tab you want to configure.

Type of attribute or property	Setup activity	Do this
Subclass properties	Define properties, for example, for Name, Description, Number Source, AutoNumber Required, Site-specific BOM, and so forth	In the Classes window: <ul style="list-style-type: none"> Double-click a subclass name. Set properties on General Information tab.
Subclass-specific attribute (Page Three tab only)	Define attributes for: Page Three	In the Classes window: <ul style="list-style-type: none"> Double-click a subclass name. Choose User Interface Tabs > Page Three tab.

For example, to define attributes for the Affected Items tab of the Change Orders class:

1. Under **Data Settings**, double-click **Classes**. The Classes window appears.
2. Double-click **Change Orders Class**.
3. Click the **User Interface Tabs** tab.
4. Double-click **Affected Items**. The Affected Items tabbed setup window appears.

Recognizing Attribute Types

An attribute's type indicates how it is used in Agile PLM. For example, a Text attribute is used for entering text into a field on a Java Client or Web Client tab. The types of attributes used in Agile PLM are listed in the table below.

Type	What to Enter in the Field
Date	Enter date and time, or select date and time from a pop-up calendar.
Heading	Displays a heading above a group of attributes. Allows the user to identify a group of associated attributes on these tabs. Heading attributes are available on Page Two and Page Three . They are also available on the General Information and Preferences tabs of User classes.
Icon	Read-only attribute type. Used to display icons in tables (for example, BOM table, search results table) that indicate, for example, the object type, that the object has attachments, that the object has a manufacturer, or that the object has a pending change.
List	Select one item from a list. Select one item from a cascading list.
Money	Enter a monetary amount.
MultiList	Select one or more items from a multiple-selection list. The list can be a cascading list. Note: There is no limit to the number of list entries in a multi-list field and the number of possible multi-list fields on Items P2 is 15.
MultiText	Enter a block of text (up to 4,000 characters) that wraps across multiple lines.
Numeric	Enter a numeric value.

Type	What to Enter in the Field
Text	Enter a single line of text; the allowable length varies, but generally it is up to 50 characters.
The Agile PLM administrator can set default values (such as the current date, or current user) to automatically appear in a field when new objects are created. See Setting Default Values on page 85.	

Defining Attribute Properties

The following table lists the attribute properties, the settings available for these properties, and how the settings are applied in Agile PLM. It also indicates the attribute types each property can be applied to.

- Note** The “Required” property (found near the end of this table) is important to understand, as it provides a visual cue for users to attend to that attribute when creating a business object in that class or subclass. Also, there is a corner case involving required fields detailed in [An Exception Involving Required Fields in Object Modification](#) on page 83.
- Note** Please note that a field that is “required to fulfill creation” of an object, this idea is not the same thing as “required fields” that are found in Agile Workflows.

Property	Attribute type	Setting	Application in Agile PLM
Name	All	Supplied by administrator	<p>The name of the field as you want it to be displayed for users, limited to 40 characters.</p> <p>Although all characters are supported within Agile PLM, and should not create issues within Agile's clients, it is recommended that you avoid using the following characters when renaming or creating attributes, due to issues that could potentially arise in integrations or custom applications written on the SDK.</p> <p>, comma . period (dot) : colon ; semicolon = equal sign</p>
API Name	All	System-generated at object creation	Unique systemwide identifier for objects and can be autogenerated. You can specify an API name, but internal consistency is enhanced by accepting the system-generated name.
*Type	All	N/A	<i>Not configurable by the Agile PLM administrator.</i> Indicates the type of attribute: date, list, multilist, text, multitext, numeric, image, or heading.
Visible	All	Yes	Makes the attribute visible in Agile PLM clients. Users will see this attribute when they create objects in this class or subclass.

Property	Attribute type	Setting	Application in Agile PLM
		No	Keeps the attribute hidden in Agile PLM clients. Users will not see this attribute when they create objects in this class or subclass. Note that all Item Title Block fields can be disabled.
List	List MultiList	Supplied by administrator	Selections to appear in the drop-down list for users to choose from. The default value must appear among the selections entered here. For list attributes whose selections are defined elsewhere, this property reads (List) and the property is not editable on the attribute setup window. For example, the Lifecycle Phase attribute selections are those that are defined on the Lifecycle Phases node. List entries are limited to 255 characters each.
Default Value	All	Supplied by administrator	The default value to display when a new object is created. For lists and multilists, the default value must be one of the values in the selection list (see Setting Default Values for Lists on page 101). For some fields, you can use a default variable. For MultiText attributes, the administrator is constrained to 510 characters of default text, despite the Max (System) Length value of 4,000. Web and Java client users are not constrained in this field in business objects.
Enable for Search Criteria	All	Generally “No” but can be set to Yes by administrator	Permits (Yes) or prevents (No) the attribute from being added as a criteria for a Parametric search. (Parametric searches are documented in <i>Getting Started with Agile PLM</i> .)
MaxLength	Text MultiText	Supplied by administrator	Sets the maximum number of bytes that can be entered in the field (spaces = 1 byte; carriage returns = 2 bytes). Valid settings range from 0 to the maximum allowed for that attribute (see the attribute’s Max (System) Length property). Generally speaking, 1 character = 1 byte; however, some Agile installations are localized with Chinese or Japanese characters that can use 2 or 3 bytes per character. This must be factored in when setting the value of this property in relation to Max (System) Length value. Because many attributes appear in many areas of Agile PLM, and the MaxLength can be set independently for specific attributes, issues can develop if there is too much range of MaxLengths for similar attributes. For example, a part number may appear on the Title Block of the part, the BOM of (same or other) parts, and the

Property	Attribute type	Setting	Application in Agile PLM
			<p>Affected Items of changes. It is best to set the MaxLengths of such similar attributes to a standard value.</p> <p>When setting MaxLengths, consider field length limitations of other applications used by your company to which Agile PLM data is exported.</p>
*Max (System) Length	Text MultiText	N/A	<p><i>Not configurable by the Agile PLM administrator.</i></p> <p>Designates the maximum length of the data field in bytes, and represents the maximum number of bytes allowed in the field by Agile PLM clients. An attribute's Max (System) Length value cannot be exceeded by its MaxLength value.</p>
Include Characters	Text Multitext	Select from list	This setting determines whether spaces are allowed in the field and which types of alphabetic and numeric characters are allowed. Select from the list of character sets defined on your Agile PLM system. For more information, see Character Sets on page 91.
Min Value	Numeric	Supplied by administrator	The minimum value for the numeric field.
Max Value	Numeric	Supplied by administrator	The maximum value for the numeric field; must be greater than or equal to zero (0).
* Order	All	N/A	This number indicates the order in which the attribute field appears on the table or form. It is an Agile system-generated number greater than 0. The Agile system generates this number when you use the Order visible attributes button to arrange the attributes.

Property	Attribute type	Setting	Application in Agile PLM
Site-Specific Field		Select from list	<p>Common = this attribute inherits its value from the global value.</p> <p>Site-Specific = the value of this attribute is independent from the global value.</p> <p>This property does not apply to all attributes. If it does not apply, it is set to N/A and it is not editable.</p> <p>This property is not editable for all attributes where it does apply. In those cases, the property has a default value of either Common or Site-Specific and it cannot be edited.</p> <p>For examples, view the attribute setup for the Affected Items tab of the Change Orders class.</p>
Height	MultiText	Supplied by administrator	Determines the number of lines in the text area that are displayed when in edit mode. (In Web Client, the text area displays 4 lines.)
Scale	Numeric Money	Supplied by administrator	The number of digits after the decimal point in a numeric field. This setting must be greater than or equal to zero (0).
*Attribute	All	N/A	<i>Not configurable by the Agile PLM administrator.</i> Lists the database attribute name for the selected node. Since the Name property gives the attribute name as it will appear to the Agile PLM user, the Attribute and Name properties are often different.
*Base ID	All	N/A	<i>Not configurable by the Agile administrator.</i> Lists the original system ID for the attribute before it was modified in any way.
Input Width	MultiText List (Web Client) MultiList (Web Client)		<p>Controls the display width of attributes. Settings are Medium and Long.</p> <p>Note For List attributes there is an additional setting of Small available.</p>

Property	Attribute type	Setting	Application in Agile PLM
Input Height	MultiText		Controls the display height of MultiText attributes. Settings are numeric integers ranging from 3 to 15.
Required	All	Yes	<p>The field appears to the user in bold font, which is a visual cue that the field should be populated. If an attribute that has Required set to Yes is not populated during the Create New process (in Web Client), or it is emptied during an Edit and the user tries to Save (in both clients), the user will be prompted to fill the field, and the procedure will not complete.</p> <p>You can set Heading attributes to be Required. (There was an issue in Classes > User Interface Tabs > Page Two > Attributes:Page Two > Heading01 attribute that the field Required was missing.)</p> <p>See An Exception Involving Required Fields in Object Modification on page 83.</p>
		No	The field does not appear to the user in bold font , and it does not stop the Create New or Edit/Save process if it is not populated.
Available for Subscribe	All	Yes/No	Determines whether or not this attribute can be subscribed to by a user (who has sufficient privileges). Subscription is documented in <i>Getting Started with Agile PLM</i> , Chapter 5, Working with Objects.
*The Agile PLM administrator cannot change these properties.			
The file type of an attached file is determined by the characters following the last period in a file name. Therefore, users should not use filenames ending with a period (.).			

An Exception Involving Required Fields in Object Modification

If you modify a business object and you select a different subclass as part of the modification, you receive this warning: **“You are changing the subclass of the object. Do you want to continue using the same object name or number?”** This warning does not warn you of another risk, that the object’s original subclass and the subclass to which the object is being assigned may have differing required fields. A field that is set to be required in the “new” subclass may not be required in the “original” subclass, but the system does not check for “new” required fields, nor does it warn you of this possible

discrepancy.

Image Attributes

To include an image attribute on a table, set its Visible property to Yes. The image attribute's Name property identifies which type of icon the image attribute displays. The name does not appear to the end user; you do not need to modify it.

To determine in which table column the image will appear, see [Modifying Attribute Order on a Form Tab](#) on page 67.

Configuring Attributes

A property may be configurable for one attribute and not for another. For example, you cannot edit the Name property of the lifecycle phase attribute on the **Title Block** tab, but you can edit the Name property of the item lifecycle phase on the **BOM** tab.

As the Agile PLM administrator, you can easily change a configurable property. For example, if you decide the maximum allowable length for the change order number should be 15 characters instead of 30 characters, you can change the MaxLength property setting on the Change Orders **Cover Page** tab.



Note	Because many attributes appear in many areas of Agile PLM, and the MaxLength can be set independently for specific attributes, issues can develop if there is too much range of MaxLengths for similar attributes. For example, a part number may appear on the Title Block of the part, the BOM of (same or other) parts, and the Affected Items of changes. It is best to set the MaxLengths of such similar attributes to a standard value.
-------------	--

Modifying Attributes

To modify an attribute property:

1. Under **Data Settings**, double-click **Classes**. The Classes window appears.
2. To modify any class tab attribute, double-click the class name.
 - a. For example, to modify the **Affected Items** tab attributes for change orders, double-click Change Orders, then select the **User Interface Tabs** tab. All the Change Orders class tabs are listed.
 - b. Click **Affected Items**. The Classes Tab setup window appears.
 - c. Select the **Attributes:Affected Items** tab. All the fields for that tab are listed.
3. To modify a **Page Three** tab attribute for a specific subclass, double-click the name of the subclass listed under the class name.
 - a. For example, double-click ECO under Change Orders class, then select the **User Interface Tabs** tab. All the ECO subclass class tabs are listed.
 - b. Double-click **Page Three**. The Class Tabs setup window appears.
 - c. Select the **Attributes:Page Three** tab. All the fields for that tab are listed.
4. Double-click the attributes you want to modify.
5. Modify the attribute properties. Depending on the type of property, use one of the following

methods:

- Enter text.
- Select a value from a list.
- Click  to open a dialog box.
- For date attribute default values, click  to select a specific date, or use a variable. See [Default Value Variables](#) on page 15.

6. When you have finished your modifications, click **Save**.

Matching the Properties of Attributes Common to Several Tabs

When the same attribute appears on several tabs, you must establish the same properties for it everywhere it appears.

For example, an item's Number attribute appears on the item's **Title Block** (that is, its "**Page One**" tab), the item's **BOM** tab (Item Number attribute), and the **Affected Items** tab of any associated changes (Item Number attribute). You must establish identical properties for this attribute in all three locations.

For example, in an item's **Title Block.Number** field, if you set its Include Characters property to All, you should also set the item's **BOM.Item Number.Include Characters** property to All, and set [associated change].**Affected Items.Item Number.Include Characters** property to All. If you do not, when you try to add an affected item, for example, Agile PLM clients prevent you from adding the affected item, and return an error message.

Setting proper attributes allows **Page Two** and **Page Three** data to be copied properly when using **SaveAs** to create a new object (for instance, a project number field on **Pg2** of both ECOs and MCOs), and allows you to display information from an item's **Pg2** on its **BOM** table or an associated change's **Affected Items** tab (for instance, a Unit of Measure field).

Regarding the **SaveAs** method of object creation: if a subclass has Required fields set up (by the administrator) and the user does a **SaveAs** but there is a type violation in the source object on one of the required fields, **SaveAs** will complete with the value still copied over to the source. Previously in this case, the user would encounter an error during **SaveAs** saying that a violation occurred on certain attributes, and **SaveAs** cannot be completed.

Setting Default Values

You can set default values to appear for attributes.

To change a default value setting:

1. Locate the attribute you want, and double-click it to open the setup window.
(For detailed instructions, see [Modifying Attributes](#) on page 84.)
2. In the **DefaultValue** field, enter the default value you want. Depending on the type of attribute, enter a variable (see [Default Value Variables](#) on page 15), enter text, select from a drop-down list, or select a date.
3. When you have finished your modifications, click **Save**.

The new default value appears in the Agile PLM client field when a new object is created.

Showing or Hiding an Attribute on a Tab

Many attributes can be either hidden or displayed on a tab. For example, you can either show or hide the fields on the **Pending Changes** tab, and the attributes on the **Page Two** tab are hidden until you need to use them.

To show or hide an attribute on a tab:

1. Locate the attribute you want and double-click it.
(For detailed instructions, see [Modifying Attributes](#) on page 84.)
2. In the **Visible** field for the attribute, select Yes to make the attribute visible. To hide the attribute, select No.
3. When you have finished your modifications, click **Save**.

The attribute is now either visible or hidden on the tab. To view the modifications, open the object in Java Client or Web Client where the attribute appears.

Editing a Field Label or Table Column Name

You can change the field label or the heading of a table column by editing the attribute's Name property.

For example, attributes on the **Title Block** tab of Parts class objects are displayed as labeled fields. You can modify the labels that appear by editing the attributes' Name properties. Fields on the **Affected Items** tab of Change Orders class objects are displayed in a table; the table column heading, or field, is the attribute name. You can modify the table column heading by editing the attribute's Name property.

Note The Lifecycle Phase attribute name on the Parts and Documents class **Title Block** tabs cannot be edited.

To edit a field label or a column name in a table:

1. Locate the attribute you want and double-click it.
(For detailed instructions, see [Modifying Attributes](#) on page 84.)
2. In the **Name** field, highlight the text you want to edit and enter a new name.
3. When you finish all the attribute modifications, click **Save**.

To verify that the name was changed, open an object in Java Client or Web Client where the table appears. Click the tab to view the field or table and confirm the modification.

Using Custom Icons for Subclasses

Each of the predefined subclasses provided with Agile PLM has a default icon associated with it. The subclass icons appear (in Java Client and Web Client) to visually differentiate the various types of objects. You can replace some or all of these icons at any time.

To replace the default subclass icon with a custom icon:

1. Open the subclass and, on the **General Information** tab, enter a filename in the **Icon** property for that subclass.

For Documents and Parts subclasses, there is an additional property called **Icon for Assembly**. This is the icon image that is used when the object represents an assembly.

For both the **Icon** and **Icon for Assembly** properties, fill in only the graphic filename (including extension), for example, **electrical.gif**.

2. You must place the custom graphic in two locations on the proxy server, one for Web Client and one for Java Client. The system finds the graphic depending on the client being used.

- **Web Client** – <webserver_root>\PLMContent\images
- **Java Client** – <webserver_root>\JavaClient\lib\images\custom.jar

Note For Java Client, custom icons must be added to the custom.jar file. For instructions on how to update a JAR file, refer to Sun's documentation on the JAR utility. An online tutorial on the JAR utility is available at <http://java.sun.com/docs/books/tutorial/jar/>. You can also use many Zip-compatible utilities, such as WinZip, to update a JAR file.

3. The Agile Application Server must be restarted for the new icons to take effect.

Quick Access to Objects and Files

You can generate quick access URLs that provide direct pointers to either Agile objects or to Agile attachment files.

These quick access URLs can be pasted into other applications or files such as spreadsheet files, word processing files, a company Intranet web page or WIKI page, or into an email.

For information about quick access to Agile objects using quick access URLs, see:

- Agile-Generated Quick Access Object URLs
- Formats for User-Generated Smart Object URLs
- Using Quick Access Object URLs

For information about quick access to attachment files using attachment quick access URLs, see:

- [Generating Attachment Quick Access URLs](#) on page 407

Agile-Generated Quick Access Object URLs

From Web Client, you can generate Agile PLM object quick access URLs from the Web Client **Actions** menu.

To generate an Agile PLM object quick access URL:

1. Login to Agile PLM Web Client and open the desired object.

2. In the **Actions** menu, choose **Copy URL to Clipboard**.
3. The URL is copied to your clip board. You can then paste it into another application or file, such as a word processing file, a spreadsheet file, or an email.

Formats for User-Generated Smart Object URLs

The Agile Smart Object URL feature is designed to enable effective collaboration through email, spreadsheets, documents, WIKIs, and so forth. Users or automated tools can generate smart readable URLs that point to a specific object in Agile. By using the following format, a user does not need to log into Agile to generate the object URL. Automated tools can also use this format to generate object URLs.

Smart Object URLs can be used for objects available from Web Client.

Smart Object URL Format

URLs for pointing to Agile objects use the following format:

<http://server:port/VirtualPath/object/ObjectType/ObjectName>

The following table defines the Smart Object URL parameters:

Parameter	Description
<a href="http://server:port/<VirtualPath>/object/<ObjectType>/<ObjectName>">http://server:port/<VirtualPath>/object/<ObjectType>/<ObjectName>	
server port VirtualPath	Server, port, and VirtualPath identify the Agile PLM instance.
object	The text "object" indicates to Agile that the URL is an object URL.
ObjectType	ObjectType refers to the subclass (type) of object, for example, ECO, Part, Manufacturer, File Folder, Program, Project, Activity, or Discussion.
ObjectName	ObjectName refers to the unique identifier for the object. Depending on the object class, the unique identifier is either an object number or a name. Note Manufacturer Parts are a special class of objects that are uniquely identified by two parameters: a Manufacturer Name and a Manufacturer Part Number. Therefore, a URL referring to a specific Manufacturer Part uses the following format: http://server:port/VirtualPath/object/ObjectType/MfrName/MfrPartNumber

Agile PLM identifies and handles special tags (such as %20) added to URLs to handle special characters (such as spaces and other special characters such as asterisk "*") in an object's unique identifier. For example, the URL

<http://server:port/VirtualPath/object/Manufacturer/Philips%20Semiconductor>

resolves to the manufacturer "Philips Semiconductor".

Using Quick Access Object URLs

When a user clicks a Quick Access Object URL, the user actions are the same whether the URL is an Agile-generated quick access URL or a user-generated Smart Object URL:

1. The user clicks the URL and the Agile PLM login screen is displayed in a browser window.
2. The user enters her login information.
3. Upon successful login, Agile PLM searches for the object specified in the link.

(If the object is not found, Agile PLM displays an error and returns to the user's Home page.)

When the object is found, Agile PLM verifies that the user has the appropriate privileges to read the object and displays the object's first tab, for example, the **Title Page**.

Character Sets

This chapter includes the following:

▪ Available Character Sets	91
▪ Creating a Character Set	92
▪ Modifying a Character Set	93

This chapter provides information about how to customize and configure character sets.

Available Character Sets

The **Character Sets** node lets you view and create sets of valid characters in Agile PLM.

Character sets are lists of valid characters that are used to manage the Include Characters property of Text and MultiText attributes. You can create and delete character sets. Any language supported by Agile PLM can be supported by character sets.

The following table lists character sets provided with Agile PLM. They are all enabled by default and cannot be modified.

Name	Description
All	All valid characters
All Characters with space and Lower Case	Only lowercase characters, but including the space character
All Characters with space and Mixed Case	All upper- and lowercase characters, and including the space character
All Characters with space and Upper Case	Only uppercase characters, but including the space character
All Characters without space and Lower Case	Only lowercase characters and no space character
All Characters without space and Mixed Case	All upper- and lowercase characters and no space character
All Characters without space and Upper Case	Only uppercase characters and no space character
Alpha All	Upper- and lowercase alphabet only
Alpha All & Space	Same as Alpha All plus space character
Alpha Lower Case	Lowercase alphabet only

Name	Description
Alpha Lower Case & Space	Same as Alpha Lower Case plus space character
Alpha Upper Case	Uppercase alphabet only
Alpha Upper Case & Space	Same as Alpha Upper Case plus space character
AlphaNumeric All	Upper- and lowercase alphabet and numbers
AlphaNumeric All& Space	Same as AlphaNumeric All plus space character
AlphaNumeric Lower Case	Lowercase alphabet and numbers
AlphaNumeric Lower Case & Space	Same as AlphaNumeric Lower Case plus space character
AlphaNumeric Upper Case	Uppercase alphabet and numbers
AlphaNumeric Upper Case & Space	Same as AlphaNumeric Upper Case plus space character
Numeric	Numbers only
Numeric & Space	Numbers only plus space character

Creating a Character Set

You can create a character set that is tailored to your company's requirements. Each character set is limited to 100 characters.

Caution	Although all characters are supported within Agile PLM, and should not create issues within Agile's clients, it is recommended that you avoid using the following characters when naming or renaming objects (for instance, subclasses or attributes), due to issues that could potentially arise in integrations or custom applications written on the SDK.
----------------	--

, comma . period (dot)

Previously, Agile experienced issues with certain Unicode characters, specifically katakana characters, as they were not valid XML name characters. Agile PLM has addressed these issues within aXML.

Regarding the “slash” character (/), the SDK makes use of certain characters within its query language, but the recommended practice is to refer to classes and fields by ID, rather than by name. For easy access to folders (e.g., search folders), the SDK allows indication of folders like this: “folder/folder/folder/object” — thus, slashes in folder names could cause issues; however, you can use the escape sequence (with “\”).

To create a new character set:

1. Under **Data Settings**, double-click **Character Sets**. The Character Sets window appears.
2. Click the **New** button. The Define Character Set dialog box appears.

3. In the **Name**, **API Name** and **Description** fields, type a unique name and a description, respectively.
4. In the **Enabled** list, select Yes.
5. In the **Valid Character Set** field, enter up to 100 characters to include in the set. Duplicate characters are not allowed.
6. To add special characters, click the **Special Character** button and select space (^s), new line/carriage return (^p), or caret (^_).
7. When you have finished, click **OK**.

Note Custom character sets can affect the performance of your system if very large character sets are defined and many attributes use them.

Modifying a Character Set

You can modify the contents, name, and description of a character set that you have created from the **Character Sets** window. The default character sets provided with Agile PLM are read-only.

To modify a character set:

1. Under **Data Settings**, double-click the **Character Sets** node. The Character Sets window appears.
2. Double-click a character set to open it.
3. In the **Name** and **Description** fields, type a unique name and a description, respectively.
4. In the **Valid Character Set** field, add or remove characters.
5. When you have finished, click **Save**.

To delete a character set:

1. Under **Data Settings**, double-click the **Character Sets** node. The Character Sets window appears.
2. Select a character set.
3. Click the **Delete** button, and then click **Yes** to confirm.

Note If the character set is currently assigned to any Text or MultiText attributes in the Agile PLM system, it cannot be deleted.

Make sure you choose appropriate character sets where required. There is a potential problem when adding files or URLs from a business object to a file folder object. If the file folder's File Description attribute has a Character Set = Numeric, but the business object's File Description attribute has a Character Set = Alpha or AlphaNumeric, the latter will override the former, meaning whatever control you wanted to impose in the file folder's File Description (being numeric) will be lost, the system will save the original character set.

Lists

This chapter includes the following:

▪ Overview	95
▪ Routing Manager Lists	95
▪ More Kinds of Lists	97
▪ Configuring Lists	99
▪ Creating Cascading Lists	102

This chapter provides information about how to customize and configure lists.

Overview

The **List** node accesses a collection or library of lists. This is used to manage lists that are used across multiple classes. You can define custom lists that can be used for **Page Two** and **Page Three** list attributes. Many attributes in the Agile PLM system are configured to be lists. Attributes, properties, flex fields on tables, and cells can all be lists.

Routing Manager Lists

There are six lists that pertain to the routing managers of workflows: **Change Analyst** list, **Component Engineer** list, **Price Administrator** list, **Compliance Manager** list, **Quality Analyst** list, and **Quality Administrator** list. They are not editable from the **Lists** node. Names of users are added and removed from these lists according to what you set for a given user's Lists property (**Users** > <user> > **General Info** tab (**Profile** area) > **Lists**).

On the **Lists** node, the single editable property for these six lists is called **Display Type**. This property lets you choose whether the “routing manager” list field in routable objects appears to the originating user as a **List** or as a **Search** format. For companies sized so only a few people are on each list, the dropdown list may be fine. Larger companies may have, for example, one or two dozen change analysts, and they will find the Search format useful: you can select the appropriate change analyst for a change order and all the other analysts will not receive notifications about that change order.

Note The default for the **Display Type** field is List.

Creating Custom Lists and Adding to Lists

ID	Name	Description	Enabled	Editable	Is Cascading?
18414	Action Status	Action Status	Yes	Yes	No
2249	AML Preferred Status	AML Preferred Status	Yes	Yes	No
4682	AttachType List	AttachType List	Yes	Yes	No
6820	Audit Result	Audit Result	Yes	Yes	No
8934	Buyer	Buyer	Yes	Yes	No
2000000192	Category 10 List	Category 10 List	Yes	Yes	No
2000000189	Category 7 List	Category 7 List	Yes	Yes	No
2000000190	Category 8 List	Category 8 List	Yes	Yes	No
2000000191	Category 9 List	Category 9 List	Yes	Yes	No
730	Change Analysts	Change Analysts	Yes	No	No
411	Change Category	Change Category	Yes	Yes	No
331	Change Function	Change Function	Yes	Yes	No
8223	Changes	All Change Objects	Yes	No	No
12941	Commodities	Commodities for Items	Yes	No	No
750	Comp Engineers	Component Engineers	Yes	No	No
2000004949	Compliance Manager	Compliance Manager	Yes	No	No
4598	Continent	Continent	Yes	Yes	No
365	Country	Country	Yes	Yes	No
8704	Currencies	Currencies	Yes	No	No
2000000107	Customer List	Customer List	Yes	Yes	No
6505	Customers	All Customer Objects	Yes	No	No
2000002155	Declarations	All Declaration Objects	Yes	No	No
18412	Discussion Priority List	Discussion Priority List	Yes	Yes	No
8229	Discussions	All Discussion Objects	Yes	No	No

To create a custom list for the list library:

1. Under **Data Settings**, double-click **Lists**. The Lists window appears.
2. Click the **New** button. The Create List dialog box appears.
3. Fill in the **Name**, **API Name** and **Description** fields. They are both limited to 255 characters.
4. Select Enabled or Disabled in the **Enabled** list.
5. Select Yes or No in the **Cascade** list.
6. Click **OK**. The new List:<name> window appears. The new list also appears in the list library.
7. The Create a new list value window automatically appears. Fill in the **Name**, **API Name** and **Description** fields.
8. Select Yes or No in the **Active** list.
9. Click **Add** or **Add Another**.

Note You can create a list without populating it with list items.

To add values to a list:

1. Under **Data Settings**, double-click **Lists**. The Lists window appears.
2. If necessary, use the filter bar to display the list you want to populate. Double-click a list to open it.
3. Click the **List** tab. The List:<name> List window appears.
4. Click the **New** button. A dialog box appears.
5. Type the item name, type two colons (::), the API name, type two colons (::), and then type a description of the item. The name and description can each be up to 255 characters. The format will be List Value (name)::API Name::List Description.

Note Do **not** use commas when adding values to a list.

On separate lines, enter additional list items as needed. You can type names and descriptions of as many list items as you want, separating them with a carriage return. You can also paste list items into the dialog box from a text editor, such as Notepad.

Note This dialog box is limited to 4000 bytes. The “carriage return” for each item uses 1 byte. If the average list item uses 20 bytes (including spaces and the carriage return), the list can contain approximately 200 items. Additional list items can be added by selecting **New** again.

6. After you finish typing new list items, click **OK**. The list items are added to the list.

By default, the **Active** property of a list item is set to Yes. If you want to make it inactive, double-click the row and choose No for the **Active** property.

This process of adding multiple list items at a time is called “batch add.”

More Kinds of Lists

Given that users see Custom and Object lists, let’s further distinguish what kinds of lists users see in their work. You are familiar with the “List” (SingleList) and “MultiList” attributes from [Classes](#) on page 51, on page 54.

- SingleList Lists
- MultiList Lists
- Cascading Lists
- Dynamic Lists

SingleList Lists

A SingleList attribute or cell presents a list from which only one value can be selected. The following figure shows the **Time Format** field, a SingleList cell in Web Client.

Overhead Rate: United States Dollar ▼

United States Dollar

Euro

Pound Sterling

Hong Kong Dollar

Irish Punt

Japanese Yen

MultiList Lists

A MultiList attribute or cell is a list from which multiple values can be selected. In Web Client, you can select values for a MultiList cell using the Multiple Value Selection window, shown in the following figure.


Product Line

Filter:

↑ Name	Description
BioPod	
Common	
Capricorn	
Gemini	
Leo	
LaserSplash	
Ryker Computer Corp.	
Scorpio	
Taurus	
Virgo	

Cascading Lists

A SingleList or MultiList attribute can be configured in Java Client to have multiple hierarchical levels. A list with multiple hierarchical levels is called a cascading list. The following figure shows the setup window (in Java Client) for the Location list, a cascading list. The list has separate levels for continent, country, and city.



Note The Location list is the only cascading list that ships with Agile PLM. However, you can define your own cascading lists.

For more information about cascading lists, see [Creating Cascading Lists](#) on page 102.

Dynamic Lists

The Agile PLM server has both static lists and dynamic lists. Static lists are lists that contain an unchanging selection of values. Dynamic lists contain a list of values that are updated at run time. Static lists can be modified; new values can be added and current values can be made obsolete. Dynamic lists cannot be modified; consequently, the Editable property of dynamic lists is set to No.

Configuring Lists

This section provides instructions for configuring dropdown lists in Java Client. These instructions

apply to ordinary lists and cascading lists.

To modify a list:

1. Under **Data Settings**, double-click **Lists**. The Lists window appears.
2. If necessary, use the filter bar to display the list you want to modify.
3. Double-click a list to open it.
4. On the **General Information** tab, edit the **Name** or **Description** fields.
5. To disable the list, change the **Enabled** field to No.

Note If the list is currently being used in the Agile PLM system, it cannot be disabled.

6. To modify the list values (that is, the list entries), click the **List** tab. Add, delete, or modify values as necessary.

Note If the list is currently being used in the Agile PLM system, its list entry values can be deleted, but there will be a warning message. It is recommended that you deactivate a list entry value so that it no longer appears in Agile PLM clients.

7. Click **Save** to save your changes.

To delete a list:

1. Under **Data Settings**, double-click **Lists**. The Lists window appears.
2. If necessary, use the filter bar to display the list you want to delete.
3. Select a list.
4. Click the **Delete** button, and then click **Yes** to confirm.

Note If the list is currently being used in the Agile PLM system, it cannot be deleted or disabled.

To modify a list value (list entry):

1. Under **Data Settings**, double-click **Lists**. The Lists window appears.
2. If necessary, use the filter bar to display the list you want to modify.
3. Double-click a list to open it.
4. Click the **List** tab.
5. Double-click a list value to open it.
6. Fill in the **Name** and **Description** fields. They are both limited to 255 characters.
7. To deactivate the value, set the **Active** field to No.

Note By making a list value inactive, you effectively hide it from Agile PLM clients. However, users can still search for inactive values.

8. Click **OK** to save your changes.

To delete a list value (list entry):

1. Under **Data Settings**, double-click **Lists**. The Lists window appears.
2. If necessary, use the filter bar to display the list you want to modify.
3. Double-click a list to open it.
4. Click the **List** tab.
5. Select a list value.
6. Click the **Delete** button: you may see the Confirm Dialog with a warning (and the prompt "Do you want to continue to delete?"), click Yes to continue the delete.

You may see the Delete List Item dialog, which indicates the system's assessment that the list item (list entry) is in use, and that you must first remove all references to the list entry before trying again to delete it.

Note If the list is currently being used in the Agile PLM system, its values cannot be deleted. However, you can deactivate a list value so that it no longer appears in Agile PLM clients.

To change the list used by a List or MultiList attribute:

1. Under **Data Settings**, double-click **Classes**. The Classes window appears.
2. Open the class or subclass whose attributes you want to modify.
3. Click the **User Interface Tabs** tab.
4. Double-click a tab to open it.
5. Click the **Attributes:<Table>** tab.
6. Double-click the List or MultiList attribute you want to modify.
7. For the **List** property, select a list. You can also click **New List** to create a new list.
8. Click **Save** to save your changes.

Note If any Agile PLM objects have the attribute set to use the currently selected list, you cannot select a different list.

Setting Default Values for Lists

Once you have created the list for a List attribute, you can establish its default value if necessary. For more information, see [Setting Default Values](#) on page 85. A default value is one that is selected automatically for a field when you create a new Agile PLM object. The default value for a List attribute must be one of the values in its associated list.

Note Only the administrator has the ability to set a multi-value default for a multilist attribute.

Display Type for Lists in Web Client_93

The Display Type setting available for Routing Manager Lists is also an available setting for Lists and Multilists for Web Client. In Java Client the administrator chooses whether the object list attribute is displayed as a List or Search format in Web Client. If the selection is List mode then the entries display in a dropdown list. If the selection is Search mode then the entries display in a search palette.

Note For list attributes that contain more than 250 entries, the Web Client automatically displays the entries in Search mode.

Failure Mode Lists

Failure mode is used by product service requests (PSRs) to indicate how the item failed when quality incidents are reported. The failure mode is a list of values that are specific to each item subclass. For instance, if a customer created a subclass of Items called Optics, then a Failure Mode list would be created for Optics that contains the types of defects specific to optical components. Failure mode lists have the following special characteristics:

- When you create a new subclass of the Documents or Parts classes, the list library automatically creates a new Failure Mode list for that subclass.
- If you change the subclass name after it has been created, the name of the related failure mode list is *not* updated. This list will be updated after refresh.
- The **Where Used** tab of failure mode lists is disabled due to the special handling of failure modes in the Agile PLM system.
- A failure mode list cannot be deleted unless its corresponding subclass has been deleted.

Because of their special characteristics, failure mode lists should not be used for other types of list attributes.

Creating Cascading Lists

Cascading lists have multiple hierarchical levels, presenting several lists within lists.

Configuring cascading lists is very similar to configuring single-level lists. See [Configuring Lists](#) on page 99 for more information about modifying lists. Cascading lists have the following additional restrictions:

- Once you create a cascading list, you cannot change it to an ordinary list. After the list is saved, the **Is Cascading?** property is read-only.
- Each folder within a cascading list must contain unique values. However, different folders within a cascading list can share the same values.
- Cascading list values must be added one at a time. There isn't a batch method for adding cascading list values.
- A cascading list can have any number of levels. However, in practice you should try to limit a cascading list to no more than four levels.

- Ability to choose a branch value of a cascading list; both the nodes and the final list values.

To create a new cascading list:

1. Under **Data Settings**, double-click **Lists**. The Lists window appears.
2. Click the **New** button. The Create List dialog box appears.
3. Fill in the **Name**, **API Name** and **Description** fields.
4. To enable the list, make sure the **Enabled** list is set to Yes.
5. In the **Is Cascading?** list, select Yes.
6. Click **OK**. The new List:<name> window appears.
7. To add values to the list, click the **List** tab.
8. Click the **New** button. A dialog box appears.
9. Type in the list item name, the API name, and then type a description of the list item.
10. Click **Add** to add the value and close the dialog box. If you wish to save the value and add other values to the same level, click **Add Another**.

Note List values are always added to the level *below* the currently selected value in the cascading list.

11. To add more values, repeat steps 8 through 10.

Process Extensions

This chapter includes the following:

▪ Overview to Process Extensions	105
▪ Using the Process Extension Library	106
▪ Assigning Process Extensions to Classes	108
▪ Assigning Process Extensions to Workflow Statuses	108

This chapter provides information about how to customize and configure process extensions.

Overview to Process Extensions

The **Process Extensions** node lets you define custom actions that extend the functionality of the Agile PLM system. The custom actions you define can be used to create custom reports, user-driven and workflow-triggered custom actions, and custom tools accessible through Agile PLM clients.

A Process Extension (PX) is either a Java class deployed on the Agile Application Server or a link to a URL. The URL can be a simple Web site or the location of a Web-based application.

There are two types of process extensions available in Agile PLM:

- *Custom process extensions* (Custom PX) is a general name for PXs created in **Data Settings > Process Extensions** node. These PXs have limited initiation capability. This node continues as the site to store and manage your custom PXs.
- *Event-based process extensions* (Event PX) are created in the **System Settings > Event Management > Event Handlers** node. For more information about Event-based process extensions, see [Handler Types](#) on page 312 of [Event Management](#) on page 305.

There are several integration points for process extensions available in Agile PLM clients. You can invoke process extensions from the following areas:

- Actions menu
- Tools menu
- Workflow Status
- External reports
- Dashboard — URL-based process extensions that are created with Dashboard as the integration point are listed in the Dashboard Extension field, while a Dashboard table with View Type List is created. The output of the URL-based process extension is displayed in the Dashboard table.

Note Technically, a custom AutoNumber source is another type of process extension because it uses the same server-side framework as custom actions. For more information about custom AutoNumber sources, see [Autonumbers](#) on page 111.

What tools do you need to develop process extensions? For URL-based PXs, you don't need any additional tools. You can define any number of URL-based PXs in the Process Extension Library and specify where those URLs can be accessed from in the client.

Note A server property called `agile.sso.expirationTime` controls the expiration of the cookie used by a URL-based PX. The default value of the property is 86400 (seconds), which means the cookie will expire after one day. The administrator can increase or decrease the expiration time by adding this property to **agile.properties** under `<AgileHome>\agileDomain\config`. Remember the value is in seconds.

To create process extensions that are Java classes deployed on the Agile Application Server, you need to use the Agile SDK, work with Oracle Consulting – Agile Practice, or work with an Agile partner to develop process extensions that suit your company.

For more information about how to use the process extensions framework to develop and deploy custom AutoNumber sources and custom actions, see the *Agile SDK Developer Guide*.

Using the Process Extension Library

The Process Extension Library is where you define the custom actions that can be used in Agile PLM clients. When you add a custom action to the Process Extension Library, you specify how to initiate that action from the client.

Agile PLM provides two default process extensions, as shown in the following table.

Name	Description
Accept Package Response	Sends an Accept response to the Agile PLM system that submitted a Package.
Reject Package Response	Sends a Reject response to the Agile PLM system that submitted a Package.

These process extensions are used by Agile Content Service (ACS) to automatically send Accept or Reject responses during Agile-to-Agile communication. For more information, see *Agile Content Service User Guide*.


There are several out-of-the-box process extensions used by Product Governance & Compliance. For more information, see *Product Governance & Compliance User Guide*.

Of course, you can add any number of additional process extensions to the Process Extension Library.

To add a custom action to the Process Extension Library:

1. Under **Data Settings**, double-click **Process Extensions**. The Process Extension Library window

opens.

2. In the Process Extension Library window, click . The Add Process Extension dialog box appears.
3. Enter the following information:
 - **Name:** Enter the name of the custom action.
 - **API Name:** autogenerated
 - **Description:** Enter a brief description of the custom action.
 - **Type:** Select URL or Internal Custom Action.
 - **Address:** Specify a Web address (if Type is set to URL).
 - **Internal Custom Action:** Select a custom action from the list (if **Type** is set to Internal Custom Action). The list reflects the custom actions that have been deployed on the Agile Application Server using the process extensions framework. If no custom actions have been deployed, the list is empty.
 - **Initiate From:** Select one or more locations from which the custom action can be initiated. Select from the following options:
 - **Actions Menu:** Allows users to select the custom action from the **Actions** menu of a properly configured class.
 - **External Report:** Allows users to generate a report by accessing an external resource or URL. If the process extension is an internal custom action, the External Report option is unavailable.
 - **Tools Menu:** Allows users to select the custom action from the Tools menu.
 - **Workflow State (status):** Invokes the custom action whenever a properly configured workflow enters a particular status. If the process extension is a URL, the Workflow State option is unavailable.

If you specify that a custom action is initiated from the **Actions** menu or a workflow status, you can configure subclasses or workflows to use that custom action. If you specify that a URL is used to generate an external report, you can use the Agile Web Client to create the report. If you specify that an action is initiated from the **Tools** menu, it's available at all times in the Agile client.
 - **Roles:** Select one or more roles to use for the custom action. To use the roles and privileges of the current user, leave this field blank. To temporarily override roles and privileges of the current user, select one or more roles. Once the custom action is completed, the client reverts to the current user's roles and privileges.
 - **Enabled:** Select Yes.
4. Click **OK** to save the process extension.


To modify a process extension:

1. Under **Data Settings**, double-click **Process Extensions**. The Process Extension Library window opens.
2. Open the process extension you want to modify.
3. Change the settings, and then click **OK**.

To delete a process extension:

1. Under **Data Settings**, double-click **Process Extensions**. The Process Extension Library window

opens.

2. Select the process extension you want to delete, and then click .

Note Custom actions currently being used by a class, workflow, or external report cannot be deleted. If you disable a custom action, it is inactive. Removing a custom action from the Process Extension Library does not affect custom code that has been deployed on the Agile Application Server.

Assigning Process Extensions to Classes



To add custom actions to the **Actions** menu of an Agile PLM object (such as a part or an ECO), you configure the object's class. Each base class, class, and subclass has a **Process Extensions** tab. The custom actions that you assign to a class must be previously defined in the Process Extension Library.

Process extensions are inherited from classes and base classes. Consequently, if you assign a process extension to a base class, it is also assigned to classes and subclasses beneath the base class.

Note Process extensions can be assigned to only one level in a class hierarchy. For example, if a process extension is assigned to the Part subclass it can't be assigned to the Item base class.

However, in the case of Agile Portlets, using the process extension Configurator, process extensions can be assigned only to base classes, that is, Items base class, not Parts or Documents classes, nor Part or Document subclasses.

To assign process extensions to a class:


1. Under **Data Settings**, double-click **Classes**. The Classes window opens.
2. Double-click the base class, class, or subclass you want to work with.
3. Click the **Process Extensions** tab.
4. In the toolbar, click . The Assign Process Extension dialog box appears.
5. Select custom actions in the **Choice List**, and then click  to move them into the **Selected List**. When you are finished, click **OK**.
6. Click **OK** to save settings.

Assigning Process Extensions to Workflow Statuses

For each workflow status except the Pending status, you can assign one or more custom actions that are initiated when the workflow enters that status. The custom actions you assign to a workflow status must be previously defined in the Process Extension Library.

Note The Automated Transfer Orders (ATOs) class and its subclasses do not support workflow-initiated process extensions.

To assign process extensions to a workflow status:

1. Under **Workflow Settings**, double-click **Workflows**. The Workflows window opens.
2. Double-click the workflow you want to work with.
3. Click the **Status** tab.
4. Select a status other than Pending. The Criteria properties table for the selected status appears below the status table.
5. Double-click the selected status in the Criteria properties table.
6. In the **Process Extensions** list, click . A popup window appears.
7. Select custom actions in the **Choices List**, and then click the > button to move them into the **Selected List**. When you are finished, click **OK**.
8. Click **Save** to save settings.

Autonumbers

This chapter includes the following:

▪ How Autonumbers Are Used	111
▪ About Autonumber Sources.....	112
▪ Configuring Autonumber Sources.....	114
▪ Creating a New Autonumber Source	116
▪ Deleting an Autonumber Source.....	118

This chapter describes how to manage the automatic numbering of Agile PLM objects.

How Autonumbers Are Used

From the **AutoNumbers** node, you can configure sources for automatic numbering in Agile PLM. For example, you can change the name of an autonumber source or its subclass assignments, or expand the sequence when necessary.

You can also specify your own prefix or suffix for an autonumber source, or create new autonumber sources. You can delete an autonumber source that is no longer needed as long as it has not been used to create an object in Agile PLM clients.

There are two types of autonumbers that can be used; a standard and a custom method. The standard method is to define a sequence by specifying the prefix, suffix, character set, and number of characters allowed. The custom method is more flexible and uses the process extensions framework to define any numbering sequence.

To use process extensions to create custom autonumber sources, you need to either purchase the Agile SDK or work with Oracle Consulting – Agile Practice or an Agile partner to develop process extensions that suit your company's needs. For more information about process extensions, see the *Agile SDK Developer Guide*.

Modifying an Autonumber Source

You can modify any number source from the **AutoNumbers** node.

To modify an autonumber source:

1. Under **Data Settings**, double-click **AutoNumbers**. The AutoNumbers window appears.
2. Double-click a row to open that source's window (for example, the AutoNumber: Deviation Number window).
3. In any editable field, enter a new value or select from the dropdown list.
4. When you have finished, click **Save**.

5. If you wish to revert to the original settings or start over, click **Cancel**. You will be prompted whether you want to cancel the new settings in the window; click **OK** if you do or **Cancel** if you do not.

The autonumber properties are described in [Configuring Autonumber Sources](#) on page 114.

About Autonumber Sources

An autonumber source is a predefined, consecutive number series used for the automatic numbering of objects created in Agile PLM clients. Each object in Agile PLM is assigned a number when it is created. You can allow users to choose between assigning numbers manually or letting Agile PLM assign numbers automatically, or you can prevent manual number assignment.

The Agile PLM administrator sets up the number assignment convention for the Agile PLM system from the following two administrative nodes:

- From the **Classes** node, you assign specific autonumber sources to specific subclasses. See [Changing the AutoNumber Source Property](#) on page 61.
- From the **AutoNumbers** node, you configure the number sources themselves, including their names, whether they have a prefix or suffix, and how many numbers are in each sequence. You can view which subclasses are assigned to a specific number source, and you can configure this arrangement. You can also create new number sources or delete number sources that are not needed.

Autonumber sources are assigned to subclasses so that Agile PLM will know which number source to use when automatically assigning numbers to objects. A separate autonumber source is provided and assigned to most subclasses with your Agile PLM installation.

Note Several Agile PLM subclasses, such as Manufacturer and User, do not allow autonumbering.

To view the existing autonumber sources, double-click the **AutoNumbers** node. You can use the autonumber sources provided, or you can make any of the following changes to the configuration:

- Create new autonumber sources using the **New** button.
- Enable or disable an autonumber source using the **Enable** or **Disable** buttons.
- Assign one or more autonumber sources to a subclass.
- Assign one or more subclasses to an autonumber source.
- Add a prefix or suffix to an autonumber source using the **Prefix** or **Suffix** field in the setup window.
- Change the name of an autonumber source using the **Name** field in the setup window.
- When all numbers in an existing autonumber source have been used, expand the number series using the **Next Number** field in the setup window.
- Delete an autonumber source that is not needed using the **Delete** button.

Note For information about requiring automatic numbering, see [Preventing Manual Number Assignment](#) on page 62.

If you create a new subclass, you can assign it any existing number sources for autonumbering, or create a new number source just for that subclass.

The following table lists the autonumber sources as configured at installation.

Name	Where Used	Prefix	Number of Characters
ATO Number	ATO	ATO	7
Audit Number	Audit	Audit	5
Broker Number	Broker	BROKER	5
CAPA Number	CAPA	CAPA	5
Component Manufacturer Number	Component Manufacturer	COMMR	5
Contract Manufacturer Number	Contract Manufacturer	CTMR	5
Contracts Number	Contract	CONTRACT	1
CTO Number	CTO	CTO	7
Customer Number	Customer	CUST	5
Declaration Number	Declaration	MD	5
Designs Number	Design	DESIGN	5
Deviation Number	Deviation	DEV-	6
Discussion AutoNumber	Discussion	D	5
Distributor Number	Distributor	DISTRIBUTOR	5
Document Number	Document	DOC	6
ECO Number	ECO	ECO-	6
ECR Number	ECR	ECR-	6
File Folder Number	File Folder	FOLDER	7
Gate AutoNumber	Gate	G	5
Historical Report File Folder Number	Historical Report File Folder	HFILE	5
Manufacturer Rep Number	Manufacturer Representative	MR	5
Markup Number	Markup	MARKUP	7
Mfr. Orders Number	MCO	MCO-	6
NCR Number	NCR	NCR	5
Package Number	Package	PKG	5

Name	Where Used	Prefix	Number of Characters
Part Number	Part	P	6
PCO Number	PCO	PCO	5
Phase AutoNumber	Phase	PH	5
PR Number	Problem Report	PR	5
Program AutoNumber	Program	PGM	5
Project AutoNumber		PROJECT	7
Project Number	Sourcing Project	PRJ	5
Project Number - Cost Management			
Project Number - New Products			
Publish Price Number	Published Price	PRICE	5
Quote History Number	Quote History	QUOTE	5
RFQ Number	Request for Quote	RFQ	5
RFQ Number - Cost Management			
RFQ Number - New Product			
Site Change Orders Number	SCO	SCO	5
StopShip Number	Stop Ship	STOP-	6
Task AutoNumber	Task	T	5

Configuring Autonumber Sources

Autonumber sources have the properties listed in the following table.

Property	Description
Name	This is the name of the autonumber source. It might simply be the same as the subclass, or it might represent a further distinction, for example, Fasteners or Fasteners-Red. You can change this name.
API Name	Unique systemwide identifier for objects and can be autogenerated. You can specify an API name, but internal consistency is enhanced by accepting the system-generated name.
Description	A brief description about the autonumber source. This is an optional field.
Enabled	Whether this autonumber source is enabled (Yes) or not (No). The default is Yes.
Type	Standard or Custom. The default is Standard. Custom autonumbering is available to customers with SDK capabilities, which allow you to add a process extension that incorporates existing numbering schema. See Process Extensions on page 105,

Property	Description
	and <i>Agile SDK Developer Guide</i> .
Prefix	Property of a standard autonumber. The characters that precede each number that Agile PLM automatically assigns for this autonumber source, for example, Acme000759 (Acme = prefix). You can change the prefix.
Suffix	Property of a standard autonumber. The characters that follows each number that Agile PLM automatically assigns for this autonumber source, for example, Acme000759SW5 (SW5 = suffix). You can change this suffix.
Character Set	Property of a standard autonumber. The characters that are entered in this property are used to create the autonumber. Appropriate for internal autonumber only. Character set can include only a–z, A–Z, 0–9; no special characters are supported.
Number of Characters	Property of a standard autonumber. Sets the number of characters to use or the length. So if “4” is entered, the numbering can be 0001–9999. Appropriate for internal autonumber only. Limit is 10, so this property can be populated only with 1, 2, 3, 4, 5, 6, 7, 8, 9, or 10.
Starting Number	Property of a standard autonumber. The first number that Agile PLM automatically assigns in the sequence. This property can be thought of as an arbitrary “next number.”
Next Number	Property of a standard autonumber. While you can manipulate the “Starting Number” value, the Next Number simply reports what the system will use for the next offered autonumber.
Custom Autonumber	This property of a <i>custom autonumber</i> is only activated (and visible) when Type is Custom. A dropdown list field that you populate with your company’s customized autonumbering system. The list of custom autonumbers reflects the set of custom autonumbers deployed on the Agile Application Server.

Note For out-of-box subclasses, the defaults of AutoNumber Required = No and Autogenerate = Yes means that a number will be automatically generated when you create an object in that subclass; however, users can enter a new object number.

Changing an Autonumber’s Prefix or Suffix

The Prefix and Suffix properties identify the fixed string of letters or numbers that precede or follow an autonumber. For example, the autonumber prefix for parts is P, so all parts created in Agile PLM clients have numbers preceded by the prefix P, such as P00678. If the autonumber source also had a suffix of 00, number assignments would be followed with 00.


The Agile PLM administrator can change the prefix and suffix properties for an autonumber source. New objects created for subclasses that use this autonumber source have the new prefix or suffix in their autonumbers.

Note It is not recommended to change any properties other than **Name**, **Description** and **Enabled** for an autonumber already in use.

Changing Where an Autonumber Source Is Used

The Where Used property shows you what subclasses use a particular autonumber source in Agile PLM. You can modify this property to permit additional subclasses to use the number source, or to prevent a subclass from using it.

To view or change the subclasses that use a particular autonumber source:

1. Under **Data Settings**, double-click **AutoNumbers**. The AutoNumbers window appears.
2. Double-click a row, and that source's window appears (for example, the Deviation Number window).
3. On the **Where Used** tab, click the **Add** button .

The "Add classes to where used tab" dialog box appears, showing all subclasses that exist in your Agile PLM system. The subclasses listed in the **Selected List** list use this number source for objects created in Agile PLM clients. The subclasses listed in the **Choice List** list do not use this number source.

4. To change the configuration, double-click a subclass name to move it from one list to the other.
5. To save your changes and close the dialog box, click **OK**.
6. When you have finished, click **Save**.
7. If you wish to revert to the original settings or start over, click **Cancel**. You are prompted to confirm whether you want to cancel new settings on the window; click **OK** if you do or **Cancel** if you do not.

Custom Autonumbers

Select a custom autonumber source from the list. You can create custom autonumber sources only if they have been deployed on the Agile Application Server using the process extensions framework. When you create a custom autonumber source, you select from the **Custom Autonumber** drop-down list. If no custom autonumber sources have been deployed, the list is empty.

Timeout

Enter the number of seconds after which a timeout error will occur if the custom autonumber source does not respond. The default is 30 seconds.

Creating a New Autonumber Source

You can create a new autonumber source for user-defined subclasses if required.

Before You Begin

Consider the following details before creating a new autonumber source.

- Which subclasses will use the new autonumber source?
- What name will you give the new autonumber source?
- Will the new autonumber source require a prefix? If so, what prefix?
- Will the new autonumber source require a suffix? If so, what suffix?
- What size number sequence is required?

To create a new autonumber source:

1. Under **Data Settings**, double-click **AutoNumbers**. The AutoNumbers window appears.
2. Click **New**. The Define the AutoNumber dialog box appears.
3. Fill in the **Name**, **API Name** and **Description** fields, and select Yes or No in the **Enabled** list.
Set the value in the **Enabled** list to Yes if you are ready to introduce this new number source to the Agile PLM system. The default is Yes in this dialog box, but it may be prudent to set it to No until the subclass is entirely set up.
4. Select the type of new autonumber:
If you selected Standard, fill in, as your company's needs require, the **Prefix**, **Suffix**, **Character Set**, **Number of Characters**, and **Starting Number** fields.
To prevent duplicating a number source, see About Autonumber Sources for a list of the prefixes for autonumber sources already provided with your Agile PLM installation.
The Number of Characters setting determines how many autonumbers can be assigned. For example, if you enter 4 in the **Number of Characters** field, the range of numbers available for this series is from 0001 to 9999 (or a total of 9,999 numbers). Choose a value that will prevent the sequence from being exhausted in a short time.
5. If you selected Custom, fill in **Custom AutoNumber** and **Timeout** (seconds) fields.
6. Click the down arrow for the **Where Used** list. A dialog box appears, showing all subclasses that exist in your Agile PLM system. Since you are creating a new number source, the **Selected** field will be empty.
7. If you have already created the subclass that will use this number source, double-click the subclass's name in the **Choices** list to move it to the **Selected** list. If you have not created the subclass that will use this number source, this step cannot be completed; in this case, leave the **Enabled** field set to No.
8. To save your changes and close the dialog box, click **OK**.
The new name appears as a new object on the AutoNumbers window.

For information about how to prevent Agile PLM users from manually assigning numbers for this subclass, see [Preventing Manual Number Assignment](#) on page 62.

Deleting an Autonumber Source

The Agile PLM administrator can delete an autonumber source that is not needed, as long as it has not been used to create an object in Agile PLM clients.

Note If an autonumber source has been used to create an object, disabling it makes it unavailable for further use. See [Modifying an Autonumber Source](#) on page 111.

To delete an autonumber source:

1. Under **Data Settings**, double-click **AutoNumbers**. The AutoNumbers window appears.
2. Select the autonumber source you want to delete.
3. Click the **Delete** button.

If the autonumber source has already been used to create an object in Agile PLM clients, you see an error message stating that the object is already in use, and the Agile PLM system does not delete it.

If the autonumber source has not already been used to create an object in Agile PLM clients, a dialog box appears to confirm the deletion.

4. Click **OK** to confirm the deletion.

The autonumber source is deleted, and is no longer available for assignment to a user-defined subclass.

Criteria

This chapter includes the following:

▪ About Reusable Criteria.....	119
▪ Exploring Reusable Criteria	120
▪ Creating a New Criteria	121
▪ Modifying an Existing Reusable Criteria	123
▪ Using Affected Items Tab Fields in Reusable Criteria	123
▪ Using \$CURRENTREV and \$LATESTREV in Criteria for Items	125

This chapter examines the criteria used in Agile PLM workflows, and explains how to create reusable criteria.

About Reusable Criteria

A reusable criteria is a database query, just like an advanced search. The attributes used to create reusable criteria are similar to the attributes used to create advanced searches. They are also like filters that qualify the objects moving through a workflow process or the conditions for which the privileges masks apply.

The **Criteria** node is where reusable criteria are stored and maintained. From this node, you can create, delete, or modify the reusable criteria that are a fundamental building block of Agile PLM workflows and privileges. Reusable criteria are also used to define designated escalation persons and signoff transfer authority.

Reusable criteria can be assigned to multiple workflows, and to multiple statuses within a single workflow. You can define criteria that:

- Specify or distinguish combinations of **approvers** or **observers**, whether they are selected users, existing or created global groups, or even personal groups.
- Specify each of the company's **product lines**.
- Correspond to **Agile PLM classes**.
- Correspond to any other combination of attributes of **Agile PLM objects**—items, changes, packages, manufacturers and manufacturer parts.

Since changes to the reusable criteria for these workflows are global (that is, a refinement to a reusable criteria affects every workflow in which it appears), you can complete systemwide changes to your workflows in one step.

By specifying a list of reusable criteria for each workflow, you limit which changes can use a specific workflow. For more information about reusable criteria applied as matching criteria, see [Using Affected Items Tab Fields in Reusable Criteria](#) on page 123.

Exploring Reusable Criteria

To view the available reusable criteria:

1. Under **Data Settings**, double-click **Criteria**. The Criteria window appears.
2. Filter criteria records to narrow your search. For example, filter records by Description Contains Item to find all the reusable criteria for item objects. (See [Filtering Data](#) on page 8.)

The filtered list of reusable criteria is displayed in the table. The Criteria table shows the name, description, and object type for each reusable criteria. Click a column header to sort the table by that column.

Use the buttons at the top of the window to perform various reusable criteria management tasks.

Button	Description
Delete	Deletes the selected reusable criteria. A reusable criteria cannot be deleted if it is already in use.
Import	Imports an archive file (.AGI) to create a new criteria. See Administrator Import and Export on page 28.
Export	Exports reusable criteria data for the selected reusable criteria. See Administrator Import and Export on page 28.
Export All	Exports all reusable criteria data. See Administrator Import and Export on page 28.
New Criteria	Create a new reusable criteria. See Creating a New Criteria on page 121.

Viewing a Reusable Criteria

The reusable criteria can have any of the Agile PLM classes or subclasses as an object type. Many of the out-of-box reusable criteria have been used to define privilege masks.

To view a specific reusable criteria:

1. Under **Data Settings**, double-click **Criteria**. The Criteria window appears.
2. Filter criteria records to narrow your search. For example, filter records by Description Contains Item to find all the reusable criteria for item objects. (See [Filtering Data](#) on page 8.)
3. In the Criteria window, click the name of the reusable criteria you want.

The tabbed window for that reusable criteria appears.

The **General Information** tab of the Criteria setup window has button you can use to perform the available actions described in the following table:

Action	Description
Delete	Deletes the reusable criteria if it is not in use.

Action	Description
Export	Exports the reusable criteria information. See Administrator Import and Export on page 28.
Save As	Allows you to copy the reusable criteria and give the copy a new name. <ul style="list-style-type: none"> Click Save As. Enter a new name in the dialog box that appears. Click OK.

Criteria Windows and Tabs

When you double-click an existing reusable criteria, its properties are displayed in a tabbed window in the right pane. The **General Information** tab displays the name and description of the criteria, and object type that criteria applies to. You can use the **Edit** button to edit the name and description.

The **Criteria** tab lists the type—class or subclass—that the criteria is associated with and the criteria parameters. These are the conditions that define how each reusable criteria works.

Note You can edit a reusable criteria that's already being used, but its **Name**, **Description**, and **Object Type** fields are read-only.

The **Where Used** tab tells where reusable criteria are used in criteria-specific properties, matching criteria, privilege masks, escalations, and transfers. The **History** tab lists the actions that have been performed in relation to this reusable criteria.


Creating a New Criteria

You create reusable criteria according to the needs of your workflow or privilege mask. Because reusable criteria can be widely used in Agile PLM, their purpose and function need to be clear from the start.

It is recommended that you devise a system or convention for naming reusable criteria.

Caution Although you can change the name of reusable criteria at any time, doing so too often may confuse users, who do *not* see a name change until they have logged out and back into the Agile PLM client.

A possible naming scheme could be:



For example, a criteria name of "MCO_Acme_July2000" is a lot easier for your users to decipher than "MCO6."

Note Reusable criteria created by the Agile PLM administrator appear in the Transfer Authority dialog as *Global.Criteria name*. Personal reusable criteria created by other users appear in the Transfer Authority dialog box as *User.Criteria name*.

To create a new reusable criteria:

1. Under **Data Settings**, double-click **Criteria**. The Criteria window appears.
 2. Click the **New** button. The Create Criteria dialog box appears.
 3. Fill in the **Name**, **API Name** and **Description** fields, and select the object type that your reusable criteria will apply to. This list comprises all the Agile PLM classes and subclasses.
-
- Note** The reusable criteria name must be unique. If you specify a reusable criteria name that is already used, you get a duplicate name error message.
-
4. If you want the criteria to be case-sensitive, select the **Case Sensitive** checkbox. Case-sensitive searches improve system performance and can simplify how you define reusable criteria:
 - If you enter text in the **Value** field, the criteria will look for text that is an exact match.
 - If you define a numerical value, checking **Case Sensitive** allows the Agile PLM system to make use of internal database settings to find objects more quickly.
 5. Click **Add** and select the Agile PLM attribute you want from the **Attribute** drop-down list. The values that are available change according to the Agile PLM class or subclass you selected in the previous step. Click **OK** in the small dialog box.
 6. Click the **Match if** field and specify the search operator.
 7. Click the **Value** field, and select a value for the field you selected from the **Attribute** list. Click **OK** in the small dialog box.
 8. If you are going to add additional conditions, click the **Add** button again, and then in the **And/Or** field, select And or Or.
 9. You can click the **Insert** button to add a condition above the currently highlighted row.
 10. Repeat step 5 through step 8 until your reusable criteria is complete.

11. When the criteria is complete, Click **OK**.

Note Changing the criteria in the **Object Type** field resets the entire reusable criteria. A reusable criteria covers one entire Agile PLM class or subclass. You need to create a separate global criteria to cover a different class or subclass.

Click the () button to place parentheses around the specified condition or conditions, which changes the order in which the search conditions are evaluated. The () button functions like a formula within parentheses in an algebraic equation, following the standard algebraic order of operations. The grouped criteria within parentheses are resolved before any others.

Modifying an Existing Reusable Criteria

You cannot modify an existing reusable criteria if it is already in use. You can, however, remove the reusable criteria from its assigned objects, modify it, then reassign it again. Or, you can create a new reusable criteria, assign the new criteria to the objects and remove the old criteria from the objects. The **Where Used** tab lists all the objects where the reusable criteria is in use.

To modify an existing reusable criteria:

1. Under **Data Settings**, double-click **Criteria**. The Criteria window appears.
2. Filter criteria records to narrow your search. For example, filter records by Description Contains Item to find all the reusable criteria for item objects. (See [Filtering Data](#) on page 8.)
3. In the Criteria window, double-click the name of the reusable criteria object you want.
4. The criteria setup window appears containing the existing information about the criteria. Modify the criteria just as when creating it.
5. When you are finished, click **Save**.

Note You cannot delete a reusable criteria once it has been used to create a Transfer Authority privilege, even when you delete that transfer authority. You might rename the criteria you want to delete so it is, for instance, dropped to the bottom of the list of reusable criteria.

Using Affected Items Tab Fields in Reusable Criteria

There are many similarities between reusable criteria and other searches in the Agile PLM system, but there are a few important differences.

How Changes Are Matched When Reusable Criteria Specify Affected Items Tab Fields

To select a specific routable object in Agile PLM clients, an affected items field condition must be true for all the objects on the **Affected Items** tab of that routable object. For example, if you specify Affected Items.Old Lifecycle Phase Equals Preliminary, then all the objects on the **Affected Items** tab must have the **Old Lifecycle** field equal to Preliminary. If you select Contains as the search operator, then every object on the **Affected Items** tab must contain the specified value in the specified field.

When you create a reusable criteria in Java Client, you can include criteria conditions against item fields (such as **Part Category**), provided the item fields are displayed on the **Affected Items** tab of the routable object.

Note Criteria that specify Affected Items attributes cannot be used to create privilege masks. If a criteria does not appear in a privilege mask's dropdown list, it cannot be used to define the privilege mask. See also *Revising Item Descriptions*.

In the Create Criteria dialog box, the **Attributes** list contains **Affected Items** tab fields, including those from the Items themselves. This allows you to create reusable criteria that return changes according to fields of the Items that appear on the **Affected Items** tab. For this kind of query to work, the **Affected Items** tab field must be visible.

For example, to find changes with Items on their Affected Items tab that have a Part Category field equal to Engineering, do the following:

1. Under **Data Settings**, double-click **Classes**. The Classes window appears.
2. Click the class you want (for example, Change Orders).
3. In the Class setup window, click the **User Interface Tabs** tab.
4. Double-click **Affected Items**. The Class Tabs setup window appears.
5. Click the **Attributes** tab.
6. Find **Item Category** in the Name column. double-click the row to display the Attributes setup window.
7. In the **Visible** dropdown list, select Yes. The Visible property is now set to Yes.

Difference Between “Item” and “Part” in Affected Items Names

It is important to understand how the system interprets the naming of affected items when you create reusable criteria, as shown in the following table:

Name (general)	Applies to...	Name (example)	Applies to...
Affected Items.Item fieldname	Parts and documents	Affected Items.Items.P2 Text20	Text20 field for both parts and documents
Affected Items.Part fieldname	Parts only	Affected Items.Part.P2 List03	List03 field for part

Most list and multilist fields for Documents class objects cannot be used to create reusable criteria. For instance, the list fields on **Page Two** and **Page Three** tabs are not available. The two available **Documentation** list fields are **Documentation.Product Line** and **Documentation.Size**.

More about Affected Items: Adding Approvers and Observers

Default change analysts (or default component engineers) may want to monitor changes assigned

to them to make sure that the list of approvers and observers is complete. When workflows assign approvers and observers according to the attributes of the affected items of a routable object, you may want to add approvers that were not automatically assigned by the workflow.

For example, at Acme Inc., each product line has several projects in development at one time. Acme uses a field on **Page Two** (in Agile Java Client) to identify which project or projects each item (part or document) belongs to. The Libra Product Line workflow looks at the project assigned to the affected items on an ECO to determine which default approvers and observers to assign.

Mary Green creates ECO 333 in Agile Java Client. She adds six Orion project objects to the **Affected Items** tab: three parts and three documents. Mary finishes preparing ECO 333 and switches it to the next status, where the change is submitted to Bob Smith, the default change analyst.

To select approvers for the Orion project, the Libra Product Line workflow examines each item on the Affected Items table to determine if the **Page Two** field contains Orion. If *any* the items on the Affected Items table belong to the Orion project, then the list of Orion approvers, as defined in the workflow, are automatically added to the **Workflow** tab when ECO 333 is submitted to Bob.

However, when some of the objects on the Affected Items table are documents, Acme requires that Orion team members in the Publications department must also sign off the change. Since not all ECOs include documents to sign off, the Libra Product Line workflow does not automatically add approvers from the Publications department to every ECO.

Bob, the change analyst, examines ECO 333 and notices that some of the affected items are documents. Bob clicks the **Add Approvers** button on the **Workflow** tab of ECO 333 and adds all the members of the Orion Publications group as approvers. Bob can add approvers to any future Review or Released status type; the ECO does not need to be in the Review or Released status type for approvers or observers to be added.

Using \$CURRENTREV and \$LATESTREV in Criteria for Items

\$CURRENTREV and \$LATESTREV are two powerful system variables available to the administrator to construct criteria that can target specific revisions of items (parts and documents) and specific workflow statuses (for those workflows that apply to rev-based changes, that is, Change Orders, Sites Change Orders, and Manufacturer Orders).

Be aware that this functionality is quite granular and will be best understood when you have become familiar with item revisions (in Production Collaboration) and workflows. It may be helpful to request assistance from your Oracle Consulting – Agile Practice representative.

Note that these variables are also used to construct some criteria in Privilege Masks, which is another area of robust capability and granularity. Variables were introduced in Chapter 2, see [Default Value Variables](#) on page 15; \$CURRENTREV in conjunction with the Modify privilege is detailed in [Controlling the Ability to Modify Items at Introductory Revision with \\$CURRENTREV](#) on page 247.

About TitleBlock.Rev

Title Block.Rev is currently not available for use in criteria conditions. Instead, use \$CURRENTREV criteria conditions to identify which revision the user has selected.

Rules for Using the \$CURRENTREV Variable

The \$CURRENTREV variable is used to construct criteria based on the workflow status of the change (Change Order or Manufacturing Change Order) that corresponds to a selected item revision.

The following rules govern the usage of the \$CURRENTREV variable:

- \$CURRENTREV may only be used in defining criteria against objects belonging to the Items base class (including Parts and Documents classes and their subclasses)..
- \$CURRENTREV is available as a value in the Attribute list. \$CURRENTREV itself does not evaluate to a value: the entire condition itself is evaluated as an expression.
- The **Match If** operator can be set to **Equal To** and **Not Equal To**.
- **Value** can be set to the following values.

The list of values is comprised of \$STATUSTYPE variables for all predefined Change Status Types, as well as all possible Workflow.StatusName values for all configured Workflows created for the Changes object type.

Note The only Change types that are pertinent to this feature are the ones that appear in the Item's Rev dropdown list, that is, those belonging to Change Orders (ECOs), Manufacturer Change Orders (MCOs), and Site Change Orders (SCOs) classes. However, the other Change classes (Change Requests, Deviations, Stop Ships, and PCOs) do appear in this list. **For expressions pertaining to \$CURRENTREV, only statuses pertaining to workflows developed for ECOs, MCOs, and SCOs should be used.**

- The condition **\$CURRENTREV Equal To \$STATUSTYPE.PENDING** evaluates to True if the selected item revision corresponds to a Change whose current status type is Pending. Similar statements can be constructed for other status types as well. The supported status type variables include:

\$UNASSIGNED

\$STATUSTYPE.PENDING

\$STATUSTYPE.SUBMIT

\$STATUSTYPE.REVIEW

\$STATUSTYPE.RELEASED

\$STATUSTYPE.COMPLETE

\$STATUSTYPE.HOLD

Note that **\$STATUSTYPE.CANCEL** is not available, since revisions pertaining to Canceled changes do not appear in the Rev dropdown list for items, and therefore may not be selected. In any case, the expression **\$CURRENTREV Equal To \$STATUSTYPE.CANCEL** would always evaluate to False.

- The condition **\$CURRENTREV Equal To Default Change Orders.Pending** evaluates to True if the selected item revision corresponds to a change that is assigned the Default Change Orders workflow, and whose current status is Pending. Similar statements can be constructed for other workflows and statuses as well. The general format is:

<WorkflowName>.<StatusName>

Note that <WorkflowName>.CANCEL is not available.

- While the workflow status values above cover all possible statuses for a pending or released revision, special criteria values are provided for the Introductory revision because there are no changes associated with that revision.

Based on the possible use cases, one of the following conditions would hold true when an Introductory revision of an item is selected (the term Pending change below implies a change in its pre-Released state, for example, Submitted, Review):

- **\$INTRODUCTORY_NOCHANGE** – There are no Pending or Released changes against the item (the **Changes** tab is empty). This condition also covers the case where any past Pending changes against the item have been soft or hard deleted from the Agile system.
- **\$INTRODUCTORY_PENDINGCHANGE** – The item has never been released, but there are Pending changes against the item. This condition also covers the case where the item has been released in the past, but the released changes have all been unreleased
- **\$INTRODUCTORY_RELEASEDCHANGE** – The item has one or more released changes against it. It may also have one or more Pending changes against it.

Note that an expression involving any of these three values will always evaluate to False if the selected revision is not the Introductory rev.

- To support the use case where users are allowed to read, make changes to or get file attachments from only the latest released revision of an item (this is important in regulated industries (for example, medical devices) where it is important that users refer to only the latest design or spec files), another variable called \$LATEST is introduced to the set of valid values for \$CURRENTREV expressions. The expression **\$CURRENTREV Equal To \$LATEST** evaluates to True if the selected revision is the Latest Released revision for the item. This expression also evaluates to True if the selected revision is Introductory and the item does not have any Released ECOs, MCOs or SCO's against it.

The expression **\$CURRENTREV Equal To \$LATEST** has the exact same functionality as the obsolete expression **Title Block.Rev Equal To \$LATEST**.

The behavior of item Description on the Latest Released revision deserves special mention here. When a user has the privilege to modify the Latest Released revision only (**Title Block.Rev = \$LATEST**) and not Pending revisions, and he modifies the description of the item, he is presented with a message asking if he'd like to update the description of all the pending revisions to this updated description. If the user chooses to do so, all the pending revision descriptions are also updated irrespective of whether or not the user has privilege to update descriptions on pending revisions.

Rules for Using the \$LATESTREV Variable

The \$LATESTREV variable is another Administrator attribute used to construct criteria based on the workflow status of the Change Order (ECO/MCO/SCO) corresponding to the latest released revision of an item.

The following rules govern the usage of the \$LATESTREV variable:

- \$LATESTREV may only be used in defining criteria against objects belonging to the Items base class, which includes Parts and Documents classes and their subclasses..
- \$LATESTREV is available as a value in the Attribute list. \$LATESTREV itself does not evaluate to a value. The whole condition itself is evaluated as a boolean expression.

- Unlike **\$CURRENTREV**, you must specify only the **Match If** field to construct a valid expression using **\$LATESTREV**. The only operators available for **Match If** are **Is Released** and **Is Introductory**.
- The condition **\$LATESTREV Is Released** evaluates to True if the selected item has been released on at least one Change of type ECO or MCO. Note that SCO is not included because an item has to be released on an ECO or MCO before it can be released on an SCO.
- The condition **\$LATESTREV Is Introductory** evaluates to True if the selected item does not have any released ECO or MCO against it.

Item Relationship Creation Using **\$CURRENTREV** and **\$LATESTREV** Criteria

To create a relationship and a relationship rule between any two Agile objects requires that the user has Modify privileges for both objects applied to <object>.Relationships.Name attribute (to create a relationship) and <object>.Relationships.Rule (to create a relationship rule). See [Some 'Modify' Basics and Rules](#) on page 246.

Modify Item privilege masks that use a **\$CURRENTREV** criteria condition to limit item modification also limit which items can be selected for item-to-item relationships. For example, if a user has a Modify privilege that limits his Modify Item privilege mask with the criteria condition **\$CURRENTREV Equal To \$STATUSTYPE.PENDING**, that user can modify only items with a change in the Pending status. The items that can be selected for item-to-item relationships are also limited to items with a change in the Pending status.

To avoid this limitation to item-to-item relationships when using **\$CURRENTREV** criteria conditions in Modify Item privilege masks, use the following criteria:

```
$CURRENTREV Equal to $LATEST
```

to create a Modify privilege mask with only one Applied To attribute, Item.Relationship.Name. That is:

```
Modify Items $CURRENTREV Equal to $LATEST Applied To  
Item.Relationships.Name
```

To ensure that users can create item-to-item relationships between any two items, include this Modify privilege mask in any role that includes Modify Item privilege masks.

Note Relationships are not revision-specific.

Workflows

This chapter includes the following:

▪ How Workflows Automate the Change Control Process	129
▪ Workflow Basics	130
▪ Default Status-Based Workflows	133
▪ Status Types Defined	133
▪ Creating New Workflows with Save As.....	135
▪ General Workflow Properties.....	136
▪ Creating and Using Custom Workflows	139
▪ Status Properties Defined.....	145
▪ Criteria-Specific Properties Defined.....	151
▪ Workflow Functionality Testing	156
▪ Migrating Workflows to Production	158
▪ Changing Active Workflows	158

The Workflows node stores the default workflows that Agile PLM client users select to create and send routable objects for approval. From this node, you can also define and create custom workflows.

How Workflows Automate the Change Control Process

The **Workflows** node stores the default workflows that Agile PLM client users select to create and send routable objects for approval. From this node, you can also define and create custom workflows

A workflow is an organized sequence of stages involving people's decisions—their creation, modification, review, and approval or rejection of a routable object. An Agile PLM workflow is an automated sequence of statuses that a routable object follows as it goes through a company's change control process. (For a detailed description of a typical change control process, see the chapter about workflows in *Getting Started with Agile PLM*.)

Workflows automate the change control process in a variety of ways:

- The changes that are available for a particular routable object are completely configurable. When users create a routable object, they select a workflow from the list of workflows that are available for that routable object.
- When all required fields are filled in for a released routable object, and when all the approvers have signed off for a Review or Released status type, the routable object can be moved automatically—"autopromoted"—to the next status.
- Approval and rejection of the routable object occurs within defined permissions and other checks. You can preassign default approvers and observers.
- Email automatically notifies users of the creation and progress of a routable object. For example, when an approver does not respond within the specified time period, a reminder

email notification is triggered to be sent.

- If the approver does not respond within the specified period, the routable object is sent to that user's designated escalation person, who can approve or reject the routable object.
- By defining a workflow with multiple Review and Released statuses, routable objects can be sequentially routed to different lists of approvers and observers.
- A user can transfer authority to approve routable objects to another user for a specified period of time. With the appropriate privileges, a user can similarly transfer signoff authority for other users.

Modifying a Workflow

The following sequence applies to modifying a workflow in the **Workflows** node.

To modify the Workflow settings:

1. Under **Workflow Settings**, double-click **Workflows**. The Workflows window appears.
2. Double-click the workflow you want to modify, for example, Default Change Orders. The Workflow: Default Change Orders window appears. The setup tabs are:
 - **General Information**
 - **Status:** the Status table defines status properties, and the Criteria table defines criteria-specific properties.
 - **History**
3. With the **General Information** setup tab selected, in the field you want to edit, enter a new value or select from the dropdown list. The two **Criteria Matching Type** fields on the **General Information** tab should be left alone at this point.
4. When you have finished, click **Save**.

To modify this workflow's status properties or criteria-specific properties, begin by clicking the **Status** tab.

For information about changing workflows that are active (that is, are enabled and may have routable objects moving through them), see Changing Active Workflows.

Note Alterations to workflow statuses have implications for process extensions (see [Process Extensions](#) on page 105) and transfer orders (see *Agile Content Service User Guide*).

Workflow Basics

Routing Managers

Any object that can be routed for approval is a **routable object**. The user who oversees the routing and approval process is the *routing manager*. The various routing managers (see the table below) are simply roles assigned to users by the administrator. Once a user has been assigned a role of, say, change analyst, his name appears on the Change Analyst List and can be selected manually by a Java Client or Web Client user. Routing managers evaluate and assign routable objects, and

they receive email notifications pertaining to the objects to which they are assigned.

The following table lists routable objects and the corresponding default routing manager.

Routable object (with base class)	Default routing manager
Change: All changes except MCOs & PCOs: change orders (ECOs), change requests (ECRs), site change orders (SCOs), stop ships, deviations	Change analyst
Change: Manufacturer orders (MCOs)	Component engineer
Change: Price change orders (PCOs)	Price administrator
Declarations (all)	Compliance manager
Packages	Program manager
Product service requests (PSRs): problem reports and nonconformance reports (NCRs)	Quality analyst
Project: activities and gates	PPM program manager
Quality change request (QCRs): corrective and preventive actions (CAPAs) and audits	Quality administrator
Transfer Order: content transfer orders (CTOs) and automated transfer orders (ATOs)	Content manager

Other Workflow Basics

Here is some other basic information about Agile PLM workflows:

- A workflow consists of a unique name, one or more *matching criteria*, and a *status list*, or sequence of statuses. An enabled workflow is visible and usable by Agile PLM client users.
- Each workflow must be qualified by at least one matching criteria; these are broad qualifiers that determine which workflow a routable object may follow. Agile PLM tests the routable object against all the matching criteria for all the workflows and determines which workflows match the routable object.
- A workflow can contain any number of statuses. *Status names* are editable, but their underlying *status types* are not. Only one status type is required, Pending, and this must be the first status in the workflow. Three status types—Submit, Review, and Released—may be used multiple times in a workflow, with unique names for each instance. Review and Released are the most versatile status types.
- Each and every status in a workflow's status list comprises *status properties* and *criteria-specific properties*.
- Status properties define some specific actions that can be automatically triggered or manually performed—or both. Status properties determine what happens to the routable object when assigned people approve, reject, or even forget to review the routable object.
- Criteria-specific properties are defined by filters called *reusable criteria*, which are created separately and stored in the **Criteria** node. Each individual status may have many criteria-specific properties. Criteria-specific properties describe specific actions that are triggered

(automatically, or they can be manually performed) if the routable object meets the conditions defined in the reusable criteria while the routable object is entering or exiting a status. Criteria-specific properties apply to individual statuses, not to the workflow as a whole.

- For example, criteria-specific properties can be used to define the following actions for a specific Review status of a workflow. When a routable object enters the status, if the routable object's Product Line field contains, for example, Libra, a specific set of approvers is assigned. If the Product Line field contains Scorpio, a different set of approvers is assigned. If the Product Line field contains both Libra and Scorpio, both sets of approvers are assigned.

Keep It Simple!

Agile PLM workflows are a robust feature that offers a great deal of choice and flexibility for your company's change control process. For best results, plan thoroughly and gather all necessary data and information.

To prepare properly, follow these three steps before you attempt to customize Agile PLM workflows:

1. Compile information for tailored workflows. You must fully understand and define your company's required change control processes. This step is crucial to successful implementation of automated workflows.

This process is not covered in this manual. Consulting services are available from Oracle Consulting – Agile Practice consultants, who can provide you with assistance in creating business process validation plans and guidance. During business process validation, you can propose workflows to simulate real scenarios and typical usage.
2. Learn about Agile PLM workflows in this chapter and elsewhere in this manual.
 - Be sure you understand the purposes and limitations of the status types. See [Status Types Defined](#) on page 133.
 - Use default workflows at first, which you can use immediately without modification. See [Default Status-Based Workflows](#) on page 133.
 - Create some original workflows (in your test environment—see the next step) that meet specific needs at your company. See [Creating and Using Custom Workflows](#) on page 139.
3. Establish a testing environment and complete test procedure. Test all new workflows! For example, create a routable object and send it through your enabled workflow. In any case, verify that new workflows work correctly, and alter them as necessary. For more information, see:
 - Workflow Functionality Testing
 - Migrating Workflows to Production
 - Changing Active Workflows

Although you can create as many workflows as your company needs, you are encouraged to explore the capacities of the out-of-box default workflows first. Creating too many workflows too quickly could create maintenance issues later.

Default Status-Based Workflows

Agile PLM provides the following status-based workflows:

- Default Activities
- Default ATOs
- Default Audits
- Default CAPAs
- Default Change Orders
- Default Change Requests
- Default CTOs
- Default Declarations
- Default Deviations
- Default File Folders
- Default Gates
- Default Manufacturer Orders
- Default Non-Conformance Reports
- Default Packages
- Default Price Change Orders
- Default Problem Reports
- Default Site Change Orders
- Default Stop Ships

Note Default ATOs and Default File Folders are read-only workflows. They cannot be modified.

The default workflows can be used without modification. They ensure that all routable objects match criteria for a workflow. You can also tailor the default workflows to your requirements. If modifying the default workflows still does not meet your requirements, you can create custom workflows.

Caution	As a best practices approach, it is recommended that you save a set of the default workflows, unmodified and disabled. You can do this easily using Save As (see Creating New Workflows with Save As on page 135).
----------------	---

Status Types Defined

Agile PLM workflows are defined by their list of statuses, and each status is of a particular status

type. Workflows are created from five basic status types—Pending, Submit, Review, Released, and Complete. Two special status types, Cancel and Hold, handle routable objects that have failed to advance and must be stored.

The status types have sequence dependencies that determine where and how often you can use them in a workflow. A clear understanding of these dependencies is essential to constructing usable workflows. The following table defines the status types and provides details about these dependencies.

A workflow can have as many statuses as needed. Submit, Review, and Released are the status types that can be used more than once, with differently named and defined statuses. When you define a workflow with multiple Review and Released statuses, routable objects can be sequentially routed to different lists of approvers and observers.

Status type	Definition
Before a workflow is selected for a routable object	
Unassigned	Unassigned is the default initial status name before a routable object has been matched with a workflow.
Basic Status Types (Active)	
Pending	<ul style="list-style-type: none"> ▫ An originator is developing the routable object. ▫ A workflow must begin with a Pending status type; it is the first status in every workflow.
Submit	The Submit status type sends the routable object to the specified routing manager, who determines whether or not to promote the routable object to the next status.
Review	The Review status type routes the routable object to CCB members (approvers and observers). When all approvers have signed off, and required fields have been completed, the routable object is automatically promoted to next status in the status list if AutoPromote is on, or it is manually moved by the routing manager if AutoPromote is off.
Released	<ul style="list-style-type: none"> ▫ When a routable object enters the <i>first</i> Released type status, the software performs a series of checks; it also creates new revisions of the affected items (ECOs) with the new BOM, incorporates redlines into a new “rev,” or updates the manufacturer part information (MCOs). ▫ Like the Review status type, the Released status type may have approvers and observers and be routed for signoff and may be autopromoted. ▫ <i>Only the first Released status actually releases the routable object.</i> Subsequent Released status types—given distinguishing status names—provide additional review/approval cycles for the released routable object. ▫ Returning a released routable object to any of the first three status types <i>unreleases</i> the routable object—removes approvals that were gathered. A Deviation can be unreleased if it does not have affected items. <p>Note: Although Agile PLM allows you to configure Change Order workflows that allow the release of an item without specifying a value for the New Lifecycle Phase, configuration management best-practices require that a New Lifecycle Phase always be specified prior to releasing an item on an ECO or MCO. In order to make sure there is a New Lifecycle Phase, make sure it is a required field in the Workflow Criteria.</p>

Status type	Definition
Complete	<ul style="list-style-type: none"> ▫ If Complete status type is used, it must be the last <i>active</i> status in the workflow, and it may be used only once.
Special Status Types (Inactive)	
Hold	<ul style="list-style-type: none"> ▫ The Hold status types provides a way to temporarily remove a routable object from the workflow and reinsert it later. It is added to the <i>end</i> of the status list as it is <i>never</i> part of the active sequence of statuses. ▫ Hold does not unrelease a routable object. ▫ Given appropriate privileges, the user can manually move a routable object to Hold from any other status in the workflow <i>except</i> Complete (assuming it is listed as a valid next status under the Manual Valid Next Status property). It stays there until you manually move it back into the workflow. These moves require proper Change Status privileges.
Cancel	<ul style="list-style-type: none"> ▫ The Cancel status provides a way to remove a routable object from the workflow. It is not possible to re-activate the workflow once it is moved to Cancel status. ▫ Cancel un releases a routable object. ▫ Given appropriate privileges, the user can manually move a routable object to Cancel from any other status in the workflow <i>except</i> Complete (assuming it is listed as a valid next status under the Manual Valid Next Status property). <p>Note In assigning privileges to move a workflow to the Cancel status, the administrator must recognize the potential for user-error. Because a Canceled workflow can not be re-activated by any means, the fact that it is relatively easy to change a workflow to Cancel must be recognized and allowed for.</p>

You can use the default workflows without modification. It is best to work with the default workflows with no modifications until you are familiar with their uses and capabilities.

Caution Agile recommends using **Save As** to create “archive” copies of all the default workflows. This ensures that you can always return to an unaltered version if you have customized the default workflows.

Creating New Workflows with Save As

You can create a new workflow from an existing one and give it a new name. This makes it easy to create an archive of the default workflows or to create a custom workflow that starts from the foundation of a proven default workflow.

To create a new (or “archive”) workflow from an existing one:

1. Under **Workflow Settings**, double-click **Workflows**. The Workflows window appears.
2. Double-click the workflow you want to base the new workflow on. That specific workflow's window appears.
3. Click the **Save As** button, and enter a descriptive, unique name. Autogenerate the API name

If you are creating an archive copy, use a name that will distinguish it as “off limits,” for example, “EXAMPLE Default Chg Orders.”

4. Click **OK**. The setup window displays the new name in the title bar.
5. Change the information as necessary, and click **Save**.

The new workflow is disabled (the Enabled property is No), and can remain so for archived workflows, or will be enabled when you have finished constructing a customized workflow.

Note Workflows created with **Save As** are disabled. A common mistake after creating a custom workflow is forgetting to enable it.

Each Change Status privilege mask applies to one status of one specific workflow. You must create Change Status privilege masks for each status of every new workflow you create and enable, including workflows created by Save As. See [Change Status](#) on page 221.

General Workflow Properties

Double-clicking the **Workflows** node opens the Workflows window, which lists the available default workflows and any custom workflows you have created.

The window has the following buttons: **New**, **Delete**, **Edit Workflow Init Settings**, **Import**, **Export**, **Export All**, **Enable**, and **Disable**.

The **Edit Workflow Init Settings** button opens a dialog box with the following fields:

Field	Type	Default
Default Initial Status Name	Text	Unassigned
Status Stamp Color	List (of colors)	Blue

General Information Tab

When you double-click a default workflow in the Workflows window, the **General Information** tab of the setup window opens. The tab has the **Delete**, **SaveAs**, and **Export** buttons. It has the following fields:

Field	Description
Name	The name of the workflow. Each workflow name must be unique
API Name	Unique systemwide identifier for objects and can be autogenerated. You can specify an API name, but internal consistency is enhanced by accepting the system-generated name.
Enabled	Enables or disables the workflow. An enabled workflow is visible and usable by Agile PLM client users.
Object Type	The type of routable object for which the workflow applies. Available for the following: changes, CTOs, QCRs, PSRs, projects, packages. Object types are listed in Agile PLM Class Structure on page 52. Object Type is read-only after the workflow is created.

Field	Description
Matching Criteria	Determines which routable objects can follow the workflow. Can use any reusable criteria, for example, All Change Orders.
Workflow Criteria Matching Type	Refines how the matching criteria determines which changes can follow the workflow. It defines what happens when a routable object meets one or more reusable criteria that contain information about affected items. Choose Same, All, or Some. See Workflow Criteria Matching Type on page 137.
Status Criteria Matching Type	Determines what happens when criteria-specific properties that contain information about affected items apply to a routable object. Choose Same, All, or Some. See Status Criteria Matching Type on page 138.

About Workflow name

The workflow's name and whether or not it is enabled are defined at this level. The default workflows are already enabled. For information about what takes place when a workflow is enabled, see [Status Properties Defined](#) on page 145. For information about modifying or fixing problems in active workflows, see [Changing Active Workflows](#).

When a workflow is created by the administrator, the **Object Type** field is limited to base class choices. The **Matching Criteria** property in a workflow selects an object type, and that is what the system picks up when a workflow is selected as the object type of an Event mask. For more information regarding Events and how they relate to Workflows, see [Event Management](#) on page 305.

Workflow Criteria Matching Type

For each workflow, by specifying a list of reusable criteria in the Workflow Criteria Matching Type property, you limit which changes can use that workflow. Some examples of possible reusable criteria applied as matching criteria are:

- **All MECOs** — Finds all the changes that are MECOs (mechanical ECOs).
- **Scorpio ECOs** — Finds all the ECOs that include “Scorpio” in the **Product Line(s)** field of the routable object.
- **Libra Project** — Finds all the changes that have any items on the **Affected Items** tab that contain “Libra” in the **Product Line(s)** field of the item.

For example, you might create a workflow named “General Use,” and select the three reusable criteria named above (All MECOs, Scorpio ECOs, and Libra Project) as the matching criteria for that workflow.

Example 1: If an Agile PLM client user creates a change that is a mechanical ECO (MECO), it successfully matches one of the matching criteria of the General Use workflow (All MECOs). The General Use workflow will appear in the **Workflow** dropdown list on the **Cover Page** tab of the change (Java Client) or the Cover Page page of the change (Web Client).

Example 2: If the user creates a change that is an ECO that includes “Scorpio” in the **Product Line(s)** field of the ECO, it successfully matches one of the matching criteria of the General Use workflow (Scorpio ECOs). The General Use workflow appears in the **Workflow** dropdown list on the **Cover Page** tab of the change (Java Client) or the Cover Page of the ECO (Web Client).

Example 3: If the user creates a change order and adds items to its **Affected Items** tab that contain “Libra” in the **Product Line(s)** field of the item, Agile PLM examines the **Product Lines** field on the **Affected Items** tab for every affected item. The General Use workflow will appear in the **Workflow** dropdown list on the **Cover Page** tab of the change (Java Client) or the Cover Page of the Change Order (Web Client) depending on the setting of the Criteria Matching Type property for the workflow:

- **Same** — All affected items must match the *same* affected item–based reusable criteria, in this case, Libra Project.
- **All** — When multiple affected item–based reusable criteria are used as matching criteria, *each* affected item must match at least one affected item–based reusable criteria; however, each affected item does not have to match the *same* reusable criteria.
- **Some** — One or more (but not all) affected items must match the affected item–based reusable criteria, in this case, Libra Project.

As the user adds items to the **Affected Items** tab and completes the fields on the tabs of the routable object, the **Workflow** dropdown list on the **Cover Page** tab may vary, depending on which matching criteria apply at the moment.

Status Criteria Matching Type

Because reusable criteria appear on a workflow’s **Status** tab for each discrete status, Status Criteria Matching Type applies to the groups of reusable criteria in each status. The property is applied in Agile PLM clients when a status’s criteria-specific properties contain information about affected items that is pertinent to the routable object, for instance, which approvers or observers should be assigned to it.

The property values and their behavior are listed below, followed by an example.

- **Same** — All affected items must match the *same* affected item–based reusable criteria in a given status. If *all* the affected items don’t match the same reusable criteria, the ECO does not satisfy *any* exit criteria, and the “If No Criteria Apply at Exit, Notify” property is applied.
- **All** — When multiple affected item–based reusable criteria are used as criteria-specific properties in a given status, *each* affected item must match at least one affected item–based reusable criteria; however, each affected item does not have to match the *same* reusable criteria. “All” ensures that every affected item has an appropriate approver.

For example, for each reusable criteria in a status that one of the affected items matches, the specified approvers are added to the **Workflow** tab of the ECO. If *each* of the affected items does not meet *at least* one of the reusable criteria, the ECO would not satisfy *any* exit criteria, and the “If No Criteria Apply at Exit, Notify” property is applied.

- **Some** — One or more (but not all) affected items must match at least one affected item–based reusable criteria in *each* status’s criteria-specific properties. For each reusable criteria in a status that one of the affected items matches, the approvers are added together for the ECO.

The general setting (that is, on a workflow’s **General Information** tab) for Status Criteria Matching Type

is validated against *both* the reusable criteria (the group of criteria in that status's Criteria table on the **Status** tab) for the present status *and* the reusable criteria for the next status in the workflow.

For example, Sarah has written a change called "ECO2" with the following affected items (on the **Affected Items** tab of the change in Java Client):

- Affected Item 1 (AI-1): **Product Line** = Aries, **Category** = Electrical
- Affected Item 2 (AI-2): **Product Line** = Aries, **Category** = Mechanical

For ECO2's Submitted status (Submit status type), on the Criteria table on the **Status** tab, is a reusable criteria that specifies:

- Reusable Criteria W (RC-W): **Product Line** = Aries, **Affected Item.Category** = Electrical, **Required fields** = change description

Next, for ECO2's CCB status (Review status type), on the Criteria table on the **Status** tab, is a reusable criteria that specifies:

- Reusable Criteria X (RC-X): **Product Line** = Aries, **Affected Item.Category** = Mechanical, **Approver** = Paul

If Sarah wanted to move the change from Submit to CCB, ECO2's Status Criteria Matching Type (SCMT) is set to All, AI-1 (the Electrical part) now matches RC-W, but AI-2 (the Mechanical part) does not match RC-W. If Sarah put RC-X under Submit as well, AI-2 now matches a criteria for Submit; however, because Criteria Matching Type is set to All, the change still cannot move to CCB because AI-1 does not match RC-X under CCB.

If SCMT is set to Some, Sarah can advance her change in both cases because one of the affected items matches a criteria for each status (a different AI for each status in this case, first Electrical, then Mechanical).

If SCMT is set to Same, even after Sarah adds RC-X to Submit, ECO2 is not able to advance because each affected item does not match each criteria: AI-1 matched RC-W and AI-2 matched RC-X.

Creating and Using Custom Workflows

You will probably find it is much easier to create a new workflow by saving one of the default workflows with a new name (see [Creating New Workflows with Save As](#) on page 135), and then modifying the status properties and criteria-specific properties to suit your purposes.

The value of creating a custom workflow from scratch is that you go through all the elements of a workflow so that you are more familiar with the entire process, including the point where you will have to troubleshoot a workflow that is not doing what it is supposed to.

When creating a custom workflow, you must specify the following things:

- Name of the workflow.
- API name of the workflow.
- Matching criteria — at least one for any workflow.
- Status list — including how many statuses, status names, status types.

- Status properties — defined for each status in the workflow.
- Criteria-specific properties — defined for each status in the workflow.

Before You Begin

It is important to plan as thoroughly as possible before you create an original workflow. To get the most out of this process, you need to do *all* of the following:


- Read this manual and become familiar with workflows documentation.
- Enable and use one or more of the default Agile PLM workflows in live situations (see [Default Status-Based Workflows](#) on page 133).
- Compile specific information and data that define what you need an original workflow to do. This includes a sequence of statuses that differ from those in the default workflows.

Custom Workflow Example

The next several sections describe how to create the workflow in the figure below. This customized workflow demonstrates several departures from the “one status per status type” structure of the default workflows:

- The Submit status does not immediately follow the Pending.
- There are three Review statuses. The names in the example are less important than the idea that you can have as many Reviews as you need.
- Two statuses use the Released status type—but the second one is named Manufacturing Planning, which acts like another Review. Because the Review and Released status types share many attributes—approvers, autopromotion, and so on—this permits additional Review cycles *without unreleasing the routable object*. If a routable object enters a Review *following* a Released status type, it is *unreleased*, which means:
 - The routable object must qualify again for release (through the release audit: see Release Audit, or Audit Current Status for Conditions to Release).

Any revisions that were assigned to the affected items are revoked.



Guidelines for Creating Workflows

The guidelines below describe the steps required to build a custom workflow. The steps are explained in detail in the following sections.

To build a custom workflow:

1. Define your change control process, including the kinds of routable objects you'll need to process with workflows.

Contact your Agile representative or Agile Consulting Partner for help in defining your workflow

processes.

2. Create all required reusable criteria from the **Criteria** node first; these are necessary to describe (for the system) the distinguishing characteristics of the workflow.

See [Criteria](#) on page 119.

3. Create a new workflow and give it a unique name, but don't enable it. Enabling is the final step.

See [Creating a New Workflow](#) on page 142

4. Select at least one reusable criteria (defined from the **Criteria** node) for the matching criteria.
5. Create the Status list for the new workflow.
6. Modify the properties of each status on the **Status** tab, understanding that the available status properties are different for each status type.
7. Add criteria to the Criteria table on the **Status** tab and define the criteria-specific properties of the statuses, particularly required fields and approvers and observers.
8. Assign appropriate privileges that allow users to refine statuses in a new workflow. The privileges most pertinent to workflows are Add Approver/Observer, Remove Approver/Observer, Change Status, Override; Transfer Authority for Self, and Transfer Authority for Others.

See [Privileges and Privilege Masks](#) on page 211. To move a routable object through the new workflow, users must have Change Status privileges for that specific workflow; see [Change Status](#) on page 221.

9. Set SmartRules for systemwide workflow functionality. See General System Settings.
10. Enable the modified workflow and test it. When it is ready, notify your Agile PLM users that it is available. They will be able to use it the next time they log in to Agile PLM.

Creating a New Workflow

It will be helpful to create a list like this table with the statuses of your new workflow defined both by name and by status type.

Status name	Status type
Originate	Pending
Review-PM	Review
Submit-CA	Submit
Review-CCB	Review
Review-Sr.PM	Review
Released	Released
Review-Mfg.Planning	Released
Implemented	Complete

To create a new workflow:

1. Under **Workflow Settings**, double-click **Workflows**. The Workflows window appears.
2. Click **New**. The Create Workflow dialog box opens.
3. Enter a unique name, such as **Taurus ECOs** and an API name.

A “best practice” may be to conceptualize a system of naming your original workflows. For some ideas about naming conventions, refer to [Creating a New Criteria](#) on page 121 and [Naming Privilege Masks](#) on page 227.

The **Enabled** field on the **General Information** tab is not available at this point. No new workflow can be enabled until it is complete. When you have completed a new workflow, you must enable it to use it. Agile PLM client users will see the newly enabled workflow the next time they log in to Agile PLM.

4. In the **Workflow Criteria Matching Type** and **Status Criteria Matching Type** dropdown lists, allow (or select) **Same**.

Matching criteria are used to find which workflows may be used for each routable object. Agile PLM checks all the matching criteria for all the workflows and determines which workflows match the routable object. For example, if a reusable criteria called All Taurus ECOs is a matching criteria for a workflow, then the user can select that workflow for an ECO in the Taurus project.

The factors you need to consider to take full advantage of these three criteria properties are fairly complex. Detailed information is provided in [Using Affected Items Tab Fields in Reusable Criteria](#) on page 123.

5. From the **Object Type** dropdown list, select the appropriate base class.
6. In the **Matching Criteria** dropdown list, scroll down and select All Change Orders.
7. Click **OK**. The new workflow is added to the list on the Workflows window.

To complete setting up the new workflow, you need to double-click it in the Workflows window and create statuses with defined status properties and criteria-specific properties.

To create statuses for a new workflow:

1. Open the workflow, click the **Status** tab, and click **New** just above the Status table. The Add Workflow Status dialog box appears.
2. Type an appropriate name; in our example, it is **Originate** and API name.
3. In the **Status Type** dropdown list, select an appropriate status type, in this case Pending (the required first status for any workflow).
4. In the **Status Stamp Color** dropdown list, select a color for the type in the status stamp that will appear for that status in Agile PLM clients.
5. Click **OK**. Repeat this process for all statuses you wish the workflow to have.

If you scroll to the right in the Statuses table, you see two status properties—“If No Criteria Apply At Exit, Notify” and “Manual Valid Next Status”—that need to be given values.

Agile recommends creating all the statuses, then filling in the status properties before considering the criteria-specific properties. However, with so many factors to consider, the most important thing is to develop your own method or systematic approach to constructing an error-free workflow.

To designate reusable criteria for a new workflow:

1. Open the workflow, click the **Status** tab, select a status (row) in the Status table, then click the **New** button just above the Criteria table. The Add Workflow Criteria dialog box appears.
2. The **Status Name** field is grayed and populated with the name of the status you have selected. Click the down arrow for the **Select Criteria** field, and select one or more reusable criteria for that status.
3. When you have finished, click **Save**.
Repeat this process for all statuses in the new workflow.
4. When you have completed the construction of your custom workflow, and have verified that it is ready for users to apply routable objects (see Workflow Functionality Testing), you need to enable it. In the setup window for the workflow, select Yes in the **Enabled** dropdown list.

Note A new workflow is disabled as you create it. A common mistake after creating a custom workflow is forgetting to enable it.

Note To move a routable object through the new workflow, users must have Change Status privileges for that specific workflow. See [Change Status](#) on page 221.

Agile PLM client users will see the new workflow when they restart their client application *after* you have enabled the workflow.

When a New Workflow is Enabled

When a workflow is enabled, the system checks the following items:

- The first status is the status type Pending.
- If there is a status of status type Complete, then it must be the final status of the workflow (excluding special statuses Cancel and Hold).
- The workflow's matching criteria must contain at least one reusable criteria.
- Each status in the workflow must be assigned at least one reusable criteria in the workflow's Criteria table.
- If there are Cancel or Hold statuses, they must appear at the end of the status list. If there is a Hold status, it must be the last status on the list.

If any of these requirements are not completed, an error message appears, and the workflow is not enabled.

Routing to a User Group

A user can assign a user group (global group, not a personal group) as an approver or observer using valid approvers and observers. The administrator or Agile Web Client user who is assigning a user group can select whether one member or all members must sign off the routable object. You can select either *[group name - Any]* or *[group name - All]*. See [Adding User Groups as Approvers of a Change](#) on page 183.

When *[group name - Any]* (for example, *[Manufacturing - Any]*) has been assigned as an approver or observer on a routable object, the following things are true:

- All users who are members of the user group see the routable object in their Inboxes.
- All users who are members of the user group receive the email notifications.
- Only *one* member of the user group needs to approve the routable object. When one user has approved the routable object, all users in the user group have their Inboxes updated, and the routable object is removed where appropriate.

The person who signed off the routable object is recorded on the **Workflow** tab as the signoff user.

When [*group name* - All] (for example, [Manufacturing - All]) has been assigned as an approver or observer on a routable object, the following things are true:

- All users who are members of the user group see the routable object in their Inboxes.
- All users who are members of the user group receive the email notifications.
- All the users who are members of the user group need to approve the routable object.

Status Properties Defined

This section describes all of the Status Properties found in Agile PLM workflows. When you double-click a default workflow in the Workflows window, then click the Status tab, the status properties are found in the Status table: double-click a status in the table, the Workflow Status: [Status Name] dialog appears.

If No Criteria Apply At Exit, Notify

Answers the question: Who should be notified if the routable object does not match its present criteria (that is, it is stuck)?

General default (in default workflows): \$CHANGEANALYST (see [Routing Manager Variables](#) on page 18)

This property indicates who is notified by automatic email if the routable object cannot advance to the next status because does not meet the conditions defined by the criteria in the current status' criteria-specific properties. If a routable object cannot be promoted to the next status in the workflow because there are no criteria that permit the promotion, the defined people are notified by automatic email.

Use the Address Book dialog to add users, user groups, Originators, Approvers (all approvers for statuses the routable object has already gone through), and Observers (all observers for statuses the routable object has already gone through) to be notified.

Note If the email notification is disabled, email will not be sent. See [Notifications](#) on page 279.

Manual Valid Next Status

Answers the question: Besides the next status in the status list, what are other statuses the routable object could go to from the present one?

General default (in default workflows): (no general default)

For each status, use the Choices–Selected dialog to define additional valid “next statuses” that the routable object can move into from the current status. The system understands that the *next* status in the workflow’s status list is always valid, so that status is not present in the Choices list. (The current status is, of course, never a valid “next status.”) The system does *not* assume validity for Complete (since there is *no* status after a routable object arrives at Complete), Cancel or Hold (since they are never part of a workflow), so these must be specified.

Caution	In assigning privileges to move a workflow to the Cancel status, the administrator must recognize the potential for user-error. Because a Canceled workflow can not be re-activated by any means, the fact that it is relatively easy to change a workflow to Cancel must be recognized and allowed for.
----------------	---

Save Routing Slip Content when Advancing Change

When the user manually advances a workflow to the next status, the routing slip appears to be filled in. This contains approvers, observers, “notify” users, and comments, and the user may spend several minutes completing the slip. When user clicks **Route**, Agile performs an automatic workflow status audit and presents the user with a dialog if a problem is found. The user is asked if he wants to continue: previously, if No was selected, the user was returned to the routable object and lost all the work; this has been fixed so the routing slip content is preserved.

Send Workflow Status Comments and Notifications to all Previous and Current CCB Members

When sending comments from a Review or Released status in a change, the user can specify whether the comments are to be sent to only the *current* review or released status reviewers – that is, for the workflow’s current status – or if comments are to be sent to all reviewers in both current and previous Review and Released statuses. A dropdown box (after the “Notify Reviewers for” checkbox) contains Current **Status** and **Current and Previous Statuses** for selection.

AutoPromote

Answers the question: Will the system automatically promote the routable object to the next status?

General default (in default workflows): No

Use the AutoPromote property to permit a routable object to automatically advance to its next status. For each Review and Released status type, you can determine if the workflow can be autopromoted to the next status.

When a routable object enters a status where AutoPromote is enabled, the system immediately attempts to autopromote it; if there are no approvers and all the required fields are complete, the routable object advances to the next status. Status advance is usually more involved than that scenario: for example, Review statuses will often have one or more approvers (and all approvers at a current status must approve the routable object for it to advance), and required fields can easily block autopromotion to the next status.

Also, the Change Status Approver Rejected Change SmartRule must be set to Allow for an approver’s rejection not to hold up autopromotion of the workflow.

-
- Note** Autopromote checks required fields only once when the workflow *enters* a specific status. However, when the last required field is populated, the system registers this fact and the routable object does autopromote to the next status.
- Note** However, Autopromote does check the workflow every time an approver either approves or rejects. If there are more approvers who have not yet approved or rejected, the status is not advanced; when the final approver approves or rejects, the Autopromote function evaluates according to the above-named SmartRule and promotes the status or not accordingly.
-

If not all approvers have approved the routable object, anyone who has the Override privilege can still manually promote it. If the routable object is rejected by an approver or other participant with appropriate permissions, the routable object goes to the status defined in If Rejected, Set Status To (see If Rejected, Set Status To), which is done automatically, whether the AutoPromote feature is on or off.

The AutoPromote feature needs to be set in relation to the Override privilege and the following two SmartRules:

- Change Status Approver Rejected Change
- Change Status Observer Rejected Change

Caution	When these two SmartRules are set to Warning, and an approver or observer rejects to the routable object, the system still autopromotes the routable object and records the warning on the History tab of the routable object.
----------------	---

You can define required fields that, when filled in on a routable object, determine if it can be promoted to the next status (see Entry Required Fields and Exit Required Fields). All required fields for a status must be filled in before it can be autopromoted to the next status. For example, when the last user approves the routable object and all required fields are present, the routable object immediately advances to the next status.

Caution	Do not alter any property before the Released status in any workflows for CTOs (content transfer orders). For instance, if you set AutoPromote to Yes, the CTO output files will not be generated.
----------------	--

If AutoPromote Fails, Notify

Answers the question: Who should be notified if AutoPromote fails?

General default (in default workflows): \$CHANGEANALYST (see [Routing Manager Variables](#) on page 18)

For each Review and Released status type, the Agile PLM administrator defines who is notified by automatic email if AutoPromote fails.

When the routable object is approved by all approvers, the system attempts to autopromote the routable object. AutoPromote fails if:

- Not all the required fields are filled in
- SmartRules are not adhered to

Autopromote checks required fields only once when the workflow *enters* a specific status. However, when the last required field is populated, the system registers this fact and the routable object does autopromote to the next status.

If the autopromotion fails, this fact is captured and automatically emailed to users and groups identified in the current status's setting for If AutoPromote Fails, Notify.

Ability to Fail Autopromote More than Once within same Change Status

This feature notifies whomever is specified in the status's If Autopromote Fails, Notify setting each time a change order fails to autopromote if new approvers were added since the last autopromote failure. Additionally, History is updated. Autopromote fails when a new approver is added but doesn't complete all workflow-required fields.

Use the Address Book dialog to add users, user groups, Originators, Approvers (all approvers for statuses the routable object has already gone through), and Observers (all observers for statuses the routable object has already gone through) to be notified.

The email regarding failure of autopromotion is sent only when there is a failure after the last approver (designated for that status) has approved the routable object. The system sends *one* email notification of failure to autopromote.

Note If the email notification is disabled, email will not be sent. See [Notifications](#) on page 279.

Ad Hoc Approvers/Observers

Answers the question: Can “ad hoc” approvers and observers be added once the routable object has entered the status?

General default (in default workflows): Yes

For each Review and Released status type, the Agile PLM administrator defines whether approvers and observers can be added as a routable object actively progresses. When this property is set to Yes, users with Add Approver and Remove Approver privileges can add or remove approvers and observers on the **Workflow** tab of a routable object in a Review or Released status type. They are also prompted with an Ad Hoc Approvers/Observers window during the release cycle.

Note A user with the Remove Approver/Observer privilege may successfully remove an observer from one status and then not be allowed to remove approvers and observers on the next status; this indicates the Ad Hoc Approvers/Observers property for the latter status is set to No.

If Rejected, Set Status To

Answers the question: Should the status be automatically changed if a user rejects the routable object? (If so, enter the appropriate status.)

General default (in default workflows): (none)

For each Review and Released status type, the Agile PLM administrator defines If Rejected, Set Status To. If the routable object is rejected by an approver or other participant with appropriate permissions (this status property does not apply to observers), the routable object goes to the

status defined in this setting. This is done automatically, whether the AutoPromote feature is on or off.

Note Although it is possible to set this property so the routable object moves forward despite a rejection, Agile recommends that it be used to prevent the routable object from advancing until the reason it was rejected is examined. Note that if this status property is set to null (no setting), then when a user rejects the change, the workflow will advance to the default status, that is, the next status in the workflow.

If Rejected, Notify

Answers the question: Who should be notified if the routable object is rejected?

General default (in default workflows): \$CHANGEANALYST (see [Routing Manager Variables](#) on page 18)

For each Review and Released status type, the Agile PLM administrator defines If Rejected, Notify. This property indicates who is notified by automatic email if the routable object is rejected by an approver or observer.

Use the Address Book dialog to add users, user groups, Originators, Approvers (all approvers for statuses the routable object has already gone through), and Observers (all observers for statuses the routable object has already gone through) to be notified.

Note If the email notification is disabled, email will not be sent. See [Notifications](#) on page 279.

Reminder Period

Answers the question: How long after a routable object has been routed for approval should approvers be sent email reminders to approve or reject it (at that status)?

General default (in default workflows): 48 hours

The reminder period is a period of time defined for each Review and Released status type in all workflows. When the reminder period elapses, if an approver has not approved or rejected a routable object, a reminder email notice is sent to the approver. The routing manager receives a similar email notice, which also includes a list of the approvers who received reminder email.

If you delete an existing value or attempt to leave the field empty (null), clicking **Save** results in a 0 being placed by the system. A value of 0 is the same as disabling the property, and no reminder notifications will be sent.

Note If the email notification is disabled, email will not be sent. See [Notifications](#) on page 279.

Each Review and Released status type has its own reminder period. The reminder period is set in hours and begins when the routable object enters each Review or Released status type. If a workflow has multiple Review or Released status types, each of these may have reminder periods of different lengths. The reminder periods for the default workflows are all 48 hours.

Review Escalation Period

Answers the question: How long should the system wait before escalating a routable object?

General default (in default workflows): 96 hours

The review escalation period is a period of time defined for each Review and Released status type in all workflows. When the escalation period elapses, if an approver has not approved or rejected a routable object, email is sent to the approver's appropriate designated escalation person. The routing manager receives similar email, notifying her that the routable object has been escalated to the specified designated escalation person. The designated escalation person may approve or reject the routable object in the place of the original approver.

If you delete an existing value or attempt to leave the field empty (null), clicking **Save** results in a 0 being placed by the system. A value of 0 is the same as disabling the property, and no reminder notifications will be sent.

Note If the email notification is disabled, email will not be sent. See [Notifications](#) on page 279.

Each Review and Released status type has its own review escalation period. The review escalation period is set in hours and begins when the routable object enters a Review or Released status type. If a workflow has multiple Review or Released status types, each of these may have review escalation periods of a different length. The review escalation periods for the default workflows are all 96 hours.

Escalation occurs only once per status for any sequence of user (or user group) to the designated escalation person.

Designated Escalation Person

You can define a designated escalation person for each user from the **Users** base node (see Users and User Groups). This is useful for expediting the routable object when a particular user has not reviewed and signed off on the routable object. You can also set a designated escalation person for each global user group from the **User Groups** node.

All escalation assignments are done from the Administrator nodes. Each user or user group may have multiple designated escalation persons. (Personal groups do not have designated escalation persons.)

If the review escalation period elapses, the approver's designated escalation persons are notified by email that the approver has not responded to the routable object. Now the designated escalation persons may approve or reject the routable object in the place of the original approver. The designated escalation person's name is recorded in Agile Java Client on the **Workflow** tab and the **History** tab as the Signoff user.

Note If the email notification is disabled, email will not be sent. See [Notifications](#) on page 279.

You determine whether a user's designated escalation persons can sign off a routable object at any time (= Always), or only after the escalation period has elapsed (= After Escalation). (See [User Properties Defined](#) on page 172.) The escalation person may or may not have appropriate permission to approve or reject the routable object, but the notification still goes through. If, for

example, a user's manager is his designated escalation person but is not involved with the routable object approval process, the manager would at least know the routable object had been held up, and could take appropriate action.

Note If the designated escalation person is a group, only one member of the group needs to sign off the routable object. When the routable object has been signed off, the routable object no longer appears in the Inbox of the other members of the group.

Comments for Approval

Answers the question: Should comments be required in the Review status of this workflow when it is rejected?

General default (in default workflows): Allowed.

For each Review status, the Agile PLM administrator can define whether approval comments are allowed, required, or prohibited. The default "Allowed" means that comments are allowed, but not required for the workflow in that status. "Required" means that when an Approver approves the workflow at that status, he must enter a comment for the workflow to proceed. "Prohibited" means that when an Approver approves the workflow at that status, he cannot enter a comment for the workflow to proceed.

Comments for Rejection

Answers the question: Should comments be required in the Review status of this workflow when it is rejected?

General default (in default workflows): Allowed.

For each Review status, the Agile PLM administrator can define whether rejection comments are allowed, required, or prohibited. The default "Allowed" means that comments are allowed for rejection, but not required for the workflow. "Required" means that when an Approver rejects the workflow at that status, he must enter a comment for the workflow. "Prohibited" means that when an Approver rejects the workflow at that status, he cannot enter a comment for the workflow.

Criteria-Specific Properties Defined

This section describes all of the Criteria-specific Properties found in Agile PLM workflows. When you double-click a default workflow in the Workflows window, then click the **Status** tab, the criteria-specific properties are found in the Criteria table. First select a status (row) in the Status table, that status appears in the Criteria table; double-click the row in the Criteria table, the Workflow Criteria: [Criteria Name] dialog appears.

Approvers and Observers

Answers the question: Who should approve or reject, and who should simply observe, the routable object in this status?

General default (in default workflows): (none)

The Agile PLM administrator defines default approvers and observers, who are selected automatically—and notified by email—when the routable object enters the Review or Released status type. The default approvers and observers are assigned to a routable object based on the

attribute values and the matching criteria of the workflow when it enters the Review or Released status.

Note If the email notification is disabled, email will not be sent. See [Notifications](#) on page 279.

Criteria Usage

Answers the question: What are the criteria-specific properties for this status?

General default (in default workflows): All Change Orders for Default Change Orders workflow

Criteria are the conditions that specify how the reusable criteria work in the specific status. Each status must have at least one reusable criteria in its criteria-specific properties.

Criteria are checked when the routable object is about to exit the particular status. Criteria also define which criteria-specific properties apply. Several criteria-specific properties could be applied to a single routable object.

Because this is a comprehensive topic, for more information about criteria, see:

- [Criteria](#) on page 119
- [Privilege Mask Component 3: Criteria](#) on page 230
- In *Getting Started with Agile PLM*, please see the chapter “Finding Agile Data with Searches” for information about how to use the Advanced Search process, which is similar to the Create Criteria process.

Default Change Analyst / Component Engineer

Answers the question: Who should be the default routing manager on this routable object? (See [Routing Manager Variables](#) on page 18.)

General default (in default workflows): Default routing managers can be chosen; for Pending status only.

You can define different default routing managers for each workflow (component engineers for MCOs, price administrator for PCOs, change analysts for the other changes, and so forth). Under the criteria-specific properties in the Pending status, you can select a different default change analyst for each criteria. If there is no default change analyst, the user can enter one. If the **Change Analyst** field is left blank in Agile Java Client, all change analysts are notified if \$CHANGEANALYST (or \$COMPONENTENGINEER) is set by the administrator.

Users can edit the **Change Analyst** field, assuming they have the proper privilege, but the system does not assign the new change analyst until the routable object moves from Pending to the next status. If the change analyst has been selected by the user, but the workflow has been set up with a default change analyst who does not match, the user is warned.

If you define more than one change analyst (that is, if the routable object matches multiple criteria for different change analysts), the user is warned when the routable object moves from Pending to the next status. He sees a dialog box with a list of change analysts and can select one for that workflow.

For information about adding approvers and observers, see [More about Affected Items: Adding](#)

[Approvers and Observers](#) on page 124.

Notify Upon Entry

Answers the question: Who should know that the routable object entered a new status?

General default (in default workflows): (none)

The Notify Upon Entry property indicates which users are notified by email when a routable object enters each status.

Use the Address Book dialog to add users, user groups, Change Analysts, Originators, Approvers (all approvers for statuses the routable object has already gone through), and Observers (all observers for statuses the routable object has already gone through) to be notified.

Note If the email notification is disabled, email will not be sent. See [Notifications](#) on page 279.

You can set whether the change analyst receives email notification that the routable object has been released. The Notify Upon Entry property is also used to set the Notify defaults for the status transition dialog boxes for manual status transitions. The user can determine who is notified (for example, originator, approvers and observers, change analyst).

Note If a user does not have Field-level Read privilege for the **Change Analyst** field on a routable object, and the default change analyst is specified on the Notify Upon Entry list, the label No Privilege appears in the **Notify** field of the Change Status dialog box. No Privilege is, of course, not recognized as a valid user, and will generate an error message.

Pass Release Audit

Answers the question: Should all the release audits (for example, SmartRules, required fields) be addressed before moving to the next status?

General default (in default workflows): No

User-available audits affected by Pass Release Audit: Status Audit and Release Audit

Status Audit answers: Can the routable object advance to the next status?

Release Audit answers: Do conditions (in this status) support releasing the routable object?

Agile PLM performs a complete release audit *automatically* when a routable object is promoted to its first Released status type.

At any time, an Agile PLM client user can use the **Audit Status** button or **Audit Release** button (or menu command) to initiate a status audit or release audit, respectively. These are discussed in Two Levels of Audit.

For each Pending, Submit, or Review status, the administrator specifies whether a routable object can advance from its present status with or without an audit, as follows:

- **Yes** — A release audit is performed, and the routable object does not advance unless the required fields are completed and the release checks and SmartRule conditions are met (see Release Audit, or Audit Current Status for Conditions to Release).
- **No** — The routable object can advance without being audited.

- **Warning** — During a status audit, you are prompted to choose whether to follow it with a release audit ("OK to perform Release Audit?") or not ("Cancel Release Audit").

This prompt may result in either an Error or Warning. There is an anomaly that causes a Warning to appear when you would expect an Error: when the user does not have Override privilege, and Pass Release Audit = Warning or No, the Status Audit should give an Error (which requires user to fix conditions) instead of a Warning.

Note Setting Pass Release Audit to Yes does, in effect, examine if the conditions in the present status would permit the routable object to be released, but this is not a cumulative process; that is, the audit does *not* consider the required fields of any *previous* or *future* statuses.

Even with the automatic release audit at the Released status, an advantage to setting up earlier audits (by setting Pass Release Audit to Yes for specific statuses) is to prevent impeding the routable object if it fails the audit at a Released type status. This can happen if the routable object has advanced past a status where a person who has pertinent information might enter it, for instance, the originator of the routable object who reviewed it at the Pending status, or a routing manager who reviewed it at the Submit status. It's better that a release audit reveal that something is missing at the status where the person who has the missing information can provide it.

For example, for ECOs, the release audit checks whether the rev number already exists. If you set Pass Release Audit to Yes at the Pending status of a routable object, this forces the originator to supply the correct rev number.

Please see the Caution about this property in [Override](#) on page 223.

Two Levels of Audit

There are actually two levels of audit available to the user, a status audit and a release audit, which are defined below. Every release audit includes a status audit.

The ability to audit a routable object does not require a privilege. The results of any audit can be copied to the Clipboard, pasted to a new document, and printed.

Status Audit, or Audit Current Status for Conditions to Advance

The status audit can be thought of as “auditing the current status for proper conditions to advance.”

The **status audit** is performed automatically when you use the Change Status function or the workflow attempts to autopromote to the next status. You can perform a status audit at any time by using the **Audit Status** button or menu selections. It performs the following checks:

- Makes sure the Exit Required Fields for the current status are filled in.
- If the current status is a Review status type or a Released status type, makes sure that all approvers have approved.
- Checks the workflow settings of the Pass Release Audit property for the current status. If Pass Release Audit is set to either Yes or Warning, Agile PLM also performs a release audit.

Release Audit, or Audit Current Status for Conditions to Release

The release audit can be thought of as “auditing the current status for proper conditions to release

the routable object.”

Agile PLM performs a release audit automatically when the routable object is promoted to the first Released type status in the workflow. You can perform a release audit at any time by using the **Audit Release** button or menu selections.

The release audit performs the status audit for both the current status and the release status.

It performs the following additional checks:

- For ECOs, checks if the proposed new revision number on the **Affected Items** tab already exists.
- For ECOs, SCOs, PCOs and MCOs, checks if there are manufacturer redlines that will be lost after the routable object is released.
- For ECOs and SCOs, checks if there are BOM redlines that will be lost after the routable object is released.
- For ECOs, SCOs, PCOs and MCOs, checks if there are conflicts due to another ECO, SCO, or MCO being released first.
- For ECOs, SCOs, and MCOs, if the BOM Multi-level Recursive SmartRule is set to Disallow, checks for recursive BOM structures, that is, when a subassembly includes one of its parent items from an upper level of the BOM tree structure on its own BOM. (A recursive BOM structure, if carried to its logical conclusion, would repeat indefinitely).

The BOM tree is evaluated from top to bottom. The Audit Release error message indicates, for each affected item with a recursive BOM, the first item found in the BOM tree whose first-level BOM table includes an item that appears at a higher level in the BOM tree, thus causing a recursive BOM structure. Although there may be multiple instances of recursive BOM structure in an affected item BOM tree, only the first found instance is displayed in the audit results.

- For ECOs, SCOs, and PCOs, depending on SmartRule settings, checks for duplicate items, duplicate find numbers and duplicate reference designators caused by a change rebase. (When there are multiple pending changes for the same item, when one change is released, the remaining pending changes are rebased on the latest released change.)
- For ECOs, SCOs, and MCOs, checks for duplication of the same manufacturer part on an item. (MultipleItemsPerManufPart is set to Warning or Disallow.)

(Duplication of the same manufacturer part on an item occurs when an item has multiple pending changes which associate the same manufacturer part to that item and one change is released. The remaining pending changes are rebased on the latest released change. The remaining pending changes now include manufacturer part redline modifications to add a manufacturer part that already exists on the released item's Manufacturers table.)

- For ECOs, SCOs, and MCOs, checks for the use of the same manufacturer part on multiple items. (MultipleItemsPerManufPart is set to Warning or Disallow.)

(Duplication of the same manufacturer part on multiple items occurs when multiple changes add the same manufacturer part to two or more item's Manufacturers tables, either by redline addition or redline replacement. When one of the changes is released, the manufacturer part's Where Used table is rebased to refer to the newly released item. The remaining pending changes now include manufacturer part redline modifications that would allow a single manufacturer part to be used by multiple items.)

- For ECOs, SCOs, and PCOs, if the Item Release First SmartRule is set to Disallow or Warning, then the routable object is checked to see if the child components have been released.

- Checks if any of the attachments of the routable object remain checked out.
- For every affected item, checks if any of the attachments remain checked out.
- Checks the Effectivity Date Order and Effectivity Gap SmartRule settings.
- Checks if items on the **Affected Items** tab have any other pending routable objects.
- For ECOs, validates the affected item's **Sites** tab **Make/Buy** setting with the site's **Site AML Allowed** and **AML Required on Buy** settings. For more information, see *Product Collaboration User Guide*.

Exit Required Fields

Answers the question: What are the required fields on the routable object and its affected items?
General default (in default workflows): (none)

Exit required fields are attributes or fields that must be completed for each Pending, Submit, Review, Released, and Complete status type before a routable object can exit that status.

Some required fields are uneditable, or defaults.

Caution Required fields are primary targets for status and release audits (see Pass Release Audit). In the default workflows, required fields are concentrated in the Review status type. In your custom workflows, however, you may wish to introduce required fields for other statuses. This will help users verify that specific required fields are passing the audits, which will prevent trying to pass a single audit containing many required fields at the first Released status.

Please see the Caution about this property in [Override](#) on page 223.

When exit required fields are not filled in by the time the routable object moves from one status to another, the user sees a dialog box listing the fields that are required.

If a user does not have the privilege to modify a required field, the routable object cannot be advanced to the next status until a user with sufficient privileges modifies it.

For Criteria written against Affected Items fields, the required fields are calculated independently for each affected item, based on which Criteria were matched.

Workflow Functionality Testing

It is strongly recommended that you thoroughly test the workflow before releasing it for general use. Depending on the size of your system, this may or may not be safely done within your users' production environment.

Areas of Workflow Validation

This section outlines some aspects of workflows that you will want to validate, within or outside the production environment. You may find reasons to modify a workflow as you test its functionality and

understand how it will support your change processes.

When testing workflow functionality, you should validate the following areas:

- Reusable criteria applied to the workflow and to each status
- Manual Valid Next Status settings for each status
- Status properties for each status
- Criteria-specific properties for each status
- Criteria Matching Type, for Matching Criteria of the workflow and for each status' criteria-specific properties
- All entry and exit required fields
- Autopromotions
- All notifications and approvals
- Reminder and escalation periods
- SmartRules
- Privileges for each role

Quick Tips on Testing

- You must enable the workflow before it will be available in the Agile PLM clients (see [Status Properties Defined](#) on page 145).
- If you are testing a new workflow (not modifications to one of the default workflows), you will also need to create some basic Change Status privileges so users can move routable objects through the workflow (see [Change Status](#) on page 221). To move a routable objects through the new workflow, users must have Change Status privileges for that specific workflow.
- Once you enable a workflow, you can make only limited changes to the its configuration (see Modifying Properties in an Enabled Workflow).
- To make more extensive modifications, you must disable the workflow (see Disabling, Changing, and Reactivating Workflows).
- Additionally, even if you disable the workflow, you may not make certain modifications if a routable object is in the workflow, including deleting or adding statuses from the status list (see What You Cannot Modify If a Workflow Has Any Routable Objects Applied). You can use Save As on a test workflow to create a new disabled workflow that will allow more extensive modifications.

In addition to functional testing, which determines if you have configured Agile PLM workflows correctly, it is recommended that you validate your business process and data migration systems. Consulting services are available from Oracle Consulting – Agile Practice consultants, who can provide you with guidance and assistance in creating business process and data migration validation plans. During the business process validation, you should use your proposed workflows to accomplish real scenarios and simulate typical usage. These activities will help you refine and confirm your workflow configuration and allow you to document your change processes in the

context of the Agile PLM solution for future reference and training purposes.

Migrating Workflows to Production

If you are in the first phase of an Agile PLM implementation, this section may not apply to you, because you do not yet have a separate production environment, and migration of initial Agile PLM configuration is a normal part of your production cutover process.

Quick Tip on Migrating Workflows

Quick Tip on Migrating Workflows

- In the Workflows window, use **Export** and **Export All** to export workflows, and use **Import** to migrate workflows from a test to a production environment, greatly reducing the number of manual steps required (see [Administrator Import and Export](#) on page 28).

Workflow Migration Process

Once you have validated your workflow configuration, you need to implement the workflows in your production Agile PLM system. The following steps outline the general process of migration.

1. Complete validation of workflow configuration in a test environment.
2. Run the following Administrator reports and save them to a local drive. Run additional reports as needed.
 - Agile Classes Report
 - Workflows Configuration Report
 - Criteria Library Configuration Report
 - Users Configuration Report
 - User Groups Configuration Report
 - SmartRules Configuration Report
3. Ensure that you have your workflow configuration clearly documented.

Changing Active Workflows

You may have to change a workflow that has been enabled. Some possible situations and your options are detailed in this section.

Note	It is not possible to delete a workflow that has been assigned to a routable object, even if the assignment has been withdrawn and the workflow is not assigned to any other routable object. We recommend either disabling an unwanted workflow, or modifying it so that it is once again usable.
-------------	--

Modifying Properties in an Enabled Workflow

You can modify a workflow that is enabled and visible to your Agile PLM users, either with or without a routable object moving through it. If the workflow is already in use (a routable object has been assigned the workflow), you cannot add statuses, although you can make other modifications, as described below.

Caution If you add a status to an enabled workflow, you *must* modify or create appropriate permissions and other Change Status privileges for each role in your Agile PLM system.

Note When you attempt to add a status to an enabled workflow, the workflow's Enabled property automatically changes to No.

When You Can Disable, Modify, and Re-enable a Workflow

If no routable object has been applied to a particular workflow, there is no problem with disabling it, modifying it, and re-enabling it. (To save duplicating efforts, you might email people who could be developing or close to originating a new routable object.)

What You Can Modify If a Workflow Has Any Routable Objects Applied

You *can* alter many properties after a workflow is enabled and a routable object is actively progressing. These properties are listed in the following table. You must disable the workflow to alter settings for properties. Also, be aware that a change analyst or an approver may want to react to a progressing routable object while it is disabled.

When you disable a workflow, these two best-practice actions are recommended:

- Notify appropriate people that the workflow is going to be disabled, and
- Alter the workflow promptly, enable it, and re-notify the affected users.

Properties of workflow	Status properties of each status	Criteria-specific properties of each status
Workflow name	Ad Hoc Approvers/Observers AutoPromote If AutoPromote Fails, Notify If No Criteria Apply At Exit, Notify If Rejected, Notify If Rejected, Set Status To Manual Valid Next Status Reminder Period Review Escalation Period	Approvers Default Change Analyst/ Default Component Engineer Notify Upon Entry Observers Pass Release Audit Required Fields

Properties of workflow	Status properties of each status	Criteria-specific properties of each status
Properties of statuses		
Status name		
Criteria-specific properties	You can add new criteria-specific properties to any status.	
Note: Depending on the setting being altered, routable objects already in process may or may not use the new setting if they are already in the status. For example, changing the Notify Upon Entry setting does not resend email about a routable object already in the status that is changed.		

What You Cannot Modify If a Workflow Has Any Routable Objects Applied

Once a routable object has been originated in a default or new workflow, and that object has gone through even a single status transition, you cannot modify certain things:

- You cannot add or delete a status to that workflow.
- You cannot alter the order of the statuses in that workflow.

If these are the elements of an active workflow that you need to alter, see [Disabling, Changing, and Reactivating Workflows](#).

Disabling, Changing, and Reactivating Workflows

Despite best efforts at fully defining your workflow processes and the many elements of a customized workflow, naturally the time will come when an active workflow—with multiple routable objects already applied and moving through it—simply needs to be fixed.

Caution	All modifications to enabled workflows have the potential to cause “ripple effects” that have to be detected, evaluated, and corrected across multiple nodes in Administrator. In particular, alterations to workflow statuses have implications for transfer orders (see <i>Agile Content Service User Guide</i>) and process extensions (see Process Extensions on page 105). To fix an active workflow:
----------------	---

1. Move each active routable object using that workflow to the Pending status type.

Note	This step is no longer absolutely required, and may not be necessary if you are doing a small and quick modification (see Modifying Properties in an Enabled Workflow). This precaution is helpful when the change may take some time and many objects and people may be affected.
-------------	---

2. Disable the workflow.
3. Rename the workflow, using the Save As procedure (described in [Creating New Workflows with Save As](#) on page 135).
4. You may now wish to rename the old workflow, especially if you decide it can still be useful but

has a different purpose.

5. Modify or fix the new workflow.
6. When you are confident that the existing problem has been remedied, enable the workflow.
7. Apply the routable objects from the old to the new workflow.

Account Policy

This chapter includes the following:

- Before You Begin..... 163
- Configuring the Account Policy..... 163

To provide an enhanced level of access security in Agile PLM, you can set a systemwide user account policy. The features of this policy include password aging, length, uniqueness, and lockout.

Before You Begin


Before configuring systemwide user account policy for Agile PLM, make sure you answer the following questions:

- Will you be using an LDAP system to create Agile PLM users? You may decide to set up **Account Policy** functionality on your LDAP server. See [LDAP as a Node in Administrator](#) on page 171.
- Do you want user passwords to expire? If so, how often (number of days)?
- Do you want users to be able to change their passwords at any time? If not, how often (number of days) should they be changed?
- What is the minimum number of characters permitted?
- Do you want to prevent users from using the same password over again? If so, how many previous passwords do you want the system to remember?
- Do you want a systemwide lockout policy to prevent unauthorized attempts to log in to the system?
- If a user is locked out, do you want yourself or others to be notified?

Configuring the Account Policy

To configure your systemwide account policy:

1. Under **User Settings**, double-click **Account Policy**. The Account Policy window appears.
2. Configure your systemwide account policy by setting the properties described in the table below.

Property	Description
Account Lockout	Controls whether the system remembers failed logons. When this property is set to Disabled, the system does not remember failed logons, and these properties are not in use: Logon Attempts, Reset Count Time, Logout Duration, and Account Lockout Notify User. When Account Lockout is set to Enabled, these properties are enabled.
Logon Attempts	Enabled when Account Lockout is set to Enabled. Enter a value between 1 and 999,999,999 . The default is 3 failed attempts, in which case the lockout of that user account occurs upon the third failure.
Reset Count Time (in minutes)	<p>Enabled when Account Lockout is set to Enabled. Enter a value between 1 and 999,999,999. The default is 30 minutes, after which that user account reverts to allowing the number of attempts set in Logon Attempts.</p> <p>Note A user who is locked out, and whose Lockout Duration value is set higher than Reset Count Time, will still be locked out when Reset Count Time expires, while another user can log on once Reset Count Time has expired.</p>
Lockout Duration (in minutes)	Enabled when Account Lockout is set to Enabled. Enter a value between 1 and 999,999,999 . The default is 0, which means the user is locked out until you reset that user account. Lockout Duration and Reset Count Time do not “trump” each other, meaning a user, upon being locked out, will have to wait for the higher value of these two properties to expire.
Maximum Password Age (in days)	Enter a number of days you want as a limit of how long passwords may remain in effect. Default is 0.
Minimum Password Length	This value sets the minimum number of <i>characters</i> that any user's password can be. Default is 1.
Password Uniqueness	<p>The value 0 (default) permits users to re-use passwords they have used before when it comes time to change passwords. To prevent users from reusing passwords, enter a number, which is the number of passwords that the system remembers for each user, and does not allow to be re-used.</p> <p>For example, with a value of 3, users will not be able to re-use their first password when it is time to select their fourth password. When it is time to select their fifth password, however, each user could re-use their first password, because the system remembers their second, third, and fourth passwords, but not their first.</p>
Account Lockout Notify User	<p>Enabled when Account Lockout is set to Enabled. To assign users to receive email notification if a user is locked out, click the  button at the right for the address book to appear, and select any number of users to be notified.</p> <p>On the User Groups tab of the address book, when you select a user group, only the button that adds all the members of the group is enabled; you can, however, add all the members of a group and then remove individuals from the Recipients list.</p>

Note The account lockout rules apply to all Agile PLM clients, including Java Client, Web Client, ChangeCAST, AIS, ACP, Agile Drive, and SDK.

Administrator Reset of Locked Out Account

If a user is locked out of their account because of entering the wrong password more times than **Logon Attempts** allows, and the **Reset Count Time** is a high value, you should reset the user's login password. This will reset the user's locked status and allow them to access the system.

Note An additional setting concerning passwords (for Web Client users) is under **Preferences** node. See [Allow Password Reset](#) on page 385.

Users

This chapter includes the following:

▪ Adding New Users	167
▪ About Usernames	169
▪ About Passwords	169
▪ LDAP as a Node in Administrator	171
▪ Modifying User Properties	171
▪ User Properties Defined	172

From the **Users** node, you can give new users access to Agile PLM or modify the properties of existing users, including changing user group, role, and escalation approval settings.

The **Users** node lets you view and configure the following aspects of Agile PLM:

- Add new users
- Modify any user properties such as licenses, roles, sites, and passwords
- Disable or delete users

The process of adding users involves establishing the properties that govern their access to Agile PLM applications. For example, their passwords allow them to log in, and their role assignments establish their access to Agile PLM objects from point of discovery forward. It is important to consider precisely what access and permissions your users require.

Important Also available is the possibility of integrating aspects of your PLM system with Single Sign-On (SSO) capability. With SSO configured and deployed for your PLM system, a user that has signed in to the system once (for instance, through the corporate portal) is not prompted again by a "login" dialog (see [Appendix A, Configuring Single Sign-On](#) on page 421).

Note A "supplier user" is a particular kind of user who is associated with a Supplier; supplier users, or "contact users" may not be created by the administrator but by certain Manager roles. You may assign the Organization Manager or Compliance Manager role to an Agile PLM user, and this person creates Suppliers and populates them with contact users who can respond to RFQs or RFIs via their (Restricted) role. For more information, see *Product Cost Management User Guide* and *Product Governance & Compliance User Guide*.

Adding New Users

Once you have assembled information about new users and assessed their access requirements, you can add them to the Agile PLM system.

Users created in an LDAP system must be imported to Agile PLM and synchronized in the Agile PLM database using the **Refresh** button. See [LDAP as a Node in Administrator](#) on page 171.

Before You Begin

Before creating a new Agile PLM user, make sure you answer the following questions:

- What does this user need to be able to do in Agile PLM? What default roles are required for this user?
- What should this user be prevented from doing in Agile PLM?
- Will this user need to have separate Login and Approval passwords?
- On which Agile PLM lists will the user's name appear?
- Which Agile PLM searches should the user be able to use?
- Is the user a Power User? A Power User can log in at any time and is not counted as a member of the concurrent user pool.

To create a new user in Java Client:

1. Under **User Settings**, double-click **Users**. The Users window appears.
2. Click the **New** button. The Create User dialog box opens.
3. Enter values for **User ID**, **First Name**, **Last Name**, and **Email**.
4. Type the **Username** and **Password**. Repeat the password in the **Retype Login Password** field.


Note Passwords are case-sensitive. For example, if you enter the password here in all capital letters, then the user must always enter the password in all capital letters when logging in to Agile PLM.
5. If the user requires a separate approval password, uncheck **Use Login Password for Approval Password**, then enter an approval password (the new user's approval password) in the **Approval Password** and **Confirm Approval Password** fields.
6. Click **OK**. The setup window for the new user appears.
7. Under **Profile**, click the **Role(s)** list and assign roles to the user. Remember, the user cannot do anything in Agile PLM until a role is assigned.
8. In the **Profile** section, enter other values as needed. These fields are not required and may be filled in later.
9. On the **Preferences** tab, enter values for the properties. You can accept the default values.
10. Click **Save**.

To create a new user in Web Client:

1. From the left navigation pane choose **Tools and Settings > Address Book > Users**.
2. Click **Add**. The Create New User window opens.

3. Type the **Username** and **Login Password**. Repeat the password in the **Confirm Login Password** field.

Note Passwords are case-sensitive. For example, if you enter the password here in all capital letters, then the user must always enter the password in all capital letters when logging in to Agile PLM.

4. If the user requires a separate approval password, uncheck **Use Login Password for Approval Password**, then enter an Approval Password (the new user's approval password) and Confirm Approval Password.
5. Enter values for **First Name**, **Last Name**, and **email**.
6. Click **Save**. The General Information page of the newly created user appears ready to edit.
7. To open the **Role(s)** list, click **Launch the Palette**  to the right of the field. Assign roles to the user. Remember, the user cannot do anything in Agile PLM until a role is assigned.
8. In the **Profile** section, enter other values as needed. These fields are not required and may be filled in later. Click **Save**.
9. To confirm the addition and review the new user's properties, click **Tools and Settings > Address Book > Users**. Double-click the new user ID in the table of users. The new user's page appears.

About Usernames

For security reasons, Agile PLM usernames must be unique. You can create multiple users with the same name (first and last), as long as the username is unique.

If there is an active or inactive user with the same username as a deleted user and the deleted user is undeleted, you must change the username of the deleted user to make it unique. All history references from other objects to the undeleted user remain intact.

Note The "Username" property is now called "User ID." Both of these terms are seen in the Agile PLM clients and documentation, and they can be thought of as equivalent.

Caution To prevent frequent user inconvenience, it is important to periodically evaluate your license requirements with your Agile Account Executive, and upgrade as needed.

About Passwords

When you add new users, you assign passwords so that they can log in to Agile PLM for the first time. Users can then change their passwords themselves based on the settings in their Password property and the systemwide account policy. The Agile PLM administrator can also change a user password later if necessary.

Although the account policy established from the **Account Policy** node governs password expiration, length, and uniqueness, you can specify settings from the **Users** node that override those settings; however, it is a best practice that the settings you specify from the **Users** node for individual users do not routinely conflict with your established security policy for Agile PLM as represented in the **Account Policy** node.

For example, if you want users to change their passwords periodically, you can designate an expiration interval when you set up your account policy. If you set passwords to expire in 30 days in the account policy, and then set a user's Password property to never expire, the setting in that user's Password property overrides the systemwide setting in the account policy.

For additional security, users can have different passwords for login and approval. For more information, see [Changing a User's Password](#) on page 171.

For more information, see [Account Policy](#) on page 163.

Change Internal User Password

There are four “special users” in Agile PLM, which are used for internal purposes.

Special User	Purpose
superadmin (internal user)	used internally to gain access to all data
agileuser (internal user)	used internally to gain access to all data
ifsuser (external user)	needed for access by File Manager
etluser (external user)	needed for access by ETL tool

The difficulty with these users is that these users are not exposed through the UI, that is, they exist in the PLM database table but are not visible in Java Client. However, anyone who knows the password can access agile data through SDK.

You can change the default passwords for the “IFS” user (file server), the “ETL” user (Datamart), and the “Agile” user.

Important The “Super Admin” user password cannot be changed.

To reset, for example, the “ifsuser” password:

1. Under **User Settings**, double-click **Users**. The Users window appears.
2. In the menu bar, click the **Change Internal Password User** dropdown list.
3. Click **Change Password of “ifsuser”**. The Change Password of “ifsuser” dialog opens.
4. Fill with appropriate values for the Old Password, New Password, and Retype New Password fields. When you are finished, Click **OK**.
5. When the password for ifsuser is reset, the following steps must be performed:
 - Run `<AgileHome>\agileDomain\bin\encryptpwd.cmd` to encrypt the new password.
 - Paste the new password to **agile.properties** under `<AgileHome>\agileDomain\config` and **server.conf** under `<AgileHome>\apache-tomcat\webapps\Filemgr\WEB-INF\classes\com\lagile\webfs\configuration` and `<AgileHome>\apache-tomcat-6.0.18\webapps\webdav\WEB-INF\classes`.

If the **ifsuser** password is changed during installation, only this second step needs to be performed.

The File Manager needs to be restarted for the configuration change to take effect.

LDAP as a Node in Administrator

Administrator has an **LDAP** node under the **Server Settings** node folder in which to configure a Lightweight Directory Access Protocol. Please see LDAP.

Modifying User Properties

You can modify any of the fields for existing users from the **Users** node. The following is a general process for changing property settings.

Note For information about the filter bar at the top of the Users window, see [Filtering Data](#) on page 8.

To modify a user's fields in Java Client:

1. Under **User Settings**, double-click **Users**. The Users window appears.
2. Double-click the user's name in the list. That user's window appears.
3. Modify fields directly, make a selection from a list, or make changes in a dialog box.
4. Click the **Save** button.

To modify a user's fields in Web Client:

1. Open the User object, either from a search result or from the **Users** tab of **Address Book**.
2. Click **Edit**. The fields become editable. You can directly edit a field, make a selection from a list, or make changes in a dialog box. Modify the fields you want.
3. Click the **Save** button.

The next time the user logs in, he will see the results of changes you have made to his user properties. However, for some properties (for example, **Time Zone** and **Receive Email Notification**), you must log out and log back in to Web Client to see your changes to these properties.

Changing a User's Password

When you are adding new users, you assign passwords so that users can log in to Agile PLM for the first time. Users can then change their passwords within Agile PLM if necessary. The Agile PLM administrator can also change a user's password.

Each user can have both a login password and an approval password, although a single password can be used for both purposes.

Important If the Signoff User Dual Identification Type preference is set to Login Password then the Login and Approval password may not be identical.
--

You can specify whether to establish separate login and approval passwords, or to use a single password for both. The login password is required to establish access to Agile PLM. In addition, the

system prompts users who approve objects, such as changes, for an approval password.

Using separate approval passwords provides additional security. If your company requires this type of security, or requires the assurance that only the correct person can approve an object (perhaps for audit purposes), set **Use Login Password for Approval** to No.

To change a user's login or approval password in Java Client:

1. Under **User Settings**, double-click **Users**. The Users window appears.
2. Double-click the user's name in the list. That user's window appears.
3. Click the **Reset Password** button to change the login password.
4. The Reset Password (or Reset Approval Password) dialog box appears. Select the Reset Login Password checkbox. Enter the new login or approval password, remembering that passwords are case-sensitive. If you enter the password here in all capital letters, then the user must always enter the password in all capital letters when logging in to Agile PLM.
5. Confirm the password by retyping it in the Retype New Password field. Click **OK**.
6. Click the **OK** button in the confirmation message that appears.

To change a user's login or approval password in Web Client:

1. Open the User object, either from a search result or from the **Users** tab of **Address Book**.
2. Click the **Reset Passwords** button to change the login password.
3. The Reset Passwords window appears. Enter the new login or approval password, remembering that passwords are case-sensitive. If you enter the password here in all capital letters, then the user must always enter the password in all capital letters when logging in to Agile PLM.
4. Confirm the password by retyping it. Click **Save**.

Changing a User's Role Assignments

You can modify a user's role assignments from the **Users** node, the **Roles** node, or the user object.

- From the **Users** node, you can change an individual user's role assignments by selecting a user and clicking the **Assign Roles** button.
- From the **Roles** node, you can see and change the users assigned to a particular role from the **Users** tab of a particular role.
- From the user object, you can see or change an individual user's role assignments by editing the roles under the **Profile** heading of the **General Information** page.

User Properties Defined

The table below lists and describes the properties common to all users in the Agile PLM system. The **General Info**, **Preferences**, **Escalations**, and **User Groups** tabs are documented. **Share**, **Subscription**, **Attachments**, and **History** tabs are all automatically populated, and do not have fields or properties.

Note Preferences for users are found on the **Preferences** tab of any user object. There are three sub-categories of user preferences: system-related, format-related, and display-related. These “user preferences” should not be confused with **Administrator > Server Settings > Preferences** node of “systemwide preferences.”

Property	Description (default is underlined)
General Info tab, required fields	
User ID (username)	The user's Agile PLM login user identification, or username. It must be unique in the Agile PLM address book. The maximum is 128 characters. See About Usernames on page 169.
First Name and Last Name	The user's public name. Neither of the user's Names fields has to be unique in the system, only the user's User ID must be unique (see About Usernames on page 169).
Email	The user's valid email address for change notification/routing. <i>Example:</i> danny.design@agile.com . Note: If there is not a valid email address in the Email field, the user will not receive any email notifications.
General Info tab, optional user information	
Status	Active or Inactive. (This is the same thing as Enabled or Disabled, respectively.)
Title	The user's title, for example, Senior Engineer.
Address fields	There are four address fields that are used for informational purposes only: Address (street), Geography , City , and Postal/Zip Code . The Geography field is a series of drop-down lists.
Phone number fields	The user's Business Phone , Home Phone , and Mobile Phone numbers (for informational purposes only).
Fax	The user's fax number (for informational purposes only).
Pager	The user's pager number (for informational purposes only).
Secondary Email	The Secondary Email is optional, but when the field is filled in, the user receives notifications at both email addresses.
General Info tab, Profile fields	
Role(s)	The user's role assignments. This property determines a user's access to the objects in Agile PLM from the point of discovery forward. The default roles (automatically assigned when you create a user) are My User Profile and Read And Discover By Creator. For more information, see Roles on page 189, and also Read and Discover Objects I Created Role.

Property	Description (default is underlined)
Lists	<p>Note: these lists are particular to routable objects and their workflows, as specified below. They are not editable at the Lists node; names are added or removed from these lists based on this setting in a user's profile.</p> <ul style="list-style-type: none"> ▫ Change Analyst List controls whether the user's name appears in the Change Analyst list on the Cover Page of Engineering Changes. ▫ Component Engineer List controls whether the user's name appears in the Component Engineer list on the Cover Page of Manufacturing Changes. ▫ Compliance Manager List controls whether the user's name appears in the Compliance Manager list on the Cover Page of Declarations. ▫ Price Administrator List controls whether the user's name appears in the Price Administrator list on the Cover Page of Price objects (PCOs, Quote Histories, and Published Prices). ▫ Quality Administrator List controls whether the user's name appears in the Quality Administrator list on the Cover Page of Quality Change Request objects (CAPAs and Audits). ▫ Quality Analyst List controls whether the user's name appears in the Quality Analyst list on the Cover Page of Product Service Request objects (Problem Reports and NCRs).
Searches	<p>Change Analyst Searches controls whether a user has the following in Java or Web Client:</p> <ul style="list-style-type: none"> ▫ A Change Analyst Searches folder ▫ Change Analyst queries in My Inbox <p>Component Engineer Searches controls whether a user has a Component Engineer Searches folder in Java or Web Client.</p> <p>Quality Searches controls whether a user has the following in Java or Web Client:</p> <ul style="list-style-type: none"> ▫ A Quality Search folder ▫ Quality queries in My Inbox <p>Content Manager, Price, Project, Supplier RFQ, and Sourcing Searches</p>
User Category	Power, Concurrent, or Restricted. See User Licenses.
Use Login Password for Approval	Each user has a login password and approval password (used to approve changes). Set Use Login Password for Approval to Yes to use one password for both. Set it to No if you require an approval password. Use the Change Password button at the top of the setup window to define new (case-sensitive) passwords for the user.

Property	Description (default is underlined)
Allow Escalation Designation Approval	If the user has identified one or more designated escalation persons (DEPs), this setting determines when the DEPs can approve or reject a routable object. <i>Settings:</i> After Escalation – The user's DEP can approve a routable object only after it has been escalated. Always – The user's DEP can always approve or reject a routable object. (For more information about designated escalation person status, see Assigning Escalation Persons to User Groups on page 182.)
Home Organization	The name of the company profile (organization name) for all users created from the Users node and the supplier name and supplier number for all users created from the Supplier Groups node.
Default Site and Site(s)	Sites are used for distributed manufacturing, and indicate all of the company's locations where the user is involved; selecting from the drop-down list for this property populates the drop-down list for Default Site. Default Site is the user's main base of work.
Ship-To address fields	Home Ship-To is the primary location where the user is responsible for sourcing activities. Authorized Ship-To (called "Site" in earlier versions of PCM), used only by PCM, indicates all company locations where the user can initiate sourcing activity; selecting from the drop-down list for this property populates the drop-down list for Home Ship-To .
Program Manager for Partners	The partners for which this user is program manager (which is the change analyst for Package objects). See Setting Up User Groups as Partners on page 184.
Rate fields	There are three Rates fields: Bill Rate , Labor Rate , and Overhead Rate . The drop-down lists in these fields show all currencies entered in the Currency Exchange Rates node. You can select a currency different from the user's Preferred Currency (see Preferences tab). Used by PPM.
Comment	The Agile PLM administrator may enter a comment regarding the user. This comment does appear to the user when he or she clicks Settings > User Profile .
Project Type	Types of projects the user can participate in. Available values depend the Project Type List.
Region	Regions the user has belongs to. Available values depend the Region List.
Division	Divisions the user belongs to. Available values depend on the Division List.
Product Line	Product lines the user has access to. Available values depend on the Product Line List.
Customer	Customers the user is associated with. Available values depend on the Customer List.
Launch Year	Product launch years the user is associated with. Available values depend on the Launch Year List.
Category 7, Category 8, Category 9, Category 10	Optional Product Portfolio Management Dashboard fields.

Property	Description (default is underlined)
Preferences tab: System Preferences	
Preferred Client	<p>This field controls the type of link provided in system notifications to the user. Select Web Client or Java Client to determine which client is automatically opened to the object to which the notification's link points.</p> <p>Important: Agile's PCM, PG&C, and PPM solutions operate only in Web Client. Users who work primarily in those areas should have their Preferred Client set to Web Client.</p>
Preferred File Manager	<p>Select from the list of file servers. For best performance, select a file server that is a local server for the user. For example, for a user in the United States, select a server located in the United States. (For more information about file management servers, see File Management in Agile PLM on page 356.)</p>
Receive Email Notification	<p>Controls whether the user can receive automatically generated email notifications from the system.</p> <p><i>Settings</i> = Yes or No</p>
File Productivity Preference	<p>Controls whether the user has access to advanced productivity components, or standard components, or wants to be prompted in each situation. If set to Standard mode, non-supported files will not be opened automatically. Instead, the user is prompted to choose Save or Open.</p> <p><i>Settings</i> = Prompt, Advanced, or Standard</p> <p>Note: this user preference will not appear in any user's Profile if the systemwide preference Allow Download of Productivity Components is set to No. (See Preferences on page 379.)</p>
Preferences tab: Format Preferences	
Language	<p>English is available with all Agile PLM licenses. Agile PLM includes Japanese, Traditional Chinese, Simplified Chinese, French, or German, per your license.</p>
Workweek Settings	<p>This setting is for future use only, and is not referenced in any Agile PLM module.</p> <p>Note: this property is not applicable to any Agile PLM module including Product Portfolio Management and Microsoft Project schedules.</p>
Preferred Date Format	<p>The format in which dates are displayed to the user. Default is MM/dd/yyyy.</p>
Time Zone	<p>The time zone where the user is located.</p>
Preferred Time Format	<p>The format in which times are displayed to the user. The default is hh:mm:ss aaa (aaa = am or pm).</p>
Preferred Currency	<p>The currency in which prices/costs are displayed to the user. The default is U.S. Dollar. The drop-down list in this property shows all currencies entered from the Currency Exchange Rates node.</p>
Number Format	<p>The format in which numbers are displayed to the user. The administrator or user selects a type of format (for example, use commas for thousand separators and point for decimal separator; use nothing for thousand and comma for decimal). An example of each format is displayed in the drop-down list.</p>

Property	Description (default is underlined)
Preferences tab: Display Preferences	
Preferred Start Page	Select between Home, Dashboard, Dashboard Financial, Dashboard My Activities, Dashboard Projects, and Dashboard Resources.
Response Edit Mode	Choose between Basic, Advanced Table Edit, and Advanced Wizard Edit. The Basic setting brings the user – generally a “supplier” who does not work at the “buyer” company – to a simplified Web Client user interface. The two Advanced settings bring the user to the familiar Web Client UI. For more information about these settings, see <i>PCM Supplier Handbook</i> and <i>PG&C Supplier Guide</i> .
Static Table Headers	Set to Yes to carry table headers to additional pages.
Encode Type	Select from: Western European (ISO) , Japanese (Shift JIS) , Traditional Chinese (Big 5) , Japanese (EUC) , Simplified Chinese (GB2312) , and Unicode (UTF-8) .
Thumbnails	Off or On Off is default
Table Display Mode	Standard or With Thumbnails
Search Display Mode	Only Thumbnails, Standard, or Standard with Thumbnails
Show Timesheet	Set to Yes to display the Timesheet tab. Default setting is No.
Escalations tab	
Criteria and Notify Users	Set Criteria and Notify Users , which is an individual user or user group (personal or global) to be notified when a workflow status exceeds its escalation time period without a signoff by the user. A user can have multiple designated escalation persons assigned to a variety of workflow-related criteria. For more information, see Assigning Escalation Persons to User Groups on page 182.
User Group tab	
Group Name and Status	<p>This will list the user groups that the selected user is a member of. From here the administrator can add a user group membership for the user or remove the user from membership of a user group. A user can belong to multiple groups. These fields can be set in this tab or on the Users tab of the user group setup window. For more information, see User Groups on page 179.</p> <p>Note that this does not display the Personal User Groups created by the user.</p>

User Groups

This chapter includes the following:

▪ Creating a New User Group	179
▪ User Group Properties	181
▪ Modifying a User Group	182
▪ Assigning Escalation Persons to User Groups	182
▪ Adding User Groups as Approvers of a Change	183
▪ Setting Up User Groups as Partners	184

From the **User Groups** node, you can assign users and designated escalation persons to user groups, change a user group's name, or create new user groups.

You can also define project teams, partners, departments, business units, divisions, site-related groups and global groups and their assigned users. This configuration is reflected in the **User Groups** node of the Agile PLM address book for use in addressing email notifications.

Agile PLM administrators set up the user group configuration for their Agile PLM system from the following two nodes:

- From the **User Groups** node, you set up user groups by creating, naming, and assigning users to them. User groups are displayed in the Agile PLM address book. When a user clicks the **To** button in the Send Object dialog box in Agile PLM clients, the address book opens. You can select a user group in the address book. Any user group assignments you make in the **User Groups** node are also reflected on the user's **User Groups** tab of the user's window or page.
- From the **Users** node, you configure user properties, including user group assignments. Any user group assignments you make from the **Users** node are also reflected in the Users property of that user group in the **User Groups** node. When you add new users in the **Users** node, you can assign them to one or more user groups. You can change these assignments later as necessary, from either the **Users** node or the **User Groups** node. For information about how to change a user's properties, see [Modifying User Properties](#) on page 171.


Note If you create a new user group and want to assign existing users, it is faster to configure the new user group's User property than each user's User Group property.


If you have upgraded to Agile PLM from a previous version of Agile Product Collaboration, and want to keep your existing organizational structures in the system, you can create subclasses of user groups called, for instance, Departments, Global Groups, and Partners.

Creating a New User Group

Before creating a new user group, you should review the user groups you currently have. Run the User Group Configuration report (under the **Analytics and Reports** tab > **Standard Reports** > **Administrator Reports** node): it lists current user groups and the users assigned to them. (See [Administrator Reports](#) on page 20 for more information about reports.)

To create a new user group in Java Client:

1. Under **User Settings**, double-click **User Groups**. The User Groups window appears.
 2. Click the **New** button . The Create User Group dialog opens.
 3. From the **Subclass** dropdown list, select the type of user group.

User Groups is the only subclass available if you have not created another one in that class. If you want to designate a new group to be of a type that has not been created, you must first create it from the **Classes** node for it to appear in the dropdown list.
 4. Fill in a value in the **Name** field.
 5. Select if the user group will be Global or Personal.
 6. Click  next to the **Users** field. The address book appears. Move users (from the **Names** list) or other user groups (from the **Groups** list) to the **Recipients** list.
 7. Click **OK**. The new user group object appears.
- The new user group object is available to users from this point on. Its name appears under the **User Groups** node, and user group assignments are updated in the **Users** node. The new user group name also appears in the Agile PLM address book.

To create a new user group in Web Client:

1. From the left navigation pane, click **Tools and Settings > Address Book > User Groups**. The User Groups page appears.
2. Click **Add**. The Create New User Group window opens.
3. From the **Type** dropdown list, select the subclass type of user group.

If you want to designate the new user group to be of a type that has not been created, you will have to create that from the **Classes** node in Java Client before it will appear in the dropdown list.
4. Fill in a value in the **Name** field.
5. Select if the user group will be Global or Personal.
6. Click **Save**. The User Group General Information page appears and is ready to edit.
7. Enter user group properties as needed. For more information, see [User Group Properties](#) on page 181.
8. When you are finished, click **Save**. Then click the Users tab.

To create the new user group without assigning users, click **Finish**. The new user group name appears on the User Groups page on the **Users** tab, and in the Agile PLM address book.
9. To assign a user to the user group, click **Add**. You may type a name to find the user, or search a list of existing users.
10. Select one or more names and drag and drop them onto the table of users for the user group or double-click.

The new user group name appears on the User Groups page, and user group assignments are updated on the Users page. The new user group name also appears in the Agile PLM address book.

User Group Properties

The following table lists user group properties.

Property	Description
Name	Allows you to enter a user group name of up to 29 characters.
Type	Select a subclass. The out-of-box subclass is User Group. The administrator can create other subclasses in the User Groups class; these will appear in this drop-down list.
Description	Description of the user group.
Status	Whether the user group is active or inactive. An active group appears in the address book, an inactive group does not.
Global/Personal	Global user groups can be used for all users. Personal groups are seen and used only by their creators.
Roles	Roles applied to groups apply to all the users in the group.
Resource Pool	Allows this user group to be used as a resource pool for assignment in Product Portfolio Management objects
Define as Partner Group	If the user group is to be a partner (members can create and submit package objects), select Yes. The user group will then appear in the list of valid partners when you set any user's Program Manager for Partners property. See Setting Up User Groups as Partners on page 184.
Allow Escalation Designation Approval	If the user group has identified one or more designated escalation persons (DEPs), this setting determines when the DEPs can approve or reject a routable object. <i>Settings:</i> After Escalation—the user group's DEP can approve a routable object only after it has been escalated. Always—the user group's DEP can always approve or reject a routable object. (For more information about designated escalation person status, see Assigning Escalation Persons to User Groups on page 182.)
Owner	Names the creator of the user group; for information purposes. The owner is the creator by default, but can be modified by a user.
Max Number of Named Users	Maximum number of users the user group can have. <i>Settings:</i> Blank (default) — The number of users is unlimited. Any positive integer — Defines the maximum number of users contained in the user group. The number can exceed the number of user licenses, but it cannot be less than the number of users already assigned to the user group.
Lists, Project Type, Region, Division, Product Line, Customer, Launch Year, Labor Rate, Overhead Rate, and Bill	See User Properties Defined.

Property	Description
Rate	

Modifying a User Group

The following sequence applies to modifying any property of a user group.

To modify the User Groups settings in Java Client:

1. Under **User Settings**, double-click **User Groups**. The User Groups window appears.
2. Double-click a specific user group, say, Customer Support. The Customer Support window appears. The user group tabs are **General Info**, **Users**, **Escalations**, **Attachments**, **History**, and **Share**.
3. In any editable field, enter a new value or select from the dropdown list.
4. When you have finished, click **Save**.
5. If you wish to revert to the original settings or start over, click **Close**. You will be prompted whether you want to save new settings on the window; click **Yes** if you do or **No** if you do not.

Note If your company uses an LDAP system with PLM, if the User Group "synch" function enabled, you cannot remove or add users on a user group's **Users** tab that have been synchronized (that is, where users have been added to a user group via LDAP). See [Synchronizing Users and User Groups](#) on page 377.

To modify the User Groups settings in Web Client:

1. Click **Tools and Settings > Address Book > User Groups**. The User Groups page appears.
2. Click a specific user group, say, Customer Support. The User Group: Customer Support page appears. The user group tabs are **General Info**, **Users**, **Escalations**, **Attachments**, **Share**, and **History**.
3. On the **General Info** tab, click **Edit**.
4. In any editable field, enter a new value or select from the dropdown list.
5. When you have finished, click **Save**.
6. If you wish to revert to the original settings or start over, click **Cancel**. You will be prompted whether you want to cancel new settings on the page; Click **OK** if you do or **Cancel** if you do not.

Assigning Escalation Persons to User Groups

When a workflow status exceeds its escalation time period without a signoff, user groups or individual users can be notified. These entities are called designated escalation persons. The Allow Escalation Designation Approval property determines when the designated escalation person can approve or reject a routable object.

To assign designated escalation persons to a user group in Java Client:

1. Under **User Settings**, double-click **User Groups**. The User Groups window appears.
2. Double-click the name of the user group you want. The user group's tabbed window appears.
3. Click the **Escalations** tab to bring it forward.
4. Click the **Add** button. Use the dropdown list to select the reusable criteria for this escalation, such as All Change Orders.
5. Click next to the **Notify Users** field. In the Select Users window, select and move appropriate users (from the **Users** list) or other user groups (from the **User Groups** list) to the **Recipients** list, and Click **OK**.

Click **Save**. The escalations are added to the **Escalations** tab.

If you want to cancel your changes, click **Close**.

Now, if the escalation period for the specified criteria passes without a signoff, those users who were selected receive an escalation notification email.

To assign designated escalation persons to a user group in Web Client:

1. Click **Tools and Settings > Address Book > User Groups**. The User Groups page appears.
2. Click the name of the user group you want. The user group's tabbed object page appears.
3. Click the **Escalations** tab to bring it forward.
4. Click **Add**. In the Add Escalations page select the Criteria from the dropdown list to select the reusable criteria for this escalation, such as All Change Orders.
5. Click the Address Book button next to the **Notify Users** field. Use the selection window to search for users or groups and drag and drop them onto the table of users for the escalation or double-click.
6. Click **Add More** or **Add** (There is also a **Cancel** button.) The escalations are listed on the **Escalations** tab.

Now, if the escalation period for the specified criteria passes without a signoff, those users who were selected receive an escalation notification email.

Adding User Groups as Approvers of a Change

In an Agile PLM workflow, two properties—Approvers and Observers—must be filled out for criteria-specific properties of each Review and Released status.

The possible selections in the **Available Values** list in the selection dialog depends on the selection you make in the **Select Group** dropdown list.

Select Group dropdown list choice	Possible selections in the Available Values list
All	When you select All, the Available Values list includes: <ul style="list-style-type: none">▫ Variables (for example, \$CHANGEANALYST).▫ All the Agile PLM users.▫ All the global groups, listed twice with the suffixes Any and All. For example, if you select [Sales - Any], the routable object is routed to all users in the group, but only one user needs to approve or reject. If you select [Sales - All], the routable object is routed to all the users in the group, and all the users in the group must approve or reject.
All Groups	When you select All Groups, the Available Values list includes: <ul style="list-style-type: none">▫ All the global groups, listed twice with the suffixes Any and All. For example, if you select [Sales - Any], the routable object is routed to all users in the group, but only one user needs to approve or reject. If you select [Sales - All], the routable object is routed to all the users in the group, and all the users in the group must approve or reject.
group name	When you select a group name, the Available Values list includes: <ul style="list-style-type: none">▫ The members of that group. For example, if you select [Sales], the Available Values list contains the names of the members of that group. This allows you to select a subset of the group members.

Select these in the same way you use any multilist dialog box: either double-click single names or select multiple names and click the right arrow to move users or user groups to the **Selected Values** list on the right. Click **OK** to return to the **Criteria** table on the **Status** tab, and click **Save** to complete assigning approvers for that status.

Note When [user group - Any] is assigned to a workflow as an approver, any member of the user group may sign off a routable object (passing through the status in which the group was named), and the individual's signoff is, in effect, for the entire user group; no one else needs to or can approve or reject the routable object. Once one member of the group has approved or rejected it, the routable object no longer appears in the Inbox of the other users in the group.

However, other members *can* approve or reject the routable object after the first user has responded. If a member rejects the routable object, a warning appears, "You are about to override a previous signoff in CCB (or Released) which differs from yours." If this user clicks **OK**, it will override the approval by the earlier user.

Setting Up User Groups as Partners

This section collects the various elements that must be set up to enable Agile partners to send packages and to have program managers manage their package submissions. A "partner" may be defined as a company that works with your company and that has Agile users who need to send packages; or, a partner could be any Agile user that represents a company to your company.

Note The term “program manager” refers to the change analyst who manages package objects (instances of the Packages class); here it does *not* refer to the Agile role “Program Manager.”
Also, this use of “program” is *not* involved with the Programs base class.

To create partners and program managers to function together in Agile:

1. Define Agile partners, which are Agile users – usually external – who belong to a user group that has been defined as a partner. Each user group object has a **Define as Partner Group** property. When set to Yes, the user group will appear on the list of partners available under any user’s **Program Manager for Partners** property.
2. Partners can be assigned the Partner role, which gives them the privileges to create and submit packages.
3. Define one or more Agile users – usually internal – as a program manager of each partner. The **Program Manager for Partners** user property lists all “Partner” user groups, which you set up in Step 1. You pick the partner groups for each program manager, that is, you can have one user be program manager for one or more of the partner groups, and another user can be program manager for the same or different partner groups.
4. Program managers for partners need to be assigned the Content Manager role, which enables them to work with Agile package objects. Again, as stated in the Note above, do not be misled by the Agile role called Program Manager – that role deals with functionality in the PE/PPM solution.

Supplier Groups

This chapter includes the following:

- Overview 187
- Properties 187

Overview

The **Supplier Groups** node provides a way to “bundle” approved suppliers so that users who are involved in the PCM solution can easily select multiple suppliers during the RFQ process.

Using Java Client or Web Client, the administrator can set up global supplier groups that can be leveraged by users with appropriate roles. An Agile PLM user can also define (create, edit, delete) a unique supplier group that meets his particular needs as a personal supplier group. Administrators (users who have the ability to create and modify user profiles) can also create, edit, and delete user-level supplier groups for each user.

Properties

In Java Client, under **User Settings**, double-click **Supplier Groups** to display the main Supplier Groups window. Supplier groups are created with the following properties.

Property	Description	Editable	Default
Name	Name of supplier group	Yes	Empty
Description	Description of supplier group	Yes	Empty
Suppliers	List of suppliers in the supplier group	Yes	Empty
Type	Type of supplier group: Global or Personal group. Note If you create a supplier group in Java Client, the default is Global with no alternative; if you create a supplier group in Web Client, Personal is available.	Not after creating the supplier group	Global
Enabled	Whether the supplier group is active or inactive	Yes	Yes


Available actions

- **Create** – A user administrator can create a new supplier group.
- **Edit** – A user administrator can edit a supplier group. To add or remove suppliers (users who


have been assigned Supplier Administrator, Supplier Manager, or Supplier Project User roles) from the group, the user administrator can add or remove suppliers from the group.

- **Enable and Disable** – Supplier groups can be enabled or disabled in Edit mode (Web Client) or using the buttons at the top of the Supplier Group window (Java Client).

To create a supplier group in Java Client:

1. Under **User Settings**, double-click **Supplier Groups**. The Supplier Groups window appears.
2. Click the **New** button. The Create New Supplier Group dialog box opens.
3. Fill in the **Name** and **Description** fields, and select Yes or No in the **Enabled** field.
4. The **Type** field is grayed, with the value of Global entered. (As noted in the table, “Personal” is an available choice when creating a supplier group in Web Client.)
5. Click  next to the **Suppliers** field, and move suppliers from the **Choices** list to the **Selected** list.
6. Click **OK**, and Click **OK** again. The new user group object is listed in the Supplier Groups window. It is available to users from this point on.

To create a supplier group in Web Client:

1. Click **Tools and Settings > Address Book > Supplier Groups**. The Supplier Groups page appears.
2. Click **Add**. The Add Supplier Group window appears.
3. Fill in the **Supplier Group Name** and **Supplier Group Description** fields.
4. Select the **Supplier Group Type**, either Global or Personal.
5. Click  next to the **Suppliers** field. Select suppliers from the list.

Note The supplier group must have at least one supplier selected.

6. Click **Add**.

To edit a supplier group in Java Client:

1. Under **User Settings**, double-click **Supplier Groups**. The Supplier Groups window appears.
2. Double-click the group you want to modify. The Supplier Group setup window appears.
3. On the **General Info** tab, select or accept values from the dropdown lists. Add or remove supplier users by moving them into or out of the **Selected** list.
4. When you are finished, click **Save**.

This chapter includes the following:

▪ Overview of Roles and Privileges in Agile PLM	189
▪ Getting Familiar with Roles	190
▪ Default Agile PLM Roles	192
▪ Securing and Maintaining Roles and Privilege Masks	199
▪ Working with Roles	202

This chapter explains how to use Agile PLM's preconfigured roles and how to create new ones.

Overview of Roles and Privileges in Agile PLM

Roles and privileges govern a user's access to Agile PLM business objects and functionality.

For a PLM user to be able to perform tasks, users must be assigned to at least one role. Each user (or user group) can be assigned to multiple roles, depending on which actions they need to perform.

Agile PLM includes a wide-ranging set of preconfigured roles and base privileges. While you can always modify roles and tailor privileges as needed, you are encouraged to become familiar with the default roles in Agile PLM before constructing your own; the default roles are listed in a few pages.

What is a Privilege Mask?

This chapter examines PLM roles – both default and customized – and the next chapter takes up privileges and privilege masks. However, it is important to understand from the start what these elements are. (The next page describes the process to view the default roles in the **Roles** node; the **Privileges** node can be expanded in the "node tree" to see a list of the default privileges.)

The following table defines *privilege*, *privilege mask*, and *role*.

Term	Definition	Examples
Privilege	The action users are allowed to take. A privilege is only a "building block": to be assigned to users, it must be combined with other components, like Criteria and a target object.	Administrator (privilege) Create Read Modify
Privilege mask	A set of <i>criteria</i> statements that define under what specific conditions an action can be taken on a named business object. Each role requires at least one privilege mask.	Administrator (privilege mask) Create Designs; Create Items Read Designs; Read Items Modify Designs; Modify Items

Term	Definition	Examples
Role	<p>A common set of privileges that can be assigned to one or more users who perform the same functions in the change control process.</p> <p>A role is a tailored assembly of privilege masks.</p> <p>A user can be assigned to more than one role.</p> <p>The default roles are set up for immediate use.</p>	<p>Administrator (role)</p> <p>Change Analyst</p> <p>Compliance Manager</p> <p>Component Engineer</p> <p>> Each role comprises several-to-many privilege masks.</p>

From this table, we can make these summary statements:

- The actions that users can perform in Agile PLM – such as creating, sending, or canceling – are based on *privileges*. But privileges do not function "by themselves".
- *Privilege masks* are combinations of: privileges, reusable criteria (introduced in earlier chapter), and target object (which can be as granular as required). A privilege mask is a functional unit that acts as a filter to manage user actions. Privilege masks can be added to roles (default or custom) or can be assigned to users without being part of a role.
- *Roles* are groupings or assemblies of several-to-many privilege masks. (A role like "Enforce Field-Level Read" has but 2 or 3 privilege masks, while "Change Analysts" has dozens.)

Roles provide a way to allocate a common set of privileges to a group of users who have common functions in the change control process.

When you assign a role or a privilege mask to a user, it takes effect only after the user has logged out and logged back into an Agile PLM client.

This introduction to "roles *and* privileges" in Agile PLM now turns to Roles; the following chapter goes into detail about privileges.

Getting Familiar with Roles

You can modify the default PLM Roles in the following ways:

- Change the name of an existing role.
Exceptions are the **(Restricted)** roles, and the Administrator, My User Profile, and View Historical Report roles, whose names cannot be changed.
- Enable or disable a role on its **General Information** tab.
Exceptions are the **(Restricted)** roles, and the Administrator, My User Profile, and View Historical Report roles, which cannot be disabled.
- Assign a user to a role or remove a user assignment from a role on the **Users** tab.
Exceptions are the **(Restricted)** roles, and the My User Profile and View Historical Report roles, which don't allow you to modify user assignments.
- Add or remove privilege masks for the role by using the **Privileges** tab.
Exceptions are the **(Restricted)** roles, and the My User Profile and View Historical Report roles,

which don't allow you to add or remove privilege masks.

- On the **Privileges** tab, double-click the name of a privilege mask to display the privilege mask's tabbed object window. When a privilege mask's tabbed window is displayed, you can modify that privilege mask.

You *cannot* do the following from the Roles window:

- Change the object type of a privilege mask.
- Modify any of the Example Roles (or its privilege masks) or the Example Privileges. These are found in **Examples > Example Roles** and **Example Privileges**.

Viewing the Roles Window

To view the Roles window:

1. Under **User Settings**, double-click **Roles**. The Roles window appears
2. You can filter roles records to narrow your search.

For example, set **Filter By** to Description, **Match If** to Contains, and **Value** to Change, then click **Apply** to find all the roles pertaining to "change" objects. (See [Filtering Data](#) on page 8.)

To see all roles currently in PLM, set **Match If** to Show All and click **Apply**.

The list of roles is displayed in the table. The Roles table shows the name, description and enabled status for each role.

The buttons on the Roles window allow you to perform various role management tasks.

Button	Action
New	Create a new role. See Creating a New Role on page 205.
Delete	Deletes the selected roles. A role cannot be deleted if it is already in use.
Enable	Enables the selected roles.
Disable	Disables the selected roles.
Import	Import a text file to create a new role. See Object History on page 24.
Export	Exports role data for the selected role. See Object History on page 24.
Refresh	Refreshes the table with the latest information about the list of roles.

Viewing a Role

To view a specific role:

1. In the Roles window, double-click the role you want.

The tabbed window for that role appears. The buttons that appear at the top of the window of each role are **Save As**, **Delete**, and **Export**.

2. The role's basic properties are displayed on the **General Information** tab. These include Name, API Name, Description, and Enabled.
3. The *privilege masks* that are assembled in the role are displayed on the **Privileges** tab.
You can double-click any row to open that privilege-mask object; on its **General Information** tab, the field Privilege (which is grayed-out because it cannot be changed) shows the basic privilege that drives that privilege mask.
4. The **Users** tab lists users who have been assigned to this role. The **User Groups** tab lists user groups that have been assigned to this role.
On both these tabs, you can add or remove users or user groups, respectively. Note that when you "delete" a user or user group from one of these tabs, you are only removing the role assignment (the role you are "in") from that "user object."
5. The **History** tab displays the history of actions taken on this role object.

Guidelines for Working with Roles

Follow these steps when working with roles:

1. Print a Roles and Privileges Summary report and a Privilege Mask Detail report to see the definitions currently active in your Agile PLM system. See [Administrator Reports](#) on page 20.

Caution	The Privilege Mask Detail report can be extremely long. You may wish to generate and view the report before printing it.
----------------	--

2. Read and follow the security recommendations in [Securing and Maintaining Roles and Privilege Masks](#) on page 199.
3. If necessary, modify and create roles, as described later in this chapter.
4. Assign users to appropriate roles. See [Modifying a Role](#) on page 202.

Default Agile PLM Roles

When you double-click the **Roles** node, you see a list of your currently configured roles. The table below lists the out-of-box roles and briefly describes what each role allows the user to do.

You can assign a user as many or as few roles as he needs to perform his duties. You can use the roles provided as they are, or you can copy a provided role (using Save As) and modify the copy to create a new role, or you can create a new role from scratch.

Caution	As much as possible, copy (using Save As) and adapt the roles and privilege masks provided with your Agile PLM installation rather than create new ones. This is especially true for roles, since the nature of their privilege mask combinations is not immediately obvious.
----------------	---

Role	Applies to these base classes (or other PLM utility)	Description
Administrator roles <p>These roles apply only to users who work in the Administrator modules in Java Client (Admin tab) and in Web Client (Tools and Settings > Administration).</p> <p>An important part of tailoring the Administrator roles is the <code>AppliedTo</code> property in the Administrator privilege; see Administrator Privilege and the AppliedTo Capability on page 233.</p>		
Administrator	All Classes	Perform all administrative tasks. The other, specialized Administrator roles (including Discussion, Folder, Price, Program, Quality, Resource Pool, Sourcing, and User administrators) all have less capability than this role.
User Administrator	Users, User Groups	Perform administrative tasks (create, modify, delete) as defined by the Agile administrator
General-function Agile PLM roles <p>These roles apply to users who work across all Agile PLM solutions.</p>		
Approve/Reject	Changes, Packages, QCRs, PSRs, ATOs, and Projects	Approve or reject routable objects via workflows, and read items and changes
Creator can read and discover object he or she created	All objects	<p>The creator of a business object can always read and discover that object. This role is enabled and part of every new user's profile, by default. There is no change in behavior with existing users (that is, "legacy" users for upgrading customers).</p> <p>Removing this role from a user <i>prevents</i> Read or Discovery of objects they create.</p>
Discussion Administrator	Discussions	Create and manage discussion objects. Discussions are used primarily in Agile PPM and PCM solutions, but it is possible to use that class in other solutions.
Discussion Participant (Restricted) Discussion Participant	Discussions	Manage portions of discussions; the (Restricted) Discussion Partner would generally be someone who works outside the enterprise.

Role	Applies to these base classes (or other PLM utility)	Description
Enforce Field-Level Read	(Works in conjunction with other roles)	This role (contains only Enforce Field-level Read privilege mask) is used in conjunction with other roles: it enforces the AppliedTo fields under Read privileges in all roles assigned to the user, which reduces the user's capabilities.
Export	(Allows access to Export utility.)	Allows user to export objects for which they have Discover and Read privileges. (Contains only Export privilege mask.)
Folder Administrator	File Folders	Create and manage file folders. For additional information, see Attachment Privileges on page 400.
Folder Manager	File Folders	Create and manage file folders. For additional information, see Attachment Privileges on page 400.
Markup for All	File Folders (Affected Item Attachments)	Modify the redline Markups or other users' for File Folders or for the Affected Item attachments of change orders. User must have Read privileges for the file folder objects or change order objects. For additional information, see Redline Markup Default Roles and Privileges on page 405.
Markup for Self	File Folders (Affected Item Attachments)	Create and modify the user's own redline Markups for File Folders or for the Affected Item attachments of change orders. User must have Read privileges for the file folder objects or change order objects. For additional information, see Redline Markup Default Roles and Privileges on page 405.
My File Folder	File Folders	Permits reading file folders created by the assignee.
My User Profile (Restricted) My User Profile	Users	View and modify his own user profile properties under My Settings, and create and modify personal user groups. Assigned to every user, and is required to use the Agile PLM system
(Restricted) Grant	All objects	Grant roles to users in a controlled, finite way, using Access Control List (ACL) capability.
Engineering Collaboration role This role applies to users who work in the Agile EC solution.		
Design Engineer	File Folders (Designs class objects)	Create and manage Designs class objects and Design Model structures.

Role	Applies to these base classes (or other PLM utility)	Description
Product Collaboration roles These roles apply to users who work in the Agile PC solution.		
Change Analyst	Changes, Items, Manufacturers, Mfr. Parts, File Folders	Create items and changes, and manage the routing and release process of changes through workflows. Also create BOMs, MPNs, AMLs, and to manage file folder references
Component Engineer	Items, Manufacturers, Mfr. Parts, Mfr. Orders (MCOs)	Create manufacturer change objects and manage the routing and release process of MCOs
Incorporator	Changes, Items, Mfr Parts, Manufacturers, Prices,	Incorporate items and numerous functions with the listed base classes (this role is similar to Change Analyst, but with fewer capabilities).
Item Content Manager	Changes, Items	Create items, and create and submit changes
Manufacturer Content Manager	Items, Manufacturers, Mfr. Parts, Mfr. Orders (MCOs)	Create items, manufacturers, and manufacturer parts, and create and submit MCOs
Modify Item Released	Items	Change the Description of an item that has been released (contains only one privilege mask for this).
Partner	Packages	Create and submit package objects
Product Content Read Only	Changes, Items, Manufacturers, Manufacturer Parts	Discover, read, comment, get, print, send, and view items, changes, manufacturers, and manufacturer parts
Product Quality Management roles These roles apply to users who work in the Agile PQM solution.		
Organization Manager	Suppliers, Customers	Manage suppliers and customers (also applies to PCM solution)
Quality Administrator	Quality Change Requests	Manage the corrective and preventive action and audit processes
Quality Analyst	Product Service Requests	Submit quality incidents and manage their resolution
Quality Analytics User	(Quality Analytics application)	Permits PQM user to access (Run, Discover, Read) the Quality Analytics application.

Role	Applies to these base classes (or other PLM utility)	Description
Product Cost Management roles These roles apply to users who work in the Agile PCM solution.		
Organization Manager	Suppliers, Customers	Create and manage suppliers and customers (also applies to PQM solution)
Price Administrator	Prices, Price Change Orders	Control price management activities, including PCOs
Price Manager	Prices, Price Change Orders	Manage pricing information through creation of price objects and PCOs
(Restricted) Price Collaborator	Prices, Price Change Orders	Manage pricing information through creation of price objects and PCOs, but more limited than price manager role; typically provided to supplier users
RFQ Manager	RFQs, RFQ Responses	Create RFQs and manage the RFQ process
(Restricted) RFQ Responder	RFQ Responses	Respond to RFQs; this role is generally provided to supplier users
Sourcing Administrator	Sourcing Projects, RFQs	Control sourcing activities, including the ability to view and modify all sourcing projects and RFQs
Sourcing Project Manager	Sourcing Projects	Create and manage sourcing projects
(Restricted) Supplier Manager	Suppliers	Manage supplier information, limited to suppliers' own organizations, including the ability to create users in the supplier organization
Product Portfolio Management roles These roles apply to users who work in the Agile PPM solution. (Note: The base class Programs is changed to Projects as of Rel. 9.3.0; the PPM roles and privilege masks may still use the term "Program".)		
Executive	Projects	Global read access to all projects that have matching categories; for example, if a project is associated with the North American region, and a user has an Executive privilege for all North American, then he can read them
Portfolio Analytics User	(Portfolio Analytics applications)	Permits PPM user to access (Run, Discover, Read) the Portfolio Analytics application.
Program Administrator	Projects	Create and manage complete projects

Role	Applies to these base classes (or other PLM utility)	Description
Program Manager	Projects	Create and manage routing and release process for projects
Program Team Member	Projects	Manage portions of projects
Resource Pool Administrator	Projects	Create and manage resource pools
Resource Pool Owner	Projects	Manage resource pools
Timesheet Administrator	Projects	Perform administrative tasks on all timesheets that are created in the system
Reports roles These roles apply to users who work with Reports.		
Report Manager	Reports	Access and manage all reports, even those they did not create
Report User	Reports	Create new custom reports and manage reports they created
View Historical Report	Reports, Historical Report File Folders	View specific instances of previously executed reports; this is a non-editable role and is automatically assigned whenever a report instance is shared with a user
Agile Content Services role This role applies to users who work in the ACS solution.		
Content Manager	Transfer Orders, Packages	Create, modify, route, release and implement CTO and ATO objects, as well as package objects
Product Governance & Compliance roles These roles apply to users who work in the Agile PG&C solution.		
Compliance Manager	Declarations, Commodities, Specifications, Substances	Create and manage PG&C objects, run PG&C reports, and route material declarations to suppliers
(Restricted) Material Provider	Declarations	Create, modify, and complete material declarations; this role is generally provided to supplier users

Role	Applies to these base classes (or other PLM utility)	Description
Agile Configuration Propagation roles These roles apply to users who work in the ACP solution. For more information see the current <i>ACP User Guide</i> .		
(Propagation) Administrator	All Classes	Perform propagation tasks.
(Propagation) User Administrator	Users, User Groups	Perform propagation tasks that are limited to users and user groups.

Example Roles

Your Agile PLM installation includes both a read–write version and a read-only example or reference copy of the roles. double-click the **Example Roles** node under the **Example** node folder to see the reference copy, which is provided so that you always have default copies of the roles as they were installed. To restore the default version of any role, you can just make a copy (using Save As) of its Example role.

For example, the following are the two versions of the Change Analyst role provided at installation:

- **Change Analyst** — This is a modifiable (Read–Write) role that you can assign to users.
- **Example–Change Analyst** — This is an uneditable (Read–Only) reference copy of the Change Analyst role.

Note If Agile PLM users are unable to move a routable object from one status to another, for example from Hold to CCB, often they don't have appropriate privileges to make these status changes. In such cases, check the roles they are assigned and the privilege masks included in those roles.

More information about example roles is in [Using the Example Roles](#) on page 207.

Restricted Roles

Some roles are restricted in the extent to which they can operate on their specified objects; these role names are preceded by the word Restricted in parentheses. Their purpose is the same as the like-named role that is not preceded by "(Restricted)". They are generally assigned to members of supplier organizations, that is, Agile PLM users who work outside the enterprise.

Role-based Enhancements

User Administrator Enhancement

The PLM role User Administrator has a privilege mask called "Admin Access for User Admin"; its *AppliedTo* property dictates which User-related Administrator *nodes* can be accessed (Users, User Groups, and so forth). The User Administrator can also access the User-specific functions in Web Client (accessed via **Tools and Settings > Address Book**).

The User Administrator role also has a privilege (and privilege mask) called "User Administrator". The *AppliedTo* property of the User Administrator privilege mask is populated with PLM *Roles*. This means that a user administrator can be configured so that he can only assign specified roles to PLM users.

This is more fully described in [Options for Building Administrator Assistants](#) on page 235, which is part of the important topic [AppliedTo Capability](#) on page 232.

Advanced Search Security

Two restrictions have been added to Advanced Search utility.

The first restriction applies to the "Search for" field when a user creates any type of search (Quick, Advanced, Parametric search). Now he will see (in the drop-down list of classes) only those classes for which he has been assigned the Discovery privilege.

Similarly, "Field" criteria condition (drop-down list) will not display fields if user does not have a Read privilege (or Enforce Field-level Read privilege) to them. In order to ensure restricted field-level read, the user's Read privilege mask must include in its *AppliedTo* property only the fields you wish the user to read. In addition, the user must also be assigned an Enforce Field Level Read privilege mask, for example, by assigning the Enforce Field Level Read role.

For a user to be able to view **Workflow Routings** folder under **Search** tab (on the Navigation pane), in the user's profile > Searches field, "Workflow Routings" must be moved from Choices to Selected table.

Securing and Maintaining Roles and Privilege Masks

Important This section is intended to both warn you of potential risks if you do not have a "security and maintenance plan" and provide some steps for simple troubleshooting if you do encounter a problem in PLM. Please discuss this matter with your Oracle Consulting – Agile Practice representative, or call Agile Support.

By following the recommended plan described in this section, you will help prevent security violations, interruptions in your change control process, and confusion if you need to restore the system to a previous security configuration.

Caution Failure to follow the recommendations in this section could have serious consequences: without your knowledge, users may unexpectedly be able to perform actions they had been prohibited from performing; also, users could suddenly lose their ability to carry out required actions.

When corruption or unplanned alteration to your Agile PLM system occurs, you will have to interrupt regular system management just to restore essential permissions, which itself could result in additional violations.

Using Agile Configuration Propagation to Restore Admin Settings

You have access to Agile Configuration Propagation (ACP), which lets you propagate the configuration of one Agile instance to another instance of the same version. ("The configuration" is a general term that refers to "all settings content of all Java Client Administrator nodes in one Agile instance".) Any single propagation may consist of the complete Administrator data for an instance, or it may consist of a selected subset of Administration data for an instance.

The subsections that follow, regarding Admin Export and running Administrator Reports, offer some steps to troubleshoot or to diagnose a problem you may suspect exists. By these means, if you detect a problem with a role or some roles or privileges in your production instance of PLM, you may be able to resolve it from within the Administrator module itself.

However, if you determine that your production instance has a serious and widespread problem in Roles and Privileges (or, indeed, with other parts of the PLM application), you may need to do a propagation using ACP to restore correct (and validated) settings. In this case, see *Agile Configuration Propagation Guide* for this release.

Recommended Security and Maintenance Plan

You should take great care when making changes to the powerful Agile PLM roles. Please follow these configuration and maintenance recommendations:

- It is strongly recommended that one person be assigned responsibility for configuring roles and privileges. If a change in ownership is to occur, the current administrator should explain to the new owner:
 - The roles and privileges configuration
 - Any changes that have been made
 - The system of tracking changes to roles and privileges
- Perform a roles export (in the Roles window, select all roles, and click **Export**) and run the Roles and Privileges Summary report and the Privilege Mask Detail report before you change or create roles or privilege masks. Save the results for later comparison in case you need to determine what changes caused particular effects. Keep a log of changes to the privileges configuration. For more information about exporting, see [Object History](#) on page 24. For more information about reports see [Administrator Reports](#) on page 20.
- Use the supplied roles and privileges and make only required alterations.
- Follow the Action–Criteria–Object Type privilege mask naming convention (described in [About Privileges and Privilege Masks](#) on page 211) to avoid confusion and potential security breaches. Include at least these three recommended basic identifying parts, and maintain

consistent word order. Use the names of the privilege masks provided at installation as your guide.

- Avoid changing role and privilege assignments after their initial assignment. For example, if a change originator or CCB member has the Discovery privilege removed after an ECO has been routed, the originator or CCB member still receives notifications but cannot view the change.
- Avoid changing role and privilege assignments while users are working on the system. If such changes are made, users must log out and restart Agile PLM clients again for some changes to take full effect.

Database Backup Procedures

Before you make any changes, it is a good idea to back up the entire Agile PLM database, and run Administrator reports. You can use the database backup to rebuild the previous database. You can compare “before-and-after” reports and use them to diagnose the cause of changes to Agile PLM security.

Exporting Agile PLM Administrative Settings

Follow the instructions in [Object History](#) on page 24. When you have finished backing up current role and privilege settings, run your reports.

Note If you are importing these settings, be certain you are importing to the same database or the Agile PLM administrative data will not match.

Running Reports

When you run an Administrator report, include the report date and time in the filename, such as Roles_072601_3pm.csv. If you keep these report files, you can compare them later to track changes.

Note Be aware that the Privilege Masks Details report can be quite long (hundreds of pages), depending on the number of users on the system.

To run the Roles and Privileges Summary report:

1. Select the **Analytics and Reports** tab in the navigation pane. The **Analytics and Reports** folders appear.
2. Expand the **Standard Reports > Administrator Reports** folder.
3. Double-click (Java Client) or click (Web Client) the Roles and Privileges Summary report. The Roles and Privileges Summary Report page appears.
4. Click **Execute**. The Get Attachment window appears.
5. Click **Continue**. This accepts the displayed default encoding type (Western European (ISO)). If you need to use a different encoding type, select it in the drop-down list and click **Continue**.
6. Follow the directions in the File Download and Save As dialog boxes to save the file to disk and specify a location to save it.
7. Modify the filename to include the report date and time. For example, **Roles072602_3pm.csv**

8. When the download is complete, Click **OK** in the Get Attachment dialog box.

To run the Privilege Mask Detail report:

1. Select the **Analytics and Reports** tab in the navigation pane. The **Analytics and Reports** folders appear.
2. Expand the **Standard Reports > Administrator Reports** folder.
3. Double-click (Java Client) or click (Web Client) the Privilege Mask Detail report. The Privilege Mask Detail Report page appears.
4. Click **Execute**. The Get Attachment window appears.
5. Click **Continue**. This accepts the displayed default encoding type (Western European (ISO)). If you need to use a different encoding type, select it in the drop-down list and click **Continue**.
6. Follow the directions in the File Download and Save As dialog boxes to save the file to disk and specify a location to save it.
7. Modify the filename to include the report date and time. For example, **Privmask072602_3pm.csv**
8. When the download is complete, Click **OK** in the Get Attachment dialog box.

Note Be aware that the Privilege Masks Details report can be quite long (hundreds of pages), depending on the number of users on the system.

By running the Roles and Privileges Summary report and the Privilege Mask Detail report, you create a record of the current roles and privileges configuration. These reports are ASCII text files in .CSV format (comma separated values) that can be opened with an analysis application, such as Microsoft Excel.

You can also use a word processing program to compare two versions of the same report. If the changes you make to the security configuration produce unexpected results, you can run these reports again, and compare them in the word processing program to see the changes that you made.

Working with Roles

You can modify existing roles and create new ones. Once a role exists, you can assign it to users. This section describes the following role-management tasks:

- Modifying a Role
- Creating a New Role
- Deleting a Role

Modifying a Role

When you open a role, you can change its name, description, whether it's enabled or disabled, its list of privilege masks, and the users assigned to it. You cannot modify the properties for the Example–ReadOnly roles.

To change the name or description of a role:

1. Under **User Settings**, double-click **Roles**. The Roles window appears.
2. Use the filter bar to display the role you want to modify.
3. Double-click a role to open it.
4. In the **Name** field, type a unique name (up to 255 characters).

Note You cannot rename the Administrator, My User Profile, or View Historical Report roles, or any of the Restricted roles.

5. In the **Description** field, type a short description (up to 510 characters).
6. Click **Save**.

To disable a role:

1. Under **User Settings**, double-click **Roles**. The Roles window appears.
2. Use the filter bar to display the role you want to modify.
3. Click the **Disable** button.

Note You can also disable a role by opening it and changing its **Enabled** property. You cannot disable the Administrator, My User Profile, or View Historical Report roles, or any of the Restricted roles.

To remove privileges from a role:

1. Under **User Settings**, double-click **Roles**. The Roles window appears.
2. Use the filter bar to display the role you want to modify.
3. Double-click a role to open it.
4. Click the **Privileges** tab.
5. Select the privilege you want to remove.
6. Click **Remove** to delete the selected privilege from the role.
7. Click **Yes** on the Delete dialog.

To add privileges to a role:

1. Under **User Settings**, double-click **Roles**. The Roles window appears.
2. Use the filter bar to display the role you want to modify.
3. Double-click a role to open it.
4. Click the **Privileges** tab.
5. Click **Add Privileges** to open the Select Privileges dialog box.

6. Select privilege masks in the **Choices** list and use the right arrow to move privilege masks to the **Selected** list.
7. When you are finished, Click **OK**.

To remove a user from a role:

1. Under **User Settings**, double-click **Roles**. The Roles window appears.
2. Use the filter bar to display the role you want to modify.
3. Double-click a role to open it.
4. Click the **Users** tab.
5. Select the user you want to remove.
6. Click **Remove** to delete the selected user from the list of assigned users.
7. Click Yes on the Delete dialog.

To add users to a role:

1. Under **User Settings**, double-click **Roles**. The Roles window appears.
2. Use the filter bar to display the role you want to modify.
3. Double-click a role to open it.
4. Click the **Users** tab.
5. Click **Add Users** to open the Select Users dialog box.
6. Select and use the arrows to move users from the **Names** list to the **Recipients** list.
7. When you are finished, Click **OK**.

Building and Testing Attributes, Read/Modify Privileges, and Roles

Agile's privilege model is powerful and flexible, but it is also complex. The following task is a simple procedure for you to check that attributes (both pre-defined and user-defined attributes), privilege masks, and roles all work together as you customize them for your users' work.

To test that an attribute works with Read or Modify privilege masks and roles:

1. In a class, for example, Parts class, create a new, simple **Page Two** attribute. In this example, you are creating **Parts.PageTwo.Test01**. (See [About Attributes, Flex Fields, and Read-Through Fields](#) on page 72.)
2. Create test privilege masks called Read Parts and Modify Parts. Apply them to the Test01 attribute. (See [AppliedTo Capability](#) on page 232. You may want to examine [Discovery and Read Privileges](#) on page 241.)
3. Assign the Read Parts and Modify Parts privilege masks to the Content Manager role. (See [Adding a Privilege Mask to a Role](#) on page 215.)

4. Assign the Content Manager role to a user, perhaps a test user you create for the purpose. (That task precedes this section.)
5. Log out of your client, log in as that user, and check to see that you can both read and modify the Test01 field.

Note This procedure is an overview of building and testing attributes, privileges, and roles. The task of setting up Agile PLM for your company is quite large, and you might consider enlisting the services of an Oracle Consulting – Agile Practice consultant for this important task.

Creating a New Role

Before creating a new role, you should review the roles you currently have. Run the Roles and Privileges Summary report to see a listing of current roles and their privilege masks (see [Running Reports](#) on page 201).

The recommended method for creating a new role is to copy an existing role, and then make any necessary changes to the copy (see [Creating a New Role Using Save As](#) on page 205). You can also create a new role from scratch (see [Creating a New Role from Scratch](#) on page 206).

Note If you delete a role, you can reuse the name of the deleted role when you create a new role or rename an existing role.

Before You Begin

Before creating a new role, answer the following questions:

- What will you name the new role?
- Which users will be assigned to the new role?
- What do you want the users assigned to this role to be able to do in Agile PLM?
- What do you want users assigned to this role to be prevented from doing in Agile PLM?
- Can you modify one or more existing roles to achieve the results you want?
- Is there an existing role that you can copy and modify to avoid having to create the role from scratch?

Creating a New Role Using Save As

You might find it easier to duplicate an existing role under a new name.

Note Creating a new role by duplicating one of the Example roles is a different process and produces different results. Review both processes to determine which one meets your needs. See [Using the Example Roles](#) on page 207.

To create a new role from an existing role:

1. Under **User Settings**, double-click **Roles**. The Roles window appears.
2. Use the filter bar to display the role you want to modify.
3. Double-click the role you want. The tabbed window for that role appears.
4. Click the **Save As** button. The Save As dialog box appears.
5. Enter a new name and API name for the role.
6. Click **OK**.

The new role is created with the new name, and its tabbed window appears. The new role has the same description as the one you copied. You can modify the description now, if you want. See [Modifying a Role](#) on page 202.

The list of privilege masks assigned to the original role is also assigned to the new role. However, no users have been assigned to the new role.

For example, if the original role included the Modify Item privilege mask, the new role also includes the Modify Item privilege mask.

Note A read-only example role has read-only example privileges. When you use Save As to create a copy of an example role, the way the privilege masks are copied from the example role is different from what is described above. See [Using the Example Roles](#) on page 207 for details.

7. Do one or more of the following:
 - On the **Privileges** tab, remove the privilege masks you do not want in the role.
 - On the **Privileges** tab, add the privilege masks you want to include in the role.


For instructions on how to add or remove privilege masks, see [Modifying a Role](#) on page 202.

8. To assign the new role to specific users, see [Modifying a Role](#) on page 202.

Creating a New Role from Scratch


You may decide to create a role or roles from scratch.

To create a new role from scratch:

1. Under **User Settings**, double-click **Roles**. The Roles window appears.
2. Click the **New** button. The Create Role dialog box appears.
3. Type the name, API name and description of the new role.
4. To enable or disable the role, select Yes or No in the **Enabled** drop-down list. It is suggested that you disable the role while you develop it; select No.
5. Do one of the following:
 - To finish creating the role without assigning privilege masks or users (you can assign privilege masks and users later), click **Finish**.
 - To assign privilege masks to the role, click  next to the **Privilege** field. The Select Privileges dialog box opens. Continue with step 6.

6. Select privilege masks in the **Choices** list and use the right arrow to move privilege masks to the **Selected** list.
7. When you are finished, Click **OK**.

Note You can also click **New** in the dialog box to create a new privilege mask. The Create Privilege dialog box opens. See [Creating a New Privilege Mask from Scratch](#) on page 238. (Start with step 3.) The new privilege mask will be added to the role, and the privilege mask will appear in the list of available privilege masks in the **Privileges** node.

8. Do one of the following:
 - a. To finish creating the role without assigning users, click **Finish**. You might want to do this while developing the role and its privilege masks.
 - b. To assign specific users to the new role, click  next to the **Users** field. The address book opens. Continue with step 9.
9. Select users from the **Names** tab—and groups from the **Groups** tab—and use the right arrow to move them to the **Recipients** list.
10. When you are finished, Click **OK**.
11. When you are finished defining the new role, click **Finish**.

The new role name appears in the Roles table. (Click **Refresh** if you do not see the role in the table.) Add privileges and users as needed. If you disabled the role in step 4, the **Enabled** field says No. You must enable the role for its assignment to users to go into effect.

Using the Example Roles

Agile PLM includes a number of example roles that you can use as references or as a starting point for your own roles. They are stored under the **Example** node folder in the **Example Roles** node. Example roles are read-only and cannot be modified. However, you can use Save As to make a copy of an example role and modify the copy.

Each example role corresponds to one of the preconfigured roles provided when Agile PLM is first installed. If you have modified the preconfigured roles and privileges, you can view the example roles to compare your modifications to the original construction of the preconfigured roles and privileges.

Example Privilege Masks in Example Roles

Example roles include example privilege masks. Example privilege masks are also read-only and cannot be modified. When you use Save As to create a copy of an example role, the system populates the new role with copies of the read-only example privileges.

For example, the Example - Creator role includes an example privilege mask named Example - CS - Submit ChgOrder. If you use Save As to make a copy of the Example - Creator role, the new role will include a privilege named Copy of Example - CS - Submit ChgOrder. This privilege mask copy is a new privilege mask that did not exist in the database before you copied the example role. All the privilege masks in the new role are copied in the same manner.

Creating a New Role from an Example Role Using Save As

To create a new role from an example role:

1. Under **Examples**, double-click **Example Roles**. The Example Roles page appears.
2. You can filter roles records to narrow your search. (See [Filtering Data](#) on page 8.)
3. In the Example Roles window, double-click the example role you want. The tabbed window for that example role appears.
4. Click the **Save As** button. The Save As dialog box appears.
5. Enter a new name and API name for the role.
6. Click **OK**.

The new role is created with the new name, and its tabbed window appears. The new role has the same description as the example role you copied. You can modify the description now, if you want. See [Modifying a Role](#) on page 202.

The privilege masks in the new role are copies of the example privilege masks in the example role. For more information, see “Example Privilege Masks in Example Roles” above.

7. Do one or more of the following:
 - On the **Privileges** tab, remove the privilege masks you do not want in the role.
 - On the **Privileges** tab, add the privilege masks you want to include in the role.

For instructions on how to add or remove privilege masks, see [Modifying a Role](#) on page 202.

You can also change the names of the privilege masks or change the criteria or applied to properties of the privilege masks.

On the **Privileges** tab, double-click a privilege mask to display its tabbed object page. Once you have displayed the privilege mask window, you can:

- Change the name or description.
- Modify the privilege mask criteria (see [Modifying Privilege Mask Criteria](#)).
- Modify the privilege mask applied to property (see [Viewing and Modifying the AppliedTo Property](#) on page 233).

8. For information about how to assign the new role to specific users, see [Modifying a Role](#) on page 202.

Deleting a Role

If a role is no longer needed and no users have been assigned it, you can delete it.

To delete a role:

1. Under **User Settings**, double-click **Roles**. The Roles window appears.
2. Click the role you want to delete. The tabbed window for that role appears.
3. Click the **Users** tab to bring it forward.

Note You cannot delete a role if it has been assigned to any users or user groups. Before you can delete the role, you must remove all of its users and user groups. Remember that it is always possible to disable a role if you are not ready to delete it but want to block its effect on assigned users and user groups.

4. If there are any users listed on the **Users** tab, select all the users on the table.
5. Click **Remove** to clear the **Users** tab.
6. Repeat steps 3, 4, and 5 for the **User Groups** tab.
7. Click the **Delete** button.

Privileges and Privilege Masks

This chapter includes the following:

▪ About Privileges and Privilege Masks	211
▪ Getting Familiar with Privileges and Privilege Masks	211
▪ Default Agile PLM Privileges	215
▪ Privilege Mask Components	225
▪ Enabling a Privilege Mask	231
▪ Modifying Privilege Masks	232
▪ Creating New Privilege Masks	237
▪ Combining Options in Criteria and AppliedTo Attributes	239
▪ Discovery and Read Privileges	241
▪ Modify Privilege	246
▪ Applying Create User Criteria	250
▪ Using Privilege Mask Criteria Variables	251

This chapter explains how to use Agile PLM's preconfigured privileges and privilege masks, and how to create new ones.

About Privileges and Privilege Masks

This chapter focuses on privileges and the construction of privilege masks. The actions that users can perform in Agile PLM—such as creating, sending, or canceling—are based on *privileges*. Privileges are combined with reusable criteria to create *privilege masks*, which act as filters to manage user actions. Privilege masks are then grouped into *roles* that provide a way of allocating a common set of privileges to a group of users who have common functions in the change control process.

Agile PLM provides a comprehensive set of preconfigured roles, privilege masks, and reusable criteria that are accessible from the **Roles**, **Privileges**, and **Criteria** nodes, respectively. You can change the preconfigured roles and privilege masks as necessary, or you can create new ones to fit your specific needs.

Note When you assign a role or a privilege mask to a user, it takes effect only after the user has logged out and logged back into an Agile PLM client.

Getting Familiar with Privileges and Privilege Masks

To view the **Privileges** window:

1. Under **User Settings**, expand the **Privileges** node. The **Privileges** node expands to show all the basic privileges (the action component of privilege masks) as subnodes.
2. Double-click a **Privileges** subnode. The page that opens is called **Privileges for <selected privilege>**,

although no privilege masks are listed. For example, when you double-click **Administrator**, the Privileges for Administrator page opens. You must set some filter criteria; often it is useful to set the Match If field to **Show All**, then click the **Apply** button to the right. All the privilege masks that use the Administrator privilege are displayed.

The page in this example reads “Privileges for Administrator” but makes more sense as follows: “**Privilege Masks that use Administrator privilege**”.

3. You can filter the returned privilege masks to further narrow your search of privilege masks. In this example, setting a new filter with Match If set to **Contains** and Value with **User** typed in, clicking **Apply** reduces the returns to Admin Access for User Admin. (See [Filtering Data](#) on page 8.)

You can click a column header in the privilege mask table to sort the table by that column.

Viewing Privilege Masks

The privilege masks that make up a role define the actions its users can perform. Agile PLM provides you with a set of preconfigured privilege masks for the installed roles. Every role has at least one privilege mask.

To view the privilege masks for a particular role:

1. Under **User Settings**, double-click **Roles**.
2. In the Roles window, double-click the role. The role’s tabbed window appears.
3. Click the **Privileges** tab. The privilege masks are displayed in the table.

Viewing Privilege Mask Properties

Each of the privilege masks that make up a role has its own set of properties that define the privilege being controlled. The available privilege mask properties are listed and described in the following table. Not all of these properties are configurable for all privilege masks.

Property	Description
Name	A name, for example, “Modify Resume Date.” A privilege mask name of up to 255 characters.
Description	A maximum 510-character description of the privilege mask, for example Modify Resume Date After Release.
Enabled	Yes or No. When set to No, allows you to work with a privilege without its being in effect. This is useful when setting up privileges.
Privilege (governing action)	A privilege, for example, Create. Identifies the privilege, or action, such as Create, Delete, Modify, Print, or Read. Only one privilege is defined in a privilege mask. After the privilege mask has been created, this property is not editable.

Property	Description
Privilege Criteria	<p>The reusable criteria selected for this privilege mask. Only one reusable criteria is selected for each privilege mask. The selected reusable criteria defines two important properties of the privilege mask:</p> <ul style="list-style-type: none"> ▫ Object Type — Identifies the Agile PLM object type for the privilege mask. ▫ Criteria — Specifies the exact conditions for applying the privilege, for example, Cover Page.Status Equal to StatusType.Released. The reusable criteria specifies all possible fields and match-if values for the object type.
AppliedTo	<p>Modify, Read, Administrator, Dashboard Management, and Microsoft Project privileges only.</p> <p>Specifies the attributes that a Modify or Read privilege mask is applied to, such as Cover Page.Date Originated. See Discovery and Read Privileges on page 241 and Modify Privilege on page 246.</p> <p>Specifies which administrator node the Administrator privilege mask is applied to, such as Users. See AppliedTo Capability on page 232.</p> <p>Two other privileges that use AppliedTo are describe in Dashboard Management on page 38 and PPM-specific Privileges.</p>
Workflow	<p>(Change Status and Override privileges only)</p> <p>For Change Status, specifies the workflow in which the user can change statuses or override change status actions.</p> <p>For Override, the From Status and To Status properties define the change status action the user can override.</p>
From Status	<p>(Change Status and Override privileges only)</p> <p>For Change Status, specifies the statuses from which the user can change to another status.</p> <p>For Override, the From Status and To Status properties define the change status action the user can override.</p>
To Status	<p>(Change Status and Override privileges only)</p> <p>For Change Status, specifies the statuses the user can change to.</p> <p>For Override, the From Status and To Status properties define the change status action the user can override.</p>

To view privilege mask properties:

1. Under **User Settings**, double-click **Privileges**.
2. In the Privileges window, double-click the privilege mask you want to view. The privilege mask window appears.

Note Filter privilege mask records to narrow your search. For example, filter records by Privilege Contains Modify to find all the Modify privilege masks on the list. (See [Filtering Data](#) on page 8.)

3. To modify a property, enter text in text fields or use the drop-down lists.

Note The **Privilege (governing action)** field is not editable.

- When you are finished, click **Save**, or click **Close** to exit without saving your modifications.

Tasks Performed from the Privileges Window

You perform various privilege mask management task from the Privileges window by selecting one or more privilege masks, then clicking the appropriate button.

Page menu button	Action
Enable	Enables the selected privilege masks. When the privilege mask is enabled, Yes appears in the Enabled column.
Disable	Disables the selected privilege masks. When the privilege mask is disabled, No appears in the Enabled column.
Delete	Deletes the selected privilege masks.
New	Opens the Create Privilege dialog box. See Creating a New Privilege Mask from Scratch on page 238.
Assign Roles	Allows you to add the privilege mask to one or more roles. Note: When you assign a role or a privilege mask to a user, or change the privilege masks in a role, the change takes effect for a given user only after the user has logged out and logged back in to an Agile PLM client.
Export	Exports the selected privilege masks to a text file. See Object History on page 24.
Export All	Exports all privilege masks to a text file. See Object History on page 24.
Import	Imports a text file to create one or more new privilege masks. See Object History on page 24.
Refresh	Refresh the displayed table with the latest information.

When you double-click a privilege mask, the privilege mask's tabbed window appears.

Removing a Privilege Mask from a Role

To remove a privilege mask from a role on the privilege mask *Where Used* tab:

- Under **User Settings**, expand the **Privileges** node in the navigation pane. The list of basic privileges appears.
- Double-click the basic privilege for the privilege mask you're interested in. The form for that privilege appears.
- Click the **Refresh** button at the bottom of the form. All the privilege masks for that privilege appears.
- Double-click the specific privilege mask you want. Its tabbed window appears.
- Click the **Where Used** tab to bring it forward. The roles that include the privilege mask are listed in the table.

6. Select the role from which you want to delete the privilege mask, and click the **Remove** button.
7. When the confirmation dialog appears, Click **OK**. You are not deleting the role itself, you are removing the privilege mask (which is the actual object you have opened) from that role.

Adding a Privilege Mask to a Role

To add a privilege mask to a role on the privilege mask **Where Used** tab:

1. Under **User Settings**, expand the **Privileges** node in the navigation pane. The list of basic privileges appears.
2. Double-click the basic privilege for the privilege mask you're interested in. The form for that privilege appears.
3. Click the **Refresh** button at the bottom of the form. All the privilege masks for that privilege appears.
4. Double-click the specific privilege mask you want. Its tabbed window appears.
5. Click the **Where Used** tab to bring it forward. The roles that include the privilege mask are listed in the table.
6. Click the **Add Roles** button. The Select Roles dialog box appears.
7. Move roles from the **Choices** list to the **Selected** list.
8. Click **OK** when you are finished. You are not adding a role in any way, you are adding the privilege mask (which is the actual object you have opened) to that role.

Note You may want to review the simple tutorial [Building and Testing Attributes, Read/Modify Privileges, and Roles](#) on page 204.

Default Agile PLM Privileges

The following table lists and defines the privileges supplied with Agile PLM. Some privileges depend on the basic Read privilege for their effectiveness, since users must first be able to open and read objects before they can perform most other functions. This table indicates which privileges work only if the user also has a Read privilege.

For more information about the Read privilege and privilege masks, see [Relationships among Discovery and Read Privileges](#) on page 243.

Privilege	Allows the user to...	Requires basic Read privilege
Add Approver/Observer	Add approvers/observers to the Workflow tab of a routable object. For more information, see Add Approver/Observer and Remove Approver/Observer on page 221.	Yes

Privilege	Allows the user to...	Requires basic Read privilege
Administrator	Log in to Java Client with access to PLM Administrator functions. The Administrator role includes the Administrator privilege mask, which can be made specific to nodes based on values selected in the AppliedTo property. For more information, see Administrator Privilege and the AppliedTo Capability on page 233.	No
Approve/Reject	Approve or reject a routable object that the user has been named as an Approver.	Yes
Attachment Redlines for Self	This privilege is disabled out-of-the-box. They should be enabled if the administrator wants to create Criteria specific to Workflow Statuses that, for example, prevents users from redlining once the workflow has reached Review or Released statuses. Note: The general ability to enable and control access to attachment redline markups is provided by the Markups subclass (of File Folders class) and its associated Create, Read, Modify, Checkin, and Checkout privilege masks. For more information about relining in PLM, see Redline Markup Default Roles and Privileges on page 405.	-
Attachment Redlines for Others	This privilege is disabled out-of-the-box. They should be enabled if the administrator wants to create Criteria specific to Workflow Statuses that, for example, prevents users from redlining once the workflow has reached Review or Released statuses. Note: The general ability to enable and control access to attachment redline markups is provided by the Markups subclass (of File Folders class) and its associated Read, Modify, Checkin, and Checkout privilege masks. For more information about redlining in PLM, see Redline Markup Default Roles and Privileges on page 405.	-
Cancel Checkout	Cancel a checkout of an attachment (file or URL). For more information, see Attachment Privileges on page 400.	Yes
Change Status	Move a routable object from any status to any other status. The class of the criteria that is selected determines the list of available workflows to which to apply the Change Status privilege. For more information, see Change Status on page 221.	Yes
Checkin	Check in an attachment (file or URL). (For more information, see Attachment Privileges on page 400.)	Yes
Checkout	Check out an attachment file (file or URL). For more information, see Attachment Privileges on page 400.	Yes

Privilege	Allows the user to...	Requires basic Read privilege
Comment	Comment on a routable object. The comment is emailed to specified users, and is recorded in History. (Not the same as comments submitted during approval or rejection of a routable object.)	Yes
Create	<p>Create a new object in the business class specified in the privilege mask.</p> <p>Note 1: The Create privilege is required for users of the Agile PLM Import utility.</p> <p>Note 2: If you have activated the CreateUser attribute for an Agile PLM class by making it visible on the Page Two tab, the user can open and create objects that have a Read privilege. See Applying Create User Criteria on page 250.</p> <p>Note 3: The Create privilege allows the user to fill in required fields at the time of creation even if the user does not have Modify privilege for those fields. Required fields are fields with their attribute property Required set to Yes; see Defining Attribute Properties on page 79.</p>	Yes
Create From Template	Used in Create Program From Template privilege mask, which is enabled out-of-the-box for Program Manager and Program Administrator roles.	Yes
Dashboard Tab View	<p>Used in Read Dashboard Tabs privilege mask, which is enabled out-of-the-box for Executive, Project Manager, and Project Administrator roles.</p> <p>All newly created Dashboard tabs under Systems Settings > Dashboard Management require this privilege to permit viewing the tab in Web Client.</p> <p>For more information, see Dashboard Management on page 38.</p>	Yes
Delete	<p>Delete an object.</p> <p>Note: A routable object must be Pending or Unassigned.</p>	Yes
Discovery	<p>Learn that an object exists.</p> <p>Note 1: You must restart the WebLogic server when you change the Enabled property of Discovery Privilege in the Database node.</p> <p>Note 2: If Discovery Privilege is disabled in the Database node, users with a basic Read privilege can discover all objects.</p> <p>For more information, see Discovery Privilege on page 241.</p>	No
Enforce Field Level Read	<p>Control certain performance consequences when a user does a Field-level Read query.</p> <p>For more information, see Enforce Field-Level Read Privilege on page 244, including Important note about a workaround due to</p>	Yes

Privilege	Allows the user to...	Requires basic Read privilege
	removal of the Specify Output Columns privilege.	
Export	Extract data from selected objects and export it to either a comma-delimited text file or a PDX package. For more information about this privilege, see Export on page 222.	Yes
FileLoad	Run the FileLoad utility. See the Import and Export Guide for more information about the FileLoad utility.	Yes
FullSearchDisplay	See a full return of reports queries on objects. For more information, see Full Search Display on page 222.	Yes
GetFile	Get or open a file from an object's Attachments tab. Note that GetFile privilege works in tandem with Checkout privilege to actually deliver the attachment file to the user's machine. The GetFile privilege (without Checkout) allows the administrator to permit a user to get a file without being able to change it in the product record. For more information, see Attachment Privileges on page 400.	Yes
GlobalSearches	Create, modify, or delete a search that shows up in everyone's search list. This privilege also allows user to order searches and search folders: in Java Client, there is a button with a down arrow when you click on any search folder or search; in Web Client, in the Organize Search popup, there is an extra Order button.	No
Grant	Grant roles, and therefore privileges, to users in a controlled, finite way, using Access Control List (ACL) capability.	Yes
Import	Use the Import process. See the <i>Import and Export Guide</i> for more information about the Import tool.	Yes
Incorporate	Toggle the incorporation status on the Attachments tab. Note: An item can be Incorporated or Unincorporated under an Introductory rev.	Yes
Manage Report	Modify and delete report schedules and layouts, and create and delete global report folders.	Yes
Microsoft Project	Access, use, or modify Microsoft Project, and part of Project Manager and Project Administrator roles. See Microsoft Project Privilege.	Yes
Modify	Modify fields on the tab of an object. Modify privileges are assigned using the AppliedTo attribute settings. For more information about various aspects of the Modify privilege, see Modify Privilege on page 246, AppliedTo Capability on page 232, and Modify Privilege and Attachments on page 402.	Yes

Privilege	Allows the user to...	Requires basic Read privilege
Override	Override incomplete required fields and required approvers who have not signed off, and move the routable object to the next status. For more information, see Override on page 223.	Yes
PrintFile	Print from the AutoVue for Agile window. The user must also have ViewFile privilege. For more information, see Attachment Privileges on page 400.	Yes
PrintTab	Print from the tabs of an object.	Yes
Purge Folder Version	Purge unused file folder version from the Agile File Management vault. See Purge Folder Version Privilege on page 224.	
Read	Open an object to read all tabs. For more information, see Discovery and Read Privileges on page 241. The Read privilege is based on the AppliedTo property for specific attributes. See Field-Level Read Privilege and AppliedTo Capability on page 232. The Read privilege is further applied on a field-by-field basis when Enforce Field-level Read is assigned to the same user. For more information, see Enforce Field-Level Read Privilege on page 244. Note: If Discovery Privilege is enabled in the Database node, a corresponding Discovery privilege mask is required.	Yes
Remove Approver/Observer	Remove approvers/observers from a routable object. For more information, see Add Approver/Observer and Remove Approver/Observer on page 221.	Yes
Reset	Reset the checksum in the Agile PLM database to match a referenced file. Reset privilege is found in Reset File Checksum privilege mask, which is not included in any out-of-box Agile role. See Handle File Checksum on page 358.	Yes
Run Report	Run reports, create schedules for reports, and create report layouts. Modify and delete a user's own schedules and layouts.	Yes
SaveAs	Copy an object by saving to another name.	Yes
Send	Carry out a File Send on an open object. A corresponding Create privilege mask is required.	Yes
Subscribe	Subscribe to notification emails when selected attributes of an object are modified. Note that the Database-node property Notification Enabled must also be set to Yes.	Yes

Privilege	Allows the user to...	Requires basic Read privilege
Transfer Authority for Self	Designates users to approve changes for a specified period of time when the designator—oneself—is an approver (but not observer) on a routable object. For more information, see Transfer Authority for Self on page 224.	No
Transfer Authority for Others	Designates users to approve changes for a specified period of time when the original user—an “other”—is an approver (but not observer) on a routable object; the original approver is copied on all notifying email. For more information, see Transfer Authority for Others on page 225.	No
Undelete	Undelete an object.	Yes
Unincorporate	Unincorporate an item.	Yes
Update All Timesheets	View all tasks for a selected user and change timesheet details entered by that user for each task. Overrides system privileges for viewing tasks – the user accessing the timesheet need not be a team member on the task. This privilege also allows the user to search timesheet entries by all users in the system.	Yes
User Administrator	Uses its AppliedTo property to tailor which roles that user can assign to other users.	Yes
ViewFile	View files in the AutoVue for Agile window. For more information, see Attachment Privileges on page 400.	Yes

Further Discussion of Specific Privileges

The following section gives more information about selected privileges:

- [More Information about Selected Privileges](#) on page 221

Later this chapter explores how privilege masks are constructed, beginning with [Privilege Mask Components](#) on page 225. Subsequent sections provide detailed information about the Discover, Read, and Modify privileges, as well as the important AppliedTo property (which is found in Administrator and just a few other PLM Privileges).

- [Discovery and Read Privileges](#) on page 241
- [Modify Privilege](#) on page 246
- [AppliedTo Capability](#) on page 232

More Information about Selected Privileges

This section provides detailed information about some important Agile PLM privileges. It is not a comprehensive detailing of all the privileges in the Agile PLM system. Keep in mind, the privileges do not work alone; they must be cited by a privilege mask—for example, Create Item—and then activated by inclusion in a role that includes that privilege mask.

Note Information about privileges that are involved in working with attachments is provided in [Attachment Privileges](#) on page 400.

Add Approver/Observer and Remove Approver/Observer

The Add Approver/Observer privilege allows the user to designate a user, global user group, or partner to approve or reject a specific routable object. This privilege also allows the designation of any of these categories to be an observer that can see the routable object, is not required to approve or reject the routable object, but still can approve or reject if necessary.

The Remove Approver/Observer privilege allows the user to remove any of these from the list of approvers or observers on a specific routable object. For more information about adding an approver or observer, see [More about Affected Items: Adding Approvers and Observers](#) on page 124.

Note To successfully add or remove approvers or observers from a Review or Released status of a workflow, the Ad Hoc Approvers/Observers property for that status must be set to Yes.

Change Status

Change Status is crucial in the approval process that advances changes through workflows. The Change Status privileges use privilege criteria to control the statuses a user can manipulate—for specified changes, move forward or backward in the workflow. The function of the privilege is to designate which statuses can be affected by a user in a given role.

Note Each Change Status privilege mask applies to one named status of one specified workflow. You must create Change Status privilege masks for each status of every new workflow you create and enable them, including the statuses of workflows created by SaveAs (that is, a workflow that is given another name via SaveAs, whether it is modified or not, needs its own Change Status privileges).

The status types that are available to the privilege are determined by the workflow selection for the privilege when it is created. This is also affected by the reusable criteria applied to the privilege.

There can be multiple “From” or “To” settings defined in Change Status. The administrator can designate a role to move a change from multiple statuses to a single status, for example, Pending, Submit, or Review to Hold status. Or the administrator can designate a role to move a change from a single to multiple statuses, for example, Hold to Pending, Submit, or Review status.

To define a Change Status privilege mask:

1. Under **User Settings**, double-click **Privileges**.

2. In the Privileges window, click the **New** button. The Create Privilege dialog box appears.
3. Fill in the **Name** and **Description** fields for the Change Status privilege mask.
4. By default, the privilege mask is enabled. If you want, select No in the **Enable** field to disable the privilege mask.
5. In the **Privilege** field, select Change Status from the dropdown list.
6. In the **Criteria** field, select a criteria from the list, and click the **OK** button.

Or click the **New Criteria** button to define a new reusable criteria. (See [Creating a New Criteria](#) on page 121.)

7. In the **Workflow** field, select a workflow from the dropdown list.

Additional fields, **Status-From** and **Status-To**, are displayed in the dialog box.

Note	If you select All in the Workflow field, the Status-From and Status-To fields are not available. When you select All for the workflow name, you create a Change Status privilege mask that allows a user to change from any status to any status in any workflow. This is useful when you want to test workflows.
-------------	--

8. In the **Status-From** dialog box, move statuses from the **Choices** list to the **Selected** list. Click **OK** when you are finished.
9. In the **Status-To** dialog box, move statuses from the **Choices** list to the **Selected** list. Click **OK** when you are finished. When you have complete all the fields in the dialog box, Click **OK**.

Export

This privilege allows Agile users to extract data from selected objects and export it to such formats as: a comma-delimited text file, a Microsoft Excel file, a PDX package, or an "Agile XML" (aXML) file.

PDX is a standard for electronic exchange of engineering and manufacturing information across the supply chain. A PDX package is an XML file that can be viewed with Agile eXpress, a free client.

Please contact Oracle Consulting–Agile Practice for information about the eXpress viewer.

Full Search Display

The Full Search Display *privilege* does not apply to searches. It applies to results of report queries. Users with the Full Report Display *privilege mask* will see all results of reports; users without the privilege mask will see up to the maximum number of results specified by the Maximum Query Results Displayed preference. Additionally, all privilege checking is bypassed on users with this privilege when they view report results.

Grant

A user's ability to grant roles to another user for a specific object is handled by the Grant privilege.

The *sharing* feature of Agile PLM lets a user "grant" one or more of his roles to another Agile PLM user or user group for specific objects. The capability to share a given role includes:

- The user's assigned, "permanent" roles, although he shares the role with another user

regarding only a specific object

- Roles that have been shared with the user (by another user) for a particular object
- Roles that have been shared with the user by virtue of belonging to a user group to which the role has been shared.

The named user (or members of the named user group) can then perform actions permitted by the roles for that object only; the user does not acquire the role in any permanent or far-reaching way.

A user's or user group's **Share** tab lists those objects for which the user has been granted "shared roles" by a different user. A user can click **User Profile > Share** to see objects being shared with them and what role(s) inform their interaction with each. A user can click **User Profile > User Groups > (specific group) > Share** to see objects being shared with you via user group.

Override

The Override privilege governs who can override the required fields and required approvers for a status and move the change to the next status without those fields being filled in or approvers signed off. With Override privilege, a user can release a change even when all required fields are not filled in.

The Override privilege is specific to each status. A change can be moved to the next status without all approvals as long as the user has the privilege to move a change to the next status. For example, a user might be able to override the promotion of a change from the Manager Review status to the CCB Review status, but not the promotion of a change from Final Review to Released.

A warning is issued to the user if there are missing fields, approvers, or other requirements for the usual move to the next status level.

Caution A user with the Override privilege can promote a routable object to the next status in all of the following situations:

- Regardless of the presence of any required fields.
- When Pass Release Audit is set to Yes.
- When the Change Status Approver Rejected Change SmartRule is set to Warning or Disallow.
- When the Change Status Observer Rejected Change SmartRule is set to Warning or Disallow.
- When the Change Status No Response Change SmartRule is set to Warning or Disallow.

For the Change Status Approver Rejected Change and Change Status Observer Rejected Change SmartRules, a Warning setting does not prevent the routable object from being autopromoted; that is, the SmartRules *must* be set to Disallow to prevent autopromotion.

To allow the change analyst to decide whether or not to promote a routable object that has been rejected, the following conditions need to be true:

- AutoPromotion is set to Yes for that status.
- These two SmartRules are set to Disallow.
- The change analyst has the Override privilege for this status.

The Override privilege calls for specific “From” and “To” settings, such as Change Status. The Override privilege lets a user change the status of a routable object, even if the Pass Release Audit is set to Yes. The only exception is during the initial release of a routable object. If the Pass Release Audit is set to Warning, then the warning appears even during an override.

Note that when the user does not have Override privilege, and Pass Release Audit = Warning or No, the Status Audit should give an Error (which requires user to fix conditions) instead of a Warning.

Purge Folder Version Privilege

The Purge Folder Version (PFV) privilege allows a user to purge unused file folder versions from the Agile File Management fault. The file folder version number is removed from the file folder **Version** drop-down list. You can create Purge Folder Version privilege masks for specific subclasses of folders by selecting the appropriate folder object criteria when you create and define the PFV privilege mask. The user must have appropriate privilege masks to discover and read the file folder object in order to select the file folder version to purge. If a file folder version is checked out, has redlines, or is in use on a business object **Attachments** tab or **Content** tab, it cannot be purged.

The **Purge Folder Version** command appears on the file folder object **More...** menu (Java Client) and **Actions** menu (Web Client).

Transfer Authority for Self

The Transfer Authority for Self privilege allows the user to designate a target user, who is allowed to approve or reject changes for her for a specified period of time. The authority transfer applies when the user is an approver on a routable object, but not when the user is an observer. Transfer Authority for Self is very useful for situations where the original user is going on a vacation or extended leave.

The target user can vary depending on criteria within the privilege. For example, all changes for Project A can be directed to Mary and all changes for Project B can go to Joe. If the criteria for the different transfers overlap, then both users who have been defined as the target of the transfer receive the notifications and are able to sign off for the original user.

The transfer of authority is in effect for the duration specified by the start and end dates. Once this time has elapsed, signoff authority is automatically transferred back to the original user.

If a user’s authority needs to be transferred to more than one person, such as multiple targets during a longer vacation, the target users should be specified sequentially, as shown in the following table.

From User	To User	Start Date	End Date
Brian Henson	David Goelz	14-July-2007	30-July-2007
Brian Henson	Kevin Clash	31-July-2001	12-Aug-2007

Caution	If you need to remove a user from the system who is named as the “To” user in signoff authority transfers, see Deleting and Undeleting Users on page 254 for more information.
----------------	--

Transfer Authority for Others

The Transfer Authority for Others privilege allows an authorized user to transfer an original approver's right to approve or reject changes to another user for a specified period of time. The authority transfer applies when the original user is an approver on a routable object, but not an observer.

This privilege overrides transfers designated by users who have the Transfer Authority for Self privilege. The original approver is copied on all notifying email.

Note When you create a transfer criteria, you can include criteria conditions with **Affected Items** tab fields. To select a specific routable object, an **Affected Items** field condition must be true for all the objects on the **Affected Items** tab of that routable object.

For example, if you specify Affected Items.Old Lifecycle Phase Equals Preliminary, then all the objects on the **Affected Items** tab must have the **Old Lifecycle** field equal to Preliminary. If you select Contains as the search operator, then every object on the **Affected Items** tab must contain the specified value in the specified field.

Site Change Order Save As Limitations

You cannot initiate Save As from a non-Site Change Order (SCO) change object to create an SCO object, nor can you initiate Save As from an SCO object to create a non-SCO change object. Because Site Change Orders (SCOs) affect only site-specific information, and other types of changes are not limited to site-specific information (for example, ECOs and MCOs), SCOs can be Save-As-created only from another SCO. The Site Change Order's site-specific only usage makes it incompatible with other change types when using the Save As feature.

Subscribe

The **Subscribe** privilege allows a user to *subscribe* to an object to receive notification of events that happen to that object. Users can even be notified when specified fields are modified, and can select the events about which to be notified.

The user needs the Subscribe privilege for a specific object class to be able to subscribe to that class's objects.

On the **Subscriptions** tab of a user, you can view the objects to which this user has subscribed.

Subscription events trigger two types of notifications: Email and Inbox. Email notifications are sent only if the user's Receive Email Notification preference is set to Yes; this property is on the **Preferences** tab of the user object.

Privilege Mask Components

Privilege masks are a powerful and complex feature. Each privilege mask is composed of several components. Together, the privilege mask components define the following:

- What action the user can perform;
- The object type on which the action can be performed;

- Filtering conditions that define a subset of objects on which the action can be performed.
- AppliedTo attributes – found only in privilege masks based on the Administrator, Modify, Read, Microsoft Project, and Dashboard Management privileges – which displays specific object attributes;
- For the Change Status privilege, the workflow, the status the user can change from, and the status the user can change to (see the second diagram in [Combining Options in Criteria and AppliedTo Attributes](#) on page 239).

All Privilege Masks have a Privilege, an Object Type, and a Criteria

Privilege masks act as filters to either enable or prevent user actions. By combining the types of action with the precise conditions under which it should be enabled, privilege masks control user activity in Agile PLM. The following components are used to construct privilege masks and are among the privilege mask properties:


1. The **privilege** or action (see [Privilege Mask Component 1: Privileges](#) on page 227)
2. The **object type** to be acted upon (see [Privilege Mask Component 2: Object Type](#) on page 229)
3. The **criteria** or conditions under which to apply the action (see [Privilege Mask Component 3: Criteria](#) on page 230)
4. The **attributes** to which the action will be applied to (see [Privilege Mask Component 4: Attributes](#) on page 230)

A Few Privileges are the Basis to Privilege Masks with AppliedTo

The final item in the above list refers to attributes in privilege masks; but this element is not found in all privilege masks. A small subset of the PLM privileges – Administrator, User Administrator, Read, Modify, Microsoft Project, and Dashboard Tab View – are the basis of privilege masks that require a fourth component, that is, named attributes found in the AppliedTo property of the privilege. This important property is detailed in [AppliedTo Property in Select Privileges](#) on page 232.


Diagramming Privilege Masks

Privilege masks employ a reusable criteria to define the object type and filtering conditions. When you create a privilege mask, you select a reusable criteria from the list of criteria objects, as seen in the schematic diagram.



Naming Privilege Masks

The following convention for naming privilege masks has been used so their purpose and function is as clear as possible.




Some privilege masks consist of only the privilege and the object type, for example, Send Changes.

Privilege Mask Component 1: Privileges

The fundamental building block of a privilege mask is the *privilege*, or the action it enables, such as Discovery, Modify, or Submit. We have already looked at the basic privileges in the Agile PLM

system in Agile PLM Privileges.



This basic privilege is defined when the privilege mask is created, and can be viewed on the **General Information** tab of the privilege mask. For example:

To view the properties of the Modify Eng Changes privilege mask:


1. Under **User Settings**, double-click **Privileges**.
2. In the Privileges window (which actually lists Privilege Masks based on the named Privilege), double-click the privilege mask **Modify Eng Changes**. The privilege mask object appears.

Note Filter privilege records by Privilege Contains Modify to find the all the Modify privilege masks on the list. (See [Filtering Data](#) on page 8.)

3. You can now modify the editable fields of the **General Information** tab.
Notice that you cannot edit the **Privilege** field, indicating that you cannot change this value after the privilege mask is created. Notice, also, that you can edit the **Privilege Criteria** field.
4. Click **Cancel** when you have finished viewing the editable properties of the privilege mask.

Privilege Mask Component 2: Object Type

Most privilege masks consist of the *object type* to be acted upon, for example, Changes base class, Change Orders class, or ECO subclass. The object type is also a privilege mask property that is defined when the privilege mask is created, when you select the reusable criteria. The object types are defined in the **Classes** node. For more information about object types, see [Installed Object Types](#) on page 54.



Some privilege masks, such as Send Changes (depicted above), consist of only the privilege and the object type. For this type of privilege mask, select a reusable criteria that specifies the object type only with no filtering criteria, such as the For Changes Only reusable criteria.

You can use the object type to broaden or narrow the privilege. The following example illustrates how a Modify Changes privilege mask could be broadened to include all changes, or narrowed to include just ECOs. See *Installed Agile PLM Classes, Base Classes, and Subclasses* for a complete list of Agile PLM object types.


Select this object type	To allow user to modify...	
	<i>These classes:</i>	<i>These subclasses:</i>
Changes	Change Orders class Change Requests class Deviations class Manufacturer Orders class Price Change Orders class Site Change Orders class Stop Ships class	ECO ECR Deviation MCO PCO SCO Stop Ship
Change Orders class	Change Orders class	ECO (also includes any other Change Order subclasses that you have defined)

Select this object type	To allow user to modify...	
	<i>These classes:</i>	<i>These subclasses:</i>
ECO	N/A	ECO (includes this subclass only)

Note If you remember to use the Action–Criteria–Object Type naming convention, the object type is part of the privilege mask name. (See [Naming Privilege Masks](#) on page 227.)

Privilege Mask Component 3: Criteria

Another property of a privilege mask is the set of *criteria* you want to apply, or the conditions under which the privilege mask will work. Criteria are defined in the reusable criteria when it is created. The criteria for the privilege mask is defined when the privilege mask is created and the reusable criteria is selected from the list. You can select a different reusable criteria later.




Using this particular reusable criteria allows users to modify only engineering changes in one of the status types defined in the reusable criteria (Pending, Submit, Review, Cancel, Hold, or Unassigned).

Privilege Mask Component 4: Attributes

Another building block of a privilege mask is the *attribute* (or attributes) you want the privilege mask applied to. These are called AppliedTo attributes, and are used only in Modify and Read privilege masks. AppliedTo attributes are defined when the privilege mask is created and can also be changed later.

Modify privilege masks are designed to let users modify the attributes on a particular tab, such as the **Cover Page**, **Title Block**, or **General Information** tab.

For example, the Modify Eng Changes privilege mask provided with your Agile PLM installation is designed to apply to, or allow users to modify, the attributes shown in the figure below:




To view these AppliedTo attributes:

1. Under **User Settings**, double-click **Privileges**.
2. In the Privileges window, double-click the privilege mask **Modify Eng Changes**. The privilege mask appears; see the schematic above.

Note Filter privilege records by Privilege Contains Modify to find all the Modify privilege masks on the list. (See [Filtering Data](#) on page 8.)

The AppliedTo attributes are listed on the **General Information** tab.

3. To view the lists of available attribute values and selected attribute values, click the down-arrow  next to the **AppliedTo** field. The **Choices** and **Selected** lists appear in the selection dialog box.
4. Click **Cancel** when you have finished viewing the lists. Click **Close** when you have finished viewing the **General Information** tab fields.

Enabling a Privilege Mask

To enable a privilege mask that is currently disabled:

1. Under **User Settings**, double-click **Privileges**. The Privileges window appears.
2. Click the privilege mask you want to enable.

Note Filter privilege mask records to narrow your search. For example, filter records by Privilege Contains Modify to find all the Modify privilege masks on the list. (See [Filtering Data](#) on page 8.) Or you can click the Enabled column header to sort by Yes (enabled) or No (disabled).

3. Click the **Enable** button on the window toolbar.

The disabled privilege mask is now enabled.

Note You can also enable and disable a privilege mask when you edit the **General Information** tab of the privilege mask.

Modifying Privilege Masks

You can modify privilege masks in many ways. This section describes these modifications.

Modifying Privilege Mask Criteria

To modify existing Privilege Mask Criteria:

1. Under **User Settings**, double-click **Privileges**.
2. In the Privileges window, click the privilege mask you want to modify. The privilege mask window appears.

Note Filter privilege mask records to narrow your search. For example, filter records by Privilege Contains Modify to find all the Modify privilege masks on the list. (See [Filtering Data](#) on page 8.)

The privilege mask properties are displayed on the **General Information** tab.

3. To modify a property, enter text in text fields or use the drop-down lists.
4. In the **Privilege Criteria** field, select a different reusable criteria from the drop-down list.
Or click **Create** to define a new reusable criteria. (See [Creating a New Criteria](#) on page 121.)
5. When you are finished, click **Save**. To cancel the changes, click **Close**.

AppliedTo Property in Select Privileges

The AppliedTo capability is set in privilege masks based on the following privileges.

Remember, in a privilege object, the rows are its constituent privilege masks: double-click a row to open the privilege mask object (which has AppliedTo property if it is based on these privileges):

- **Administrator** privilege: Administrator and "Admin Access for User Admin"; see [Administrator Privilege and the AppliedTo Capability](#) on page 233.
- **User Administrator** privilege: User Administrator privilege mask sets roles that user can assign to other users; [Specialized Administrator Privilege Masks](#) on page 234.
- **Read** privilege: see [Field-Level Read Privilege](#) on page 243 and [Enforce Field-Level Read Privilege](#) on page 244.

- **Modify** privilege: see [Modify Privilege](#) on page 246.
- **Microsoft Project** privilege, a PPM-specific privilege: see [Project Summary Page Configuration](#) on page 237.
- **Dashboard Tab View** privilege, a PPM-specific privilege: see [Dashboard Management](#) on page 38.

Although the following discussion centers on the `AppliedTo` capability as it works with the Administrator-specific privilege masks, the information in this section is pertinent to the privilege masks based on Read, Modify, Microsoft Project, and Dashboard Tab View privileges.


Administrator Privilege and the `AppliedTo` Capability

The Administrator role is built on the "Administrator" privilege mask, which provides access to Administrator nodes in Java Client, and the "Admin Access for User Admin" privilege mask, which provides access to Administrator nodes in Web Client.

The User Administrator role includes the "Admin Access for User Admin" privilege mask and the "User Administrator" privilege mask, which defines roles that can be assigned to other users (more on this in [Options for Building Administrator Assistants](#) on page 235).

If an Agile administrator or assisting "user administrator" does not have a particular node properly selected in the `AppliedTo` property of their "Administrator" privilege mask or "Admin Access for User Admin" privilege mask, that node will *not* be a *live link* in that user's view of the Administrator nodes, so that user will not be able to access the capability.


Show Visible Attributes Only Checkbox

In the task below, you will view the **General Info** tab of a privilege mask that contains the `AppliedTo` property. When you click the down-arrow  of the `AppliedTo` property, the **Show visible attributes only** checkbox is displayed. It is checked by default: uncheck it if you want to view attributes whose Visible property is set to No; all non-visible attributes are then displayed in the Choices list.

Viewing the `AppliedTo` Property

This task can be applied to any of the privilege masks that contain the `AppliedTo` property.

To view the `AppliedTo` property of the Administrator privilege:

1. Under **User Settings** node folder, expand **Privileges** node.
2. Double-click **Administrator** privilege. The Privileges for Administrator filter dialog appears.
3. In Match If field dropdown list, select **Show All**. Click the **Apply** button.
4. Available Administrator-related privilege masks appear. Double-click **Administrator** privilege mask.
5. On the Administrator privilege mask's **General Info** tab, click the down-arrow  of `AppliedTo` property.
6. The **Choices** list displays all Administrator nodes or other Admin utilities (for example, Global Replace) that are not currently available (visible) to any user whose roles and privileges include this privilege mask. The **Selected** list displays all nodes that are visible. (The **Show visible attributes only** checkbox will be checked; it does not really affect matters in the Administrator

privileges.)

Important The **Choices** list reflects the nature of the privilege mask. "Admin nodes and utilities" are selected in Administrator-, Read-, and Modify-based privilege masks. Microsoft Project and Dashboard Tab View-based privilege masks offer a different array of choices; see [Dashboard Management](#) on page 38 and [Project Summary Page Configuration](#) on page 237.


Modifying the AppliedTo Property

To select the **AppliedTo** attributes for a qualified privilege mask:

1. Under **User Settings**, double-click **Privileges**. The Privileges window appears.
2. Double-click the qualified privilege mask you want to modify. The privilege mask window appears.

Note Filter privilege mask records to narrow your search. For example, filter records by Privilege Contains Modify to find all the Modify privilege masks on the list. (See [Filtering Data](#) on page 8.)

The privilege mask properties are displayed on the **General Information** tab.

3. On the **General Information** tab, click the down-arrow  next to the **AppliedTo** field. The selection dialog box opens.
4. Use right arrow to move selected values from the **Choices** list to the **Selected** list.
5. When you are finished, Click **OK**.
6. To finish editing the privilege mask, click **Save**.

Note The AppliedTo selection dialog box lets you select from all available fields on a tab. However, users may not be able to modify all the fields you select under all conditions.

For example, when creating the Modify Released Eng. Changes privilege mask, you can select from all fields on the **Affected Items** tab, including **Item Number**, **New Rev**, and **Type**. However, these fields cannot be modified once the routable object is released. Because you can select these attributes from the **Choices** list in the AppliedTo selection dialog box, it doesn't necessarily follow that users can modify those fields under all conditions.

Specialized Administrator Privilege Masks

It is possible to create specialized **Administrator** privilege masks. Particularly with this privilege mask, it is safer to alter the individual case, as it is assigned to one or several users, than to change the out-of-box privilege.

Caution Be extremely careful about modifying the AppliedTo properties of Administrator privilege masks that are already in use. For example, if you were to modify the AppliedTo property of the Administrator privilege mask so that it no longer included Privileges, you and other administrators would no longer have access to the **Privileges** node, and it would be very difficult to modify the Administrator privilege mask to apply to privileges again. (This kind of scenario is where **Example Roles** could be needed.)

If you need multiple administrator privileges and roles, test the new roles and privileges carefully before you modify or disable any existing administrator roles and privileges.

Note Carefully consider the impact on your company of having multiple administrative users, each with specific tasks. This allows you to divide administrative tasks among a larger group of people, restricting each user to a specific type of administrative task. Be sure to read [Options for Building Administrator Assistants](#) on page 235.

Here are specific caveats for removing nodes from the **AppliedTo** property of a user's **Administrator** privilege mask, regarding access to Admin nodes in Java Client.

- If **Criteria** is removed, there will be no Criteria link from the privilege object's **General Information** tab, the **Workflow** node, the workflow object's **General Information** tab, or the subscriber object's **General Information** tab. Also, the **New Criteria** buttons in Create Workflow and Create Privilege dialog boxes will be disabled.
- If **Role** is removed, there will be no Role link from the **Users** or **Deleted Users** nodes.
- If **Workflow** is removed, there will be no Workflow link from the Criteria Where Used table.
- If **Privilege** is removed, there will be no Privileges link from the Criteria Where Used table.

Options for Building Administrator Assistants

The User Administrator role operates with a "User Administrator" privilege and privilege mask. The User Administrator privilege mask performs a different function than "Admin Access for User Admin."

You, the main Agile PLM administrator, have decided that you want the assistance of a few select users in your administrative tasks. (How many and what kind of assisting administrators depends on the size of your company, the number of PLM solutions purchased, and so forth.) Here are your options:

- Assign and refine the Administrator role to give a user access to administrative functions in Java Client. In each user object (to whom you are assigning Administrator privilege mask), use the **AppliedTo** property to tailor which nodes that user can work in.
- Assign and refine the User Administrator role to give a user access to administrative functions in Web Client. The User Administrator performs administrative tasks via Web Client > **Tools and Settings** > **Address Book** and **Tools and Settings** > **Administration**.
 - The User Administrator role uses the privilege mask called Admin Access for User Admin, with a reduced **AppliedTo** list of nodes. In each user object (to whom you are assigning Admin Access for User Admin privilege mask), use the **AppliedTo** property to tailor which Web Client nodes that user can work in.
 - The User Administrator role also uses the new privilege mask called User Administrator. Using the same sequence of steps (in "Viewing and Modifying AppliedTo Property" above), you see that the **Choices** list is populated not with names of Admin nodes but with a complete list of PLM roles. In each user object (to whom you are assigning User Administrator privilege mask), use the **AppliedTo** property to tailor which roles that user can assign to other users.

A role that is moved over to the **Selected** list permits that user to assign that role to another user.

Save Import Preference Setting (AppliedTo Choice)

"Save Import Preference Setting" is a new Choice in the Administrator-specific AppliedTo property (found in **Administrator** and **Admin Access for User Admin** privilege masks). This setting (when moved to Selected) enables you or an assistant administrator to set default preferences in the PLM Import utility (**Web Client > Tools > Import**) that users of Import will see when they use the utility.

Of course, any user can reset preferences in Import for their own use, but these will not be saved. However, it is possible to assign the **Admin Access for User Admin** privilege mask to any user and select this one Choice in AppliedTo: this enables that user to have no other "User Administrator" capability other than saving preferences in Import.

Manage Report Template (AppliedTo Choice)

"Manage Report Templates" is a choice in the Administrator-specific AppliedTo property (that is, found in **Administrator** and **Admin Access for User Admin** privilege masks).

When it is moved to the Selected table, Manage Report Templates enables you or an assistant administrator to upload templates for reports in the PLM Report Template utility. Choose **Web Client > Tools and Settings > Administration > Report Template** to bring up the Manage Report Template page.

Users see these templates, per assigned privileges, when they use the Reports function in Web Client.

Dashboard Management

From the **Dashboard Management** node, you can configure the information display and behavior of the Agile PLM Dashboard. The Dashboard is highly configurable and can be used to present key project information to the user, according to preferences.

As an administrator, you can add an unlimited number of system-level tabs to the dashboard. The visibility of each tab can be controlled through roles and privileges.

You can configure a dashboard tab to generate and display content from any Agile object. Custom dashboard extensions (DXs) can be used to retrieve and present data from external systems (for example, ERP inventory numbers) into the dashboard. Tables within a dashboard tab can be configured to display data retrieved through advanced search queries or process extensions in various graphical formats. You can even configure a dashboard table to display an internal or external Web site.

Within Dashboard Management, you can:

- View and edit all dashboard tabs
- Add or delete optional dashboard tabs
- Add tables to optional dashboard tabs
- Configure multiple sources of data for the tables, such as:
 - Advanced search queries
 - Dashboard extensions (chart and table)
 - Custom content through URL process extensions (PXs)
- Configure the display of dashboard tabs

Project Summary Page Configuration

The Administrator privilege mask with Project Summary Page Configuration specified as the Applied to property is used to configure the widgets for the Summary page of a project. Widget and page configuration for the Project Summary page can be done using the **Tools and Settings > Administration** menu in Agile Web Client.

Creating New Privilege Masks

As with roles, it is easy to create new privilege masks, although you should use extreme caution whenever you change user access and permissions. Before creating a new privilege mask, you should review the privilege masks you currently have. Generate the Privilege Mask Detail report from the **Administrator Reports** node for a listing of current privilege masks and their criteria (see [Administrator Reports](#) on page 20).

We recommend that you modify (or copy and modify) an existing privilege mask that is similar to the one you need instead of creating a new one. The existing privilege masks have been tested extensively; their operation and interaction in Agile PLM are documented.

Before You Begin

Consider the following details before creating a new privilege mask.

- Does the privilege mask you want already exist? If so, you can assign it to the role without creating a new privilege mask. If the appropriate reusable criteria exists, check its **Where Used** tab for the privilege mask you want.
- What action do you want the privilege mask to enable in Agile PLM?
- What action do you want the privilege mask to prevent in Agile PLM?
- Upon what object type will the privilege mask act?
- What will you name the new privilege mask? Remember to use the *Action–Criteria–Object Type* naming convention.
- Which role will require the new privilege mask?
- If you are creating a basic Read or Modify privilege mask, do you also need to create a corresponding Discover privilege mask? Does a corresponding Discover privilege mask already exist? (A Discover privilege mask is **not** automatically created when you create a new Read or Modify privilege mask.)
- If it is not a Read privilege mask, does its effectiveness depend on a Read privilege?
- Under what specific conditions do you want to enable this privilege mask? Is there an existing reusable criteria that you can select when you create the privilege mask? If so, check the reusable criteria's **Where Used** tab to see if the privilege mask you want already exists.
- Will the privilege mask conflict with any existing masks in the role?
- Does the role have an existing privilege mask you can modify to achieve the results you want?
- Is there an existing privilege mask, either in this role or another role, that you can copy (using

Save As) and modify to avoid having to create one from scratch?

You can create a new privilege mask by using the Save As process as in the following procedure. You can also create a new privilege mask from scratch.

Copying a Privilege Mask Using Save As

Use the **Save As** button in the privilege mask window to make a copy of an existing privilege mask. You can change the copy to suit your needs.

To copy a privilege mask:

1. Under **User Settings**, double-click **Privileges**. The Privileges window appears.
2. Double-click the privilege mask you want to copy. The privilege mask window appears.

Note Filter privilege mask records to narrow your search. For example, filter records by Privilege Contains Modify to find all the Modify privilege masks on the list. (See [Filtering Data](#) on page 8.)

3. Click the **Save As** button.
4. Enter a name and API name for the new privilege mask.
5. Click **Save** when you are finished. The new privilege mask appears.

Creating a New Privilege Mask from Scratch

To create a new privilege mask:

1. Under **User Settings**, double-click **Privileges**. The Privileges window appears.
2. Click **New** on the toolbar. The Create Privilege dialog box appears.
3. Enter a name and an API name. Remember to use the Action–Criteria–Object Type naming convention. (See [Naming Privilege Masks](#) on page 227.)
4. Enter a description.
5. By default, the privilege mask is enabled. If you want, select No in the **Enabled** field to disable the privilege mask. You may want to do this while developing the privilege mask.
6. Select a privilege from the **Privilege** dropdown list.


Depending on which privilege you select, more fields may appear for you to complete.

Note If you selected the Change Status privilege, see [Change Status](#) on page 221 for detailed information about completing a Change Status privilege mask.

7. Do one of the following:
 - To finish creating a privilege mask that does not require a privilege criteria (reusable criteria), click **Finish**.
8. For all other privileges, in the **Privilege Criteria** field, select a reusable criteria from the dropdown list. The reusable criteria defines both the object type and the filtering conditions (criteria) for the privilege mask.

Or click the **New** button in the dialog box to define a new reusable criteria. See [Creating a New Criteria](#) on page 121.

(See [Privilege Mask Component 2: Object Type](#) on page 229 for more information about selecting an object type for your privilege mask. See [Criteria](#) on page 119 for more information about reusable criteria.)

9. If you are creating a Read or Modify or Administrator privilege mask, you can select the object fields for which the Read or Modify privilege is applied. (See [Privilege Mask Component 4: Attributes](#) on page 230.)
 - Click  at the **AppliedTo** field. The selection dialog box opens.
 - Use the right and left arrows to move selected values from one list to the other.
 - When you are finished, Click **OK**.
10. If you are creating a Change Status or Override privilege, see [Change Status](#) on page 221.
11. When you have completed the fields on the Create Privilege dialog box, Click **OK**.


Note If you disabled the privilege mask while you were creating it, remember to enable it so it can be used.

Combining Options in Criteria and AppliedTo Attributes



When you create or modify a privilege mask, the AppliedTo and Criteria dialog boxes let you make selections from all possible combinations of attributes, but not all criteria or attributes make sense for all privilege masks. Evaluate the options you combine to make sure they function as expected.

For example, when modifying the Modify Released Eng Changes privilege mask, you can select the Affected Items.Item Number and Affected Items.New Rev fields from the list in the AppliedTo dialog box. However, these two fields cannot be modified once the routable object has been released. Because you *can* specify these attributes in the AppliedTo dialog box, it doesn't necessarily follow that you *can* modify those fields on a released routable object.

The following are examples of privilege masks and their properties that are provided with your Agile PLM installation.



The Change Status privilege does not include AppliedTo properties, like the one in the figure above. However, the Change Status privilege includes properties for Workflow, From Status, and To Status, as seen in the figure below.



Discovery and Read Privileges

This section looks closely at Discovery and Read privileges.

The Read and Modify privilege masks are made specific by, among other properties, the `AppliedTo` property naming individual attributes that can be accessed. (To contrast, the Administrator privilege mask is made specific by the `AppliedTo` property naming individual nodes that can be accessed.)

Note A section in the previous chapter, [Advanced Search Security](#) on page 199, describes enhancements to "search security" that apply to Discovery, Read, and Field-level Read privileges (not repeated in this section).

Discovery Privilege

As outsourcing and "virtual companies" become more common, Agile PLM customers are allowing employees of other companies in their supply chain to access their Agile PLM database. For security reasons, it is important that these outside users see only information that applies directly to them. For example, you might not want one supplier to know that another supplier is providing the same part, or that you are providing the same part to a company and its close competitor.

The Agile PLM Discovery features—Discovery Privilege database property, Discovery privilege, and Discover privilege mask—are designed to address these security issues. These features control whether users are allowed to learn that certain objects exist in Agile PLM.

You control object discovery in two ways:

- At a global level, by setting the Discovery Privilege database property (in **Server Settings > Database**) to Enabled or Disabled.
- At the level of roles, with Discover privilege masks.

For example, if employees of one supply chain partner have the Discovery privilege only for parts provided by that partner, they can be blocked from seeing parts provided by other partners in search results tables or even on BOMs (see [Related SmartRules](#) on page 242).

Note If you grant users Read or Create privileges, you must also grant users a corresponding Discovery privilege for objects that they are allowed to read. Users should always be able to discover and read objects that they created.

For example, if you create a role that has a Read privilege mask applying to All Change Orders criteria, you must also include in that role a Discovery privilege mask applying to All Change Orders criteria.

For information about using the Discovery Privilege database property for global discovery control, see [Database](#) on page 365.

For more information about the Discover privilege masks assigned to each role supplied with Agile PLM, see [Viewing a Role](#) on page 191.

Note If a change originator or CCB member has the Discovery privilege removed after an ECO has been routed, the originator or CCB member still receives notifications but cannot view the change. For best results, avoid removing Discovery privileges after their initial assignment.

Discovery Privilege and Sites

Site objects are explicitly filtered out of Discovery privilege criteria. Therefore, you cannot define a new Discovery privilege mask to control a user's ability to access Sites.

To control a user's access to Sites, set user properties appropriately. Open a user in Java Client or Web Client, and specify the **Sites** and **Default Site** properties.

Discovery Privilege and Life Cycle Phases

If you create Discovery privilege criteria based on RFQ Response lifecycle phases, you must restart the Agile Application Server to run a search that uses the criteria. Otherwise, the search won't return any results.

Related SmartRules

The following SmartRules define how Agile PLM responds when users encounter objects that their privileges don't allow them to discover:

- Display BOM Tables
- Discovery Object Tables
- DiscoveryResultsTable

For more information about these SmartRules and their default settings, see [SmartRules Defined](#) on page 258.

Discovery Privilege and Reports

Agile users do not see and cannot run the Administrator reports. The following information is about the availability of specific objects in the standard reports that users can run.

A user who does not have Discovery privilege for an object cannot include that object in a report. Parts for which a user does not have Discovery privilege are displayed in the same way they are displayed on BOMs.

If you, the administrator, have decided to display a warning message, that warning message will appear in the reports. You also have the option of displaying either the item number only or the item description only, so the user can see all the items in the report, but does not have access to the undiscovered items.

To run a report on a particular type of object, a user must be granted the following privileges:

- Read privilege
- Discovery privilege

- Run Reports privilege

Note The Manage Reports privilege alone is not sufficient to execute the report.

Relationships among Discovery and Read Privileges

Agile PLM administrators can use the Discovery and Read privileges to grant users several levels of access to Agile PLM data, as shown in the following table.

Access level	Discovery privilege	Read privilege
Full access	Granted	Granted for all tabs
Limited access	Granted	Not granted for History or Workflow tabs
Discovery only	Granted	Not granted
No discovery	Not granted	Not granted

Privilege masks made up of the Discovery and Read privileges build on each other, as shown in the following table.

Privilege mask type	Effects and comments
Discover	<ul style="list-style-type: none"> ▫ Can see that the discoverable object exists
Read	<ul style="list-style-type: none"> ▫ Must be able to discover the object ▫ Can open the object ▫ Can read all tabs as defined in the privilege mask's AppliedTo dialog box (see below)

Note If you remove or modify a Read privilege mask, the Discovery privilege mask is not automatically removed or modified at the same time.


Field-Level Read Privilege

“Field-level Read” describes an Agile PLM client user’s ability or inability to read various fields within tabs through the Read privilege mask. Any field in any tab can be hidden from any user. A good use of Field-level Read is a customer hiding a “cost” field on the **Page Two** tab from certain suppliers.

To see a field of an object:

- A user must have a Read privilege to the object.
- The field must appear in the **AppliedTo** property for that user’s Read privilege mask.

For example, in the **Privileges** window, double-click any Read privilege mask to display it. The **AppliedTo** field on the **General Information** tab lists all the fields to which the Read privilege is applied.

When you create a Read privilege mask, there are no values listed in the **AppliedTo** property. During the creation process, at the **AppliedTo** field, you click  to display the selection dialog box. All the fields of the object are in the **Choices** list. You refine the privilege mask by moving fields from the **Choices** list on the left to the **Selected** list on the right.

If you wished to prevent the user from seeing the **Workflow** tab for the object specified by the criteria, all the **Workflow** tab fields would remain in the **Choices** list. Only the fields in the **Selected** list will be visible to the user. This is an example of Field-level Read.

The Field-level Read capability may be affected by whether the user has the Enforce Field-level Read privilege, which is discussed in “Enforce Field-Level Read Privilege” below.


Modifying the AppliedTo Fields of Read Privilege Masks

This task is specific to Read privilege masks. The **AppliedTo** capability is used by a few other privileges – for more information, see [AppliedTo Capability](#) on page 232.

To modify the list of fields to which a Read privilege mask is applied:

1. Under **User Settings**, double-click **Privileges**. The Privileges window appears.

Note	Filter privilege mask records to narrow your search. For example, filter records by Privilege Contains Read to find all the Read privilege masks on the list. (See Filtering Data on page 8.)
-------------	---

2. Double-click the privilege mask you want to modify. The privilege mask window appears. The privilege mask properties are displayed on the **General Info** tab.
3. On the **General Info** tab, click  next to the **AppliedTo** field. The selection dialog box opens.
4. Use the right and left arrows to move selected values from one list to the other list.
5. When you are finished, Click **OK**.
6. To finish editing the privilege mask, click **Save**.

Enforce Field-Level Read Privilege

The Enforce Field-level Read privilege is a way the Agile PLM administrator can control certain small performance consequences when a user is under the restrictions of a Field-level Read (see [Field-Level Read Privilege](#) on page 243). The Enforce Field-level Read role comprises only the Enforce Field-level Read privilege mask.

If a user has a role with Enforce Field-level Read privilege included, the software checks everything at the

“field level,” that is, the fields within tabs in Agile PLM clients. Users with this privilege may notice their computers’ performance on some operations is slightly slower; this is because the software is checking all possible fields. This impact depends on how many items are in the tables being searched (for instance, BOMs, affected items, results).

If the user does not have a role with this privilege included, the system does not check everything at the field level, and so computer performance is not affected. In this case, even if the user has the Read privilege defined at the field level, the system does not check everything at the field level; that

is done only when the Enforce Field-level Read privilege is present and enabled.

Important Previous versions of Agile PLM used the Specify Output Column privilege to permit users to select output attributes in setting up advanced searches. That privilege is removed; therefore, all users can potentially specify output attributes in advanced searches. However, you may want to assign the Enforce Field Level Read privilege to any user who did *not* have Specify Output Column privilege previously. This ensures that search results will be appropriately filtered—for example, for sensitive fields such as costs.

For a user with two roles, one with Enforce Field-level Read privilege and one without, the default is to “enforce” the Field-level Read. Similarly, for a user with a single role that has two Enforce Field-level Read privileges, one disabled and one enabled, the default is to “enforce” the Field-level Read. In both these cases, users can see only the fields for which they have the Read privilege. For this reason, Agile recommends that only users who are prevented from seeing certain fields have this privilege enabled.

System behavior with Enforce Field-level Read set to Yes interacts with certain privileges and SmartRule as follows:

- **Discovery privilege** — Dictates if the object is listed on Results and other tables.
- **User does not have the Read privilege for the object** — The user sees “no privilege” in the object’s fields on the Results and most other tables. The display of these objects on the BOM table is governed by the Display BOM Tables SmartRule. The user cannot open these objects.
- **User has Read privilege for the Object Number and Description fields** — The user sees object number and description on Results and other tables. The user can open these objects.
- **User has Read privilege for all fields** — The user sees all fields on all tables. The user can open these objects.

Display on Tables Due to Enforce Field-level Read

Up to Agile’s Product Collaboration Release 7, if a user had a role that included the Enforce Field-level Read privilege, the display of objects that the user could not read but could discover (in the Results, Where Used, Affected Items, and Manufacturers tables) has “no privilege” in all the corresponding fields, and the user could open the objects to view them. Display of fields on the BOM table was governed by the Display BOM Tables SmartRule.

If you wish a user to “mimic” the 6.x behavior on the tables, you need to add the Read privilege to the user’s roles for a subset of fields. The Read privilege could include the object number and description as AppliedTo attributes, and only these fields will be displayed on the returned tables.

For example, for a certain type of object, you might define Attachment Type values such as Internal Only and External, and then give users outside the company privileges only for files marked as External. If an Agile PLM client user adds an attachment to that type of object and defines it as Internal Only, outside suppliers and contractors won’t be able to access the file.

To use the Attachment Type attribute in privilege mask criteria, the object type that you specify cannot be a base class (Items, Changes, Reports, and so forth).

Note If you decide to enable the Attachment Type attribute to control access to attachments, be sure to tell the users how to use the field. This field can be edited in Agile PLM clients.

Modify Privilege

The crucial Modify privilege is covered generally in “Some ‘Modify’ Basics and Rules” below and in an important specific context in [Controlling the Ability to Modify Items at Introductory Revision with \\$CURRENTREV](#) on page 247. Again, the Read and Modify privilege masks are made specific by, among other properties, the AppliedTo property naming individual attributes that can be accessed.

Some ‘Modify’ Basics and Rules

The Modify privilege allows a user to modify or edit fields on the tab of an object. Modify privileges are assigned using the AppliedTo attribute settings.

Note The Create privilege allows the user to fill in required fields at the time of object creation even if the user does not have Modify privilege for those fields. (Required fields are fields with their attribute property **Required** set to Yes; see [Defining Attribute Properties](#) on page 79.)

- The Modify privilege is required for users of the Agile PLM Import utility.
- Modify privilege and Relationships: To create a relationship between two objects without setting up a rule (detailed in *Getting Started with Agile PLM*), you must have the appropriate Modify privilege for both objects tailored to Relationships. To create a rule between two related objects, you must, in addition, have the appropriate Modify privilege for both objects tailored to Rules. For example, for items, a user must have a Modify Items privilege mask that includes, in its AppliedTo property, the **Relationship** tab "Name" attribute and the **Relationship** tab "Rule" attribute.
- Users with the Modify Manufacturer Parts privilege mask can modify Manufacturer Parts attributes that also appear on the **Manufacturers** tab without an MCO or ECO being issued.

Note A user must be assigned the Modify privilege for both **Manufacturer.Mfr Name** and **Manufacturer.Mfr Part Number** fields to properly modify Manufacturer (AML) information.

- Item, New Rev, and Type (Lifecycle) fields on the **Affected Items** tab of changes cannot be modified at Released or Implemented statuses.
 - For other changes, the item number fields on the **Affected Items** tab cannot be modified at Released, Closed, Expired, or Resumed statuses.
- To be able to modify a **Page Three** tab, users must have a Modify privilege mask for the specific subclass and attributes.

Important Although Agile PLM can be configured to allow modification of the lifecycle phase of previously released revisions by modifying released ECOs, such a practice is highly discouraged because of the following reasons:

- a) Potential regulatory compliance violations
- b) Potential data integrity issues in the system

It is strongly recommended that user privileges be configured not to allow modification of lifecycle of released revisions by directly modifying released ECOs.

Agile PLM does not allow you to modify the item Rev and item Description on the **Affected Items** table of a released ECO, even if you have Modify ECO privileges that would, in theory, allow that.

The Modify privilege is also utilized with regard to attachments; this capability is documented in [Modify Privilege and Attachments](#) on page 402.

Controlling the Ability to Modify Items at Introductory Revision with \$CURRENTREV

Modify privilege masks for item objects that use \$CURRENTREV in their criteria can be used to control a user's ability to modify (or inability to modify) items that are either released, preliminary, or introductory. To further define a user's modify ability, you can use multiple \$CURRENTREV conditions to identify an Introductory revision, the latest revision, and the workflow statuses of the change order associated with the selected item revision..

Applicable Item Attributes

On item objects, the user can use the **Rev** drop-down list to display information for a specific revision. The user's assigned Modify privilege masks determine whether he can modify those attributes.

- **Revision** drop-down list is available for the item **Sites** tab in both Web Client and Java Client.
- **Revision** drop-down list is available for the item **Page Two** and **Page Three** tabs in Java Client
- Because the item **Page Two** and **Page Three** data in Web Client is displayed on the **Title Block** tab, the **Revision** drop-down list on Web Client Title Block tab also controls display of Page Two and Page Three data.

\$CURRENTREV Criteria Logic

Agile has a special variable that can be used in Criteria against items, \$CURRENTREV, that allows administrators to build in privilege control based on the displayed revision. With a criteria written using \$CURRENTREV, Agile evaluates the currently selected revision in Web Client or Java Client to evaluate the match. That is, when a user has selected a revision in the **Revision** drop-down list, the \$CURRENTREV criteria is evaluated against that displayed revision.

This functionality is discussed in [Controlling the Ability to Modify Items at Introductory Revision with \\$CURRENTREV](#) on page 247.

Using \$CURRENTREV in an item criteria allows the administrator to build in privilege control based

on the displayed revision. Using combinations of multiple \$CURRENTREV criteria conditions allows the administrator to narrowly define which items a user is allowed to modify.

A \$CURRENTREV criteria condition can be set to be **Equal To** or **Not Equal To** the following values:

- \$LATEST (the latest released revision of the item)
- Status type variables, for example, \$STATUSTYPE.RELEASED.
- Workflow statuses pertaining to specific workflows, for example, Default Change Orders.Pending.
- Special values for evaluating Introductory revisions:
 - \$INTRODUCTORY_NOCHANGE
 - \$INTRODUCTORY_PENDINGCHANGE
 - \$INTRODUCTORY_RELEASEDCHANGE

For detailed information about \$CURRENTREV criteria values, see [Using \\$CURRENTREV and \\$LATESTREV](#) on page 125.

Definition of a Released Revision

A Released Revision occurs when the change object (Change Order or Manufacturer Order) that created the Revision is in its workflow at a status type of Released or Implemented. This is indicated in both clients when the Revision is not in parentheses.

Definition of a Pending Revision

A Pending Revision occurs when the change object that created the Revision is in its workflow at a status type of Unassigned, Pending, Submit, Review, or Hold. This is indicated in both clients when the Revision is in parentheses.

Note	A change object in Canceled status is not applicable because it will not appear in the Revision dropdown listing.
-------------	---

Building Criteria for Specific Use Cases

Typically, there are three cases where the Agile administrator needs to control Modify privileges. These can be extended with additional criteria as are needed.

1. Allow broad Modify at Introductory only
2. Allow targeted Modify for a Pending revision
3. Allow targeted Modify for a Released revision

1. Allow broad Modify at Introductory only

Items (\$CURRENTREV Equal To \$INTRODUCTORY_NOCHANGE OR
\$CURRENTREV Equal To \$INTRODUCTORY_PENDINGCHANGE OR
\$CURRENTREV Equal to \$UNASSIGNED)

This combination of statements will allow a user to modify the Introductory revision of an item if the item has never been released. The item may have no changes or it may have a pending change. If the item has a pending change, the user must select the Introductory revision in the Rev dropdown list.

Use of a criteria with this combination of statements in a Modify Item privilege mask with many AppliedTo fields will allow broad Modify privilege at Introductory while there is no Released revision, and then prevent broad Modify privilege after the first Released revision when there is a Pending revision.

2. Allow targeted Modify for a Pending revision

Items (\$CURRENTREV Equal To \$UNASSIGNED OR
 \$CURRENTREV Equal To \$STATUSTYPE.PENDING OR
 \$CURRENTREV Equal To \$STATUSTYPE.SUBMIT OR
 \$CURRENTREV Equal To \$STATUSTYPE.REVIEW OR
 \$CURRENTREV Equal To \$STATUSTYPE.HOLD)

Writing a criteria with these statements will generally satisfy this requirement. Use this criteria in a Modify Item privilege mask with a small number of AppliedTo fields. When the user selects a pending revision from the Rev dropdown list, he will be able to modify the specified fields of the selected pending item revision.

3. Allow targeted Modify for a Released revision

Items (\$CURRENTREV Equal To \$STATUSTYPE.RELEASED OR
 \$CURRENTREV Equal To \$STATUSTYPE.IMPLEMENTED)

This combination of criteria statements evaluates as True when the workflow status of change that released the selected item revision has a status type of either Released or Implemented. Use this criteria in a Modify Item privilege mask with a small number of AppliedTo fields. When the user selects a Released revision in the Rev dropdown list, he will be able to modify the specified fields of the selected released item revision.

\$CURRENTREV Criteria Examples

This section shows examples of ten different criteria statements using \$CURRENTREV and \$LATESTREV and illustrates how they are evaluated for different item revisions.

The following table shows the ten criteria that are used in the examples:

Criteria #	Description
1	\$CURRENTREV Equal To \$INTRODUCTORY_NOCHANGE
2	\$CURRENTREV Equal To \$INTRODUCTORY_PENDINGCHANGE
3	\$CURRENTREV Equal To \$INTRODUCTORY_RELEASEDCHANGE
4	\$CURRENTREV Equal To \$LATEST
5	\$LATESTREV Is Introductory
6	\$LATESTREV Is Released

7	\$CURRENTREV Equal To \$UNASSIGNED or \$CURRENTREV Equal To \$STATUSTYPE.PENDING
8	\$CURRENTREV Equal To ECO.Released or \$CURRENTREV Equal To ECO.Implemented
9	\$CURRENTREV Equal To Default Change Orders.Implemented
10	\$CURRENTREV Equal To \$INTRODUCTORY_NOCHANGE or \$CURRENTREV Equal To \$INTRODUCTORY_PENDINGCHANGE or (\$LATESTREV Is Introductory and (\$CURRENTREV Equal To \$UNASSIGNED or \$CURRENTREV Equal To \$STATUSTYPE.PENDING))

The following table shows five items (EX-1 – EX-5) and the revision history for each of these items. This table illustrates how each of the criteria detailed in the above table (Criteria #1 – #10) will evaluate (T = True; Blank table cell = False) when a specific revision is selected from the Rev dropdown list of the example items.

Item Number	Revision	Change Status	Status Type	1	2	3	4	5	6	7	8	9	10
EX-1	Introductory	N/A		T			T	T					T
EX-2	Introductory	N/A			T		T	T					T
	(?)	Unassigned						T		T			T
EX-3	Introductory	N/A				T			T				
	A	ECO.Implemented	Complete				T		T		T		
EX-4	Introductory	N/A				T			T				
	A	ECO.Implemented	Complete				T		T		T		
	(?)	Unassigned							T	T			
EX-5	Introductory	N/A				T			T				
	A	ECO.Released	Released				T		T		T		
	(B)	ECO.CCB	Review						T				
	(C)	ECO.Submitted	Submit						T				
	(D)	ECO.Pending	Pending						T	T			

Applying Create User Criteria

Create User criteria statements restrict users to reading only those objects they have created. The Create User feature allows a user without a read privilege to create an object. To implement Create User criteria, you need to first make both of the following visible:

- The **Page Two** tab of that class (see [Showing, Hiding, or Renaming a Tab](#) on page 66).
- The **Create User** attribute field on the **Page Two** tab of an Agile PLM class (see [Showing or Hiding an Attribute on a Tab](#) on page 86).

Once you've done this, Agile PLM clients automatically display the creator's name in the **Create User** field of the **Page Two** tab *for that class*. Any user who has a Create privilege can now open a blank form *for that class* and create an object. In this way, users don't need to have a basic Read privilege to create objects. However, this privilege limits users to reading only pending or preliminary objects they've created.

For users who have the Create privilege, you can expand the Read privilege to include all objects they've created, regardless of the state, by creating a Read privilege mask for the subclass with a reusable criteria that specifies Page Two.Create User criteria conditions. In addition to making the **Page Two** tab visible and making visible the **Create User** field on the tab, you need to:

- Create a reusable criteria that specifies the Page Two.Create User attribute, typically Page Two.Create User Equal to \$USER.
- Create a privilege mask that specifies the reusable criteria you created.

For example, for a user who creates ECOs, create a new privilege mask as follows:

- **Name** — Read ECOs
- **Description** — Read-Only ECOs created by this user
- **Privilege** — Read
- Select or create a reusable criteria that specifies:
 - **Type:** ECO
 - **Attribute:** Page Two.Create User
 - **Match If:** Equal To \$USER

You can read the Create User attribute into the **Manufacturers** tab for both Manufacturers and Manufacturer Parts by making it visible on these tabs. Remember to first make the **Page Two** tab and its Create User attribute visible for the class.

Using Privilege Mask Criteria Variables

You can use the variables listed and described in the following table when creating a reusable criteria for use as a privilege mask criteria. In the Create Criteria dialog box, some variables appear on the **Attribute** list, and others can be entered in the **Value** field. See [Agile PLM Variables](#) on page 14 for a complete list of Agile PLM variables.

Variable	Description
\$CHECKOUTUSER	The user who checked out the object's attachment.
\$LATEST	The latest revision of an object; more specifically, the latest released revision for a released item, or the latest pending revision for an unreleased item (with Pending changes); \$LATEST applies only to the Read and Modify privilege.

Variable	Description
\$CREATEUSER	The user who created the object. To specify the Create User as an attribute (for example, Create User equal to \$USER), select Page two.Create User in the Attribute field when you are defining a reusable criteria. See also Applying Create User Criteria on page 250.
\$PARTNER	The current supply chain partner company.
\$CURRENTREV	The current revision of an object you have selected from the rev list, or the revision of an object you are currently viewing.

Other User Settings

This chapter includes the following:

- User Monitor 253
- Deleting and Undeleting Users 254

User Monitor

The User Monitor window lists the users that are presently logged in to the Agile PLM system. It displays the following information about each logged-in user.

Table column	Description
User Name	The first and last name of the logged in user.
User ID	The login username of the user.
Host	Indicates the user's host.
Login Time	The time the user logged in.

Refreshing the User Monitor Window

The User Monitor window is not dynamic; it shows the user session information at the moment that the window was displayed. To see the most current information, click **Refresh** to update the information displayed in the window.

Terminating a User Session

You can use the User Monitor window to terminate a user session.

To terminate a user session in Java Client:

1. Under **User Settings**, double-click **User Monitor**.
2. Select one or more users whose sessions you want to terminate.
3. Click the **Terminate Session** button.

The users sessions are not terminated immediately. It may take up to a minute to terminate active user sessions. When you click the **Terminate Session** button, users can continue working for one minute. When the session is terminated, the login window is displayed in the user's browser.

Deleting and Undeleting Users

You cannot either “hard delete” or “soft delete” a user that is associated with any other object. A newly created user who is not associated can be deleted from the **Users** node. You will then find the user object on the **Deleted Users** node.

This process can be reversed: on the **Deleted Users** node, select a deleted user and click the **Undelete** button. The user object is restored to the **Users** node; you will, however, have to close and re-open the **Users** node to see this user, this cannot be accomplished with the **Refresh** button.

If someone leaves the company, or will no longer be using Agile PLM, or you need to prevent a user from logging in to the Agile PLM system, disable the user object by setting the Status property to Inactive. The user remains on the **Users** node, and the name still appears on existing workflows, escalations, and so forth, but the user will no longer appear in the Address Book for other users to select. You can re-set the user to Active status at any time.

For users you have made Inactive, you can use Global Replace to locate and replace him in all the places in the system that his name is used (see [Global Replace](#) on page 22).

Deleting a User Group

You can delete a user group that is no longer needed. If you delete a user group to which users have been assigned, you can do so without removing the users who were in the user group: when you delete the user group, user assignments to that user group are also deleted.

When you delete a user group, it is removed from the Agile PLM address book. You cannot delete a user group if it is in use in these cases:

- It is on any routable object signoff list in Agile PLM clients.
- It is listed in any workflow “Notify” properties (in the Workflows window).
- It is used as a designated escalation person for any users, user groups, and partners.

Note When you remove a user from a user group, use the Global Replace tool to determine all the places in the system that user is used (see [Global Replace](#) on page 22).

To temporarily delete a user group in Java Client:

1. Under **User Settings**, double-click **User Groups**. The User Groups window appears.
2. Select a user group name in the list.
3. Click the **Delete** button. You are prompted to confirm the deletion.
4. Click **Yes**. The user group no longer appears on the User Groups window.

To temporarily delete a user group in Web Client:

1. Click **Tools and Settings > Address Book > User Groups**. The User Groups page appears.
2. Click a user group name in the list. That user group page appears.
3. From the **Actions** menu, choose **Delete**. You are prompted to confirm the deletion.

4. Click **Yes**. The user group no longer appears on the User Groups page.

Hard-Deleting a User Group

When you delete a user group, it is moved to the **Deleted User Groups** node. Although it does not appear in the address book, it still exists in the database. This is referred to as a “soft-deleted” user group. To permanently remove a user group, you can delete it from the **Deleted User Groups** node. This is referred to as a “hard-deleted” user group.

Note A hard-deleted user group is permanently removed from the database and cannot be restored or undeleted.

To hard-delete a deleted user group in Java Client:

1. Under **User Settings**, double-click **Deleted User Groups**. The Deleted User Groups window appears.
2. Click to select the user group you want to hard-delete, and click the **Delete** button.

The user group no longer appears in the Deleted User Groups window.

To hard-delete a deleted user group in Web Client:

1. Click

Undeleting a User Group

From the **Deleted User Groups** node, you can view user groups that have been deleted from the Agile PLM system. It is useful to know which user groups have been deleted because the user group may have been assigned as an approver for routable objects. This allows you to maintain a complete “audit trail” of a product’s entire history.

A user group may be “undeleted.” By undeleting a deleted user group, you restore it to active use, and it appears in the address book again.

To undelete a user group in Java Client:

1. Under **User Settings**, double-click **Deleted User Groups**. The Deleted User Groups window appears.
2. Click to select the user group you want to undelete.
3. Click the **Undelete** button.
4. The user group’s name is added to the User Groups window. You might have to click the **Refresh** button to see the group listed in the window.

To undelete a user group in Web Client:

1. Click

SmartRules

This chapter includes the following:

▪ Modifying SmartRules Settings.....	257
▪ SmartRules Defined.....	258

The Agile PLM SmartRules are documented in SmartRules.

Modifying SmartRules Settings

To modify a SmartRules setting:

1. Under **System Settings**, double-click **SmartRules**. The SmartRules window appears.
2. At the rule you want to change, select a setting from the drop-down list. The list of possible settings can include the following values:
 - **Allow** — The system allows the process to occur.
 - **Disallow** — The system prevents the process from occurring.
 - **Warning** — The system warns the user that the process is occurring.
 - **Remove** — Removes all approvals/rejections on the **Workflow** tab when the routable object returns to the status where first rejected.
 - **Retain** — Keeps all approvals/rejections on the **Workflow** tab when the routable object returns to the status where first rejected.
 - **Display** — Displays the object in the table.
 - **Display with Just Description** — Displays the object with its subclass and description. The part number and other values read from the object are not displayed.
 - **Display with Just Part Num and Rev** — Displays the object with its subclass, part number, and revision. The description and other values read from the object are not displayed.
 - **No Display** — Does not display the object in the table. No warning is given.
 - **No Display with Warning** — Does not display the object in the table. Issues the following on the tab: "There are x objects not displayed due to insufficient user privilege."
3. When you have finished, click **Save**.
4. If you wish to revert to the original settings or start over, click **Close**. You will be prompted whether you want to close the window without saving; click **Yes** if you do or **No** if you do not.

SmartRules Defined

Allow Deletion of Attachments

Settings: Yes, No (default)

When set to Yes, upon removing an attached file from a business object Attachments tab, if the file folder is not in use by any other business object (that is, no versions of the file folder are referenced by a business object), the file folder is automatically soft-deleted.

A user with the appropriate search capabilities can run the File Folder Recycle Bin Search and hard-delete (or undelete) the soft-deleted file folder.

Auto-Installs from PPM

Settings: Allow (default), Disallow, Warning

Allows or disallows automatic installation of Microsoft Project (2002 and 2003) DLLs into a user's system registry. Installation of these DLLs enables seamless publishing using an Agile menu within Microsoft Project. It should be set to Disallow if your company does not want any applications to be automatically installed, or if you prefer to set up an Agile–MS Project connection systemwide.

Auto Publish Quote History

Settings: Allow (default), Disallow, Warning

Allows or disallows RFQ or response-line data to be published to objects in the Quote History subclass.

BOM Multi-Level Recursion

Settings: Allow (default for non-Oracle DB systems, and for upgrading customers), Disallow (default for Oracle DB systems)

For systems based on Oracle DB, this SmartRule validates whether a BOM recursion can occur, that is, when a subassembly includes one of its parent items from an upper level of the BOM tree structure on its own BOM. (A recursive BOM structure, if carried to its logical conclusion, would repeat indefinitely).

The validation happens when a change order (ECO, SCO, and MCO) advances to Released, or when Release Audit is performed, or when the change tries to advance when current status needs to Pass Release Audit (assuming SR setting is Disallow).

Note	Because non-Oracle DB systems do not allow or check for recursion, this SmartRule has no effect; these systems should see the default setting is Allow.
-------------	---

Important The PG&C and PCM solutions do not support BOM recursion. For companies using either of these solutions, set this SR to Disallow.

Change Status Approver Rejected Change

Settings: Allow, Disallow, Warning (default)

Determines whether to allow movement of the routable object to the next status or warn the user that an approver has rejected the change. It affects all Review or Released status types.

If you require the ability to determine if a routable object should be allowed to proceed when it does not meet the SmartRule, set it to Disallow. A user with Override privilege can advance the routable object in the workflow. Please see the Caution about this property in Override.

Note To make sure that a routable object is not autopromoted through the workflow after a user has rejected it, set this SmartRule to “Disallow.” Setting it to “Warning” will, in some cases, allow the routable object to be autopromoted through the workflow even when that is not the intended behavior.

Change Status No Response Change

Settings: Allow, Disallow, Warning (default)

Determines whether to allow movement of the routable object to the next status when an approver has not responded with either an approval or a rejection. It affects all Review or Released status types and applies only to changes that are being manually moved to the next level. Autopromotion requires that each approver either approve or reject the routable object.

Change Status Observer Rejected Change

Settings: Allow, Disallow, Warning (default)

Determines whether to allow movement of the routable object to the next status or warn the user that an observer has rejected it. It affects all Review or Released status types.

If you require the ability to determine if a routable object should be allowed to proceed when it does not meet the SmartRule, set it to Disallow. A user with Override privilege can promote the routable object. Please see the Caution about this property in [Override](#) on page 223.

Check In Attachment With Different File Extension

Settings: Allow, Disallow (default), Warning

Determines whether an attachment file that is being checked in can have a different file extension than the file that was checked out.

Note This rule is overridden when an item’s attachment is Latest-x and the file extension in the attached file folder is changed and is therefore different than the extension of the item’s checked-out file.

Copy Files to Rev

Settings: Copy, Copy with Warning, Disallow, Reference (default), Reference with Warning

Controls automatic copying of files to a new revision. The system checks this SmartRule only when a pending change is created and not when attachments are added. The settings work as follows:

Copy – For the item's new pending revision, Agile creates a new file folder and creates a new copy of the attachment file, which is placed in the new file folder.

Reference – Agile uses the existing file folder and creates a new reference to it on the item's new pending revision Attachments tab.

Disallow – The new item pending revision is created with no attachments.

Copy with Warning – The same as the Copy setting, with the option of choosing no attachments for the new pending revision.

When you add items to the pending ECO, you are presented with a warning dialog that includes a row for each item you are adding.

To add the item and to copy the attachments, check both the Add checkbox and the Attachments checkbox.

To add the item with no attachments, check only the Add checkbox.

Reference with Warning – The same as the Reference setting, with the option of choosing no attachments for the new pending revision.

When you add items to the pending ECO, you are presented with a warning dialog that includes a row for each item you are adding.

To add the item and to reference the existing attachments, check both the Add checkbox and the Attachments checkbox.

To add the item with no attachments, check only the Add checkbox.

Note	If you set this rule to Disallow, files that were added to the Introductory revision after the object was associated with a change (that will result in released Rev A) will not be copied to subsequent revisions. Also, when a new Change is created, all the files that were added to the Introductory revision won't be added to the newly created revision.
-------------	--

Demotion Approvers Removal

Settings: Retain (default), Remove

Defines whether ad hoc (not the default) approvers and observers will be removed from the list when the routable object is rejected and returned (that is, demoted) to a previous status. It affects all Review and Released status types in all workflows.

Retain: When a workflow is returned to a previous status (including Pending), the ad hoc approvers are retained and they will see the change when it advances through the workflow again.

Remove: When a workflow is returned to a previous status (including Pending), the ad hoc approvers are removed – they will not see the change again unless the originator or change analyst adds them back.

Demotion Signoff Removal

Settings: Retain (default), Remove

Defines whether approvals/rejections already recorded will be removed from the routable object's Workflow tab when it is rejected and returned (that is, demoted) to a previous status. It affects all Review and Released status types in all workflows.

Retain: When a workflow is returned to a previous status (including Pending), the signoffs that are already recorded are retained.

Remove: When a workflow is returned to a previous status (including Pending), the signoffs are removed and approvers will have to sign off again when the change advances through the workflow.

Detailed TimeSheet Entry

Settings: Disallow (default), Allow

Controls the display of the Timesheet tab in Product Portfolio Management.

Disallow: The Timesheet tab and all associated actions are disabled.

Allow: The Timesheet tab is displayed next to the My Assignments tab for users to enter Actual Hours against a task or activity. When the Timesheet is enabled, data entry for Actual Hours on the Team tab is disabled.

Discovery Object Tables

Settings: Warning (default), No Display

Controls the display of information about an object on the Change History, Where Used, Affected Items, Manufacturers, BOM, or Pending Changes tables when the user doesn't have the Discovery privilege for the object. Possible settings are Warning (the default) and No Display.

If the Discovery Privilege property in the Database node is disabled, then so is this SmartRule.

Note When this setting is changed, users must exit the Agile Java Client and log in again before the change takes effect.

Discovery Results Table

Settings: Warning (default), No Display

Controls the display of information about the Results table when the user does not have the Discovery privilege for an object in the table.

If the Discovery Privilege property in the Database node is disabled, so is this SmartRule.

Note When this setting is changed, users must exit Java Client and log in again before the change takes effect.

Display BOM Tables

Settings: No Display with Warning (default), Display, Display with Just Description, Display with Just Part Num and Rev, No Display

Controls the display of information about an item in the BOM table when the user does not have the Discovery privilege for the item.

Note When this setting is changed, users must exit Java Client and log in again before the change takes effect.

Display Structure Tables

Settings: Display (default), No Display

Controls the display of model structures that are created by objects of the Designs class.

Duplicate Find Numbers

Settings: Allow, Disallow, Warning (default)

Controls the use of duplicate find numbers when users add items to a BOM.

This SmartRule has been expanded to dictate whether or not the same find number can be used in a site-specific portion of a BOM as is used in the global portion of a BOM. It also dictates whether or not the same find number can be used within a site-specific portion of the BOM.

For example: If the Duplicate Find Numbers SmartRule is set to Disallow, then:

Find Number 1 cannot be used for Part 123 on the Milpitas BOM if Find Number 1 is used for Part 234 on the Global BOM.

Find Number 1 cannot be used for Part 123 on the Milpitas BOM if Find Number 1 is also used for Part 234 on the Milpitas BOM.

The same find number can be used in more than one site-specific portion of the BOM regardless of the Duplicate Find Numbers SmartRule setting.

For example: Find Number 1 could be used for Part 123 on the Singapore section of the BOM and Find Number 1 could be used for Part 234 on the Milpitas section of the BOM. The setting of the Duplicate Find Numbers SmartRule does not affect this behavior.

If the Duplicate Find Numbers SmartRule is set to Allow, any item can have the same find number as another item regardless of what site section of the BOM they are on.

Duplicate Ref Des

Settings: Allow, Disallow, Warning

Controls whether duplicate reference designators can be used on a BOM. This SmartRule has been expanded to dictate whether or not the same reference designator can be used in a site-specific portion of a BOM as is used in the global portion of a BOM. It also dictates whether or not the same reference designator can be used within a site-specific portion of the BOM.

For example: If the Duplicate Ref Des SmartRule is set to Disallow, then:

Reference Designator 1 cannot be used for Part 123 on the Milpitas BOM if Reference Designator 1 is used for Part 234 on the Global BOM.

Reference Designator 1 cannot be used for Part 123 on the Milpitas BOM if Reference Designator 1 is also used for Part 234 on the Milpitas BOM.

The same reference designator can be used in more than one site-specific portion of the BOM regardless of the Duplicate Ref Des SmartRule setting.

For example: Reference Designator 1 could be used for Part 123 on the Singapore section of the BOM and Reference Designator 1 could be used for Part 234 on the Milpitas section of the BOM. The setting of the Duplicate Ref Des SmartRule does not affect this behavior.

If the Duplicate Ref Des SmartRule is set to Allow, any item can have the same reference designator as another item regardless of what site section of the BOM they are on.

Effectivity Date Order

Settings: Allow, Disallow, Warning (default)

Controls whether a new rev can be released with an effective date that is earlier than one or more old revisions. This SmartRule also applies to the effectivity dates for site-specific items on the Affected Items table.

Effectivity Gap

Settings: Allow, Disallow, Warning (default)

Controls gaps between the obsolete date of an existing part and the effective date of its replacement part on affected items. This SmartRule also applies to the effectivity dates for site-specific items on the Affected Items table.

Effectivity Overlap

Settings: Allow, Disallow, Warning (default)

Controls overlaps in the effective dates of an existing part and the obsolete date of its replacement parts on an affected item. This SmartRule also applies to the effectivity dates for site-specific items on the Affected Items table.

Enable Addition of Activities and Gates to Completed Activities

Settings: Allow, Disallow (default)

Controls ability to add new data from PPM Activities or Gates to completed (Released) Activities.

Enable Comments for Deleting, Archiving & Delegating

Settings: Disallow (default), Allow

Controls whether comments can be recorded while performing Delete, Archive, or Delegate actions in Product Portfolio Management.

Force Commodity and Part Family to be Identical

Settings: Yes (default), No

This rule applies only to customers that have both the PCM and PG&C solutions. Otherwise, you can ignore it.

The rule controls whether legacy Part Family objects (in PG&C solution) and new Commodity objects (in PCM solution) are to be treated by the system as Commodity objects that are shared by both solutions. The default is Yes.

If you want to treat Part Families and Commodities differently, set the rule to No. However, you must also configure the Commodities class to make the rule effective. For more information, see [Part Groups: Configuring Part Families](#).

Items Released First

Settings: Allow, Disallow, Warning (default)

Controls whether an item can be released when the item's BOM contains unreleased items. This SmartRule is pertinent to multiple sites: when a "parent" item is released, the rule checks the BOM components for site association and whether the BOM components are also released for that particular site.

Many Items per PSR

Settings: Allow, Disallow (default), Warning

Allows or limits the association of items (parts or documents) with PSRs (problem reports or NCRs).

Many QCR per PSR

Settings: Allow, Disallow (default), Warning

Allows or limits the association of QCRs (CAPAs or audits) with PSRs (problem reports or NCRs).

Multiple Items Per Manuf Part

Settings: Allow, Disallow, Warning (default)

Controls whether a manufacturer part can have multiple item parents.

If set to Disallow or Warning (the default), the system checks items as the change order's Workflow performs a Release Audit. This function has been enhanced; for more information, see Release Audit, or Audit Current Status for Conditions to Release.

Negative Value For Material Price Adder Fields

Settings: Allow, Disallow (default), Warning

Controls the entering of “negative prices” in the Material Price Adder attribute.

Negative Value For Material Price Fields

Settings: Allow, Disallow (default), Warning

Controls the entering of “negative prices” in the Material Price fields.

Negative Value For Non-Material Price Fields

Settings: Allow, Disallow (default), Warning

Controls the entering of “negative prices” in Non-Material Price fields.

Notify Resource Pool Owner for Proposed Programs

Settings: Allow (default), Disallow

Controls the sending of notifications to resource pool owners for programs in Proposed state.

Overlap Price Line Effectivity Periods

Settings: Allow, Disallow (default), Warning

Controls overlapping effectivity periods of price lines on price objects and PCOs.

PSR Contains Items and Related PSRs

Settings: Allow, Disallow (default), Warning

Controls whether a PSR can be associated with both affected items and related PSRs (Allow), or only affected items or related PSRs (Disallow).

Note There is no business logic between items on the Affected Items tab and items on the Related PSR tab (that is, an item listed on Related PSR will not be copied to the Affected Items of the parent PSR).

 There is business logic between PSRs and QCRs, so if a PSR is associated with a QCR, items from both the PSR's Affected Items tab and its Related PSR tab will automatically populate the QCR's Affected Items tab.

Redline Attributes

Settings: Allow, Disallow (default)

Controls the display in Web Client of Redline Title Block tab for Change Orders and Manufacturer Orders.

Redline Manufacturers On Change Order

Settings: Allow (default), Disallow

Controls whether users are allowed to redline the Manufacturers tab from an ECO. If the setting is Disallow, all buttons in the Redline Manufacturer table are disabled. Possible settings are Allow (the default) or Disallow.

Release QCR With Un-resolved Items

Settings: No Display (default), Warning

Controls whether a QCR can be released either manually or through auto-promotion even though all items on the Affected Items tab have not been associated with a Change.

If you set it to No Display, the SmartRule allows a QCR to be released even though all its affected items do not have an associated Change. Such a QCR will also pass a release audit without a warning.

If you set it to Warning, the SmartRule warns users that a QCR is being released even though all its affected items do not have an associated Change.

Released Rev Required

Settings: Allow, Disallow, Warning (default)

Controls whether a routable object can be unreleased if has an affected item that is on the BOM of a released assembly.

Unrelease Change Order

Settings: Allow, Disallow, Warning (default)

Controls whether change orders can be unreleased.

Unrelease Change Request

Settings: Allow, Disallow, Warning (default)

Controls whether change requests can be unreleased.

Unrelease Deviation

Settings: Allow, Disallow, Warning (default)

Controls whether deviations can be unreleased.

Unrelease Manufacturing Order

Settings: Allow, Disallow, Warning (default)

Controls whether manufacturer orders can be unreleased.

Unrelease Stop Ship

Settings: Allow, Disallow, Warning (default)

Controls whether stop ships can be unreleased.

Workflow Matching Criteria Attribute Modification

Settings: Allow, Disallow (default), Warning

Note	None of the choices result in the workflow being altered.
-------------	---

A user may modify an attribute by giving it a value that does not match the workflow's matching criteria. This SmartRule governs whether the system accepts the changed attribute.

Note	If this SmartRule is set to Warning or Disallow, any attempt to modify attributes of the routable object that are specified in the workflow's matching criteria results in an immediate warning or prevention of the modification. However, if the workflow's matching criteria includes a reusable criteria that specifies an item's attribute, the user will be allowed to modify the value of that item attribute to a value that does not match the reusable criteria. No warning will be given. If, after that item attribute has been modified, the user then modifies the routable object in any way, the user is warned that the routable object no longer matches the workflow's matching criteria.
-------------	--

Zero Value For Material Price Fields

Settings: Allow, Disallow, Warning (default)

Controls the use of “0” as a value for the Material Price field.

Zero Value For Material Price Adder Fields

Settings: Allow, Disallow, Warning (default)

Controls the use of “0” as a value for the Material Price Adder field.

Zero Value For Non-Material Price Fields

Settings: Allow, Disallow, Warning (default)

Controls the use of “0” as a value for the Non-Material Price field.

Viewer and Files

This chapter includes the following:

▪ Introduction	269
▪ Viewer & Files Properties	269
▪ Options for Purging and Retaining Files	270
▪ File Association tab.....	273
▪ Printing Banners and Watermarks.....	275

Introduction

You can double-click **Viewer and Files** under **System Settings** to open the Viewer & Files window. You can set viewing preferences for files that are attached to Agile PLM objects.

Viewer & Files Properties

The following table lists the properties on the **General Information** tab of the Viewer & Files window; elaborations about some of the properties follow.

Property	Description	Default
AutoPurge Enabled	Determines whether old versions of attachments should be deleted from the Agile File Manager.	No
File Version Keep	Dictates the number of versions to keep for archival purposes; used with AutoPurge Enabled set to Yes. Whether or not these versions include redlined versions depends on the settings of AutoPurge Enabled and Purge Redlined Files; see Note in text below.	3
Purge Redlined Files	Determines whether files with redlines are deleted, depending on the setting of AutoPurge Enabled. Overrides the File Version Keep preference.	No
Purge Historical Reports Unaccessed (in days)	Dictates the number of days that a Historical Report is not accessed before it is automatically purged.	30
Directly Use These Thumbnail Image Types	This setting provides a list of file types (listed as the extension names) that will be directly converted to thumbnails.	bmp, gif, jfif, jpe, jpeg, jpg, and png These are the default image types and the user should not remove or add

Property	Description	Default
		to these.
CAD Revision BOM Attribute	This field lets the administrator enable a text field in the Documents class, which permits assigning Revision letters (A, B, etc.) to CAD modeling BOMs (structured BOMs). The process to set up this field is described in Structured File Types and CAD Revision BOM Attribute on page 272.	—
Upload File Size Limit (in MB)	Defines the maximum size (in MB) of uploaded files for Java Client, Web Client, Portal Client, and SDK. The default value, 0, indicates "No Limit"; any non-negative integer sets the size limit in MB. Users get error message in Java & Web clients if a file is too large. Files that successfully upload (before a failure occurs) remain uploaded, other files (after a failure occurs) will not be uploaded.	0 (= No limit to file size)

Options for Purging and Retaining Files

The following settings determine the circumstances under which files are purged or retained on the Agile PLM system and on users' local computers. Purging and retaining take place only during checkout and checkin routines.

AutoPurge Enabled

Old versions of attachments can be automatically deleted from the Agile File Manager when new versions are checked in; the system does this after the checkout or checkin routine. If **AutoPurge Enabled** is set to Yes, old versions are deleted. To specify how many versions of the files you want to keep, use the **File Version Keep** field. See [File Version Keep](#) on page 271 and [Purge Redlined Files](#) on page 271 below.

If **AutoPurge Enabled** is set to No, old versions of attachments are kept on the Agile PLM system.

Caution There is no operation to restore an autopurged file. AutoPurge is *not* an archive function.

To enable or disable AutoPurge:

1. Under **System Settings**, double-click **Viewer & Files**. The Viewer & Files window appears.
2. In the **Auto Purge Enabled** drop-down list, select No (disabled) or Yes (enabled).
3. When you are finished, click **Save**.

File Version Keep

Use this property to specify how many old versions of the files you wish to keep. For example, if the value is set to 3, then the three most recent versions of the file are archived. (The latest version is also kept.) Use this property when **Auto Purge Enabled** is set to Yes; if **Auto Purge Enabled** is set to No, all versions are kept. See [AutoPurge Enabled](#) on page 270 above and [Purge Redlined Files](#) on page 271.

To specify the number of attachment versions to keep:

1. Under **System Settings**, double-click **Viewer & Files**. The Viewer & Files window appears.
2. In the **File Version Keep** field, type a number. The number indicates how many attachment versions you want to keep, in addition to the current version.
3. When you are finished, click **Save**.

Purge Redlined Files

The **Purge Redlined File** field determines whether redlined files are automatically deleted along with files without redlines, depending on the setting of **Auto Purge Enabled**.

With **Auto Purge Enabled** set to Yes and **Purge Redlined File** set to Yes, the value of **File Version Keep** is the number of versions that will be kept. All earlier redlined files are purged. With **Auto Purge Enabled** set to Yes and **Purge Redlined File** set to No, the value of **File Version Keep** is the number of versions (either redlined or non-redlined) that will be kept. All earlier redline files are also kept.

See [AutoPurge Enabled](#) on page 270 and [Purge Redlined Files](#) on page 271.

To set the Purge Redlined File property:

1. Under **System Settings**, double-click **Viewer & Files**. The Viewer & Files window appears.
2. In the **Purge Redlined File** drop-down list, select No (disabled) or Yes (enabled).
3. When you are finished, click **Save**.

Directly Use These Thumbnail Image Types

This setting provides a list of file types (listed as the extension names) that will be directly converted to thumbnails in Web Client without requiring the use of the view server because the conversion is done directly by the browser and occurs immediately when the file is attached. This setting also is a list of file types that can be used for the Replace function of manually specifying an image file to use for the thumbnail. The administrator can add supported image file types to this list. Be sure to have only one file type (entered in as an extension name) per line.

The default list of file types included in this field are:

bmp
 gif
 jfif
 jpe

jpeg

jpg

png

For more information regarding Thumbnails, see *Getting Started with Agile PLM*, [Configuring a File Manager](#) on page 360, and [Preferences Defined](#) on page 379.

Important Thumbnail images display in Web Client only.

Thumbnail generation options

The file types listed in **Directly Use These Thumbnail Image Types** need to also be checked in the **Auto Generate Thumbnail** column of the **File Association** tab in order to be successfully rendered in the browser. It is possible to have no file types listed in **Directly Use These Thumbnail Image Types** and only have the file types checked in the **Auto Generate Thumbnail** column and successfully have those types rendered in the browser, but it takes much longer because it is using the view server.

Note It is necessary to restart the file server to successfully render these images once the settings have been changed.

For more information see [Specifying Supported File Types for the Agile Viewer](#).

CAD Revision BOM Attribute

This value identifies the attribute that is configured as part of Agile's EC CAD Connectors to hold the "As Saved" revision.

To set the CAD Revision BOM Attribute:

1. Double-click **Viewer & Files**.
2. From the CAD Revision BOM Attribute dropdown list, select the BOM attribute that you previously configured for holding the CAD Revision, as part of your EC installation. Click **OK**, then click **Save**.

If you wish to use the CAD Revision BOM Attribute to provide fixed BOM resolution for the viewer even though you are not using an Agile EC CAD Connector, you must manually store the current value of the Revision field, for each object in the BOM, in the BOM attribute you designate for "CAD Revision".


Note If CAD Revision BOM Attribute field is left "blank," the system uses standard Agile BOM resolution to determine how to traverse the structure to find files. Standard resolution is considered "floating", in that child objects can "rev" forward even after the parent object is released.
--

File Association tab

Specifying Supported File Types for AutoVue for Agile

In the **File Type** list on the **File Association** tab, you can select the types of files that users can view with the AutoVue for Agile. By selecting CAD Structure support then that particular file type will have the Viewer will render the structure. By selecting Auto Generate Thumbnails then that particular file type will have the Viewer render a thumbnail image in Agile.

Note The user needs to be assigned the ViewFile privilege to view attachments.



Note All of the Auto Generate Thumbnails check-boxes are un-checked by default.

For more information regarding Thumbnails, see *Getting Started with Agile PLM*, [Configuring a File Manager](#) on page 360, [Directly Use These Thumbnail Image Types](#) on page 271 and [Preferences Defined](#) on page 379.

The “2D” file formats in the following table are automatically listed in the **File Type** list in

Administrator. Current customers may also have additional file types listed after upgrading.

File extension	File type
BMP	Microsoft bitmap
CAL	CALS Group IV
CGM	Computer Graphics Metafile
DGN	Intergraph
DOC	Microsoft Word
DWG	AutoCAD Drawing File v 14, 2000
DXF	AutoCAD Drawing Exchange Format
GIF	Graphic Interchange Format
GP4	a neutral 2D viewable format
JPG, JPEG	Joint Photographic Experts Group
PCX	Microsoft Paintbrush
PDF	Adobe Portable Document Format
PLT	HPGL & HPGL 2
PPT	Microsoft PowerPoint
PS	Adobe Postscript
SLDDRW	SolidWorks 2D
TIF, TIFF	Tagged Image File Format
TXT	Text
XLS	Microsoft Excel
ZIP	Zip

AutoVue for Agile is the integration of Oracle's AutoVue visualization tool with Agile PLM. For an updated list of file formats supported by AutoVue, see <http://www.oracle.com/technology/documentation/autovue.html>.

File types are listed by extension. The **View** button is enabled by default, but if a user selects an attached file that has an unsupported filename extensions, the system will throw an error.

Caution	If you are the administrator of Agile PLM on a Chinese, Hebrew, or Swedish operating system, Agile recommends that you remove the Supported File Types property of all file-type extensions. This is because the AutoVue for Agile is not supported on those operating systems. For detailed information about using Agile PLM with international operating systems, contact the Agile support Web site.
----------------	--

To add or delete a file to the Supported File Types list:

1. Go to **System Settings > Viewer & Files > File Association** tab.
2. To delete a file type from the **File Type** list, select that line and click **Delete**.
3. To add a file type to the **File Type** list, click the **New** button, and then enter its name on the new line. You can also use Ctrl-C and Ctrl-V to copy and paste a list from one of the other file type fields or from another application.
4. When you are finished, click **Save**.

Printing Banners and Watermarks

The Viewer & Files window includes a **Watermark** tab and a **Banners** tab. The settings on these tabs determine whether banners and watermarks appear on printouts of files attached to Agile PLM business objects, and the content of those banners and watermarks. These banners and watermarks appear on files printed with the AutoVue for Agile.

The only way to have no print appear is to make sure the Banner and Banner Text pairs (and Attribute Watermark/Attribute Watermark Text) are *both* blank: delete the text in the appropriate text field. For example, if you make Top Left Banner blank, you will then see an unwanted “Printed by:” because this was not deleted from Top Left Banner Text.

The following table lists the watermark properties; these can be set on the **Watermarks** tab.

Property	Description	Default Text or Setting
Attribute Watermark	The value of this attribute appears in the watermark as text after the Attribute Watermark Text.	[Select from drop-down list. This becomes \$ATTRIBUTENAME:]
Attribute Watermark Text	Text that appears before the text of the value in the Attribute Watermark.	[None: enter your own text, including colon if appropriate.]
Back Rev Watermark Text	Watermark text that appears if the item object is not the latest revision. This property is available only for the Parts and Documents Banner & Watermark attributes.	Back Revision
Name	Lists all the Agile PLM business classes for selection	[one for each business class]
Pending Rev Watermark Text	Watermark text that appears if the Item object is a pending revision. This property is available only for the Parts and Documents Banner & Watermark attributes.	Pending Revision
Print Watermark	Turns printed watermarking on (Yes) and off (No).	No

The following table lists the banner properties; these can be set on the **Banners** tab.

Property	Description	Default Text or Setting
Name	Lists all the Agile PLM business classes for selection	[one for each business class]
Bottom Left Banner	Banner appears at the bottom of the printout, on the left, after the Bottom Left Banner Text.	[object number]
Bottom Left Banner Text	Text that appears before the text that is the value of the Bottom Left Banner.	\$ATTRIBUTENAME:
Bottom Middle Banner	Banner appears at the bottom of the printout, in the middle, after the Bottom Middle Banner Text.	<i>Item:</i> "Rev [letter] of Latest Released Revision" Empty for other classes
Bottom Middle Banner Text	Text that appears before the text that is the value of the Bottom Middle Banner.	<i>Item:</i> "Rev:" Empty for other classes
Bottom Right Banner	Banner appears at the bottom of the printout, on the right, after the Bottom Right Banner Text.	[Status for workflow class; Lifecycle Phase for non-workflow class]
Bottom Right Banner Text	Text that appears before the text that is the value of the Bottom Right Banner.	"Status:" [or] "Lifecycle phase:"
Top Left Banner	Banner appears at the top of the printout, on the left, after the Top Left Banner Text.	[Print User]
Top Left Banner Text	Text that appears before the text that is the value of the Top Left Banner.	"Printed By:"
Top Middle Banner	Banner appears at the top of the printout, in the middle, after the Top Middle Banner Text.	—
Top Middle Banner Text	Text that appears before the text that is the value of the Top Middle Banner.	—
Top Right Banner	Banner appears at the top of the printout, on the right, after the Top Right Banner Text.	[Print Date]
Top Right Banner Text	Text that appears before the text that is the value of the Top Right Banner.	"Printed On:"

Here are a few points about the watermark and banner settings:

- All the properties except Print Watermark can be filled with your own text.
- For any specific attachment, only one setting is available per banner or watermark property.
- You cannot create multiline banners.
- The variable "\$ATTRIBUTENAME:" inserts the name of the attribute that is selected in the

Attribute Watermark property or the banner properties.

- *Within* the Banner Text and Attribute Watermark Text properties, it is possible to enter your own text *before* the “\$ATTRIBUTENAME:” variable, but not after.

Banner and Watermark Properties

When you set values that specify text to appear in printed banners and watermarks, you select from a drop-down list of variables and attributes (fields that appear in Agile PLM clients). The following table lists and describes the choices.

Variable in drop-down list for property	Default printed value and restriction
Effective Date – Obsolete Date	<i>Effective from: [effective date] to: [obsolete date]</i> Available for items only: Effective Date and Obsolete Date are derived from the Affected Items tab of the change that created the specific rev of the item.
Page Number	<i>Page [page number]</i> Also specifies the region of an image when a specific region is printed.
Page Number and Page Count	<i>Page [page number] of [total pages]</i> Also specifies the region of an image when a specific region is printed.
Print Date	<i>[print date]</i>
Print User	<i>[user]</i>
Rev of Latest Released Revision	<i>[rev letter of latest released revision]</i> Available for items only.
Watermark Text	The value specified for the Watermark Attribute property, regardless of whether that property is enabled. Available as a variable for banners only.
Attribute	<i>[attribute name].[attribute value]</i> Many selections: Attachments.[value], Change History.[value], Page Two.[value], Title Block.[value], Cover Page.[value], General Info.[value]

To print watermarking and specify watermark text:

1. Under **System Settings**, double-click **Viewer & Files**. The Viewer & Files window appears.
2. Click the **Watermark** tab to bring it forward.
3. Double-click the watermark you want, and update the property setting for the class.
4. Select Yes in the **Print Watermark** drop-down list to enable watermark printing.
5. To select watermark text, in the **Attribute Watermark** the drop-down list, select an attribute. The value of this attribute will appear as watermark text when **Print Watermark** is set to Yes.
6. To specify custom text for back revisions and pending revisions, in the **Back Rev Watermark Text** or the **Pending Rev Watermark Text** field, type the text that you want to appear in the watermark or accept the default text.

7. When you are finished modifying the **Watermark** tab, click **Save**.

Specifying Banner Text and Location

To specify a banner to print on Agile PLM object printouts:

1. Under **System Settings**, double-click **Viewer & Files**. The Viewer & Files window appears.
2. Click the **Banners** tab to bring it forward.
3. For each banner you want to appear (Bottom Left, Middle, or Right; or Top Left, Middle, or Right), select an attribute or variable from the drop-down list. The value of this attribute or variable will appear in the banner.
4. If you want to remove the default text or enter new text in the banner, place your cursor in the corresponding text field of the banner, for instance, **Bottom Left Banner Text**, and delete or alter the text. Since this text appears *before* the value in **Bottom Left Banner** property, you may end this text with a colon.
5. To change a text property, in the corresponding text field of the banner, for instance, **Bottom Left Banner Text**, delete or alter the text, type the new text or variable in its place.
6. When you are finished modifying the **Banners** tab, click **Save**.

Notifications

This chapter includes the following:

▪ Overview of Notifications	279
▪ Default Notifications	280
▪ Event-based Notifications	281
▪ Working with Default and Event-based Notifications	285

Overview of Notifications

Agile PLM has the capability to send notifications to users, either when the user is required to take action, or to notify the user that various actions have taken place.

With the introduction of the **Event Management** framework, there are now two types of notifications in PLM. The **Notifications** node stores both types:

- *Default notifications* can be modified but only in a limited way; for this reason they are sometimes referred to as *notification templates*.
- *Event-based notifications* are admin-user-created and permit much more flexibility and creativity in how and when notifications are sent by the system.

The default notifications are triggered by the system based on system- or end-user-generated actions that have been captured in the notification templates. Default notifications have an uneditable Object Type property. They cannot be used by Event Subscriptions, that is, unless you perform SaveAs on the default notification and proceed to configure a Notification mask.

Event-based notifications can be distinguished by their configurable Object Type property. They can be triggered by Event Subscriptions that are configured in the **Event Subscribers** node.

Preliminary Admin Settings for Notifications

It is necessary for the administrator to enable a database setting before *any* notifications are sent. In **Server Settings > Database**, ensure that the setting of the **Notification Enabled** property is Yes. If this property is set to No, PLM does not send notification emails or messages to the users in the system.

An *individual* notification is sent only if it has been enabled by setting its **Enabled** attribute to Yes. Depending on the **Notification Type** property setting for the notification, the notification appears in the user's Inbox, is sent by email, or both. The **Enabled** and **Notification Type** attributes can be set as needed for each notification.

A user can receive notifications with links back to Java Client or Web Client; more explicitly, the User preference Preferred Client (under **User Settings > Users > <any user> > Preferences** tab) determines which client is automatically opened to the object to which the notification's link points.

Since Agile users working in the PPM, PCM, and PG&C solutions operate only in Web Client, it is recommended that the Preferred Client be set to Web Client for those users.

To fully configure email notification in Agile PLM Clients, please see [Configuring Web Client Notification](#) on page 355 and [Configuring Java Client Notification](#) on page 356.

Default Notifications

Default notifications are listed in the **System Settings > Notifications** node. Default notifications are not and cannot be associated with any events configured by the administrator in the **Event Management** node; however, a Default notification can be saved to create a new notification that can be associated with an Event Subscription. See [Creating a Notification Using SaveAs](#) on page 286 for more information.

Attributes of Default Notifications

Default notification attribute	Description
Name	Name of notification; not editable
API Name	API Name is non-editable in Default notifications
Object Type	Object Type is non-editable in Default notifications
Enabled	Yes = the notification is enabled, so it can be sent (by the system). No = the notification is disabled, it cannot be sent.
Priority	Default is Regular; list includes High and Low
From	Select a user from the list who will be listed in the "From:" field of the notification. Only one user can be selected for the From attribute. The defaults are variables: \$AGILE is always present on the dropdown list; \$ORIGINATOR and \$SENDER are often present; on routable objects, the appropriate routing manager variable is present (for example, \$CHANGE ANALYST).
To	To: is always empty on Default notifications.
Notification Type	Select Email, Email and Inbox, or Inbox from the dropdown list.
Subject (and Data)	By including Data tags when you compose the subject line, you can include references specific to the triggering event, such as Change Number and Originator. See Entering Subject and Body Text on page 285.
Body (and Data)	By including Data tags when you compose the body text, you can include references specific to the triggering event, such as Change Number and Originator. See Entering Subject and Body Text on page 285.

\$NOTIFY picks up only the default Notify users from manual routing. In this case, when Change Status is brought about by autopromotion (for example, when a Relationship is triggered), the default Notify users are not picked up. This is a difference between how Default notifications and Event-based notifications process change status.

Event-based Notifications

Event-based (or "admin-created" or "user-defined") notifications are created in the **Notifications** node. A notification created by the administrator has much more flexibility than the default notifications. Event-based notifications support **Page Three** attributes (if any) for subclass notification.

Event-based notifications are the Handler in those Event Subscriptions that are dedicated to notifications. (See [Event Management](#) on page 305 and [Handler Types](#) on page 312.) For an example of a Notification mask configured into an Event Subscription, see [Notify when Affected Items Table is Modified](#) on page 351.

Notifications can also be called by the Agile SDK and a Script PX handler. (See [Invoking Notifications Programmatically](#) on page 284) For an example of generating a notification through the SDK, see [Notify Create User when Item is Incorporated](#) on page 346.

When a notification is triggered in the application, a Scheduled Notification is tracked in the **History** tab of the object. It shows the triggered Event and Notification as well as the \$NOTIFY users that may receive the notification.

In an admin-created notification, \$NOTIFY picks up the "Notify" users entered by end-user in the Notify field in routing slips, Signoff dialog box, and Comment dialog box; it also picks up the "Checkbox" users in Signoff dialog box and Comment dialog box.

In addition, if the Default notification is used for Reminders, it picks up the Approvers to be reminded; if the Default notification is used for Escalations, it picks up the Escalation persons of the Approvers.

To find a list of only Event-based notifications that are created by the administrator go to **System Settings > Event Management > Event Handler Type > Notifications > Where Used** tab.

Note Unlike Default notifications, admin-created notifications can be deleted. See [Deleting a Notification](#) on page 284.

Important	<p>For notification-specific Event Subscriptions, the object type of the Event mask must be appropriate for the object type of the Notification mask. Either the notification applies to all objects of the Object Type (subclass), or, the notification is derived from the Object Type (base class and class).</p> <p>For example, if the Notification mask specifies Change Orders (a class), the Event mask must specify the class or ECO (subclass) or any other subclass derived from the Change Order class.</p>
------------------	---

Attributes of Event-based Notifications

Event-based notification attribute	Description
General Information tab attributes	
Name	Name of Notification mask
API Name	Name of the object that is used by external processes to identify the object. You can specify an API name, but internal consistency is enhanced by accepting the system-generated name once you have specified the Name of the Notification mask. See API Name on page 19.
Object Type	<p>The object type is used to limit the notification to actions on objects of the type specified. This required field is selected from a dropdown list of Base Class, Class, and Subclass options.</p> <p>The object type selected also dictates the available From options and available attributes (Cover Page, Page One, Page Two, or Page Three) to be added as tags for the Subject and Body fields in the notification. It also dictates some of the variables available in the "To" options (for example, \$CHANGEANALYST).</p> <p>Object Type can be changed in the Create Notification (Mask) dialog for user-defined notifications. Object Type is non-editable once the Notification mask has been created.</p> <p>(See "Important" note just above this table.)</p>
Enabled	<p>Yes = the notification is enabled, so it can be sent (by Event Subscription or even programmatically, i.e., by SDK).</p> <p>No = this notification is disabled, it cannot be sent.</p>
Priority	Default is Regular; list includes High and Low.
From	<p>Select a user from the list who will be listed in the "From:" field of the notification. Only one user can be selected for the From attribute.</p> <p>The defaults are variables: \$AGILE is always present on the dropdown list; \$ORIGINATOR and \$SENDER are often present; on routable objects, the appropriate routing manager variable is present (for example, \$CHANGE ANALYST).</p>
To	<p>Select a user from the list who will be listed in the "To:" field and receive the notification. The variable \$NOTIFY is available, as well as specific recipient users from the Address Book.</p> <p>Note If the object type is a routable object then the available list of recipients will also include workflow users. The list of users may include users that will not receive notifications because of lack of privileges.</p>
Notification Type	Select Email, Email and Inbox, or Inbox from the dropdown list.

Event-based notification attribute	Description
Subject (and Data)	<p>You may compose a subject line for the notification.</p> <p>By including Data tags when you compose the subject line, you can include references specific to the triggering event, such as Change Number and Originator.</p> <p>See Entering Subject and Body Text on page 285.</p>
Body (and Data)	<p>You may compose body text for the notification.</p> <p>By including Data tags when you compose the body text, you can include references specific to the triggering event, such as Change Number and Originator.</p> <p>See Entering Subject and Body Text on page 285.</p>
<i>Where Used tab attributes</i>	
Name	Names of Event Subscribers (masks) that point to the notification
Description	Description of Subscriber masks that point to the notification
Enabled	The setting of Enabled for the Subscriber masks
Event	The Event mask that is associated with the Subscriber masks
Event Handler	The current notification's name. This is always the Notification currently opened because the Notification functions as the Handler for the associated Subscriber masks.
Trigger Type	The trigger type for a notification is always Post. See Trigger Type: Pre and Post on page 326.
Execution Mode	The execution mode for a notification is always Asynchronous. See Execution Mode on page 326.
Order	Disabled; the column does not display data because the property does not apply to notifications.
Error Handling Rule	Disabled; the column does not display data because the property does not apply to notifications.

Working with Events-based Notifications

The following tasks apply to Events-based notifications, not Default notifications.

Creating a Notification

This is the procedure to create a Notification mask. It can then be named by a Subscriber mask that binds it to an Event mask to become a complete Events-based notification.

To create a Notification mask:

1. Under **System Settings**, double-click **Notifications**. The Notifications window appears.
2. Click **New**.
3. Enter a name in the **Name** field.
4. Enter a name or click the **Autonumber** button to generate the required API name.
5. For the required **Object Type** field, choose a Base Class, Class, or Subclass type of object.
6. Click **Next**.
7. Set the **Enabled** field to Yes or No.
8. Set **Priority** to High, Low, or Regular.
9. In the **From** field select from the dropdown list of the available values for the object type selected, such as \$AGILE or \$CHANGEANALYST, depending on Base Class, Class, or Subclass.
10. In the required **To** field select from the Address Book of Users and User Groups who the notification will be sent to.
11. Set the **Notification Type** as Email, Email and Inbox, or Inbox only.
12. To insert a data tag (or data variable) into the **Subject** or **Body** field, click **Add Data Tag**. For more information, see [Entering Subject and Body Text](#) on page 285.
13. Click **Finish**.

Deleting a Notification

Notification masks can be deleted only if they are not used by Subscribers. Default notifications cannot be deleted; they can be enabled and disabled.

To delete a user-defined notification:

1. Under **System Settings**, double-click **Notifications**. The Notifications window appears.
2. Use the filter to find the specific notification you want to delete.
3. Select the notification and click **Delete**.

You can also double-click the notification and then click **Delete**. By doing so, you can look through the settings and properties to be sure you want to delete the notification.

Note If you delete a Notification mask that has already sent notifications to users, then the subject of the notifications in the users' inboxes will change to appear as null, reflecting that the notification is deleted.

Invoking Notifications Programmatically

SDK and Scripting allows notifications to be sent out programmatically. A notification invocation uses the following parameters, whose use is explained:

- **SendNotification**: the program module or method used to send out a notification.

- **Notification Name:** the name of the notification.
- **Urgent:** whether the notification is to be flagged as Urgent or not; the value can be True or False.
- **Addressee List:** list of users who may be notified; this set of values is appended to the list of people listed in the "To" field of the notification. This list of Addressees is only picked up if \$NOTIFY is assigned in the "To" field.
- **Comment:** refers to the comment passed to the Comment data tag, if assigned in the notification template.
- **Object:** an object of the type corresponding to that associated with the notification in its definition. For example, an ECO object needs to be passed to a notification tied to a notification associated with the ECO subclass (it can also be passed to a notification tied to the Change Orders class or Changes base class). This object is used to derive the values of variables used in the notification Subject, Body, and To fields.

For more information about sending notifications using Agile SDK, see Chapter 9, "Subscribing to Agile PLM Objects" in the *Oracle Agile PLM SDK Developer's Guide*.

Working with Default and Event-based Notifications

The following tasks apply to both Default notifications and Events-based notifications.

Editing a Notification

To edit a notification:

1. Under **System Settings**, double-click **Notifications**. The Notifications window appears.
2. Filter the notifications by Name or Object Type.
3. Double-click the name of the notification you want to edit. Its window appears.
4. Edit the attributes in the appropriate manner: select from a dropdown list or enter text. Refer to the table found above.
5. To insert a data tag (or data variable) into the **Subject** or **Body** field, click the **Add Data Tag** button. For more information, see [Entering Subject and Body Text](#) on page 285.
6. Click **Save**.

Entering Subject and Body Text

Subject and Body fields are required to be populated. Each Default notification includes text for the subject and body of the message. You can use the default text, or you can enter a text message that you want to use.

During the editing or creation of a notification, when you enter the text you want to appear in the subject line and body of the notification, you can add data tags that refer to pertinent information for that notification.

The available tags are dictated by the object type associated with the notification.

For example, for an ECO Status Promotion, Approvers and Change Analyst notification, you might want the subject line to say:

[Cover Page.Change Type] [Cover Page.Number] has been moved from [From Status] to the [To Status] of [Cover Page.Workflow] workflow.

To include the From Status in the subject line:

1. Click to position the cursor in the appropriate place in the subject message.
2. Select From Status in the **Data** field dropdown next to the **Subject** field.
3. Click Add **Data Tag**. The data tag [From Status] appears in the **Subject** field.
4. As you continue to enter text in the subject line, you can add more data tags.

Similarly, use the **Data** field next to the **Body** field to add data tags to the body text.

Creating a Notification using SaveAs

From existing notifications you can perform a SaveAs function to create a new notification with a new name and configure the values according to your needs.

Important All Default notification templates that are not bound to an object type (for example, Transfer Authority, Create, or Modify) as well as those for Product Cost Management cannot use the SaveAs feature.

When you create a notification using SaveAs, the object type of the original notification cannot be changed for the new one. The new notification is automatically associated with the object type of the original notification.

This is the only way a Default notification can be recast as a Notification mask and be used as an Event-based notification.

Also, if the source notification is a Default notification, then the **To** field in the new notification is unpopulated and can now be selected.

To create a new notification using SaveAs:

1. From an open notification click **SaveAs**.
2. Enter a new name and autogenerate the API Name.
3. On the **General Information** tab enter a To recipient.
4. Click **Save**.

Use the instructions in "Editing the Notification" to tailor the new notification as desired.

Full Text Search

This chapter includes the following:

▪ Full Text Search Limitations	287
▪ Full Text Search Properties	288
▪ Indexing Attachment Files	289

From the **Full Text Search** node, you specify how the search is done and manage the indexing of attachment files. The information on indexing in this chapter applies only to indexing files. Indexing of database information for Web searches is always done synchronously.

When a user searches for attachment file content, the search results list each object that contains files matching the search criteria. Only the latest versions of attachments are listed. For more information about setting up searches and finding data in Agile PLM, see *Getting Started with Agile PLM*.

Note Regarding the Agile multi-language capability, Full Text Search is supported for attachment files in Japanese, Traditional Chinese, Simplified Chinese, German, and French localized versions.

Full Text Search Limitations

Full Text Search has the following known limitations:

- Full Text Search follows existing roles and privileges. Users who do not have privileges for objects do not see these objects in search results.
- Users who do not have Field-level Read for fields do not see these fields in the search results.
- Full Text Search does not support searches for the following:
 - Synonyms
 - URL attachments
 - Viewer (Cimmetry) redline data
- For non-English text in documents, Full Text Search is supported only for attachment files, not for Stem searches or Concept searches.
- Attachment files that can be returned by a full text search must be created and saved in Microsoft Word (.DOC) or Excel (.XLS). Non-English-text attachment files created in .RTF or .TXT formats are not returned (although .TXT files might work if the encoding type is Unicode).
- Files on any Agile File Management file vault are available to Full Text Search, and are indexed based on the Administrator settings.
- If an object contains multiple files (that is, multiple documents are attached to the object), even

if only one of the files contains the search text, the entire object is returned. The file that contains the text is not indicated, and you may need to look through all attachment files to find the appropriate one.

Full Text Search Properties

When you double-click the **Full Text Search** node, the Full Text Search window appears, with **General Information** and **History** tabs. There is more information about the settings for indexing attachment files in the next section.

Property	Editable ?	Default	Notes
Stem Searching	Yes	Disabled	Finds variations of a word. From "run" it could find <i>ran</i> , <i>runs</i> , <i>running</i> .
Concept Searching	Yes	Disabled	Finds words that fit the same general concept. From "sports" it could find <i>running</i> , <i>track</i> , <i>basketball</i> , and the like. Important: Concept searching is not supported on Microsoft SQL Server.
Indexing	Yes	Synchronous	Indicates when words in a file will be available for full text search: Manual – indexes files when a user clicks the Index Attachments button only. Scheduled – indexes files according to the specified schedule—see next table. Synchronous – indexes files as soon as a file is added. See Indexing Attachment Files on page 289.
Index File Type	Yes	doc, ppt, pdf, txt, html, rtf, xml, xls	Makes possible selective indexing of specified files. A comma separates each file type, which are not case-sensitive. The default values cover a range of common file types. If you narrow the field to include one or two file types for a specific search, be sure to re-populate the field with your preferred file types upon completion of the search.
Last Indexed	No	N/A	Date the system was last indexed.
Next Scheduled Index	No	System-generated if scheduled indexing is running	Indicates the time the next scheduled index will occur. Only appropriate if indexing is "Scheduled."
Recurrence	Yes	N/A	Indicates how frequently indexing occurs. Activated when indexing is "Scheduled."

The following additional attributes appear when you click the Recurrence field:

Property	Editable?	Default	Notes
[Once a Day] or [Every X Hours Y Minutes]	Yes	No	Specifies the frequency that indexing occurs.
Starting At	Yes	0:00:00 am	Indicates the starting time of the schedule
Ending At	Yes	0:00:00 am	Indicates the ending time of the schedule. This option will be disabled if recurrence = Once A Day.
Days	Yes	M–F	Indicates which days the schedule will take effect


Indexing Attachment Files

There are some best practice recommendations for setting the system for indexing attachment files.

Using FileLoad and Indexing New Files

If the Indexing property is set to Synchronous and a large number of files are added to the File Management file vault using Agile FileLoad, the indexing process can take a long time. It has been found that setting this field to Manual increases the loading speed for a large number of files. Or, if the files being added tend to be large documents, set the Indexing property to Scheduled and set up an indexing schedule for once every 3 or 4 hours. If most of the new files are relatively small, the Indexing property can be set to Synchronous.

Index Attachment Button

Use the **Index Attachment** button  on the toolbar (**Admin > System Settings > Full Text Search**) to manually index new attachments that are not yet indexed. The **Index Attachment** button is available only when indexing is set to Manual.

"Stop" Words

There are short, common words called “stop” words that are ignored by the system in searching against attachment files. So, a search for “the mouse” will return only matches for “mouse”. You don’t need to know the words unless you run a lot of searches; the list of words is in “Using Quick Search to Find Attachment File Content” in the Searches chapter in *Getting Started with Agile PLM*.

My Assignments

This chapter includes the following:

- Overview 291
- Columns 291

Overview

This node configures some aspects of what your users see when they click the **My Assignments** tab in Web Client's home page. (If a user's Preferred Inbox View user preference is set to My Assignments, it will already be displayed when that user opens Web Client.) You can set the order of the columns, and you can rename the column names; the default columns are called Name, Status, Due Date, % Complete, Related To, Actual Hours, and Flag.

Columns

To change the order of the columns:

1. Under **System Settings**, double-click **My Assignments**. The Configure My Assignment Table opens.
2. Click the **Order Columns** icon. The Order dialog opens.
3. Select a column name and use the **Up** or **Down** buttons to move that name in the list. ("Top-to-bottom" in the list is equivalent to "left-to-right" in the user interface.)
4. When you are finished, Click **OK**. The dialog closes and you see the numbers in the Order column reflect the new order. A user will have to open or re-start Web Client to see the columns in the revised order.

To change the name of a column:

1. Under **System Settings**, double-click **My Assignments**. The Configure My Assignment Table opens.
2. Click in the field of the Column Name that you want to change. The field becomes editable.
3. Enter the new name. You can change other column names in this procedure.
4. When you are finished, click **Save**. A user will have to open or re-start Web Client to see the new column names.

To create a new column:

1. Under **System Settings**, double-click **My Assignments**. The Configure My Assignment Table opens.
2. Click **New**. A new row (representing the eventual column in Web Client user interface), is created.
3. Enter a name in the Column Name field.

4. In the Column Data Source field, use the dropdown dialog to select a data source for the column. You can choose a Class – Activities or Gates – and enter a Find value, using the **Down** or **Up** buttons to “find next” or “find previous,” respectively. When you have selected a data source, Click **OK**.
5. Use the **Order Columns** icon to adjust the order of the new column with the others (and to activate the **Save** button). When finished, click **Save** to complete the procedure. A user will have to open or re-start Web Client to see the new column.

To remove a column:

1. Under **System Settings**, double-click **My Assignments**. The Configure My Assignment Table opens.
2. Select the row that you want to remove. (It is easiest to click in Data Type or Order column of the row.)
3. Click the **Remove Column** icon. The row will be removed.

Note Default Columns cannot be removed, they can only be made non-visible by unselecting the checkbox in the Visible column.

4. When you are finished removing columns, click **Save**.

Unit of Measure (UOM)

This chapter includes the following:

- Creating Categories of Measure and Units of Measure..... 293

Note If you do not see the **UOM** node under **System Settings**, modify the Administrator privilege so that the Applied To list includes **UOM**.

The **UOM** node allows you to define different units of measure for use in Agile PLM. Units of measure are important for Product Governance & Compliance (PG&C), where you must measure the weight or quantity of restricted substances contained in your products.

You can define a new measure, and then specify the units used for that measure. You can also specify units of measure for any existing measure defined in your Agile PLM system. For example, the Dram unit of measure could be added to the Weight measure. In avoirdupois weights, 16 drams equal 1 ounce.

Each measure has a standard unit. All unit of measure values are normalized to the standard unit using a conversion factor. If you define a new unit of measure, you must specify the conversion factor relative to the standard unit. For example, if the standard unit of the Weight measure is Gram, the conversion factor for Ounce is 31.1034.

Creating Categories of Measure and Units of Measure

The following tasks describe how to create a new category of measure and new units of measure.

To create a new category of measure:

1. Under **System Settings**, double-click **UOM**. The Measures window opens.
2. Click the **New** button. The Create a New Measure dialog box appears, referring to a new category of measure, just as Weight and Quantity really are kinds or categories of measurement.
3. Enter the **Name**, **API Name**, **Description**, and **Range Match Factor** for your new category of measure.
The Range Match Factor expands the range of search results for a particular unit of measure that you search for. Its purpose is to adjust for inexact conversions to the standard unit for a measure.
4. Click **OK**.

To create a new unit of measure:

1. Under **System Settings**, double-click **UOM**. The Measures window opens.
2. Double-click a category of measure in which your new UOM belongs. The Measure: <Name> window appears.

3. Click the **UOM** tab.
4. Click the **New** button. The Create a New Unit of Measure dialog box appears.
5. Enter values for fields described in the following table. When you have finished Click **OK**.

Unit of Measure Attribute	Description
Name	Name of the unit of measure.
API Name	Unique systemwide identifier for objects and can be autogenerated. You can specify an API name, but internal consistency is enhanced by accepting the system-generated name.
Abbreviation	Standard abbreviation for the unit of measure.
Conversion Factor	Factor used to convert values to the standard unit. (See “Is Standard” description.)
Is Exact Conversion	Select Yes if the specified conversion is exact.
Is Standard	<p>Select Yes if the unit is the standard for your company. Only one unit of measure can be the standard.</p> <p>The first UOM that you create in a new category of measure must be the standard, whose conversion factor must be 1. All subsequent unit of measure values are normalized to the standard unit using the specified conversion factor.</p> <p>Note Once a unit of measure is set as a standard and compliance related data is created in Agile, it is recommended to not change the standard UOM. Changing the UOM will affect searches and compliance calculations.</p>
Enabled	Whether the unit of measure is enabled. Only enabled units of measure appear to the end-users of Agile PLM clients.

Other System Settings

This chapter includes the following:

▪ Company Profile	295
▪ Currency Exchange Rates	295

Company Profile

The **Company Profile** node provides a single location for storing information about your company.

To define the company profile:

1. Under **System Settings**, double-click **Company Profile**. The Company Profile window opens.
2. Enter the name, address, phone and fax numbers, URL, corporate currency, and the display name.
3. Click **Save**.

Currency Exchange Rates

From the **Currency Exchange Rates** node, you manage the Currency Exchange Rates table for in-system currency conversion. The list of available currencies is determined when Agile PLM is installed. For information about maintaining the list of available currencies, contact your Oracle Consulting – Agile Practice representative. The table in the Currency Exchange Rates window displays the currencies in use and their exchange rates for the corporate base currency.

Note Currency exchange rates affect costs in two solutions: Product Portfolio Management and Product Cost Management.

Currency conversion rates are used to convert currency values to the selected corporate currency. For instructions on how to select the corporate currency, see [Company Profile](#) on page 295.

Currency conversion is not an automatic process. Your system can be configured to have money fields on **Page Two** or **Page Three** of items. If you change the currency for a money field (for example, from USD to GBP), the field value is not automatically recalculated for the new currency.

To add a currency:

1. Under **System Settings**, double-click **Currency Exchange Rates**. The Currency Exchange Rates window opens.
2. Click the **New** button. The Add Currency dialog box appears.
3. Select one or more currencies in the **Choices** list and use the right-arrow to move them to the **Selected** list.

An additional dialog box opens for entering conversion rates.

4. Type the appropriate values in all **Conversion Rate** fields. Enter rates as decimal values, for example, 1.04 or 0.96.
5. Click **OK**. The new currency exchange rates appear in the list.

To modify the exchange rate for a currency:

1. Under **System Settings**, double-click **Currency Exchange Rates**. The Currency Exchange Rates window opens.
2. Double-click a currency to update. The Currency window opens.
3. In the **Conversion Rate** field, type a decimal value.
4. Click **OK**. The new currency exchange rates appear in the list.

Note To import updated currency exchange rates from a Microsoft® Excel file or a delimited text file, choose **Tools > Import**. For more information, see *Getting Started with Agile PLM*.

To view historical rates for a currency:

1. Under **System Settings**, double-click **Currency Exchange Rates**. The Currency Exchange Rates window opens.
2. Double-click a currency. The currency window opens.
3. Click the **Historical Rates** tab. The **Historical Rates** tab displays a list of conversion rates for the currency by date. You cannot edit historical currency rates.
4. Click **Close**.


Dashboard Management

This chapter includes the following:

▪ View Dashboard Tabs	297
▪ Adding Dashboard Tabs	297
▪ Deleting Dashboard Tabs	297
▪ Adding Tables to Optional Tabs	298
▪ Adding Charts to Optional Tabs	299
▪ Adding Custom (URL) Process Extensions for Optional Tables	301
▪ Reordering Table Rows in a Tab	301
▪ Displaying Optional Tabs	301


The Dashboard Tab View privilege is used to configure Dashboard tabs. For more information, see [Dashboard Management](#) on page 38.

View Dashboard Tabs

To view dashboard tabs, click **System Settings > Dashboard Management** node. The list of default dashboard tabs displays. You can reorder this list using the  icon, to change the order in which the tabs display in Web Client. To navigate to a tab, click on its name. You can edit the name and description of the tab, and specify whether the tab should be visible or not.


Optional tabs can be renamed and configured.

Adding Dashboard Tabs

To add a new tab, click the  icon in **Dashboard Management**. In the **Create Dashboard Tab** dialog, enter a Name, API Name and Description. In the **Visible** field, select Yes.

Note Although you can create an unlimited number of tabs, the tabs displayed in Web Client are restricted by the user's roles and privileges. To enable a user to view a particular dashboard tab, you must assign the Dashboard Tab View privilege to that user, and select the required tab in the **AppliedTo** property of that privilege. For further information, see [AppliedTo Capability](#) on page 232.

Deleting Dashboard Tabs

You can only delete dashboard tabs that you have created. Default tabs cannot be deleted. To delete a newly created Dashboard tab, within Dashboard Management, select the tab and click .

Note Once a tab has been accessed, you cannot delete it. Attempts to delete it will result in an error - "Object is in use."


Adding Tables to Optional Tabs

Once a new optional tab is created, tables need to be inserted into the tab. To add a table, double-click the new tab name in Dashboard Management and click the **Tables** tab. Click the **Create Dashboard Table** icon.

The table below lists the properties in the Create Dashboard Table for Table type.

Property	Description	Possible Settings
Name	Enter the name of the table	
API Name	You can specify an API name, but internal consistency is enhanced by accepting the system-generated name.	
Description	Enter the description of the table	
View List Type	Lists the type of table type. Select Table	Chart, Table, Custom, Advanced Search
Dashboard Extension (DX)	Lists all the dashboard extensions created for Table type list.	
Visible	To enable in Web Client	Yes/ No

Adding Data to Tables

Double-click the new table, click on **Attributes** tab and click on the **Add an Attribute**  icon to create a new attribute. Agile currently supports Text, Numeric, Image, Date, Money, and Link type of table attributes.

Note Attributes need to be of a specific type which is supported by Agile. While creating a DX, the data for the DX would already be defined as currency, numeric, text, and so on.

In the Column attribute General Information tab, the **Attribute** field needs to be mapped to the attribute name mentioned in the DX. For example, if an attribute name in the DX is Mytext and the attribute type is selected as Text, the attribute field should be mapped with the attribute name Mytext.

Adding Charts to Optional Tabs

To create a chart type table in a newly created optional tab:

1. In Dashboard Management, double-click the name of the new tab to open it.
2. In the **Tables** tab, click the **New Dashboard Table** icon.
3. Specify table fields and attributes as described in the table below:

Property	Description	Possible Settings
Name	Enter a name for the table.	
API Name	You can specify an API name, but internal consistency is enhanced by accepting the system-generated name.	
Description	Enter a description for the table	(optional)
View List Type	Lists the type of table. Select Chart (when you select Chart, additional options are displayed) .	Chart, Table, Custom, Advanced Search
Dashboard Extension	Lists all the dashboard extensions created for chart type. Select the dashboard extension you want.	
Visible	Select Yes to enable display in Web Client	Yes/ No
Chart Type	Select the type of chart you want displayed.	Area, Bar, Line, Pie, Polar, Scatter, Stacked Area, Stacked Bar, Table
X axis	Type the X axis label.	(optional)
Y axis	Type the Y axis label.	(optional)
Show Legend	Specify whether the chart legend should display on screen.	Yes/ No
Legend Position	Specify the position where the Legend should be displayed.	Bottom, default, left, right, top
3D Style	Specify whether the view should be 3-dimensional.	Yes/ No
Header	Enter a header note if required.	(optional)
Footer	Enter a footer note if required.	(optional)

Note For Stacked type Charts, the Chart DX can be coded with unlimited X- and Y-axis values.

Important In the **Dashboard Extension** field, all Chart type DXs will be displayed only if the user has the SDK license and if the DX was created as Chart type. There are two classes for creating Chart type dashboard extensions: 1. ChartDataModel, and 2. ChartDataSet. These classes should be used while creating Chart DXs. The saved Chart DX needs to be saved in the *agile_home/integration/sdk/extensions* folder and linked in the **Dashboard Extension** field. For further information on creating DXs, refer to Agile PLM SDK Guide

Adding Advanced Search to Optional Tabs

To create a dashboard table that uses an Advanced Search query as the data source:

1. In Dashboard Management, double-click the name of the new tab to open it.
2. In the **Tables** tab, click the **New Dashboard Table** icon.
3. Specify table fields and attributes as described in the table below.

Property	Description	Possible Settings
Name	Enter a name for the table.	
API Name	You can specify an API name, but internal consistency is enhanced by accepting the system-generated name.	
Description	Enter a description for the table.	(optional)
View List Type	Select Advanced Search.	Chart, Table, Custom, Advanced Search
Dashboard Extension		Disabled (not applicable for Advanced Search)
Visible	Select Yes to enable display in Web Client.	Yes/ No

Note When you select View List type as Advanced Search, the dialog box automatically displays fields applicable only to Advanced Search type table.

Configure Table for Advanced Search

Once the table is created, double-click the new created table and click the **Configure Dashboard Table**

icon in the General Information tab.

You can create a new or use a saved search. The Configure Table dialog is similar to the Advanced Search function of Agile except for a few differences as follows:


- Output Fields
 - The **Output Fields** option allows you to select the available fields as the X and Y axis values. Clicking the **Output Fields** button displays the Customize Output Display dialog. Select the required fields from the Available Fields list and click the left and right arrow buttons to move field names to and from the Available Fields and Selected Fields lists.
 - The **Display Chart** button allows a Chart and Table type display option. If Chart option is selected, the Configure Table dialog is displayed. You can do the following:
 - Select the Chart type.
 - Select the 3D style for Chart.
 - Show or Hide the Legend.
 - Select the position of the Legend to be displayed in the Chart.
 - Select the X axis value from the drop down list (which is displayed from the Customize Output field)
 - Label the header, footer, X axis and Y axis values on the chart
 - Perform a mathematical function for the Data values such as Average, Count, Max, Min, and Sum.

Adding Custom (URL) Process Extensions for Optional Tables

URL process extensions that are created with Dashboard as the integration point are listed in the Dashboard Extension field, while a Dashboard table with View Type List is created. The output of the URL process extension is displayed in the Dashboard table.

For more information, see the *Agile SDK Developer Guide*.

Reordering Table Rows in a Tab

You can reorder the tables in a tab from **Dashboard Management > [OptionalTab Name] > Tables > Config Dashboard** icon . The **Config Tab** dialog is displayed in which you can select all the tables from the Available Content field and place it in the required rows. There are only three rows; by default the new tabs are created in Row 3. You can reorder the tabs in the order of the rows to be displayed.

Displaying Optional Tabs

To ensure that all optional tabs that are newly created under **Systems Settings > Dashboard Management** display properly, go to **User Settings > Privileges > Dashboard Tab View** and enable each tab for end-

users in Web Client.

Select the New icon and type in a new privilege name and description. Set **Enabled** to **Yes**. All created tabs will be displayed in the **AppliedTo > Choices** field. Select the tabs you want displayed in the Dashboard and use the right arrow icon to move these to the **Selected** area. Any tab you choose can be set as the Home page.

Solution-specific Administration

This chapter includes the following:

- Documentation..... 303
- Configurable solutions for Administrator 303

Documentation

User guides for the PLM solutions contain a chapter for the administrator that deals with specific settings and configurations for each solution, and are mandatory reading for each solution purchased by your company.

For instance, every installation of PLM includes the solution called Product Collaboration. In the *Agile PLM Product Collaboration User Guide*, there is a chapter dedicated to the Agile administrator, not the end-user.

The Agile administrator should also become familiar with the end-user documentation as the manuals for end-users contain valuable information that assist the Agile administrator in grasping what the solution is all about and what the user experience incorporates.

Configurable solutions for Administrator

The solution-specific nodes and sub-nodes are the following:

Product Cost Management node folder

- Ship To Locations
- RFQ Terms and Conditions

Product Portfolio Management node folder

- Schedule Status
- Cost Status
- Quality Status
- Resource Status
- Default Role
- UI Configuration Data

Agile Content Service node folder

- Subscribers
- Destinations

Events

Filters

Package Services

Product Governance & Compliance node folder

Signoff Message

Compliance Rollup Scheduling

Compliance Rollup Role Setting

Supplier Declaration Process Extension

Specification Mapping

Note Product Collaboration is not seen as a solution folder, but is also a solution that requires configuration by the Agile administrator.

Event Management

This chapter includes the following:

▪ Introduction to Event Management.....	305
▪ Anatomy of Event Subscriptions.....	307
▪ Handler Types	312
▪ Event Types.....	313
▪ Working in Events Node	317
▪ Working in Event Handlers Node.....	320
▪ Working in Event Subscribers Node	323
▪ Sample Event Subscriptions	328
▪ Monitoring Events	329
▪ Control of Event Components.....	331
▪ More about Selected Event Types.....	333

Introduction to Event Management

Event Management allows Agile PLM customers to automate their business processes across the PLM suite of solutions. The Event Management framework provides the administrator with a flexible alternative to Process Extensions for extending Agile PLM.

This chapter describes the components of Event Subscriptions and how the administrator creates those components in the **Event Management** nodes. Two other chapters in this manual pertain to this robust new feature of Agile PLM:

- Event-based Notifications are created in the **Notifications** node and are documented in [Event-based Notifications](#) on page 281.
- [Scripting and Sample Events](#) on page 341 gives a brief introduction to the scripting capability and sample configured Event Subscriptions.

Also, *Agile PLM SDK Developer's Guide* provides technical documentation of the Event framework for the Agile administrator or assisting programmer. Event Management leverages the Agile SDK just as Process Extensions do, only with much greater flexibility and specificity to PLM business objects and user actions.

Preliminary Configuration

Access to the Event Management nodes

Ensure that your own User Profile has proper access to all six **Event Management** nodes via the **AppliedTo** property in the Administrator privilege mask.

Global Event control

Once you can access the **Event Management** node folder, still, the Event functions are initially disabled on all 9.3 PLM installations. When the administrator has configured Event Subscriptions and wants to commence their use by the system, Event triggers are enabled by the **Enable Triggering Events** button on the Admin toolbar. Only users with the Administrator privilege can see and use this button.

Caution It is highly recommended that Event Subscriptions and their various masks are first created and tested on a PLM Test system before introducing them into the Production system. With Agile Configuration Propagation (ACP, see separate manual), fully tested Event Management configurations can easily be transferred from Test to Production systems.

There is extensive control of the layers of Event Management; for more information, see [Control of Event Components](#) on page 331.

Once initially enabled, Event Management will start automatically when the Agile Application Server is restarted; this step does not need to occur again.

Systemwide Preferences that pertain to Events

Several systemwide Preferences must be set to govern some aspects of Event Management: *Agile Script Log Level*, *Event Maximum Nested Levels Allowed*, and *Event Monitor Log Level*. These are detailed in [Preferences Defined](#) on page 379.

Event Management Node Folder

These are the nodes in the **Event Management** node folder and a brief description of the purpose of each node.



Events node –

Create and manage Event masks.

Event Handlers node –

Create and manage Handler masks based on "Java PX" and "Script PX" handler types.

Notifications, the third handler type, are created and managed in **Notifications** node.

Event Subscribers node –

Create and manage Subscriber masks.

Event Types node –

Library of default Event Types (see [Event Types Defined](#) on page 314).

Event Handler Types node –

Library of default Handler Types (see [Event Handler Types](#) on page 312).

Event Handler Monitor node –

Review the status of transactions and results, such as messages or errors, from Handler transactions that have been invoked (see [Event Handler Monitor](#) on page 329).

About Process Extensions and Notifications Nodes

With the incorporation of the Events framework, PLM has two types of Notifications and multiple types of Process Extensions. Please note the distinctions and naming conventions below.

Default Notifications and Event-based Notifications

- *Default Notifications* are the "out-of-the-box" notification templates in the **Notifications** node. These Notifications are still useful, particularly before you have deployed Event-based notifications.
- *Event-based Notifications* are created in the **Notifications** node. A notification created in PLM 9.3.x has much more flexibility than a default notification. Most Event Subscriptions that are dedicated to notifications have a configured Notification mask for the Handler. See [Handler Types](#) on page 312.

Custom Process Extensions and Event-based Process Extensions

- *Custom process extensions* (Custom PX) is a general name for PXs created in **Data Settings > Process Extensions** node. These PXs have limited initiation capability, for instance, they can be added to objects' **Actions** menu. It may be preferable to maintain your Custom process extensions until you have developed and tested Java PX Event Subscriptions (outside your Production system).
- *Event-based process extensions* (Event PX) are created in the **Event Management** nodes. "Event PX" is a general term to contrast with "Custom PX", but we will be referring more to the specific kinds of Event-based PXs, namely, *Java PXs* and *Script PXs*.

Anatomy of Event Subscriptions

An *Event Subscription* is a single instance of an "administrator-configured event".

The Event Subscription provides complete instructions for an automation, including what kind of object is to be acted on, what actions will be taken, and what result or outcome will be accomplished by the system.

An Event Subscription, configured and ready to be invoked, consists of...

- an **Event mask** – *specifies the conditions under which an automation will be invoked*, includes an Event Type, an Object Type (often but not always), and additional attributes;
- and a **Handler mask** or a **Notification mask** – *describes the intended automated result*, a Handler mask is a configured Java PX or a configured Script PX; a Notification mask is a configured Notification;
- and a **Subscriber mask** – *binds a Handler to an Event*, a Subscriber names Event and Handler/Notification masks to work in tandem with additional attributes that refine the Event Subscription's behavior;

... and when the Event Subscription is invoked, the configured result is completed by the system.

As end-users perform normal actions in PLM, the default Event Types may be triggered dozens of times a day. However, nothing happens unless one (or more) Event Subscription gives the information to the system about what to do when an event type is triggered.

Note Be careful how you think of "Events" and "triggered Events". It is the Event Types that are triggered by user actions; but nothing happens unless a proper combination of the three masks are in place.

You cannot create "duplicate" Event masks, that is, there can be only one Event mask that names an Event Type–Object Type combination. However, Event and Handler masks are reusable, that is, they can be named by any number of Subscriber masks to create highly specific Event Subscriptions.

For every Event Subscription that you configure, you must be clear about the object type you want to affect – whether it is a subclass, or a class (and all of its subclasses), or a base class (and all of its "descendant" classes and subclasses).

Note There are several Event Types that are not specific to object types; this is the first category in the table in [Event Types Defined](#) on page 314.

So a "Create Object" Event mask for Items base class is triggered for the Parts and Documents classes and, in turn, their children subclasses. A "Create Object" Event mask for Parts class trigger for all subclasses of the Parts class. A "Create Object" Event mask for Part subclass triggers for that subclass only, not for other subclasses in the Parts class.

When you create the masks, an automatic naming capability provides a name that you can accept or modify; or, you can create your own name. For example, you may prefix mask names with a business process or subclass.

Note System-provided names follow internal conventions, but the provided name may not be unique and you may need to modify the provided name.

A naming system will be a benefit when you have stored many masks in your Event-node libraries. In any case, choose names that help you see at a glance what their use is.

Here is an example of names for three masks in a possible Event Subscription.

Let's say the administrator builds on the "Create Object" event type to specify "objects from the

Capacitor subclass". The name of the Event mask is:

[Create Object Capacitor]

Every Event mask names an Event Type, in this case the Create Object event type. This event type takes an object type (most of them do), so this Event mask specifies Capacitor, a subclass of the Parts class.

Now a Handler mask is created:

[New Part on ECO]

This handler's name gives the idea that a change order will be created with the new part associated with it. Also, you can see that this Handler mask will work with any Event mask that names a subclass of the Parts class, or the Parts class itself.

Finally, a Subscriber mask that names the Event mask and Handler mask is:

[Create Object Capacitor New Part on ECO]

When the system recognizes that a Capacitor was just created, and this Event Subscription is invoked, the Subscriber provides the specific instructions and the system runs the Handler that produces the desired outcome:

"Since a Capacitor was just created, now (automatically) create a new Change Order and add that new object on the ECO."

With this automation, the user does not have to create an ECO and associate it with the part; the user simply creates a part and soon after sees the system-generated ECO containing the part.

The names of the default Event Types (see [Event Types Defined](#) on page 314) give an idea of the range of automated Event Subscriptions in PLM that the administrator can create in the Event Management framework.


Event Subscription Components are Interconnected

This schematic depicts the connections between individual objects that are created in **Event Management** nodes.

For example, when you open an event type from the **Event Types** node, it has a **Where Used** tab that lists all event masks that use that event type. In the other direction, when you open an event mask from **Events** node, the field "Event Type" is a live link to the named event type object.

The rightmost element "Object Screen" represents any object type – each row in **Classes** node – and each and every object type has an **Event Subscribers** tab that lists all event subscribers that are associated to this object type (because a given subscriber names an event mask that names the object type).

Note For Event-based Notifications, a Notification mask is the Handler. The distinction between Handler mask and Notification mask is simply because they are created in different nodes in Administrator, namely, **Events Handlers** node and **Notifications** node.



Event Subscribers Tab on All Object Types

The **Event Subscribers** tab has been added to every base class, class, and subclass (default and administrator-created). When you create an Event Subscription that points to an object type, you can open the object type in **Classes** and see all its associated Subscribers under this tab.

This is also the best way to see which Subscribers are active or inactive, by using a dropdown filter with these values:

- **All** – displays both Active and Inactive subscribers, per the other criteria in the filtering process.
- **Active** – a subscriber can be Active if each of the three masks are enabled: the Subscriber mask itself is enabled, the Event mask it names is enabled, and the Handler mask or Notification mask it names is enabled.

In addition, the entire **Event Management** framework must be enabled (through **Admin** toolbar > **Enable Triggering Events** button), as well as the associated Event Type, Handler Type (all three), or Notifications (via **Server Settings** > **Database** > **Notification Enabled**).

- **Inactive** – a Subscriber mask may be enabled, but if either the Event mask or Handler mask that it names is disabled (or if base Event Type, Handler Type, or Event Management itself are disabled), the subscriber is considered Inactive; any disabled Subscriber is also Inactive.

The Inactive Reason field is automatically populated in every subscriber displayed by filtering for Inactive. The Inactive Reason field displays these various reasons:

- [Blank, no value] if the Subscriber is active;
- "Event triggering disabled" if the global **Event Management** control is disabled;
- "Event is disabled" if the Event mask is disabled;
- "Event type disabled" if the Event Type is disabled;
- "Handler type disabled" if the Handler Type (Java PX, Script PX, or Notification) is disabled;

- "Event handler disabled" if the Notification itself is disabled, or
- "Notifications are disabled" if global notifications are disabled.

Remember for any filtering of subscribers on a given object type, the hierarchy of base class, class, and subclass is in effect, as follows:

- If you open a base class, you see those handlers available to that base class (through subscribers).
- If you open a class, you see those handlers available to that class and its parent base class (through subscribers).
- If you open a subclass, you see those handlers available to that subclass, its parent class, and its parent base class (through subscribers).

Handler Types

The **Event Handler Types** node contains a library of the available Handler Types. Currently there are three handler types, which are described below; first, this table clarifies some terms used with regard to Event Handler Types.

Category of Handler Type	Handler Type	Kind of Mask	Where created & managed	Comment
PX-based Handler Types	Java PX	Handler mask	Event Handlers node	When you create a Handler mask, only Java PX and Script PX are in dropdown menu for selection.
	Script PX			
Notification-based Handler Type	Notification	Notification mask	Notifications node	"Create" in Notifications node creates a Notification mask. These can be associated with Event and Subscriber masks, or they can be triggered by Java PX or Script PX handler.

The Handler Type dictates the form that the Handler's instructions will take. The Handler mask or Notification mask identify what to invoke when the related Event mask has been invoked.

Process Extension-based Handler Types

Java Process Extensions

A Java Process Extension (**Java PX** or **jPX**) is a Java class deployed on the Agile Application Server. The Java PX handler type allows you to trigger compiled Java code. Compared with Custom PXs (created and stored at **Process Extensions** node), the Events framework gives Java PXs much greater potential for your targeted automations.

Java PXs are stored on the Agile Application Server directory structure. Refer to *Agile PLM SDK Developer's Guide* for information about writing Java PX code and deploying PXs.

Script Process Extensions

The Script PX handler type (**Script PX** or **sPX**) – a new form of process extension in Agile PLM – allows you to store code directly in the system database. The script is always visible and can be edited right in the Handler mask.

Important Groovy is the only scripting language that is supported in Agile PLM 9.3.x.

Scripting is introduced to the administrator in [Overview of Scripting in Agile PLM](#) on page 341, and there is substantial information for the developer about scripting in *Agile PLM SDK Developer's Guide*.

Notification-based Handler Type

Notification Masks

Admin-created Notification masks work in conjunction with the Event framework. Use the **Notifications** node to create Notification masks, as well as manage the Default notifications.

In an Event Subscription whose outcome is a notification, the Subscriber mask names the Notification mask, rather than a Handler mask (example: [Notify when Affected Items Table is Modified](#) on page 351). Notification masks also can be triggered by Java PX or Script PX handler (example: [Notify Create User when Item is Incorporated](#) on page 346).

Details about Handler masks, their attributes, and related business rules are taken up in [Working in Event Handlers Node](#) on page 320. Notification masks are detailed in [Notifications](#) on page 279.

Notes on Event Handler Types Node

When you double-click to open a handler type, the **General Information** tab contains just a few attributes: Name, API Name, and Description are all uneditable.

All handler types are enabled by default, and they can be enabled and disabled (see [When a Handler Type is Disabled](#) on page 332).

On the **Where Used** tab of the handler types:

- Java PX – lists all Handler masks that are based on the Java PX handler type.
- Script PX – lists all Handler masks that are based on the Script PX handler type.
- Notifications – lists all Event-based Notification masks.

The rows in these **Where Used** tables are active links so you can "click" directly to a specific Handler mask.

Event Types

The **Event Types** node lists all of the supported Event Types. The event types are enabled out of the box, and you can disable and re-enable them at any time. See [Control of Event Components](#) on page 331.

Use the list in **Event Types** node to see what user actions can be the starting point for automated Event Subscriptions. Because the event types name what the system is "triggering," it may also help to think of the event types as the points in PLM where Handler masks are invoked.

The Name of each event type begins with the action (or verb, for example, Approve) and a target (or noun, for example, Workflow, so, **Approve for Workflow**). If you click the Description column header, the event types sort by the *targets*, alphabetically (so, **Workflow, Approve for**), ascending or descending.

The **Where Used** tab lists all Event masks that are associated with that event type. These rows are active links so you can go directly to a specific Event mask.

Default Event Types

The following table lists all of the event types that are available to create Event masks. The default event types can be categorized in four groups to help understand their scope:

- **Global event types** – do not apply directly to PLM object types
- **Generic Object-based event types** – apply to all PLM object types
- **Specific Object-based event types** – apply to specific PLM object types
- **Workflow-based event types** – apply to all Workflow objects

The purpose of each event type is described by what user action will trigger the event type (right column) and by the PLM base class it applies to (center column).

Information about selected event types beyond the scope of this table is presented in [More about Selected Event Types](#) on page 333.

Event Type	Applies to these PLM base classes	Event type is triggered by this end-user Action (or system action or through SDK)
<i>Global Event Types</i>		
Scheduled Event	(Global event types do not apply directly to PLM base classes.)	There is a Schedule Event Task that controls the execution of this event type. See Task Configuration on page 392 > Schedule Event Task .
Export Object		Action > Export , or whenever the Export utility is opened.
Extend Tools Menu		Event triggered from the Tools Menu.
Transfer Authority		Transfer Authority is added, removed, or changed.
<i>Generic Object-based Event Types</i>		
Extend Actions Menu	All base classes	Creates link or action, or something that can be activated from a business object's Actions menu.

Event Type	Applies to these PLM base classes	Event type is triggered by this end-user Action (or system action or through SDK)
Create Object	All base classes	An object is created; this does not include objects that are created by the "Save As" method of object creation (see Save As Object).
Delete Object	All base classes	An object is Deleted.
Save As Object	All base classes	An object is created by Actions > Save As , which creates a copy of the current object.
Check In Files	All base classes except Reports; also excludes Automated Transfer Orders class	A File Folder is checked in, either from direct action on the file folder or through an object's Attachments tab. The Replace File action is part of checkin and will not generate an Update Table event on the file folder.
Check Out Files	All base classes except Reports; also excludes Automated Transfer Orders class	A File Folder is checked out, either from direct action on the file folder or through an object's Attachments tab. From Web Client, the Checkout action creates a separate Get File action and event.
Cancel Check Out Files	All base classes except Reports; also excludes Automated Transfer Orders class	A File Folder checkout is canceled, either from direct action on the file folder or through an object's Attachments tab.
Get File	All base classes except Reports; also excludes Automated Transfer Orders class	A user requests to Get a file; this can occur through use of the Get button or if selecting the filename causes a Get action.
Update Relationship	All base classes	A user adds, removes, or directly edits a Relationship on an object's Relationships tab; editing includes either updating the Relationship Rule or editing a field on the row.
Update Table	All base classes; however, certain tables are not supported.	A user modifies a table on a business object, for example, on Items' BOM tab, or Changes' Affected Items tab. See details and exceptions in Update Table on page 335.
Update Title Block	All base classes	A user directly edits any fields on an object's Page1 , Page2 , or Page3 .
Specific Object-based Event Types		
Change Status for Sourcing Object	Requests For Quote, Sourcing Projects	A user performs Action > Change Status on a PCM-solution object, also from the RFQ tab of Sourcing Projects.
Compliance Rollup on Object	Items, Mfr.Parts, Part Groups, Declarations	A manual or scheduled rollup commences, e.g., when user performs Action > Calculate Compliance on the object, or when the declaration's workflow

Event Type	Applies to these PLM base classes	Event type is triggered by this end-user Action (or system action or through SDK)
		changes status (manually or automatically).
Incorporate Item	Items: Parts and Documents	A user selects Action > Item Incorporate .
Unincorporate Item	Items: Parts and Documents	A user selects Action > Item Unincorporate .
Purge Version Files	File Folders	A user selects Action > File Folder Purge .
Workflow Object-based Event Types		
Approve for Workflow	Changes, Declarations, Programs, PSRs, QCRs, Transfer Orders, Packages, File Folders	A user approves a workflow
Audit for Workflow		A user initiates a Status Audit or a Release Audit on a workflow using Actions > Audit Status or Actions > Audit Release . (System audit does not trigger it.)
Change Approvers or Observers for Workflow		A user adds an Approver/Observer to, or removes Approver/Observer from, the Workflow tab. This event type is not triggered when Approver/Observer is added or removed via Routing Slip.
Change Status for Workflow		A workflow moves from one status to another, either by user action, or by autopromotion, or by forced change due to Relationship rule.
Comment for Workflow		A user comments on a workflow.
Escalation for Workflow		A workflow has been in a status awaiting signoff longer than the period defined by Review Escalation Period on the status.
Promotion Failure for Workflow		A system-initiated workflow status promotion fails; promotion failures can occur due to autopromotions or Relationship triggers.
Reject for Workflow		A user rejects a workflow.
Reminder for Workflow		A workflow has been in a status awaiting signoff longer than the period defined by Reminder Period on the status.

Additional information about selected event types is presented in [More about Selected Event Types](#) on page 333.

Multiple Triggers from Single Action

Generally one user action in a PLM client will trigger one event type; however, there are many

actions in PLM that trigger secondary actions, and this fact accounts for how a single user action may trigger more than one event type.

For example, on an item's Actions menu is **Create Change**. When a user selects this action, the Create Object event type is triggered. Meanwhile, when PLM creates the change order associated with the original item, it automatically adds the item to the change's **Affected Items** table, and so the Update Table event type is also triggered.

Here are some additional examples of this:

- Item > **Actions** > **Create Declaration**: triggers Create Object and Update Table (the **Parts** table on the new Declaration) event types;
- QCR > **Actions** > **Create Change**: triggers Create Object and Update Relationship (the **Relationships** tab on the new change order) event types;
- Change object > **Actions** > **Bulk Change**: triggers Update Table (the **Affected Items** table on each new Change, one for each item that is "affected") and Update Table (for each **BOM** or **Manufacturers** table that is redlined on each affected item);
- Checking out a file triggers Checkout File and Get File event types;
- Checking in a file on Agile object (except File Folder) triggers Checkin File and Update Table (Attachments) event types; Modify action if the folder version of the attachment is not the latest; Update Table event type is not triggered if the folder version is set to the latest;
- Action > Create File Folder triggers Create Object and Checkout File event types;
- In Java Client, adding two URLs to a File Folder triggers two events (adding two URLs to any other business object, only one event is triggered; note also that the user can add two URLs to a File Folder in Web Client, only one event is triggered).

User \$AGILEUSER

The following three event types, when used in an Event mask, work in the background:

- Scheduled Event
- Escalation for Workflow
- Reminder for Workflow

For them, the Handler will be invoked as \$AGILEUSER. By default, this user is a PLM-system user with many roles assigned, *even though it is not available in the Administrator user interface* (for example, ACS uses it). As a result, if the Handler doesn't have a role assigned, these "invisible" roles that are assigned to \$AGILEUSER are used when running the Handler.

Working in Events Node

The **Events** node is where you create and manage Event masks.

Attributes of Event Masks

The table below lists attributes found on the **General Information** tab in Event masks.

All Event masks must name an Event Type. Most Event masks must name an Object Type (excepting those that name one of the "Global" event types).

Note System-generated names are a helpful feature when creating Event masks and Subscriber masks. The **Name Helper** button can be used: it concatenates Event Type and Object Type (as long as you select them before you manually enter a Name) to generate a Name and API Name.

Additional attributes may appear in the Create dialog as certain event types and object types are selected; these are given general mention in this table. "Additional attributes" are also noted by event type in [More about Selected Event Types](#) on page 333.

The **Where Used** tab lists all Subscriber masks that use the Event mask.

Attribute	Description
Event Type	Event type categorizes what user action will trigger the event. In a configured Event mask, this field becomes uneditable. " Event Type " itself is a live link: click it to go to the event type.
Name	Name of the Event mask. You can specify the name, but it is best if the name includes the event type and object type. If you populate Event Type and Object Type fields first, the Name Helper button produces a system-generated name (see Note above this table).
API Name	Name of the object that is used by external processes to identify the object. You can specify an API name, but internal consistency is enhanced by accepting the system-generated name once you have specified the Name of the Event mask. See API Name on page 19.
Description	Enter a useful description of the Event mask. Descriptions are searchable.
Enabled	Value is Yes or No; see Control of Event Components on page 331.
Object Type	Object Type specifies what kind of business object is being acted on (by the user's task) for the event to be triggered. (Exception: when a workflow is selected as the object type of an Event mask, the system uses the object type of the first Matching Criteria property of the workflow. See More about Workflow-based Event Types on page 336.) Only object types that support the Event Type may be selected. Note: The Global event types take no object type: Scheduled Event, Export Object, Extend Tools Menu, Transfer Authority.
Workflow	Appears only if a workflow-specific event type is selected. See More about Workflow-based Event Types on page 336. Specify a workflow in the system, or <All> workflows. (<All> is not available for the Change Status for Workflow event type.)

Attribute	Description
	If <All> is chosen, Object Type attribute becomes uneditable.
Status – from	Appears if Change Status for Workflow event type is selected; choose one or multiple statuses, or <Any> status.
Status – to	Appears if Change Status for Workflow event type is selected; choose one or multiple statuses, or <Any> status.
Action	Appears and lists appropriate actions for some event types; the list of actions may also be modified by selected object type.
Source Object	Appears only for the Update Relationship event type; names one or multiple object types as source of the relationship ("relating to"). See Update Relationship on page 335.
Target Object	Appears only for the Update Relationship event type; names one or multiple object types as target of the relationship ("related from"). See Update Relationship on page 335.
Frequency	Appears only for the event type Scheduled Event; the dropdown is a scheduling utility (similar to Frequency property for Scheduled Event under Events of ACS). See Scheduled Event on page 333.
Table Name	Appears only for Update Table event type; list of tabs/tables pertains to selected object type. See Update Table on page 335.

Checklist for Creating an Event Mask

This is a checklist of questions to ask (of, perhaps, a company Change Analyst or Product Analyst) and have answered when you begin to create Event Subscriptions and, more specifically, when you create any Event mask.

- For my company's installed PLM solutions – and routine tasks performed by Agile users – what are all the PLM Actions that I want to automate the system? Are there any automations needed to supplement actions such as Create, Save As, Update Title Block, Update Table, or by other object behaviors (that are represented by the event types)?
- From a given event type being triggered, what is the result that we want to automatically happen?
- What is the proper object type that this Event mask will apply to? You may need to ask: will the Handler or Notification (the outcome of this automation) apply to a specific subclass or subclasses? Can the handler apply to all the subclasses for a class and/or base class?
- If the event involves a Change, which Workflow(s) does it apply to? Does it apply to all workflows or a specific workflow?
- Are there any Event Type–specific parameters to consider? For example, for the event type Delete Object Action, is the Handler mask going to handle soft deletes or hard deletes?

Creating an Event Mask

To create an Event mask:

1. Open the **Events** node and click the **New** button. The new Event mask object appears.
2. In the Event Type field, use the dropdown arrow to select an event type. Use the information in [Event Types Defined](#) on page 314 and [More about Selected Event Types](#) on page 333 to base your choice.
3. In the Object Type field, use the dropdown arrow to select an object type.

It is possible to select a disabled object type, so you must be clear about the status of all object types in your PLM system (the **Classes** node).

If the event type you selected applies to workflows, the Workflow field appears: select the appropriate workflow and then, if Object Type is enabled, an appropriate object type.

Selection of object type may have also caused the Action field to appear, in which case it is required.

Important If you intend to create an Event mask whose Handler is a notification (sent by email to selected users), the object type of the Event mask must be appropriate for the object type of the Notification mask. For example, if the Notification mask specifies Change Orders (a class), the Event mask must specify the class or ECO (subclass) or any other subclass derived from the Change Order class. For Update Relationship event type, the Notification object type must match the Source object type (or the common object type if there is more than one Source object type) of the Event mask.

4. At the Name field, click the **Name Helper** button to the right; the system uses the event type and object type names to generate a standard name for the Event mask.
5. Accept the auto-generated API Name. You can enter your own API name, but it is recommended to let the system's name stand for naming consistency.
6. Fill in a description.
7. In the Enabled field, accept Yes or select No.

Note A disabled Event mask cannot be invoked; any Subscriber mask that names an Event mask that is disabled will itself be Inactive.

8. Click **OK** to save the configured Event mask.

Working in Event Handlers Node

The **Event Handlers** node is where you create and manage Handler masks that are based on the Java PX or Script PX handler types.

Note Here are a couple of tips for quick sorting in the Filter (which becomes more useful as you accumulate Handler and Notification masks).

In Event Handlers node: if you set **Filter By** to Handler Type and **Match If** to Starts With, in the field you can simply type "j" or "s" for all Handler masks based on Java PX or script PX handler types, respectively.

However, in **Event Handlers** node, typing "n" for Notifications does not return the Notification masks; instead, open **Event Handler Types** node, open Notifications handler type, and look under the **Where Used** tab for that list; or, open **Notifications** node itself.

Attributes of Handler Masks

The table below lists attributes found on the **General Information** tab in Handler masks.

The **Where Used** tab on a Handler mask lists all Subscriber masks that point to the Handler mask.

Attribute	Description
Handler Type	Java PX or Script PX. In a configured Handler mask, this field becomes uneditable; however, "Handler Type" has become a live link: click it to go to the handler type.
Name	Name of the Handler mask: you specify the name (there is no Name Helper as in other parts of these masks). It is recommended that the name describes what the purpose or result of the Handler is.
API Name	Name of the object that is used by external processes to identify the object. You can specify an API name, but internal consistency is enhanced by accepting the system-generated name once you have specified the Name of the Handler mask. See API Name on page 19.
Description	Enter a description that is useful; descriptions are searchable.
Enabled	Value is Yes or No; see Control of Event Components on page 331.
Role	Select one or more roles to override the user's default roles when the system executes the Handler. See Roles in Handler Masks on page 321.
Event Action	Appears if handler type is Java PX. The dropdown list allows the user to pick from a list of Java PXs that have been deployed and are available in the system. Note that the completed Events-based process extension itself is deployed in the same manner that you deploy Custom PXs.
Script	Appears if handler type is Script PX; the script code is pasted into this field; for more information, see Editing Scripts in the Handler Mask on page 343 and Introduction to Scripting in Events on page 341.

Roles in Handler Masks

The PLM Roles that are specified in Handler masks determine what roles are taken into account by the system when running the Handler.

If no role is specified in the Roles attribute, the Handler is run with the system observing the assigned role(s) of the user who performed the original action (that triggered the Event Type that is named by the Event mask that has been invoked in the current Subscription).

Whereas, If the Roles attribute is populated, the Handler is run with the system observing only the roles specified in that field, which essentially overrides the user's roles for the actions dictated by the Handler.

With no overriding role specified in the Handler mask, an error condition will occur if that user does not have sufficient privileges to perform the action (or some partial action) dictated by the Handler.

In this way, the administrator uses the Roles attribute to guarantee that the Handler can complete all of its specified actions.

Checklist for Creating a Handler Mask

This is a checklist of questions to ask and have answered when you create a Handler mask. These items can also serve as a communication vehicle between yourself and a programmer who is tasked to create Java-based PXs and Groovy script-based process extensions.

- Do I already have configured Event masks? What Event mask am I trying to handle?
- Is this a notification or a process extension? That is, what broad result does the Handler need to accomplish? What kind of instructions must the system have to complete a successful automation?
- If the Handler is to be a notification, has the Notification mask already been created (in **System Settings > Notifications**)?
- If the Handler is to be a process extension, what is the proper handler type for this Handler mask?
- Who is providing the Java code, SDK or Groovy script that will drive this Handler mask?
- Has the Java process extension been developed and tested? Is it properly deployed so the Java PX Handler mask will be able to find it?
- What Roles are needed to run the handler mask? Will the user performing the PLM action always have the right Roles?

Creating a Handler Mask

To create a Handler mask:

1. Open the **Event Handlers** node and click the **New** button. The new Handler mask object appears.
2. In the Event Handler Type field, choose Java PX or Script PX.

Remember that while Notifications are categorically a handler type, Notification masks are created in **Notifications** node and thus are not offered as a choice when creating a Handler mask.

If you select Script PX, the Script field appears with this default Groovy script:


```
import com.agile.agileDSL.ScriptObj.IBaseScriptObj
// add other import statements here
void invokeScript(IBaseScriptObj obj) {
//script body starts here.
}
```

3. In the Name field, enter a name.
4. Accept the auto-generated API Name.
5. In the Role field, enter the roles that will permit the Handler to be run as. If a role is specified here, it overrides the original user's roles when the Handler is executed. See [Roles in Handler Masks](#) on page 321.
6. Enabled should be set to Yes if you want this Handler mask to be available for Event Subscriptions.
7. Script field: paste in the script for this handler. (You can create the Handler mask without providing a script yet; in this case it is better to set Enabled to No.)
8. Click **Validate Script** to make sure the script will run properly.
9. Click **OK** to save the configured Handler mask.

Working in Event Subscribers Node

The **Event Subscribers** node is where you create and manage Subscriber masks.

The Subscriber binds (by naming) an Event mask and a Handler mask, and provides concrete "How" and "When" information about the automated outcome with such fields as Trigger Type (Pre- or Post), Execution Mode (Synchronous or Asynchronous), Order and Error Handling Rule; all of these are defined later in this section.

You can create more than one Subscriber mask that names a given Event mask. A second Subscriber mask naming the same Event mask would name a different Handler mask. In this case, when this Event fires, more than one Handler will be executed. The Subscriber can specify the order for the system to run the Handlers (Order), as well as how to handle error cases (Error Handler Rule).

Note Here are a couple of tips for quick sorting in the Filter (which becomes more useful as you accumulate Handler and Notification masks).

In **Event Subscribers** node, if you set **Filter By** to Handler Type and **Match If** to Starts With, in the **Value** field you can simply type "j" or "s" to return all Subscribers with a Handler mask based on, respectively, *Java PX* or *Script PX* handler types. In this node, you also can enter "n" and Subscribers with a Notification mask are returned (unlike in the **Event Handlers** node).

Filtering in Dialogs during Create Subscriber

When you create a subscriber mask, two dialogs offer similar filtering attributes, which are mentioned here for comparison.

- **Event [Mask]** field dropdown arrow brings up the **Select Event [Mask]** dialog, in which you can **Filter By**:
 - Name [of Event masks]
 - Event Type
 - Object Type
- **Event Handler [Mask]** field dropdown arrow brings up the **Select Event Handler [Mask]** dialog, in which you can **Filter By**:
 - Name [of Handler masks or Notification masks]
 - Handler Type
 - Object Type

In this second dialog, if **Filter By** is Handler Type, and **Match If** is Starts With, in the **Value** field this dialog returns the appropriate Handler or Notification masks when you type "j" (*J*ava PX Handler masks), "s" (*S*cript PX Handler masks), or "n" (*N*otification masks).

It may be said explicitly (as these filters imply) that the selectable Event mask and selectable Handler mask must be compatible. This point may help explain why some Event masks or Handler masks do not show up as you construct the Subscriber mask.. Other compatibility concerns come up with Subscriber attributes such as Trigger Type and Execution Mode; they are suggested in the definitions of Subscriber attributes below and in sections after the table.

Attributes of Subscriber Masks

The table below lists attributes found on the **General Information** tab in Subscriber masks.

Subscriber masks also have a **Monitor** tab, which provides a view of the row for the current Subscriber mask from the **Event Handler Monitor** (described in [Event Handler Monitor](#) on page 329).

Attribute	Description
Name	Name of the Subscriber mask: it can be system-generated the Event (mask) and Event Handler (mask) fields are given values
API Name	Name of the object that is used by external processes to identify the object. You can specify an API name, but internal consistency is enhanced by accepting the system-generated name once you have specified the Name of the Subscriber mask. See API Name on page 19.
Description	Enter a description that is useful; descriptions are searchable
Enabled	Value is Yes or No; see Control of Event Components on page 331
Event	Name of Event mask bound by this Subscriber mask: use dropdown arrow to bring up Select Event dialog to filter and choose Event mask. In a configured Subscriber mask, although this field remains editable (because you can modify the Subscriber to point to another Event mask), " Event " has become a live link: click it to go to the designated Event mask itself.
Event Type	Appears (uneditable) in the saved Subscriber mask from the selected Event mask
Object Type	Appears (uneditable) in the saved Subscriber mask from the selected Event mask

Attribute	Description
Event Handler	<p>Name of Handler mask bound by this Subscriber mask: use dropdown arrow to bring up Select Event Handler dialog to filter and choose Handler mask.</p> <p>In a configured Subscriber mask, although this field remains editable (because you can modify the Subscriber to point to another Handler mask), "Event Handler" has become a live link: click it to go to the designated Handler mask itself.</p>
Handler Type	Appears (uneditable) in the saved Subscriber mask from the selected Handler mask
Trigger Type	<p>Pre – invokes the Handler before the action (described by the event type named in the Event mask) occurs.</p> <p>Post – invokes the Handler after the action (described by the event type named in the Event mask) occurs. "Post" is generally the more applicable setting.</p> <p>See Trigger Type: Pre and Post on page 326 and Trigger Types and Execution Mode on page 326.</p>
Execution Mode	<p>Asynchronous – the transaction completes and the interface control is returned to the user while the Handler is executed in a different thread in the background.</p> <p>Synchronous – the user waits for interface control to return until after the handler completes and then handler is executed in the same thread.</p> <p>If Trigger Type is Pre, Execution Mode can only be Synchronous.</p> <p>See Execution Mode on page 326.</p>
Order	<p>A number (integer) that sets the sequence of synchronous events.</p> <p>Applies to synchronous Subscribers only.</p> <p>See Order and Execution Mode on page 326.</p>
Error Handling Rule	<p><i>The basic definitions of Continue and Stop are elaborated below.</i></p> <p>Continue – If there is an error during the execution of a Handler with synchronous execution mode, the error is ignored.</p> <p>Stop – If there is an error during the execution of a Handler with synchronous execution mode, the original action and the Event Subscription is ceased.</p> <p><i>When Execution Mode is Synchronous:</i></p> <ul style="list-style-type: none"> ▫ When the Handler is Pre and Synchronous – Continue allows remaining Handlers and the transaction to continue; Stop ceases remaining handlers and the transaction. ▫ When the Handler is Post and Synchronous – Continue allows remaining Handlers to continue; Stop ceases remaining synchronous Handlers. <p><i>When Execution Mode is Asynchronous:</i></p> <ul style="list-style-type: none"> ▫ When Execution Mode is Asynchronous, the Error Handling Rule is disabled; the Event Subscription runs, the PLM transaction has already occurred, so the user sees a successful result.

Trigger Type: Pre and Post

Pre and Post are settings for the Subscriber mask attribute Trigger Type. The familiar prefixes "pre" and "post" are used to mean, respectively, before and after. In configuring Event Subscriptions, you must choose whether you want the Event Subscription to be run before or after the transaction.

- **Pre**(-event) trigger types signal a point just **before** the system starts the transaction for the PLM action that the user requested. A Subscriber with a Pre trigger type can be used to prepare objects or data for a subsequent, upcoming action; or to validate objects or data.
- **Post**(-event) trigger types signal a point just **after** the system completes transaction for the PLM action that the user requested. A Subscriber with a Post trigger type can be used for notifications, reminders, escalations, or to perform some auditing tasks based on an earlier action (such as tasks accomplished by Pre-event Subscribers); or external-system integration tasks.

Notification masks are handled only by Post-type Event Subscriptions.

This discussion only defines these terms; you may consult the schematic called "Triggering and Processing an Agile PLM Event" in Chapter 24 of *Agile PLM SDK Developer's Guide*.

Execution Mode: Synchronous or Asynchronous

Event handlers can be run either asynchronously or synchronously.

Generally, *asynchronous* means "not occurring at the same time" and *synchronous* means "occurring at the same time".

In Event Management, an asynchronous Handler means the Handler is executed in a separate thread, and the original thread does not wait for the Handler to finish (that is, it is not blocked). A synchronous Handler is executed in the same thread as the initiator, and it waits for the Handler to finish.

Trigger Types and Execution Mode

The choice of the handler's Execution Mode varies based on the choice of Trigger Type:

- Pre-event triggers support only those handlers that can be run synchronously.
- Post-event triggers support handlers that can be run both asynchronously and synchronously.

Notifications are always Post trigger type and Asynchronous execution mode.

Note	Be sure to read the nuances about Pre, Post, and Synchronous in "Error Handling Rule" in the above table.
-------------	---

Order and Execution Mode

For synchronous Subscribers, either pre or post, the Order value is used to determine the sequence of calling handlers.

For example, if there are three Subscriber masks that trigger based on a user creating a part. These could have been triggered because of Event masks that name the object types Items (base class), Parts (class), or Part (subclass).

The system evaluates all three Subscribers together: it sorts first by values for Order, so if you entered 1, 2, and 3, respectively, in these three Subscribers, the system knows which one to act on first, and so on.

If Order has no values or the same value, the system resorts to selecting Subscriber names in alphabetical order to determine the sequence of calling Handlers.

Again, you may consult the schematic called "Triggering and Processing an Agile PLM Event" in Chapter 24 of *Agile PLM SDK Developer's Guide*.

Checklist for Creating a Subscriber Mask

Here are some questions to be answered when you set up a Subscriber mask. The attributes in the Subscriber mask may have been already considered when you set up the Event and Handler masks.

- Do I have all the relevant Subscribers to support my Event masks and Handler masks?
- What Event mask is being named in this Subscriber mask? What is the event type that you are interested in?
- What Handler mask or Notification mask is being named in this Subscriber mask? What Handler do you want invoked when the event type of interest is triggered?
- Which Trigger Type should be used, Pre or Post? Why do you want the Handler to invoke Pre or Post?
- Which Execution Mode should be used, Asynchronous or Synchronous?
- What is the Order in which the Handler mask should be invoked?
- What Error Handling Rule should be used?
- Am I certain that all elements of this Event Subscription are enabled? Can I verify that this Subscriber mask is Active? (See [Event Subscribers Tab](#) on page 311.)

Creating a Subscriber Mask

Note System-generated names are a helpful feature when creating Event masks and Subscriber masks. The **Name Helper** button can be used: when you create a Subscriber mask, the system concatenates selected Event mask name and Handler mask name (as long as you select them before you manually enter a Description, in which case the system uses the Description to generate the name, with a limit of 150 characters).

To create a Subscriber mask:

1. Open the **Event Subscribers** node and click the **New** button. The new Subscriber mask object appears.
2. At the Event field, use the dropdown arrow to bring up Select Event dialog.

Use **Filter By** and **Match If** criteria (see [Filtering in Dialogs during Create Subscriber](#) on page 323) to return Event masks, and select one.

3. At the Event Handler field, use the dropdown arrow to bring up Select Event Handler dialog. Use **Filter By** and **Match If** criteria (see [Filtering in Dialogs during Create Subscriber](#) on page 323) to return Handler masks or Notification masks, and select one.

Important If you are creating an Event Subscription whose outcome is a notification (sent by email to selected users), the object type of the Event mask must be the same as the object type of the Notification mask. This is a good time to verify that this condition is met by the Event mask (designated in step 2) and the Notification mask (designated in this step).

4. At Name field, click the **Name Helper** button to the right; the system uses the Event mask and Handler mask names to generate a standard name, as well as the API Name. If the system-generated name is not sufficient, you may change it.
5. A new Subscriber mask is enabled by default; you can set Enabled field to No, but of course it will not run the Subscription until it is enabled.
6. At Trigger Type field, select Pre or Post.
7. At Execution Mode field, select Asynchronous or Synchronous.
If Trigger Type is Post, Execution Mode field is automatically set to Asynchronous.
Post and Asynchronous are the correct settings for notification-specific Event Subscriptions.
8. If appropriate, at Order field, give an order number.
9. Similarly, if an Error Handling Rule is required, select one.
10. Click **OK** to save the configured Subscriber mask.

Sample Event Subscriptions

The next chapter introduces scripting for the administrator and presents five sample Event Subscriptions, including the script, as appropriate.

- [Update Item Description](#) on page 345

This Event Subscription updates an item's Description when a user updates the **Title Block** of any business object from one of all the Parts-class subclasses.

- [Notify Create User when Item is Incorporated](#) on page 346

This Event Subscription creates a notification and sends it to the user who created that part or document when an item – an instance of any subclass in the Parts or Documents subclass, and therefore of the Items base class – is incorporated. Note that this notification is generated by instructions from a script (a Script PX handler), rather than a Notification mask created by the administrator (as in last example below).

- [Set Change Analyst](#) on page 347 when ECO changes status

This Event Subscription automatically sets the Change Analyst when an ECO changes status to Submitted.

- [Add Document to New Part](#) on page 349
This Event Subscription automatically creates a Document and adds it to the Assembly BOM any time a part is created.
- [Notify when Affected Items Table is Updated](#) on page 351
This Event Subscription automatically sends a notification (created in **Notifications** node) any time the **Affected Items** table of a Change is updated.

Monitoring Events

The **Event Management** framework provides several means to monitoring handlers and subscribers, or troubleshooting problems with triggered events:

- **Event Handler Monitor** node is a monitor of event activities; it is detailed below;
- An Event-specific log file; see [Event Log File](#) on page 330;
- Runtime error messages are presented in an error dialog; and,
- Execution of Java PX, Script, or Notification is logged on the object's **History** tab.

Event Handler Monitor

The **Event Handler Monitor** keeps track of which Handlers have been run as a result of events being triggered. The administrator can see how many handlers have been invoked and how many are still running. For each Handler, the administrator can see when it was invoked, what Event mask was involved, the Handler's current status, when it finished, explicit return messages from the Handler, or exceptions if something is wrong.

The systemwide Preference **Event Handler Logging** can be set to log all invoked Handlers (*All*), to log only errors (*Error*), or turned off (*Off*).

When you open **Event Handler Monitor** node, use the filter bar (table search) to return existing event masks. The **Filter By** attributes in the **Event Handler Monitor** node are:

- Event [that is, name of Event mask]
- Event Handler [that is, name of Handler mask or Notification mask]
- Event Subscriber [that is, name of Subscriber mask]
- Status
- Object

Attributes of Event Handler Monitor

This table defines the Event Handler Monitor attributes. Note that each Subscriber mask has a monitor view that shows essentially the same information, only for Handlers named by that Subscriber.

Attribute	Definition
Event Type	The event type of the triggered Event mask
Event	Name of the Event mask
Handler Type	The handler type of the designated Handler mask
Event Handler	Name of the Handler mask
Event Subscriber	Name of the Subscriber mask
Trigger Type	Whether the Event Subscription is to be run before or after the transaction
Execution Mode	Whether the Handler is to be run synchronously or asynchronously
Object	The specific business object on which the Event was triggered
Start Time	When the Handler begins to run, displayed in the user's Time Zone
Stop Time	When the Handler has finished running, displayed in the user's Time Zone
Owner	The end-user whose action triggered the Event
Status	These are the values for Status and what they mean: Running – handler is in progress Completed – handler has finished Failed – handler did not finish Queued – waiting to be run, only applies to asynchronous handlers Unknown – handler failed but the reason is unknown Submit for Notification – status for Notification handler
Message	The result message that is returned by the handler mask
Thread ID	ID of thread for which the Handler runs
Event Count	Tracks the level of "nested" events, that is, events triggered by an event (not a user's action). The allowed maximum of nested events is defined in the systemwide preference "Event Maximum Nested Levels Allowed".

Event Log File

In addition to the Event Handler Monitor, Agile PLM also provides an Event Log file, **SOAEvent.log**. It records all event-related activities occurring in the application.

This log file is configured in **Log.xml**, which is established at Install time. The "log level" can be configured from log.xml. Like other Agile log files, SOAEvent.log resides on the File Server.

Log.xml is found in **<AgileInstallFolder> \ AgileDomain \ config**

Object History Tab

A business object's **History** tab will indicate such information as: in the Action column, what user-defined action called the process extension; in the Details column, what the Handler name is and any returned message (if an event was triggered on the object). Scheduled Notification is also tracked in an object's **History** tab.

Control of Event Components

The following subsections specify the "stop controls" in **Event Management** nodes.

In any given Event Management node, multiple rows can be selected and disabled or enabled with one click. The details that follow all come with an implicit warning to be careful about what you are disabling or, for that matter, enabling.

Important It is highly recommended that Event Subscriptions and their various masks are first created and tested on a PLM Test system before introducing them into the Production system. With Agile Configuration Propagation (ACP, see separate manual), fully tested Event Management configurations can easily be transferred from Test to Production systems.

Global Event Control

The Administrator toolbar has a button called **Disable Triggering Events**. When it is clicked (and you respond to the prompt), no Events are triggered from that point on, until the same button – which changed to **Enable Triggering Events** – is clicked. At that point, event triggering resumes.

The **Disable Triggering Events** button is, like the other buttons on the Admin toolbar, enabled only for those users who have been assigned the Administrator privilege mask.

When Triggering is disabled, all currently running transactions will be completed, but no new events are triggered. The button only disables triggering, that is, it does not impact administrator configuration of events.

Note The **Disable/Enable Triggering Events** button creates a persistent setting: on startup, the system begins with this setting in the mode used when the server was stopped.

Any indirect changes in the setting of this button – which includes changes caused by switching database, or being enabled/disabled by another administrator – does not take effect until logout and log back in to Java Client.

When an Event Type is Disabled

If you disable an Event Type, the system does not change the Enabled property of the Event masks that use that event type; however, as a result, each and every Event mask of the disabled event type is effectively inactive – which renders inactive any Subscriber that names it.

So with one click you could effectively "shut down" all *Get File*-based events, for example.

You can still create Event masks of that event type while it is disabled.

If you re-enable that event type (by selecting its row and clicking the **Enable** button), the system resumes triggering for that event type. Subscribers that name such Event masks may be active again.

When a Handler Type is Disabled

If you disable a handler type, the system does not change the Enabled property of any Handler masks that use that handler type; however, each and every Handler mask of the disabled handler type is effectively inactive – which will render inactive any Subscriber that names that Handler.

By disabling any handler type, you are therefore effectively preventing the execution of the Handler with that handler type. So you could effectively "shut down" all *Java PX*-based events, or all *Script PX*-based events, or all *Notification*-based events with one click.

You can still create Handler masks of that handler type while it is disabled; they simply won't be executed.

If you re-enable that handler type (by selecting the row and clicking the **Enable** button), the system resumes responding to all Handler masks based on the handler type. Subscribers that name such Handlers may be active again.

When an Event Mask is Disabled

If you disable an Event mask, Subscribers that name such Event masks are then inactive.

You can still modify a disabled Event mask; it simply won't respond when invoked.

If you re-enable that Event mask, the system resumes responding to it. Subscribers that name such Event masks may be active again.

When a Handler Mask is Disabled

If you disable a Handler mask, all Subscribers that name that Handler are then inactive.

You can still modify a disabled Handler mask.

If you re-enable that Handler mask, the system resumes responding to it. Subscribers that name that Handler may be active again.

When a Subscriber Mask is Disabled

If you disable a Subscriber mask, that Subscriber mask is immediately inactive and cannot be executed.

You can still modify a disabled Subscriber mask.

If you re-enable that Subscriber mask, the system resumes responding to it; and the Subscriber mask is active.

More about Selected Event Types

This section adds information about selected event types that is not captured in the table in [The 29 Event Types](#) on page 314.

More about Selected Global Event Types

Extend Tools Menu

Extend Tools Menu event type is a direct parallel to the existing capability for legacy PXs to appear in the client's **Tools** menu. Use of this event type will place the Event mask in the **Tools** menu.

There is no relevance to Pre and Post conditions, so this event type only triggers on Post.

The event mask's Name is what appears in the **Tools** menu. Note that the listing of PXs in the **Tools** menu is alphabetical, with legacy PXs and new event mask Names sorted together.

Scheduled Event

Scheduled Event allows for the execution of any Event Subscription at a time you select.

All standard fields in event masks are available. Selecting Scheduled Event adds the **Frequency** field, similar to Scheduled Event in ACS with the same settings. Object Type is Not Applicable.

Only Post event is possible for this event type.

The timestamp (Time that is displayed) is in GMT time zone.

More about Selected Generic Object-based Event Types

Extend Actions Menu

Extend Actions Menu event type is a direct parallel to the existing capability for legacy PXs to appear in an object's **Actions** menu. Use of this event type will place the Event mask in the correct object's **Actions** menu.

There is no relevance to Pre and Post conditions, so this event type only triggers on Post.

The event mask's Name is what appears in the **Actions** menu.

Create Object

Besides the **Create** menu in Web Client, there are several other ways to initiate object creation: through the Actions shortcuts (as in an Item > **Actions** > **Create Change**); through a Table action; through the Agile SDK; or through Agile Web Services.

Use of Save As to create objects is covered by a separate event type.

Note When a user creates a Project by means of Create Program from Template action, the Save As Object event type is triggered, not Create Object event type.

Entering Required Fields during the "Create" process is not considered an "Update" action, and so does not trigger the Update Title Block event type.

Delete Object

The "Delete" action occurs in Java Client through the **Delete** button or, in Web Client, by **Actions** > **Delete**. This action can also be called by SDK or Web Services.

When an object is first deleted, it is recognized as an Initial, or "soft", delete. The object is not yet removed from the database and can be retrieved through Recycle Bin searches. After opening the object from a Recycle Bin search, the user can select Delete again to trigger a final delete ("hard" delete).

Additional Attributes

▫ **Delete Type** – Soft, Hard

For an Agile business object that does not support hard delete, there is no risk in selecting Hard since the event itself will never trigger.

RFQs class supports only Hard delete. RFQ Responses class does not support either type of delete.

Get File

The Get File event type is triggered in the following cases:

- on a business object's **Attachments** table, user hits **Get** button
- on a business object's **Attachments** table, user clicks a filename link:
 - if the file is a viewable file, Agile Viewer is launched; no event type is triggered.
 - If the file is not a viewable file, the system performs the Get File action and the Get File event type is triggered; in general, from Java Client the Get File event type is triggered on File Folder objects, while from Web Client it is triggered on business objects.

Also, in Java Client, the number of Get File triggers depends on whether the "Download the files in one ZIP file" option is selected or not: if selected, one Get File trigger fires; if this option is not selected, multiple Get File triggers are fired.

Update Relationship

The Update Relationship event type is triggered whenever a Relationship is added, removed, or directly edited on a business object's **Relationships** tab. Editing can include editing any field on the row, including the Relationship Rule.

The "Relationship" use case is treated as a discrete event type (compared to Update Table) because the target object is significant, that is, any PLM object can be in Relationship to any other PLM object.

This event type is not triggered due simply to the Relationship Rule being met. For example, let the rule for an ECO be: set an ECR to Closed status when the ECO moves to its Implemented status; so, when the ECO moves to Implemented, the condition of the rule is met, and Agile PLM attempts to move the ECR to Closed. If the ECR is moved to Closed, then the Change Status event type is triggered; whereas, if the move to Closed fails, then the Promotion Failure for Workflow event type is triggered.

Additional Attributes

- **Source Object Type** – select from list of object types that can trigger this event type when a user modifies the Relationships tab.
- **Target Object Type** – select from list of object types that can be updated as a result of the Relationships tab update.

To set up a Subscriber mask for a Notification handler when the Event mask is based on Update Relationship event type, the object type of Source Object Type and the object type of the Notification mask must match. If multiple Source object types under the same class hierarchy are selected, the Update Relationship-based Event mask can be bound to a Notification mask whose object type is common among all selected Source object types.

Update Table

Not all tabs of all objects support the Update Table event type.

Inclusions

- Update Table event type captures user-initiated object table edits. In general, this includes Items > **BOM** table, Changes > **Affected Items** table, **Attachments** table, and so forth.
- Mass Update from a file folder object causes Update Table to be called for the relevant actions. Different events are triggered for each object's **Attachments** tab.
- A Changes > **Redline** table for **BOM**, **Manufacturers**, or **Attachments** triggers an event on the Item, not on any Changes table.
- For PCM-specific, PPM-specific, or "Common Services" objects.
 - Supported in **Attachments** only.

Exclusions

- The **Relationships** table warrants its own event type, as noted above.
- In general, Update Table event type excludes those kinds of tables that are Read Only, for

example, all **Where Used** and all **History** tables.

- Secondary table updates are also excluded, for instance, **Changes** and **Quality** tables, because the primary action is taking place elsewhere.
- Modifications to the **BOM** and **Manufacturers** tables do not trigger an update when an ECO is released – the trigger is used on the **Changes > Redline** tables or on **Change Status**.

Additional Attribute

Table – This multilist field contains all relevant Tables that are valid for the object and that are enabled for Events; tables are listed once they are implemented for Events. All implemented tables display for the object, even if they are not made Visible for users within Administrator.

There is no **<All>** table action. As a multilist field, customers can select multiple values.

Update Title Block

The Update Title Block event type is triggered when a user directly edits any fields on an object's **PageOne** (that is, **Cover Page**, **General Information**, or **Title Block**), **PageTwo**, or **PageThree**. It does not trigger based on system-written values, for example, releasing a Change Order to update Lifecycle Phase.

The new Attribute Change Management feature of Change Orders and Manufacturing Orders are treated consistently with a **BOM** or **AML** update. Update Title Block event type is invoked only because of direct data entry, not because the Change was released with Attribute Change Management.

Redlining the **Title Block** on a Change Order or Manufacturer Order will trigger the Update Title Block event on the Item, not on the Change. A property of the Event Context Object indicates whether the update is occurring as a Redline; see *Agile PLM SDK Developer's Guide*.

LDAP updates do not invoke the Update Title Block event type.

More about Selected Specific Object-based Event Types

Change Status for Sourcing Object

The PCM solution does not use the standard Agile workflow. Change Status for Sourcing Object event type captures various changes to the statuses of PCM objects.

Additional Attributes

- **Action** – In general, this is the list of Lifecycle Phases for PCM Objects.
 - List for Requests for Quote
 - List for Sourcing Projects

More about Workflow-based Event Types

When a workflow is created by the administrator, the only object type that can be chosen is a base class. Events are designed to be more definable than that; the system therefore uses the workflow's

Matching Criteria property.

For all of the Workflow-based event types, the *Workflow* property is added to the Event mask. This property follows these rules:

- For all but Change Status for Workflow event type, the *Workflow* value can be <All>; when <All> is selected, *Object Type* property is disabled.
- When, however, a class-based workflow is chosen, if that workflow's *Matching Criteria* property has one value, the system uses that value as the *Object Type* of the Event mask.
- If the workflow's *Matching Criteria* property has multiple values, the system uses them to provide a dropdown list from which the administrator selects the *Object Type* for the Event mask.

Approve for Workflow

Additional Attribute

Workflow – populating this property and *Object Type* property observes the rules stated at start of this section.

Audit for Workflow

Besides a user starting a Status Audit or a Release Audit, the Audit for Workflow event type can be initiated through SDK or Web Services. (For more information, see *Agile PLM SDK Developer's Guide*.) System-generated audits that occur during status changes do not trigger this event. Any failure information is included in the Event Context Object; see *Agile PLM SDK Developer's Guide*.

Additional Attributes

- **Type** – Status (audit), Release (audit)
- **Workflow** – populating this property and *Object Type* property observes the rules stated at start of this section.

Change Approvers or Observers for Workflow

There is no "affected status" for this event type.

Additional Attributes

- **Workflow** – populating this property and *Object Type* property observes the rules stated at start of this section
- **Action** – Add Approver or Observer, or, Remove Approver or Observer

Change Status for Workflow

Besides a Change Status in a workflow taking place because of user action, this event type recognizes Change Status in these cases: autopromotion within the server; when a Relationship Rule is matched which forces a Change Status; when "If Rejected, Set Status To" status property is used to change status. This event type triggers whenever a workflow moves from one status to

another.

The Pre-event is before the object exits the "From" status. The Post-event is after the object arrives in the "To" status. This event type is structured in this way because there is no valid condition between statuses – the Change Status transaction is a "black box" to the programmer.

Additional Attributes

- **Workflow** – value cannot be <All> or blank; there is a single list of valid workflows for the selected object. Once a workflow is chosen, populating *Object Type* property observes the rules stated at start of this section.
- **Status – From** – list of statuses from the selected workflow; <Any> is valid and indicates any status
- **Status – To** – list of statuses from the selected workflow; <Any> is valid and indicates any status

Comment for Workflow

Additional Attribute

Workflow – populating this property and *Object Type* property observes the rules stated at start of this section.

Escalation for Workflow

Since this event type is predicated on a system action that must complete (regarding the status property Review Escalation Period), the Pre-event is not available, so Trigger Type is Post only.

Additional Attribute

- **Workflow** – populating this property and *Object Type* property observes the rules stated at start of this section.

Promotion Failure for Workflow

Since this is a system action which must complete, the Pre-event is not available, so Trigger Type is Post only.

Additional Attribute

- **Workflow** – populating this property and *Object Type* property observes the rules stated at start of this section.

Reject for Workflow

Additional Attribute

- **Workflow** – populating this property and *Object Type* property observes the rules stated at start of this section.

Reminder for Workflow

Since this event type is predicated on a system action that must complete (regarding the status property Reminder Period), the Pre-event is not available, so Trigger Type is Post only.

Additional Attribute

- **Workflow** – populating this property and *Object Type* property observes the rules stated at start of this section.

Scripting and Sample Event Subscriptions

This chapter includes the following:

- Overview to Scripting in Agile PLM..... 341
- Using Groovy Scripting Language 342
- Logging of Scripts 343
- Checklist for Specifying Script-based Event Subscriptions 344
- Sample Event Subscriptions with Scripts 345


Overview to Scripting in Agile PLM

This chapter provides an introduction to the Scripting capability, which permits scripted instructions of any length and complexity in Event Handlers. The scripting capability is fully embedded in the **Event Management** framework, with a server-side scripting engine that runs inside the PLM server (Agile Application Server). The script code is stored in a Large Character field in the database. You have access to the Script APIs and the Agile SDK, so you can write SDK programs.

The use of the Agile SDK is a key aspect to exploiting the potential of automated Events. The SDK programmer will find technical information about PLM Events in the *Agile PLM SDK Developer's Guide*.

The sample Event Subscriptions later in this chapter are models for the administrator's understanding of configured Event Subscriptions; they can help a non-programming administrator become familiar with scripting in Groovy (however, the samples are not specific "tutorials" in script-writing). While it is not necessary that the Agile-system administrator be able to write scripts for Handlers, if you do have the assistance of a programmer, you must be able to describe to that person what you want to achieve with the Event Management framework in Agile PLM.

The source code should be available in the production system at runtime, so script code is delivered in plain text, not in object code.



Using Groovy Scripting Language

To contribute to Script PX Handler masks, the script-writer must know how to write scripts in Groovy, how to use the Script API, and how to use Agile Java SDK.

Ideally, the contributing programmer must understand the basics of Event Subscriptions and Handler masks. (A programmer who has not read the previous chapter, "Event Management", should start with [Handler Types](#) on page 312 and [Working in Event Handlers Node](#) on page 320.)

A scripting language is an excellent means to write user-readable and user-modifiable programs that perform simple operations and control the execution of other programs.

Groovy is a dynamic language for the Java platform. Its many features are inspired by languages such as Python, Ruby, and Smalltalk, making them available to Java developers using a Java-like syntax. With Groovy's simplified syntax, your code becomes easy to read and maintain.

These and other factors led to the selection of Groovy as the supported scripting language for the Agile PLM Event Management framework. Groovy is the only scripting language that is supported in Agile PLM 9.3.x.

There are many resources for learning Groovy, both in print and electronic media.

Choosing Script-based Handlers

Scripts are normally dynamically typed (type checked at runtime) instead of statically typed (type checked while compiling). You should use or specify Script-based Handlers over Java-based Handlers in these cases:

- whenever there is a premium on user- (that is, administrator)-readable programs,
- cases where the business logic will need to be updated without explicit compiling or deploying,
- and especially for rapid prototyping of business logic; once validated, you may want to convert a Script PX to Java PX for better performance.

Steps to Develop or Update Handler Masks

The steps that are needed to develop or update Handler masks is another factor to consider.

To develop a Script PX Handler Mask:

1. Define requirements (see Checklists below).
2. Write Groovy script.
3. Associate completed Script PX Handler mask into an Event Subscription.
4. Test the Handler.

To develop a Java PX Handler Mask:

1. Define requirements (see Checklists below).
2. Write Java code.

3. Compile code and test PX.
4. Deploy PX on Agile Application Server.
5. Associate completed Java PX Handler mask into an Event Subscription.

To update a Script PX Handler Mask:

1. Revise the Groovy script.

To update a Java PX Handler Mask:

1. Update the Java process extension.
2. Compile code and test PX.
3. Deploy revised PX on Agile Application Server.

Editing Scripts in the Handler Mask

A Handler mask based on the Script PX handler type is an effective script editor.

On the **General Information** tab of a Handler mask, you can copy-and-paste your script for direct editing in Administrator.

Some editing features are available, particularly the **Validate Script** button, which performs a syntax check of script code, such as proper syntax with parentheses, "Equal" signs, and simple text errors.

The **Where Used** tab shows all Subscriber masks that use this script-based Handler mask.

The **History** tab displays the editing history of the script, such as its creation and instances of modification.

Logging of Scripts

There are several different types of logging of scripts, which are activated and logged differently.

- Systems Logging
 - The systemwide Preference "Agile Script Log Level" controls the amount of information that is written to the Script PX log.
- Object-related Scripts
 - Explicit logs are written into server-side LOG4J trace files.
 - There is one log file for each PLM user. The log filename resembles:
`<userID>_agileScript.Log`.
 - Runtime error messages give information to the administrator.
 - Object-related script execution is logged in the object's **History** tab.
- Event Handler Monitor
 - The **Event Handler Monitor** provides information about handlers being run. See [Event Handler Monitor](#) on page 329.

- The systemwide Preference "Event Monitor Log Level" controls the level of script logs to the Handler Monitor.

Checklist for Specifying Script-based Event Subscriptions

In the "Event Management" chapter, checklist questions were listed in the sections about creating Event masks, Handler masks, and Subscriber masks. Some of these questions are collected below for your use in describing desired Script PX handlers.

- **Event Mask:**
 - From a given Event being triggered, what is the result that you want to automatically happen?
 - Will the Handler mask apply to a single subclass? Will the Handler apply to multiple subclasses from a single class, but not all of its subclasses?
 - If the event involves a Change, which Workflow(s) does it apply to? Does it apply to all workflows or a specific workflow?
 - Are there any Event Type-specific parameters to consider? For example, for the event type Delete Object Action, is the Handler mask going to handle soft deletes or hard deletes?
- **Handler Mask:**
 - What broad outcome does the Handler need to accomplish? What kind of instructions must the system have to complete a successful automation?
 - If the Handler is to be a process extension, what is the proper handler type for this Handler mask?
 - Who is providing the Java code, SDK or Groovy script that will drive this Handler mask?
 - What Roles are needed to run the handler mask? Will the user performing the PLM action always have the right Roles?
- **Subscriber Mask:**
 - What Handler mask is being named in this Subscriber mask? What Handler do you want invoked when the Event of interest is triggered?
 - Which Trigger Type should be used, Pre or Post? Why do you want the Handler to invoke Pre or Post?
 - Which Execution Mode should be used, Asynchronous or Synchronous?
 - What is the Order in which the Handler mask should be invoked?
 - What Error Handling Rule should be used?

Sample Event Subscriptions with Scripts

The following sample Event Subscriptions provide models of the various masks in several use cases. They demonstrate how a Groovy script drives certain Subscription outcomes.

Event Management has been deployed as a working "out-of-box" feature, but It is not assumed that the PLM administrator knows – or has to learn – how to write scripts in Groovy. There is more technical documentation, including samples, about Agile Events and Scripting in *Agile PLM SDK Developer's Guide*. The full potential of Events can be realized with the assistance of a programmer working with that manual.

Note The solution-based PLM user guides may contain information about how the solution can be enhanced by the Event framework. This would be in the administrator configuration chapter or appendix (for example, in the *PG&C* and *PCM User Guides*).

These sample events and Groovy scripts have been tested, but they are not guaranteed to work "verbatim" in any customer system without scrutiny and modifications.

Update Item Description

In this case, when a user updates the Title Block of any business object from one of all the Items base-class (grandchild) subclasses, the item's Description field is updated. This can be done with the primary business objects of any of the PLM solutions, for instance, auto-updating the Content objects of a Project in PPM.

In this sample, the action that triggers this Event Subscription is when a user updates the Title Block of a part. If Description is set with, say, "Testing", and the user modifies Text07 to "SOA" and Text08 to "Project" and Saves, this Event Subscription replaces the existing Description value with "Testing SOA Project". The Handler's execution status can be verified from the Handler Monitor.

Event mask: [Update Title Block Items]

- **Event Type:** Update Title Block
- **Object Type:** Items

Handler mask: [Update Item Description]

- **Handler Type:** Script PX
- **Script:**

```
import com.agile.agileDSL.ScriptObj.IBaseScriptObj
// add other import statements here
import com.agile.api.ItemConstants

void invokeScript(IBaseScriptObj obj) {
    //script body starts here.
```

```
// get old item description value
oldItemDescription =
obj.getValueByAttId(ItemConstants.ATT_TITLE_BLOCK_DESCRIPTION);

// get the first field from pageTwo
field1 = obj.getValueByAttId(ItemConstants.ATT_PAGE_TWO_TEXT07);
// get the second field from pageTwo field2 =
obj.getValueByAttId(ItemConstants.ATT_PAGE_TWO_TEXT08);
// set the new description
obj.setValueByAttId(ItemConstants.ATT_TITLE_BLOCK_DESCRIPTION,
oldItemDescription + " " + field1 + " " + field2);

// get the new description
newItemDescription =
obj.getValueByAttId(ItemConstants.ATT_TITLE_BLOCK_DESCRIPTION);

// log to Event Handler Monitor
obj.logMonitor( "Old description: " + oldItemDescription + "| " +
"New description: " + newItemDescription);
}
```

Subscriber mask: [Update Title Block Items Update Item Description]

- **Event:** [Update Title Block Items]
- **Event Handler:** [Update Item Description]
- **Trigger Type:** Post
- **Execution Mode:** Synchronous
- **Order:** 0
- **Error Handling Rule:** Continue

Notify Create User when Item is Incorporated

In this case, when an item – an instance of any subclass in the Parts or Documents classes, and therefore of the Items base class – is incorporated, a notification is created and sent to the user who created that part or document.

More specifically, the action that triggers this Event Subscription is a user creates a part, and from the **Actions** menu selects **Incorporate**.

The item changes to Incorporated, and a notification is sent to the part's creator. The Handler's execution status can be verified from the Handler Monitor.

Note that this notification is generated by instructions from a script (a Script PX handler), rather than a Notification mask created by the administrator (as in last example in this set).

Event mask: [Incorporate Item]

- **Event Type:** Incorporate Item
- **Object Type:** Items

Handler mask: [Incorporated Item]

- **Handler Type:** Script PX
- **Script:**

```
import com.agile.agileDSL.ScriptObj.IBaseScriptObj
// add other import statements here
import com.agile.api.ItemConstants

void invokeScript(IBaseScriptObj obj) {
    //script body starts here.

    // get create user
    createUser =
    obj.getValueByAttId(ItemConstants.ATT_PAGE_TWO_CREATE_USER)

    // send notification
    sendToList = [createUser];
    obj.sendNotification("Notify On Incorporate", false, sendToList,
    "Comments: send from Script handler");

    // log to Event Handler Monitor
    obj.logMonitor( "Notify On Incorporate sent to: " + sendToList);
}
```

Subscriber mask: [Incorporate Item Incorporated Item]

- **Event:** [Incorporate Item]
- **Event Handler:** [Incorporated Item]
- **Trigger Type:** Post
- **Execution Mode:** Synchronous
- **Order:** 0
- **Error Handling Rule:** Continue

Set Change Analyst

This Event Subscription is a model for automatically setting the Change Analyst when a workflow

changes status.

More specifically, the action that triggers this Event Subscription is a user creates an ECO and sets the product lines to one from this list: Capricorn, Leo, Pisces, Scorpio, Taurus, Test, Virgo. The field for Change Analyst is left unfilled.

When the system (or a user manually) changes the status to Submitted, the Change Analyst for the ECO is set according to the product lines. The Handler's execution status can be verified from the Handler Monitor.

Event mask: [Change Analyst for Workflow]

- **Event Type:** Change Status for Workflow
- **Workflow:** Default Change Orders
- **Object Type:** Change Orders
- **Status – From:** Pending
- **Status – To:** Submitted

Handler mask: [Set Change Analyst]

- **Handler Type:** Script PX

- **Script:**

```
import com.agile.agileDSL.ScriptObj.BaseScriptObj;
import com.agile.agileDSL.ScriptObj.AgileDSLException;
import com.agile.api.ChangeConstants;

/**
 * Sets the change analyst upon setting an ECO to submitted.
 */
BaseScriptObj invokeScript(BaseScriptObj obj) {
    def PRODUCTLINES_ATTID =
    ChangeConstants.ATT_COVER_PAGE_PRODUCT_LINES;
    def CHANGEANALYST_ATTID =
    ChangeConstants.ATT_COVER_PAGE_CHANGE_ANALYST;
    def CAMap = [
        'Capricorn':'user1',
        'Leo':'user2',
        'Pisces':'user3',
        'Scorpio':'user4',
        'Taurus':'user5',
        'Test':'user6',
        'Virgo':'user7'
    ]

    def toStatus = obj.getToStatus();
    def workflow = obj.getWorkflow();
    def changeAnalyst = obj.getValueByAttId(CHANGEANALYST_ATTID);
```

```

// update change analyst based on the product lines if the next
status is CCB and CA list is not filled yet
if(workflow == "Default Change Orders" && toStatus == "Submitted" &&
  (changeAnalyst == null || changeAnalyst == "")) {
  def productLines = obj.getValueByAttId(PRODUCTLINES_ATTID);
  if(productLines == null || productLines == "") throw new
    AgileDSLException("Product Line can't be null, please fill in!");
  else
    obj.logMonitor("Current productlines are " + productLines);
  def productLinesList = productLines.tokenize(";")
  // Set change analyst based on the product lines
  changeAnalyst = CMap.subMap(productLinesList).values().min();
  obj.setValueByAttId(CHANGEANALYST_ATTID, changeAnalyst);
  obj.logMonitor("||Set change analyst to " + changeAnalyst);
}
}

```

Subscriber mask: [Change Analyst for Workflow Set Change Analyst]

- ▣ **Event:** [Change Analyst for Workflow]
- ▣ **Event Handler:** [Set Change Analyst]
- ▣ **Trigger Type:** Post
- ▣ **Execution Mode:** Synchronous
- ▣ **Order:** 0
- ▣ **Error Handling Rule:** Continue

Add Document to New Part

This Event Subscription is a model for automatically creating a Document and adding it to the Assembly BOM any time a part is created. It could be set up for any single subclass from the Parts class, as it is here, or for any object in all the Parts-class subclasses (by populating Object Type field with Parts Class).

More specifically, the action that triggers this Event Subscription is a user creates a part in Web or Java client.

When you click on the part's **BOM** tab, you see a document has been added to the part and the part has been changed to an assembly. The Handler's execution status can be verified from the Handler Monitor.

Event mask: [Create Parts]

- ▣ **Event Type:** Create Object
- ▣ **Object Type:** Parts

Handler mask: [Add Doc to New Part]

▫ **Handler Type:** Script PX

▫ **Script:**

```
import com.agile.agileDSL.ScriptObj.IBaseScriptObj;
import com.agile.agileDSL.ScriptObj.AgileDSLException;

import com.agile.api.IAdmin;
import com.agile.api.IAgileClass
import com.agile.api.IAgileSession;
import com.agile.api.IAutoNumber;
import com.agile.api.IItem;
import com.agile.api.INode;
import com.agile.api.ITable;
import com.agile.api.ItemConstants;
import com.agile.px.EventActionResult;
import com.agile.px.IEventAction;
import com.agile.px.IEventInfo;
import com.agile.px.ICreateEventInfo;
import com.agile.px.EventConstants;
import com.agile.px.ActionResult;

import java.text.SimpleDateFormat;
import java.util.*;

/**
 *Post event of create item action, create document and add the document
into BOM table of assembly.
 * It's mainly using SDK
 *
 */

void invokeScript(IBaseScriptObj obj) {
    IAgileSession session = obj.getAgileSDKSession();
    IEventInfo req = obj.getPXEventInfo();

    try {
        int eventType=req.getEventType();
        int triggerType=req.getEventTriggerType();
        if(eventType!=EventConstants.EVENT_CREATE_OBJECT &&
        triggerType!=EventConstants.EVENT_TRIGGER_POST)
            throw new AgileDSLException("The PX is only applicable for
            post create event");
        ICreateEventInfo info=(ICreateEventInfo)req;
        Integer newSubClassId=info.getNewSubclassId();

        IAdmin admin=session.getAdminInstance();
        IAgileClass partclass=admin.getAgileClass(newSubClassId);
```

```

IAgileClass
docclass=admin.getAgileClass(ItemConstants.CLASS_DOCUMENT);

// get the part object
IItem part = (IItem) session.getObject(partclass,
info.getNewNumber());
if(part==null)
    throw new AgileDSLException("The part is not
        created:"+info.getNewNumber());
if(partclass.getSuperClass().getId().equals(ItemConstants.CLASS_P
ARTS_CLASS)){
IAutoNumber docNumber = docclass.getAutoNumberSources()[0];
//create a new document
IItem doc = (IItem) session.createObject(docclass, docNumber);
//add the document into BOM table of the new part.
ITable tab = part.getTable(ItemConstants.TABLE_BOM);
tab.createRow(doc);
obj.logMonitor("Succeed to add document '"+ doc.getName() +" to
assemblby '"+part.getName()+"");
}
else
obj.logMonitor("The PX is only applicable for creating part
object.");
} catch (Exception e) {
e.printStackTrace();
throw new AgileDSLException(e);
}
}

```

Subscriber mask:

- **Event:** [Create Parts]
- **Event Handler:** [Add Doc to New Part]
- **Trigger Type:** Post
- **Execution Mode:** Synchronous
- **Order:** 0
- **Error Handling Rule:** Continue

Notify when Affected Items Table is Updated

This event is a model for automatically creating and sending a notification (the Notification mask has been created in the **Notifications** node) any time the **Affected Items** table of a Change is updated.

It could be set up for any single subclass from the Change Orders class, or for any object in all the Change Orders-class subclasses (by populating Object Type field with Change Orders Class), or for any object in all the Changes base class (by populating Object Type field with Changes Base Class).

In this case, when the system modifies the **Affected Items** table (this is always an automatic process)

of an instance of the subclass (and object type) ECO, a notification is created and sent to the users named on it. The Notification's execution status can be verified from the Handler Monitor.

Event mask: [Update Table ECO]

- **Event Type:** Update Table
- **Object Type:** ECO
- **Table Name:** Affected Items

Notification mask: [Notify ECO AffItem Change]

- **Object Type:** Change Orders
- Here is a screenshot of the Notification mask:

The screenshot shows a configuration window for a notification mask. It has three tabs: 'General Information', 'Where Used', and 'History'. The 'General Information' tab is active. The form contains the following fields:

- Name:** NotifyEcoAffItemChange
- API Name:** NotifyEcoAffItemChange
- Enabled:** Yes
- Object Type:** Change Orders
- Priority:** Regular
- From:** \$AGILE
- To:** \$APPROVER;\$CHANGEANALYST;\$ORIGINATOR;\$OBSERVER
- Notification Type:** Inbox
- Subject:** Affected Items changed on [Cover Page.Number] by [User Name]. To the right is a 'Data:' dropdown set to 'Access URL' and a '<< Add Data Tag' button.
- Body:** Affected Items changed on [Cover Page.Number] by [User Name]. Current Affected Items: [Change.Affected Items (Number, Description)]. To the right is a 'Data:' dropdown set to 'Access URL' and a '<< Add Data Tag' button.

Subscriber mask: [Update Table ECO Notify Item ECO AffItem Change]

- **Event:** [Update Table ECO]

- **Event Handler:** [NotifyItemECOAffItemChange]
- **Trigger Type:** Post
- **Execution Mode:** Asynchronous
- **Order:** —
- **Error Handling Rule:** —

Locations and File Management

This chapter includes the following:

- Configuring Web Client Notification 355
- Configuring Java Client Notification 356
- File Management in Agile PLM 356

The Locations window displays information about the location of the application and various servers in your Agile PLM configuration.

On the **General Information** tab of the Locations window, you can specify the following properties with appropriate URLs:

- Web Server URL
- Java Client URL.
- Online Help Manuals URL

Note These properties should only be changed by you, the administrator, with previous confirmation from your IT people.

Properties that are also seen on the **General Information** tab but are not editable were populated when the Agile PLM system was installed:

- Application Server URL
- DB Server Hostname
- DB Server Username
- Name (an informal name of the database server)

Configuring Web Client Notification

Agile PLM users whose Preferred Client property is set to Web Client will receive automatic email notifications that contain a link to the Web Client. You can specify the Web Client location in the **Web Server URL** setting.

Important Agile's Product Cost Management (PCM), Product Governance & Compliance (PG&C), and Product Portfolio Management (PPM) solutions operate only in Web Client. Users who work primarily in those areas should have their Preferred Client set to Web Client.

To configure Web Client notification by modifying the Web Server URL:

1. Under **Server Settings**, double-click **Locations**. The Locations window appears.

2. Enter your Web Server URL in this format: <http://Web Server:<port>/Agile/PLMServlet>

Note The Web Server URL is case-sensitive. Ports are usually configurable. A port listed herein is either an industry-standard port or a default port. If the Web server uses the standard HTTP port (80), the port isn't needed in the URL.

3. When you are finished, click **Save**.

Configuring Java Client Notification

Agile PLM users whose Preferred Client property is set to Java Client will receive automatic email notifications that contain a link to the Java Client. You can specify the Java Client location in the **Java Client URL** setting.

Note Although you can access the Java Client through a proxy server, the Java Client URL must be the location where Java Client is deployed on the application server for email notifications to work.

To configure Java Client notification by modifying the Java Client URL:

1. Under **Server Settings**, double-click **Locations**. The Locations window appears.
2. Enter the Java Client URL appropriate for your application server

Oracle Application Server:

<http://<appserver>:8888/JavaClient/start.jsp>

WebLogic Application Server:

<http://<appserver>:7001/JavaClient/start.jsp>

Note The Java Client URL is case-sensitive.

3. When you are finished, click **Save**.

File Management in Agile PLM

Administrator settings on the **Server Settings > Locations > File Manager** tab are important in relation to attachment files and where originals and copies are found. This is documented in [File Management in Agile PLM](#) on page 356.

The Checksum internal utility is a security measure against improper handling of files. Reset privilege and Checksum Computation preference are described in [Handle File Checksum](#) on page 358.

Agile File Management Server

There are two main components to Agile File Manager (AFM): the file server and the file vault. When a file is added to Agile, it is assigned an internal Agile identifier (ID) number by the file server and added to the file vault. It is not stored in the file vault under its original filename: mapping information is maintained in the Agile PLM database, and the filename is modified per Filename Prefix systemwide preference.

When a user requests a file through an Agile PLM client (which requires privileges such as Get, View, or Checkout), the request is routed to the file server, which looks up the file's ID, retrieves the file from the file vault, and sends it to the user.

File Vault

The file vault contains all file attachments stored by AFM. It is recommended that a separate server or storage device be designated as the Agile File Vault to store attachments or files. This is particularly useful when taking advantage of application clustering because each server in the cluster needs access to the same file vault.

Using FileLoad and Indexing New Files

If the Indexing property is set to Synchronous and a large number of files are added to the File Management file vault using Agile FileLoad, the indexing process can take a long time. It has been found that setting this field to Manual increases the loading speed for a large number of files. Or, if the files being added tend to be large documents, set the Indexing property to Scheduled and set up an indexing schedule for once every 3 or 4 hours. If most of the new files are relatively small, the Indexing property can be set to Synchronous.

Distributed File Management

Due to the geographically dispersed nature of the global enterprise, multiple AFM servers can be deployed in a distributed configuration for efficient distribution of product content. A Distributed File Management (DFM) setup allows you to manage files efficiently at remote locations. Deploying DFM servers reduce download time by placing Agile PLM files closer to where they are needed, and allowing users configure which file manager to use. Agile PLM supports a large number of DFM servers.

Optimized Replication Systemwide Preference

When there are more than two File Managers, this systemwide preference (**Preferences** node) allows the PLM system to keep track of the File Managers that contain each file. During replication, the requesting FM only contacts other FMs that contain the file, and downloads a given file from the nearest FM (which is determined by shortest 'ping' to all the FM servers). Set to Enabled or Disabled, the latter can be set to troubleshoot problems with the optimizations.

Using the AutoVue for Agile Server in a Distributed Environment

If AutoVue for Agile is used, an AutoVue for Agile Server should be installed locally with each DFM server. The local viewer server can be installed on the same machine as the DFM. If local users are accessing Agile PLM from outside the firewall, a proxy is recommended in the DFM configuration.

How Distributed File Manager Works

Agile's file management servers have a peer-to-peer relationship. When a user requests a file, the request is directed to that user's configured file manager (see [Configuring a File Manager](#) on page 360). If the file is found, it is served to the user. If the file is not found at that location, the FM sends a request for the file to its peer file servers. The peer file server who has the file sends it back. The local file server saves it to its vault and serves it to the user.

A DFM scenario might be as follows: the AAS is installed in San Jose, California, and a DFM server is installed in Tokyo, Japan. A user from the Tokyo site selects a file attachment to view. The DFM in Tokyo determines that the file is located in San Jose and downloads the file, copies it to the file vault in Tokyo, and serves the file to the user through the View Server. Another user selects the same file attachment. Since the file now resides in the Tokyo DFM vault, it is served directly to the user.

You can install multiple file vaults, or DFM servers. Multiple file vaults are defined on the **Server Settings > Locations > File Manager** tab. On the **Preferences** tab for each Agile PLM user, you can specify the preferred file server for that user.

Note If your Agile PLM system is using multiple DFM servers, your users must use the full domain URL when logging in. If a user does not use the full domain URL, she will be asked to provide login information again when he performs a file operation.

File Management Security

There are two components to file security: server security and client access security. There is also a utility called Handle File Checksum in Java Client that permits users to be warned of problems with improperly accessed files and a means to fix them.


Server Security

Content in Agile file vaults must be protected from deletion or modification by unauthorized users. Agile recommends allowing access only to Agile PLM administrators. System users who access files through the clients do not need Add and Read privileges to the Agile file vault or file directory because Agile file servers retrieve files for users, this task is not performed by individual users.

Client Access Security

Whether you access files from Java or Web Clients, your files are secure. When the client is run behind the firewall, the files are transferred behind the firewall, which secures your files from outside intervention. When clients access files from outside the firewall, Secure Sockets Layer (SSL) communications protocol is supported.

Handle File Checksum

File Checksum is a feature in Agile that warns users when they encounter a file – say, an attachment to a business object – that may have been accessed improperly. In both Java and Web Clients, the **Attachments** tab of business objects and the **Files** tab of file folders have a field called **Has Checksum Error** . When a file on an attachment row has a checksum error, the Has Checksum Error field displays the same symbol.

In support of the Checksum feature, the administrator can manage file validation with a systemwide preference and a privilege mask:


- **Checksum Computation** systemwide preference sets whether to enable or disable checksum computation for attachment files. Note that the default setting is Disabled, which does not allow for this security feature to function. (It is possible that server speed is improved when this preference is set to Disabled, but that may not be as important as enabling the Checksum

functionality.)

- **Reset File Checksum** privilege mask, which is built on the Reset privilege. All users who have been assigned this privilege mask will be notified of any file with a checksum problem. (Note that this privilege mask is not included with any out-of-box Agile role.) You can add the privilege mask to any existing role; at first, however, it may be safest to add it to specific individual's role, or perhaps to your Administrator role and to your User Administrators.

The notification provides such information as the offending file's filename, the file folder(s) to which it is associated, the File Manager that hosts the file, and the file's location.

Besides the Reset File Checksum privilege, you will need to assign Read and Modify privileges for file folders to enable users to resolve checksum errors.

Checksum errors are resolved at the level of the file folder. Use the notification link to open the file folder, then click the  in the offending file's row and use the dialog to resolve the error. You can click one of three options:

1. **Delete the file** – Deletes the file attachment itself across the Agile system. Use this option when you believe that the file is corrupted and irrecoverable, even across DFMs.
2. **Delete only invalid files** – This option can be used to attempt to fix the checksum issue:
 - Deletes the file from File Managers where the file status is Invalid.
 - Resets the checksum flag.
3. **Upload a new file to replace the problematic file in iFS vault** – Replaces the current file with a new file and resets the checksum to the value of the new file in the database. The file's ID in the database and the filename in the vault remain unchanged.

Configuring a File Manager

On the **Server Settings > Locations > File Manager** tab, you can define multiple file managers.

When you click the **File Manager** tab and either click the **New** button or double-click one of the property fields, you see the first four fields in the table below. Click the **Advanced** button to see the other fields. From the advanced view, you can click the **Standard** button to return to the standard view.

Important You must re-start your file server when you make changes on the **File Manager** tab, or create a new one, for the changes to take effect.

If a URL is specified in the documentation or release notes, copy the upper- and lower-case characters exactly, including the full domain name specified.

Field	Description
Fields in the “Create a File Manager” dialog and File Manager “Standard” view	

Field	Description
Name	The informal name of this instance of File Manager. Use a descriptive name that is easy for you and your user administrators to understand, especially in a DFM (multiple) server configuration. This name will appear in the Preferred File Server dropdown list on each user's Preferences tab.
API Name	Unique systemwide identifier for objects and can be autogenerated. You can specify an API name, but internal consistency is enhanced by accepting the system-generated name.
File Manager URL	The file server URL that Agile Web Client will connect to. The format is: <a href="http://<proxy/loadbalancer>:<port>/<fileserver_virtual_path>/AttachmentServlet">http://<proxy/loadbalancer>:<port>/<fileserver_virtual_path>/AttachmentServlet
Enabled	Enables or disables the file management server. If you want to create the file manager now and enable it later, select No.
Primary File Server	Select Yes or No from the dropdown list to make this server the primary file server or not. The primary file server should be co-located with the application server, that is, in the same LAN. Setting a different file manager to be "primary" – setting this field to Yes when another file manager is already the primary – will automatically re-set this field in the previous primary file server to No.
Click the Advanced button to view and edit these fields:	
File Manager Internal Locator	The file application server URL for the File Manager or other component application (such as Agile SDK) to use. The format is: <a href="http://<File Manager host>:<port>/<fileserver_virtual_path>/services/FileServer">http://<File Manager host>:<port>/<fileserver_virtual_path>/services/FileServer
Viewer Server URL	The viewer server (jVue server) URL that Agile Web Client will connect to. The format is: <a href="http://<proxy/loadbalancer>:<port>/<fileserver_virtual_path>/VueServlet">http://<proxy/loadbalancer>:<port>/<fileserver_virtual_path>/VueServlet
Viewer Proxy URL	The viewer proxy URL that the Viewer Server uses to communicate with the File Manager. If local users are accessing Agile PLM from outside the firewall, a proxy is recommended in the DFM configuration. The format is: <a href="http://<File Manager host>:<port>/<fileserver_virtual_path>/VueLink">http://<File Manager host>:<port>/<fileserver_virtual_path>/VueLink
Viewer Content URL	The location from where the Viewer Applet is downloaded. The format is: <a href="http://<proxy/loadbalancer>:<port>/<appserver_virtual_path>/jVue">http://<proxy/loadbalancer>:<port>/<appserver_virtual_path>/jVue
Thumbnail Generation	This area of the File Manager Advanced dialog contains a few settings: <ul style="list-style-type: none"> ▫ Enable Thumbnail Generation by Vue Server checkbox: check to enable "Thumbnail" graphics ▫ Vue Server Host: <Vue Server host> ▫ Vue Server Port: <Vue Server port> <p>Note Enabling Thumbnail generation with these settings is also enabling metafile generation.</p>

To create a new File Manager:

1. Under **Server Settings**, double-click **Locations**. The Locations window appears.
2. Click the **File Manager** tab.
3. Click **New**. The Create a File Manager dialog appears.
4. Fill in the fields for **Name**, **API Name**, **File Manager URL**, and **Primary File Server**, which are described

in the table above.

Note If your company is using AutoVue for Agile, an AutoVue for Agile Server should be installed locally with each DFM server.

5. The **Enabled** field must be set to Yes for that server to be put into active use.
6. Click the **Add New Vault** button to add and configure a new file vault.
7. When you have defined the new file manager, Click **OK**.

Once you have created this new instance of a file manager, you can open it and add other server definitions, as described in the next task.

Creating a Custom File Vault

If you are using Java Client to upload references to files stored in a Custom file vault, you must set up the vault first. A Custom vault is “Read Only” and is not available to users to check out and modify attachments; it is used for uploading files using Agile FileLoad (which is documented in *Agile PLM Import & Export Guide*).

To set up a Custom file vault:

1. Under **Server Settings**, double-click **Locations**. The Locations window appears.
2. Click the **File Manager** tab.
3. Double-click the entry to display the File Manager dialog box.
4. Click the + button to add a new vault.
5. In the Vault Type field, select Custom.
6. In the Description field, type a description of the vault.
7. In the Base Storage Directory field, enter the primary location where the files are stored. See next subsection
8. In the Purge Directory field, enter the primary location where the purged files are moved to. See next subsection.
9. Click **OK**.
10. Restart the Agile File Manager.

Base Storage Directory and Purge Directory Fields

The Base Storage Directory default location is \files. The location can be a shared network storage directory, such as a Storage Area Network (SAN).

<p>Important Do not specify a mapped location. Instead, specify the actual machine name and directory, like this:</p>
--

[\\filesserver\files](#)

The Purge Directory field indicates where purged (deleted) files are automatically moved. The default location is agile_home\files\purge. The location can be a shared network storage directory, such as a Storage Area Network (SAN).

Important Do not specify a mapped location. Instead, specify the actual machine name and directory, like this:

[\\fileserver\files\purge](#)

Modifying a File Manager Definition

To modify a File Manager definition:

1. Under **Server Settings**, double-click **Locations**. The Locations window appears.
2. Click the **File Manager** tab.
3. Double-click the row of the file manager you want to modify. The File Manager dialog appears.
Be sure to navigate to the correct server field – use the **Advanced** button as needed.
4. When you have finished your modifications, Click **OK**.

Deleting a File Manager Definition or Removing a File Server

To delete a file manager definition:

1. Under **Server Settings**, double-click **Locations**. The Locations window appears.
2. Click the **File Manager** tab.
3. Double-click the row of the file server you want to modify. The File Manager dialog appears.
Be sure to navigate to the correct server field – use the **Advanced** button as needed.
4. You can simply delete the reference to the server in the field – the file server definition.
To remove a configured server, select a row and click the **Remove Selected Vault** button. If you have rights to that server, it will be removed.
5. When you are finished, and Click **OK**.

Setting the Preferred File Manager for a User

If your Agile PLM system uses Distributed File Management, each user should specify the preferred file manager to use. For best performance, specify a file server in the same location as the user. For example, users in the United States should select a file manager located in the United States and not one located in China.

To set a user's preferred file manager in Java Client:

1. Under **User Settings**, double-click **Users**. The Users window appears.
2. Double-click the user's name in the list. That user's window appears.
3. Click the **Preferences** tab.
4. For **Preferred File Manager**, select a local file manager from the list.
5. Click **Save**.

To set a user's preferred file manager in Web Client:

1. Click **Tools and Settings > Administration > Users**. The Users page appears.
2. Click the user's name in the list. That user's page appears.
3. Click the **Preferences** tab.
4. Click **Edit**. The fields become editable.
5. For **Preferred File Manager**, select a local file server from the list.
6. Click **Save**.

Purging Older Versions of Files

If AutoPurge is enabled for your Agile PLM system (see [Viewer and Files](#) on page 269), the Agile File Manager automatically purges old versions of files. A background thread starts every day at 6:00 am local time that determines what files should be purged. If there are such files, a folder named by date and time is created in the purged files location and the files are moved into it. If no files need to be purged, the dated folder is not created. You can change the default interval between the hard-coded time and the time that the purge actually takes place. This interval is set in Attachment Purging Task; see [Task Configuration](#) on page 392.

Note The Agile File Manager doesn't permanently remove purged files from the system. Your company's IT personnel must handle that task.

Use Case for Attachment Purging Task

If there happened to be server failure during the time that was configured for attachment purging, the task would not run that day. For example, if the task runs at 6:00 am every day but the server shut down between 5:00 am and 9:00 am, the task would not run because the Task Lookback Window is set to 120 minutes, and 9:00 am is a greater value of minutes from 6:00 am. The workaround is to temporarily set Task Lookback Window to a value that is larger than 180 minutes (in this case), say, to 200 minutes. Then the task will run when the server is restarted.

In general, the value for Task Lookback Window (**Server Settings > Task Configuration > <any task> > General Info** page) should always be bigger than the value for Task Interval to make sure that no event is skipped.

This chapter includes the following:

- Configuration of Database Settings 365
- Database Properties 365

Configuration of Database Settings

From the **Database** node you can view and configure Agile PLM's systemwide database settings.

To modify a Database setting:

1. Under **Server Settings**, double-click **Database**. The Database window appears.
2. In any editable field, enter a new value or select from the dropdown list.
3. When you have finished, click **Save**.
4. Restart the Agile Application Server to activate the change.

Caution If you change the **Notification Enabled** setting, it takes effect immediately. Changing any other Database setting requires that you restart the Agile Application Server for the new setting to take effect. All active users' connections will be terminated when the Agile Application Server is restarted.

Database Properties

The following table lists Database properties.

Property	Description	Default
Discovery Privilege	Enabling Discovery Privilege allows all Discover privilege masks for this Agile PLM system to function. If Disabled, all Discover privilege masks and Discovery-related SmartRules are disabled. If you are not using Discovery functions, you can improve your system's performance by setting this property to Disabled.	Enabled
GUID	The unique ID for your company's Agile PLM database. This property is not editable.	(GUID)
Name	The name of the main Agile PLM database; you can rename the node, using up to 29 letters.	Agile Database

Property	Description	Default
Notification Enabled	Whether email notifications are sent to users. If this property is disabled (= No), all other email notification settings are ignored. This setting is especially important with regard to Event Management : all "event-based" notifications will <i>not</i> be active if Notification Enabled is set to No.	No
Schema	Database "username," or the name of the schema, that is used to log in to the database. This property is not editable.	(Schema name)
Server	The name of the current Agile PLM database server. This property is not editable.	(Server name)
DB Version	The version of Agile PLM database being used. This property is not editable.	(DB version)
Mail From Domain	Domain name for email notification, for example, mydomain.com.	(None)
Mail From User	The From email address that is used in Agile PLM email notifications. The value must be a valid email address, for example, AgileAdmin@mydomain.com .	(None)
Mail Server External	The name of the computer running your external email server.	(None)
Mail Server Internal	The name of the computer running your internal email server.	(None)
Customer ID	The unique ID for your company. This property is not editable.	(ID number)
Year Cycle – Start Month	First month of your company's fiscal year.	(Set during installation)
Year Cycle – Start Day	First day of your company's fiscal year.	(Set during installation)

This chapter includes the following:

▪ Configuring WebLogic Server for LDAP with Agile PLM.....	367
▪ Creating Users in an LDAP Directory	372
▪ Enhanced LDAP	373
▪ Synchronizing LDAP and Agile PLM	374
▪ LDAP-controlled User Properties.....	374
▪ Agile LDAP Configuration	375

Many enterprises use the Lightweight Directory Access Protocol (LDAP) system, as well as a dedicated LDAP server, to create their user accounts. The **Server Settings** node folder now includes an **LDAP** node. When you open the **LDAP** node, the LDAP Configuration Editor appears. The administrator can change LDAP settings (especially the search filter), preview the results, and save the changes, all without having to re-start the server.

Note The LDAP node may not be visible in your out-of-box Administrator tree. If your company does not use an LDAP system, the node is not needed. The node is made visible through the AppliedTo capability; see [Administrator Privilege and the AppliedTo Capability](#) on page 233.

Agile PLM supports LDAP authentication through the Agile Directory Server Integration Module. You can integrate Agile with your existing directory server to manage your users in one place. This approach can be fully integrated into Agile PLM, for these supported directory servers:

- Oracle Internet Directory Server
- Microsoft Active Directory Server
- Sun Java System Directory Server

If you chose to manage your user accounts through a directory server (instead of the database) during installation, then all new users (except supplier users) are added, and certain user attributes are configured, only through the directory server. Supplier users are authenticated by the database and managed by the supplier administrator.

Note Agile Administrator has the capability of integrating aspects of your PLM system with Single Sign-On (SSO) capability. With SSO configured and deployed for your PLM system, a user that has signed in to the system once (for instance, through the corporate portal) is not prompted again by a "login" dialog (see Appendix A, [Single Sign-On](#) on page 421).

Configuring WebLogic Server for LDAP with Agile PLM

Oracle Application Server supports the Agile-certified LDAP servers; however, Oracle WebLogic

Server requires further configuration to support them, as detailed in the tasks below.

Configuring WebLogic with Oracle Internet Directory

To configure WebLogic with an Oracle Internet Directory Server:

1. Open the Administration console page by typing the following URL:
http://localhost:<port_number>/console
2. In the left pane, choose **Lock & Edit**.
3. In the left pane, choose **agileDomain > Security Realms > AgileRealm > Providers > Authentication**.
4. Click **New** and enter a name, such as "OracleInternetDirectory" for the OID authenticator and select **LDAPAuthenticator** and click **OK**.
5. Click on the newly created OracleInternetDirectory authenticator and change the value of the Control Flag to **SUFFICIENT** and then click **Save**.
6. Select provider specific from the current page and fill in the following entries with the following values:
 - User Name Attribute: `cn`
 - Propagate Cause for Login Exception: Check the Box
 - Principal: `cn=orcladmin`
 - Host: `<Machine Name where the OID running>`
 - User Object Class: `person`
 - All Users Filter: (Specify the User Filter Name or leave blank
`objectclass=person`)
 - User Search Scope: `Subtree`
 - All Groups Filter: `<Specify the Group Filter Name or leave blank>`
 - Static Member DN Attribute: `uniquemember`
 - Group from Name Filter: `(& (cn=%g)(objectclass=groupofuniqueNames))`
 - Static Group DNs from Member DN Filter:
`(&(uniquemember=%M)(objectclass=groupofuniqueNames))`
 - Use Retrieved User Name as Principal: (check the box)
 - Results Time Limit: `0`
 - Cache TTL: `60`
 - Dynamic Group Name Attribute: `uniquemember`
 - Credential: `<Password given for OID login>`
 - Confirm Credential: `<Password given for OID login>`
 - Group Search Scope: `subtree`
 - Group Base DN: `cn=Groups,dc=agile,dc=agilesoft,dc=com`

- Dynamic Group Object class: (empty)
 - User from Name Filter: (&(cn=%u)(objectclass=person))
 - Cache Size: 32
 - Dynamic Member URL Attribute: (labeledurl)
 - SSLEnabled: (empty)
 - Cache Enabled: (check the box)
 - Connection Retry Limit: 1
 - Connect Timeout: 0
 - Parallel Connect Delay: 0
 - User Dynamic Group DN Attribute: cn
 - Static Group Name Attribute: cn
 - User Base DN: cn=Users,dc=agile,dc=agilessoft,dc=com
 - Follow Referrals: (check the box)
 - Port: 389
 - Ignore Duplicate Membership: (uncheck the box)
 - Static Group Object Class: groupofuniquenames
 - Group Membership Searching: unlimited
 - Max Group Membership Search Level: 0
1. Click **Save**.
 2. On the left pane click the button **Activate Changes** to activate all the changes made.
 3. Log out from the console, and restart the WebLogic server and, if installed in a cluster, all managed servers to successfully have all the changes activated.

Configuring WebLogic with Sun Java System Directory Server

To configure WebLogic with a Sun Java System Directory Server:

1. Open the Administration console page by typing the following URL:
http://localhost:<port_number>/console
2. In the left pane, choose **Lock & Edit**.
3. In the left pane, choose **agileDomain > Security Realms > AgileRealm > Providers > Authentication**.
4. Click **New** and enter a name, such as "Iplanet" for the iplanet authenticator and select **iPlanet Authenticator** and click **OK**.
5. Click on the newly created iplanet authenticator and change the value of the Control Flag to **SUFFICIENT** and then click **Save**.
6. Select provider specific from the current page and fill in the following entries with the following

values:

- User Name Attribute: uid
- Host: <machine name where the iplanet server is running>
- Principal: <uid=admin,ou=administrators,ou=topologymanagement,o=netscaperoot >
- User object class: Person
- User Search Scope: subtree
- Static Member DN Attribute: uniquemember
- Group From Name Filter:
(|(&(cn=%g)(objectclass=groupofUniqueNames))(&(cn=%g)(objectclass=grou
pOfURLs)))
- Static Group DNs from Member DN Filter:
(&(uniquemember=%M)(objectclass=groupofuniquenames))
- Results Time Limit: 0
- Cache TTL: 60
- Dynamic Group Name Attribute: cn
- Credential: <password given for the iplanet to authenticate>
- Confirm Credential: <confirm the password>
- Group Search Scope: subtree
- Group Base DN: ou=agile, dc=agile,dc=agilesoft,dc=com
- Dynamic Group Object Class: groupofURLs
- User From Name Filter: (&(uid=%u)(objectclass=person))
- Dynamic Member URL Attribute: memberURL
- Cache size: 32
- Cache Enabled: select the check box
- Connection Retry Limit: 1
- Connect Timeout: 0
- Parallel Connect Delay: 0
- User Dynamic Group DN Attribute: < Fill this if you are using dynamic
group>
- Static Group Name Attribute: cn
- User Base DN: ou=agile, dc=agile,dc=agilesoft,dc=com
- Follow Referrals: select the check box
- Port: 389
- Static Group Object Class: groupofuniquenames

- Group Membership Searching: unlimited
- Max Group Membership Search Level: 0
- 1. Click **Save**.
- 2. On the left pane click the button **Activate Changes** to activate all the changes made.
- 3. Log out from the console, and restart the WebLogic server and, if installed in a cluster, all managed servers to successfully have all the changes activated.

Configuring WebLogic with Microsoft Active Directory Server

To configure WebLogic with Microsoft Active Directory Server:

1. Open the Administration console page by typing the following URL:
http://localhost:<port_number>/console
2. In the left pane, choose **Lock & Edit**.
3. In the left pane, choose **agileDomain > Security Realms > AgileRealm > Providers > Authentication**.
4. Click **New** and enter a name, such as “ActiveDirectoryServer” for the ADS authenticator and select **ActiveDirectoryAuthenticator** and click **OK**.
5. Click on the newly created ActiveDirectoryServer authenticator and change the value of the Control Flag to **SUFFICIENT** and then click **Save**.
6. Select provider specific from the current page and fill in the following entries with the following values:
 - User Name Attribute: sAMAccountName
 - Principal: Administrator@enterprise.uab.edu
 - Host: 10.176.138.35
 - All Users Filter: (objectclass=person)
 - User Search Scope: subtree
 - All Groups Filter: (Keep it Empty)
 - Static Member DN Attribute: member
 - Group from Name Filter: (Keep it Empty)
 - Bind Anonymously On Referrals (Uncheck this Box)
 - Static Group DNs from Member DN Filter:
(&(member=%M)(objectclass=group))
 - Results Time Limit: 0
 - Credential: < password given for the ADS to authenticate>
 - Confirm Credential: < password given for the ADS to authenticate>
 - Group Search Scope: subtree
 - Cache Size: 32

- User from Name Filter: (keep it empty)
 - Dynamic Member URL Attribute: (keep it empty)
 - Connection Retry Limit: 1
 - Connect Timeout: 0
 - User Dynamic Group DN Attribute: (keep it empty)
 - Static Group Name Attribute: cn
 - User Base DN: OU=agile,DC=enterprise,DC=uab,DC=edu
 - Use Token Groups for Group Membership Lookup (Uncheck this Box)
 - Port: 389
 - Follow Referrals (check this Box)
 - Propagate Cause for Login Exception (Uncheck this box)
 - User Object Class: user
 - Cache TTL: 60
 - Use Retrieved User Name as Principal (uncheck the box)
 - Dynamic Group Name Attribute: (keep the field empty)
 - Group Base DN: OU=agile,DC=enterprise,DC=uab,DC=edu
 - Dynamic Group Object Class: (keep the field empty)
 - SSLEnabled: (uncheck the box)
 - Cache Enabled (check this box)
 - Parallel Connect Delay: 0
 - Ignore Duplicate Membership: (uncheck this box)
 - Static Group Object Class: group
 - Group Membership Searching: unlimited
 - Max Group Membership Search Level: 0
1. Click **Save**.
 2. On the left pane click the button **Activate Changes** to activate all the changes made.
 3. Log out from the console, and restart the WebLogic server and, if installed in a cluster, all managed servers to successfully have all the changes activated.

Creating Users in an LDAP Directory

You have the following options for creating Agile PLM users:

- **Create all users in Agile PLM** – this can be done even if your company uses LDAP for its non-Agile applications.

- **Create all user objects using the corporate LDAP system** – the basic user data (for instance, user ID, first and last name, password, email address) are imported to Agile PLM, where each user's profile is completed.
- **Combine the two approaches** – your company may use LDAP for its employees that are assigned to use Agile PLM, but create non-employees (for instance, supplier users) within the Agile PLM system. In this case, the LDAP accounts are imported and validated, and there is no risk reconciling user data within Agile PLM.

Note You cannot create regular Agile PLM users (that is, Power or Concurrent users) *both* in Agile PLM and in LDAP. The only way to combine the two approaches is to use Agile PLM to create Restricted users only.

Note More specifically, you should not create multiple users with the same User ID (username), especially in the WebSphere environment. WebSphere uses an embedded LDAP adapter to authenticate users, and that adapter does not allow multiple users with the same ID.

Users created in Agile PLM with the “(Restricted)” supplier user roles are authenticated through the Agile PLM database.

Configuring Multiple LDAP User Repositories

You can configure multiple LDAP user repositories for the security domain by repeating the configuration steps for the specific directory server.

Do *not* delete the AgileAuthenticator authentication provider: it is used to authenticate users against the Agile database. The Control Flag for the AgileAuthenticator must remain **Optional**. AgileAuthenticator must be the first authentication provider in the list if there are additional authentication providers, such as Sun Java System or Microsoft Active Directory.

Enhanced LDAP

To modify LDAP information:

1. Under **Server Settings**, double-click **LDAP** node. The LDAP Configuration Editor window appears.
2. On the **LDAP Configuration** tab, double-click the row that names the LDAP server you want to populate. This is also where you can create a new LDAP server configuration.

The **Edit LDAP** dialog presents the contents of the LDAP server you selected for your modification.

3. When you have completed entering modifications, click **OK**.
4. With the row selected (for the LDAP server you modified), click the **Preview** button. The **Preview Results** tab lets you preview the results of your LDAP query.

When you click **Preview**, the server validates the LDAP configuration. If there are errors – such as inconsistent data across LDAP servers in a cluster, or duplicated users on multiple servers, or syntax errors – the server passes an exception back to the client, and you will see a popup window displaying the errors.

- If the LDAP configuration contains clustered LDAP servers, the preview shows data from only one of the LDAP servers, since the data is identical across the cluster.
 - If the LDAP configuration contains multiple LDAP servers, the preview shows the union of data from all LDAP servers.
5. Click **Save** to save changes to the LDAP configuration. Again, the server validates the LDAP configuration. If any errors are detected, an error message displays and the exception prevents the Save operation from completing.

Synchronizing LDAP and Agile PLM

In Java Client, the **Refresh Users from LDAP** button on the **Users** node toolbar window integrates LDAP-originated users into the Agile PLM system. In Web Client, if you use LDAP, the **Refresh from Directory Server** button is enabled in the **Users** node under the More button menu options (under **Tools and Settings > Address Book > Users**) for the same purpose.

Refer to your LDAP documentation to import user accounts to Agile PLM.

After clicking **Refresh** (or **Refresh from Directory Server**) to automatically update the accounts for use in Agile PLM, complete each user object by populating Agile PLM user properties as required.

Synchronization of Agile PLM users with LDAP-created user accounts depends on the Agile PLM users' Login ID being equivalent to the LDAP user-accounts' Login ID. During an upgrade of Agile PLM systems, it assumes user authentication through the Agile PLM database.

There is another way to synchronize users between LDAP and Agile PLM: a script is included in the Bin directory called `migrateUserToDB.bat/sh` that you can run manually or on a scheduled basis. This script serves the same purpose as the **Refresh** (or **Refresh from Directory Server**) button in Java and Web clients, respectively.

Important Be sure to restart the application server after executing the script.
--

LDAP-controlled User Properties

If your company is using LDAP for user accounts, the following properties will always be managed by LDAP. They cannot be edited in Agile PLM.

- UserID
- First Name
- Last Name
- Password
- Email Address
- Title
- Work Phone
- Mobile Phone

- Fax Number

Note If an LDAP directory is used to create and manage Agile PLM users, by default users do not require a separate approval password. However, you can uncheck the **Use Login Password for Approval Password** property for a user and enter an approval password.

You can set up **Account Policy** functionality on the LDAP server. For more information, see your LDAP system documentation.

Agile LDAP Configuration

The LDAP Configuration Editor (**Server Settings > LDAP** node) is used to configure your integration between Agile PLM and your company's LDAP system.

Click the **New LDAP** icon and fill in the properties (defined below). You can double-click an existing configuration (row in the table) to bring up the Edit LDAP dialog. You can remove an existing configuration by selecting its row, clicking the **Delete LDAP** icon, and following the prompt.

You can define multiple sets of parameters to configure integration with multiple directory servers.

Important Verify all settings in LDAP Configuration Editor with your LDAP administrator.

Directory Service Connection Parameters

Connection parameters include the hostname, port, protocol, account name and filter. The account name is used to connect to the directory server during synchronization, so it must have the appropriate privileges. The filter is used to select only a subset of the users defined in the directory server as Agile users.

Configuration Parameters Defined


The properties in the New LDAP configuration page are described in the table below:

Field Name	Description
ID	Unique string identifying the LDAP server. The string must be less than 30 characters and cannot be changed once in use.
Description	Information about the server configuration
Agent	The Directory Server used for authentication; valid values are SunONEDirectory or ActiveDirectory
URL	The URL for the authentication agent
Domain	The authentication string when using Active Directory Server in the format of <username>@<auth.domain.name>
Username	Username (does not need to be the LDAP Administrator)
Password	Encrypted password of the user

Field Name	Description
User Path	Tree under which all Agile users can be found; this property should be set to the node closest to the root of the Directory Tree structure; any user that is not found under the subtree starting at this node should not be on the Agile system.
Search Scope	Scope of search for Agile users under the user-path node; valid values are ONE_LEVEL or SUB_TREE; this property should be set to ONE_LEVEL only if all users in the organization are directly under the User Path node
Search Filter	Search filter for Agile users under the <user-path> node; this must be a valid LDAP search filter that matches all Agile users under the scope defined by <auth.ldap.user.path> and <auth.ldap.user.search.scope>; users not matching this filter are considered invalid users on the Agile system; a valid LDAP search filter must be enclosed in parentheses.
Mechanism	Authentication mechanism supported by the directory server; valid values are "simple" or "strong"
Group Path	This property should be set to the node closest to root of the Directory Tree structure; it's the path in which group search starts
Group Scope	Valid values: ONE_LEVEL, SUB_TREE; similar to <search-scope>
Group Filter	<p>This must be a valid LDAP search filter that matches the LDAP groups where all expected users to be used in Agile are contained.</p> <p>When using the Group Filter to synchronize all users and user groups from the LDAP server, the <user-path> and <search-scope> must be set for the Search Filter.</p> <p>With User Group Sync function enabled. You cannot remove/ add users for LDAP Synched User group on User's Tab</p>
Group Membership	Used for authentication to check if the current user belongs to the specified group (defined in group-filter); using "%M" to designate current login user DN.
Dynamic Group Filter	This must be a valid LDAP search filter that matches the LDAP Dynamic groups that contain all expected users to be used in Agile
Failover Links	Links that point to alternate LDAP servers that the system tries to access, in listed order, when the primary LDAP server fails
Fail Attempts	Specifies the maximum number of attempts to access other servers that the system can make when the LDAP server fails
Disable Agile User If Not Found In LDAP	<p>Valid values: TRUE or FALSE</p> <p>When set to TRUE and the administrator runs the "migrateUsersToDB -p" command, the Agile active users (migrated from LDAP and made active) who are either removed from LDAP or not in the current LDAP search path are disabled.</p>

Mapping LDAP Attributes

To map an Agile attribute to an LDAP-system attribute:

1. In the User-LDAP Attributes Mapping or Usergroup-LDAP Attributes Mapping field, click Add  to create a new entry.
2. From the New Attribute Mapping dialog, choose an Agile ID (that is, attribute) from the dropdown list.
3. In the LDAP ID field, type the name of an attribute from your LDAP system that you want mapped to the selected Agile attribute.

For example, "Date09" might map to an attribute called "End Date".

Multiple Directory Server Support

It is possible to indicate multiple directory servers. This is useful if you have users in multiple domains that need access to Agile, or if you have backup directory servers to provide fail-over support.

On the Edit LDAP page, create one or more nodes depending on how many directories need to be supported; click the **Preview Result** tab: it will display all the users on the first node or server. Now, if you stop the services of this server, then the Preview Result will display the users from the backup or secondary server. (Remember to restore services to the primary server.)

If a backup or secondary directory server is configured, the integration module tries the backup server if access to the primary server fails.

Configuration Scripts

One directory server can be configured during the Agile installation. Additional directory servers can be configured manually after installation. Agile provides scripts to enable configuration after installation. These scripts are located in the *agile_home\agileDomain\bin* directory:

- `encryptpwd` — `ldapconfig.xml` needs an encrypted password for the directory server user; this script generates an encrypted password based on the existing user password
- `checkLDAPConfig` — use for checking LDAP configurations; all errors should be fixed, if encountered
- `migrateUserstoDB` — use to migrate a user from LDAP to the Agile database; this script allows you to update existing users and to create new users in the database.

Synchronizing Users and User Groups

This feature applies to iPlanet server.

- LDAP user groups and group members can be synchronized into the Agile system using `<group-filter>` to "synch" the static users in the user group, and `<dynamic-group-filter>` to "synch" dynamic group users. To enable this function, make sure that **auth.ldap.group** is enabled (set to True) in **agile.properties** file.

Note With User Group "synch" function enabled, you cannot remove or add users on a user group's **Users** tab that have been synchronized (that is, where users have been added to a user group via LDAP).

Systemwide Preferences

This chapter includes the following:

▪ Modifying Preferences	379
▪ Default Systemwide Preferences.....	379
▪ Details of Selected Preferences	385
▪ Languages tab	387

Modifying Preferences

The **Preferences** node lets you view and configure Agile PLM's systemwide preferences and Languages.

Note There is no connection between the **Preferences** node, which are systemwide server settings, and User Preferences, which are found on every user object (**User Settings > Users** node > [any user] > **Preferences** tab). However, a subset of the User Preferences are "system-related"; again, these do not pertain to settings in **Preferences**.

To modify Preference settings:

1. Under **Server Settings**, double-click **Preferences**. The Preferences window appears.
2. In any editable field, enter a new value or select from the dropdown list.
3. When you have finished, click **Save**.

Default Systemwide Preferences

The following table lists and describes the Agile PLM Preferences. They are listed in alphabetical order.

Preference Name	Description	Default
Add User's Default Site to New Items	For enterprises that utilize "Sites" information, this Preference can be set so the Default Site of a user is automatically added when the user creates an item.	No
Agile Drive	Controls the user created Agile Drive access to Agile objects and documents outside of Agile. See Agile Drive on page 385 for more information.	Disabled

Preference Name	Description	Default
Agile Script Log Level	Sets "level" of logging on an Agile system. A production system might be set to a lower level, such as Off, Error, or Warn. A development system would likely be set to a higher level, such as All, Debug, or Fatal. Settings are All, Debug, Error, Fatal, Info, Off, or Warn.	Off
Allow Download of Productivity Components	Controls whether your users will have access to the Java applets that permit advanced file uploading and other features, depending on what is allowed by the License Key your company purchased. Settings are No and Yes. See Allow Download of Productivity Components on page 399, on page 385.	No
Allow Password Reset	Lets you select whether Web Client users who forget their password can automatically receive a new one by clicking a link on login screen. See Allow Password Reset on page 385.	No
Allow Unsecured Files	Allows Agile PLM to manage pointers to unsecured URLs, that is, it allows attachments to be URLs (as opposed to files). If you select Yes, pointers to URLs are stored on the Agile Application Server computer, although Checkin and Checkout are disabled for referenced URLs.	Yes
Checksum Computation	Sets whether to enable or disable checksum computation for attachment files. Settings are Enabled or Disabled. See Handle File Checksum on page 358.	Disabled
Content Service Maximum Retries	Determines how many times, after the initial attempt, a transfer order object will attempt to make delivery to a failing destination before further delivery attempts are blocked. See Content Service Maximum Retries on page 386.	5
Content Service Wait Time (in seconds)	Determines how often the Content Server "wakes up" to check for transfer order objects to process.	300
Default User Name	Names of users appear with the first name appearing before the last name, or vice versa (with appropriate comma). Changing Default User Name setting requires re-starting the server for the change to take effect.	FirstName LastName
Display URLs as Hyperlinks	Text and Multitext fields enable typed URLs to automatically convert to hyperlinks. Setting this to No will display URLs typed in Text and Multitext fields as plain text. Note that certain "URL" and "mail" fields in Agile are not controlled by this preference; they will always convert typed URLs to hyperlinks.	Yes

Preference Name	Description	Default
Display User ID	Determines whether or not User IDs (usernames) appear. Changing Display User ID setting requires re-starting the server for the change to take effect.	No
Enable BI Publisher for Reports	Determines whether or not BI Publisher is used to generate reports in multiple output formats. Setting this to Yes generates reports in multiple output formats using BI Publisher. Setting this to No means reports continue using existing reporting layout.	No
Event Maximum Nested Levels Allowed	Determines how many times any script will run. If you intend that scripts run multiple times to complete their designed operation, adjust this setting to the desired maximum times allowed. But other scripts will also run multiple times, with possible unintended effects.	10
Event Monitor Log Level	Sets the level of logging in Event Handler Monitor (System Settings > Event Management) . Settings are All (logs all invoked Subscribers), Error (logs only errors), or Off (does not display log information).	All
Filename Prefix	Agile File Manager uses a prefix that is attached to each file that is stored in the file vault. Type in the identifier that will be automatically added to every attachment file. The default is "agile". Caution! This effects of this systemwide preference are far-reaching and the value should not be changed without good reason.	agile
Garbage Collection Wake-up Time (in seconds)	The "garbage collection" is a thread for cleaning out idle threads in the cache. After "cleaning," garbage collection is put to "sleep" for the number of seconds in this setting. 300 seconds (5 minutes) is a reasonable value.	300
Load to CAD	Pertains to Engineering Collaboration solution. When set to Enabled, a Load to CAD button appears and is functional in Web Client. Design objects can then be uploaded to your designers' CAD system.	Disabled

Preference Name	Description	Default
Maximum Query Results Displayed	<p>Sets a maximum number of search results that can be displayed (advanced or quick searches); can be any positive integer less than 5000, but 1000 is recommended.</p> <p>If a user's Max Rows Displayed user preference is set to fewer rows than this systemwide preference, the former value will override the latter value.</p> <p>Caution: The Full Search Display privilege applies to results of report queries, not to ordinary searches. All users, whether or not they have the Full Search Display privilege, will see the maximum number of search results specified in this property.</p>	1000
Maximum Report Results	<p>Determines maximum number of objects displayed in Agile PLM Custom Reports; note that it does not apply to Standard Reports.</p> <p>This preference is overridden by Full Search Display (FSD) privilege (see Caution).</p> <p>The upper limit to this field has been increased to 500,000 (a comma is not needed in the field).</p> <p>Note that the "Export to Excel" feature of search results (in Java Client, from page of Search Results: Export Search Result menu icon > Excel or CSV) regards this Preference: the number in this field limits the maximum number of results exported to Excel or CSV files. (This is not to be confused with this sequence accessed from Business Object: Actions > Microsoft Excel > Export to Excel, which does not use this setting.)</p> <p>Caution: Users with the FSD privilege see all results of reports; also, all privilege checking is bypassed on users with this privilege when they view report results. Users without the FSD privilege see the maximum number of reports specified in this property.</p>	50,000
Maximum Running Reports	Defines maximum number of reports that the application server will run simultaneously.	50
Notification Wait Time (in seconds)	Determines how often the system "wakes up" to check for notification emails to send. Default is 600. Valid setting is 30 to 3600 seconds.	60
Notification Time Out (in seconds)	This setting is the timeout time for the user transaction in the notification thread. Valid setting is 30 to 3600 seconds.	1800

Preference Name	Description	Default
Object Cache Table Size	Sets the relative size of the object cache table (Hashtable), which helps determine how objects are distributed in cache (smaller means more objects per row, larger means fewer objects per row). You can choose Small, Medium, or Large Table (default is Medium Table), but it is an internally used attribute used in server implementation; therefore, no recommendation regarding performance is offered for this setting.	Medium Table
Optimized Replication	When there are more than two File Managers, allows the PLM system to keep track of the File Managers that contain each file. During replication, the requesting FM only contacts other FMs that contain the file, and downloads a given file from the nearest FM (shortest 'ping'). Settings are Enabled or Disabled. Disabled can be set to troubleshoot problems with the optimizations.	Enabled
Recently Visited Folder Size	Controls the maximum number of objects that each user can store. The list selection allows these values: 10, 25, 50, 100.	10
Reference Designators Allow Range Expand Collapse	Allows reference designators to be described as a range instead of a sequence. See Reference Designators Allow Range Expand Collapse on page 386.	Collapse
Reference Designator Range Indicator	The symbol that appears between lower and upper range values in reference designator statements. Available symbols are asterisk (*), at (@), caret (^), plus (+), hyphen (-), colon (:), semicolon (;), tilde (~), or None .	Hyphen (-)
Reminder/Escalation Weekend Setting	In escalation and reminder periods of changes, determines how the system will count weekend days (Skip Saturday <i>or</i> Sunday, Skip Saturday <i>and</i> Sunday, or Don't Skip [= <i>count both weekend days</i>]). This preference is not part of Product Portfolio Management scheduling.	Don't skip
Retain Local Files	When adding an attachment to a business object or checking it in, determines whether local files (on user's computer) will be deleted or retained, or whether the user is prompted to choose to delete it (Yes) or not (No). Settings are Delete, Retain, and Warning. Note: This preference is applicable only in Advanced uploader, and is not applicable in Standard uploader: Standard uploader does not delete files automatically when this preference is set to Delete.	Warning
Save As Attachments	Permits one of two ways to replicate a file, or allows each user to be prompted to choose the method. Settings are Prompt, Create new copy of file(s), Do not copy file(s), and Reference existing file(s). See Save .	Reference existing file(s)

Preference Name	Description	Default
	As Attachments on page 397.	
Save As BOM for Different Classes	Indicates whether or not to copy BOM tab values when copying from one item to another. See more information about the “Save As” preferences in Copy Values along with Tabs on page 386.	Values Copied
Save As Manufacturer for Different Classes	Indicates whether or not to copy Manufacturers tab values when copying from one item to another.	Values Copied
Save As Page 2 for Different Classes	Indicates whether or not to copy Page Two tab values when copying from one class to another.	Values Copied
Save As Page 3 for Different Classes	Indicates whether or not to copy Page Three tab values when copying from one class to another.	Values Copied
Save As Page 3 for Different Subclasses	Indicates whether or not to copy Page Three tab values when copying from one subclass to another.	Values Copied
Signoff User Dual Identification Type	Controls whether approve/reject signoff (including user signing off for “self” or for another user due to Escalation or Transfer Authority) requires a dual identification, or “second signoff.” Settings are N/A (Not Applicable, the default), User ID, and Login Password. Selecting N/A means that these situations will not require a dual ID; selecting either User ID or Login Password means a dual ID is always required to sign off. For more information, see Signoff User Dual Identification on page 387.	N/A
Threshold (in seconds)	One of the settings that determines when certain system actions, such as cleanup and reset tasks, are performed on any object that is idle in the logged-in user session longer than the value of the setting. Valid setting is 30–3600 sec.	300
Thumbnail Support	Allows the system to present thumbnail representations for Agile objects in Web Client.	Disabled
Web Client Timeout for Corporate Users	This setting dictates the number of minutes corporate users can be idle in Web Client before Agile terminates the session.	25
Web Client Timeout for Supplier Users	This setting dictates the number of minutes supplier users can be idle in Web Client before Agile terminates the session.	25

Note The proxy server for your Agile PLM system has a default connection timeout of 1500 seconds, or 25 minutes. For information on how to change the proxy timeout setting, see the chapter “Installing and Configuring Agile Web Components” in the *Agile PLM Installation Guide for Windows*.

Details of Selected Preferences

This section contains details about selected systemwide Preferences.

Agile Drive

Enabling the Agile Drive preference allows the administrator to access the Agile Drive system of managing the file attachments of Agile objects in the form of files and folders from your computer system, without requiring you to invoke the Agile application. It connects Agile's Distributed File Manager as a Network Place on your system, thus enabling Explorer-like operations, such as copy or delete, on file attachments of Agile objects. See [Administering Agile Drive](#) and *Agile Drive User Guide* for more information.

Allow Download of Productivity Components

This preference controls whether your users will have access to the Java applets that permit advanced file uploading, download of multiple files and the Excel integration (in PG&C). If it is set to No, users will not see the File Productivity Preference in their own user profile. If it is set to Yes, users will see the File Productivity Preference and be able to choose their own method.

- The preference allows the following functions regarding attachment management. The systemwide preference operates in conjunction with each user's File Productivity (user) Preference.
 - Advanced File Uploader
 - Automated checkin based on checkout location
 - Allow download of individual files instead of a Zip file in Web Client.
- The preference allows the Microsoft Excel-based Client to be integrated with Agile PG&C, which allows supplier users to provide compliance information to buyers while using Microsoft Excel.

Allow Password Reset

The **Allow Password Reset** preference lets you choose whether Web Client users who forget their password can automatically receive a new one. The default setting is No, which forces a user to contact the administrator to reset the password. Java Client users who forget their password must contact the administrator for a new one.

When **Allow Password Reset** is set to Yes, the **Forgot your password?** link appears on Web Client's login screen. Since **Preferences** are *systemwide* settings, every Web Client user sees the link. If a user clicks the **Forgot your password?** link, he can enter his username and email address to receive a new

random seven-character password. When the user logs into Web Client again, he is prompted to choose a new password.

Copy Values along with Tabs

The several “Save As” preferences determine whether values are copied from the **BOM**, **Manufacturers**, **Page Two**, and **Page Three** tabs when you use Save As to copy an object from one class to another. By default, values are copied.

Caution	There are exceptions to copying values during Save As operations. If an attribute in the source object does not exist or is not used in the target object, it is not copied even if the Save As preference is set to Values Copied. Also, if an attribute is a list value and the list ID of the source attribute is not the same as the list ID of the target attribute, the value is not copied even if the Save As preference is set to Values Copied.
----------------	---

Content Service Wait Time

The **Content Service Wait Time** preference controls how often the system processes transfer order objects. For example, if this setting is 300, every 300 seconds the system checks if there are any transfer order objects to process and begins to process them.

Content Service Maximum Retries

The **Content Service Maximum Retries** preference controls how many times, after the initial attempt, a transfer order object will attempt to make delivery to a failing destination. For example, if this setting is 5, the transfer order object will make one attempt at delivery. If that attempt fails, the transfer order object will make up to 5 more attempts. After the last attempt, further delivery attempts are blocked.

Reference Designators Allow Range Expand Collapse

This preference (RDAREC) determines how reference designators are displayed in the BOM table when *not* in edit mode. This preference affects only the end user display of the reference designator data stored in the Agile database.

- **Expand** — Displays ranges of reference designators in expanded format; each reference designator is listed and the range is not collapsed. For example, the range of reference designators beginning with **R1** and ending with **R5** is displayed as:
R1, R2, R3, R4, R5
- **Collapse** — Displays ranges of reference designators in collapse or concatenated format. Ranges of reference designators (3 or more reference designators in a sequence) are indicated by the first reference designator in the sequence, the reference designator range indicator character, and the last reference designator in the sequence. For example, the range of reference designators beginning with **R1** and ending with **R5** is displayed as:

R1-R5

Signoff User Dual Identification

FDA-regulated or other companies may have a corporate policy that requires double authentication of user identify in approving or rejecting change orders. The Signoff User Dual Identification preference controls whether approve/reject signoff requires a dual identification, or "second signoff."

This setting is applied to the Review and Released statuses of all default and custom workflows, that is, when the Signoff dialog is filled in by a user, the system verifies the electronic signatures before advancing the workflow to the Review or Released status. The preference comprises all situations when the user is signing off for himself, signing off as a member of a user group, signing off for another user due to Escalation or Transfer Authority, or a combination of signoff responsibilities. (The Signoff UI options are detailed in *Getting Started with Agile PLM*, the chapter about Workflow.)

The administrator must attend to a combination of settings to properly realize the "second signoff" functionality.

Setting this preference to N/A (Not Applicable, which is the default) means that signoffs require only a single signoff from any user in any capacity. The password already required to sign off is the Approval Password; this represents the first level of security in the signoff protocol.

The other two settings, User ID and Login Password, effectively enable the dual ID requirement for any user in any signoff capacity. They dictate that users also be required to enter their User ID (also called username), or the Login Password.

If you set this preference to Login Password, then it is imperative to ensure that every user's Use Login Password for Approval property is set to No; once you change all users' Use Login Password for Approval property to No, only then can you set the Login Password. (For bulk settings, contact your Agile representative for a script called SecondSignature.Zip.)


If you set this preference to User ID, you should set Display User ID preference to No

Languages tab

The **Languages** tab lists the available languages for the Agile system. The administrator can select one or more languages at a time and enable or disable them using the Enable/Disable buttons.

Note By default, English is enabled and you cannot disable English.

You will be able to see in two columns the name of the language and whether or not the language is currently enabled or disabled with a setting of Yes or No.



Important This list of supported languages is current as of May, 2010 and is subject to change. Please see the languages tab found in the **Preferences** node for your current installation supported languages.

Once you are finished with applying the settings you desire then click **Save**. At this point there will be a message alerting you that you must restart the server in order to apply the changes.

The Agile PLM server will successfully load translated labels and fields for languages that are enabled. The Administrator history is only generated for enabled languages.

Note User preferences for languages are limited to the enabled system languages.

For more information about Agile PLM Language settings, see the [Administrator Functions in Java Client](#) on page 30 chapter.

Licenses

This chapter includes the following:

- General Info Tab 389
- Modules Tab 390

The **Licenses** node appears under **Server Settings**. This node provides information about your company's Agile PLM license configuration.

Agile's "User Licenses" are tabulated in **General Info** tab. User licenses are assigned to each user by the Agile PLM administrator. The combination of assigned user licenses and assigned roles and privileges determines which specific tasks a user can perform.

To view licenses information:

1. Under **Server Settings**, double-click **Licenses** node. The Licenses window appears.
2. Click the **General Information**, **Modules**, or **History** tab.

General Info Tab

Agile PLM has three types of user licenses: Named (formerly "Power"), Concurrent, and Restricted.

Restricted users are people outside your company (such as distributors and suppliers) who are given limited access to the Agile PLM system.

Named users and Concurrent users have access to the same Agile PLM functionality based on their roles and privileges and the company's licensing.

The key difference is that users with a Named license are not applied against concurrency counts. This means that a Named user can log in to the system at any time. All users who are not Named or Restricted are subject to concurrency counts, and may be locked out of the system due to a concurrency limit.

The **User Category** field in every user's profile displays which user license has been assigned to the user. For more information, see [User Properties Defined](#) on page 172.

The **General Info** tab of the Licenses window includes the information shown in the following table. You cannot edit this information.

"Name" field	Description
Count of Named Users	Shows the number of users who are active.
Count of Restricted Users	Keeps track of how many Restricted User licenses have been assigned.

"Name" field	Description
Count of Concurrent Users	Shows the number of Concurrent User licenses purchased by the company. Concurrent users can access all Agile PLM functionality purchased by the company, but are subject to concurrency counts, and may be locked out of the system due to a concurrency limit.
Total Count of Users	Keeps track of how many PLM users of all types have been created by the company.

Modules Tab

The biggest change to "licensing" in Agile PLM is the removal of Agile's "Server Licenses". An Oracle "license key" was obtained (at <http://licensecodes.oracle.com/agile.html#PLM>) and was input at install time.

Now the administrator uses the **Modules** tab of the **Licenses** node to simply select the PLM solutions that his company has purchased. This will enable those PLM Classes and other solution-based functions that pertain to your company's business, while disabling those classes and functions that do not pertain.

For Product Collaboration, select Yes from the drop-down list. Then open each of the remaining drop-down lists and select Yes or No, as appropriate. When you are finished and click the Save button, you will be prompted "Please verify your company is contractually licensed to use the modules [PLM solutions] selected." You will need to re-start the system for a module selection to take effect.

Product Portfolio Management (PPM) is the only PLM solution that can operate without Product Collaboration (PC); however, it is likely that even a company using only PPM will also use PC.

Important While it is possible to enable a PLM solution (by selecting Yes in **Licenses > Modules**) that your company has not purchased, it is not a Best Practice to attempt to do business using an unpurchased solution. You are likely working closely with an Oracle Consulting – Agile Practice representative, and you will likely need Support services at some point. However, if a problem you have encountered has been caused in the course of deploying and creating business objects from a PLM solution that your company has not purchased, you will find it more difficult to obtain the support for PLM that you and your company require.

If you encounter difficulties in enabling the PLM solutions that your company has purchased, please contact your Agile PLM representative.

Task Monitor and Task Configuration

This chapter includes the following:

▪ Task Monitor	391
▪ Task Configuration	392

Task Monitor

The **Task Monitor** node is used to track the progress of certain scheduled tasks. These include:

- **Report tasks** – standard and custom reports that are scheduled to be executed
-
- Note** Administrator reports cannot be scheduled.
-
- **User tasks** – refreshes user list from Directory Server (for example, LDAP server)
 - **Full Text Search task** – indexing of attachments for full text search
 - **Attachment Purge task** – periodic purging of attachments in the DFM server
 - **PPM-specific tasks** – there are several Activity tasks
 - **PCM-specific tasks** – there are several RFQ Notification tasks
 - **PG&C-specific task** – the Compliance Rollup task has been added to manage scheduled compliance rollups.

You can use the **Thread Status** dropdown list to display only the tasks matching the following criteria:

- **All** – shows all tasks
- **Scheduled** – shows tasks scheduled when it's generating schedule results.
- **Running** – shows tasks currently running; this is the default filter
- **Finished** – shows tasks that have been successfully executed
- **Failed** – shows tasks that failed during execution
- **Timed Out** – shows tasks that timed out before full execution. Compliance Rollup task cannot time-out.



Note Thread status criteria (except for All) do not apply to all types of tasks. For example, report tasks are listed in the Task Monitor window only when the selected **Thread Status** is All or Finished.

The following table lists the properties of the Task Monitor window. The properties are read-only.

Property	Notes
Name	Name of the scheduled report (custom or standard). Null for all other tasks.
Task Type	Report Task, FTS Task, or Attachment Purge Task.
Owner	Name of the owner of the report schedule. Null for all other tasks.
Time Executed	When the task began.
Status	Current status of the task: Scheduled, Running, Finished, Failed, Timed Out

The **Purge** button allows you to delete tasks listed in the Task Monitor window. The Purge action applies only to selected tasks that fall within the specified date range.

To purge tasks from the Task Monitor:

1. Select a Thread Status to list certain tasks, such as all tasks or finished tasks.
2. Select one or more tasks.
3. Click the **Purge** button .
4. Specify values for **From Date** and **To Date**. Tasks that fall within the date range will be purged. Click the  button to select a date and time for each field.
5. Click **OK**.

Task Configuration

From the **Task Configuration** node, you can manage various scheduled server-side activities such as reports and full text search indexing. Tasks never “time-out” before completion.

Name	Description	Default interval (minutes)
Refresh User List From Directory Server	Updates the Agile PLM user list with information from the Directory Server.	1440 (1 day)
Report Task	Checks if there are any scheduled report tasks to run. If so, it generates the report in the background, saves it on the file server, and sends an email notification to the report's owner and shared users.	30
Activity Summary Task	In PPM solution, identifies the list of activities scheduled for the coming week and notifies the owners in a summary format.	User-defined
Full Text Search Scheduler	Indexes the content in files for full text search capability.	600 (10 hours)

Name	Description	Default interval (minutes)
Attachment Purging Task	Moves outdated files into a special folder and cleans up metadata in the database. The system is hard-coded to begin this process at 6:00 am local time; the default interval value of 1440 re-starts the process 24 hours later. Another value entered for this task alters the start time, then re-starts it at the new interval. See Use Case for Attachment Purging Task on page 364 for a particular use case of Attachment Purging Task.	1440 (1 day)
Activity Reminder Task	In PPM solution, identifies the list of activities that should start today and reminds the owners of these activities.	User-defined
Activity Health Task	In PPM solution, updates the “health” for all activities. It also updates the actual duration, variance, and estimated variance for these activities.	2
Compliance Rollup Task	In PG&C solution, runs compliance rollup calculations. Note: Even if the Product Governance & Compliance server license is disabled and not available, “Compliance Rollup Task” still appears in this list of tasks.	30
Due Tomorrow Notifications Task	In PCM solution, this sets how often the server checks for new RFQ-related notifications.	2
Admin Cache Synchronization Task	Synchronizes servers via Web Client > Tools > Administration > Cache Health Monitor .	5
Schedule Event Task	The settings for this task run in support of triggered events that use the Scheduled Event event type.	30
Compliance Migration Task	This task sorts all legacy compositions into three categories: Fully Disclosed, Partially Disclosed, or Undisclosed. Note In PG&C solution, for upgrades in the 9.2.x releases, this task must be enabled and run <i>once</i> ; then this task can be disabled and is not needed.	1 (this task is run only once by upgrade customers)

When you double-click a task in the **Task Configuration** page (anywhere in the row), the Task Configuration **General Info** window appears. It has the following properties; you can modify the properties and save the new settings.

Property	Description
Name	Name of the task being configured.
Task Interval	Periodic time interval in minutes after which the server updates the status of the task. In general, the value for Task Lookback Window should always bigger than the value for Task Interval to make sure that no event is skipped.

Property	Description
Task Delay Time	How many minutes the event is delayed before it starts to run.
Task Lookback Window	<p>How far back in minutes the task manager is to look to retrieve the events that can be run now.</p> <p>See Use Case for Attachment Purging Task on page 364 for a particular use case that involves temporarily re-setting Task Lookback Window.</p> <p>In general, the value for Task Lookback Window should always bigger than the value for Task Interval to make sure that no event is skipped.</p>
Task Max Event Number	How many events can be running at the same time on one server.
Task Restart Upon Failure	Indicates whether the event should be restarted after it failed. Yes or No.
Task Load Across Server	Indicates whether the event can be executed at the same time in different servers of a cluster. Yes or No.
Task Disabled	<p>Indicates whether this task is disabled (Yes) or enabled (No).</p> <p>Notes: In order for a given task to be executed, this property must be set to No. Also, when this property is changed for any task, it is no longer required to re-start the system.</p>
Task Start Time	<p>Allows you to specify the exact time a task should start. For example, you can specify that an Activity Reminder Task or an Activity Summary Task should be triggered at 8 a.m every morning.</p> <p>Note: Once you reset the time, you must restart the server for the changes to apply.</p>

To disable a task in the Task Configuration window:

1. Double-click the task to open it.
2. In the **Task Disabled** list, select Yes.
3. Click **Save**.

Administering Attachments

This chapter includes the following:

▪ Evaluating Your Company's Needs with Attachments or Designs	395
▪ Administrator Settings Related to Attachments	395
▪ Assign Roles and Privileges for Attachments	400
▪ Document Management Enhancements	406
▪ Generating Attachment Quick Access URLs	407

Evaluating Your Company's Needs with Attachments or Designs

As with other areas of Agile PLM administration, the most important step comes before setting properties in Administrator. You have to determine an overall “policy” that supports your company's uses of attachment files, file folders, and design models.

As you decide about company objectives, these are a few factors you might evaluate:

- Does your company produce CAD design and graphic files? If so, you will build from the Designs class. Please refer to the next chapter,
- Does your company need to organize and track attachments and bundles of attachments? This may indicate building from the File Folder subclass.
- Are there other special purposes or uses of Agile's attachment capabilities to take into account?
- Invisible or Visible file folders?
- How should attachment files be named? Are such files to be named in a dictated or organized system? Or is it alright to allow users to name attachment files and count on users to use file folders to search and find specific attachments?

Administrator Settings Related to Attachments

This section collects various Administrator settings – SmartRules, systemwide Preferences, and a user preference – for convenience. Roles and privileges that pertain to attachments are discussed in a subsequent section. Refer to node-specific chapters for more information about the capabilities in Administrator.

File Management in Agile PLM

Administrator settings on the **Server Settings > Locations > File Manager** tab are important in relation to

attachment files and where originals and copies are found. This is documented in [File Management in Agile PLM](#) on page 356.

The Checksum internal utility is a security measure against improper handling of files. Reset privilege and Checksum Computation preference are described in [Handle File Checksum](#) on page 358.

How SmartRules affect Attachments

Copy Files To Rev

The Copy Files To Rev smartrule controls automatic copying of attachment files to a new revision; that is, the pending item revision that is created when an item is added to the Affected Item table of a change. The system checks this SmartRule only when a pending change is created and not when attachments are added. Possible settings are Copy, Reference (the default), Disallow, Copy with Warning, and Reference with Warning.

The following table illustrates how each setting works in the case of the following example:

- Part 55, Revision B, **Attachments** tab table lists attached file Test.txt, version 3; that is:
File Name = Test.txt, **File Folder** = Folder004, **Folder Version** = 3.
- Part 55, Revision B is added to the **Affected Items** tab of a change object, thus creating pending revision C.

Setting	How it works
Copy	<p>For the item's new pending revision, Agile creates a new file folder and creates a new copy of the attachment file, which is placed in the new file folder.</p> <p>So, when pending revision C is created, the Attachments tab table lists the same attachments as revision B, that is, revision C inherits the same attachments as revision B:</p> <p>File Name = Test.txt, File Folder = Folder004, Folder Version = 3</p>
Reference	<p>Agile uses the existing file folder and creates a new reference to it on the item's pending revision Attachments tab.</p>
Disallow	<p>When pending revision C is created, the Attachments tab table is empty. No attachment references are copied.</p>
Copy with Warning	<p>The same as the Copy setting, with the option of choosing no attachments for the new pending revision.</p> <p>When you add items to the pending ECO, you are presented with a warning dialog that includes a row for each item you are adding. To add the item and to copy the attachments, check both the Add checkbox and the Attachments checkbox. To add the item with no attachments, check only the Add checkbox.</p>
Reference with Warning	<p>The same as the Reference setting, with the option of choosing no attachments for the new pending revision.</p> <p>When you add items to the pending ECO, you are presented with a warning dialog that includes a row for each item you are adding. To add the item and to reference the existing attachments, check both the Add checkbox and the Attachments checkbox. To add the item with no</p>

Setting	How it works
	attachments, check only the Add checkbox.

If you set this smartrule to Disallow, files that were added to the Introductory revision after the object was associated with a change (that will result in released Rev A) will not be copied to subsequent revisions. Also, when a new Change is created, all the files that were added to the Introductory revision won't be added to the newly created revision.

Check In Attachment With Different File Extension

This smartrule determines whether an attachment file that is being checked in can have a different file extension than the file that was checked out. This smartrule applies to all business objects.

This rule is overridden when a business object's attachment is Latest-x and the file extension in the attached file folder is changed and is therefore different than the extension of the business object's checked-out file.

How Preferences affect Attachments

Systemwide preferences are documented in [Preferences](#) on page 379.

Filename Prefix

Agile File Manager uses a prefix that is attached to each file that is stored in the file vault. You can type in the identifier that will be automatically added to every attachment file. The default is "agile".

Optimized Replication

When there are more than two File Managers, this preference allows the PLM system to keep track of the File Managers that contain each file. During replication, the requesting FM only contacts other FMs that contain the file, and downloads a given file from the nearest FM (which is determined by shortest 'ping' to all the FM servers).

Settings are Enabled or Disabled. Disabled can be set to troubleshoot problems with the optimizations.

Save As Attachments

Here are further details on the available choices for the Save As Attachments preference. When Save As is used to create a new business object will include the same attached files; your choice is whether to create new copies of the files (which includes new file folders), to reuse the same file folders attached to the original business object, not to copy any files, or to allow the user to choose one of these methods at the time he performs the Save As operation.

Select the setting that best suites your company's business practices.

Note This preference does not apply to File Folder objects themselves, except as outlined in the table below.

For Product Portfolio Management objects, this preference applies only to attachments in the current object; it does not propagate down to all children tasks. The preference does apply when creating a new project from a PPM template.

The following table illustrates how each setting works in the case of the following example:

- Object ABC includes the following attachment:
File Name = Test.txt, **File Folder** = Folder004, **Folder Version** = 3.
- A user opens Object ABC and uses Save As to create Object XYZ.

Setting	Example of how it works
Create new copy of file(s)	<p>When Object XYZ is created, a new copy of the Test.txt is attached in a new file folder. Object XYZ's Attachments tab lists:</p> <ul style="list-style-type: none"> ▫ File Name = Test.txt ▫ File Folder = Folder013 ▫ Version = 1 <p>A new copy of Test.txt is created in the file vault, and a new file folder (Folder013, Version 1) is created.</p> <p>The end result (new copy of the file, new file folder, at Version 1) is the same as if the user had added the attachment Test.txt by using the Add Files button on the Attachments tab of Object XYZ.</p>
Reference existing file(s)	<p>When Object XYZ is created, it reuses the same attachments as the original Object ABC. Object XYZ's Attachments tab is the same as Object ABC's Attachments tab, and lists:</p> <ul style="list-style-type: none"> ▫ File Name = Test.txt ▫ File Folder = Folder004 ▫ Version = 3 <p>The end result (the file folder attachments are reused) is the same as if the user had added the attachment Test.txt by using the Add By Search button on the Attachments tab of Object XYZ, searching for Object ABC and selecting its attachment: Test.txt, Folder004, Version 3.</p>
Do not copy file(s)	<p>When Object XYZ is created, no attachments are copied from the original Object ABC.</p> <p>The end result is that the newly created Object XYZ has no attachments; its Attachments tab is empty.</p>
Prompt	<p>The user is prompted to select one of the Save As Attachment methods:</p> <ul style="list-style-type: none"> ▫ Reference existing file(s) ▫ Create new copy of file(s) ▫ Do not copy file(s) <p>Agile PLM always prompts each user whenever a Save As operation is performed. However, if the original Object ABC does not have any attachments (the Attachments table is empty), the prompt will not appear.</p>

Allow Download of Productivity Components

This preference controls whether your users — specifically Web Client users — will have access to Java applets that permit advanced features. Besides specific applications to the PPM and PG&C solutions, this preference enhances system behavior with regard to attachments in these three ways:

- The Advanced File Uploader is available to users in Web Client.
- Automated checkin is based on the checkout location in Web Client.
- Allow download of individual files instead of a single Zip file in Web Client.

Note Java Client users always have access to these advanced attachment features, regardless of the setting of this preference.

If this preference is set to Yes, the end user must also have the appropriate user profile setting for his **File Productivity Preference** attribute.

If you have set this preference to Yes, and a Web Client user does not have access to the advanced attachment features, check his user profile. See also [File Productivity User Preference in the User Profile](#) on page 399.

Setting	Results
Yes	File Productivity Preference attribute appears in the user profile, Preferences tab. User may set this to Advanced, Standard, or Prompt. If set to Advanced or Prompt, the Web Client user has access to advanced attachment features.
No	File Productivity Preference attribute does not appear in the user profile, Preferences tab. The Web Client user does not have access to advanced attachment features.

File Productivity User Preference in the User Profile

Note **File Productivity Preference** is a user preference – strictly, simply an attribute in every User object – not a systemwide preference. It is discussed here because it works in conjunction with Allow Download of Productivity Components systemwide preference: the **File Productivity Preference** user preference will not appear in any user's Profile if the Allow Download of Productivity Components systemwide preference is set to No.

User properties are documented in [User Properties Defined](#) on page 172.

This user setting controls whether the user has access to advanced productivity components, or standard components, or wants to be prompted in each situation. The available settings are Prompt, Advanced, or Standard. The default is Prompt; you as administrator can set any of the values for any user; each user can change the setting in their User Profile (again, assuming the systemwide preference **Allow Download of Productivity Components** is set to Yes).

Note The “Working with Attachments” chapter of *Agile PLM Getting Started Guide* includes instructions for the end user for setting his user profile **File Productivity Preference** and explains the behavior of each setting.

If the user preference is set to Standard mode, non-supported files will not be opened automatically. Instead, the user is prompted to choose Save or Open.

Note Make sure you choose appropriate character sets where required. There is a potential problem when adding files or URLs from a business object to a file folder object. If the file folder's File Description attribute has a Character Set = Numeric, but the business object's File Description attribute has a Character Set = Alpha or AlphaNumeric, the latter will override the former, meaning whatever control you wanted to impose in the file folder's File Description (being numeric) will be lost, the system will save the original character set.

Assign Roles and Privileges for Attachments

Agile PLM roles are fully documented in [Roles](#) on page 189, and privileges are fully documented in [Privileges and Privilege Masks](#) on page 211. You should evaluate your objectives carefully before creating new roles and privileges. While customized roles and privileges may need to be created, it is always preferable if your objectives can be handled by out-of-box roles and privilege masks.

The following section provides information about privileges that are constructed to realize attachment capabilities.

Attachment Privileges

Some privileges allow users to perform actions on attachments; we will call them “attachment privileges” in this discussion. Users who are assigned Folder Administrator or Folder Manager roles may need to review the information below.

The following privileges allow users to perform actions on attachments:

- Checkin
- Checkout
- Cancel Checkout
- GetFile
- PrintFile
- ViewFile
- Modify

Important GetFile privilege works in tandem with Checkout privilege to actually deliver the attachment file to the user's machine. A user with Checkout but not GetFile will see in History that the file is checked out, but it has not been downloaded to the user. The GetFile privilege (without Checkout) allows the administrator to permit a user to get a file – open it, read it – without being able to change it in the product record.

You can create privilege masks and roles that allow you to provide users all attachment actions from the business object **Attachments** tab; direct access to the file folder object is not required. Thus, file folder objects are “invisible” to the user, even though the user has the capability to perform all attachment actions from the business object **Attachments** tab.

Note Attachment actions performed from the business object's **Attachments** tab are carried out on the referenced file folder object. For example, checking out an attached file on the **Attachments** tab actually checks out the referenced file folder. However, if the user has the correct attachment privileges, he does not also require file folder privileges.

However, if required, attachment privileges can apply directly to file folder objects, and privileges for file folder objects should be reserved for those users who will actively maintain those objects. These users can search for file folder objects, open them, check files in and out on the **Files** tab, get files, print files, and view files. But you don't want every user to have this range of permissions on the file folders, and those roles don't give users the correct functionality anyway.

What will be more useful for standard users is having attachment privileges for specific classes or subclasses of business objects (or, as needed, specific objects). A user who has attachment privileges for manufacturer parts can perform attachment actions on any manufacturer part's **Attachments** tab, provided that the Folder Version selected in the attachments table is the latest version. If a user's attachment privileges pertain to a subclass of manufacturer parts, say, Resistors, the user can perform attachment actions on any resistor's **Attachments** tab, again provided that the Folder Version selected in the attachments table is the latest version.

As long as the latest version is selected, a user—from the **Attachments** tab of the current object—can check out and check in and perform the other attachment actions.

Therefore, a user with attachment privileges for *only* manufacturer parts can perform attachment actions from a manufacturer part's **Attachments** tab but *not* from an item's **Attachments** tab.

To summarize, users do not need privileges for file folder objects to work with attachments; however, they do need privileges for the business objects they will be working with (with the privilege specifying a class, subclass, or specific object). Users can create, check in, and check out file folder objects, but only in association with the Agile PLM class, subclass, or object for which they have business object attachment capability privileges.

Attachment Capability Privileges in a Role

Some out-of-box roles have all of the above-named attachment privileges for the object types that role would usually work with, that is, the object types that the role is designed to create and modify. They may also have file capabilities (get, view, and print) for other related object types.

For example, the Item Content Manager role includes all seven attachment privileges for items and changes. It also includes GetFile, PrintFile, and ViewFile privileges (not Checkout or Checkin) for manufacturers, manufacturer parts, and price objects (that is, objects that are listed on the

Manufacturers and **Prices** tabs of an item).

Following the Item Content Manager role as an example, you can create roles that allow users to get, print, and view attachments for all objects related to that user's Agile PLM system activities, and limit the checkin/checkout privileges to only those objects that the user can create and modify. A role that includes privileges for file folder objects does not allow you to control the user's attachment capabilities to the same level of granularity.

Modify Privilege and Attachments

The Modify privilege allows a user to modify or edit fields on the tab of an object. Modify privileges are assigned using the AppliedTo attribute settings.

Agile PLM uses Modify privilege mask Applied To properties to determine and control certain specific user actions and attachment capabilities. For example, if a user has a role that includes a Modify privilege mask for parts and the Applied To property includes the **Parts.Attachment.FileDescription** attribute, then that user is able to modify the File Description field on the **Attachments** tab of a part object. This same modify action will also modify the File Description field on the **Files** tab of the referenced file folder object, however, a modify privilege mask for the file folder object is *not* required.

The following table lists the Modify privilege mask Applied To properties and which attachment actions they control.

Note This table uses File Folder or Business Object as a placeholder for the class or subclass name in the Applied To attribute column. The actual class or subclass name in any privilege mask is determined by the reusable criteria specified in the privilege mask. (See [Privilege Mask Components](#) on page 225.) If you view the example privilege masks mentioned in the Notes column, the Applied To properties will be appropriate for that specific privilege mask (for example, Manufacturer parts.Attachments.FileName).

The Notes column lists at least one example privilege mask that demonstrates a privilege mask that provides the user action; it is not a comprehensive list of example privilege masks. In cases where a Modify privilege mask is not required, only the needed privilege mask is listed (such as Example - Checkin for File Folders). If multiple privilege masks (in addition to a modify privilege mask) are needed to enable the user action, they are all listed.

User action	Privilege	Class	Applied to	Example Privilege Mask or Role / Notes
File Folder attachment actions				
Add file to File Folder	Modify	File Folder	Files.FileName	Example - Modify File Folders
Checkin File from File Folder	Checkin	File Folder		Example - Checkin for all File Folders (criteria = Example - All File Folders) Example - Checkin for File Folders

User action	Privilege	Class	Applied to	Example Privilege Mask or Role / Notes
				(criteria = Example - All File Folders Checked Out By Me)
Delete File from File Folder	Modify	File Folder	Files.Filename	Example - Modify File Folders
<p>Example file folder roles:</p> <p>Example - File Folder Manager allows user to work with his own file folder objects.</p> <p>Example - File Folder Administrator allows user to work with any file folder objects.</p>				
Business Object attachment actions				
Add new attachment to Business Object	Modify	Business Object	Attachment.Filename	Example - Modify Mfr Parts
Add attachment by search to Business Object	Discover	Business Object (the business object being searched against)		As an example, if the user is searching for item objects from which to add attachments to a Mfr Part, then he requires: Example - Discover Items
	Modify	Business Object	Attachment.Filename	Example - Modify Mfr Parts
				Example - Component Engineer role includes both these example privilege masks and would allow a user to add an attachment to a Manufacturer Part by using Add Search to search for Items.
Add multiple attachments in one file folder to business object and specify Folder Description	Modify	Business Object	Attachment.Filename	Example - Modify Mfr Parts
	Modify	Business Object	Attachment.Folder Description	Example - Modify Mfr Parts
Checkin attachment on Business Object	Checkin	Business Object		Example - Checkin for Mfr Parts

User action	Privilege	Class	Applied to	Example Privilege Mask or Role / Notes
Remove attachment from Business Object	Modify	Business Object	Attachment.Filename	Example - Modify Mfr Parts
Edit File Description on Business Object Attachments tab	Modify	Business Object	Attachment.File Description	Example - Modify Mfr Parts
Edit Folder Description on Business Object Attachments tab	Modify	Business Object	Attachment.Folder Description	Example - Modify Mfr Parts
Show Version on Business Object Attachments tab	Read	Business Object	Attachment.Filename	Example - Read Mfr Parts

Markup Subclass

Note Attachment redline markups and file folder Ad Hoc redline markups are created, modified, and viewed in the AutoVue for Agile.

The Markup subclass of the File Folders class is used to save attachment-file redline markups. By assigning the appropriate privilege masks to different kinds of users, specific users (for example, vendors) can see and modify only their own markups, but cannot see markups created by other users.

For detailed information about Markup subclass privilege masks, see [Redline Markup Default Roles and Privileges](#) on page 405.

Markup subclass objects are visible in Agile PLM for any user that has Read privileges for Markup objects. For example, if a user searches for File Folders class objects, Markup objects are included in the search results. However, the redline markup file they contain can be viewed only when viewing the item attachment-file or the file-folder file with which the redlines are associated. Attempting to view the redline markup from the **Files** tab of the Markup subclass object displays an error message when the AutoVue for Agile opens.

See also [Discovery and Read Privileges](#) on page 241.

Markup Promotion

Markup Promotion is a generic capability supported within AutoVue to “promote” (copy) markup files from one base file to another. The user can promote markups from previous revisions (for change-based markup) or previous versions (for ad-hoc markup), permitting the user to see if the changes made in the following revision or version address the comments originally made in the markup.

This works with both File Folders class (therefore, objects from File Folder and Markup subclasses) and the new Designs class (objects from Design subclass). It works with both types of markup:

- Change-based – from Changes **Redline Attachments** tab
- Ad-hoc – from File Folders or Designs **Files** tab

Markups are selectable for promotion if they are on a previous revision or version and the base file extension is the same, for example, if Version 1 is **file_v1.pdf** and Version 2 is **file_v2.pdf**.

Redline Markup Default Roles and Privileges

Agile PLM uses the file folder subclass Markup to store attachment redline markups created in the AutoVue for Agile. Agile PLM provides a default set of Markup subclass privilege masks and two default roles, **Markup for Self** and **Markup for All**. If you have upgraded PLM, you must create these roles by referring to the example roles **Example - Markup for Self** and **Example - Markup for Others**. See also [Markup Subclass](#) on page 404.

Note The **Markup for Self** and **Markup for All** default roles replace the Attachment Redlines for Self (ARS) and Attachment Redlines for Others (ARO) privileges. The privileges ARS and ARO are disabled; ARS and ARO privilege masks have no effect. However, any previously assigned custom ARS or ARO privilege masks are not deleted or removed; so, you can refer to the ARS and ARO privilege masks when creating and assigning redline capabilities with Markup subclass privilege masks or roles.

A user with Markup capabilities can create and modify the following types of redline markups:

- Create and modify attachment redline markups for the affected items of any change order object for which he has Read privileges.
- Create and modify Ad Hoc file folder redline markups for any file folder object for which he has Read privileges.

The **Markup for Self** role allows the user to redline attachments from the **Affected Items** tab of a change order and to Ad Hoc redline files on the **Files** tab of a file folder, and he can modify or delete only those redlines he created. The privilege masks in the **Markup for Self** role are based on the Markup for Self criteria: Markup Page Two.Create User Equal to \$USER.

The **Markup for Others** role allows the user to redline attachments from the **Affected Items** tab of a change order and to Ad Hoc redline files on the **Files** tab of a file folder, and he can modify or delete only those redlines created by other users. The privilege masks for the **Markup for Others** role are based on the All Markups criteria.

The following table lists the default privilege masks in each of the default roles for Markup subclass:

Markup for Self role	Markup for Others role
Read My Markups	Read All Markups
Modify My Markups	Modify All Markups
Checkout My Markups	Checkout All Markups
Checkin My Markups	Checkin All Markups

Create Markups	Create Markups
----------------	----------------

Redline Markup Privilege Guidelines

The following rules and guidelines apply to redline markup capabilities:

- If a user does not have Read privilege for a specific Markup object, the associated redline markup is not listed in the markup panel in AutoVue for Agile.
- If a user does not have Modify privilege for a specific Markup object listed in the AutoVue for Agile markup panel, the AutoVue for Agile markup panel is disabled and the user cannot edit any redline markup for that viewed file.
- If a user does not have a Create Markup object privilege mask, he cannot create new markups from the AutoVue for Agile.
- In **Admin > Settings > Data Settings > Classes**, for **File folders** class, the Page Two attribute **Create User** must be enabled. The default value is \$USER. This attribute is used to determine "ownership" of each redline markup.
- In order to differentiate between privilege masks for Markup subclasses and all other file folder subclasses, Create, Read, Modify, Checkout, and Checkin privilege masks for file folders must use criteria that specify specific file folder subclasses (for example, Markup subclass and File Folder subclass). This allows you to use a set of privilege masks specific to Markup subclass. The Markup-specific privilege masks are assigned only to those users to whom you wish to grant redline capabilities.

In contrast, privilege masks based on criteria that specify the File Folders base class or the File folders class will apply to all file folder subclasses, thus depriving you of the ability to restrict redline capabilities (by *not* assigning to users Markup subclass privilege masks). That is, privilege masks based on criteria for the File Folders base class or the File folders class will always apply to Markup subclass objects.

- The default Markup subclass privilege masks are based on broadly-defined reusable criteria (**All Markups** and **Markups for Self**). However, you are not limited to these criteria when creating Markup subclass privilege masks. For example, you can enable a list attribute or a multilist attribute, then create criteria that will determine Markup capabilities based on the settings of that list attribute or multilist attribute.

Document Management Enhancements

A few recent enhancements concerning attachments are discussed below.

View All Versions

On the standard **Actions** menu, the most significant added Action is **View All Versions**. The View All Versions action is available in File Folder and Design objects.

The **View All Versions** utility is extremely useful as file-folder structures or design structures grow, as it tracks the versions of each design or file-folder. Each version displays:

- Approved (users who have approved file folder or design in workflow), including the Awaiting Approval icon (users who have not yet approved);
- Checkin Date;
- Checkin User (which captures the user who checked in the version, and also can read through to the design **Structure** tab and to **Attachments** tabs in designs or file folders);
- Change Info and Label (as filled in by users); and,
- Revision and Revision Date.

Many of these fields are pulled from the object's **Title Block** tab.

Using the **View** dropdown, you can have a quick **View** of a selected version of the design, or select two versions and **Compare** them visually.

Limit Attachment Size

Administrators can set the maximum file size that can be uploaded at **System Settings > Viewer and Files > Upload File Size Limit (in MB)**. This setting defines the maximum size (in MB) of uploaded files for Java Client, Web Client, Portal Client, and SDK.

The default value, 0, indicates "No Limit"; any non-negative integer sets the size limit in MB. Users will see an error message in Java and Web clients if a file is too large. Files that successfully upload (before a failure occurs) remain uploaded, other files (after a failure occurs) will not be uploaded.

Identify Checkin User

The Checkin User field is available on File Folders and Designs **Title Block** tab and on any business object's **Attachments** tab. It identifies the user who checked in the specified version.

This field is not available on Project Content Tab.

URLs can be up to 255 characters

Attached URLs can be up to 255 characters in length.

Generating Attachment Quick Access URLs

Attachment URLs allow you to do the following:

- Generate a URL for an attachment on item objects.
- Generate a URL for a file on file folder objects.
- Generate a URL for a file on the **Content** tab of Project objects.
- Paste URLs from Agile to another application
- Externally open files outside of the Agile application.

You can generate attachment URLs from Items, Activities, and File Folders by two methods:

- Using Agile PLM commands to copy a URL to your clipboard:

[Agile-Generated Attachment Quick Access URLs](#) on page 407

- Manually typing an Attachment Smart URL in an easy-to-understand format:

[User-Generated Attachment Quick Access Smart URL Formats](#) on page 408

The URL format enables you to identify which object and files are being referenced. Because of the easy-to-understand format, you can generate your own URLs to point to specific file attachments without logging into the Agile system, if you know where the files are located.

Agile-Generated Attachment Quick Access URLs

From Web Client, you can only generate Attachment Quick Access URLs from the **Attachments** tab of any object, the **Content** tab of Activities, and **Files** tab File Folders by clicking **Get Shortcut** after performing one of the following scenarios:

- Selecting **only** one row from the **Attachments**, **Content**, or **Files** tab to generate a URL that points to the folder corresponding to the file on that row.
- Selecting all the rows on the **Attachments**, **Content**, or **Files** tab to generate a URL that points to the collection of files on the tab.

Note You must have Read privileges for an object in order to generate a URL for the object.

Caution	If you select more than one row on the Attachments , Content , or Files tab, the Get Shortcut link is disabled.
----------------	--

The URL is copied to your clip board. You can then paste it into another application or file, such as a word processing file, a spreadsheet file, or an email.

User-Generated Attachment Quick Access Smart URL Formats

With the easy-to-understand Smart URL format, you can generate your own URLs to point to specific file attachments without logging into the Agile system, if you know where the files are located.

The formats of user-generated attachment Smart URLs depend on the object type, and fall into three main categories:

- [Item Attachment Quick Access URL Formats](#) (on page 408)
- [File Folders Quick Access URL Formats](#) (on page 410)
- [Program Content Quick Access URL Formats](#) (on page 411)

Item Attachment Quick Access Smart URL Formats

You can generate Smart URLs for item attachments in the following format:

[http://<server:port>/<VirtualPath>/link/<ObjectType>/<ObjectNumber>\[/Revision/ChangeNumber\]/files/Folder/<FolderNumber>\[/<FileAction>\]](#)

or

[http://<server:port>/<VirtualPath>/link/<ObjectType>/<ObjectNumber>\[/Revision/ChangeNumber\]/files/<FileName>\[/<FileAction>\]](http://<server:port>/<VirtualPath>/link/<ObjectType>/<ObjectNumber>[/Revision/ChangeNumber]/files/<FileName>[/<FileAction>])

where

<Server:Port>/<Virtual Path> element	Identifies the Agile instance
link	The text "link" identifies the URL as a special attachment URL to the Agile server.
ObjectType	Refers to the subclass of the Item, File Folder, or Project/Activity.
ObjectNumber	Refers to the actual object number for the object type.
Revision	Identifies an item revision by specifying the change number corresponding to that revision.
ChangeNumber	Identifies a unique revision (Released or Pending) of the item. If the number is not specified, the latest released revision is attached. If the number is not specified and the item does not have a released change, the Introductory revision is attached.
Folder	Indicates that the object is a file folder, not the actual file.
FolderNumber	Identifies the file folder related to the selected row. The version of the file retrieved is the most current version, based on the specific revision of the item.
FileName	Refers to the name of the specific file attached to the specified revision of the item.
FileAction	Determines the action performed with the retrieved files. Values are GET or VIEW. If FileAction is not specified, a GET is performed. If the parameters specified in the URL point to a single file, the file is retrieved in its native format. If the parameters specified in the URL point to a collection of files, then all the files are returned as a zipped file called "Download.zip".

If the specific revision of an item has multiple files contained in the same folder on the Attachments tab, but is referenced from different versions of the folder, then a Folder-based URL may not reflect the actual set of attachments from the item revision's Attachments tab.

Examples of user-generated URLs for item attachments:

- <http://myappserver/mycompany/Link/Document/DOC0001/files/Folder/Folder001>

Returns a zipped file containing all files from Folder001 that are attached to the latest released revisions of DOC0001.
- <http://myappserver/mycompany/Link/Document/DOC0001/files/Folder/Folder001/VIEW>

Opens all files from FOLDER001 that are attached to the latest released revision of DOC0001 in the Viewer.

Limitations for Item Object Attachment Quick Access Smart URLs

The following limitations apply to retrieving the attached files of item objects:

- In the case where a specific revision of an item has multiple files on its **Attachments** tab that belong to the same folder, but are referenced from different versions of the folder, a folder-based URL may not reflect the true set of attachments from that item+revision's **Attachments** tab. For example, consider an item P0001, whose revision A has two attachments: P0001_3dmodel.dwg and P0001_specs.pdf, both in Folder1. Assume that the DWG file is from version 2 of the file folder, and the PDF file is from version 5 of the file folder. In this case, the following URL:

<http://server:port/<VirtualPath>/link/Part/P0001/Revision/C0001/files/Folder/Folder1>

returns all the files contained in either version 5 or version 2 (results are not predictable) of Folder1.

However, the following URL:

<http://server:port/<VirtualPath>/link/Part/P0001/Revision/C0001/files/ALL>

returns the complete set of files belonging to revision A of the item, including P0001_3dmodel.dwg from version 2 of Folder1 and P0001_specs.pdf from version 5 of Folder1.

- You cannot generate an item-based URL that will return a file from a historical version of a file folder referenced on an item's attachments tab. The user can, however, generate a folder-based URL to achieve this.
- In case of the following format example,

[http://server:port/<VirtualPath>/link/ObjectType/ObjectNumber\[/Rev/ChangeNumber\]/files/FileName\[/FileAction\]](http://server:port/<VirtualPath>/link/ObjectType/ObjectNumber[/Rev/ChangeNumber]/files/FileName[/FileAction])

If two files of the same name (filename + file extension) exist on the attachments table, and a user generate a URL using filename, only the first encountered file is retrieved. If the "ALL" option is used to access files from the **Attachments** tab of an item where there are multiple files by the same name on the attachments table, or if a URL is generated to return all the files of a file folder where there are more than one file with the same name, an error is displayed indicating that there are multiple files by the same name and therefore a valid zip archive of files cannot be generated.

- If the ALL option is used to access files from a Project's **Content** tab where multiple files with the same name exist, an error is displayed indicating that there are multiple files by the same name and therefore a valid zip archive of files cannot be generated.

File Folders Quick Access Smart URL Formats

You can generate Smart URLs for file folders in the following format:

[http://<server:port>/<VirtualPath>/link/<ObjectType>/<ObjectNumber>/files/<FileName>\[/</version>\[/<FileAction>\]](http://<server:port>/<VirtualPath>/link/<ObjectType>/<ObjectNumber>/files/<FileName>[/</version>[/<FileAction>])

where

<Server:Port>/<Virtual Path> element	Identifies the Agile instance
link	The text "link" identifies the URL as a special attachment URL to the Agile server.

version	Identifies the specific version of the file folder. The value can be a number, or the string, LATEST (default).
FileName	Refers to the name of the specific file from the folder or string ALL which attaches all the files in the specified version of the folder. If more than one file of the same name exists in a specific version of a folder and a URL is generated based on filename, only the first version of the file is attached. You cannot use the ALL value to access files from a folder where more than one file of the same name exists.
FileAction	Determines the action performed with the retrieved files. Values are GET or VIEW. If fileaction is not specified, a GET is performed. If the parameters specified in the URL point to a single file, the file is retrieved in its native format. If the parameters specified in the URL point to a collection of files, then all the files are returned as a zipped file called "Download.zip".

Examples of user-generated URLs for file folder attachments:

- <http://myappserver/mycompany/Link/FileFolder/Folder0001/files/abc.txt/1>
Gets the abc.txt file from version 1 of Folder0001.
- <http://myappserver/mycompany/Link/FileFolder/Folder0001/files/ALL/VIEW>
Opens all files from the latest version of FOLDER001 in the Viewer.

Program Content Quick Access Smart URL Formats

You can generate Smart URLs for files on the **Content** tab of Projects and Activities. The **Content** tab allows specification of any object as valid content and allows the addition of external files, just like the **Attachments** tab. However, the **Content** tab stores the folder object related to an attached file as valid content. So, when retrieving, you must attach the entire folder.

The Smart URL for files on the **Content** tab is generated in the following format:

[http://<server:port>/<VirtualPath>/link/<ObjectType>/<ObjectNumber>/content/Folder/<FolderNumber>\[/<FileAction>\]](http://<server:port>/<VirtualPath>/link/<ObjectType>/<ObjectNumber>/content/Folder/<FolderNumber>[/<FileAction>])

where

ObjectType	Represents the subclass of the Project object.
ObjectNumber	Represents the identifier of the Project object.
Content	Indicates the Content tab.
Folder	Indicates that a specific folder is being retrieved.
FolderNumber	Refers to the number of the folder being retrieved from the Content tab. The most current version of the folder is always retrieved.
FileAction	Determines the action performed with the retrieved files. Values are GET or VIEW. If fileaction is not specified, a GET is performed. If the parameters specified in the URL point to a single file, the file is retrieved in its native format. If the parameters specified in the URL point to a collection of files, then all the files are returned as a zipped file called "Download.zip".

Accessing Attachment Files using Quick Access URLs

After clicking or opening an Attachment Quick Access URL, a login popup appears and you must log into the Agile system to view the attachment. Agile PLM then validates that you have the appropriate privileges to get or view the file or set of files specified in the URL. The attachments are viewable in all supported browsers, the AutoVue for Agile, or the native application.

For example:

1. In an email, the user clicks the Attachment Quick Access URL and an Agile login popup is displayed.
2. The user enters her login information.

Agile PLM verifies that the user has the appropriate privileges to read and view the file.

Note	If the URL returns a collection of files and the user does not have the appropriate Get or View privilege for one or more files, those files are excluded from the returned collection. However, a collection of files is returned to the user containing the rest of the files for which he does have the appropriate Get or View privileges.
-------------	--

Administering Designs

This chapter includes the following:

▪ Evaluating Your Company's Needs with Designs.....	413
▪ Purpose of Design Data Model.....	413
▪ Designs Class Overview.....	414
▪ Designs Class Tabs.....	415
▪ Administrator Settings Related to Designs	418

Evaluating Your Company's Needs with Designs

As with other areas of Agile PLM administration, the most important step comes before setting properties in Administrator. This chapter assumes that you answered the first question in the previous chapter affirmatively.

- Does your company produce CAD design and graphic files? If so, you will build from the Designs class.

The Designs class is a business class in the File Folders base class.

Objects created in the Designs class have many of the same properties and behaviors of File Folders. The Designs class is enhanced for use with the Engineering Collaboration (EC) solution; therefore, this chapter highlights those differences. The chapter on [Administering Attachments](#) on page 395 contains foundation details about the File Folders base class.

Note Deployment of Design structures in Agile PLM requires an Agile EC integration. That is, full use of CAD design graphics files needs an integration application that can automatically check out and check in Designs objects, track and update parent-to-child versioning of design structures, and so forth. Contact your Oracle Consulting–Agile Practice representative for additional information about Agile EC.

Purpose of Design Data Model

The Designs class supports structures between Design objects with explicit versions – let's call these "design structures" – and it supports integration with CAD tools. The Design object is very similar to File Folders, but has a few "extras" and specific features to realize its intended purpose.

The Designs class overcomes limitations that have existed in PLM using Documents class and the "DocuBOM" data model, which were not expressly designed for CAD use-cases. Three primary issues are resolved with design structures:

- **Structure Resolution is easily captured**
 - "Structure" information between designs can be captured, as required by CAD

environments, while the "DocuBOM" structure does not directly support fixed structure resolution.

- **Data Navigation is greatly enhanced**
 - Structures of Designs objects are evident and easy to navigate, while the combination of Part-and-Document BOMs are difficult to navigate in the Agile user interface.
- **Change Control Process carries much less "overhead"**
 - The full change control process (in the Product Collaboration solution) has too much overhead for many CAD use cases.

Although the Designs class is enabled in new installations, it is disabled upon PLM upgrade: in upgrading installations, the Agile administrator must enable the Designs class.

Benefits of Designing Structures using the Designs Class

Besides the benefits to CAD environments mentioned above, additional benefits are:

- Easy recognition of CAD data in PLM; CAD data will "look" more like it does in CAD
- Users can "double-use" part names since Designs and Parts are separate classes of objects
- Searching for design objects will be easier for CAD engineers
- Using a single object has several advantages:
 - Change history is on the Design object instead of on a separate Change object
 - Design files are not in a separate "file folder"
 - Version-specific Where Used
 - Version-specific Routing Slip
- Designs class enables the next version of Agile Engineering Collaboration, which will capture and exploit the capabilities built into the PLM model structures.

Designs Class Overview

The Design object can be opened from Java Client, but it opens Web Client and the user works with Designs exclusively in Web Client.

There is a **Checkout** button, and modifications to a design structure cannot be done by a user without checking out the design.

Since a "parent" version of a design explicitly points at a "child" version, a user has to check out a version, update the children, and check it back in for the parent to reflect the changes. In CAD there can be multiple models for 1 part – there could be, for example, 20 or 30 versions of a single object – but in Product Collaboration the part is assigned to a single structure; moreover, the system lets you check in a "design structure" *without* checking in all child parts.

Now, those engineers who have "child" parts checked out must check that part back in, that is, he cannot "Cancel Checkout" for the part to "rejoin" the BOM. Attempting to do so will throw the error message: "This version is in use and cannot be canceled."

A feature of the Version dropdown list is that the checked-out version is incremented and displayed

in brackets, for example [4], so the user can always see what the new version number will be when the object is checked back in. This applies to both File Folders and Designs classes.

View All Versions

On the standard **Actions** menu, the most significant added Action is **View All Versions**. The View All Versions action is available in File Folder and Design objects.

The **View All Versions** utility is extremely useful as file-folder structures or design structures grow, as it tracks the versions of each design or file-folder. Each version displays:

- Approved (users who have approved file folder or design in workflow), including the Awaiting Approval icon (users who have not yet approved);
- Checkin Date;
- Checkin User (which captures the user who checked in the version, and also can read through to the design **Structure** tab and to **Attachments** tabs in designs or file folders);
- Change Info and Label (as filled in by users); and,
- Revision and Revision Date.

Many of these fields are pulled from the object's **Title Block** tab.

Using the **View** dropdown, you can have a quick **View** of a selected version of the design, or select two versions and **Compare** them visually.

Designs Class Tabs

The tabs on Designs objects are: **Title Block**, **Files**, **Structure**, **Routing Slip**, **Relationships**, **Where Used**, and **History**. Most of these are given a look in the sections below; **Relationships** and **History** tabs are documented in *Getting Started with Agile PLM*.

Title Block Tab

By default, the Design object **Title Block** tab contains the fields listed in the following table. The administrator determines which fields are enabled and visible on the **Title Block** tab.

In Web Client, the **Title Block** can contain two additional sections, called **PageTwo** and **PageThree** by default. Agile administrators can add custom class fields to **PageTwo** section and custom subclass fields to the **PageThree** section. The Agile administrator determines whether these sections are enabled, and what they are called.

Field	Description
Number	The Design object's number, completed when the file object is created.
Type	The subclass of this Design object. Depending on Agile system settings, this field is automatically completed when the Design object is created.
Lifecycle Phase	Current lifecycle; selected from a list.
Description	Text describing the Design object

Field	Description
Version	The currently selected version of the Design object
Last Modified Date	Date the Design object was last modified
Checkout Status	Indicates whether the Design object is currently checked out or checked in.
Checkout User	When the Design object is checked out, displays the user who checked out the Design object
Checkout Date	When the Design object is checked out, displays the checkout date
Checkout Location	When the checkout user's File Productivity Preference is set to Advanced, the checkout location is automatically filled in
Checkin Date	When the Design object is checked in, displays the checkin date
Create Date	The date the Design object was created
Label	Version-specific text field that holds a specified label
Component Type	Displays the type of component represented by the Design
Thumbnail	Displays information about thumbnail graphics in Design objects; whether it is enabled or not is determined by the systemwide Preference Thumbnail Support and the User Preference settings.
Revision	Version-specific text field that holds the targeted revision of the Design version
Revision Date	Version-specific date field that holds the revision date associated with the Design version
Checkin User	Version-specific field indicating the user who checked in the currently selected version; completed automatically

Files Tab

The actions available on Designs **Files** tab are generally the same as File Folders **Files** tab. Similarly, privileges around the **Files** tab of both kinds of objects will mostly be the same; however, for best control of user access, privileges should not be based on the File Folders *base class*, which will apply to the **Files** tab of both File Folders and Designs *class* objects.

In order for the end-user to execute **Files** tab actions for Design model objects, he must have the appropriate Modify privilege masks. Refer to [Attachment Privileges](#) on page 400, especially [Modify Privilege and Attachments](#) on page 402: see the section of the table for File Folder Attachment Actions.

Important If you are using privilege masks based on the File Folders *base class*, assigned users will have the *same* Modify, Checkin, Checkout (and so forth) capabilities for both File Folders class objects and Designs class objects. If you need to give users separate types of access to these two classes, you must create and define privilege masks based on the File Folders class (or subclasses) or the Designs class (or subclasses).

Structure Tab

The Designs **Structure** tab supports "read-through" fields from Designs **Title Block** tab or **PageTwo**.

Like the **Files** tab, the **Structure** tab can only be edited when the object is checked out.

In Structure, the parent explicitly specifies the version of the child.

The Multi-level dropdown allows you to **Expand** or **Collapse** the structure.

AutoVue for Agile supports Designs **Structure** tab as well as File Folder **Attachments** tab.

Note File Folders (objects from File Folder and Markup subclasses) do not have a Structure tab, and they cannot be in a model structure. On the other hand, where you can use an "attachment" (that is, a file folder object), you can use a Design.

Icons indicate whether a Design is:

- Checked out
- Attached
- Latest Version
- Has Attachments

Routing Slip Tab

The Routing Slip tab is functionally "version-specific". Signoff on the Design object only signs off that specific version of the object.

Adding and removing Approvers and Observers can be done only when Design objects are checked in. In order to add or remove approvers and perform signoff actions, the user needs the appropriate privilege masks for Design objects.

Where Used Tab

Files that are associated with this design are listed on two tables of the **Where Used** tab, the **Attachments** table and **Design** table.

The **Where Used** tables inherit **Structure** tab columns and read-through fields.

Administrator Settings Related to Designs

This section collects various Administrator settings for convenience. Refer to node-specific chapters for more information about the capabilities in Administrator.

Display Structure Tables SmartRule

The SmartRule “Display Structure Tables” offers the choice between No Display (appropriate for non-CAD business environments) or Display.

Design-specific Role & Privilege

Design Engineer is a Role tailored to create, access, and manage Designs class objects.

Privileges and privilege masks around the Designs business object use the Agile PLM Discovery and Read model, including on the **Structure** tab.

In order to add or remove approvers and perform signoff actions, the user needs the appropriate privilege masks for Design objects.

Note	When working in conjunction with a CAD-to-Agile PLM integration application, each CAD user must also be an Agile PLM user. Each CAD user must have appropriate PLM roles and privileges to allow him to perform Checkout, Modify, Checkin (and so forth) actions on Design model objects. Contact your Oracle Consulting–Agile Practice representative for additional information about CAD-to-Agile PLM integration applications.
-------------	--

Important	Remember that privilege masks written at the File Folder <i>base class</i> level will affect both the File Folders class (File Folder and Markup subclass) and the Designs class (Design subclass). Privilege masks tailored for CAD environments should be entered at Designs class level.
------------------	---

Administering Agile Drive

This chapter includes the following:

- Overview 419

Overview

Agile Drive is a system extension enabling users to perform file management operations of Agile objects without requiring the user to invoke the Agile PLM application. It connects Agile's Distributed File Manager as a Network Place on your system, thus enabling Explorer-like operations, such as copy or delete, on file attachments of Agile objects. Agile Drive displays Agile objects as folders, and its attachments as files in these folders.

File Management

With Agile Drive, you can work on files such as documents, drawings, etc., associated with Agile objects as file attachments in Agile. The actions a user can perform on files are the following:

- View / Read a file
- Save a file
- Update / Edit a file
- Delete a file
- View file properties
- Add a file
- Move a file
- Copy files

The action a user can perform on folders is the following:

- View Folder Properties

Enabling Agile Drive

To enable Agile Drive:

1. Go to **System Settings > Preferences**.
2. From the **Agile Drive** dropdown list, select Enabled.
3. Restart all Distributed File Managers.

Note By default, Agile Drive is set to Disabled.
Once you enable the Agile Drive, the access will be Read-only.

For more detailed information about how to configure the required settings, set up Agile Drive for users, and perform actions using Agile Drive, see *Agile Drive User Guide*.

Configuring Single Sign-On

This Appendix includes the following:

- Overview of Single Sign-On in PLM 421
- Configuring and Deploying SSO with Windows NTLM 422

Agile PLM has the possibility of integrating aspects of your PLM system with Single Sign-On (SSO) capability.

Overview of Single Sign-On in PLM


With SSO configured and enabled for your PLM system, a user that has signed in to the system once (for instance, through the corporate portal) is not prompted again by a "login" dialog in such cases as:

- Launching Web Client
- Clicking on a URL for an email notification
- When a customer's supplier launches the Microsoft Excel-based Solution from a Declaration
- When Web Client times out.

Note SSO is a Web-based solution that can be enabled only for Agile Web Client. SSO cannot be configured or applied from Java Client, Administrator module in Java Client, or the Agile SDK.

Single Sign-on integrates with the centralized security management, other business and training applications, and improves user productivity in Agile Web Client environment.


The sections below give a general overview to Single Sign-On in Agile PLM, followed by steps to configure and deploy SSO with Windows NTLM.



Configuring and Deploying SSO with Windows NTLM

The following sections outline the steps to configure and deploy NTLM for Single sign-on capability.

SSO NTLM Authentication



Configure SSO for Windows NTLM

Microsoft Windows NTLM has been certified for Agile PLM. Please discuss your company's needs with your Oracle Consulting – Agile Practice representative.

Configure IIS Proxy

These are the steps to configure Windows NTLM for Single sign-on with Internet Information Services (IIS) as proxy server.

Note The prerequisite for this configuration is that the Windows server on which IIS is running has been joined to a Windows domain. "Microsoft Active Directory" is the name of the Windows Domain controller since Windows 2000.

1. In Windows 2003, choose **Start > Settings > Administrative Tools > IIS Manager**.
2. Select local computer, right-click and go to **Properties**.
3. Select **Directory Security** tab.
4. Click **Edit**.
5. Uncheck **Enable anonymous access**, check **Integrated Windows authentication**, and click **Apply**.
6. Restart IIS service.

Configure PLM for NTLM

To configure your PLM system for SSO with NTLM, please perform these operations.

A. Edit this file:

oracle_home/j2ee/home/config/jazn.xml.

- Comment out the following elements:


```
<!--property name="idm.authentication.name" value="JavaSSO" />
<property name="idm.token.assertter.class"
value="oracle.security.jazn.sso.SSOCookieTokenAsserter" />
<property name="idm.token.collector.class"
value="oracle.security.jazn.sso.SSOCookieTokenCollector" />
<property name="idm.token.type" value="HTTP_COOKIE" />
<property name="idm.token.collector.cookie.1" value="ORA_OC4J_SSO"
/-->
```
- Add the following elements:


```
<property name="idm.authentication.name" value="AgilePLM-SSO" />
<property name="idm.token.assertter.class"
value="com.agile.admin.security.oracle.TokenAsserterImpl" />
<property name="idm.token.collector.class"
value="com.agile.admin.security.oracle.TokenCollectorImpl" />
<property name="idm.token.type" value="HTTP_REQUEST" />
<!-- SSO Type, can be one of following values: SECURE-PROXY,
SITEINDER, NTLM /-->
<property name="agile.security.sso.interceptor.type" value="SECURE-
PROXY" />
```

B. Edit this file:

oracle_home/j2ee/home/application-deployments/Agile/orion-application.xml.

- Add this element:


```
<jazn-web-app auth-method="CUSTOM_AUTH" />
```

C. Edit this file:

<OracleHome>/j2ee/home/applications/Agile/APP-INF/classes/agile.properties

- Change the following element:
- ```
agile.sso.cookie.name = CMSession
```
- to
- ```
agile.sso.cookie.name = oproxy_username
```

Note Setting this cookie property name enables users to have the correct behavior following an idle session timeout period in OAS.

D. Restart Agile.

Deploy NTLM

The following are possible SSO deployment scenarios with NTLM, one for secure proxy and one for transparent or no proxy.

With Secure Proxy

With this deployment, authentication takes place on the proxy server, so it is recommended for those companies that use a proxy server.

Request flow with this deployment:

1. User launches browser to access Agile PLM (for example, <http://agileplm.xyz.com/Agile/PLMServlet>).
2. The NTLM-enabled IIS server challenges the browser for credentials.
3. After a successful NTLM handshake, the request reaches Agile Application Server (AAS) agent with user information.

NTLM is a connection-based authentication protocol. For each new socket connection between client and server (or proxy), it has to exchange credentials by sending and responding to HTTP requests and responses.

4. The AAS agent passes the user information to the application server security framework.
5. The user will be allowed to access Agile applications.

This authentication happens whenever the client sends an HTTP POST request; therefore, authentication can re-occur even during an established user session.

With Transparent Proxy or No Proxy

Request flow with this deployment:

1. User launches browser to access Agile (for example, <http://agileplm.xyz.com/Agile/PLMServlet>).
2. The Agile Application Server (AAS) agent installed on server challenges the browser for credentials.

3. After a successful NTLM handshake, the AAS agent passes the user information to the application server security framework.
4. The user will be allowed to access Agile applications.

