



Sun Master Index Configuration Guide



Sun Microsystems, Inc.
4150 Network Circle
Santa Clara, CA 95054
U.S.A.

Part No: 821-0865-11
December 2009

Copyright 2009 Sun Microsystems, Inc. 4150 Network Circle, Santa Clara, CA 95054 U.S.A. All rights reserved.

Sun Microsystems, Inc. has intellectual property rights relating to technology embodied in the product that is described in this document. In particular, and without limitation, these intellectual property rights may include one or more U.S. patents or pending patent applications in the U.S. and in other countries.

U.S. Government Rights – Commercial software. Government users are subject to the Sun Microsystems, Inc. standard license agreement and applicable provisions of the FAR and its supplements.

This distribution may include materials developed by third parties.

Parts of the product may be derived from Berkeley BSD systems, licensed from the University of California. UNIX is a registered trademark in the U.S. and other countries, exclusively licensed through X/Open Company, Ltd.

Sun, Sun Microsystems, the Sun logo, the Solaris logo, the Java Coffee Cup logo, docs.sun.com, Java, and Solaris are trademarks or registered trademarks of Sun Microsystems, Inc. or its subsidiaries in the U.S. and other countries. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. in the U.S. and other countries. Products bearing SPARC trademarks are based upon an architecture developed by Sun Microsystems, Inc.

The OPEN LOOK and SunTM Graphical User Interface was developed by Sun Microsystems, Inc. for its users and licensees. Sun acknowledges the pioneering efforts of Xerox in researching and developing the concept of visual or graphical user interfaces for the computer industry. Sun holds a non-exclusive license from Xerox to the Xerox Graphical User Interface, which license also covers Sun's licensees who implement OPEN LOOK GUIs and otherwise comply with Sun's written license agreements.

Products covered by and information contained in this publication are controlled by U.S. Export Control laws and may be subject to the export or import laws in other countries. Nuclear, missile, chemical or biological weapons or nuclear maritime end uses or end users, whether direct or indirect, are strictly prohibited. Export or reexport to countries subject to U.S. embargo or to entities identified on U.S. export exclusion lists, including, but not limited to, the denied persons and specially designated nationals lists is strictly prohibited.

DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID.

Contents

Configuring Sun Master Indexes	9
Related Topics	10
Master Index Configuration Overview	11
About the Master Index Configuration Files	11
Modifying the Master Index XML Files Directly	14
Using the Master Index Master Index Configuration Editor	14
Maintaining Version Control in the Master Index Configuration Files	16
Copying, Cutting, and Pasting Files	16
Configuring the Master Index Object Structure	16
Adding an Object to the Master Index Object Structure	17
Modifying an Object's Name In the Master Index Object Definition	19
Deleting an Object From the Master Index Object Structure	20
Adding a Field to the Master Index Object Structure	21
Deleting a Field from the Master Index Object Structure	23
Modifying Master Field Properties	24
Defining Relationships Between Master Index Objects	26
Master Index Field Properties and Name Restrictions	27
Master Index Field Name Restrictions	27
Master Index Configuration Editor Field Properties	27
Master Index Field Property Elements	30
Creating a Master Index Basic Query	32
▼ To Create a Basic Query (Configuration Editor)	32
▼ To Create a Basic Query (XML Editor)	33
Master Index Query Builder Dialog Box Fields and XML Elements	34
Creating Master Index Blocking Queries	35
▼ To Create a Blocking Query (Configuration Editor)	36
▼ To Create a Blocking Query (XML Editor)	37
Master Index Query Block Fields and XML Elements	39

Modifying Master Index Queries	41
Modifying a Master Index Query	42
Adding a Query Block to a Master Index Query	44
Modifying a Query Block for a Master Index Query	46
Deleting a Query Block From a Master Index Query	48
Deleting a Master Index Query	50
▼ To Delete a Query (Configuration Editor)	50
▼ To Delete a Query	50
Configuring Master Index Processing Options	51
Specifying Master Index Custom Logic Classes	51
Specifying the Master Index Update Mode	52
Configuring Master Index Merged Record Updates	53
Specifying the Master Index Blocking Query for Matching	54
Setting Master Index Blocking Query Options	54
Defining Master Index Transactional Support	55
Configuring Matching Parameters	58
Specifying the Master Index Decision Maker Class	58
Defining How to Handle Multiple Assumed Matches (OneExactMatch)	58
Specifying Whether Same System Matches are Allowed (SameSystemMatch)	60
Specifying the Master Index Duplicate Threshold	61
Specifying the Master Index Match Threshold	62
Adding and Deleting Master Index Decision Maker Parameters	63
Configuring Master Index EUIDs	64
Specifying the Master Index EUID Generator Class	65
Specifying the Master Index EUID Length	65
Specifying a Master Index Checksum Length	66
Specifying the Master Index Chunk Size	67
Adding and Deleting Master Index EUID Generator Parameters	67
Defining Master Index Normalization Rules	69
Defining a Master Index Field to be Normalized	69
Master Index Normalization and Standardization Structure Properties	73
Master Index Variants Properties	75
Modifying a Master Index Normalization Definition	75
Deleting a Master Index Normalization Definition	77
Defining Master Index Standardization Rules	78
Defining Master Index Fields to be Standardized	78

Master Index Standardization Source and Target Field Elements	82
Modifying a Master Index Standardization Definition	83
▼ To Modify a Standardization Definition (XML Editor)	84
Deleting a Master Index Standardization Definition	85
Defining Phonetic Encoding for the Master Index	86
Defining Master Index Fields for Phonetic Encoding	87
Master Index Phonetic Encoding Fields and Elements	88
Modifying a Master Index Phonetic Encoding Definition	89
Deleting a Master Index Phonetic Encoding Definition	90
Defining a Master Index Phonetic Encoder	91
Master Index Encoder Elements and Types	92
Modifying a Master Index Phonetic Encoder	93
Deleting a Master Index Phonetic Encoder	94
Defining the Master Index Match String	95
Creating the Master Index Match String	95
Modifying the Master Index Match String	97
Defining how Master Index Query Blocks are Processed	99
▼ To Specify the Block Picker	99
▼ To Specify the Pass Controller Class	100
Defining the Master Index Survivor Calculator	100
Specifying the Master Index Survivor Helper	101
Specifying a Master Index Default Survivor Strategy	101
Master Index Default Survivor Strategy Parameter Elements	103
Defining the Master Index Single Best Record Structure	104
Defining a Master Index Survivor Strategy for a Field or Object	106
Defining Master Index Custom Weighted Strategies	107
Master Index Weighted Calculator Parameter Elements	111
Filtering Default Values From Master Index Processes	112
▼ To Filter Default Values From the SBR, Blocking Query, or Match Process	112
Filter Definition Elements	113
Configuring Master Index Update Policies	114
Defining Master Index Update Policies	115
Setting the Master Index Update Policy Flag	116
Defining Custom Field Validations for the Master Index	117
▼ To Implement a Validation Rule	117
Configuring the Match Engine	118

Specifying a Match Engine for the Master Index	118
Configuring the Comparison Functions for a Master Index Application	119
Match Comparator Configuration Properties for Sun Master Index	121
Importing Custom Comparison Functions	123
Deleting a Custom Comparison Function	124
Configuring the Standardization Engine	125
Specifying a Standardization Engine for the Master Index	125
Modifying Master Index Standardization Files	126
Importing Standardization Data Types and Variants	127
Deleting a Standardization Variant or Data Type	128
Configuring the Master Index MIDM Appearance	128
Adding Objects to the MIDM	129
Modifying MIDM Objects	130
Deleting Objects From the MIDM	130
Adding Fields to the MIDM	132
MIDM Field Configuration Elements	132
Removing Fields From the MIDM	134
Modifying MIDM Field Display Options	135
Specifying a Drop-Down List for an MIDM Field	136
Specifying an MIDM Field's Length and Format	136
Modifying an MIDM Field's Data Type	137
Defining Key Fields for an Object	138
Masking Field Values on the MIDM	139
Defining MIDM Object Relationships	140
Defining MIDM Local ID Labels	140
Configuring the Master Index MIDM Pages	141
Specifying the Initial View for the MIDM	141
Configuring the MIDM Duplicate Records Page	142
Duplicate Records Page Configuration Elements	145
Configuring the MIDM Record Details Page	147
Creating Search Pages on the Record Details Page	148
Record Details Search Page Definition Elements	151
Record Details Search Field Definition Elements	152
Record Details Search Option Elements	153
Modifying a Search Page on the Record Details Page	154
Configuring the MIDM Assumed Matches Page	156

Configuring the MIDM Transactions Page	158
Configuring the MIDM Reports Page	160
Production Reports Definition Elements	163
Activity Reports Definition Elements	164
Configuring the MIDM Source Record Page	165
Configuring the MIDM Audit Log Page	167
Configuring Master Index MIDM Implementation Information	168
Specifying the Master Controller JNDI Class	168
Specifying the Master Index Report Generator JNDI Class	169
Specifying Master Index Validation Services	170
Setting Master Index Debug Options	170
Specifying a Master Index Field Masking Class	171

Configuring Sun Master Indexes

The topics listed here provide information about configuring a master index application. You can perform the tasks listed on this page after you create the master index framework. This document is designed to be used in conjunction with *Sun Master Index Configuration Reference*, which describes the configuration file structure and explains the configuration options and how they affect processing.

What You Need to Know

These topics provide information you should know before you start customizing a master index application.

- [“About the Master Index Configuration Files” on page 11](#)
- [“Modifying the Master Index XML Files Directly” on page 14](#)
- [“Using the Master Index Master Index Configuration Editor” on page 14](#)
- [“Maintaining Version Control in the Master Index Configuration Files” on page 16](#)

What You Need to Do

These topics provide instructions on how to configure the components of a master index application, either by modifying the XML files directly or by using the graphical Configuration Editor.

- [“Configuring the Master Index Object Structure” on page 16](#)
- [“Creating a Master Index Basic Query” on page 32](#)
- [“Creating Master Index Blocking Queries” on page 35](#)
- [“Modifying Master Index Queries” on page 41](#)
- [“Deleting a Master Index Query” on page 50](#)
- [“Configuring Master Index Processing Options” on page 51](#)
- [“Configuring Matching Parameters” on page 58](#)
- [“Configuring Master Index EUIDs” on page 64](#)
- [“Defining Master Index Normalization Rules” on page 69](#)
- [“Defining Master Index Standardization Rules” on page 78](#)
- [“Defining Phonetic Encoding for the Master Index” on page 86](#)

- “Defining the Master Index Match String” on page 95
- “Defining how Master Index Query Blocks are Processed” on page 99
- “Defining the Master Index Survivor Calculator” on page 100
- “Filtering Default Values From Master Index Processes” on page 112
- “Configuring Master Index Update Policies” on page 114
- “Defining Custom Field Validations for the Master Index” on page 117
- “Configuring the Match Engine” on page 118
- “Configuring the Standardization Engine” on page 125
- “Configuring the Master Index MIDM Appearance” on page 128
- “Configuring the Master Index MIDM Pages” on page 141
- “Configuring Master Index MIDM Implementation Information” on page 168

More Information

These topics provide additional information you should know when configuring a master index.

- “Master Index Field Properties and Name Restrictions” on page 27
- “Master Index Query Builder Dialog Box Fields and XML Elements” on page 34
- “Master Index Query Block Fields and XML Elements” on page 39
- “Master Index Normalization and Standardization Structure Properties” on page 73
- “Master Index Variants Properties” on page 75
- “Master Index Phonetic Encoding Fields and Elements” on page 88
- “Master Index Encoder Elements and Types” on page 92
- “Master Index Default Survivor Strategy Parameter Elements” on page 103
- “Master Index Weighted Calculator Parameter Elements” on page 111
- “Filter Definition Elements” on page 113
- “Match Comparator Configuration Properties for Sun Master Index” on page 121
- “MIDM Field Configuration Elements” on page 132
- “Duplicate Records Search Page Elements” on page 145
- “Duplicate Records Search Results List Elements” on page 146
- “Record Details Search Page Definition Elements” on page 151
- “Record Details Search Field Definition Elements” on page 152
- “Record Details Search Option Elements” on page 153
- “Production Reports Definition Elements” on page 163
- “Activity Reports Definition Elements” on page 164

Related Topics

Several topics provide information and instructions for implementing and using a master index application. For a complete list of topics related to working with Sun Master Index, see “[Related Topics](#)” in *Sun Master Index User’s Guide*.

Master Index Configuration Overview

Sun Master Index provides a very flexible framework for creating a master index application that is customized for your requirements. A Sun Master Index project includes several files in XML format that define the configuration of the runtime environment. You can configure a master index application by modifying the XML files directly or by using the Configuration Editor. Make sure to verify the configuration of the application before deploying the project.

Note – It is helpful to review the information provided in [Sun Master Index Configuration Reference](#) to learn about the relationships between the files and what components and processes can be configured. Certain components can only be configured by modifying the XML files directly.

The following topics provide an overview of the configuration files and editors.

- “About the Master Index Configuration Files” on page 11
- “Modifying the Master Index XML Files Directly” on page 14
- “Using the Master Index Master Index Configuration Editor” on page 14
- “Maintaining Version Control in the Master Index Configuration Files” on page 16
- “Copying, Cutting, and Pasting Files” on page 16

About the Master Index Configuration Files

Several XML configuration files define primary characteristics of the master index application, such as how data is processed, queried, and matched. These files configure runtime components of the master index application.

object.xml

In the wizard, you define the objects and fields contained in the object structure, along with properties for those fields. The information you specify is written to `object.xml` in the master index project. This file defines the objects stored in the master index application and their relationships to one another. It also defines the fields contained in each object, as well as certain properties of each field, such as length, data type, whether it is required, whether it is a unique key, and so on. This file contains one parent object; all other objects must be child objects to that parent object. The object structure you define in `object.xml` determines the structure of the database tables that store object data, the structure of the Java API, and the structure of the OTD generated for the project.

query.xml

In `query.xml`, you configure the *Query Builder* component of the master index application and define the available queries. In this file, you define the types of queries that can be performed from the Master Index Data Manager (MIDM) and the queries that are used during the match

process. You can define both phonetic and alphanumeric searches for the MIDM. By default, these are called *basic queries*. You can also define *blocking queries*, which define blocks of criteria fields for the match process. The master index application queries the database using the criteria defined in each block, one at a time. After completing a query on the criteria defined in one block, it performs another pass using the next block of defined criteria. Blocking queries can also be used in place of the basic phonetic query in the MIDM.

mefa.xml

In *mefa.xml*, you configure the *Matching Service* by specifying the fields to be standardized and the fields to be used for matching, as well as defining how the fields are standardized and matched. This file specifies the match and standardization engines to use and the query process for matching. Standardization includes defining fields to be reformatted (or parsed), normalized, or phonetically encoded. For matching, you must also define the data string to be passed to the match engine. The rules you define for standardization and matching are dependent on the standardization and match engine in use. [Master Index Match Engine Reference](#) and [Master Index Standardization Engine Reference](#) describe the rules for the Master Index Standardization Engine and Master Index Match Engine.

You can also configure portions of the match process in *master.xml*, described below, which defines certain match parameters that control weight thresholds, how assumed matches are processed, how potential duplicates are processed, and the query to use for matching.

master.xml

In *master.xml*, you configure the *Manager Service* and define properties of the match process. You specify the match and duplicate thresholds in this file, and define certain system parameters, such as the update mode, how to process records above the match threshold, how to manage same system matches, and whether merged records can be updated. This file also specifies which of the queries defined in the Query Builder to use for matching queries.

This file also configures the EUIDs assigned by the master index application. You can specify an EUID length, whether a checksum value is used for additional verification, and a “chunk size”. Specifying a chunk size allows the EUID generator to obtain a block of EUIDs from the *sbyn_seq_table* database table so it does not need to query the table each time it generates a new EUID.

update.xml

In *update.xml*, you define formulas that determine which data in an enterprise record should be considered the most reliable and how updates to the single best record (SBR) will be handled. The survivor calculator uses these formulas to decide what data from each system record to include in each object’s SBR. The SBR is the portion of the enterprise record that represents the data that is considered to be the most accurate and current for an entity.

The SBR is defined by a mapping of fields from external system records. Since there might be many external systems, you can optionally specify a strategy to select the value for an SBR field from the list of external values. You can also specify any additional fields that might be required by the selection strategy to determine which external system contains the best data, such as the object's update date and time.

You can create Java classes that define special processing to perform against a record when the record is created, updated, merged, or unmerged. These classes must be created in the Source Packages folder of the EJB project and can be specified for each transaction type in `update.xml`.

filter.xml

You can further configure the survivor calculator, blocking query, and match process by defining exclusion lists in `filter.xml`. Exclusion lists allow you to define values that should not be populated into the SBR, that should not be considered in the composite matching weight, and that should be ignored in the blocking query. Values you would want to filter out primarily include default values that are used when the actual value for a field is unknown. Default values can cause the blocking query to return records that are not a close match and can skew matching results.

validation.xml

By default, `validation.xml` defines certain validations for the local identifiers assigned by each external system. You can create custom Java classes that define rules for validating field values before they are saved to the master index database. You can then specify the Java classes in `validation.xml` to make them part of the master index application.

security.xml

This file defines security roles and permissions for the client applications that access the master index database.

midm.xml

In `midm.xml`, you configure the appearance and processing properties of the Master Index Data Manager (MIDM). In this file, you define each object and field that appears on the MIDM, along with the properties of each field, such as the field type and length, field labels, format masks, and so on. You can also define the order in which objects and fields appear on the MIDM pages.

This file defines several additional properties of the MIDM, including the types of searches available, whether wildcard characters can be used, the criteria for the searches, and the results fields that appear. You can also specify whether an audit log is maintained of each instance data is accessed through the MIDM. For healthcare-based master index applications this supports the privacy rules mandated by the HIPAA regulation for healthcare.

Finally, `midm.xml` defines certain implementation information, such as the application server in use, debugging rules, and security activation.

The files that configure the components of the master index application are created by the wizard and define characteristics of the application, such as how data is processed, queried, and matched, and how it appears on the MIDM. These files configure the runtime components of the master index application.

Modifying the Master Index XML Files Directly

Make sure that when you modify the configuration files, you use the versioning controls in NetBeans to maintain version control. Even if you modify the files using the Master Index Configuration Editor, check the files in and out before and after using the editor.

There are a few restraints on modifying these files. In addition to the general rules listed below, the match or standardization engine you choose might place other requirements on customizations. Be sure to review [Master Index Match Engine Reference](#) and [Master Index Standardization Engine Reference](#) before modifying mefa.xml.

Keep the following guidelines in mind when modifying the XML files directly.

- All fields specified in any of the configuration files must be included in object.xml.
- If you add fields to the object structure, make sure you add them to the survivor calculator in update.xml.
- If you define additional fields for normalization, parsing, or phonetic encoding, make sure to add the normalized, parsed, and phonetic fields to object.xml and, optionally, the blocking query.
- After modifying any of the configuration files, you must regenerate the master index application and redeploy the project. You must also refresh any client projects that reference the master index server project.

Using the Master Index Master Index Configuration Editor

The Configuration Editor has built in validations to ensure that integrity is maintained between the configuration files. For example, it does not allow you to define a field for normalization if that field is not already defined in the object structure. While you can use the Configuration Editor to modify most of the configurable components, some components can only be modified using the XML editor. Following is a summary of which features can be configured using the Configuration Editor and which need to be modified using an XML editor.

object.xml

You can modify most elements of object.xml using the Configuration Editor. The following can only be modified using the XML editor:

- Database type

- Date format
- Maximum field value
- Minimum field value

It is not recommended you change the database type, but if you modify the database type or date format elements, you need to regenerate the application to create the updated database scripts. This does not recreate the Systems or Code Lists scripts; that needs to be done manually.

query.xml

You can modify all elements in query.xml using the Configuration Editor. If you create a query to use in the MIDM or to use for the matching query, you need to add the query to the appropriate file manually (master.xml or midm.xml).

master.xml

Most elements in master.xml cannot be modified using the Configuration Editor. You can only modify the duplicate and match thresholds from the Configuration Editor.

mefa.xml

You can use the Configuration Editor to modify all commonly modified elements in mefa.xml, including defining standardization structures, normalization structures, and phonetic encoding. If you create custom classes to implement a block picker, pass controller, match engine, or standardization engine, you need to specify the implementation classes in this file using the XML editor.

update.xml

The Configuration Editor does not modify update.xml. If you make any changes to the object structure (either through the Configuration Editor or XML editor) review this file to verify that all fields or objects are included in the survivor strategy and that the field and object names are correct.

validation.xml

The Configuration Editor does not modify update.xml. If you create a custom field validation class, you need to specify the implementation class in this file using the XML editor.

midm.xml

Most elements in midm.xml are not modified using the Configuration Editor. You can add and delete fields that appear on the MIDM and modify the display name and the value and input masks. All other field properties can only be modified using the XML editor.

Field integrity is maintained when you delete a field using the Configuration Editor. The field is automatically deleted from the MIDM object structure and from any MIDM page definitions that include the field, such as a search page or report.

Match Configuration File (matchConfigFile.cfg)

You can modify all components of the Match Configuration file using the Configuration Editor, including adding and removing comparators. The Configuration Editor does not validate the extra parameters that can be used for certain comparators, so you should verify your changes by reviewing the match configuration file manually.

Maintaining Version Control in the Master Index Configuration Files

Whether you modify the XML files directly or configure the master index application through the Master Index Configuration Editor, be sure to maintain version control by checking files out before modifying them and checking them back in after you are finished. You can use any of NetBeans supported platforms for version control. When working with the Configuration Editor, make sure to check out each file that will be modified, either directly or indirectly. For example, if you add a new field to the object structure, add the field to the match string, and add the field to a blocking query, the Master Index Configuration Editor updates object.xml, query.xml, and mefa.xml.

Copying, Cutting, and Pasting Files

You can use standard cut, copy, and paste commands to copy or move files between projects. Sun Master Index follows the standard NetBeans functionality, with the exception that you can only copy or move a component from one project into the same node of another project. For example, you can only paste a copied configuration file into the Configuration node of another project. In addition, you cannot cut components that are essential to a project, such as the configuration files, match and standardization files, and so on.

Configuring the Master Index Object Structure

After you create the master index framework and create the configuration files, you can modify the object structure that you defined. The properties for the objects and fields you will store in the master index database are defined in object.xml. For more information about this file and the configurable options, see [“Master Index Object Definition Configuration” in Sun Master Index Configuration Reference](#).

The object tree in the Configuration Editor corresponds to object.xml in the master index application. Any changes you make to the object structure in the Configuration Editor are reflected in object.xml, and MIDM field property changes are also reflected in midm.xml. If you modify the XML file directly, you need to update midm.xml manually.

Changing the object structure might also require that you make corresponding changes to the other configuration files. For example, if you add a new field to object.xml that you want to include in queries and matching, you need to make the corresponding changes to query.xml, mefa.xml, and update.xml. Only changes made before generating the project take effect for the new application.

You can configure the object structure either through the Master Index Configuration Editor or by modifying the XML file directly. Both methods are described here. Perform any of the following actions to configure the object structure.

- [“Adding an Object to the Master Index Object Structure” on page 17](#)
- [“Modifying an Object's Name In the Master Index Object Definition” on page 19](#)
- [“Deleting an Object From the Master Index Object Structure” on page 20](#)
- [“Adding a Field to the Master Index Object Structure” on page 21](#)
- [“Deleting a Field from the Master Index Object Structure” on page 23](#)
- [“Modifying Master Field Properties” on page 24](#)
- [“Defining Relationships Between Master Index Objects” on page 26](#)

Adding an Object to the Master Index Object Structure

You can add new objects to the object structure as needed. Note that the object structure can contain only one parent object but multiple child objects. If you use the Configuration Editor, you can either create an undefined object or create an object from a predefined template. A predefined object includes a set of predefined fields with default configurations.

Note – Due to database naming constraints, the length of the name of the parent object plus the length of any child object names must be 21 characters or less.

▼ To Add an Undefined Object (Configuration Editor)

- 1 **In the Projects window, right-click the Configuration node in the project you want to modify, and then click Edit.**

The Configuration Editor appears.

- 2 **Select the parent object, and then click Add Sub Object Node on the Configuration Editor toolbar.**

The object structure expands, and a new child object appears at the bottom of the object structure.

- 3 **Type a new name for the object, and then press Enter.**
- 4 **Define the fields for the new object, as described in [“Adding a Field to the Master Index Object Structure” on page 21](#).**

- 5 On the Configuration Editor toolbar, click Save.

▼ To Add a Predefined Object (Configuration Editor)

- 1 In the Projects window, right-click the Configuration node in the project you want to modify, and then click Edit.
The Configuration Editor appears.
- 2 Select the parent object, click Templates in the toolbar, and then select the template you want to use.
The new child object and any defined fields appear in the object tree.
- 3 To change the name of the new object, double-click the object name, type the new name, and then press Enter.
- 4 Do any of the following:
 - Add fields to the new object, as described in [“Adding a Field to the Master Index Object Structure” on page 21](#).
 - Delete fields from the new objects, as described in [“Deleting a Field from the Master Index Object Structure” on page 23](#).
 - Modify the properties of the fields in the object, as described in [“Modifying Master Field Properties” on page 24](#).
- 5 On the Configuration Editor toolbar, click Save.

▼ To Add an Undefined Object (XML editor)

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click object.xml.
The file opens in the NetBeans XML editor.
- 2 Scroll to the location where you want to create the new object (after the database element but before relationships).
- 3 Create a nodes element.

- 4 **Create and name a tag element within the new nodes element (the value of the tag element is the name of the object you are defining).**

Make sure the new nodes element does not fall within any existing nodes elements. For example:

```
<nodes>
    <tag>Person</tag>
    ...
</nodes>
<nodes>
    <tag>Address</tag>
</nodes>
```

- 5 **Define the fields for the new object, as described in [“Adding a Field to the Master Index Object Structure” on page 21](#).**
- 6 **Define the relationship of the new object to the existing objects, as described in [“Defining Relationships Between Master Index Objects” on page 26](#).**
- 7 **Save and close the file.**

Modifying an Object's Name In the Master Index Object Definition

You can modify the name of an object in object.xml, but you must also make the corresponding changes to the remaining configuration files.

▼ To Modify an Object's Name (Configuration Editor)

- 1 **In the Projects window, right-click the Configuration node in the project you want to modify, and then click Edit.**
The Configuration Editor appears.
- 2 **Click the plus sign next to the parent object to expand the object structure.**
- 3 **Click twice on the name of the object you want to change.**
- 4 **Type in the new name, and then press Enter.**
- 5 **On the Configuration Editor toolbar, click Save.**

▼ To Modify an Object's Name (XML Editor)

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `object.xml`.
The file opens in the NetBeans XML editor.
- 2 Scroll to the `tag` element defining the object you want to modify.
- 3 Change the value of the `tag` element.
- 4 Modify the object name in the relationships definition, as described in [“Defining Relationships Between Master Index Objects” on page 26](#).
- 5 Save and close the file.

Deleting an Object From the Master Index Object Structure

If you define an object in error, you can remove the object from `object.xml`. If you modify the XML file directly, you must also remove the relationship definition for the object. Remember to make the corresponding changes to the remaining configuration files.

▼ To Delete an Object (Configuration Editor)

- 1 In the Projects window, right-click the Configuration node in the project you want to modify, and then click **Edit**.
The Configuration Editor appears.
- 2 Expand the object structure by clicking the plus sign by the parent object.
- 3 Do any of the following:
 - Right-click in the object tree panel, and then click **Delete**.
 - Press the **Delete** key.
 - In the Configuration Editor toolbar, click **Delete**.
- 4 On the confirmation dialog box, click **Yes**.
The object and any fields associated with that object are deleted. If you remove the parent object, all child objects are also removed.

- 5 On the Configuration Editor toolbar, click Save.

▼ To Delete an Object (XML Editor)

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `object.xml`.

The file opens in the NetBeans XML editor.

- 2 Scroll to the `nodes` element containing the object you want to delete.
- 3 Delete all text between and including the `nodes` tags that contain the object tag.

For example, to delete the Address object below, delete the boldface text.

```
<nodes>
  <tag>Person</tag>
</nodes>
<nodes>
  <tag>Address</tag>
</nodes>
```

- 4 Remove the object name from the relationship list, as described in [“Defining Relationships Between Master Index Objects” on page 26](#).
- 5 Save and close the file.

Adding a Field to the Master Index Object Structure

Once you define an object in `object.xml`, you can add new fields to the object and configure the properties for those fields. Be sure to add the field to any relevant structures in the remaining configuration files. For information about field naming restrictions, see [“Master Index Field Name Restrictions” on page 27](#).

▼ To Add a Field (Configuration Editor)

- 1 In the Projects window, right-click the Configuration node in the project you want to modify, and then click Edit.

The Configuration Editor appears.

- 2 Expand the object structure until you see the object to which you want to add a field.

3 In the object tree panel, do one of the following:

- To add the field to the end of the object's field list, select the name of the object to which you want to add a new field and then click Add Field in the toolbar.
- To add the field immediately following an existing field, select the field after which you want to add the new field and then click Add Field in the toolbar.

The tree expands and a new field is inserted.

4 To change the field name, double-click the new field, type the new name, and then press Enter.

5 Continue to [“Modifying Master Field Properties” on page 24](#).

▼ To Add a Field (XML Editor)

1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click object.xml.

The file opens in the NetBeans XML editor.

2 Scroll to the `tag` element defining the object to which you want to add a field.

3 Under the `tag` element, create a new `fields` element.

For example:

```
<nodes>
  <tag>Address</tag>
  <fields>
  </fields>
</nodes>
```

4 Specify the field properties described in [“Master Index Field Property Elements” on page 30](#) within the new `fields` tags.

For example:

```
<fields>
  <field-name>AddressType</field-name>
  <field-type>string</field-type>
  <size>8</size>
  <updateable>true</updateable>
  <required>true</required>
  <code-module>ADDRTYPE</code-module>
  <pattern/>
  <key-type>true</key-type>
</fields>
```

5 Save and close the file.

Deleting a Field from the Master Index Object Structure

If a field is defined for an object but does not belong to that object, you can delete the field from the object structure. Make the corresponding changes to the remaining configuration files.

▼ To Delete a Field (Configuration Editor)

- 1 In the **Projects** window, right-click the **Configuration** node in the project you want to modify, and then click **Edit**.

The Configuration Editor appears.

- 2 Expand the object structure until the field you want to delete is visible.

- 3 Select the field and do any of the following:

- Right-click in the object tree panel, and then click **Delete**.
- Press the **Delete** key.
- In the Configuration Editor toolbar, click **Delete**.

- 4 On the confirmation dialog, click **Yes**.

The field is removed from the object tree.

- 5 On the Configuration Editor toolbar, click **Save**.

▼ To Delete a Field (XML Editor)

- 1 In the **Projects** window, expand the **Configuration** node in the project you want to modify, and then double-click **object.xml**.

The file opens in the NetBeans XML editor.

- 2 Scroll to the **tag** element defining the object from which you want to delete a field.

- 3 Scroll to the **fields** element containing the field to delete, and then delete all text between and including the **fields** tags defining that field.

For example, to delete the **AddressLine1** field below, delete all text in the sample.

```
<fields>
  <field-name>AddressLine1</field-name>
  <field-type>string</field-type>
  <size>5</size>
```

```
<updateable>true</updateable>
<required>false</required>
<key-type>false</key-type>
<code-module/>
<pattern/>
<key-type/>
</fields>
```

- 4 Save and close the file.

Modifying Master Field Properties

Every field in the object structure has a set of properties that must be configured before deploying the master index application. When a field is created, a set of default properties are defined for that field. You can modify the property configuration for each field to suit your data processing, storage, and display requirements. Field properties include general field attributes, such as the name, length, and data type, and MIDM field properties, such as the display name for the field and display formatting.

Note – On the Configuration Editor, the fields in the MIDM section cannot be configured if the field is not defined to appear on the MIDM (that is, it does not appear in midm.xml).

▼ To Modify Field Properties (Configuration Editor)

- 1 In the Projects window, right-click the Configuration node in the project you want to modify, and then click Edit.
The Configuration Editor appears.
- 2 Expand the object structure until the field you want to configure is visible.
- 3 In the object structure, select the field to configure.
The General Properties page appears.
- 4 On the Properties page in the right side of the window, modify the value of any of the properties listed in [“Master Index Configuration Editor Field Properties” on page 27](#).

Note – After you modify a property value, press Enter to apply the change.

- 5 To view or modify matching properties, click the Matching tab and configure the properties as described in [“To Configure the Comparison Functions \(Configuration Editor\)” on page 119](#).

This tab is only visible for fields that have a value in the Match Type field.

- 6 On the Configuration Editor toolbar, click Save.

▼ To Modify Field Properties (XML Editor)

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click object.xml.
The file opens in the NetBeans XML editor.
- 2 Scroll to the tag element defining the object to modify, and then to the fields element containing the field to modify.
- 3 Modify the value of any of the elements described in [“Master Index Field Property Elements” on page 30](#).

Note – If you modify the name of a field, make the corresponding changes to the remaining configuration files. Some property elements might not exist for a field; add any necessary elements to the field definition to configure the field.

- 4 Save and close the file.

Example 1 Field Properties in object.xml

The following example defines an address type field that is required in order to enter a record, and that uniquely identifies each address object in a record. It also defines a list, named ADDRTYPE, from which MIDM users can select a value to enter into the field.

```
<field-name>AddressType</field-name>
<field-type>string</field-type>
<size>8</size>
<updateable>true</updateable>
<required>true</required>
<pattern></pattern>
<code-module>ADDRTYPE</code-module>
<key-type>true</key-type>
```

The following example defines an employee ID field where the must be equal to or greater than 100001 and less than or equal to 199999. Only the characters 0–9 are allowed.

```
<field-name>EmployeeID</field-name>
<field-type>string</field-type>
<size>6</size>
<updateable>true</updateable>
<required>true</required>
<minimum-value>100001</minimum-value>
```

```
<maximum-value>199999</maximum-value>  
<pattern>[0-9]{6}</pattern>  
<key-type>false</key-type>
```

Defining Relationships Between Master Index Objects

Once all objects are customized, you must define relationships between those objects if you are modifying the XML file directly. If you are using the Configuration Editor, the relationships are automatically defined in the object tree.

▼ To Define Object Relationships (XML Editor)

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `object.xml`.

The file opens in the NetBeans XML editor.

- 2 Scroll to the `relationships` element near the end of the file.

- 3 To specify a new parent object, modify the value of the `name` element.

For example:

```
<name>Individual</name>
```

Note – This is not recommended. Changing the parent name requires changing all instances of the name in all configuration files. To change the parent object name, use the Configuration Editor, which automatically propagates the change.

- 4 To change the name of a child object, modify the value of the appropriate `children` element.
- 5 To add a child object, create and name a new `children` element.
- 6 To delete a child object, delete all text between and including the appropriate `children` element.
- 7 Save and close the file.

Note – You can only specify one name element. The values you specify for the name and children elements must match an object name specified in the nodes elements earlier in the file.

Master Index Field Properties and Name Restrictions

Once you create the object structure of the master index application, you can customize several properties for each field, such as whether the field is required, will include a drop-down menu on the MIDM, will be used in a blocking query, and so on. There are also some restrictions for how fields can be named and how the properties are defined on the Configuration Editor and in the configuration files.

The following topics provide information about the naming restrictions and about the field properties of the wizard.

- [“Master Index Field Name Restrictions” on page 27](#)
- [“Master Index Configuration Editor Field Properties” on page 27](#)
- [“Master Index Field Property Elements” on page 30](#)

Master Index Field Name Restrictions

When you name the fields in your object structure, be sure to keep the following guidelines in mind to avoid errors when compiling or running the master index application.

- Sun Master Index automatically creates a field for each object named *objectId*, where *object* is the name of an object or sub-object. You cannot create fields with those names. For example, you cannot create a field named “AddressId” if there is an Address object in the object structure.
- If you enter a field name longer than 20 characters, a warning dialog box appears. While most databases can handle names up to at least 30 characters, Sun Master Index appends text to the end of fields defined for phonetic encoding or standardization. For fields that will be parsed, normalized, or phonetically encoded, make sure the name of the original field does not exceed 20 characters. Any other field can have a name up to 30 characters long. For information about the names of the fields automatically created by the wizard, see [Appendix A, “Match Types and Field Names,” in *Understanding Sun Master Index Processing*](#).
- In field names, do not use characters or names restricted by Java, XML, or the database platform you are using.

Master Index Configuration Editor Field Properties

The following table lists and describes the properties you can define on the Field Properties page of the Configuration Editor.

Property	Description
Name	A name for the field. See “Master Index Field Name Restrictions” on page 27 for information on valid field names.
Data Type	<p>The data type for each field. Possible data types are:</p> <ul style="list-style-type: none"> ■ string - Fields of this type contain a string of characters. ■ date - Fields of this type contain a date value. ■ float - Fields of this type contain a floating point integer. ■ int - Fields of this type contain an integer. ■ char - Fields of this type contain a single character. ■ boolean - Fields of this type can contain either true or false.
Match Type	<p>The type of matching to be performed against the field, if the field is to be used for match weight generation. You must define at least one field for matching or no weights will be generated.</p> <p>Note – The match types you specify here define the structure of mefa.xml, including the match string. The match types in mefa.xml might differ from the match types specified here. See Appendix A, “Match Types and Field Names,” in Understanding Sun Master Index Processing for information about the available options for this field.</p>
Blocking	An indicator of whether the field will be used in the blocking query. Select this option to add the field to the blocking query; deselect this option to omit the field from the blocking query.
Key Type	<p>An indicator of whether the field is used to identify unique objects. For example, a business index might store several addresses for each business. Each address is assigned an address type and each business can only have one address of each type. Select this option if the field is a unique record identifier; otherwise, deselect it.</p> <p>Key type fields should also be required fields unless a combination of fields are specified as key types for an object.</p> <p>Note – It is recommended that each child object contain a key type field, but this is not required. If child objects do not contain one or more key type fields, each enterprise object might accumulate a very large number of child objects depending on the survivor strategy used.</p>
Updateable	An indicator of whether the field can be updated from the MIDM and external system messages. Select this option if the field can be updated; otherwise deselect it.
Required	An indicator of whether the field is required in order to save an enterprise object to the database. Select this option if the field is required; otherwise, deselect it.
Field Size	The number of characters allowed in each field. This determines the number of characters allowed in the database columns and defines the maximum number of characters that can be entered into each field on the MIDM.

Property	Description
Pattern	The required data pattern for the field. For more information about possible values and using Java patterns, see “Patterns” in the class list for <code>java.util.regex</code> in the Javadocs provided with the Java EE Platform. You might want to define patterns for date, telephone, or SSN fields. Note that for the MIDM, the pattern is further restricted by the value entered for the input mask described later in this table. If no input mask is specified, all regex patterns are supported.
Code Module	The identification code for the drop-down list that appears for this field in the MIDM. Note – This must match an entry in the <i>code</i> column of the <i>sbyn_common_header</i> database table and, by default, an entry for the code you enter is created in the <i>Code List</i> database script. You can further customize code lists directly in the Code List script.
User Code	The processing code for the drop-down list that appears on the MIDM for the fields defined by the <i>constraint-by</i> property, described below. These codes are used for non-unique IDs, such as account numbers, insurance policies, credit cards, and so on. Note – This must match an entry in the <i>code_list</i> column of the <i>sbyn_user_code</i> database table.
Constrained By	The name of the field that contains the corresponding User Code value (described above) to use to validate the current field. The User Code and Constrained By properties are used in conjunction to define non-unique ID types, such as credit card numbers or account numbers. The first purpose is to define a drop-down list for the field that contains the User Code value. The second purpose is to validate the field that contains the Constrained By value against definitions for the field with the user code value. For example, if you store non-unique IDs such as credit card numbers or insurance policy numbers, you could create a field named ID Type with a User Code of CREDCARD (CREDCARD also needs to be defined as a code in the <i>sbyn_user_code</i> table). This gives the ID Type field a drop-down list based on the definitions for CREDCARD in the <i>sbyn_user_code</i> table. Definitions would be VISA, MASTERCARD, AMEX, and so on. You could then create a field named ID that would be constrained by the formats defined for the ID Type field. Any credit card numbers you enter would be validated against the format defined for the type of credit card you selected in ID Type .
Display Name	The name of the field as it will appear on the MIDM.

Property	Description
Input Mask	<p>A mask used by the GUI to add punctuation to a field. For example, if users enter the date in the format MMDDYYYY, you can add an input mask to display the dates as MM/DD/YYYY. Use the value mask (described below) to strip the punctuation from the value before storing it in the database.</p> <p>To define an input mask, type a character type for each character in the field and place any necessary punctuation between the character types. For example, the input mask for the above date format is DD/DD/DDDD.</p> <p>Note that the value you enter can further restrict the data pattern for the field (this is the Pattern property). The following character types can be used.</p> <ul style="list-style-type: none"> ■ D – indicates a numeric character. ■ L – indicates an alphabetic character. ■ A – indicates an alphanumeric character.
Value Mask	<p>A mask used by the index to strip any extra characters that were added by the input mask (see above). This mask ensures that data is stored in the database in the correct format.</p> <p>To specify a value mask, type the same value as is entered for the input mask, but type an “x” in place of each punctuation mark. For example, if an SSN field has an input mask of DDD-DD-DDDD, specify a value mask of DDDxDDxDDDD to strip the dashes before storing the SSN. A value mask is not required for date fields.</p>

Master Index Field Property Elements

The following table lists and describes the properties you can define for each field inobject.xml.

Element	Description
field-name	The name of the field. Follow the guidelines under “Master Index Field Name Restrictions” on page 27 when naming fields.
field-type	<p>The data type of the field. Possible values are:</p> <ul style="list-style-type: none"> ■ string - Fields of this type contain a string of characters. ■ date - Fields of this type contain a date value. ■ float - Fields of this type contain a floating point integer. ■ int - Fields of this type contain an integer. ■ char - Fields of this type contain a single character. ■ boolean - Fields of this type can contain either “true” or “false”.
size	The number of characters allowed in each field. If you modify this element, be sure to modify the length of the corresponding database column accordingly.

Element	Description
updateable	An indicator of whether the field can be updated from the MIDM or by back-end messages. Specify true if the field can be updated, or specify false if it cannot.
required	An indicator of whether the field is required in order to save an enterprise object in the database. Specify true if the field is required, or specify false if it is not.
code-module	The identification code for the menu list that appears for this field in the MIDM. This must match a value in the code column of the sbyn_comment_header database table. This element is optional.
maximum-value	The maximum value allowed in the field. To specify a value for a date field, use the format YYYY-MM-DD. This element is optional.
minimum-value	The minimum value allowed in the field. To specify a value for a date field, use the format YYYY-MM-DD. This element is optional.
pattern	<p>The required pattern for the field. For more information about possible values and using Java patterns, see “Patterns” in the class list for <code>java.util.regex</code> in the Javadocs provided with J2SE Platform. You might want to define patterns for date, telephone, or SSN fields. Note that for the MIDM, the pattern is further restricted by the value entered for the input mask. If no input mask is specified, all regex patterns are supported.</p> <p>This element is optional.</p>
user-code	<p>The processing code for the drop-down list that appears on the MIDM for the fields defined by the <code>constraint-by</code> property, described below. These codes are used for non-unique IDs, such as account numbers, insurance policies, credit cards, and so on.</p> <p>Note – This must match an entry in the <code>code_list</code> column of the <code>sbyn_user_code</code> database table.</p>
constraint-by	<p>The name of the field that contains the corresponding <code>user-code</code> value (described above) to use to validate the current field. The <code>user-code</code> and <code>constraint-by</code> properties are used in conjunction to define non-unique ID types, such as credit card numbers or account numbers. The first purpose is to define a drop-down list for the field that contains the user code value. The second purpose is to validate the field that contains the constraint value against definitions for the field with the user code value.</p> <p>For example, if you store non-unique IDs such as credit card numbers or insurance policy numbers, you could create a field named ID Type with a <code>user-code</code> of CREDCARD (CREDCARD also needs to be defined as a code in the <code>sbyn_user_code</code> table). This gives the ID Type field a drop-down list based on the definitions for CREDCARD in the <code>sbyn_user_code</code> table. Definitions would be VISA, MASTERCARD, AMEX, and so on. You could then create a field named ID that would be constrained by the formats defined for the ID Type field. Any credit card numbers you enter would be validated against the format defined for the type of credit card you selected in ID Type.</p>

Element	Description
key-type	<p>An indicator of whether the field is used to identify unique objects. Specify true if the element is a unique object identifier; specify false if it is not. Key type fields should also be required fields unless a combination of fields are specified as key types for an object. This element is optional.</p> <p>Note – Each child object should contain at least one field that is a unique object identifier, but this is not required. If two or more fields are unique identifiers, the combined value of these fields must be unique in a given enterprise record.</p>

Creating a Master Index Basic Query

By default, two basic queries are predefined in query.xml, one phonetic and one exact alphanumeric. If the default queries do not meet your query requirements, you can define new queries for the master index application. You can either use an existing query builder class or create a custom query builder by creating a custom plug-in (for more information, see [“Custom Plug-Ins for Master Index Custom Components”](#) in *Sun Master Index User’s Guide*).

The changes you make on the Query page of the Configuration Editor are reflected in query.xml. For more information about this file and the configurable query options, see [“Query Configuration”](#) in *Sun Master Index Configuration Reference*. If you create a new query to use from the MIDM, make sure to add that query to one of the search definitions in midm.xml. Unless specifically defined for range searching in midm.xml, basic queries use exact searching. No configuration is required in query.xml for basic exact or range searching.

You can create basic queries either through the Configuration Editor or by modifying the XML file directly. Both methods are described here.

▼ To Create a Basic Query (Configuration Editor)

- 1 In the Projects window, right-click the Configuration node in the project you want to modify, and then click Edit.

The Configuration Editor appears.

- 2 Click the Query tab.

The Query page appears.

- 3 In the Basic Queries section, click Add.

The Basic Query Builder dialog box appears.

- 4 Enter values and select options for the fields described in [“Master Index Query Builder Dialog Box Fields and XML Elements”](#) on page 34.

- 5 On the Configuration Editor toolbar, click Save.

▼ To Create a Basic Query (XML Editor)

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click query.xml.

The file opens in the NetBeans XML editor.

- 2 Create a new query-builder element in the QueryBuilderConfig element.

Make sure the new element is created outside of any existing query-builder elements.

- 3 For the new query-builder element, define the attributes listed in [“Master Index Query Builder Dialog Box Fields and XML Elements” on page 34](#).

For example:

```
<query-builder name="PHONETIC-SEARCH" class=
  "com.sun.mdm.index.user.CustomQueryBuilder"
  parser-class=
  "com.sun.mdm.index.configurator.impl.querybuilder.KeyValueConfiguration"
  standardize="false" phoneticize="true">
</query-builder>
```

- 4 To configure the query to use wildcard characters, do the following:

- a. Add a new config element after the opening query-builder element.

For example:

```
<query-builder name="ALPHA-SEARCH" class=
  "com.sun.mdm.index.querybuilder.BasicQueryBuilder"
  parser-class=
  "com.sun.mdm.index.configurator.impl.querybuilder.KeyValueConfiguration"
  standardize="true" phoneticize="true">
  <config>
  </config>
</query-builder>
```

- 5 In the new config element, create an option element and then define key and value attributes for the new element.

For example:

```
<config>
  <option key="UseWildcard" value="true"/>
</config>
```

Note – For the default basic query, only the `UseWildcard` parameter is supported. If you create a custom basic query builder, you can use these elements to define additional parameters. For more information, see [“Master Index Query Builder Dialog Box Fields and XML Elements” on page 34](#).

6 Save and close the file.

Master Index Query Builder Dialog Box Fields and XML Elements

The following table lists and describes the fields on the Basic Query Builder and Blocking Query Builder dialog boxes on the Configuration Editor, along with the corresponding elements and attributes in `query.xml`.

Configuration Editor Field	XML Element/Attribute	Description
Query Builder Name	query-builder/name	A unique ID that identifies the Query Builder and is referenced from <code>midm.xml</code> when specifying the query to use on a search page. It is also referenced from <code>mefa.xml</code> when specifying the query to use for matching. No spaces are allowed in the name.
Query Builder Class	query-builder/class	<p>The fully qualified name of the query class. Two default Query Builder classes are provided.</p> <ul style="list-style-type: none">■ <code>com.sun.mdm.index.querybuilder.BasicQueryBuilder</code> – Builds dynamic queries using all the available input fields. When configured to use normalized and phonetic data, this query performs phonetic searches; when configured to not use normalized and phonetic data, this query is used for exact alphanumeric searches.■ <code>com.sun.mdm.index.querybuilder.BlockerQueryBuilder</code> – Builds queries using the criteria defined in the block definitions defined for the query. When a blocking query is performed, the application searches only on the blocks for which they query has complete data.
Parser Class	query-builder/ parser-class	The fully qualified name of the class that parses the configuration elements for each query. The default parser class is <code>com.sun.mdm.index.configurator.impl.querybuilder.KeyValueConfiguration</code> .

Configuration Editor Field	XML Element/Attribute	Description
Standardize	query-builder/ standardize	An indicator of whether any of the query criteria is standardized before being passed to the query. On the Configuration Editor, select this check box if any search fields are standardized. In the XML file, enter true if any search fields are standardized; otherwise enter false .
Phoneticize	query-builder/ phoneticize	An indicator of whether any of the query criteria is phonetically encoded before being passed to the query. On the Configuration Editor, select this check box if any search fields are phonetically encoded. In the XML file, enter true if any search fields are phonetically encoded; otherwise enter false .
Use Wildcard	option/key option/value	<p>An indicator of whether wildcard characters are allowed when executing this search. This parameter is available for basic queries only. On the Configuration Editor, select this check box if wildcard characters are allowed in any of the search fields.</p> <p>In the XML file, each <code>option</code> element configures one parameter for the query and contains a key and value pair. The key attribute names the parameter. For the default basic query, the name is <code>UseWildcard</code>. The <code>value</code> attribute specifies the value of the corresponding key attribute. For the <code>UseWildcard</code> parameter, specify true to allow wildcard characters for that query type; otherwise specify false.</p> <p>When wildcard characters are enabled, you can enter a percent sign (%) into search criteria to represent multiple unknown characters.</p> <p>Note – If you define a custom query, you can use key and value options to define any required parameters.</p>

Creating Master Index Blocking Queries

By default, one blocking query is predefined in `query.xml`. If the default query does not meet your requirements, you can define new queries for the master index application. You can either use an existing query builder class or create a custom query builder by creating a custom plug-in (for more information, see [“Implementing Master Index Custom Plug-ins” in *Sun Master Index User’s Guide*](#)). Blocking queries contain *block definitions*, which define the groups of fields used for each query pass and how those groups are processed. Each block definition contains one or more set of *query blocks*. Each query block defines the query rules for one of the groups of fields that make up the block definition. You can further configure a blocking query by filtering out unwanted values from the query process. For more information, see [“Filtering Default Values From Master Index Processes” on page 112](#).

The changes you make on the Query page of the Configuration Editor are reflected in `query.xml`. For more information about this file and the configurable query options, see [“Query](#)

[Configuration](#)” in *Sun Master Index Configuration Reference* . If you create a new query to use from the MIDM, make sure to add that query to one of the search definitions in midm.xml.

You can create blocking queries either through the Configuration Editor or by modifying the XML file directly. Both methods are described here.

▼ To Create a Blocking Query (Configuration Editor)

- 1 In the Projects window, right-click the Configuration node in the project you want to modify, and then click Edit.

The Configuration Editor appears.

- 2 Click the Query tab.

The Query page appears.

- 3 In the Blocking Queries section, click Add.

The Blocking Query Builder dialog box appears.

- 4 In the Query Builder section, enter the fields described in [“Master Index Query Builder Dialog Box Fields and XML Elements” on page 34](#).

- 5 Do the following for each query block you want to include in the query:

- a. In the Block Definitions section, click Add.

The Block Definition dialog box appears.

- b. In the Block Name field, enter a unique name for the query block.

- c. (Optional) In the Hint field, define MySQL, Oracle or SQL Server hints for the query block.

For SQL Server, you can only use OPTION hints.

- d. In the Block By section, click Add.

The Block Rule dialog box appears, where you can specify a field to include in the query block.

- e. Enter values for the fields on the dialog box as described in [“Master Index Query Block Fields and XML Elements” on page 39](#), and then click OK.

- f. For each field to include in the query block, repeat the previous two steps.

- g. When you are done specifying fields for the rule, click OK on the Block Definition dialog box.

- 6 For each query block you want to create for this query, repeat the previous step.
- 7 When you are done defining the query blocks, click OK.
- 8 On the Configuration Editor toolbar, click Save.
- 9 To define values to exclude as criteria during the query process, see [“Filtering Default Values From Master Index Processes” on page 112.](#)

▼ To Create a Blocking Query (XML Editor)

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `query.xml`.
The file opens in the NetBeans XML editor.
- 2 Create a new query-builder element in the `QueryBuilderConfig` element.
Make sure the new element is created outside of any existing query-builder elements.
- 3 For the new query-builder element, define the attributes listed in [“Master Index Query Builder Dialog Box Fields and XML Elements” on page 34.](#)

For example:

```
<query-builder name="PHONETIC-SEARCH" class=
  "com.sun.mdm.index.user.CustomQueryBuilder"
  parser-class=
  "com.sun.mdm.index.configurator.impl.querybuilder.KeyValueConfiguration"
  standardize="false" phoneticize="true">
</query-builder>
```

- 4 Create a new config element between the query-builder tags.
- 5 To create a query block, do the following:
 - a. In the new config element, create a new block-definition element with a number attribute and assign a unique ID code to the number attribute.

For example:

```
<query-builder name="BLOCKING-SEARCH" class=
  "com.sun.mdm.index.querybuilder.BlockingQueryBuilder"
  parser-class=
  "com.sun.mdm.index.configurator.impl.querybuilder.
  KeyValueConfiguration"
  standardize="true" phoneticize="true">
  <config>
```

```

        <block-definition number="ID1">
        </block-definition>
    </config>
</query-builder>

```

- b. To add a database hint, create and define a new hint element in the new block-definition element.**

The following example illustrates an Oracle hint.

```

<config>
    <block-definition number="ID1">
        <hint>FIRST_ROWS_100</hint>
    </block-definition>
</config>

```

Tip – Hints are especially useful when a blocking query uses only child object fields; the hint can specify to scan the child object table first. For SQL Server, only OPTION hints are supported.

- c. In the new block-definition element, create a block-rule element.**
- d. For each field in the data block, create the elements and attributes listed in “[Master Index Query Block Fields and XML Elements](#)” on page 39.**

The following example illustrates the use of both range and equals elements, as well as upper and lower bounds.

```

<config>
    <block-definition number="ID1">
        <hint>FIRST_ROWS_100</hint>
        <block-rule>
            <equals>
                <field>Enterprise.SystemSBR.Person.FirstNamePh</field>
                <source>Person.FirstNamePh</source>
            </equals>
            <equals>
                <field>Enterprise.SystemSBR.Person.LastNamePh</field>
                <source>Person.LastNamePh</source>
            </equals>
            <range>
                <field>Enterprise.SystemSBR.Person.DateOfBirth</field>
                <source>Person.DateOfBirth</source>
                <default>
                    <lower-bound type="offset">-5</lower-bound>
                    <upper-bound type="constant">2009-01-01</upper-bound>
                </default>
            </range>
        </block-rule>
    </block-definition>
</config>

```

```
        </block-rule>
    </block-definition>
</config>
```

- 6 Repeat the previous step for each data block you need to define for the query.
All data blocks for one query must be defined within one config element.
- 7 Save and close the file.
- 8 To define values to exclude as criteria during the query process, see [“Filtering Default Values From Master Index Processes” on page 112](#).

Master Index Query Block Fields and XML Elements

The following table lists and describes the fields on the Block Rule dialog box of the Configuration Editor, along with the corresponding elements and attributes in query.xml. To see how the XML elements are organized, see the sample in [“Adding a Query Block to a Master Index Query” on page 44](#). For more information about the structure of a query block, see [“Query Configuration” in Sun Master Index Configuration Reference](#).

Configuration Editor Field	XML Element/Attribute	Description
Field	field	The name of the field to be included in the query block. On the Configuration Editor, you can click Browse to select a field or enter the fully qualified field name manually.
Source	source	<p>The name of the source field in the object from which the criteria is obtained. Click Browse to select a field, or enter the qualified field name manually. An asterisk (*) can be used as a wildcard character.</p> <p>Tip – When a field in a child object is defined for a blocking query, use the asterisk wildcard character in the ePath to the source field to ensure all instances of the child object in an incoming message are used as search criteria. Each instance is joined by an OR operator. For example, this configuration:</p> <pre><field>Enterprise.SystemSBR.Person.Name.FirstName </field> <source>Person.Name[*].FirstName</source></pre> <p>would result in a WHERE clause similar to this:</p> <pre>WHERE Name.FirstName="Meg" OR Name.FirstName="Maggie"</pre>

Configuration Editor Field	XML Element/Attribute	Description
Operator	<i>type of search</i>	<p>An indicator of the type of search to perform on the field. On the Configuration Editor, you can select one of the following values from the drop-down list. In the XML file, you specify one of the following names for the XML element that defines one field in a query block.</p> <ul style="list-style-type: none"> ■ equals - Performs an exact search against either the criteria or the value defined for the “Use Constants” option. ■ not-equals - Searches for values that do not equal either the criteria or the value defined for the “Use Constants” option. ■ greater-than-or-equal - Performs a search for values that are greater than or equal to either the criteria or the value defined for the “Use Constants” option. ■ less-than-or-equal - Performs a search for values that are less than or equal to either the criteria or the value defined for the “Use Constants” option. ■ range - Performs a search against a range of either static or user-defined ranges. If you select this option, you must specify upper and lower bounds. <p>Tip – If a field is to be used for simple range searching (where the user or incoming message supplies lower and upper limits of the range are supplied) be sure to define that field for range searching in midm.xml for the searches that use this query. For more complex range searches that use offset values or constants instead of user-supplied limits, do not define the field for range searching in midm.xml.</p>
Use Constant/Value	constant	<p>On the Configuration Editor, this is an indicator of whether to use a constant value as the search criteria for the field. When this option is selected, you need to enter the constant in the corresponding Value field. In the XML file, enter the value of the constant in the constant element.</p>

Configuration Editor Field	XML Element/Attribute	Description
Upper Bound Type	upper-bound/type	<p>For range searching only, the type of value to use for the upper limit of the search range. Select or enter one of the following options.</p> <ul style="list-style-type: none"> ■ not defined - No specific upper limit is defined; a user enters the value when performing the search. Be sure to define this field for range searching in the MIDM as well. In the XML file, this is indicated by omitting the upper - bound element. ■ constant - A specific value is defined to use as the upper limit of the range when no search criteria is entered or when incomplete information is available. ■ offset - A value to be added to the user-supplied value to determine the upper limit on the search range. For constant and offset, enter the value in the corresponding Value field.
Lower Bound Type	lower-bound/type	<p>For range searching only, the type of value to use for the lower limit of the search range. Select one of the options listed for Upper Bound Type. If you select offset, the value you specify for the offset will be subtracted from the user-supplied value.</p>
Value (for the upper and lower bounds)	upper-bound lower-bound	<p>For constant and offset range searching, the upper or lower limit of the range. For constants, this is the upper or lower limit; for offsets, this is the value added to or subtracted from the user-supplied value. It can be numeric, date, or string. In the XML file, the upper - bound and lower - bound elements fall within an element named default.</p>

Modifying Master Index Queries

By default, two basic queries and one blocking query are predefined in query.xml and you can create additional queries. Once a query is defined, you can modify it as needed. If you make changes to a query defined for a search in the MIDM, you might need to modify the search definition in midm.xml. For example, if you deselect the Use Wildcard option for a query and the wildcard feature is enabled for that query in the MIDM, you need to disable that feature in midm.xml.

You can customize the queries used in your implementation by performing any of the following actions.

- [“Modifying a Master Index Query” on page 42](#)
- [“Adding a Query Block to a Master Index Query” on page 44](#)
- [“Modifying a Query Block for a Master Index Query” on page 46](#)
- [“Deleting a Query Block From a Master Index Query” on page 48](#)

You can also define exclusion lists to filter out unwanted values from a blocking query. For more information, see [“Filtering Default Values From Master Index Processes” on page 112](#).

Modifying a Master Index Query

Once you define a basic query, you can modify the attributes and parameters for that query. If you defined a custom query, you might need to modify certain elements of the query directly in the XML file instead of through the Configuration Editor.

▼ To Modify a Basic Query (Configuration Editor)

- 1 **In the Projects window, right-click the Configuration node in the project you want to modify, and then click Edit.**
The Configuration Editor appears.
- 2 **Click the Query tab.**
The Query page appears.
- 3 **Do one of the following:**
 - **To modify a blocking query, select the query to modify in the Blocking Queries section, and then click Edit.**
The Blocking Query Builder dialog box appears.
 - **To modify a basic query, select the query to modify in the Basic Queries section, and then click Edit.**
The Basic Query Builder dialog box appears.
- 4 **Modify any of the fields and configuration options described in [“Master Index Query Builder Dialog Box Fields and XML Elements” on page 34](#).**
- 5 **For blocking queries, you can modify query blocks by performing any of the following procedures:**
 - [“Adding a Query Block to a Master Index Query” on page 44](#)
 - [“Modifying a Query Block for a Master Index Query” on page 46](#)
 - [“Deleting a Query Block From a Master Index Query” on page 48](#)
- 6 **When you are done editing the query, click OK.**

- 7 On the Configuration Editor toolbar, click Save.
- 8 To modify or define values to be excluded as criteria (for blocking queries only), go to [“Filtering Default Values From Master Index Processes” on page 112](#).

▼ To Modify a Query (XML Editor)

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `query.xml`.

The file opens in the NetBeans XML editor.

- 2 Scroll to the `query-builder` element that contains the query you want to modify.
- 3 Modify any of the attributes listed in [“Master Index Query Builder Dialog Box Fields and XML Elements” on page 34](#).

For example:

```
<query-builder name="ALPHA-SEARCH" class=
  "com.sun.mdm.index.querybuilder.MyQueryBuilder"
  parser-class=
  "com.sun.mdm.index.configurator.impl.querybuilder.KeyValueConfiguration"
  standardize="true" phoneticize="false">
</query-builder>
```

- 4 To add a new query parameter (for custom query builders only):
 - a. Add a new `config` element between the `query-builder` tags.
 - b. In the new `config` element, create an `option` element and then define key and value attributes for the new element.

For example:

```
<config>
  <option key="SearchAlias" value="true"/>
</config>
```

See [“Master Index Query Builder Dialog Box Fields and XML Elements” on page 34](#) for information about the key and value pairs available to the default basic queries.

- 5 To modify a parameter, scroll to the `option` element that defines the parameter and then change the value of the `value` attribute.

- 6 To delete a parameter, scroll to the `config` element of that query, and then delete the option element containing the parameter to remove.**

For example, to remove the SearchAlias parameter in the following sample, delete the boldface text.

```
<config>
  <option key="SearchAlias" value="true"/>
  <option key="UseWildcard" value="false"/>
</config>
```

- 7 For blocking queries, you can modify query blocks by performing any of the following procedures:**
 - [“Adding a Query Block to a Master Index Query” on page 44](#)
 - [“Modifying a Query Block for a Master Index Query” on page 46](#)
 - [“Deleting a Query Block From a Master Index Query” on page 48](#)
- 8 Save and close the file.**
- 9 To modify or define values to be excluded as criteria (for blocking queries only), go to [“Filtering Default Values From Master Index Processes” on page 112](#).**

Adding a Query Block to a Master Index Query

Some query blocks might be predefined for you based on information you specified in the wizard. You can create additional query blocks for a blocking query.

▼ To Add a Query Block (Configuration Editor)

- 1 In the Projects window, right-click the Configuration node in the project you want to modify, and then click Edit.**

The Configuration Editor appears.
- 2 Click the Query tab.**

The Query page appears.
- 3 In the Blocking Queries section, select the query you want to modify and then click Edit.**

The Blocking Query Builder dialog box appears.
- 4 In the Block Definitions section, click Add.**

The Block Definition dialog box appears.

- 5 In the **Block Name** field, enter a unique name for the query block.
- 6 (Optional) In the **Hint** field, define a database hint for the query block. For SQL Server, you can only use **OPTION** hints.
- 7 In the **Block By** section, click **Add**.
The **Block Rule** dialog box appears, where you can specify a field to include in the query block.
- 8 Enter values for the fields on the dialog box as described in [“Master Index Query Block Fields and XML Elements” on page 39](#), and then click **OK**.
- 9 Repeat the previous two steps for each field to add to the query block.
- 10 When you are done, click **OK** on the **Block Definition** dialog box.
- 11 On the **Blocking Query Builder** dialog box, click **OK**.
- 12 On the **Configuration Editor** toolbar, click **Save**.

▼ To Add a Query Block (XML Editor)

- 1 In the **Projects** window, expand the **Configuration** node in the project you want to modify, and then double-click **query.xml**.
The file opens in the NetBeans XML editor.
- 2 Scroll to the **query-builder** element that contains the blocking query to configure.
- 3 If a **config** element does not exist for the query, create one between the **query-builder** tags.
- 4 In the **config** element, create a new **block-definition** element with a **number** attribute and assign a unique ID code to the **number** attribute.

For example:

```
<config>
  <block-definition number="ID1">
  </block-definition>
</config>
</query-builder>
```

- 5 To add a hint, create and define a new **hint** element in the new **block-definition** element.

The following example illustrates an Oracle hint.

```
<config>
  <block-definition number="ID1">
    <hint>FIRST_ROWS_100</hint>
  </block-definition>
</config>
```

```

    </block-definition>
</config>

```

- 6 In the new `block-definition` element, create a `block-rule` element.
- 7 For each field in the data block, define the elements described in [“Master Index Query Block Fields and XML Elements” on page 39](#).

For example:

```

<config>
  <block-definition number="ID1">
    <hint>FIRST_ROWS_100</hint>
    <block-rule>
      <equals>
        <field>Enterprise.SystemSBR.Person.FirstNamePh</field>
        <source>Person.FirstNamePh</source>
      </equals>
      <equals>
        <field>Enterprise.SystemSBR.Person.LastNamePh</field>
        <source>Person.LastNamePh</source>
      </equals>
      <range>
        <field>Enterprise.SystemSBR.Person.DateOfBirth</field>
        <source>Person.DateOfBirth</source>
        <default>
          <lower-bound type="offset">-5</lower-bound>
          <upper-bound type="constant">2006-01-01</upper-bound>
        </default>
      </range>
    </block-rule>
  </block-definition>
</config>

```

- 8 Save and close the file.

Modifying a Query Block for a Master Index Query

Once block definitions are created for a blocking query, you can modify those definitions if needed. You can add, modify, and remove block fields. When adding or removing fields from a query block, verify that the query will still include all the needed fields.

▼ To Modify a Query Block (Configuration Editor)

- 1 In the Projects window, right-click the Configuration node in the project you want to modify, and then click Edit.

The Configuration Editor appears.

- 2 Click the Query tab.

The Query page appears.

- 3 In the Blocking Queries section, select the query you want to modify and then click Edit.

The Blocking Query Builder dialog box appears.

- 4 In the Block Definitions section, select the block to modify and then click Edit.

The Block Definition dialog box appears.

- 5 Do any of the following:

- To add a new field, click Add, enter the fields described in [“Master Index Query Block Fields and XML Elements” on page 39](#), and then click OK.
- To edit an existing field, select the field you want to modify, click Edit, modify any of the fields described in [“Master Index Query Block Fields and XML Elements” on page 39](#), and then click OK.
- To delete an existing field, select the field you want to delete, click Remove, and then click Yes on the dialog box that appears.

- 6 When you are done modifying the query block, click OK.

- 7 On the Blocking Query Builder dialog box, click OK.

- 8 On the Configuration Editor toolbar, click Save.

▼ To Modify a Query Block (XML Editor)

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click query.xml.

The file opens in the NetBeans XML editor.

- 2 Scroll to the `block-rule` element containing the query block you want to modify.

- 3 To add a new blocking field, add and populate the elements described in [“Master Index Query Block Fields and XML Elements” on page 39](#).

For example:

```
<block-rule>
  <equals>
    <field>Enterprise.SystemSBR.Person.DOB</field>
    <source>Person.DOB</source>
  </equals>
  ...
```

- 4 To edit an existing field, modify any of the elements described in [“Master Index Query Block Fields and XML Elements” on page 39](#).
- 5 To delete an existing field, delete all text between and including the search type elements that define the field (such as `equals`, `range`, `not-equals`, and so on).
For example, to delete the DOB field defined above, you would delete the text between and including the `equals` elements.
- 6 Save and close the file.

Deleting a Query Block From a Master Index Query

Once you create a block definition, you can delete it if needed. When deleting a query block, verify that the query will still include all the needed fields.

▼ To Delete a Query Block (Configuration Editor)

- 1 In the Projects window, right-click the Configuration node in the project you want to modify, and then click Edit.
The Configuration Editor appears.
- 2 Click the Query tab.
The Query page appears.
- 3 In the Blocking Queries section, select the query you want to modify and then click Edit.
The Blocking Query Builder dialog box appears.
- 4 In the Block Definitions section, select the definition you want to delete.
- 5 Click Remove.
- 6 On the confirmation dialog box, click Yes.

- 7 On the Configuration Editor toolbar, click Save.

▼ To Delete a Query Block (XML Editor)

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click query.xml.

The file opens in the NetBeans XML editor.

- 2 Scroll to the query-builder element that contains the blocking query to modify.
- 3 In that query-builder element, delete all text between and including the block-definition element defining the data block to remove.

For example, in the sample below, to delete the SSN block you would delete the boldface text.

```
<config>
  <block-definition number="ID000007">
    <block-rule>
      <equals>
        <field>Enterprise.SystemSBR.Person.SSN</field>
        <source>Person.SSN</source>
      </equals>
    </block-rule>
  </block-definition>
  <block-definition number="ID000008">
    <block-rule>
      <equals>
        <field>Enterprise.SystemSBR.Person.DOB</field>
        <source>Person.DOB</source>
      </equals>
    </block-rule>
  </block-definition>
```

Note – Each blocking query must contain one config element, and the config element must contain at least one block definition.

- 4 Save and close the file.

Deleting a Master Index Query

Once you create a query, you can delete it if needed. If any of the queries you delete are defined as the matching query in `master.xml` or as a search in `midm.xml`, modify those files to point to an existing query. If a defined query is no longer used, you can leave the query in `query.xml` as it will not affect processing if you do not delete the query.

Note – The changes you make on the Query page of the Configuration Editor are reflected in `query.xml`. For more information about this file and the configurable query options, see [“Query Configuration” in *Sun Master Index Configuration Reference*](#).

▼ To Delete a Query (Configuration Editor)

- 1 In the Projects window, right-click the Configuration node in the project you want to modify, and then click **Edit**.
The Configuration Editor appears.
- 2 Click the **Query** tab.
The Query page appears.
- 3 In the **Blocking Queries** or **Basic Queries** section, select the query you want to delete.
- 4 Click **Remove**.
- 5 On the Configuration Editor toolbar, click **Save**.

▼ To Delete a Query

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `query.xml`.
The file opens in the NetBeans XML editor.
- 2 Scroll to the `query-builder` element that contains the query you want to remove.

- 3 **Delete all text between and including the query-builder element defining the query, including any defined query blocks.**

For example, to delete the query named PHONETIC-SEARCH, you would remove all text below.

```
<query-builder name="PHONETIC-SEARCH"
  class= "com.sun.mdm.index.querybuilder.BasicQueryBuilder"
  parser-class= "com.sun.mdm.index.configurator.impl.querybuilder.KeyValueConfiguration"
  standardize="true" phoneticize="true">
  <config>
  <option key="UseWildcard" value="false"/>
  </config>
</query-builder>
```

- 4 **Save and close the file.**

Configuring Master Index Processing Options

The Master Controller defines how transactions are processed, and is configured in master.xml. You can specify Java classes that insert additional logic into the match process, configure the blocking query to use for matching, define how merged record updates are handled, and specify whether a record's potential duplicates are reevaluated after it is updated. You can customize the Master Controller by performing any of the following actions.

- [“Specifying Master Index Custom Logic Classes” on page 51](#)
- [“Specifying the Master Index Update Mode” on page 52](#)
- [“Configuring Master Index Merged Record Updates” on page 53](#)
- [“Specifying the Master Index Blocking Query for Matching” on page 54](#)
- [“Setting Master Index Blocking Query Options” on page 54](#)
- [“Defining Master Index Transactional Support” on page 55](#)

Specifying Master Index Custom Logic Classes

The logic-class element specifies custom match processing logic for messages coming from external systems. The and logic-class-gui element specifies custom match processing logic for the MIDM. If no custom plug-ins were created to define the custom logic, leave these elements empty. Custom logic classes can only be specified by modifying the XML file directly.

▼ To Specify Custom Logic for External System Messages

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click master.xml.

- 2 In the `MasterControllerConfig` element, change the value of the `logic-class` element to the name of the custom plug-in that contains the back-end logic.

For example:

```
<logic-class>com.sun.mdm.index.user.CustomProcessing</logic-class>
```

- 3 Save and close the file.

▼ To Specify Custom Logic for the Master Index Data Manager

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `master.xml`.

- 2 In the `MasterControllerConfig` element, change the value of the `logic-class-gui` element to the name of the custom plug-in that contains the MIDM logic.

For example:

```
<logic-class-gui>com.sun.mdm.index.user.CustomMIDM</logic-class-gui>
```

- 3 Save and close the file.

Specifying the Master Index Update Mode

The `update-mode` element specifies whether potential duplicates are reevaluated for a record each time the record is updated. If you specify that potential duplicates are reevaluated, the reevaluation only occurs when updates are made to fields involved in blocking and matching. The update mode can only be specified by modifying the XML file directly.

▼ To Specify Potential Duplicates be Reevaluated at Each Update

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `master.xml`.

- 2 In the `MasterControllerConfig` element, change the value of the `update-mode` element to **Pessimistic**.

For example:

```
<update-mode>Pessimistic</update-mode>
```

- 3 Save and close the file.

▼ To Specify Potential Duplicates not be Reevaluated at Each Update

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click master.xml.

- 2 In the MasterControllerConfig element, change the value of the update-mode element to **Optimistic**.

For example:

```
<update-mode>Optimistic</update-mode>
```

- 3 Save and close the file.

Configuring Master Index Merged Record Updates

The merged-record-update element allows you to define whether updates can be made to records with a status of Merged.

▼ To Allow Merged Record Updates

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click master.xml.

- 2 In the MasterControllerConfig element, change the value of the merged-record-update element to **Enabled**.

For example:

```
<merged-record-update>Enabled</merged-record-update>
```

- 3 Save and close the file.

▼ To Prevent Merged Record Updates

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click master.xml.

- 2 In the MasterControllerConfig element, change the value of the merged-record-update element to **Disabled**.

For example:

```
<merged-record-update>Disabled</merged-record-update>
```

- 3 Save and close the file.

Specifying the Master Index Blocking Query for Matching

You need to specify the query that will be used by the master index application to retrieve a candidate selection pool of records that closely match an incoming record and that will be used for probabilistic weighting. The name of the blocking query you specify here must match the name of one of the blocking queries defined in query.xml. You can only specify one blocking query for matching in the master index application.

Note – Modifying the blocking query once your system is in production is not recommended because it can cause issues with data integrity.

▼ To Specify the Blocking Query for Matching

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click master.xml.
- 2 Scroll to the `execute-match` element in the `MasterControllerConfig` element.

- 3 Modify the value of the `query-builder` name to the name of the blocking query you want to use. For example:

```
<execute-match>
  <query-builder name="MY-BLOCKER">
    <option key="key" value="value"/>
  </query-builder>
</execute-match>
```

Note – Make sure the name you specify exactly matches the name of one of the blocking queries defined in query.xml.

- 4 Set the blocking query options, as described in [“Setting Master Index Blocking Query Options” on page 54](#).
- 5 Save and close the file.

Setting Master Index Blocking Query Options

Key and value pairs are designed to fine-tune the operation of custom blocking queries. In the default blocking queries defined in query.xml, key and value pairs are not used. However, if you create a custom blocking query, you can configure the query to use key and value pairs. The key describes the option, and the value specifies the value of the option.

▼ To Set Blocking Query Options

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click master.xml.
- 2 Scroll to the `execute-match` element.
- 3 To specify a key and value pair, modify the values of the key and value attributes in the option element.
For example:

```
<option key="wildcard" value="true"/>
```
- 4 To delete a key and value pair, remove the option element.
- 5 Save and close the file.

Defining Master Index Transactional Support

You can define the master index application to distribute transactions across applications, to distribute transactions only within the master index application, or to not use distributed transactions at all. You can define transactional support by using the Configuration Editor or by modifying the XML file directly. When you define transactional support for the master index, make sure to use the appropriate transaction properties for the database connection in the Sun Java System Admin Console.

▼ To Configure the Master Index for Local Transactions

- 1 In the Projects window, right-click the Configuration node in the project you want to modify, and then click Edit.
The Configuration Editor appears.
- 2 Click the Deployment tab.
- 3 In the Transaction Mode field, select LOCAL.
- 4 On the Configuration Editor toolbar, click Save.

- 5 To configure the database connection, launch the application service Admin Console, and do one of the following:
 - If the database connection is already defined, do the following on the Admin Console:
 - a. In the left frame, expand Resources > JDBC > Connection Pools.
 - b. Select the database connection pool that is defined for your master index application.
 - c. On the Edit Connection Pool page, select either `javax.sql.DataSource` or `javax.sql.ConnectionPoolDataSource` for the Resource Type and click Save.
 - If the database connection is not already defined, follow the instructions provided in [“Defining the Database Connection Pools”](#) in *Sun Master Index User’s Guide*. Select either `javax.sql.DataSource` or `javax.sql.ConnectionPoolDataSource` for the connection pool Resource Type.

▼ To Configure the Master Index to Distributed Transactions Across Applications

- 1 In the Projects window, right-click the Configuration node in the project you want to modify, and then click Edit.

The Configuration Editor appears.
- 2 Click the Deployment tab.
- 3 In the Transaction Mode field, select XA (across applications).
- 4 On the Configuration Editor toolbar, click Save.
- 5 Launch the application server Admin Console (from NetBeans, click the Services tab, expand Servers, right-click the domain, and select View Admin Console).
- 6 To configure the database connection, launch the application service Admin Console, and do one of the following:
 - If the database connection is already defined, do the following on the Admin Console:
 - a. In the left frame, expand Resources > JDBC > Connection Pools.
 - b. Select the database connection pool that is defined for your master index application.

c. On the Edit Connection Pool page, select `javax.sql.XADataSource` for the Resource Type and click Save.

- If the database connection is not already defined, follow the instructions provided in [“Defining the Database Connection Pools” in *Sun Master Index User’s Guide*](#). Select `javax.sql.XADataSource` for the Resource Type.

▼ To Configure the Master Index for Distributed Transactions Within the Master Index Application Only

- 1 In the Projects window, right-click the Configuration node in the project you want to modify, and then click Edit.
The Configuration Editor appears.
- 2 Click the Deployment tab.
- 3 In the Transaction Mode field, select XA (within application only).
- 4 On the Configuration Editor toolbar, click Save.
- 5 To configure the database connection, launch the application server Admin Console and do one of the following:
 - If the database connection is already defined, do the following on the Admin Console:
 - a. In the left frame, expand Resources > JDBC > Connection Pools.
 - b. Select the database connection pool that is defined for your master index application.
 - c. On the Edit Connection Pool page, select `javax.sql.XADataSource` for the Resource Type and click Save.
 - If the database connection is not already defined, follow the instructions provided in [“Defining the Database Connection Pools” in *Sun Master Index User’s Guide*](#). Select `javax.sql.XADataSource` for the Resource Type.

Configuring Matching Parameters

The Decision Maker is configured in master.xml and defines how to handle certain decision points in the matching process, such as weight thresholds, how to handle multiple records above the match threshold, and whether records originating from the same system can be automatically matched.

You can customize the Decision Maker by performing any of the following actions:

- [“Specifying the Master Index Decision Maker Class” on page 58](#)
- [“Defining How to Handle Multiple Assumed Matches \(OneExactMatch\)” on page 58](#)
- [“Specifying Whether Same System Matches are Allowed \(SameSystemMatch\)” on page 60](#)
- [“Specifying the Master Index Duplicate Threshold” on page 61](#)
- [“Specifying the Master Index Match Threshold” on page 62](#)
- [“Adding and Deleting Master Index Decision Maker Parameters” on page 63](#)

Specifying the Master Index Decision Maker Class

If you create your own Decision Maker class, you can specify the new class to be used by changing the value of the decision-maker-class element.

▼ To Specify the Decision Maker Class

- 1 **In the Projects window, expand the Configuration node in the project you want to modify, and then double-click master.xml.**
- 2 **Scroll to the DecisionMakerConfig element.**
- 3 **Change the value of the decision-maker-class element to the path and name of the new Decision Maker class.**

For example:

```
<decision-maker-class>com.sun.mdm.index.decision.impl.MyDecisionMaker
</decision-maker-class>
```

- 4 **Save and close the file.**

Defining How to Handle Multiple Assumed Matches (OneExactMatch)

The OneExactMatch parameter determines how records above the match threshold are processed. This parameter can only be modified directly in the XML file. For more information,

see “Manager Service Configuration” in *Sun Master Index Configuration Reference* and “Understanding Operational Processes,” in *Understanding Sun Master Index Processing*.

▼ To Create Potential Duplicates When Multiple Records Match

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click master.xml.
- 2 Scroll to the `OneExactMatch` element in the `DecisionMakerConfig` element.
- 3 Change the value of the `parameter-value` element to `true`.

For example:

```
<parameter>
  <parameter-name>OneExactMatch</parameter-name>
  <parameter-type>java.lang.Boolean</parameter-type>
  <parameter-value>true</parameter-value>
</parameter>
```

- 4 Save and close the file.

▼ To Match the Highest Weighted Records When Multiple Records Match

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click master.xml.
- 2 Scroll to the `OneExactMatch` element in the `DecisionMakerConfig` element.
- 3 Change value of the `parameter-value` element to `false`.

For example:

```
<parameter>
  <parameter-name>OneExactMatch</parameter-name>
  <parameter-type>java.lang.Boolean</parameter-type>
  <parameter-value>>false</parameter-value>
</parameter>
```

- 4 Save and close the file.

Specifying Whether Same System Matches are Allowed (SameSystemMatch)

The SameSystemMatch parameter determines whether two records with local IDs from the same system can be merged automatically. If your local systems contain reliable data, and rarely duplicate their own records, set this parameter to **true**. This parameter can only be modified directly through the XML file.

▼ To Allow Same System Records to be Automatically Merged

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click master.xml.
- 2 Scroll to the SameSystemMatch element in the DecisionMakerConfig element.
- 3 Change the value of the parameter-value element to false.

For example:

```
<parameter>
  <parameter-name>SameSystemMatch</parameter-name>
  <parameter-type>java.lang.Boolean</parameter-type>
  <parameter-value>>false</parameter-value>
</parameter>
```

- 4 Save and close the file.

▼ To Prevent Same System Records From Being Automatically Merged

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click master.xml.
- 2 Scroll to the SameSystemMatch element in the DecisionMakerConfig element.
- 3 Change the value of the parameter-value element to true.

For example:

```
<parameter>
  <parameter-name>SameSystemMatch</parameter-name>
  <parameter-type>java.lang.Boolean</parameter-type>
  <parameter-value>>true</parameter-value>
</parameter>
```

- 4 Save and close the file.

Specifying the Master Index Duplicate Threshold

The duplicate threshold is the lowest matching probability weight at which two records are considered potential duplicates of one another. Any records with lower probability weights are not considered to be possible matches. Any records between the duplicate and match thresholds are flagged as potential duplicates, and must be resolved manually. You can configure the duplicate threshold by using the Configuration Editor or by modifying the XML file directly.

▼ To Specify the Duplicate Threshold (Configuration Editor)

- 1 In the Projects window, right-click the Configuration node in the project you want to modify, and then click Edit.

The Configuration Editor appears.

- 2 Click the Matching tab.
- 3 In the Duplicate Threshold field, enter the lowest weight at which two records should be considered a potential match.

Note – This value can be any float value lower than the match threshold but higher than the lowest possible matching probability weight.

- 4 On the Configuration Editor toolbar, click Save.

▼ To Specify the Duplicate Threshold (XML Editor)

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click master.xml.
- 2 Scroll to the DuplicateThreshold element in the DecisionMakerConfig element.
- 3 Change the value of the parameter-value element. For example:

```
<parameter>
  <parameter-name>DuplicateThreshold</parameter-name>
  <parameter-type>java.lang.Float</parameter-type>
  <parameter-value>7.9</parameter-value>
</parameter>
```

Note – This value can be any float value lower than the match threshold but higher than the lowest possible matching probability weight.

- 4 **Save and close the file.**

Specifying the Master Index Match Threshold

The match threshold specifies the matching probability weight at which two records will be automatically merged, depending on the value of the `OneExactMatch` parameter and the number of records at or above the match threshold. You can configure the match threshold by using the Configuration Editor or by modifying the XML file directly.

▼ To Specify the Match Threshold (Configuration Editor)

- 1 **In the Projects window, right-click the Configuration node in the project you want to modify, and then click Edit.**
The Configuration Editor appears.
- 2 **Click the Matching tab.**
- 3 **In the Match Threshold field, enter the lowest weight at which two records should be considered a match.**

Note – This value can be any float value higher than the duplicate threshold but lower than the highest possible matching probability weight.

- 4 **On the Configuration Editor toolbar, click Save.**

▼ To Specify the Match Threshold (XML Editor)

- 1 **In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `master.xml`.**
- 2 **Scroll to the `MatchThreshold` element in the `DecisionMakerConfig` element.**
- 3 **Change the value of the `parameter-value` element.**

For example:

```
<parameter>  
  <parameter-name>MatchThreshold</parameter-name>  
  <parameter-type>java.lang.Float</parameter-type>
```

```
<parameter-value>28.5</parameter-value>
</parameter>
```

Note – This value can be any float value higher than the duplicate threshold but lower than the highest possible matching probability weight.

- 4 **Save and close the file.**

Adding and Deleting Master Index Decision Maker Parameters

New parameters cannot be used with the default Decision Maker class and existing parameters should not be deleted. If you create a custom Decision Maker class, you might need to add new parameters or delete existing ones for the new class. You can only perform these tasks by modifying the XML file directly.

▼ To Add a New Decision Maker Parameter

- 1 **In the Projects window, expand the Configuration node in the project you want to modify, and then double-click master.xml.**
- 2 **Scroll to the `DecisionMakerConfig` element.**
- 3 **Create a parameter element inside the parameters element, but outside any existing parameter elements. Define the following elements:**
 - `parameter-name` – The name of the parameter.
 - `parameter-type` – The type of parameter. Valid values are `java.lang.Long`, `java.lang.Short`, `java.lang.Byte`, `java.lang.String`, `java.lang.Integer`, `java.lang.Boolean`, `java.lang.Double`, or `java.lang.Float`.
 - `parameter-value` – The value of the parameter.

For example:

```
<parameters>
  <parameter>
    <parameter-name>OneExactMatch</parameter-name>
    <parameter-type>java.lang.Boolean</parameter-type>
    <parameter-value>false</parameter-value>
  </parameter>
  <parameter>
    <parameter-name>MaxDuplicates</parameter-name>
    <parameter-type>java.lang.Boolean</parameter-type>
```

```
        <parameter-value>5</parameter-value>
      </parameter>
    </parameters>
```

- 4 Save and close the file.

▼ To Delete a Decision Maker Parameter

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click master.xml.
- 2 Scroll to the `DecisionMakerConfig` element.
- 3 To delete one parameter, remove all text between and including the parameter element.

For example, to delete the `ExtensiveSearch` parameter in the following sample, you would delete the boldface text.

```
<parameters>
  <parameter>
    <parameter-name>OneExactMatch</parameter-name>
    <parameter-type>java.lang.Boolean</parameter-type>
    <parameter-value>>false</parameter-value>
  </parameter>
  <parameter>
    <parameter-name>ExtensiveSearch</parameter-name>
    <parameter-type>java.lang.Boolean</parameter-type>
    <parameter-value>true</parameter-value>
  </parameter>
</parameters>
```

- 4 To remove all parameters, remove all text between and including the starting and ending `parameters` element.
- 5 Save and close the file.

Configuring Master Index EUIDs

The EUID Generator controls how the enterprise-wide unique identifiers (EUIDs) are created by the master index application, including the length of the ID and the checksum value. The EUID generator can only be configured by modifying master.xml directly.

You can customize the EUID Generator by performing any of the following actions:

- [“Specifying the Master Index EUID Generator Class” on page 65](#)
- [“Specifying the Master Index EUID Length” on page 65](#)

- “Specifying a Master Index Checksum Length” on page 66
- “Specifying the Master Index Chunk Size” on page 67
- “Adding and Deleting Master Index EUID Generator Parameters” on page 67

Specifying the Master Index EUID Generator Class

The default EUID generator creates sequential EUIDs based on the value specified for the EUID sequence in the `sbyn_seq_table` database table. If you create a new EUID generator class to process EUIDs differently, you must specify the name of the new class in the `euid-generator-class` element of `master.xml`.

▼ To Specify the EUID Generator Class

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `master.xml`.
- 2 Scroll to the `EuidGeneratorConfig` element.
- 3 Change the value of the `euid-generator-class` element to the path and name of the new EUID generator class.

For example:

```
<euid-generator-class>com.sun.mdm.index.idgen.impl.MyEuidGenerator
</euid-generator-class>
```

- 4 Save and close the file.

Specifying the Master Index EUID Length

By default, the length of the EUIDs generated by the master index application is 10 characters. You can modify this value if needed. You can also specify a new starting EUID number. This is described in “[Creating the Master Index Database](#)” in *Sun Master Index User’s Guide*.

If you increase the length of the EUIDs to longer than 20 characters or if the EUID length plus the checksum length is longer than 20 characters, you need to increase the length of the EUID columns in the script that creates the database tables.

▼ To Specify the EUID Length

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `master.xml`.
- 2 Scroll to the first parameter element, `IdLength`, in the `EuidGeneratorConfig` element.

- 3 **Change the value of the `parameter-value` element to the desired length of the EUID.**

For example:

```
<parameter>
  <parameter-name>IdLength</parameter-name>
  <parameter-type>java.lang.Integer</parameter-type>
  <parameter-value>12</parameter-value>
</parameter>
```

- 4 **Save and close the file.**

Specifying a Master Index Checksum Length

A checksum value is a number appended to the end of each EUID that allows systems to validate EUIDs to ensure accurate identification of records throughout the network. For detailed information about checksum values and how they work, see [“Manager Service Components” in *Sun Master Index Configuration Reference*](#).

If you specify **0** (zero), checksum values are not used for validation. If the EUID length plus the checksum length is greater than 20, you need to increase the length of the EUID columns in the database creation scripts.

▼ To Specify a Checksum Length

- 1 **In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `master.xml`.**
- 2 **Scroll to the second `parameter` element, `ChecksumLength`, in the `EuidGeneratorConfig` element.**
- 3 **Change the value of the `parameter-value` element to the desired length of the checksum value.**

For example:

```
<parameter>
  <parameter-name>ChecksumLength</parameter-name>
  <parameter-type>java.lang.Integer</parameter-type>
  <parameter-value>2</parameter-value>
</parameter>
```

- 4 **Save and close the file.**

Specifying the Master Index Chunk Size

You can specify a number of EUIDs to be allocated at one time to the EUID generator. This allows the generator to assign EUIDs to multiple records without needing to query the `sbyn_seq_table` database table each time, which improves performance. For detailed information about the chunk size and how EUIDs are allocated, see “[Manager Service Components](#)” in *Sun Master Index Configuration Reference*.

▼ To Specify the Chunk Size

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `master.xml`.
- 2 Scroll to the third parameter element, `ChunkSize`, in the `EuidGeneratorConfig` element.
- 3 Change the value of the `parameter-value` element to the desired chunk size.

For example:

```
<parameter>
  <parameter-name>EuidGeneratorConfig</parameter-name>
  <parameter-type>java.lang.Integer</parameter-type>
  <parameter-value>100</parameter-value>
</parameter>
```

- 4 Save and close the file.

Adding and Deleting Master Index EUID Generator Parameters

You cannot add or delete parameters for the default EUID Generator class, but if you create a custom EUID generator class, you can create additional parameters for the new class and delete the existing parameters if they are not used.

▼ To Add EUID Generator Parameters

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `master.xml`.
- 2 Scroll to the `EuidGeneratorConfig` element.
- 3 Create a new parameter element inside the `parameters` element, but outside any existing parameter elements. Add the following elements:

- `parameter-name` – The name of the parameter.
- `parameter-type` – The type of parameter. Valid values are `java.lang.Long`, `java.lang.Short`, `java.lang.Byte`, `java.lang.String`, `java.lang.Integer`, `java.lang.Boolean`, `java.lang.Double`, or `java.lang.Float`.
- `parameter-value` – The value of the parameter.

For example:

```
<parameters>
  <parameter>
    <parameter-name>IdLength</parameter-name>
    <parameter-type>java.lang.Integer</parameter-type>
    <parameter-value>10</parameter-value>
  </parameter>
  <parameter>
    <parameter-name>IncrementBy</parameter-name>
    <parameter-type>java.lang.Integer</parameter-type>
    <parameter-value>5</parameter-value>
  </parameter>
</parameters>
```

4 Save and close the file.

▼ To Delete EUID Generator Parameters

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `master.xml`.
- 2 Scroll to the `EuidGeneratorConfig` element.
- 3 To delete one parameter, do the following:

- a. Scroll to the `parameter` element you want to delete.
- b. Remove all text between and including the `parameter` element.

For example, to remove the `StartNumber` parameter in the sample below, delete all boldface text.

```
<parameters>
  <parameter>
    <parameter-name>IdLength</parameter-name>
    <parameter-type>java.lang.Integer</parameter-type>
    <parameter-value>10</parameter-value>
  </parameter>
  <parameter>
    <parameter-name>StartNumber</parameter-name>
```

```

        <parameter-type>java.lang.Integer</parameter-type>
        <parameter-value>1000000001</parameter-value>
    </parameter>
</parameters>

```

- 4 To remove all parameters, remove all text between and including the `parameters` element.
- 5 Save and close the file.

Defining Master Index Normalization Rules

Normalization is a part of the standardization process, and is the process of changing non-standard values to a common, standard value. For example, the first name a person uses might not be their given name, but might be a nickname instead. To ensure that a proper match is made between first names, nicknames are normalized based on a configurable list. For example, the common value for “Liz” and “Elizabeth” would be “Elizabeth”.

Normalization is defined in `mefa.xml`. You can define normalization by either using the Configuration Editor or modifying the XML file directly. The changes you make on the Normalization page of the Configuration Editor are reflected in the normalization structures of `mefa.xml`. The Configuration Editor provides a simplified way of defining normalization.

Perform any of the following tasks to define normalization:

- [“Defining a Master Index Field to be Normalized” on page 69](#)
- [“Modifying a Master Index Normalization Definition” on page 75](#)
- [“Deleting a Master Index Normalization Definition” on page 77](#)

Defining a Master Index Field to be Normalized

When you define a field for normalization, you define which field contains the data that needs to be normalized and which field will contain the normalized data. You can also specify one or more variants to use for normalization. A sample normalization structure for the XML file appears at the end of these instructions.

▼ To Define a Field to be Normalized (Configuration Editor)

- 1 In the **Projects** window, right-click the **Configuration** node in the project you want to modify, and then click **Edit**.

The Configuration Editor appears.

- 2 In the object structure in the left pane, add the field that will contain the normalized value. For more information, see [“Adding a Field to the Master Index Object Structure” on page 21](#).

3 Click the Normalization tab.

The Normalization page appears.

4 Click Add.

The Normalized Field dialog box appears.

5 Enter or select a value for each of the fields described in “[Master Index Normalization and Standardization Structure Properties](#)” on page 73.

6 To specify a variant for the type of data being standardized, do the following:

- a. In the Variant Field Name field, select the field whose value in incoming records will indicate which variant to use.
- b. In the Variants section, click Add.
- c. On the dialog box that appears, enter values in the fields described in “[Master Index Variants Properties](#)” on page 75.
- d. Click OK.

If you selected the multiple domain selector, you can add multiple variants; otherwise, you can add one default variant and one field-defined variant.

7 On the Normalized Field dialog box, click OK.

The new normalization definition appears in the list.

8 On the Configuration Editor toolbar, click Save.

▼ To Define a Field to be Normalized (XML Editor)

Before You Begin In object.xml, create the field that will contain the new normalized value. For more information, see “[Adding a Field to the Master Index Object Structure](#)” on page 21.

1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click mefa.xml.

The file opens in the NetBeans XML editor.

2 In the structures-to-normalize element, create and name a new group element.

Make sure the new element falls within the structures-to-normalize element, but outside any existing group tags.

- 3 In the new group element, define the standardization-type and domain-selector attributes (these are described in [“Master Index Normalization and Standardization Structure Properties” on page 73](#)).
- 4 If you specified the multiple domain selector for the domain-selector attribute, do the following:
 - a. In the group element, create a locale-field-name element and a locale-maps element (described in [“Master Index Normalization and Standardization Structure Properties” on page 73](#) and [“Master Index Variants Properties” on page 75](#)).
 - b. For each variant you want to use, define a locale-codes, value, and locale element in the locale-maps element (described in [“Master Index Variants Properties” on page 75](#)).
- 5 To specify the source fields to normalize, do the following:
 - a. Create a new unnormalized-source-fields element in the group element.
 - b. Create a source-mapping element in the new unnormalized-source-fields element.
 - c. Define the unnormalized-source-field-name and standardized-object-field-id elements (these are described in [“Master Index Normalization and Standardization Structure Properties” on page 73](#)).
- 6 To map the normalized data to destination fields, do the following:
 - a. Create a new normalization-targets element under the unnormalized-source-fields element that defines the field to map.
 - b. Create a target-mapping element in the new normalization-targets element.
 - c. Define the standardized-object-field-id and standardized-target-field-name elements (these are described in [“Master Index Normalization and Standardization Structure Properties” on page 73](#)).
- 7 Save and close the file.

Example 2 First and Last Name Normalization

```
<structures-to-normalize>
  <group standardization-type="PersonName" domain-selector=
    "com.sun.mdm.index.matching.impl.MultiDomainSelector">
    <locale-field-name>Person.PobCountry</locale-field-name>
    <locale-maps>
      <locale-codes>
```

```
<value>GB</value>
<locale>UK</locale>
</locale-codes>
<locale-codes>
  <value>UNST</value>
  <locale>US</locale>
</locale-codes>
<locale-codes>
  <value>Default</value>
  <locale>US</locale>
</locale-codes>
</locale-maps>
<unnormalized-source-fields>
  <source-mapping>
    <unnormalized-source-field-name>
      Person.Alias[*].FirstName
    </unnormalized-source-field-name>
    <standardized-object-field-id>FirstName
    </standardized-object-field-id>
  </source-mapping>
  <source-mapping>
    <unnormalized-source-field-name>
      Person.Alias[*].LastName
    </unnormalized-source-field-name>
    <standardized-object-field-id>LastName
    </standardized-object-field-id>
  </source-mapping>
</unnormalized-source-fields>
<normalization-targets>
  <target-mapping>
    <standardized-object-field-id>FirstName
    </standardized-object-field-id>
    <standardized-target-field-name>
      Person.Alias[*].StdFirstName
    </standardized-target-field-name>
  </target-mapping>
  <target-mapping>
    <standardized-object-field-id>LastName
    </standardized-object-field-id>
    <standardized-target-field-name>
      Person.Alias[*].StdLastName
    </standardized-target-field-name>
  </target-mapping>
</normalization-targets>
</group>
```


Master Index Normalization and Standardization Structure Properties

The following table lists and describes the Configuration Editor fields and their corresponding XML elements that define the fields to be normalized or standardized in the master index application.

You can specify one or more variants for data to be standardized. A variant is a subset of a data type. For example, if the data type is address, variants are defined for addresses from different countries. The rule set for each country is called a variant. For a single variant, you only need to specify the variant if you need to standardize data that is not from the United States. If you are standardizing data from multiple countries, use the multiple domain selector. This requires that one field in the object structure identify which variant to use for each field that will be standardized. For example, the value of the Country field in a system record could be used to tell the standardization engine which variant to use for a particular set of data. If you specified the multiple domain selector in the `domain-selector` element, you must also define the identifying field and then map the values that can be populated into that field to their corresponding variant.

The following rules apply to the multiple domain selector:

- You can specify a value of “Default” for the identifying field. The corresponding variant is used if the identifying field is blank, contains the value “Default”, or contains a value not defined by any of the `value` elements.
- If a “Default” value is not defined, the system default variant, United States, is used as the default.

For more information about the fields and elements described in the following table, see [Master Index Standardization Engine Reference](#).

Configuration Editor Field	XML File Element or Attribute	Description
Data Type	standardization-type	The type of standardization to perform on the source fields. This is specific to the type of data being processed.

Configuration Editor Field	XML File Element or Attribute	Description
Domain Selector	domain-selector	<p>The Java class used by the standardization engine to determine the variant of the data being processed. For the Master Index Standardization Engine, the following classes can be specified. If no selector is specified, the default is US. The Master Index Standardization Engine supports Australian, French, United Kingdom, and United States variants. Possible values for this field are:</p> <ul style="list-style-type: none"> ■ com.sun.mdm.index.matching.impl. SingleDomainSelectorAU ■ com.sun.mdm.index.matching.impl. SingleDomainSelectorFR ■ com.sun.mdm.index.matching.impl. SingleDomainSelectorUK ■ com.sun.mdm.index.matching.impl. SingleDomainSelectorUS ■ com.sun.mdm.index.matching.impl. MultipleDomainSelector
Variant Field Name	locale-field-name	The ePath to an identifying field in the object structure that identifies which of the defined variants (element <code>locale-codes</code>) to use. If no field is specified for the Master Index Standardization Engine, the standardization engine defaults to the United States, regardless of whether any variants are defined. This field must be contained in the object that contains the fields defined for normalization in this structure.
Unnormalized Source	unnormalized-source-field-name	The field that contains the data to be normalized. The field is designated by its ePath (for example, <code>Person.FirstName</code>).
Unnormalized Standardization Component	standardized-object-field-id	An identification code that identifies the field to normalize to the standardization engine. This ID is specific to the standardization engine and must correspond to a standardization component defined by that engine.
Normalized Standardization Component	standardized-object-field-id	An identification code that identifies the field that contains the normalized data to the standardization engine. This is specific to the standardization engine in use and must correspond to a standardization component defined by that engine.
Normalized Target	standardized-target-field-name	The field that will store the normalized data. The field is designated by its ePath (for example, <code>Person.Alias[*].StdLastName</code>).

Master Index Variants Properties

The following table lists and describes the Configuration Editor fields and XML elements that define a variant for normalization or standardization. In the XML file, each value and locale pair are defined within a `locale_codes` element. A list of `locale_codes` elements can be defined in the `locale_maps` element.

Configuration Editor Field	XML File Element or Attribute	Description
Value	value	A value that indicates to the standardization engine which variant to use to standardize the data. When the value is contained in the Variant Field Name field (or the <code>locale-field-name</code> element), the standardization engine uses the corresponding Variant field (or locale element) to determine the variant. To specify a default variant, enter "Default".
Variant	locale	A code indicating which variant to use to standardize data when the identifying field value in a transaction matches the corresponding Value field or element. Select one of the following codes. <ul style="list-style-type: none"> ■ AU - Australia ■ FR - France ■ UK - United Kingdom ■ US - United States

Modifying a Master Index Normalization Definition

Once you create a normalization definition, you can modify it as needed. Use caution when modifying normalization definitions once a system is in production. This can cause inconsistent match results.

▼ To Modify a Normalization Definition (Configuration Editor)

- 1 In the **Projects** window, right-click the **Configuration** node in the project you want to modify, and then click **Edit**.

The Configuration Editor appears.

- 2 Click the **Normalization** tab.

The Normalization page appears.

- 3 In the **Normalization Mappings** list, click the definition you want to modify.

- 4 Click **Edit**.

- 5 Do any of the following:
 - Modify any of the fields described in [“Master Index Normalization and Standardization Structure Properties” on page 73](#).
 - To modify a variant, select the variant under Variants, and then click Edit. Modify either field on the dialog box that appears.
 - To remove a variant, select the variant under Variants, and then click Remove. Click Yes on the dialog box that appears.
 - Click OK.
- 6 On the Configuration Editor toolbar, click Save.

▼ To Modify a Normalization Structure (XML Editor)

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click mefa.xml.
The file opens in the NetBeans XML editor.
- 2 Scroll to the `structures-to-normalize` element in the `StandardizationConfig` element.
- 3 To modify the normalization type, change the value of the `standardization-type` attribute.
- 4 To change the national domain, change the value of the `domain-selector` element as described in [“Master Index Normalization and Standardization Structure Properties” on page 73](#).
- 5 To modify an existing source field, scroll to the `unnormalized-source-fields` element in the appropriate `group` element, and then change the value of any source field elements (these are described in [“Master Index Normalization and Standardization Structure Properties” on page 73](#)).
- 6 To modify an existing destination field, scroll to the `normalization-targets` element in the appropriate `group` element, and then change the value of any target field elements (these are described in [“Master Index Normalization and Standardization Structure Properties” on page 73](#)).
- 7 Save and close the file.

Deleting a Master Index Normalization Definition

If a defined normalization structure is not needed, you can delete the normalization structure from the standardization configuration. If no data requires normalization, you can delete all normalization structures. It is not recommend that you delete a normalization definition once a system is in production. This can cause inconsistent match results.

▼ To Delete a Normalization Definition

- 1 In the **Projects** window, right-click the **Configuration** node in the project you want to modify, and then click **Edit**.

The Configuration Editor appears.

- 2 In the **Configuration Editor** toolbar, click the **Normalization** tab.

The Normalization page appears.

- 3 In the **Normalization Mappings** list, click the definition you want to delete.

- 4 Click **Remove**.

- 5 On the **Configuration Editor** toolbar, click **Save**.

▼ To Delete a Normalization Structure

- 1 In the **Projects** window, expand the **Configuration** node in the project you want to modify, and then double-click **mefa.xml**.

The file opens in the NetBeans XML editor.

- 2 Scroll to the **structures-to-normalize** element in the **StandardizationConfig** element.

- 3 Do either of the following:

- To delete an existing normalization structure, delete all text between and including the **group** element that defines the structure.
- To specify that no objects require normalization, delete all text between, but not including, the **structures-to-normalize** element.

- 4 Save and close the file.

Defining Master Index Standardization Rules

If any of the fields against which searching or matching is performed are entered in free-form text format, those fields must be standardized before being sent to the standardization engine. The process of standardization includes reformatting, or parsing, the input data field and then normalizing some of the parsed data to a standard value. For example, street addresses can be parsed into the house number, street name, street type, and so on. The street name and type can then be normalized to their commonly used values. “Ave” might be normalized to “Avenue”, “St.” to “Street”, and so on.

Standardization is defined in mefa.xml. You can define standardization by either using the Configuration Editor or modifying the XML file directly. The changes you make on the Standardization page of the Configuration Editor are reflected in the standardization structures of mefa.xml. The Configuration Editor provides a simplified way of defining standardization.

Perform any of the following tasks to define standardization:

- [“Defining Master Index Fields to be Standardized” on page 78](#)
- [“Modifying a Master Index Standardization Definition” on page 83](#)
- [“Deleting a Master Index Standardization Definition” on page 85](#)

Defining Master Index Fields to be Standardized

When you define fields for standardization, you can specify the type of standardization to perform on each field or group of fields, the nationality of the data, and a field that indicates which nationality to use (if you specify more than one). You also specify which fields contain the data that needs to be parsed and normalized, and which fields contain the parsed and normalized data. For each standardization structure, you can specify more than one source field, but they must use the same standardization type. The source fields in one standardization structure are concatenated before being parsed.

A sample standardization structure for the XML file is included at the end of these instructions.

▼ To Define Fields to be Standardized (Configuration Editor)

- 1 In the Projects window, right-click the Configuration node in the project you want to modify, and then click Edit.

The Configuration Editor appears.

- 2 In the object structure in the left pane, create the fields that will contain the parsed components of the new field to be standardized.

For more information, see [“Adding a Field to the Master Index Object Structure” on page 21](#).

3 Click the Standardization tab.

The Standardization page appears.

4 Click Add.

The Standardization Type dialog box appears.

5 Enter values for the Data Type, Domain Selector, and Variant Field Name fields (these are described in “[Master Index Normalization and Standardization Structure Properties](#)” on page 73).**6 To define a variant for the standardization engine to use, do the following:**

a. In the Variants section, Click Add.

b. On the Variant dialog box, enter values in the fields described in “[Master Index Variants Properties](#)” on page 75.

c. Click OK.

If you selected the multiple domain selector, you can add multiple variants; otherwise, you can define one default variant and one defined variant.

7 Under Source Fields to be Standardized, click Add.

The Select Source Field(s) dialog box appears.

8 In the left panel, select the field that contains the data that needs to be parsed and normalized, and then click the right arrow.

Note – If the data is contained in more than one field, select all fields that contain the data. For example, a street address might be contained in two fields, such as Street Address and Unit. Both fields should be selected for standardization; they will be concatenated during the standardization process.

9 If you add a field in error, select the field in the Selected Source Field(s) list, and then click the left arrow.**10 Click OK.****11 For each field in which the parsed and normalized data will be stored, do the following:**

a. On the Standardized Fields dialog box, click Add under Target Mappings.

The Target Mapping dialog box appears.

b. In the Select Target field, select the name of a field that will contain standardized data.

- c. In the Available Standardization Components list, select the ID associated with the field, and then click Add between the left and right panels.
- d. To change the priority of a component in the Selected Standardization Components list, select the component and then click Move Up or Move Down.
- e. If you add a component in error, select the component in the Selected Standardization Components list, and then click Remove.
- f. Click OK.

Note – For more information about standardization components and the fields to which they pertain, see [Master Index Standardization Engine Reference](#).

- 12 Click OK on the Standardization Type dialog box.
The new standardization definition appears in the list.
- 13 On the Configuration Editor toolbar, click Save.

▼ To Define Fields to be Standardized (XML Editor)

Before You Begin In object.xml, create the fields that will contain the parsed components of the field to be standardized. For more information, see “[Adding a Field to the Master Index Object Structure](#)” on page 21.

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click mefa.xml.
The file opens in the NetBeans XML editor.
- 2 Scroll to the free-form-texts-to-standardize element in the StandardizationConfig element.
- 3 Create a new group element in the free-form-texts-to-standardize element, and then define the standardization-type and domain-selector attributes (these are described in “[Master Index Normalization and Standardization Structure Properties](#)” on page 73).
Make sure the new element falls within the free-form-texts-to-standardize element, but outside any existing group tags.
- 4 If you specified the multiple domain selector for the domain-selector attribute, do the following:
 - a. In the group element, create a locale-field-name element and a locale-maps element.

- b. Define the elements described in [“Master Index Variants Properties” on page 75](#)).
- 5 To specify the source fields to standardize, do the following:
 - a. If it does not currently exist, create an `unstandardized-source-fields` element in the appropriate group element (each group element can only include one `unstandardized-source-fields` element).
 - b. For each field standardized by the specified standardization type, create and name a new `unstandardized-source-field-name` element in the new `unstandardized-source-fields` element.

Note – If more than one source field is defined, the fields are concatenated prior to standardization (with a pipe (|) between them for the Master Index Standardization Engine). If you want the fields to be processed separately, you need to create two standardization structures. Source fields are designated by their ePaths.

- 6 To specify the destination fields for the standardized data, do the following:
 - a. In the group element for which destination fields need to be defined, create a `standardization-targets` element after the `unstandardized-source-fields` element.
 - b. In the new element, create a `target-mapping` element for each destination field, and then define the last two elements described in [“Master Index Standardization Source and Target Field Elements” on page 82](#).
- 7 Save and close the file.

Example 3 Address Standardization Structure

```
<group standardization-type="Address" domain-selector=
"com.sun.mdm.index.matching.impl.SingleDomainSelectorUS">
  <locale-field-name>Person.Address[*].CountryCode
</locale-field-name>
  <locale-maps>
    <locale-codes>
      <value>GB</value>
      <locale>UK</locale>
    </locale-codes>
    <locale-codes>
      <value>UNST</value>
      <locale>US</locale>
    </locale-codes>
    <locale-codes>
      <value>AU</value>
```

```

        <locale>AU</locale>
    </locale-codes>
    <locale-codes>
        <value>Default</value>
        <locale>AU</locale>
    </locale-codes>
</locale-maps>
<unstandardized-source-fields>
    <unstandardized-source-field-name>Person.Address[*].AddressLine1
</unstandardized-source-field-name>
    <unstandardized-source-field-name>Person.Address[*].AddressLine2
</unstandardized-source-field-name>
</unstandardized-source-fields>
<standardization-targets>
    <target-mapping>
        <standardized-object-field-id>HouseNumber
        </standardized-object-field-id>
        <standardized-target-field-name>Person.Address[*].HouseNumber
        </standardized-target-field-name>
    </target-mapping>
    <target-mapping>
        <standardized-object-field-id>MatchStreetName
        </standardized-object-field-id>
        <standardized-target-field-name>Person.Address[*].StreetName
        </standardized-target-field-name>
    </target-mapping>
</standardization-targets>
</group>
```

Master Index Standardization Source and Target Field Elements

The following table lists and describes the XML elements that define the source and target fields for standardization. The data from the source fields is standardized, and the standardized values are stored in the target fields.

XML File Element or Attribute	Description
unstandardized-source-field-name	The field or fields that contain the data to be standardized. The field is designated by its ePath (for example, Person.FirstName).

XML File Element or Attribute	Description
standardized-object-field-id	An code that identifies the standardized component from the source field to store in the target field. This is specific to the standardization engine in use and must correspond to a standardization component defined by that engine. For more information, see Master Index Standardization Engine Reference .
standardized-target-field-name	The field that stores the standardized data. You can have multiple target fields, depending on how much of the standardized data you want to store. The fields are designated by their ePaths (for example, Person.Alias[*].StdLastName).

Modifying a Master Index Standardization Definition

You can modify an existing standardization definition. Use caution when modifying standardization after a system is in production because it can cause inconsistent matching results.

▼ To Modify a Standardization Definition (Configuration Editor)

- 1 In the Projects window, right-click the Configuration node in the project you want to modify, and then click Edit.
The Configuration Editor appears.
- 2 Click the Standardization tab.
The Standardization page appears.
- 3 In the Standardization Types list, select the definition you want to modify, and then click Edit.
The Standardization Type dialog box appears.
- 4 Do any of the following:
 - Modify any of the fields or perform any of the functions described in [“Defining Master Index Fields to be Standardized” on page 78](#).
 - To modify a variant, select the code under Variants, and then click Edit. Modify either field on the dialog that appears.
 - To remove a variant, select the code under Variants, and then click Remove. Click Yes on the dialog box that appears.
 - To remove a source field, select the field under Source fields to be standardized, and then click Remove. Click Yes on the dialog box that appears.

Note – There must be at least one field in this list.

- **To edit a target field, select the field in the Specifying Target Mappings list and then click Edit.**

Note – You can select new components, move selected components up and down in priority, and remove components.

- **To delete a target field, select the field in the Specifying Target Mappings list, and then click Remove. Click Yes on the dialog box that appears.**
- 5 **When you are done making changes, click OK on the Standardization Type dialog box.**
 - 6 **On the Configuration Editor toolbar, click Save.**

▼ **To Modify a Standardization Definition (XML Editor)**

- 1 **In the Projects window, expand the Configuration node in the project you want to modify, and then double-click mefa.xml.**
The file opens in the NetBeans XML editor.
- 2 **Scroll to the `structures-to-normalize` element in the `StandardizationConfig` element.**
- 3 **To modify the standardization type, change the value of the `standardization-type` attribute.**
- 4 **To change the variant, change the value of the `domain-selector` element (described in [“Master Index Normalization and Standardization Structure Properties” on page 73](#)).**
- 5 **To modify an existing source field, scroll to the appropriate `group` element, and then change the value of the `unstandardized-source-field-name` element to the ePath of the new field.**
- 6 **To modify an existing destination field, scroll to the `target-mapping` element in the `standardization-targets` section, and then change the value of either target mapping element (these are the last two elements described in [“Master Index Standardization Source and Target Field Elements” on page 82](#)).**
- 7 **To remove an existing source field, delete all text between and including the `unstandardized-source-field-name` element that defines the field.**

Note – If no fields require standardization in a defined standardization structure, delete the entire structure as described in [“Deleting a Master Index Standardization Definition” on page 85](#).

- 8 To remove an existing destination field, delete all text between and including the target-mapping tags that define the field.**
-

Note – Each standardization structure must have at least one destination field defined for standardized data. If a structure does not contain any fields that need to be standardized, you can delete the entire structure, as described in [“Deleting a Master Index Standardization Definition” on page 85](#).

- 9 Save and close the file.**

Deleting a Master Index Standardization Definition

You can delete an existing standardization definition. It is not recommended that a standardization definition be deleted after a system is in production since this can cause inconsistent matching results.

▼ To Delete a Standardization Definition (Configuration Editor)

- 1 In the Projects window, right-click the Configuration node in the project you want to modify, and then click Edit.**
The Configuration Editor appears.
- 2 Click the Standardization tab.**
The Standardization page appears.
- 3 In the Standardization Types list, select the definition you want to delete.**
- 4 Click Remove.**
- 5 Click Yes on the dialog box that appears.**
- 6 On the Configuration Editor toolbar, click Save.**

▼ To Delete a Standardization Definition (Configuration Editor)

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click **mefa.xml**.

The file opens in the NetBeans XML editor.

- 2 Scroll to the **free-form-texts-to-standardize** element in the **StandardizationConfig** element.

- 3 Do either of the following:

- To delete an existing standardization structure, delete all text between and including the **group** element that defines the structure.

Using the example below, to delete the Address object, delete all boldface text.

```
<free-form-texts-to-standardize>
  <group standardization-type="BusinessName" domain-selector=
    "com.sun.mdm.index.matching.impl.SingleDomainSelectorUS">
    ...
  </group>
  <group standardization-type="Address" domain-selector=
    "com.sun.mdm.index.matching.impl.SingleDomainSelectorUS">
    ...
  </group>
</free-form-texts-to-standardize>
```

- To specify that no fields require standardization, delete all text between, but not including, the **free-form-texts-to-standardize** element.

This deletes all standardization structures.

- 4 Save and close the file.

Defining Phonetic Encoding for the Master Index

Sun Master Index provides configurable phonetic encoding capabilities. Phonetic encoding is a part of the standardization process, and is the process of changing the value of a data field to its phonetic equivalent. It is used to retrieve records with similar field values from the database for matching. You can specify which fields are phonetically encoded before matching and how they are encoded. There are several different encoders you can use for this purpose. This is most commonly done for first names and street names.

Phonetic encoding is defined in **mefa.xml**. You can define phonetic encoding by either using the Configuration Editor or modifying the XML file directly. The changes you make on the

Phoneticized Field page of the Configuration Editor are reflected in the phonetic encoding structures and the match service section of mefa.xml. The Configuration Editor provides a simplified way of defining phonetic encoding.

Perform any of the following tasks to define phonetic encoding rules:

- [“Defining Master Index Fields for Phonetic Encoding” on page 87](#)
- [“Modifying a Master Index Phonetic Encoding Definition” on page 89](#)
- [“Deleting a Master Index Phonetic Encoding Definition” on page 90](#)
- [“Defining a Master Index Phonetic Encoder” on page 91](#)
- [“Modifying a Master Index Phonetic Encoder” on page 93](#)
- [“Deleting a Master Index Phonetic Encoder” on page 94](#)

Defining Master Index Fields for Phonetic Encoding

You can specify the fields you want to be phonetically encoded, the fields that store the encoded values, and the type of phonetic encoder to use for each field, such as NYSIIS or Soundex. A sample phonetic encoding structure for the XML file is included at the end of these instructions.

▼ To Define a Field for Phonetic Encoding (Configuration Editor)

- 1 **In the Projects window, right-click the Configuration node in the project you want to modify, and then click Edit.**
The Configuration Editor appears.
- 2 **In the object structure in the left pane, create the field that will contain the phonetic value of the field to be encoded.**
For more information, see [“Adding a Field to the Master Index Object Structure” on page 21](#).
- 3 **Click the Phoneticized Fields tab.**
The Phoneticized Field page appears.
- 4 **In the Phoneticized Fields section, click Add.**
The Phoneticized Field dialog box appears.
- 5 **Select values for the fields described in [“Master Index Phonetic Encoding Fields and Elements” on page 88](#).**
- 6 **Click OK.**
The phonetic encoding definition is added to the Phoneticized Fields list.
- 7 **On the Configuration Editor toolbar, click Save.**

▼ **To Define a Field for Phonetic Encoding (XML Editor)**

In object.xml, create the field that will contain the phonetic value. For more information, see [“Adding a Field to the Master Index Object Structure” on page 21](#).

- 1 **In the Projects window, expand the Configuration node in the project you want to modify, and then double-click mefa.xml.**
The file opens in the NetBeans XML editor.
- 2 **Scroll to the phoneticize- fields element in the PhoneticEncodersConfig element.**
- 3 **Create a new phoneticize- field element within the phoneticize- fields element.**
- 4 **In the new phoneticize- field element, create and define the elements described in “Master Index Phonetic Encoding Fields and Elements” on page 88.**
- 5 **Save and close the file.**

Example 4 **Phonetic Encoding Structure**

```
<phoneticize-fields>
  <phoneticize-field>
    <unphoneticized-source-field-name>Person.FirstName
    </unphoneticized-source-field-name>
    <phoneticized-target-field-name>Person.FirstNamePhoneticCode
    </phoneticized-target-field-name>
    <encoding-type>Soundex</encoding-type>
  </phoneticize-field>
</phoneticize-fields>
```

Master Index Phonetic Encoding Fields and Elements

The following table lists and describes the Configuration Editor fields and XML file elements used to define how fields will be phonetically encoded.

Configuration Editor Field	XML File Element	Description
Unphoneticized Source	unphoneticized-source-field-name	The ePath of the source field in the system object that contains the data to be phonetically encoded (for example, Person.Address[*].StreetName). Note – This can refer to the original field or to a standardized or normalized field.

Configuration Editor Field	XML File Element	Description
Phoneticized Target	phoneticized-target-field-name	The ePath of the field in the system object that will store the phonetically encoded value of the source field.
	phoneticized-object-field-id	A field ID to identify the field to the phonetic encoder. This is not currently used with the Master Index Standardization Engine, but could be used with a custom standardization engine.
Encoder	encoding-type	The phonetic encoder to use for this field. This must correspond to an encoder defined in the Encoders section on the Configuration Editor (or the <code>PhoneticEncodersConfig</code> element of the XML file).

Modifying a Master Index Phonetic Encoding Definition

Once you create a phonetic encoding definition, you can modify it as needed. Use caution when modifying definitions once a system is in production. This can cause inconsistent match results.

▼ To Modify a Phonetic Encoding Definition (Configuration Editor)

- 1 In the Projects window, right-click the Configuration node in the project you want to modify, and then click Edit.
The Configuration Editor appears.
- 2 Click the Phoneticized Fields tab.
The Phoneticized Field page appears.
- 3 In the Phoneticized Fields section, select the phonetic encoding definition you want to modify, and then click Edit.
The Phoneticized Field dialog box appears.
- 4 Modify any of the fields listed in [“Master Index Phonetic Encoding Fields and Elements” on page 88](#), and then click OK.
- 5 On the Configuration Editor toolbar, click Save.

▼ To Modify a Phonetic Encoding Definition (XML Editor)

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `mefa.xml`.

The file opens in the NetBeans XML editor.

- 2 Scroll to the `phoneticize-fields` element.
- 3 In the `phoneticize-field` element that defines the phonetic encoding you want to modify, change the value of any of the elements described in [“Master Index Phonetic Encoding Fields and Elements” on page 88](#).
- 4 Save and close the file.

Deleting a Master Index Phonetic Encoding Definition

Once you create a phonetic encoding definition, you can delete it as needed. Use caution when deleting definitions once a system is in production. This can cause inconsistent match results.

▼ To Delete a Phonetic Encoding Definition (Configuration Editor)

- 1 In the Projects window, right-click the Configuration node in the project you want to modify, and then click Edit.

The Configuration Editor appears.

- 2 Click the **Phoneticized Fields** tab.
The Phoneticized Field page appears.
- 3 In the Phoneticized Fields section, select the phonetic encoding definition you want to delete.
- 4 Click **Remove**.
- 5 Click **Yes** on the dialog that appears.
- 6 On the Configuration Editor toolbar, click **Save**.

▼ To Delete a Phonetic Encoding Definition (XML Editor)

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `mefa.xml`.

The file opens in the NetBeans XML editor.

2 Scroll to the **phoneticize-fields** element in the **PhoneticEncodersConfig** element.

3 Do either of the following:

- To delete a field currently specified for phonetic conversion, delete all text between and including the **phoneticize-field** element that defines the field.

Using the example below, to delete the first name phonetic field, delete the boldface text.

```
<phoneticize-fields>
  <phoneticize-field>
    <unphoneticized-source-field-name>Person.LastName
  </unphoneticized-source-field-name>
    <phoneticized-target-field-name>Person.LastNamePhoneticCode
  </phoneticized-target-field-name>
    <encoding-type>NYSIIS</encoding-type>
  </phoneticize-field>
  <phoneticize-field>
    <unphoneticized-source-field-name>Person.FirstName
  </unphoneticized-source-field-name>
    <phoneticized-target-field-name>Person.FirstNamePhoneticCode
  </phoneticized-target-field-name>
    <encoding-type>Soundex</encoding-type>
  </phoneticize-field>
</phoneticize-fields>
```

- To delete all fields currently specified for phonetic conversion, delete all text between, but not including, the **phoneticize-fields** element.

4 Save and close the file.

Defining a Master Index Phonetic Encoder

Each type of phonetic encoder provided with Sun Master Index is defined in the **PhoneticEncodersConfig** section of **meфа.xml**. They are listed in the **Encoders** section of the Configuration Editor.

▼ To Define a Phonetic Encoder (Configuration Editor)

1 In the **Projects** window, right-click the **Configuration** node in the project you want to modify, and then click **Edit**.

The Configuration Editor appears.

2 Click the **Phoneticized Fields** tab.

The Phoneticized Field page appears.

- 3 In the Encoders section, click Add.
The Phonetic Encoder dialog box appears.
- 4 In the Encoder field, enter a descriptive name for the encoder.
- 5 In the Implementation Class field, enter the fully qualified Java path of the class to use for the encoder.

Note – For more information about the encoder class paths, see “[Master Index Encoder Elements and Types](#)” on page 92.

- 6 Click OK.
The phonetic encoder is added to the Encoders list.
- 7 On the Configuration Editor toolbar, click Save.

▼ **To Define a Phonetic Encoder (XML Editor)**

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click mefa.xml.
The file opens in the NetBeans XML editor.
- 2 Scroll to the PhoneticEncodersConfig section.
- 3 Create a new encoder element, and then define the elements described in “[Master Index Encoder Elements and Types](#)” on page 92.
- 4 Save and close the file.

Master Index Encoder Elements and Types

The following table lists and describes the elements that configure the phonetic encoders used by the master index application.

Element	Description
encoding-type	The name of the phonetic encoder, such as NYSIIS, Soundex, or Metaphone. See the following table for a list of default encoders for the Master Index Standardization Engine.

Element	Description
encoder-implementation-class	The fully qualified name of the Java class that determines the behavior of the phonetic encoder. See the following table for a complete list of default classes for the Master Index Standardization Engine.

The following table lists the phonetic encoders supported by the Master Index Standardization Engine along with the names of their default classes.

Encoding Type	class-name
NYSIIS	com.sun.mdm.index.phonetic.impl.Nysiis
Soundex	com.sun.mdm.index.phonetic.impl.Soundex
Metaphone	com.sun.mdm.index.phonetic.impl.Metaphone
Double Metaphone	com.sun.mdm.index.phonetic.impl.DoubleMetaphone
Refined Soundex	com.sun.mdm.index.phonetic.impl.RefinedSoundex
French Soundex	com.sun.mdm.index.phonetic.impl.SoundexFR

Modifying a Master Index Phonetic Encoder

Once you define a phonetic encoder, you can change the implementation class to use for the encoder. Use caution when modifying definitions once a system is in production. This can cause inconsistent match results.

▼ To Modify a Phonetic Encoder (Configuration Editor)

- 1 In the **Projects** window, right-click the **Configuration** node in the project you want to modify, and then click **Edit**.

The Configuration Editor appears.

- 2 Click the **Phoneticized Fields** tab.

The Phoneticized Field page appears.

- 3 In the **Encoders** section, select the encoder you want to modify and then click **Edit**.

The Phonetic Encoder dialog box appears.

- 4 Change the implementation class, and then click **OK**.

- 5 On the Configuration Editor toolbar, click **Save**.

▼ To Modify a Phonetic Encoder (XML Editor)

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `mefa.xml`.

The file opens in the NetBeans XML editor.

- 2 Scroll to the `PhoneticEncodersConfig` section.
- 3 Modify the value of any of the elements in the `encoder` element you want to modify (for more information, see [“Master Index Encoder Elements and Types” on page 92](#)).
- 4 Save and close the file.

Deleting a Master Index Phonetic Encoder

Once you define a phonetic encoder, you can delete it if needed. Use caution when deleting encoders once a system is in production. This can cause inconsistent match results. If you delete an encoder that is referenced by a phonetic encoding definition, make sure to modify that definition by referencing an existing encoder.

▼ To Delete a Phonetic Encoder (Configuration Editor)

- 1 In the Projects window, right-click the Configuration node in the project you want to modify, and then click **Edit**.

The Configuration Editor appears.

- 2 In the Configuration Editor toolbar, click the **Phoneticized Fields** tab.
The Phoneticized Field page appears.

- 3 In the Encoders section, select the encoder you want to delete.
- 4 Click **Remove**.
- 5 Click **Yes** on the dialog box that appears.
- 6 On the Configuration Editor toolbar, click **Save**.

▼ To Delete a Phonetic Encoder (XML Editor)

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `mefa.xml`.

The file opens in the NetBeans XML editor.

- 2 **Scroll to the `PhoneticEncodersConfig` section.**
- 3 **Delete the text between and including the `encoder` element the defines the encoder you want to remove.**
- 4 **Save and close the file.**

Defining the Master Index Match String

The match string defines the fields that are passed to the match engine for probabilistic weighting. By default, the fields defined for matching are the fields you specified for matching in the wizard or Configuration Editor. You can modify and delete fields in the match string if necessary. At least one field must be defined in the match string or no weights will be generated.

If you do modify the match string, you might need to make corresponding changes to the match engine configuration files as well. For more information about modifying these files, see [Master Index Match Engine Reference](#).

Perform either of the following tasks to configure the match string.

- “Creating the Master Index Match String” on page 95
- “Modifying the Master Index Match String” on page 97

You can further configure the match string by defining exclusion lists that filter out unwanted values from the match process. For more information, see “[Filtering Default Values From Master Index Processes](#)” on page 112.

Creating the Master Index Match String

A default match string is predefined based on the match type information you specified in the wizard. If no match types were defined using the wizard, the structure of the match string is still defined but with no fields. You can use normalized or phonetically encoded fields for the match string.

▼ To Create the Match String (Configuration Editor)

- 1 **In the Projects window, right-click the Configuration node in the project you want to modify, and then click Edit.**
The Configuration Editor appears.
- 2 **Expand the object structure so all fields are visible.**
- 3 **To add a field to the match string, click on the field name and then select a value for the Match Type field on the Properties page.**

Note – The match types you can use are listed in the first column of `matchConfigFile.cfg`. For more information about Master Index Match Engine match types, see [Master Index Match Engine Reference](#).

- 4 Perform the previous step for each field in the match string.
- 5 On the Configuration Editor toolbar, click Save.
- 6 To remove unwanted or invalid field values from the match process, see [“Filtering Default Values From Master Index Processes” on page 112](#).

▼ To Create the Match String (XML Editor)

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `mefa.xml`.
The file opens in the NetBeans XML editor.
- 2 In the `MatchingConfig` element, scroll to the `match-columns` element in the `match-system-object` element.
- 3 To add a field to the match string, do the following:
 - a. In the `match-columns` element, create a new `match-column` element.
 - b. In the new `match-column` element, create and define a `column-name` element.
Enter the fully qualified field name of the field on which to match (for example, `Enterprise.SystemSBR.Person.Address.City`).
 - c. Following the `column-name` element, create and define a `match-type` element.
Enter an ID that identifies the field to the match engine. For the Master Index Match Engine, this value must correspond to a defined match type.

For example:

```
<match-system-object>
  <object-name>Address</object-name>
  <match-columns>
    <match-column>
      <column-name>Enterprise.SystemSBR.Person.Address.StreetName
      </column-name>
      <match-type>StreetName</match-type>
    </match-column>
  </match-columns>
</match-system-object>
```


- 4 Repeat the previous step for each field to add to the match string.
- 5 Save and close the file.
- 6 To remove unwanted or invalid field values from the match process, see [“Filtering Default Values From Master Index Processes” on page 112](#).

Modifying the Master Index Match String

Once you define a match string, you can modify or delete information about the fields in the match string as necessary. This should only be done prior to moving to production. Otherwise, unexpected matching results might occur. For more information about Master Index Match Engine match types and field IDs, see [Master Index Match Engine Reference](#).

▼ To Modify the Match String (Configuration Editor)

- 1 In the Projects window, right-click the Configuration node in the project you want to modify, and then click Edit.
The Configuration Editor appears.
- 2 Expand the object structure so all fields are visible.
- 3 To add a field to the match string, click the field name and then select a value for the Match Type field on the Properties page.
The field is added to the match string.
- 4 To modify the match type specified for a field, click the name of the field defined for matching and then select a new value for the Match Type field on the Properties page.
- 5 To remove a field from the match string, click the name of the field defined for matching and then select None for the Match Type field on the Properties page.
- 6 On the Configuration Editor toolbar, click Save.
- 7 To define or modify exclusion lists of values to be removed from the match process, see [“Filtering Default Values From Master Index Processes” on page 112](#)

▼ To Modify the Match String (XML Editor)

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click mefa.xml.
The file opens in the NetBeans XML editor.

2 Scroll to the MatchingConfig element, and then scroll to the match-system-object element.

3 To add a field to the match string, do the following:

a. In the match-columns element, create a new match-column element.

b. In the new match-column element, create and define a column-name element.

Enter the fully qualified field name of the field on which to match (for example, Enterprise.SystemSBR.Person.Address.City).

c. Following the column-name element, create and define a match-type element.

Enter an ID that identifies the field to the match engine. For the Master Index Match Engine, this value must correspond to a defined match type.

For example:

```
<match-system-object>
  <object-name>Address</object-name>
  <match-columns>
    <match-column>
      <column-name>Enterprise.SystemSBR.Person.Address.StreetName
    </column-name>
    <match-type>StreetName</match-type>
  </match-column>
</match-columns>
</match-system-object>
```

4 To change a field used in the match string, change the value of the column-name element.

Enter the fully qualified field name of the new field (for example, Enterprise.SystemSBR.Person.FirstName).

5 To change the type of matching to perform for a field, change the value of the match-type element.

Enter an ID that identifies the field to the match engine. For the Master Index Match Engine, this value must correspond to a defined match type.

6 To delete a field from the match string, delete all text between and including the match-column element defining the field you want to delete.

Using the example below, to delete the HouseNo field from the match string, delete the boldface text.

```
<match-system-object>
  <object-name>Address</object-name>
  <match-columns>
    <match-column>
      <column-name>Enterprise.SystemSBR.Person.Address.StreetName
```

```

        </column-name>
        <match-type>StreetName</match-type>
    </match-column>
    <match-column>
        <column-name>Enterprise.SystemSBR.Person.Address.HouseNo
        </column-name>
        <match-type>HouseNumber</match-type>
    </match-column>

```

- 7 Save and close the file.
- 8 To define or modify exclusion lists of values to be removed from the match process, see [“Filtering Default Values From Master Index Processes” on page 112](#)

Defining how Master Index Query Blocks are Processed

The block picker and pass controller define how query blocks are processed for matching. Default components are defined by Sun Master Index, but you can create your own Java classes to define custom versions of these components.

The block picker determines the blocking strategy to use for each match pass. Blocking strategies define how the queries are created that check the database for a subset of the records to be used for matching. The default Block Picker has access to the match results from previous match passes, as well as lists of applicable blocking definitions that have been executed and of those that have not. The default Block Picker class is `com.sun.mdm.index.matching.impl.PickAllBlocksAtOnce`, which selects all blocks during the first pass.

The pass controller determines whether to continue processing the defined blocks. The matching process can be executed in multiple stages. Each query block in the blocking query is executed in a separate match pass. After a block is evaluated, the pass controller determines if the results found are sufficient or if the query should continue by performing another match pass. The default pass controller is `com.sun.mdm.index.matching.impl.PassAllBlocks`. This class instructs the match engine to continue calculating match weights until all applicable block definitions have been processed.

These components can only be configured by modifying the XML file directly.

▼ To Specify the Block Picker

- 1 In the **Projects** window, expand the **Configuration** node in the project you want to modify, and then double-click `mefa.xml`.

The file opens in the NetBeans XML editor.

- 2 **Scroll to the `block-picker` element in the `MatchingConfig` section.**
- 3 **In the `class-name` element, specify the Java class for the block picker you want to use, using the fully qualified class name.**

For example:

```
<block-picker>
  <class-name>com.sun.mdm.index.matching.impl.PickAllBlocksAtOnce
</class-name>
</block-picker>
```

- 4 **Save and close the file.**

▼ To Specify the Pass Controller Class

- 1 **In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `mefa.xml`.**

The file opens in the NetBeans XML editor.

- 2 **Scroll to the `pass-controller` element in the `MatchingConfig` section.**
- 3 **In the `class-name` element, specify the Java class for the Pass Controller you want to use, using the fully qualified class name.**

For example:

```
<pass-controller>
  <class-name>com.sun.mdm.index.matching.impl.PassAllBlocks
</class-name>
</pass-controller>
```

- 4 **Save and close the file.**

Defining the Master Index Survivor Calculator

The survivor calculator is configured in `update.xml` and defines how field values are populated into the single best record, along with the type of survivor strategy to use for each field. If no strategy is defined for a field, the default survivor strategy is used to populate that field in the SBR. Before you begin to define the survivor calculator, make sure you know which fields to include in the SBR and how those fields should be updated. Typically, all but phonetic and standardized fields are included here.

You can further configure the survivor calculator by defining exclusion lists to filter out unwanted values from the SBRs. For more information, see [“Filtering Default Values From Master Index Processes” on page 112](#).

The survivor calculator can only be configured by modifying the XML file directly. Perform the following tasks to configure the survivor calculator.

- [“Specifying the Master Index Survivor Helper” on page 101](#)
- [“Specifying a Master Index Default Survivor Strategy” on page 101](#)
- [“Defining the Master Index Single Best Record Structure” on page 104](#)
- [“Defining a Master Index Survivor Strategy for a Field or Object” on page 106](#)
- [“Defining Master Index Custom Weighted Strategies” on page 107](#)

Specifying the Master Index Survivor Helper

The survivor helper class determines how to retrieve values from system records and how to set them in the SBR. The default class is

`com.sun.mdm.index.survivor.impl.DefaultSurvivorHelper`, which uses the `ePath` method to retrieve and set the values. You can create a custom survivor helper class to support other methods for retrieving and setting values. If you implement a custom survivor helper class, it must extend `com.sun.mdm.index.survivor.AbstractSurvivorHelper`.

▼ To Specify the Survivor Helper

- 1 In the **Projects** window, expand the **Configuration** node in the project you want to modify, and then double-click **update.xml**.

The file opens in the NetBeans XML editor.

- 2 Scroll to the **helper-class** element in the **SurvivorHelperConfig** element.
- 3 Change the value of the **helper-class** element to the fully qualified name of new helper class.

For example:

```
<helper-class>com.sun.mdm.index.survivor.impl.MySurvivorHelper
</helper-class>
```

- 4 Save and close the file.

Specifying a Master Index Default Survivor Strategy

The default survivor strategy specifies the name of the Java class that defines the survivor calculation strategy to use for most of the fields in the SBR. By defining a default strategy, you do not need to define a strategy for every candidate field; you only need to define a strategy for fields that do not use the default strategy.

Note – If you create a customized class for the default survivor strategy, make sure the class implements `com.sun.mdm.index.survivor.SurvivorStrategyInterface` and is accessible by the EJB class loader.

▼ To Specify a Default Survivor Strategy

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `update.xml`.

The file opens in the NetBeans XML editor.

- 2 Scroll to the `default-survivor-strategy` element in the `SurvivorHelperConfig` element.

- 3 To change the name of the default class, modify the value of the `strategy-class` element to the fully qualified name of the new default strategy class.

For example:

```
<default-survivor-strategy>
  <strategy-class>com.sun.mdm.index.survivor.impl.MySurvivorStrategy
</strategy-class>
</default-survivor-strategy>
```

- 4 Configure the strategy parameters, as described in [“Configuring the Default Survivor Strategy” on page 102](#).
- 5 Save and close the file.

Configuring the Default Survivor Strategy

Once you define a default survivor strategy, you might need to specify certain parameters for the strategy. One parameter is required for the `WeightedSurvivorStrategy` and for the `DefaultSurvivorStrategy`. If you create a custom strategy, additional parameters can be used.

▼ To Configure the Default Survivor Strategy

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `update.xml`.

The file opens in the NetBeans XML editor.

- 2 Scroll to the `default-survivor-strategy` element, and then to the `strategy-class` element.

3 Do any of the following:

- To modify an existing parameter value, scroll to the parameter you want to modify, and then change the value of the `parameter-value` element.

For example:

```
<default-survivor-strategy>
  <strategy-class>com.sun.mdm.index.survivor.impl.MySurvivorStrategy
</strategy-class>
  <parameters>
    <parameter>
      <parameter-name>ConfigModuleName</parameter-name>
      <parameter-type>java.lang.String</parameter-type>
      <parameter-value>MySurvivorCalculator</parameter-value>
    </parameter>
  </parameters>
</default-survivor-strategy>
```

- To add a new parameter, create a new `parameter` element within the `parameters` element, and then define the parameter elements described in [“Master Index Default Survivor Strategy Parameter Elements” on page 103](#).
- To delete a parameter, scroll to the `parameters` element, and then delete all text between and including the `parameter` element that define the parameter.
- To delete all parameters, delete the all text between and including the `parameters` element.

4 Save and close the file.

Master Index Default Survivor Strategy Parameter Elements

The following table lists and describes the elements that configure the parameters for the default survivor strategy in `update.xml`.

Element	Value
description	This is an optional element that briefly describes the parameter. Note that there are no parameters to define for the <code>UnionSurvivorStrategy</code> .

Element	Value
parameter-name	<p>The name of the parameter.</p> <ul style="list-style-type: none"> ■ For the DefaultSurvivorStrategy, this value is “preferredSystem”. ■ For the WeightedSurvivorStrategy, this value is “ConfigurationModuleName”. ■ For the UnionSurvivorStrategy, this is not used.
parameter-type	The Java data type for the parameter value. For both the DefaultSurvivorStrategy and the WeightedSurvivorStrategy, this value is <code>java.lang.String</code> .
parameter-value	<p>The value of the named parameter.</p> <ul style="list-style-type: none"> ■ For the DefaultSurvivorStrategy, this is the processing code of the source system from which the SBR field value is retrieved. ■ For the WeightedSurvivorStrategy, this is the name of the <code>module-name</code> element that defines the weighted calculator to use as the default strategy (by default, <code>WeightedSurvivorCalculator</code>).

Defining the Master Index Single Best Record Structure

In order for a field to be populated in the SBR, that field must be defined in the candidate field list of the survivor helper. By default, all the fields that were specified in the wizard are also defined here. Any candidate fields defined for the SBR must also be defined in `object.xml`. If you add a field to the object definition, you should also add the field here.

The SBR can only be defined by modifying the XML file directly.

▼ To Specify a Candidate Field

- 1 In the **Projects** window, expand the **Configuration** node in the project you want to modify, and then double-click `update.xml`.

The file opens in the NetBeans XML editor.

- 2 Scroll to the **candidate-definitions** element in the **SurvivorHelperConfig** element.

- 3 Do any of the following:

- To add a new field, add a new **candidate-field** element within the **candidate-definitions** tags, and then name the new element using the **ePath** of the field.

For example:

```
<candidate-definitions>
  <candidate-field name="Person.LastName"/>
</candidate-definitions>
```



```
<candidate-field name="Person.DateOfBirth"/>
<candidate-definitions>
```

- To modify an existing field, scroll to the `candidate-field` element you want to modify, and then change the value of the attribute.
 - If any of the updated fields do not use the default strategy, define a strategy for those fields, as described in [“Defining a Master Index Survivor Strategy for a Field or Object” on page 106](#).
- 4 Save and close the file.
 - 5 To define or modify exclusion lists of values to be excluded from the SBR, see [“Filtering Default Values From Master Index Processes” on page 112](#)

Deleting Candidate Fields

Once a field is defined in the SBR candidate field list, you can delete the field if you do not want to include the field in the SBR. If you delete a field from the object definition, make sure to delete the field here as well.

▼ To Delete a Candidate Field

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `update.xml`.

The file opens in the NetBeans XML editor.

- 2 Scroll to the `candidate-definitions` element in the `SurvivorHelperConfig` element.
- 3 Delete all text between and including the appropriate `candidate-field` element.

Using the example below, to delete the Religion field, delete the boldface text; to delete the Alias object, delete the plain text.

```
<candidate-field name="Person.Religion"/>
<candidate-field name="Person.Alias[*].*"/>
  <system-fields>
    <field-name>LastModified</field-name>
  </system-fields>
</survivor-strategy>
  <strategy-class>com.sun.mdm.index.user.MyStrategy
  </strategy-class>
</survivor-strategy>
</candidate-field>
```

Note – Do not delete all candidate fields; at a minimum, the match fields must be defined.

- 4 **Save and close the file.**

Defining a Master Index Survivor Strategy for a Field or Object

To use a strategy for a specific field other than the strategy defined in the `default-survivor-strategy` element, you need to specify the new strategy for the appropriate `candidate-field` element. A `candidate-field` element can represent a field or child object. You do not need to specify a strategy for any fields that use the default survivor strategy.

▼ To Define a Survivor Strategy for a Field

- 1 **In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `update.xml`.**

The file opens in the NetBeans XML editor.

- 2 **Scroll to the `candidate-definitions` element in the `SurvivorHelperConfig` element.**
- 3 **In the `candidate-field` element for which you want to specify a new strategy, create a new `survivor-strategy` element.**

For example:

```
<candidate-field name="Person.Alias[*].*">
  <survivor-strategy>
  </survivor-strategy>
</candidate-field>
```

- 4 **In the new `survivor-strategy` element, create and name a new `strategy-class` element.**

Make sure to specify the fully qualified name of the Java class for the strategy. For example:

```
<candidate-field name="Person.Alias[*].*">
  <survivor-strategy>
    <strategy-class>
      com.sun.mdm.index.survivor.impl.UnionSurvivorStrategy
    </strategy-class>
  </survivor-strategy>
</candidate-field>
```

Note – To specify the default survivor strategy for a field, make sure the corresponding candidate-field element does not contain a survivor-strategy element. If you implement a custom strategy class, that class must be defined as a custom plug-in.

- 5 **Save and close the file.**
- 6 **To define or modify exclusion lists of values to be excluded from the SBR, see [“Filtering Default Values From Master Index Processes” on page 112](#)**

Defining Master Index Custom Weighted Strategies

The `WeightedCalculator` element defines the Java class used for weighted survivor calculations. If the weighted calculator is defined for the `default-survivor-strategy` element, then the strategies you define here are used for all fields for which no specific survivor strategy is defined. The weighted calculator defines a default strategy to use for most fields and specialized strategies to use for specific fields.

Configuring the weighted calculator involves the following tasks.

- [“Defining Custom Weighted Strategies” on page 107](#)
- [“Configuring Weighted Strategies” on page 108](#)
- [“Modifying Weighted Calculator Parameters” on page 109](#)
- [“Deleting Weighted Calculator Parameters” on page 110](#)

Defining Custom Weighted Strategies

The `WeightedCalculator` element defines both default and custom survivor strategies. You can override the default weighted calculator strategy for specific fields by defining custom strategies for those fields in the candidate-field elements of the `WeightedCalculator` element.

▼ To Define Custom Weighted Calculators

- 1 **In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `update.xml`.**

The file opens in the NetBeans XML editor.

- 2 **Scroll to the `WeightedCalculator` element.**

- 3 **Add and name a new candidate-field element in the `WeightedCalculator`.**

For example:

```
<WeightedCalculator module-name="WeightedSurvivorCalculator"
  parser-class=
```

```
"com.sun.mdm.index.configurator.impl.WeightedCalculatorConfig">
  <candidate-field name="Person.DOB">
    </candidate-field>
```

4 Create one or more parameter elements for the new candidate field.

```
<candidate-field name="Person.DOB">
  <parameter>
  </parameter>
  <parameter>
  </parameter>
</candidate-field>
```

5 For each new parameter element, define the elements listed in “[Master Index Weighted Calculator Parameter Elements](#)” on page 111.

```
<candidate-field name="Person.DOB">
  <parameter>
    <quality>SourceSystem</quality>
    <preference>CDI</preference>
    <utility>80.0</utility>
  </parameter>
  <parameter>
    <quality>MostRecentModified</quality>
    <utility>75.0</utility>
  </parameter>
</candidate-field>
```

6 Save and close the file.

Configuring Weighted Strategies

The wizard creates a default weighted strategy that defines a general weighting structure to be used by most fields. Unless custom weighted calculator strategies are defined for a field, the default strategies defined in the `default-parameters` element are used for each field using the weighted calculator.

▼ To Add Default Weighted Calculator Parameters

1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `update.xml`.

The file opens in the NetBeans XML editor.

2 Scroll to the `default-parameters` element in the `WeightedCalculator` element.

3 Create new a new parameter element within the `default-parameters` element, but outside any existing parameter elements.

- 4 In the new parameter element, define the elements listed in [“Master Index Weighted Calculator Parameter Elements” on page 111](#).

For example:

```
<default-parameters>
  <parameter>
    <quality>SourceSystem</quality>
    <preference>CDA</preference>
    <utility>80.0</utility>
  </parameter>
  <parameter>
    <quality>MostRecentModified</quality>
    <utility>75.0</utility>
  </parameter>
</default-parameters>
```

- 5 Save and close the file.

Modifying Weighted Calculator Parameters

Once a candidate field is specified and custom weighted calculators are defined for the field, you can modify the parameters. You can also modify any existing default weighted calculator parameters.

▼ To Modify Weighted Calculator Parameters

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `update.xml`.

The file opens in the NetBeans XML editor.

- 2 Scroll to the `WeightedCalculator` element.

- 3 Do either of the following:

- To modify a custom weighted calculator parameter, scroll to the candidate-field element naming the field to modify.
- To modify a default weighted calculator parameter, scroll to the `default-parameters` element.

- 4 Modify the value of any of the elements listed in [“Master Index Weighted Calculator Parameter Elements” on page 111](#).

For example:

```
<parameter>
  <quality>SourceSystem</quality>
```

```
<preference>DDI</preference>
<utility>60.0</utility>
</parameter>
```

5 Save and close the file.

Deleting Weighted Calculator Parameters

Once default and custom parameters are defined, they can be deleted if necessary. If a candidate field is defined for custom weighted calculations, you can specify that the field use the default weighted calculator instead by removing the entire field from the candidate-fields list.

▼ To Delete Weighted Calculator Parameters

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `update.xml`.

The file opens in the NetBeans XML editor.

- 2 Scroll to the `WeightedCalculator` element and then to the `candidate-field` element identifying the field you want to delete.
- 3 Do either of the following:
 - To delete a custom weighted calculator parameter, scroll to the `candidate-field` element naming the field to modify.
 - To delete a default weighted calculator parameter, scroll to the `default-parameters` element.
- 4 To delete an existing parameter, scroll to the `parameter` element you want to delete, and then remove all text between and including the `parameter` element.

For example, to delete the `SourceSystem` parameter below, delete the boldface text.

```
<parameter>
  <quality>SourceSystem</quality>
  <preference>CDI</preference>
  <utility>80.0</utility>
</parameter>
<parameter>
  <quality>MostRecentModified</quality>
  <utility>75.0</utility>
</parameter>
```

Note – At least one parameter must be defined for the default -parameter element; you cannot delete all parameters from this section. You cannot delete all parameters from a candidate field, but you can delete the entire candidate field (see below for more information).

5 To delete a field from the candidate field list, delete all text between and including the candidate-field tags for the field you want to delete.

Using the following example, to delete the Person.DOB candidate field from the custom calculator, delete all the text below.

```
<candidate-field name="Person.DOB">
  <parameter>
    <quality>SourceSystem</quality>
    <preference>CDI</preference>
    <utility>80.0</utility>
  </parameter>
  <parameter>
    <quality>MostRecentModified</quality>
    <utility>75.0</utility>
  </parameter>
</candidate-field>
```

6 Save and close the file.

Master Index Weighted Calculator Parameter Elements

The following table lists and describes the elements that configure the parameters for the weighted calculator in update.xml.

Element	Description
quality	The type of weighted calculation to perform, such as: <ul style="list-style-type: none"> ■ SourceSystem ■ SystemAgreement ■ MostRecentModified For more information about these qualities, see “Survivor Strategy Configuration” in Sun Master Index Configuration Reference .
preference	The preferred value for the specified quality. This element is only used for the SourceSystem quality and the preference must be a source system code.

Element	Description
utility	A value that indicates the reliability of the specified quality for determining the best field value for the SBR. You define the scale for the utility values.

Filtering Default Values From Master Index Processes

You might want to prevent certain default values from being used in the match process or from being populated into the single best record (SBR). For the blocking query, default values result in a large number of non-matching records being returned for a match query. For the match process, default values result in inaccurately high match weights. Finally, you do not want invalid values to appear in the SBR when it is possible to remove them.

The master index application provides a configuration file, `filter.xml`, in which you can define filtering rules. You can specify fields and values to filter directly in this file, and you can create exclusion lists in a flat file. Exclusion lists contain all the values to filter for a specific field.

▼ To Filter Default Values From the SBR, Blocking Query, or Match Process

- 1 To use flat files to define values to filter, create a flat file for each field to be filtered.
- 2 In this file, list each value to exclude for each filter definition you will create and separate each value by a delimiter.
- 3 In the Projects window, expand the master index application and then expand Filter.
- 4 Open `filter.xml`.
- 5 For each field to be filtered, define the elements and attributes described in [“Filter Definition Elements” on page 113](#).
- 6 Save and close the file.

Example 5 Filter Definitions

The `filter.xml` file provides a simple format for you to define filters for survivor calculation, blocking queries, and matching. The following sample defines a rule that filters out the listed values from the `FirstName` field in the SBR. It defines a second rule that filters out the values listed in `FirstNameFilters.txt` from the `SSN` field.


```
<exclusion-List module-name="ExclusionFilter"
parser-class="com.sun.mdm.index.configurator.impl.ExclusionFilterConfig">
  <field sbr="true" matching="false" blocking="false">
    <name>Person.FirstName</name>
    <value>
      <field-value>Baby</field-value>
      <field-value>Baby Boy</field-value>
      <field-value>Baby Girl</field-value>
    </value>
  </field>
  <field sbr="true" matching="true" blocking="true">
    <name>Person.SSN</name>
    <value>
      <file delimiter="|">
        <file-name>SSN.txt</file-name>
      </file>
    </value>
  </exclusion-List>
```

The filter values file for the SSN field in the above example would look similar to the following:

```
000000000|111111111|222222222|333333333|444444444|555555555|666666666|777777777|
888888888|999999999
```

Filter Definition Elements

The following table lists and describes the XML elements and attributes that define the filters to be used for the SBR, blocking query, or match process. You can either define the exclusion lists directly in `filter.xml` or in a flat file that is referenced from `filter.xml`.

Element	Attribute	Description
field		A filter definition for one field. The definition includes the following elements and attributes. You can define multiple filter definitions, and each can define filters for the SBR, blocking, matching, or any combination of the three.
	sbr	An indicator of whether to apply the filter to the SBR. Specify true to apply the filter to the SBR; otherwise specify false .
	matching	An indicator of whether to apply the filter to the blocking query. Specify true to apply the filter to the blocking query; otherwise specify false .

Element	Attribute	Description
	blocking	An indicator of whether to apply the filter to the matching process. Specify true to apply the filter to the matching process; otherwise specify false .
name		The qualified name for the field; for example, Person.SSN or Person.Address.PostalCode. For more information about qualified field names, see “Master Index Field Notations” in Sun Master Index Configuration Reference .
value		A list of field-value elements that specify the values to filter.
field-value		A value to filter from the SBR, blocking query, or matching process. You can define multiple field values. To use values listed in a flat file, define a file element instead of a field-value element.
file		A definition of the file that contains the list of values to filter.
	delimiter	The character that delimits the values listed in the exclusion list flat file.
file-name		The path and name of a file that contains the list of values to filter. Be sure the values in this file are delimited by the character specified above.

Configuring Master Index Update Policies

When update.xml is generated, no Java classes are defined for the update policies. You can create custom update policy classes and specify that the custom classes be used instead. Custom update policies must implement `com.sun.mdm.index.update.UpdatePolicy` and must be defined as custom classes in the Sun Master Index project to be recognized as an update policy. The names of the custom plug-ins you create are the values you enter for the update policies. You can also set the update policy flag to specify whether the policies are performed when no changes are made to an existing record.

Perform the following tasks to configure the update policies:

- [“Defining Master Index Update Policies” on page 115](#)
- [“Setting the Master Index Update Policy Flag” on page 116](#)

Defining Master Index Update Policies

You can define update policies for any of the seven update policy elements. You do not need to specify a policy for each element.

▼ To Define Update Policies

- 1 In the **Projects** window, expand the **Configuration** node in the project you want to modify, and then double-click **update.xml**.

The file opens in the NetBeans XML editor.

- 2 Scroll to the **UpdateManagerConfig** section of the file.

- 3 Do any of the following:

- To modify the merge policy for enterprise objects, change the value of the **EnterpriseMergePolicy** element to the fully qualified name of the new Java class.

For example:

```
<EnterpriseMergePolicy>com.sun.mdm.index.user.MyEntMergePolicy
</EnterpriseMergePolicy>
```

- To modify the unmerge policy for enterprise objects, change the value of the **EnterpriseUnmergePolicy** element to the fully qualified name of the new Java class.

For example:

```
<EnterpriseUnmergePolicy>com.sun.mdm.index.user.MyEntUnmergePolicy
</EnterpriseUnmergePolicy>
```

- To modify the update policy for enterprise objects, change the value of the **EnterpriseUpdatePolicy** element to the fully qualified name of the new Java class.

For example:

```
<EnterpriseUpdatePolicy>com.sun.mdm.index.user.MyEntUpdatePolicy
</EnterpriseUpdatePolicy>
```

- To modify the create policy for enterprise objects, change the value of the **EnterpriseCreatePolicy** element to the fully qualified name of the new Java class.

For example:

```
<EnterpriseCreatePolicy>com.sun.mdm.index.user.MyCreatePolicy
</EnterpriseCreatePolicy>
```

- **To modify the merge policy for system objects, change the value of the `SystemMergePolicy` element to the fully qualified name of the new merge policy Java class.**

For example:

```
<SystemMergePolicy>com.sun.mdm.index.user.MySysMergePolicy
</SystemMergePolicy>
```

- **To modify the unmerge policy for system objects, change the value of the `SystemUnmergePolicy` element to the fully qualified name of the new Java class.**

For example:

```
<SystemUnmergePolicy>com.sun.mdm.index.user.MySysUnmergePolicy
</SystemUnmergePolicy>
```

- **To modify the assumed match policy, change the value of the `UndoAssumeMatchPolicy` element to the fully qualified name of the new Java class.**

For example:

```
<UndoAssumeMatchPolicy>com.sun.mdm.index.user.MyUndoAsmMatchPolicy
</UndoAssumeMatchPolicy>
```

4 Save and close the file.

Setting the Master Index Update Policy Flag

The update flag determines whether update policies are performed against a record when a transaction does not cause any changes to the record's data.

▼ To Set the Update Policy Flag

- 1 **In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `update.xml`.**

The file opens in the NetBeans XML editor.

- 2 **Scroll to the `UpdateManagerConfig` section of the file.**
- 3 **To specify that update policies are not performed when no updates are made, set the `SkipUpdateIfNoChange` element to `true`.**

For example:

```
<SkipUpdateIfNoChange>true</SkipUpdateIfNoChange>
```

- 4 To specify that update policies are performed even though no updates are made, set the `SkipUpdateIfNoChange` element to `false`.

For example:

```
<SkipUpdateIfNoChange>false</SkipUpdateIfNoChange>
```

- 5 Save and close the file.

Defining Custom Field Validations for the Master Index

By default, `validation.xml` defines one validation rule named “`validate-local-id`”. This rule defines certain validations to perform against local ID and system fields before they are entered into the database. The local ID validator verifies that the system code is valid, the local ID format is correct, the local ID is the correct length, and that neither field is null.

You can define additional validations for your data by creating the Java class and appropriate methods. Create the custom class in the Source Package folder of the master index EJB project so you can include the custom validation rule in the master index application code package. The custom validation classes must implement

`com.sun.mdm.index.objects.validation.ObjectValidator`. The exception thrown is `com.sun.mdm.index.objects.validation.exception.ValidationException`.

▼ To Implement a Validation Rule

- 1 Create the custom validation rules in the Source Package folder of the EJB project.
- 2 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `validation.xml`.
The file opens in the NetBeans XML editor.
- 3 Create a new rule element in the rules element.
- 4 In the new rule element, create the following attributes:
 - `name` – A unique name for the validation rule.
 - `object-name` – The name of the master index Java class that defines the object to which the validation rule is applied, such as `SystemObject` or `Parent_NameObject` (where *Parent_Name* is the name of the parent object in the object definition)

- **class** – The complete path of the Java class to call for the validation rule.

For example:

```
<ValidationConfig module-name="Validation" parser-class=
  "com.sun.mdm.index.configurator.impl.validation.ValidationConfiguration"
  <rules>
    <rule name="validate-auxiliary-id" object-name="PersonObject"
      class="com.sun.mdm.index.user.AuxiliaryId"/>
    <rule name="validate-birth-date" object-name="PersonObject"
      class="com.sun.mdm.index.user.BirthDate"/>
  </rules>
</ValidationConfig>
```

- 5 Save and close the file.

Configuring the Match Engine

You can configure the match engine by specifying the match engine to use and configuring the predefined comparison functions. You can also plug in custom standardization and matching rules. You only need to specify the match engine to use if you are using an engine other than the Master Index Match Engine.

Perform any of these steps to configure the match engine:

- [“Specifying a Match Engine for the Master Index” on page 118](#)
- [“Configuring the Comparison Functions for a Master Index Application” on page 119](#)
- [“Importing Custom Comparison Functions” on page 123](#)
- [“Deleting a Custom Comparison Function” on page 124](#)

Specifying a Match Engine for the Master Index

Sun Master Index can support different match engines depending on the adapter configured to communicate with the engine. Default classes are provided for using the Master Index Match Engine. You can implement a custom match engine along with custom adapters. The match engine configuration is defined by the `matcher-api` and `matcher-config` elements.

Note – The default adapters for the Master Index Match Engine are `com.sun.mdm.index.matching.adapter.SbmeMatcherAdapter` and `com.sun.mdm.index.matching.adapter.SbmeMatcherAdapterConfig`.

▼ To Configure the Match Engine

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `mefa.xml`.

The file opens in the NetBeans XML editor.

- 2 Scroll to the `matcher-api` element in the `MatchingConfig` section.

- 3 Specify the Java class for the matching adapter to use, using the fully qualified class name as shown below.

```
<matcher-api>
  <class-name>com.sun.mdm.index.matching.adapter.SbmeMatcherAdapter
</class-name>
</matcher-api>
```

- 4 In the `matcher-config` element, specify the Java class for the configuration of the matching adapter, using the fully qualified class name as shown below.

```
<matcher-config>
  <class-name>
    com.sun.mdm.index.matching.adapter.SbmeMatcherAdapterConfig
  </class-name>
</matcher-config>
```

- 5 Save and close the file.

Configuring the Comparison Functions for a Master Index Application

The match configuration file in the Match Engine node of the master index project lists and defines the configuration for each match type based on the predefined comparison function for the Master Index Match Engine. These match types can be applied to each field in the match string. You can modify the configuration of the existing matches types, add new match types, and specify whether the match engine should use agreement and disagreement weights or m-probabilities and u-probabilities.

For more information about the structure of the match configuration file and the comparison functions you can use, see [Master Index Match Engine Reference](#).

▼ To Configure the Comparison Functions (Configuration Editor)

- 1 In the Projects window, right-click the Configuration node in the project you want to modify, and then click **Edit**.

The Configuration Editor appears.

2 Click the Matching tab.

The Matching page appears with a list of fields defined for matching and a list of comparators that you can modify.

3 In the Probability Type field, select one of the following:

- **Use Agree/Disagreement Weight Ranges** – Uses agreement and disagreement weights for matching. If agreement and disagreement weights are used, the m-probability and u-probability fields are ignored and do not appear on the Matching page.
- **Use M-Probabilities/U-Probabilities** – Uses m-probabilities and u-probabilities for matching. If m-probabilities and u-probabilities are used, the agreement and disagreement weight fields are ignored and do not appear on the page.

4 To add a new matching rule:

- a. **Click Add in the lower right portion of the window.**

The Edit Matching Rules dialog box appears.

- b. **Fill in the fields described in [“Match Comparator Configuration Properties for Sun Master Index” on page 121](#).**

- c. **Click OK.**

5 To edit an existing matching rule:

- a. **Click Edit in the lower right portion of the window.**

The Edit Matching Rules dialog box appears.

- b. **Change the value of any of the fields described in [“Match Comparator Configuration Properties for Sun Master Index” on page 121](#).**

- c. **Click OK.**

6 To remove an existing matching rule:

- a. **In the matching rule table, select the rule you want to delete.**

- b. **Click Remove.**

7 On the Configuration Editor toolbar, click Save.

▼ To Configure the Comparison Functions (Text Editor)

- 1 In the project window, expand the master index project, and then expand the master index application.
- 2 In the Match Engine folder, double-click `matchConfigFile.cfg`.
- 3 For the Probability Type, enter one of the following values:
 - **0** – Uses m-probabilities and u-probabilities for matching. If m-probabilities and u-probabilities are used, the agreement and disagreement weight fields are ignored.
 - **1** – Uses agreement and disagreement weights for matching. If agreement and disagreement weights are used, the m-probability and u-probability fields are ignored.
- 4 For each comparison function you want to configure, modify the value of any of the columns described in [“Match Comparator Configuration Properties for Sun Master Index” on page 121](#).
- 5 Save and close the file.

Match Comparator Configuration Properties for Sun Master Index

The following table lists and describes the Configuration Editor fields used to define the comparison functions. It also lists the corresponding column in the match configuration file if you want to modify the file directly.

Configuration Editor Field	Match Configuration File Element and Column Number	Description
Match Type	match-type (column 1)	A value that indicates to the Master Index Match Engine how each field should be weighted. Each field included in the match string (the <code>MatchingConfig</code> section of <code>mefa.xml</code>) must have a match type corresponding to a match type defined in this file.
Match Size	size (column 2)	The number of characters on which matching is performed, beginning with the first character. For example, to match on only the first four characters in a 10-digit field, the value of this column should be “4”.

Configuration Editor Field	Match Configuration File Element and Column Number	Description
Null Field	null-field (column 3)	<p>An index that specifies how to calculate the total weight for null fields or fields that only contain spaces. You can specify any of the following values. The Configuration Editor value is given first, followed by the match configuration file value in parenthesis.</p> <ul style="list-style-type: none"> ■ Zero weight (0) - If one or both fields are empty, the weight used for the field is 0 (zero). ■ Full Combination weight (1) - If both fields are empty, the agreement weight is used; if only one field is empty, the disagreement weight is used. ■ Full Agreement weight (a1) - Specifies to use the full agreement weight if both fields are null. ■ 1/x of the Agreement weight (ax) - Specifies to use the a fraction of the agreement weight if both fields are empty. The agreement weight is multiplied by the fraction 1/x to obtain the match weight for that field. When modifying the match configuration file directly, the default is “2” if no number is specified. You can specify any number from 1 through 10. ■ Full disagreement weight (d1) - Specifies to use the full disagreement weight if both fields are null. ■ 1/x of the disagreement weight (dx) - Specifies to use the disagreement weight if only one field is empty. The disagreement weight is multiplied by the fraction 1/x to obtain the match weight for the field. When modifying the match configuration file directly, the default is “2” if no number is specified. You can specify any number from 1 through 10. <p>In the above descriptions, the agreement and disagreement weights are either specified in this file or calculated using a logarithmic formula based on the m and u-probabilities (depending on the probability type).</p>

Configuration Editor Field	Match Configuration File Element and Column Number	Description
Function	function (column 4)	The type of comparison to perform when weighting the field. For information about the available comparison functions, see “Master Index Match Engine Comparison Functions,” in <i>Understanding the Master Index Match Engine</i> .
Agreement Weight	agreement-weight (column 7)	The matching weight to be assigned to a field given that the fields match between two records; that is, the maximum match weight for a field. This number can be between 0 and 100 and can have up to 16 decimal points. Only set this value if the Probability Type is set to use agreement and disagreement weights.
Disagreement Weight	disagreement-weight (column 8)	The matching weight to be assigned to a field given that the fields do not match between two records; that is, the minimum match weight for a field. This number can be between 0 and -100 and can have up to 16 decimal points. Only set this value if the Probability Type is set to use agreement and disagreement weights.
M-Probability	m-prob (column 5)	The initial probability that the specified field in two records will match if the records match. The probability is a double value between 0 and 1, and can have up to 16 decimal points. Only set this value if the Probability Type is set to use probabilities.
U-Probability	u-prob (column 6)	The initial probability that the specified field in two records will match if the records do not match. The probability is a double value between 0 and 1, and can have up to 16 decimal points. Only set this value if the Probability Type is set to use probabilities.
Extra Parameters	parameters (column 9)	Parameters correspond to the comparison function specified in the Function field or column. Some comparison functions do not take any parameters and some take multiple parameters. For information about which functions take parameters and the parameters they take, see “Master Index Match Engine Comparison Functions,” in <i>Understanding the Master Index Match Engine</i> .

Importing Custom Comparison Functions

The Master Index Match Engine is based on a very flexible framework that allows you to define new algorithms in the form of comparison functions that compare field values between two

records. You need to import the comparison function into NetBeans to make it available to all master index applications or only the current application.

This section only describes importing custom comparison functions after they have been created. For information about creating a custom comparison function, see “[Creating Custom Comparators for the Master Index Match Engine](#),” in *Understanding the Master Index Match Engine*

▼ To Import a Comparison Function

- 1 In the Projects window, expand the main master index project.
- 2 Right-click Match Engine, and select Import Comparator Plug-in.
- 3 In the dialog box that appears, navigate to the location of the plug-in ZIP file.
- 4 Select the file containing the plug-in, and then click Open.
- 5 Do one of the following:
 - To import the plug-in and make it available to all future master index application, click Yes.
 - To import the plug-in and make it only available to the current master index application, click No.

The contents of the ZIP file are imported into the Match Engine node and the new comparators are added to the list of comparator definitions in `comparatorsList.xml`.

- 6 In the Match Engine node, navigate to the `/lib` folder that was added and verify that all of the required files are there.
- 7 Open `comparatorsList.xml` and verify the new comparator definitions are included.

Deleting a Custom Comparison Function

If you add a custom comparison function to a master index application in error, you can remove it from the Match Engine node. Optionally, you can simply make the comparison function unavailable by removing it from the comparators list in `comparatorsList.xml`.

▼ To Delete a Custom Comparison Function

- 1 Back up the source files for the function in case you need them at a later time.

- 2 In the Project window, navigate to the Match Engine node in the master index project and then to the `/lib` folder.
- 3 Right-click the folder containing the files to remove, and then select Delete.
A confirmation dialog appears.
- 4 Click Yes.
The source files are removed from the project.
- 5 Open `comparatorsList.xml` and remove the comparator definitions from the list.
- 6 Save and close the file.

Configuring the Standardization Engine

You can configure the standardization engine by specifying the standardization engine to use, configuring the files that define data standardization, and plugging in custom standardization and matching rules. You only need to specify the standardization engine to use if you are using an engine other than the Master Index Standardization Engine.

Perform any of these steps to configure the standardization engine:

- [“Specifying a Standardization Engine for the Master Index” on page 125](#)
- [“Modifying Master Index Standardization Files” on page 126](#)
- [“Importing Standardization Data Types and Variants” on page 127](#)
- [“Deleting a Standardization Variant or Data Type” on page 128](#)

Specifying a Standardization Engine for the Master Index

Sun Master Index can support standardization engines from different vendors depending on the adapter configured to communicate with the engine. Default classes are provided for using the Master Index Standardization Engine. You can implement a custom standardization engine along with customized adapters. The standardization engine configuration is defined by `standardizer-api` and `standardizer-config` elements.

Note – The default adapters for the Master Index Standardization Engine are `com.sun.mdm.index.matching.adapter.SbmeStandardizerAdapter` and `com.sun.mdm.index.matching.adapter.SbmeStandardizerAdapterConfig`.

▼ To Specify the Standardization Engine

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `mefa.xml`.

The file opens in the NetBeans XML editor.

- 2 Scroll to the `standardizer-api` element in the `MatchingConfig` section.
- 3 Specify the Java class for the standardization adapter to use, using the fully qualified class name as shown below.

```
<standardizer-api>
  <class-name>
    com.sun.mdm.index.matching.adapter.MyStandardizerAdapter
  </class-name>
</standardizer-api>
```

- 4 In the `standardizer-config` element, specify the Java class for the configuration of the standardization adapter, using the fully qualified class name as shown below.

```
<standardizer-config>
  <class-name>
    com.sun.mdm.index.matching.adapter.SbmeStandardizerAdapterConfig
  </class-name>
</standardizer-config>
```

- 5 Save and close the file.

Modifying Master Index Standardization Files

You can fine-tune the standardization process by modifying the standardization files. For example, you can insert additional names or terms into the normalization or lexicon files, such as `givenNames.txt` and `givenNameNormalizatin.txt`. Depending on your data requirements, you might need to modify additional standardization files. Some of the patterns files (most notably the address patterns files) are very complex and should only be modified by personnel who thoroughly understand the defined patterns and tokens. If you modify standardization files, make sure you modify them for each variant specified in `mefa.xml`.

You can modify the data configuration files (lexicon and normalization files), and you can also modify the process configuration files that define the data types, variants, and how data is standardized. The process files are more complex, and should only be modified by one who is familiar with standardization concepts and with the Master Index Standardization Engine. Instructions for modifying these files are not included here. For information about these files, see [Master Index Standardization Engine Reference](#).

▼ To Modify Standardization Data Configuration Files

- 1 In the Projects window, expand the master index project to configure and then expand Standardization Engine.
- 2 Expand instance, expand the variant to modify, and then expand resources.
- 3 Open the file you want to modify in the NetBeans text editor.
- 4 Modify the file in accordance with the information presented for each data type in [Master Index Standardization Engine Reference](#).
- 5 Save and close the file.

Importing Standardization Data Types and Variants

The Master Index Standardization Engine is based on a very flexible framework that allows you to define new data types and variants so you can standardize any type of data in a custom manner. You can create new data types and variants based on the finite state machine and new variants for the existing rules-based data types. You need to import the data type or variant package into NetBeans to make it available to all master index applications or only the current one.

This section only describes importing custom data types and variants after they have been created. For information about creating a custom data type or variant, see [Master Index Standardization Engine Reference](#)

▼ To Import a Data Type or Variant

- 1 In the Projects window, expand the main master index project.
- 2 Right-click Standardization Engine, and select Import Standardization Plug-in.
- 3 In the dialog box that appears, navigate to the location of the plug-in package.
- 4 Select the file containing the plug-in, and then click Open.
- 5 Do one of the following:
 - To import the plug-in and make it available to all future master index application, click Yes.
 - To import the plug-in and make it only available to the current master index application, click No.

The data type or variant is imported into the Standardization Engine node. Data types add folders just beneath the Standardization Engine node; variants add folders under the appropriate data type (as specified in the variant package).

- 6 **In the Standardization Engine node, navigate to the new data type or variant you added and verify that all of the required files are there.**

Deleting a Standardization Variant or Data Type

If you add a data type or variant to a master index application in error, you can remove it from the Standardization Engine node. You can also delete any of the existing data types or variants if they are not in use. Use caution when removing variants or data types; this action cannot be undone.

▼ To Delete a Variant or Data Type

- 1 **Back up the source files for the data type or variant in case you need them at a later time.**

Note – The default data types and variants are stored in *NetBeansHome/soa2/modules/ext/mdm/standardizer/deployment*.

- 2 **In the Project window, navigate to the Standardization Engine node in the master index project and then to the data type or variant you want to remove.**
- 3 **Right-click the folder containing the files to remove, and then select Delete.**
A confirmation dialog appears.
- 4 **Click Yes.**
The data type or variant is removed from the project.

Configuring the Master Index MIDM Appearance

You can modify the configuration of the fields and objects to specify how they appear on the MIDM pages by modifying *midm.xml*. You can perform any of the following actions to customize the general appearance of the MIDM. Though some appearance options can be configured using the Configuration Editor, it is best to modify the XML file directly.

Perform any of the following tasks to configure the appearance of the MIDM.

- [“Adding Objects to the MIDM” on page 129](#)
- [“Modifying MIDM Objects” on page 130](#)

- “Deleting Objects From the MIDM” on page 130
- “Adding Fields to the MIDM” on page 132
- “MIDM Field Configuration Elements” on page 132
- “Removing Fields From the MIDM” on page 134
- “Modifying MIDM Field Display Options” on page 135
- “Specifying a Drop-Down List for an MIDM Field” on page 136
- “Specifying an MIDM Field’s Length and Format” on page 136
- “Modifying an MIDM Field’s Data Type” on page 137
- “Defining Key Fields for an Object” on page 138
- “Masking Field Values on the MIDM” on page 139
- “Defining MIDM Object Relationships” on page 140
- “Defining MIDM Local ID Labels” on page 140

Adding Objects to the MIDM

You can define additional objects for the MIDM as long as those objects are defined in `object.xml`. Each object can only contain the fields that are also defined for that object in `object.xml`. If you add objects to the object structure using the Configuration Editor, the new objects are automatically added to the `midm.xml` and you do not need to perform these steps.

▼ To Add an Object to the MIDM

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `midm.xml`.

The file opens in the NetBeans XML editor.

- 2 In the nodes list of the file, create a new node element.
- 3 In the new node element, create and define the following elements.

- `name` – The name of the object.
- `display-order` – The order in which the child object types are displayed on the MIDM pages.

For example:

```
<node>
  <name>Phone</name>
  <display-order>3</display-order>
</node>
```

Note – You might need to renumber any existing objects to keep the numbering sequential.

- 4 Define fields for the new object, as described in [“Adding Fields to the MIDM” on page 132](#).

- 5 **Define the relationship of the object, as described in “[Defining MIDM Object Relationships](#)” on [page 140](#).**
- 6 **Save and close the file.**

Modifying MIDM Objects

Once an object is defined in `midm.xml`, you can modify the name or display order. Only modify the name of an object if you modify the corresponding object name in `object.xml` and the remaining configuration files. Do not change the parent object name. If you modify an object in the object definition on the Configuration Editor, the `midm.xml` is automatically updated as well.

▼ To Modify an MIDM Object

- 1 **In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `midm.xml`.**

The file opens in the NetBeans XML editor.

- 2 **To modify the object name, change the value of the `name` element to the new name for the object.**

Note – If you change an object name, modify the name in the relationships section as well.

- 3 **To modify the order in which the object appears on the MIDM, change the value of the `display-order` element.**
- 4 **If necessary, renumber the order of other child objects so they are sequential.**
- 5 **Save and close the file.**

Deleting Objects From the MIDM

Once an object is defined in `midm.xml`, you can remove the object. If the object remains defined in `object.xml`, then the object is still a part of the enterprise record, but does not appear on the MIDM. Before removing an object from the `midm.xml`, make sure none of its fields are required in order to create a new record. If you delete an object using the Configuration Editor, the object is automatically deleted from `midm.xml`.

▼ To Delete an Object

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `midm.xml`.

The file opens in the NetBeans XML editor.

- 2 Scroll to the node element naming the object to delete.

- 3 Delete all text between and including the node element for that object.

Using the sample below, to delete the Phone object, delete all the text in the sample.

```
<node>
  <name>Phone</name>
  <display-order>3</display-order>
  <field>
    <name>PhoneType</name>
    <display-name>Phone Type</display-name>
    <display-order>1</display-order>
    <max-length>8</max-length>
    <gui-type>MenuList</gui-type>
    <value-list>PHONTYPE</value-list>
    <value-type>string</value-type>
    <key-type>true</key-type>
  </field>
  <field>
    <name>Phone</name>
    <display-name>PhoneNumber</display-name>
    <display-order>2</display-order>
    <max-length>20</max-length>
    <gui-type>TextBox</gui-type>
    <value-type>string</value-type>
    <input-mask>(DDD)DDD-DDDD</input-mask>
    <value-mask>xDDDxDDDxDDDD</value-mask>
  </field>
</node>
```

- 4 If necessary, renumber the order of the remaining objects so they are sequential.
- 5 Remove the object from the relationship definition, as described in [“Defining Relationships Between Master Index Objects” on page 26](#).
- 6 Save and close the file.

Adding Fields to the MIDM

You can define new fields for an object in `midm.xml`, but the field must correspond with a field defined for that object in `object.xml`. Only the fields defined in `midm.xml` appear on the MIDM windows. If you add a field to the object structure using the Configuration Editor, it is automatically added to `midm.xml`.

▼ To Define New Fields

- 1 In the **Projects** window, expand the **Configuration** node in the project you want to modify, and then double-click `midm.xml`.
The file opens in the NetBeans XML editor.
- 2 Scroll to the **node** element that defines the object to which you want to add a field.
- 3 In the **node** element, create a new element named `field`.
- 4 Define and configure the elements listed in [“MIDM Field Configuration Elements” on page 132](#) for the new `field-field_name` element.

For example:

```
<field
  <name>LastName</name>
  <display-name>LastName</display-name>
  <display-order>2</display-order>
  <max-length>40</max-length>
  <gui-type>TextBox</gui-type>
  <value-type>string</value-type>
  <is-sensitive>false</is-sensitive>
  <key-type>false</key-type>
</field>
```

- 5 If necessary, renumber any existing fields to keep the numbering sequential.
- 6 Save and close the file.

MIDM Field Configuration Elements

The following table lists and describes the XML elements that define the fields that appear on the Master Index Data Manager.

Element	Description
name	The name of the field as it appears in the object definition.
display-name	The name of the field as it will appear on the MIDM.
display-order	The order in which the field appears in the object on the MIDM. For example, specify 1 to indicate this is the first field on the MIDM pages, 2 to indicate it is the second field, and so on. The display order goes from left to right,
max-length	The maximum number of characters displayed on the MIDM for the field.
gui-type	An indicator of the type of display for the field. Specify TextBox for a standard data entry field; MenuList for a field that must be populated by selecting from a drop-down list; or TextArea for a long field that requires a scrollbar, such as a comments field.
value-type	<p>The Sun Master Index data type for the data populated in the field. Enter one of the following values:</p> <ul style="list-style-type: none"> ■ string - Field contains a string of characters. ■ date - Field contains a date value. ■ float - Field contains a floating point integer. ■ int - Field contains an integer. ■ char - Field contains a single character. ■ boolean - Field contains either “true” or “false”.
input-mask	<p>A mask used by the MIDM to add punctuation to a field. You can add an input mask to display telephone numbers as “(123)456-7890” even though no punctuation is entered by the user.</p> <p>To define an input mask, type a character type for each character in the field, and place any necessary punctuation between the character types. For example, the input mask for the above telephone format is “(DDD)DDD-DDDD”. The following character types are allowed:</p> <ul style="list-style-type: none"> ■ D - indicates a numeric character. ■ L - indicates an alphabetic character. ■ A - indicates an alphanumeric character. <p>Note – If the length of the input mask is greater than the value specified for the max - length element, update the value of the max - length element to match.</p>

Element	Description
value-mask	<p>A mask used by the master index application to strip any extra characters that were added by the input mask. This mask ensures that data is stored in the database in the correct format. This mask must be the same length as the input mask.</p> <p>To specify a value mask, type the same value as is entered for the input mask, but type an “x” in place of each punctuation mark. For example, if an SSN field has an input mask of DDD-DD-DDDD, you need to specify a value mask of DDDxDDxDDDD to strip the dashes before storing the SSN. A value mask is not required for date fields.</p>
value-list	The name of the menu list used to populate the drop-down list for the field. This is required if the <code>gui - type</code> specified for the field is <code>MenuList</code> , and it must match a code of an element in the <code>sbyn_common_header</code> database table.
is-sensitive	<p>An indicator of whether the value of the field is hidden on the MIDM for records with a VIP status of “VIP”. Only users with the required security permissions can view the hidden information. Specify true to hide the field value; specify false (or remove the <code>is-sensitive</code> element) to display the field value.</p> <p>Note – This element is only used if the <code>object-sensitive-plug-in-class</code> in the <code>impl-details</code> section is populated.</p>
key-type	An indicator of whether the field (or a combination of key fields) must be unique in an enterprise record. Unique key fields identify unique child objects in an enterprise object. For example, if the object structure contains a child object for addresses and each record can have only one of each type of address (for example, one home address and one work address), then the address type field would be a key field. Specify true to indicate the field is a key field; specify false if it is not.

Removing Fields From the MIDM

If a field is defined for an object in `midm.xml`, that field appears on the MIDM windows. If there are any fields defined in the object structure that you do not want to display on the MIDM, you can remove the field definition from `midm.xml`. If you remove a field from the object structure using the Configuration Editor, it is automatically removed from `midm.xml`.

Note – If you remove a unique key type field, you must write a custom plug-in that will automatically populate a value into the field in order to meet unique key type field constraints.

▼ To Remove a Field From the MIDM

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `midm.xml`.

The file opens in the NetBeans XML editor.

- 2 Scroll to the `field` element that defines the field you want to remove.
- 3 Delete the field elements that define the field you want to remove.
- 4 If necessary, renumber the remaining fields, as described in [“Modifying MIDM Field Display Options” on page 135](#).
- 5 Save and close the file.

Modifying MIDM Field Display Options

Once a field is defined for an object in `midm.xml`, you can change the name that appears on the MIDM for that field, the location of the field, and the type for the field (such as text box, menu list, and so on).

▼ To Modify a Field’s Display Options

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `midm.xml`.

The file opens in the NetBeans XML editor.

- 2 Scroll to the `node` element that defines the object that contains the field you want to modify.
- 3 Scroll to the `field` element you want to modify, .
- 4 To modify the field label, change the value of the `display-name` element.

For example:

```
<display-name>Last Name</display-name>
```

- 5 To modify the location of the field on the MIDM, change the value of the `display-order` element.

For example:

```
<display-order>1</display-order>
```

Note – If you change the order of one field, you must change the order of at least one other field to maintain sequential numbering. For example, if you change a field’s location from “2” to “1”, you must then change the location of the field originally specified for location 1.

- 6 To modify the type of field to display, change the value of the `gui-type` element.

For example:

```
<gui-type>TextBox</gui-type>
```

Note – You can enter TextBox (for a standard field), MenuList (for a field whose value must be selected from a drop-down list), or TextArea (for a long field that requires a scrollbar).

- 7 **Save and close the file.**

Specifying a Drop-Down List for an MIDM Field

Once a field is defined for an object in `midm.xml`, you can specify or change the name of the drop-down list for the field. If you modify the Code Module for the field in the Configuration Editor, the drop-down list is automatically updated in `midm.xml`.

▼ To Specify a Drop-Down List

- 1 **In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `midm.xml`.**

The file opens in the NetBeans XML editor.

- 2 **Scroll to the `node` element that defines the object containing the field you want to modify.**
- 3 **Scroll to the `field` element you want to modify.**
- 4 **Enter the name of the drop-down list in the `value-list` element.**

If the element does not exist for the field, create a new `value-list` element. For example:

```
<value-list>STATE</value-list>
```

Note – The value of the `gui-type` element for the field must be “MenuList” if you specify a drop-down list. The `value-list` element must match a code column value in the `sbyn_common_header` database table unless the drop-down list is populated by information in the `sbyn_user_code` table (as they might be for auxiliary IDs). In this case, the `value-list` element must match a `code_list` column value in `sbyn_user_code`.

- 5 **Save and close the file.**

Specifying an MIDM Field's Length and Format

Once a field is defined for an object in `midm.xml`, you can change the number of characters that can be entered for the field in the MIDM. You can also specify whether to automatically enter punctuation into a field on the MIDM, but remove the punctuation in the database. If you modify the field's length and format in the object structure using the Configuration Editor, `midm.xml` is automatically updated as well.

Note – Field length here is constrained by the length of the database column containing the field and the length defined in object.xml. This applies to the max-length element and the input and value masks.

▼ To Modify a Field's Length and Format

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click midm.xml.

The file opens in the NetBeans XML editor.

- 2 Scroll to the node element that defines the object containing the field you want to modify.

- 3 Scroll to the field element you want to modify.

- 4 To modify the length of a field, change the value of the max-length element.

For example:

```
<max-length>100</max-length>
```

- 5 To modify the format of the field, change the value of the input-mask and value-mask elements.

If these element do not exist for the field, create new input-mask and value-mask elements. For example:

```
<input-mask>(DDD)DDD-DDDD</input-mask>
```

```
<value-mask>xDDDxDDDxDDDD</value-mask>
```

Note – If an input mask is defined, in most cases a value mask must also be defined. If the input mask exceeds the length specified by the max-length element, update the max-length element to match. For information about input and value masks, see [“MIDM Field Configuration Elements” on page 132](#).

- 6 Save and close the file.

Modifying an MIDM Field's Data Type

Each field on the MIDM requires a specific type of data to be entered. For example, name fields generally require a data string and date fields require a valid date or numeric characters. The type of data defined for each field must correspond with the field type defined for that field in object.xml and in the database. If you modify a field's data type in the object structure using the Configuration Editor, midm.xml is automatically updated as well.

▼ To Modify the Data Type

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `midm.xml`.

The file opens in the NetBeans XML editor.

- 2 Scroll to the `node` element that defines the object that contains the field you want to modify.
- 3 Scroll to the `field` element you want to modify.
- 4 Change the value of the `value-type` element.

For example:

```
<value-type>string</value-type>
```

- 5 Save and close the file.

Defining Key Fields for an Object

You can specify that a certain field or combination of fields be unique in a system object or SBR. An example of a unique fields would be the address type if only one address of each type is allowed. A field's key type status in `midm.xml` must match its key type status in `object.xml`. If you modify a field's key type status in the object structure using the Configuration Editor, `midm.xml` is automatically updated as well.

▼ To Modify the Key Status

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `midm.xml`.

The file opens in the NetBeans XML editor.

- 2 Scroll to the `node` element that defines the object containing the field you want to modify.
- 3 Scroll to the `field` element you want to modify.
- 4 To specify that a field must be unique in a system object, change the value of the `key-type` element to `true`.

- 5 To specify that a field does not need to be unique in a system object, change the value of the `key-type` element to `false`.

For example:

```
<key-type>false</key-type>
```

- 6 To specify that a combination of fields must be unique for an object rather than just one single field, set the `key-type` element to `true` for each field.
- 7 Save and close the file.

Masking Field Values on the MIDM

You can specify that the values of certain fields be hidden on the MIDM from users without the appropriate access permissions. You can create a custom plug-in that uses the value of the `VIP Flag` field to determine whether the values of specified fields are hidden (typically in records with a `VIP` status of “VIP” or “Employee”). In records with any other `VIP` status, the field values would be visible regardless of whether the field is marked for masking.

This option is only available if the `object-sensitive-plug-in-class` element in the `impl-details` section is populated with the custom plug-in class (by default, this element is empty).

Note – To mask field values, you need to define a custom plug-in to implement the masking rules.

▼ To Mask Field Values on the MIDM

- 1 In the **Projects** window, expand the **Configuration** node in the project you want to modify, and then double-click `midm.xml`.
The file opens in the NetBeans XML editor.
- 2 Scroll to the `node` element that defines the object containing the field you want to modify.
- 3 Scroll to the `field` element you want to modify.
- 4 Change the value of the `is-sensitive` element to `true`.

If the element does not exist for the field, create a new `is-sensitive` element. For example:

```
<is-sensitive>true</is-sensitive>
```

Note – The `is-sensitive` element must appear before the `key-type` element in the field definition.

- 5 Save and close the file.

Defining MIDM Object Relationships

The relationships in `midm.xml` are predefined based on the information you provided when you created the object structure definition (`object.xml`). The relationship structure in `midm.xml` should match that of `object.xml`.

▼ To Define Relationships

- 1 In the **Projects** window, expand the **Configuration** node in the project you want to modify, and then double-click `midm.xml`.

The file opens in the NetBeans XML editor.

- 2 Scroll to the **relationships** element.
- 3 Specify the name of the parent object in the `name` element.
- 4 Specify the name of the child objects in the `children` elements.

For example:

```
<relationships>
  <name>Person</name>
  <children>Alias</children>
  <children>Address</children>
  <children>Phone</children>
  <children>AuxId</children>
</relationships>
```

- 5 To remove a child object from the relationships list, delete the `children` element defining the object you want to delete.
- 6 Save and close the file.

Defining MIDM Local ID Labels

The `local-id` element, which is nested in the `gui-definition` element, defines alternate names for the local ID headings and labels. The name defined here replaces the default local ID heading and field names on all pages, including the search result column names. This element is optional, and if it does not exist the label names default to “Local ID”.

▼ To Define Local ID Labels

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `midm.xml`.

The file opens in the NetBeans XML editor.

- 2 Scroll to the `local-id` element in the `gui-definition` element.
- 3 Enter the name you want to appear on the MIDM for the local ID fields and headings.
- 4 Save and close the file.

Configuring the Master Index MIDM Pages

You can configure certain pages that appear on the MIDM by modifying the `midm.xml`. Each page on the MIDM is configured separately, though many contain the same XML elements and attributes. For the Record Details page, you can configure and create search pages and search results lists. If you add a new query to `query.xml` and you want to access that query from the MIDM, you need to create a new search page for the query on the Record Details page. The Dashboard page cannot be configured.

Perform any of the following actions to configure the pages of the MIDM.

- [“Specifying the Initial View for the MIDM” on page 141](#)
- [“Configuring the MIDM Duplicate Records Page” on page 142](#)
- [“Configuring the MIDM Record Details Page” on page 147](#)
- [“Creating Search Pages on the Record Details Page” on page 148](#)
- [“Modifying a Search Page on the Record Details Page” on page 154](#)
- [“Configuring the MIDM Assumed Matches Page” on page 156](#)
- [“Configuring the MIDM Transactions Page” on page 158](#)
- [“Configuring the MIDM Reports Page” on page 160](#)
- [“Production Reports Definition Elements” on page 163](#)
- [“Configuring the MIDM Source Record Page” on page 165](#)
- [“Configuring the MIDM Audit Log Page” on page 167](#)

Specifying the Initial View for the MIDM

By default, the Record Details page appears when a user logs in to the Master Index Data Manager. You can specify any of the other tabbed pages as the initial view. Each page on the MIDM is identified by a screen ID in `midm.xml`, which is an integer defined in the `screen-id` element for each page. Use this ID to specify which page to display first when a user logs in.

▼ To Specify the Initial View

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `midm.xml`.

The file opens in the NetBeans XML editor.

- 2 Locate the page definition for the page you want to display first, and note the value of its `screen-id` element.
- 3 Scroll to the `initial-screen-id` element, located in the `gui-definition` element.
- 4 Enter the value of the `screen-id` element for the page you want to display first.
- 5 Save and close the file.

Configuring the MIDM Duplicate Records Page

The Duplicate Records page allows you to search for potential duplicate records, view a results list, and then view a comparison of the records you select. It also provides features to resolve or merge the potential duplicates in question. You can configure several aspects of the Duplicate Records page, including display options, search pages, and the results list.

The following topics provide instructions for each type of configuration:

- [“Configuring Duplicate Records Display Options” on page 142](#)
- [“Configuring Duplicate Records Search Pages” on page 143](#)
- [“Configuring the Duplicate Records Results List” on page 144](#)

Configuring Duplicate Records Display Options

You can configure certain display options for the Duplicate Records page, such as the name of the tabbed heading and the order in which the tab appears on the MIDM. Below is a sample of the display option elements for the Duplicate Records page.

```
<duplicate-records>
  <root-object>Person</root-object>
  <tab-name>Duplicate Records</tab-name>
  <screen-id>3</screen-id>
  <display-order>1</display-order>
  ...
</duplicate-records>
```

You should never need to modify the `root-object` or `screen-id` element for the Duplicate Records page.

▼ To Configure Duplicate Records Display Options

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `midm.xml`.
The file opens in the NetBeans XML editor.
- 2 Scroll to the `duplicate-records` element (located in the `gui-definition` element).
- 3 To specify a different name for the Duplicate Record tab, modify the value of the `tab-name` element.
- 4 To change the order in which the Duplicate Records tab appears on the MIDM, change the value of the `display-order` element.

Note – You might need to renumber the remaining tabs to keep the numbering sequential.

- 5 Save and close the file.

Configuring Duplicate Records Search Pages

For the Duplicate Records search pages, you can configure the names of the searches that can be performed, the fields to use as search criteria (within a limited set of system fields), and instructions for performing a search. Below is a sample of the search page configuration for the Duplicate Records page.

```
<duplicate-records>
  ...
  <simple-search-page>
    <screen-title>Advanced Search</screen-title>
    <search-result-id>0</search-result-id>
    <search-screen-order>0</search-screen-order>
    <show-euid>true</show-euid>
    <show-lid>true</show-lid>
    <show-status>true</show-status>
    <show-create-date>true</show-create-date>
    <show-create-time>true</show-create-time>
    <instruction></instruction>
    <field-group/>
  </simple-search-page>
  ...
</duplicate-records>
```

▼ To Configure the Duplicate Records Search Page

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `midm.xml`.

The file opens in the NetBeans XML editor.

- 2 Scroll to the `duplicate-records` element (located in the `gui-definition` element).
- 3 Modify any of the elements described in “Duplicate Records Search Page Elements” on page 145.
- 4 Save and close the file.

Configuring the Duplicate Records Results List

For the Duplicate Records results list, you can configure the number of results to display at one time, the total number of results a search can return, and the fields that appear in the results list. Below is a sample results list configuration for the Duplicate Records page.

```
<duplicate-records>
...
  <search-result-pages>
    <search-result-list-page>
      <search-result-id>0</search-result-id>
      <item-per-page>10</item-per-page>
      <max-result-size>100</max-result-size>
      <field-group>
        <description></description>
        <field-ref>Person.FirstName</field-ref>
        <field-ref>Person.LastName</field-ref>
        <field-ref>Person.SSN</field-ref>
        <field-ref>Person.DOB</field-ref>
        <field-ref>Person.Gender</field-ref>
      </field-group>
    </search-result-list-page>
  </search-result-pages>
</duplicate-records>
```

▼ To Configure the Duplicate Records Results List

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `midm.xml`.

The file opens in the NetBeans XML editor.

- 2 Scroll to the `duplicate-records` element (located in the `gui-definition` element).

- 3 Modify any of the elements described in [“Duplicate Records Search Results List Elements” on page 146](#).
- 4 To add a field to the results list, create and name a new `field-ref` element in the `field-group` element.
- 5 To delete a field from the results list, delete the `field-ref` element defining the field.
- 6 Save and close the file.

Duplicate Records Page Configuration Elements

The following two tables describe the configuration elements in `midm.xml` for the Duplicate Records search and results pages. The same elements are also used for the Source Record View/Edit page.

Duplicate Records Search Page Elements

The following table lists and describes the configurable elements for the Duplicate Records and Source Record search pages.

TABLE 1 Duplicate Records Search Page Configuration

Element/Attribute	Description
<code>search-pages</code>	A container element that lists and defines the searches that are available from the page.
<code>simple-search-page</code>	A container element that defines one type of search for the Duplicate Records page. You can define multiple simple search pages.
<code>screen-title</code>	The name of the search as it appears on the search page. MIDM users can select a type of search to perform based on the titles you define for the searches here.
<code>search-screen-order</code>	The order in which the search page appears on the MIDM.
<code>show-euid</code>	An indicator of whether to display the EUID field as search criteria. Specify true to display the EUID; otherwise specify false .
<code>show-lid</code>	An indicator of whether to display the local ID and system fields as search criteria. Specify true to display the fields; otherwise specify false .
<code>show-status</code>	An indicator of whether to display the record status field as search criteria. Specify true to display the field; otherwise specify false .

TABLE 1 Duplicate Records Search Page Configuration (Continued)

Element/Attribute	Description
show-create-date	An indicator of whether to display the create date field to allow searching on the date the potential duplicate flag was created. Specify true to display the field; otherwise specify false .
show-create-time	An indicator of whether to display the create time field to allow searching on the time the potential duplicate flag was created. Specify true to display the field; otherwise specify false .
instruction	A short statement to help the user process a search. The text you enter here appears above the search fields on the Search page.
field-group	A list of fields that appear on the Search page. You can define multiple field groups, and each group can be contained in a labelled box on the Search page.
description	A description of the fields defined for the <code>field-group</code> element. This value appears as a box label for the area of the page that contains the specified fields.
field-ref	One field definition for a field in the field group. Use the simple field name of the field with their corresponding objects as the root. For example, the path to the <code>FirstName</code> field in the <code>Person</code> object is “ <code>Person.FirstName</code> ”. You can define multiple <code>field-ref</code> elements for each field group.

Duplicate Records Search Results List Elements

The following table lists and describes the configurable elements for the Duplicate Records search results list.

TABLE 2 Duplicate Records Search Results Configuration

Element/Attribute	Description
search-result-pages	A container element for a list of search result page definitions.
search-result-list-page	A container element for the configuration information for the search results page.
item-per-page	The number of resulting records to display on one page.
max-result-size	The maximum number of records to return for a search.
field-group	A container element for a list of fields that appear in the search results.
description	A brief description for the field group. This value appears on the MIDM above the fields that are returned from a search.

TABLE 2 Duplicate Records Search Results Configuration (Continued)

Element/Attribute	Description
field-ref	A definition for one field that appears in the search results list. Use the simple field names with their corresponding objects as the root. For example, the path to the FirstName field in the Person object is "Person.FirstName". You can define multiple field-ref elements.

Configuring the MIDM Record Details Page

You can configure certain display options for the Record Details page, such as the name of the tabbed heading and the order in which the tab appears on the MIDM. You can also create, modify, and delete search pages and search results lists. Search configuration is described in [“Creating Search Pages on the Record Details Page” on page 148](#) and [“Modifying a Search Page on the Record Details Page” on page 154](#).

Below is a sample of the display option elements for the Record Details page.

```
<record-details>
  <root-object>Person</root-object>
  <tab-name>Record Details</tab-name>
  <screen-id>1</screen-id>
  <display-order>2</display-order>
  ...
</duplicate-records>
```

You should never need to modify the root-object or screen-id element.

▼ To Configure Record Details Display Options

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click midm.xml.

The file opens in the NetBeans XML editor.

- 2 Scroll to the record-details element (located in the gui-definition element).
- 3 To specify a different name for the Record Details tab, modify the value of the tab-name element.
- 4 To change the order in which the Record Details tab appears on the MIDM, change the value of the display-order element.

Note – You might need to renumber the remaining tabs to keep the numbering sequential.

- 5 Save and close the file.

Creating Search Pages on the Record Details Page

Several search pages are created by the Master Index Wizard based on the information you specify. You can create and customize new search pages for the Record Details page. Each search you define must use a query that is defined in `query.xml`.

Follow these steps to create a new search page:

- [“Step 1: Define the Search Page” on page 148](#)
- [“Step 2: Define the Search Fields” on page 149](#)
- [“Step 3: Specify Search Options” on page 150](#)

Step 1: Define the Search Page

The first step in creating a search page is to define certain properties for the appearance of the page, such as its name, whether to display the EUID or local ID field, and general instructions for the search.

Note – If either the EUID field or the local ID and system fields appear on a search page, any values entered into these fields take precedence over information entered into other search fields. For example, if an invalid EUID is entered but valid first and last names are entered, no results are returned due to the invalid EUID. The EUID field takes precedence over the local ID and system fields.

▼ To Define the Search Page

- 1 **In the Projects window, expand the Configuration node in the Project you want to modify, and then double-click `midm.xml`.**

The file opens in the NetBeans XML editor.

- 2 **Scroll to the `record-details` element, and then create a `simple-search-page` element.**

Make sure the new element falls within the `record-details` element, but outside any existing `simple-search-page` elements. For example:

```
<record-details>
  <simple-search-page>
    ...
  </simple-search-page>
  <simple-search-page>
    </simple-search-page>
</record-details>
```

- 3 In the new `simple-search-page` element, create the elements listed in [“Record Details Search Page Definition Elements” on page 151](#) and enter the appropriate value for each element.

For example:

```
<record-details>
  <simple-search-page>
    ...
  </simple-search-page>
</simple-search-page>
  <screen-title>Address Search</screen-title>
  <search-result-id>1</search-result-id>
  <show-euid>true</show-euid>
  <show-lid>false</show-lid>
  <instruction>Enter address information below.</instruction>
</simple-search-page>
</record-details>
```

- 4 Continue to [“Step 2: Define the Search Fields” on page 149](#).

Step 2: Define the Search Fields

Once you define the search page, you need to specify the fields that appear on the page. Fields are specified in field groups, and each field group represents an area on the search page. All fields specified for a field group appear in the area defined by that group. The label for the area is defined by the description of the field group.

▼ To Define Search Fields

- 1 Complete [“Step 1: Define the Search Page” on page 148](#).
- 2 In the new `simple-search-page` element, create a `field-group` element.

For example:

```
<simple-search-page>
  <screen-title>Simple Person Search</screen-title>
  <search-result-id>2</search-result-id>
  <search-screen-order>1</search-screen-order>
  <show-euid>false</show-euid>
  <show-lid>false</show-lid>
  <field-group>
  </field-group>
</simple-search-page>
```

- 3 In the new field-group element, create the elements and attributes listed in [“Record Details Search Field Definition Elements” on page 152](#) and enter the appropriate value for each.

For example:

```
<simple-search-page>
  ..
  <field-group>
    <description>Address</description>
    <field-ref>Address.AddressType</field-ref>
    <field-ref>Address.AddressLine1</field-ref>
    <field-ref>Address.AddressLine2</field-ref>
    <field-ref required="true">Address.City</field-ref>
    <field-ref>Address.State</field-ref>
  </field-group>
</simple-search-page>
```

- 4 Repeat steps 2 and 3 for each field group you want to display on the selected search page.
- 5 Continue to [“Step 3: Specify Search Options” on page 150](#).

Step 3: Specify Search Options

After you define the criteria fields for the MIDM search, you can specify certain options for the search, such as the types of available searches, whether each search is weighted, and whether the search allows wildcard characters.

Note – Wildcards should not be allowed for blocking queries or phonetic searches.

▼ To Specify Search Options

- 1 Complete [“Step 2: Define the Search Fields” on page 149](#).
- 2 In the simple-search-page element you created, create a search-option element.

For example:

```
<simple-search-page>
  <screen-title>Simple Person Search</screen-title>
  <search-result-id>2</search-result-id>
  <search-screen-order>1</search-screen-order>
  <show-euid>false</show-euid>
  <show-lid>false</show-lid>
  <field-group>
    ..
  </field-group>
  <search-option>
```

```

</search-option>
</simple-search-page>

```

- 3 In the new `search-option` element, create the elements listed in [“Record Details Search Option Elements” on page 153](#) and enter the appropriate value for each element.

For example:

```

<search-option>
  <display-name>Alpha Search</display-name>
  <query-builder>ALPHA-SEARCH</query-builder>
  <weighted>false</weighted>
  <parameter>
    <name>UseWildCard</name>
    <value>true</value>
  </parameter>
</search-option>

```

- 4 Repeat the previous two steps for each search type you want to make available on the selected search page.

Note – If you define multiple search option elements, an option button (labelled by the value of the `display-name` element) appears on the search page for each search option.

- 5 Save and close the file.

Record Details Search Page Definition Elements

The following table lists and describes the elements you can configure in `midm.xml` to define the search pages on the Record Details page.

Element	Description
<code>screen-title</code>	The name of the search as it appears on the search page. Users can select a type of search to perform based on the titles you define for the searches here.
<code>search-result-id</code>	The unique identifier for the search results page that appears for the search. You can define multiple search results pages for each MIDM page, and each results page has a unique ID. You can enter any of the search result ID values defined in the <code>search-results-pages</code> element.
<code>search-screen-order</code>	The order in which the search page appears on the MIDM.
<code>show-euid</code>	An indicator of whether to display the EUID. Specify true to display the EUID; otherwise specify false . Only display this field if you want it to take precedence over all other search criteria.

Element	Description
show-lid	An indicator of whether to display the local ID and system fields. Specify true to display the fields; otherwise specify false . Only display these fields if you want them to take precedence over all other search criteria (except the EUID field).
instruction	A short statement to help the user process a search. The text you enter here appears above the search fields on the Search page.

Record Details Search Field Definition Elements

The following table lists and describes the elements you can configure in midm.xml to define the fields for each search on the Record Details page.

Element/Attribute	Description
description	A description of the fields defined for the <code>field-group</code> element. This value appears as a box label for the area of the page that contains the specified fields.
field-ref	One field definition for a field in the field group. Use the simple field names of the fields with their corresponding objects as the root. For example, the path to the <code>FirstName</code> field in the <code>Person</code> object is “ <code>Person.FirstName</code> ”. You can define multiple <code>field-ref</code> elements for each field group, each of which are further configured by the following two optional attributes.
field-ref/required	<p>An indicator of whether the field is required in order to perform a search. Specify any of the following values:</p> <ul style="list-style-type: none">■ true – The corresponding field is required to perform the search. These fields are marked with an asterisk (*) on the search page.■ false – The corresponding field is not required to perform the search. If the <code>required</code> attribute is not defined, the default is false.■ one of – The corresponding fields with this designation are a group of search criteria, at least one of which is required to perform the search. This designation specifies that at least one field in the group of fields with the “one of” designation is required. If a group of fields is designated as “one of”, those fields are marked with a dagger (†) on the search page. <p>Tip – If you make a field required for a search, it is a good idea to make it required when creating a record as well by specifying <code>true</code> for the <code>required</code> property for the field in <code>object.xml</code>. Otherwise, searches performed from the MIDM could result in no possible matches even though possible matches exist.</p>

Element/Attribute	Description
field-ref/choice	<p>An indicator of whether the field allows you to search by a range of values rather than an exact value. Specify any of the following values:</p> <ul style="list-style-type: none"> ■ exact – The search is performed on the exact value entered (wildcard characters may be allowed). If the choice attribute is not specified, this is the default value. ■ range – The search is performed on a range of values based on the entered search criteria. Fields with this designation appear twice on the search page, once with “From” appended to the field label and once with “to” appended to the field label. If you specify “range” for a field in a search that uses a blocking query, be sure to modify the query block in query.xml accordingly. <p>Tip – You can specify the same field for both exact and range searching by adding it twice to the field list with different attribute values, giving the choice of performing an exact search or a range search from the MIDM. For more information about range searching, see “Range Searching” in Sun Master Index Configuration Reference.</p>

Record Details Search Option Elements

The following table lists and describes the elements you can configure in midm.xml to define the attributes for each search on the MIDM, such as which query to use, whether the search results are weighted, and so on.

Element	Description
display-name	A short phrase describing the type of search to perform, such as “Alphanumeric Search” or “Phonetic Search”. This appears next to the option button on the search page when multiple search options are defined.
query-builder	The type of query to use when this type of search is selected. The value entered here must match a query-builder name in query.xml.
weighted	An indicator of whether the results of the search are assigned matching probability weights. Specify true to assign matching weights; specify false to return unweighted results.
candidate-threshold	The maximum number of records to return for a search. This value must be a positive number and can only be used for blocking queries. Setting the candidate threshold to zero is equivalent to not setting a threshold.
parameter	A list of optional parameters for the search, specified by name and value elements (described below).
name	The name of the parameter. Currently, only UseWildcard is available.

Element	Description
value	The value of the parameter. For the UseWildcard parameter, this is an indicator of whether the parameter is enabled or disabled. Specify true to allow wildcard characters; specify false to perform exact-match searches.

Modifying a Search Page on the Record Details Page

Once a search page is defined for the Record Details page, it can be modified as needed. Be sure to review the search pages automatically generated by the wizard to see if any further configuration is required. You can perform any of the following actions to customize existing search page elements.

- “Modifying a Search Page Definition ” on page 154
- “Modifying Search Fields” on page 155
- “Modifying Record Details Search Page Options” on page 156

Modifying a Search Page Definition

Once a search page is defined for the Record Details page, you can modify the search page definition. The search page definition includes properties like the name of the page, the order of the search, the results list to use for the search, and so on.

▼ To Modify a Search Page Definition

- 1 In the Projects window, expand the Configuration node in the Project you want to modify, and then double-click `midm.xml`.
The file opens in the NetBeans XML editor.
- 2 Scroll to the `simple-search-page` element you want to modify in the `record-details` element.
- 3 In the `simple-search-page` element, change the value of any of the elements listed in “Record Details Search Page Definition Elements” on page 151.

For example:

```
<simple-search-page>
  <screen-title>Customer Search</screen-title>
  <search-result-id>2</search-result-id>
  <search-screen-order>2</search-screen-order>
  <show-euid>true</show-euid>
  <show-lid>false</show-lid>
  <instruction>Enter the EUID below.</instruction>
</simple-search-page>
```

- 4 Save and close the file.

Modifying Search Fields

Once field groups and fields are specified for a Record Details search page, you can modify the properties of the group and of the fields contained in a group. For more information about the elements that contain the search field configuration, see [“Record Details Search Field Definition Elements” on page 152](#).

▼ To Modify Search Fields

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `midm.xml`.
The file opens in the NetBeans XML editor.
- 2 Scroll to the `simple-search-page` element you want to modify in the `record-details` element.
- 3 In the field-group you want to modify, do any of the following:
 - To modify the name of the area in which the field group appears in the MIDM, change the value of the `description` element.
 - To add a new field to a field group, create and name a new `field-ref` element in the appropriate `field-group` element.
 - To modify the name of a field defined for a field group, change the value of the `field-ref` element.
 - To specify whether a field is required, add a `required` attribute and specify a value defined in [“Record Details Search Page Definition Elements” on page 151](#).
 - To specify whether a field is used for range searching, add a `choice` attribute and specify a value defined in [“Record Details Search Field Definition Elements” on page 152](#).
 - To delete a field from a field group, delete all text between and including the `field-ref` tags that define the field to be deleted.
 - To delete an entire field group, delete all text between and including the `field-group` tags that define the field group to be deleted.
- 4 Save and close the file.

Modifying Record Details Search Page Options

Once search options are defined for a Record Details search page, you can modify those options if needed. For more information about the elements that define search options, see [“Record Details Search Option Elements”](#) on page 153.

▼ To Modify Search Page Options

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `midm.xml`.

The file opens in the NetBeans XML editor.

- 2 Scroll to the `simple-search-page` element you want to modify in the `record-details` element.
- 3 In the `search-option` element, and do any of the following:
 - To modify the name of the search option button, change the value of the `display-name` element.
 - To modify the query type of the selected search, change the value of the `query-builder` element. The query you specify must match a query defined in `query.xml`.
 - To specify that a search return weighted results, change the value of the `weighted` element to `true`.
 - To specify that a search return unweighted results, change the value of the `weighted` element to `false`.
 - To specify that wildcard characters can be used in a search, change the `UseWildcard` parameter value element to `true`.
 - To specify that wildcard characters cannot be used in a search, change the `UseWildcard` parameter value element to `false`.
- 4 Save and close the file.

Configuring the MIDM Assumed Matches Page

The Assumed Matches page allows you to search for assumed match records, view a results list, and then view the details for the record you select. You can also undo an assumed match if you think it was made in error. You can configure the name of the tabbed heading for the page, the

display order, the number of records to return and display for a search, and the fields to display in the result list. The fields on the search page and in the results list are automatically generated and cannot be modified.

Below is a sample Assumed Matches page definition.

```
<assumed-matches>
  <root-object>Person</root-object>
  <tab-name>Assumed Matches</tab-name>
  <screen-id>4</screen-id>
  <display-order>3</display-order>
  <search-pages/>
  <search-result-pages>
    <search-result-list-page>
      <search-result-id>0</search-result-id>
      <item-per-page>10</item-per-page>
      <max-result-size>100</max-result-size>
      <field-group>
        <description></description>
        <field-ref>Person.FirstName</field-ref>
        <field-ref>Person.LastName</field-ref>
        <field-ref>Person.SSN</field-ref>
        <field-ref>Person.DOB</field-ref>
        <field-ref>Person.Gender</field-ref>
        <field-ref>Person.Address.AddressLine1</field-ref>
        <field-ref>Person.Address.AddressLine2</field-ref>
      </field-group>
    </search-result-list-page>
  </search-result-pages>
</assumed-matches>
```

▼ To Configure the Assumed Matches Page

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `midm.xml`.

The file opens in the NetBeans XML editor.

- 2 Scroll to the `assumed-matches` element (located in the `gui-definition` element).
- 3 Make any of the following configuration changes:
 - To specify a new name for the Assumed Matches tab, modify the value of the `tab-name` element.
 - To change the order in which the Assumed Matches tab appears on the MIDM, change the value of the `display-order` element.

Note – If you change the order of one tab, make sure to change the order of the remaining tabs so no tabs have an identical display order value.

- **To specify the number of records to display on the Assumed Matches search results list, change the value of the `item-per-page` element.**
- **To specify a maximum number of records to return for an Assumed Matches search, change the value of the `max-result-size` element.**
- **To add a search description, enter the description text into the `description` element.**
- **To modify the fields that appear in the results list in addition to the system fields, change the value of an existing `field-ref` element, create a new `field-ref` element, or delete an existing `field-ref` element.**

For example:

```
<field-group>
  <field-ref>Person.FirstName</field-ref>
  <field-ref>Person.LastName</field-ref>
  <field-ref>Person.SSN</field-ref>
  <field-ref>Person.DOB</field-ref>
</field-group>
```

4 Save and close the file.

Configuring the MIDM Transactions Page

The Transactions page allows you to search for transaction records, view a results list, and then view the changes for the record you select. You can configure the name of the tabbed heading for the page, the display order, and the number of records to return and to display in the results list. The fields on the search page and results list are automatically generated and cannot be modified with the exception of the EUID, system, and local ID.

Below is the default Transactions page definition.

```
<transactions>
  <root-object>Person</root-object>
  <tab-name>Transactions</tab-name>
  <screen-id>2</screen-id>
  <display-order>4</display-order>
  <search-pages>
    <simple-search-page>
      <show-euid>true</show-euid>
      <show-lid>true</show-lid>
```

```

        </simple-search-page>
    </search-pages>
    <search-result-pages>
        <search-result-list-page
            <search-result-id>0</search-result-id>
            <item-per-page>10</item-per-page>
            <max-result-size>100</max-result-size>
            <field-group/>
        </search-result-list-page>
    </search-result-pages>
</transactions>

```

▼ To Configure the Transactions Page

- 1 In the **Projects** window, expand the **Configuration** node in the project you want to modify, and then double-click **midm.xml**.

The file opens in the NetBeans XML editor.

- 2 Scroll to the **transactions** element (located in the **gui-definition** element).

- 3 Make any of the following configuration changes:

- To specify a new name for the Transactions tab, modify the value of the **tab-name** element.
- To change the order in which the Transactions tab appears on the MIDM, change the value of the **display-order** element.

Note – If you change the order of one tab, make sure to change the order of the remaining tabs so no tabs have an identical display order value.

- To include the EUID as a Transactions search field, change the value of the **show-euid** element to **true**.
- To exclude the EUID from the Transactions search fields, change the value of the **show-euid** element to **false**.
- To include the system and local ID as Transactions search fields, change the value of the **show-lid** element to **true**.
- To exclude the system and local ID from the Transactions search fields, change the value of the **show-euid** element to **false**.
- To specify the number of records to display on the Transactions search results list, change the value of the **item-per-page** element.

- To specify a maximum number of records to return for a Transactions search, change the value of the `max-result-size` element.
- 4 Save and close the file.

Configuring the MIDM Reports Page

Configuring the Reports page consists of configuring the page itself and configuring the individual reports. Production reports are each configured in the same way in their own sub-screen definition element. Activity reports are configured together in one sub-screen definition. The sub-screen definitions means there are a series of tabbed pages within the Reports page for each different type of report.

Perform any of the following tasks to configure the reports:

- [“Configuring the Reports Page Definition” on page 160](#)
- [“Configuring Production Reports” on page 161](#)
- [“Configuring Activity Reports” on page 162](#)

Configuring the Reports Page Definition

For the Reports page, you can configure the name of the tabbed heading for the page and the order in which the tab appears on the MIDM. The report configuration section defines the appearance of the Reports page, and is located within a set of `reports` tags near the end of the file. Following is a sample of the Reports page configuration elements.

```
<reports>
  <root-object>Person</root-object>
  <tab-name>Reports</tab-name>
  <screen-id>6</screen-id>
  <display-order>5</display-order>
  <search-pages/>
  <search-result-pages/>
```

▼ To Configure the Reports Page Definition

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `midm.xml`.
The file opens in the NetBeans XML editor.
- 2 Scroll to the `reports` element (located in the `gui-definition` element).
- 3 To specify a different name for the Reports tab, modify the value of the `tab-name` element.

- 4 To change the order in which the Reports tab appears on the MIDM, change the value of the `display-order` element.

Note – You might need to renumber the remaining tabs to keep the numbering sequential.

Note – You might need to renumber the remaining tabs to keep the numbering sequential.

- 5 When you have finished configuring the Reports page, save and close the file.

Configuring Production Reports

A sub-screen on the Reports page is defined for each of the production reports. Use these sections to configure each production report to display information as you want to view it. You can also specify which reports can be run from the MIDM. Following is an example of a report configuration stanza.

```
<subscreen>
  <enable>true</enable>
  <root-object>Person</root-object>
  <tab-name>Potential Duplicate Report</tab-name>
  <report-name>Potential Duplicate</report-name>
  <screen-id>0</screen-id>
  <display-order>5</display-order>
  <search-pages/>
  <search-result-pages>
    <search-result-list-page>
      <search-result-id>0</search-result-id>
      <item-per-page>10</item-per-page>
      <max-result-size>2000</max-result-size>
      <field-group>
        <description></description>
        <field-ref>Person.FirstName</field-ref>
        <field-ref>Person.LastName</field-ref>
        <field-ref>Person.SSN</field-ref>
        <field-ref>Person.DOB</field-ref>
        <field-ref>Person.Address.AddressLine1</field-ref>
        <field-ref>Person.Address.AddressLine2</field-ref>
        <field-ref>Person.Address.City</field-ref>
      </field-group>
    </search-result-list-page>
  </search-result-pages>
</subscreen>
```

▼ To Configure Production Reports

Perform the following steps for each production report.

- 1 **In the Projects window, expand the Configuration node in the project you want to modify, and then double-click midm.xml.**
The file opens in the NetBeans XML editor.
- 2 **Scroll to the reports element (located in the gui-def element).**
- 3 **For each report, specify values for the elements and attributes listed in “[Production Reports Definition Elements](#)” on page 163.**
- 4 **When you have finished configuring each report, save and close the file.**

Configuring Activity Reports

A sub-screen on the Reports page is defined for all of the activity reports. Use this sections to configure each activity report to display information as you want to view it. You can also specify which reports can be run from the MIDM. Following is an excerpt from the Activity report configuration stanza.

```
<subscreen>
  <enable>true</enable>
  <root-object>Person</root-object>
  <tab-name>Activity Report</tab-name>
  <report-name>Transaction Summary</report-name>
  <screen-id>5</screen-id>
  <display-order>4</display-order>
  <search-pages>
    <simple-search-page>
      <screen-title>Weekly Activity</screen-title>
      <report-name>Weekly Transaction Summary Report</report-name>
      <search-result-id>0</search-result-id>
      <search-screen-order>1</search-screen-order>
      <field-group/>
    </simple-search-page>
    ...
  </search-pages>
  <search-result-pages>
    <search-result-list-page>
      <search-result-id>0</search-result-id>
      <item-per-page>10</item-per-page>
      <max-result-size>2000</max-result-size>
      <field-group/>
    </search-result-list-page>
```

```
</search-result-pages>
</subscreen>
```

▼ To Configure Activity Reports

Perform the following steps for each production and activity report.

- 1 In the **Projects** window, expand the **Configuration** node in the project you want to modify, and then double-click **midm.xml**.
The file opens in the NetBeans XML editor.
- 2 Scroll to the **reports** element. This section is located near the end of the file.
- 3 In the **subscreen** element that defines the activity reports, modify any of the elements described in [“Activity Reports Page Definition Elements” on page 164](#) to configure the Activity Reports page:
- 4 For each activity report, modify any of the elements described in [“Activity Reports Search Elements” on page 164](#).
- 5 To specify the size and display of the results returned for the search, modify any of the elements described in [“Activity Reports Results Elements” on page 165](#).
- 6 When you have finished configuring each report, save and close the file.

Production Reports Definition Elements

The following table lists and describes the elements you can configure in **midm.xml** to define the production reports.

Element/Attribute	Description
enable	An indicator of whether to display the report search page on the Reports page. Specify true to display the report search page and enable the report; specify false to disable the report.
tab-name	The name to display on the tabbed heading for the report.
report-name	The name of the report as it appears on the generated report.
display-order	An integer indicating the order in which each report tab appears on the Reports page. If you change the display order of one report, make sure to change the others to keep the numbers consecutive.

Element/Attribute	Description
item-per-page	The number of items to display on one page of the report search results.
max-result-size	The number of records to display on the report. if no value is entered, or if the value is zero (0), the size defaults to 1000 records. To retrieve all records for a report, enter a very large value for this element.
description	A description of the fields defined for the <code>field-group</code> element. This value appears as a label for the area of the page that contains the specified fields.
field-ref	One field definition for a field in the field group. Use the simple field names of the fields with their corresponding objects as the root. For example, the path to the <code>FirstName</code> field in the <code>Person</code> object is “ <code>Person.FirstName</code> ”. You can define multiple <code>field-ref</code> elements for each field group.

Activity Reports Definition Elements

The following tables list and describe the elements you can configure for the activity reports in `midm.xml`.

Activity Reports Page Definition Elements

The following table lists and describes the elements you can configure in `midm.xml` to define the Activity Reports page.

Element/Attribute	Description
enable	An indicator of whether to display the Activity Reports search page on the Reports page. Specify true to display the report search page and enable the report; specify false to disable the report.
tab-name	The name to display on the tabbed heading for the report.
report-name	The name of the report as it appears on the generated report.
display-order	An integer indicating the order in which the Activity Reports tab appears on the Reports page. If you change the display order of one report, make sure to change the others to keep the numbers consecutive.

Activity Reports Search Elements

The following table lists and describes the elements you can configure in `midm.xml` to define each activity report search.

Element/Attribute	Description
screen-title	The name of the report search page as it appears on the Activity Reports page.
report-name	The name of the report as it appears on the generated report.
search-screen-order	An integer indicating the order in which each activity report appears on the Activity Reports page. If you change the display order of one report, make sure to change the others to keep the numbers consecutive.

Activity Reports Results Elements

The following table lists and describes the elements you can configure in midm.xml to define each activity report search result.

Element/Attribute	Description
item-per-page	The number of items to display on one page of the report search results.
max-result-size	The number of records to display on the report. If no value is entered, or if the value is zero (0), the size defaults to 1000 records. To retrieve all records for a report, enter a very large value for this element.

Configuring the MIDM Source Record Page

The Source Record page is where an MIDM user adds new records to the master index database and performs actions against a source record rather than an enterprise record. This page includes sub-screen configurations, which means there are a series of tabbed pages within the Source Record page. These pages each provide different functions, such as view and edit, compare and merge, and create a new record.

- [“Configuring the Source Record Page Definition” on page 165](#)
- [“Configuring the Tabbed Pages on the Source Record Page” on page 166](#)

Configuring the Source Record Page Definition

You can configure certain display options for the main Source Record page, including the order in which the tab appears on the MIDM and the name of the page.

▼ To Configure the Source Record Page Definition

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click midm.xml.

The file opens in the NetBeans XML editor.

- 2 Scroll to the source-record element (located in the gui-definition element).

- 3 To specify a different name for the Source Record tab, modify the value of the `tab-name` element.
- 4 To change the order in which the Source Record tab appears on the MIDM, change the value of the `display-order` element.

Note – You might need to renumber the remaining tabs to keep the numbering sequential.

- 5 Save and close the file.

Configuring the Tabbed Pages on the Source Record Page

You can configure any of the pages on the Source Record page by changing the tab name and display order and by enabling or disabling each page. Do not modify the search page or search results list for the sub-screens. Below is a sample configuration for the View/Edit page on the Source Record page.

```
<subscreen>
  <enable>true</enable>
  <root-object>Person</root-object>
  <tab-name>View/Edit</tab-name>
  <screen-id>0</screen-id>
  <display-order>0</display-order>
  ...
```

You should never need to modify the `root-object` or `screen-id` elements.

▼ To Configure the Source Record Tabbed Pages

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `midm.xml`.
The file opens in the NetBeans XML editor.
- 2 Scroll to the `source-records` element, and then to the `subscreen` element containing name of the tab you want to modify.
- 3 To specify a new name for the tab, modify the value of the `tab-name` element.
- 4 To disable the sub-screen, change the value of the `enable` element to `false`.
- 5 To enable the sub-screen, change the value of the `enable` element to `true`.
- 6 To change the order in which the tab appears on the Source Records page, change the value of the `display-order` element.

Note – You might need to renumber the remaining tabs to keep the numbering sequential.

7 Save and close the file.

Configuring the MIDM Audit Log Page

When enabled, the audit log stores a history of each instance in which information from the object tables in the master index database is accessed. The MIDM allows you to search for and view the audit log entries. You can enable or disable the audit log, change the display order, and customize the size of the results list. Below is the default Audit Log page definition.

```
<audit-log>
  <allow-insert>false</allow-insert>
  <root-object>Person</root-object>
  <tab-name>Audit Log</tab-name>
  <screen-id>7</screen-id>
  <display-order>7</display-order>
  <search-pages>
    <simple-search-page>
      <show-euid>true</show-euid>
      <show-lid>true</show-lid>
    </simple-search-page>
  </search-pages>
  <search-result-pages>
    <search-result-list-page>
      <search-result-id>0</search-result-id>
      <item-per-page>10</item-per-page>
      <max-result-size>100</max-result-size>
      <field-group/>
    </search-result-list-page>
  </search-result-pages>
</audit-log>
```

▼ To Configure the Audit Log Page

- 1 In the **Projects** window, expand the **Configuration** node in the project you want to modify, and then double-click **midm.xml**.

The file opens in the NetBeans XML editor.

- 2 Scroll to the **audit-log** element (located in the **gui-definition** element).

3 Make any of the following changes:

- To specify that records be written to the audit log, change the value of the `allow-insert` element to `true`.
- To specify that records not be written to the audit log, change the value of the `allow-insert` element to `false`.
- To change the name of the Audit Log tab on the MIDM, change the value of the `tab-name` element.
- To change the order in which the Audit Log appears on the MIDM, change the value of the `display-order` parameter to a different integer.

Note – If you change the order of one tab, make sure to change the order of the remaining tabs so no tabs have an identical display order value.

- To change the number of Audit Log search results that appear on one page, change the value of the `item-per-page` element.
- To change the maximum number of audit log records that can be returned for a search, change the value of the `max-result-size` element.

4 Save and close the file.

Configuring Master Index MIDM Implementation Information

Certain configuration information is defined automatically in the implementation details section of `midm.xml` based on information you specify in the wizard. Other information in this section must be customized by modifying the XML file directly.

You can customize the implementation details by performing any of the following tasks.

- [“Specifying the Master Controller JNDI Class” on page 168](#)
- [“Specifying the Master Index Report Generator JNDI Class” on page 169](#)
- [“Specifying Master Index Validation Services” on page 170](#)
- [“Setting Master Index Debug Options” on page 170](#)
- [“Specifying a Master Index Field Masking Class” on page 171](#)

Specifying the Master Controller JNDI Class

The MIDM must know the name of the Master Controller interface for the Sun Master Index implementation. Only change this value if you create a custom Master Controller.

▼ To Specify the Master Controller JNDI Class

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `midm.xml`.

The file opens in the NetBeans XML editor.

- 2 Scroll to the `impl-details` element, and then to the `master-controller-jndi-name` element.
- 3 Modify the value of the `master-controller-jndi-name` element to the name of the Master Controller JNDI class for your server.

For example:

```
<master-controller-jndi-name>ejb/CustomerMasterController
</master-controller-jndi-name>
```

- 4 Save and close the file.

Specifying the Master Index Report Generator JNDI Class

The MIDM must know the name of the class used to generate reports for the MIDM. Only change this value if you create a custom report generator.

▼ To Specify the Report Generator JNDI Class

- 1 In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `midm.xml`.

The file opens in the NetBeans XML editor.

- 2 Scroll to the `impl-details` element, and then to the `reportgenerator-jndi-name` element.
- 3 Modify the value of the `reportgenerator-jndi-name` element to the name of the report generator JNDI class to use.

For example:

```
reportgenerator-jndi-name>ejb/CustomerReportGenerator
</reportgenerator-jndi-name>
```

- 4 Save and close the file.

Specifying Master Index Validation Services

Validation services verify processing codes for data entered into the master index database. Only change the names of the validation services if you created custom code list validators.

▼ To Specify the Validation Service

- 1 **In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `midm.xml`.**
The file opens in the NetBeans XML editor.
- 2 **Scroll to the `impl-details` element, and then to the `validation-service-jndi-name` element.**
- 3 **To change the name of the validator for processing codes stored in `sbyn_common_header`, modify the value of the `validation-service-jndi-name` element to the name of the JNDI class used for validation.**

For example:

```
<validation-service-jndi-name>ejb/CustomerCodeLookup</validation-service-jndi-name>
```

- 4 **To change the name of the validator for processing codes stored in `sbyn_user_code`, modify the value of the `usercode-jndi-name` element to the name of the JNDI class used for validation.**

For example:

```
<usercode-jndi-name>ejb/CustomerUserCodeLookup</usercode-jndi-name>
```

- 5 **Save and close the file.**

Setting Master Index Debug Options

When you first implement Sun Master Index, you might want to view detailed debug information until you are certain the application is working as required. You can set debug options in the implementation details.

▼ To Set Debug Options

- 1 **In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `midm.xml`.**
The file opens in the NetBeans XML editor.
- 2 **Scroll to the `impl-details` element, and then to the `debug-flag` element.**

- 3 **Modify the value of the `debug-flag` element to indicate whether you want debug information logged.**

For example:

```
<debug-flag>true</debug-flag>
```

Specify **true** to log debug information; specify **false** to turn logging off.

- 4 **Modify the value of the `debug-dest` element to indicate where to print debug information.**

For example:

```
<debug-dest>console</debug-dest>
```

Specify **console** to log debug information to a monitor; specify **file** to print to a file.

- 5 **Save and close the file.**

Specifying a Master Index Field Masking Class

If you implement a custom class to define field masking logic, you must specify the new class in the implementation details. The custom class must be created as a custom plug-in in the Sun Master Index project. This class can be used to mask the value of any field for which the `is-sensitive` element is set to “true”.

▼ To Specify a Field Masking Class

- 1 **In the Projects window, expand the Configuration node in the project you want to modify, and then double-click `midm.xml`.**

The file opens in the NetBeans XML editor.

- 2 **Scroll to the `impl-details` element.**

- 3 **Change the value of the `object-sensitive-plug-in-class` element to the name of the custom class.**

For example:

```
<object-sensitive-plug-in-class>
  com.sun.mdm.index.user.customfieldmasker
</object-sensitive-plug-in-class>
```

- 4 **Save and close the file.**

