

man pages section 3: Networking Library Functions

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT END USERS. Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Ce logiciel et la documentation qui l'accompagne sont protégés par les lois sur la propriété intellectuelle. Ils sont concédés sous licence et soumis à des restrictions d'utilisation et de divulgation. Sauf disposition de votre contrat de licence ou de la loi, vous ne pouvez pas copier, reproduire, traduire, diffuser, modifier, breveter, transmettre, distribuer, exposer, exécuter, publier ou afficher le logiciel, même partiellement, sous quelque forme et par quelque procédé que ce soit. Par ailleurs, il est interdit de procéder à toute ingénierie inverse du logiciel, de le désassembler ou de le décompiler, excepté à des fins d'interopérabilité avec des logiciels tiers ou tel que prescrit par la loi.

Les informations fournies dans ce document sont susceptibles de modification sans préavis. Par ailleurs, Oracle Corporation ne garantit pas qu'elles soient exemptes d'erreurs et vous invite, le cas échéant, à lui en faire part par écrit.

Si ce logiciel, ou la documentation qui l'accompagne, est concédé sous licence au Gouvernement des Etats-Unis, ou à toute entité qui délivre la licence de ce logiciel ou l'utilise pour le compte du Gouvernement des Etats-Unis, la notice suivante s'applique:

U.S. GOVERNMENT END USERS. Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

Ce logiciel ou matériel a été développé pour un usage général dans le cadre d'applications de gestion des informations. Ce logiciel ou matériel n'est destiné à être utilisé dans des applications à risque, notamment dans des applications pouvant causer des dommages corporels. Si vous utilisez ce logiciel ou matériel dans le cadre d'applications dangereuses, il est de votre responsabilité de prendre toutes les mesures de secours, de sauvegarde, de redondance et autres mesures nécessaires à son utilisation dans des conditions optimales de sécurité. Oracle Corporation et ses affiliés déclinent toute responsabilité quant aux dommages causés par l'utilisation de ce logiciel ou matériel pour ce type d'applications.

Oracle et Java sont des marques déposées d'Oracle Corporation et/ou de ses affiliés. Tout autre nom mentionné peut correspondre à des marques appartenant à d'autres propriétaires qu'Oracle.

Intel et Intel Xeon sont des marques ou des marques déposées d'Intel Corporation. Toutes les marques SPARC sont utilisées sous licence et sont des marques ou des marques déposées de SPARC International, Inc. AMD, Opteron, le logo AMD et le logo AMD Opteron sont des marques ou des marques déposées d'Advanced Micro Devices. UNIX est une marque déposée d'The Open Group.

Ce logiciel ou matériel et la documentation qui l'accompagne peuvent fournir des informations ou des liens donnant accès à des contenus, des produits et des services émanant de tiers. Oracle Corporation et ses affiliés déclinent toute responsabilité ou garantie expresse quant aux contenus, produits ou services émanant de tiers. En aucun cas, Oracle Corporation et ses affiliés ne sauraient être tenus pour responsables des pertes subies, des coûts occasionnés ou des dommages causés par l'accès à des contenus, produits ou services tiers, ou à leur utilisation.

Contents

Preface	15
Networking Library Functions	19
accept(3SOCKET)	20
accept(3XNET)	22
ber_decode(3LDAP)	24
ber_encode(3LDAP)	29
bind(3SOCKET)	33
bind(3XNET)	35
byteorder(3SOCKET)	38
cldap_close(3LDAP)	39
cldap_open(3LDAP)	40
cldap_search_s(3LDAP)	41
cldap_setretryinfo(3LDAP)	43
connect(3SOCKET)	44
connect(3XNET)	46
dial(3NSL)	49
dlpi_arptype(3DLPI)	51
dlpi_bind(3DLPI)	52
dlpi_close(3DLPI)	53
dlpi_disabnotify(3DLPI)	54
dlpi_enabmulti(3DLPI)	55
dlpi_enabnotify(3DLPI)	56
dlpi_fd(3DLPI)	58
dlpi_get_physaddr(3DLPI)	59
dlpi_iftype(3DLPI)	60
dlpi_info(3DLPI)	61
dlpi_linkname(3DLPI)	64

dlpi_mactype(3DLPI)	65
dlpi_open(3DLPI)	66
dlpi_promisc(3DLPI)	68
dlpi_recv(3DLPI)	69
dlpi_send(3DLPI)	71
dlpi_set_physaddr(3DLPI)	73
dlpi_set_timeout(3DLPI)	74
dlpi_strerror(3DLPI)	75
dlpi_unbind(3DLPI)	76
doconfig(3NSL)	77
endhostent(3XNET)	80
endnetent(3XNET)	82
endprotoent(3XNET)	84
endservent(3XNET)	86
ethers(3SOCKET)	88
freeaddrinfo(3XNET)	90
gai_strerror(3XNET)	94
getaddrinfo(3SOCKET)	95
gethostbyname(3NSL)	102
gethostname(3XNET)	108
getipnodebyname(3SOCKET)	109
getipsecalgbyname(3NSL)	115
getipsecprotobyname(3NSL)	118
getnameinfo(3XNET)	120
getnetbyname(3SOCKET)	123
getnetconfig(3NSL)	127
getnetpath(3NSL)	129
getpeername(3SOCKET)	131
getpeername(3XNET)	132
getprotobyname(3SOCKET)	134
getpublickey(3NSL)	137
getrpcbyname(3NSL)	138
getservbyname(3SOCKET)	141
getsockname(3SOCKET)	145
getsockname(3XNET)	146
getsockopt(3SOCKET)	148

getsockopt(3XNET)	152
getsourcefilter(3SOCKET)	156
gss_accept_sec_context(3GSS)	159
gss_acquire_cred(3GSS)	165
gss_add_cred(3GSS)	168
gss_add_oid_set_member(3GSS)	172
gss_canonicalize_name(3GSS)	173
gss_compare_name(3GSS)	175
gss_context_time(3GSS)	177
gss_create_empty_oid_set(3GSS)	178
gss_delete_sec_context(3GSS)	179
gss_display_name(3GSS)	181
gss_display_status(3GSS)	183
gss_duplicate_name(3GSS)	185
gss_export_name(3GSS)	186
gss_export_sec_context(3GSS)	187
gss_get_mic(3GSS)	189
gss_import_name(3GSS)	191
gss_import_sec_context(3GSS)	193
gss_indicate_mechs(3GSS)	195
gss_init_sec_context(3GSS)	196
gss_inquire_context(3GSS)	203
gss_inquire_cred(3GSS)	206
gss_inquire_cred_by_mech(3GSS)	208
gss_inquire_mechs_for_name(3GSS)	210
gss_inquire_names_for_mech(3GSS)	212
gss_oid_to_str(3GSS)	213
gss_process_context_token(3GSS)	215
gss_release_buffer(3GSS)	217
gss_release_cred(3GSS)	218
gss_release_name(3GSS)	219
gss_release_oid(3GSS)	220
gss_release_oid_set(3GSS)	221
gss_store_cred(3GSS)	222
gss_str_to_oid(3GSS)	225
gss_test_oid_set_member(3GSS)	227

gss_unwrap(3GSS)	228
gss_verify_mic(3GSS)	230
gss_wrap(3GSS)	232
gss_wrap_size_limit(3GSS)	234
htonl(3XNET)	236
icmp6_filter(3SOCKET)	237
if_nametoindex(3SOCKET)	238
if_nametoindex(3XNET)	240
inet(3SOCKET)	242
inet6_opt(3SOCKET)	246
inet6_rth(3SOCKET)	249
inet_addr(3XNET)	252
inet_ntop(3XNET)	254
ldap(3LDAP)	256
ldap_abandon(3LDAP)	266
ldap_add(3LDAP)	267
ldap_ber_free(3LDAP)	269
ldap_bind(3LDAP)	270
ldap_charset(3LDAP)	273
ldap_compare(3LDAP)	275
ldap_control_free(3LDAP)	277
ldap_delete(3LDAP)	278
ldap_disptmpl(3LDAP)	280
ldap_entry2text(3LDAP)	286
ldap_error(3LDAP)	290
ldap_first_attribute(3LDAP)	294
ldap_first_entry(3LDAP)	295
ldap_first_message(3LDAP)	297
ldap_friendly(3LDAP)	298
ldap_get_dn(3LDAP)	300
ldap_get_entry_controls(3LDAP)	302
ldap_getfilter(3LDAP)	303
ldap_get_lang_values(3LDAP)	305
ldap_get_option(3LDAP)	307
ldap_get_values(3LDAP)	313
ldap_memcache(3LDAP)	315

ldap_memfree(3LDAP)	318
ldap_modify(3LDAP)	319
ldap_modrdn(3LDAP)	321
ldap_open(3LDAP)	323
ldap_parse_result(3LDAP)	325
ldap_result(3LDAP)	326
ldap_search(3LDAP)	328
ldap_searchprefs(3LDAP)	331
ldap_sort(3LDAP)	333
ldap_ufn(3LDAP)	335
ldap_url(3LDAP)	337
ldap_version(3LDAP)	340
listen(3SOCKET)	341
listen(3XNET)	342
netdir(3NSL)	344
nis_error(3NSL)	348
nis_groups(3NSL)	350
nis_local_names(3NSL)	353
nis_names(3NSL)	355
nis_objects(3NSL)	361
nis_ping(3NSL)	370
nis_server(3NSL)	371
nis_subr(3NSL)	373
nis_tables(3NSL)	376
nlsgetcall(3NSL)	384
nlsprovider(3NSL)	385
nlsrequest(3NSL)	386
rcmd(3SOCKET)	388
recv(3SOCKET)	391
recv(3XNET)	394
recvfrom(3XNET)	397
recvmsg(3XNET)	400
resolver(3RESOLV)	403
rexec(3SOCKET)	409
rpc(3NSL)	411
rpcbind(3NSL)	420

rpc_clnt_auth(3NSL)	422
rpc_clnt_calls(3NSL)	424
rpc_clnt_create(3NSL)	429
rpc_control(3NSL)	438
rpc_gss_getcred(3NSL)	440
rpc_gss_get_error(3NSL)	442
rpc_gss_get_mechanisms(3NSL)	443
rpc_gss_get_principal_name(3NSL)	445
rpc_gss_max_data_length(3NSL)	447
rpc_gss_mech_to_oid(3NSL)	448
rpc_gss_seccreate(3NSL)	450
rpc_gss_set_callback(3NSL)	452
rpc_gss_set_defaults(3NSL)	454
rpc_gss_set_svc_name(3NSL)	455
rpcsec_gss(3NSL)	456
rpc_soc(3NSL)	460
rpc_svc_calls(3NSL)	473
rpc_svc_create(3NSL)	477
rpc_svc_err(3NSL)	482
rpc_svc_input(3NSL)	484
rpc_svc_reg(3NSL)	486
rpc_xdr(3NSL)	488
rstat(3RPC)	490
rusers(3RPC)	491
rwall(3RPC)	492
sasl_authorize_t(3SASL)	493
sasl_auxprop(3SASL)	495
sasl_auxprop_add_plugin(3SASL)	498
sasl_auxprop_getctx(3SASL)	499
sasl_auxprop_request(3SASL)	500
sasl_canonuser_add_plugin(3SASL)	501
sasl_canon_user_t(3SASL)	502
sasl_chalprompt_t(3SASL)	504
sasl_checkpop(3SASL)	505
sasl_checkpass(3SASL)	506
sasl_client_add_plugin(3SASL)	508

<code>sasl_client_init(3SASL)</code>	509
<code>sasl_client_new(3SASL)</code>	510
<code>sasl_client_plug_init_t(3SASL)</code>	512
<code>sasl_client_start(3SASL)</code>	513
<code>sasl_client_step(3SASL)</code>	515
<code>sasl_decode(3SASL)</code>	517
<code>sasl_decode64(3SASL)</code>	518
<code>sasl_dispose(3SASL)</code>	519
<code>sasl_done(3SASL)</code>	520
<code>sasl_encode(3SASL)</code>	521
<code>sasl_encode64(3SASL)</code>	522
<code>sasl_erasebuffer(3SASL)</code>	523
<code>sasl_errdetail(3SASL)</code>	524
<code>sasl_errors(3SASL)</code>	525
<code>sasl_errstring(3SASL)</code>	527
<code>sasl_getcallback_t(3SASL)</code>	528
<code>sasl_getopt_t(3SASL)</code>	529
<code>sasl_getpath_t(3SASL)</code>	530
<code>sasl_getprop(3SASL)</code>	531
<code>sasl_getrealm_t(3SASL)</code>	533
<code>sasl_getsecret_t(3SASL)</code>	534
<code>sasl_getsimple_t(3SASL)</code>	535
<code>sasl_global_listmech(3SASL)</code>	536
<code>sasl_idle(3SASL)</code>	537
<code>sasl_listmech(3SASL)</code>	538
<code>sasl_log_t(3SASL)</code>	540
<code>sasl_server_add_plugin(3SASL)</code>	542
<code>sasl_server_init(3SASL)</code>	543
<code>sasl_server_new(3SASL)</code>	544
<code>sasl_server_plug_init_t(3SASL)</code>	546
<code>sasl_server_start(3SASL)</code>	547
<code>sasl_server_step(3SASL)</code>	549
<code>sasl_server_userdb_checkpass_t(3SASL)</code>	550
<code>sasl_server_userdb_setpass_t(3SASL)</code>	551
<code>sasl_set_alloc(3SASL)</code>	552
<code>sasl_seterror(3SASL)</code>	553

sasl_set_mutex(3SASL)	554
sasl_setpass(3SASL)	555
sasl_setprop(3SASL)	556
sasl_utf8verify(3SASL)	558
sasl_verifyfile_t(3SASL)	559
sasl_version(3SASL)	560
sctp_bindx(3SOCKET)	561
sctp_getladdrs(3SOCKET)	563
sctp_getpaddrs(3SOCKET)	565
sctp_opt_info(3SOCKET)	567
sctp_peeloff(3SOCKET)	572
sctp_rcvmsg(3SOCKET)	573
sctp_send(3SOCKET)	574
sctp_sendmsg(3SOCKET)	576
sdp_add_origin(3COMMPUTIL)	578
sdp_clone_session(3COMMPUTIL)	584
sdp_delete_all_field(3COMMPUTIL)	585
sdp_delete_media(3COMMPUTIL)	586
sdp_find_attribute(3COMMPUTIL)	587
sdp_find_media(3COMMPUTIL)	589
sdp_find_media_rtpmap(3COMMPUTIL)	590
sdp_new_session(3COMMPUTIL)	592
sdp_parse(3COMMPUTIL)	593
sdp_session_to_str(3COMMPUTIL)	599
secure_rpc(3NSL)	600
send(3SOCKET)	605
send(3XNET)	608
sendmsg(3XNET)	611
sendto(3XNET)	615
setsockopt(3XNET)	618
shutdown(3SOCKET)	622
shutdown(3XNET)	623
sip_add_branchid_to_via(3SIP)	624
sip_add_from(3SIP)	625
sip_add_header(3SIP)	634
sip_add_param(3SIP)	635

<code>sip_add_request_line(3SIP)</code>	636
<code>sip_branchid(3SIP)</code>	638
<code>sip_clone_msg(3SIP)</code>	639
<code>sip_copy_start_line(3SIP)</code>	640
<code>sip_create_dialog_req(3SIP)</code>	642
<code>sip_create_OKack(3SIP)</code>	644
<code>sip_create_response(3SIP)</code>	646
<code>sip_delete_dialog(3SIP)</code>	647
<code>sip_delete_start_line(3SIP)</code>	648
<code>sip_enable_counters(3SIP)</code>	650
<code>sip_enable_trans_logging(3SIP)</code>	653
<code>sip_get_contact_display_name(3SIP)</code>	656
<code>sip_get_cseq(3SIP)</code>	667
<code>sip_get_dialog_state(3SIP)</code>	668
<code>sip_get_header(3SIP)</code>	671
<code>sip_get_header_value(3SIP)</code>	672
<code>sip_get_msg_len(3SIP)</code>	673
<code>sip_get_num_via(3SIP)</code>	674
<code>sip_get_param_value(3SIP)</code>	675
<code>sip_get_request_method(3SIP)</code>	677
<code>sip_get_request_uri_str(3SIP)</code>	679
<code>sip_get_resp_desc(3SIP)</code>	681
<code>sip_get_trans(3SIP)</code>	682
<code>sip_get_trans_method(3SIP)</code>	683
<code>sip_get_uri_parsed(3SIP)</code>	686
<code>sip_guid(3SIP)</code>	687
<code>sip_hold_dialog(3SIP)</code>	688
<code>sip_hold_msg(3SIP)</code>	689
<code>sip_hold_trans(3SIP)</code>	690
<code>sip_init_conn_object(3SIP)</code>	691
<code>sip_is_sip_uri(3SIP)</code>	692
<code>sip_msg_is_request(3SIP)</code>	696
<code>sip_msg_to_str(3SIP)</code>	697
<code>sip_new_msg(3SIP)</code>	699
<code>sip_parse_uri(3SIP)</code>	700
<code>sip_process_new_packet(3SIP)</code>	702

<code>sip_register_sent_by(3SIP)</code>	703
<code>sip_sendmsg(3SIP)</code>	704
<code>sip_stack_init(3SIP)</code>	706
<code>slp_api(3SLP)</code>	711
<code>SLPclose(3SLP)</code>	720
<code>SLPDelAttrs(3SLP)</code>	721
<code>SLPDereg(3SLP)</code>	722
<code>SLPEscape(3SLP)</code>	723
<code>SLPFindAttrs(3SLP)</code>	725
<code>SLPFindScopes(3SLP)</code>	727
<code>SLPFindSrvs(3SLP)</code>	729
<code>SLPFindSrvTypes(3SLP)</code>	731
<code>SLPFree(3SLP)</code>	733
<code>SLPGetProperty(3SLP)</code>	734
<code>SLPGetRefreshInterval(3SLP)</code>	735
<code>SLPopen(3SLP)</code>	736
<code>SLPParseSrvURL(3SLP)</code>	738
<code>SLPReg(3SLP)</code>	740
<code>SLPSetProperty(3SLP)</code>	742
<code>slp_strerror(3SLP)</code>	743
<code>SLPUnescape(3SLP)</code>	744
<code>socketatmark(3XNET)</code>	746
<code>socket(3SOCKET)</code>	748
<code>socket(3XNET)</code>	751
<code>socketpair(3SOCKET)</code>	753
<code>socketpair(3XNET)</code>	754
<code>spray(3SOCKET)</code>	756
<code>t_accept(3NSL)</code>	758
<code>t_alloc(3NSL)</code>	762
<code>t_bind(3NSL)</code>	765
<code>t_close(3NSL)</code>	769
<code>t_connect(3NSL)</code>	771
<code>t_errno(3NSL)</code>	775
<code>t_error(3NSL)</code>	777
<code>t_free(3NSL)</code>	779
<code>t_getinfo(3NSL)</code>	781

t_getprotaddr(3NSL)	785
t_getstate(3NSL)	787
t_listen(3NSL)	789
t_look(3NSL)	792
t_open(3NSL)	794
t_optmgmt(3NSL)	798
t_rcv(3NSL)	805
t_rcvconnect(3NSL)	808
t_rcvdis(3NSL)	811
t_rcvrel(3NSL)	813
t_rcvreldata(3NSL)	815
t_rcvudata(3NSL)	817
t_rcvuderr(3NSL)	820
t_rcvv(3NSL)	822
t_rcvvudata(3NSL)	825
t_snd(3NSL)	827
t_snddis(3NSL)	831
t_sndrel(3NSL)	833
t_sndreldata(3NSL)	835
t_sndudata(3NSL)	837
t_sndv(3NSL)	840
t_sndvudata(3NSL)	844
t_strerror(3NSL)	847
t_sync(3NSL)	849
t_sysconf(3NSL)	851
t_unbind(3NSL)	852
xdr(3NSL)	854
xdr_admin(3NSL)	856
xdr_complex(3NSL)	858
xdr_create(3NSL)	861
xdr_simple(3NSL)	863
ypclnt(3NSL)	867
yp_update(3NSL)	873

Preface

Both novice users and those familiar with the SunOS operating system can use online man pages to obtain information about the system and its features. A man page is intended to answer concisely the question “What does it do?” The man pages in general comprise a reference manual. They are not intended to be a tutorial.

Overview

The following contains a brief description of each man page section and the information it references:

- Section 1 describes, in alphabetical order, commands available with the operating system.
- Section 1M describes, in alphabetical order, commands that are used chiefly for system maintenance and administration purposes.
- Section 2 describes all of the system calls. Most of these calls have one or more error returns. An error condition is indicated by an otherwise impossible returned value.
- Section 3 describes functions found in various libraries, other than those functions that directly invoke UNIX system primitives, which are described in Section 2.
- Section 4 outlines the formats of various files. The C structure declarations for the file formats are given where applicable.
- Section 5 contains miscellaneous documentation such as character-set tables.
- Section 6 contains available games and demos.
- Section 7 describes various special files that refer to specific hardware peripherals and device drivers. STREAMS software drivers, modules and the STREAMS-generic set of system calls are also described.
- Section 9 provides reference information needed to write device drivers in the kernel environment. It describes two device driver interface specifications: the Device Driver Interface (DDI) and the Driver/Kernel Interface (DKI).
- Section 9E describes the DDI/DKI, DDI-only, and DKI-only entry-point routines a developer can include in a device driver.
- Section 9F describes the kernel functions available for use by device drivers.
- Section 9S describes the data structures used by drivers to share information between the driver and the kernel.

Below is a generic format for man pages. The man pages of each manual section generally follow this order, but include only needed headings. For example, if there are no bugs to report, there is no BUGS section. See the `intro` pages for more information and detail about each section, and [man\(1\)](#) for more information about man pages in general.

NAME	This section gives the names of the commands or functions documented, followed by a brief description of what they do.
SYNOPSIS	<p>This section shows the syntax of commands or functions. When a command or file does not exist in the standard path, its full path name is shown. Options and arguments are alphabetized, with single letter arguments first, and options with arguments next, unless a different argument order is required.</p> <p>The following special characters are used in this section:</p> <ul style="list-style-type: none">[] Brackets. The option or argument enclosed in these brackets is optional. If the brackets are omitted, the argument must be specified.. . . Ellipses. Several values can be provided for the previous argument, or the previous argument can be specified multiple times, for example, "filename...". Separator. Only one of the arguments separated by this character can be specified at a time.{ } Braces. The options and/or arguments enclosed within braces are interdependent, such that everything enclosed must be treated as a unit.
PROTOCOL	This section occurs only in subsection 3R to indicate the protocol description file.
DESCRIPTION	This section defines the functionality and behavior of the service. Thus it describes concisely what the command does. It does not discuss OPTIONS or cite EXAMPLES. Interactive commands, subcommands, requests, macros, and functions are described under USAGE.
IOCTL	This section appears on pages in Section 7 only. Only the device class that supplies appropriate parameters to the ioctl(2) system call is called <code>ioctl</code> and generates its own

	<p>heading. <code>ioctl</code> calls for a specific device are listed alphabetically (on the man page for that specific device). <code>ioctl</code> calls are used for a particular class of devices all of which have an <code>io</code> ending, such as <code>mtio(7I)</code>.</p>
OPTIONS	<p>This section lists the command options with a concise summary of what each option does. The options are listed literally and in the order they appear in the SYNOPSIS section. Possible arguments to options are discussed under the option, and where appropriate, default values are supplied.</p>
OPERANDS	<p>This section lists the command operands and describes how they affect the actions of the command.</p>
OUTPUT	<p>This section describes the output – standard output, standard error, or output files – generated by the command.</p>
RETURN VALUES	<p>If the man page documents functions that return values, this section lists these values and describes the conditions under which they are returned. If a function can return only constant values, such as 0 or -1, these values are listed in tagged paragraphs. Otherwise, a single paragraph describes the return values of each function. Functions declared void do not return values, so they are not discussed in RETURN VALUES.</p>
ERRORS	<p>On failure, most functions place an error code in the global variable <code>errno</code> indicating why they failed. This section lists alphabetically all error codes a function can generate and describes the conditions that cause each error. When more than one condition can cause the same error, each condition is described in a separate paragraph under the error code.</p>
USAGE	<p>This section lists special rules, features, and commands that require in-depth explanations. The subsections listed here are used to explain built-in functionality:</p> <ul style="list-style-type: none">CommandsModifiersVariablesExpressionsInput Grammar

EXAMPLES	This section provides examples of usage or of how to use a command or function. Wherever possible a complete example including command-line entry and machine response is shown. Whenever an example is given, the prompt is shown as <code>example%</code> , or if the user must be superuser, <code>example#</code> . Examples are followed by explanations, variable substitution rules, or returned values. Most examples illustrate concepts from the SYNOPSIS, DESCRIPTION, OPTIONS, and USAGE sections.
ENVIRONMENT VARIABLES	This section lists any environment variables that the command or function affects, followed by a brief description of the effect.
EXIT STATUS	This section lists the values the command returns to the calling program or shell and the conditions that cause these values to be returned. Usually, zero is returned for successful completion, and values other than zero for various error conditions.
FILES	This section lists all file names referred to by the man page, files of interest, and files created or required by commands. Each is followed by a descriptive summary or explanation.
ATTRIBUTES	This section lists characteristics of commands, utilities, and device drivers by defining the attribute type and its corresponding value. See attributes(5) for more information.
SEE ALSO	This section lists references to other man pages, in-house documentation, and outside publications.
DIAGNOSTICS	This section lists diagnostic messages with a brief explanation of the condition causing the error.
WARNINGS	This section lists warnings about special conditions which could seriously affect your working conditions. This is not a list of diagnostics.
NOTES	This section lists additional information that does not belong anywhere else on the page. It takes the form of an aside to the user, covering points of special interest. Critical information is never covered here.
BUGS	This section describes known bugs and, wherever possible, suggests workarounds.

REFERENCE

Networking Library Functions

Name accept – accept a connection on a socket

Synopsis `cc [flag ...] file ... -lsocket -lnsl [library ...]`
`#include <sys/types.h>`
`#include <sys/socket.h>`

```
int accept(int s, struct sockaddr *addr, socklen_t *addrlen);
```

Description The argument *s* is a socket that has been created with [socket\(3SOCKET\)](#) and bound to an address with [bind\(3SOCKET\)](#), and that is listening for connections after a call to [listen\(3SOCKET\)](#). The `accept()` function extracts the first connection on the queue of pending connections, creates a new socket with the properties of *s*, and allocates a new file descriptor, *ns*, for the socket. If no pending connections are present on the queue and the socket is not marked as non-blocking, `accept()` blocks the caller until a connection is present. If the socket is marked as non-blocking and no pending connections are present on the queue, `accept()` returns an error as described below. The `accept()` function uses the [netconfig\(4\)](#) file to determine the STREAMS device file name associated with *s*. This is the device on which the connect indication will be accepted. The accepted socket, *ns*, is used to read and write data to and from the socket that connected to *ns*. It is not used to accept more connections. The original socket (*s*) remains open for accepting further connections.

The argument *addr* is a result parameter that is filled in with the address of the connecting entity as it is known to the communications layer. The exact format of the *addr* parameter is determined by the domain in which the communication occurs.

The argument *addrlen* is a value-result parameter. Initially, it contains the amount of space pointed to by *addr*; on return it contains the length in bytes of the address returned.

The `accept()` function is used with connection-based socket types, currently with `SOCK_STREAM`.

It is possible to [select\(3C\)](#) or [poll\(2\)](#) a socket for the purpose of an `accept()` by selecting or polling it for a read. However, this will only indicate when a connect indication is pending; it is still necessary to call `accept()`.

Return Values The `accept()` function returns `-1` on error. If it succeeds, it returns a non-negative integer that is a descriptor for the accepted socket.

Errors `accept()` will fail if:

<code>EBADF</code>	The descriptor is invalid.
<code>ECONNABORTED</code>	The remote side aborted the connection before the <code>accept()</code> operation completed.
<code>EFAULT</code>	The <i>addr</i> parameter or the <i>addrlen</i> parameter is invalid.
<code>EINTR</code>	The <code>accept()</code> attempt was interrupted by the delivery of a signal.

EMFILE	The per-process descriptor table is full.
ENODEV	The protocol family and type corresponding to <code>s</code> could not be found in the <code>netconfig</code> file.
ENOMEM	There was insufficient user memory available to complete the operation.
ENOSR	There were insufficient STREAMS resources available to complete the operation.
ENOTSOCK	The descriptor does not reference a socket.
EOPNOTSUPP	The referenced socket is not of type <code>SOCK_STREAM</code> .
EPROTO	A protocol error has occurred; for example, the STREAMS protocol stack has not been initialized or the connection has already been released.
EWOULDBLOCK	The socket is marked as non-blocking and no connections are present to be accepted.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Safe

See Also [poll\(2\)](#), [bind\(3SOCKET\)](#), [connect\(3SOCKET\)](#), [listen\(3SOCKET\)](#), [select\(3C\)](#), [socket.h\(3HEAD\)](#), [socket\(3SOCKET\)](#), [netconfig\(4\)](#), [attributes\(5\)](#)

Name accept – accept a new connection on a socket

Synopsis `cc [flag ...] file ... -lxnet [library ...]`
`#include <sys/socket.h>`

```
int accept(int socket, struct sockaddr *restrict address,
           socklen_t *restrict address_len);
```

Description The `accept()` function extracts the first connection on the queue of pending connections, creates a new socket with the same socket type protocol and address family as the specified socket, and allocates a new file descriptor for that socket.

The function takes the following arguments:

<i>socket</i>	Specifies a socket that was created with socket(3XNET) , has been bound to an address with bind(3XNET) , and has issued a successful call to listen(3XNET) .
<i>address</i>	Either a null pointer, or a pointer to a <code>sockaddr</code> structure where the address of the connecting socket will be returned.
<i>address_len</i>	Points to a <code>socklen_t</code> which on input specifies the length of the supplied <code>sockaddr</code> structure, and on output specifies the length of the stored address.

If *address* is not a null pointer, the address of the peer for the accepted connection is stored in the `sockaddr` structure pointed to by *address*, and the length of this address is stored in the object pointed to by *address_len*.

If the actual length of the address is greater than the length of the supplied `sockaddr` structure, the stored address will be truncated.

If the protocol permits connections by unbound clients, and the peer is not bound, then the value stored in the object pointed to by *address* is unspecified.

If the listen queue is empty of connection requests and `O_NONBLOCK` is not set on the file descriptor for the socket, `accept()` will block until a connection is present. If the [listen\(3XNET\)](#) queue is empty of connection requests and `O_NONBLOCK` is set on the file descriptor for the socket, `accept()` will fail and set `errno` to `EAGAIN` or `EWOULDBLOCK`.

The accepted socket cannot itself accept more connections. The original socket remains open and can accept more connections.

Usage When a connection is available, [select\(3C\)](#) will indicate that the file descriptor for the socket is ready for reading.

Return Values Upon successful completion, `accept()` returns the nonnegative file descriptor of the accepted socket. Otherwise, `-1` is returned and `errno` is set to indicate the error.

Errors The `accept()` function will fail if:

EAGAIN	
EWOULDBLOCK	O_NONBLOCK is set for the socket file descriptor and no connections are present to be accepted.
EBADF	The <i>socket</i> argument is not a valid file descriptor.
ECONNABORTED	A connection has been aborted.
EFAULT	The <i>address</i> or <i>address_len</i> parameter can not be accessed or written.
EINTR	The <code>accept()</code> function was interrupted by a signal that was caught before a valid connection arrived.
EINVAL	The <i>socket</i> is not accepting connections.
EMFILE	OPEN_MAX file descriptors are currently open in the calling process.
ENFILE	The maximum number of file descriptors in the system are already open.
ENOTSOCK	The <i>socket</i> argument does not refer to a socket.
EOPNOTSUPP	The socket type of the specified socket does not support accepting connections.

The `accept()` function may fail if:

ENOBUFS	No buffer space is available.
ENOMEM	There was insufficient memory available to complete the operation.
ENOSR	There was insufficient STREAMS resources available to complete the operation.
EPROTO	A protocol error has occurred; for example, the STREAMS protocol stack has not been initialized.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also [bind\(3XNET\)](#), [connect\(3XNET\)](#), [listen\(3XNET\)](#), [socket\(3XNET\)](#), [attributes\(5\)](#), [standards\(5\)](#)

Name ber_decode, ber_alloc_t, ber_free, ber_bvdup, ber_init, ber_flatten, ber_get_next, ber_skip_tag, ber_peek_tag, ber_scanf, ber_get_int, ber_get_stringa, ber_get_stringal, ber_get_stringb, ber_get_null, ber_get_boolean, ber_get_bitstring, ber_first_element, ber_next_element, ber_bvfree, ber_bvecfree – Basic Encoding Rules library decoding functions

Synopsis `cc[flag...] file... -lldap[library...]`

```
#include <lber.h>

BerElement *ber_alloc_t(int options);

struct berval *ber_bvdup(struct berval *bv);

void ber_free(BerElement *ber, int freebuf);

BerElement *ber_init(struct berval *bv);

int ber_flatten(BerElement *ber, struct berval **bvPtr);

ber_get_next(Sockbuf *sb, unsigned long *len, char *bv_val);

ber_skip_tag(BerElement **ber, unsigned long **len);

ber_peek_tag(BerElement **ber, unsigned long **len);

ber_get_int(BerElement **ber, long **num);

ber_get_stringb(BerElement **ber, char **buf, unsigned long **len);

ber_get_stringa(BerElement **ber, char ***buf);

ber_get_stringal(BerElement **ber, struct berval ***bv);

ber_get_null(BerElement **ber);

ber_get_boolean(BerElement **ber, int **bool);

ber_get_bitstringa(BerElement **ber, char ***buf,
    unsigned long **blen);

ber_first_element(BerElement **ber, unsigned long **len,
    char ***cookie);

ber_next_element(BerElement **ber, unsigned long **len, char **cookie);

ber_scanf(BerElement **ber, char **fmt [, arg...]);

ber_bvfree(struct berval *bv);

ber_bvecfree(struct berval ***bvec);
```

Description These functions provide a subfunction interface to a simplified implementation of the Basic Encoding Rules of ASN.1. The version of BER these functions support is the one defined for the LDAP protocol. The encoding rules are the same as BER, except that only definite form lengths are used, and bitstrings and octet strings are always encoded in primitive form. In addition, these lightweight BER functions restrict tags and class to fit in a single octet (this

means the actual tag must be less than 31). When a “tag” is specified in the descriptions below, it refers to the tag, class, and primitive or constructed bit in the first octet of the encoding. This man page describes the decoding functions in the lber library. See [ber_encode\(3LDAP\)](#) for details on the corresponding encoding functions.

Normally, the only functions that need be called by an application are `ber_get_next()` to get the next BER element and `ber_scanf()` to do the actual decoding. In some cases, `ber_peek_tag()` may also need to be called in normal usage. The other functions are provided for those applications that need more control than `ber_scanf()` provides. In general, these functions return the tag of the element decoded, or `-1` if an error occurred.

The `ber_get_next()` function is used to read the next BER element from the given Sockbuf, *sb*. A Sockbuf consists of the descriptor (usually socket, but a file descriptor works just as well) from which to read, and a BerElement structure used to maintain a buffer. On the first call, the *sb_ber* struct should be zeroed. It strips off and returns the leading tag byte, strips off and returns the length of the entire element in *len*, and sets up *ber* for subsequent calls to `ber_scanf()`, and all to decode the element.

The `ber_scanf()` function is used to decode a BER element in much the same way that [scanf\(3C\)](#) works. It reads from *ber*, a pointer to a BerElement such as returned by `ber_get_next()`, interprets the bytes according to the format string *fmt*, and stores the results in its additional arguments. The format string contains conversion specifications which are used to direct the interpretation of the BER element. The format string can contain the following characters.

- a Octet string. A `char **` should be supplied. Memory is allocated, filled with the contents of the octet string, null-terminated, and returned in the parameter.
- s Octet string. A `char *` buffer should be supplied, followed by a pointer to an integer initialized to the size of the buffer. Upon return, the null-terminated octet string is put into the buffer, and the integer is set to the actual size of the octet string.
- O Octet string. A struct `ber_val **` should be supplied, which upon return points to a memory allocated struct `berval` containing the octet string and its length. `ber_bvfree()` can be called to free the allocated memory.
- b Boolean. A pointer to an integer should be supplied.
- i Integer. A pointer to an integer should be supplied.
- B Bitstring. A `char **` should be supplied which will point to the memory allocated bits, followed by an unsigned long `*`, which will point to the length (in bits) of the bitstring returned.
- n Null. No parameter is required. The element is simply skipped if it is recognized.
- v Sequence of octet strings. A `char ***` should be supplied, which upon return points to a memory allocated null-terminated array of `char *`'s containing the octet strings. NULL is returned if the sequence is empty.

- V Sequence of octet strings with lengths. A struct `berval ***` should be supplied, which upon return points to a memory allocated, null-terminated array of struct `berval *`'s containing the octet strings and their lengths. NULL is returned if the sequence is empty. `ber_bvecfree()` can be called to free the allocated memory.
- x Skip element. The next element is skipped.
- { Begin sequence. No parameter is required. The initial sequence tag and length are skipped.
- } End sequence. No parameter is required and no action is taken.
- [Begin set. No parameter is required. The initial set tag and length are skipped.
-] End set. No parameter is required and no action is taken.

The `ber_get_int()` function tries to interpret the next element as an integer, returning the result in *num*. The tag of whatever it finds is returned on success, -1 on failure.

The `ber_get_stringb()` function is used to read an octet string into a preallocated buffer. The *len* parameter should be initialized to the size of the buffer, and will contain the length of the octet string read upon return. The buffer should be big enough to take the octet string value plus a terminating NULL byte.

The `ber_get_stringa()` function is used to allocate memory space into which an octet string is read.

The `ber_get_stringal()` function is used to allocate memory space into which an octet string and its length are read. It takes a struct `berval **`, and returns the result in this parameter.

The `ber_get_null()` function is used to read a NULL element. It returns the tag of the element it skips over.

The `ber_get_boolean()` function is used to read a boolean value. It is called the same way that `ber_get_int()` is called.

The `ber_get_bitstringa()` function is used to read a bitstring value. It takes a `char **` which will hold the allocated memory bits, followed by an unsigned long *, which will point to the length (in bits) of the bitstring returned.

The `ber_first_element()` function is used to return the tag and length of the first element in a set or sequence. It also returns in *cookie* a magic cookie parameter that should be passed to subsequent calls to `ber_next_element()`, which returns similar information.

`ber_alloc_t()` constructs and returns `BerElement`. A null pointer is returned on error. The options field contains a bitwise-or of options which are to be used when generating the encoding of this `BerElement`. One option is defined and must always be supplied:

```
#define LBER_USE_DER 0x01
```

When this option is present, lengths will always be encoded in the minimum number of octets. Note that this option does not cause values of sets and sequences to be rearranged in tag and byte order, so these functions are not suitable for generating DER output as defined in X.509 and X.680

The `ber_init` function constructs a `BerElement` and returns a new `BerElement` containing a copy of the data in the `bv` argument. `ber_init` returns the null pointer on error.

`ber_free()` frees a `BerElement` which is returned from the API calls `ber_alloc_t()` or `ber_init()`. Each `BerElement` must be freed by the caller. The second argument *freebuf* should always be set to 1 to ensure that the internal buffer used by the BER functions is freed as well as the `BerElement` container itself.

`ber_bvdup()` returns a copy of a *berval*. The *bv_val* field in the returned *berval* points to a different area of memory as the *bv_val* field in the argument *berval*. The null pointer is returned on error (that is, is out of memory).

The `ber_flatten` routine allocates a struct *berval* whose contents are BER encoding taken from the *ber* argument. The *bvPtr* pointer points to the returned *berval*, which must be freed using `ber_bvfree()`. This routine returns 0 on success and -1 on error.

Examples **EXAMPLE 1** Assume the variable *ber* contains a lightweight BER encoding of the following ASN.1 object:

```
AlmostASearchRequest := SEQUENCE {
    baseObject      DistinguishedName,
    scope           ENUMERATED {
        baseObject      (0),
        singleLevel     (1),
        wholeSubtree    (2)
    },
    derefAliases     ENUMERATED {
        neverDerefaliases (0),
        derefInSearching  (1),
        derefFindingBaseObj (2),
        alwaysDerefAliases (3N)
    },
    sizelimit        INTEGER (0 .. 65535),
    timelimit        INTEGER (0 .. 65535),
    attrsOnly        BOOLEAN,
    attributes       SEQUENCE OF AttributeType
}
```

EXAMPLE 2 The element can be decoded using `ber_scanf()` as follows.

```
int    scope, ali, size, time, attrsonly;
char   *dn, **attrs;
```

EXAMPLE 2 The element can be decoded using `ber_scanf()` as follows. *(Continued)*

```
if ( ber_scanf( ber, "{aiiiib{v}}", &dn, &scope, &ali,
               &size, &time, &attrsonly, &attrs ) == -1 )
    /* error */
else
    /* success */
```

Errors If an error occurs during decoding, generally these functions return `-1`.

Notes The return values for all of these functions are declared in the `<lber.h>` header file. Some functions may allocate memory which must be freed by the calling application.

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [ber_encode\(3LDAP\)](#)

Yeong, W., Howes, T., and Hardcastle-Kille, S., “Lightweight Directory Access Protocol”, OSI-DS-26, April 1992.

Information Processing - Open Systems Interconnection - Model and Notation - Service Definition - Specification of Basic Encoding Rules for Abstract Syntax Notation One, International Organization for Standardization, International Standard 8825.

Name ber_encode, ber_alloc, ber_printf, ber_put_int, ber_put_ostring, ber_put_string, ber_put_null, ber_put_boolean, ber_put_bitstring, ber_start_seq, ber_start_set, ber_put_seq, ber_put_set – simplified Basic Encoding Rules library encoding functions

Synopsis cc[*flag...*] *file...* -lldap[*library...*]
#include <lber.h>

```
BerElement *ber_alloc();

ber_printf(BerElement *ber, char **fmt[, arg... ]);

ber_put_int(BerElement *ber, long num, char tag);

ber_put_ostring(BerElement *ber, char **str, unsigned long len,
                char tag);

ber_put_string(BerElement *ber, char **str, char tag);

ber_put_null(BerElement *ber, char tag);

ber_put_boolean(BerElement *ber, int bool, char tag);

ber_put_bitstring(BerElement *ber, char *str, int blen, char tag);

ber_start_seq(BerElement *ber, char tag);

ber_start_set(BerElement *ber, char tag);

ber_put_seq(BerElement *ber);

ber_put_set(BerElement *ber);
```

Description These functions provide a subfunction interface to a simplified implementation of the Basic Encoding Rules of ASN.1. The version of BER these functions support is the one defined for the LDAP protocol. The encoding rules are the same as BER, except that only definite form lengths are used, and bitstrings and octet strings are always encoded in primitive form. In addition, these lightweight BER functions restrict tags and class to fit in a single octet (this means the actual tag must be less than 31). When a “tag” is specified in the descriptions below, it refers to the tag, class, and primitive or constructed bit in the first octet of the encoding. This man page describes the encoding functions in the lber library. See [ber_decode\(3LDAP\)](#) for details on the corresponding decoding functions.

Normally, the only functions that need be called by an application are `ber_alloc()`, to allocate a BER element, and `ber_printf()` to do the actual encoding. The other functions are provided for those applications that need more control than `ber_printf()` provides. In general, these functions return the length of the element encoded, or -1 if an error occurred.

The `ber_alloc()` function is used to allocate a new BER element.

The `ber_printf()` function is used to encode a BER element in much the same way that `sprintf(3S)` works. One important difference, though, is that some state information is kept with the *ber* parameter so that multiple calls can be made to `ber_printf()` to append things to the end of the BER element. `Ber_printf()` writes to *ber*, a pointer to a `BerElement` such as

returned by `ber_alloc()`. It interprets and formats its arguments according to the format string `fmt`. The format string can contain the following characters:

- `b` Boolean. An integer parameter should be supplied. A boolean element is output.
- `B` Bitstring. A `char *` pointer to the start of the bitstring is supplied, followed by the number of bits in the bitstring. A bitstring element is output.
- `i` Integer. An integer parameter should be supplied. An integer element is output.
- `n` Null. No parameter is required. A null element is output.
- `o` Octet string. A `char *` is supplied, followed by the length of the string pointed to. An octet string element is output.
- `O` Octet string. A `struct berval *` is supplied. An octet string element is output.
- `s` Octet string. A null-terminated string is supplied. An octet string element is output, not including the trailing null octet.
- `t` Tag. An int specifying the tag to give the next element is provided. This works across calls.
- `v` Several octet strings. A null-terminated array of `char *` is supplied. Note that a construct like `{v}` is required to get an actual sequence of octet strings.
- `{` Begin sequence. No parameter is required.
- `}` End sequence. No parameter is required.
- `[` Begin set. No parameter is required.
- `]` End set. No parameter is required.

The `ber_put_int()` function writes the integer element *num* to the BER element *ber*.

The `ber_put_boolean()` function writes the boolean value given by *bool* to the BER element.

The `ber_put_bitstring()` function writes *blen* bits starting at *str* as a bitstring value to the given BER element. Note that *blen* is the length in *bits* of the bitstring.

The `ber_put_ostring()` function writes *len* bytes starting at *str* to the BER element as an octet string.

The `ber_put_string()` function writes the null-terminated string (minus the terminating `"`) to the BER element as an octet string.

The `ber_put_null()` function writes a NULL element to the BER element.

The `ber_start_seq()` function is used to start a sequence in the BER element. The `ber_start_set()` function works similarly. The end of the sequence or set is marked by the nearest matching call to `ber_put_seq()` or `ber_put_set()`, respectively.

The `ber_first_element()` function is used to return the tag and length of the first element in a set or sequence. It also returns in *cookie* a magic cookie parameter that should be passed to subsequent calls to `ber_next_element()`, which returns similar information.

Examples **EXAMPLE 1** Assuming the following variable declarations, and that the variables have been assigned appropriately, an BER encoding of the following ASN.1 object:

```
AlmostASearchRequest := SEQUENCE {
    baseObject      DistinguishedName,
    scope           ENUMERATED {
        baseObject      (0),
        singleLevel     (1),
        wholeSubtree    (2)
    },
    derefAliases     ENUMERATED {
        neverDerefAliases (0),
        derefInSearching  (1),
        derefFindingBaseObj (2),
        alwaysDerefAliases (3N)
    },
    sizelimit        INTEGER (0 .. 65535),
    timelimit        INTEGER (0 .. 65535),
    attrsOnly        BOOLEAN,
    attributes       SEQUENCE OF AttributeType
}
```

can be achieved like so:

```
int    scope, ali, size, time, attrsonly;
char   *dn, **attrs;

/* ... fill in values ... */
if ( (ber = ber_alloc( )) == NULLBER )
/* error */

if ( ber_printf( ber, "{iiiiib{v}}", dn, scope, ali,
    size, time, attrsonly, attrs ) == -1 )
/* error */
else
/* success */
```

Return Values If an error occurs during encoding, `ber_alloc()` returns NULL; other functions generally return -1.

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Committed

See Also [ber_decode\(3LDAP\)](#), [attributes\(5\)](#)

Yeong, W., Howes, T., and Hardcastle-Kille, S., “Lightweight Directory Access Protocol”, OSI-DS-26, April 1992.

Information Processing - Open Systems Interconnection - Model and Notation - Service Definition - Specification of Basic Encoding Rules for Abstract Syntax Notation One, International Organization for Standardization, International Standard 8825.

Notes The return values for all of these functions are declared in `<ldap.h>`.

Name bind – bind a name to a socket

Synopsis `cc [flag ...] file ... -lsocket -lnsl [library ...]`
`#include <sys/types.h>`
`#include <sys/socket.h>`

```
int bind(int s, const struct sockaddr *name, int namelen);
```

Description The `bind()` function assigns a name to an unnamed socket. When a socket is created with `socket(3SOCKET)`, it exists in a name space (address family) but has no name assigned. The `bind()` function requests that the name pointed to by *name* be assigned to the socket.

Return Values Upon successful completion 0 is returned. Otherwise, -1 is returned and `errno` is set to indicate the error.

Errors The `bind()` function will fail if:

EACCES	The requested address is protected, and {PRIV_NET_PRIVADDR} is not asserted in the effective set of the current process.
EADDRINUSE	The specified address is already in use.
EADDRNOTAVAIL	The specified address is not available on the local machine.
EBADF	<i>s</i> is not a valid descriptor.
EINVAL	<i>namelen</i> is not the size of a valid address for the specified address family.
EINVAL	The socket is already bound to an address.
ENOSR	There were insufficient STREAMS resources for the operation to complete.
ENOTSOCK	<i>s</i> is a descriptor for a file, not a socket.

The following errors are specific to binding names in the UNIX domain:

EACCES	Search permission is denied for a component of the path prefix of the pathname in <i>name</i> .
EIO	An I/O error occurred while making the directory entry or allocating the inode.
EISDIR	A null pathname was specified.
ELOOP	Too many symbolic links were encountered in translating the pathname in <i>name</i> .
ENOENT	A component of the path prefix of the pathname in <i>name</i> does not exist.
ENOTDIR	A component of the path prefix of the pathname in <i>name</i> is not a directory.
EROFS	The inode would reside on a read-only file system.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Safe

See Also [unlink\(2\)](#), [socket\(3SOCKET\)](#), [attributes\(5\)](#), [privileges\(5\)](#), [socket.h\(3HEAD\)](#)

Notes Binding a name in the UNIX domain creates a socket in the file system that must be deleted by the caller when it is no longer needed by using [unlink\(2\)](#).

The rules used in name binding vary between communication domains.

Name bind – bind a name to a socket

Synopsis `cc [flag ...] file ... -lxnet [library ...]`
`#include <sys/socket.h>`

```
int bind(int socket, const struct sockaddr *address,
        socklen_t address_len);
```

Description The `bind()` function assigns an *address* to an unnamed socket. Sockets created with [socket\(3XNET\)](#) function are initially unnamed. They are identified only by their address family.

The function takes the following arguments:

<i>socket</i>	Specifies the file descriptor of the socket to be bound.
<i>address</i>	Points to a <code>sockaddr</code> structure containing the address to be bound to the socket. The length and format of the address depend on the address family of the socket.
<i>address_len</i>	Specifies the length of the <code>sockaddr</code> structure pointed to by the <i>address</i> argument.

The socket in use may require the process to have appropriate privileges to use the `bind()` function.

Usage An application program can retrieve the assigned socket name with the [getsockname\(3XNET\)](#) function.

Return Values Upon successful completion, `bind()` returns 0. Otherwise, `-1` is returned and `errno` is set to indicate the error.

Errors The `bind()` function will fail if:

EADDRINUSE	The specified address is already in use.
EADDRNOTAVAIL	The specified address is not available from the local machine.
EAFNOSUPPORT	The specified address is not a valid address for the address family of the specified socket.
EBADF	The <i>socket</i> argument is not a valid file descriptor.
EFAULT	The <i>address</i> argument can not be accessed.
EINVAL	The socket is already bound to an address, and the protocol does not support binding to a new address; or the socket has been shut down.
ENOTSOCK	The <i>socket</i> argument does not refer to a socket.

EOPNOTSUPP The socket type of the specified socket does not support binding to an address.

If the address family of the socket is AF_UNIX, then bind() will fail if:

EACCES A component of the path prefix denies search permission, or the requested name requires writing in a directory with a mode that denies write permission.

EDESTADDRREQ
EISDIR The *address* argument is a null pointer.

EIO An I/O error occurred.

ELOOP Too many symbolic links were encountered in translating the pathname in *address*.

ENAMETOOLONG A component of a pathname exceeded NAME_MAX characters, or an entire pathname exceeded PATH_MAX characters.

ENOENT A component of the pathname does not name an existing file or the pathname is an empty string.

ENOTDIR A component of the path prefix of the pathname in *address* is not a directory.

EROFS The name would reside on a read-only filesystem.

The bind() function may fail if:

EACCES The specified address is protected, and {PRIV_NET_PRIVADOR} is not asserted in the effective set of the current process.

EINVAL The *address_len* argument is not a valid length for the address family.

EISCONN The socket is already connected.

ENAMETOOLONG Pathname resolution of a symbolic link produced an intermediate result whose length exceeds PATH_MAX.

ENOBUFS Insufficient resources were available to complete the call.

ENOSR There were insufficient STREAMS resources for the operation to complete.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also `connect(3XNET)`, `getsockname(3XNET)`, `listen(3XNET)`, `socket(3XNET)`,
`attributes(5)`, `privileges(5)`, `standards(5)`

Name byteorder, htonl, htons, ntohl, ntohs – convert values between host and network byte order

Synopsis

```
cc [ flag... ] file... -lsocket -lnsl [ library... ]
#include <sys/types.h>
#include <netinet/in.h>
#include <inttypes.h>

uint32_t htonl(uint32_t hostlong);
uint16_t htons(uint16_t hostshort);
uint32_t ntohl(uint32_t netlong);
uint16_t ntohs(uint16_t netshort);
```

Description These routines convert 16-bit and 32-bit quantities between network byte order and host byte order. On some architectures these routines are defined as NULL macros in the include file `<netinet/in.h>`. On other architectures, the routines are functional when the host byte order is different from network byte order.

The routines are most often used in conjunction with Internet addresses and ports as returned by `gethostent()` and `getservent()`. See [gethostbyname\(3NSL\)](#) and [getservbyname\(3SOCKET\)](#).

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Safe

See Also [gethostbyname\(3NSL\)](#), [getservbyname\(3SOCKET\)](#), [inet.h\(3HEAD\)](#), [attributes\(5\)](#)

Name cldap_close – dispose of connectionless LDAP pointer

Synopsis cc[*flag...*] *file...* -lldap[*library...*]

```
#include <lber.h>
#include <ldap.h>

void cldap_close(LDAP *ld);
```

Description The `clldap_close()` function disposes of memory allocated by `clldap_open(3LDAP)`. It should be called when all CLDAP communication is complete.

Parameters *ld* The LDAP pointer returned by a previous call to `clldap_open(3LDAP)`.

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit) SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [ldap\(3LDAP\)](#), [clldap_open\(3LDAP\)](#), [clldap_search_s\(3LDAP\)](#),
[clldap_setretryinfo\(3LDAP\)](#)

Name cldap_open – LDAP connectionless communication preparation

Synopsis cc[*flag...*] *file...* -lldap[*library...*]

```
#include <lber.h>
#include <ldap.h>
```

```
LDAP *clldap_open(char *host, int port);
```

Parameters *host* The name of the host on which the LDAP server is running.
port The port number to connect.

Description The cldap_open() function is called to prepare for connectionless LDAP communication (over [udp\(7P\)](#)). It allocates an LDAP structure which is passed to future search requests.

If the default IANA-assigned port of 389 is desired, LDAP_PORT should be specified for *port*. *host* can contain a space-separated list of hosts or addresses to try. cldap_open() returns a pointer to an LDAP structure, which should be passed to subsequent calls to [clldap_search_s\(3LDAP\)](#), [clldap_setretryinfo\(3LDAP\)](#), and [clldap_close\(3LDAP\)](#). Certain fields in the LDAP structure can be set to indicate size limit, time limit, and how aliases are handled during operations. See [ldap_open\(3LDAP\)](#) and <ldap.h> for more details.

Errors If an error occurs, cldap_open() will return NULL and errno will be set appropriately.

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [ldap\(3LDAP\)](#), [clldap_search_s\(3LDAP\)](#), [clldap_setretryinfo\(3LDAP\)](#), [clldap_close\(3LDAP\)](#), [attributes\(5\)](#), [udp\(7P\)](#)

Name cldap_search_s – connectionless LDAP search

Synopsis cc[*flag...*] *file...* -lldap[*library...*]

```
#include <lber.h>
```

```
#include <ldap.h>
```

```
int cldap_search_s(LDAP *ld, char *base, int scope, char *filter,
                  char *attrs, int attrsonly, LDAPMessage **res, char *logdn);
```

Description The `clldap_search_s()` function performs an LDAP search using the Connectionless LDAP (CLDAP) protocol.

`clldap_search_s()` has parameters and behavior identical to that of `ldap_search_s(3LDAP)`, except for the addition of the `logdn` parameter. `logdn` should contain a distinguished name to be used only for logging purposed by the LDAP server. It should be in the text format described by *RFC 1779, A String Representation of Distinguished Names*.

Retransmission Algorithm `clldap_search_s()` operates using the CLDAP protocol over [udp\(7P\)](#). Since UDP is a non-reliable protocol, a retry mechanism is used to increase reliability. The [clldap_setretryinfo\(3LDAP\)](#) function can be used to set two retry parameters: *tries*, a count of the number of times to send a search request and *timeout*, an initial timeout that determines how long to wait for a response before re-trying. *timeout* is specified seconds. These values are stored in the `ld_cldaptries` and `ld_cldaptimeout` members of the `ld` LDAP structure, and the default values set in [ldap_open\(3LDAP\)](#) are 4 and 3 respectively. The retransmission algorithm used is:

- Step 1 Set the current timeout to `ld_cldaptimeout` seconds, and the current LDAP server address to the first LDAP server found during the [ldap_open\(3LDAP\)](#) call.
- Step 2 Send the search request to the current LDAP server address.
- Step 3 Set the wait timeout to the current timeout divided by the number of server addresses found during [ldap_open\(3LDAP\)](#) or to one second, whichever is larger. Wait at most that long for a response; if a response is received, STOP. Note that the wait timeout is always rounded down to the next lowest second.
- Step 4 Repeat steps 2 and 3 for each LDAP server address.
- Step 5 Set the current timeout to twice its previous value and repeat Steps 2 through 5 a maximum of *tries* times.

Examples Assume that the default values for *tries* and *timeout* of 4 tries and 3 seconds are used. Further, assume that a space-separated list of two hosts, each with one address, was passed to [clldap_open\(3LDAP\)](#). The pattern of requests sent will be (stopping as soon as a response is received):

Time	Search Request Sent To:
+0	Host A try 1
+1 (0+3/2)	Host B try 1

```
+2  (1+3/2)      Host A try 2
+5  (2+6/2)      Host B try 2
+8  (5+6/2)      Host A try 3
+14 (8+12/2)     Host B try 3
+20 (14+12/2)    Host A try 4
+32 (20+24/2)    Host B try 4
+44 (20+24/2)    (give up - no response)
```

Errors cldap_search_s() returns LDAP_SUCCESS if a search was successful and the appropriate LDAP error code otherwise. See [ldap_error\(3LDAP\)](#) for more information.

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [ldap\(3LDAP\)](#), [ldap_error\(3LDAP\)](#), [ldap_search_s\(3LDAP\)](#), [clldap_open\(3LDAP\)](#), [clldap_setretryinfo\(3LDAP\)](#), [clldap_close\(3LDAP\)](#), [attributes\(5\)](#), [udp\(7P\)](#)

Name cldap_setretryinfo – set connectionless LDAP request retransmission parameters

Synopsis cc[*flag...*] *file...* -lldap[*library...*]

```
#include <lber.h>
```

```
#include <ldap.h>
```

```
void cldap_setretryinfo(LDAP *ld, int tries, int timeout);
```

Parameters *ld* LDAP pointer returned from a previous call to [clldap_open\(3LDAP\)](#).

tries Maximum number of times to send a request.

timeout Initial time, in seconds, to wait before re-sending a request.

Description The `clldap_setretryinfo()` function is used to set the CLDAP request retransmission behavior for future [clldap_search_s\(3LDAP\)](#) calls. The default values (set by [clldap_open\(3LDAP\)](#)) are 4 tries and 3 seconds between tries. See [clldap_search_s\(3LDAP\)](#) for a complete description of the retransmission algorithm used.

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit) SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [ldap\(3LDAP\)](#), [clldap_open\(3LDAP\)](#), [clldap_search_s\(3LDAP\)](#), [clldap_close\(3LDAP\)](#), [attributes\(5\)](#)

Name connect – initiate a connection on a socket

Synopsis `cc [flag ...] file ... -lsocket -lnsl [library ...]`
`#include <sys/types.h>`
`#include <sys/socket.h>`

```
int connect(int s, const struct sockaddr *name, int namelen);
```

Description The parameter *s* is a socket. If it is of type `SOCK_DGRAM`, `connect()` specifies the peer with which the socket is to be associated. This address is the address to which datagrams are to be sent if a receiver is not explicitly designated. This address is the only address from which datagrams are to be received. If the socket *s* is of type `SOCK_STREAM`, `connect()` attempts to make a connection to another socket. The other socket is specified by *name*. *name* is an address in the communication space of the socket. Each communication space interprets the *name* parameter in its own way. If *s* is not bound, then *s* will be bound to an address selected by the underlying transport provider. Generally, stream sockets can successfully `connect()` only once. Datagram sockets can use `connect()` multiple times to change their association. Datagram sockets can dissolve the association by connecting to a null address.

Return Values If the connection or binding succeeds, 0 is returned. Otherwise, -1 is returned, `errno` is set to indicate the error, and state of the socket is unspecified. Applications should close the file descriptor and create a new socket before attempting to reconnect.

Errors The call fails if:

EACCES	Search permission is denied for a component of the path prefix of the pathname in <i>name</i> .
EADDRINUSE	The address is already in use.
EADDRNOTAVAIL	The specified address is not available.
EAFNOSUPPORT	Addresses in the specified address family cannot be used with this socket.
EALREADY	The socket is non-blocking, and a previous connection attempt has not yet been completed.
EBADF	<i>s</i> is not a valid descriptor.
ECONNREFUSED	The attempt to connect was forcefully rejected.
EINPROGRESS	The socket is non-blocking, and the connection cannot be completed immediately. You can use select(3C) to complete the connection by selecting the socket for writing.
EINTR	The connection attempt was interrupted before any data arrived by the delivery of a signal. The connection, however, will be established asynchronously.
EINVAL	<i>namelen</i> is not the size of a valid address for the specified address family.

EIO	An I/O error occurred while reading from or writing to the file system.
EISCONN	The socket is already connected.
ELOOP	Too many symbolic links were encountered in translating the pathname in <i>name</i> .
ENETUNREACH	The network is not reachable from this host.
EHOSTUNREACH	The remote host is not reachable from this host.
ENOENT	A component of the path prefix of the pathname in <i>name</i> does not exist.
ENOENT	The socket referred to by the pathname in <i>name</i> does not exist.
ENOSR	There were insufficient STREAMS resources available to complete the operation.
ENXIO	The server exited before the connection was complete.
ETIMEDOUT	Connection establishment timed out without establishing a connection.
EWOULDBLOCK	The socket is marked as non-blocking, and the requested operation would block.

The following errors are specific to connecting names in the UNIX domain. These errors might not appear in future versions of the UNIX IPC domain.

ENOTDIR	A component of the path prefix of the pathname in <i>name</i> is not a directory.
ENOTSOCK	<i>s</i> is not a socket.
ENOTSOCK	<i>name</i> is not a socket.
EPROTOTYPE	The file that is referred to by <i>name</i> is a socket of a type other than type <i>s</i> . For example, <i>s</i> is a SOCK_DGRAM socket, while <i>name</i> refers to a SOCK_STREAM socket.

Usage If `connect ()` fails, the state of the socket is unspecified. Portable applications should close the file descriptor and create a new socket before attempting to reconnect.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Safe

See Also [close\(2\)](#), [accept\(3SOCKET\)](#), [getsockname\(3SOCKET\)](#), [select\(3C\)](#), [socket\(3SOCKET\)](#), [socket.h\(3HEAD\)](#), [attributes\(5\)](#)

Name connect – connect a socket

Synopsis `cc [flag ...] file ... -lxnet [library ...]
#include <sys/socket.h>`

```
int connect(int socket, const struct sockaddr *address,  
            socklen_t address_len);
```

Description The `connect()` function requests a connection to be made on a socket. The function takes the following arguments:

<i>socket</i>	Specifies the file descriptor associated with the socket.
<i>address</i>	Points to a <code>sockaddr</code> structure containing the peer address. The length and format of the address depend on the address family of the socket.
<i>address_len</i>	Specifies the length of the <code>sockaddr</code> structure pointed to by the <i>address</i> argument.

If the socket has not already been bound to a local address, `connect()` will bind it to an address which, unless the socket's address family is `AF_UNIX`, is an unused local address.

If the initiating socket is not connection-mode, then `connect()` sets the socket's peer address, but no connection is made. For `SOCK_DGRAM` sockets, the peer address identifies where all datagrams are sent on subsequent [send\(3XNET\)](#) calls, and limits the remote sender for subsequent [recv\(3XNET\)](#) calls. If *address* is a null address for the protocol, the socket's peer address will be reset.

If the initiating socket is connection-mode, then `connect()` attempts to establish a connection to the address specified by the *address* argument.

If the connection cannot be established immediately and `O_NONBLOCK` is not set for the file descriptor for the socket, `connect()` will block for up to an unspecified timeout interval until the connection is established. If the timeout interval expires before the connection is established, `connect()` will fail and the connection attempt will be aborted. If `connect()` is interrupted by a signal that is caught while blocked waiting to establish a connection, `connect()` will fail and set `errno` to `EINTR`, but the connection request will not be aborted, and the connection will be established asynchronously.

If the connection cannot be established immediately and `O_NONBLOCK` is set for the file descriptor for the socket, `connect()` will fail and set `errno` to `EINPROGRESS`, but the connection request will not be aborted, and the connection will be established asynchronously. Subsequent calls to `connect()` for the same socket, before the connection is established, will fail and set `errno` to `EALREADY`.

When the connection has been established asynchronously, [select\(3C\)](#) and [poll\(2\)](#) will indicate that the file descriptor for the socket is ready for writing.

The socket in use may require the process to have appropriate privileges to use the `connect()` function.

Usage If `connect()` fails, the state of the socket is unspecified. Portable applications should close the file descriptor and create a new socket before attempting to reconnect.

Return Values Upon successful completion, `connect()` returns 0. Otherwise, `-1` is returned and `errno` is set to indicate the error.

Errors The `connect()` function will fail if:

EADDRNOTAVAIL	The specified address is not available from the local machine.
EAFNOSUPPORT	The specified address is not a valid address for the address family of the specified socket.
EALREADY	A connection request is already in progress for the specified socket.
EBADF	The <i>socket</i> argument is not a valid file descriptor.
ECONNREFUSED	The target address was not listening for connections or refused the connection request.
EFAULT	The address parameter can not be accessed.
EINPROGRESS	O_NONBLOCK is set for the file descriptor for the socket and the connection cannot be immediately established; the connection will be established asynchronously.
EINTR	The attempt to establish a connection was interrupted by delivery of a signal that was caught; the connection will be established asynchronously.
EISCONN	The specified socket is connection-mode and is already connected.
ENETUNREACH	No route to the network is present.
ENOTSOCK	The <i>socket</i> argument does not refer to a socket.
EPROTOTYPE	The specified address has a different type than the socket bound to the specified peer address.
ETIMEDOUT	The attempt to connect timed out before a connection was made.

If the address family of the socket is `AF_UNIX`, then `connect()` will fail if:

EIO	An I/O error occurred while reading from or writing to the file system.
ELOOP	Too many symbolic links were encountered in translating the pathname in <i>address</i> .
ENAMETOOLONG	A component of a pathname exceeded <code>NAME_MAX</code> characters, or an entire pathname exceeded <code>PATH_MAX</code> characters.

- ENOENT A component of the pathname does not name an existing file or the pathname is an empty string.
- ENOTDIR A component of the path prefix of the pathname in *address* is not a directory.

The connect () function may fail if:

- EACCES Search permission is denied for a component of the path prefix; or write access to the named socket is denied.
- EADDRINUSE Attempt to establish a connection that uses addresses that are already in use.
- ECONNRESET Remote host reset the connection request.
- EHOSTUNREACH The destination host cannot be reached (probably because the host is down or a remote router cannot reach it).
- EINVAL The *address_len* argument is not a valid length for the address family; or invalid address family in sockaddr structure.
- ENAMETOOLONG Pathname resolution of a symbolic link produced an intermediate result whose length exceeds PATH_MAX.
- ENETDOWN The local interface used to reach the destination is down.
- ENOBUFS No buffer space is available.
- ENOSR There were insufficient STREAMS resources available to complete the operation.
- EOPNOTSUPP The socket is listening and can not be connected.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also [close\(2\)](#), [poll\(2\)](#), [accept\(3XNET\)](#), [bind\(3XNET\)](#), [getsockname\(3XNET\)](#), [select\(3C\)](#), [send\(3XNET\)](#), [shutdown\(3XNET\)](#), [socket\(3XNET\)](#), [attributes\(5\)](#), [standards\(5\)](#)

Name dial, undial – establish an outgoing terminal line connection

Synopsis `cc [flag...] file... -lnsl [library...]`
`#include <dial.h>`

```
int dial(CALL call);
void undial(int fd);
```

Description The `dial()` function returns a file-descriptor for a terminal line open for read/write. The argument to `dial()` is a `CALL` structure (defined in the header `<dial.h>`).

When finished with the terminal line, the calling program must invoke `undial()` to release the semaphore that has been set during the allocation of the terminal device.

`CALL` is defined in the header `<dial.h>` and has the following members:

```
struct termio *attr;      /* pointer to termio attribute struct */
int             baud;      /* transmission data rate */
int             speed;     /* 212A modem: low=300, high=1200 */
char            *line;     /* device name for out-going line */
char            *telno;    /* pointer to tel-no digits string */
int             modem;     /* specify modem control for direct lines */
char            *device;   /* unused */
int             dev_len;   /* unused */
```

The `CALL` element `speed` is intended only for use with an outgoing dialed call, in which case its value should be the desired transmission baud rate. The `CALL` element `baud` is no longer used.

If the desired terminal line is a direct line, a string pointer to its device-name should be placed in the `line` element in the `CALL` structure. Legal values for such terminal device names are kept in the `Devices` file. In this case, the value of the `baud` element should be set to -1. This value will cause `dial` to determine the correct value from the `<Devices>` file.

The `telno` element is for a pointer to a character string representing the telephone number to be dialed. Such numbers may consist only of these characters:

0-9	dial 0-9
*	dail *
#	dail #
=	wait for secondary dial tone
-	delay for approximately 4 seconds

The `CALL` element `modem` is used to specify modem control for direct lines. This element should be non-zero if modem control is required. The `CALL` element `attr` is a pointer to a `termio` structure, as defined in the header `<termio.h>`. A `NULL` value for this pointer element may be

passed to the `dial` function, but if such a structure is included, the elements specified in it will be set for the outgoing terminal line before the connection is established. This setting is often important for certain attributes such as parity and baud-rate.

The CALL elements `device` and `dev_len` are no longer used. They are retained in the CALL structure for compatibility reasons.

Return Values On failure, a negative value indicating the reason for the failure will be returned. Mnemonics for these negative indices as listed here are defined in the header `<dial.h>`.

```
INTRPT  -1      /* interrupt occurred */
D_HUNG   -2      /* dialer hung (no return from write) */
NO_ANS   -3      /* no answer within 10 seconds */
ILL_BD   -4      /* illegal baud-rate */
A_PROB   -5      /* acu problem (open( ) failure) */
L_PROB   -6      /* line problem (open( ) failure) */
NO_Ldv   -7      /* can't open Devices file */
DV_NT_A  -8      /* requested device not available */
DV_NT_K  -9      /* requested device not known */
NO_BD_A -10      /* no device available at requested baud */
NO_BD_K -11      /* no device known at requested baud */
DV_NT_E -12      /* requested speed does not match */
BAD_SYS  -13     /* system not in Systems file*/
```

Files `/etc/uucp/Devices`
`/etc/uucp/Systems`
`/var/spool/uucp/LCK..tty-device`

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTETYPE	ATTRIBUTE VALUE
MT-Level	Unsafe

See Also [uucp\(1C\)](#), [alarm\(2\)](#), [read\(2\)](#), [write\(2\)](#), [attributes\(5\)](#), [termio\(7I\)](#)

Notes Including the header `<dial.h>` automatically includes the header `<termio.h>`. An [alarm\(2\)](#) system call for 3600 seconds is made (and caught) within the `dial` module for the purpose of “touching” the `LCK..` file and constitutes the device allocation semaphore for the terminal device. Otherwise, [uucp\(1C\)](#) may simply delete the `LCK..` entry on its 90-minute clean-up rounds. The alarm may go off while the user program is in a [read\(2\)](#) or [write\(2\)](#) function, causing an apparent error return. If the user program expects to be around for an hour or more, error returns from `read()`s should be checked for (`errno==EINTR`), and the `read()` possibly reissued.

This interface is unsafe in multithreaded applications. Unsafe interfaces should be called only from the main thread.

Name dlpi_arptype – convert a DLPI MAC type to an ARP hardware type

Synopsis

```
cc [ flag... ] file... -ldlpi [ library... ]  
#include <libdlpi.h>  
uint_t dlpi_arptype(uint_t dlpitype);
```

Description The `dlpi_arptype()` function converts a DLPI MAC type to an ARP hardware type defined in `<netinet/arp.h>`

Return Values Upon success, the corresponding ARP hardware type is returned. Otherwise, zero is returned.

Attributes See [attributes\(5\)](#) for description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [libdlpi\(3LIB\)](#), [attributes\(5\)](#)

Name dlpi_bind – bind DLPI handle

Synopsis `cc [flag ...] file ... -ldlpi [library ...]
#include <libdlpi.h>`

`int dlpi_bind(dlpi_handle_t dh, uint_t sap, uint_t *boundsap);`

Description The `dlpi_bind()` function attempts to bind the DLPI handle *dh* to the SAP *sap*. The handle must be in the DL_UNBOUND DLPI state and will transition to the DL_IDLE DLPI state upon success. Some DLPI MAC types can bind to a different SAP than the SAP requested, in which case *boundsap* returns the actual bound SAP. If *boundsap* is set to NULL, `dlpi_bind()` fails if the bound SAP does not match the requested SAP. If the caller does not care which SAP is chosen, DLPI_ANY_SAP can be specified for *sap*. This is primarily useful in conjunction with `dlpi_promiscon()` and DL_PROMISC_SAP to receive traffic from all SAPs. If DLPI_ANY_SAP is specified, any transmitted messages must explicitly specify a SAP using `dlpi_send(3DLPI)`.

Upon success, the caller can use `dlpi_recv(3DLPI)` to receive data matching the bound SAP that is sent to the DLPI link associated with *dh*. In addition, the caller can use `dlpi_send(3DLPI)` to send data over the bound SAP address associated with DLPI handle *dh*. The physical address of the bound handle can be retrieved with `dlpi_info(3DLPI)`.

Return Values Upon success, DLPI_SUCCESS is returned. If DL_SYSERR is returned, *errno* contains the specific UNIX system error value. Otherwise, a DLPI error value defined in <sys/dlpi.h> or an error value listed in the following section is returned.

Errors	DLPI_EBADMSG	Bad DLPI message
	DLPI_EINHANDLE	Invalid DLPI handle
	DLPI_ETIMEDOUT	DLPI operation timed out
	DLPI_EUNAVAILSAP	Unavailable DLPI SAP

Attributes See [attributes\(5\)](#) for description of the following attributes:

ATTRIBUTETYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [dlpi_info\(3DLPI\)](#), [dlpi_recv\(3DLPI\)](#), [dlpi_send\(3DLPI\)](#), [dlpi_unbind\(3DLPI\)](#), [libdlpi\(3LIB\)](#), [attributes\(5\)](#)

Name dlpi_close – close DLPI link

Synopsis `cc [flag ...] file ... -ldlpi [library ...]`
`#include <libdlpi.h>`

`void dlpi_close(dlpi_handle_t dh);`

Description The `dlpi_close()` function closes the open DLPI link instance associated with *dh* and destroys *dh* after closing the DLPI link instance.

Attributes See [attributes\(5\)](#) for description of the following attributes:

ATTRIBUTETYPE	ATTRIBUTEVALUE
Interface Stability	Committed
MT-Level	Safe

See Also [dlpi_open\(3DLPI\)](#), [libdlpi\(3LIB\)](#), [attributes\(5\)](#)

Name dlpi_disabnotify – disable DLPI notification

Synopsis `cc [flag...] file... -ldlpi [library...]
#include <libdlpi.h>`

```
int dlpi_disabnotify(dlpi_handle_t dh, dlpi_notifyid_t id,  
void **argp);
```

Description The `dlpi_disabnotify()` function disables the notification registration associated with identifier *id*. If *argp* is not NULL, the argument *arg* that was passed to [dlpi_enabnotify\(3DLPI\)](#) during registration is also returned. This operation can be performed in any DLPI state of a handle.

Closing the DLPI handle *dh* will also remove all associated callback functions.

Return Values Upon success, DLPI_SUCCESS is returned. If DL_SYSERR is returned, `errno` contains the specific UNIX system error value. Otherwise, a DLPI error value defined in `<sys/dlpi.h>` or an error value listed in the following section is returned.

Errors	DLPI_EINHANDLE	A DLPI handle is invalid.
	DLPI_EINVAL	An argument is invalid.
	DLPI_ENOTEIDINVAL	The DLPI notification ID is invalid.
	DLPI_FAILURE	The DLPI operation failed.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [dlpi_enabnotify\(3DLPI\)](#), [libdlpi\(3LIB\)](#), [attributes\(5\)](#)

Name dlpi_enabmulti, dlpi_disabmulti – enable or disable DLPI multicast messages for an address

Synopsis

```
cc [ flag... ] file... -ldlpi [ library... ]
#include <libdlpi.h>

int dlpi_enabmulti(dlpi_handle_t dh, const void *addrp,
                  size_t addrlen);

int dlpi_disabmulti(dlpi_handle_t dh, const void *addrp,
                  size_t addrlen);
```

Description The `dlpi_enabmulti()` function enables reception of messages destined to the multicast address pointed to by *addrp* on the DLPI link instance associated with DLPI handle *dh*. The DLPI link instance will pass up only those messages destined for enabled multicast addresses. This operation can be performed in any DLPI state of a handle.

The `dlpi_disabmulti()` function disables a specified multicast address pointed to by *addrp* on the DLPI link instance associated with DLPI handle *dh*. This operation can be performed in any DLPI state of a handle.

Return Values Upon success, `DLPI_SUCCESS` is returned. If `DL_SYSERR` is returned, `errno` contains the specific UNIX system error value. Otherwise, a DLPI error value defined in `<sys/dlpi.h>` or `DLPI_EINHANDLE` is returned.

- Errors**
- `DLPI_EBADMSG` Bad DLPI message
 - `DLPI_EINHANDLE` Invalid DLPI handle
 - `DLPI_EINVAL` Invalid argument
 - `DLPI_ETIMEDOUT` DLPI operation timed out

Attributes See [attributes\(5\)](#) for description of the following attributes:

ATTRIBUTETYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [libdlpi\(3LIB\)](#), [attributes\(5\)](#)

Name dlpi_enabnotify – enable DLPI notification

Synopsis `cc [flag...] file... -ldlpi [library...]
#include <libdlpi.h>`

```
int dlpi_enabnotify(dlpi_handle_t dh, uint_t notes,  
    dlpi_notifyfunc_t *funcp, void *arg, dlpi_notifyid_t *id);  
  
typedef void dlpi_notifyfunc_t(dlpi_handle_t,  
    dlpi_notifyinfo_t *, void *);
```

Description The `dlpi_enabnotify()` function enables a notification callback for the set of events specified in *notes*, which must be one or more (by a logical OR operation) of the DLPI notifications documented in [dlpi\(7P\)](#). The callback function *funcp* is registered with the DLPI handle *dh* and is invoked when *dh* receives notification for any of the specified event types. Upon success, *id* contains the identifier associated with the registration.

Multiple event types can be registered for a callback function on the DLPI handle *dh*. Similarly, the same event type can be registered multiple times on the same handle.

Once a callback has been registered, `libdlpi` will check for notification events on the DLPI handle *dh*, when exchanging DLPI messages with the underlying DLPI link instance. The [dlpi_recv\(3DLPI\)](#) function will always check for notification events, but other `libdlpi` operations may also lead to an event callback being invoked. Although there may be no expected data messages to be received, `dlpi_recv()` can be called, as shown below, with a null buffer to force a check for pending events on the underlying DLPI link instance.

```
dlpi_recv(dh, NULL, NULL, NULL, NULL, 0, NULL);
```

When a notification event of interest occurs, the callback function is invoked with the arguments *arg*, originally passed to [dlpi_disabnotify\(3DLPI\)](#), and *info*, whose members are described below.

<code>uint_t dni_note</code>	Notification event type.
<code>uint_t dni_speed</code>	Current speed, in kilobits per second, of the DLPI link. Valid only for <code>DL_NOTE_SPEED</code> .
<code>uint_t dni_size</code>	Current maximum message size, in bytes, that the DLPI link is able to accept for transmission. Valid only for <code>DL_NOTE_SDU_SIZE</code> .
<code>uchar_t dni_physaddrlen</code>	Link-layer physical address length, in bytes. Valid only for <code>DL_NOTE_PHYS_ADDR</code> .
<code>uchar_t dni_physaddr[]</code>	Link-layer physical address of DLPI link. Valid only for <code>DL_NOTE_PHYS_ADDR</code> .

The `libdlpi` library will allocate and free the `dlpi_notifyinfo_t` structure and the caller must not allocate the structure or perform any operations that require its size to be known.

The callback is not allowed to block. This precludes calling `dlpi_enabnotify()` from a callback, but non-blocking `libdlpi` functions, including `dlpi_disabnotify()`, can be called.

Return Values Upon success, `DLPI_SUCCESS` is returned. If `DL_SYSERR` is returned, `errno` contains the specific UNIX system error value. Otherwise, a DLPI error value defined in `<sys/dlpi.h>` or an error value listed in the following section is returned.

Errors	<code>DLPI_EINHANDLE</code>	A DLPI handle is invalid.
	<code>DLPI_EINVAL</code>	An argument is invalid.
	<code>DLPI_ENOTEIDINVAL</code>	The DLPI notification ID is invalid.
	<code>DLPI_ENOTENOTSUP</code>	The DLPI notification is not supported by the link.
	<code>DLPI_ETIMEDOUT</code>	The DLPI operation timed out.
	<code>DLPI_FAILURE</code>	The DLPI operation failed.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [dlpi_disabnotify\(3DLPI\)](#), [dlpi_rcv\(3DLPI\)](#), [libdlpi\(3LIB\)](#), [attributes\(5\)](#), [dlpi\(7P\)](#)

Name dlpi_fd – get DLPI file descriptor

Synopsis

```
cc [ flag ... ] file ... -ldlpi [ library ... ]
#include <libdlpi.h>

int dlpi_fd(dlpi_handle_t dh);
```

Description The `dlpi_fd()` function returns the integer file descriptor that can be used to directly operate on the open DLPI stream associated with the DLPI handle *dh*. This file descriptor can be used to perform non-DLPI operations that do not alter the state of the DLPI stream, such as waiting for an event using [poll\(2\)](#), or pushing and configuring additional STREAMS modules, such as [pfmod\(7M\)](#). If DLPI operations are directly performed on the file descriptor, or a STREAMS module is pushed that alters the message-passing interface such that DLPI operations can no longer be issued, future operations on *dh* might not behave as documented.

The returned file descriptor is managed by [libdlpi\(3LIB\)](#) and the descriptor must not be closed.

Return Values The function returns the integer file descriptor associated with the DLPI handle *dh*. If *dh* is invalid, -1 is returned.

Attributes See [attributes\(5\)](#) for description of the following attributes:

ATTRIBUTETYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [poll\(2\)](#), [libdlpi\(3LIB\)](#), [attributes\(5\)](#), [dlpi\(7P\)](#), [pfmod\(7M\)](#)

Name dmpi_get_physaddr – get physical address using DMP

Synopsis

```
cc [ flag... ] file... -ldmpi [ library... ]
#include <libdmpi.h>
```

```
int dmpi_get_physaddr(dmpi_handle_t dh, uint_t type,
    void *addrp, size_t *addrlenp);
```

Description The `dmpi_get_physaddr()` function gets a physical address from the DMP link instance associated with DMP handle *dh*. The retrieved address depends upon *type*, which can be:

`DM_FACT_PHYS_ADDR` Factory physical address

`DM_CURR_PHYS_ADDR` Current physical address

The operation can be performed in any DMP state of *dh*.

The caller must ensure that *addrp* is at least `DM_PHYSADDR_MAX` bytes in size and *addrlenp* must contain the length of *addrp*. Upon success, *addrp* contains the specified physical address, and *addrlenp* contains the physical address length. If a physical address is not available, *addrp* is not filled in and *addrlenp* is set to zero.

Return Values Upon success, `DM_SUCCESS` is returned. If `DM_SYSERR` is returned, `errno` contains the specific UNIX system error value. Otherwise, a DMP error value defined in `<sys/dmpi.h>` or an error value listed in the following section is returned.

Errors

<code>DM_EBADMSG</code>	Bad DMP message
<code>DM_EINHANDLE</code>	Invalid DMP handle
<code>DM_EINVAL</code>	Invalid argument
<code>DM_ETIMEOUT</code>	DMP operation timed out

Attributes See [attributes\(5\)](#) for description of the following attributes:

ATTRIBUTETYPE	ATTRIBUTEVALUE
Interface Stability	Committed
MT-Level	Safe

See Also [dmpi_set_physaddr\(3DMP\)](#), [libdmpi\(3LIB\)](#), [attributes\(5\)](#)

Name dlpi_iftype – convert a DLPI MAC type to a BSD socket interface type

Synopsis

```
cc [ flag... ] file... -ldlpi [ library... ]  
#include <libdlpi.h>  
  
uint_t dlpi_iftype(uint_t dlpitype);
```

Description The `dlpi_iftype()` function converts a DLPI MAC type to a BSD socket interface type defined in `<net/if_types.h>`.

Return Values Upon success, the corresponding BSD socket interface type is returned. Otherwise, zero is returned.

Attributes See [attributes\(5\)](#) for description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [libdlpi\(3LIB\)](#), [attributes\(5\)](#)

Name dlpi_info – get DLPI information

Synopsis `cc [flag ...] file ... -ldlpi [library ...]
#include <libdlpi.h>`

```
int dlpi_info(dlpi_handle_t dh, dlpi_info_t *infop,
             uint_t opt);
```

Description The `dlpi_info()` function provides DLPI information about the open DLPI link instance associated with DLPI handle *dh*. DLPI information can be retrieved in any state of *dh*, but some of the information might not be available if *dh* is in the `DL_UNBOUND` DLPI state. The DLPI information received is copied into *infop*, which must point to a `dlpi_info_t` allocated by the caller. The *opt* argument is reserved for future use and must be set to 0.

The `dlpi_info_t` is a structure defined in `<libdlpi.h>` as follows:

```
typedef struct {
    uint_t          di_opts;
    uint_t          di_max_sdu;
    uint_t          di_min_sdu;
    uint_t          di_state;
    uchar_t         di_mactype;
    char            di_linkname[DLPI_LINKNAME_MAX];
    uchar_t         di_physaddr[DLPI_PHYSADDR_MAX];
    uchar_t         di_physaddrlen;
    uchar_t         di_bcastaddr[DLPI_PHYSADDR_MAX];
    uchar_t         di_bcastaddrlen;
    uint_t          di_sap;
    int             di_timeout;
    dl_qos_cl_sel_t di_qos_sel;
    dl_qos_cl_range_t di_qos_range;
} dlpi_info_t;
```

<i>di_opts</i>	Reserved for future <code>dlpi_info_t</code> expansion.
<i>di_max_sdu</i>	Maximum message size, in bytes, that the DLPI link is able to accept for transmission. The value is guaranteed to be greater than or equal to <i>di_min_sdu</i> .
<i>di_min_sdu</i>	Minimum message size, in bytes, that the DLPI link is able to accept for transmission. The value is guaranteed to be greater than or equal to one.
<i>di_state</i>	Current DLPI state of <i>dh</i> ; either <code>DL_UNBOUND</code> or <code>DL_IDLE</code> .
<i>di_mactype</i>	MAC type supported by the DLPI link associated with <i>dh</i> . See <code><sys/dlpi.h></code> for the list of possible MAC types.
<i>di_linkname</i>	Link name associated with DLPI handle <i>dh</i> .
<i>di_physaddr</i>	Link-layer physical address of bound <i>dh</i> . If <i>dh</i> is in the <code>DL_UNBOUND</code> DLPI state, the contents of <i>di_physaddr</i> are unspecified.

<i>di_physaddrlen</i>	Physical address length, in bytes. If <i>dh</i> is in the DL_UNBOUND DLPI state, <i>di_physaddrlen</i> is set to zero.
<i>di_bcastaddr</i>	Link-layer broadcast address. If the <i>di_mactype</i> of the DLPI link does not support broadcast, the contents of <i>di_bcastaddr</i> are unspecified.
<i>di_bcastaddrlen</i>	Link-layer broadcast address length, in bytes. If the <i>di_mactype</i> of the DLPI link does not support broadcast, <i>di_bcastaddrlen</i> is set to zero.
<i>di_sap</i>	SAP currently bound to handle. If <i>dh</i> is in the DL_UNBOUND DLPI state, <i>di_sap</i> is set to zero.
<i>di_timeout</i>	Current timeout value, in seconds, set on the <i>dlpi</i> handle.
<i>di_qos_sel</i>	Current QOS parameters supported by the DLPI link instance associated with <i>dh</i> . Unsupported QOS parameters are set to DL_UNKNOWN.
<i>di_qos_range</i>	Available range of QOS parameters supported by a DLPI link instance associated with the DLPI handle <i>dh</i> . Unsupported QOS range values are set to DL_UNKNOWN.

Return Values Upon success, DLPI_SUCCESS is returned. If DL_SYSERR is returned, *errno* contains the specific UNIX system error value. Otherwise, a DLPI error value defined in `<sys/dlpi.h>` or an error value listed in the following section is returned.

Errors	DLPI_EBADMSG	Bad DLPI message
	DLPI_EINHANDLE	Invalid DLPI handle
	DLPI_EINVAL	Invalid argument
	DLPI_EMODENOTSUP	Unsupported DLPI connection mode
	DLPI_ETIMEDOUT	DLPI operation timed out
	DLPI_EVERNOTSUP	Unsupported DLPI Version
	DLPI_FAILURE	DLPI operation failed

Examples **EXAMPLE 1** Get link-layer broadcast address

The following example shows how `dlpi_info()` can be used.

```
#include <libdlpi.h>

uchar_t *
get_bcastaddr(const char *linkname, uchar_t *baddrlenp)
{
    dlpi_handle_t    dh;
    dlpi_info_t      dinfo;
    uchar_t          *baddr;
```

EXAMPLE 1 Get link-layer broadcast address *(Continued)*

```

    if (dlpi_open(linkname, &dh, 0) != DLPI_SUCCESS)
        return (NULL);

    if (dlpi_info(dh, &dlinfo, 0) != DLPI_SUCCESS) {
        dlpi_close(dh);
        return (NULL);
    }
    dlpi_close(dh);

    *baddrlenp = dlinfo.di_bcastaddrlen;
    if ((baddr = malloc(*baddrlenp)) == NULL)
        return (NULL);

    return (memcpy(baddr, dlinfo.di_bcastaddr, *baddrlenp));
}

```

Attributes See [attributes\(5\)](#) for description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [dlpi_bind\(3DLPI\)](#), [libdlpi\(3LIB\)](#), [attributes\(5\)](#)

Name dlpi_linkname – get DLPI link name

Synopsis

```
cc [ flag ... ] file ... -ldlpi [ library ... ]
#include <libdlpi.h>

const char *dlpi_linkname(dlpi_handle_t dh);
```

Description The dlpi_linkname() function returns a pointer to the link name of the DLPI link instance associated with the DLPI handle *dh*.

The returned string is managed by libdlpi and must not be modified or freed by the caller.

Return Values Upon success, the function returns a pointer to the link name associated with the DLPI handle.

Attributes See [attributes\(5\)](#) for description of the following attributes:

ATTRIBUTETYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [libdlpi\(3LIB\)](#), [attributes\(5\)](#)

Name dlpi_mactype – convert a DLPI MAC type to a string

Synopsis

```
cc [ flag ... ] file ... -ldlpi [ library ... ]
#include <libdlpi.h>
```

```
const char *dlpi_mactype(uint_t mactype);
```

Description The `dlpi_mactype()` function returns a pointer to a string that describes the specified *mactype*. Possible MAC types are defined in `<sys/dlpi.h>`. The string is not dynamically allocated and must not be freed by the caller.

Return Values Upon success, the function returns a pointer string that describes the MAC type. If *mactype* is unknown, the string “Unknown MAC Type” is returned.

Attributes See [attributes\(5\)](#) for description of the following attributes:

ATTRIBUTETYPE	ATTRIBUTEVALUE
Interface Stability	Committed
MT-Level	Safe

See Also [libdlpi\(3LIB\)](#), [attributes\(5\)](#)

Name dlpi_open – open DLPI link

Synopsis `cc [flag ...] file ... -ldlpi [library ...]`
`#include <libdlpi.h>`

```
int dlpi_open(const char *linkname, dlpi_handle_t *dhp,
              uint_t flags);
```

Description The `dlpi_open()` function creates an open instance of the DLPI Version 2 link named by *linkname* and associates it with a dynamically-allocated `dlpi_handle_t`, which is returned to the caller in *dhp* upon success. The DLPI handle is left in the `DL_UNBOUND` DLPI state after a successful open of the DLPI link. The DLPI handles can only be used by one thread at a time, but multiple handles can be used by multiple threads. This function can open both `DL_STYLE1` and `DL_STYLE2` DLPI links.

By default (if `DLPI_DEVIPNET` is not set in *flags*), the `dlpi_open()` function scans the `/dev/net` and `/dev` directories for DLPI links, in order. Within each scanned directory, `dlpi_open()` first looks for a matching `DL_STYLE1` link, then for a matching `DL_STYLE2` link. If *provider* is considered the *linkname* with its trailing digits removed, a matching `DL_STYLE1` link has a filename of *linkname*, and a matching `DL_STYLE2` link has a filename of *provider*. If a `DL_STYLE2` link is opened, `dlpi_open()` automatically performs the necessary DLPI operations to place the DLPI link instance and the associated DLPI handle in the `DL_UNBOUND` state. See [dlpi\(7P\)](#) for the definition of *linkname*.

If `DLPI_DEVIPNET` is set in *flags*, `dlpi_open()` opens the file *linkname* in `/dev/ipnet` as a `DL_STYLE1` DLPI device and does not look in any other directories.

The value of *flags* is constructed by a bitwise-inclusive-OR of the flags listed below, defined in `<libdlpi.h>`.

<code>DLPI_NATIVE</code>	Enable DLPI native mode (see <code>DLIOCNative</code> in dlpi(7P)) on a DLPI link instance. Native mode persists until the DLPI handle is closed by dlpi_close(3DLPI) .
<code>DLPI_PASSIVE</code>	Enable DLPI passive mode (see <code>DL_PASSIVE_REQ</code> in dlpi(7P)) on a DLPI link instance. Passive mode persists until the DLPI handle is closed by dlpi_close(3DLPI) .
<code>DLPI_RAW</code>	Enable DLPI raw mode (see <code>DLIOCRAW</code> in dlpi(7P)) on a DLPI link instance. Raw mode persists until the DLPI handle is closed by dlpi_close(3DLPI) .

Each DLPI handle has an associated timeout value that is used as a timeout interval for certain `libdlpi` operations. The default timeout value ensures that `DLPI_ETIMEDOUT` is returned from a `libdlpi` operation only in the event that the DLPI link becomes unresponsive. The timeout value can be changed with [dlpi_set_timeout\(3DLPI\)](#), although this should seldom be necessary.

Return Values Upon success, `DLPI_SUCCESS` is returned. If `DL_SYSERR` is returned, `errno` contains the specific UNIX system error value. Otherwise, a DLPI error value defined in `<sys/dlpi.h>` or listed in the following section is returned.

Errors The `dlpi_open()` function will fail if:

<code>DLPI_EBADLINK</code>	Bad DLPI link
<code>DLPI_EIPNETINFONOTSUP</code>	The <code>DLPI_IPNETINFO</code> flag was set but the device opened does not support the <code>DLIOCIPNETINFO</code> ioctl.
<code>DLPI_ELINKNAMEINVAL</code>	Invalid DLPI <i>linkname</i>
<code>DLPI_ENOLINK</code>	DLPI link does not exist
<code>DLPI_ERAWNOTSUP</code>	DLPI raw mode not supported
<code>DLPI_ETIMEDOUT</code>	DLPI operation timed out
<code>DLPI_FAILURE</code>	DLPI operation failed

Attributes See [attributes\(5\)](#) for description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [dlpi_close\(3DLPI\)](#), [dlpi_set_timeout\(3DLPI\)](#), [libdlpi\(3LIB\)](#), [attributes\(5\)](#), [dlpi\(7P\)](#)

Name dlpi_promiscon, dlpi_promiscoeff – enable or disable DLPI promiscuous mode

Synopsis

```
cc [ flag... ] file... -ldlpi [ library... ]
#include <libdlpi.h>

int dlpi_promiscon(dlpi_handle_t dh, uint_t level);
int dlpi_promiscoeff(dlpi_handle_t dh, uint_t level);
```

Description The `dlpi_promiscon()` function enables promiscuous mode on a DLPI link instance associated with DLPI handle *dh*, at the specified *level*. After enabling promiscuous mode, the caller will be able to receive all messages destined for the DLPI link instance at the specified *level*. This operation can be performed in any DLPI state of a handle.

The `dlpi_promiscoeff()` function disables promiscuous mode on a DLPI link instance associated with DLPI handle *dh*, at the specified level. This operation can be performed in any DLPI state of a handle in which promiscuous mode is enabled at the specified *level*.

- The *level* modes are:
- DL_PROMISC_PHYS Promiscuous mode at the physical level
 - DL_PROMISC_SAP Promiscuous mode at the SAP level
 - DL_PROMISC_MULT I Promiscuous mode for all multicast addresses

Return Values Upon success, DLPI_SUCCESS is returned. If DL_SYSERR is returned, *errno* contains the specific UNIX system error value. Otherwise, a DLPI error value defined in `<sys/dlpi.h>` or an error value listed in the following section is returned.

- Errors**
- DLPI_EBADMSG Bad DLPI message
 - DLPI_EINHANDLE Invalid DLPI handle
 - DLPI_EINVAL Invalid argument
 - DLPI_ETIMEDOUT DLPI operation timed out

Attributes See [attributes\(5\)](#) for description of the following attributes:

ATTRIBUTETYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [libdlpi\(3LIB\)](#), [attributes\(5\)](#)

Name dlpi_recv – receive a data message using DLPI

Synopsis `cc [flag ...] file ... -ldlpi [library ...]
#include <libdlpi.h>`

```
int dlpi_recv(dlpi_handle_t dh, void *saddrp,
             size_t *saddrlenp, void *msgbuf, size_t *msglenp,
             int msec, dlpi_recvinfo_t *recvp);
```

Description The `dlpi_recv()` function attempts to receive data messages over the DLPI link instance associated with the DLPI handle *dh*. If *dh* is not in the DL_IDLE DLPI state, the attempt fails. The caller must ensure that *msgbuf* is at least *msglenp* bytes in size. Upon success, *msgbuf* contains the data message received, *msglenp* contains the number of bytes placed in *msgbuf*.

The caller must ensure that *saddrp* is at least DLPI_PHYSADDR_MAX bytes in size and *saddrlenp* must contain the length of *saddrp*. Upon success, *saddrp* contains the address of the source sending the data message and *saddrlenp* contains the source address length. If the caller is not interested in the source address, both *saddrp* and *saddrlenp* can be left as NULL. If the source address is not available, *saddrp* is not filled in and *saddrlenp* is set to zero.

The *dlpi_recvinfo_t* is a structure defined in `<libdlpi.h>` as follows:

```
typedef struct {
    uchar_t          dri_destaddr[DLPI_PHYSADDR_MAX];
    uchar_t          dri_destaddrlen;
    dlpi_addrtype_t  dri_destaddrtype;
    size_t           dri_totmsglen;
} dlpi_recvinfo_t;
```

Upon success, if *recvp* is not set to NULL, *dri_destaddr* contains the destination address, *dri_destaddrlen* contains the destination address length, and *dri_totmsglen* contains the total length of the message received. If the destination address is unicast, *dri_destaddrtype* is set to DLPI_ADDRTYPE_UNICAST. Otherwise, it is set to DLPI_ADDRTYPE_GROUP.

The values of *msglenp* and *dri_totmsglen* might vary when a message larger than the size of *msgbuf* is received. In that case, the caller can use *dri_totmsglen* to determine the original total length of the message.

If the handle is in raw mode, as described in [dlpi_open\(3DLPI\)](#), *msgbuf* starts with the link-layer header. See [dlpi\(7P\)](#). The values of *saddrp*, *saddrlenp*, and all the members of *dlpi_recvinfo_t* except *dri_totmsglen* are invalid because the address information is already included in the link-layer header returned by *msgbuf*.

If no message is received within *msec* milliseconds, `dlpi_recv()` returns DLPI_ETIMEDOUT. If *msec* is 0, `dlpi_recv()` does not block. If *msec* is -1, `dlpi_recv()` does block until a data message is received.

Return Values Upon success, DLPI_SUCCESS is returned. If DL_SYSERR is returned, errno contains the specific UNIX system error value. Otherwise, a DLPI error value defined in <sys/dlpi.h> or an error value listed in the following section is returned.

Errors	DLPI_EBADMSG	Bad DLPI message
	DLPI_EINHANDLE	Invalid DLPI handle
	DLPI_EINVAL	Invalid argument
	DLPI_ETIMEDOUT	DLPI operation timed out
	DLPI_EUNAVAILSAP	Unavailable DLPI SAP
	DLPI_FAILURE	DLPI operation failed

Attributes See [attributes\(5\)](#) for description of the following attributes:

ATTRIBUTETYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [dlpi_bind\(3DLPI\)](#), [dlpi_open\(3DLPI\)](#), [libdlpi\(3LIB\)](#), [attributes\(5\)](#), [dlpi\(7P\)](#)

Name dlpi_send – send a data message using DLPI

Synopsis `cc [flag...] file... -ldlpi [library...]
#include <libdlpi.h>`

```
int dlpi_send(dlpi_handle_t dh, const void *daddrp,
              size_t daddrlen, const void *msgbuf, size_t msglen,
              const dlpi_sendinfo_t *sendp);
```

Description The `dlpi_send()` function attempts to send the contents of *msgbuf* over the DLPI link instance associated with the DLPI handle *dh* to the destination address specified by *daddrp*. The size of *msgbuf* and *daddrp* are provided by the *msglen* and *daddrlen* arguments, respectively. The attempt will fail if *dh* is not in the DL_IDLE DLPI state, the address named by *daddrp* is invalid, *daddrlen* is larger than DLPI_PHYSADDR_MAX, or *msglen* is outside the range reported by `dlpi_info(3DLPI)`.

If the *sendp* argument is NULL, data is sent using the bound SAP associated with *dh* (see `dlpi_bind(3DLPI)`) and with default priority. Otherwise, *sendp* must point to a `dlpi_sendinfo_t` structure defined in `<libdlpi.h>` as follows:

```
typedef struct {
    uint_t      dsi_sap;
    dl_priority_t dsi_prio;
} dlpi_sendinfo_t;
```

The *dsi_sap* value indicates the SAP to use for the message and the *dsi_prio* argument indicates the priority. The priority range spans from 0 to 100, with 0 being the highest priority. If one wishes to only alter the SAP or priority (but not both), the current SAP can be retrieved using `dlpi_info(3DLPI)`, and the default priority can be specified by using the DL_QOS_DONT_CARE constant.

If the handle is in raw mode (see DLPI_RAW in `dlpi_open(3DLPI)`), *msgbuf* must start with the link-layer header (see `dlpi(7P)`). In raw mode, the contents of *daddrp* and *sendp* are ignored, as they are already specified by the link-layer header in *msgbuf*.

If *msgbuf* is accepted for delivery, no error is returned. However, because only unacknowledged connectionless service (DL_CLDLS) is currently supported, a successful return does not guarantee that the data will be successfully delivered to *daddrp*.

Return Values Upon success, DLPI_SUCCESS is returned. If DL_SYSERR is returned, *errno* contains the specific UNIX system error value. Otherwise, a DLPI error value defined in `<sys/dlpi.h>` or an error value listed in the following section is returned.

Errors	DLPI_EINHANDLE	Invalid DLPI handle
	DLPI_EINVAL	Invalid argument

Attributes See [attributes\(5\)](#) for description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [dlpi_bind\(3DLPI\)](#), [dlpi_info\(3DLPI\)](#), [dlpi_open\(3DLPI\)](#), [libdlpi\(3LIB\)](#), [attributes\(5\)](#), [dlpi\(7P\)](#)

Name dlpi_set_physaddr – set physical address using DLPI

Synopsis

```
cc [ flag... ] file... -ldlpi [ library... ]
#include <libdlpi.h>

int dlpi_set_physaddr(dlpi_handle_t dh, uint_t type,
    const void *addrp, size_t *addrlen);
```

Description The `dlpi_set_physaddr()` function sets the physical address via DLPI handle *dh* associated with the DLPI link instance. Upon success, the physical address is set to *addrp* with a length of *addrlen* bytes.

In this release, *type* must be set to `DL_CURR_PHYS_ADDR`, which sets the current physical address.

Return Values Upon success, `DLPI_SUCCESS` is returned. If `DL_SYSERR` is returned, `errno` contains the specific UNIX system error value. Otherwise, a DLPI error value defined in `<sys/dlpi.h>` or an error value listed in the following section is returned.

- Errors**
- `DLPI_EBADMSG` Bad DLPI message
 - `DLPI_EINHANDLE` Invalid DLPI handle
 - `DLPI_EINVAL` Invalid argument
 - `DLPI_ETIMEOUT` DLPI operation timed out

Attributes See [attributes\(5\)](#) for description of the following attributes:

ATTRIBUTETYPE	ATTRIBUTEVALUE
Interface Stability	Committed
MT-Level	Safe

See Also [dlpi_get_physaddr\(3DLPI\)](#), [libdlpi\(3LIB\)](#), [attributes\(5\)](#)

Name dlpi_set_timeout – set DLPI handle timeout interval

Synopsis

```
cc [ flag ... ] file ... -ldlpi [ library ... ]
#include <libdlpi.h>

int dlpi_set_timeout(dlpi_handle_t dh, int sec);
```

Description The `dlpi_set_timeout()` function sets the timeout interval to *sec* seconds on DLPI handle *dh*. This timeout is used by [libdlpi\(3LIB\)](#) functions that require explicit acknowledgment from the associated DLPI link, and bounds the number of seconds that a function will wait for an acknowledgment before returning `DLPI_ETIMEDOUT`. Except for [dlpi_recv\(3DLPI\)](#), which has a *timeout* argument, any function that is documented to return `DLPI_ETIMEDOUT` can take up to the *timeout* interval to complete.

Callers that do not require an upper bound on timeouts are strongly encouraged to never call `dlpi_set_timeout()`, and allow `libdlpi` to use its default *timeout* value. The default *timeout* value is intended to ensure that `DLPI_ETIMEDOUT` will only be returned if the DLPI link has truly become unresponsive. The default *timeout* value is intended to ensure that `DLPI_ETIMEDOUT` will be returned only if the DLPI link has truly become unresponsive.

Callers that do require an explicit upper bound can specify that value at any time by calling `dlpi_set_timeout()`. However, note that values less than 5 seconds may trigger spurious failures on certain DLPI links and systems under high load, and thus are discouraged. Attempts to set the *timeout* value to less than 1 second will fail.

If *sec* is set to `DLPI_DEF_TIMEOUT`, the default *timeout* value is restored.

Return Values Upon success, `DLPI_SUCCESS` is returned. Otherwise, a DLPI error value is returned.

Errors `DLPI_EINHANDLE` Invalid DLPI handle

Attributes See [attributes\(5\)](#) for description of the following attributes:

ATTRIBUTETYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [libdlpi\(3LIB\)](#), [attributes\(5\)](#)

Name dlpi_strerror – get DLPI error message

Synopsis

```
cc [ flag... ] file... -ldlpi [ library... ]
#include <libdlpi.h>
```

```
const char *dlpi_strerror(int err);
```

Description The `dlpi_strerror()` function maps the error code in *err* into an error message string and returns a pointer to that string.

If *err* is `DL_SYSERR`, a string that describes the current value of `errno` is returned. Otherwise, if *err* corresponds to an error code listed in `<libdlpi.h>` or `<sys/dlpi.h>`, a string which describes that error is returned.

The string is not dynamically allocated and must not be freed by the caller.

Return Values Upon success, the function returns a pointer to the error message string. If the error code is unknown, the string “Unknown DLPI error” is returned.

Attributes See [attributes\(5\)](#) for description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [libdlpi\(3LIB\)](#), [attributes\(5\)](#)

Name dlpi_unbind – unbind DLPI handle

Synopsis

```
cc [ flag ... ] file ... -ldlpi [ library ... ]
#include <libdlpi.h>

int dlpi_unbind(dlpi_handle_t dh);
```

Description The `dlpi_unbind()` function unbinds to bind the DLPI handle *dh* from the bound SAP. The handle must be in the `DL_IDLE` DLPI state and upon success, the handle transitions to the `DL_UNBOUND` state.

Upon success, the caller will no longer be able to send or receive data using the DLPI link associated with *dh*.

Return Values Upon success, `DLPI_SUCCESS` is returned. If `DL_SYSERR` is returned, `errno` contains the specific UNIX system error value. Otherwise, a DLPI error value defined in `<sys/dlpi.h>` or an error value `DLPI_ETIMEDOUT` will be returned.

Errors

<code>DLPI_EBADMSG</code>	Bad DLPI message
<code>DLPI_EINHANDLE</code>	Invalid DLPI handle
<code>DLPI_ETIMEDOUT</code>	DLPI operation timed out

Attributes See [attributes\(5\)](#) for description of the following attributes:

ATTRIBUTETYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [dlpi_bind\(3DLPI\)](#), [libdlpi\(3LIB\)](#), [attributes\(5\)](#)

Name doconfig – execute a configuration script

Synopsis `cc [flag ...] file ... -lnsl [library ...]`
`# include <sac.h>`

```
int doconfig(int fildes, char *script, long rflag);
```

Description `doconfig()` is a Service Access Facility library function that interprets the configuration scripts contained in the files `</etc/saf/pmtag/_config>`, `</etc/saf/_sysconfig>`, and `</etc/saf/pmtag/svctag>`, where *pmtag* specifies the tag associated with the port monitor, and *svctag* specifies the service tag associated with a given service. See [pmadm\(1M\)](#) and [sacadm\(1M\)](#).

script is the name of the configuration script; *fildes* is a file descriptor that designates the stream to which stream manipulation operations are to be applied; *rflag* is a bitmask that indicates the mode in which *script* is to be interpreted. If *rflag* is zero, all commands in the configuration script are eligible to be interpreted. If *rflag* has the NOASSIGN bit set, the assign command is considered illegal and will generate an error return. If *rflag* has the NORUN bit set, the run and runwait commands are considered illegal and will generate error returns.

The configuration language in which *script* is written consists of a sequence of commands, each of which is interpreted separately. The following reserved keywords are defined: assign, push, pop, runwait, and run. The comment character is #; when a # occurs on a line, everything from that point to the end of the line is ignored. Blank lines are not significant. No line in a command script may exceed 1024 characters.

`assign variable=value`

Used to define environment variables. *variable* is the name of the environment variable and *value* is the value to be assigned to it. The value assigned must be a string constant; no form of parameter substitution is available. *value* may be quoted. The quoting rules are those used by the shell for defining environment variables. assign will fail if space cannot be allocated for the new variable or if any part of the specification is invalid.

`push module1[, module2, module3, ...]`

Used to push STREAMS modules onto the stream designated by *fildes*. *module1* is the name of the first module to be pushed, *module2* is the name of the second module to be pushed, etc. The command will fail if any of the named modules cannot be pushed. If a module cannot be pushed, the subsequent modules on the same command line will be ignored and modules that have already been pushed will be popped.

`pop` [*module*]

Used to pop STREAMS modules off the designated stream. If `pop` is invoked with no arguments, the top module on the stream is popped. If an argument is given, modules will be popped one at a time until the named module is at the top of the stream. If the named module is not on the designated stream, the stream is left as it was and the command fails. If *module* is the special keyword `ALL`, then all modules on the stream will be popped. Note that only modules above the topmost driver are affected.

`runwait` *command*

The `runwait` command runs a command and waits for it to complete. *command* is the pathname of the command to be run. The command is run with `/usr/bin/sh -c` prepended to it; shell scripts may thus be executed from configuration scripts. The `runwait` command will fail if *command* cannot be found or cannot be executed, or if *command* exits with a non-zero status.

`run` *command*

The `run` command is identical to `runwait` except that it does not wait for *command* to complete. *command* is the pathname of the command to be run. `run` will not fail unless it is unable to create a child process to execute the command.

Although they are syntactically indistinguishable, some of the commands available to `run` and `runwait` are interpreter built-in commands. Interpreter built-ins are used when it is necessary to alter the state of a process within the context of that process. The `doconfig()` interpreter built-in commands are similar to the shell special commands and, like these, they do not spawn another process for execution. See [sh\(1\)](#). The built-in commands are:

```
cd
ulimit
umask
```

Return Values `doconfig()` returns 0 if the script was interpreted successfully. If a command in the script fails, the interpretation of the script ceases at that point and a positive number is returned; this number indicates which line in the script failed. If a system error occurs, a value of -1 is returned. When a script fails, the process whose environment was being established should not be started.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Unsafe

See Also [sh\(1\)](#), [pmadm\(1M\)](#), [sacadm\(1M\)](#), [attributes\(5\)](#)

Notes This interface is unsafe in multithreaded applications. Unsafe interfaces should be called only from the main thread.

Name endhostent, gethostbyaddr, gethostbyname, gethostent, sethostent – network host database functions

Synopsis

```
cc [ flag ... ] file ... -lxnet [ library ... ]  
#include <netdb.h>  
extern int h_errno;
```

```
void endhostent(void)  
  
struct hostent *gethostbyaddr(const void *addr, socklen_t len, int type);  
  
struct hostent *gethostbyname(const char *name);  
  
struct hostent *gethostent(void)  
  
void sethostent(int stayopen);
```

Description The `gethostent()`, `gethostbyaddr()`, and `gethostbyname()` functions each return a pointer to a `hostent` structure, the members of which contain the fields of an entry in the network host database.

The `gethostent()` function reads the next entry of the database, opening a connection to the database if necessary.

The `gethostbyaddr()` function searches the database and finds an entry which matches the address family specified by the `type` argument and which matches the address pointed to by the `addr` argument, opening a connection to the database if necessary. The `addr` argument is a pointer to the binary-format (that is, not null-terminated) address in network byte order, whose length is specified by the `len` argument. The datatype of the address depends on the address family. For an address of type `AF_INET`, this is an `in_addr` structure, defined in `<netinet/in.h>`. For an address of type `AF_INET6`, there is an `in6_addr` structure defined in `<netinet/in.h>`.

The `gethostbyname()` function searches the database and finds an entry which matches the host name specified by the `name` argument, opening a connection to the database if necessary. If `name` is an alias for a valid host name, the function returns information about the host name to which the alias refers, and `name` is included in the list of aliases returned.

The `sethostent()` function opens a connection to the network host database, and sets the position of the next entry to the first entry. If the `stayopen` argument is non-zero, the connection to the host database will not be closed after each call to `gethostent()` (either directly, or indirectly through one of the other `gethost*()` functions).

The `endhostent()` function closes the connection to the database.

Usage The `gethostent()`, `gethostbyaddr()`, and `gethostbyname()` functions may return pointers to static data, which may be overwritten by subsequent calls to any of these functions.

These functions are generally used with the Internet address family.

Return Values On successful completion, `gethostbyaddr()`, `gethostbyname()` and `gethostent()` return a pointer to a `hostent` structure if the requested entry was found, and a null pointer if the end of the database was reached or the requested entry was not found. Otherwise, a null pointer is returned.

On unsuccessful completion, `gethostbyaddr()` and `gethostbyname()` functions set `h_errno` to indicate the error.

Errors No errors are defined for `endhostent()`, `gethostent()` and `sethostent()`.

The `gethostbyaddr()` and `gethostbyname()` functions will fail in the following cases, setting `h_errno` to the value shown in the list below. Any changes to `errno` are unspecified.

<code>HOST_NOT_FOUND</code>	No such host is known.
<code>NO_DATA</code>	The server recognised the request and the name but no address is available. Another type of request to the name server for the domain might return an answer.
<code>NO_RECOVERY</code>	An unexpected server failure occurred which can not be recovered.
<code>TRY_AGAIN</code>	A temporary and possibly transient error occurred, such as a failure of a server to respond.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also [endservent\(3XNET\)](#), [htonl\(3XNET\)](#), [inet_addr\(3XNET\)](#), [attributes\(5\)](#), [standards\(5\)](#)

Name endnetent, getnetbyaddr, getnetbyname, getnetent, setnetent – network database functions

Synopsis `cc [flag ...] file ... -lxnet [library ...]`
`#include <netdb.h>`

```
void endnetent(void); struct netent *getnetbyaddr(in_addr_t net, int type);  
struct netent *getnetbyname(const char *name);  
struct netent *getnetent(void)  
void setnetent(int stayopen);
```

Description The `getnetbyaddr()`, `getnetbyname()` and `getnetent()`, functions each return a pointer to a `netent` structure, the members of which contain the fields of an entry in the network database.

The `getnetent()` function reads the next entry of the database, opening a connection to the database if necessary.

The `getnetbyaddr()` function searches the database from the beginning, and finds the first entry for which the address family specified by `type` matches the `n_addrtype` member and the network number `net` matches the `n_net` member, opening a connection to the database if necessary. The `net` argument is the network number in host byte order.

The `getnetbyname()` function searches the database from the beginning and finds the first entry for which the network name specified by `name` matches the `n_name` member, opening a connection to the database if necessary.

The `setnetent()` function opens and rewinds the database. If the `stayopen` argument is non-zero, the connection to the net database will not be closed after each call to `getnetent()` (either directly, or indirectly through one of the other `getnet*()` functions).

The `endnetent()` function closes the database.

Usage The `getnetbyaddr()`, `getnetbyname()` and `getnetent()`, functions may return pointers to static data, which may be overwritten by subsequent calls to any of these functions.

These functions are generally used with the Internet address family.

Return Values On successful completion, `getnetbyaddr()`, `getnetbyname()` and `getnetent()`, return a pointer to a `netent` structure if the requested entry was found, and a null pointer if the end of the database was reached or the requested entry was not found. Otherwise, a null pointer is returned.

Errors No errors are defined.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also [attributes\(5\)](#), [standards\(5\)](#)

Name endprotoent, getprotobynumber, getprotobynname, getprotoent, setprotoent – network protocol database functions

Synopsis `cc [flag ...] file ... -lxnet [library ...]
#include <netdb.h>`

```
void endprotoent(void)

struct protoent *getprotobynname(const char *name);

struct protoent *getprotobynumber(int proto);

struct protoent *getprotoent(void)

void setprotoent(int stayopen);
```

Description The `getprotobynname()`, `getprotobynumber()` and `getprotoent()`, functions each return a pointer to a `protoent` structure, the members of which contain the fields of an entry in the network protocol database.

The `getprotoent()` function reads the next entry of the database, opening a connection to the database if necessary.

The `getprotobynname()` function searches the database from the beginning and finds the first entry for which the protocol name specified by *name* matches the `p_name` member, opening a connection to the database if necessary.

The `getprotobynumber()` function searches the database from the beginning and finds the first entry for which the protocol number specified by *number* matches the `p_proto` member, opening a connection to the database if necessary.

The `setprotoent()` function opens a connection to the database, and sets the next entry to the first entry. If the *stayopen* argument is non-zero, the connection to the network protocol database will not be closed after each call to `getprotoent()` (either directly, or indirectly through one of the other `getproto*()` functions).

The `endprotoent()` function closes the connection to the database.

Usage The `getprotobynname()`, `getprotobynumber()` and `getprotoent()` functions may return pointers to static data, which may be overwritten by subsequent calls to any of these functions.

These functions are generally used with the Internet address family.

Return Values On successful completion, `getprotobynname()`, `getprotobynumber()` and `getprotoent()` functions return a pointer to a `protoent` structure if the requested entry was found, and a null pointer if the end of the database was reached or the requested entry was not found. Otherwise, a null pointer is returned.

Errors No errors are defined.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also [attributes\(5\)](#), [standards\(5\)](#)

Name endservent, getservbyport, getservbyname, getservent, setservent – network services database functions

Synopsis `cc [flag ...] file ... -lxnet [library ...]
#include <netdb.h>`

```
void endservent(void)

struct servent *getservbyname(const char *name, const char *proto);

struct servent *getservbyport(int port, const char *proto);

struct servent *getservent(void)

void setservent(int stayopen);
```

Description The `getservbyname()`, `getservbyport()` and `getservent()` functions each return a pointer to a `servent` structure, the members of which contain the fields of an entry in the network services database.

The `getservent()` function reads the next entry of the database, opening a connection to the database if necessary.

The `getservbyname()` function searches the database from the beginning and finds the first entry for which the service name specified by *name* matches the `s_name` member and the protocol name specified by *proto* matches the `s_proto` member, opening a connection to the database if necessary. If *proto* is a null pointer, any value of the `s_proto` member will be matched.

The `getservbyport()` function searches the database from the beginning and finds the first entry for which the port specified by *port* matches the `s_port` member and the protocol name specified by *proto* matches the `s_proto` member, opening a connection to the database if necessary. If *proto* is a null pointer, any value of the `s_proto` member will be matched. The *port* argument must be in network byte order.

The `setservent()` function opens a connection to the database, and sets the next entry to the first entry. If the *stayopen* argument is non-zero, the net database will not be closed after each call to the `getservent()` function, either directly, or indirectly through one of the other `getserv*()` functions.

The `endservent()` function closes the database.

Usage The *port* argument of `getservbyport()` need not be compatible with the port values of all address families.

The `getservent()`, `getservbyname()` and `getservbyport()` functions may return pointers to static data, which may be overwritten by subsequent calls to any of these functions.

These functions are generally used with the Internet address family.

Return Values On successful completion, `getservbyname()`, `getservbyport()` and `getservent()` return a pointer to a `servent` structure if the requested entry was found, and a null pointer if the end of the database was reached or the requested entry was not found. Otherwise, a null pointer is returned.

Errors No errors are defined.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also [endhostent\(3XNET\)](#), [endprotoent\(3XNET\)](#), [htonl\(3XNET\)](#), [inet_addr\(3XNET\)](#), [attributes\(5\)](#), [standards\(5\)](#)

Name ethers, ether_ntoa, ether_aton, ether_ntohost, ether_hostton, ether_line – Ethernet address mapping operations

Synopsis

```
cc [ flag ... ] file ... -lsocket -lnsl [ library ... ]  
#include <sys/types.h>  
#include <sys/ethernet.h>
```

```
char *ether_ntoa(const struct ether_addr *e);  
struct ether_addr *ether_aton(const char *s);  
int ether_ntohost(char *hostname, const struct ether_addr *e);  
int ether_hostton(const char *hostname, struct ether_addr *e);  
int ether_line(const char *l, struct ether_addr *e, char *hostname);
```

Description These routines are useful for mapping 48 bit Ethernet numbers to their ASCII representations or their corresponding host names, and vice versa.

The function `ether_ntoa()` converts a 48 bit Ethernet number pointed to by *e* to its standard ASCII representation; it returns a pointer to the ASCII string. The representation is of the form *x:x:x:x:x:x* where *x* is a hexadecimal number between 0 and ff. The function `ether_aton()` converts an ASCII string in the standard representation back to a 48 bit Ethernet number; the function returns NULL if the string cannot be scanned successfully.

The function `ether_ntohost()` maps an Ethernet number (pointed to by *e*) to its associated hostname. The string pointed to by *hostname* must be long enough to hold the hostname and a NULL character. The function returns zero upon success and non-zero upon failure. Inversely, the function `ether_hostton()` maps a hostname string to its corresponding Ethernet number; the function modifies the Ethernet number pointed to by *e*. The function also returns zero upon success and non-zero upon failure. In order to do the mapping, both these functions may lookup one or more of the following sources: the ethers file, the NIS maps `ethers.byname` and `ethers.byaddr` and the NIS+ table `ethers`. The sources and their lookup order are specified in the `/etc/nsswitch.conf` file. See [nsswitch.conf\(4\)](#) for details.

The function `ether_line()` scans a line, pointed to by *l*, and sets the hostname and the Ethernet number, pointed to by *e*. The string pointed to by *hostname* must be long enough to hold the hostname and a NULL character. The function returns zero upon success and non-zero upon failure. The format of the scanned line is described by [ethers\(4\)](#).

Files	<code>/etc/ethers</code>	Ethernet address to hostname database or domain
	<code>/etc/nsswitch.conf</code>	configuration file for the name service switch

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [ethers\(4\)](#), [nsswitch.conf\(4\)](#), [attributes\(5\)](#)

Name freeaddrinfo, getaddrinfo – get address information

Synopsis

```
cc [ flag ... ] file ... -lXnet [ library ... ]  
#include <sys/socket.h>  
#include <netdb.h>  
  
void freeaddrinfo(struct addrinfo *ai);  
  
int getaddrinfo(const char *restrict nodename,  
               const char *restrict servname, const struct addrinfo *restrict hints,  
               struct addrinfo **restrict res);
```

Description The `freeaddrinfo()` function frees one or more `addrinfo` structures returned by `getaddrinfo()`, along with any additional storage associated with those structures. If the `ai_next` member of the structure is not null, the entire list of structures is freed. The `freeaddrinfo()` function supports the freeing of arbitrary sublists of an `addrinfo` list originally returned by `getaddrinfo()`.

The `getaddrinfo()` function translates the name of a service location (for example, a host name) and/or a service name and returns a set of socket addresses and associated information to be used in creating a socket with which to address the specified service.

The `nodename` and `servname` arguments are either null pointers or pointers to null-terminated strings. One or both of these two arguments are supplied by the application as a non-null pointer.

The format of a valid name depends on the address family or families. If a specific family is not given and the name could be interpreted as valid within multiple supported families, the implementation attempts to resolve the name in all supported families and, in absence of errors, one or more results are returned.

If the `nodename` argument is not null, it can be a descriptive name or can be an address string. If the specified address family is `AF_INET`, `AF_INET6`, or `AF_UNSPEC`, valid descriptive names include host names. If the specified address family is `AF_INET` or `AF_UNSPEC`, address strings using Internet standard dot notation as specified in [inet_addr\(3XNET\)](#) are valid.

If the specified address family is `AF_INET6` or `AF_UNSPEC`, standard IPv6 text forms described in [inet_ntop\(3XNET\)](#) are valid.

If `nodename` is not null, the requested service location is named by `nodename`; otherwise, the requested service location is local to the caller.

If `servname` is null, the call returns network-level addresses for the specified `nodename`. If `servname` is not null, it is a null-terminated character string identifying the requested service. This string can be either a descriptive name or a numeric representation suitable for use with the address family or families. If the specified address family is `AF_INET`, `AF_INET6`, or `AF_UNSPEC`, the service can be specified as a string specifying a decimal port number.

If the *hints* argument is not null, it refers to a structure containing input values that can direct the operation by providing options and by limiting the returned information to a specific socket type, address family and/or protocol. In this *hints* structure every member other than *ai_flags*, *ai_family*, *ai_socktype*, and *ai_protocol* is set to 0 or a null pointer. A value of *AF_UNSPEC* for *ai_family* means that the caller accepts any address family. A value of 0 for *ai_socktype* means that the caller accepts any socket type. A value of 0 for *ai_protocol* means that the caller accepts any protocol. If *hints* is a null pointer, the behavior is as if it referred to a structure containing the value 0 for the *ai_flags*, *ai_socktype*, and *ai_protocol* members, and *AF_UNSPEC* for the *ai_family* member.

The *ai_flags* member to which the *hints* parameter points is set to 0 or be the bitwise-inclusive OR of one or more of the values *AI_PASSIVE*, *AI_CANONNAME*, *AI_NUMERICHOST*, and *AI_NUMERICSERV*.

If the *AI_PASSIVE* flag is specified, the returned address information is suitable for use in binding a socket for accepting incoming connections for the specified service. In this case, if the *nodename* argument is null, then the IP address portion of the socket address structure is set to *INADDR_ANY* for an IPv4 address or *IN6ADDR_ANY_INIT* for an IPv6 address. If the *AI_PASSIVE* flag is not specified, the returned address information is suitable for a call to [connect\(3XNET\)](#) (for a connection-mode protocol) or for a call to [connect\(\)](#), [sendto\(3XNET\)](#), or [sendmsg\(3XNET\)](#) (for a connectionless protocol). In this case, if the *nodename* argument is null, then the IP address portion of the socket address structure is set to the loopback address.

If the *AI_CANONNAME* flag is specified and the *nodename* argument is not null, the function attempts to determine the canonical name corresponding to *nodename* (for example, if *nodename* is an alias or shorthand notation for a complete name).

If the *AI_NUMERICHOST* flag is specified, then a non-null *nodename* string supplied is a numeric host address string. Otherwise, an *EAI_NONAME* error is returned. This flag prevents any type of name resolution service (for example, the DNS) from being invoked.

If the *AI_NUMERICSERV* flag is specified, then a non-null *servname* string supplied is a numeric port string. Otherwise, an *EAI_NONAME* error is returned. This flag prevents any type of name resolution service (for example, NIS+) from being invoked.

If the *AI_V4MAPPED* flag is specified along with an *ai_family* of *AF_INET6*, then [getaddrinfo\(\)](#) returns IPv4-mapped IPv6 addresses on finding no matching IPv6 addresses (*ai_addrlen* is 16). The *AI_V4MAPPED* flag is ignored unless *ai_family* equals *AF_INET6*. If the *AI_ALL* flag is used with the *AI_V4MAPPED* flag, then [getaddrinfo\(\)](#) returns all matching IPv6 and IPv4 addresses. The *AI_ALL* flag without the *AI_V4MAPPED* flag is ignored.

The *ai_socktype* member to which argument *hints* points specifies the socket type for the service, as defined in [socket\(3XNET\)](#). If a specific socket type is not given (for example, a value of 0) and the service name could be interpreted as valid with multiple supported socket types, the implementation attempts to resolve the service name for all supported socket types

and, in the absence of errors, all possible results are returned. A non-zero socket type value limits the returned information to values with the specified socket type.

If the `ai_family` member to which hints points has the value `AF_UNSPEC`, addresses are returned for use with any address family that can be used with the specified *nodename* and/or *servname*. Otherwise, addresses are returned for use only with the specified address family. If `ai_family` is not `AF_UNSPEC` and `ai_protocol` is not 0, then addresses are returned for use only with the specified address family and protocol; the value of `ai_protocol` is interpreted as in a call to the `socket()` function with the corresponding values of `ai_family` and `ai_protocol`.

Return Values A 0 return value for `getaddrinfo()` indicates successful completion; a non-zero return value indicates failure. The possible values for the failures are listed in the ERRORS section.

Upon successful return of `getaddrinfo()`, the location to which `res` points refers to a linked list of `addrinfo` structures, each of which specifies a socket address and information for use in creating a socket with which to use that socket address. The list includes at least one `addrinfo` structure. The `ai_next` member of each structure contains a pointer to the next structure on the list, or a null pointer if it is the last structure on the list. Each structure on the list includes values for use with a call to the `socket` function, and a socket address for use with the `connect` function or, if the `AI_PASSIVE` flag was specified, for use with the `bind(3XNET)` function. The `ai_family`, `ai_socktype`, and `ai_protocol` members are usable as the arguments to the `socket()` function to create a socket suitable for use with the returned address. The `ai_addr` and `ai_addrlen` members are usable as the arguments to the `connect()` or `bind()` functions with such a socket, according to the `AI_PASSIVE` flag.

If *nodename* is not null, and if requested by the `AI_CANONNAME` flag, the `ai_canonname` member of the first returned `addrinfo` structure points to a null-terminated string containing the canonical name corresponding to the input *nodename*. If the canonical name is not available, then `ai_canonname` refers to the *nodename* argument or a string with the same contents. The contents of the `ai_flags` member of the returned structures are undefined.

All members in socket address structures returned by `getaddrinfo()` that are not filled in through an explicit argument (for example, `sin6_flowinfo`) are set to 0, making it easier to compare socket address structures.

Errors The `getaddrinfo()` function will fail if:

<code>EAI_AGAIN</code>	The name could not be resolved at this time. Future attempts might succeed.
<code>EAI_BADFLAGS</code>	The <code>ai_flags</code> member of the <code>addrinfo</code> structure had an invalid value.
<code>EAI_FAIL</code>	A non-recoverable error occurred when attempting to resolve the name.
<code>EAI_FAMILY</code>	The address family was not recognized.
<code>EAI_MEMORY</code>	There was a memory allocation failure when trying to allocate storage for the return value.

EAI_NONAME	he name does not resolve for the supplied parameters. Neither <i>nodename</i> nor <i>servname</i> were supplied. At least one of these must be supplied.
EAI_SERVICE	The service passed was not recognized for the specified socket type.
EAI_SOCKTYPE	The intended socket type was not recognized.
EAI_SYSTEM	A system error occurred. The error code can be found in <code>errno</code> .
EAI_OVERFLOW	An argument buffer overflowed.

Usage If the caller handles only TCP and not UDP, for example, then the `ai_protocol` member of the *hints* structure should be set to `IPPROTO_TCP` when `getaddrinfo()` is called.

If the caller handles only IPv4 and not IPv6, then the `ai_family` member of the *hints* structure should be set to `AF_INET` when `getaddrinfo()` is called.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also [connect\(3XNET\)](#), [gai_strerror\(3XNET\)](#), [gethostbyname\(3XNET\)](#), [getnameinfo\(3XNET\)](#), [getservbyname\(3XNET\)](#), [inet_addr\(3XNET\)](#), [inet_ntop\(3XNET\)](#), [socket\(3XNET\)](#), [attributes\(5\)](#), [standards\(5\)](#)

Name `gai_strerror` – address and name information error description

Synopsis `cc [flag ...] file ... -lxnet [library ...]`
 `#include <netdb.h>`

 `const char *gai_strerror(int ecode);`

Description The `gai_strerror()` function returns a text string describing an error value for the [getaddrinfo\(3XNET\)](#) and [getnameinfo\(3XNET\)](#) functions listed in the `<netdb.h>` header.

When the *ecode* argument is one of the following values listed in the `<netdb.h>` header:

`EAI_AGAIN`
`EAI_BADFLAGS`
`EAI_FAIL`
`EAI_FAMILY`
`EAI_MEMORY`
`EAI_NONAME`
`EAI_SERVICE`
`EAI_SOCKTYPE`
`EAI_SYSTEM`

the function return value points to a string describing the error. If the argument is not one of those values, the function returns a pointer to a string whose contents indicate an unknown error.

Return Values Upon successful completion, `gai_strerror()` returns a pointer to a string describing the error value.

Errors No errors are defined.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also [getaddrinfo\(3XNET\)](#), [getnameinfo\(3XNET\)](#), [attributes\(5\)](#), [standards\(5\)](#)

Name getaddrinfo, getnameinfo, freeaddrinfo, gai_strerror – translate between node name and address

Synopsis

```
cc [ flag... ] file ... -lsocket -lnsl [ library ... ]
#include <sys/socket.h>
#include <netdb.h>

int getaddrinfo(const char *nodename, const char *servname,
               const struct addrinfo *hints, struct addrinfo **res);

int getnameinfo(const struct sockaddr *sa, socklen_t salen,
               char *host, size_t hostlen, char *serv, size_t servlen,
               int flags);

void freeaddrinfo(struct addrinfo *ai);

char *gai_strerror(int errcode);
```

Description These functions perform translations from node name to address and from address to node name in a protocol-independent manner.

The `getaddrinfo()` function performs the node name to address translation. The *nodename* and *servname* arguments are pointers to null-terminated strings or NULL. One or both of these arguments must be a non-null pointer. In the normal client scenario, both the *nodename* and *servname* are specified. In the normal server scenario, only the *servname* is specified.

A non-null *nodename* string can be a node name or a numeric host address string. The *nodename* can also be an IPv6 zone-id in the form:

```
<address>%<zone-id>
```

The address is the literal IPv6 link-local address or host name of the destination. The zone-id is the interface ID of the IPv6 link used to send the packet. The zone-id can either be a numeric value, indicating a literal zone value, or an interface name such as `hme0`.

A non-null *servname* string can be either a service name or a decimal port number.

The caller can optionally pass an `addrinfo` structure, pointed to by the *hints* argument, to provide hints concerning the type of socket that the caller supports.

The `addrinfo` structure is defined as:

```
struct addrinfo {
int          ai_flags;          /* AI_PASSIVE, AI_CANONNAME,
                                AI_NUMERICHOST, AI_NUMERICSERV
                                AI_V4MAPPED, AI_ALL,
                                AI_ADDRCONFIG */
int          ai_family;        /* PF_xxx */
int          ai_socktype;      /* SOCK_xxx */
int          ai_protocol;      /* 0 or IPPROTO_xxx for IPv4 & IPv6 */
socklen_t    ai_addrlen;       /* length of ai_addr */
```

```

char          *ai_canonname; /* canonical name for nodename */
struct sockadr *ai_addr;     /* binary address */
struct addrinfo *ai_next;    /* next structure in linked list */
};

```

In this *hints* structure, all members other than *ai_flags*, *ai_family*, *ai_socktype*, and *ai_protocol* must be 0 or a null pointer. A value of `PF_UNSPEC` for *ai_family* indicates that the caller will accept any protocol family. A value of 0 for *ai_socktype* indicates that the caller will accept any socket type. A value of 0 for *ai_protocol* indicates that the caller will accept any protocol. For example, if the caller handles only TCP and not UDP, then the *ai_socktype* member of the *hints* structure should be set to `SOCK_STREAM` when `getaddrinfo()` is called. If the caller handles only IPv4 and not IPv6, then the *ai_family* member of the *hints* structure should be set to `PF_INET` when `getaddrinfo()` is called. If the third argument to `getaddrinfo()` is a null pointer, it is as if the caller had filled in an *addrinfo* structure initialized to 0 with *ai_family* set to `PF_UNSPEC`.

Upon success, a pointer to a linked list of one or more *addrinfo* structures is returned through the final argument. The caller can process each *addrinfo* structure in this list by following the *ai_next* pointer, until a null pointer is encountered. In each returned *addrinfo* structure the three members *ai_family*, *ai_socktype*, and *ai_protocol* are the corresponding arguments for a call to the [socket\(3SOCKET\)](#) function. In each *addrinfo* structure the *ai_addr* member points to a filled-in socket address structure whose length is specified by the *ai_addrlen* member.

If the `AI_PASSIVE` bit is set in the *ai_flags* member of the *hints* structure, the caller plans to use the returned socket address structure in a call to [bind\(3SOCKET\)](#). In this case, if the *nodename* argument is a null pointer, the IP address portion of the socket address structure will be set to `INADDR_ANY` for an IPv4 address or `IN6ADDR_ANY_INIT` for an IPv6 address.

If the `AI_PASSIVE` bit is not set in the *ai_flags* member of the *hints* structure, then the returned socket address structure will be ready for a call to [connect\(3SOCKET\)](#) (for a connection-oriented protocol) or either [connect\(3SOCKET\)](#), [sendto\(3SOCKET\)](#), or [sendmsg\(3SOCKET\)](#) (for a connectionless protocol). If the *nodename* argument is a null pointer, the IP address portion of the socket address structure will be set to the loopback address.

If the `AI_CANONNAME` bit is set in the *ai_flags* member of the *hints* structure, then upon successful return the *ai_canonname* member of the first *addrinfo* structure in the linked list will point to a null-terminated string containing the canonical name of the specified *nodename*.

If the `AI_NUMERICHOST` bit is set in the *ai_flags* member of the *hints* structure, then a non-null *nodename* string must be a numeric host address string. Otherwise an error of `EAI_NONAME` is returned. This flag prevents any type of name resolution service (such as DNS) from being called.

If the `AI_NUMERICSERV` flag is specified, then a non-null `servname` string supplied shall be a numeric port string. Otherwise, an `[EAI_NONAME]` error is returned. This flag prevents any type of name resolution service (for example, NIS+) from being invoked.

If the `AI_V4MAPPED` flag is specified along with an `ai_family` of `AF_INET6`, then `getaddrinfo()` returns IPv4-mapped IPv6 addresses on finding no matching IPv6 addresses (`ai_addrlen` shall be 16). For example, if no AAAA records are found when using DNS, a query is made for A records. Any found records are returned as IPv4-mapped IPv6 addresses.

The `AI_V4MAPPED` flag is ignored unless `ai_family` equals `AF_INET6`.

If the `AI_ALL` flag is used with the `AI_V4MAPPED` flag, then `getaddrinfo()` returns all matching IPv6 and IPv4 addresses. For example, when using the DNS, queries are made for both AAAA records and A records, and `getaddrinfo()` returns the combined results of both queries. Any IPv4 addresses found are returned as IPv4-mapped IPv6 addresses.

The `AI_ALL` flag without the `AI_V4MAPPED` flag is ignored.

When `ai_family` is not specified (`AF_UNSPEC`), `AI_V4MAPPED` and `AI_ALL` flags are used only if `AF_INET6` is supported.

If the `AI_ADDRCONFIG` flag is specified, IPv4 addresses are returned only if an IPv4 address is configured on the local system, and IPv6 addresses are returned only if an IPv6 address is configured on the local system. For this case, the loopback address is not considered to be as valid as a configured address. For example, when using the DNS, a query for AAAA records should occur only if the node has at least one IPv6 address configured (other than IPv6 loopback) and a query for A records should occur only if the node has at least one IPv4 address configured (other than the IPv4 loopback).

All of the information returned by `getaddrinfo()` is dynamically allocated: the `addrinfo` structures as well as the socket address structures and canonical node name strings pointed to by the `addrinfo` structures. The `freeaddrinfo()` function is called to return this information to the system. For `freeaddrinfo()`, the `addrinfo` structure pointed to by the `ai` argument is freed, along with any dynamic storage pointed to by the structure. This operation is repeated until a null `ai_next` pointer is encountered.

To aid applications in printing error messages based on the `EAI_*` codes returned by `getaddrinfo()`, the `gai_strerror()` is defined. The argument is one of the `EAI_*` values defined below and the return value points to a string describing the error. If the argument is not one of the `EAI_*` values, the function still returns a pointer to a string whose contents indicate an unknown error.

The `getnameinfo()` function looks up an IP address and port number provided by the caller in the name service database and system-specific database, and returns text strings for both in buffers provided by the caller. The function indicates successful completion by a 0 return value; a non-zero return value indicates failure.

The first argument, *sa*, points to either a `sockaddr_in` structure (for IPv4) or a `sockaddr_in6` structure (for IPv6) that holds the IP address and port number. The *salen* argument gives the length of the `sockaddr_in` or `sockaddr_in6` structure.

The function returns the node name associated with the IP address in the buffer pointed to by the *host* argument.

The function can also return the IPv6 zone-id in the form:

```
<address>%<zone-id>
```

The caller provides the size of this buffer with the *hostlen* argument. The service name associated with the port number is returned in the buffer pointed to by *serv*, and the *servlen* argument gives the length of this buffer. The caller specifies not to return either string by providing a 0 value for the *hostlen* or *servlen* arguments. Otherwise, the caller must provide buffers large enough to hold the node name and the service name, including the terminating null characters.

To aid the application in allocating buffers for these two returned strings, the following constants are defined in `<netdb.h>`:

```
#define NI_MAXHOST  1025
#define NI_MAXSERV  32
```

The final argument is a flag that changes the default actions of this function. By default, the fully-qualified domain name (FQDN) for the host is looked up in the name service database and returned. If the flag bit `NI_NOFQDN` is set, only the node name portion of the FQDN is returned for local hosts.

If the flag bit `NI_NUMERICHOST` is set, or if the host's name cannot be located in the name service, the numeric form of the host's address is returned instead of its name, for example, by calling `inet_ntop()` (see [inet\(3SOCKET\)](#)) instead of [getipnodebyname\(3SOCKET\)](#). If the flag bit `NI_NAMEREQD` is set, an error is returned if the host's name cannot be located in the name service database.

If the flag bit `NI_NUMERICSERV` is set, the numeric form of the service address is returned (for example, its port number) instead of its name. The two `NI_NUMERIC*` flags are required to support the `-n` flag that many commands provide.

A fifth flag bit, `NI_DGRAM`, specifies that the service is a datagram service, and causes [getservbyport\(3SOCKET\)](#) to be called with a second argument of `udp` instead of the default `tcp`. This is required for the few ports (for example, 512-514) that have different services for UDP and TCP.

These `NI_*` flags are defined in `<netdb.h>` along with the `AI_*` flags already defined for `getaddrinfo()`.

Return Values For `getaddrinfo()`, if the query is successful, a pointer to a linked list of one or more `addrinfo` structures is returned by the fourth argument and the function returns `0`. The order of the addresses returned in the fourth argument is discussed in the ADDRESS ORDERING section. If the query fails, a non-zero error code will be returned. For `getnameinfo()`, if successful, the strings `hostname` and `service` are copied into `host` and `serv`, respectively. If unsuccessful, zero values for either `hostlen` or `servlen` will suppress the associated lookup; in this case no data is copied into the applicable buffer. If `gai_strerror()` is successful, a pointer to a string containing an error message appropriate for the `EAI_*` errors is returned. If `errcode` is not one of the `EAI_*` values, a pointer to a string indicating an unknown error is returned.

Address Ordering `AF_INET6` addresses returned by the fourth argument of `getaddrinfo()` are ordered according to the algorithm described in *RFC 3484, Default Address Selection for Internet Protocol version 6 (IPv6)*. The addresses are ordered using a list of pair-wise comparison rules which are applied in order. If a rule determines that one address is better than another, the remaining rules are irrelevant to the comparison of those two addresses. If two addresses are equivalent according to one rule, the remaining rules act as a tie-breaker. The address ordering list of pair-wise comparison rules follow below:

Avoid unusable destinations.	Prefer a destination that is reachable through the IP routing table.
Prefer matching scope.	Prefer a destination whose scope is equal to the scope of its source address. See inet6(7P) for the definition of scope used by this rule.
Avoid link-local source.	Avoid selecting a link-local source address when the destination address is not a link-local address.
Avoid deprecated addresses.	Prefer a destination that is not deprecated (<code>IFF_DEPRECATED</code>).
Prefer matching label. This rule uses labels that are obtained through the IPv6 default address selection policy table. See ipaddrsel(1M) for a description of the default contents of the table and how the table is configured.	Prefer a destination whose label is equal to the label of its source address.
Prefer higher precedence. This rule uses precedence values that are obtained through the IPv6 default address selection policy table. See ipaddrsel(1M) for a description of the default contents of the table and how the table is configured.	Prefer the destination whose precedence is higher than the other destination.
Prefer native transport.	Prefer a destination if the interface that is used for sending packets to that destination is not an IP over IP tunnel.
Prefer smaller scope. See inet6(7P) for the definition of this rule.	Prefer the destination whose scope is smaller than the other destination.

Use longest matching prefix.	When the two destinations belong to the same address family, prefer the destination that has the longer matching prefix with its source address.
------------------------------	--

Errors The following names are the error values returned by `getaddrinfo()` and are defined in `<netdb.h>`:

<code>EAI_ADDRFAMILY</code>	Address family for <i>nodename</i> is not supported.
<code>EAI_AGAIN</code>	Temporary failure in name resolution has occurred .
<code>EAI_BADFLAGS</code>	Invalid value specified for <i>ai_flags</i> .
<code>EAI_FAIL</code>	Non-recoverable failure in name resolution has occurred.
<code>EAI_FAMILY</code>	The <i>ai_family</i> is not supported.
<code>EAI_MEMORY</code>	Memory allocation failure has occurred.
<code>EAI_NODATA</code>	No address is associated with <i>nodename</i> .
<code>EAI_NONAME</code>	Neither <i>nodename</i> nor <i>servname</i> is provided or known.
<code>EAI_SERVICE</code>	The <i>servname</i> is not supported for <i>ai_socktype</i> .
<code>EAI_SOCKTYPE</code>	The <i>ai_socktype</i> is not supported.
<code>EAI_OVERFLOW</code>	Argument buffer has overflowed.
<code>EAI_SYSTEM</code>	System error was returned in <i>errno</i> .

Files	<code>/etc/inet/hosts</code>	local database that associates names of nodes with IP addresses
	<code>/etc/netconfig</code>	network configuration database
	<code>/etc/nsswitch.conf</code>	configuration file for the name service switch

Attributes See [attributes\(5\)](#) for description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [ipaddrsel\(1M\)](#), [gethostbyname\(3NSL\)](#), [getipnodebyname\(3SOCKET\)](#), [htonl\(3SOCKET\)](#), [inet\(3SOCKET\)](#), [netdb.h\(3HEAD\)](#), [socket\(3SOCKET\)](#), [hosts\(4\)](#), [nsswitch.conf\(4\)](#), [inet6\(7P\)](#)

Draves, R. *RFC 3484, Default Address Selection for Internet Protocol version 6 (IPv6)*. Network Working Group. February 2003.

Notes IPv4-mapped addresses are not recommended.

Name gethostbyname, gethostbyname_r, gethostbyaddr, gethostbyaddr_r, gethostent, gethostent_r, sethostent, endhostent – get network host entry

Synopsis `cc [flag...] file... -lnsl [library...]
#include <netdb.h>`

```
struct hostent *gethostbyname(const char *name);

struct hostent *gethostbyname_r(const char *name,
                                struct hostent *result, char *buffer, int buflen,
                                int *h_errnop);

struct hostent *gethostbyaddr(const char *addr, int len,
                              int type);

struct hostent *gethostbyaddr_r(const char *addr, int length,
                                int type, struct hostent *result, char *buffer,
                                int buflen, int *h_errnop);

struct hostent *gethostent(void);

struct hostent *gethostent_r(struct hostent *result,
                             char *buffer, int buflen, int *h_errnop);

int sethostent(int stayopen);

int endhostent(void);
```

Description These functions are used to obtain entries describing hosts. An entry can come from any of the sources for hosts specified in the `/etc/nsswitch.conf` file. See [nsswitch.conf\(4\)](#). These functions have been superseded by [getipnodebyname\(3SOCKET\)](#), [getipnodebyaddr\(3SOCKET\)](#), and [getaddrinfo\(3SOCKET\)](#), which provide greater portability to applications when multithreading is performed or technologies such as IPv6 are used. For example, the functions described in the following cannot be used with applications targeted to work with IPv6.

The `gethostbyname()` function searches for information for a host with the hostname specified by the character-string parameter *name*.

The `gethostbyaddr()` function searches for information for a host with a given host address. The parameter *type* specifies the family of the address. This should be one of the address families defined in `<sys/socket.h>`. See the NOTES section for more information. Also see the EXAMPLES section for information on how to convert an Internet IP address notation that is separated by periods (.) into an *addr* parameter. The parameter *len* specifies the length of the buffer indicated by *addr*.

All addresses are returned in network order. In order to interpret the addresses, [byteorder\(3SOCKET\)](#) must be used for byte order conversion.

The `sethostent()`, `gethostent()`, and `endhostent()` functions are used to enumerate host entries from the database.

The `sethostent()` function sets or resets the enumeration to the beginning of the set of host entries. This function should be called before the first call to `gethostent()`. Calls to `gethostbyname()` and `gethostbyaddr()` leave the enumeration position in an indeterminate state. If the *stayopen* flag is non-zero, the system can keep allocated resources such as open file descriptors until a subsequent call to `endhostent()`.

Successive calls to the `gethostent()` function return either successive entries or `NULL`, indicating the end of the enumeration.

The `endhostent()` function can be called to indicate that the caller expects to do no further host entry retrieval operations; the system can then deallocate resources it was using. It is still allowed, but possibly less efficient, for the process to call more host retrieval functions after calling `endhostent()`.

Reentrant Interfaces The `gethostbyname()`, `gethostbyaddr()`, and `gethostent()` functions use static storage that is reused in each call, making these functions unsafe for use in multithreaded applications.

The `gethostbyname_r()`, `gethostbyaddr_r()`, and `gethostent_r()` functions provide reentrant interfaces for these operations.

Each reentrant interface performs the same operation as its non-reentrant counterpart, named by removing the `_r` suffix. The reentrant interfaces, however, use buffers supplied by the caller to store returned results and the interfaces are safe for use in both single-threaded and multithreaded applications.

Each reentrant interface takes the same parameters as its non-reentrant counterpart, as well as the following additional parameters. The parameter *result* must be a pointer to a `struct hostent` structure allocated by the caller. On successful completion, the function returns the host entry in this structure. The parameter *buffer* must be a pointer to a buffer supplied by the caller. This buffer is used as storage space for the host data. All of the pointers within the returned `struct hostent` *result* point to data stored within this buffer. See the **RETURN VALUES** section for more information. The buffer must be large enough to hold all of the data associated with the host entry. The parameter *buflen* should give the size in bytes of the buffer indicated by *buffer*. The parameter *h_errnop* should be a pointer to an integer. An integer error status value is stored there on certain error conditions. See the **ERRORS** section for more information.

For enumeration in multithreaded applications, the position within the enumeration is a process-wide property shared by all threads. The `sethostent()` function can be used in a multithreaded application but resets the enumeration position for all threads. If multiple threads interleave calls to `gethostent_r()`, the threads will enumerate disjoint subsets of the host database.

Like their non-reentrant counterparts, `gethostbyname_r()` and `gethostbyaddr_r()` leave the enumeration position in an indeterminate state.

Return Values Host entries are represented by the `struct hostent` structure defined in `<netdb.h>`:

```
struct hostent {
    char    *h_name;           /* canonical name of host */
    char    **h_aliases;       /* alias list */
    int     h_addrtype;        /* host address type */
    int     h_length;          /* length of address */
    char    **h_addr_list;     /* list of addresses */
};
```

See the **EXAMPLES** section for information about how to retrieve a "." separated Internet IP address string from the `h_addr_list` field of `struct hostent`.

The `gethostbyname()`, `gethostbyname_r()`, `gethostbyaddr()`, and `gethostbyaddr_r()` functions each return a pointer to a `struct hostent` if they successfully locate the requested entry; otherwise they return `NULL`.

The `gethostent()` and `gethostent_r()` functions each return a pointer to a `struct hostent` if they successfully enumerate an entry; otherwise they return `NULL`, indicating the end of the enumeration.

The `gethostbyname()`, `gethostbyaddr()`, and `gethostent()` functions use static storage, so returned data must be copied before a subsequent call to any of these functions if the data is to be saved.

When the pointer returned by the reentrant functions `gethostbyname_r()`, `gethostbyaddr_r()`, and `gethostent_r()` is not `NULL`, it is always equal to the *result* pointer that was supplied by the caller.

The `sethostent()` and `endhostent()` functions return `0` on success.

Errors The reentrant functions `gethostbyname_r()`, `gethostbyaddr_r()`, and `gethostent_r()` will return `NULL` and set *errno* to `ERANGE` if the length of the buffer supplied by caller is not large enough to store the result. See [Intro\(2\)](#) for the proper usage and interpretation of *errno* in multithreaded applications.

The reentrant functions `gethostbyname_r()` and `gethostbyaddr_r()` set the integer pointed to by *h_errnop* to one of these values in case of error.

On failures, the non-reentrant functions `gethostbyname()` and `gethostbyaddr()` set a global integer *h_errno* to indicate one of these error codes (defined in `<netdb.h>`): `HOST_NOT_FOUND`, `TRY_AGAIN`, `NO_RECOVERY`, `NO_DATA`, and `NO_ADDRESS`.

If a resolver is provided with a malformed address, or if any other error occurs before `gethostbyname()` is resolved, then `gethostbyname()` returns an internal error with a value of `-1`.

The `gethostbyname()` function will set *h_errno* to `NETDB_INTERNAL` when it returns a `NULL` value.

Examples EXAMPLE 1 Using `gethostbyaddr()`

Here is a sample program that gets the canonical name, aliases, and “.” separated Internet IP addresses for a given “.” separated IP address:

```
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <sys/types.h>
#include <sys/socket.h>
#include <netinet/in.h>
#include <arpa/inet.h>
#include <netdb.h>
int main(int argc, const char **argv)
{
    in_addr_t addr;
    struct hostent *hp;
    char **p;
    if (argc != 2) {
        (void) printf("usage: %s IP-address\n", argv[0]);
        exit (1);
    }
    if ((int)(addr = inet_addr(argv[1])) == -1) {
        (void) printf("IP-address must be of the form a.b.c.d\n");
        exit (2);
    }
    hp = gethostbyaddr((char *)&addr, 4, AF_INET);
    if (hp == NULL) {
        (void) printf("host information for %s not found\n", argv[1]);
        exit (3);
    }
    for (p = hp->h_addr_list; *p != 0; p++) {
        struct in_addr in;
        char **q;
        (void) memcpy(&in.s_addr, *p, sizeof (in.s_addr));
        (void) printf("%s %s", inet_ntoa(in), hp->h_name);
        for (q = hp->h_aliases; *q != 0; q++)
            (void) printf(" %s", *q);
        (void) putchar('\n');
    }
    exit (0);
}
```

Note that the preceding sample program is unsafe for use in multithreaded applications.

Files	<code>/etc/hosts</code>	hosts file that associates the names of hosts with their Internet Protocol (IP) addresses
	<code>/etc/netconfig</code>	network configuration database
	<code>/etc/nsswitch.conf</code>	configuration file for the name service switch

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	See Reentrant Interfaces in the DESCRIPTION section.

See Also [Intro\(2\)](#), [Intro\(3\)](#), [byteorder\(3SOCKET\)](#), [inet\(3SOCKET\)](#), [netdb.h\(3HEAD\)](#), [netdir\(3NSL\)](#), [hosts\(4\)](#), [netconfig\(4\)](#), [nss\(4\)](#), [nsswitch.conf\(4\)](#), [attributes\(5\)](#)

Warnings The reentrant interfaces `gethostbyname_r()`, `gethostbyaddr_r()`, and `gethostent_r()` are included in this release on an uncommitted basis only and are subject to change or removal in future minor releases.

Notes To ensure that they all return consistent results, `gethostbyname()`, `gethostbyname_r()`, and `netdir_getbyname()` are implemented in terms of the same internal library function. This function obtains the system-wide source lookup policy based on the `inet` family entries in [netconfig\(4\)](#) and the `hosts:` entry in [nsswitch.conf\(4\)](#). Similarly, `gethostbyaddr()`, `gethostbyaddr_r()`, and `netdir_getbyaddr()` are implemented in terms of the same internal library function. If the `inet` family entries in [netconfig\(4\)](#) have a “-” in the last column for `nametoaddr` libraries, then the entry for `hosts` in [nsswitch.conf](#) will be used; `nametoaddr` libraries in that column will be used, and [nsswitch.conf](#) will not be consulted.

There is no analogue of `gethostent()` and `gethostent_r()` in the `netdir` functions, so these enumeration functions go straight to the `hosts` entry in [nsswitch.conf](#). Thus enumeration can return results from a different source than that used by `gethostbyname()`, `gethostbyname_r()`, `gethostbyaddr()`, and `gethostbyaddr_r()`.

All the functions that return a `struct hostent` must always return the *canonical name* in the `h_name` field. This name, by definition, is the well-known and official hostname shared between all aliases and all addresses. The underlying source that satisfies the request determines the mapping of the input name or address into the set of names and addresses in `hostent`. Different sources might do that in different ways. If there is more than one alias and more than one address in `hostent`, no pairing is implied between them.

The system attempts to put those addresses that are on the same subnet as the caller before addresses that are on different subnets. However, if address sorting is disabled by setting `SORT_ADDRS` to `FALSE` in the `/etc/default/nss` file, the system does not put the local subnet addresses first. See [nss\(4\)](#) for more information.

When compiling multithreaded applications, see [Intro\(3\)](#), MULTITHREADED APPLICATIONS, for information about the use of the `_REENTRANT` flag.

Use of the enumeration interfaces `gethostent()` and `gethostent_r()` is discouraged; enumeration might not be supported for all database sources. The semantics of enumeration are discussed further in [nsswitch.conf\(4\)](#).

The current implementations of these functions only return or accept addresses for the Internet address family (type `AF_INET`).

The form for an address of type `AF_INET` is a `struct in_addr` defined in `<netinet/in.h>`. The functions described in [inet\(3SOCKET\)](#), and illustrated in the `EXAMPLES` section, are helpful in constructing and manipulating addresses in this form.

When the caller provides the IP address (the *addr* argument of `gethostbyaddr()` and `gethostbyaddr_r()`), the *addr* argument should be aligned on a word boundary or the code must be changed to [memcpy\(3C\)](#) the argument to an aligned area; otherwise an error such as a `SIGBUS` may result.

Name gethostname – get name of current host

Synopsis `cc [flag ...] file ... -lxnet [library ...]`
`#include <unistd.h>`

```
int gethostname(char *name, size_t namelen);
```

Description The `gethostname()` function returns the standard host name for the current machine. The *namelen* argument specifies the size of the array pointed to by the *name* argument. The returned name is null-terminated, except that if *namelen* is an insufficient length to hold the host name, then the returned name is truncated and it is unspecified whether the returned name is null-terminated.

Host names are limited to 255 bytes.

Return Values On successful completion, 0 is returned. Otherwise, -1 is returned.

Errors No errors are defined.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also [uname\(1\)](#), [gethostid\(3C\)](#), [attributes\(5\)](#), [standards\(5\)](#)

Name getipnodebyname, getipnodebyaddr, freehostent – get IP node entry

Synopsis `cc [flag...] file... -lsocket -lnsl [library...]`
`#include <sys/socket.h>`
`#include <netdb.h>`

```
struct hostent *getipnodebyname(const char *name, int af, int flags,
                                int *error_num);

struct hostent *getipnodebyaddr(const void *src, size_t len, int af,
                                int *error_num);

void freehostent(struct hostent *ptr);
```

Parameters	<i>af</i>	Address family
	<i>flags</i>	Various flags
	<i>name</i>	Name of host
	<i>error_num</i>	Error storage
	<i>src</i>	Address for lookup
	<i>len</i>	Length of address
	<i>ptr</i>	Pointer to hostent structure

Description The `getipnodebyname()` function searches the ipnodes database from the beginning. The function finds the first `h_name` member that matches the hostname specified by *name*. The function takes an *af* argument that specifies the address family. The address family can be `AF_INET` for IPv4 addresses or `AF_INET6` for IPv6 addresses. The *flags* argument determines what results are returned based on the value of *flags*. If the *flags* argument is set to 0 (zero), the default operation of the function is specified as follows:

- If the *af* argument is `AF_INET`, a query is made for an IPv4 address. If successful, IPv4 addresses are returned and the `h_length` member of the `hostent` structure is 4. Otherwise, the function returns a NULL pointer.
- If the *af* argument is `AF_INET6`, a query is made for an IPv6 address. If successful, IPv6 addresses are returned and the `h_length` member of the `hostent` structure is 16. Otherwise, the function returns a NULL pointer.

The *flags* argument changes the default actions of the function. Set the *flags* argument with a logical OR operation on any of combination of the following values:

```
AI_V4MAPPED
AI_ALL
AI_ADDRCONFIG
```

The special flags value, `AI_DEFAULT`, should handle most applications. Porting simple applications to use IPv6 replaces the call

```
hptr = gethostbyname(name);
```

with

```
hptr = getipnodebyname(name, AF_INET6, AI_DEFAULT, &error_num);
```

The *flags* value 0 (zero) implies a strict interpretation of the *af* argument:

- If *flags* is 0 and *af* is AF_INET, the caller wants only IPv4 addresses. A query is made for A records. If successful, IPv4 addresses are returned and the *h_length* member of the *hostent* structure is 4. Otherwise, the function returns a NULL pointer.
- If *flags* is 0 and *af* is AF_INET6, the caller wants only IPv6 addresses. A query is made for AAAA records. If successful, IPv6 addresses are returned and the *h_length* member of the *hostent* structure is 16. Otherwise, the function returns a NULL pointer.

Logically OR other constants into the *flags* argument to modify the behavior of the `getipnodebyname()` function.

- If the AI_V4MAPPED flag is specified with *af* set to AF_INET6, the caller can accept IPv4-mapped IPv6 addresses. If no AAAA records are found, a query is made for A records. Any A records found are returned as IPv4-mapped IPv6 addresses and the *h_length* is 16. The AI_V4MAPPED flag is ignored unless *af* equals AF_INET6.
- The AI_ALL flag is used in conjunction with the AI_V4MAPPED flag, exclusively with the IPv6 address family. When AI_ALL is logically ORed with AI_V4MAPPED flag, the caller wants all addresses: IPv6 and IPv4-mapped IPv6 addresses. A query is first made for AAAA records and, if successful, IPv6 addresses are returned. Another query is then made for A records. Any A records found are returned as IPv4-mapped IPv6 addresses and the *h_length* is 16. Only when both queries fail does the function return a NULL pointer. The AI_ALL flag is ignored unless *af* is set to AF_INET6.
- The AI_ADDRCONFIG flag specifies that a query for AAAA records should occur only when the node is configured with at least one IPv6 source address. A query for A records should occur only when the node is configured with at least one IPv4 source address. For example, if a node is configured with no IPv6 source addresses, *af* equals AF_INET6, and the node name queried has both AAAA and A records, then:
 - A NULL pointer is returned when only the AI_ADDRCONFIG value is specified.
 - The A records are returned as IPv4-mapped IPv6 addresses when the AI_ADDRCONFIG and AI_V4MAPPED values are specified.

The special flags value, AI_DEFAULT, is defined as

```
#define AI_DEFAULT (AI_V4MAPPED | AI_ADDRCONFIG)
```

The `getipnodebyname()` function allows the *name* argument to be a node name or a literal address string: a dotted-decimal IPv4 address or an IPv6 hex address. Applications do not have to call `inet_pton(3SOCKET)` to handle literal address strings.

Four scenarios arise based on the type of literal address string and the value of the *af* argument. The two simple cases occur when *name* is a dotted-decimal IPv4 address and *af* equals AF_INET and when *name* is an IPv6 hex address and *af* equals AF_INET6. The members of the returned hostent structure are:

<code>h_name</code>	Pointer to a copy of the name argument
<code>h_aliases</code>	NULL pointer.
<code>h_addrtype</code>	Copy of the <i>af</i> argument.
<code>h_length</code>	4 for AF_INET or 16 for AF_INET6.
<code>h_addr_list</code>	Array of pointers to 4-byte or 16-byte binary addresses. The array is terminated by a NULL pointer.

Return Values Upon successful completion, `getipnodebyname()` and `getipnodebyaddr()` return a hostent structure. Otherwise they return NULL.

The hostent structure does not change from the existing definition when used with [gethostbyname\(3NSL\)](#). For example, host entries are represented by the struct hostent structure defined in `<netdb.h>`:

```
struct hostent {
    char    *h_name;           /* canonical name of host */
    char    **h_aliases;       /* alias list */
    int     h_addrtype;        /* host address type */
    int     h_length;          /* length of address */
    char    **h_addr_list;     /* list of addresses */
};
```

An error occurs when *name* is an IPv6 hex address and *af* equals AF_INET. The return value of the function is a NULL pointer and `error_num` equals HOST_NOT_FOUND.

The `getipnodebyaddr()` function has the same arguments as the existing [gethostbyaddr\(3NSL\)](#) function, but adds an error number. As with `getipnodebyname()`, `getipnodebyaddr()` is thread-safe. The `error_num` value is returned to the caller with the appropriate error code to support thread-safe error code returns. The following error conditions can be returned for `error_num`:

HOST_NOT_FOUND	Host is unknown.
NO_DATA	No address is available for the <i>name</i> specified in the server request. This error is not a soft error. Another type of <i>name</i> server request might be successful.
NO_RECOVERY	An unexpected server failure occurred, which is a non-recoverable error.
TRY_AGAIN	This error is a soft error that indicates that the local server did not receive a response from an authoritative server. A retry at some later

time might be successful.

One possible source of confusion is the handling of IPv4-mapped IPv6 addresses and IPv4-compatible IPv6 addresses, but the following logic should apply:

1. If *af* is AF_INET6, and if *len* equals 16, and if the IPv6 address is an IPv4-mapped IPv6 address or an IPv4-compatible IPv6 address, then skip over the first 12 bytes of the IPv6 address, set *af* to AF_INET, and set *len* to 4.
2. If *af* is AF_INET, lookup the *name* for the given IPv4 address.
3. If *af* is AF_INET6, lookup the *name* for the given IPv6 address.
4. If the function is returning success, then the single address that is returned in the *hostent* structure is a copy of the first argument to the function with the same address family that was passed as an argument to this function.

All four steps listed are performed in order.

This structure, and the information pointed to by this structure, are dynamically allocated by `getipnodebyname()` and `getipnodebyaddr()`. The `freehostent()` function frees this memory.

Examples **EXAMPLE 1** Getting the Canonical Name, Aliases, and Internet IP Addresses for a Given Hostname

The following is a sample program that retrieves the canonical name, aliases, and all Internet IP addresses, both version 6 and version 4, for a given hostname.

```
#include <stdio.h>
#include <string.h>
#include <sys/types.h>
#include <sys/socket.h>
#include <netinet/in.h>
#include <arpa/inet.h>
#include <netdb.h>

main(int argc, const char **argv)
{
    char abuf[INET6_ADDRSTRLEN];
    int error_num;
    struct hostent *hp;
    char **p;

    if (argc != 2) {
        (void) printf("usage: %s hostname\n", argv[0]);
        exit (1);
    }

    /* argv[1] can be a pointer to a hostname or literal IP address */
```


EXAMPLE 1 Getting the Canonical Name, Aliases, and Internet IP Addresses for a Given Hostname
(Continued)

```

hp = getipnodebyname(argv[1], AF_INET6, AI_ALL | AI_ADDRCONFIG |
    AI_V4MAPPED, &error_num);
if (hp == NULL) {
    if (error_num == TRY_AGAIN) {
        printf("%s: unknown host or invalid literal address "
            "(try again later)\n", argv[1]);
    } else {
        printf("%s: unknown host or invalid literal address\n",
            argv[1]);
    }
    exit (1);
}
for (p = hp->h_addr_list; *p != 0; p++) {
    struct in6_addr in6;
    char **q;

    bcopy(*p, (caddr_t)&in6, hp->h_length);
    (void) printf("%s\t%s", inet_ntop(AF_INET6, (void *)&in6,
        abuf, sizeof(abuf)), hp->h_name);
    for (q = hp->h_aliases; *q != 0; q++)
        (void) printf(" %s", *q);
    (void) putchar('\n');
}
freehostent(hp);
exit (0);
}

```

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Evolving
MT-Level	Safe

See Also [getaddrinfo\(3SOCKET\)](#), [gethostbyname\(3NSL\)](#), [htonl\(3SOCKET\)](#), [inet\(3SOCKET\)](#), [netdb.h\(3HEAD\)](#), [hosts\(4\)](#), [nsswitch.conf\(4\)](#), [attributes\(5\)](#)

Notes No enumeration functions are provided for IPv6. Existing enumeration functions such as [sethostent\(3NSL\)](#) do not work in combination with the [getipnodebyname\(\)](#) and [getipnodebyaddr\(\)](#) functions.

All the functions that return a `struct hostent` must always return the canonical in the `h_name` field. This name, by definition, is the well-known and official hostname shared between all aliases and all addresses. The underlying source that satisfies the request determines the mapping of the input name or address into the set of names and addresses in `hostent`. Different sources might make such a determination in different ways. If more than one alias and more than one address in `hostent` exist, no pairing is implied between the alias and address.

The current implementations of these functions return or accept only addresses for the Internet address family (type `AF_INET`) or the Internet address family Version 6 (type `AF_INET6`).

The form for an address of type `AF_INET` is a `struct in_addr` defined in `<netinet/in.h>`. The form for an address of type `AF_INET6` is a `struct in6_addr`, also defined in `<netinet/in.h>`. The functions described in [inet_ntop\(3SOCKET\)](#) and [inet_pton\(3SOCKET\)](#) that are illustrated in the `EXAMPLES` section are helpful in constructing and manipulating addresses in either of these forms.

Name getipsecalgbyname, getipsecalgbynum, freeipsecalgent – query algorithm mapping entries

Synopsis `cc -flag ... file ...-lnsl [-library ...]
#include <netdb.h>`

```
struct ipsecalgent *getipsecalgbyname
    (const char *alg_name, int protocol_num, int *errnop)
struct ipsecalgent *getipsecalgbynum(int alg_num, int protocol_num,
    int *errnop)
void freeipsecalgent(struct ipsecalgent *ptr)
```

Description Use the `getipsecalgbyname()`, `getipsecalgbynum()`, `freeipsecalgent()` functions to obtain the IPsec algorithm mappings that are defined by [ipsecalgs\(1M\)](#). The IPsec algorithms and associated protocol name spaces are defined by *RFC 2407*.

`getipsecalgbyname()` and `getipsecalgbynum()` return a structure that describes the algorithm entry found. This structure is described in the RETURN VALUES section below.

`freeipsecalgent()` must be used by the caller to free the structures returned by `getipsecalgbyname()` and `getipsecalgbynum()` when they are no longer needed.

Both `getipsecalgbyname()` and `getipsecalgbynum()` take as parameter the protocol identifier in which the algorithm is defined. See [getipsecprotobyname\(3NSL\)](#) and [getipsecprotobyname\(3NSL\)](#).

The following protocol numbers are pre-defined:

IPSEC_PROTO_ESP	Defines the encryption algorithms (transforms) that can be used by IPsec to provide data confidentiality.
IPSEC_PROTO_AH	Defines the authentication algorithms (transforms) that can be used by IPsec to provide authentication.

`getipsecalgbyname()` looks up the algorithm by its name, while `getipsecalgbynum()` looks up the algorithm by its assigned number.

Parameters `errnop` A pointer to an integer used to return an error status value on certain error conditions. See ERRORS.

Return Values The `getipsecalgbyname()` and `getipsecalgbynum()` functions return a pointer to the structure `ipsecalgent_t`, defined in `<netdb.h>`. If the requested algorithm cannot be found, these functions return NULL.

The structure `ipsecalgent_t` is defined as follows:

```
typedef struct ipsecalgent {
    char **a_names;      /* algorithm names */
```

```
int a_proto_num;    /* protocol number */
int a_alg_num;      /* algorithm number */
char *a_mech_name;  /* mechanism name */
int *a_block_sizes; /* supported block sizes */
int *a_key_sizes;   /* supported key sizes */
int a_key_increment; /* key size increment */
} ipsecalgent_t;
```

If `a_key_increment` is non-zero, `a_key_sizes[0]` contains the default key size for the algorithm. `a_key_sizes[1]` and `a_key_sizes[2]` specify the smallest and biggest key sizes support by the algorithm, and `a_key_increment` specifies the valid key size increments in that range.

If `a_key_increment` is zero, the array `a_key_sizes` contains the set of key sizes, in bits, supported by the algorithm. The last key length in the array is followed by an element of value 0. The first element of this array is used as the default key size for the algorithm.

`a_name` is an array of algorithm names, terminated by an element containing a NULL pointer. `a_name[0]` is the primary name for the algorithm.

`a_proto_num` is the protocol identifier of this algorithm. `a_alg_num` is the algorithm number. `a_mech_name` contains the mechanism name associated with the algorithm.

`a_block_sizes` is an array containing the supported block lengths or MAC lengths, in bytes, supported by the algorithm. The last valid value in the array is followed by an element containing the value 0.

Errors When the specified algorithm cannot be returned to the caller, `getipsecalgbyname()` and `getipsecalgbyname()` return a value of NULL and set the integer pointed to by the *errno* parameter to one of the following values:

- ENOMEM Not enough memory
- ENOENT Specified algorithm not found
- EINVAL Specified protocol number not found

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32 bit) SUNWcslx (64 bit)
MT Level	MT Safe
Interface Stability	Evolving

See Also [cryptoadm\(1M\)](#), [ipsecalgs\(1M\)](#), [getipseccprotobyname\(3NSL\)](#),
[getipseccprotobyname\(3NSL\)](#), [attributes\(5\)](#)

Piper, D. *RFC 2407, The Internet IP Security Domain of Interpretation for ISAKMP*. Network Working Group. November, 1998.

Name getipsecprotobyname, getipsecprotobynum – query IPsec protocols entries

Synopsis `cc -flag ... file ...-lnsl [-library ...]
#include <netdb.h>`

```
int getipsecprotobyname(const char *proto_name  
char *getipsecprotobynum(int proto_num)
```

Description Use the `getipsecprotobyname()` and `getipsecprotobynum()` functions to obtain the IPsec algorithm mappings that are defined by [ipsecalgs\(1M\)](#). You can also use the `getipsecprotobyname()` and `getipsecprotobynum()` functions in conjunction with [getipsecalgbyname\(3NSL\)](#) and [getipsecalgbynum\(3NSL\)](#) to obtain information about the supported IPsec algorithms. The IPsec algorithms and associated protocol name spaces are defined by *RFC 2407*.

`getipsecprotobyname()` takes as an argument the name of an IPsec protocol and returns its assigned protocol number. The character string returned by the `getipsecprotobyname()` function must be freed by the caller when it is no longer needed.

`getipsecprotobynum()` takes as an argument a protocol number and returns the corresponding protocol name.

The following protocol numbers are pre-defined:

- IPSEC_PROTO_ESP** Defines the encryption algorithms (transforms) that can be used by IPsec to provide data confidentiality.
- IPSEC_PROTO_AH** Defines the authentication algorithms (transforms) that can be used by IPsec to provide authentication.

Parameters *proto_name* A pointer to the name of an IPsec protocol.
proto_num A pointer to a protocol number. conditions.

Return Values The `getipsecprotobyname()` function returns a protocol number upon success, or `-1` if the protocol specified does not exist.

The `getipsecprotobynum()` function returns a protocol name upon success, or the `NULL` value if the protocol number specified does not exist.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32 bit)
	SUNWcslx (64 bit)

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	MT Safe
Interface Stability	Evolving

See Also [ipsecalgs\(1M\)](#), [getipsecalgbyname\(3NSL\)](#), [getipsecalgbyname\(3NSL\)](#), [attributes\(5\)](#)

Piper, D. *RFC 2407, The Internet IP Security Domain of Interpretation for ISAKMP*. Network Working Group. November, 1998.

Name getnameinfo – get name information

Synopsis

```
cc [ flag ... ] file ... -lxnet [ library ... ]  
#include <sys/socket.h>  
#include <netdb.h>
```

```
int getnameinfo(const struct sockaddr *restrict sa, socklen_t salen,  
                char *restrict node, socklen_t nodelen, char *restrict service,  
                socklen_t servicen, unsigned flags);
```

Description The `getnameinfo()` function translates a socket address to a node name and service location, all of which are defined as in [getaddrinfo\(3XNET\)](#).

The *sa* argument points to a socket address structure to be translated. If the socket address structure contains an IPv4-mapped IPv6 address or an IPv4-compatible IPv6 address, the implementation extracts the embedded IPv4 address and lookup the node name for that IPv4 address.

If the *node* argument is non-NULL and the *nodelen* argument is non-zero, then the *node* argument points to a buffer able to contain up to *nodelen* characters that receives the node name as a null-terminated string. If the *node* argument is NULL or the *nodelen* argument is zero, the node name is not returned. If the node's name cannot be located, the numeric form of the node's address is returned instead of its name.

If the *service* argument is non-NULL and the *servicen* argument is non-zero, then the *service* argument points to a buffer able to contain up to *servicen* bytes that receives the service name as a null-terminated string. If the *service* argument is NULL or the *servicen* argument is zero, the service name is not returned. If the service's name cannot be located, the numeric form of the service address (for example, its port number) is returned instead of its name.

The *flags* argument is a flag that changes the default actions of the function. By default the fully-qualified domain name (FQDN) for the host is returned, but:

- If the flag bit `NI_NOFQDN` is set, only the node name portion of the FQDN is returned for local hosts.
- If the flag bit `NI_NUMERICHOST` is set, the numeric form of the host's address is returned instead of its name, under all circumstances.
- If the flag bit `NI_NAMEREQD` is set, an error is returned if the host's name cannot be located.
- If the flag bit `NI_NUMERICSERV` is set, the numeric form of the service address is returned (for example, its port number) instead of its name, under all circumstances.
- If the flag bit `NI_DGRAM` is set, this indicates that the service is a datagram service (`SOCK_DGRAM`). The default behavior assumes that the service is a stream service (`SOCK_STREAM`).

Return Values A 0 return value for `getnameinfo()` indicates successful completion; a non-zero return value indicates failure. The possible values for the failures are listed in the ERRORS section.

Upon successful completion, `getnameinfo()` returns the node and service names, if requested, in the buffers provided. The returned names are always null-terminated strings.

Errors The `getnameinfo()` function will fail if:

EAI_AGAIN	The name could not be resolved at this time. Future attempts might succeed.
EAI_BADFLAGS	The <i>flags</i> argument had an invalid value.
EAI_FAIL	A non-recoverable error occurred.
EAI_FAMILY	The address family was not recognized or the address length was invalid for the specified family.
EAI_MEMORY	There was a memory allocation failure.
EAI_NONAME	The name does not resolve for the supplied parameters. <code>NI_NAMEREQD</code> is set and the host's name cannot be located, or both <i>nodename</i> and <i>servname</i> were NULL.
EAI_SYSTEM	A system error occurred. The error code can be found in <code>errno</code> .

Usage If the returned values are to be used as part of any further name resolution (for example, passed to `getaddrinfo()`), applications should provide buffers large enough to store any result possible on the system.

Given the IPv4-mapped IPv6 address “::ffff:1.2.3.4”, the implementation performs a lookup as if the socket address structure contains the IPv4 address “1.2.3.4”.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also [gai_strerror\(3XNET\)](#), [getaddrinfo\(3XNET\)](#), [getservbyname\(3XNET\)](#), [socket\(3XNET\)](#), [attributes\(5\)](#), [standards\(5\)](#)

Notes The IPv6 unspecified address (“::”) and the IPv6 loopback address (“::1”) are not IPv4-compatible addresses. If the address is the IPv6 unspecified address (“::”), a lookup is not performed, and the `EAI_NONAME` error is returned.

The two `NI_NUMERICxxx` flags are required to support the `-n` flag that many commands provide.

The `NI_DGRAM` flag is required for the few `AF_INET` and `AF_INET6` port numbers (for example, [512,514]) that represent different services for UDP and TCP.

Name getnetbyname, getnetbyname_r, getnetbyaddr, getnetbyaddr_r, getnetent, getnetent_r, setnetent, endnetent – get network entry

Synopsis cc [*flag* ...] *file* ... -lsocket -lnsl [*library* ...]
#include <netdb.h>

```
struct netent *getnetbyname(const char *name);

struct netent *getnetbyname_r(const char *name, struct netent *result,
    char *buffer, int buflen);

struct netent *getnetbyaddr(long net, int type);

struct netent *getnetbyaddr_r(long net, int type, struct netent *result,
    char *buffer, int buflen);

struct netent *getnetent(void);

struct netent *getnetent_r(struct netent *result, char *buffer,
    int buflen);

int setnetent(int stayopen);

int endnetent(void);
```

Description These functions are used to obtain entries for networks. An entry may come from any of the sources for networks specified in the `/etc/nsswitch.conf` file. See [nsswitch.conf\(4\)](#).

`getnetbyname()` searches for a network entry with the network name specified by the character string parameter *name*.

`getnetbyaddr()` searches for a network entry with the network address specified by *net*. The parameter *type* specifies the family of the address. This should be one of the address families defined in `<sys/socket.h>`. See the NOTES section below for more information.

Network numbers and local address parts are returned as machine format integer values, that is, in host byte order. See also [inet\(3SOCKET\)](#).

The `netent.n_net` member in the `netent` structure pointed to by the return value of the above functions is calculated by `inet_network()`. The `inet_network()` function returns a value in host byte order that is aligned based upon the input string. For example:

Text	Value
"10"	0x0000000a
"10.0"	0x00000a00
"10.0.1"	0a000a0001

Text	Value
"10.0.1.28"	0x0a000180

Commonly, the alignment of the returned value is used as a crude approximate of pre-CIDR (Classless Inter-Domain Routing) subnet mask. For example:

```
in_addr_t addr, mask;

addr = inet_network(net_name);
mask= ~(in_addr_t)0;
if ((addr & IN_CLASSA_NET) == 0)
    addr <= 8, mask <= 8;
if ((addr & IN_CLASSA_NET) == 0)
    addr <= 8, mask <= 8;
if ((addr & IN_CLASSA_NET) == 0)
    addr <= 8, mask <= 8;
```

This usage is deprecated by the CIDR requirements. See Fuller, V., Li, T., Yu, J., and Varadhan, K. *RFC 1519, Classless Inter-Domain Routing (CIDR): an Address Assignment and Aggregation Strategy*. Network Working Group. September 1993.

The functions `setnetent()`, `getnetent()`, and `endnetent()` are used to enumerate network entries from the database.

`setnetent()` sets (or resets) the enumeration to the beginning of the set of network entries. This function should be called before the first call to `getnetent()`. Calls to `getnetbyname()` and `getnetbyaddr()` leave the enumeration position in an indeterminate state. If the *stayopen* flag is non-zero, the system may keep allocated resources such as open file descriptors until a subsequent call to `endnetent()`.

Successive calls to `getnetent()` return either successive entries or NULL, indicating the end of the enumeration.

`endnetent()` may be called to indicate that the caller expects to do no further network entry retrieval operations; the system may then deallocate resources it was using. It is still allowed, but possibly less efficient, for the process to call more network entry retrieval functions after calling `endnetent()`.

Reentrant Interfaces The functions `getnetbyname()`, `getnetbyaddr()`, and `getnetent()` use static storage that is reused in each call, making these routines unsafe for use in multi-threaded applications.

The functions `getnetbyname_r()`, `getnetbyaddr_r()`, and `getnetent_r()` provide reentrant interfaces for these operations.

Each reentrant interface performs the same operation as its non-reentrant counterpart, named by removing the “_r” suffix. The reentrant interfaces, however, use buffers supplied by the caller to store returned results, and are safe for use in both single-threaded and multi-threaded applications.

Each reentrant interface takes the same parameters as its non-reentrant counterpart, as well as the following additional parameters. The parameter *result* must be a pointer to a `struct netent` structure allocated by the caller. On successful completion, the function returns the network entry in this structure. The parameter *buffer* must be a pointer to a buffer supplied by the caller. This buffer is used as storage space for the network entry data. All of the pointers within the returned `struct netent` *result* point to data stored within this buffer. See RETURN VALUES. The buffer must be large enough to hold all of the data associated with the network entry. The parameter *buflen* should give the size in bytes of the buffer indicated by *buffer*.

For enumeration in multi-threaded applications, the position within the enumeration is a process-wide property shared by all threads. `setnetent()` may be used in a multi-threaded application but resets the enumeration position for all threads. If multiple threads interleave calls to `getnetent_r()`, the threads will enumerate disjointed subsets of the network database.

Like their non-reentrant counterparts, `getnetbyname_r()` and `getnetbyaddr_r()` leave the enumeration position in an indeterminate state.

Return Values Network entries are represented by the `struct netent` structure defined in `<netdb.h>`.

The functions `getnetbyname()`, `getnetbyname_r()`, `getnetbyaddr`, and `getnetbyaddr_r()` each return a pointer to a `struct netent` if they successfully locate the requested entry; otherwise they return `NULL`.

The functions `getnetent()` and `getnetent_r()` each return a pointer to a `struct netent` if they successfully enumerate an entry; otherwise they return `NULL`, indicating the end of the enumeration.

The functions `getnetbyname()`, `getnetbyaddr()`, and `getnetent()` use static storage, so returned data must be copied before a subsequent call to any of these functions if the data is to be saved.

When the pointer returned by the reentrant functions `getnetbyname_r()`, `getnetbyaddr_r()`, and `getnetent_r()` is non-`NULL`, it is always equal to the *result* pointer that was supplied by the caller.

The functions `setnetent()` and `endnetent()` return `0` on success.

Errors The reentrant functions `getnetbyname_r()`, `getnetbyaddr_r` and `getnetent_r()` will return `NULL` and set `errno` to `ERANGE` if the length of the buffer supplied by caller is not large enough to store the result. See [Intro\(2\)](#) for the proper usage and interpretation of `errno` in multi-threaded applications.

Files	<code>/etc/networks</code>	network name database
	<code>/etc/nsswitch.conf</code>	configuration file for the name service switch

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [Intro\(2\)](#), [Intro\(3\)](#), [byteorder\(3SOCKET\)](#), [inet\(3SOCKET\)](#), [netdb.h\(3HEAD\)](#), [networks\(4\)](#), [nsswitch.conf\(4\)](#), [attributes\(5\)](#)

Fuller, V., Li, T., Yu, J., and Varadhan, K. *RFC 1519, Classless Inter-Domain Routing (CIDR): an Address Assignment and Aggregation Strategy*. Network Working Group. September 1993.

Warnings The reentrant interfaces `getnetbyname_r()`, `getnetbyaddr_r()`, and `getnetent_r()` are included in this release on an uncommitted basis only, and are subject to change or removal in future minor releases.

Notes The current implementation of these functions only return or accept network numbers for the Internet address family (type `AF_INET`). The functions described in [inet\(3SOCKET\)](#) may be helpful in constructing and manipulating addresses and network numbers in this form.

When compiling multi-threaded applications, see [Intro\(3\)](#), *Notes On Multithread Applications*, for information about the use of the `_REENTRANT` flag.

Use of the enumeration interfaces `getnetent()` and `getnetent_r()` is discouraged; enumeration may not be supported for all database sources. The semantics of enumeration are discussed further in [nsswitch.conf\(4\)](#).

Name getnetconfig, setnetconfig, endnetconfig, getnetconfigent, freenetconfigent, nc_perror, nc_spperror – get network configuration database entry

Synopsis #include <netconfig.h>

```
struct netconfig *getnetconfig(void *handlep);
void *setnetconfig(void);
int endnetconfig(void *handlep);
struct netconfig *getnetconfigent(const char *netid);
void freenetconfigent(struct netconfig *netconfigp);
void nc_perror(const char *msg);
char *nc_spperror(void);
```

Description The library routines described on this page are part of the Network Selection component. They provide the application access to the system network configuration database, /etc/netconfig. In addition to the routines for accessing the netconfig database, Network Selection includes the environment variable NETPATH (see [environ\(5\)](#)) and the NETPATH access routines described in [getnetpath\(3NSL\)](#).

getnetconfig() returns a pointer to the current entry in the netconfig database, formatted as a struct netconfig. Successive calls will return successive netconfig entries in the netconfig database. getnetconfig() can be used to search the entire netconfig file. getnetconfig() returns NULL at the end of the file. *handlep* is the handle obtained through setnetconfig().

A call to setnetconfig() has the effect of “binding” to or “rewinding” the netconfig database. setnetconfig() must be called before the first call to getnetconfig() and may be called at any other time. setnetconfig() need *not* be called before a call to getnetconfigent(). setnetconfig() returns a unique handle to be used by getnetconfig().

endnetconfig() should be called when processing is complete to release resources for reuse. *handlep* is the handle obtained through setnetconfig(). Programmers should be aware, however, that the last call to endnetconfig() frees all memory allocated by getnetconfig() for the struct netconfig data structure. endnetconfig() may not be called before setnetconfig().

getnetconfigent() returns a pointer to the struct netconfig structure corresponding to *netid*. It returns NULL if *netid* is invalid (that is, does not name an entry in the netconfig database).

`freenetconfig()` frees the `netconfig` structure pointed to by *netconfigp* (previously returned by `getnetconfig()`).

`nc_perror()` prints a message to the standard error indicating why any of the above routines failed. The message is prepended with the string *msg* and a colon. A NEWLINE is appended at the end of the message.

`nc_sperror()` is similar to `nc_perror()` but instead of sending the message to the standard error, will return a pointer to a string that contains the error message.

`nc_perror()` and `nc_sperror()` can also be used with the NETPATH access routines defined in [getnetpath\(3NSL\)](#).

Return Values `setnetconfig()` returns a unique handle to be used by `getnetconfig()`. In the case of an error, `setnetconfig()` returns NULL and `nc_perror()` or `nc_sperror()` can be used to print the reason for failure.

`getnetconfig()` returns a pointer to the current entry in the `netconfig()` database, formatted as a `struct netconfig`. `getnetconfig()` returns NULL at the end of the file, or upon failure.

`endnetconfig()` returns 0 on success and -1 on failure (for example, if `setnetconfig()` was not called previously).

On success, `getnetconfig()` returns a pointer to the `struct netconfig` structure corresponding to *netid*; otherwise it returns NULL.

`nc_sperror()` returns a pointer to a buffer which contains the error message string. This buffer is overwritten on each call. In multithreaded applications, this buffer is implemented as thread-specific data.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [getnetpath\(3NSL\)](#), [netconfig\(4\)](#), [attributes\(5\)](#), [environ\(5\)](#)

Name getnetpath, setnetpath, endnetpath – get /etc/netconfig entry corresponding to NETPATH component

Synopsis #include <netconfig.h>

```
struct netconfig *getnetpath(void *handlep);

void *setnetpath(void);

int endnetpath(void *handlep);
```

Description The routines described on this page are part of the Network Selection component. They provide the application access to the system network configuration database, /etc/netconfig, as it is "filtered" by the NETPATH environment variable. See [environ\(5\)](#). See [getnetconfig\(3NSL\)](#) for other routines that also access the network configuration database directly. The NETPATH variable is a list of colon-separated network identifiers.

getnetpath() returns a pointer to the netconfig database entry corresponding to the first valid NETPATH component. The netconfig entry is formatted as a struct netconfig. On each subsequent call, getnetpath() returns a pointer to the netconfig entry that corresponds to the next valid NETPATH component. getnetpath() can thus be used to search the netconfig database for all networks included in the NETPATH variable. When NETPATH has been exhausted, getnetpath() returns NULL.

A call to setnetpath() "binds" to or "rewinds" NETPATH. setnetpath() must be called before the first call to getnetpath() and may be called at any other time. It returns a handle that is used by getnetpath().

getnetpath() silently ignores invalid NETPATH components. A NETPATH component is invalid if there is no corresponding entry in the netconfig database.

If the NETPATH variable is unset, getnetpath() behaves as if NETPATH were set to the sequence of "default" or "visible" networks in the netconfig database, in the order in which they are listed.

endnetpath() may be called to "unbind" from NETPATH when processing is complete, releasing resources for reuse. Programmers should be aware, however, that endnetpath() frees all memory allocated by getnetpath() for the struct netconfig data structure. endnetpath() returns 0 on success and -1 on failure (for example, if setnetpath() was not called previously).

Return Values setnetpath() returns a handle that is used by getnetpath(). In case of an error, setnetpath() returns NULL. nc_perror() or nc_spperror() can be used to print out the reason for failure. See [getnetconfig\(3NSL\)](#).

When first called, getnetpath() returns a pointer to the netconfig database entry corresponding to the first valid NETPATH component. When NETPATH has been exhausted, getnetpath() returns NULL.

endnetpath() returns 0 on success and - 1 on failure (for example, if setnetpath() was not called previously).

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [getnetconfig\(3NSL\)](#), [netconfig\(4\)](#), [attributes\(5\)](#), [environ\(5\)](#)

Name getpeername – get name of connected peer

Synopsis `cc [flag ...] file ... -lsocket -lnsl [library ...]`
`#include <sys/types.h>`
`#include <sys/socket.h>`

```
int getpeername(int s, struct sockaddr *name, socklen_t *namelen);
```

Description `getpeername()` returns the name of the peer connected to socket `s`. The `int` pointed to by the `namelen` parameter should be initialized to indicate the amount of space pointed to by `name`. On return it contains the actual size of the name returned (in bytes), prior to any truncation. The name is truncated if the buffer provided is too small.

Return Values If successful, `getpeername()` returns 0; otherwise it returns -1 and sets `errno` to indicate the error.

Errors The call succeeds unless:

EBADF	The argument <code>s</code> is not a valid descriptor.
ENOMEM	There was insufficient user memory for the operation to complete.
ENOSR	There were insufficient STREAMS resources available for the operation to complete.
ENOTCONN	The socket is not connected.
ENOTSOCK	The argument <code>s</code> is not a socket.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Safe

See Also [accept\(3SOCKET\)](#), [bind\(3SOCKET\)](#), [getsockname\(3SOCKET\)](#), [socket\(3SOCKET\)](#), [attributes\(5\)](#), [socket.h\(3HEAD\)](#)

Name getpeername – get the name of the peer socket

Synopsis `cc [flag ...] file ... -lxnet [library ...]`
`#include <sys/socket.h>`

```
int getpeername(int socket, struct sockaddr *restrict address,
                socklen_t *restrict address_len);
```

Description The `getpeername()` function retrieves the peer address of the specified socket, stores this address in the `sockaddr` structure pointed to by the *address* argument, and stores the length of this address in the object pointed to by the *address_len* argument.

If the actual length of the address is greater than the length of the supplied `sockaddr` structure, the stored address will be truncated.

If the protocol permits connections by unbound clients, and the peer is not bound, then the value stored in the object pointed to by *address* is unspecified.

Return Values Upon successful completion, 0 is returned. Otherwise, -1 is returned and `errno` is set to indicate the error.

Errors The `getpeername()` function will fail if:

- | | |
|------------|--|
| EBADF | The <i>socket</i> argument is not a valid file descriptor. |
| EFAULT | The <i>address</i> or <i>address_len</i> parameter can not be accessed or written. |
| EINVAL | The socket has been shut down. |
| ENOTCONN | The socket is not connected or otherwise has not had the peer prespecified. |
| ENOTSOCK | The <i>socket</i> argument does not refer to a socket. |
| EOPNOTSUPP | The operation is not supported for the socket protocol. |

The `getpeername()` function may fail if:

- | | |
|---------|--|
| ENOBUFS | Insufficient resources were available in the system to complete the call. |
| ENOSR | There were insufficient STREAMS resources available for the operation to complete. |

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also `accept(3XNET)`, `bind(3XNET)`, `getsockname(3XNET)`, `socket(3XNET)`, `attributes(5)`, `standards(5)`

Name getprotobyname, getprotobyname_r, getprotobynumber, getprotobynumber_r, getprotoent, getprotoent_r, setprotoent, endprotoent – get protocol entry

Synopsis cc [*flag* ...] *file* ... -lsocket -lnsl [*library* ...]
#include <netdb.h>

```
struct protoent *getprotobyname(const char *name);

struct protoent *getprotobyname_r(const char *name,
    struct protoent *result, char *buffer,
    int buflen);

struct protoent *getprotobynumber(int proto);

struct protoent *getprotobynumber_r(int proto, struct protoent *result,
    char *buffer, int buflen);

struct protoent *getprotoent(void);

struct protoent *getprotoent_r(struct protoent *result, char *buffer,
    int buflen);

int setprotoent(int stayopen);

int endprotoent(void);
```

Description These functions return a protocol entry. Two types of interfaces are supported: reentrant (getprotobyname_r(), getprotobynumber_r(), and getprotoent_r()) and non-reentrant (getprotobyname(), getprotobynumber(), and getprotoent()). The reentrant functions can be used in single-threaded applications and are safe for multithreaded applications, making them the preferred interfaces.

The reentrant routines require additional parameters which are used to return results data. *result* is a pointer to a struct protoent structure and will be where the returned results will be stored. *buffer* is used as storage space for elements of the returned results. *buflen* is the size of *buffer* and should be large enough to contain all returned data. *buflen* must be at least 1024 bytes.

getprotobyname_r(), getprotobynumber_r(), and getprotoent_r() each return a protocol entry.

The entry may come from one of the following sources: the protocols file (see [protocols\(4\)](#)), the NIS maps “protocols.byname” and “protocols.bynumber”, and the NIS+ table “protocols”. The sources and their lookup order are specified in the /etc/nsswitch.conf file (see [nsswitch.conf\(4\)](#) for details). Some name services such as NIS will return only one name for a host, whereas others such as NIS+ or DNS will return all aliases.

The getprotobyname_r() and getprotobynumber_r() functions sequentially search from the beginning of the file until a matching protocol name or protocol number is found, or until an EOF is encountered.

`getprotobyname()` and `getprotobynumber()` have the same functionality as `getprotobyname_r()` and `getprotobynumber_r()` except that a static buffer is used to store returned results. These functions are Unsafe in a multithreaded application.

`getprotoent_r()` enumerates protocol entries: successive calls to `getprotoent_r()` will return either successive protocol entries or NULL. Enumeration might not be supported by some sources. If multiple threads call `getprotoent_r()`, each will retrieve a subset of the protocol database.

`getprotent()` has the same functionality as `getprotoent_r()` except that a static buffer is used to store returned results. This routine is unsafe in a multithreaded application.

`setprotoent()` “rewinds” to the beginning of the enumeration of protocol entries. If the *stayopen* flag is non-zero, resources such as open file descriptors are not deallocated after each call to `getprotobynumber_r()` and `getprotobyname_r()`. Calls to `getprotobyname_r()`, `The getprotobyname()`, `getprotobynumber_r()`, and `getprotobynumber()` functions might leave the enumeration in an indeterminate state, so `setprotoent()` should be called before the first call to `getprotoent_r()` or `getprotoent()`. The `setprotoent()` function has process-wide scope, and “rewinds” the protocol entries for all threads calling `getprotoent_r()` as well as main-thread calls to `getprotoent()`.

The `endprotoent()` function can be called to indicate that protocol processing is complete; the system may then close any open protocols file, deallocate storage, and so forth. It is legitimate, but possibly less efficient, to call more protocol functions after `endprotoent()`.

The internal representation of a protocol entry is a `protoent` structure defined in `<netdb.h>` with the following members:

```
char  *p_name;
char  **p_aliases;
int    p_proto;
```

Return Values The `getprotobyname_r()`, `getprotobyname()`, `getprotobynumber_r()`, and `getprotobynumber()` functions return a pointer to a `struct protoent` if they successfully locate the requested entry; otherwise they return NULL.

The `getprotoent_r()` and `getprotoent()` functions return a pointer to a `struct protoent` if they successfully enumerate an entry; otherwise they return NULL, indicating the end of the enumeration.

Errors The `getprotobyname_r()`, `getprotobynumber_r()`, and `getprotoent_r()` functions will fail if:

ERANGE	The length of the buffer supplied by the caller is not large enough to store the result.
--------	--

Files /etc/protocols
/etc/nsswitch.conf

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	See NOTES below.

See Also [Intro\(3\)](#), [nsswitch.conf\(4\)](#), [protocols\(4\)](#), [attributes\(5\)](#), [netdb.h\(3HEAD\)](#)

Notes Although `getprotobyname_r()`, `getprotobynumber_r()`, and `getprotoent_r()` are not mentioned by POSIX 1003.1:2001, they were added to complete the functionality provided by similar thread-safe functions.

When compiling multithreaded applications, see [Intro\(3\)](#), *Notes On Multithread Applications*, for information about the use of the `_REENTRANT` flag.

The `getprotobyname_r()`, `getprotobynumber_r()`, and `getprotoent_r()` functions are reentrant and multithread safe. The reentrant interfaces can be used in single-threaded as well as multithreaded applications and are therefore the preferred interfaces.

The `getprotobyname()`, `getprotobyaddr()`, and `getprotoent()` functions use static storage, so returned data must be copied if it is to be saved. Because of their use of static storage for returned data, these functions are not safe for multithreaded applications.

The `setprotoent()` and `endprotoent()` functions have process-wide scope, and are therefore not safe in multi-threaded applications.

Use of `getprotoent_r()` and `getprotoent()` is discouraged; enumeration is well-defined for the protocols file and is supported (albeit inefficiently) for NIS and NIS+, but in general may not be well-defined. The semantics of enumeration are discussed in [nsswitch.conf\(4\)](#).

Bugs Only the Internet protocols are currently understood.

Name getpublickey, getsecretkey, publickey – retrieve public or secret key

Synopsis `#include <rpc/rpc.h>`
`#include <rpc/key_prot.h>`

```
int getpublickey(const char netname[MAXNETNAMELEN],
                char publickey[HEXKEYBYTES+1]);

int getsecretkey(const char netname[MAXNETNAMELEN],
                char secretkey[HEXKEYBYTES+1], const char *passwd);
```

Description The `getpublickey()` and `getsecretkey()` functions get public and secret keys for *netname*. The key may come from one of the following sources:

- `/etc/publickey` file. See [publickey\(4\)](#).
- NIS map “publickey.byname” or the NIS+ table “cred.org_dir”. The sources and their lookup order are specified in the `/etc/nsswitch.conf` file. See [nsswitch.conf\(4\)](#).

`getsecretkey()` has an extra argument, *passwd*, which is used to decrypt the encrypted secret key stored in the database.

Return Values Both routines return 1 if they are successful in finding the key. Otherwise, the routines return 0. The keys are returned as null-terminated, hexadecimal strings. If the password supplied to `getsecretkey()` fails to decrypt the secret key, the routine will return 1 but the *secretkey*[0] will be set to NULL.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Safe

See Also [secure_rpc\(3NSL\)](#), [nsswitch.conf\(4\)](#), [publickey\(4\)](#), [attributes\(5\)](#)

Warnings If `getpublickey()` gets the public key from any source other than NIS+, all authenticated NIS+ operations may fail. To ensure that this does not happen, edit the [nsswitch.conf\(4\)](#) file to make sure that the public key is obtained from NIS+.

NOTES NIS+ might not be supported in future releases of the Solaris operating system. Tools to aid the migration from NIS+ to LDAP are available in the current Solaris release. For more information, visit <http://www.sun.com/directory/nisplus/transition.html>.

Name getrpcbyname, getrpcbyname_r, getrpcbynumber, getrpcbynumber_r, getrpcent, getrpcent_r, setrpcent, endrpcent – get RPC entry

Synopsis cc [*flag* ...] *file* ... -lnsl [*library* ...]
#include <rpc/rpcent.h>

```
struct rpcent *getrpcbyname(const char *name);

struct rpcent *getrpcbyname_r(const char *name, struct rpcent *result,
                               char *buffer, int buflen);

struct rpcent *getrpcbynumber(const int number);

struct rpcent *getrpcbynumber_r(const int number, struct rpcent *result,
                                 char *buffer, int buflen);

struct rpcent *getrpcent(void);

struct rpcent *getrpcent_r(struct rpcent *result, char *buffer,
                           int buflen);

void setrpcent(const int stayopen);

void endrpcent(void);
```

Description These functions are used to obtain entries for RPC (Remote Procedure Call) services. An entry may come from any of the sources for rpc specified in the `/etc/nsswitch.conf` file (see [nsswitch.conf\(4\)](#)).

`getrpcbyname()` searches for an entry with the RPC service name specified by the parameter *name*.

`getrpcbynumber()` searches for an entry with the RPC program number *number*.

The functions `setrpcent()`, `getrpcent()`, and `endrpcent()` are used to enumerate RPC entries from the database.

`setrpcent()` sets (or resets) the enumeration to the beginning of the set of RPC entries. This function should be called before the first call to `getrpcent()`. Calls to `getrpcbyname()` and `getrpcbynumber()` leave the enumeration position in an indeterminate state. If the *stayopen* flag is non-zero, the system may keep allocated resources such as open file descriptors until a subsequent call to `endrpcent()`.

Successive calls to `getrpcent()` return either successive entries or NULL, indicating the end of the enumeration.

`endrpcent()` may be called to indicate that the caller expects to do no further RPC entry retrieval operations; the system may then deallocate resources it was using. It is still allowed, but possibly less efficient, for the process to call more RPC entry retrieval functions after calling `endrpcent()`.

Reentrant Interfaces The functions `getrpcbyname()`, `getrpcbynumber()`, and `getrpcent()` use static storage that is re-used in each call, making these routines unsafe for use in multithreaded applications.

The functions `getrpcbyname_r()`, `getrpcbynumber_r()`, and `getrpcent_r()` provide reentrant interfaces for these operations.

Each reentrant interface performs the same operation as its non-reentrant counterpart, named by removing the “_r” suffix. The reentrant interfaces, however, use buffers supplied by the caller to store returned results, and are safe for use in both single-threaded and multithreaded applications.

Each reentrant interface takes the same parameters as its non-reentrant counterpart, as well as the following additional parameters. The parameter *result* must be a pointer to a `struct rpcent` structure allocated by the caller. On successful completion, the function returns the RPC entry in this structure. The parameter *buffer* must be a pointer to a buffer supplied by the caller. This buffer is used as storage space for the RPC entry data. All of the pointers within the returned `struct rpcent result` point to data stored within this buffer (see RETURN VALUES). The buffer must be large enough to hold all of the data associated with the RPC entry. The parameter *buflen* should give the size in bytes of the buffer indicated by *buffer*.

For enumeration in multithreaded applications, the position within the enumeration is a process-wide property shared by all threads. `setrpcent()` may be used in a multithreaded application but resets the enumeration position for all threads. If multiple threads interleave calls to `getrpcent_r()`, the threads will enumerate disjoint subsets of the RPC entry database.

Like their non-reentrant counterparts, `getrpcbyname_r()` and `getrpcbynumber_r()` leave the enumeration position in an indeterminate state.

Return Values RPC entries are represented by the `struct rpcent` structure defined in `<rpc/rpcent.h>`:

```
struct rpcent {
    char *r_name;           /* name of this rpc service
    char **r_aliases;       /* zero-terminated list of alternate names */
    int r_number;           /* rpc program number */
};
```

The functions `getrpcbyname()`, `getrpcbyname_r()`, `getrpcbynumber()`, and `getrpcbynumber_r()` each return a pointer to a `struct rpcent` if they successfully locate the requested entry; otherwise they return `NULL`.

The functions `getrpcent()` and `getrpcent_r()` each return a pointer to a `struct rpcent` if they successfully enumerate an entry; otherwise they return `NULL`, indicating the end of the enumeration.

The functions `getrpcbyname()`, `getrpcbynumber()`, and `getrpcent()` use static storage, so returned data must be copied before a subsequent call to any of these functions if the data is to be saved.

When the pointer returned by the reentrant functions `getrpcbyname_r()`, `getrpcbnumber_r()`, and `getrpcent_r()` is non-NULL, it is always equal to the *result* pointer that was supplied by the caller.

Errors The reentrant functions `getrpcbyname_r()`, `getrpcbnumber_r()` and `getrpcent_r()` will return NULL and set `errno` to `ERANGE` if the length of the buffer supplied by caller is not large enough to store the result. See [Intro\(2\)](#) for the proper usage and interpretation of `errno` in multithreaded applications.

Files `/etc/rpc`
`/etc/nsswitch.conf`

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	See “Reentrant Interfaces” in DESCRIPTION.

See Also [rpcinfo\(1M\)](#), [rpc\(3NSL\)](#), [nsswitch.conf\(4\)](#), [rpc\(4\)](#), [attributes\(5\)](#)

Warnings The reentrant interfaces `getrpcbyname_r()`, `getrpcbnumber_r()`, and `getrpcent_r()` are included in this release on an uncommitted basis only, and are subject to change or removal in future minor releases.

Notes When compiling multithreaded applications, see [Intro\(3\)](#), *Notes On Multithreaded Applications*, for information about the use of the `_REENTRANT` flag.

Use of the enumeration interfaces `getrpcent()` and `getrpcent_r()` is discouraged; enumeration may not be supported for all database sources. The semantics of enumeration are discussed further in [nsswitch.conf\(4\)](#).

Name getservbyname, getservbyname_r, getservbyport, getservbyport_r, getservent, getservent_r, setservent, endservent – get service entry

Synopsis `cc [flag ...] file ... -lsocket -lnsl [library ...]`
`#include <netdb.h>`

```
struct servent *getservbyname(const char *name, const char *proto);

struct servent *getservbyname_r(const char *name, const char *proto,
                                struct servent *result, char *buffer, int buflen);

struct servent *getservbyport(int port, const char *proto);

struct servent *getservbyport_r(int port, const char *proto,
                                struct servent *result, char *buffer, int buflen);

struct servent *getservent(void);

struct servent *getservent_r(struct servent *result, char *buffer,
                             int buflen);

int setservent(int stayopen);

int endservent(void);
```

Description These functions are used to obtain entries for Internet services. An entry may come from any of the sources for services specified in the `/etc/nsswitch.conf` file. See [nsswitch.conf\(4\)](#).

The `getservbyname()` and `getservbyport()` functions sequentially search from the beginning of the file until a matching protocol name or port number is found, or until end-of-file is encountered. If a protocol name is also supplied (non-null), searches must also match the protocol.

The `getservbyname()` function searches for an entry with the Internet service name specified by the *name* parameter.

The `getservbyport()` function searches for an entry with the Internet port number *port*.

All addresses are returned in network order. In order to interpret the addresses, [byteorder\(3SOCKET\)](#)

must be used for byte order conversion. The string *proto* is used by both `getservbyname()` and `getservbyport()` to restrict the search to entries with the specified protocol. If *proto* is NULL, entries with any protocol can be returned.

The functions `setservent()`, `getservent()`, and `endservent()` are used to enumerate entries from the services database.

The `setservent()` function sets (or resets) the enumeration to the beginning of the set of service entries. This function should be called before the first call to `getservent()`. Calls to

the functions `getservbyname()` and `getservbyport()` leave the enumeration position in an indeterminate state. If the *stayopen* flag is non-zero, the system may keep allocated resources such as open file descriptors until a subsequent call to `endservent()`.

The `getservent()` function reads the next line of the file, opening the file if necessary. `getservent()` opens and rewinds the file. If the *stayopen* flag is non-zero, the net data base will not be closed after each call to `getservent()` (either directly, or indirectly through one of the other “getserv” calls).

Successive calls to `getservent()` return either successive entries or `NULL`, indicating the end of the enumeration.

The `endservent()` function closes the file. The `endservent()` function can be called to indicate that the caller expects to do no further service entry retrieval operations; the system can then deallocate resources it was using. It is still allowed, but possibly less efficient, for the process to call more service entry retrieval functions after calling `endservent()`.

Reentrant Interfaces The functions `getservbyname()`, `getservbyport()`, and `getservent()` use static storage that is re-used in each call, making these functions unsafe for use in multithreaded applications.

The functions `getservbyname_r()`, `getservbyport_r()`, and `getservent_r()` provide reentrant interfaces for these operations.

Each reentrant interface performs the same operation as its non-reentrant counterpart, named by removing the “_r” suffix. The reentrant interfaces, however, use buffers supplied by the caller to store returned results, and are safe for use in both single-threaded and multithreaded applications.

Each reentrant interface takes the same parameters as its non-reentrant counterpart, as well as the following additional parameters. The parameter *result* must be a pointer to a `struct servent` structure allocated by the caller. On successful completion, the function returns the service entry in this structure. The parameter *buffer* must be a pointer to a buffer supplied by the caller. This buffer is used as storage space for the service entry data. All of the pointers within the returned `struct servent result` point to data stored within this buffer. See the RETURN VALUES section of this manual page. The buffer must be large enough to hold all of the data associated with the service entry. The parameter *buflen* should give the size in bytes of the buffer indicated by *buffer*.

For enumeration in multithreaded applications, the position within the enumeration is a process-wide property shared by all threads. The `setservent()` function can be used in a multithreaded application but resets the enumeration position for all threads. If multiple threads interleave calls to `getservent_r()`, the threads will enumerate disjoint subsets of the service database.

Like their non-reentrant counterparts, `getservbyname_r()` and `getservbyport_r()` leave the enumeration position in an indeterminate state.

Return Values Service entries are represented by the `struct servent` structure defined in `<netdb.h>`:

```

struct servent {
    char    *s_name;           /* official name of service */
    char    **s_aliases;       /* alias list */
    int     s_port;            /* port service resides at */
    char    *s_proto;          /* protocol to use */
};

```

The members of this structure are:

<code>s_name</code>	The official name of the service.
<code>s_aliases</code>	A zero terminated list of alternate names for the service.
<code>s_port</code>	The port number at which the service resides. Port numbers are returned in network byte order.
<code>s_proto</code>	The name of the protocol to use when contacting the service

The functions `getservbyname()`, `getservbyname_r()`, `getservbyport()`, and `getservbyport_r()` each return a pointer to a `struct servent` if they successfully locate the requested entry; otherwise they return `NULL`.

The functions `getservent()` and `getservent_r()` each return a pointer to a `struct servent` if they successfully enumerate an entry; otherwise they return `NULL`, indicating the end of the enumeration.

The functions `getservbyname()`, `getservbyport()`, and `getservent()` use static storage, so returned data must be copied before a subsequent call to any of these functions if the data is to be saved.

When the pointer returned by the reentrant functions `getservbyname_r()`, `getservbyport_r()`, and `getservent_r()` is non-null, it is always equal to the *result* pointer that was supplied by the caller.

Errors The reentrant functions `getservbyname_r()`, `getservbyport_r()`, and `getservent_r()` return `NULL` and set `errno` to `ERANGE` if the length of the buffer supplied by caller is not large enough to store the result. See [Intro\(2\)](#) for the proper usage and interpretation of `errno` in multithreaded applications.

Files	<code>/etc/services</code>	Internet network services
	<code>/etc/netconfig</code>	network configuration file
	<code>/etc/nsswitch.conf</code>	configuration file for the name-service switch

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	See “Reentrant Interfaces” in DESCRIPTION.

See Also [Intro\(2\)](#), [Intro\(3\)](#), [byteorder\(3SOCKET\)](#), [netdir\(3NSL\)](#), [netconfig\(4\)](#), [nsswitch.conf\(4\)](#), [services\(4\)](#), [attributes\(5\)](#), [netdb.h\(3HEAD\)](#)

Warnings The reentrant interfaces `getservbyname_r()`, `getservbyport_r()`, and `getservent_r()` are included in this release on an uncommitted basis only, and are subject to change or removal in future minor releases.

Notes The functions that return `struct servent` return the least significant 16-bits of the `s_port` field in *network byte order*. `getservbyport()` and `getservbyport_r()` also expect the input parameter `port` in the *network byte order*. See [htons\(3SOCKET\)](#) for more details on converting between host and network byte orders.

To ensure that they all return consistent results, `getservbyname()`, `getservbyname_r()`, and `netdir_getbyname()` are implemented in terms of the same internal library function. This function obtains the system-wide source lookup policy based on the `inet` family entries in [netconfig\(4\)](#) and the `services:` entry in [nsswitch.conf\(4\)](#). Similarly, `getservbyport()`, `getservbyport_r()`, and `netdir_getbyaddr()` are implemented in terms of the same internal library function. If the `inet` family entries in [netconfig\(4\)](#) have a “-” in the last column for `nametoaddr` libraries, then the entry for `services` in [nsswitch.conf](#) will be used; otherwise the `nametoaddr` libraries in that column will be used, and [nsswitch.conf](#) will not be consulted.

There is no analogue of `getservent()` and `getservent_r()` in the `netdir` functions, so these enumeration functions go straight to the `services` entry in [nsswitch.conf](#). Thus enumeration may return results from a different source than that used by `getservbyname()`, `getservbyname_r()`, `getservbyport()`, and `getservbyport_r()`.

When compiling multithreaded applications, see [Intro\(3\)](#), *Notes On Multithread Applications*, for information about the use of the `_REENTRANT` flag.

Use of the enumeration interfaces `getservent()` and `getservent_r()` is discouraged; enumeration may not be supported for all database sources. The semantics of enumeration are discussed further in [nsswitch.conf\(4\)](#).

Name getsockname – get socket name

Synopsis `cc [flag ...] file ... -lsocket -lnsl [library ...]`
`#include <sys/types.h>`
`#include <sys/socket.h>`

```
int getsockname(int s, struct sockaddr *name, socklen_t *namelen);
```

Description `getsockname()` returns the current *name* for socket *s*. The *namelen* parameter should be initialized to indicate the amount of space pointed to by *name*. On return it contains the actual size in bytes of the name returned.

Return Values If successful, `getsockname()` returns 0; otherwise it returns -1 and sets *errno* to indicate the error.

Errors The call succeeds unless:

- EBADF** The argument *s* is not a valid file descriptor.
- ENOMEM** There was insufficient memory available for the operation to complete.
- ENOSR** There were insufficient STREAMS resources available for the operation to complete.
- ENOTSOCK** The argument *s* is not a socket.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Safe

See Also [bind\(3SOCKET\)](#), [getpeername\(3SOCKET\)](#), [socket\(3SOCKET\)](#), [attributes\(5\)](#)

Name getsockname – get the socket name

Synopsis `cc [flag ...] file ... -lxnet [library ...]`
`#include <sys/socket.h>`

```
int getsockname(int socket, struct sockaddr *restrict address,
                socklen_t *restrict address_len);
```

Description The `getsockname()` function retrieves the locally-bound name of the specified socket, stores this address in the `sockaddr` structure pointed to by the *address* argument, and stores the length of this address in the object pointed to by the *address_len* argument.

If the actual length of the address is greater than the length of the supplied `sockaddr` structure, the stored address will be truncated.

If the socket has not been bound to a local name, the value stored in the object pointed to by *address* is unspecified.

Return Values Upon successful completion, 0 is returned, the *address* argument points to the address of the socket, and the *address_len* argument points to the length of the address. Otherwise, `-1` is returned and `errno` is set to indicate the error.

Errors The `getsockname()` function will fail:

- `EBADF` The *socket* argument is not a valid file descriptor.
- `EFAULT` The *address* or *address_len* parameter can not be accessed or written.
- `ENOTSOCK` The *socket* argument does not refer to a socket.
- `EOPNOTSUPP` The operation is not supported for this socket's protocol.

The `getsockname()` function may fail if:

- `EINVAL` The socket has been shut down.
- `ENOBUFS` Insufficient resources were available in the system to complete the call.
- `ENOSR` There were insufficient STREAMS resources available for the operation to complete.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also `accept(3XNET)`, `bind(3XNET)`, `getpeername(3XNET)`, `socket(3XNET)` `attributes(5)`, `standards(5)`

Name getsockopt, setsockopt – get and set options on sockets

Synopsis `cc [flag ...] file ... -lsocket -lnsl [library ...]`
`#include <sys/types.h>`
`#include <sys/socket.h>`

```
int getsockopt(int s, int level, int optname, void *optval,
               int *optlen);
```

```
int setsockopt(int s, int level, int optname, const void *optval,
               int optlen);
```

Description The `getsockopt()` and `setsockopt()` functions manipulate options associated with a socket. Options may exist at multiple protocol levels; they are always present at the uppermost “socket” level.

When manipulating socket options, the level at which the option resides and the name of the option must be specified. To manipulate options at the “socket” level, *level* is specified as `SOL_SOCKET`. To manipulate options at any other level, *level* is the protocol number of the protocol that controls the option. For example, to indicate that an option is to be interpreted by the TCP protocol, *level* is set to the TCP protocol number. See [getprotobyname\(3SOCKET\)](#).

The parameters *optval* and *optlen* are used to access option values for `setsockopt()`. For `getsockopt()`, they identify a buffer in which the value(s) for the requested option(s) are to be returned. For `getsockopt()`, *optlen* is a value-result parameter, initially containing the size of the buffer pointed to by *optval*, and modified on return to indicate the actual size of the value returned. Use a 0 *optval* if no option value is to be supplied or returned.

The *optname* and any specified options are passed uninterpreted to the appropriate protocol module for interpretation. The include file `<sys/socket.h>` contains definitions for the socket-level options described below. Options at other protocol levels vary in format and name.

Most socket-level options take an `int` for *optval*. For `setsockopt()`, the *optval* parameter should be non-zero to enable a boolean option, or zero if the option is to be disabled. `SO_LINGER` uses a `struct linger` parameter that specifies the desired state of the option and the linger interval. `struct linger` is defined in `<sys/socket.h>`. `struct linger` contains the following members:

`l_onoff` `on = 1/off = 0`

`l_linger` linger time, in seconds

The following options are recognized at the socket level. Except as noted, each may be examined with `getsockopt()` and set with `setsockopt()`.

`SO_DEBUG` enable/disable recording of debugging information

`SO_REUSEADDR` enable/disable local address reuse

SO_KEEPAIVE	enable/disable keep connections alive
SO_DONTRROUTE	enable/disable routing bypass for outgoing messages
SO_LINGER	linger on close if data is present
SO_BROADCAST	enable/disable permission to transmit broadcast messages
SO_OOBINLINE	enable/disable reception of out-of-band data in band
SO_SNDBUF	set buffer size for output
SO_RCVBUF	set buffer size for input
SO_DGRAM_ERRIND	application wants delayed error
SO_TYPE	get the type of the socket (get only)
SO_ERROR	get and clear error on the socket (get only)
SO_MAC_EXEMPT	get or set mandatory access control on the socket. This option is available only when the system is configured with Trusted Extensions.
SO_ALLZONES	bypass zone boundaries (privileged).
SO_DOMAIN	get the domain used in the socket (get only)
SO_PROTOCOL	for socket in domains PF_INET and PF_INET6, get the underlying protocol number used in the socket. For socket in domain PF_ROUTE, get the address family used in the socket.

The SO_DEBUG option enables debugging in the underlying protocol modules. The SO_REUSEADDR option indicates that the rules used in validating addresses supplied in a [bind\(3SOCKET\)](#) call should allow reuse of local addresses. The SO_KEEPAIVE option enables the periodic transmission of messages on a connected socket. If the connected party fails to respond to these messages, the connection is considered broken and threads using the socket are notified using a SIGPIPE signal. The SO_DONTRROUTE option indicates that outgoing messages should bypass the standard routing facilities. Instead, messages are directed to the appropriate network interface according to the network portion of the destination address.

The SO_LINGER option controls the action taken when unsent messages are queued on a socket and a `close(2)` is performed. If the socket promises reliable delivery of data and SO_LINGER is set, the system will block the thread on the `close()` attempt until it is able to transmit the data or until it decides it is unable to deliver the information (a timeout period, termed the linger interval, is specified in the `setsockopt()` call when SO_LINGER is requested). If SO_LINGER is disabled and a `close()` is issued, the system will process the `close()` in a manner that allows the thread to continue as quickly as possible.

The option SO_BROADCAST requests permission to send broadcast datagrams on the socket. With protocols that support out-of-band data, the SO_OOBINLINE option requests that

out-of-band data be placed in the normal data input queue as received; it will then be accessible with `recv()` or `read()` calls without the `MSG_OOB` flag.

The `SO_SNDBUF` and `SO_RCVBUF` options adjust the normal buffer sizes allocated for output and input buffers, respectively. The buffer size may be increased for high-volume connections or may be decreased to limit the possible backlog of incoming data. The maximum buffer size for UDP is determined by the value of the `ndd` variable `udp_max_buf`. The maximum buffer size for TCP is determined the value of the `ndd` variable `tcp_max_buf`. Use the `ndd(1M)` utility to determine the current default values. See the *Solaris Tunable Parameters Reference Manual* for information on setting the values of `udp_max_buf` and `tcp_max_buf`.

By default, delayed errors (such as ICMP port unreachable packets) are returned only for connected datagram sockets. The `SO_DGRAM_ERRIND` option makes it possible to receive errors for datagram sockets that are not connected. When this option is set, certain delayed errors received after completion of a `sendto()` or `sendmsg()` operation will cause a subsequent `sendto()` or `sendmsg()` operation using the same destination address (*to* parameter) to fail with the appropriate error. See [send\(3SOCKET\)](#).

The `SO_TYPE` and `SO_ERROR` options are used only with `getsockopt()`. The `SO_TYPE` option returns the type of the socket, for example, `SOCK_STREAM`. It is useful for servers that inherit sockets on startup. The `SO_ERROR` option returns any pending error on the socket and clears the error status. It may be used to check for asynchronous errors on connected datagram sockets or for other asynchronous errors.

The `SO_MAC_EXEMPT` option is used to toggle socket behavior with unlabeled peers. A socket that has this option enabled can communicate with an unlabeled peer if it is in the global zone or has a label that dominates the default label of the peer. Otherwise, the socket must have a label that is equal to the default label of the unlabeled peer. Calling `setsockopt()` with this option returns an `EACCES` error if the process lacks the `NET_MAC_AWARE` privilege or if the socket is bound. The `SO_MAC_EXEMPT` option is available only when the system is configured with Trusted Extensions.

The `SO_ALLZONES` option can be used to bypass zone boundaries between shared-IP zones. Normally, the system prevents a socket from being bound to an address that is not assigned to the current zone. It also prevents a socket that is bound to a wildcard address from receiving traffic for other zones. However, some daemons which run in the global zone might need to send and receive traffic using addresses that belong to other shared-IP zones. If set before a socket is bound, `SO_ALLZONES` causes the socket to ignore zone boundaries between shared-IP zones and permits the socket to be bound to any address assigned to the shared-IP zones. If the socket is bound to a wildcard address, it receives traffic intended for all shared-IP zones and behaves as if an equivalent socket were bound in each active shared-IP zone. Applications that use the `SO_ALLZONES` option to initiate connections or send datagram traffic should specify the source address for outbound traffic by binding to a specific address. There is no effect from setting this option in an exclusive-IP zone. Setting this option requires the `sys_net_config` privilege. See [zones\(5\)](#).

- Return Values** If successful, `getsockopt()` and `setsockopt()` return 0. Otherwise, the functions return -1 and set `errno` to indicate the error.
- Errors** The `getsockopt()` and `setsockopt()` calls succeed unless:
- EBADF** The argument `s` is not a valid file descriptor.
 - ENOMEM** There was insufficient memory available for the operation to complete.
 - ENOPROTOOPT** The option is unknown at the level indicated.
 - ENOSR** There were insufficient STREAMS resources available for the operation to complete.
 - ENOTSOCK** The argument `s` is not a socket.
 - ENOBUFS** `SO_SNDBUF` or `SO_RCVBUF` exceeds a system limit.
 - EINVAL** Invalid length for `IP_OPTIONS`.
 - EHOSTUNREACH** Invalid address for `IP_MULTICAST_IF`.
 - EINVAL** Not a multicast address for `IP_ADD_MEMBERSHIP` and `IP_DROP_MEMBERSHIP`.
 - EADDRNOTAVAIL** Bad interface address for `IP_ADD_MEMBERSHIP` and `IP_DROP_MEMBERSHIP`.
 - EADDRINUSE** Address already joined for `IP_ADD_MEMBERSHIP`.
 - ENOENT** Address not joined for `IP_DROP_MEMBERSHIP`.
 - EPERM** No permissions.
 - EACCES** Permission denied.
 - EINVAL** The specified option is invalid at the specified socket level, or the socket has been shut down.
- Attributes** See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Safe

See Also [nnd\(1M\)](#), [close\(2\)](#), [ioctl\(2\)](#), [read\(2\)](#), [bind\(3SOCKET\)](#), [getprotobyname\(3SOCKET\)](#), [recv\(3SOCKET\)](#), [recvmsg\(3XNET\)](#), [send\(3SOCKET\)](#), [socket\(3SOCKET\)](#), [socket.h\(3HEAD\)](#), [attributes\(5\)](#), [zones\(5\)](#), [tcp\(7P\)](#), [udp\(7P\)](#)

Solaris Tunable Parameters Reference Manual

Name getsockopt – get the socket options

Synopsis `cc [flag...] file... -lxnet [library...]
#include <sys/socket.h>`

```
int getsockopt(int socket, int level, int option_name,  
               void *restrict option_value, socklen_t *restrict option_len);
```

Description The `getsockopt()` function retrieves the value for the option specified by the *option_name* argument for the socket specified by the *socket* argument. If the size of the option value is greater than *option_len*, the value stored in the object pointed to by the *option_value* argument will be silently truncated. Otherwise, the object pointed to by the *option_len* argument will be modified to indicate the actual length of the value.

The *level* argument specifies the protocol level at which the option resides. To retrieve options at the socket level, specify the *level* argument as `SOL_SOCKET`. To retrieve options at other levels, supply the appropriate protocol number for the protocol controlling the option. For example, to indicate that an option will be interpreted by the TCP (Transport Control Protocol), set *level* to the protocol number of TCP, as defined in the `<netinet/in.h>` header, or as determined by using `getprotobyname(3XNET)` function.

The socket in use might require the process to have appropriate privileges to use the `getsockopt()` function.

The *option_name* argument specifies a single option to be retrieved. It can be one of the following values defined in `<sys/socket.h>`:

<code>SO_DEBUG</code>	Reports whether debugging information is being recorded. This option stores an <code>int</code> value. This is a boolean option.
<code>SO_ACCEPTCONN</code>	Reports whether socket listening is enabled. This option stores an <code>int</code> value.
<code>SO_BROADCAST</code>	Reports whether transmission of broadcast messages is supported, if this is supported by the protocol. This option stores an <code>int</code> value. This is a boolean option.
<code>SO_REUSEADDR</code>	Reports whether the rules used in validating addresses supplied to <code>bind(3XNET)</code> should allow reuse of local addresses, if this is supported by the protocol. This option stores an <code>int</code> value. This is a boolean option.
<code>SO_KEEPALIVE</code>	Reports whether connections are kept active with periodic transmission of messages, if this is supported by the protocol. If the connected socket fails to respond to these messages, the connection is broken and threads writing to that socket are notified with a <code>SIGPIPE</code> signal. This option stores an <code>int</code> value.

This is a boolean option.

SO_LINGER	Reports whether the socket lingers on <code>close(2)</code> if data is present. If <code>SO_LINGER</code> is set, the system blocks the process during <code>close(2)</code> until it can transmit the data or until the end of the interval indicated by the <code>l_linger</code> member, whichever comes first. If <code>SO_LINGER</code> is not specified, and <code>close(2)</code> is issued, the system handles the call in a way that allows the process to continue as quickly as possible. This option stores a <code>linger</code> structure.
SO_OOBINLINE	Reports whether the socket leaves received out-of-band data (data marked urgent) in line. This option stores an <code>int</code> value. This is a boolean option.
SO_SNDBUF	Reports send buffer size information. This option stores an <code>int</code> value.
SO_RCVBUF	Reports receive buffer size information. This option stores an <code>int</code> value.
SO_ERROR	Reports information about error status and clears it. This option stores an <code>int</code> value.
SO_TYPE	Reports the socket type. This option stores an <code>int</code> value.
SO_DONTROUTE	Reports whether outgoing messages bypass the standard routing facilities. The destination must be on a directly-connected network, and messages are directed to the appropriate network interface according to the destination address. The effect, if any, of this option depends on what protocol is in use. This option stores an <code>int</code> value. This is a boolean option.
SO_MAC_EXEMPT	Gets the mandatory access control status of the socket. A socket that has this option enabled can communicate with an unlabeled peer if the socket is in the global zone or has a label that dominates the default label of the peer. Otherwise, the socket must have a label that is equal to the default label of the unlabeled peer. <code>SO_MAC_EXEMPT</code> is a boolean option that is available only when the system is configured with Trusted Extensions.
SO_ALLZONES	Bypasses zone boundaries (privileged). This option stores an <code>int</code> value. This is a boolean option. The <code>SO_ALLZONES</code> option can be used to bypass zone boundaries between shared-IP zones. Normally, the system prevents a socket from being bound to an address that is not assigned to the current zone. It also prevents a socket that is bound to a wildcard address from receiving traffic for other zones. However, some daemons which run in the global zone might need to send and receive traffic using addresses that belong to other shared-IP zones. If set before a socket is bound, <code>SO_ALLZONES</code> causes the socket to ignore zone boundaries between shared-IP zones and permits the socket to be bound to any address assigned to the shared-IP zones. If the socket is bound to a wildcard address, it receives traffic

intended for all shared-IP zones and behaves as if an equivalent socket were bound in each active shared-IP zone. Applications that use the `SO_ALLZONES` option to initiate connections or send datagram traffic should specify the source address for outbound traffic by binding to a specific address. There is no effect from setting this option in an exclusive-IP zone. Setting this option requires the `sys_net_config` privilege. See [zones\(5\)](#).

<code>SO_DOMAIN</code>	get the domain used in the socket (get only)
<code>SO_PROTOCOL</code>	for socket in domains <code>AF_INET</code> and <code>AF_INET6</code> , get the underlying protocol number used in the socket. For socket in domain <code>AF_ROUTE</code> , get the address family used in the socket.

For boolean options, a zero value indicates that the option is disabled and a non-zero value indicates that the option is enabled.

Options at other protocol levels vary in format and name.

The socket in use may require the process to have appropriate privileges to use the `getsockopt()` function.

Return Values Upon successful completion, `getsockopt()` returns 0. Otherwise, -1 is returned and `errno` is set to indicate the error.

Errors The `getsockopt()` function will fail if:

<code>EBADF</code>	The <i>socket</i> argument is not a valid file descriptor.
<code>EFAULT</code>	The <i>option_value</i> or <i>option_len</i> parameter can not be accessed or written.
<code>EINVAL</code>	The specified option is invalid at the specified socket level.
<code>ENOPROTOOPT</code>	The option is not supported by the protocol.
<code>ENOTSOCK</code>	The <i>socket</i> argument does not refer to a socket.

The `getsockopt()` function may fail if:

<code>EACCES</code>	The calling process does not have the appropriate privileges.
<code>EINTR</code>	The socket has been shut down.
<code>ENOBUFS</code>	Insufficient resources are available in the system to complete the call.
<code>ENOSR</code>	There were insufficient STREAMS resources available for the operation to complete.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also [close\(2\)](#), [bind\(3XNET\)](#), [endprotoent\(3XNET\)](#), [setsockopt\(3XNET\)](#), [socket\(3XNET\)](#), [attributes](#), [standards\(5\)](#)

Name getsourcfilter, setsourcfilter, getipv4sourcfilter, setipv4sourcfilter – retrieve and set a socket's multicast filter

Synopsis `cc [flag...] file... -lsocket [library...]`
`#include <netinet/in.h>`

```
int getsourcfilter(int s, uint32_t interface,
    struct sockaddr *group, socklen_t grouplen, uint32_t *fmode,
    uint_t *numsrc, struct sockaddr_storage *slist);

int setsourcfilter(int s, uint32_t interface,
    struct sockaddr *group, socklen_t grouplen, uint32_t fmode,
    uint_t numsrc, struct sockaddr_storage *slist);

int getipv4sourcfilter(int s, struct in_addr interface,
    struct in_addr group, uint32_t *fmode, uint32_t *numsrc,
    struct in_addr *slist);

int setipv4sourcfilter(int s, struct in_addr interface,
    struct in_addr group, uint32_t fmode, uint32_t numsrc,
    struct in_addr *slist);
```

Description These functions allow applications to retrieve and modify the multicast filtering state for a tuple consisting of socket, interface, and multicast group values.

A multicast filter is described by a filter mode, which is `MODE_INCLUDE` or `MODE_EXCLUDE`, and a list of source addresses which are filtered. If a group is simply joined with no source address restrictions, the filter mode is `MODE_EXCLUDE` and the source list is empty.

The `getsourcfilter()` and `setsourcfilter()` functions are protocol-independent. They can be used on either `PF_INET` or `PF_INET6` sockets. The `getipv4sourcfilter()` and `setipv4sourcfilter()` functions are IPv4-specific. They must be used only on `PF_INET` sockets.

For the protocol-independent functions, the first four arguments identify the socket, interface, multicast group tuple values. The argument `s` is an open socket of type `SOCK_DGRAM` or `SOCK_RAW`. The `interface` argument is the interface index. The interface name can be mapped to the index using `if_nametoindex(3SOCKET)`. The `group` points to either a `sockaddr_in` containing an IPv4 multicast address if the socket is `PF_INET` or a `sockaddr_in6` containing an IPv6 multicast address if the socket is `PF_INET6`. The `grouplen` is the size of the structure pointed to by `group`.

For the IPv4-specific functions, the first three arguments identify the same socket, interface, multicast group tuple values. The argument `s` is an open socket of type `SOCK_DGRAM` or `SOCK_RAW` and protocol family `PF_INET`. The `interface` argument is the IPv4 address assigned to the local interface. The `group` argument is the IPv4 multicast address.

The `getsourcfilter()` and `getipv4sourcfilter()` functions retrieve the current filter for the given tuple consisting of socket, interface, and multicast group values. On successful return, `fmode` contains either `MODE_INCLUDE` or `MODE_EXCLUDE`, indicating the filter mode. On

input, the *numsrc* argument holds the number of addresses that can fit in the *slist* array. On return, *slist* contains as many addresses as fit, while *numsrc* contains the total number of source addresses in the filter. It is possible that *numsrc* can contain a number larger than the number of addresses in the *slist* array. An application might determine the required buffer size by calling `getsourcefilter()` with *numsrc* containing 0 and *slist* a NULL pointer. On return, *numsrc* contains the number of elements that the *slist* buffer must be able to hold. Alternatively, the maximum number of source addresses allowed by this implementation is defined in `<netinet/in.h>`:

```
#define MAX_SRC_FILTER_SIZE    64
```

The `setsourcefilter()` and `setipv4sourcefilter` functions replace the current filter with the filter specified in the arguments *fmode*, *numsrc*, and *slist*. The *fmode* argument must be set to either `MODE_INCLUDE` or `MODE_EXCLUDE`. The *numsrc* argument is the number of addresses in the *slist* array. The *slist* argument points to the array of source addresses to be included or excluded, depending on the *fmode* value.

Return Values If successful, all four functions return 0. Otherwise, they return -1 and set `errno` to indicate the error.

Errors These functions will fail if:

EBADF	The <i>s</i> argument is not a valid descriptor.
EAFNOSUPPORT	The address family of the passed-in <i>sockaddr</i> is not <code>AF_INET</code> or <code>AF_INET6</code> .
ENOPROTOOPT	The socket <i>s</i> is not of type <code>SOCK_DGRAM</code> or <code>SOCK_RAW</code> .
ENOPROTOOPT	The address family of the group parameter does not match the protocol family of the socket.
ENOSR	Insufficient STREAMS resources available for the operation to complete.
ENXIO	The <i>interface</i> argument, either an index or an IPv4 address, does not identify a valid interface.

The `getsourcefilter()` and `getipv4sourcefilter()` functions will fail if:

EADDRNOTAVAIL	The tuple consisting of socket, interface, and multicast group values does not exist; <i>group</i> is not being listened to on <i>interface</i> by <i>socket</i> .
---------------	--

The functions `setsourcefilter()` and `setipv4sourcefilter()` can fail in the following additional case:

ENOBUFS	The source filter list is larger than that allowed by the implementation.
---------	---

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [if_nametoindex\(3SOCKET\)](#), [socket\(3SOCKET\)](#), [attributes\(5\)](#)
RFC 3678

Name gss_accept_sec_context – accept a security context initiated by a peer application

Synopsis `cc [flag...] file... -lgss [library...]
#include <gssapi/gssapi.h>`

```
OM_uint32 gss_accept_sec_context(OM_uint32 *minor_status,  
                                gss_ctx_id_t *context_handle,  
                                const gss_cred_id_t acceptor_cred_handle,  
                                const gss_buffer_t input_token,  
                                const gss_channel_bindings_t input_chan_bindings,  
                                const gss_name_t * src_name, gss_OID * mech_type,  
                                gss_buffer_t output_token, OM_uint32 *ret_flags,  
                                OM_uint32 * time_rec, gss_cred_id_t *delegated_cred_handle);
```

Parameters The parameter descriptions for `gss_accept_sec_context()` follow:

minor_status

The status code returned by the underlying mechanism.

context_handle

The context handle to return to the initiator. This should be set to `GSS_C_NO_CONTEXT` before the loop begins.

acceptor_cred_handle

The handle for the credentials acquired by the acceptor, typically through `gss_acquire_cred()`. It may be initialized to `GSS_C_NO_CREDENTIAL` to indicate a default credential to use. If no default credential is defined, the function returns `GSS_C_NO_CRED`.

input_token_buffer

Token received from the context initiative.

input_chan_bindings

Optional application-specified bindings. Allows application to securely bind channel identification information to the security context. Set to `GSS_C_NO_CHANNEL_BINDINGS` if you do not want to use channel bindings.

src_name

The authenticated name of the context initiator. After use, this name should be deallocated by passing it to `gss_release_name()`. See [gss_release_name\(3GSS\)](#). If not required, specify `NULL`.

mech_type

The security mechanism used. Set to `NULL` if it does not matter which mechanism is used.

output_token

The token to send to the acceptor. Initialize it to `GSS_C_NO_BUFFER` before the function is called (or its length field set to zero). If the length is zero, no token need be sent.

ret_flags

Contains various independent flags, each of which indicates that the context supports a specific service option. If not needed, specify `NULL`. Test the returned bit-mask *ret_flags*

value against its symbolic name to determine if the given option is supported by the context. *ret_flags* may contain one of the following values:

GSS_C_DELEG_FLAG

If true, delegated credentials are available by means of the *delegated_cred_handle* parameter. If false, no credentials were delegated.

GSS_C_MUTUAL_FLAG

If true, a remote peer asked for mutual authentication. If false, no remote peer asked for mutual authentication.

GSS_C_REPLAY_FLAG

If true, replay of protected messages will be detected. If false, replayed messages will not be detected.

GSS_C_SEQUENCE_FLAG

If true, out of sequence protected messages will be detected. If false, they will not be detected.

GSS_C_CONF_FLAG

If true, confidentiality service may be invoked by calling the `gss_wrap()` routine. If false, no confidentiality service is available by means of `gss_wrap()`. `gss_wrap()` will provide message encapsulation, data-origin authentication and integrity services only.

GSS_C_INTEG_FLAG

If true, integrity service may be invoked by calling either the `gss_get_mic(3GSS)` or the `gss_wrap(3GSS)` routine. If false, per-message integrity service is not available.

GSS_C_ANON_FLAG

If true, the initiator does not wish to be authenticated. The *src_name* parameter, if requested, contains an anonymous internal name. If false, the initiator has been authenticated normally.

GSS_C_PROT_READY_FLAG

If true, the protection services specified by the states of **GSS_C_CONF_FLAG** and **GSS_C_INTEG_FLAG** are available if the accompanying major status return value is either **GSS_S_COMPLETE** or **GSS_S_CONTINUE_NEEDED**. If false, the protection services are available only if the accompanying major status return value is **GSS_S_COMPLETE**.

GSS_C_TRANS_FLAG

If true, the resultant security context may be transferred to other processes by means of a call to `gss_export_sec_context(3GSS)`. If false, the security context cannot be transferred.

time_rec

The number of seconds for which the context will remain valid. Specify NULL if not required.

delegated_cred_handle

The credential value for credentials received from the context's initiator. It is valid only if the initiator has requested that the acceptor act as a proxy: that is, if the *ret_flag* argument resolves to GSS_C_DELEG_FLAG.

Description The `gss_accept_sec_context()` function allows a remotely initiated security context between the application and a remote peer to be established. The routine may return an *output_token*, which should be transferred to the peer application, where the peer application will present it to `gss_init_sec_context()`. See [gss_init_sec_context\(3GSS\)](#). If no token need be sent, `gss_accept_sec_context()` will indicate this by setting the length field of the *output_token* argument to zero. To complete the context establishment, one or more reply tokens may be required from the peer application; if so, `gss_accept_sec_context()` will return a status flag of GSS_S_CONTINUE_NEEDED, in which case it should be called again when the reply token is received from the peer application, passing the token to `gss_accept_sec_context()` by means of the *input_token* parameters.

Portable applications should be constructed to use the token length and return status to determine whether to send or to wait for a token.

Whenever `gss_accept_sec_context()` returns a major status that includes the value GSS_S_CONTINUE_NEEDED, the context is not fully established, and the following restrictions apply to the output parameters:

- The value returned by means of the *time_rec* parameter is undefined.
- Unless the accompanying *ret_flags* parameter contains the bit GSS_C_PROT_READY_FLAG, which indicates that per-message services may be applied in advance of a successful completion status, the value returned by the *mech_type* parameter may be undefined until `gss_accept_sec_context()` returns a major status value of GSS_S_COMPLETE.

The values of the GSS_C_DELEG_FLAG, GSS_C_MUTUAL_FLAG, GSS_C_REPLAY_FLAG, GSS_C_SEQUENCE_FLAG, GSS_C_CONF_FLAG, GSS_C_INTEG_FLAG and GSS_C_ANON_FLAG bits returned by means of the *ret_flags* parameter are values that would be valid if context establishment were to succeed.

The values of the GSS_C_PROT_READY_FLAG and GSS_C_TRANS_FLAG bits within *ret_flags* indicate the actual state at the time `gss_accept_sec_context()` returns, whether or not the context is fully established. However, applications should not rely on this behavior, as GSS_C_PROT_READY_FLAG was not defined in Version 1 of the GSS-API. Instead, applications should be prepared to use per-message services after a successful context establishment, based upon the GSS_C_INTEG_FLAG and GSS_C_CONF_FLAG values.

All other bits within the *ret_flags* argument are set to zero.

While `gss_accept_sec_context()` returns GSS_S_CONTINUE_NEEDED, the values returned by means of the *ret_flags* argument indicate the services available from the established context. If the initial call of `gss_accept_sec_context()` fails, no context object is created, and

the value of the *context_handle* parameter is set to `GSS_C_NO_CONTEXT`. In the event of a failure on a subsequent call, the security context and the *context_handle* parameter are left untouched for the application to delete using `gss_delete_sec_context(3GSS)`. During context establishment, the informational status bits `GSS_S_OLD_TOKEN` and `GSS_S_DUPLICATE_TOKEN` indicate fatal errors; GSS-API mechanisms always return them in association with a routine error of `GSS_S_FAILURE`. This pairing requirement did not exist in version 1 of the GSS-API specification, so applications that wish to run over version 1 implementations must special-case these codes.

Errors `gss_accept_sec_context()` may return the following status codes:

<code>GSS_S_COMPLETE</code>	Successful completion.
<code>GSS_S_CONTINUE_NEEDED</code>	A token from the peer application is required to complete the context, and that <code>gss_accept_sec_context()</code> must be called again with that token.
<code>GSS_S_DEFECTIVE_TOKEN</code>	Consistency checks performed on the <i>input_token</i> failed.
<code>GSS_S_DEFECTIVE_CREDENTIAL</code>	Consistency checks performed on the credential failed.
<code>GSS_S_NO_CRED</code>	The supplied credentials were not valid for context acceptance, or the credential handle did not reference any credentials.
<code>GSS_S_CREDENTIALS_EXPIRED</code>	The referenced credentials have expired.
<code>GSS_S_BAD_BINDINGS</code>	The <i>input_token</i> contains different channel bindings than those specified by means of the <i>input_chan_bindings</i> parameter.
<code>GSS_S_NO_CONTEXT</code>	The supplied context handle did not refer to a valid context.
<code>GSS_S_BAD_SIG</code>	The <i>input_token</i> contains an invalid MIC.
<code>GSS_S_OLD_TOKEN</code>	The <i>input_token</i> was too old. This is a fatal error while establishing context.
<code>GSS_S_DUPLICATE_TOKEN</code>	The <i>input_token</i> is valid, but it is duplicate of a token already processed. This is a fatal error while establishing context.
<code>GSS_S_BAD_MECH</code>	The token received specified a mechanism that is not supported by the implementation or the provided credential.
<code>GSS_S_FAILURE</code>	The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the <i>minor_status</i> parameter details the error condition.

Examples EXAMPLE 1 Invoking `gss_accept_sec_context()` Within a Loop

A typical portable caller should always invoke `gss_accept_sec_context()` within a loop:

```
gss_ctx_id_t context_hdl = GSS_C_NO_CONTEXT;

do {
    receive_token_from_peer(input_token);
    maj_stat = gss_accept_sec_context(&min_stat,
                                     &context_hdl,
                                     cred_hdl,
                                     input_token,
                                     input_bindings,
                                     &client_name,
                                     &mech_type,
                                     output_token,
                                     &ret_flags,
                                     &time_rec,
                                     &deleg_cred);

    if (GSS_ERROR(maj_stat)) {
        report_error(maj_stat, min_stat);
    };
    if (output_token->length != 0) {
        send_token_to_peer(output_token);
        gss_release_buffer(&min_stat, output_token);
    };
    if (GSS_ERROR(maj_stat)) {
        if (context_hdl != GSS_C_NO_CONTEXT)
            gss_delete_sec_context(&min_stat,
                                  &context_hdl,
                                  GSS_C_NO_BUFFER);

        break;
    };
} while (maj_stat & GSS_S_CONTINUE_NEEDED);

/* Check client_name authorization */
...

(void) gss_release_name(&min_stat, &client_name);

/* Use and/or store delegated credential */
...

(void) gss_release_cred(&min_stat, &deleg_cred);
```

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Safe

See Also [gss_delete_sec_context\(3GSS\)](#), [gss_export_sec_context\(3GSS\)](#), [gss_get_mic\(3GSS\)](#), [gss_init_sec_context\(3GSS\)](#), [gss_release_cred\(3GSS\)](#), [gss_release_name\(3GSS\)](#), [gss_store_cred\(3GSS\)](#), [gss_wrap\(3GSS\)](#), [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_acquire_cred – acquire a handle for a pre-existing credential by name

Synopsis `cc [flag...] file... -lgss [library...]
#include <gssapi/gssapi.h>`

```
OM_uint32 gss_acquire_cred(OM_uint32 *minor_status,
    const gss_name_t *desired_name, OM_uint32 time_req,
    const gss_OID_set desired_mechs, gss_cred_usage_t cred_usage,
    gss_cred_id_t *output_cred_handle, gss_OID_set *actual_mechs,
    OM_uint32 *time_rec);
```

Description The `gss_acquire_cred()` function allows an application to acquire a handle for a pre-existing credential by name. This routine is not intended as a function to login to the network; a function for login to the network would involve creating new credentials rather than merely acquiring a handle to existing credentials.

If *desired_name* is `GSS_C_NO_NAME`, the call is interpreted as a request for a credential handle that will invoke default behavior when passed to `gss_init_sec_context(3GSS)` (if *cred_usage* is `GSS_C_INITIATE` or `GSS_C_BOTH`) or `gss_accept_sec_context(3GSS)` (if *cred_usage* is `GSS_C_ACCEPT` or `GSS_C_BOTH`).

Normally `gss_acquire_cred()` returns a credential that is valid only for the mechanisms requested by the *desired_mechs* argument. However, if multiple mechanisms can share a single credential element, the function returns all the mechanisms for which the credential is valid in the *actual_mechs* argument.

`gss_acquire_cred()` is intended to be used primarily by context acceptors, since the GSS-API routines obtain initiator credentials through the system login process. Accordingly, you may not acquire `GSS_C_INITIATE` or `GSS_C_BOTH` credentials by means of `gss_acquire_cred()` for any name other than `GSS_C_NO_NAME`. Alternatively, you may acquire `GSS_C_INITIATE` or `GSS_C_BOTH` credentials for a name produced when `gss_inquire_cred(3GSS)` is applied to a valid credential, or when `gss_inquire_context(3GSS)` is applied to an active context.

If credential acquisition is time-consuming for a mechanism, the mechanism may choose to delay the actual acquisition until the credential is required, for example, by `gss_init_sec_context(3GSS)` or by `gss_accept_sec_context(3GSS)`. Such mechanism-specific implementations are, however, invisible to the calling application; thus a call of `gss_inquire_cred(3GSS)` immediately following the call of `gss_acquire_cred()` will return valid credential data and incur the overhead of a deferred credential acquisition.

Parameters The parameter descriptions for `gss_acquire_cred()` follow:

<i>desired_name</i>	The name of the principal for which a credential should be acquired.
<i>time_req</i>	The number of seconds that credentials remain valid. Specify <code>GSS_C_INDEFINITE</code> to request that the credentials have the maximum permitted lifetime

<i>desired_mechs</i>	The set of underlying security mechanisms that may be used. GSS_C_NO_OID_SET may be used to obtain a default.
<i>cred_usage</i>	A flag that indicates how this credential should be used. If the flag is GSS_C_ACCEPT, then credentials will be used only to accept security credentials. GSS_C_INITIATE indicates that credentials will be used only to initiate security credentials. If the flag is GSS_C_BOTH, then credentials may be used either to initiate or accept security contexts.
<i>output_cred_handle</i>	The returned credential handle. Resources associated with this credential handle must be released by the application after use with a call to gss_release_cred(3GSS)
<i>actual_mechs</i>	The set of mechanisms for which the credential is valid. Storage associated with the returned OID-set must be released by the application after use with a call to gss_release_oid_set(3GSS) . Specify NULL if not required.
<i>time_rec</i>	Actual number of seconds for which the returned credentials will remain valid. Specify NULL if not required.
<i>minor_status</i>	Mechanism specific status code.

Errors `gss_acquire_cred()` may return the following status code:

GSS_S_COMPLETE	Successful completion.
GSS_S_BAD_MECH	An unavailable mechanism has been requested.
GSS_S_BAD_NAMETYPE	The type contained within the <i>desired_name</i> parameter is not supported.
GSS_S_BAD_NAME	The value supplied for <i>desired_name</i> parameter is ill formed.
GSS_S_CREDENTIALS_EXPIRED	The credentials could not be acquired because they have expired.
GSS_S_NO_CRED	No credentials were found for the specified name.
GSS_S_FAILURE	The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the <i>minor_status</i> parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT-Level	Safe

See Also [gss_accept_sec_context\(3GSS\)](#), [gss_init_sec_context\(3GSS\)](#),
[gss_inquire_context\(3GSS\)](#), [gss_inquire_cred\(3GSS\)](#), [gss_release_cred\(3GSS\)](#),
[gss_release_oid_set\(3GSS\)](#), [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_add_cred – add a credential-element to a credential

Synopsis `cc [flag...] file... -lgss [library...]
#include <gssapi/gssapi.h>`

```
OM_uint32 gss_add_cred(OM_uint32 *minor_status,  
    const gss_cred_id_t input_cred_handle,  
    const gss_name_t desired_name,  
    const gss_OID desired_mech,  
    gss_cred_usage_t cred_usage,  
    OM_uint32 initiator_time_req,  
    OM_uint32 acceptor_time_req,  
    gss_cred_id_t *output_cred_handle,  
    gss_OID_set *actual_mechs,  
    OM_uint32 *initiator_time_rec,  
    OM_uint32 *acceptor_time_rec);
```

Parameters The parameter descriptions for `gss_add_cred()` follow:

<i>minor_status</i>	Mechanism specific status code.
<i>input_cred_handle</i>	Credential to which the credential-element is added. If GSS_C_NO_CREDENTIAL is specified, the function composes the new credential based on default behavior. While the credential-handle is not modified by <code>gss_add_cred()</code> , the underlying credential is modified if <i>output_cred_handle</i> is NULL.
<i>desired_name</i>	Name of the principal for which a credential should be acquired.
<i>desired_mech</i>	Underlying security mechanism with which the credential can be used. GSS_C_NULL_OID can be used to obtain a default.
<i>cred_usage</i>	Flag that indicates how a credential is used to initiate or accept security credentials. If the flag is GSS_C_ACCEPT, the credentials are used only to accept security credentials. If the flag is GSS_C_INITIATE, the credentials are used only to initiate security credentials. If the flag is GSS_C_BOTH, the credentials can be used to either initiate or accept security contexts.
<i>initiator_time_req</i>	Number of seconds that the credential may remain valid for initiating security contexts. This argument is ignored if the composed credentials are of the GSS_C_ACCEPT type. Specify GSS_C_INDEFINITE to request that the credentials have the maximum permitted initiator lifetime.
<i>acceptor_time_req</i>	Number of seconds that the credential may remain valid for accepting security contexts. This argument is ignored if the composed credentials are of the GSS_C_INITIATE type. Specify GSS_C_INDEFINITE to request that the credentials have the maximum permitted initiator lifetime.

<i>output_cred_handle</i>	Returned credential handle that contains the new credential-element and all the credential-elements from <i>input_cred_handle</i> . If a valid pointer to a <code>gss_cred_id_t</code> is supplied for this parameter, <code>gss_add_cred()</code> creates a new credential handle that contains all credential-elements from <i>input_cred_handle</i> and the newly acquired credential-element. If NULL is specified for this parameter, the newly acquired credential-element is added to the credential identified by <i>input_cred_handle</i> . The resources associated with any credential handle returned by means of this parameter must be released by the application after use by a call to <code>gss_release_cred(3GSS)</code> .
<i>actual_mechs</i>	Complete set of mechanisms for which the new credential is valid. Storage for the returned OID-set must be freed by the application after use by a call to <code>gss_release_oid_set(3GSS)</code> . Specify NULL if this parameter is not required.
<i>initiator_time_rec</i>	Actual number of seconds for which the returned credentials remain valid for initiating contexts using the specified mechanism. If a mechanism does not support expiration of credentials, the value <code>GSS_C_INDEFINITE</code> is returned. Specify NULL if this parameter is not required.
<i>acceptor_time_rec</i>	Actual number of seconds for which the returned credentials remain valid for accepting security contexts using the specified mechanism. If a mechanism does not support expiration of credentials, the value <code>GSS_C_INDEFINITE</code> is returned. Specify NULL if this parameter is not required.

Description The `gss_add_cred()` function adds a credential-element to a credential. The credential-element is identified by the name of the principal to which it refers. This function is not intended as a function to login to the network. A function for login to the network would involve creating new mechanism-specific authentication data, rather than acquiring a handle to existing data.

If the value of *desired_name* is `GSS_C_NO_NAME`, the call is interpreted as a request to add a credential-element to invoke default behavior when passed to `gss_init_sec_context(3GSS)` if the value of *cred_usage* is `GSS_C_INITIATE` or `GSS_C_BOTH`. The call is also interpreted as a request to add a credential-element to the invoke default behavior when passed to `gss_accept_sec_context(3GSS)` if the value of *cred_usage* is `GSS_C_ACCEPT` or `GSS_C_BOTH`.

The `gss_add_cred()` function is expected to be used primarily by context acceptors. The GSS-API provides mechanism-specific ways to obtain GSS-API initiator credentials through

the system login process. Consequently, the GSS-API does not support acquiring GSS_C_INITIATE or GSS_C_BOTH credentials by means of [gss_acquire_cred\(3GSS\)](#) for any name other than the following:

- GSS_C_NO_NAME
- Name produced by [gss_inquire_cred\(3GSS\)](#) applied to a valid credential
- Name produced by [gss_inquire_context\(3GSS\)](#) applied to an active context

If credential acquisition is time consuming for a mechanism, the mechanism can choose to delay the actual acquisition until the credential is required by [gss_init_sec_context\(3GSS\)](#), for example, or by [gss_accept_sec_context\(3GSS\)](#). Such mechanism-specific implementation decisions are invisible to the calling application. A call to [gss_inquire_cred\(3GSS\)](#) immediately following the call `gss_add_cred()` returns valid credential data as well as incurring the overhead of deferred credential acquisition.

The `gss_add_cred()` function can be used either to compose a new credential that contains all credential-elements of the original in addition to the newly-acquired credential-element. The function can also be used to add the new credential-element to an existing credential. If the value of the *output_cred_handle* parameter is NULL, the new credential-element is added to the credential identified by *input_cred_handle*. If a valid pointer is specified for the *output_cred_handle* parameter, a new credential handle is created.

If the value of *input_cred_handle* is GSS_C_NO_CREDENTIAL, the `gss_add_cred()` function composes a credential and sets the *output_cred_handle* parameter based on the default behavior. The call has the same effect as a call first made by the application to [gss_acquire_cred\(3GSS\)](#) to specify the same usage and to pass GSS_C_NO_NAME as the *desired_name* parameter. Such an application call obtains an explicit credential handle that incorporates the default behaviors, then passes the credential handle to `gss_add_cred()`, and finally calls [gss_release_cred\(3GSS\)](#) on the first credential handle.

If the value of the *input_cred_handle* parameter is GSS_C_NO_CREDENTIAL, a non-NULL value must be supplied for the *output_cred_handle* parameter.

Return Values The `gss_add_cred()` function can return the following status codes:

GSS_S_COMPLETE	Successful completion.
GSS_S_BAD_MECH	An unavailable mechanism has been requested.
GSS_S_BAD_NAMETYPE	The type contained within the <i>desired_name</i> parameter is not supported.
GSS_S_BAD_NAME	The value supplied for <i>desired_name</i> parameter is ill formed.
GSS_S_DUPLICATE_ELEMENT	The credential already contains an element for the requested mechanism that has overlapping usage and validity period.

GSS_S_CREDENTIALS_EXPIRED	The credentials could not be added because they have expired.
GSS_S_NO_CRED	No credentials were found for the specified name.
GSS_S_FAILURE	The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the <i>minor_status</i> parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Safe

See Also [gss_accept_sec_context\(3GSS\)](#), [gss_acquire_cred\(3GSS\)](#), [gss_init_sec_context\(3GSS\)](#), [gss_inquire_context\(3GSS\)](#), [gss_inquire_cred\(3GSS\)](#), [gss_release_cred\(3GSS\)](#), [gss_release_oid_set\(3GSS\)](#), [libgss\(3LIB\)](#), [attributes\(5\)](#)

Developer’s Guide to Oracle Solaris Security

Name gss_add_oid_set_member – add an object identifier to an object identifier set

Synopsis `cc [flag...] file... -lgss [library...]`
`#include <gssapi/gssapi.h>`

```
OM_uint32 gss_add_oid_set_member(OM_uint32 *minor_status,  
                                const gss_OID member_oid, gss_OID_set *oid_set);
```

Parameters The parameter descriptions for `gss_add_oid_set_member()` follow:

minor_status A mechanism specific status code.
member_oid Object identifier to be copied into the set.
oid_set Set in which the object identifier should be inserted.

Description The `gss_add_oid_set_member()` function adds an object identifier to an object identifier set. You should use this function in conjunction with [gss_create_empty_oid_set\(3GSS\)](#) when constructing a set of mechanism OIDs for input to [gss_acquire_cred\(3GSS\)](#). The *oid_set* parameter must refer to an OID-set created by GSS-API, that is, a set returned by [gss_create_empty_oid_set\(3GSS\)](#).

The GSS-API creates a copy of the *member_oid* and inserts this copy into the set, expanding the storage allocated to the OID-set elements array, if necessary. New members are always added to the end of the OID set's elements. If the *member_oid* is already present, the *oid_set* should remain unchanged.

Errors The `gss_add_oid_set_member()` function can return the following status codes:

GSS_S_COMPLETE
Successful completion.

GSS_S_FAILURE
The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the *minor_status* parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT-Level	Safe

See Also [gss_acquire_cred\(3GSS\)](#), [gss_create_empty_oid_set\(3GSS\)](#), [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_canonicalize_name – convert an internal name to a mechanism name

Synopsis

```
cc [flag...] file... -lgss [library...]
#include <gssapi/gssapi.h>
```

```
OM_uint32 gss_canonicalize_name(OM_uint32 *minor_status,
                                const gss_name_t input_name, const gss_OID mech_type,
                                gss_name_t *output_name);
```

Description The `gss_canonicalize_name()` function generates a canonical mechanism name from an arbitrary internal name. The mechanism name is the name that would be returned to a context acceptor on successful authentication of a context where the initiator used the *input_name* in a successful call to `gss_acquire_cred(3GSS)`, specifying an OID set containing *mech_type* as its only member, followed by a call to `gss_init_sec_context(3GSS)`, specifying *mech_type* as the authentication mechanism.

Parameters The parameter descriptions for `gss_canonicalize_name()` follow:

<i>minor_status</i>	Mechanism-specific status code.
<i>input_name</i>	The name for which a canonical form is desired.
<i>mech_type</i>	The authentication mechanism for which the canonical form of the name is desired. The desired mechanism must be specified explicitly; no default is provided.
<i>output_name</i>	The resultant canonical name. Storage associated with this name must be freed by the application after use with a call to <code>gss_release_name(3GSS)</code> .

Errors The `gss_canonicalize_name()` function may return the status codes:

GSS_S_COMPLETE	Successful completion.
GSS_S_BAD_MECH	The identified mechanism is not supported.
GSS_S_BAD_NAME	The provided internal name contains no elements that could be processed by the specified mechanism.
GSS_S_BAD_NAME	The provided internal name was ill-formed.
GSS_S_FAILURE	The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the <i>minor_status</i> parameter details the error condition.

Attributes See `attributes(5)` for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)

ATTRIBUTE TYPE	ATTRIBUTE VALUE
	SUNWgssx (64-bit)
MT-Level	Safe

See Also [gss_acquire_cred\(3GSS\)](#), [gss_init_sec_context\(3GSS\)](#), [gss_release_name\(3GSS\)](#), [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_compare_name – compare two internal-form names

Synopsis `cc [flag...] file... -lgss [library...]
#include <gssapi/gssapi.h>`

```
OM_uint32 gss_compare_name(OM_uint32 *minor_status,  
    const gss_name_t name1, const gss_name_t name2,  
    int *name_equal);
```

Description The gss_compare_name() function allows an application to compare two internal-form names to determine whether they refer to the same entity.

If either name presented to gss_compare_name() denotes an anonymous principal, the routines indicate that the two names do not refer to the same identity.

Parameters The parameter descriptions for gss_compare_name() follow:

minor_status Mechanism-specific status code.
name1 Internal-form name.
name2 Internal-form name.
name_equal If non-zero, the names refer to same entity. If 0, the names refer to different entities. Strictly, the names are not known to refer to the same identity.

Errors The gss_compare_name() function may return the following status codes:

GSS_S_COMPLETE Successful completion.
GSS_S_BAD_NAMETYPE The two names were of incomparable types.
GSS_S_BAD_NAME One or both of *name1* or *name2* was ill-formed.
GSS_S_FAILURE The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the *minor_status* parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT-Level	Safe

See Also [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_context_time – determine how long a context will remain valid

Synopsis `cc [flag...] file... -lgss [library...]
#include <gssapi/gssapi.h>`

```
OM_uint32 gss_context_time(OM_uint32 *minor_status,  
                           gss_ctx_id_t *context_handle, OM_uint32 *time_rec);
```

Description The `gss_context_time()` function determines the number of seconds for which the specified context will remain valid.

Parameters The parameter descriptions for `gss_context_time()` are as follows:

minor_status A mechanism-specific status code.

context_handle A read-only value. Identifies the context to be interrogated.

time_rec Modifies the number of seconds that the context remains valid. If the context has already expired, returns zero.

Errors The `gss_context_time()` function returns one of the following status codes:

GSS_S_COMPLETE Successful completion.

GSS_S_CONTEXT_EXPIRED The context has already expired.

GSS_S_NO_CONTEXT The *context_handle* parameter did not identify a valid context.

GSS_S_FAILURE The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the *minor_status* parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT Level	Safe

See Also [gss_init_sec_context\(3GSS\)](#), [gss_accept_sec_context\(3GSS\)](#),
[gss_delete_sec_context\(3GSS\)](#), [gss_process_context_token\(3GSS\)](#),
[gss_inquire_context\(3GSS\)](#), [gss_wrap_size_limit\(3GSS\)](#),
[gss_export_sec_context\(3GSS\)](#), [gss_import_sec_context\(3GSS\)](#), [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_create_empty_oid_set – create an object-identifier set containing no object identifiers

Synopsis `cc [flag...] file... -lgss [library...]
#include <gssapi/gssapi.h>`

```
OM_uint32 gss_create_empty_oid_set(OM_uint32 *minor_status,  
                                   gss_OID_set *oid_set);
```

Description The `gss_create_empty_oid_set()` function creates an object-identifier set containing no object identifiers to which members may be subsequently added using the [gss_add_oid_set_member\(3GSS\)](#) function. These functions can be used to construct sets of mechanism object identifiers for input to [gss_acquire_cred\(3GSS\)](#).

Parameters The parameter descriptions for `gss_create_empty_oid_set()` follow:

minor_status Mechanism-specific status code

oid_set Empty object identifier set. The function will allocate the `gss_OID_set_desc` object, which the application must free after use with a call to [gss_release_oid_set\(3GSS\)](#).

Errors The `gss_create_empty_oid_set()` function may return the following status codes:

`GSS_S_COMPLETE` Successful completion

`GSS_S_FAILURE` The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the *minor_status* parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT-Level	Safe

See Also [gss_acquire_cred\(3GSS\)](#), [gss_add_oid_set_member\(3GSS\)](#), [gss_release_oid_set\(3GSS\)](#), [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_delete_sec_context – delete a GSS-API security context

Synopsis

```
cc [ flag... ] file... -lgss [ library... ]
#include <gssapi/gssapi.h>
```

```
OM_uint32 gss_delete_sec_context(OM_uint32 *minor_status,
                                gss_ctx_id_t *context_handle, gss_buffer_t output_token);
```

Description Use the `gss_delete_sec_context()` function to delete a security context. The `gss_delete_sec_context()` function will delete the local data structures associated with the specified security context. You may not obtain further security services that use the context specified by `context_handle`.

In addition to deleting established security contexts, `gss_delete_sec_context()` will delete any half-built security contexts that result from incomplete sequences of calls to `gss_init_sec_context(3GSS)` and `gss_accept_sec_context(3GSS)`.

The Solaris implementation of the GSS-API retains the `output_token` parameter for compatibility with version 1 of the GSS-API. Both peer applications should invoke `gss_delete_sec_context()`, passing the value `GSS_C_NO_BUFFER` to the `output_token` parameter; this indicates that no token is required. If the application passes a valid buffer to `gss_delete_sec_context()`, it will return a zero-length token, indicating that no token should be transferred by the application.

Parameters The parameter descriptions for `gss_delete_sec_context()` follow:

<i>minor_status</i>	A mechanism specific status code.
<i>context_handle</i>	Context handle identifying specific context to delete. After deleting the context, the GSS-API will set <i>context_handle</i> to <code>GSS_C_NO_CONTEXT</code> .
<i>output_token</i>	A token to be sent to remote applications that instructs them to delete the context.

Errors `gss_delete_sec_context()` may return the following status codes:

<code>GSS_S_COMPLETE</code>	Successful completion.
<code>GSS_S_NO_CONTEXT</code>	No valid context was supplied.
<code>GSS_S_FAILURE</code>	The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the <i>minor_status</i> parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT-Level	Safe

See Also [gss_accept_sec_context\(3GSS\)](#), [gss_init_sec_context\(3GSS\)](#), [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_display_name – convert internal-form name to text

Synopsis cc [*flag...*] *file...* -lgss [*library...*]
 #include <gssapi/gssapi.h>

```
OM_uint32 gss_display_name(OM_uint32 *minor_status,
    const gss_name_t input_name, gss_buffer_t output_name_buffer,
    gss_OID *output_name_type);
```

Description The gss_display_name() function allows an application to obtain a textual representation of an opaque internal-form name for display purposes.

If *input_name* denotes an anonymous principal, the GSS-API returns the gss_OID value GSS_C_NT_ANONYMOUS as the *output_name_type*, and a textual name that is syntactically distinct from all valid supported printable names in *output_name_buffer*.

If *input_name* was created by a call to [gss_import_name\(3GSS\)](#), specifying GSS_C_NO_OID as the name-type, the GSS-API returns GSS_C_NO_OID by means of the *output_name_type* parameter.

Parameters The parameter descriptions for gss_display_name() follow:

<i>minor_status</i>	Mechanism-specific status code.
<i>input_name</i>	Name in internal form.
<i>output_name_buffer</i>	Buffer to receive textual name string. The application must free storage associated with this name after use with a call to gss_release_buffer(3GSS) .
<i>output_name_type</i>	The type of the returned name. The returned gss_OID will be a pointer into static storage and should be treated as read-only by the caller. In particular, the application should not attempt to free it. Specify NULL if this parameter is not required.

Errors The gss_display_name() function may return the following status codes:

GSS_S_COMPLETE	Successful completion.
GSS_S_BAD_NAME	The <i>input_name</i> was ill-formed.
GSS_S_FAILURE	The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the <i>minor_status</i> parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)

ATTRIBUTE TYPE	ATTRIBUTE VALUE
	SUNWgssx (64-bit)
MT-Level	Safe

See Also [gss_import_name\(3GSS\)](#), [gss_release_buffer\(3GSS\)](#), [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_display_status – convert a GSS-API status code to text

Synopsis `cc [flag...] file... -lgss [library...]
#include <gssapi/gssapi.h>`

```
OM_uint32 gss_display_status(OM_uint32 *minor_status,  
    OM_uint32 status_value,int status_type,  
    const gss_OID mech_type, OM_uint32 *message_context,  
    gss_buffer_t status_string);
```

Description The `gss_display_status()` function enables an application to obtain a textual representation of a GSS-API status code for display to the user or for logging purposes. Because some status values may indicate multiple conditions, applications may need to call `gss_display_status()` multiple times, with each call generating a single text string.

The `message_context` parameter is used by `gss_acquire_cred()` to store state information on error messages that are extracted from a given `status_value`. The `message_context` parameter must be initialized to 0 by the application prior to the first call, and `gss_display_status()` will return a non-zero value in this parameter if there are further messages to extract.

The `message_context` parameter contains all state information required by `gss_display_status()` to extract further messages from the `status_value`. If a non-zero value is returned in this parameter, the application is not required to call `gss_display_status()` again unless subsequent messages are desired.

Parameters The parameter descriptions for `gss_display_status()` follow:

<i>minor_status</i>	Status code returned by the underlying mechanism.
<i>status_value</i>	Status value to be converted.
<i>status_type</i>	If the value is <code>GSS_C_GSS_CODE</code> , <i>status_value</i> is a GSS-API status code. If the value is <code>GSS_C_MECH_CODE</code> , then <i>status_value</i> is a mechanism status code.
<i>mech_type</i>	Underlying mechanism that is used to interpret a minor status value. Supply <code>GSS_C_NO_OID</code> to obtain the system default.
<i>message_context</i>	Should be initialized to zero prior to the first call. On return from <code>gss_display_status()</code> , a non-zero <i>status_value</i> parameter indicates that additional messages may be extracted from the status code by means of subsequent calls to <code>gss_display_status()</code> , passing the same <i>status_value</i> , <i>status_type</i> , <i>mech_type</i> , and <i>message_context</i> parameters.
<i>status_string</i>	Textual representation of the <i>status_value</i> . Storage associated with this parameter must be freed by the application after use with a call to <code>gss_release_buffer(3GSS)</code> .

Errors The `gss_display_status()` function may return the following status codes:

GSS_S_COMPLETE	Successful completion.
GSS_S_BAD_MECH	Indicates that translation in accordance with an unsupported mechanism type was requested.
GSS_S_BAD_STATUS	The status value was not recognized, or the status type was neither GSS_C_GSS_CODE nor GSS_C_MECH_CODE.
GSS_S_FAILURE	The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the <i>minor_status</i> parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT-Level	Safe

See Also [gss_acquire_cred\(3GSS\)](#), [gss_release_buffer\(3GSS\)](#), [attributes\(5\)](#)

Developer’s Guide to Oracle Solaris Security

Name gss_duplicate_name – create a copy of an internal name

Synopsis

```
cc [flag...] file... -lgss [library...]
#include <gssapi/gssapi.h>

OM_uint32 gss_duplicate_name(OM_uint32 *minor_status,
    const gss_name_t src_name, gss_name_t *dest_name);
```

Description The `gss_duplicate_name()` function creates an exact duplicate of the existing internal name `src_name`. The new `dest_name` will be independent of the `src_name`. The `src_name` and `dest_name` must both be released, and the release of one does not affect the validity of the other.

Parameters The parameter descriptions for `gss_duplicate_name()` follow:

minor_status A mechanism-specific status code.

src_name Internal name to be duplicated.

dest_name The resultant copy of *src_name*. Storage associated with this name must be freed by the application after use with a call to [gss_release_name\(3GSS\)](#).

Errors The `gss_duplicate_name()` function may return the following status codes:

GSS_S_COMPLETE Successful completion.

GSS_S_BAD_NAME The *src_name* parameter was ill-formed.

GSS_S_FAILURE The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the *minor_status* parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT-Level	Safe

See Also [gss_release_name\(3GSS\)](#), [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_export_name – convert a mechanism name to export form

Synopsis `cc [flag...] file... -lgss [library...]
#include <gssapi/gssapi.h>`

```
OM_uint32 gss_export_name(OM_uint32 *minor_status,  
                          const gss_name_t input_name, gss_buffer_t exported_name);
```

Description The `gss_export_name()` function allows a GSS-API internal name to be converted into a mechanism-specific name. The function produces a canonical contiguous string representation of a mechanism name, suitable for direct comparison, with [memory\(3C\)](#), or for use in authorization functions, matching entries in an access-control list. The *input_name* parameter must specify a valid mechanism name, that is, an internal name generated by [gss_accept_sec_context\(3GSS\)](#) or by [gss_canonicalize_name\(3GSS\)](#).

Parameters The parameter descriptions for `gss_export_name()` follow:

minor_status A mechanism-specific status code.

input_name The mechanism name to be exported.

exported_name The canonical contiguous string form of *input_name*. Storage associated with this string must freed by the application after use with [gss_release_buffer\(3GSS\)](#).

Errors The `gss_export_name()` function may return the following status codes:

GSS_S_COMPLETE Successful completion.

GSS_S_NAME_NOT_MN The provided internal name was not a mechanism name.

GSS_S_FAILURE The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the *minor_status* parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT-Level	Safe

See Also [gss_accept_sec_context\(3GSS\)](#), [gss_canonicalize_name\(3GSS\)](#), [gss_release_buffer\(3GSS\)](#), [memory\(3C\)](#), [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_export_sec_context – transfer a security context to another process

Synopsis cc [*flag...*] *file...* -lgss [*library...*]
 #include <gssapi/gssapi.h>

```
OM_uint32 gss_export_sec_context(OM_uint32 *minor_status,
                                gss_ctx_id_t *context_handle, gss_buffer_t interprocess_token);
```

Description The gss_export_sec_context() function generates an interprocess token for transfer to another process within an end system. gss_export_sec_context() and gss_import_sec_context() allow a security context to be transferred between processes on a single machine.

The gss_export_sec_context() function supports the sharing of work between multiple processes. This routine is typically used by the context-acceptor, in an application where a single process receives incoming connection requests and accepts security contexts over them, then passes the established context to one or more other processes for message exchange. gss_export_sec_context() deactivates the security context for the calling process and creates an interprocess token which, when passed to gss_import_sec_context() in another process, reactivates the context in the second process. Only a single instantiation of a given context can be active at any one time; a subsequent attempt by a context exporter to access the exported security context will fail.

The interprocess token may contain security-sensitive information, for example cryptographic keys. While mechanisms are encouraged to either avoid placing such sensitive information within interprocess tokens or to encrypt the token before returning it to the application, in a typical object-library GSS-API implementation, this might not be possible. Thus, the application must take care to protect the interprocess token and ensure that any process to which the token is transferred is trustworthy. If creation of the interprocess token is successful, the GSS-API deallocates all process-wide resources associated with the security context and sets the context_handle to GSS_C_NO_CONTEXT. In the event of an error that makes it impossible to complete the export of the security context, the function does not return an interprocess token and leaves the security context referenced by the *context_handle* parameter untouched.

Sun's implementation of gss_export_sec_context() does not encrypt the interprocess token. The interprocess token is serialized before it is transferred to another process.

Parameters The parameter descriptions for gss_export_sec_context() are as follows:

<i>minor_status</i>	A mechanism-specific status code.
<i>context_handle</i>	Context handle identifying the context to transfer.
<i>interprocess_token</i>	Token to be transferred to target process. Storage associated with this token must be freed by the application after use with a call to gss_release_buffer(3GSS) .

Errors `gss_export_sec_context()` returns one of the following status codes:

<code>GSS_S_COMPLETE</code>	Successful completion.
<code>GSS_S_CONTEXT_EXPIRED</code>	The context has expired.
<code>GSS_S_NO_CONTEXT</code>	The context was invalid.
<code>GSS_S_UNAVAILABLE</code>	The operation is not supported.
<code>GSS_S_FAILURE</code>	The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the <i>minor_status</i> parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTETYPE	ATTRIBUTEVALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT Level	Safe

See Also [gss_accept_sec_context\(3GSS\)](#), [gss_import_sec_context\(3GSS\)](#), [gss_init_sec_context\(3GSS\)](#), [gss_release_buffer\(3GSS\)](#), [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name `gss_get_mic` – calculate a cryptographic message

Synopsis `cc [flag...] file... -lgss [library...]
#include <gssapi/gssapi.h>`

```
OM_uint32 gss_get_mic(OM_uint32 *minor_status,
    const gss_ctx_id_t context_handle, gss_qop_t qop_req,
    const gss_buffer_t message_buffer, gss_buffer_t msg_token);
```

Description The `gss_get_mic()` function generates a cryptographic MIC for the supplied message, and places the MIC in a token for transfer to the peer application. The `qop_req` parameter allows a choice between several cryptographic algorithms, if supported by the chosen mechanism.

Since some application-level protocols may wish to use tokens emitted by [gss_wrap\(3GSS\)](#) to provide secure framing, the GSS-API allows MICs to be derived from zero-length messages.

Parameters The parameter descriptions for `gss_get_mic()` follow:

<i>minor_status</i>	The status code returned by the underlying mechanism.
<i>context_handle</i>	Identifies the context on which the message will be sent.
<i>qop_req</i>	Specifies the requested quality of protection. Callers are encouraged, on portability grounds, to accept the default quality of protection offered by the chosen mechanism, which may be requested by specifying <code>GSS_C_QOP_DEFAULT</code> for this parameter. If an unsupported protection strength is requested, <code>gss_get_mic()</code> will return a <i>major_status</i> of <code>GSS_S_BAD_QOP</code> .
<i>message_buffer</i>	The message to be protected.
<i>msg_token</i>	The buffer to receive the token. Storage associated with this message must be freed by the application after use with a call to gss_release_buffer(3GSS) .

Errors `gss_get_mic()` may return the following status codes:

<code>GSS_S_COMPLETE</code>	Successful completion.
<code>GSS_S_CONTEXT_EXPIRED</code>	The context has already expired.
<code>GSS_S_NO_CONTEXT</code>	The <i>context_handle</i> parameter did not identify a valid context.
<code>GSS_S_BAD_QOP</code>	The specified QOP is not supported by the mechanism.
<code>GSS_S_FAILURE</code>	The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the <i>minor_status</i> parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT-Level	Safe

See Also [gss_release_buffer\(3GSS\)](#), [gss_wrap\(3GSS\)](#), [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_import_name – convert a contiguous string name to GSS_API internal format

Synopsis

```
cc [flag...] file... -lgss [library ...]
#include <gssapi/gssapi.h>
```

```
OM_uint32 gss_import_name(OM_uint32 * minor_status,
    const gss_buffer_t input_name_buffer, const gss_OID input_name_type,
    gss_name_t *output_name);
```

Description The `gss_import_name()` function converts a contiguous string name to internal form. In general, the internal name returned by means of the `output_name` parameter will not be a mechanism name; the exception to this is if the `input_name_type` indicates that the contiguous string provided by means of the `input_name_buffer` parameter is of type `GSS_C_NT_EXPORT_NAME`, in which case, the returned internal name will be a mechanism name for the mechanism that exported the name.

Parameters The parameter descriptions for `gss_import_name()` follow:

<i>minor_status</i>	Status code returned by the underlying mechanism.
<i>input_name_buffer</i>	The <code>gss_buffer_desc</code> structure containing the name to be imported.
<i>input_name_type</i>	A <code>gss_OID</code> that specifies the format that the <code>input_name_buffer</code> is in.
<i>output_name</i>	The <code>gss_name_t</code> structure to receive the returned name in internal form. Storage associated with this name must be freed by the application after use with a call to <code>gss_release_name()</code> .

Errors The `gss_import_name()` function may return the following status codes:

<code>GSS_S_COMPLETE</code>	The <code>gss_import_name()</code> function completed successfully.
<code>GSS_S_BAD_NAMETYPE</code>	The <code>input_name_type</code> was unrecognized.
<code>GSS_S_BAD_NAME</code>	The <code>input_name</code> parameter could not be interpreted as a name of the specified type.
<code>GSS_S_BAD_MECH</code>	The <code>input_name_type</code> was <code>GSS_C_NT_EXPORT_NAME</code> , but the mechanism contained within the <code>input_name</code> is not supported.
<code>GSS_S_FAILURE</code>	The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the <code>minor_status</code> parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)

ATTRIBUTE TYPE	ATTRIBUTE VALUE
	SUNWgssx (64-bit)
MT-Level	Safe

See Also [gss_release_buffer\(3GSS\), attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_import_sec_context – import security context established by another process

Synopsis

```
cc [ flag... ] file... -lgss [ library... ]
#include <gssapi/gssapi.h>
```

```
OM_uint32 gss_import_sec_context(OM_uint32 *minor_status,
                                const gss_buffer_t interprocess_token, gss_ctx_id_t *context_handle);
```

Description The `gss_import_sec_context()` function allows a process to import a security context established by another process. A given interprocess token can be imported only once. See [gss_export_sec_context\(3GSS\)](#).

Parameters The parameter descriptions for `gss_import_sec_context()` are as follows:

<i>minor_status</i>	A mechanism-specific status code.
<i>interprocess_token</i>	Token received from exporting process.
<i>context_handle</i>	Context handle of newly reactivated context. Resources associated with this context handle must be released by the application after use with a call to gss_delete_sec_context(3GSS) .

Errors `gss_import_sec_context()` returns one of the following status codes:

GSS_S_COMPLETE	Successful completion.
GSS_S_NO_CONTEXT	The token did not contain a valid context reference.
GSS_S_DEFECTIVE_TOKEN	The token was invalid.
GSS_S_UNAVAILABLE	The operation is unavailable.
GSS_S_UNAUTHORIZED	Local policy prevents the import of this context by the current process.
GSS_S_FAILURE	The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the <i>minor_status</i> parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT Level	Safe

See Also [gss_accept_sec_context\(3GSS\)](#), [gss_context_time\(3GSS\)](#),
[gss_delete_sec_context\(3GSS\)](#), [gss_export_sec_context\(3GSS\)](#),
[gss_init_sec_context\(3GSS\)](#), [gss_inquire_context\(3GSS\)](#),
[gss_process_context_token\(3GSS\)](#), [gss_wrap_size_limit\(3GSS\)](#), [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_indicate_mechs – determine available security mechanisms

Synopsis `cc [flag...] file... -lgss [library...]
#include <gssapi/gssapi.h>`

```
OM_uint32 gss_indicate_mechs(OM_uint32 *minor_status,  
                             gss_OID_set *mech_set);
```

Description The `gss_indicate_mechs()` function enables an application to determine available underlying security mechanisms.

Parameters The parameter descriptions for `gss_indicate_mechs()` follow:

minor_status A mechanism-specific status code.

mech_set Set of supported mechanisms. The returned `gss_OID_set` value will be a dynamically-allocated OID set that should be released by the caller after use with a call to [gss_release_oid_set\(3GSS\)](#).

Errors The `gss_indicate_mechs()` function may return the following status codes:

GSS_S_COMPLETE Successful completion.

GSS_S_FAILURE The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the *minor_status* parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT-Level	Safe

See Also [gss_release_oid_set\(3GSS\)](#), [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_init_sec_context – initiate a GSS-API security context with a peer application

Synopsis `cc [flag...] file... -lgss [library...]
#include <gssapi/gssapi.h>`

```
OM_uint32 gss_init_sec_context(OM_uint32 *minor_status,
    const gss_cred_id_t initiator_cred_handle,
    gss_ctx_id_t *context_handle, const gss_name_t *target_name,
    const gss_OID mech_type, OM_uint32 req_flags,
    OM_uint32 time_req, const gss_channel_bindings_t input_chan_bindings,
    const gss_buffer_t input_token, gss_OID *actual_mech_type,
    gss_buffer_t output_token, OM_uint32 *ret_flags,
    OM_uint32 *time_rec);
```

Parameters The parameter descriptions for `gss_init_sec_context()` follow:

<i>minor_status</i>	A mechanism specific status code.						
<i>initiator_cred_handle</i>	The handle for the credentials claimed. Supply <code>GSS_C_NO_CREDENTIAL</code> to act as a default initiator principal. If no default initiator is defined, the function returns <code>GSS_S_NO_CRED</code> .						
<i>context_handle</i>	The context handle for a new context. Supply the value <code>GSS_C_NO_CONTEXT</code> for the first call, and use the value returned in any continuation calls. The resources associated with <i>context_handle</i> must be released by the application after use by a call to gss_delete_sec_context(3GSS) .						
<i>target_name</i>	The name of the context acceptor.						
<i>mech_type</i>	The object ID of the desired mechanism. To obtain a specific default, supply the value <code>GSS_C_NO_ID</code> .						
<i>req_flags</i>	Contains independent flags, each of which will request that the context support a specific service option. A symbolic name is provided for each flag. Logically-OR the symbolic name to the corresponding required flag to form the bit-mask value. <i>req_flags</i> may contain one of the following values: <table> <tr> <td><code>GSS_C_DELEG_FLAG</code></td><td>If true, delegate credentials to a remote peer. Do not delegate the credentials if the value is false.</td></tr> <tr> <td><code>GSS_C_MUTUAL_FLAG</code></td><td>If true, request that the peer authenticate itself. If false, authenticate to the remote peer only.</td></tr> <tr> <td><code>GSS_C_REPLAY_FLAG</code></td><td>If true, enable replay detection for messages protected with gss_wrap(3GSS) or</td></tr> </table>	<code>GSS_C_DELEG_FLAG</code>	If true, delegate credentials to a remote peer. Do not delegate the credentials if the value is false.	<code>GSS_C_MUTUAL_FLAG</code>	If true, request that the peer authenticate itself. If false, authenticate to the remote peer only.	<code>GSS_C_REPLAY_FLAG</code>	If true, enable replay detection for messages protected with gss_wrap(3GSS) or
<code>GSS_C_DELEG_FLAG</code>	If true, delegate credentials to a remote peer. Do not delegate the credentials if the value is false.						
<code>GSS_C_MUTUAL_FLAG</code>	If true, request that the peer authenticate itself. If false, authenticate to the remote peer only.						
<code>GSS_C_REPLAY_FLAG</code>	If true, enable replay detection for messages protected with gss_wrap(3GSS) or						

	gss_get_mic(3GSS) . Do not attempt to detect replayed messages if false.
GSS_C_SEQUENCE_FLAG	If true, enable detection of out-of-sequence protected messages. Do not attempt to detect out-of-sequence messages if false.
GSS_C_CONF_FLAG	If true, request that confidential service be made available by means of gss_wrap(3GSS) . If false, no per-message confidential service is required.
GSS_C_INTEG_FLAG	If true, request that integrity service be made available by means of gss_wrap(3GSS) or gss_get_mic(3GSS) . If false, no per-message integrity service is required.
GSS_C_ANON_FLAG	If true, do not reveal the initiator's identity to the acceptor. If false, authenticate normally.
<i>time_req</i>	The number of seconds for which the context will remain valid. Supply a zero value to <i>time_req</i> to request a default validity period.
<i>input_chan_bindings</i>	Optional application-specified bindings. Allows application to securely bind channel identification information to the security context. Set to GSS_C_NO_CHANNEL_BINDINGS if you do not want to use channel bindings.
<i>input_token</i>	Token received from the peer application. On the initial call, supply GSS_C_NO_BUFFER or a pointer to a buffer containing the value GSS_C_EMPTY_BUFFER.
<i>actual_mech_type</i>	The actual mechanism used. The OID returned by means of this parameter will be pointer to static storage that should be treated as read-only. The application should not attempt to free it. To obtain a specific default, supply the value GSS_C_NO_ID. Specify NULL if the parameter is not required.
<i>output_token</i>	The token to send to the peer application. If the length field of the returned buffer is zero, no token need be sent to the peer application. After use storage associated with this buffer must be freed by the application by a call to gss_release_buffer(3GSS) .

ret_flags

Contains various independent flags, each of which indicates that the context supports a specific service option. If not needed, specify NULL. Test the returned bit-mask *ret_flags* value against its symbolic name to determine if the given option is supported by the context. *ret_flags* may contain one of the following values:

GSS_C_DELEG_FLAG	If true, credentials were delegated to the remote peer. If false, no credentials were delegated.
GSS_C_MUTUAL_FLAG	If true, the remote peer authenticated itself. If false, the remote peer did not authenticate itself.
GSS_C_REPLAY_FLAG	If true, replay of protected messages will be detected. If false, replayed messages will not be detected.
GSS_C_SEQUENCE_FLAG	If true, out of sequence protected messages will be detected. If false, they will not be detected.
GSS_C_CONF_FLAG	If true, confidential service may be invoked by calling the <code>gss_wrap()</code> routine. If false, no confidentiality service is available by means of gss_wrap(3GSS) . <code>gss_wrap()</code> will provide message encapsulation, data-origin authentication and integrity services only.
GSS_C_INTEG_FLAG	If true, integrity service may be invoked by calling either the gss_wrap(3GSS) or gss_get_mic(3GSS) routine. If false, per-message integrity service is not available.
GSS_C_ANON_FLAG	If true, the initiator's identity has not been revealed; it will not be revealed if any emitted token is passed to the acceptor. If false, the initiator has been or will be authenticated normally.
GSS_C_PROT_READY_FLAG	If true, the protection services specified by the states of

	GSS_C_CONF_FLAG and GSS_C_INTEG_FLAG are available if the accompanying major status return value is either GSS_S_COMPLETE or GSS_S_CONTINUE_NEEDED. If false, the protection services are available only if the accompanying major status return value is GSS_S_COMPLETE.
	GSS_C_TRANS_FLAG
	If true, the resultant security context may be transferred to other processes by means of a call to gss_export_sec_context(3GSS) . If false, the security context cannot be transferred.
<i>time_rec</i>	The number of seconds for which the context will remain valid. Specify NULL if the parameter is not required.

Description The `gss_init_sec_context()` function initiates the establishment of a security context between the application and a remote peer. Initially, the *input_token* parameter should be specified either as `GSS_C_NO_BUFFER`, or as a pointer to a `gss_buffer_desc` object with a `length` field that contains a zero value. The routine may return a *output_token*, which should be transferred to the peer application, which will present it to [gss_accept_sec_context\(3GSS\)](#). If no token need be sent, `gss_init_sec_context()` will indicate this by setting the `length` field of the *output_token* argument to zero. To complete context establishment, one or more reply tokens may be required from the peer application; if so, `gss_init_sec_context()` will return a status code that contains the supplementary information bit `GSS_S_CONTINUE_NEEDED`. In this case, make another call to `gss_init_sec_context()` when the reply token is received from the peer application and pass the reply token to `gss_init_sec_context()` by means of the *input_token* parameter.

Construct portable applications to use the token length and return status to determine whether to send or wait for a token.

Whenever the routine returns a major status that includes the value `GSS_S_CONTINUE_NEEDED`, the context is not fully established, and the following restrictions apply to the output parameters:

- The value returned by means of the *time_rec* parameter is undefined. Unless the accompanying *ret_flags* parameter contains the bit `GSS_C_PROT_READY_FLAG`, which indicates that per-message services may be applied in advance of a successful completion status, the value returned by means of the *actual_mech_type* parameter is undefined until the routine returns a major status value of `GSS_S_COMPLETE`.

- The values of the GSS_C_DELEG_FLAG, GSS_C_MUTUAL_FLAG, GSS_C_REPLAY_FLAG, GSS_C_SEQUENCE_FLAG, GSS_C_CONF_FLAG, GSS_C_INTEG_FLAG and GSS_C_ANON_FLAG bits returned by the *ret_flags* parameter contain values that will be valid if context establishment succeeds. For example, if the application requests a service such as delegation or anonymous authentication by means of the *req_flags* argument, and the service is unavailable from the underlying mechanism, `gss_init_sec_context()` generates a token that will not provide the service, and it indicate by means of the *ret_flags* argument that the service will not be supported. The application may choose to abort context establishment by calling `gss_delete_sec_context(3GSS)` if it cannot continue without the service, or if the service was merely desired but not mandatory, it may transmit the token and continue context establishment.
- The values of the GSS_C_PROT_READY_FLAG and GSS_C_TRANS_FLAG bits within *ret_flags* indicate the actual state at the time `gss_init_sec_context()` returns, whether or not the context is fully established.
- The GSS-API sets the GSS_C_PROT_READY_FLAG in the final *ret_flags* returned to a caller, for example, when accompanied by a GSS_S_COMPLETE status code. However, applications should not rely on this behavior, as the flag was not defined in Version 1 of the GSS-API. Instead, applications should determine what per-message services are available after a successful context establishment according to the GSS_C_INTEG_FLAG and GSS_C_CONF_FLAG values.
- All other bits within the *ret_flags* argument are set to zero.

If the initial call of `gss_init_sec_context()` fails, the GSS-API does not create a context object; it leaves the value of the *context_handle* parameter set to GSS_C_NO_CONTEXT to indicate this. In the event of failure on a subsequent call, the GSS-API leaves the security context untouched for the application to delete using `gss_delete_sec_context(3GSS)`.

During context establishment, the informational status bits GSS_S_OLD_TOKEN and GSS_S_DUPLICATE_TOKEN indicate fatal errors, and GSS-API mechanisms should always return them in association with a status code of GSS_S_FAILURE. This pairing requirement was not part of Version 1 of the GSS-API specification, so applications that wish to run on Version 1 implementations must special-case these codes.

Errors `gss_init_sec_context()` may return the following status codes:

GSS_S_COMPLETE	Successful completion.
GSS_S_CONTINUE_NEEDED	A token from the peer application is required to complete the context, and <code>gss_init_sec_context()</code> must be called again with that token.
GSS_S_DEFECTIVE_TOKEN	Consistency checks performed on the <i>input_token</i> failed.
GSS_S_DEFECTIVE_CREDENTIAL	Consistency checks performed on the credential failed.

GSS_S_NO_CRED	The supplied credentials are not valid for context acceptance, or the credential handle does not reference any credentials.
GSS_S_CREDENTIALS_EXPIRED	The referenced credentials have expired.
GSS_S_BAD_BINDINGS	The <i>input_token</i> contains different channel bindings than those specified by means of the <i>input_chan_bindings</i> parameter.
GSS_S_BAD_SIG	The <i>input_token</i> contains an invalid MIC or a MIC that cannot be verified.
GSS_S_OLD_TOKEN	The <i>input_token</i> is too old. This is a fatal error while establishing context.
GSS_S_DUPLICATE_TOKEN	The <i>input_token</i> is valid, but it is a duplicate of a token already processed. This is a fatal error while establishing context.
GSS_S_NO_CONTEXT	The supplied context handle does not refer to a valid context.
GSS_S_BAD_NAMETYPE	The provided <i>target_name</i> parameter contains an invalid or unsupported <i>name</i> type.
GSS_S_BAD_NAME	The supplied <i>target_name</i> parameter is ill-formed.
GSS_S_BAD_MECH	The token received specifies a mechanism that is not supported by the implementation or the provided credential.
GSS_S_FAILURE	The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the <i>minor_status</i> parameter details the error condition.

Examples **EXAMPLE 1** Invoking `gss_init_sec_context()` Within a Loop

A typical portable caller should always invoke `gss_init_sec_context()` within a loop:

```
int context_established = 0;
gss_ctx_id_t context_hdl = GSS_C_NO_CONTEXT;
...
input_token->length = 0;

while (!context_established) {
    maj_stat = gss_init_sec_context(&min_stat,
                                   cred_hdl,
                                   &context_hdl,
```

EXAMPLE 1 Invoking gss_init_sec_context() Within a Loop (Continued)

```

                                target_name,
                                desired_mech,
                                desired_services,
                                desired_time,
                                input_bindings,
                                input_token,
                                &actual_mech,
                                output_token,
                                &actual_services,
                                &actual_time);

if (GSS_ERROR(maj_stat)) {
    report_error(maj_stat, min_stat);
};

if (output_token->length != 0) {
    send_token_to_peer(output_token);
    gss_release_buffer(&min_stat, output_token)
};
if (GSS_ERROR(maj_stat)) {

    if (context_hdl != GSS_C_NO_CONTEXT)
        gss_delete_sec_context(&min_stat,
                                &context_hdl,
                                GSS_C_NO_BUFFER);

    break;
};
if (maj_stat & GSS_S_CONTINUE_NEEDED) {
    receive_token_from_peer(input_token);
} else {
    context_established = 1;
};
};
```

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Safe

See Also [gss_delete_sec_context\(3GSS\)](#), [gss_export_sec_context\(3GSS\)](#), [gss_get_mic\(3GSS\)](#), [gss_wrap\(3GSS\)](#), [attributes\(5\)](#)

Name gss_inquire_context – obtain information about a security context

Synopsis `cc [flag...] file... -lgss [library...]
#include <gssapi/gssapi.h>`

```
OM_uint32 gss_inquire_context(OM_uint32 *minor_status,  
    const gss_ctx_id_t context_handle, gss_name_t *src_name,  
    gss_name_t *targ_name, OM_uint32 *lifetime_rec,  
    gss_OID *mech_type, OM_uint32 *ctx_flags,  
    int *locally_initiated, int *open);
```

Description The `gss_inquire_context()` function obtains information about a security context. The caller must already have obtained a handle that refers to the context, although the context need not be fully established.

Parameters The parameter descriptions for `gss_inquire_context()` are as follows:

<i>minor_status</i>	A mechanism-specific status code.
<i>context_handle</i>	A handle that refers to the security context.
<i>src_name</i>	The name of the context initiator. If the context was established using anonymous authentication, and if the application invoking <code>gss_inquire_context()</code> is the context acceptor, an anonymous name is returned. Storage associated with this name must be freed by the application after use with a call to <code>gss_release_name()</code> . Specify <code>NULL</code> if the parameter is not required.
<i>targ_name</i>	The name of the context acceptor. Storage associated with this name must be freed by the application after use with a call to <code>gss_release_name()</code> . If the context acceptor did not authenticate itself, and if the initiator did not specify a target name in its call to <code>gss_init_sec_context()</code> , the value <code>GSS_C_NO_NAME</code> is returned. Specify <code>NULL</code> if the parameter is not required.
<i>lifetime_rec</i>	The number of seconds for which the context will remain valid. If the context has expired, this parameter will be set to zero. Specify <code>NULL</code> if the parameter is not required.
<i>mech_type</i>	The security mechanism providing the context. The returned OID is a pointer to static storage that should be treated as read-only by the application; in particular, the application should not attempt to free it. Specify <code>NULL</code> if the parameter is not required.
<i>ctx_flags</i>	Contains various independent flags, each of which indicates that the context supports (or is expected to support, if <code>ctx_open</code> is false) a specific service option. If not needed, specify <code>NULL</code> . Symbolic names are provided for each flag, and the symbolic names corresponding to the required flags

should be logically ANDed with the `ret_flags` value to test whether a given option is supported by the context. The flags are:

<code>GSS_C_DELEG_FLAG</code>	If true, credentials were delegated from the initiator to the acceptor. If false, no credentials were delegated.
<code>GSS_C_MUTUAL_FLAG</code>	If true, the acceptor was authenticated to the initiator. If false, the acceptor did not authenticate itself.
<code>GSS_C_REPLAY_FLAG</code>	If true, the replay of protected messages will be detected. If false, replayed messages will not be detected.
<code>GSS_C_SEQUENCE_FLAG</code>	If true, out-of-sequence protected messages will be detected. If false, out-of-sequence messages will not be detected.
<code>GSS_C_CONF_FLAG</code>	If true, confidential service may be invoked by calling the <code>gss_wrap(3GSS)</code> routine. If false, no confidential service is available through <code>gss_wrap()</code> . <code>gss_wrap()</code> provides message encapsulation, data-origin authentication, and integrity services only.
<code>GSS_C_INTEG_FLAG</code>	If true, integrity service can be invoked by calling either the <code>gss_get_mic()</code> or the <code>gss_wrap()</code> routine. If false, per-message integrity service is unavailable.
<code>GSS_C_ANON_FLAG</code>	If true, the initiator's identity is not revealed to the acceptor. The <i>src_name</i> parameter, if requested, contains an anonymous internal name. If false, the initiator has been authenticated normally.
<code>GSS_C_PROT_READY_FLAG</code>	If true, the protection services, as specified by the states of the <code>GSS_C_CONF_FLAG</code> and <code>GSS_C_INTEG_FLAG</code> , are available for use. If false, they are available only if the context is fully established, that is, if the <i>open</i> parameter is non-zero.
<code>GSS_C_TRANS_FLAG</code>	If true, resultant security context can be transferred to other processes through a call to <code>gss_export_sec_context()</code> . If

false, the security context is not transferable.

locally_initiated Non-zero if the invoking application is the context initiator. Specify NULL if the parameter is not required.

open Non-zero if the context is fully established; zero if a context-establishment token is expected from the peer application. Specify NULL if the parameter is not required.

Errors `gss_inquire_context()` returns one of the following status codes:

`GSS_S_COMPLETE` Successful completion.

`GSS_S_NO_CONTEXT` The referenced context could not be accessed.

`GSS_S_FAILURE` The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the *minor_status* parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT-Level	Safe

See Also `gss_accept_sec_context(3GSS)`, `gss_context_time(3GSS)`,
`gss_delete_sec_context(3GSS)`, `gss_export_sec_context(3GSS)`,
`gss_import_sec_context(3GSS)`, `gss_init_sec_context(3GSS)`,
`gss_process_context_token(3GSS)`, `gss_wrap(3GSS)`, `gss_wrap_size_limit(3GSS)`,
[attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_inquire_cred – obtain information about a credential

Synopsis

```
cc [ flag... ] file... -lgss [ library... ]
#include <gssapi/gssapi.h>

OM_uint32 gss_inquire_cred(OM_uint32 *minor_status,
    const gss_cred_id_t cred_handle, gss_name_t *name,
    OM_uint32 *lifetime, gss_cred_usage_t *cred_usage,
    gss_OID_set *mechanisms);
```

Parameters The parameter descriptions for gss_inquire_cred() follow:

<i>minor_status</i>	Mechanism specific status code.
<i>cred_handle</i>	Handle that refers to the target credential. Specify GSS_C_NO_CREDENTIAL to inquire about the default initiator principal.
<i>name</i>	Name of the identity asserted by the credential. Any storage associated with this name should be freed by the application after use by a call to gss_release_name(3GSS) .
<i>lifetime</i>	Number of seconds for which the credential remains valid. If the credential has expired, this parameter will be set to zero. Specify NULL if the parameter is not required.
<i>cred_usage</i>	Flag that indicates how a credential is used. The <i>cred_usage</i> parameter may contain one of the following values: GSS_C_INITIATE, GSS_C_ACCEPT, or GSS_C_BOTH. Specify NULL if this parameter is not required.
<i>mechanisms</i>	Set of mechanisms supported by the credential. Storage for the returned OID-set must be freed by the application after use by a call to gss_release_oid_set(3GSS) . Specify NULL if this parameter is not required.

Description Use the gss_inquire_cred() function to obtain information about a credential.

Return Values The gss_inquire_cred() function can return the following status codes:

GSS_S_COMPLETE	Successful completion.
GSS_S_NO_CRED	The referenced credentials could not be accessed.
GSS_S_DEFECTIVE_CREDENTIAL	The referenced credentials were invalid.
GSS_S_CREDENTIALS_EXPIRED	The referenced credentials have expired. If the <i>lifetime</i> parameter was not passed as NULL, it will be set to 0.
GSS_S_FAILURE	The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the <i>minor_status</i> parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Safe

See Also [gss_release_name\(3GSS\)](#), [gss_release_oid_set\(3GSS\)](#), [libgss\(3LIB\)](#), [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_inquire_cred_by_mech – obtain per-mechanism information about a credential

Synopsis cc [*flag...*] *file...* -lgss [*library...*]
#include <gssapi/gssapi.h>

```
OM_uint32 gss_inquire_cred_by_mech(OM_uint32 *minor_status,  
    const gss_cred_id_t cred_handle, const gss_OID mech_type,  
    gss_name_t *name, OM_uint32 *initiator_lifetime,  
    OM_uint32 *acceptor_lifetime, gss_cred_usage_t *cred_usage);
```

Parameters	<i>acceptor_lifetime</i>	The number of seconds that the credential is capable of accepting security contexts under the specified mechanism. If the credential can no longer be used to accept contexts, or if the credential usage for this mechanism is GSS_C_INITIATE, this parameter will be set to 0. Specify NULL if this parameter is not required.
	<i>cred_handle</i>	A handle that refers to the target credential. Specify GSS_C_NO_CREDENTIAL to inquire about the default initiator principal.
	<i>cred_usage</i>	How the credential may be used with the specified mechanism. The <i>cred_usage</i> parameter may contain one of the following values: GSS_C_INITIATE, GSS_C_ACCEPT, or GSS_C_BOTH. Specify NULL if this parameter is not required.
	<i>initiator_lifetime</i>	The number of seconds that the credential is capable of initiating security contexts under the specified mechanism. If the credential can no longer be used to initiate contexts, or if the credential usage for this mechanism is GSS_C_ACCEPT, this parameter will be set to 0. Specify NULL if this parameter is not required.
	<i>mech_type</i>	The mechanism for which the information should be returned.
	<i>minor_status</i>	A mechanism specific status code.
	<i>name</i>	The name whose identity the credential asserts. Any storage associated with this <i>name</i> must be freed by the application after use by a call to gss_release_name(3GSS) .

Description The `gss_inquire_cred_by_mech()` function obtains per-mechanism information about a credential.

Errors The `gss_inquire_cred_by_mech()` function can return the following status codes:

GSS_S_COMPLETE	Successful completion.
GSS_S_CREDENTIALS_EXPIRED	The credentials cannot be added because they have expired.
GSS_S_DEFECTIVE_CREDENTIAL	The referenced credentials are invalid.

GSS_S_FAILURE	The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the <i>minor_status</i> parameter details the error condition.
GSS_S_NO_CRED	The referenced credentials cannot be accessed.
GSS_S_UNAVAILABLE	The <code>gss_inquire_cred_by_mech()</code> function is not available for the specified mechanism type.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT-Level	Safe

See Also [gss_release_name\(3GSS\)](#), [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_inquire_mechs_for_name – list mechanisms that support the specified name-type

Synopsis `cc [flag...] file... -lgss [library...]
#include <gssapi/gssapi.h>`

```
OM_uint32 gss_inquire_mechs_for_name(OM_uint32 *minor_status,  
                                     const gss_name_t input_name, gss_OID_set *mech_types);
```

Description The `gss_inquire_mechs_for_name()` function returns the set of mechanisms supported by the GSS-API that may be able to process the specified name. Each mechanism returned will recognize at least one element within the internal name.

Some implementations of the GSS-API may perform this test by checking nametype information contained within the passed name and registration information provided by individual mechanisms. This means that the *mech_types* set returned by the function may indicate that a particular mechanism will understand the name, when in fact the mechanism would refuse to accept the name as input to `gss_canonicalize_name(3GSS)`, `gss_init_sec_context(3GSS)`, `gss_acquire_cred(3GSS)`, or `gss_add_cred(3GSS)`, due to some property of the name itself rather than the name-type. Therefore, this function should be used only as a pre-filter for a call to a subsequent mechanism-specific function.

Parameters The parameter descriptions for `gss_inquire_mechs_for_name()` follow in alphabetical order:

<i>minor_status</i>	Mechanism-specific status code.
<i>input_name</i>	The name to which the inquiry relates.
<i>mech_types</i>	Set of mechanisms that may support the specified name. The returned OID set must be freed by the caller after use with a call to <code>gss_release_oid_set(3GSS)</code> .

Errors The `gss_inquire_mechs_for_name()` function may return the following status codes:

GSS_S_COMPLETE	Successful completion.
GSS_S_BAD_NAME	The <i>input_name</i> parameter was ill-formed.
GSS_S_BAD_NAMETYPE	The <i>input_name</i> parameter contained an invalid or unsupported type of name.
GSS_S_FAILURE	The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the <i>minor_status</i> parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT-Level	Safe

See Also [gss_acquire_cred\(3GSS\)](#), [gss_add_cred\(3GSS\)](#), [gss_canonicalize_name\(3GSS\)](#), [gss_init_sec_context\(3GSS\)](#), [gss_release_oid_set\(3GSS\)](#), [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_inquire_names_for_mech – list the name-types supported by the specified mechanism

Synopsis

```
cc [flag...] file... -lgss [library...]
#include <gssapi/gssapi.h>
```

```
OM_uint32 gss_inquire_names_for_mech(OM_uint32 *minor_status,
                                     const gss_OID mechanism, gss_OID_set *name_types);
```

Description The gss_inquire_names_for_mech() function returns the set of name-types supported by the specified mechanism.

Parameters The parameter descriptions for gss_inquire_names_for_mech() follow:

- minor_status* A mechanism-specific status code.
- mechanism* The mechanism to be interrogated.
- name_types* Set of name-types supported by the specified mechanism. The returned OID set must be freed by the application after use with a call to [gss_release_oid_set\(3GSS\)](#).

Errors The gss_inquire_names_for_mech() function may return the following values:

- GSS_S_COMPLETE Successful completion.
- GSS_S_FAILURE The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the *minor_status* parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT-Level	Safe

See Also [gss_release_oid_set\(3GSS\)](#), [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_oid_to_str – convert an OID to a string

Synopsis

```
cc [ flag... ] file... -lgss [ library... ]
#include <gssapi/gssapi.h>
```

```
gss_oid_to_str(OM_uint32 *minor_status, const gss_OID oid,
               gss_buffer_t oid_str);
```

Parameters *minor_status* Status code returned by underlying mechanism.
oid GSS-API OID structure to convert.
oid_str String to receive converted OID.

Description The `gss_oid_to_str()` function converts a GSS-API OID structure to a string. You can use the function to convert the name of a mechanism from an OID to a simple string. This function is a convenience function, as is its complementary function, [gss_str_to_oid\(3GSS\)](#).

If an OID must be created, use [gss_create_empty_oid_set\(3GSS\)](#) and [gss_add_oid_set_member\(3GSS\)](#) to create it. OIDs created in this way must be released with [gss_release_oid_set\(3GSS\)](#). However, it is strongly suggested that applications use the default GSS-API mechanism instead of creating an OID for a specific mechanism.

Errors The `gss_oid_to_str()` function returns one of the following status codes:

GSS_S_CALL_INACCESSIBLE_READ

A required input parameter could not be read.

GSS_S_CALL_INACCESSIBLE_WRITE

A required output parameter could not be written.

GSS_S_COMPLETE

Successful completion.

GSS_S_FAILURE

The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the *minor_status* parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT-Level	Safe

See Also `gss_add_oid_set_member(3GSS)`, `gss_create_empty_oid_set(3GSS)`,
`gss_release_oid_set(3GSS)`, `gss_str_to_oid(3GSS)`, `attributes(5)`

Developer's Guide to Oracle Solaris Security

Warnings This function is included for compatibility only with programs using earlier versions of the GSS-API and should not be used for new programs. Other implementations of the GSS-API might not support this function, so portable programs should not rely on it. Sun might not continue to support this function.

Name gss_process_context_token – pass asynchronous token to security service

Synopsis

```
cc [ flag... ] file... -lgss [ library... ]
#include <gssapi/gssapi.h>
```

```
OM_uint32 gss_process_context_token(OM_uint32 *minor_status,
    const gss_ctx_id_t context_handle, const gss_buffer_t token_buffer);
```

Description The `gss_process_context_token()` function provides a way to pass an asynchronous token to the security service. Most context-level tokens are emitted and processed synchronously by `gss_init_sec_context()` and `gss_accept_sec_context()`, and the application is informed as to whether further tokens are expected by the `GSS_C_CONTINUE_NEEDED` major status bit. Occasionally, a mechanism might need to emit a context-level token at a point when the peer entity is not expecting a token. For example, the initiator's final call to `gss_init_sec_context()` may emit a token and return a status of `GSS_S_COMPLETE`, but the acceptor's call to `gss_accept_sec_context()` might fail. The acceptor's mechanism might want to send a token containing an error indication to the initiator, but the initiator is not expecting a token at this point, believing that the context is fully established. `gss_process_context_token()` provides a way to pass such a token to the mechanism at any time.

This function is provided for compatibility with the GSS-API version 1. Because `gss_delete_sec_context()` no longer returns a valid *output_token* to be sent to `gss_process_context_token()`, applications using a newer version of the GSS-API do not need to rely on this function.

Parameters The parameter descriptions for `gss_process_context_token()` are as follows:

<i>minor_status</i>	A mechanism-specific status code.
<i>context_handle</i>	Context handle of context on which token is to be processed.
<i>token_buffer</i>	Token to process.

Errors `gss_process_context_token()` returns one of the following status codes:

<code>GSS_S_COMPLETE</code>	Successful completion.
<code>GSS_S_DEFECTIVE_TOKEN</code>	Indicates that consistency checks performed on the token failed.
<code>GSS_S_NO_CONTEXT</code>	The <i>context_handle</i> did not refer to a valid context.
<code>GSS_S_FAILURE</code>	The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the <i>minor_status</i> parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT Level	Safe

See Also [gss_accept_sec_context\(3GSS\)](#), [gss_delete_sec_context\(3GSS\)](#),
[gss_init_sec_context\(3GSS\)](#), [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_release_buffer – free buffer storage allocated by a GSS-API function

Synopsis `cc [flag...] file... -lgss [library...]
#include <gssapi/gssapi.h>`

```
OM_uint32 gss_release_buffer(OM_uint32 *minor_status, gss_buffer_t buffer);
```

Description The `gss_release_buffer()` function frees buffer storage allocated by a GSS-API function. The `gss_release_buffer()` function also zeros the length field in the descriptor to which the buffer parameter refers, while the GSS-API function sets the pointer field in the descriptor to NULL. Any buffer object returned by a GSS-API function may be passed to `gss_release_buffer()`, even if no storage is associated with the buffer.

Parameters The parameter descriptions for `gss_release_buffer()` follow:

minor_status Mechanism-specific status code.

buffer The storage associated with the buffer will be deleted. The `gss_buffer_desc()` object will not be freed; however, its length field will be zeroed.

Errors The `gss_release_buffer()` function may return the following status codes:

GSS_S_COMPLETE Successful completion

GSS_S_FAILURE The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the *minor_status* parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT-Level	Safe

See Also [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_release_cred – discard a credential handle

Synopsis

```
cc [ flag... ] file... -lgss [ library... ]
#include <gssapi/gssapi.h>

OM_uint32 gss_release_cred(OM_uint32 *minor_status,
    gss_cred_id_t *cred_handle);
```

Description The gss_release_cred() function informs the GSS-API that the specified credential handle is no longer required by the application and frees the associated resources. The cred_handle parameter is set to GSS_C_NO_CREDENTIAL when this call completes successfully.

Parameters The parameter descriptions for gss_release_cred() follow:

minor_status A mechanism specific status code.

cred_handle An opaque handle that identifies the credential to be released. If GSS_C_NO_CREDENTIAL is specified, the gss_release_cred() function will complete successfully, but it will do nothing.

Errors gss_release_cred() may return the following status codes:

GSS_S_COMPLETE Successful completion.

GSS_S_NO_CRED The referenced credentials cannot be accessed.

GSS_S_FAILURE The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the minor_status parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT-Level	Safe

See Also [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_release_name – discard an internal-form name

Synopsis `cc [flag...] file... -lgss [library...]
#include <gssapi/gssapi.h`

```
OM_uint32 gss_release_name(OM_uint32 *minor_status, gss_name_t *name);
```

Description The `gss_release_name()` function frees GSS-API-allocated storage associated with an internal-form name. The *name* is set to `GSS_C_NO_NAME` on successful completion of this call.

Parameters The parameter descriptions for `gss_release_name()` follow:

minor_status A mechanism-specific status code.
name The name to be deleted.

Errors The `gss_release_name()` function may return the following status codes:

`GSS_S_COMPLETE` Successful completion.
`GSS_S_BAD_NAME` The *name* parameter did not contain a valid name.
`GSS_S_FAILURE` The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the *minor_status* parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT-Level	Safe

See Also [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_release_oid – release an object identifier

Synopsis cc [*flag...*] *file...* -lgss [*library...*]
#include <gssapi/gssapi.h>

```
gss_release_oid(OM_uint32 *minor_status, const gss_OID *oid);
```

Description The gss_release_oid() function deletes an OID. Such an OID might have been created with gss_str_to_oid().

Since creating and deleting individual OIDs is discouraged, it is preferable to use gss_release_oid_set() if it is necessary to deallocate a set of OIDs.

Parameters The parameter descriptions for gss_release_oid() are as follows:

minor_status A mechanism-specific status code.
oid The object identifier of the mechanism to be deleted.

Errors gss_release_oid() returns one of the following status codes:

GSS_S_COMPLETE Successful completion.
GSS_S_FAILURE The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the *minor_status* parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT Level	Safe

See Also [gss_release_oid_set\(3GSS\)](#), [gss_str_to_oid\(3GSS\)](#), [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Warnings This function is included for compatibility only with programs using earlier versions of the GSS-API and should not be used for new programs. Other implementations of the GSS-API might not support this function, so portable programs should not rely on it. Sun might not continue to support this function.

Name gss_release_oid_set – free storage associated with a GSS-API-generated gss_OID_set object

Synopsis

```
cc [ flag... ] file... -lgss [ library... ]
#include <gssapi/gssapi.h>
```

```
OM_uint32 gss_release_oid_set(OM_uint32 *minor_status, gss_OID_set *set);
```

Description The gss_release_oid_set() function frees storage associated with a GSS-API-generated gss_OID_set object. The set parameter must refer to an OID-set that was returned from a GSS-API function. The gss_release_oid_set() function will free the storage associated with each individual member OID, the OID set's elements array, and gss_OID_set_desc.

gss_OID_set is set to GSS_C_NO_OID_SET on successful completion of this function.

Parameters The parameter descriptions for gss_release_oid_set() follow:

minor_status A mechanism-specific status code

set Storage associated with the gss_OID_set will be deleted

Errors The gss_release_oid_set() function may return the following status codes:

GSS_S_COMPLETE Successful completion

GSS_S_FAILURE The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the *minor_status* parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT-Level	Safe

See Also [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_store_cred – store a credential in the current credential store

Synopsis `cc [flag...] file... -lgss [library...]
#include <gssapi/gssapi.h>`

```
OM_uint32 gss_store_cred(OM_uint32 *minor_status,  
    const gss_cred_id_t input_cred, const gss_cred_usage_t cred_usage,  
    const gss_OID desired_mech, OM_uint32 overwrite_cred,  
    OM_uint32 default_cred, gss_OID_set *elements_stored,  
    gss_cred_usage_t *cred_usage_stored);
```

Parameters The parameter descriptions for `gss_store_cred()` follow:

<i>input_cred</i>	The credential to be stored.
<i>cred_usage</i>	This parameter specifies whether to store an initiator, an acceptor, or both usage components of a credential.
<i>desired_mech</i>	<p>The mechanism-specific component of a credential to be stored. If <code>GSS_C_NULL_OID</code> is specified, the <code>gss_store_cred()</code> function attempts to store all the elements of the given <i>input_cred_handle</i>.</p> <p>The <code>gss_store_cred()</code> function is not atomic when storing multiple elements of a credential. All delegated credentials, however, contain a single element.</p>
<i>overwrite_cred</i>	A boolean that indicates whether to overwrite existing credentials in the current store for the same principal as that of the <i>input_cred_handle</i> . A non-zero value indicates that credentials are overwritten. A zero value indicates that credentials are not overwritten.
<i>default_cred</i>	A boolean that indicates whether to set the principal name of the <i>input_cred_handle</i> parameter as the default of the current credential store. A non-zero value indicates that the principal name is set as the default. A zero value indicates that the principal name is not set as the default. The default principal of a credential store matches <code>GSS_C_NO_NAME</code> as the <i>desired_name</i> input parameter for gss_store_cred(3GSS) .
<i>elements_stored</i>	The set of mechanism OIDs for which <i>input_cred_handle</i> elements have been stored.
<i>cred_usage_stored</i>	The stored <i>input_cred_handle</i> usage elements: initiator, acceptor, or both.
<i>minor_status</i>	Minor status code that is specific to one of the following: the mechanism identified by the <i>desired_mech_element</i> parameter, or the element of a single mechanism in the <i>input_cred_handle</i> . In all other cases, <i>minor_status</i> has an undefined value on return.

Description The `gss_store_cred()` function stores a credential in the the current GSS-API credential store for the calling process. Input credentials can be re-acquired through `gss_add_cred(3GSS)` and `gss_acquire_cred(3GSS)`.

The `gss_store_cred()` function is specifically intended to make delegated credentials available to a user's login session.

The `gss_accept_sec_context()` function can return a delegated GSS-API credential to its caller. The function does not store delegated credentials to be acquired through `gss_add_cred(3GSS)`. Delegated credentials can be used only by a receiving process unless they are made available for acquisition by calling the `gss_store_cred()` function.

The Solaris Operating System supports a single GSS-API credential store per user. The current GSS-API credential store of a process is determined by its effective UID.

In general, acceptor applications should switch the current credential store by changing the effective UID before storing a delegated credential.

Return Values The `gss_store_cred()` can return the following status codes:

<code>GSS_S_COMPLETE</code>	Successful completion.
<code>GSS_S_CREDENTIALS_EXPIRED</code>	The credentials could not be stored because they have expired.
<code>GSS_S_CALL_INACCESSIBLE_READ</code>	No input credentials were given.
<code>GSS_S_UNAVAILABLE</code>	The credential store is unavailable.
<code>GSS_S_DUPLICATE_ELEMENT</code>	The credentials could not be stored because the <i>overwrite_cred</i> input parameter was set to false (0) and the <i>input_cred</i> parameter conflicts with a credential in the current credential store.
<code>GSS_S_FAILURE</code>	The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the <i>minor_status</i> parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Unstable
MT-Level	Safe

See Also [gss_accept_sec_context\(3GSS\)](#), [gss_acquire_cred\(3GSS\)](#), [gss_add_cred\(3GSS\)](#), [gss_init_sec_context\(3GSS\)](#), [gss_inquire_cred\(3GSS\)](#), [gss_release_cred\(3GSS\)](#), [gss_release_oid_set\(3GSS\)](#), [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_str_to_oid – convert a string to an OID

Synopsis `cc [flag...] file... -lgss [library...]
#include <gssapi/gssapi.h>`

```
OM_uint32 gss_str_to_oid(OM_uint32 *minor_status,  
                        const gss_buffer_t oid_str, gss_OID *oid);
```

Description The `gss_str_to_oid()` function converts a string to a GSS-API OID structure. You can use the function to convert a simple string to an OID to . This function is a convenience function, as is its complementary function, `gss_oid_to_str(3GSS)`.

OIDs created with `gss_str_to_oid()` must be deallocated through `gss_release_oid(3GSS)`, if available. If an OID must be created, use `gss_create_empty_oid_set(3GSS)` and `gss_add_oid_set_member(3GSS)` to create it. OIDs created in this way must be released with `gss_release_oid_set(3GSS)`. However, it is strongly suggested that applications use the default GSS-API mechanism instead of creating an OID for a specific mechanism.

Parameters The parameter descriptions for `gss_str_to_oid()` are as follows:

minor_status Status code returned by underlying mechanism.
oid GSS-API OID structure to receive converted string.
oid_str String to convert.

Errors `gss_str_to_oid()` returns one of the following status codes:

GSS_S_CALL_INACCESSIBLE_READ	A required input parameter could not be read.
GSS_S_CALL_INACCESSIBLE_WRITE	A required output parameter could not be written.
GSS_S_COMPLETE	Successful completion.
GSS_S_FAILURE	The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the <i>minor_status</i> parameter details the error condition.

Attributes See `attributes(5)` for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT Level	Safe

See Also `gss_add_oid_set_member(3GSS)`, `gss_create_empty_oid_set(3GSS)`,
`gss_oid_to_str(3GSS)`, `gss_release_oid_set(3GSS)`, `attributes(5)`

Developer's Guide to Oracle Solaris Security

Warnings This function is included for compatibility only with programs using earlier versions of the GSS-API and should not be used for new programs. Other implementations of the GSS-API might not support this function, so portable programs should not rely on it. Sun might not continue to support this function.

Name gss_test_oid_set_member – interrogate an object identifier set

Synopsis

```
cc [ flag... ] file... -lgss [ library... ]
#include <gssapi/gssapi.h>

OM_uint32 gss_test_oid_set_member(OM_uint32 *minor_status,
    const gss_OID member, const gss_OID_set set,
    int *present);
```

Description The gss_test_oid_set_member() function interrogates an object identifier set to determine if a specified object identifier is a member. This function should be used with OID sets returned by gss_indicate_mechs(3GSS), gss_acquire_cred(3GSS), and gss_inquire_cred(3GSS), but it will also work with user-generated sets.

Parameters The parameter descriptions for gss_test_oid_set_member() follow:

minor_status A mechanism-specific status code

member An object identifier whose presence is to be tested

set An object identifier set.

present The value of *present* is non-zero if the specified OID is a member of the set; if not, the value of *present* is zero.

Errors The gss_test_oid_set_member() function may return the following status codes:

GSS_S_COMPLETE Successful completion

GSS_S_FAILURE The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the *minor_status* parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT-Level	Safe

See Also gss_acquire_cred(3GSS), gss_indicate_mechs(3GSS), gss_inquire_cred(3GSS), [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_unwrap – verify a message with attached cryptographic message

Synopsis cc [*flag...*] *file...* -lgss [*library...*]
#include <gssapi/gssapi.h>

```
OM_uint32 gss_unwrap(OM_uint32 *minor_status,  
    const gss_ctx_id_t context_handle,  
    const gss_buffer_t input_message_buffer,  
    gss_buffer_t output_message_buffer, int *conf_state,  
    gss_qop_t *qop_state);
```

Description The `gss_unwrap()` function converts a message previously protected by `gss_wrap(3GSS)` back to a usable form, verifying the embedded MIC. The `conf_state` parameter indicates whether the message was encrypted; the `qop_state` parameter indicates the strength of protection that was used to provide the confidentiality and integrity services.

Since some application-level protocols may wish to use tokens emitted by `gss_wrap(3GSS)` to provide secure framing, the GSS-API supports the wrapping and unwrapping of zero-length messages.

Parameters The parameter descriptions for `gss_unwrap()` follow:

<i>minor_status</i>	The status code returned by the underlying mechanism.
<i>context_handle</i>	Identifies the context on which the message arrived.
<i>input_message_buffer</i>	The message to be protected.
<i>output_message_buffer</i>	The buffer to receive the unwrapped message. Storage associated with this buffer must be freed by the application after use with a call to <code>gss_release_buffer(3GSS)</code> .
<i>conf_state</i>	If the value of <i>conf_state</i> is non-zero, then confidentiality and integrity protection were used. If the value is zero, only integrity service was used. Specify NULL if this parameter is not required.
<i>qop_state</i>	Specifies the quality of protection provided. Specify NULL if this parameter is not required.

Errors `gss_unwrap()` may return the following status codes:

GSS_S_COMPLETE	Successful completion.
GSS_S_DEFECTIVE_TOKEN	The token failed consistency checks.
GSS_S_BAD_SIG	The MIC was incorrect.
GSS_S_DUPLICATE_TOKEN	The token was valid, and contained a correct MIC for the message, but it had already been processed.
GSS_S_OLD_TOKEN	The token was valid, and contained a correct MIC for the message, but it is too old to check for duplication.

GSS_S_UNSEQ_TOKEN	The token was valid, and contained a correct MIC for the message, but has been verified out of sequence; a later token has already been received.
GSS_S_GAP_TOKEN	The token was valid, and contained a correct MIC for the message, but has been verified out of sequence; an earlier expected token has not yet been received.
GSS_S_CONTEXT_EXPIRED	The context has already expired.
GSS_S_NO_CONTEXT	The <i>context_handle</i> parameter did not identify a valid context.
GSS_S_FAILURE	The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the <i>minor_status</i> parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT-Level	Safe

See Also [gss_release_buffer\(3GSS\)](#), [gss_wrap\(3GSS\)](#), [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_verify_mic – verify integrity of a received message

Synopsis

```
cc [ flag... ] file... -lgss [ library... ]
#include <gssapi/gssapi.h>
```

```
OM_uint32 gss_verify_mic(OM_uint32 *minor_status,
    const gss_ctx_id_t context_handle, const gss_buffer_t message_buffer,
    const gss_buffer_t token_buffer, gss_qop_t *qop_state);
```

Description The `gss_verify_mic()` function verifies that a cryptographic MIC, contained in the token parameter, fits the supplied message. The `qop_state` parameter allows a message recipient to determine the strength of protection that was applied to the message.

Since some application-level protocols may wish to use tokens emitted by `gss_wrap(3GSS)` to provide secure framing, the GSS-API supports the calculation and verification of MICs over zero-length messages.

Parameters The parameter descriptions for `gss_verify_mic()` follow:

<i>minor_status</i>	The status code returned by the underlying mechanism.
<i>context_handle</i>	Identifies the context on which the message arrived.
<i>message_buffer</i>	The message to be verified.
<i>token_buffer</i>	The token associated with the message.
<i>qop_state</i>	Specifies the quality of protection gained from the MIC. Specify NULL if this parameter is not required.

Errors `gss_verify_mic()` may return the following status codes:

GSS_S_COMPLETE	Successful completion.
GSS_S_DEFECTIVE_TOKEN	The token failed consistency checks.
GSS_S_BAD_SIG	The MIC was incorrect.
GSS_S_DUPLICATE_TOKEN	The token was valid and contained a correct MIC for the message, but it had already been processed.
GSS_S_OLD_TOKEN	The token was valid and contained a correct MIC for the message, but it is too old to check for duplication.
GSS_S_UNSEQ_TOKEN	The token was valid and contained a correct MIC for the message, but it has been verified out of sequence; a later token has already been received.
GSS_S_GAP_TOKEN	The token was valid and contained a correct MIC for the message, but it has been verified out of sequence; an earlier expected token has not yet been received.
GSS_S_CONTEXT_EXPIRED	The context has already expired.

GSS_S_NO_CONTEXT	The <i>context_handle</i> parameter did not identify a valid context.
GSS_S_FAILURE	The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the <i>minor_status</i> parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT-Level	Safe

See Also [gss_wrap\(3GSS\)](#), [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name gss_wrap – attach a cryptographic message

Synopsis `cc [flag...] file... -lgss [library...]
#include <gssapi/gssapi.h>`

```
OM_uint32 gss_wrap(OM_uint32 *minor_status,  
                  const gss_ctx_id_t context_handle, int conf_req_flag,  
                  gss_qop_t qop_req, const gss_buffer_t input_message_buffer,  
                  int *conf_state, gss_buffer_t output_message_buffer);
```

Description The `gss_wrap()` function attaches a cryptographic MIC and optionally encrypts the specified *input_message*. The *output_message* contains both the MIC and the message. The *qop_req* parameter allows a choice between several cryptographic algorithms, if supported by the chosen mechanism.

Since some application-level protocols may wish to use tokens emitted by `gss_wrap()` to provide secure framing, the GSS-API supports the wrapping of zero-length messages.

Parameters The parameter descriptions for `gss_wrap()` follow:

<i>minor_status</i>	The status code returned by the underlying mechanism.
<i>context_handle</i>	Identifies the context on which the message will be sent.
<i>conf_req_flag</i>	If the value of <i>conf_req_flag</i> is non-zero, both confidentiality and integrity services are requested. If the value is zero, then only integrity service is requested.
<i>qop_req</i>	Specifies the required quality of protection. A mechanism-specific default may be requested by setting <i>qop_req</i> to <code>GSS_C_QOP_DEFAULT</code> . If an unsupported protection strength is requested, <code>gss_wrap()</code> will return a <i>major_status</i> of <code>GSS_S_BAD_QOP</code> .
<i>input_message_buffer</i>	The message to be protected.
<i>conf_state</i>	If the value of <i>conf_state</i> is non-zero, confidentiality, data origin authentication, and integrity services have been applied. If the value is zero, then integrity services have been applied. Specify NULL if this parameter is not required.
<i>output_message_buffer</i>	The buffer to receive the protected message. Storage associated with this message must be freed by the application after use with a call to <code>gss_release_buffer(3GSS)</code> .

Errors `gss_wrap()` may return the following status codes:

<code>GSS_S_COMPLETE</code>	Successful completion.
<code>GSS_S_CONTEXT_EXPIRED</code>	The context has already expired.

GSS_S_NO_CONTEXT	The <i>context_handle</i> parameter did not identify a valid context.
GSS_S_BAD_QOP	The specified QOP is not supported by the mechanism.
GSS_S_FAILURE	The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the <i>minor_status</i> parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT-Level	Safe

See Also [gss_release_buffer\(3GSS\)](#), [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name `gss_wrap_size_limit` – allow application to determine maximum message size with resulting output token of a specified maximum size

Synopsis

```
cc [ flag... ] file... -lgss [ library... ]
#include <gssapi/gssapi.h>
```

```
OM_uint32 gss_process_context_token(OM_uint32 *minor_status,
    const gss_ctx_id_t context_handle, int conf_req_flag,
    gss_qop_t qop_req, OM_uint32 req_output_size,
    OM_uint32 *max_input_size);
```

Description The `gss_wrap_size_limit()` function allows an application to determine the maximum message size that, if presented to `gss_wrap()` with the same `conf_req_flag` and `qop_req` parameters, results in an output token containing no more than `req_output_size` bytes. This call is intended for use by applications that communicate over protocols that impose a maximum message size. It enables the application to fragment messages prior to applying protection. The GSS-API detects invalid QOP values when `gss_wrap_size_limit()` is called. This routine guarantees only a maximum message size, not the availability of specific QOP values for message protection.

Successful completion of `gss_wrap_size_limit()` does not guarantee that `gss_wrap()` will be able to protect a message of length `max_input_size` bytes, since this ability might depend on the availability of system resources at the time that `gss_wrap()` is called.

Parameters The parameter descriptions for `gss_wrap_size_limit()` are as follows:

<i>minor_status</i>	A mechanism-specific status code.
<i>context_handle</i>	A handle that refers to the security over which the messages will be sent.
<i>conf_req_flag</i>	Indicates whether <code>gss_wrap()</code> will be asked to apply confidential protection in addition to integrity protection. See gss_wrap(3GSS) for more details.
<i>qop_req</i>	Indicates the level of protection that <code>gss_wrap()</code> will be asked to provide. See gss_wrap(3GSS) for more details.
<i>req_output_size</i>	The desired maximum size for tokens emitted by <code>gss_wrap()</code> .
<i>max_input_size</i>	The maximum input message size that can be presented to <code>gss_wrap()</code> to guarantee that the emitted token will be no larger than <code>req_output_size</code> bytes.

Errors `gss_wrap_size_limit()` returns one of the following status codes:

<code>GSS_S_COMPLETE</code>	Successful completion.
<code>GSS_S_NO_CONTEXT</code>	The referenced context could not be accessed.
<code>GSS_S_CONTEXT_EXPIRED</code>	The context has expired.

GSS_S_BAD_QOP	The specified QOP is not supported by the mechanism.
GSS_S_FAILURE	The underlying mechanism detected an error for which no specific GSS status code is defined. The mechanism-specific status code reported by means of the <i>minor_status</i> parameter details the error condition.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWgss (32-bit)
	SUNWgssx (64-bit)
MT Level	Safe

See Also [gss_wrap\(3GSS\)](#), [attributes\(5\)](#)

Developer's Guide to Oracle Solaris Security

Name htonl, htons, ntohl, ntohs – convert values between host and network byte order

Synopsis cc [*flag* ...] *file* ... -lxnet [*library* ...]
#include <arpa/inet.h>

```
uint32_t htonl(uint32_t hostlong);  
uint16_t htons(uint16_t hostshort);  
uint32_t ntohl(uint32_t netlong);  
uint16_t ntohs(uint16_t netshort);
```

Description These functions convert 16-bit and 32-bit quantities between network byte order and host byte order.

The uint32_t and uint16_t types are made available by inclusion of <inttypes.h>.

Usage These functions are most often used in conjunction with Internet addresses and ports as returned by [gethostent\(3XNET\)](#) and [getservent\(3XNET\)](#).

On some architectures these functions are defined as macros that expand to the value of their argument.

Return Values The htonl() and htons() functions return the argument value converted from host to network byte order.

The ntohl() and ntohs() functions return the argument value converted from network to host byte order.

Errors No errors are defined.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also [endhostent\(3XNET\)](#), [endservent\(3XNET\)](#), [attributes\(5\)](#), [standards\(5\)](#)

Name icmp6_filter – Variable allocation datatype

Synopsis

```
void ICMP6_FILTER_SETPASSALL (struct icmp6_filter *);
void ICMP6_FILTER_SETBLOCKALL (struct icmp6_filter *);
void ICMP6_FILTER_SETPASS (int, struct icmp6_filter *);
void ICMP6_FILTER_SETBLOCK (int, struct icmp6_filter *);
int ICMP6_FILTER_WILLPASS (int, const struct icmp6_filter *);
int ICMP6_FILTER_WILLBLOCK (int, const struct icmp6_filter *);
```

Description The `icmp6_filter` structure is similar to the `fd_set` datatype used with the `select()` function in the sockets API. The `icmp6_filter` structure is an opaque datatype and the application should not care how it is implemented. The application allocates a variable of this type, then passes a pointer to it. Next it passes a pointer to a variable of this type to `getsockopt()` and `setsockopt()` and operates on a variable of this type using the six macros defined below.

The `SETPASSALL` and `SETBLOCKALL` functions enable you to specify that all ICMPv6 messages are passed to the application or that all ICMPv6 messages are blocked from being passed.

The `SETPASS` and `SETBLOCKALL` functions enable you to specify that messages of a given ICMPv6 type should be passed to the application or not passed to the application (blocked).

The `WILLPASS` and `WILLBLOCK` return true or false depending whether the specified message type is passed to the application or blocked from being passed to the application by the filter pointed to by the second argument.

The pointer argument to all six `icmp6_filter` macros is a pointer to a filter that is modified by the first four macros and is examined by `ICMP6_FILTER_SETBLOCK` and `ICMP6_FILTER_WILLBLOCK`. The first argument, (an integer), to the `ICMP6_FILTER_BLOCKALL`, `ICMP6_FILTER_SETPASS`, `ICMP6_FILTER_SETBLOCK`, and `ICMP6_FILTER_WILLBLOCK` macros is an ICMPv6 message type, between 0 and 255.

The current filter is fetched and stored using `getsockopt()` and `setsockopt()` with a level of `IPPROTO_ICMPV6` and an option name of `ICMP6_FILTER`.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Safe
Interface Stability	Standard

Name if_nametoindex, if_indextoname, if_nameindex, if_freenameindex – routines to map Internet Protocol network interface names and interface indexes

Synopsis cc [*flag...*] *file...* -lsocket [*library...*]
#include <net/if.h>

```
unsigned int if_nametoindex(const char *ifname);  
  
char *if_indextoname(unsigned int ifindex, char *ifname);  
  
struct if_nameindex *if_nameindex(void)  
  
void if_freenameindex(struct if_nameindex *ptr);
```

Parameters *ifname* interface name
ifindex interface index
ptr pointer returned by if_nameindex()

Description This API defines two functions that map between an Internet Protocol network interface name and index, a third function that returns all the interface names and indexes, and a fourth function to return the dynamic memory allocated by the previous function.

Network interfaces are normally known by names such as `eri0`, `sl1`, `ppp2`, and the like. The *ifname* argument must point to a buffer of at least `IF_NAMESIZE` bytes into which the interface name corresponding to the specified index is returned. `IF_NAMESIZE` is defined in `<net/if.h>` and its value includes a terminating null byte at the end of the interface name.

if_nametoindex() The `if_nametoindex()` function returns the interface index corresponding to the interface name pointed to by the *ifname* pointer. If the specified interface name does not exist, the return value is 0, and `errno` is set to `ENXIO`. If there was a system error, such as running out of memory, the return value is 0 and `errno` is set to the proper value, for example, `ENOMEM`.

if_indextoname() The `if_indextoname()` function maps an interface index into its corresponding name. This pointer is also the return value of the function. If there is no interface corresponding to the specified index, `NULL` is returned, and `errno` is set to `ENXIO`, if there was a system error, such as running out of memory, `if_indextoname()` returns `NULL` and `errno` would be set to the proper value, for example, `ENOMEM`.

***if_nameindex()** The `if_nameindex()` function returns an array of `if_nameindex` structures, one structure per interface. The `if_nameindex` structure holds the information about a single interface and is defined when the `<net/if.h>` header is included:

```

struct if_nameindex
    unsigned int    if_index; /* 1, 2, ... */
    char           *if_name; /* null terminated name: "eri0", ... */
};

```

The end of the array of structures is indicated by a structure with an `if_index` of 0 and an `if_name` of NULL. The function returns a null pointer upon an error and sets `errno` to the appropriate value. The memory used for this array of structures along with the interface names pointed to by the `if_name` members is obtained dynamically. This memory is freed by the `if_freenameindex()` function.

`if_freenameindex()` The `if_freenameindex()` function frees the dynamic memory that was allocated by `if_nameindex()`. The argument to this function must be a pointer that was returned by `if_nameindex()`.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
MT Level	MT Safe

See Also [ifconfig\(1M\)](#), [if_nametoindex\(3XNET\)](#), [attributes\(5\)](#), [if\(7P\)](#)

Name if_nametoindex, if_indextoname, if_nameindex, if_freenameindex – functions to map Internet Protocol network interface names and interface indexes

Synopsis `cc [flag...] file... -lxnet [library...]`
`#include <net/if.h>`

```
unsigned int if_nametoindex(const char *ifname);  
char *if_indextoname(unsigned int ifindex, char *ifname);  
struct if_nameindex *if_nameindex(void)  
void if_freenameindex(struct if_nameindex *ptr);
```

Parameters These functions support the following parameters:

ifname interface name
ifindex interface index
ptr pointer returned by if_nameindex()

Description This API defines two functions that map between an Internet Protocol network interface name and index, a third function that returns all the interface names and indexes, and a fourth function to return the dynamic memory allocated by the previous function.

Network interfaces are normally known by names such as `eri0`, `sl1`, `ppp2`, and the like. The *ifname* argument must point to a buffer of at least `IF_NAMESIZE` bytes into which the interface name corresponding to the specified index is returned. `IF_NAMESIZE` is defined in `<net/if.h>` and its value includes a terminating null byte at the end of the interface name.

`if_nametoindex()` The `if_nametoindex()` function returns the interface index corresponding to the interface name pointed to by the *ifname* pointer. If the specified interface name does not exist, the return value is 0, and `errno` is set to `ENXIO`. If there was a system error, such as running out of memory, the return value is 0 and `errno` is set to the proper value, for example, `ENOMEM`.

`if_indextoname()` The `if_indextoname()` function maps an interface index into its corresponding name. This pointer is also the return value of the function. If there is no interface corresponding to the specified index, `NULL` is returned, and `errno` is set to `ENXIO`, if there was a system error, such as running out of memory, `if_indextoname()` returns `NULL` and `errno` would be set to the proper value, for example, `ENOMEM`.

`*if_nameindex()` The `if_nameindex()` function returns an array of `if_nameindex` structures, one structure per interface. The `if_nameindex` structure holds the information about a single interface and is defined when the `<net/if.h>` header is included:


```
struct if_nameindex {
    unsigned int    if_index; /* 1, 2, ... */
    char           *if_name; /* null terminated name: "eri0", ... */
};
```

The end of the array of structures is indicated by a structure with an `if_index` of 0 and an `if_name` of `NULL`. The function returns a null pointer upon an error and sets `errno` to the appropriate value. The memory used for this array of structures along with the interface names pointed to by the `if_name` members is obtained dynamically. This memory is freed by the `if_freenameindex()` function.

`if_freenameindex()` The `if_freenameindex()` function frees the dynamic memory that was allocated by `if_nameindex()`. The argument to this function must be a pointer that was returned by `if_nameindex()`.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Standard
MT-Level	MT-Safe

See Also [ifconfig\(1M\)](#), [if_nametoindex\(3SOCKET\)](#), [attributes\(5\)](#), [standards\(5\)](#), [if\(7P\)](#)

Name `inet`, `inet6`, `inet_ntop`, `inet_pton`, `inet_aton`, `inet_addr`, `inet_network`, `inet_makeaddr`, `inet_lnaof`, `inet_netof`, `inet_ntoa` – Internet address manipulation

Synopsis

```
cc [ flag... ] file... -lsocket -lnsl [ library... ]
#include <sys/types.h>
#include <sys/socket.h>
#include <netinet/in.h>
#include <arpa/inet.h>

const char *inet_ntop(int af, const void *addr, char *cp,
                      size_t size);

int inet_pton(int af, const char *cp, void *addr);

int inet_aton(const char *cp, struct in_addr *addr);

in_addr_t inet_addr(const char *cp);

in_addr_t inet_network(const char *cp);

struct in_addr inet_makeaddr(const int net, const int lna);

int inet_lnaof(const struct in_addr in);

int inet_netof(const struct in_addr in);

char *inet_ntoa(const struct in_addr in);
```

Description The `inet_ntop()` and `inet_pton()` functions can manipulate both IPv4 and IPv6 addresses. The `inet_aton()`, `inet_addr()`, `inet_network()`, `inet_makeaddr()`, `inet_lnaof()`, `inet_netof()`, and `inet_ntoa()` functions can only manipulate IPv4 addresses.

The `inet_ntop()` function converts a numeric address into a string suitable for presentation. The *af* argument specifies the family of the address which can be `AF_INET` or `AF_INET6`. The *addr* argument points to a buffer that holds an IPv4 address if the *af* argument is `AF_INET`. The *addr* argument points to a buffer that holds an IPv6 address if the *af* argument is `AF_INET6`. The address must be in network byte order. The *cp* argument points to a buffer where the function stores the resulting string. The application must specify a non-NULL *cp* argument. The *size* argument specifies the size of this buffer. For IPv6 addresses, the buffer must be at least 46-octets. For IPv4 addresses, the buffer must be at least 16-octets. To allow applications to easily declare buffers of the proper size to store IPv4 and IPv6 addresses in string form, the following two constants are defined in `<netinet/in.h>`:

```
#define INET_ADDRSTRLEN    16
#define INET6_ADDRSTRLEN  46
```

The `inet_pton()` function converts the standard text presentation form of a function to the numeric binary form. The *af* argument specifies the family of the address. Currently, the `AF_INET` and `AF_INET6` address families are supported. The *cp* argument points to the string being passed in. The *addr* argument points to a buffer where the function stores the numeric address. The calling application must ensure that the buffer referred to by *addr* is large enough to hold the numeric address, at least 4 bytes for `AF_INET` or 16 bytes for `AF_INET6`.

The `inet_aton()`, `inet_addr()`, and `inet_network()` functions interpret character strings that represent numbers expressed in the IPv4 standard '.' notation, returning numbers suitable for use as IPv4 addresses and IPv4 network numbers, respectively. The `inet_makeaddr()` function uses an IPv4 network number and a local network address to construct an IPv4 address. The `inet_netof()` and `inet_lnaof()` functions break apart IPv4 host addresses, then return the network number and local network address, respectively.

The `inet_ntoa()` function returns a pointer to a string in the base 256 notation d.d.d.d. See the following section on IPv4 addresses.

Internet addresses are returned in network order, bytes ordered from left to right. Network numbers and local address parts are returned as machine format integer values.

IPv6 Addresses There are three conventional forms for representing IPv6 addresses as strings:

1. The preferred form is x:x:x:x:x:x:x:x, where the 'x's are the hexadecimal values of the eight 16-bit pieces of the address. For example:

```
1080:0:0:8:800:200C:417A
```

It is not necessary to write the leading zeros in an individual field. There must be at least one numeral in every field, except when the special syntax described in the following is used.

2. It is common for addresses to contain long strings of zero bits in some methods used to allocate certain IPv6 address styles. A special syntax is available to compress the zeros. The use of "::" indicates multiple groups of 16 bits of zeros. The "::" may only appear once in an address. The "::" can also be used to compress the leading and trailing zeros in an address. For example:

```
1080::8:800:200C:417A
```

3. The alternative form x:x:x:x:x:x:d.d.d.d is sometimes more convenient when dealing with a mixed environment of IPv4 and IPv6 nodes. The x's in this form represent the hexadecimal values of the six high-order 16-bit pieces of the address. The d's represent the decimal values of the four low-order 8-bit pieces of the standard IPv4 address. For example:

```
::FFFF:129.144.52.38
::129.144.52.38
```

The ::FFFF:d.d.d.d and :d.d.d.d pieces are the general forms of an IPv4-mapped IPv6 address and an IPv4-compatible IPv6 address.

The IPv4 portion must be in the d.d.d.d form. The following forms are invalid:

```
::FFFF:d.d.d
::FFFF:d.d
::d.d.d
::d.d
```

The `::FFFF:d` form is a valid but unconventional representation of the IPv4-compatible IPv6 address `::255.255.0.d`.

The `::d` form corresponds to the general IPv6 address `0:0:0:0:0:0:0:d`.

IPv4 Addresses Values specified using `'.'` notation take one of the following forms:

`d.d.d.d`
`d.d.d`
`d.d`
`d`

When four parts are specified, each part is interpreted as a byte of data and assigned from left to right to the four bytes of an IPv4 address.

When a three-part address is specified, the last part is interpreted as a 16-bit quantity and placed in the right most two bytes of the network address. The three part address format is convenient for specifying Class B network addresses such as `128.net.host`.

When a two-part address is supplied, the last part is interpreted as a 24-bit quantity and placed in the right most three bytes of the network address. The two part address format is convenient for specifying Class A network addresses such as `net.host`.

When only one part is given, the value is stored directly in the network address without any byte rearrangement.

With the exception of `inet_pton()`, numbers supplied as *parts* in `'.'` notation may be decimal, octal, or hexadecimal, as specified in C language. For example, a leading `0x` or `0X` implies hexadecimal. A leading `0` implies octal. Otherwise, the number is interpreted as decimal.

For IPv4 addresses, `inet_pton()` accepts only a string in standard IPv4 dot notation:

`d.d.d.d`

Each number has one to three digits with a decimal value between 0 and 255.

The `inet_addr()` function has been obsoleted by `inet_aton()`.

Return Values The `inet_aton()` function returns nonzero if the address is valid, `0` if the address is invalid.

The `inet_ntop()` function returns a pointer to the buffer that contains a string if the conversion succeeds. Otherwise, `NULL` is returned. Upon failure, `errno` is set to `EAFNOSUPPORT` if the *af* argument is invalid or `ENOSPC` if the size of the result buffer is inadequate.

The `inet_pton()` function returns 1 if the conversion succeeds, `0` if the input is not a valid IPv4 dotted-decimal string or a valid IPv6 address string. The function returns `-1` with `errno` set to `EAFNOSUPPORT` if the *af* argument is unknown.

The value `INADDR_NONE`, which is equivalent to `(in_addr_t)(-1)`, is returned by `inet_addr()` and `inet_network()` for malformed requests.

The functions `inet_netof()` and `inet_lnaof()` break apart IPv4 host addresses, returning the network number and local network address part, respectively.

The function `inet_ntoa()` returns a pointer to a string in the base 256 notation `d.d.d.d`, described in the section on IPv4 addresses.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	See below.
MT-Level	Safe

The `inet_ntop()`, `inet_pton()`, `inet_aton()`, `inet_addr()`, and `inet_network()` functions are Committed. The `inet_lnaof()`, `inet_makeaddr()`, `inet_netof()`, and `inet_network()` functions are Committed (Obsolete).

See Also [gethostbyname\(3NSL\)](#), [getipnodebyname\(3SOCKET\)](#), [getnetbyname\(3SOCKET\)](#), [inet.h\(3HEAD\)](#), [hosts\(4\)](#), [networks\(4\)](#), [attributes\(5\)](#)

Notes The return value from `inet_ntoa()` points to a buffer which is overwritten on each call. This buffer is implemented as thread-specific data in multithreaded applications.

IPv4-mapped addresses are not recommended.

Bugs The problem of host byte ordering versus network byte ordering is confusing. A simple way to specify Class C network addresses in a manner similar to that for Class B and Class A is needed.

Name inet6_opt, inet6_opt_init, inet6_opt_append, inet6_opt_finish, inet6_opt_set_val, inet6_opt_next, inet6_opt_find, inet6_opt_get_val – Option manipulation mechanism

Synopsis cc [*flag* ...] *file* ... -lsocket [*library*...]
#include <netinet/in.h>

```
int inet6_opt_init(void *extbuf, socklen_t extlen);

int inet6_opt_append(void *extbuf, socklen_t extlen,
    int offset, uint8_t type, socklen_t len, uint_t align,
    void **databufp);

int inet6_opt_finish(void *extbuf, socklen_t extlen,
    int offset);

int inet6_opt_set_val(void *databuf, int offset,
    void *val, socklen_t vallen);

int inet6_opt_next(void *extbuf, socklen_t extlen,
    int offset, uint8_t *typep, socklen_t *lenp,
    void **databufp);

int inet6_opt_find(void *extbuf, socklen_t extlen, int offset,
    uint8_t type, socklen_t *lenp, void **databufp);

int inet6_opt_get_val(void *databuf, int offset,
    void *val, socklen_t *vallen);
```

Description The inet6_opt functions enable users to manipulate options without having to know the structure of the option header.

The inet6_opt_init() function returns the number of bytes needed for the empty extension header, that is, without any options. If *extbuf* is not NULL, it also initializes the extension header to the correct length field. If the *extlen* value is not a positive non-zero multiple of 8, the function fails and returns -1.

The inet6_opt_append() function returns the updated total length while adding an option with length *len* and alignment *align*. If *extbuf* is not NULL, then, in addition to returning the length, the function inserts any needed Pad option, initializes the option setting the type and length fields, and returns a pointer to the location for the option content in *databufp*. If the option does not fit in the extension header buffer, the function returns -1. The *type* is the 8-bit option type. The *len* is the length of the option data, excluding the option type and option length fields. Once inet6_opt_append() is called, the application can use the *databuf* directly, or inet6_opt_set_val() can be used to specify the content of the option. The option type must have a value from 2 to 255, inclusive. The values 0 and 1 are reserved for the Pad1 and PadN options, respectively. The option data length must have a value between 0 and 255, inclusive, and it is the length of the option data that follows. The align parameter must have a value of 1, 2, 4, or 8. The align value cannot exceed the value of *len*.

The inet6_opt_finish() function returns the updated total length that takes into account the final padding of the extension header to make it a multiple of 8 bytes. If *extbuf* is not NULL, the

function also initializes the option by inserting a Pad1 or PadN option of the proper length. If the necessary pad does not fit in the extension header buffer, the function returns `-1`.

The `inet6_opt_set_val()` function inserts data items of various sizes in the data portion of the option. The *val* parameter should point to the data to be inserted. The *offset* specifies the data portion of the option in which the value should be inserted. The first byte after the option type and length is accessed by specifying an *offset* of zero.

The `inet6_opt_next()` function parses the received option extension headers which return the next option. The *extbuf* and *extlen* parameters specify the extension header. The *offset* should be zero for the first option or the length returned by a previous call to either `inet6_opt_next()` or `inet6_opt_find()`. The *offset* specifies where to continue scanning the extension buffer. The subsequent option is returned by updating *typep*, *lenp*, and *databufp*. The *typep* argument stores the option type. The *lenp* argument stores the length of the option data, excluding the option type and option length fields. The *databufp* argument points to the data field of the option.

The `inet6_opt_find()` function is similar to the `inet6_opt_next()` function. Unlike `inet6_opt_next()`, the `inet6_opt_find()` function enables the caller to specify the option type to be searched for, rather than returning the next option in the extension header.

The `inet6_opt_get_val()` function extracts data items of various sizes in the portion of the option. The *val* argument should point to the destination for the extracted data. The *offset* specifies at which point in the option's data portion the value should be extracted. The first byte following the option type and length is accessed by specifying an *offset* of zero.

Return Values The `inet6_opt_init()` function returns the number of bytes needed for the empty extension header. If the *extlen* value is not a positive non-zero multiple of 8, the function fails and returns `-1`.

The `inet6_opt_append()` function returns the updated total length.

The `inet6_opt_finish()` function returns the updated total length.

The `inet6_opt_set_val()` function returns the *offset* for the subsequent field.

The `inet6_opt_next()` function returns the updated “previous” length computed by advancing past the option that was returned. When there are no additional options or if the option extension header is malformed, the return value is `-1`.

The `inet6_opt_find()` function returns the updated “previous” total length. If an option of the specified type is not located, the return value is `-1`. If the option extension header is malformed, the return value is `-1`.

The `inet6_opt_get_val()` function returns the *offset* for the next field (that is, *offset + vallen*) which can be used when extracting option content with multiple fields.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	Safe

See Also RFC 3542 – *Advanced Sockets Application Programming Interface (API) for IPv6*, The Internet Society. May 2003

Name inet6_rth, inet6_rth_space, inet6_rth_init, inet6_rth_add, inet6_rth_reverse, inet6_rth_segments, inet6_rth_getaddr – Routing header manipulation

Synopsis cc [*flag* ...] *file* ... -lsocket [*library*]
#include <netinet/in.h>

```
socklen_t inet6_rth_space(int type, int segments);

void *inet6_rth_init(void *bp, socklen_t bp_len, int type, int segments);

int inet6_rth_add(void *bp, const struct in6_addr *addr);

int inet6_rth_reverse(const void *in, void *out);

int inet6_rth_segments(const void *bp);

struct in6_addr *inet6_rth_getaddr(const void *bp, int index);
```

Description The inet6_rth functions enable users to manipulate routing headers without having knowledge of their structure.

The inet6_rth_init() function initializes the buffer pointed to by *bp* to contain a routing header of the specified type and sets *ip6r_len* based on the *segments* parameter. The *bp_len* argument is used only to verify that the buffer is large enough. The *ip6r_segleft* field is set to zero and inet6_rth_add() increments it. The caller allocates the buffer and its size can be determined by calling inet6_rth_space().

The inet6_rth_add() function adds the IPv6 address pointed to by *addr* to the end of the routing header that is being constructed.

The inet6_rth_reverse() function takes a routing header extension header pointed to by the first argument and writes a new routing header that sends datagrams along the reverse of the route. The function reverses the order of the addresses and sets the *segleft* member in the new routing header to the number of segments. Both arguments can point to the same buffer (that is, the reversal can occur in place).

The inet6_rth_segments() function returns the number of segments (addresses) contained in the routing header described by *bp*.

The inet6_rth_getaddr() function returns a pointer to the IPv6 address specified by *index*, which must have a value between 0 and one less than the value returned by inet6_rth_segments() in the routing header described by *bp*. Applications should first call inet6_rth_segments() to obtain the number of segments in the routing header.

The inet6_rth_space() function returns the size, but the function does not allocate the space required for the ancillary data routing header.

Routing Headers To receive a routing header, the application must enable the `IPV6_RECVRTHDR` socket option:

```
int on = 1;
setsockopt (fd, IPPROTO_IPV6, IPV6_RECVRTHDR, &on, sizeof(on));
```

Each received routing header is returned as one ancillary data object described by a `cmsghdr` structure with `msg_type` set to `IPV6_RTHDR`.

To send a routing header, the application specifies it either as ancillary data in a call to `sendmsg()` or by using `setsockopt()`. For the sending side, this API assumes the number of occurrences of the routing header as described in *RFC-2460*. Applications can specify no more than one outgoing routing header.

The application can remove any sticky routing header by calling `setsockopt()` for `IPV6_RTHDR` with a zero option length.

When using ancillary data, a routing header is passed between the application and the kernel as follows: The `msg_level` member has a value of `IPPROTO_IPV6` and the `msg_type` member has a value of `IPV6_RTHDR`. The contents of the `msg_data` member is implementation-dependent and should not be accessed directly by the application, but should be accessed using the `inet6_rth` functions.

The following constant is defined as a result of including the `<netinet/in.h>`:

```
#define IPV6_RTHDR_TYPE_0    0 /* IPv6 Routing header type 0 */
```

ROUTING HEADER OPTION Source routing in IPv6 is accomplished by specifying a routing header as an extension header. There are a number of different routing headers, but IPv6 currently defines only the Type 0 header. See *RFC-2460*. The Type 0 header supports up to 127 intermediate nodes, limited by the length field in the extension header. With this maximum number of intermediate nodes, a source, and a destination, there are 128 hops.

Return Values The `inet6_rth_init()` function returns a pointer to the buffer (*bp*) upon success.

For the `inet6_rth_add()` function, the `segl` member of the routing header is updated to account for the new address in the routing header. The function returns 0 upon success and -1 upon failure.

The `inet6_rth_reverse()` function returns 0 upon success or -1 upon an error.

The `inet6_rth_segments()` function returns 0 or greater upon success and -1 upon an error.

The `inet6_rth_getaddr()` function returns NULL upon an error.

The `inet6_rth_space()` function returns the size of the buffer needed for the routing header.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	Safe

See Also RFC 3542– *Advanced Sockets Application Programming Interface (API) for IPv6*, The Internet Society. May 2003

Name `inet_addr`, `inet_network`, `inet_makeaddr`, `inet_lnaof`, `inet_netof`, `inet_ntoa` – Internet address manipulation

Synopsis `cc [flag ...] file ... -lXnet [library ...]`
`#include <arpa/inet.h>`

```
in_addr_t inet_addr(const char *cp);
in_addr_t inet_lnaof(struct in_addr in);
struct in_addr inet_makeaddr(in_addr_t net, in_addr_t lna);
in_addr_t inet_netof(struct in_addr in);
in_addr_t inet_network(const char *cp);
char *inet_ntoa(struct in_addr in);
```

Description The `inet_addr()` function converts the string pointed to by *cp*, in the Internet standard dot notation, to an integer value suitable for use as an Internet address.

The `inet_lnaof()` function takes an Internet host address specified by *in* and extracts the local network address part, in host byte order.

The `inet_makeaddr()` function takes the Internet network number specified by *net* and the local network address specified by *lna*, both in host byte order, and constructs an Internet address from them.

The `inet_netof()` function takes an Internet host address specified by *in* and extracts the network number part, in host byte order.

The `inet_network()` function converts the string pointed to by *cp*, in the Internet standard dot notation, to an integer value suitable for use as an Internet network number.

The `inet_ntoa()` function converts the Internet host address specified by *in* to a string in the Internet standard dot notation.

All Internet addresses are returned in network order (bytes ordered from left to right).

Values specified using dot notation take one of the following forms:

- `a.b.c.d` When four parts are specified, each is interpreted as a byte of data and assigned, from left to right, to the four bytes of an Internet address.
- `a.b.c` When a three-part address is specified, the last part is interpreted as a 16-bit quantity and placed in the rightmost two bytes of the network address. This makes the three-part address format convenient for specifying Class B network addresses as `128.net.host`.

- a . b When a two-part address is supplied, the last part is interpreted as a 24-bit quantity and placed in the rightmost three bytes of the network address. This makes the two-part address format convenient for specifying Class A network addresses as *net . host*.
- a When only one part is given, the value is stored directly in the network address without any byte rearrangement.

All numbers supplied as parts in dot notation may be decimal, octal, or hexadecimal, that is, a leading 0x or 0X implies hexadecimal, as specified in the *ISO C* standard; otherwise, a leading 0 implies octal; otherwise, the number is interpreted as decimal.

Usage The return value of `inet_ntoa()` may point to static data that may be overwritten by subsequent calls to `inet_ntoa()`.

Return Values Upon successful completion, `inet_addr()` returns the Internet address. Otherwise, it returns `(in_addr_t)(-1)`.

Upon successful completion, `inet_network()` returns the converted Internet network number. Otherwise, it returns `(in_addr_t)(-1)`.

The `inet_makeaddr()` function returns the constructed Internet address.

The `inet_lnaof()` function returns the local network address part.

The `inet_netof()` function returns the network number.

The `inet_ntoa()` function returns a pointer to the network address in Internet-standard dot notation.

Errors No errors are defined.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also [endhostent\(3XNET\)](#), [endnetent\(3XNET\)](#), [attributes\(5\)](#), [standards\(5\)](#)

Name `inet_ntop`, `inet_pton` – convert IPv4 and IPv6 addresses between binary and text form

Synopsis `cc [flag ...] file ... -lxnet [library ...]`
`#include <arpa/inet.h>`

```
const char *inet_ntop(int af, const void *restrict src,  
                      char *restrict dst, socklen_t size);  
  
int inet_pton(int af, const char *restrict src, dst);
```

Description The `inet_ntop()` function converts a numeric address into a text string suitable for presentation. The *af* argument specifies the family of the address. This can be `AF_INET` or `AF_INET6`. The *src* argument points to a buffer holding an IPv4 address if the *af* argument is `AF_INET`, or an IPv6 address if the *af* argument is `AF_INET6`. The *dst* argument points to a buffer where the function stores the resulting text string; it cannot be `NULL`. The *size* argument specifies the size of this buffer, which must be large enough to hold the text string (`INET_ADDRSTRLEN` characters for IPv4, `INET6_ADDRSTRLEN` characters for IPv6).

The `inet_pton()` function converts an address in its standard text presentation form into its numeric binary form. The *af* argument specifies the family of the address. The `AF_INET` and `AF_INET6` address families are supported. The *src* argument points to the string being passed in. The *dst* argument points to a buffer into which the function stores the numeric address; this must be large enough to hold the numeric address (32 bits for `AF_INET`, 128 bits for `AF_INET6`).

If the *af* argument of `inet_pton()` is `AF_INET`, the *src* string is in the standard IPv4 dotted-decimal form:

`ddd.ddd.ddd.ddd`

where “ddd” is a one to three digit decimal number between 0 and 255 (see [inet_addr\(3XNET\)](#)). The `inet_pton()` function does not accept other formats (such as the octal numbers, hexadecimal numbers, and fewer than four numbers that `inet_addr()` accepts).

If the *af* argument of `inet_pton()` is `AF_INET6`, the *src* string is in one of the following standard IPv6 text forms:

1. The preferred form is “x:x:x:x:x:x:x:x”, where the 'x's are the hexadecimal values of the eight 16-bit pieces of the address. Leading zeros in individual fields can be omitted, but there must be at least one numeral in every field.
2. A string of contiguous zero fields in the preferred form can be shown as “:.”. The “:.” can only appear once in an address. Unspecified addresses (“0:0:0:0:0:0:0:0”) can be represented simply as “:.”.
3. A third form that is sometimes more convenient when dealing with a mixed environment of IPv4 and IPv6 nodes is “x:x:x:x:x:x:d.d.d.d”, where the 'x's are the hexadecimal values of the six high-order 16-bit pieces of the address, and the 'd's are the decimal values of the four low-order 8-bit pieces of the address (standard IPv4 representation).

A more extensive description of the standard representations of IPv6 addresses can be found in RFC 2373.

Return Values The `inet_ntop()` function returns a pointer to the buffer containing the text string if the conversion succeeds. Otherwise it returns `NULL` and sets `errno` to indicate the error.

The `inet_pton()` function returns 1 if the conversion succeeds, with the address pointed to by *dst* in network byte order. It returns 0 if the input is not a valid IPv4 dotted-decimal string or a valid IPv6 address string. It returns `-1` and sets `errno` to `EAFNOSUPPORT` if the *af* argument is unknown.

Errors The `inet_ntop()` and `inet_pton()` functions will fail if:

`EAFNOSUPPORT` The *af* argument is invalid.

`ENOSPC` The size of the `inet_ntop()` result buffer is inadequate.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also [inet_addr\(3XNET\)](#), [attributes\(5\)](#)

Name ldap – Lightweight Directory Access Protocol package

Synopsis `cc[flag...] file... -lldap[library...]`
`#include <lber.h>`
`#include <ldap.h>`

Description The Lightweight Directory Access Protocol (“LDAP”) package (SUNWlldap) includes various command line LDAP clients and a LDAP client library to provide programmatic access to the LDAP protocol. This man page gives an overview of the LDAP client library functions.

An application might use the LDAP client library functions as follows. The application would initialize a LDAP session with a LDAP server by calling `ldap_init(3LDAP)`. Next, it authenticates to the LDAP server by calling `ldap_sasl_bind(3LDAP)` and friends. It may perform some LDAP operations and obtain results by calling `ldap_search(3LDAP)` and friends. To parse the results returned from these functions, it calls `ldap_parse_result(3LDAP)`, `ldap_next_entry(3LDAP)`, and `ldap_first_entry(3LDAP)` and others. It closes the LDAP session by calling `ldap_unbind(3LDAP)`.

LDAP operations can be either synchronous or asynchronous. By convention, the names of the synchronous functions end with “_s.” For example, a synchronous binding to the LDAP server can be performed by calling `ldap_sasl_bind_s(3LDAP)`. Complete an asynchronous binding with `ldap_sasl_bind(3LDAP)`. All synchronous functions return the actual outcome of the operation, either LDAP_SUCCESS or an error code. Asynchronous routines provide an invocation identifier which can be used to obtain the result of a specific operation by passing it to the `ldap_result(3LDAP)` function.

Initializing a LDAP session Initializing a LDAP session involves calling the `ldap_init(3LDAP)` function. However, the call does not actually open a connection to the LDAP server. It merely initializes a LDAP structure that represents the session. The connection is opened when the first operation is attempted. Unlike `ldap_init()`, `ldap_open(3LDAP)` attempts to open a connection with the LDAP server. However, the use of `ldap_open()` is deprecated.

Authenticating to a LDAP server The `ldap_sasl_bind(3LDAP)` and `ldap_sasl_bind_s(3LDAP)` functions provide general and extensible authentication for an LDAP client to a LDAP server. Both use the Simple Authentication Security Layer (SASL). Simplified routines `ldap_simple_bind(3LDAP)` and `ldap_simple_bind_s(3LDAP)` use cleartext passwords to bind to the LDAP server. Use of `ldap_bind(3LDAP)` and `ldap_bind_s(3LDAP)`(3LDAP) is deprecated.

Searching a LDAP directory Search for an entry in a LDAP directory by calling the `ldap_search_ext(3LDAP)` or the `ldap_search_ext_s(3LDAP)` functions. These functions support LDAPv3 server controls, client controls and variable size and time limits as arguments for each search operation. `ldap_search(3LDAP)` and `ldap_search_s(3LDAP)` are identical functions but do not support the controls and limits as arguments to the call.

-
- Adding or Deleting an entry** Use `ldap_add_ext(3LDAP)` and `ldap_delete_ext(3LDAP)` to add or delete entries in a LDAP directory server. The synchronous counterparts to these functions are `ldap_add_ext_s(3LDAP)` and `ldap_delete_ext_s(3LDAP)`. The `ldap_add(3LDAP)`, `ldap_add_s(3LDAP)`, `ldap_delete(3LDAP)`, and `ldap_delete_s(3LDAP)` provide identical functionality to add and to delete entries, but they do not support LDAP v3 server and client controls.
- Modifying Entries** Use `ldap_modify_ext(3LDAP)` and `ldap_modify_ext_s(3LDAP)` to modify an existing entry in a LDAP server that supports for LDAPv3 server and client controls. Similarly, use `ldap_rename(3LDAP)` and `ldap_rename_s(3LDAP)` to change the name of an LDAP entry. The `ldap_modrdn(3LDAP)`, `ldap_modrdn_s(3LDAP)`, `ldap_modrdn2(3LDAP)` and `ldap_modrdn2_s(3LDAP)` interfaces are deprecated.
- Obtaining Results** Use `ldap_result(3LDAP)` to obtain the results of a previous asynchronous operation. For all LDAP operations other than search, only one message is returned. For the search operation, a list of result messages can be returned.
- Handling Errors and Parsing Results** Use the `ldap_parse_result(3LDAP)`, `ldap_parse_sasl_bind_result(3LDAP)`, and the `ldap_parse_extended_result(3LDAP)` functions to extract required information from results and to handle the returned errors. To convert a numeric error code into a null-terminated character string message describing the error, use `ldap_err2string(3LDAP)`. The `ldap_result2error(3LDAP)` and `ldap_perror(3LDAP)` functions are deprecated. To step through the list of messages in a result returned by `ldap_result()`, use `ldap_first_message(3LDAP)` and `ldap_next_message(3LDAP)`. `ldap_count_messages(3LDAP)` returns the number of messages contained in the list.
- You can use `ldap_first_entry(3LDAP)` and `ldap_next_entry(3LDAP)` to step through and obtain a list of entries from a list of messages returned by a search result. `ldap_count_entries(3LDAP)` returns the number of entries contained in a list of messages. Call either `ldap_first_attribute(3LDAP)` and `ldap_next_attribute(3LDAP)` to step through a list of attributes associated with an entry. Retrieve the values of a given attribute by calling `ldap_get_values(3LDAP)` and `ldap_get_values_len(3LDAP)`. Count the number of values returned by using `ldap_count_values(3LDAP)` and `ldap_count_values_len(3LDAP)`.
- Use the `ldap_get_lang_values(3LDAP)` and `ldap_get_lang_values_len(3LDAP)` to return an attribute's values that matches a specified language subtype. The `ldap_get_lang_values()` function returns an array of an attribute's string values that matches a specified language subtype. To retrieve the binary data from an attribute, call the `ldap_get_lang_values_len()` function instead.
- Uniform Resource Locators (URLS)** You can use the `ldap_url(3LDAP)` functions to test a URL to verify that it is an LDAP URL, to parse LDAP URLs into their component pieces, to initiate searches directly using an LDAP URL, and to retrieve the URL associated with a DNS domain name or a distinguished name.

- User Friendly Naming** The `ldap_ufn(3LDAP)` functions implement a user friendly naming scheme by means of LDAP. This scheme allows you to look up entries using fuzzy, untyped names like “mark smith, umich, us”.
- Caching** The `ldap_memcache(3LDAP)` functions provide an in-memory client side cache to store search requests. Caching improves performance and reduces network bandwidth when a client makes repeated requests.
- Utility Functions** There are also various utility functions. You can use the `ldap_sort(3LDAP)` functions are used to sort the entries and values returned by means of the ldap search functions. The `ldap_friendly(3LDAP)` functions will map from short two letter country codes or other strings to longer “friendlier” names. Use the `ldap_charset(3LDAP)` functions to translate to and from the T.61 character set that is used for many character strings in the LDAP protocol.
- Generating Filters** Make calls to `ldap_init_getfilter(3LDAP)` and `ldap_search(3LDAP)` to generate filters to be used in `ldap_search(3LDAP)` and `ldap_search_s(3LDAP)`. `ldap_init_getfilter()` reads `ldapfilter.conf(4)`, the LDAP configuration file, while `ldap_init_getfilter_buf()` reads the configuration information from *buf* of length *buflen*. `ldap_getfilter_free(3LDAP)` frees memory that has been allocated by means of `ldap_init_getfilter()`.
- BER Library** The LDAP package includes a set of lightweight Basic Encoding Rules (“BER”) functions. The LDAP library functions use the BER functions to encode and decode LDAP protocol elements through the slightly simplified BER defined by LDAP. They are not normally used directly by an LDAP application program will not normally use the BER functions directly. Instead, these functions provide a `printf()` and `scanf()`-like interface, as well as lower-level access.

List Of Interfaces	<code>ldap_open(3LDAP)</code>	Deprecated. Use <code>ldap_init(3LDAP)</code> .
	<code>ldap_init(3LDAP)</code>	Initialize a session with a LDAP server without opening a connection to a server.
	<code>ldap_result(3LDAP)</code>	Obtain the result from a previous asynchronous operation.
	<code>ldap_abandon(3LDAP)</code>	Abandon or abort an asynchronous operation.
	<code>ldap_add(3LDAP)</code>	Asynchronously add an entry
	<code>ldap_add_s(3LDAP)</code>	Synchronously add an entry.
	<code>ldap_add_ext(3LDAP)</code>	Asynchronously add an entry with support for LDAPv3 controls.
	<code>ldap_add_ext_s(3LDAP)</code>	Synchronously add an entry with support for LDAPv3 controls.
	<code>ldap_bind(3LDAP)</code>	Deprecated. Use <code>ldap_sasl_bind(3LDAP)</code> or <code>ldap_simple_bind(3LDAP)</code> .

<code>ldap_sasl_bind(3LDAP)</code>	Asynchronously bind to the directory using SASL authentication
<code>ldap_sasl_bind_s(3LDAP)</code>	Synchronously bind to the directory using SASL authentication
<code>ldap_bind_s(3LDAP)</code>	Deprecated. Use <code>ldap_sasl_bind_s(3LDAP)</code> or <code>ldap_simple_bind_s(3LDAP)</code> .
<code>ldap_simple_bind(3LDAP)</code>	Asynchronously bind to the directory using simple authentication.
<code>ldap_simple_bind_s(3LDAP)</code>	Synchronously bind to the directory using simple authentication.
<code>ldap_unbind(3LDAP)</code>	Synchronously unbind from the LDAP server, close the connection, and dispose the session handle.
<code>ldap_unbind_ext(3LDAP)</code>	Synchronously unbind from the LDAP server and close the connection. <code>ldap_unbind_ext()</code> allows you to explicitly include both server and client controls in the unbind request.
<code>ldap_set_rebind_proc(3LDAP)</code>	Set callback function for obtaining credentials from a referral.
<code>ldap_memcache_init(3LDAP)</code>	Create the in-memory client side cache.
<code>ldap_memcache_set(3LDAP)</code>	Associate an in-memory cache that has been already created by calling the <code>ldap_memcache_init(3LDAP)</code> function with an LDAP connection handle.
<code>ldap_memcache_get(3LDAP)</code>	Get the cache associated with the specified LDAP structure.
<code>ldap_memcache_flush(3LDAP)</code>	Flushes search requests from the cache.
<code>ldap_memcache_destroy(3LDAP)</code>	Frees the specified LDAPMemCache structure pointed to by cache from memory.
<code>ldap_memcache_update(3LDAP)</code>	Checks the cache for items that have expired and removes them.
<code>ldap_compare(3LDAP)</code>	Asynchronous compare with a directory entry.
<code>ldap_compare_s(3LDAP)</code>	Synchronous compare with a directory entry.
<code>ldap_compare_ext(3LDAP)</code>	Asynchronous compare with a directory entry, with support for LDAPv3 controls.

<code>ldap_compare_ext_s(3LDAP)</code>	Synchronous compare with a directory entry, with support for LDAPv3 controls.
<code>ldap_control_free(3LDAP)</code>	Dispose of an LDAP control.
<code>ldap_controls_free(3LDAP)</code>	Dispose of an array of LDAP controls.
<code>ldap_delete(3LDAP)</code>	Asynchronously delete an entry.
<code>ldap_delete_s(3LDAP)</code>	Synchronously delete an entry.
<code>ldap_delete_ext(3LDAP)</code>	Asynchronously delete an entry, with support for LDAPv3 controls.
<code>ldap_delete_ext_s(3LDAP)</code>	Synchronously delete an entry, with support for LDAPv3 controls.
<code>ldap_init_templates(3LDAP)</code>	Read a sequence of templates from a LDAP template configuration file.
<code>ldap_init_templates_buf(3LDAP)</code>	Read a sequence of templates from a buffer.
<code>ldap_free_templates(3LDAP)</code>	Dispose of the templates allocated.
<code>ldap_first_reference(3LDAP)</code>	Step through a list of continuation references from a search result.
<code>ldap_next_reference(3LDAP)</code>	Step through a list of continuation references from a search result.
<code>ldap_count_references(3LDAP)</code>	Count the number of messages in a search result.
<code>ldap_first_message(3LDAP)</code>	Step through a list of messages in a search result.
<code>ldap_count_messages(3LDAP)</code>	Count the messages in a list of messages in a search result.
<code>ldap_next_message(3LDAP)</code>	Step through a list of messages in a search result.
<code>ldap_msgtype(3LDAP)</code>	Return the type of LDAP message.
<code>ldap_first_disptmpl(3LDAP)</code>	Get first display template in a list.
<code>ldap_next_disptmpl(3LDAP)</code>	Get next display template in a list.
<code>ldap_oc2template(3LDAP)</code>	Return template appropriate for the objectclass.
<code>ldap_name2template(3LDAP)</code>	Return named template
<code>ldap_tmplattrs(3LDAP)</code>	Return attributes needed by the template.

<code>ldap_first_tmplrow(3LDAP)</code>	Return first row of displayable items in a template.
<code>ldap_next_tmplrow(3LDAP)</code>	Return next row of displayable items in a template.
<code>ldap_first_tmplcol(3LDAP)</code>	Return first column of displayable items in a template.
<code>ldap_next_tmplcol(3LDAP)</code>	Return next column of displayable items in a template.
<code>ldap_entry2text(3LDAP)</code>	Display an entry as text by using a display template.
<code>ldap_entry2text_search(3LDAP)</code>	Search for and display an entry as text by using a display template.
<code>ldap_vals2text(3LDAP)</code>	Display values as text.
<code>ldap_entry2html(3LDAP)</code>	Display an entry as HTML (HyperText Markup Language) by using a display template.
<code>ldap_entry2html_search(3LDAP)</code>	Search for and display an entry as HTML by using a display template.
<code>ldap_vals2html(3LDAP)</code>	Display values as HTML.
<code>ldap_perror(3LDAP)</code>	Deprecated. Use ldap_parse_result(3LDAP) .
<code>ldap_result2error(3LDAP)</code>	Deprecated. Use ldap_parse_result(3LDAP) .
<code>ldap_err2string(3LDAP)</code>	Convert LDAP error indication to a string.
<code>ldap_first_attribute(3LDAP)</code>	Return first attribute name in an entry.
<code>ldap_next_attribute(3LDAP)</code>	Return next attribute name in an entry.
<code>ldap_first_entry(3LDAP)</code>	Return first entry in a chain of search results.
<code>ldap_next_entry(3LDAP)</code>	Return next entry in a chain of search results.
<code>ldap_count_entries(3LDAP)</code>	Return number of entries in a search result.
<code>ldap_friendly_name(3LDAP)</code>	Map from unfriendly to friendly names.
<code>ldap_free_friendlymap(3LDAP)</code>	Free resources used by ldap_friendly(3LDAP) .
<code>ldap_get_dn(3LDAP)</code>	Extract the DN from an entry.
<code>ldap_explode_dn(3LDAP)</code>	Convert a DN into its component parts.

<code>ldap_explode_dns(3LDAP)</code>	Convert a DNS-style DN into its component parts (experimental).
<code>ldap_is_dns_dn(3LDAP)</code>	Check to see if a DN is a DNS-style DN (experimental).
<code>ldap_dns_to_dn(3LDAP)</code>	Convert a DNS domain name into an X.500 distinguished name.
<code>ldap_dn2ufn(3LDAP)</code>	Convert a DN into user friendly form.
<code>ldap_get_values(3LDAP)</code>	Return an attribute's values.
<code>ldap_get_values_len(3LDAP)</code>	Return an attribute's values with lengths.
<code>ldap_value_free(3LDAP)</code>	Free memory allocated by <code>ldap_get_values(3LDAP)</code> .
<code>ldap_value_free_len(3LDAP)</code>	Free memory allocated by <code>ldap_get_values_len(3LDAP)</code> .
<code>ldap_count_values(3LDAP)</code>	Return number of values.
<code>ldap_count_values_len(3LDAP)</code>	Return number of values.
<code>ldap_init_getfilter(3LDAP)</code>	Initialize getfilter functions from a file.
<code>ldap_init_getfilter_buf(3LDAP)</code>	Initialize getfilter functions from a buffer.
<code>ldap_getfilter_free(3LDAP)</code>	Free resources allocated by <code>ldap_init_getfilter(3LDAP)</code> .
<code>ldap_getfirstfilter(3LDAP)</code>	Return first search filter.
<code>ldap_getnextfilter(3LDAP)</code>	Return next search filter.
<code>ldap_build_filter(3LDAP)</code>	Construct an LDAP search filter from a pattern.
<code>ldap_setfilteraffixes(3LDAP)</code>	Set prefix and suffix for search filters.
<code>ldap_modify(3LDAP)</code>	Asynchronously modify an entry.
<code>ldap_modify_s(3LDAP)</code>	Synchronously modify an entry.
<code>ldap_modify_ext(3LDAP)</code>	Asynchronously modify an entry, return value, and place message.
<code>ldap_modify_ext_s(3LDAP)</code>	Synchronously modify an entry, return value, and place message.
<code>ldap_mods_free(3LDAP)</code>	Free array of pointers to mod structures used by <code>ldap_modify(3LDAP)</code> .

<code>ldap_modrdn2(3LDAP)</code>	Deprecated. Use <code>ldap_rename(3LDAP)</code> instead.
<code>ldap_modrdn2_s(3LDAP)</code>	Deprecated. Use <code>ldap_rename_s(3LDAP)</code> instead.
<code>ldap_modrdn(3LDAP)</code>	Deprecated. Use <code>ldap_rename(3LDAP)</code> instead.
<code>ldap_modrdn_s(3LDAP)</code>	Deprecated. Use <code>ldap_rename_s(3LDAP)</code> instead.
<code>ldap_rename(3LDAP)</code>	Asynchronously modify the name of an LDAP entry.
<code>ldap_rename_s(3LDAP)</code>	Synchronously modify the name of an LDAP entry.
<code>ldap_msgfree(3LDAP)</code>	Free result messages.
<code>ldap_parse_result(3LDAP)</code>	Search for a message to parse.
<code>ldap_parse_extended_result(3LDAP)</code>	Search for a message to parse.
<code>ldap_parse_sasl_bind_result(3LDAP)</code>	Search for a message to parse.
<code>ldap_search(3LDAP)</code>	Asynchronously search the directory.
<code>ldap_search_s(3LDAP)</code>	Synchronously search the directory.
<code>ldap_search_ext(3LDAP)</code>	Asynchronously search the directory with support for LDAPv3 controls.
<code>ldap_search_ext_s(3LDAP)</code>	Synchronously search the directory with support for LDAPv3 controls.
<code>ldap_search_st(3LDAP)</code>	Synchronously search the directory with support for a local timeout value.
<code>ldap_ufn_search_s(3LDAP)</code>	User friendly search the directory.
<code>ldap_ufn_search_c(3LDAP)</code>	User friendly search the directory with cancel.
<code>ldap_ufn_search_ct(3LDAP)</code>	User friendly search the directory with cancel and timeout.
<code>ldap_ufn_setfilter(3LDAP)</code>	Set filter file used by <code>ldap_ufn(3LDAP)</code> functions.
<code>ldap_ufn_setprefix(3LDAP)</code>	Set prefix used by <code>ldap_ufn(3LDAP)</code> functions.

<code>ldap_ufn_timeout(3LDAP)</code>	Set timeout used by <code>ldap_ufn(3LDAP)</code> functions.
<code>ldap_is_ldap_url(3LDAP)</code>	Check a URL string to see if it is an LDAP URL.
<code>ldap_url_parse(3LDAP)</code>	Break up an LDAP URL string into its components.
<code>ldap_free_urldesc(3LDAP)</code>	Free an LDAP URL structure.
<code>ldap_url_search(3LDAP)</code>	Asynchronously search by using an LDAP URL.
<code>ldap_url_search_s(3LDAP)</code>	Synchronously search by using an LDAP URL.
<code>ldap_url_search_st(3LDAP)</code>	Asynchronously search by using an LDAP URL, with support for a local timeout value.
<code>ldap_dns_to_url(3LDAP)</code>	Locate the LDAP URL associated with a DNS domain name.
<code>ldap_dn_to_url(3LDAP)</code>	Locate the LDAP URL associated with a distinguished name.
<code>ldap_init_searchprefs(3LDAP)</code>	Initialize searchprefs functions from a file.
<code>ldap_init_searchprefs_buf(3LDAP)</code>	Initialize searchprefs functions from a buffer.
<code>ldap_free_searchprefs(3LDAP)</code>	Free memory allocated by searchprefs functions.
<code>ldap_first_searchobj(3LDAP)</code>	Return first searchpref object.
<code>ldap_next_searchobj(3LDAP)</code>	Return next searchpref object.
<code>ldap_sort_entries(3LDAP)</code>	Sort a list of search results.
<code>ldap_sort_values(3LDAP)</code>	Sort a list of attribute values.
<code>ldap_sort_strcasecmp(3LDAP)</code>	Case insensitive string comparison.
<code>ldap_set_string_translators(3LDAP)</code>	Set character set translation functions used by LDAP library.
<code>ldap_translate_from_t61(3LDAP)</code>	Translate from the T.61 character set to another character set.
<code>ldap_translate_to_t61(3LDAP)</code>	Translate to the T.61 character set from another character set.
<code>ldap_enable_translation(3LDAP)</code>	Enable or disable character translation for an LDAP entry result.

<code>ldap_version(3LDAP)</code>	Get version information about the LDAP SDK for C.
<code>ldap_get_lang_values(3LDAP)</code>	Return an attribute's value that matches a specified language subtype.
<code>ldap_get_lang_values_len(3LDAP)</code>	Return an attribute's value that matches a specified language subtype along with lengths.
<code>ldap_get_entry_controls(3LDAP)</code>	Get the LDAP controls included with a directory entry in a set of search results.
<code>ldap_get_option(3LDAP)</code>	Get session preferences in an LDAP structure.
<code>ldap_set_option(3LDAP)</code>	Set session preferences in an LDAP structure.
<code>ldap_memfree(3LDAP)</code>	Free memory allocated by LDAP API functions.

Attributes See `attributes(5)` for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit) SUNWcslx (64-bit)
Stability Level	Evolving

See Also `attributes(5)`

Name ldap_abandon – abandon an LDAP operation in progress

Synopsis cc[*flag...*] *file...* -lldap[*library...*]

```
#include <lber.h>
#include <ldap.h>

int ldap_abandon(LDAP *ld, int msgid);
```

Description The `ldap_abandon()` function is used to abandon or cancel an LDAP operation in progress. The `msgid` passed should be the message id of an outstanding LDAP operation, as returned by [ldap_search\(3LDAP\)](#), [ldap_modify\(3LDAP\)](#), etc.

`ldap_abandon()` checks to see if the result of the operation has already come in. If it has, it deletes it from the queue of pending messages. If not, it sends an LDAP abandon operation to the the LDAP server.

The caller can expect that the result of an abandoned operation will not be returned from a future call to [ldap_result\(3LDAP\)](#).

Errors `ldap_abandon()` returns 0 if successful or -1 otherwise and setting `ld_errno` appropriately. See [ldap_error\(3LDAP\)](#) for details.

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [ldap\(3LDAP\)](#), [ldap_result\(3LDAP\)](#), [ldap_error\(3LDAP\)](#), [attributes\(5\)](#)

Name ldap_add, ldap_add_s, ldap_add_ext, ldap_add_ext_s – perform an LDAP add operation

Synopsis cc[*flag...*] *file...* -lldap[*library...*]

```
#include <lber.h>
#include <ldap.h>

intldap_add(LDAP *ld, char *dn, LDAPMod *attrs[]);

intldap_add_s(LDAP *ld, char *dn, LDAPMod *attrs[]);

int ldap_add_ext(LDAP *ld, char *dn, LDAPMod **attrs,
                 LDAPControl **serverctrls, int *msgidp);

int ldap_add_ext_s(LDAP *ld, char *dn, LDAPMod **attrs,
                  LDAPControl **serverctrls, LDAPControl **clientctrls);
```

Description The `ldap_add_s()` function is used to perform an LDAP add operation. It takes *dn*, the DN of the entry to add, and *attrs*, a null-terminated array of the entry's attributes. The `LDAPMod` structure is used to represent attributes, with the *mod_type* and *mod_values* fields being used as described under [ldap_modify\(3LDAP\)](#), and the *ldap_op* field being used only if you need to specify the `LDAP_MOD_BVALUES` option. Otherwise, it should be set to zero.

Note that all entries except that specified by the last component in the given DN must already exist. `ldap_add_s()` returns an LDAP error code indicating success or failure of the operation. See [ldap_error\(3LDAP\)](#) for more details.

The `ldap_add()` function works just like `ldap_add_s()`, but it is asynchronous. It returns the message id of the request it initiated. The result of this operation can be obtained by calling [ldap_result\(3LDAP\)](#).

The `ldap_add_ext()` function initiates an asynchronous add operation and returns `LDAP_SUCCESS` if the request was successfully sent to the server, or else it returns a LDAP error code if not (see [ldap_error\(3LDAP\)](#)). If successful, `ldap_add_ext()` places the message id of **msgidp*. A subsequent call to `ldap_result()`, can be used to obtain the result of the add request.

The `ldap_add_ext_s()` function initiates a synchronous add operation and returns the result of the operation itself.

Errors `ldap_add()` returns `-1` in case of error initiating the request, and will set the *ld_errno* field in the *ld* parameter to indicate the error. `ldap_add_s()` will return an LDAP error code directly.

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)

ATTRIBUTE TYPE	ATTRIBUTE VALUE
	SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [ldap\(3LDAP\)](#), [ldap_error\(3LDAP\)](#), [ldap_modify\(3LDAP\)](#), [attributes\(5\)](#)

Name ldap_ber_free – free a BerElement structure from memory

Synopsis `cc -flag ... file ...-lldap [-library ...]
#include <ldap.h>`

`void ldap_ber_free(BerElement *ber, int freebuf`

Description You can make a call to the `ldap_ber_free()` function to free `BerElement` structures allocated by `ldap_first_attribute()` and by `ldap_next_attribute()` function calls. When freeing structures allocated by these functions, specify 0 for the *freebuf* argument. The `ldap_first_attribute()` and by `ldap_next_attribute()` functions do not allocate the extra buffer in the `BerElement` structure.

For example, to retrieve attributes from a search result entry, you need to call the `ldap_first_attribute()` function. A call to this function allocates a `BerElement` structure, which is used to help track the current attribute. When you are done working with the attributes, this structure should be freed from memory, if it still exists.

This function is deprecated . Use the `ber_free()` function instead.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Obsolete

See Also [ber_free\(3LDAP\)](#), [ldap_first_attribute\(3LDAP\)](#), [ldap_next_attribute\(3LDAP\)](#), [attributes\(5\)](#)

Name ldap_bind, ldap_bind_s, ldap_sasl_bind, ldap_sasl_bind_s, ldap_simple_bind, ldap_simple_bind_s, ldap_unbind, ldap_unbind_s, ldap_unbind_ext, ldap_set_rebind_proc, ldap_sasl_interactive_bind_s – LDAP bind functions

Synopsis

```
cc [ flag... ] file... -lldap [ library... ]
#include <lber.h>
#include <ldap.h>

int ldap_bind(LDAP *ld, char *who, char *cred, int method);
int ldap_bind_s(LDAP *ld, char *who, char *cred, int method);
int ldap_simple_bind(LDAP *ld, char *who, char *passwd);
int ldap_simple_bind_s(LDAP *ld, char *who, char *passwd);
int ldap_unbind(LDAP *ld);
int ldap_unbind_s(LDAP *ld);
int ldap_unbind_ext(LDAP *ld, LDAPControl **serverctrls,
    LDAPControl **clientctrls);
void ldap_set_rebind_proc(LDAP *ld, int (*rebindproc));
int ldap_sasl_bind(LDAP *ld, char *dn, char *mechanism,
    struct berval **serverctrls, LDAPControl **clientctrls,
    int *msgidp);
int ldap_sasl_bind_s(LDAP *ld, char *dn, char *mechanism,
    struct berval *cred, LDAPControl **serverctrls,
    LDAPControl **clientctrls);
int ldap_sasl_interactive_bind_s(LDAP *ld, char *dn,
    char *saslMechanism, LDAPControl **sctrl, LDAPControl **cctrl,
    LDAPControl **unsigned_flags, LDAP_SASL_INTERACT_PROC *callback,
    void *defaults);
```

Description These functions provide various interfaces to the LDAP bind operation. After a connection is made to an LDAP server, the `ldap_bind()` function returns the message ID of the request initiated. The `ldap_bind_s()` function returns an LDAP error code.

Simple Authentication The simplest form of the bind call is `ldap_simple_bind_s()`. The function takes the DN (Distinguished Name) of the `dn` parameter and the userPassword associated with the entry in `passwd` to return an LDAP error code. See [ldap_error\(3LDAP\)](#).

The `ldap_simple_bind()` call is asynchronous. The function takes the same parameters as `ldap_simple_bind_s()` but initiates the bind operation and returns the message ID of the request sent. The result of the operation can be obtained by a subsequent call to [ldap_result\(3LDAP\)](#).

General Authentication The `ldap_bind()` and `ldap_bind_s()` functions are used to select the authentication method at runtime. Both functions take an extra *method* parameter to set the authentication method. For simple authentication, the *method* parameter is set to `LDAP_AUTH_SIMPLE`. The `ldap_bind()` function returns the message id of the request initiated. The `ldap_bind_s()` function returns an LDAP error code.

SASL Authentication The `ldap_sasl_bind()` and `ldap_sasl_bind_s()` functions are used for general and extensible authentication over LDAP through the use of the Simple Authentication Security Layer. The routines both take the DN to bind as the authentication method. A dotted-string representation of an OID identifies the method, and the `berval` structure holds the credentials. The special constant value `LDAP_SASL_SIMPLE` ("") can be passed to request simple authentication. Otherwise, the `ldap_simple_bind()` function or the `ldap_simple_bind_s()` function can be used.

The `ldap_sasl_interactive_bind_s()` helper function takes its data and performs the necessary `ldap_sasl_bind()` and associated SASL library authentication sequencing with the LDAP server that uses the provided connection (*ld*).

Upon a successful bind, the `ldap_sasl_bind()` function will, if negotiated by the SASL interface, install the necessary internal `libldap` plumbing to enable SASL integrity and privacy (over the wire encryption) with the LDAP server.

The `LDAP_SASL_INTERACTIVE` option flag is passed to the `libldap` API through the `flags` argument of the API. The flag tells the API to use the SASL interactive mode and to have the API request SASL authentication data through the `LDAP_SASL_INTERACTIVE_PROC` callback as needed. The callback provided is in the form:

```
typedef int (LDAP_SASL_INTERACT_PROC)
    (LDAP *ld, unsigned flags, void* defaults, void *interact);
```

The user-provided SASL callback is passed to the current LDAP connection pointer, the current `flags` field, an optional pointer to user-defined data, and the list of `sasl_interact_t` authentication values requested by [libsasl\(3LIB\)](#) to complete authentication.

The user-defined callback collects and returns the authentication information in the `sasl_interact_t` array according to `libsasl` rules. The authentication information can include user IDs, passwords, realms, or other information defined by SASL. The SASL library uses this data during sequencing to complete authentication.

Unbinding The `ldap_unbind()` call is used to unbind from a directory, to terminate the current association, and to free the resources contained in the *ld* structure. Once the function is called, the connection to the LDAP server is closed and the *ld* structure is invalid. The `ldap_unbind_s()` and `ldap_unbind()` calls are identical and synchronous in nature.

The `ldap_unbind_ext()` function is used to unbind from a directory, to terminate the current association, and to free the resources contained in the LDAP structure. Unlike `ldap_unbind()` and `ldap_unbind_s()`, both server and client controls can be explicitly included with

`ldap_unbind_ext()` requests. No server response is made to an unbind request and responses should not be expected from server controls included with unbind requests.

Rebinding While Following Referral The `ldap_set_rebind_proc()` call is used to set a function called back to obtain bind credentials. The credentials are used when a new server is contacted after an LDAP referral. If `ldap_set_rebind_proc()` is never called, or if it is called with a `NULL` *rebindproc* parameter, an unauthenticated simple LDAP bind is always done when chasing referrals.

The `rebindproc()` function is declared as shown below:

```
int rebindproc(LDAP *ld, char **whop, char **credp,
               int *methodp, int freeit);
```

The LDAP library first calls the `rebindproc()` to obtain the referral bind credentials. The *freeit* parameter is zero. The *whop*, *credp*, and *methodp* parameters should be set as appropriate. If `rebindproc()` returns `LDAP_SUCCESS`, referral processing continues. The `rebindproc()` is called a second time with a non-zero *freeit* value to give the application a chance to free any memory allocated in the previous call.

If anything but `LDAP_SUCCESS` is returned by the first call to `rebindproc()`, referral processing is stopped and the error code is returned for the original LDAP operation.

Return Values Make a call to [ldap_result\(3LDAP\)](#) to obtain the result of a bind operation.

Errors Asynchronous functions will return `-1` in case of error. See [ldap_error\(3LDAP\)](#) for more information on error codes returned. If no credentials are returned, the result parameter is set to `NULL`.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Evolving
MT-Level	Safe

See Also [ldap\(3LDAP\)](#), [ldap_error\(3LDAP\)](#), [ldap_open\(3LDAP\)](#), [ldap_result\(3LDAP\)](#), [libsasl\(3LIB\)](#), [attributes\(5\)](#)

Name ldap_charset, ldap_set_string_translators, ldap_t61_to_8859, ldap_8859_to_t61, ldap_translate_from_t61, ldap_translate_to_t61, ldap_enable_translation – LDAP character set translation functions

Synopsis cc[*flag...*] *file...* -lldap[*library...*]

```
#include <lber.h>
#include <ldap.h>

void ldap_set_string_translators(LDAP *ld,
                                BERTranslateProc encode_proc, BERTranslateProc decodeproc);

typedef int(*BERTranslateProc)(char **bufp, unsigned long *buflenp,
                                int free_input);

int ldap_t61_to_8859(char **bufp, unsigned long *buflenp,
                     int free_input);

int ldap_8859_to_t61(char **bufp, unsigned long *buflenp,
                     int free_input);

int ldap_translate_from_t61(LDAP *ld, char **bufp,
                           unsigned long *lenp, int free_input);

int ldap_translate_to_t61(LDAP *ld, char **bufp, unsigned long *lenp,
                          int free_input);

void ldap_enable_translation(LDAP *ld, LDAPMessage *entry, int enable);
```

Description These functions are used to enable translation of character strings used in the LDAP library to and from the T.61 character set used in the LDAP protocol. These functions are only available if the LDAP and LBER libraries are compiled with STR_TRANSLATION defined. It is also possible to turn on character translation by default so that all LDAP library callers will experience translation; see the LDAP Make-common source file for details.

ldap_set_string_translators() sets the translation functions that will be used by the LDAP library. They are not actually used until the *ld_lberoptions* field of the LDAP structure is set to include the LBER_TRANSLATE_STRINGS option.

ldap_t61_to_8859() and ldap_8859_to_t61() are translation functions for converting between T.61 characters and ISO-8859 characters. The specific 8859 character set used is determined at compile time.

ldap_translate_from_t61() is used to translate a string of characters from the T.61 character set to a different character set. The actual translation is done using the *decode_proc* that was passed to a previous call to ldap_set_string_translators(). On entry, **bufp* should point to the start of the T.61 characters to be translated and **lenp* should contain the number of bytes to translate. If *free_input* is non-zero, the input buffer will be freed if translation is a success. If the translation is a success, LDAP_SUCCESS will be returned, **bufp* will point to a newly malloc'd buffer that contains the translated characters, and **lenp* will contain the length of the result. If translation fails, an LDAP error code will be returned.

`ldap_translate_to_t61()` is used to translate a string of characters to the T.61 character set from a different character set. The actual translation is done using the *encode_proc* that was passed to a previous call to `ldap_set_string_translators()`. This function is called just like `ldap_translate_from_t61()`.

`ldap_enable_translation()` is used to turn on or off string translation for the LDAP entry *entry* (typically obtained by calling `ldap_first_entry()` or `ldap_next_entry()` after a successful LDAP search operation). If `enable` is zero, translation is disabled; if non-zero, translation is enabled. This function is useful if you need to ensure that a particular attribute is not translated when it is extracted using `ldap_get_values()` or `ldap_get_values_len()`. For example, you would not want to translate a binary attributes such as `jpegPhoto`.

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [ldap\(3LDAP\)](#), [attributes\(5\)](#)

Name ldap_compare, ldap_compare_s, ldap_compare_ext, ldap_compare_ext_s – LDAP compare operation

Synopsis cc[*flag...*] *file...* -lldap[*library...*]

```
#include <lber.h>
#include <ldap.h>

int ldap_compare(LDAP *ld, char *dn, char *attr, char *value);

int ldap_compare_s(LDAP *ld, char *dn, char *attr, char *value);

int ldap_compare_ext(LDAP *ld, char *dn, char *attr,
    struct berval *bvalue, LDAPControl **serverctrls,
    LDAPControl **clientctrls, int *msgidp);

int ldap_compare_ext_s(LDAP *ld, char *dn, char *attr,
    struct berval *bvalue, LDAPControl **serverctrls,
    LDAPControl **clientctrls);
```

Description The `ldap_compare_s()` function is used to perform an LDAP compare operation synchronously. It takes *dn*, the DN of the entry upon which to perform the compare, and *attr* and *value*, the attribute type and value to compare to those found in the entry. It returns an LDAP error code, which will be `LDAP_COMPARE_TRUE` if the entry contains the attribute value and `LDAP_COMPARE_FALSE` if it does not. Otherwise, some error code is returned.

The `ldap_compare()` function is used to perform an LDAP compare operation asynchronously. It takes the same parameters as `ldap_compare_s()`, but returns the message id of the request it initiated. The result of the compare can be obtained by a subsequent call to [ldap_result\(3LDAP\)](#).

The `ldap_compare_ext()` function initiates an asynchronous compare operation and returns `LDAP_SUCCESS` if the request was successfully sent to the server, or else it returns a LDAP error code if not (see [ldap_error\(3LDAP\)](#)). If successful, `ldap_compare_ext()` places the message id of the request in **msgidp*. A subsequent call to `ldap_result()`, can be used to obtain the result of the add request.

The `ldap_compare_ext_s()` function initiates a synchronous compare operation and as such returns the result of the operation itself.

Errors `ldap_compare_s()` returns an LDAP error code which can be interpreted by calling one of [ldap_perror\(3LDAP\)](#) and friends. `ldap_compare()` returns `-1` if something went wrong initiating the request. It returns the non-negative message id of the request if it was successful.

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)

ATTRIBUTE TYPE	ATTRIBUTE VALUE
	SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [ldap\(3LDAP\)](#), [ldap_error\(3LDAP\)](#), [attributes\(5\)](#)

Bugs There is no way to compare binary values using `ldap_compare()`.

Name ldap_control_free, ldap_controls_free – LDAP control disposal

Synopsis cc[*flag...*] *file...* -lldap[*library...*]

```
#include <lber.h>
```

```
#include <ldap.h>
```

```
void ldap_control_free(LDAPControl *ctrl);
```

```
void ldap_controls_free(LDAPControl *ctrls);
```

Description ldap_controls_free() and ldap_control_free() are routines which can be used to dispose of a single control or an array of controls allocated by other LDAP APIs.

Return Values None.

Errors No errors are defined for these functions.

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [ldap_error\(3LDAP\)](#), [ldap_result\(3LDAP\)](#), [attributes\(5\)](#)

Name ldap_delete, ldap_delete_s, ldap_delete_ext, ldap_delete_ext_s – LDAP delete operation

Synopsis cc[*flag...*] *file...* -lldap[*library...*]

```
#include <lber.h>
#include <ldap.h>

int ldap_delete(LDAP *ld, char *dn);

int ldap_delete_s(LDAP *ld, char *dn);

int ldap_delete_ext(LDAP *ld, char *dn, LDAPControl **serverctrls,
    LDAPControl **clientctrls, int *msgidp);

int ldap_delete_ext_s(LDAP *ld, char *dn, LDAPControl **serverctrls,
    LDAPControl **clientctrls);
```

Description The `ldap_delete_s()` function is used to perform an LDAP delete operation synchronously. It takes *dn*, the DN of the entry to be deleted. It returns an LDAP error code, indicating the success or failure of the operation.

The `ldap_delete()` function is used to perform an LDAP delete operation asynchronously. It takes the same parameters as `ldap_delete_s()`, but returns the message id of the request it initiated. The result of the delete can be obtained by a subsequent call to [ldap_result\(3LDAP\)](#).

The `ldap_delete_ext()` function initiates an asynchronous delete operation and returns `LDAP_SUCCESS` if the request was successfully sent to the server, or else it returns a LDAP error code if not (see [ldap_error\(3LDAP\)](#)). If successful, `ldap_delete_ext()` places the message id of the request in **msgidp*. A subsequent call to `ldap_result()`, can be used to obtain the result of the add request.

The `ldap_delete_ext_s()` function initiates a synchronous delete operation and as such returns the result of the operation itself.

Errors `ldap_delete_s()` returns an LDAP error code which can be interpreted by calling one of [ldap_perror\(3LDAP\)](#) functions. `ldap_delete()` returns `-1` if something went wrong initiating the request. It returns the non-negative message id of the request if things were successful.

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [ldap\(3LDAP\)](#), [ldap_error\(3LDAP\)](#), [attributes\(5\)](#)

Name ldap_disptmpl, ldap_init_templates, ldap_init_templates_buf, ldap_free_templates, ldap_first_disptmpl, ldap_next_disptmpl, ldap_oc2template, ldap_name2template, ldap_tmplattrs, ldap_first_tmplrow, ldap_next_tmplrow, ldap_first_tmplcol, ldap_next_tmplcol – LDAP display template functions

Synopsis cc[*flag...*] *file...* -lldap[*library...*]

```
#include <lber.h>
#include <ldap.h>

int ldap_init_templates(char *file, struct ldap_disptmpl **tmplist);
int ldap_init_templates_buf(char *buf, unsigned long len,
    struct ldap_disptmpl **tmplist);
void ldap_free_templates(struct ldap_disptmpl *tmplist);
struct ldap_disptmpl *ldap_first_disptmpl
    (struct ldap_disptmpl *tmplist);
struct ldap_disptmpl *ldap_next_disptmpl
    (struct ldap_disptmpl *tmplist, struct ldap_disptmpl *tmpl);
struct ldap_disptmpl *ldap_oc2template (char **oclist,
    struct ldap_disptmpl *tmplist);
struct ldap_disptmpl *ldap_name2template (char *name,
    struct ldap_disptmpl *tmplist);
char **ldap_tmplattrs(struct ldap_disptmpl *tmpl, char **includeattrs,
    int exclude;, unsigned long syntaxmask);
struct ldap_tmplitem *ldap_first_tmplrow(struct ldap_disptmpl *tmpl);
struct ldap_tmplitem *ldap_next_tmplrow(struct ldap_disptmpl *tmpl,
    struct ldap_tmplitem *row);
struct ldap_tmplitem *ldap_first_tmplcol(struct ldap_disptmpl *tmpl,
    struct ldap_tmplitem *row, struct ldap_tmplitem *col);
struct ldap_tmplitem *ldap_next_tmplcol(struct ldap_disptmpl *tmpl,
    struct ldap_tmplitem *row, struct ldap_tmplitem *col);
```

Description These functions provide a standard way to access LDAP entry display templates. Entry display templates provide a standard way for LDAP applications to display directory entries. The general idea is that it is possible to map the list of object class values present in an entry to an appropriate display template. Display templates are defined in a configuration file. See [ldaptemplates.conf\(4\)](#). Each display template contains a pre-determined list of items, where each item generally corresponds to an attribute to be displayed. The items contain information and flags that the caller can use to display the attribute and values in a reasonable fashion. Each item has a syntaxid, which are described in the SYNTAX IDS section below. The [ldap_entry2text\(3LDAP\)](#) functions use the display template functions and produce text output.

`ldap_init_templates()` reads a sequence of templates from a valid LDAP template configuration file (see `ldaptemplates.conf(4)`). Upon success, `0` is returned, and *tmplist* is set to point to a list of templates. Each member of the list is an `ldap_disptmpl` structure (defined below in the DISPTMPL Structure Elements section).

`ldap_init_templates_buf()` reads a sequence of templates from *buf* (whose size is *buflen*). *buf* should point to the data in the format defined for an LDAP template configuration file (see `ldaptemplates.conf(4)`). Upon success, `0` is returned, and *tmplist* is set to point to a list of templates.

The `LDAP_SET_DISPTMPL_APPDATA()` macro is used to set the value of the `dt_appdata` field in an `ldap_disptmpl` structure. This field is reserved for the calling application to use; it is not used internally.

The `LDAP_GET_DISPTMPL_APPDATA()` macro is used to retrieve the value in the `dt_appdata` field.

The `LDAP_IS_DISPTMPL_OPTION_SET()` macro is used to test a `ldap_disptmpl` structure for the existence of a template option. The options currently defined are:

`LDAP_DTmpl_OPT_ADDABLE` (it is appropriate to allow entries of this type to be added),
`LDAP_DTmpl_OPT_ALLOWMODRDN` (it is appropriate to offer the “modify rdn” operation),
`LDAP_DTmpl_OPT_ALTVIEW` (this template is merely an alternate view of another template, typically used for templates pointed to be an `LDAP_SYN_LINKACTION` item).

`ldap_free_templates()` disposes of the templates allocated by `ldap_init_templates()`.

`ldap_first_disptmpl()` returns the first template in the list *tmplist*. The *tmplist* is typically obtained by calling `ldap_init_templates()`.

`ldap_next_disptmpl()` returns the template after *tmpl* in the template list *tmplist*. A `NULL` pointer is returned if *tmpl* is the last template in the list.

`ldap_oc2template()` searches *tmplist* for the best template to use to display an entry that has a specific set of objectClass values. *oclist* should be a null-terminated array of strings that contains the values of the objectClass attribute of the entry. A pointer to the first template where all of the object classes listed in one of the template's `dt_oclist` elements are contained in *oclist* is returned. A `NULL` pointer is returned if no appropriate template is found.

`ldap_tmplattns()` returns a null-terminated array that contains the names of attributes that need to be retrieved if the template *tmpl* is to be used to display an entry. The attribute list should be freed using `ldap_value_free()`. The *includeattrs* parameter contains a null-terminated array of attributes that should always be included (it may be `NULL` if no extra attributes are required). If *syntaxmask* is non-zero, it is used to restrict the attribute set returned. If *exclude* is zero, only attributes where the logical AND of the template item syntax id and the *syntaxmask* is non-zero are included. If *exclude* is non-zero, attributes where the logical AND of the template item syntax id and the *syntaxmask* is non-zero are excluded.

`ldap_first_tmplrow()` returns a pointer to the first row of items in template *tmpl*.

`ldap_next_tmplrow()` returns a pointer to the row that follows *row* in template *tmpl*.

`ldap_first_tmplcol()` returns a pointer to the first item (in the first column) of row *row* within template *tmpl*. A pointer to an `ldap_tmplitem` structure (defined below in the TEMPLITEM Structure Elements section) is returned.

The `LDAP_SET_TMPLITEM_APPDATA()` macro is used to set the value of the `ti_appdata` field in a `ldap_tmplitem` structure. This field is reserved for the calling application to use; it is not used internally.

The `LDAP_GET_TMPLITEM_APPDATA()` macro is used to retrieve the value of the `ti_appdata` field.

The `LDAP_IS_TMPLITEM_OPTION_SET()` macro is used to test a `ldap_tmplitem` structure for the existence of an item option. The options currently defined are:

`LDAP_DITEM_OPT_READONLY` (this attribute should not be modified),

`LDAP_DITEM_OPT_SORTVALUES` (it makes sense to sort the values),

`LDAP_DITEM_OPT_SINGLEDVALUED` (this attribute can only hold a single value),

`LDAP_DITEM_OPT_VALUEREQUIRED` (this attribute must contain at least one value),

`LDAP_DITEM_OPT_HIDEIFEMPTY` (do not show this item if there are no values), and

`LDAP_DITEM_OPT_HIDEIFFALSE` (for boolean attributes only: hide this item if the value is FALSE).

`ldap_next_tmplcol()` returns a pointer to the item (column) that follows column *col* within row *row* of template *tmpl*.

DISPTMPL Structure Elements The `ldap_disptmpl` structure is defined as:

```
struct ldap_disptmpl {
    char                *dt_name;
    char                *dt_pluralname;
    char                *dt_iconname;
    unsigned long       dt_options;
    char                *dt_authattrname;
    char                *dt_defrdnattrname;
    char                *dt_defaddlocation;
    struct ldap_oclist  *dt_oclist;
    struct ldap_adddeflist *dt_adddeflist;
    struct ldap_tmplitem *dt_items;
    void                *dt_appdata;
    struct ldap_disptmpl *dt_next;
};
```

The `dt_name` member is the singular name of the template. The `dt_pluralname` is the plural name. The `dt_iconname` member will contain the name of an icon or other graphical element that can be used to depict entries that correspond to this display template. The `dt_options` contains options which may be tested using the `LDAP_IS_TMPLITEM_OPTION_SET()` macro.

The `dt_authattrname` contains the name of the DN-syntax attribute whose value(s) should be used to authenticate to make changes to an entry. If `dt_authattrname` is NULL, then authenticating as the entry itself is appropriate. The `dt_defrdnattrname` is the name of the attribute that is normally used to name entries of this type, for example, "cn" for person entries. The `dt_defaddlocation` is the distinguished name of an entry below which new entries of this type are typically created (its value is site-dependent).

`dt_oclist` is a pointer to a linked list of object class arrays, defined as:

```
struct ldap_oclist {
    char            **oc_objclasses;
    struct ldap_oclist *oc_next;
};
```

These are used by the `ldap_oc2template()` function.

`dt_adddeflist` is a pointer to a linked list of rules for defaulting the values of attributes when new entries are created. The `ldap_adddeflist` structure is defined as:

```
struct ldap_adddeflist {
    int            ad_source;
    char           *ad_attrname;
    char           *ad_value;
    struct ldap_adddeflist *ad_next;
};
```

The `ad_attrname` member contains the name of the attribute whose value this rule sets. If `ad_source` is `LDAP_ADSRC_CONSTANTVALUE` then the `ad_value` member contains the (constant) value to use. If `ad_source` is `LDAP_ADSRC_ADDERSDN` then `ad_value` is ignored and the distinguished name of the person who is adding the new entry is used as the default value for `ad_attrname`.

TMPLITEM Structure Elements

The `ldap_tmplitem` structure is defined as:

```
struct ldap_tmplitem {
    unsigned long    ti_syntaxid;
    unsigned long    ti_options;
    char             *ti_attrname;
    char             *ti_label;
    char             **ti_args;
    struct ldap_tmplitem *ti_next_in_row;
    struct ldap_tmplitem *ti_next_in_col;
    void             *ti_appdata;
};
```

Syntax IDs Syntax ids are found in the `ldap_tmplitem` structure element `ti_syntaxid`, and they can be used to determine how to display the values for the attribute associated with an item. The `LDAP_GET_SYN_TYPE()` macro can be used to return a general type from a syntax id. The five general types currently defined are: `LDAP_SYN_TYPE_TEXT` (for attributes that are most

appropriately shown as text), LDAP_SYN_TYPE_IMAGE (for JPEG or FAX format images), LDAP_SYN_TYPE_BOOLEAN (for boolean attributes), LDAP_SYN_TYPE_BUTTON (for attributes whose values are to be retrieved and display only upon request, for example, in response to the press of a button, a JPEG image is retrieved, decoded, and displayed), and LDAP_SYN_TYPE_ACTION (for special purpose actions such as “search for the entries where this entry is listed in the seeAlso attribute”).

The LDAP_GET_SYN_OPTIONS macro can be used to retrieve an unsigned long bitmap that defines options. The only currently defined option is LDAP_SYN_OPT_DEFER, which (if set) implies that the values for the attribute should not be retrieved until requested.

There are sixteen distinct syntax ids currently defined. These generally correspond to one or more X.500 syntaxes.

LDAP_SYN_CASEIGNORESTR is used for text attributes which are simple strings whose case is ignored for comparison purposes.

LDAP_SYN_MULTILINESTR is used for text attributes which consist of multiple lines, for example, postalAddress, homePostalAddress, multilineDescription, or any attributes of syntax caseIgnoreList.

LDAP_SYN_RFC822ADDR is used for case ignore string attributes that are RFC-822 conformant mail addresses, for example, mail.

LDAP_SYN_DN is used for attributes with a Distinguished Name syntax, for example, seeAlso.

LDAP_SYN_BOOLEAN is used for attributes with a boolean syntax.

LDAP_SYN_JPEGIMAGE is used for attributes with a jpeg syntax, for example, jpegPhoto.

LDAP_SYN_JPEGBUTTON is used to provide a button (or equivalent interface element) that can be used to retrieve, decode, and display an attribute of jpeg syntax.

LDAP_SYN_FAXIMAGE is used for attributes with a photo syntax, for example, Photo. These are actually Group 3 Fax (T.4) format images.

LDAP_SYN_FAXBUTTON is used to provide a button (or equivalent interface element) that can be used to retrieve, decode, and display an attribute of photo syntax.

LDAP_SYN_AUDIOBUTTON is used to provide a button (or equivalent interface element) that can be used to retrieve and play an attribute of audio syntax. Audio values are in the “mu law” format, also known as “au” format.

LDAP_SYN_TIME is used for attributes with the UTCTime syntax, for example, lastModifiedTime. The value(s) should be displayed in complete date and time fashion.

LDAP_SYN_DATE is used for attributes with the UTCTime syntax, for example, lastModifiedTime. Only the date portion of the value(s) should be displayed.

LDAP_SYN_LABELEDURL is used for labeledURL attributes.

LDAP_SYN_SEARCHACTION is used to define a search that is used to retrieve related information. If `ti_attrname` is not NULL, it is assumed to be a boolean attribute which will cause no search to be performed if its value is FALSE. The `ti_args` structure member will have four strings in it: `ti_args[0]` should be the name of an attribute whose values are used to help construct a search filter or “-dn” is the distinguished name of the entry being displayed should be used, `ti_args[1]` should be a filter pattern where any occurrences of “%v” are replaced with the value derived from `ti_args[0]`, `ti_args[2]` should be the name of an additional attribute to retrieve when performing the search, and `ti_args[3]` should be a human-consumable name for that attribute. The `ti_args[2]` attribute is typically displayed along with a list of distinguished names when multiple entries are returned by the search.

LDAP_SYN_LINKACTION is used to define a link to another template by name. `ti_args[0]` will contain the name of the display template to use. The `ldap_name2template()` function can be used to obtain a pointer to the correct `ldap_disptmpl` structure.

LDAP_SYN_ADDDNACTION and LDAP_SYN_VERIFYDNACTION are reserved as actions but currently undefined.

Errors The init template functions return LDAP_TMPL_ERR_VERSION if *buf* points to data that is newer than can be handled, LDAP_TMPL_ERR_MEM if there is a memory allocation problem, LDAP_TMPL_ERR_SYNTAX if there is a problem with the format of the templates buffer or file. LDAP_TMPL_ERR_FILE is returned by `ldap_init_templates` if the file cannot be read. Other functions generally return NULL upon error.

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [ldap\(3LDAP\)](#), [ldap_entry2text\(3LDAP\)](#), [ldaptemplates.conf\(4\)](#), [attributes\(5\)](#)

Name ldap_entry2text, ldap_entry2text_search, ldap_entry2html, ldap_entry2html_search, ldap_vals2html, ldap_vals2text – LDAP entry display functions

Synopsis cc[*flag...*] *file...* -lldap[*library...*]

```
#include <lber.h>
#include <ldap.h>

int ldap_entry2text(LDAP *ld, char *buf, LDAPMessage *entry,
    struct ldap_disptmpl *tmpl, char **defattrs, char ***defvals,
    int (*writeproc)(), void *writeparm, char *eol, int rdncount,
    unsigned long opts);

int ldap_entry2text_search(LDAP *ld, char *dn, char *base,
    LDAPMessage *entry, struct ldap_disptmpl *tmplist,
    char **defattrs, char ***defvals, int (*writeproc)(),
    void *writeparm, char *eol, int rdncount,
    unsigned long opts);

int ldap_vals2text(LDAP *ld, char *buf, char **vals, char *label,
    int labelwidth, unsigned long syntaxid, int (*writeproc)(),
    void *writeparm, char *eol, int rdncount);

int ldap_entry2html(LDAP *ld, char *buf, LDAPMessage *entry,
    struct ldap_disptmpl *tmpl, char **defattrs, char ***defvals,
    int (*writeproc)(), void *writeparm, char *eol, int rdncount,
    unsigned long opts, char *urlprefix, char *base);

int ldap_entry2html_search(LDAP *ld, char *dn, LDAPMessage *entry,
    struct ldap_disptmpl *tmplist, char **defattrs, char ***defvals,
    int (*writeproc)(), void *writeparm, char *eol, int rdncount,
    unsigned long opts, char *urlprefix);

int ldap_vals2html(LDAP *ld, char *buf, char **vals,
    char *label, int labelwidth, unsigned long syntaxid,
    int (*writeproc)(), void *writeparm, char *eol, int rdncount,
    char *urlprefix);

#define LDAP_DISP_OPT_AUTOLABELWIDTH 0x00000001

#define LDAP_DISP_OPT_HTMLBODYONLY 0x00000002

#define LDAP_DTmpl_BUFSIZ 2048
```

Description These functions use the LDAP display template functions (see [ldap_disptmpl\(3LDAP\)](#) and `ldap_templates.conf(4)`) to produce a plain text or an HyperText Markup Language (HTML) display of an entry or a set of values. Typical plain text output produced for an entry might look like:

```
"Barbara J Jensen, Information Technology Division"
Also Known As:
Babs Jensen
Barbara Jensen
```

```

Barbara J Jensen
E-Mail Address:
bjensen@terminator.rs.itd.umich.edu
Work Address:
535 W. William
Ann Arbor, MI 48103
Title:
Mythical Manager, Research Systems
...

```

The exact output produced will depend on the display template configuration. HTML output is similar to the plain text output, but more richly formatted.

`ldap_entry2text()` produces a text representation of *entry* and writes the text by calling the *writeproc* function. All of the attributes values to be displayed must be present in *entry*; no interaction with the LDAP server will be performed within `ldap_entry2text`. *ld* is the LDAP pointer obtained by a previous call to `ldap_open`. *writeproc* should be declared as:

```

int writeproc( writeparm, p, len )
void *writeparm;
char *p;
int len;

```

where *p* is a pointer to text to be written and *len* is the length of the text. *p* is guaranteed to be zero-terminated. Lines of text are terminated with the string *eol*. *buf* is a pointer to a buffer of size `LDAP_DTML_BUFSIZ` or larger. If *buf* is NULL then a buffer is allocated and freed internally. *tmpl* is a pointer to the display template to be used (usually obtained by calling `ldap_oc2template`). If *tmpl* is NULL, no template is used and a generic display is produced. *defattrs* is a NULL-terminated array of LDAP attribute names which you wish to provide default values for (only used if *entry* contains no values for the attribute). An array of NULL-terminated arrays of default values corresponding to the attributes should be passed in *defvals*. The *rdncount* parameter is used to limit the number of Distinguished Name (DN) components that are actually displayed for DN attributes. If *rdncount* is zero, all components are shown. *opts* is used to specify output options. The only values currently allowed are zero (default output), `LDAP_DISP_OPT_AUTOLABELWIDTH` which causes the width for labels to be determined based on the longest label in *tmpl*, and `LDAP_DISP_OPT_HTMLBODYONLY`. The `LDAP_DISP_OPT_HTMLBODYONLY` option instructs the library not to include `<HTML>`, `<HEAD>`, `<TITLE>`, and `<BODY>` tags. In other words, an HTML fragment is generated, and the caller is responsible for prepending and appending the appropriate HTML tags to construct a correct HTML document.

`ldap_entry2text_search()` is similar to `ldap_entry2text`, and all of the like-named parameters have the same meaning except as noted below. If *base* is not NULL, it is the search base to use when executing search actions. If it is NULL, search action template items are ignored. If *entry* is not NULL, it should contain the *objectClass* attribute values for the entry to be displayed. If *entry* is NULL, *dn* must not be NULL, and `ldap_entry2text_search` will retrieve the *objectClass* values itself by calling `ldap_search_s`. `ldap_entry2text_search` will

determine the appropriate display template to use by calling `ldap_oc2template`, and will call `ldap_search_s` to retrieve any attribute values to be displayed. The *tmplist* parameter is a pointer to the entire list of templates available (usually obtained by calling `ldap_init_templates` or `ldap_init_templates_buf`). If *tmplist* is NULL, `ldap_entry2text_search` will attempt to read a load templates from the default template configuration file `ETCDIR/ldaptemplates.conf`

`ldap_vals2text` produces a text representation of a single set of LDAP attribute values. The *ld*, *buf*, *writeproc*, *writeparm*, *eol*, and *rdncount* parameters are the same as the like-named parameters for `ldap_entry2text`. *vals* is a NULL-terminated list of values, usually obtained by a call to `ldap_get_values`. *label* is a string shown next to the values (usually a friendly form of an LDAP attribute name). *labelwidth* specifies the label margin, which is the number of blank spaces displayed to the left of the values. If zero is passed, a default label width is used. *syntaxid* is a display template attribute syntax identifier (see [ldap_disptmpl\(3LDAP\)](#) for a list of the pre-defined LDAP_SYN_... values).

`ldap_entry2html` produces an HTML representation of *entry*. It behaves exactly like [ldap_entry2text\(3LDAP\)](#), except for the formatted output and the addition of two parameters. *urlprefix* is the starting text to use when constructing an LDAP URL. The default is the string `ldap:///`. The second additional parameter, *base*, the search base to use when executing search actions. If it is NULL, search action template items are ignored.

`ldap_entry2html_search` behaves exactly like [ldap_entry2text_search\(3LDAP\)](#), except HTML output is produced and one additional parameter is required. *urlprefix* is the starting text to use when constructing an LDAP URL. The default is the string `ldap:///`

`ldap_vals2html` behaves exactly like `ldap_vals2text`, except HTML output is and one additional parameter is required. *urlprefix* is the starting text to use when constructing an LDAP URL. The default is the string `ldap:///`

Errors These functions all return an LDAP error code. LDAP_SUCCESS is returned if no error occurs. See [ldap_error\(3LDAP\)](#) for details. The *ld_errno* field of the *ld* parameter is also set to indicate the error.

Files `ETCDIR/ldaptemplates.conf`

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [ldap\(3LDAP\)](#), [ldap_disptmpl\(3LDAP\)](#), [ldaptemplates.conf\(4\)](#), [attributes\(5\)](#)

Name ldap_error, ldap_err2string, ldap_perror, ldap_result2error – LDAP protocol error handling functions

Synopsis

```
cc[ flag... ] file... -lldap[ library... ]
#include <lber.h>
#include <ldap.h>
```

```
char *ldap_err2string(int err);

void ldap_perror(LDAP *ld, const char *s);

int ldap_result2error(LDAP *ld, LDAPMessage *res, int freet);
```

Description These functions interpret the error codes that are returned by the LDAP API routines. The `ldap_perror()` and `ldap_result2error()` functions are deprecated for all new development. Use `ldap_err2string()` instead.

You can also use `ldap_parse_sasl_bind_result(3LDAP)`, `ldap_parse_extended_result(3LDAP)`, and `ldap_parse_result(3LDAP)` to provide error handling and interpret error codes returned by LDAP API functions.

The `ldap_err2string()` function takes *err*, a numeric LDAP error code, returned either by `ldap_parse_result(3LDAP)` or another LDAP API call. It returns an informative, null-terminated, character string that describes the error.

The `ldap_result2error()` function takes *res*, a result produced by `ldap_result(3LDAP)` or other synchronous LDAP calls, and returns the corresponding error code. If the *freet* parameter is non-zero, it indicates that the *res* parameter should be freed by a call to `ldap_result(3LDAP)` after the error code has been extracted.

Similar to the way `perror(3C)` works, the `ldap_perror()` function can be called to print an indication of the error to standard error.

Errors The possible values for an LDAP error code are:

LDAP_SUCCESS	The request was successful.
LDAP_OPERATIONS_ERROR	An operations error occurred.
LDAP_PROTOCOL_ERROR	A protocol violation was detected.
LDAP_TIMELIMIT_EXCEEDED	An LDAP time limit was exceeded.
LDAP_SIZELIMIT_EXCEEDED	An LDAP size limit was exceeded.
LDAP_COMPARE_FALSE	A compare operation returned false.
LDAP_COMPARE_TRUE	A compare operation returned true.
LDAP_STRONG_AUTH_NOT_SUPPORTED	The LDAP server does not support strong authentication.
LDAP_STRONG_AUTH_REQUIRED	Strong authentication is required for the operation.

LDAP_PARTIAL_RESULTS	Only partial results are returned.
LDAP_NO_SUCH_ATTRIBUTE	The attribute type specified does not exist in the entry.
LDAP_UNDEFINED_TYPE	The attribute type specified is invalid.
LDAP_INAPPROPRIATE_MATCHING	The filter type is not supported for the specified attribute.
LDAP_CONSTRAINT_VIOLATION	An attribute value specified violates some constraint. For example, a postalAddress has too many lines, or a line that is too long.
LDAP_TYPE_OR_VALUE_EXISTS	An attribute type or attribute value specified already exists in the entry.
LDAP_INVALID_SYNTAX	An invalid attribute value was specified.
LDAP_NO_SUCH_OBJECT	The specified object does not exist in the directory.
LDAP_ALIAS_PROBLEM	An alias in the directory points to a nonexistent entry.
LDAP_INVALID_DN_SYNTAX	A syntactically invalid DN was specified.
LDAP_IS_LEAF	The object specified is a leaf.
LDAP_ALIAS_DEREF_PROBLEM	A problem was encountered when dereferencing an alias.
LDAP_INAPPROPRIATE_AUTH	Inappropriate authentication was specified. For example, LDAP_AUTH_SIMPLE was specified and the entry does not have a userPassword attribute.
LDAP_INVALID_CREDENTIALS	Invalid credentials were presented, for example, the wrong password.
LDAP_INSUFFICIENT_ACCESS	The user has insufficient access to perform the operation.
LDAP_BUSY	The DSA is busy.
LDAP_UNAVAILABLE	The DSA is unavailable.
LDAP_UNWILLING_TO_PERFORM	The DSA is unwilling to perform the operation.
LDAP_LOOP_DETECT	A loop was detected.
LDAP_NAMING_VIOLATION	A naming violation occurred.
LDAP_OBJECT_CLASS_VIOLATION	An object class violation occurred. For example, a must attribute was missing from the entry.

LDAP_NOT_ALLOWED_ON_NONLEAF	The operation is not allowed on a nonleaf object.
LDAP_NOT_ALLOWED_ON_RDN	The operation is not allowed on an RDN.
LDAP_ALREADY_EXISTS	The entry already exists.
LDAP_NO_OBJECT_CLASS_MODS	Object class modifications are not allowed.
LDAP_OTHER	An unknown error occurred.
LDAP_SERVER_DOWN	The LDAP library cannot contact the LDAP server.
LDAP_LOCAL_ERROR	Some local error occurred. This is usually the result of a failed <code>malloc(3C)</code> call or a failure to <code>fflush(3C)</code> the <code>stdio</code> stream to files, even when the LDAP requests were processed successfully by the remote server.
LDAP_ENCODING_ERROR	An error was encountered encoding parameters to send to the LDAP server.
LDAP_DECODING_ERROR	An error was encountered decoding a result from the LDAP server.
LDAP_TIMEOUT	A time limit was exceeded while waiting for a result.
LDAP_AUTH_UNKNOWN	The authentication method specified to <code>ldap_bind(3LDAP)</code> is not known.
LDAP_FILTER_ERROR	An invalid filter was supplied to <code>ldap_search(3LDAP)</code> , for example, unbalanced parentheses.
LDAP_PARAM_ERROR	An LDAP function was called with a bad parameter, for example, a NULL <i>ld</i> pointer, and the like.
LDAP_NO_MEMORY	A memory allocation call failed in an LDAP library function, for example, <code>malloc(3C)</code> .
LDAP_CONNECT_ERROR	The LDAP client has either lost its connection to an LDAP server or it cannot establish a connection.
LDAP_NOT_SUPPORTED	The requested functionality is not supported., for example, when an LDAPv2 client requests some LDAPv3 functionality.
LDAP_CONTROL_NOT_FOUND	An LDAP client requested a control not found in the list of supported controls sent by the server.
LDAP_NO_RESULTS_RETURNED	The LDAP server sent no results.
LDAP_MORE_RESULTS_TO_RETURN	More results are chained in the message chain.

LDAP_CLIENT_LOOP	A loop has been detected, for example, when following referrals.
LDAP_REFERRAL_LIMIT_EXCEEDED	The referral exceeds the hop limit. The hop limit determines the number of servers that the client can hop through to retrieve data.

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit) SUNWcslx (64-bit)
Interface Stability	Committed

See Also [fflush\(3C\)](#), [ldap\(3LDAP\)](#), [ldap_bind\(3LDAP\)](#), [ldap_result\(3LDAP\)](#), [ldap_parse_extended_result\(3LDAP\)](#), [ldap_parse_result\(3LDAP\)](#), [ldap_parse_sasl_bind_result\(3LDAP\)](#), [ldap_search\(3LDAP\)](#), [malloc\(3C\)](#), [perror\(3C\)](#), [attributes\(5\)](#)

Name ldap_first_attribute, ldap_next_attribute – step through LDAP entry attributes

Synopsis cc [*flag...*] *file...* -lldap[*library...*]

```
#include <lber.h>
#include <ldap.h>

char *ldap_first_attribute(LDAP *ld, LDAPMessage *entry,
    BerElement **berptr);

char *ldap_next_attribute(LDAP *ld, LDAPMessage *entry,
    BerElement *ber);
```

Description The ldap_first_attribute() function gets the value of the first attribute in an entry.

The ldap_first_attribute() function returns the name of the first attribute in the entry. To get the value of the first attribute, pass the attribute name to the ldap_get_values() function or to the ldap_get_values_len() function.

The ldap_next_attribute() function gets the value of the next attribute in an entry.

After stepping through the attributes, the application should call ber_free() to free the BerElement structure allocated by the ldap_first_attribute() function if the structure is other than NULL.

Errors If an error occurs, NULL is returned and the ld_errno field in the ld parameter is set to indicate the error. See [ldap_error\(3LDAP\)](#) for a description of possible error codes.

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTETYPE	ATTRIBUTEVALUE
MT-Level	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [ldap\(3LDAP\)](#), [ldap_first_entry\(3LDAP\)](#), [ldap_get_values\(3LDAP\)](#), [ldap_error\(3LDAP\)](#), [attributes\(5\)](#)

Notes The ldap_first_attribute() function allocates memory that might need to be freed by the caller by means of [ber_free\(3LDAP\)](#).

Name ldap_first_entry, ldap_next_entry, ldap_count_entries, ldap_count_references, ldap_first_reference, ldap_next_reference – LDAP entry parsing and counting functions

Synopsis cc[*flag...*] *file...* -lldap[*library...*]

```
#include <lber.h>
#include <ldap.h>

LDAPMessage *ldap_first_entry(LDAP *ld, LDAPMessage *result);
LDAPMessage *ldap_next_entry(LDAP *ld, LDAPMessage *entry);
ldap_count_entries(LDAP *ld, LDAPMessage *result);
LDAPMessage *ldap_first_reference(LDAP *ld, LDAPMessage *res);
LDAPMessage *ldap_next_reference(LDAP *ld, LDAPMessage *res);
int ldap_count_references(LDAP *ld, LDAPMessage *res);
```

Description These functions are used to parse results received from [ldap_result\(3LDAP\)](#) or the synchronous LDAP search operation functions [ldap_search_s\(3LDAP\)](#) and [ldap_search_st\(3LDAP\)](#).

The `ldap_first_entry()` function is used to retrieve the first entry in a chain of search results. It takes the *result* as returned by a call to [ldap_result\(3LDAP\)](#) or [ldap_search_s\(3LDAP\)](#) or [ldap_search_st\(3LDAP\)](#) and returns a pointer to the first entry in the result.

This pointer should be supplied on a subsequent call to `ldap_next_entry()` to get the next entry, the result of which should be supplied to the next call to `ldap_next_entry()`, etc. `ldap_next_entry()` will return NULL when there are no more entries. The entries returned from these calls are used in calls to the functions described in [ldap_get_dn\(3LDAP\)](#), [ldap_first_attribute\(3LDAP\)](#), [ldap_get_values\(3LDAP\)](#), etc.

A count of the number of entries in the search result can be obtained by calling `ldap_count_entries()`.

`ldap_first_reference()` and `ldap_next_reference()` are used to step through and retrieve the list of continuation references from a search result chain.

The `ldap_count_references()` function is used to count the number of references that are contained in and remain in a search result chain.

Errors If an error occurs in `ldap_first_entry()` or `ldap_next_entry()`, NULL is returned and the `ld_errno` field in the *ld* parameter is set to indicate the error. If an error occurs in `ldap_count_entries()`, -1 is returned, and `ld_errno` is set appropriately. See [ldap_error\(3LDAP\)](#) for a description of possible error codes.

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit) SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [ldap\(3LDAP\)](#), [ldap_result\(3LDAP\)](#), [ldap_search\(3LDAP\)](#),
[ldap_first_attribute\(3LDAP\)](#), [ldap_get_values\(3LDAP\)](#), [ldap_get_dn\(3LDAP\)](#),
[attributes\(5\)](#)

Name ldap_first_message, ldap_count_messages, ldap_next_message, ldap_msgtype – LDAP message processing functions

Synopsis cc[*flag...*] *file...* -lldap[*library...*]

```
#include <lber.h>
#include <ldap.h>

int ldap_count_messages(LDAP *ld, LDAPMessage *res);

LDAPMessage *ldap_first_message(LDAP *ld, LDAPMessage *res);

LDAPMessage *ldap_next_message(LDAP *ld, LDAPMessage *msg);

int ldap_msgtype(LDAPMessage *res);
```

Description ldap_count_messages() is used to count the number of messages that remain in a chain of results if called with a message, entry, or reference returned by ldap_first_message(), ldap_next_message(), ldap_first_entry(), ldap_next_entry(), ldap_first_reference(), and ldap_next_reference().

ldap_first_message() and ldap_next_message() functions are used to step through the list of messages in a result chain returned by ldap_result().

ldap_msgtype() function returns the type of an LDAP message.

Return Values ldap_first_message() and ldap_next_message() return LDAPMessage which can include referral messages, entry messages and result messages.

ldap_count_messages() returns the number of messages contained in a chain of results.

Errors ldap_first_message() and ldap_next_message() return NULL when no more messages exist. NULL is also returned if an error occurs while stepping through the entries, in which case the error parameters in the session handle *ld* will be set to indicate the error.

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [ldap_error\(3LDAP\)](#), [ldap_result\(3LDAP\)](#), [attributes\(5\)](#)

Name ldap_friendly, ldap_friendly_name, ldap_free_friendlymap – LDAP attribute remapping functions

Synopsis

```
cc[ flag... ] file... -lldap[ library... ]
#include <lber.h>
#include <ldap.h>
```

```
char *ldap_friendly_name(char *filename, char *name,
    FriendlyMap **map);

void ldap_free_friendlymap(FriendlyMap **map);
```

Description This function is used to map one set of strings to another. Typically, this is done for country names, to map from the two-letter country codes to longer more readable names. The mechanism is general enough to be used with other things, though.

filename is the name of a file containing the unfriendly to friendly mapping, *name* is the unfriendly name to map to a friendly name, and *map* is a result-parameter that should be set to NULL on the first call. It is then used to hold the mapping in core so that the file need not be read on subsequent calls.

For example:

```
FriendlyMap *map = NULL;
printf( "unfriendly %s => friendly %s\n", name,
    ldap_friendly_name( "ETCDIR/ldapfriendly", name, &map ) );
```

The mapping file should contain lines like this: unfriendlyname\tfriendlyname. Lines that begin with a '#' character are comments and are ignored.

The ldap_free_friendlymap() call is used to free structures allocated by ldap_friendly_name() when no more calls to ldap_friendly_name() are to be made.

Errors NULL is returned by ldap_friendly_name() if there is an error opening *filename*, or if the file has a bad format, or if the *map* parameter is NULL.

Files ETCDIR/ldapfriendly.conf

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [ldap\(3LDAP\)](#), [attributes\(5\)](#)

Name ldap_get_dn, ldap_explode_dn, ldap_dn2ufn, ldap_is_dns_dn, ldap_explode_dns, ldap_dns_to_dn – LDAP DN handling functions

Synopsis cc[*flag...*] *file...* -lldap[*library...*]

```
#include <lber.h>
#include <ldap.h>

char *ldap_get_dn(LDAP *ld, LDAPMessage *entry);

char **ldap_explode_dn(char *dn, int notypes);

char *ldap_dn2ufn(char *dn);

int ldap_is_dns_dn(char *dn);

char **ldap_explode_dns(char *dn);

char *ldap_dns_to_dn(char *dns_name, int *nameparts);
```

Description These functions allow LDAP entry names (Distinguished Names, or DN's) to be obtained, parsed, converted to a user-friendly form, and tested. A DN has the form described in RFC 1779 *A String Representation of Distinguished Names*, unless it is an experimental DNS-style DN which takes the form of an RFC 822 mail address.

The `ldap_get_dn()` function takes an *entry* as returned by `ldap_first_entry(3LDAP)` or `ldap_next_entry(3LDAP)` and returns a copy of the entry's DN. Space for the DN will have been obtained by means of `malloc(3C)`, and should be freed by the caller by a call to `free(3C)`.

The `ldap_explode_dn()` function takes a DN as returned by `ldap_get_dn()` and breaks it up into its component parts. Each part is known as a Relative Distinguished Name, or RDN. `ldap_explode_dn()` returns a null-terminated array, each component of which contains an RDN from the DN. The *notypes* parameter is used to request that only the RDN values be returned, not their types. For example, the DN "cn=Bob, c=US" would return as either { "cn=Bob", "c=US", NULL } or { "Bob", "US", NULL }, depending on whether *notypes* was 0 or 1, respectively. The result can be freed by calling `ldap_value_free(3LDAP)`.

`ldap_dn2ufn()` is used to turn a DN as returned by `ldap_get_dn()` into a more user-friendly form, stripping off type names. See RFC 1781 "Using the Directory to Achieve User Friendly Naming" for more details on the UFN format. The space for the UFN returned is obtained by a call to `malloc(3C)`, and the user is responsible for freeing it by means of a call to `free(3C)`.

`ldap_is_dns_dn()` returns non-zero if the dn string is an experimental DNS-style DN (generally in the form of an RFC 822 e-mail address). It returns zero if the dn appears to be an RFC 1779 format DN.

`ldap_explode_dns()` takes a DNS-style DN and breaks it up into its component parts. `ldap_explode_dns()` returns a null-terminated array. For example, the DN "mcs.umich.edu" will return { "mcs", "umich", "edu", NULL }. The result can be freed by calling `ldap_value_free(3LDAP)`.

`ldap_dns_to_dn()` converts a DNS domain name into an X.500 distinguished name. A string distinguished name and the number of nameparts is returned.

Errors If an error occurs in `ldap_get_dn()`, NULL is returned and the `ld_errno` field in the *ld* parameter is set to indicate the error. See [ldap_error\(3LDAP\)](#) for a description of possible error codes. `ldap_explode_dn()`, `ldap_explode_dns()` and `ldap_dn2ufn()` will return NULL with [errno\(3C\)](#) set appropriately in case of trouble.

If an error in `ldap_dns_to_dn()` is encountered zero is returned. The caller should free the returned string if it is non-zero.

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [ldap\(3LDAP\)](#), [ldap_first_entry\(3LDAP\)](#), [ldap_error\(3LDAP\)](#), [ldap_value_free\(3LDAP\)](#)

Notes These functions allocate memory that the caller must free.

Name ldap_get_entry_controls – get the LDAP controls included with a directory entry in a set of search results

Synopsis cc-flag ... *file*...-lldap [-library ...]
#include <ldap.h>

```
int ldap_get_entry_controls(LDAP *ld, LDAPMessage *entry,  
LDAPControl ***serverctrlsp
```

Description The ldap_get_entry_controls() function retrieves the LDAP v3 controls included in a directory entry in a chain of search results. The LDAP controls are specified in an array of LDAPControl structures. Each LDAPControl structure represents an LDAP control. The function takes entry as a parameter, which points to an LDAPMessage structure that represents an entry in a chain of search results.

The entry notification controls that are used with persistent search controls are the only controls that are returned with individual entries. Other controls are returned with results sent from the server. You can call ldap_parse_result() to retrieve those controls.

Errors ldap_get_entry_controls() returns the following error codes.

- LDAP_SUCCESS LDAP controls were successfully retrieved.
- LDAP_DECODING_ERROR An error occurred when decoding the BER-encoded message.
- LDAP_PARAM_ERROR An invalid parameter was passed to the function.
- LDAP_NO_MEMORY Memory cannot be allocated.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [ldap_error\(3LDAP\)](#), [ldap_parse_result\(3LDAP\)](#), [attributes\(5\)](#)

Name ldap_getfilter, ldap_init_getfilter, ldap_init_getfilter_buf, ldap_getfilter_free, ldap_getfirstfilter, ldap_getnextfilter, ldap_setfilteraffixes, ldap_build_filter – LDAP filter generating functions

Synopsis cc[*flag...*] *file...* -lldap[*library...*]

```
#include <lber.h>
#include <ldap.h>
#define LDAP_FILT_MAXSIZ    1024

LDAPFiltDesc *ldap_init_getfilter(char *file);

LDAPFiltDesc *ldap_init_getfilter_buf(char *buf, long buflen);

ldap_getfilter_free(LDAPFiltDesc *lfdp);

LDAPFiltInfo *ldap_getfirstfilter(LDAPFiltDesc *lfdp, char *tagpat,
    char *value);

LDAPFiltInfo *ldap_getnextfilter(LDAPFiltDesc *lfdp);

void ldap_setfilteraffixes(LDAPFiltDesc *lfdp, char *prefix,
    char *suffix);

void ldap_build_filter(char *buf, unsigned long buflen, char *pattern,
    char *prefix, char *suffix, char *attr, char *value,
    char **valwords);
```

Description These functions are used to generate filters to be used in [ldap_search\(3LDAP\)](#) or [ldap_search_s\(3LDAP\)](#). Either `ldap_init_getfilter` or `ldap_init_getfilter_buf` must be called prior to calling any of the other functions except `ldap_build_filter`.

`ldap_init_getfilter()` takes a file name as its only argument. The contents of the file must be a valid LDAP filter configuration file (see [ldapfilter.conf\(4\)](#)). If the file is successfully read, a pointer to an `LDAPFiltDesc` is returned. This is an opaque object that is passed in subsequent get filter calls.

`ldap_init_getfilter_buf()` reads from *buf*, whose length is *buflen*, the LDAP filter configuration information. *buf* must point to the contents of a valid LDAP filter configuration file. See [ldapfilter.conf\(4\)](#). If the filter configuration information is successfully read, a pointer to an `LDAPFiltDesc` is returned. This is an opaque object that is passed in subsequent get filter calls.

`ldap_getfilter_free()` deallocates the memory consumed by `ldap_init_getfilter`. Once it is called, the `LDAPFiltDesc` is no longer valid and cannot be used again.

`ldap_getfirstfilter()` retrieves the first filter that is appropriate for *value*. Only filter sets that have tags that match the regular expression *tagpat* are considered. `ldap_getfirstfilter` returns a pointer to an `LDAPFiltInfo` structure, which contains a filter with *value* inserted as

appropriate in `lfi_filter`, a text match description in `lfi_desc`, `lfi_scope` set to indicate the search scope, and `lfi_isexact` set to indicate the type of filter. NULL is returned if no matching filters are found. `lfi_scope` will be one of LDAP_SCOPE_BASE, LDAP_SCOPE_ONELEVEL, or LDAP_SCOPE_SUBTREE. `lfi_isexact` will be zero if the filter has any '~' or '*' characters in it and non-zero otherwise.

`ldap_getnextfilter()` retrieves the next appropriate filter in the filter set that was determined when `ldap_getfirstfilter` was called. It returns NULL when the list has been exhausted.

`ldap_setfilteraffixes()` sets a *prefix* to be prepended and a *suffix* to be appended to all filters returned in the future.

`ldap_build_filter()` constructs an LDAP search filter in *buf*. *buflen* is the size, in bytes, of the largest filter *buf* can hold. A pattern for the desired filter is passed in *pattern*. Where the string %a appears in the pattern it is replaced with *attr*. *prefix* is pre-pended to the resulting filter, and *suffix* is appended. Either can be NULL, in which case they are not used. *value* and *valwords* are used when the string %v appears in *pattern*. See [ldapfilter.conf\(4\)](#) for a description of how %v is handled.

Errors NULL is returned by `ldap_init_getfilter` if there is an error reading *file*. NULL is returned by `ldap_getfirstfilter` and `ldap_getnextfilter` when there are no more appropriate filters to return.

Files `ETCDIR/ldapfilter.conf` LDAP filtering routine configuration file.

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [ldap\(3LDAP\)](#), [ldapfilter.conf\(4\)](#), [attributes\(5\)](#)

Notes The return values for all of these functions are declared in the `<ldap.h>` header file. Some functions may allocate memory which must be freed by the calling application.

Name ldap_get_lang_values, ldap_get_lang_values_len – return an attribute's values that matches a specified language subtype

Synopsis cc -flag ... *file*...-lldap [-library ...]
#include <ldap.h>

```
char **ldap_get_lang_values(LDAP *ld, LDAPMessage *entry,
                           const char *target, char **type)

struct berval **ldap_get_lang_values_len(LDAP *ld, LDAPMessage *entry,
                                         const char *target, char **type)
```

Description The ldap_get_lang_values() function returns an array of an attribute's string values that matches a specified language subtype. To retrieve the binary data from an attribute, call the ldap_get_lang_values_len() function instead.

ldap_get_lang_values() should be called to retrieve a null-terminated array of an attribute's string values that match a specified language subtype. The *entry* parameter is the entry retrieved from the directory. The *target* parameter should contain the attribute type the values that are required, including the optional language subtype. The *type* parameter points to a buffer that returns the attribute type retrieved by this function. Unlike the ldap_get_values() function, if a language subtype is specified, this function first attempts to find and return values that match that subtype, for example, cn;lang-en.

ldap_get_lang_values_len() returns a null-terminated array of pointers to berval structures, each containing the length and pointer to a binary value of an attribute for a given entry. The *entry* parameter is the result returned by ldap_result() or ldap_search_s() functions. The *target* parameter is the attribute returned by the call to ldap_first_attribute() or ldap_next_attribute(), or the attribute as a literal string, such as jpegPhoto or audio.

These functions are deprecated. Use ldap_get_values() or ldap_get_values_len() instead.

Return Values If successful, ldap_get_lang_values() returns a null-terminated array of the attribute's values. If the call is unsuccessful, or if no such attribute exists in the *entry*, it returns a NULL and sets the appropriate error code in the LDAP structure.

The ldap_get_lang_values_len() function returns a null-terminated array of pointers to berval structures, which in turn, if successful, contain pointers to the attribute's binary values. If the call is unsuccessful, or if no such attribute exists in the *entry*, it returns a NULL and sets the appropriate error code in the LDAP structure.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Obsolete

See Also [ldap_first_attribute\(3LDAP\)](#), [ldap_first_attribute\(3LDAP\)](#),
[ldap_get_values\(3LDAP\)](#), [ldap_result\(3LDAP\)](#), [ldap_search\(3LDAP\)](#), [attributes\(5\)](#)

Name ldap_get_option, ldap_set_option – get or set session preferences in the ldap structure.

Synopsis

```
cc [ flag... ] file... -lldap [ library... ]
#include <lber.h>
#include <ldap.h>
```

```
LDAP ldap_set_option(LDAP *ld, int option, void *optdata[]);
```

```
LDAP ldap_get_option(LDAP *ld, int option, void optdata[]);
```

Description These functions provide an LDAP structure with access to session preferences. The ldap_get_option() function gets session preferences from the LDAP structure. The ldap_set_option() function sets session preferences in the LDAP structure.

The *ld* parameter specifies the connection handle, a pointer to an LDAP structure that contains information about the LDAP server connection. The *option* parameter specifies the name of the option to be read or modified. The *optdata* parameter serves as a pointer to the value of the option that you set or get.

Parameters The following values can be specified for the *option* parameter:

LDAP_OPT_API_INFO

Retrieves basic information about the LDAP API implementation at execution time. The data type for the *optdata* parameter is (LDAPAPIInfo *). This option is READ-ONLY and cannot be set.

LDAP_OPT_DEREF

Determines how aliases are handled during a search. The data type for the *optdata* parameter is (int *). The following values can be specified for the *optdata* parameter:

LDAP_DEREF_NEVER

Specifies that aliases are never dereferenced.

LDAP_DEREF_SEARCHING

Specifies that aliases are dereferenced when searching under the base object, but not when finding the base object.

LDAP_DEREF_FINDING

Specifies that aliases are dereferenced when finding the base object, but not when searching under the base object.

LDAP_DEREF_ALWAYS

Specifies that aliases are always dereferenced when finding the base object

	and searching under the base object.				
LDAP_OPT_SIZELIMIT	Specifies the maximum number of entries returned by the server in search results. The data type for the <i>optdata</i> parameter is (int *). Setting the <i>optdata</i> parameter to LDAP_NO_LIMIT removes any size limit enforced by the client.				
LDAP_OPT_TIMELIMIT	Specifies the maximum number of seconds spent by the server when answering a search request. The data type for the <i>optdata</i> parameter is (int *). Setting the <i>optdata</i> parameter to LDAP_NO_LIMIT removes any time limit enforced by the client.				
LDAP_OPT_REFERRALS	Determines whether the client should follow referrals. The data type for the <i>optdata</i> parameter is (int *). The following values can be specified for the <i>optdata</i> parameter: <table><tr><td>LDAP_OPT_ON</td><td>Specifies that the client should follow referrals.</td></tr><tr><td>LDAP_OPT_OFF</td><td>Specifies that the client should not follow referrals.</td></tr></table> By default, the client follows referrals.	LDAP_OPT_ON	Specifies that the client should follow referrals.	LDAP_OPT_OFF	Specifies that the client should not follow referrals.
LDAP_OPT_ON	Specifies that the client should follow referrals.				
LDAP_OPT_OFF	Specifies that the client should not follow referrals.				
LDAP_OPT_RESTART	Determines whether LDAP I/O operations are automatically restarted if aborted prematurely. It can be set to one of the constants LDAP_OPT_ON or LDAP_OPT_OFF.				
LDAP_OPT_PROTOCOL_VERSION	Specifies the version of the protocol supported by the client. The data type for the <i>optdata</i> parameter is (int *). The version LDAP_VERSION2 or LDAP_VERSION3 can be specified. If no version is set, the default version LDAP_VERSION2 is set. To use LDAP v3 features, set the protocol version to LDAP_VERSION3.				
LDAP_OPT_SERVER_CONTROLS	Specifies a pointer to an array of LDAPControl structures that represent the LDAP v3 server controls sent by default with every request. The data type for the <i>optdata</i> parameter for ldap_set_option() is (LDAPControl **). For ldap_get_option(), the data type is (LDAPControl ***).				

LDAP_OPT_CLIENT_CONTROLS	Specifies a pointer to an array of LDAPControl structures that represent the LDAP v3 client controls sent by default with every request. The data type for the <i>optdata</i> parameter for <code>ldap_set_option()</code> is (LDAPControl **). For <code>ldap_get_option()</code> , the data type is (LDAPControl ***).
LDAP_OPT_API_FEATURE_INFO	Retrieves version information at execution time about extended features of the LDAP API. The data type for the <i>optdata</i> parameter is (LDAPAPIFeatureInfo *). This option is READ-ONLY and cannot be set.
LDAP_OPT_HOST_NAME	Sets the host name or a list of hosts for the primary LDAP server. The data type for the <i>optdata</i> parameter for <code>ldap_set_option()</code> is (char *). For <code>ldap_get_option()</code> , the data type is (char **).
LDAP_OPT_ERROR_NUMBER	Specifies the code of the most recent LDAP error that occurred for this session. The data type for the <i>optdata</i> parameter is (int *).
LDAP_OPT_ERROR_STRING	Specifies the message returned with the most recent LDAP error that occurred for this session. The data type for the <i>optdata</i> parameter for <code>ldap_set_option()</code> is (char *) and for <code>ldap_get_option()</code> is (char **).
LDAP_OPT_MATCHED_DN	Specifies the matched DN value returned with the most recent LDAP error that occurred for this session. The data type for the <i>optdata</i> parameter for <code>ldap_set_option()</code> is (char *) and for <code>ldap_get_option()</code> is (char **).
LDAP_OPT_REBIND_ARG	Sets the last argument passed to the routine specified by LDAP_OPT_REBIND_FN. This option can also be set by calling the <code>ldap_set_rebind_proc()</code> function. The data type for the <i>optdata</i> parameter is (void *).
LDAP_OPT_REBIND_FN	Sets the routine to be called to authenticate a connection with another LDAP server. For example, the option is used to set the routine called during the course of a referral. This option can also be by calling the <code>ldap_set_rebind_proc()</code> function. The data type for the <i>optdata</i> parameter is (LDAP_REBINDPROC_CALLBACK *).

LDAP_OPT_X_SASL_MECH	Sets the default SASL mechanism to call <code>ldap_interactive_bind_s()</code> . The data type for the <i>optdata</i> parameter is <code>(char *)</code> .
LDAP_OPT_X_SASL_REALM	Sets the default SASL_REALM. The default SASL_REALM should be used during a SASL challenge in response to a SASL_CB_GETREALM request when using the <code>ldap_interactive_bind_s()</code> function. The data type for the <i>optdata</i> parameter is <code>(char *)</code> .
LDAP_OPT_X_SASL_AUTHCID	Sets the default SASL_AUTHNAME used during a SASL challenge in response to a SASL_CB_AUTHNAME request when using the <code>ldap_interactive_bind_s()</code> function. The data type for the <i>optdata</i> parameter is <code>(char *)</code> .
LDAP_OPT_X_SASL_AUTHZID	Sets the default SASL_USER that should be used during a SASL challenge in response to a SASL_CB_USER request when using the <code>ldap_interactive_bind_s</code> function. The data type for the <i>optdata</i> parameter is <code>(char *)</code> .
LDAP_OPT_X_SASL_SSF	A read-only option used exclusively with the <code>ldap_get_option()</code> function. The <code>ldap_get_option()</code> function performs a <code>sasl_getprop()</code> operation that gets the SASL_SSF value for the current connection. The data type for the <i>optdata</i> parameter is <code>(sasl_ssf_t *)</code> .
LDAP_OPT_X_SASL_SSF_EXTERNAL	A write-only option used exclusively with the <code>ldap_set_option()</code> function. The <code>ldap_set_option()</code> function performs a <code>sasl_setprop()</code> operation to set the SASL_SSF_EXTERNAL value for the current connection. The data type for the <i>optdata</i> parameter is <code>(sasl_ssf_t *)</code> .
LDAP_OPT_X_SASL_SECPROPS	A write-only option used exclusively with the <code>ldap_set_option()</code> . This function performs a sasl_setprop(3SASL) operation for the SASL_SEC_PROPS value for the current connection during an <code>ldap_interactive_bind_s()</code> operation. The data type for the <i>optdata</i> parameter is <code>(char *)</code> , a comma delimited string containing text values for any of the SASL_SEC_PROPS that should be set. The text values are:

	noanonymous	Sets the SASL_SEC_NOANONYMOUS flag
	nodict	Sets the SASL_SEC_NODICTIONARY flag
	noplain	Sets the SASL_SEC_NOPLAINTEXT flag
	forwardsec	Sets the SASL_SEC_FORWARD_SECRECY flag
	passcred	Sets the SASL_SEC_PASS_CREDENTIALS flag
	minssf=N	Sets minssf to the integer value N
	maxssf=N	Sets maxssf to the integer value N
	maxbufsize=N	Sets maxbufsize to the integer value N
LDAP_OPT_X_SASL_SSF_MIN		Sets the default SSF_MIN value used during a <code>ldap_interactive_bind_s()</code> operation. The data type for the <i>optdata</i> parameter is (char *) numeric string.
LDAP_OPT_X_SASL_SSF_MAX		Sets the default SSF_MAX value used during a <code>ldap_interactive_bind_s()</code> operation. The data type for the <i>optdata</i> parameter is (char *) numeric string.
LDAP_OPT_X_SASL_MAXBUFSIZE		Sets the default SSF_MAXBUFSIZE value used during a <code>ldap_interactive_bind_s()</code> operation. The data type for the <i>optdata</i> parameter is (char *) numeric string.

Return Values The `ldap_set_option()` and `ldap_get_option()` functions return:

LDAP_SUCCESS	If successful
-1	If unsuccessful

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Evolving
MT-Level	Safe

See Also [ldap_init\(3LDAP\)](#), [sasl_setprop\(3SASL\)](#), [attributes\(5\)](#)

Notes There are other elements in the LDAP structure that should not be changed. No assumptions should be made about the order of elements in the LDAP structure.

Name ldap_get_values, ldap_get_values_len, ldap_count_values, ldap_count_values_len, ldap_value_free, ldap_value_free_len – LDAP attribute value handling functions

Synopsis cc[*flag...*] *file...* -lldap[*library...*]

```
#include <lber.h>
#include <ldap.h>

char **ldap_get_values(LDAP *ld, LDAPMessage *entry, char *attr);

struct berval **ldap_get_values_len(LDAP *ld, LDAPMessage *entry,
    char *attr);

ldap_count_values(char **vals);

ldap_count_values_len(struct berval **vals);

ldap_value_free(char **vals);

ldap_value_free_len(struct berval **vals);
```

Description These functions are used to retrieve and manipulate attribute values from an LDAP entry as returned by [ldap_first_entry\(3LDAP\)](#) or [ldap_next_entry\(3LDAP\)](#). `ldap_get_values()` takes the *entry* and the attribute *attr* whose values are desired and returns a null-terminated array of the attribute's values. *attr* may be an attribute type as returned from [ldap_first_attribute\(3LDAP\)](#) or [ldap_next_attribute\(3LDAP\)](#), or if the attribute type is known it can simply be given.

The number of values in the array can be counted by calling `ldap_count_values()`. The array of values returned can be freed by calling `ldap_value_free()`.

If the attribute values are binary in nature, and thus not suitable to be returned as an array of `char *`'s, the `ldap_get_values_len()` function can be used instead. It takes the same parameters as `ldap_get_values()`, but returns a null-terminated array of pointers to `berval` structures, each containing the length of and a pointer to a value.

The number of values in the array can be counted by calling `ldap_count_values_len()`. The array of values returned can be freed by calling `ldap_value_free_len()`.

Errors If an error occurs in `ldap_get_values()` or `ldap_get_values_len()`, NULL returned and the `ld_errno` field in the `ld` parameter is set to indicate the error. See [ldap_error\(3LDAP\)](#) for a description of possible error codes.

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)

ATTRIBUTE TYPE	ATTRIBUTE VALUE
	SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [ldap\(3LDAP\)](#), [ldap_first_entry\(3LDAP\)](#), [ldap_first_attribute\(3LDAP\)](#), [ldap_error\(3LDAP\)](#), [attributes\(5\)](#)

Notes These functions allocates memory that the caller must free.

Name ldap_memcache, ldap_memcache_init, ldap_memcache_set, ldap_memcache_get, ldap_memcache_flush, ldap_memcache_destroy, ldap_memcache_update – LDAP client caching functions

Synopsis `cc -flag ... file...-lldap [-library ...]
#include <ldap.h>`

```
int ldap_memcache_init(unsigned long ttl, unsigned long size,
    char **baseDNs, struct ldap_thread_fns *thread_fns,
    LDAPMemCache **cachep)

int ldap_memcache_set(LDAP *ld, LDAPMemCache **cache)

int ldap_memcache_get(LDAP *ld, LDAPMemCache **cachep)

void ldap_memcache_flush(LDAPMemCache *cache, char *dn, int scope)

void ldap_memcache_destroy(LDAPMemCache *cache)

void ldap_memcache_update(LDAPMemCache *cache)
```

Description Use the `ldap_memcache` functions to maintain an in-memory client side cache to store search requests. Caching improves performance and reduces network bandwidth when a client makes repeated requests. The *cache* uses search criteria as the key to the cached items. When you send a search request, the *cache* checks the search criteria to determine if that request has been previously stored. If the request was stored, the search results are read from the *cache*.

Make a call to `ldap_memcache_init()` to create the in-memory client side *cache*. The function passes back a pointer to an `LDAPMemCache` structure, which represents the *cache*. Make a call to the `ldap_memcache_set()` function to associate this *cache* with an LDAP connection handle, an LDAP structure. *ttl* is the the maximum amount of time (in seconds) that an item can be cached. If a *ttl* value of 0 is passed, there is no limit to the amount of time that an item can be cached. *size* is the maximum amount of memory (in bytes) that the cache will consume. A zero value of *size* means the cache has no size limit. *baseDNS* is an array of the base DN strings representing the base DN's of the search requests you want cached. If *baseDNS* is not NULL, only the search requests with the specified base DN's will be cached. If *baseDNS* is NULL, all search requests are cached. The *thread_fns* parameter takes an `ldap_thread_fns` structure specifying the functions that you want used to ensure that the cache is thread-safe. You should specify this if you have multiple threads that are using the same connection handle and cache. If you are not using multiple threads, pass NULL for this parameter.

`ldap_memcache_set()` associates an in-memory *cache* that you have already created by calling the `ldap_memcache_init()` function with an LDAP connection handle. The *ld* parameter should be the result of a successful call to `ldap_open(3LDAP)`. The *cache* parameter should be the result of a *cache* created by the `ldap_memcache_init()` call. After you call this function, search requests made over the specified LDAP connection will use this cache. To disassociate the cache from the LDAP connection handle, make a call to the `ldap_bind(3LDAP)` or

`ldap_bind(3LDAP)` function. Make a call to `ldap_memcache_set()` if you want to associate a cache with multiple LDAP connection handles. For example, call the `ldap_memcache_get()` function to get the *cache* associated with one connection, then you can call this function and associate the *cache* with another connection.

The `ldap_memcache_get()` function gets the *cache* associated with the specified connection handle (LDAP structure). This *cache* is used by all search requests made through that connection. When you call this function, the function sets the *cachep* parameter as a pointer to the LDAPMemCache structure that is associated with the connection handle.

`ldap_memcache_flush()` flushes search requests from the *cache*. If the base DN of a search request is within the scope specified by the *dn* and *scope* arguments, the search request is flushed from the *cache*. If no DN is specified, the entire cache is flushed. The *scope* parameter, along with the *dn* parameter, identifies the search requests that you want flushed from the *cache*. This argument can have one of the following values:

LDAP_SCOPE_BASE
LDAP_SCOPE_ONELEVEL
LDAP_SCOPE_SUBTREE

`ldap_memcache_destroy()` frees the specified LDAPMemCache structure pointed to by *cache* from memory. Call this function after you are done working with a *cache*.

`ldap_memcache_update()` checks the cache for items that have expired and removes them. This check is typically done as part of the way the *cache* normally works. You do not need to call this function unless you want to update the *cache* at this point in time. This function is only useful in a multithreaded application, since it will not return until the *cache* is destroyed.

Parameters	<i>ttl</i>	The maximum amount of time (in seconds) that an item can be cached
	<i>size</i>	The maximum amount of memory (in bytes) that the cache will consume.
	<i>baseDNs</i>	An array of the base DN strings representing the base DN's of the search requests you want cached
	<i>thread_fns</i>	A pointer to the <code>ldap_thread_fns</code> structure.
	<i>cachep</i>	A pointer to the LDAPMemCache structure
	<i>cache</i>	The result of a <i>cache</i> created by the <code>ldap_memcache_init()</code> call
	<i>ld</i>	The result of a successful call to <code>ldap_open(3LDAP)</code>
	<i>dn</i>	The search requests that you want flushed from the <i>cache</i>
	<i>scope</i>	The search requests that you want flushed from the <i>cache</i>

Errors The functions that have int return values return LDAP_SUCCESS if the operation was successful. Otherwise, they return another LDAP error code. See [ldap_error\(3LDAP\)](#) for a list of the LDAP error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [ldap_error\(3LDAP\)](#), [ldap_open\(3LDAP\)](#), [ldap_search\(3LDAP\)](#), [attributes\(5\)](#)

Name ldap_memfree – free memory allocated by LDAP API functions

Synopsis

```
cc -flag ... file ...-lldap [ -library ... ]
#include < lber.h>
#include < ldap.h>
```

```
void ldap_memfree(void *p
```

Description The ldap_memfree() function frees the memory allocated by certain LDAP API functions that do not have corresponding functions to free memory. These functions include [ldap_get_dn\(3LDAP\)](#), [ldap_first_attribute\(3LDAP\)](#), and [ldap_next_attribute\(3LDAP\)](#).

The ldap_memfree() function takes one parameter, *p*, which is a pointer to the memory to be freed.

Parameters *p* A pointer to the memory to be freed.

Return Values There are no return values for the ldap_memfree() function.

Errors No errors are defined for the ldap_memfree() function.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [ldap\(3LDAP\)](#), [ldap_first_attribute\(3LDAP\)](#), [ldap_get_dn\(3LDAP\)](#), [ldap_next_attribute\(3LDAP\)](#), [attributes\(5\)](#)

Name ldap_modify, ldap_modify_s, ldap_mods_free, ldap_modify_ext, ldap_modify_ext_s – LDAP entry modification functions

Synopsis cc[*flag...*] *file...* -lldap[*library...*]

```
#include <lber.h>
#include <ldap.h>

int ldap_modify(LDAP *ld, char *dn, LDAPMod *mods[]);
int ldap_modify_s(LDAP *ld, char *dn, LDAPMod *mods[]);
void ldap_mods_free(LDAPMod **mods, int freemods);
int ldap_modify_ext(LDAP *ld, char *dn, LDAPMod **mods,
    LDAPControl **serverctrls, LDAPControl **clientctrls, int *msgidp);
int ldap_modify_ext_s(LDAP *ld, char *dn, LDAPMod **mods,
    LDAPControl **serverctrls, LDAPControl **clientctrls);
```

Description The function `ldap_modify_s()` is used to perform an LDAP modify operation. *dn* is the DN of the entry to modify, and *mods* is a null-terminated array of modifications to make to the entry. Each element of the *mods* array is a pointer to an LDAPMod structure, which is defined below.

```
typedef struct ldapmod {
    int mod_op;
    char *mod_type;
    union {
        char **modv_strvals;
        struct berval **modv_bvals;
    } mod_vals;
} LDAPMod;
#define mod_values mod_vals.modv_strvals
#define mod_bvalues mod_vals.modv_bvals
```

The *mod_op* field is used to specify the type of modification to perform and should be one of LDAP_MOD_ADD, LDAP_MOD_DELETE, or LDAP_MOD_REPLACE. The *mod_type* and *mod_values* fields specify the attribute type to modify and a null-terminated array of values to add, delete, or replace respectively.

If you need to specify a non-string value (for example, to add a photo or audio attribute value), you should set *mod_op* to the logical OR of the operation as above (for example, LDAP_MOD_REPLACE) and the constant LDAP_MOD_BVALUES. In this case, *mod_bvalues* should be used instead of *mod_values*, and it should point to a null-terminated array of struct bervals, as defined in `<lber.h>`.

For LDAP_MOD_ADD modifications, the given values are added to the entry, creating the attribute if necessary. For LDAP_MOD_DELETE modifications, the given values are deleted from the entry, removing the attribute if no values remain. If the entire attribute is to be deleted, the

mod_values field should be set to NULL. For LDAP_MOD_REPLACE modifications, the attribute will have the listed values after the modification, having been created if necessary. All modifications are performed in the order in which they are listed.

`ldap_modify_s()` returns the LDAP error code resulting from the modify operation.

The `ldap_modify()` operation works the same way as `ldap_modify_s()`, except that it is asynchronous, returning the message id of the request it initiates, or `-1` on error. The result of the operation can be obtained by calling `ldap_result(3LDAP)`.

`ldap_mods_free()` can be used to free each element of a null-terminated array of mod structures. If *freemods* is non-zero, the *mods* pointer itself is freed as well.

The `ldap_modify_ext()` function initiates an asynchronous modify operation and returns LDAP_SUCCESS if the request was successfully sent to the server, or else it returns a LDAP error code if not. See `ldap_error(3LDAP)`. If successful, `ldap_modify_ext()` places the message id of the request in **msgidp*. A subsequent call to `ldap_result(3LDAP)`, can be used to obtain the result of the add request.

The `ldap_modify_ext_s()` function initiates a synchronous modify operation and returns the result of the operation itself.

Errors `ldap_modify_s()` returns an LDAP error code, either LDAP_SUCCESS or an error. See `ldap_error(3LDAP)`.

`ldap_modify()` returns `-1` in case of trouble, setting the error field of *ld*.

Attributes See `attributes(5)` for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit) SUNWcslx (64-bit)
Interface Stability	Evolving

See Also `ldap(3LDAP)`, `ldap_add(3LDAP)`, `ldap_error(3LDAP)`, `ldap_get_option(3LDAP)`, `attributes(5)`

Name ldap_modrdn, ldap_modrdn_s, ldap_modrdn2, ldap_modrdn2_s, ldap_rename, ldap_rename_s – modify LDAP entry RDN

Synopsis cc[*flag...*] *file...*-l ldap [*library...*]

```
#include <lber.h>
#include <ldap.h>

int ldap_modrdn(LDAP *ld, const char *dn, const char *newrdn);

int ldap_modrdn_s(LDAP *ld, const char *dn, const char *newrdn,
                  int deleteoldrdn);

int ldap_modrdn2(LDAP *ld, const char *dn, const char *newrdn,
                  int deleteoldrdn);

int ldap_modrdn2_s(LDAP *ld, const char *dn,
                   const char *newrdn, int deleteoldrdn);

int ldap_rename(LDAP *ld, const char *dn, const char *newrdn,
                const char *newparent, int deleteoldrdn,
                LDAPControl **serverctrls, LDAPControl **clientctrls,
                int *msgidp);

int ldap_rename_s(LDAP *ld, const char *dn, const char *newrdn,
                  const char *newparent, const int deleteoldrdn,
                  LDAPControl **serverctrls, LDAPControl **clientctrls);
```

Description The ldap_modrdn() and ldap_modrdn_s() functions perform an LDAP modify RDN (Relative Distinguished Name) operation. They both take *dn*, the DN (Distinguished Name) of the entry whose RDN is to be changed, and *newrdn*, the new RDN, to give the entry. The old RDN of the entry is never kept as an attribute of the entry. ldap_modrdn() is asynchronous. It return the message id of the operation it initiates. ldap_modrdn_s() is synchronous. It returns the LDAP error code that indicates the success or failure of the operation.

The ldap_modrdn2() and ldap_modrdn2_s() functions also perform an LDAP modify RDN operation. They take the same parameters as above. In addition, they both take the *deleteoldrdn* parameter, which is used as a boolean value to indicate whether or not the old RDN values should be deleted from the entry.

The ldap_rename(), ldap_rename_s() routines are used to change the name, that is, the RDN of an entry. These routines deprecate the ldap_modrdn() and ldap_modrdn_s() routines, as well as ldap_modrdn2() and ldap_modrdn2_s().

The ldap_rename() and ldap_rename_s() functions both support LDAPv3 server controls and client controls.

Errors The synchronous (_s) versions of these functions return an LDAP error code, either LDAP_SUCCESS or an error. See [ldap_error\(3LDAP\)](#).

The asynchronous versions return `-1` in the event of an error, setting the `ld_errno` field of *ld*. See [ldap_error\(3LDAP\)](#) for more details. Use [ldap_result\(3LDAP\)](#) to determine a particular unsuccessful result.

Attributes See [attributes\(5\)](#) for a description of the following attributes of the `ldap_modrdn()`, `ldap_modrdn_s()`, `ldap_modrdn2()` and `ldap_modrdn2_s()` functions:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit) SUNWcslx (64-bit)
Interface Stability	Obsolete

The `ldap_rename()` and `ldap_rename_s()` functions have the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit) SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [ldap\(3LDAP\)](#), [ldap_error\(3LDAP\)](#), [attributes\(5\)](#)

Name ldap_open, ldap_init – initialize an LDAP session

Synopsis

```
cc [ flag... ] file... -lldap [ library... ]
#include <lber.h>
#include <ldap.h>
```

```
LDAP *ldap_open(const char *host, int port);
```

```
LDAP *ldap_init(const char *host, int port);
```

Description The `ldap_open()` function initializes an LDAP session and also opens a connection to an LDAP server before it returns to the caller. Unlike `ldap_open()`, `ldap_init()` does not open a connection to the LDAP server until an operation, such as a search request, is performed.

The `ldap_open()` function is deprecated and should no longer be used. Call `ldap_init()` instead.

A list of LDAP hostnames or an IPv4 or IPv6 address can be specified with the `ldap_open()` and `ldap_init()` functions. The hostname can include a port number, separated from the hostname by a colon (:). A port number included as part of the hostname takes precedence over the `port` parameter. The `ldap_open()` and `ldap_init()` functions attempt connections with LDAP hosts in the order listed and return the first successful connection.

Parameters These functions support the following parameters.

host The hostname, IPv4 or IPv6 address of the host that runs the LDAP server. A space-separated list of hostnames can also be used for this parameter.

port TCP port number of a connection. Supply the constant `LDAP_PORT` to obtain the default LDAP port of 389. If a host includes a port number, the default parameter is ignored.

Return Values The `ldap_open()` and `ldap_init()` functions return a handle to an LDAP session that contains a pointer to an opaque structure. The structure must be passed to subsequent calls for the session. If a session cannot be initialized, the functions return `NULL` and `errno` should be set appropriately.

Various aspects of this opaque structure can be read or written to control the session-wide parameters. Use the [ldap_get_option\(3LDAP\)](#) to access the current option values and the [ldap_set_option\(3LDAP\)](#) to set values for these options.

Examples **EXAMPLE 1** Specifying IPv4 and IPv6 Addresses

LDAP sessions can be initialized with hostnames, IPv4 or IPv6 addresses, such as those shown in the following examples.

```
ldap_init("hosta:636 hostb", 389)
ldap_init("192.168.82.110:389", 389)
ldap_init("[fec0::114:a00:20ff:ab3d:83ed]", 389)
```

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Evolving
MT-Level	Safe

See Also [errno\(3C\)](#), [ldap\(3LDAP\)](#), [ldap_bind\(3LDAP\)](#), [ldap_get_option\(3LDAP\)](#), [ldap_set_option\(3LDAP\)](#), [attributes\(5\)](#)

Name ldap_parse_result, ldap_parse_extended_result, ldap_parse_sasl_bind_result – LDAP message result parser

Synopsis cc[*flag...*] *file...* -lldap[*library...*]

```
#include <lber.h>
#include <ldap.h>

int ldap_parse_result(LDAP *ld, LDAPMessage *res, int *errcodep,
    char **matcheddn, char **errmsgp, char ***referralsp,
    LDAPControl ***serverctrlsp, int freeit);

int ldap_parse_sasl_bind_result(LDAP *ld, LDAPMessage *res,
    struct berval **servercredp, int freeit);

int ldap_parse_extended_result(LDAP *ld, LDAPMessage *res,
    struct bervalchar **resultoidp, **resultdata, int freeit);
```

Description The ldap_parse_extended_result(), ldap_parse_result() and ldap_parse_sasl_bind_result() routines search for a message to parse. These functions skip messages of type LDAP_RES_SEARCH_ENTRY and LDAP_RES_SEARCH_REFERENCE.

Return Values They return LDAP_SUCCESS if the result was successfully parsed or an LDAP error code if not (see ldap_error(3LDAP)).

Attributes See attributes(5) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Evolving

See Also ldap_error(3LDAP), ldap_result(3LDAP), attributes(5)

Name ldap_result, ldap_msgfree – wait for and return LDAP operation result

Synopsis

```
cc[ flag... ] file... -lldap[ library... ]
#include <lber.h>
#include <ldap.h>

int ldap_result(LDAP *ld, int msgid, int all,
               struct timeval *timeout, LDAPMessage **result);

int ldap_msgfree(LDAPMessage *msg);
```

Description The `ldap_result()` function is used to wait for and return the result of an operation previously initiated by one of the LDAP asynchronous operation functions, for example, [ldap_search\(3LDAP\)](#), and [ldap_modify\(3LDAP\)](#). Those functions all return `-1` in case of error, and an invocation identifier upon successful initiation of the operation. The invocation identifier is picked by the library and is guaranteed to be unique across the LDAP session. It can be used to request the result of a specific operation from `ldap_result()` through the `msgid` parameter.

The `ldap_result()` function will block or not, depending upon the setting of the `timeout` parameter. If `timeout` is not a null pointer, it specifies a maximum interval to wait for the selection to complete. If `timeout` is a null pointer, the select blocks indefinitely. To effect a poll, the `timeout` argument should be a non-null pointer, pointing to a zero-valued `timeval` structure. See [select\(3C\)](#) for further details.

If the result of a specific operation is required, `msgid` should be set to the invocation identifier returned when the operation was initiated, otherwise `LDAP_RES_ANY` should be supplied. The `all` parameter only has meaning for search responses and is used to select whether a single entry of the search response should be returned, or all results of the search should be returned.

A search response is made up of zero or more search entries followed by a search result. If `all` is set to 0, search entries will be returned one at a time as they come in, by means of separate calls to `ldap_result()`. If it is set to a non-zero value, the search response will only be returned in its entirety, that is, after all entries and the final search result have been received.

Upon success, the type of the result received is returned and the `result` parameter will contain the result of the operation. This result should be passed to the LDAP parsing functions, (see [ldap_first_entry\(3LDAP\)](#)) for interpretation.

The possible result types returned are:

```
#define LDAP_RES_BIND          0x61L
#define LDAP_RES_SEARCH_ENTRY  0x64L
#define LDAP_RES_SEARCH_RESULT 0x65L
#define LDAP_RES_MODIFY        0x67L
#define LDAP_RES_ADD           0x69L
#define LDAP_RES_DELETE        0x6bL
#define LDAP_RES_MODRDN        0x6dL
#define LDAP_RES_COMPARE       0x6fL
```

The `ldap_msgfree()` function is used to free the memory allocated for a result by `ldap_result()` or `ldap_search_s(3LDAP)` functions. It takes a pointer to the result to be freed and returns the type of the message it freed.

Errors The `ldap_result()` function returns `-1` on error and `0` if the specified timeout was exceeded.

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Committed

See Also [select\(1\)](#), [ldap\(3LDAP\)](#), [ldap_search\(3LDAP\)](#), [attributes\(5\)](#)

Notes The `ldap_result()` function allocates memory for results that it receives. The memory can be freed by calling `ldap_msgfree`.

Name ldap_search, ldap_search_s, ldap_search_ext, ldap_search_ext_s, ldap_search_st – LDAP search operations

Synopsis

```
cc [ flag... ] file... -lldap[ library...]
#include <sys/time.h> /* for struct timeval definition */
#include <lber.h>
#include <ldap.h>

int ldap_search(LDAP *ld, char *base, int scope, char *filter,
               char *attrs[], int attrsonly);

int ldap_search_s(LDAP *ld, char *base, int scope, char *filter,
                 char *attrs[], int attrsonly, LDAPMessage **res);

int ldap_search_st(LDAP *ld, char *base, int scope, char *filter,
                  char *attrs[], int attrsonly, struct timeval *timeout,
                  LDAPMessage **res);

int ldap_search_ext(LDAP *ld, char *base, int scope, char
                  *filter, char **attrs, int attrsonly, LDAPControl **serverctrls,
                  LDAPControl **clientctrls, struct timeval *timeoutp,
                  int sizelimit, int *msgidp);

int ldap_search_ext_s(LDAP *ld, char *base, int scope, char *filter,
                     char **attrs, int attrsonly, LDAPControl **serverctrls,
                     LDAPControl **clientctrls, struct timeval *timeoutp,
                     int sizelimit, LDAPMessage **res);
```

Description These functions are used to perform LDAP search operations. The `ldap_search_s()` function does the search synchronously (that is, not returning until the operation completes). The `ldap_search_st()` function does the same, but allows a *timeout* to be specified. The `ldap_search()` function is the asynchronous version, initiating the search and returning the message ID of the operation it initiated.

The *base* is the DN of the entry at which to start the search. The *scope* is the scope of the search and should be one of `LDAP_SCOPE_BASE`, to search the object itself, `LDAP_SCOPE_ONELEVEL`, to search the object's immediate children, or `LDAP_SCOPE_SUBTREE`, to search the object and all its descendents.

The *filter* is a string representation of the filter to apply in the search. Simple filters can be specified as *attributetype=attributevalue*. More complex filters are specified using a prefix notation according to the following BNF:

```
<filter> ::= '(' <filtercomp> ')'  
<filtercomp> ::= <and> | <or> | <not> | <simple>  
<and> ::= '&' <filterlist>  
<or> ::= '|' <filterlist>  
<not> ::= '!' <filter>  
<filterlist> ::= <filter> | <filter> <filterlist>  
<simple> ::= <attributetype> <filtertype> <attributevalue>  
<filtertype> ::= '=' | '~=' | '<=' | '>='
```


The '~=' construct is used to specify approximate matching. The representation for <attributetype> and <attributevalue> are as described in RFC 1778. In addition, <attributevalue> can be a single * to achieve an attribute existence test, or can contain text and *'s interspersed to achieve substring matching.

For example, the filter `mail=*` finds entries that have a mail attribute. The filter `mail=*@terminator.rs.itd.umich.edu` finds entries that have a mail attribute ending in the specified string. Use a backslash (\) to escape parentheses characters in a filter. See RFC 1588 for a more complete description of the filters that are allowed. See [ldap_getfilter\(3LDAP\)](#) for functions to help construct search filters automatically.

The *attrs* is a null-terminated array of attribute types to return from entries that match *filter*. If NULL is specified, all attributes are returned. The *attrsonly* is set to 1 when attribute types only are wanted. The *attrsonly* is set to 0 when both attributes types and attribute values are wanted.

The *sizelimit* argument returns the number of matched entries specified for a search operation. When *sizelimit* is set to 50, for example, no more than 50 entries are returned. When *sizelimit* is set to 0, all matched entries are returned. The LDAP server can be configured to send a maximum number of entries, different from the size limit specified. If 5000 entries are matched in the database of a server configured to send a maximum number of 500 entries, no more than 500 entries are returned even when *sizelimit* is set to 0.

The `ldap_search_ext()` function initiates an asynchronous search operation and returns LDAP_SUCCESS when the request is successfully sent to the server. Otherwise, `ldap_search_ext()` returns an LDAP error code. See [ldap_error\(3LDAP\)](#). If successful, `ldap_search_ext()` places the message ID of the request in **msgidp*. A subsequent call to [ldap_result\(3LDAP\)](#) can be used to obtain the result of the add request.

The `ldap_search_ext_s()` function initiates a synchronous search operation and returns the result of the operation itself.

Errors The `ldap_search_s()` and `ldap_search_st()` functions return the LDAP error code that results from a search operation. See [ldap_error\(3LDAP\)](#) for details.

The `ldap_search()` function returns -1 when the operation terminates unsuccessfully.

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTETYPE	ATTRIBUTE VALUE
Interface Stability	Evolving

See Also [ldap\(3LDAP\)](#), [ldap_result\(3LDAP\)](#), [ldap_getfilter\(3LDAP\)](#), [ldap_error\(3LDAP\)](#), [attributes\(5\)](#)

Howes, T., Kille, S., Yeong, W., Robbins, C., Wenn, J. *RFC 1778, The String Representation of Standard Attribute Syntaxes*. Network Working Group. March 1995.

Postel, J., Anderson, C. *RFC 1588, White Pages Meeting Report*. Network Working Group. February 1994.

Notes The read and list functionality are subsumed by `ldap_search()` functions, when a filter such as `objectclass=*` is used with the scope `LDAP_SCOPE_BASE` to emulate read or the scope `LDAP_SCOPE_ONELEVEL` to emulate list.

The `ldap_search()` functions may allocate memory which must be freed by the calling application. Return values are contained in `<ldap.h>`.

Name ldap_searchprefs, ldap_init_searchprefs, ldap_init_searchprefs_buf, ldap_free_searchprefs, ldap_first_searchobj, ldap_next_searchobj – LDAP search preference configuration routines

Synopsis cc[*flag...*] *file...* -lldap[*library...*]

```
# include <lber.h>
# include <ldap.h>

int ldap_init_searchprefs(char **file,
    struct ldap_searchobj ***solistp);

int ldap_init_searchprefs_buf(char **buf, unsigned longlen,
    struct ldap_searchobj ***solistp);

struct ldap_searchobj **ldap_free_searchprefs
    (struct ldap_searchobj ***solist);

struct ldap_searchobj **ldap_first_searchobj
    (struct ldap_searchobj ***solist);

struct ldap_searchobj **ldap_next_searchobj
    (struct ldap_searchobj ***solist, struct ldap_searchobj **so);
```

Description These functions provide a standard way to access LDAP search preference configuration data. LDAP search preference configurations are typically used by LDAP client programs to specify which attributes a user may search by, labels for the attributes, and LDAP filters and scopes associated with those searches. Client software presents these choices to a user, who can then specify the type of search to be performed.

ldap_init_searchprefs() reads a sequence of search preference configurations from a valid LDAP searchpref configuration file. See [ldapsearchprefs.conf\(4\)](#). Upon success, 0 is returned and *solistp* is set to point to a list of search preference data structures.

ldap_init_searchprefs_buf() reads a sequence of search preference configurations from *buf*, whose size is *buflen*. *buf* should point to the data in the format defined for an LDAP search preference configuration file. See [ldapsearchprefs.conf\(4\)](#). Upon success, 0 is returned and *solistp* is set to point to a list of search preference data structures.

ldap_free_searchprefs() disposes of the data structures allocated by ldap_init_searchprefs().

ldap_first_searchpref() returns the first search preference data structure in the list *solist*. The *solist* is typically obtained by calling ldap_init_searchprefs().

ldap_next_searchpref() returns the search preference after *so* in the template list *solist*. A NULL pointer is returned if *so* is the last entry in the list.

Errors `ldap_init_search_prefs()` and `ldap_init_search_prefs_bufs()` return:

`LDAP_SEARCHPREF_ERR_VERSION` ***buf* points to data that is newer than can be handled.

`LDAP_SEARCHPREF_ERR_MEM` Memory allocation problem.

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit) SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [ldap\(3LDAP\)](#), [ldapsearchprefs.conf\(4\)](#), [attributes\(5\)](#)

Yeong, W., Howes, T., and Hardcastle-Kille, S., “Lightweight Directory Access Protocol”, OSI-DS-26, April 1992.

Howes, T., Hardcastle-Kille, S., Yeong, W., and Robbins, C., “Lightweight Directory Access Protocol”, OSI-DS-26, April 1992.

Hardcastle-Kille, S., “A String Representation of Distinguished Names”, OSI-DS-23, April 1992.

Information Processing - Open Systems Interconnection - The Directory, International Organization for Standardization. International Standard 9594, (1988).

Name ldap_sort, ldap_sort_entries, ldap_sort_values, ldap_sort_strcasecmp – LDAP entry sorting functions

Synopsis `cc[flag...] file... -lldap[library...]`

```
#include <lber.h>
#include <ldap.h>

ldap_sort_entries(LDAP *ld, LDAPMessage **chain, char *attr,
                  int (*cmp)());

ldap_sort_values(LDAP *ld, char **vals, int (*cmp)());

ldap_sort_strcasecmp(char *a, char *b);
```

Description These functions are used to sort lists of entries and values retrieved from an LDAP server. `ldap_sort_entries()` is used to sort a chain of entries retrieved from an LDAP search call either by DN or by some arbitrary attribute in the entries. It takes *ld*, the LDAP structure, which is only used for error reporting, *chain*, the list of entries as returned by [ldap_search_s\(3LDAP\)](#) or [ldap_result\(3LDAP\)](#). *attr* is the attribute to use as a key in the sort or NULL to sort by DN, and *cmp* is the comparison function to use when comparing values (or individual DN components if sorting by DN). In this case, *cmp* should be a function taking two single values of the *attr* to sort by, and returning a value less than zero, equal to zero, or greater than zero, depending on whether the first argument is less than, equal to, or greater than the second argument. The convention is the same as used by [qsort\(3C\)](#), which is called to do the actual sorting.

`ldap_sort_values()` is used to sort an array of values from an entry, as returned by [ldap_get_values\(3LDAP\)](#). It takes the LDAP connection structure *ld*, the array of values to sort *vals*, and *cmp*, the comparison function to use during the sort. Note that *cmp* will be passed a pointer to each element in the *vals* array, so if you pass the normal `char **` for this parameter, *cmp* should take two `char **`'s as arguments (that is, you cannot pass *strcasecmp* or its friends for *cmp*). You can, however, pass the function `ldap_sort_strcasecmp()` for this purpose.

For example:

```
LDAP *ld;
LDAPMessage *res;
/* ... call to ldap_search_s( ), fill in res, retrieve sn attr ... */

/* now sort the entries on surname attribute */
if ( ldap_sort_entries( ld, &res, "sn", ldap_sort_strcasecmp ) != 0 )
    ldap_perror( ld, "ldap_sort_entries" );
```

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit) SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [ldap\(3LDAP\)](#), [ldap_search\(3LDAP\)](#), [ldap_result\(3LDAP\)](#), [qsort\(3C\)](#), [attributes\(5\)](#)

Notes The `ldap_sort_entries()` function applies the comparison function to each value of the attribute in the array as returned by a call to [ldap_get_values\(3LDAP\)](#), until a mismatch is found. This works fine for single-valued attributes, but may produce unexpected results for multi-valued attributes. When sorting by DN, the comparison function is applied to an exploded version of the DN, without types. The return values for all of these functions are declared in the `<ldap.h>` header file. Some functions may allocate memory which must be freed by the calling application.

Name ldap_ufn, ldap_ufn_search_s, ldap_ufn_search_c, ldap_ufn_search_ct, ldap_ufn_setfilter, ldap_ufn_setprefix, ldap_ufn_timeout – LDAP user friendly search functions

Synopsis cc[*flag...*] *file...* -lldap[*library...*]

```
#include <lber.h>
#include <ldap.h>

int ldap_ufn_search_c(LDAP *ld, char *ufn, char **attrs,
    int attrsonly, LDAPMessage **res, int (*cancelproc)(),
    void *cancelparm);

int ldap_ufn_search_ct(LDAP *ld, char *ufn, char **attrs,
    int attrsonly, LDAPMessage **res, int (*cancelproc)(),
    void *cancelparm, char *tag1, char *tag2,
    char *tag3);

int ldap_ufn_search_s(LDAP *ld, char *ufn, char **attrs,
    int attrsonly, LDAPMessage **res);

LDAPFiltDesc *ldap_ufn_setfilter(LDAP *ld, char *fname);

void ldap_ufn_setprefix(LDAP *ld, char *prefix);

int ldap_ufn_timeout(void *tparam);
```

Description These functions are used to perform LDAP user friendly search operations. `ldap_ufn_search_s()` is the simplest form. It does the search synchronously. It takes *ld* to identify the the LDAP connection. The *ufn* parameter is the user friendly name for which to search. The *attrs*, *attrsonly* and *res* parameters are the same as for `ldap_search(3LDAP)`.

The `ldap_ufn_search_c()` function functions the same as `ldap_ufn_search_s()`, except that it takes *cancelproc*, a function to call periodically during the search. It should be a function taking a single void * argument, given by *cancelparm*. If *cancelproc* returns a non-zero result, the search will be abandoned and no results returned. The purpose of this function is to provide a way for the search to be cancelled, for example, by a user or because some other condition occurs.

The `ldap_ufn_search_ct()` function is like `ldap_ufn_search_c()`, except that it takes three extra parameters. *tag1* is passed to the `ldap_init_getfilter(3LDAP)` function when resolving the first component of the UFN. *tag2* is used when resolving intermediate components. *tag3* is used when resolving the last component. By default, the tags used by the other UFN search functions during these three phases of the search are “ufn first”, “ufn intermediate”, and “ufn last”.

The `ldap_ufn_setfilter()` function is used to set the `ldapfilter.conf(4)` file for use with the `ldap_init_getfilter(3LDAP)` function to *fname*.

The `ldap_ufn_setprefix()` function is used to set the default prefix (actually, it's a suffix) appended to UFNs before searching. UFNs with fewer than three components have the prefix

appended first, before searching. If that fails, the UFN is tried with progressively shorter versions of the prefix, stripping off components. If the UFN has three or more components, it is tried by itself first. If that fails, a similar process is applied with the prefix appended.

The `ldap_ufn_timeout()` function is used to set the timeout associated with `ldap_ufn_search_s()` searches. The *timeout* parameter should actually be a pointer to a struct timeval. This is so `ldap_ufn_timeout()` can be used as a cancelproc in the above functions.

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Evolving

See Also [gettimeofday\(3C\)](#), [ldap\(3LDAP\)](#), [ldap_search\(3LDAP\)](#), [ldap_getfilter\(3LDAP\)](#), [ldapfilter.conf\(4\)](#), [ldap_error\(3LDAP\)](#), [attributes\(5\)](#)

Notes These functions may allocates memory. Return values are contained in `<ldap.h>`.

Name ldap_url, ldap_is_ldap_url, ldap_url_parse, ldap_url_parse_nodn, ldap_free_urldesc, ldap_url_search, ldap_url_search_s, ldap_url_search_st, ldap_dns_to_url, ldap_dn_to_url – LDAP Uniform Resource Locator functions

Synopsis cc[*flag...*] *file...* -lldap[*library...*]

```
#include <lber.h>
```

```
#include <ldap.h>
```

```
int ldap_is_ldap_url(char *url);
```

```
int ldap_url_parse(char *url, LDAPURLDesc **ludpp);
```

```
int ldap_url_parse_nodn(char *url, LDAPURLDesc **ludpp);
```

```
ldap_free_urldesc(LDAPURLDesc *ludp);
```

```
int ldap_url_search(LDAP *ld, char *url, int attrsonly);
```

```
int ldap_url_search_s(LDAP *ld, char *url,
    int attrsonly, LDAPMessage **res);
```

```
int ldap_url_search_st(LDAP *ld, char *url, int attrsonly,
    struct timeval *timeout, LDAPMessage **res);
```

```
char *ldap_dns_to_url(LDAP *ld, char *dns_name, char *attrs,
    char *scope, char *filter);
```

```
char *ldap_dn_to_url(LDAP *ld, char *dn, int nameparts);
```

Description These functions support the use of LDAP URLs (Uniform Resource Locators). The following shows the formatting used for LDAP URLs.

```
ldap://hostport/dn[?attributes[?scope[?filter]]]
```

where:

hostport Host name with an optional :portnumber.

dn Base DN to be used for an LDAP search operation.

attributes Comma separated list of attributes to be retrieved.

scope One of these three strings: base one sub (default=base).

filter LDAP search filter as used in a call to [ldap_search\(3LDAP\)](#).

The following is an example of an LDAP URL:

```
ldap://ldap.itd.umich.edu/c=US?o,description?one?o=umich
```

URLs preceded URL : or wrapped in angle-brackets are tolerated. URLs can also be preceded by URL : and wrapped in angle-brackets.

`ldap_is_ldap_url()` returns a non-zero value if *url* looks like an LDAP URL (as opposed to some other kind of URL). It can be used as a quick check for an LDAP URL; the `ldap_url_parse()` function should be used if a more thorough check is needed.

`ldap_url_parse()` breaks down an LDAP URL passed in *url* into its component pieces. If successful, zero is returned, an LDAP URL description is allocated, filled in, and *ludpp* is set to point to it. See RETURN VALUES for values returned upon error.

`ldap_url_parse_nodn()` acts just like `ldap_url_parse()` but does not require *dn* in the LDAP URL.

`ldap_free_urldesc()` should be called to free an LDAP URL description that was obtained from a call to `ldap_url_parse()`.

`ldap_url_search()` initiates an asynchronous LDAP search based on the contents of the *url* string. This function acts just like `ldap_search(3LDAP)` except that many search parameters are pulled out of the URL.

`ldap_url_search_s()` performs a synchronous LDAP search based on the contents of the *url* string. This function acts just like `ldap_search_s(3LDAP)` except that many search parameters are pulled out of the URL.

`ldap_url_search_st()` performs a synchronous LDAP URL search with a specified *timeout*. This function acts just like `ldap_search_st(3LDAP)` except that many search parameters are pulled out of the URL.

`ldap_dns_to_url()` locates the LDAP URL associated with a DNS domain name. The supplied DNS domain name is converted into a distinguished name. The directory entry specified by that distinguished name is searched for a labeled URI attribute. If successful then the corresponding LDAP URL is returned. If unsuccessful then that entry's parent is searched and so on until the target distinguished name is reduced to only two nameparts. If *dns_name* is NULL then the environment variable LOCALDOMAIN is used. If *attrs* is not NULL then it is appended to the URL's attribute list. If *scope* is not NULL then it overrides the URL's scope. If *filter* is not NULL then it is merged with the URL's filter. If an error is encountered then zero is returned, otherwise a string URL is returned. The caller should free the returned string if it is non-zero.

`ldap_dn_to_url()` locates the LDAP URL associated with a distinguished name. The number of nameparts in the supplied distinguished name must be provided. The specified directory entry is searched for a labeled URI attribute. If successful then the LDAP URL is returned. If unsuccessful then that entry's parent is searched and so on until the target distinguished name is reduced to only two nameparts. If an error is encountered then zero is returned, otherwise a string URL is returned. The caller should free the returned string if it is non-zero.

Return Values Upon error, one of these values is returned for `ldap_url_parse()`:

<code>LDAP_URL_ERR_BADSCOPE</code>	URL scope string is invalid.
<code>LDAP_URL_ERR_HOSTPORT</code>	URL hostport is invalid.
<code>LDAP_URL_ERR_MEM</code>	Can't allocate memory space.
<code>LDAP_URL_ERR_NODN</code>	URL has no DN (required).
<code>LDAP_URL_ERR_NOTLDAP</code>	URL doesn't begin with <code>ldap://</code> .

Attributes See [attributes\(5\)](#) for a description of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Evolving

See Also [ldap\(3LDAP\)](#), [ldap_search\(3LDAP\)](#), [attributes\(5\)](#)

An LDAP URL Format , Tim Howes and Mark Smith, December 1995. Internet Draft (work in progress). Currently available at this URL.

`ftp://ds.internic.net/internet-drafts/draft-ietf-asid-ldap-format-03.txt`

Name ldap_version – get version information about the LDAP SDK for C

Synopsis cc -flag ... file...-lldap [-library ...]
#include <ldap.h>

```
int ldap_version(LDAPVERSION *ver);
```

Description A call to this function returns the version information for the LDAP SDK for C. This is a deprecated function. Use [ldap_get_option\(3LDAP\)](#) instead. The version information is returned in the LDAPVersion structure pointed to by *ver*. If NULL is passed for *ver*, then only the SDK version will be returned.

Return Values The `ldap_version()` function returns the version number of the LDAP SDK for C, multiplied by 100. For example, for version 1.0 of the LDAP SDK for C, the function returns 100.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Obsolete

See Also [ldap_get_option\(3LDAP\)](#), [attributes\(5\)](#)

Name listen – listen for connections on a socket

Synopsis `cc [flag ...] file ... -lsocket -lnsl [library ...]`
`#include <sys/types.h>`
`#include <sys/socket.h>`

```
int listen(int s, int backlog);
```

Description To accept connections, a socket is first created with [socket\(3SOCKET\)](#), a backlog for incoming connections is specified with `listen()` and then the connections are accepted with [accept\(3SOCKET\)](#). The `listen()` call applies only to sockets of type `SOCK_STREAM` or `SOCK_SEQPACKET`.

The *backlog* parameter defines the maximum length the queue of pending connections may grow to.

If a connection request arrives with the queue full, the client will receive an error with an indication of `ECONNREFUSED` for `AF_UNIX` sockets. If the underlying protocol supports retransmission, the connection request may be ignored so that retries may succeed. For `AF_INET` and `AF_INET6` sockets, the TCP will retry the connection. If the *backlog* is not cleared by the time the tcp times out, the connect will fail with `ETIMEDOUT`.

Return Values A 0 return value indicates success; -1 indicates an error.

Errors The call fails if:

<code>EBADF</code>	The argument <i>s</i> is not a valid file descriptor.
<code>ENOTSOCK</code>	The argument <i>s</i> is not a socket.
<code>EOPNOTSUPP</code>	The socket is not of a type that supports the operation <code>listen()</code> .

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Safe

See Also [accept\(3SOCKET\)](#), [connect\(3SOCKET\)](#), [socket\(3SOCKET\)](#), [attributes\(5\)](#), [socket.h\(3HEAD\)](#)

Notes There is currently no *backlog* limit.

Name listen – listen for socket connections and limit the queue of incoming connections

Synopsis `cc [flag ...] file ... -lxnet [library ...]`
`#include <sys/socket.h>`

```
int listen(int socket, int backlog);
```

Description The `listen()` function marks a connection-mode socket, specified by the *socket* argument, as accepting connections, and limits the number of outstanding connections in the socket's listen queue to the value specified by the *backlog* argument.

If `listen()` is called with a *backlog* argument value that is less than 0, the function sets the length of the socket's listen queue to 0.

The implementation may include incomplete connections in the queue subject to the queue limit. The implementation may also increase the specified queue limit internally if it includes such incomplete connections in the queue subject to this limit.

Implementations may limit the length of the socket's listen queue. If *backlog* exceeds the implementation-dependent maximum queue length, the length of the socket's listen queue will be set to the maximum supported value.

The socket in use may require the process to have appropriate privileges to use the `listen()` function.

Return Values Upon successful completions, `listen()` returns 0. Otherwise, `-1` is returned and `errno` is set to indicate the error.

Errors The `listen()` function will fail if:

EBADF	The <i>socket</i> argument is not a valid file descriptor.
EDESTADDRREQ	The socket is not bound to a local address, and the protocol does not support listening on an unbound socket.
EINVAL	The <i>socket</i> is already connected.
ENOTSOCK	The <i>socket</i> argument does not refer to a socket.
EOPNOTSUPP	The socket protocol does not support <code>listen()</code> .

The `listen()` function may fail if:

EACCES	The calling process does not have the appropriate privileges.
EINVAL	The <i>socket</i> has been shut down.
ENOBUFS	Insufficient resources are available in the system to complete the call.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also [accept\(3XNET\)](#), [connect\(3XNET\)](#), [socket\(3XNET\)](#), [attributes\(5\)](#), [standards\(5\)](#)

Name netdir, netdir_getbyname, netdir_getbyaddr, netdir_free, netdir_options, taddr2uaddr, uaddr2taddr, netdir_perror, netdir_sperror, netdir_mergeaddr – generic transport name-to-address translation

Synopsis `cc [flag...] file... -lnsl [library...]`
`#include <netdir.h>`

```
int netdir_getbyname(struct netconfig *config,
                    struct nd_hostserv *service, struct nd_addrlist **addrs);

int netdir_getbyaddr(struct netconfig *config,
                    struct nd_hostservlist **service, struct netbuf *netaddr);

void netdir_free(void *ptr, int struct_type);

int netdir_options(struct netconfig *config, int option, int fildes,
                  char *point_to_args);

char *taddr2uaddr(struct netconfig *config, struct netbuf *addr);

struct netbuf *uaddr2taddr(struct netconfig *config, char *uaddr);

void netdir_perror(char *s);

char *netdir_sperror(void);
```

Description The netdir functions provide a generic interface for name-to-address mapping that will work with all transport protocols. This interface provides a generic way for programs to convert transport specific addresses into common structures and back again. The netconfig structure, described on the [netconfig\(4\)](#) manual page, identifies the transport.

The netdir_getbyname() function maps the machine name and service name in the nd_hostserv structure to a collection of addresses of the type understood by the transport identified in the netconfig structure. This function returns all addresses that are valid for that transport in the nd_addrlist structure. The nd_hostserv structure contains the following members:

```
char *h_host;      /* host name */
char *h_serv;      /* service name */
```

The nd_addrlist structure contains the following members:

```
int n_cnt;         /* number of addresses */
struct netbuf *n_addrs;
```

The netdir_getbyname() function accepts some special-case host names. The host names are defined in <netdir.h>. The currently defined host names are:

HOST_SELF	Represents the address to which local programs will bind their endpoints. HOST_SELF differs from the host name provided by gethostname(3C) , which represents the address to which <i>remote</i> programs will bind their endpoints.
-----------	--

HOST_ANY	Represents any host accessible by this transport provider. HOST_ANY allows applications to specify a required service without specifying a particular host name.
HOST_SELF_CONNECT	Represents the host address that can be used to connect to the local host.
HOST_BROADCAST	Represents the address for all hosts accessible by this transport provider. Network requests to this address are received by all machines.

All fields of the `nd_hostserv` structure must be initialized.

To find the address of a given host and service on all available transports, call the `netdir_getbyname()` function with each `struct netconfig` structure returned by [getnetconfig\(3NSL\)](#).

The `netdir_getbyaddr()` function maps addresses to service names. The function returns *service*, a list of host and service pairs that yield these addresses. If more than one tuple of host and service name is returned, the first tuple contains the preferred host and service names:

```
struct nd_hostservlist {
    int *h_cnt; /* number of hostservs found */
    struct hostserv *h_hostservs;
}
```

The `netdir_free()` structure is used to free the structures allocated by the name to address translation functions. The *ptr* parameter points to the structure that has to be freed. The parameter `struct_type` identifies the structure:

```
struct netbuf          ND_ADDR
struct nd_addrlist     ND_ADDRLIST
struct hostserv        ND_HOSTSERV
struct nd_hostservlist ND_HOSTSERVLIST
```

The `free()` function is used to free the universal address returned by the `taddr2uaddr()` function.

The `netdir_options()` function is used to do all transport-specific setups and option management. *filde*s is the associated file descriptor. *option*, *filde*s, and *pointer_to_args* are passed to the `netdir_options()` function for the transport specified in *config*. Currently four values are defined for *option*:

```
ND_SET_BROADCAST
ND_SET_RESERVEDPORT
ND_CHECK_RESERVEDPORT
ND_MERGEADDR
```

The `taddr2uaddr()` and `uaddr2taddr()` functions support translation between universal addresses and TLI type `netbufs`. The `taddr2uaddr()` function takes a `struct netbuf` data structure and returns a pointer to a string that contains the universal address. It returns `NULL` if the conversion is not possible. This is not a fatal condition as some transports do not support a universal address form.

The `uaddr2taddr()` function is the reverse of the `taddr2uaddr()` function. It returns the `struct netbuf` data structure for the given universal address.

If a transport provider does not support an option, `netdir_options` returns `-1` and the error message can be printed through `netdir_perror()` or `netdir_spperror()`.

The specific actions of each option follow.

<code>ND_SET_BROADCAST</code>	Sets the transport provider up to allow broadcast if the transport supports broadcast. <i>fildev</i> is a file descriptor into the transport, that is, the result of a <code>t_open</code> of <code>/dev/udp</code> . <i>pointer_to_args</i> is not used. If this completes, broadcast operations can be performed on file descriptor <i>fildev</i> .
<code>ND_SET_RESERVEDPORT</code>	Allows the application to bind to a reserved port if that concept exists for the transport provider. <i>fildev</i> is an unbound file descriptor into the transport. If <i>pointer_to_args</i> is <code>NULL</code> , <i>fildev</i> is bound to a reserved port. If <i>pointer_to_args</i> is a pointer to a <code>netbuf</code> structure, an attempt is made to bind to any reserved port on the specified address.
<code>ND_CHECK_RESERVEDPORT</code>	Used to verify that the address corresponds to a reserved port if that concept exists for the transport provider. <i>fildev</i> is not used. <i>pointer_to_args</i> is a pointer to a <code>netbuf</code> structure that contains the address. This option returns <code>0</code> only if the address specified in <i>pointer_to_args</i> is reserved.
<code>ND_MERGEADDR</code>	<p>Used to take a "local address" such as a <code>0.0.0.0</code> TCP address and return a "real address" to which client machines can connect. <i>fildev</i> is not used. <i>pointer_to_args</i> is a pointer to a <code>struct nd_mergearg</code> which has the following members:</p> <pre>char s_uaddr; /* server's universal address */ char c_uaddr; /* client's universal address */ char m_uaddr; /* the result */</pre> <p>If <i>s_uaddr</i> is an address such as <code>0.0.0.0.1.12</code>, and the call is successful <i>m_uaddr</i> is set to an address such as <code>192.11.109.89.1.12</code>. For most transports, <i>m_uaddr</i> is identical to <i>s_uaddr</i>.</p>

Return Values The `netdir_perror()` function prints an error message in standard output that states the cause of a name-to-address mapping failure. The error message is preceded by the string given as an argument.

The `netdir_sperror()` function returns a string with an error message that states the cause of a name-to-address mapping failure.

The `netdir_sperror()` function returns a pointer to a buffer which contains the error message string. The buffer is overwritten on each call. In multithreaded applications, this buffer is implemented as thread-specific data.

The `netdir_getbyaddr()` function returns 0 on success and a non-zero value on failure.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Safe

See Also [gethostname\(3C\)](#), [getnetconfig\(3NSL\)](#), [getnetpath\(3NSL\)](#), [netconfig\(4\)](#), [attributes\(5\)](#)

Name `nis_error`, `nis_sperno`, `nis_perror`, `nis_terror`, `nis_sperror`, `nis_sperror_r` – display NIS+ error messages

Synopsis `cc [flag ...] file ... -lnsl [library ...]`
`#include <rpcsvc/nis.h>`

```
char *nis_sperno(nis_error status);  
void nis_perror(nis_error status, char *label);  
void nis_terror(nis_error status, char *label);  
char *nis_sperror_r(nis_error status, char *label, char *buf, int length);  
char *nis_sperror(nis_error status, char *label);
```

Description These functions convert NIS+ status values into text strings.

`nis_sperno()` simply returns a pointer to a string constant which is the error string.

`nis_perror()` prints the error message corresponding to *status* as “*label*: error message” on standard error.

`nis_terror()` sends the error text to [syslog\(3C\)](#) at level LOG_ERR.

The function `nis_sperror_r()`, returns a pointer to a string that can be used or copied using the `strdup()` function (See [string\(3C\)](#)). The caller must supply a string buffer, *buf*, large enough to hold the error string (a buffer size of 128 bytes is guaranteed to be sufficiently large). *status* and *label* are the same as for `nis_perror()`. The pointer returned by `nis_sperror_r()` is the same as *buf*, that is, the pointer returned by the function is a pointer to *buf*. *length* specifies the number of characters to copy from the error string to *buf*.

The last function, `nis_sperror()`, is similar to `nis_sperror_r()` except that the string is returned as a pointer to a buffer that is reused on each call. `nis_sperror_r()` is the preferred interface, since it is suitable for single-threaded and multi-threaded programs.

When compiling multithreaded applications, see [Intro\(3\)](#), *Notes On Multithread Applications*, for information about the use of the `_REENTRANT` flag.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Safe

See Also [niserror\(1\)](#), [string\(3C\)](#), [syslog\(3C\)](#), [attributes\(5\)](#)

Notes NIS+ might not be supported in future releases of the Solaris operating system. Tools to aid the migration from NIS+ to LDAP are available in the current Solaris release. For more information, visit <http://www.sun.com/directory/nisplus/transition.html>.

Name `nis_groups`, `nis_ismember`, `nis_addmember`, `nis_removemember`, `nis_creategroup`, `nis_destroygroup`, `nis_verifygroup`, `nis_print_group_entry` – NIS+ group manipulation functions

Synopsis `cc [flag ...] file ... -lnsl [library ...]`
`#include <rpcsvc/nis.h>`

```
bool_t nis_ismember(nis_name principal, nis_name group);
nis_error nis_addmember(nis_name member, nis_name group);
nis_error nis_removemember(nis_name member, nis_name group);
nis_error nis_creategroup(nis_name group, uint_t flags);
nis_error nis_destroygroup(nis_name group);
void nis_print_group_entry(nis_name group);
nis_error nis_verifygroup(nis_name group);
```

Description These functions manipulate NIS+ groups. They are used by NIS+ clients and servers, and are the interfaces to the group authorization object.

The names of NIS+ groups are syntactically similar to names of NIS+ objects but they occupy a separate namespace. A group named “a.b.c.d.” is represented by a NIS+ group object named “a.groups_dir.b.c.d.”; the functions described here all expect the name of the group, not the name of the corresponding group object.

There are three types of group members:

- An *explicit* member is just a NIS+ principal-name, for example “wickedwitch.west.oz.”
- An *implicit* (“domain”) member, written “*.west.oz.”, means that all principals in the given domain belong to this member. No other forms of wildcarding are allowed: “wickedwitch.*.oz.” is invalid, as is “wickedwitch.west.*.”. Note that principals in subdomains of the given domain are *not* included.
- A *recursive* (“group”) member, written “@cowards.oz.”, refers to another group. All principals that belong to that group are considered to belong here.

Any member may be made *negative* by prefixing it with a minus sign (‘-’). A group may thus contain explicit, implicit, recursive, negative explicit, negative implicit, and negative recursive members.

A principal is considered to belong to a group if it belongs to at least one non-negative group member of the group and belongs to no negative group members.

The `nis_ismember()` function returns TRUE if it can establish that *principal* belongs to *group*; otherwise it returns FALSE.

The `nis_addmember()` and `nis_removemember()` functions add or remove a member. They do not check whether the member is valid. The user must have read and modify rights for the group in question.

The `nis_creategroup()` and `nis_destroygroup()` functions create and destroy group objects. The user must have create or destroy rights, respectively, for the `groups_dir` directory in the appropriate domain. The parameter *flags* to `nis_creategroup()` is currently unused and should be set to zero.

The `nis_print_group_entry()` function lists a group's members on the standard output.

The `nis_verifygroup()` function returns `NIS_SUCCESS` if the given group exists, otherwise it returns an error code.

These functions only accept fully-qualified NIS+ names.

A group is represented by a NIS+ object with a variant part that is defined in the `group_obj` structure. See [nis_objects\(3NSL\)](#). It contains the following fields:

```
uint_t    gr_flags;    /* Interpretation Flags
                        (currently unused) */
struct {
    uint_t    gr_members_len;
    nis_name  *gr_members_val;
} gr_members;          /* Array of members */
```

NIS+ servers and clients maintain a local cache of expanded groups to enhance their performance when checking for group membership. Should the membership of a group change, servers and clients with that group cached will not see the change until either the group cache has expired or it is explicitly flushed. A server's cache may be flushed programmatically by calling the `nis_servstate()` function with tag `TAG_GCACHE` and a value of 1.

There are currently no known methods for `nis_ismember()`, `nis_print_group_entry()`, and `nis_verifygroup()` to get their answers from only the master server.

Examples **EXAMPLE 1** Simple Memberships

Given a group `sadsouls.oz.` with members `tinman.oz.`, `lion.oz.`, and `scarecrow.oz.`, the function call

```
bool_var = nis_ismember("lion.oz.", "sadsouls.oz.");
```

will return 1 (TRUE) and the function call

```
bool_var = nis_ismember("toto.oz.", "sadsouls.oz.");
```

will return 0 (FALSE).

EXAMPLE 2 Implicit Memberships

Given a group `baddies.oz.`, with members `wickedwitch.west.oz.` and `*.monkeys.west.oz.`, the function call `bool_var = nis_ismember("hogan.monkeys.west.oz.", "baddies.oz.");` will return 1 (TRUE) because any principal from the `monkeys.west.oz.` domain belongs to the implicit group `*.monkeys.west.oz.`, but the function call `bool_var = nis_ismember("hogan.big.monkeys.west.oz.", "baddies.oz.");` will return 0 (FALSE).

EXAMPLE 3 Recursive Memberships

Given a group `goodandbad.oz.`, with members `toto.kansas@sadsouls.oz.`, and `@baddies.oz.`, and the groups `sadsouls.oz.` and `baddies.oz.` defined above, the function call `bool_var = nis_ismember("wickedwitch.west.oz.", "goodandbad.oz.");` will return 1 (TRUE), because `wickedwitch.west.oz.` is a member of the `baddies.oz.` group which is recursively included in the `goodandbad.oz.` group.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [nisgrpadm\(1\)](#), [nis_objects\(3NSL\)](#), [attributes\(5\)](#)

Notes NIS+ might not be supported in future releases of the Solaris operating system. Tools to aid the migration from NIS+ to LDAP are available in the current Solaris release. For more information, visit <http://www.sun.com/directory/nisplus/transition.html>.

Name `nis_local_names`, `nis_local_directory`, `nis_local_host`, `nis_local_group`, `nis_local_principal` – NIS+ local names

Synopsis `cc [flag ...] file ... -lnsl [library ...]`
`#include <rpcsvc/nis.h>`

```
nis_name nis_local_directory(void);
nis_name nis_local_host(void);
nis_name nis_local_group(void);
nis_name nis_local_principal(void);
```

Description These functions return several default NIS+ names associated with the current process.

`nis_local_directory()` returns the name of the NIS+ domain for this machine. This is currently the same as the Secure RPC domain returned by the [sysinfo\(2\)](#) system call.

`nis_local_host()` returns the NIS+ name of the current machine. This is the fully qualified name for the host and is either the value returned by the [gethostname\(3C\)](#) function or, if the host name is only partially qualified, the concatenation of that value and the name of the NIS+ directory. Note that if a machine's name and address cannot be found in the local NIS+ directory, its hostname must be fully qualified.

`nis_local_group()` returns the name of the current NIS+ group name. This is currently set by setting the environment variable `NIS_GROUP` to the groupname.

`nis_local_principal()` returns the NIS+ principal name for the user associated with the effective UID of the calling process. This function maps the effective uid into a principal name by looking for a LOCAL type credential in the table named `cred.org_dir` in the default domain. See [nisaddcred\(1M\)](#).

The result returned by these routines is a pointer to a data structure with the NIS+ library, and should be considered a “read-only” result and should not be modified.

Environment Variables `NIS_GROUP` This variable contains the name of the local NIS+ group. If the name is not fully qualified, the value returned by `nis_local_directory()` will be concatenated to it.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [nisdefaults\(1\)](#), [nisaddcred\(1M\)](#), [sysinfo\(2\)](#), [gethostname\(3C\)](#), [nis_names\(3NSL\)](#), [nis_objects\(3NSL\)](#), [attributes\(5\)](#)

Notes NIS+ might not be supported in future releases of the Solaris operating system. Tools to aid the migration from NIS+ to LDAP are available in the current Solaris release. For more information, visit <http://www.sun.com/directory/nisplus/transition.html>.

Name nis_names, nis_lookup, nis_add, nis_remove, nis_modify, nis_freeresult – NIS+ namespace functions

Synopsis cc [*flag* ...] *file* ... -lnsl [*library* ...]
#include <rpcsvc/nis.h>

```
nis_result *nis_lookup(nis_name name, uint_t flags);
nis_result *nis_add(nis_name name, nis_object *obj);
nis_result *nis_remove(nis_name name, nis_object *obj);
nis_result *nis_modify(nis_name name, nis_object *obj);
void nis_freeresult(nis_result *result);
```

Description The NIS+ namespace functions are used to locate and manipulate all NIS+ objects except the NIS+ entry objects. See [nis_objects\(3NSL\)](#). To look up the NIS+ entry objects within a NIS+ table, refer to [nis_subr\(3NSL\)](#).

`nis_lookup()` resolves a NIS+ name and returns a copy of that object from a NIS+ server. `nis_add()` and `nis_remove()` add and remove objects to the NIS+ namespace, respectively. `nis_modify()` can change specific attributes of an object that already exists in the namespace.

These functions should be used only with names that refer to an NIS+ Directory, NIS+ Table, NIS+ Group, or NIS+ Private object. If a name refers to an NIS+ entry object, the functions listed in [nis_subr\(3NSL\)](#) should be used.

`nis_freeresult()` frees all memory associated with a `nis_result` structure. This function must be called to free the memory associated with a NIS+ result. `nis_lookup()`, `nis_add()`, `nis_remove()`, and `nis_modify()` all return a pointer to a `nis_result()` structure which must be freed by calling `nis_freeresult()` when you have finished using it. If one or more of the objects returned in the structure need to be retained, they can be copied with [nis_clone_object\(3NSL\)](#). See [nis_subr\(3NSL\)](#).

`nis_lookup()` takes two parameters, the name of the object to be resolved in *name*, and a flags parameter, *flags*, which is defined below. The object name is expected to correspond to the syntax of a non-indexed NIS+ name. See [nis_tables\(3NSL\)](#). The `nis_lookup()` function is the only function from this group that can use a non-fully qualified name. If the parameter *name* is not a fully qualified name, then the flag `EXPAND_NAME` must be specified in the call. If this flag is not specified, the function will fail with the error `NIS_BADNAME`.

The *flags* parameter is constructed by logically ORing zero or more flags from the following list.

<code>FOLLOW_LINKS</code>	When specified, the client library will “follow” links by issuing another NIS+ lookup call for the object named by the link. If the linked object is
---------------------------	--

	itself a link, then this process will iterate until the either a object is found that is not a LINK type object, or the library has followed 16 links.
HARD_LOOKUP	When specified, the client library will retry the lookup until it is answered by a server. Using this flag will cause the library to block until at least one NIS+ server is available. If the network connectivity is impaired, this can be a relatively long time.
NO_CACHE	When specified, the client library will bypass any object caches and will get the object from either the master NIS+ server or one of its replicas.
MASTER_ONLY	When specified, the client library will bypass any object caches and any domain replicas and fetch the object from the NIS+ master server for the object's domain. This insures that the object returned is up to date at the cost of a possible performance degradation and failure if the master server is unavailable or physically distant.
EXPAND_NAME	When specified, the client library will attempt to expand a partially qualified name by calling the function <code>nis_getnames()</code> , which uses the environment variable <code>NIS_PATH</code> . See nis_subr(3NSL) .

The status value may be translated to ASCII text using the function `nis_sperno()`. See [nis_error\(3NSL\)](#).

On return, the *objects* array in the result will contain one and possibly several objects that were resolved by the request. If the FOLLOW_LINKS flag was present, on success the function could return several entry objects if the link in question pointed within a table. If an error occurred when following a link, the objects array will contain a copy of the link object itself.

The function `nis_add()` will take the object *obj* and add it to the NIS+ namespace with the name *name*. This operation will fail if the client making the request does not have the *create* access right for the domain in which this object will be added. The parameter *name* must contain a fully qualified NIS+ name. The object members *zo_name* and *zo_domain* will be constructed from this name. This operation will fail if the object already exists. This feature prevents the accidental addition of objects over another object that has been added by another process.

The function `nis_remove()` will remove the object with name *name* from the NIS+ namespace. The client making this request must have the *destroy* access right for the domain in which this object resides. If the named object is a link, the link is removed and *not* the object that it points to. If the parameter *obj* is not NULL, it is assumed to point to a copy of the object being removed. In this case, if the object on the server does not have the same object identifier as the object being passed, the operation will fail with the NIS_NOTSAMEOBJ error. This feature allows the client to insure that it is removing the desired object. The parameter *name* must contain a fully qualified NIS+ name.

The function `nis_modify()` will modify the object named by *name* to the field values in the object pointed to by *obj*. This object should contain a copy of the object from the name space that is being modified. This operation will fail with the error `NIS_NOTSAMEOBJ` if the object identifier of the passed object does not match that of the object being modified in the namespace.

Normally the contents of the member `zo_name` in the `nis_object` structure would be constructed from the name passed in the *name* parameter. However, if it is non-null the client library will use the name in the `zo_name` member to perform a rename operation on the object. This name *must not* contain any unquoted '.' (dot) characters. If these conditions are not met the operation will fail and return the `NIS_BADNAME` error code.

You cannot modify the name of an object if that modification would cause the object to reside in a different domain.

You cannot modify the schema of a table object.

Results These functions return a pointer to a structure of type `nis_result`:

```
struct nis_result {
    nis_error status;
    struct {
        uint_t    objects_len;
        nis_object *objects_val;
    } objects;
    netobj    cookie;
    uint32_t  zticks;
    uint32_t  dticks;
    uint32_t  aticks;
    uint32_t  cticks;
};
```

The *status* member contains the error status of the the operation. A text message that describes the error can be obtained by calling the function `nis_sperno()`. See [nis_error\(3NSL\)](#).

The *objects* structure contains two members. *objects_val* is an array of `nis_object` structures; *objects_len* is the number of cells in the array. These objects will be freed by the call to `nis_freeresult()`. If you need to keep a copy of one or more objects, they can be copied with the function `nis_clone_object()` and freed with the function `nis_destroy_object()`. See [nis_server\(3NSL\)](#). Refer to [nis_objects\(3NSL\)](#) for a description of the `nis_object` structure.

The various ticks contain details of where the time was taken during a request. They can be used to tune one's data organization for faster access and to compare different database implementations.

<i>zticks</i>	The time spent in the NIS+ service itself. This count starts when the server receives the request and stops when it sends the reply.
<i>dticks</i>	The time spent in the database backend. This time is measured from the time a database call starts, until the result is returned. If the request results in multiple calls to the database, this is the sum of all the time spent in those calls.
<i>aticks</i>	The time spent in any “accelerators” or caches. This includes the time required to locate the server needed to resolve the request.
<i>cticks</i>	The total time spent in the request. This clock starts when you enter the client library and stops when a result is returned. By subtracting the sum of the other ticks values from this value, you can obtain the local overhead of generating a NIS+ request.

Subtracting the value in *dticks* from the value in *zticks* will yield the time spent in the service code itself. Subtracting the sum of the values in *zticks* and *aticks* from the value in *cticks* will yield the time spent in the client library itself. Note: all of the tick times are measured in microseconds.

Return Values The client library can return a variety of error returns and diagnostics. The more salient ones are documented below.

NIS_SUCCESS	The request was successful.
NIS_S_SUCCESS	The request was successful, however the object returned came from an object cache and not directly from the server. If you do not wish to see objects from object caches you must specify the flag NO_CACHE when you call the lookup function.
NIS_NOTFOUND	The named object does not exist in the namespace.
NIS_CACHEEXPIRED	The object returned came from an object cache taht has <i>expired</i> . The time to live value has gone to zero and the object may have changed. If the flag NO_CACHE was passed to the lookup function then the lookup function will retry the operation to get an unexpired copy of the object.
NIS_NAMEUNREACHABLE	A server for the directory of the named object could not be reached. This can occur when there is a network partition or all servers have crashed. See the HARD_LOOKUP flag.
NIS_UNKNOWNOBJ	The object returned is of an unknown type.
NIS_TRYAGAIN	The server connected to was too busy to handle your request. For the <i>add</i> , <i>remove</i> , and <i>modify</i> operations this is returned when either the master server for a directory is unavailable, or it is in the process of checkpointing its database. It can also be returned when the server is updating its internal state. In the case of <code>nis_list()</code> ,

	NIS_TRYAGAIN is returned if the client specifies a callback and the server does not have enough resources to handle the callback.
NIS_SYSTEMERROR	A generic system error occurred while attempting the request. Most commonly the server has crashed or the database has become corrupted. Check the syslog record for error messages from the server.
NIS_NOT_ME	A request was made to a server that does not serve the name in question. Normally this will not occur, however if you are not using the built in location mechanism for servers you may see this if your mechanism is broken.
NIS_NOMEMORY	Generally a fatal result. It means that the service ran out of heap space.
NIS_NAMEEXISTS	An attempt was made to add a name that already exists. To add the name, first remove the existing name and then add the new object or modify the existing named object.
NIS_NOTMASTER	An attempt was made to update the database on a replica server.
NIS_INVALIDOBJ	The object pointed to by <i>obj</i> is not a valid NIS+ object.
NIS_BADNAME	The name passed to the function is not a legal NIS+ name.
NIS_LINKNAMEERROR	The name passed resolved to a LINK type object and the contents of the link pointed to an invalid name.
NIS_NOTSAMEOBJ	An attempt to remove an object from the namespace was aborted because the object that would have been removed was not the same object that was passed in the request.
NIS_NOSUCHNAME	This hard error indicates that the named directory of the table object does not exist. This occurs when the server that should be the parent of the server that serves the table, does not know about the directory in which the table resides.
NIS_NOSUCHTABLE	The named table does not exist.
NIS_MODFAIL	The attempted modification failed.
NIS_FOREIGNNS	The name could not be completely resolved. When the name passed to the function would resolve in a namespace that is outside the NIS+ name tree, this error is returned with a NIS+ object of type DIRECTORY, which contains the type of namespace and contact information for a server within that namespace.
NIS_RPCERROR	This fatal error indicates the RPC subsystem failed in some way. Generally there will be a syslog(3C) message indicating why the

RPC request failed.

Environment Variables **NIS_PATH** If the flag EXPAND_NAME is set, this variable is the search path used by nis_lookup().

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [nis_error\(3NSL\)](#), [nis_objects\(3NSL\)](#), [nis_server\(3NSL\)](#), [nis_subr\(3NSL\)](#), [nis_tables\(3NSL\)](#), [attributes\(5\)](#)

Notes NIS+ might not be supported in future releases of the Solaris operating system. Tools to aid the migration from NIS+ to LDAP are available in the current Solaris release. For more information, visit <http://www.sun.com/directory/nisplus/transition.html>.

Name nis_objects – NIS+ object formats

Synopsis cc [*flag* ...] *file* ... -lnsl [*library* ...]
/usr/include/rpcsvc/nis_objects.x

Description

Common Attributes The NIS+ service uses a variant record structure to hold the contents of the objects that are used by the NIS+ service. These objects all share a common structure that defines a set of attributes that all objects possess. The `nis_object` structure contains the following members:

```
typedef      char      *nis_name;
struct      nis_object {
    nis_oid      zo_oid;
    nis_name     zo_name;
    nis_name     zo_owner;
    nis_name     zo_group;
    nis_name     zo_domain;
    uint_t      zo_access;
    uint32_t     zo_ttl;
    objdata     zo_data;
};
```

In this structure, the first member `zo_oid`, is a 64 bit number that uniquely identifies this instance of the object on this server. This member is filled in by the server when the object is created and changed by the server when the object is modified. When used in conjunction with the object's name and domain it uniquely identifies the object in the entire NIS+ namespace.

The second member, `zo_name`, contains the leaf name of the object. This name is never terminated with a '.' (dot). When an object is created or added to the namespace, the client library will automatically fill in this field and the domain name from the name that was passed to the function.

`zo_domain` contains the name of the NIS+ domain to which this object belongs. This information is useful when tracking the parentage of an object from a cache. When used in conjunction with the members `zo_name` and `zo_oid`, it uniquely identifies an object. This makes it possible to always reconstruct the name of an object by using the code fragment

```
printf(buf, "%s.%s", obj->zo_name, obj->zo_domain);
```

The `zo_owner` and `zo_group` members contain the NIS+ names of the object's principal owner and group owner, respectively. Both names must be NIS+ fully qualified names. However, neither name can be used directly to identify the object they represent. This stems from the condition that NIS+ uses itself to store information that it exports.

The `zo_owner` member contains a fully qualified NIS+ name of the form *principal.domain*. This name is called a NIS+ principal name and is used to identify authentication information in a credential table. When the server constructs a search query of the form

```
[cname=principal], cred.org_dir.domain.
```

The query will return to the server credential information about *principal* for all flavors of RPC authentication that are in use by that principal. When an RPC request is made to the server, the authentication flavor is extracted from the request and is used to find out the NIS+ principal name of the client. For example, if the client is using the AUTH_DES authentication flavor, it will include in the authentication credentials the network name or *netname* of the user making the request. This netname will be of the form

```
unix.UID@domain
```

The NIS+ server will then construct a query on the credential database of the form

```
[auth_name=netname, auth_type=AUTH_DES], cred.org_dir.domain.
```

This query will return an entry which contains a principal name in the first column. This NIS+ principal name is used to control access to NIS+ objects.

The group owner for the object is treated differently. The group owner member is optional (it should be the null string if not present) but must be fully qualified if present. A group name takes the form

```
group.domain.
```

which the server then maps into a name of the form

```
group.groups_dir.domain.
```

The purpose of this mapping is to prevent NIS+ group names from conflicting with user specified domain or table names. For example, if a domain was called *engineering.foo.com.*, then without the mapping a NIS+ group of the same name to represent members of engineering would not be possible. The contents of groups are lists of NIS+ principal names which are used exactly like the *zo_owner* name in the object. See [nis_groups\(3NSL\)](#) for more details.

The *zo_access* member contains the bitmask of access rights assigned to this object. There are four access rights defined, and four are reserved for future use and must be zero. This group of 8 access rights can be granted to four categories of client. These categories are the object's owner, the object's group owner, all authenticated clients (world), and all unauthenticated clients (nobody). Note that access granted to "nobody" is really access granted to everyone, authenticated and unauthenticated clients.

The *zo_ttl* member contains the number of seconds that the object can "live" in a cache before it is expired. This value is called the time to live for this object. This number is particularly important on group and directory (domain) objects. When an object is cached, the current time is added to the value in *zo_ttl*. Then each time the cached object is used, the time in *zo_ttl* is compared with the current time. If the current time is later than the time in *zo_ttl* the object is said to have expired and the cached copy should not be used.

Setting the TTL is somewhat of an art. You can think of it as the “half life” of the object, or half the amount of time you believe will pass before the object changes. The benefit of setting the ttl to a large number is that the object will stay in a cache for long periods of time. The problem with setting it to a large value is that when the object changes it will take a long time for the caches to flush out old copies of that object. The problems and benefits are reversed for setting the time to a small value. Generally setting the value to 43200 (12 hrs) is reasonable for things that change day to day, and 3024000 is good for things that change week to week. Setting the value to 0 will prevent the object from ever being cached since it would expire immediately.

The `zo_data` member is a discriminated union with the following members:

```
zotypes zo_type;
union {
    struct directory_obj    di_data;
    struct group_obj       gr_data;
    struct table_obj       ta_data;
    struct entry_obj       en_data;
    struct link_obj        li_data;
    struct {
        uint_t    po_data_len;
        char      *po_data_val;
    } po_data;
} objdata_u;
```

The union is discriminated based on the type value contained in `zo_type`. There six types of objects currently defined in the NIS+ service. These types are the directory, link, group, table, entry, and private types.

```
enum zotypes {
    BOGUS_OBJ    = 0,
    NO_OBJ       = 1,
    DIRECTORY_OBJ = 2,
    GROUP_OBJ    = 3,
    TABLE_OBJ   = 4,
    ENTRY_OBJ    = 5,
    LINK_OBJ     = 6,
    PRIVATE_OBJ  = 7
};
typedef enum zotypes zotypes;
```

All object types define a structure that contains data specific to that type of object. The simplest are private objects which are defined to contain a variable length array of octets. Only the owner of the object is expected to understand the contents of a private object. The following section describe the other five object types in more significant detail.

Directory Objects The first type of object is the *directory* object. This object's variant part is defined as follows:

```
enum nstype {
    UNKNOWN    = 0,
    NIS        = 1,
```

```
SUNYP    = 2,
DNS      = 4,
X500     = 5,
DNANS    = 6,
XCHS     = 7,
}
typedef enum nstype nstype;
struct oar_mask {
    uint_t    oa_rights;
    zotypes   oa_otype;
}
typedef struct oar_mask oar_mask;
struct endpoint {
    char      *uaddr;
    char      *family;
    char      *proto;
}
typedef struct endpoint endpoint;
struct nis_server {
    nis_name   name;
    struct {
        uint_t    ep_len;
        endpoint   *ep_val;
    } ep;
    uint_t     key_type;
    netobj     pkey;
}
typedef struct nis_server nis_server;
struct directory_obj {
    nis_name    do_name;
    nstype      do_type;
    struct {
        uint_t    do_servers_len;
        nis_server *do_servers_val;
    } do_servers;
    uint32_t     do_ttl;
    struct {
        uint_t    do_armask_len;
        oar_mask   *do_armask_val;
    } do_armask;
}
typedef struct directory_obj directory_obj;
```

The main structure contains five primary members: `do_name`, `do_type`, `do_servers`, `do_ttl`, and `do_armask`. The information in the `do_servers` structure is sufficient for the client library to create a network connection with the named server for the directory.

The `do_name` member contains the name of the directory or domain represented in a format that is understandable by the type of nameservice serving that domain. In the case of NIS+

domains, this is the same as the name that can be composed using the `zo_name` and `zo_domain` members. For other name services, this name will be a name that they understand. For example, if this were a directory object describing an X.500 namespace that is “under” the NIS+ directory *eng.sun.com.*, this name might contain “/C=US, /O=Sun Microsystems, /OU=Engineering/”. The type of nameservice that is being described is determined by the value of the member `do_type`.

The `do_servers` structure contains two members. `do_servers_val` is an array of *nis_server* structures; `do_servers_len` is the number of cells in the array. The *nis_server* structure is designed to contain enough information such that machines on the network providing name services can be contacted without having to use a name service. In the case of NIS+ servers, this information is the name of the machine in *name*, its public key for authentication in *pkey*, and a variable length array of endpoints, each of which describes the network endpoint for the `rpcbind` daemon on the named machine. The client library uses the addresses to contact the server using a transport that both the client and server can communicate on and then queries the `rpcbind` daemon to get the actual transport address that the server is using.

Note that the first server in the *do_servers* list is always the master server for the directory.

The *key_type* field describes the type of key stored in the *pkey* netobj (see `/usr/include/rpc/xdr.h` for a definition of the network object structure). Currently supported types are `NIS_PK_NONE` for no public key, `NIS_PK_DH` for a Diffie-Hellman type public key, and `NIS_PK_DHEXT` for an extended Diffie-Hellman public key.

The `do_ttl` member contains a copy of the `zo_ttl` member from the common attributes. This is duplicated because the cache manager only caches the variant part of the directory object.

The `do_armask` structure contains two members. `do_armask_val` is an array of *oar_mask* structures; `do_armask_len` is the number of cells in the array. The *oar_mask* structure contains two members: `oa_rights` specifies the access rights allowed for objects of type `oa_otype`. These access rights are used for objects of the given type in the directory when they are present in this array.

The granting of access rights for objects contained within a directory is actually two-tiered. If the directory object itself grants a given access right (using the `zo_access` member in the *nis_object* structure representing the directory), then all objects within the directory are allowed that access. Otherwise, the `do_armask` structure is examined to see if the access is allowed specifically for that type of structure. This allows the administrator of a namespace to set separate policies for different object types, for example, one policy for the creation of tables and another policy for the creation of other directories. See [NIS+\(1\)](#) for more details.

Link Objects Link objects provide a means of providing *aliases* or symbolic links within the namespace. Their variant part is defined as follows.

```
struct link_obj {
    zotypes    li_rtype;
    struct {
```

```

        uint_t    li_attrs_len;
        nis_attr   *li_attrs_val;
    } li_attrs;
    nis_name li_name;
}

```

The `li_rtype` member contains the object type of the object pointed to by the link. This is only a hint, since the object which the link points to may have changed or been removed. The fully qualified name of the object (table or otherwise) is specified in the member `li_name`.

NIS+ links can point to either other objects within the NIS+ namespace, or to entries within a NIS+ table. If the object pointed to by the link is a table and the member `li_attrs` has a nonzero number of attributes (index name/value pairs) specified, the table is searched when this link is followed. All entries which match the specified search pattern are returned. Note, that unless the flag `FOLLOW_LINKS` is specified, the [nis_lookup\(3NSL\)](#) function will always return non-entry objects.

Group Objects Group objects contain a membership list of NIS+ principals. The group objects' variant part is defined as follows.

```

struct group_obj {
    uint_t    gr_flags;
    struct {
        uint_t    gr_members_len;
        nis_name   *gr_members_val;
    } gr_members;
}

```

The `gr_flags` member contains flags that are currently unused. The `gr_members` structure contains the list of principals. For a complete description of how group objects are manipulated see [nis_groups\(3NSL\)](#).

Table Objects The NIS+ table object is analogous to a YP map. The differences stem from the access controls, and the variable schemas that NIS+ allows. The table objects data structure is defined as follows:

```

#define TA_BINARY    1
#define TA_CRYPT     2
#define TA_XDR       4
#define TA_SEARCHABLE 8
#define TA_CASE      16
#define TA_MODIFIED  32
struct table_col {
    char    *tc_name;
    uint_t   tc_flags;
    uint_t   tc_rights;
}
typedef struct table_col table_col;
struct table_obj {

```

```

char    *ta_type;
uint_t   ta_maxcol;
uchar_t   ta_sep;
struct {
    uint_t   ta_cols_len;
    table_col *ta_cols_val;
} ta_cols;
char    *ta_path;
}

```

The `ta_type` member contains a string that identifies the type of entries in this table. NIS+ does not enforce any policies as to the contents of this string. However, when entries are added to the table, the NIS+ service will check to see that they have the same “type” as the table as specified by this member.

The structure `ta_cols` contains two members. `ta_cols_val` is an array of `table_col` structures. The length of the array depends on the number of columns in the table; it is defined when the table is created and is stored in `ta_cols_len`. `ta_maxcol` also contains the number of columns in the table and always has the same value as `ta_cols_len`. Once the table is created, this length field cannot be changed.

The `ta_sep` character is used by client applications that wish to print out an entry from the table. Typically this is either space (“ ”) or colon (“:”).

The `ta_path` string defines a concatenation path for tables. This string contains an ordered list of fully qualified table names, separated by colons, that are to be searched if a search on this table fails to match any entries. This path is only used with the flag `FOLLOW_PATH` with a `nis_list()` call. See [nis_tables\(3NSL\)](#) for information on these flags.

In addition to checking the type, the service will check that the number of columns in an entry is the same as those in the table before allowing that entry to be added.

Each column has associated with it a name in `tc_name`, a set of flags in `tc_flags`, and a set of access rights in `tc_rights`. The name should be indicative of the contents of that column.

The `TA_BINARY` flag indicates that data in the column is binary (rather than text). Columns that are searchable cannot contain binary data. The `TA_CRYPT` flag specifies that the information in this column should be encrypted prior to sending it over the network. This flag has no effect in the export version of NIS+. The `TA_XDR` flag is used to tell the client application that the data in this column is encoded using the XDR protocol. The `TA_BINARY` flag must be specified with the `XDR` flag. Further, by convention, the name of a column that has the `TA_XDR` flag set is the name of the XDR function that will decode the data in that column.

The `TA_SEARCHABLE` flag specifies that values in this column can be searched. Searchable columns must contain textual data and must have a name associated with them. The flag `TA_CASE` specifies that searches involving this column ignore the case of the value in the column. At least one of the columns in the table should be searchable. Also, the combination

of all searchable column values should uniquely select an entry within the table. The `TA_MODIFIED` flag is set only when the table column is modified. When `TA_MODIFIED` is set, and the object is modified again, the modified access rights for the table column must be copied, not the default access rights.

Entry Objects Entry objects are stored in tables. The structure used to define the entry data is as follows.

```
#define EN_BINARY    1
#define EN_CRYPT     2
#define EN_XDR       4
#define EN_MODIFIED   8
struct entry_col {
    uint_t    ec_flags;
    struct {
        uint_t    ec_value_len;
        char      *ec_value_val;
    } ec_value;
}
typedef struct entry_col entry_col;
struct entry_obj {
    char      *en_type;
    struct {
        uint_t    en_cols_len;
        entry_col *en_cols_val;
    } en_cols;
}
```

The `en_type` member contains a string that specifies the type of data this entry represents. The NIS+ server will compare this string to the type string specified in the table object and disallow any updates or modifications if they differ.

The `en_cols` structure contains two members: `en_cols_len` and `en_cols_val`. `en_cols_val` is an array of `entry_col` structures. `en_cols_len` contains a count of the number of cells in the `en_cols_val` array and reflects the number of columns in the table -- it always contains the same value as the `table_obj.ta_cols.ta_cols_len` member from the table which contains the entry.

The `entry_col` structure contains information about the entry's per-column values. `ec_value` contains information about a particular value. It has two members: `ec_value_val`, which is the value itself, and `ec_value_len`, which is the length (in bytes) of the value. `entry_col` also contains the member `ec_flags`, which contains a set of flags for the entry.

The flags in `ec_flags` are primarily used when adding or modifying entries in a table. All columns that have the flag `EN_CRYPT` set will be encrypted prior to sending them over the network. Columns with `EN_BINARY` set are presumed to contain binary data. The server will ensure that the column in the table object specifies binary data prior to allowing the entry to be

added. When modifying entries in a table, only those columns that have changed need be sent to the server. Those columns should each have the EN_MODIFIED flag set to indicate this to the server.

See Also [NIS+\(1\)](#), [nis_groups\(3NSL\)](#), [nis_names\(3NSL\)](#), [nis_server\(3NSL\)](#), [nis_subr\(3NSL\)](#), [nis_tables\(3NSL\)](#)

Notes NIS+ might not be supported in future releases of the Solaris operating system. Tools to aid the migration from NIS+ to LDAP are available in the current Solaris release. For more information, visit <http://www.sun.com/directory/nisplus/transition.html>.

Name nis_ping, nis_checkpoint – NIS+ log administration functions

Synopsis cc [*flag* ...] *file* ... -lnsl [*library* ...]
#include <rpcsvc/nis.h>

```
void nis_ping(nis_name dirname, uint32_t utime, nis_object *dirobj);  
nis_result *nis_checkpoint(nis_name dirname);
```

Description nis_ping() is called by the master server for a directory when a change has occurred within that directory. The parameter *dirname* identifies the directory with the change. If the parameter *dirobj* is NULL, this function looks up the directory object for *dirname* and uses the list of replicas it contains. The parameter *utime* contains the timestamp of the last change made to the directory. This timestamp is used by the replicas when retrieving updates made to the directory.

The effect of calling nis_ping() is to schedule an update on the replica. A short time after a ping is received, typically about two minutes, the replica compares the last update time for its databases to the timestamp sent by the ping. If the ping timestamp is later, the replica establishes a connection with the master server and request all changes from the log that occurred after the last update that it had recorded in its local log.

nis_checkpoint() is used to force the service to checkpoint information that has been entered in the log but has not been checkpointed to disk. When called, this function checkpoints the database for each table in the directory, the database containing the directory and the transaction log. Care should be used in calling this function since directories that have seen a lot of changes may take several minutes to checkpoint. During the checkpointing process, the service will be unavailable for updates for all directories that are served by this machine as master.

nis_checkpoint() returns a pointer to a *nis_result* structure. See [nis_tables\(3NSL\)](#). This structure should be freed with *nis_freeresult()*. See [nis_names\(3NSL\)](#). The only items of interest in the returned result are the status value and the statistics.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [nislog\(1M\)](#), [nis_names\(3NSL\)](#), [nis_tables\(3NSL\)](#), [nisfiles\(4\)](#), [attributes\(5\)](#)

Notes NIS+ might not be supported in future releases of the Solaris operating system. Tools to aid the migration from NIS+ to LDAP are available in the current Solaris release. For more information, visit <http://www.sun.com/directory/nisplus/transition.html>.

Name `nis_server`, `nis_mkdir`, `nis_rmdir`, `nis_servstate`, `nis_stats`, `nis_getservlist`, `nis_freeservlist`, `nis_freetags` – miscellaneous NIS+ functions

Synopsis `cc [flag...] file... -lnsl [library...]`
`#include <rpcsvc/nis.h>`

```

nis_error nis_mkdir(nis_name dirname, nis_server *machine);

nis_error nis_rmdir(nis_name dirname, nis_server *machine);

nis_error nis_servstate(nis_server *machine, nis_tag *tags, int numtags,
    nis_tag **result);

nis_error nis_stats(nis_server *machine, nis_tag *tags, int numtags,
    nis_tag **result);

void nis_freetags(nis_tag *tags, int numtags);

nis_server **nis_getservlist(nis_name dirname);

void nis_freeservlist(nis_server **machines);

```

Description These functions provide a variety of services for NIS+ applications.

The `nis_mkdir()` function is used to create the necessary databases to support NIS+ service for a directory, *dirname*, on a server, *machine*. If this operation is successful, it means that the directory object describing *dirname* has been updated to reflect that server *machine* is serving the named directory. For a description of the `nis_server` structure, refer to [nis_objects\(3NSL\)](#).

Per-server and per-directory access restrictions can apply to the `nis_mkdir()` function. See [nisopaccess\(1\)](#).

The `nis_rmdir()` function is used to delete the directory, *dirname*, from the specified server machine. The *machine* parameter cannot be NULL. The `nis_rmdir()` function does not remove the directory *dirname* from the namespace or remove a server from the server list in the directory object. To remove a directory from the namespace you must call `nis_remove()` to remove the directory *dirname* from the namespace and call then `nis_rmdir()` for each server in the server list to remove the directory from the server. To remove a replica from the server list, you need to first call `nis_modify()` to remove the server from the directory object and then call `nis_rmdir()` to remove the replica.

Per-server and per-directory access restrictions can apply to `nis_rmdir()`. See [nisopaccess\(1\)](#).

For a description of the `nis_server` structure, refer to [nis_objects\(3NSL\)](#).

The `nis_servstate()` function is used to set and read the various state variables of the NIS+ servers. In particular the internal debugging state of the servers can be set and queried.

The `nis_stats()` function is used to retrieve statistics about how the server is operating. Tracking these statistics can help administrators determine when they need to add additional replicas or to break up a domain into two or more subdomains. For more information on reading statistics, see [nisstat\(1M\)](#)

The `nis_servstate()` and `nis_stats()` functions use the tag list. The tag list is a variable length array of `nis_tag` structures whose length is passed to the function in the `numtags` parameter. The set of legal tags are defined in the file `<rpcsvc/nis_tags.h>` which is included in `<rpcsvc/nis.h>`. Because these tags can and do vary between implementations of the NIS+ service, it is best to consult this file for the supported list. Passing unrecognized tags to a server will result in their `tag_value` member being set to the string `unknown`. Both of these functions return their results in malloced tag structure, `*result`. If there is an error, `*result` is set to `NULL`. The `tag_value` pointers points to allocated string memory which contains the results. Use `nis_freetags()` to free the tag structure.

Per-server and per-directory access restrictions can apply to the `NIS_SERVSTATE` or `NIS_STATUS` (`nis_stats()`) operations and their sub-operations (`tags`). See [nisopaccess\(1\)](#).

The `nis_getservlist()` function returns a null terminated list of `nis_server` structures that represent the list of servers that serve the domain named `dirname`. Servers from this list can be used when calling functions that require the name of a NIS+ server. For a description of the `nis_server` refer to [nis_objects\(3NSL\)](#). `nis_freeservlist()` frees the list of servers list of servers returned by `nis_getservlist()`. Note that this is the only legal way to free that list.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [nisopaccess\(1\)](#), [nisstat\(1M\)](#), [nis_names\(3NSL\)](#), [nis_objects\(3NSL\)](#), [nis_subr\(3NSL\)](#), [attributes\(5\)](#)

Notes NIS+ might not be supported in future releases of the Solaris operating system. Tools to aid the migration from NIS+ to LDAP are available in the current Solaris release. For more information, visit <http://www.sun.com/directory/nisplus/transition.html>.

Name nis_subr, nis_leaf_of, nis_name_of, nis_domain_of, nis_getnames, nis_freenames, nis_dir_cmp, nis_clone_object, nis_destroy_object, nis_print_object – NIS+ subroutines

Synopsis cc [*flag* ...] *file* ... -lnsl [*library* ...]
#include <rpcsvc/nis.h>

```

nis_name nis_leaf_of(const nis_name name);
nis_name nis_name_of(const nis_name name);
nis_name nis_domain_of(const nis_name name);
nis_name *nis_getnames(const nis_name name);
void nis_freenames(nis_name *namelist);
name_pos nis_dir_cmp(const nis_name n1, const nis_name n2);
nis_object *nis_clone_object(const nis_object *src, nis_object *dest);
void nis_destroy_object(nis_object *obj);
void nis_print_object(const nis_object *obj);

```

Description These subroutines are provided to assist in the development of NIS+ applications. They provide several useful operations on both NIS+ names and objects.

The first group, `nis_leaf_of()`, `nis_domain_of()`, and `nis_name_of()` provide the functions for parsing NIS+ names. `nis_leaf_of()` will return the first label in an NIS+ name. It takes into account the double quote character “” which can be used to protect embedded ‘.’ (dot) characters in object names. Note that the name returned will never have a trailing dot character. If passed the global root directory name “.”, it will return the null string.

`nis_domain_of()` returns the name of the NIS+ domain in which an object resides. This name will always be a fully qualified NIS+ name and ends with a dot. By iteratively calling `nis_leaf_of()` and `nis_domain_of()` it is possible to break a NIS+ name into its individual components.

`nis_name_of()` is used to extract the unique part of a NIS+ name. This function removes from the tail portion of the name all labels that are in common with the local domain. Thus if a machine were in domain `foo.bar.baz.` and `nis_name_of()` were passed a name `bob.friends.foo.bar.baz.`, then `nis_name_of()` would return the unique part, `bob.friends`. If the name passed to this function is not in either the local domain or one of its children, this function will return null.

`nis_getnames()` will return a list of candidate names for the name passed in as *name*. If this name is not fully qualified, `nis_getnames()` will generate a list of names using the default NIS+ directory search path, or the environment variable `NIS_PATH` if it is set. The returned array of pointers is terminated by a null pointer, and the memory associated with this array should be freed by calling `nis_freenames()`

Though `nis_dir_cmp()` can be used to compare any two NIS+ names, it is used primarily to compare domain names. This comparison is done in a case independent fashion, and the results are an enum of type `name_pos`. When the names passed to this function are identical, the function returns a value of `SAME_NAME`. If the name *n1* is a direct ancestor of name *n2*, then this function returns the result `HIGHER_NAME`. Similarly, if the name *n1* is a direct descendant of name *n2*, then this function returns the result `LOWER_NAME`. When the name *n1* is neither a direct ancestor nor a direct descendant of *n2*, as it would be if the two names were siblings in separate portions of the namespace, then this function returns the result `NOT_SEQUENTIAL`. Finally, if either name cannot be parsed as a legitimate name then this function returns the value `BAD_NAME`.

The second set of functions, consisting of `nis_clone_object()` and `nis_destroy_object()`, are used for manipulating objects. `nis_clone_object()` creates an exact duplicate of the NIS+ object *src*. If the value of *dest* is non-null, it creates the clone of the object into this object structure and allocate the necessary memory for the variable length arrays. If this parameter is null, a pointer to the cloned object is returned. Refer to [nis_objects\(3NSL\)](#) for a description of the `nis_object` structure.

`nis_destroy_object()` can be used to destroy an object created by `nis_clone_object()`. This will free up all memory associated with the object and free the pointer passed. If the object was cloned into an array using the *dest* parameter to `nis_clone_object()`, then the object *cannot* be freed with this function. Instead, the function `xdr_free(xdr_nis_object, dest)` must be used.

`nis_print_object()` prints out the contents of a NIS+ object structure on the standard output. Its primary use is for debugging NIS+ programs.

`nis_leaf_of()`, `nis_name_of()` and `nis_clone_object()` return their results as thread-specific data in multithreaded applications.

Environment Variables

NIS_PATH

This variable overrides the default NIS+ directory search path used by `nis_getnames()`. It contains an ordered list of directories separated by ':' (colon) characters. The '\$' (dollar sign) character is treated specially. Directory names that end in '\$' have the default domain appended to them, and a '\$' by itself is replaced by the list of directories between the default domain and the global root that are at least two levels deep. The default NIS+ directory search path is '\$'.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Safe

See Also [nis_names\(3NSL\)](#), [nis_objects\(3NSL\)](#), [nis_tables\(3NSL\)](#), [attributes\(5\)](#)

Notes NIS+ might not be supported in future releases of the Solaris operating system. Tools to aid the migration from NIS+ to LDAP are available in the current Solaris release. For more information, visit <http://www.sun.com/directory/nisplus/transition.html>.

Name `nis_tables`, `nis_list`, `nis_add_entry`, `nis_remove_entry`, `nis_modify_entry`, `nis_first_entry`, `nis_next_entry` – NIS+ table functions

Synopsis `cc [flag ...] file ... -lnsl [library ...]`
`#include <rpcsvc/nis.h>`

```
nis_result *nis_list(nis_name name, uint_t flags,
                    int (*callback)(nis_name table_name, nis_object *object,
                                     void *userdata), void *userdata);

nis_result *nis_add_entry(nis_name table_name, nis_object *object,
                          uint_t flags);

nis_result *nis_remove_entry(nis_name name, nis_object *object,
                              uint_t flags);

nis_result *nis_modify_entry(nis_name name, nis_object *object,
                              uint_t flags);

nis_result *nis_first_entry(nis_name table_name);

nis_result *nis_next_entry(nis_name table_name, netobj *cookie);

void nis_freeresult(nis_result *result);
```

Description Use the NIS+ table functions to search and modify NIS+ tables. `nis_list()` is used to search a table in the NIS+ namespace. `nis_first_entry()` and `nis_next_entry()` are used to enumerate a table one entry at a time. `nis_add_entry()`, `nis_remove_entry()`, and `nis_modify_entry()` are used to change the information stored in a table. `nis_freeresult()` is used to free the memory associated with the `nis_result` structure.

Entries within a table are named by NIS+ indexed names. An indexed name is a compound name that is composed of a search criteria and a simple NIS+ name that identifies a table object. A search criteria is a series of column names and their associated values enclosed in bracket '[']' characters. Indexed names have the following form:

```
[ colname=value, . . . ], tablename
```

The list function, `nis_list()`, takes an indexed name as the value for the *name* parameter. Here, the *tablename* should be a fully qualified NIS+ name unless the `EXPAND_NAME` flag (described below) is set. The second parameter, *flags*, defines how the function will respond to various conditions. The value for this parameter is created by logically ORing together one or more flags from the following list.

FOLLOW_LINKS If the table specified in *name* resolves to be a LINK type object (see [nis_objects\(3NSL\)](#)), this flag specifies that the client library follow that link and do the search at that object. If this flag is not set and the name resolves to a link, the error `NIS_NOTSEARCHABLE` will be returned.

FOLLOW_PATH This flag specifies that if the entry is not found within this table, the list operation should follow the path specified in the table object. When used

in conjunction with the `ALL_RESULTS` flag below, it specifies that the path should be followed regardless of the result of the search. When used in conjunction with the `FOLLOW_LINKS` flag above, named tables in the path that resolve to links will be followed until the table they point to is located. If a table in the path is not reachable because no server that serves it is available, the result of the operation will be either a “soft” success or a “soft” failure to indicate that not all tables in the path could be searched. If a name in the path names is either an invalid or non-existent object then it is silently ignored.

<code>HARD_LOOKUP</code>	This flag specifies that the operation should continue trying to contact a server of the named table until a definitive result is returned (such as <code>NIS_NOTFOUND</code>).
<code>ALL_RESULTS</code>	This flag can only be used in conjunction with <code>FOLLOW_PATH</code> and a callback function. When specified, it forces all of the tables in the path to be searched. If <i>name</i> does not specify a search criteria (imply that all entries are to be returned), then this flag will cause all of the entries in all of the tables in the path to be returned.
<code>NO_CACHE</code>	This flag specifies that the client library should bypass any client object caches and get its information directly from either the master server or a replica server for the named table.
<code>MASTER_ONLY</code>	This flag is even stronger than <code>NO_CACHE</code> in that it specifies that the client library should <i>only</i> get its information from the master server for a particular table. This guarantees that the information will be up to date. However, there may be severe performance penalties associated with contacting the master server directly on large networks. When used in conjunction with the <code>HARD_LOOKUP</code> flag, this will block the list operation until the master server is up and available.
<code>EXPAND_NAME</code>	When specified, the client library will attempt to expand a partially qualified name by calling <code>nis_getnames()</code> , which uses the environment variable <code>NIS_PATH</code> . See nis_local_names(3NSL) .
<code>RETURN_RESULT</code>	This flag is used to specify that a copy of the returning object be returned in the <code>nis_result</code> structure if the operation was successful.

The third parameter to `nis_list()`, *callback*, is an optional pointer to a function that will process the `ENTRY` type objects that are returned from the search. If this pointer is `NULL`, then all entries that match the search criteria are returned in the *nis_result* structure, otherwise this function will be called once for each entry returned. When called, this function should return `0` when additional objects are desired and `1` when it no longer wishes to see any more objects. The fourth parameter, *userdata*, is simply passed to callback function along with the returned entry object. The client can use this pointer to pass state information or other relevant data that the callback function might need to process the entries.

The `nis_list()` function is not MT-Safe with callbacks.

`nis_add_entry()` will add the NIS+ object to the NIS+ *table_name*. The *flags* parameter is used to specify the failure semantics for the add operation. The default (*flags* equal 0) is to fail if the entry being added already exists in the table. The `ADD_OVERWRITE` flag may be used to specify that existing object is to be overwritten if it exists, (a modify operation) or added if it does not exist. With the `ADD_OVERWRITE` flag, this function will fail with the error `NIS_PERMISSION` if the existing object does not allow modify privileges to the client.

If the flag `RETURN_RESULT` has been specified, the server will return a copy of the resulting object if the operation was successful.

`nis_remove_entry()` removes the identified entry from the table or a set of entries identified by *table_name*. If the parameter *object* is non-null, it is presumed to point to a cached copy of the entry. When the removal is attempted, and the object that would be removed is not the same as the cached object pointed to by *object* then the operation will fail with an `NIS_NOTSAMEOBJ` error. If an object is passed with this function, the search criteria in *name* is optional as it can be constructed from the values within the entry. However, if no object is present, the search criteria must be included in the *name* parameter. If the *flags* variable is null, and the search criteria does not uniquely identify an entry, the `NIS_NOTUNIQUE` error is returned and the operation is aborted. If the flag parameter `REM_MULTIPLE` is passed, and if remove permission is allowed for each of these objects, then all objects that match the search criteria will be removed. Note that a null search criteria and the `REM_MULTIPLE` flag will remove all entries in a table.

`nis_modify_entry()` modifies an object identified by *name*. The parameter *object* should point to an entry with the `EN_MODIFIED` flag set in each column that contains new information.

The owner, group, and access rights of an entry are modified by placing the modified information into the respective fields of the parameter, *object*: *zo_owner*, *zo_group*, and *zo_access*.

These columns will replace their counterparts in the entry that is stored in the table. The entry passed must have the same number of columns, same type, and valid data in the modified columns for this operation to succeed.

If the *flags* parameter contains the flag `MOD_SAMEOBJ` then the object pointed to by *object* is assumed to be a cached copy of the original object. If the OID of the object passed is different than the OID of the object the server fetches, then the operation fails with the `NIS_NOTSAMEOBJ` error. This can be used to implement a simple read-modify-write protocol which will fail if the object is modified before the client can write the object back.

If the flag `RETURN_RESULT` has been specified, the server will return a copy of the resulting object if the operation was successful.

`nis_first_entry()` fetches entries from a table one at a time. This mode of operation is extremely inefficient and callbacks should be used instead wherever possible. The table containing the entries of interest is identified by *name*. If a search criteria is present in *name* it is ignored. The value of *cookie* within the `nis_result` structure must be copied by the caller into local storage and passed as an argument to `nis_next_entry()`.

`nis_next_entry()` retrieves the “next” entry from a table specified by *table_name*. The order in which entries are returned is not guaranteed. Further, should an update occur in the table between client calls to `nis_next_entry()` there is no guarantee that an entry that is added or modified will be seen by the client. Should an entry be removed from the table that would have been the “next” entry returned, the error `NIS_CHAINBROKEN` is returned instead.

The path used when the flag `FOLLOW_PATH` is specified, is the one present in the *first* table searched. The path values in tables that are subsequently searched are ignored.

It is legal to call functions that would access the nameservice from within a list callback. However, calling a function that would itself use a callback, or calling `nis_list()` with a callback from within a list callback function is not currently supported.

There are currently no known methods for `nis_first_entry()` and `nis_next_entry()` to get their answers from only the master server.

The `nis_list()` function is not MT-Safe with callbacks. `nis_list()` callbacks are serialized. A call to `nis_list()` with a callback from within `nis_list()` will deadlock. `nis_list()` with a callback cannot be called from an rpc server. See [rpc_svc_calls\(3NSL\)](#). Otherwise, this function is MT-Safe.

Return Values These functions return a pointer to a structure of type `nis_result`:

```
struct nis_result {
    nis_error    status;
    struct {
        uint_t    objects_len;
        nis_object *objects_val;
    } objects;
    netobj      cookie;
    uint32_t    zticks;
    uint32_t    dticks;
    uint32_t    aticks;
    uint32_t    cticks;
};
```

The *status* member contains the error status of the the operation. A text message that describes the error can be obtained by calling the function `nis_strerror()`. See [nis_error\(3NSL\)](#).

The objects structure contains two members. *objects_val* is an array of *nis_object* structures; *objects_len* is the number of cells in the array. These objects will be freed by a call to `nis_freeresult()`. See [nis_names\(3NSL\)](#). If you need to keep a copy of one or more objects, they can be copied with the function `nis_clone_object()` and freed with the function `nis_destroy_object()`. See [nis_server\(3NSL\)](#).

The various ticks contain details of where the time, in microseconds, was taken during a request. They can be used to tune one's data organization for faster access and to compare different database implementations.

- | | |
|---------------|--|
| <i>zticks</i> | The time spent in the NIS+ service itself, this count starts when the server receives the request and stops when it sends the reply. |
| <i>dticks</i> | The time spent in the database backend, this time is measured from the time a database call starts, until a result is returned. If the request results in multiple calls to the database, this is the sum of all the time spent in those calls. |
| <i>aticks</i> | The time spent in any “accelerators” or caches. This includes the time required to locate the server needed to resolve the request. |
| <i>cticks</i> | The total time spent in the request, this clock starts when you enter the client library and stops when a result is returned. By subtracting the sum of the other ticks values from this value you can obtain the local overhead of generating a NIS+ request. |

Subtracting the value in *dticks* from the value in *zticks* will yield the time spent in the service code itself. Subtracting the sum of the values in *zticks* and *aticks* from the value in *cticks* will yield the time spent in the client library itself. Note: all of the tick times are measured in microseconds.

Errors The client library can return a variety of error returns and diagnostics. The more salient ones are documented below.

- | | |
|------------------|---|
| NIS_BADATTRIBUTE | The name of an attribute did not match up with a named column in the table, or the attribute did not have an associated value. |
| NIS_BADNAME | The name passed to the function is not a legal NIS+ name. |
| NIS_BADREQUEST | A problem was detected in the request structure passed to the client library. |
| NIS_CACHEEXPIRED | The entry returned came from an object cache that has <i>expired</i> . This means that the time to live value has gone to zero and the entry may have changed. If the flag NO_CACHE was passed to the lookup function then the lookup function will retry the operation to get an unexpired copy of the object. |
| NIS_CBERROR | An RPC error occurred on the server while it was calling back to the client. The transaction was aborted at that time and any unsent data was discarded. |

NIS_CBRESULTS	Even though the request was successful, all of the entries have been sent to your callback function and are thus not included in this result.
NIS_FOREIGNNS	The name could not be completely resolved. When the name passed to the function would resolve in a namespace that is outside the NIS+ name tree, this error is returned with a NIS+ object of type DIRECTORY. The returned object contains the type of namespace and contact information for a server within that namespace.
NIS_INVALIDOBJ	The object pointed to by <i>object</i> is not a valid NIS+ entry object for the given table. This could occur if it had a mismatched number of columns, or a different data type than the associated column in the table, for example, binary or text.
NIS_LINKNAMEERROR	The name passed resolved to a LINK type object and the contents of the object pointed to an invalid name.
NIS_MODFAIL	The attempted modification failed for some reason.
NIS_NAMEEXISTS	An attempt was made to add a name that already exists. To add the name, first remove the existing name and then add the new name or modify the existing named object.
NIS_NAMEUNREACHABLE	This soft error indicates that a server for the desired directory of the named table object could not be reached. This can occur when there is a network partition or the server has crashed. Attempting the operation again may succeed. See the HARD_LOOKUP flag.
NIS_NOCALLBACK	The server was unable to contact the callback service on your machine. This results in no data being returned.
NIS_NOMEMORY	Generally a fatal result. It means that the service ran out of heap space.
NIS_NOSUCHNAME	This hard error indicates that the named directory of the table object does not exist. This occurs when the server that should be the parent of the server that serves the table, does not know about the directory in which the table resides.
NIS_NOSUCHTABLE	The named table does not exist.
NIS_NOT_ME	A request was made to a server that does not serve the given name. Normally this will not occur, however if you are not using the built in location mechanism for servers, you may see this if your mechanism is broken.

NIS_NOTFOUND	<p>No entries in the table matched the search criteria. If the search criteria was null (return all entries) then this result means that the table is empty and may safely be removed by calling the <code>nis_remove()</code>.</p> <p>If the FOLLOW_PATH flag was set, this error indicates that none of the tables in the path contain entries that match the search criteria.</p>
NIS_NOTMASTER	<p>A change request was made to a server that serves the name, but it is not the master server. This can occur when a directory object changes and it specifies a new master server. Clients that have cached copies of the directory object in the <code>/var/nis/NIS_SHARED_DIRCACHE</code> file will need to have their cache managers restarted to flush this cache. Use <code>nis_cachemgr -i</code>.</p>
NIS_NOTSAMEOBJ	<p>An attempt to remove an object from the namespace was aborted because the object that would have been removed was not the same object that was passed in the request.</p>
NIS_NOTSEARCHABLE	<p>The table name resolved to a NIS+ object that was not searchable.</p>
NIS_PARTIAL	<p>This result is similar to NIS_NOTFOUND except that it means the request succeeded but resolved to zero entries. When this occurs, the server returns a copy of the table object instead of an entry so that the client may then process the path or implement some other local policy.</p>
NIS_RPCERROR	<p>This fatal error indicates the RPC subsystem failed in some way. Generally there will be a <code>syslog(3C)</code> message indicating why the RPC request failed.</p>
NIS_S_NOTFOUND	<p>The named entry does not exist in the table, however not all tables in the path could be searched, so the entry may exist in one of those tables.</p>
NIS_S_SUCCESS	<p>Even though the request was successful, a table in the search path was not able to be searched, so the result may not be the same as the one you would have received if that table had been accessible.</p>
NIS_SUCCESS	<p>The request was successful.</p>
NIS_SYSTEMERROR	<p>Some form of generic system error occurred while attempting the request. Check the <code>syslog(3C)</code> record for error messages from the server.</p>
NIS_TOOMANYATTRS	<p>The search criteria passed to the server had more attributes than the table had searchable columns.</p>

NIS_TRYAGAIN	The server connected to was too busy to handle your request. <code>add_entry()</code> , <code>remove_entry()</code> , and <code>modify_entry()</code> return this error when the master server is currently updating its internal state. It can be returned to <code>nis_list()</code> when the function specifies a callback and the server does not have the resources to handle callbacks.
NIS_TYPEMISMATCH	An attempt was made to add or modify an entry in a table, and the entry passed was of a different type than the table.

Environment Variables `NIS_PATH` When set, this variable is the search path used by `nis_list()` if the flag `EXPAND_NAME` is set.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe with exceptions

See Also [niscat\(1\)](#), [niserror\(1\)](#), [nismatch\(1\)](#), [nis_cachemgr\(1M\)](#), [nis_clone_object\(3NSL\)](#), [n_nis_destroy_object\(3NSL\)](#), [nis_error\(3NSL\)](#), [nis_getnames\(3NSL\)](#), [nis_local_names\(3NSL\)](#), [nis_names\(3NSL\)](#), [nis_objects\(3NSL\)](#), [nis_server\(3NSL\)](#), [rpc_svc_calls\(3NSL\)](#), [syslog\(3C\)](#), [attributes\(5\)](#)

Warnings Use the flag `HARD_LOOKUP` carefully since it can cause the application to block indefinitely during a network partition.

Notes NIS+ might not be supported in future releases of the Solaris operating system. Tools to aid the migration from NIS+ to LDAP are available in the current Solaris release. For more information, visit <http://www.sun.com/directory/nisplus/transition.html>.

Name nlsgetcall – get client's data passed via the listener

Synopsis #include <sys/tiuser.h>

```
struct t_call *nlsgetcall(int fildes);
```

Description nlsgetcall() allows server processes started by the listener process to access the client's t_call structure, that is, the *sndcall* argument of t_connect(3NSL).

The t_call structure returned by nlsgetcall() can be released using t_free(3NSL).

nlsgetcall() returns the address of an allocated t_call structure or NULL if a t_call structure cannot be allocated. If the t_alloc() succeeds, undefined environment variables are indicated by a negative *len* field in the appropriate netbuf structure. A *len* field of zero in the netbuf structure is valid and means that the original buffer in the listener's t_call structure was NULL.

Return Values A NULL pointer is returned if a t_call structure cannot be allocated by t_alloc(). t_errno can be inspected for further error information. Undefined environment variables are indicated by a negative length field (*len*) in the appropriate netbuf structure.

Files /usr/lib/libnls.so.1 shared object

Attributes See attributes(5) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Unsafe

See Also nlsadmin(1M), getenv(3C), t_alloc(3NSL), t_connect(3NSL), t_error(3NSL), t_free(3NSL), t_sync(3NSL), attributes(5)

Warnings The *len* field in the netbuf structure is defined as being unsigned. In order to check for error returns, it should first be cast to an int.

The listener process limits the amount of user data (*udata*) and options data (*opt*) to 128 bytes each. Address data *addr* is limited to 64 bytes. If the original data was longer, no indication of overflow is given.

Notes Server processes must call t_sync(3NSL) before calling this routine.

This interface is unsafe in multithreaded applications. Unsafe interfaces should be called only from the main thread.

Name nlsprovider – get name of transport provider

Synopsis `char *nlsprovider(void);`

Description `nlsprovider()` returns a pointer to a null-terminated character string which contains the name of the transport provider as placed in the environment by the listener process. If the variable is not defined in the environment, a NULL pointer is returned.

The environment variable is only available to server processes started by the listener process.

Return Values If the variable is not defined in the environment, a NULL pointer is returned.

Files `/usr/lib/libnls.so.1` shared object

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Unsafe

See Also [nlsadmin\(1M\)](#), [attributes\(5\)](#)

Notes This interface is unsafe in multithreaded applications. Unsafe interfaces should be called only from the main thread.

Name nlsrequest – format and send listener service request message

Synopsis #include <listen.h>

```
int nlsrequest(int fildes, char *service_code);
extern int _nlslogt_errno;
extern char *_nlsrmsg;
```

Description Given a virtual circuit to a listener process (*fildes*) and a service code of a server process, `nlsrequest()` formats and sends a *service request message* to the remote listener process requesting that it start the given service. `nlsrequest()` waits for the remote listener process to return a *service request response message*, which is made available to the caller in the static, null-terminated data buffer pointed to by `_nlsrmsg`. The *service request response message* includes a success or failure code and a text message. The entire message is printable.

Return Values The success or failure code is the integer return code from `nlsrequest()`. Zero indicates success, other negative values indicate `nlsrequest()` failures as follows:

−1 Error encountered by `nlsrequest()`, see `t_errno`.

Positive values are error return codes from the *listener* process. Mnemonics for these codes are defined in `<listen.h>`.

- 2 Request message not interpretable.
- 3 Request service code unknown.
- 4 Service code known, but currently disabled.

If non-null, `_nlsrmsg` contains a pointer to a static, null-terminated character buffer containing the *service request response message*. Note that both `_nlsrmsg` and the data buffer are overwritten by each call to `nlsrequest()`.

If `_nlslog` is non-zero, `nlsrequest()` prints error messages on `stderr`. Initially, `_nlslog` is zero.

Files /usr/lib/libnls.so.1 shared object

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Unsafe

See Also [nlsadmin\(1M\)](#), [t_error\(3NSL\)](#), [t_snd\(3NSL\)](#), [t_rcv\(3NSL\)](#), [attributes\(5\)](#)

Warnings `nlsrequest()` cannot always be certain that the remote server process has been successfully started. In this case, `nlsrequest()` returns with no indication of an error and the caller will receive notification of a disconnect event by way of a `T_LOOK` error before or during the first `t_snd()` or `t_rcv()` call.

Notes These interfaces are unsafe in multithreaded applications. Unsafe interfaces should be called only from the main thread.

Name rcmd, rcmd_af, rresvport, rresvport_af, ruserok – routines for returning a stream to a remote command

Synopsis

```
cc [ flag ... ] file... -lsocket -lnsl [ library... ]
#include <netdb.h>
#include <unistd.h>

int rcmd(char **ahost, unsigned short inport, const char *luser,
          const char *ruser, const char *cmd, int *fd2p);

int rcmd_af(char **ahost, unsigned short inport, const char *luser,
             const char *ruser, const char *cmd, int *fd2p, int af);

int rresvport(int *port);

int rresvport_af(int *port, int af);

int ruserok(const char *rhost, int suser, const char *ruser,
             const char *luser);
```

Description The `rcmd()` function is used by the superuser to execute a command on a remote machine with an authentication scheme based on reserved port numbers. An `AF_INET` socket is returned with `rcmd()`. The `rcmd_af()` function supports `AF_INET`, `AF_INET6` or `AF_UNSPEC` for the address family. An application can choose which type of socket is returned by passing `AF_INET` or `AF_INET6` as the address family. The use of `AF_UNSPEC` means that the caller will accept any address family. Choosing `AF_UNSPEC` provides a socket that best suits the connectivity to the remote host.

The `rresvport()` function returns a descriptor to a socket with an address in the privileged port space. The `rresvport_af()` function is the equivalent to `rresvport()`, except that you can choose `AF_INET` or `AF_INET6` as the socket address family to be returned by `rresvport_af()`. `AF_UNSPEC` does not apply to the `rresvport()` function.

The `ruserok()` function is a routine used by servers to authenticate clients that request as service with `rcmd`.

All of these functions are present in the same file and are used by the `in.rshd(1M)` server among others.

The `rcmd()` and `rcmd_af()` functions look up the host `*ahost` using [getaddrinfo\(3SOCKET\)](#) and return `-1` if the host does not exist. Otherwise, `*ahost` is set to the standard name of the host and a connection is established to a server residing at the Internet port `inport`.

If the connection succeeds, a socket in the Internet domain of type `SOCK_STREAM` is returned to the caller. The socket is given to the remote command as standard input (file descriptor 0) and standard output (file descriptor 1). If `fd2p` is non-zero, an auxiliary channel to a control process is set up and a descriptor for it is placed in `*fd2p`. The control process returns diagnostic output file (descriptor 2) from the command on the auxiliary channel. The control process also accepts bytes on this channel as signal numbers to be forwarded to the process

group of the command. If *fd2p* is 0, the standard error (file descriptor 2) of the remote command is made the same as its standard output. No provision is made for sending arbitrary signals to the remote process, other than possibly sending out-of-band data.

The protocol is described in detail in [in.rshd\(1M\)](#).

The `rresvport()` and `rresvport_af()` functions are used to obtain a socket bound to a privileged port number. The socket is suitable for use by `rcmd()` and `rresvport_af()` and several other routines. Privileged Internet ports are those in the range 1 to 1023. Only the superuser is allowed to bind a socket to a privileged port number. The application must pass in *port*, which must be in the range 512 to 1023. The system first tries to bind to that port number. If it fails, the system then tries to bind to another unused privileged port, if one is available.

The `ruserok()` function takes a remote host name returned by the `gethostbyaddr()` function with two user names and a flag to indicate whether the local user's name is that of the superuser. See [gethostbyname\(3NSL\)](#). The `ruserok()` function then checks the files `/etc/hosts.equiv` and possibly `.rhosts` in the local user's home directory to see if the request for service is allowed. A 0 value is returned if the machine name is listed in the `/etc/hosts.equiv` file, or if the host and remote user name are found in the `.rhosts` file. Otherwise, the `ruserok()` function returns -1. If the superuser flag is 1, the `/etc/hosts.equiv` is not checked.

The error code EAGAIN is overloaded to mean "All network ports in use."

Return Values The `rcmd()` and `rcmd_af()` functions return a valid socket descriptor upon success. The functions returns -1 upon error and print a diagnostic message to standard error.

The `rresvport()` and `rresvport_af()` functions return a valid, bound socket descriptor upon success. The functions return -1 upon error with the global value `errno` set according to the reason for failure.

Files `/etc/hosts.equiv` system trusted hosts and users
`~/.rhosts` user's trusted hosts and users

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Unsafe

This interface is Unsafe in multithreaded applications. Unsafe interfaces should be called only from the main thread.

See Also [rlogin\(1\)](#), [rsh\(1\)](#), [in.rexecd\(1M\)](#), [in.rshd\(1M\)](#), [Intro\(2\)](#), [getaddrinfo\(3SOCKET\)](#), [gethostbyname\(3NSL\)](#), [rexec\(3SOCKET\)](#), [attributes\(5\)](#)

Name recv, recvfrom, recvmsg – receive a message from a socket

Synopsis

```
cc [ flag... ] file... -lsocket -lnsl [ library... ]
#include <sys/types.h>
#include <sys/socket.h>
#include <sys/uio.h>

ssize_t recv(int s, void *buf, size_t len, int flags);

ssize_t recvfrom(int s, void *buf, size_t len, int flags,
    struct sockaddr *from, socklen_t *fromlen);

ssize_t recvmsg(int s, struct msghdr *msg, int flags);
```

Description The `recv()`, `recvfrom()`, and `recvmsg()` functions are used to receive messages from another socket. The `s` socket is created with [socket\(3SOCKET\)](#).

If *from* is a non-NULL pointer, the source address of the message is filled in. The value-result parameter *fromlen* is initialized to the size of the buffer associated with *from* and modified on return to indicate the actual size of the address stored in the buffer. The length of the message is returned. If a message is too long to fit in the supplied buffer, excess bytes may be discarded depending on the type of socket from which the message is received. See [socket\(3SOCKET\)](#).

If no messages are available at the socket, the receive call waits for a message to arrive. If the socket is non-blocking, -1 is returned with the external variable `errno` set to `EWOULDBLOCK`. See [fcntl\(2\)](#).

For processes on the same host, `recvmsg()` can be used to receive a file descriptor from another process, but it cannot receive ancillary data. See [libxnet\(3LIB\)](#).

If a zero-length buffer is specified for a message, an EOF condition results that is indistinguishable from the successful transfer of a file descriptor. For that reason, one or more bytes of data should be provided when `recvmsg()` passes a file descriptor.

The [select\(3C\)](#) call can be used to determine when more data arrives.

The *flags* parameter is formed by an OR operation on one or more of the following:

MSG_OOB	Read any <i>out-of-band</i> data present on the socket rather than the regular <i>in-band</i> data.
MSG_PEEK	Peek at the data present on the socket. The data is returned, but not consumed to allow a subsequent receive operation to see the same data.
MSG_WAITALL	Messages are blocked until the full amount of data requested is returned. The <code>recv()</code> function can return a smaller amount of data if a signal is caught, the connection is terminated, <code>MSG_PEEK</code> is specified, or if an error is pending for the socket.

MSG_DONTWAIT Pending messages received on the connection are returned. If data is unavailable, the function does not block. This behavior is the equivalent to specifying `O_NONBLOCK` on the file descriptor of a socket, except that write requests are unaffected.

The `recvmsg()` function call uses a `msghdr` structure defined in `<sys/socket.h>` to minimize the number of directly supplied parameters.

Return Values Upon successful completion, these functions return the number of bytes received. Otherwise, they return `-1` and set `errno` to indicate the error.

Errors The `recv()`, `recvfrom()`, and `recvmsg()` functions return errors under the following conditions:

EBADF	The <code>s</code> file descriptor is invalid.
EINVAL	The <code>MSG_OOB</code> flag is set and no out-of-band data is available.
EINTR	The operation is interrupted by the delivery of a signal before any data is available to be received.
EIO	An I/O error occurs while reading from or writing to the file system.
ENOMEM	Insufficient user memory is available to complete operation.
ENOSR	Insufficient STREAMS resources are available for the operation to complete.
ENOTSOCK	<code>s</code> is not a socket.
ESTALE	A stale NFS file handle exists.
EWOULDBLOCK	The socket is marked non-blocking and the requested operation would block.
ECONNREFUSED	The requested connection was refused by the peer. For connected IPv4 and IPv6 datagram sockets, this indicates that the system received an ICMP Destination Port Unreachable message from the peer.

The `recv()` and `recvfrom()` functions fail under the following conditions:

EINVAL The `len` argument overflows a `ssize_t`.

The `recvmsg()` function returns errors under the following conditions:

EINVAL	The <code>msg_iovlen</code> member of the <code>msghdr</code> structure pointed to by <code>msg</code> is less than or equal to <code>0</code> , or greater than <code>[IOV_MAX]</code> . See Intro(2) for a definition of <code>[IOV_MAX]</code> .
EINVAL	One of the <code>iov_len</code> values in the <code>msg_iov</code> array member of the <code>msghdr</code> structure pointed to by <code>msg</code> is negative, or the sum of the <code>iov_len</code> values in the <code>msg_iov</code> array overflows a <code>ssize_t</code> .

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [fcntl\(2\)](#), [ioctl\(2\)](#), [read\(2\)](#), [connect\(3SOCKET\)](#), [getsockopt\(3SOCKET\)](#), [libxnet\(3LIB\)](#), [select\(3C\)](#), [send\(3SOCKET\)](#), [socket\(3SOCKET\)](#), [socket.h\(3HEAD\)](#), [attributes\(5\)](#)

Name recv – receive a message from a connected socket

Synopsis cc [*flag* ...] *file* ... -lxnet [*library* ...]
#include <sys/socket.h>

```
ssize_t recv(int socket, void *buffer, size_t length, int flags);
```

Description The `recv()` function receives a message from a connection-mode or connectionless-mode socket. It is normally used with connected sockets because it does not permit the application to retrieve the source address of received data. The function takes the following arguments:

socket Specifies the socket file descriptor.

buffer Points to a buffer where the message should be stored.

length Specifies the length in bytes of the buffer pointed to by the *buffer* argument.

flags Specifies the type of message reception. Values of this argument are formed by logically OR'ing zero or more of the following values:

MSG_PEEK	Peeks at an incoming message. The data is treated as unread and the next <code>recv()</code> or similar function will still return this data.
MSG_OOB	Requests out-of-band data. The significance and semantics of out-of-band data are protocol-specific.
MSG_WAITALL	Requests that the function block until the full amount of data requested can be returned. The function may return a smaller amount of data if a signal is caught, if the connection is terminated, if MSG_PEEK was specified, or if an error is pending for the socket.

The `recv()` function returns the length of the message written to the buffer pointed to by the *buffer* argument. For message-based sockets such as `SOCK_DGRAM` and `SOCK_SEQPACKET`, the entire message must be read in a single operation. If a message is too long to fit in the supplied buffer, and `MSG_PEEK` is not set in the *flags* argument, the excess bytes are discarded. For stream-based sockets such as `SOCK_STREAM`, message boundaries are ignored. In this case, data is returned to the user as soon as it becomes available, and no data is discarded.

If the `MSG_WAITALL` flag is not set, data will be returned only up to the end of the first message.

If no messages are available at the socket and `O_NONBLOCK` is not set on the socket's file descriptor, `recv()` blocks until a message arrives. If no messages are available at the socket and `O_NONBLOCK` is set on the socket's file descriptor, `recv()` fails and sets `errno` to `EAGAIN` or `EWOULDBLOCK`.

Usage The `recv()` function is identical to `recvfrom(3XNET)` with a zero *address_len* argument, and to `read()` if no flags are used.

The `select(3C)` and `poll(2)` functions can be used to determine when data is available to be received.

Return Values Upon successful completion, `recv()` returns the length of the message in bytes. If no messages are available to be received and the peer has performed an orderly shutdown, `recv()` returns 0. Otherwise, `-1` is returned and `errno` is set to indicate the error.

Errors The `recv()` function will fail if:

EAGAIN	
EWOULDBLOCK	The socket's file descriptor is marked <code>O_NONBLOCK</code> and no data is waiting to be received; or <code>MSG_OOB</code> is set and no out-of-band data is available and either the socket's file descriptor is marked <code>O_NONBLOCK</code> or the socket does not support blocking to await out-of-band data.
EBADF	The <i>socket</i> argument is not a valid file descriptor.
ECONNRESET	A connection was forcibly closed by a peer.
EFAULT	The <i>buffer</i> parameter can not be accessed or written.
EINTR	The <code>recv()</code> function was interrupted by a signal that was caught, before any data was available.
EINVAL	The <code>MSG_OOB</code> flag is set and no out-of-band data is available.
ENOTCONN	A receive is attempted on a connection-mode socket that is not connected.
ENOTSOCK	The <i>socket</i> argument does not refer to a socket.
EOPNOTSUPP	The specified flags are not supported for this socket type or protocol.
ETIMEDOUT	The connection timed out during connection establishment, or due to a transmission timeout on active connection.

The `recv()` function may fail if:

EIO	An I/O error occurred while reading from or writing to the file system.
ENOBUFS	Insufficient resources were available in the system to perform the operation.
ENOMEM	Insufficient memory was available to fulfill the request.
ENOSR	There were insufficient STREAMS resources available for the operation to complete.

Attributes See `attributes(5)` for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also [poll\(2\)](#), [recvmsg\(3XNET\)](#), [recvfrom\(3XNET\)](#), [select\(3C\)](#), [send\(3XNET\)](#), [sendmsg\(3XNET\)](#), [sendto\(3XNET\)](#), [shutdown\(3XNET\)](#), [socket\(3XNET\)](#), [attributes\(5\)](#), [standards\(5\)](#)

Name recvfrom – receive a message from a socket

Synopsis `cc [flag ...] file ... -lxnet [library ...]`
`#include <sys/socket.h>`

```
ssize_t recvfrom(int socket, void *restrict buffer, size_t length,
                 int flags, struct sockaddr *restrict address,
                 socklen_t *restrict address_len);
```

Description The `recvfrom()` function receives a message from a connection-mode or connectionless-mode socket. It is normally used with connectionless-mode sockets because it permits the application to retrieve the source address of received data.

The function takes the following arguments:

<i>socket</i>	Specifies the socket file descriptor.						
<i>buffer</i>	Points to the buffer where the message should be stored.						
<i>length</i>	Specifies the length in bytes of the buffer pointed to by the <i>buffer</i> argument.						
<i>flags</i>	Specifies the type of message reception. Values of this argument are formed by logically OR'ing zero or more of the following values: <table data-bbox="528 798 1328 1154"> <tr> <td>MSG_PEEK</td><td>Peeks at an incoming message. The data is treated as unread and the next <code>recvfrom()</code> or similar function will still return this data.</td></tr> <tr> <td>MSG_OOB</td><td>Requests out-of-band data. The significance and semantics of out-of-band data are protocol-specific.</td></tr> <tr> <td>MSG_WAITALL</td><td>Requests that the function block until the full amount of data requested can be returned. The function may return a smaller amount of data if a signal is caught, if the connection is terminated, if MSG_PEEK was specified, or if an error is pending for the socket.</td></tr> </table>	MSG_PEEK	Peeks at an incoming message. The data is treated as unread and the next <code>recvfrom()</code> or similar function will still return this data.	MSG_OOB	Requests out-of-band data. The significance and semantics of out-of-band data are protocol-specific.	MSG_WAITALL	Requests that the function block until the full amount of data requested can be returned. The function may return a smaller amount of data if a signal is caught, if the connection is terminated, if MSG_PEEK was specified, or if an error is pending for the socket.
MSG_PEEK	Peeks at an incoming message. The data is treated as unread and the next <code>recvfrom()</code> or similar function will still return this data.						
MSG_OOB	Requests out-of-band data. The significance and semantics of out-of-band data are protocol-specific.						
MSG_WAITALL	Requests that the function block until the full amount of data requested can be returned. The function may return a smaller amount of data if a signal is caught, if the connection is terminated, if MSG_PEEK was specified, or if an error is pending for the socket.						
<i>address</i>	A null pointer, or points to a <code>sockaddr</code> structure in which the sending address is to be stored. The length and format of the address depend on the address family of the socket.						
<i>address_len</i>	Specifies the length of the <code>sockaddr</code> structure pointed to by the <i>address</i> argument.						

The `recvfrom()` function returns the length of the message written to the buffer pointed to by the *buffer* argument. For message-based sockets such as `SOCK_DGRAM` and `SOCK_SEQPACKET`, the entire message must be read in a single operation. If a message is too long to fit in the supplied buffer, and `MSG_PEEK` is not set in the *flags* argument, the excess bytes are discarded. For stream-based sockets such as `SOCK_STREAM`, message boundaries are ignored. In this case, data is returned to the user as soon as it becomes available, and no data is discarded.

If the `MSG_WAITALL` flag is not set, data will be returned only up to the end of the first message.

Not all protocols provide the source address for messages. If the *address* argument is not a null pointer and the protocol provides the source address of messages, the source address of the received message is stored in the `sockaddr` structure pointed to by the *address* argument, and the length of this address is stored in the object pointed to by the *address_len* argument.

If the actual length of the address is greater than the length of the supplied `sockaddr` structure, the stored address will be truncated.

If the *address* argument is not a null pointer and the protocol does not provide the source address of messages, the value stored in the object pointed to by *address* is unspecified.

If no messages are available at the socket and `O_NONBLOCK` is not set on the socket's file descriptor, `recvfrom()` blocks until a message arrives. If no messages are available at the socket and `O_NONBLOCK` is set on the socket's file descriptor, `recvfrom()` fails and sets `errno` to `EAGAIN` or `EWOULDBLOCK`.

Usage The [select\(3C\)](#) and [poll\(2\)](#) functions can be used to determine when data is available to be received.

Return Values Upon successful completion, `recvfrom()` returns the length of the message in bytes. If no messages are available to be received and the peer has performed an orderly shutdown, `recvfrom()` returns 0. Otherwise the function returns `-1` and sets `errno` to indicate the error.

Errors The `recvfrom()` function will fail if:

<code>EAGAIN</code>	
<code>EWOULDBLOCK</code>	The socket's file descriptor is marked <code>O_NONBLOCK</code> and no data is waiting to be received, or <code>MSG_OOB</code> is set and no out-of-band data is available and either the socket's file descriptor is marked <code>O_NONBLOCK</code> or the socket does not support blocking to await out-of-band data.
<code>EBADF</code>	The <i>socket</i> argument is not a valid file descriptor.
<code>ECONNRESET</code>	A connection was forcibly closed by a peer.
<code>EFAULT</code>	The <i>buffer</i> , <i>address</i> or <i>address_len</i> parameter can not be accessed or written.
<code>EINTR</code>	A signal interrupted <code>recvfrom()</code> before any data was available.
<code>EINVAL</code>	The <code>MSG_OOB</code> flag is set and no out-of-band data is available.
<code>ENOTCONN</code>	A receive is attempted on a connection-mode socket that is not connected.
<code>ENOTSOCK</code>	The <i>socket</i> argument does not refer to a socket.
<code>EOPNOTSUPP</code>	The specified flags are not supported for this socket type.

ETIMEDOUT The connection timed out during connection establishment, or due to a transmission timeout on active connection.

The `recvfrom()` function may fail if:

- EIO** An I/O error occurred while reading from or writing to the file system.
- ENOBUFS** Insufficient resources were available in the system to perform the operation.
- ENOMEM** Insufficient memory was available to fulfill the request.
- ENOSR** There were insufficient STREAMS resources available for the operation to complete.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also [poll\(2\)](#), [recv\(3XNET\)](#), [recvmsg\(3XNET\)](#), [select\(3C\)](#) [send\(3XNET\)](#), [sendmsg\(3XNET\)](#), [sendto\(3XNET\)](#), [shutdown\(3XNET\)](#), [socket\(3XNET\)](#), [attributes\(5\)](#), [standards\(5\)](#)

Name recvmsg – receive a message from a socket

Synopsis `cc [flag...] file... -lxnet [library...]
#include <sys/socket.h>`

```
ssize_t recvmsg(int socket, struct msghdr *message, int flags);
```

Description The `recvmsg()` function receives a message from a connection-mode or connectionless-mode socket. It is normally used with connectionless-mode sockets because it permits the application to retrieve the source address of received data.

The `recvmsg()` function receives messages from unconnected or connected sockets and returns the length of the message.

The `recvmsg()` function returns the total length of the message. For message-based sockets such as `SOCK_DGRAM` and `SOCK_SEQPACKET`, the entire message must be read in a single operation. If a message is too long to fit in the supplied buffers, and `MSG_PEEK` is not set in the *flags* argument, the excess bytes are discarded, and `MSG_TRUNC` is set in the `msg_flags` member of the `msghdr` structure. For stream-based sockets such as `SOCK_STREAM`, message boundaries are ignored. In this case, data is returned to the user as soon as it becomes available, and no data is discarded.

If the `MSG_WAITALL` flag is not set, data will be returned only up to the end of the first message.

If no messages are available at the socket, and `O_NONBLOCK` is not set on the socket's file descriptor, `recvmsg()` blocks until a message arrives. If no messages are available at the socket and `O_NONBLOCK` is set on the socket's file descriptor, the `recvmsg()` function fails and sets `errno` to `EAGAIN` or `EWOULDBLOCK`.

In the `msghdr` structure, defined in [socket.h\(3HEAD\)](#), the `msg_name` and `msg_namelen` members specify the source address if the socket is unconnected. If the socket is connected, the `msg_name` and `msg_namelen` members are ignored. The `msg_name` member may be a null pointer if no names are desired or required.

The `msg_control` and `msg_controllen` members specify a buffer to receive ancillary data sent along with a message. Ancillary data consists of a sequence of pairs. Each pair is composed of a `cmsgdr` structure followed by a data array. The `cmsgdr` structure, defined in [socket.h\(3HEAD\)](#), contains descriptive information which allows an application to correctly parse data. The data array contains the ancillary data message.

If ancillary data is not transferred, `msg_control` is set to `NULL` and `msg_controllen` is set to `0`.

The `msg_iov` and `msg_iovlen` fields of the `msghdr` structure are used to specify where the received data will be stored. `msg_iov` points to an array of `iovec` structures. The `msg_iovlen` must be set to the dimension of this array. In each `iovec` structure, the `iov_base` field specifies a storage area and the `iov_len` field gives its size in bytes. Each storage area indicated by `msg_iov` is filled with received data in turn until all of the received data is stored or all of the areas have been filled.

On successful completion, the `msg_flags` member of the message header is the bitwise-inclusive OR of all of the following flags that indicate conditions detected for the received message:

<code>MSG_EOR</code>	End of record was received (if supported by the protocol).
<code>MSG_OOB</code>	Out-of-band data was received.
<code>MSG_TRUNC</code>	Normal data was truncated.
<code>MSG_CTRUNC</code>	Control data was truncated.

Parameters The function takes the following arguments:

<i>socket</i>	Specifies the socket file descriptor.						
<i>message</i>	Points to a <code>msg_hdr</code> structure, containing both the buffer to store the source address and the buffers for the incoming message. The length and format of the address depend on the address family of the socket. The <code>msg_flags</code> member is ignored on input, but may contain meaningful values on output.						
<i>flags</i>	Specifies the type of message reception. Values of this argument are formed by logically OR'ing zero or more of the following values: <table data-bbox="485 781 1345 1072"> <tr> <td><code>MSG_OOB</code></td><td>Requests out-of-band data. The significance and semantics of out-of-band data are protocol-specific.</td></tr> <tr> <td><code>MSG_PEEK</code></td><td>Peeks at the incoming message.</td></tr> <tr> <td><code>MSG_WAITALL</code></td><td>Requests that the function block until the full amount of data requested can be returned. The function may return a smaller amount of data if a signal is caught, if the connection is terminated, if <code>MSG_PEEK</code> was specified, or if an error is pending for the socket.</td></tr> </table>	<code>MSG_OOB</code>	Requests out-of-band data. The significance and semantics of out-of-band data are protocol-specific.	<code>MSG_PEEK</code>	Peeks at the incoming message.	<code>MSG_WAITALL</code>	Requests that the function block until the full amount of data requested can be returned. The function may return a smaller amount of data if a signal is caught, if the connection is terminated, if <code>MSG_PEEK</code> was specified, or if an error is pending for the socket.
<code>MSG_OOB</code>	Requests out-of-band data. The significance and semantics of out-of-band data are protocol-specific.						
<code>MSG_PEEK</code>	Peeks at the incoming message.						
<code>MSG_WAITALL</code>	Requests that the function block until the full amount of data requested can be returned. The function may return a smaller amount of data if a signal is caught, if the connection is terminated, if <code>MSG_PEEK</code> was specified, or if an error is pending for the socket.						

Usage The `select(3C)` and `poll(2)` functions can be used to determine when data is available to be received.

Return Values Upon successful completion, `recvmsg()` returns the length of the message in bytes. If no messages are available to be received and the peer has performed an orderly shutdown, `recvmsg()` returns 0. Otherwise, -1 is returned and `errno` is set to indicate the error.

Errors The `recvmsg()` function will fail if:

<code>EAGAIN</code>	
<code>EWOULDBLOCK</code>	The socket's file descriptor is marked <code>O_NONBLOCK</code> and no data is waiting to be received; or <code>MSG_OOB</code> is set and no out-of-band data is available and either the socket's file descriptor is marked <code>O_NONBLOCK</code> or the socket does not support blocking to await out-of-band data.

EBADF	The <i>socket</i> argument is not a valid open file descriptor.
ECONNRESET	A connection was forcibly closed by a peer.
EFAULT	The <i>message</i> parameter, or storage pointed to by the <i>msg_name</i> , <i>msg_control</i> or <i>msg_iov</i> fields of the <i>message</i> parameter, or storage pointed to by the <i>iovec</i> structures pointed to by the <i>msg_iov</i> field can not be accessed or written.
EINTR	This function was interrupted by a signal before any data was available.
EINVAL	The sum of the <i>iov_len</i> values overflows an <i>ssize_t</i> , or the MSG_OOB flag is set and no out-of-band data is available.
EMSGSIZE	The <i>msg_iovlen</i> member of the <i>msghdr</i> structure pointed to by <i>message</i> is less than or equal to 0, or is greater than IOV_MAX.
ENOTCONN	A receive is attempted on a connection-mode socket that is not connected.
ENOTSOCK	The <i>socket</i> argument does not refer to a socket.
EOPNOTSUPP	The specified flags are not supported for this socket type.
ETIMEDOUT	The connection timed out during connection establishment, or due to a transmission timeout on active connection.

The `recvmsg()` function may fail if:

EIO	An IO error occurred while reading from or writing to the file system.
ENOBUFS	Insufficient resources were available in the system to perform the operation.
ENOMEM	Insufficient memory was available to fulfill the request.
ENOSR	There were insufficient STREAMS resources available for the operation to complete.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also [poll\(2\)](#), [recv\(3XNET\)](#), [recvfrom\(3XNET\)](#), [select\(3C\)](#), [send\(3XNET\)](#), [sendmsg\(3XNET\)](#), [sendto\(3XNET\)](#), [setsockopt\(3XNET\)](#), [shutdown\(3XNET\)](#), [socket\(3XNET\)](#), [socket.h\(3HEAD\)](#), [attributes\(5\)](#), [standards\(5\)](#)

Name resolver, res_ninit, fp_resstat, res_hostalias, res_nquery, res_nsearch, res_nquerydomain, res_nmkquery, res_nsend, res_nclose, res_nsendsigned, dn_comp, dn_expand, hstrerror, res_init, res_query, res_search, res_mkquery, res_send, error, res_getservers, res_setservers, res_ndestroy – resolver routines

Synopsis BIND 8.2.2 Interfaces

```
cc [ flag ... ] file ... -lresolv -lsocket -lnsl [ library ... ]
#include <sys/types.h>
#include <netinet/in.h>
#include <arpa/nameser.h>
#include <resolv.h>
#include <netdb.h>

int res_ninit(res_state statp);
void res_ndestroy(res_state statp);
void fp_resstat(const res_state statp, FILE *fp);
const char *res_hostalias(const res_state statp, const char *name,
    char * name, char *buf, size_tbuflen);
int res_nquery(res_state statp, const char *dname, int class, int type,
    u_char *answer, int datalen, int anslen);
int res_nsearch(res_state statp, const char *dname, int class, int type,
    u_char *answer, int anslen);
int res_nquerydomain(res_state statp, const char *name,
    const char *domain, int class, int type,
    u_char *answer, int anslen);
int res_nmkquery(res_state statp, int op, const char *dname, int class,
    int type, u_char *answer, int datalen,
    int anslen);
int res_nsend(res_state statp, const u_char *msg, int msglen,
    u_char *answer, int anslen);
void res_nclose(res_state statp);
int res_nsendsigned(res_state statp, const u_char *msg,
    int msglen, ns_tsig_key *key, u_char *answer, int anslen);
int dn_comp(const char *exp_dn, u_char *comp_dn, int length,
    u_char **dnptrs, **lastdnptr);
int dn_expand(const u_char *msg, *eomorig, *comp_dn, char *exp_dn,
    int length);
const char *hstrerror(int err);
void res_setservers(res_state statp, const union res_sockaddr_union *set,
    int cnt);
```

```
int res_getservers(res_state statp, union res_sockaddr_union *set,
    int cnt);
```

Deprecated Interfaces

```
cc [ flag ... ] file ... -lresolv -lsocket -lnsl [ library ... ]
#include <sys/types.h>
#include <netinet/in.h>
#include <arpa/nameser.h>
#include <resolv.h>
#include <netdb.h>
```

```
int res_init(void)
```

```
int res_query(const char *dname, int class,
    int type, u_char *answer,
    int anslen);
```

```
int res_search(const char *dname, int class,
    int type, u_char *answer, int anslen);
```

```
int res_mkquery(int op, const char *dname, int class,
    int type, const char *data, int datalen,
    struct rrec *newrr, u_char *buf, int buflen);
```

```
int res_send(const u_char *msg, int msglen, u_char *answer,
    int anslen);
```

```
void herror(const char *s);
```

Description These routines are used for making, sending, and interpreting query and reply messages with Internet domain name servers.

State information is kept in *statp* and is used to control the behavior of these functions. Set *statp* to all zeros prior to making the first call to any of these functions.

The `res_ndestroy()` function should be called to free memory allocated by `res_ninit()` after the last use of *statp*.

The functions `res_init()`, `res_query()`, `res_search()`, `res_mkquery()`, `res_send()`, and `herror()` are deprecated. They are supplied for backwards compatability. They use global configuration and state information that is kept in the structure `_res` rather than state information referenced through *statp*.

Most of the values in *statp* and `_res` are initialized to reasonable defaults on the first call to `res_ninit()` or `res_init()` and can be ignored. Options stored in `statp->options` or `_res.options` are defined in `<resolv.h>`. They are stored as a simple bit mask containing the bitwise OR of the options enabled.

RES_INIT True if the initial name server address and default domain name are initialized, that is, `res_init()` or `res_ninit()` has been called.

RES_DEBUG Print debugging messages.

RES_AAONLY	Accept authoritative answers only. With this option, <code>res_send()</code> will continue until it finds an authoritative answer or finds an error. Currently this option is not implemented.
RES_USEVC	Use TCP connections for queries instead of UDP datagrams.
RES_STAYOPEN	Use with RES_USEVC to keep the TCP connection open between queries. This is a useful option for programs that regularly do many queries. The normal mode used should be UDP.
RES_IGNTC	Ignore truncation errors; that is, do not retry with TCP.
RES_RECURSE	Set the recursion-desired bit in queries. This is the default. <code>res_send()</code> and <code>res_nsend()</code> do not do iterative queries and expect the name server to handle recursion.
RES_DEFNAMES	If set, <code>res_search()</code> and <code>res_nsearch()</code> append the default domain name to single-component names, that is, names that do not contain a dot. This option is enabled by default.
RES_DNSRCH	If this option is set, <code>res_search()</code> and <code>res_nsearch()</code> search for host names in the current domain and in parent domains. See hostname(1) . This option is used by the standard host lookup routine gethostbyname(3NSL) . This option is enabled by default.
RES_NOALIASES	This option turns off the user level aliasing feature controlled by the HOSTALIASES environment variable. Network daemons should set this option.
RES_BLAST	If the RES_BLAST option is defined, <code>resolver()</code> queries will be sent to all servers. If the RES_BLAST option is not defined, but RES_ROTATE is, the list of nameservers are rotated according to a round-robin scheme. RES_BLAST overrides RES_ROTATE.
RES_ROTATE	This option causes <code>res_nsend()</code> and <code>res_send()</code> to rotate the list of nameservers in <code>statp->nsaddr_list</code> or <code>_res.nsaddr_list</code> .
RES_KEEPTSIG	This option causes <code>res_nsendsigned()</code> to leave the message unchanged after TSIG verification. Otherwise the TSIG record would be removed and the header would be updated.
<code>res_ninit, res_init</code>	The <code>res_ninit()</code> and <code>res_init()</code> routines read the configuration file, if any is present, to get the default domain name, search list and the Internet address of the local name server(s). See resolv.conf(4) . If no server is configured, <code>res_init()</code> or <code>res_ninit()</code> will try to obtain name resolution services from the host on which it is running. The current domain name is defined by domainname(1M) , or by the hostname if it is not specified in the configuration file. Use the environment variable LOCALDOMAIN to override the domain name. This environment variable may contain several blank-separated tokens if you wish to override the search list on a per-process basis. This is similar to the search command in the configuration file. You can set

the `RES_OPTIONS` environment variable to override certain internal resolver options. You can otherwise set them by changing fields in the `statp/_res` structure. Alternatively, they are inherited from the configuration file's `options` command. See [resolv.conf\(4\)](#) for information regarding the syntax of the `RES_OPTIONS` environment variable. Initialization normally occurs on the first call to one of the other resolver routines.

res_nquery, res_query The `res_nquery()` and `res_query()` functions provide interfaces to the server query mechanism. They construct a query, send it to the local server, await a response, and make preliminary checks on the reply. The query requests information of the specified *type* and *class* for the specified fully-qualified domain name *dname*. The reply message is left in the *answer* buffer with length *anslen* supplied by the caller. `res_nquery()` and `res_query()` return the length of the *answer*, or -1 upon error.

The `res_nquery()` and `res_query()` routines return a length that may be bigger than *anslen*. In that case, retry the query with a larger *buf*. The *answer* to the second query may be larger still], so it is recommended that you supply a *buf* larger than the *answer* returned by the previous query. *answer* must be large enough to receive a maximum UDP response from the server or parts of the *answer* will be silently discarded. The default maximum UDP response size is 512 bytes.

res_nsearch, res_search The `res_nsearch()` and `res_search()` routines make a query and await a response, just like `res_nquery()` and `res_query()`. In addition, they implement the default and search rules controlled by the `RES_DEFNAMES` and `RES_DNSRCH` options. They return the length of the first successful reply which is stored in *answer*. On error, they return -1.

The `res_nsearch()` and `res_search()` routines return a length that may be bigger than *anslen*. In that case, retry the query with a larger *buf*. The *answer* to the second query may be larger still], so it is recommended that you supply a *buf* larger than the *answer* returned by the previous query. *answer* must be large enough to receive a maximum UDP response from the server or parts of the *answer* will be silently discarded. The default maximum UDP response size is 512 bytes.

res_nmkquery, res_mkquery These routines are used by `res_nquery()` and `res_query()`. The `res_nmkquery()` and `res_mkquery()` functions construct a standard query message and place it in *buf*. The routine returns the *size* of the query, or -1 if the query is larger than *buflen*. The query type *op* is usually `QUERY`, but can be any of the query types defined in `<arpa/nameser.h>`. The domain name for the query is given by *dname*. *newrr* is currently unused but is intended for making update messages.

res_nsend, res_send, res_nsendsigned The `res_nsend()`, `res_send()`, and `res_nsendsigned()` routines send a pre-formatted query that returns an *answer*. The routine calls `res_ninit()` or `res_init()`. If `RES_INIT` is not set, the routine sends the query to the local name server and handles timeouts and retries. Additionally, the `res_nsendsigned()` uses TSIG signatures to add authentication to the query and verify the response. In this case, only one name server will be contacted. The routines return the length of the reply message, or -1 if there are errors.

The `res_nsend()` and `res_send()` routines return a length that may be bigger than *anslen*. In that case, retry the query with a larger *buf*. The *answer* to the second query may be larger still], so it is recommended that you supply a *buf* larger than the *answer* returned by the previous query. *answer* must be large enough to receive a maximum UDP response from the server or parts of the *answer* will be silently discarded. The default maximum UDP response size is 512 bytes.

- `fp_resstat` The function `fp_resstat()` prints out the active flag bits in `statp->options` preceded by the text “;; res options:” on *file*.
- `res_hostalias` The function `res_hostalias()` looks up *name* in the file referred to by the `HOSTALIASES` environment variable and returns the fully qualified host name. If *name* is not found or an error occurs, `NULL` is returned. `res_hostalias()` stores the result in *buf*.
- `res_nclose` The `res_nclose()` function closes any open files referenced through *statp*.
- `res_ndestroy` The `res_ndestroy()` function calls `res_nclose()`, then frees any memory allocated by `res_ninit()` referenced through *statp*.
- `dn_comp` The `dn_comp()` function compresses the domain name *exp_dn* and stores it in *comp_dn*. The `dn_comp()` function returns the size of the compressed name, or `-1` if there were errors. *length* is the size of the array pointed to by *comp_dn*.
- The *dnptrs* parameter is a pointer to the head of the list of pointers to previously compressed names in the current message. The first pointer must point to the beginning of the message. The list ends with `NULL`. The limit to the array is specified by *lastdnptr*.
- A side effect of calling `dn_comp()` is to update the list of pointers for labels inserted into the message by `dn_comp()` as the name is compressed. If *dnptrs* is `NULL`, names are not compressed. If *lastdnptr* is `NULL`, `dn_comp()` does not update the list of labels.
- `dn_expand` The `dn_expand()` function expands the compressed domain name *comp_dn* to a full domain name. The compressed name is contained in a query or reply message. *msg* is a pointer to the beginning of that message. The uncompressed name is placed in the buffer indicated by *exp_dn*, which is of size *length*. The `dn_expand()` function returns the size of the compressed name, or `-1` if there was an error.
- `hstrerror, herror` The variables `statp->res_h_errno` and `_res.res_h_errno` and external variable *h_errno* are set whenever an error occurs during a resolver operation. The following definitions are given in `<netdb.h>`:

```
#define NETDB_INTERNAL -1 /* see errno */
#define NETDB_SUCCESS 0 /* no problem */
#define HOST_NOT_FOUND 1 /* Authoritative Answer Host not found */
#define TRY_AGAIN 2 /* Non-Authoritative not found, or SERVFAIL */
#define NO_RECOVERY 3 /* Non-Recoverable: FORMERR, REFUSED, NOTIMP */
#define NO_DATA 4 /* Valid name, no data for requested type */
```

The `herror()` function writes a message to the diagnostic output consisting of the string parameters, the constant string “:”, and a message corresponding to the value of `h_errno`.

The `hsterror()` function returns a string, which is the message text that corresponds to the value of the `err` parameter.

`res_setservers`,
`res_getservers` The functions `res_getservers()` and `res_setservers()` are used to get and set the list of servers to be queried.

Files `/etc/resolv.conf` resolver configuration file

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWcsl (32-bit) SUNWcslx (64-bit)
Interface Stability	Evolving
MT-Level	Unsafe for Deprecated Interfaces; MT-Safe for all others.

See Also [domainname\(1M\)](#), [gethostbyname\(3NSL\)](#), [libresolv\(3LIB\)](#), [resolv.conf\(4\)](#), [attributes\(5\)](#)

Lottor, M. *RFC 1033, Domain Administrators Operations Guide*. Network Working Group. November 1987.

Mockapetris, Paul. *RFC 1034, Domain Names - Concepts and Facilities*. Network Working Group. November 1987.

Mockapetris, Paul. *RFC 1035, Domain Names - Implementation and Specification*. Network Working Group. November 1987.

Partridge, Craig. *RFC 974, Mail Routing and the Domain System*. Network Working Group. January 1986.

Stahl, M. *RFC 1032, Domain Administrators Guide*. Network Working Group. November 1987.

Vixie, Paul, Dunlap, Kevin J., Karels, Michael J. *Name Server Operations Guide for BIND*. Internet Software Consortium, 1996.

Notes When the caller supplies a work buffer, for example the *answer* buffer argument to `res_nsend()` or `res_send()`, the buffer should be aligned on an eight byte boundary. Otherwise, an error such as a SIGBUS may result.

Name rexec, rexec_af – return stream to a remote command

Synopsis `cc [flag ...] file... -lsocket -lnsl [library...]`
`#include <netdb.h>`
`#include <unistd.h>`

```
int rexec(char **ahost, unsigned short inport, const char *user,
          const char *passwd, const char *cmd, int *fd2p);

int rexec_af(char **ahost, unsigned short inport, const char *user,
             const char *passwd, const char *cmd, int *fd2p, int af);
```

Description The `rexec()` and `rexec_af()` functions look up the host *ahost* using [getaddrinfo\(3SOCKET\)](#) and return `-1` if the host does not exist. Otherwise *ahost* is set to the standard name of the host. The username and password are used in remote host authentication. When a username and password are not specified, the `.netrc` file in the user's home directory is searched for the appropriate information. If the search fails, the user is prompted for the information.

The `rexec()` function always returns a socket of the `AF_INET` address family. The `rexec_af()` function supports `AF_INET`, `AF_INET6`, or `AF_UNSPEC` for the address family. An application can choose which type of socket is returned by passing `AF_INET` or `AF_INET6` as the address family. The use of `AF_UNSPEC` means that the caller will accept any address family. Choosing `AF_UNSPEC` provides a socket that best suits the connectivity to the remote host.

The port *inport* specifies which DARPA Internet port to use for the connection. The port number used must be in network byte order, as supplied by a call to [htons\(3XNET\)](#). The protocol for connection is described in detail in [in.rexecd\(1M\)](#).

If the call succeeds, a socket of type `SOCK_STREAM` is returned to the caller, and given to the remote command as its standard input and standard output. If *fd2p* is non-zero, an auxiliary channel to a control process is set up and a file descriptor for it is placed in **fd2p*. The control process returns diagnostic output (file descriptor 2), from the command on the auxiliary channel. The control process also accepts bytes on this channel as signal numbers to be forwarded to the process group of the command. If *fd2p* is 0, the standard error (file descriptor 2) of the remote command is made the same as its standard output. No provision is made for sending arbitrary signals to the remote process, other than possibly sending out-of-band data.

There is no way to specify options to the `socket()` call made by the `rexec()` or `rexec_af()` functions.

Return Values If `rexec()` succeeds, a file descriptor number is returned of the socket type `SOCK_STREAM` and the address family `AF_INET`. The parameter **ahost* is set to the standard name of the host. If the value of *fd2p* is other than `NULL`, a file descriptor number is placed in **fd2p* which represents the standard error stream of the command.

If `rexec_af()` succeeds, the routine returns a file descriptor number of the socket type `SOCK_STREAM` in the address family `AF_INET` or `AF_INET6`, as determined by the value of the *af* parameter.

If either `rexec()` or `rexec_af()` fails, `-1` is returned.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Unsafe

This interface is Unsafe in multithreaded applications. Unsafe interfaces should be called only from the main thread.

See Also [in.rexecd\(1M\)](#), [getaddrinfo\(3SOCKET\)](#), [gethostbyname\(3NSL\)](#), [getservbyname\(3SOCKET\)](#), [htonl\(3XNET\)](#), [socket\(3SOCKET\)](#), [attributes\(5\)](#)

Name	rpc – library routines for remote procedure calls								
Synopsis	<pre>cc [flag ...] file ... -lnsl [library ...] #include <rpc/rpc.h> #include <netconfig.h></pre>								
Description	<p>These routines allow C language programs to make procedure calls on other machines across a network. First, the client sends a request to the server. On receipt of the request, the server calls a dispatch routine to perform the requested service, and then sends back a reply.</p> <p>All RPC routines require the header <code><rpc/rpc.h></code>. Routines that take a <code>netconfig</code> structure also require that <code><netconfig.h></code> be included. Applications using RPC and XDR routines should be linked with the <code>libnsl</code> library.</p>								
Multithread Considerations	<p>In the case of multithreaded applications, the <code>-mt</code> option must be specified on the command line at compilation time to enable a thread-specific version of <code>rpc_createerr()</code>. See rpc_clnt_create(3NSL) and threads(5).</p> <p>When used in multithreaded applications, client-side routines are MT-Safe. CLIENT handles can be shared between threads; however, in this implementation, requests by different threads are serialized (that is, the first request will receive its results before the second request is sent). See rpc_clnt_create(3NSL).</p> <p>When used in multithreaded applications, server-side routines are usually Unsafe. In this implementation the service transport handle, SVCXPRT contains a single data area for decoding arguments and encoding results. See rpc_svc_create(3NSL). Therefore, this structure cannot be freely shared between threads that call functions that do this. Routines that are affected by this restriction are marked as unsafe for MT applications. See rpc_svc_calls(3NSL).</p>								
Nettyp	<p>Some of the high-level RPC interface routines take a <i>nettype</i> string as one of the parameters (for example, <code>clnt_create()</code>, <code>svc_create()</code>, <code>rpc_reg()</code>, <code>rpc_call()</code>). This string defines a class of transports which can be used for a particular application.</p> <p><i>nettype</i> can be one of the following:</p> <table> <tr> <td><code>netpath</code></td><td>Choose from the transports which have been indicated by their token names in the NETPATH environment variable. If NETPATH is unset or NULL, it defaults to <code>visible</code>. <code>netpath</code> is the default <i>nettype</i>.</td></tr> <tr> <td><code>visible</code></td><td>Choose the transports which have the visible flag (<code>v</code>) set in the <code>/etc/netconfig</code> file.</td></tr> <tr> <td><code>circuit_v</code></td><td>This is same as <code>visible</code> except that it chooses only the connection oriented transports (semantics <code>tpi_cots</code> or <code>tpi_cots_ord</code>) from the entries in the <code>/etc/netconfig</code> file.</td></tr> <tr> <td><code>datagram_v</code></td><td>This is same as <code>visible</code> except that it chooses only the connectionless datagram transports (semantics <code>tpi_clts</code>) from the entries in the <code>/etc/netconfig</code> file.</td></tr> </table>	<code>netpath</code>	Choose from the transports which have been indicated by their token names in the NETPATH environment variable. If NETPATH is unset or NULL, it defaults to <code>visible</code> . <code>netpath</code> is the default <i>nettype</i> .	<code>visible</code>	Choose the transports which have the visible flag (<code>v</code>) set in the <code>/etc/netconfig</code> file.	<code>circuit_v</code>	This is same as <code>visible</code> except that it chooses only the connection oriented transports (semantics <code>tpi_cots</code> or <code>tpi_cots_ord</code>) from the entries in the <code>/etc/netconfig</code> file.	<code>datagram_v</code>	This is same as <code>visible</code> except that it chooses only the connectionless datagram transports (semantics <code>tpi_clts</code>) from the entries in the <code>/etc/netconfig</code> file.
<code>netpath</code>	Choose from the transports which have been indicated by their token names in the NETPATH environment variable. If NETPATH is unset or NULL, it defaults to <code>visible</code> . <code>netpath</code> is the default <i>nettype</i> .								
<code>visible</code>	Choose the transports which have the visible flag (<code>v</code>) set in the <code>/etc/netconfig</code> file.								
<code>circuit_v</code>	This is same as <code>visible</code> except that it chooses only the connection oriented transports (semantics <code>tpi_cots</code> or <code>tpi_cots_ord</code>) from the entries in the <code>/etc/netconfig</code> file.								
<code>datagram_v</code>	This is same as <code>visible</code> except that it chooses only the connectionless datagram transports (semantics <code>tpi_clts</code>) from the entries in the <code>/etc/netconfig</code> file.								

circuit_n	This is same as netpath except that it chooses only the connection oriented datagram transports (semantics tpi_cots or tpi_cots_ord).
datagram_n	This is same as netpath except that it chooses only the connectionless datagram transports (semantics tpi_clts).
udp	This refers to Internet UDP.
tcp	This refers to Internet TCP.

If *nettype* is NULL, it defaults to netpath. The transports are tried in left to right order in the NETPATH variable or in top to down order in the /etc/netconfig file.

Derived Types In a 64-bit environment, the derived types are defined as follows:

typedef	uint32_t	rpcprog_t;
typedef	uint32_t	rpcvers_t;
typedef	uint32_t	rpcproc_t;
typedef	uint32_t	rpcprot_t;
typedef	uint32_t	rpcport_t;
typedef	int32_t	rpc_inline_t;

In a 32-bit environment, the derived types are defined as follows:

typedef	unsigned long	rpcprog_t;
typedef	unsigned long	rpcvers_t;
typedef	unsigned long	rpcproc_t;
typedef	unsigned long	rpcprot_t;
typedef	unsigned long	rpcport_t;
typedef	long	rpc_inline_t;

Data Structures Some of the data structures used by the RPC package are shown below.

```
The AUTH Structure union des_block {
    struct {
        u_int32 high;
        u_int32 low;
    } key;
    char c[8];
};
typedef union des_block des_block;
```

```

extern bool_t xdr_des_block( );
/*
 * Authentication info. Opaque to client.
 */
struct opaque_auth {
    enum_t oa_flavor;          /* flavor of auth */
    caddr_t oa_base;           /* address of more auth stuff */
    uint_t oa_length;          /* not to exceed MAX_AUTH_BYTES */
};
/*
 * Auth handle, interface to client side authenticators.
 */
typedef struct {
    struct opaque_auth ah_cred;
    struct opaque_auth ah_verf;
    union des_block ah_key;
    struct auth_ops {
        void(*ah_nextverf)( );
        int(*ah_marshall)( ); /* nextverf & serialize */
        int(*ah_validate)( ); /* validate verifier */
        int(*ah_refresh)( ); /* refresh credentials */
        void(*ah_destroy)( ); /* destroy this structure */
    } *ah_ops;
    caddr_t ah_private;
} AUTH;

```

The CLIENT Structure /*

```

 * Client rpc handle.
 * Created by individual implementations.
 * Client is responsible for initializing auth.
 */
typedef struct {
    AUTH *cl_auth;           /* authenticator */
    struct clnt_ops {
        enum clnt_stat (*cl_call)( ); /* call remote procedure */
        void (*cl_abort)( ); /* abort a call */
        void (*cl_geterr)( ); /* get specific error code */
        bool_t (*cl_freeres)( ); /* frees results */
        void (*cl_destroy)( ); /* destroy this structure */
        bool_t (*cl_control)( ); /* the ioctl( ) of rpc */
        int (*cl_settimers)( ); /* set rpc level timers */
    } *cl_ops;
    caddr_t cl_private; /* private stuff */
    char *cl_netid; /* network identifier */
    char *cl_tp; /* device name */
} CLIENT;

```

```

The SVCXPRT Structure  enum xpirt_stat {
    XPRT_DIED,
    XPRT_MOREREQS,
    XPRT_IDLE
};
/*
 * Server side transport handle
 */
typedef struct {
    int      xp_fd;                /* file descriptor for the
    ushort_t xp_port;            /* obsolete */
    struct xp_ops {
        bool_t (*xp_rcv)(); /* receive incoming requests */
        enum xpirt_stat (*xp_stat)(); /* get transport status */
        bool_t (*xp_getargs)(); /* get arguments */
        bool_t (*xp_reply)(); /* send reply */
        bool_t (*xp_freeargs)(); /* free mem allocated
                                   for args */
        void (*xp_destroy)(); /* destroy this struct */
    } *xp_ops;
    int xp_addrlen;                /* length of remote addr.
                                   Obsolete */
    char *xp_tp;                  /* transport provider device
                                   name */
    char *xp_netid;               /* network identifier */
    struct netbuf xp_ltaddr;      /* local transport address */
    struct netbuf xp_rtaddr;      /* remote transport address */
    char xp_raddr[16];           /* remote address. Obsolete */
    struct opaque_auth xp_verf;   /* raw response verifier */
    caddr_t xp_p1;               /* private: for use
                                   by svc ops */
    caddr_t xp_p2;               /* private: for use
                                   by svc ops */
    caddr_t xp_p3;               /* private: for use
                                   by svc lib */
    int xp_type                  /* transport type */
} SVCXPRT;

The svc_reg Structure  struct svc_req {
    rpcprog_t rq_prog;           /* service program number */
    rpcvers_t rq_vers;           /* service protocol version */
    rpcproc_t rq_proc;           /* the desired procedure */
    struct opaque_auth rq_cred; /* raw creds from the wire */
    caddr_t rq_clntcred;         /* read only cooked cred */
    SVCXPRT *rq_xprt;           /* associated transport */

};

```

```

The XDR Structure  /*
    * XDR operations.
    * XDR_ENCODE causes the type to be encoded into the stream.
    * XDR_DECODE causes the type to be extracted from the stream.
    * XDR_FREE can be used to release the space allocated by an XDR_DECODE
    * request.
    */
enum xdr_op {
    XDR_ENCODE=0,
    XDR_DECODE=1,
    XDR_FREE=2
};
/*
    * This is the number of bytes per unit of external data.
    */
#define BYTES_PER_XDR_UNIT    (4)
#define RNDUP(x)  (((x) + BYTES_PER_XDR_UNIT - 1) /
    BYTES_PER_XDR_UNIT) \ * BYTES_PER_XDR_UNIT)
/*
    * A xdrproc_t exists for each data type which is to be encoded or
    * decoded. The second argument to the xdrproc_t is a pointer to
    * an opaque pointer. The opaque pointer generally points to a
    * structure of the data type to be decoded. If this points to 0,
    * then the type routines should allocate dynamic storage of the
    * appropriate size and return it.
    * bool_t (*xdrproc_t)(XDR *, caddr_t *);
    */
typedef bool_t (*xdrproc_t)( );
/*
    * The XDR handle.
    * Contains operation which is being applied to the stream,
    * an operations vector for the particular implementation
    */
typedef struct {

enum xdr_op x_op;    /* operation; fast additional param */
struct xdr_ops {

    bool_t      (*x_getlong)( );    /* get long from underlying stream */
    bool_t      (*x_putlong)( );    /* put long to underlying stream */
    bool_t      (*x_getbytes)( );    /* get bytes from underlying stream */
    bool_t      (*x_putbytes)( );    /* put bytes to underlying stream */
    uint_t      (*x_getpostn)( );    /* returns bytes off from beginning */
    bool_t      (*x_setpostn)( );    /* reposition the stream */
    rpc_inline_t (*x_inline)( );    /* buf quick ptr to buffered data */
    void         (*x_destroy)( );    /* free privates of this xdr_stream */
    bool_t      (*x_control)( );    /* changed/retrieve client object info*/
    bool_t      (*x_getint32)( );    /* get int from underlying stream */

```

```
bool_t      (*x_putint32)( );      /* put int to underlying stream */

} *x_ops;

caddr_t     x_public;              /* users' data */
caddr_t     x_priv                 /* pointer to private data */
caddr_t     x_base;                /* private used for position info */
int         x_handy;               /* extra private word */
XDR;
```

Index to Routines The following table lists RPC routines and the manual reference pages on which they are described:

RPC Routine	Manual Reference Page
<code>auth_destroy</code>	rpc_clnt_auth(3NSL)
<code>authdes_create</code>	rpc_soc(3NSL)
<code>authdes_getucred</code>	secure_rpc(3NSL)
<code>authdes_seccreate</code>	secure_rpc(3NSL)
<code>authnone_create</code>	rpc_clnt_auth(3NSL)
<code>authsys_create</code>	rpc_clnt_auth(3NSL)
<code>authsys_create_default</code>	rpc_clnt_auth(3NSL)
<code>authunix_create</code>	rpc_soc(3NSL)
<code>authunix_create_default</code>	rpc_soc(3NSL)
<code>callrpc</code>	rpc_soc(3NSL)
<code>clnt_broadcast</code>	rpc_soc(3NSL)
<code>clnt_call</code>	rpc_clnt_calls(3NSL)
<code>clnt_control</code>	rpc_clnt_create(3NSL)
<code>clnt_create</code>	rpc_clnt_create(3NSL)
<code>clnt_destroy</code>	rpc_clnt_create(3NSL)
<code>clnt_dg_create</code>	rpc_clnt_create(3NSL)
<code>clnt_freeres</code>	rpc_clnt_calls(3NSL)
<code>clnt_geterr</code>	rpc_clnt_calls(3NSL)
<code>clnt_pcreateerror</code>	rpc_clnt_create(3NSL)
<code>clnt_perrno</code>	rpc_clnt_calls(3NSL)
<code>clnt_perror</code>	rpc_clnt_calls(3NSL)

<code>clnt_raw_create</code>	<code>rpc_clnt_create(3NSL)</code>
<code>clnt_spcreateerror</code>	<code>rpc_clnt_create(3NSL)</code>
<code>clnt_sperrno</code>	<code>rpc_clnt_calls(3NSL)</code>
<code>clnt_sperror</code>	<code>rpc_clnt_calls(3NSL)</code>
<code>clnt_tli_create</code>	<code>rpc_clnt_create(3NSL)</code>
<code>clnt_tp_create</code>	<code>rpc_clnt_create(3NSL)</code>
<code>clnt_udprecreate</code>	<code>rpc_soc(3NSL)</code>
<code>clnt_vc_create</code>	<code>rpc_clnt_create(3NSL)</code>
<code>clntraw_create</code>	<code>rpc_soc(3NSL)</code>
<code>clnttcp_create</code>	<code>rpc_soc(3NSL)</code>
<code>clntudp_bufcreate</code>	<code>rpc_soc(3NSL)</code>
<code>get_myaddress</code>	<code>rpc_soc(3NSL)</code>
<code>getnetname</code>	<code>secure_rpc(3NSL)</code>
<code>host2netname</code>	<code>secure_rpc(3NSL)</code>
<code>key_decryptsession</code>	<code>secure_rpc(3NSL)</code>
<code>key_encryptsession</code>	<code>secure_rpc(3NSL)</code>
<code>key_gendes</code>	<code>secure_rpc(3NSL)</code>
<code>key_setsecret</code>	<code>secure_rpc(3NSL)</code>
<code>netname2host</code>	<code>secure_rpc(3NSL)</code>
<code>netname2user</code>	<code>secure_rpc(3NSL)</code>
<code>pmap_getmaps</code>	<code>rpc_soc(3NSL)</code>
<code>pmap_getport</code>	<code>rpc_soc(3NSL)</code>
<code>pmap_rmtcall</code>	<code>rpc_soc(3NSL)</code>
<code>pmap_set</code>	<code>rpc_soc(3NSL)</code>
<code>pmap_unset</code>	<code>rpc_soc(3NSL)</code>
<code>registerrpc</code>	<code>rpc_soc(3NSL)</code>
<code>rpc_broadcast</code>	<code>rpc_clnt_calls(3NSL)</code>
<code>rpc_broadcast_exp</code>	<code>rpc_clnt_calls(3NSL)</code>
<code>rpc_call</code>	<code>rpc_clnt_calls(3NSL)</code>

<code>rpc_reg</code>	<code>rpc_svc_calls(3NSL)</code>
<code>svc_create</code>	<code>rpc_svc_create(3NSL)</code>
<code>svc_destroy</code>	<code>rpc_svc_create(3NSL)</code>
<code>svc_dg_create</code>	<code>rpc_svc_create(3NSL)</code>
<code>svc_dg_enablecache</code>	<code>rpc_svc_calls(3NSL)</code>
<code>svc_fd_create</code>	<code>rpc_svc_create(3NSL)</code>
<code>svc_fds</code>	<code>rpc_soc(3NSL)</code>
<code>svc_freeargs</code>	<code>rpc_svc_reg(3NSL)</code>
<code>svc_getargs</code>	<code>rpc_svc_reg(3NSL)</code>
<code>svc_getcaller</code>	<code>rpc_soc(3NSL)</code>
<code>svc_getreq</code>	<code>rpc_soc(3NSL)</code>
<code>svc_getreqset</code>	<code>rpc_svc_calls(3NSL)</code>
<code>svc_getrpccaller</code>	<code>rpc_svc_calls(3NSL)</code>
<code>svc_raw_create</code>	<code>rpc_svc_create(3NSL)</code>
<code>svc_reg</code>	<code>rpc_svc_calls(3NSL)</code>
<code>svc_register</code>	<code>rpc_soc(3NSL)</code>
<code>svc_run</code>	<code>rpc_svc_reg(3NSL)</code>
<code>svc_sendreply</code>	<code>rpc_svc_reg(3NSL)</code>
<code>svc_tli_create</code>	<code>rpc_svc_create(3NSL)</code>
<code>svc_tp_create</code>	<code>rpc_svc_create(3NSL)</code>
<code>svc_unreg</code>	<code>rpc_svc_calls(3NSL)</code>
<code>svc_unregister</code>	<code>rpc_soc(3NSL)</code>
<code>svc_vc_create</code>	<code>rpc_svc_create(3NSL)</code>
<code>svcerr_auth</code>	<code>rpc_svc_err(3NSL)</code>
<code>svcerr_decode</code>	<code>rpc_svc_err(3NSL)</code>
<code>svcerr_noproc</code>	<code>rpc_svc_err(3NSL)</code>
<code>svcerr_noprogram</code>	<code>rpc_svc_err(3NSL)</code>
<code>svcerr_progvers</code>	<code>rpc_svc_err(3NSL)</code>
<code>svcerr_systemerr</code>	<code>rpc_svc_err(3NSL)</code>

svcerr_weakauth	rpc_svc_err(3NSL)
svcfld_create	rpc_soc(3NSL)
svcrow_create	rpc_soc(3NSL)
svctcp_create	rpc_soc(3NSL)
svcudp_bufcreate	rpc_soc(3NSL)
svcudp_create	rpc_soc(3NSL)
user2netname	secure_rpc(3NSL)
xdr_accepted_reply	rpc_xdr(3NSL)
xdr_authsys_parms	rpc_xdr(3NSL)
xdr_authunix_parms	rpc_soc(3NSL)
xdr_callhdr	rpc_xdr(3NSL)
xdr_callmsg	rpc_xdr(3NSL)
xdr_opaque_auth	rpc_xdr(3NSL)
xdr_rejected_reply	rpc_xdr(3NSL)
xdr_replymsg	rpc_xdr(3NSL)
xprt_register	rpc_svc_calls(3NSL)
xprt_unregister	rpc_svc_calls(3NSL)

Files /etc/netconfig

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe with exceptions

See Also [getnetconfig\(3NSL\)](#), [getnetpath\(3NSL\)](#), [rpc_clnt_auth\(3NSL\)](#), [rpc_clnt_calls\(3NSL\)](#), [rpc_clnt_create\(3NSL\)](#), [rpc_svc_calls\(3NSL\)](#), [rpc_svc_create\(3NSL\)](#), [rpc_svc_err\(3NSL\)](#), [rpc_svc_reg\(3NSL\)](#), [rpc_xdr\(3NSL\)](#), [rpcbind\(3NSL\)](#), [secure_rpc\(3NSL\)](#), [threads\(5\)](#), [xdr\(3NSL\)](#), [netconfig\(4\)](#), [rpc\(4\)](#), [attributes\(5\)](#), [environ\(5\)](#)

Name rpcbind, rpcb_getmaps, rpcb_getaddr, rpcb_gettime, rpcb_rmtcall, rpcb_set, rpcb_unset – library routines for RPC bind service

Synopsis #include <rpc/rpc.h>

```
struct rpcblist *rpcb_getmaps(const struct netconfig *nnetconf,
                             const char *host);

bool_t rpcb_getaddr(const rpcprog_t prognum, const rpcvers_t versnum,
                   const struct netconfig *netconf, struct netbuf *ssvcaddr,
                   const char *host);

bool_t rpcb_gettime(const char *host, time_t *timep);

enum clnt_stat rpcb_rmtcall(const struct netconfig *netconf,
                           const char *host, const rpcprog_t prognum,
                           const rpcvers_t versnum, const rpcproc_t procnum,
                           const xdrproc_t inproc, const caddr_t in,
                           const xdrproc_t outproc, const caddr_t out,
                           const struct timeval tout, struct netbuf *svcaddr);

bool_t rpcb_set(const rpcprog_t prognum, const rpcvers_t versnum,
               const struct netconfig *netconf, const struct netbuf *svcaddr);

bool_t rpcb_unset(const rpcprog_t prognum, const rpcvers_t versnum,
                  const struct netconfig *netconf);
```

Description These routines allow client C programs to make procedure calls to the RPC binder service. rpcbind maintains a list of mappings between programs and their universal addresses. See [rpcbind\(1M\)](#).

- | | |
|----------|---|
| Routines | <p>rpcb_getmaps() An interface to the rpcbind service, which returns a list of the current RPC program-to-address mappings on <i>host</i>. It uses the transport specified through <i>netconf</i> to contact the remote rpcbind service on <i>host</i>. This routine will return NULL, if the remote rpcbind could not be contacted.</p> <p>rpcb_getaddr() An interface to the rpcbind service, which finds the address of the service on <i>host</i> that is registered with program number <i>prognum</i>, version <i>versnum</i>, and speaks the transport protocol associated with <i>netconf</i>. The address found is returned in <i>svcaddr</i>. <i>svcaddr</i> should be preallocated. This routine returns TRUE if it succeeds. A return value of FALSE means that the mapping does not exist or that the RPC system failed to contact the remote rpcbind service. In the latter case, the global variable <code>rpc_createerr</code> contains the RPC status. See rpc_clnt_create(3NSL).</p> <p>rpcb_gettime() This routine returns the time on <i>host</i> in <i>timep</i>. If <i>host</i> is NULL, <code>rpcb_gettime()</code> returns the time on its own machine. This routine</p> |
|----------|---|

returns TRUE if it succeeds, FALSE if it fails. `rpcb_gettime()` can be used to synchronize the time between the client and the remote server. This routine is particularly useful for secure RPC.

`rpcb_rmtcall()` An interface to the `rpcbind` service, which instructs `rpcbind` on *host* to make an RPC call on your behalf to a procedure on that host. The `netconfig` structure should correspond to a connectionless transport. The parameter `*svcaddr` will be modified to the server's address if the procedure succeeds. See `rpc_call()` and `clnt_call()` in [rpc_clnt_calls\(3NSL\)](#) for the definitions of other parameters.

This procedure should normally be used for a “ping” and nothing else. This routine allows programs to do lookup and call, all in one step.

Note: Even if the server is not running `rpcbind` does not return any error messages to the caller. In such a case, the caller times out.

Note: `rpcb_rmtcall()` is only available for connectionless transports.

`rpcb_set()` An interface to the `rpcbind` service, which establishes a mapping between the triple [*prognum*, *versnum*, *netconf->nc_netid*] and *svcaddr* on the machine's `rpcbind` service. The value of *nc_netid* must correspond to a network identifier that is defined by the `netconfig` database. This routine returns TRUE if it succeeds, FALSE otherwise. See also `svc_reg()` in [rpc_svc_calls\(3NSL\)](#). If there already exists such an entry with `rpcbind`, `rpcb_set()` will fail.

`rpcb_unset()` An interface to the `rpcbind` service, which destroys the mapping between the triple [*prognum*, *versnum*, *netconf->nc_netid*] and the address on the machine's `rpcbind` service. If *netconf* is NULL, `rpcb_unset()` destroys all mapping between the triple [*prognum*, *versnum*, *all-transport*s] and the addresses on the machine's `rpcbind` service. This routine returns TRUE if it succeeds, FALSE otherwise. Only the owner of the service or the super-user can destroy the mapping. See also `svc_unreg()` in [rpc_svc_calls\(3NSL\)](#).

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [rpcbind\(1M\)](#), [rpcinfo\(1M\)](#), [rpc_clnt_calls\(3NSL\)](#), [rpc_clnt_create\(3NSL\)](#), [rpc_svc_calls\(3NSL\)](#), [attributes\(5\)](#)

Name `rpc_clnt_auth`, `auth_destroy`, `authnone_create`, `authsys_create`, `authsys_create_default` – library routines for client side remote procedure call authentication

Synopsis

```
void auth_destroy(AUTH *auth);

AUTH *authnone_create    (void)

AUTH *authsys_create(const char *host, const uid_t uid, const gid_t gid,
                     const int len, const gid_t *aup_gids);

AUTH *authsys_create_default(void)
```

Description These routines are part of the RPC library that allows C language programs to make procedure calls on other machines across the network, with desired authentication.

These routines are normally called after creating the CLIENT handle. The `cl_auth` field of the CLIENT structure should be initialized by the AUTH structure returned by some of the following routines. The client's authentication information is passed to the server when the RPC call is made.

Only the NULL and the SYS style of authentication is discussed here. For the DES style authentication, please refer to [secure_rpc\(3NSL\)](#).

The NULL and SYS style of authentication are safe in multithreaded applications. For the MT-level of the DES style, see its pages.

Routines The following routines require that the header `<rpc/rpc.h>` be included (see [rpc\(3NSL\)](#) for the definition of the AUTH data structure).

```
#include <rpc/rpc.h>
```

`auth_destroy()` A function macro that destroys the authentication information associated with *auth*. Destruction usually involves deallocation of private data structures. The use of *auth* is undefined after calling `auth_destroy()`.

`authnone_create()` Create and return an RPC authentication handle that passes nonusable authentication information with each remote procedure call. This is the default authentication used by RPC.

`authsys_create()` Create and return an RPC authentication handle that contains AUTH_SYS authentication information. The parameter *host* is the name of the machine on which the information was created; *uid* is the user's user ID; *gid* is the user's current group ID; *len* and *aup_gids* refer to a counted array of groups to which the user belongs.

`authsys_create_default` Call `authsys_create()` with the appropriate parameters.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [rpc\(3NSL\)](#), [rpc_clnt_calls\(3NSL\)](#), [rpc_clnt_create\(3NSL\)](#), [secure_rpc\(3NSL\)](#), [attributes\(5\)](#)

Name `rpc_clnt_calls`, `clnt_call`, `clnt_send`, `clnt_freeres`, `clnt_geterr`, `clnt_perrno`, `clnt_perror`, `clnt_sperrno`, `clnt_sperror`, `rpc_broadcast`, `rpc_broadcast_exp`, `rpc_call` – library routines for client side calls

Synopsis `#include <rpc/rpc.h>`

```
enum clnt_stat clnt_call(CLIENT *clnt, const rpcproc_t procnum,
                        const xdrproc_t inproc, const caddr_t in, const xdrproc_t outproc,
                        caddr_t out, const struct timeval tout);

enum clnt_stat clnt_send (CLIENT *clnt, const u_long
                        procnum, const xdrproc_t proc, const caddr_t in);

bool_t clnt_freeres(CLIENT *clnt, const xdrproc_t outproc,
                    caddr_t out);

void clnt_geterr(const CLIENT *clnt, struct rpc_err *errp);

void clnt_perrno(const enum clnt_stat stat);

void clnt_perror(const CLIENT *clnt, const char *s);

char *clnt_sperrno(const enum clnt_stat stat);

char *clnt_sperror(const CLIENT *clnt, const char *s);

enum clnt_stat rpc_broadcast(const rpcprog_t prognum,
                            const rpcvers_t versnum, const rpcproc_t procnum,
                            const xdrproc_t inproc, const caddr_t in,
                            const xdrproc_t outproc, caddr_t out,
                            const resultproc_t eachresult, const char *nettype);

enum clnt_stat rpc_broadcast_exp(const rpcprog_t prognum,
                                const rpcvers_t versnum, const rpcproc_t procnum,
                                const xdrproc_t txargs, caddr_t argsp, const xdrproc_t txresults,
                                caddr_t resultsp, const resultproc_t eachresult, const int inittime,
                                const int waittime, const char *nettype);

enum clnt_stat rpc_call(const char *host, const rpcprog_t prognum,
                       const rpcvers_t versnum, const rpcproc_t procnum, const xdrproc_t inproc,
                       const char *in, const xdrproc_t outproc, char *out, const char *nettype);
```

Description RPC library routines allow C language programs to make procedure calls on other machines across the network. First, the client calls a procedure to send a request to the server. Upon receipt of the request, the server calls a dispatch routine to perform the requested service and then sends back a reply.

The `clnt_call()`, `rpc_call()`, and `rpc_broadcast()` routines handle the client side of the procedure call. The remaining routines deal with error handling.

Some of the routines take a CLIENT handle as one of the parameters. A CLIENT handle can be created by an RPC creation routine such as `clnt_create()`. See [rpc_clnt_create\(3NSL\)](#).

These routines are safe for use in multithreaded applications. CLIENT handles can be shared between threads; however, in this implementation requests by different threads are serialized. In other words, the first request will receive its results before the second request is sent.

Routines See [rpc\(3NSL\)](#) for the definition of the CLIENT data structure.

`clnt_call()` A function macro that calls the remote procedure *procnum* associated with the client handle, *clnt*, which is obtained with an RPC client creation routine such as `clnt_create()`. See [rpc_clnt_create\(3NSL\)](#). The parameter *inproc* is the XDR function used to encode the procedure's parameters, and *outproc* is the XDR function used to decode the procedure's results. *in* is the address of the procedure's argument(s), and *out* is the address of where to place the result(s). *tout* is the time allowed for results to be returned, which is overridden by a time-out set explicitly through `clnt_control()`. See [rpc_clnt_create\(3NSL\)](#).

If the remote call succeeds, the status returned is `RPC_SUCCESS`. Otherwise, an appropriate status is returned.

`clnt_send()` Use the `clnt_send()` function to call a remote asynchronous function.

The `clnt_send()` function calls the remote function *procnum()* associated with the client handle, *clnt*, which is obtained with an RPC client creation routine such as `clnt_create()`. See [rpc_clnt_create\(3NSL\)](#). The parameter *proc* is the XDR function used to encode the procedure's parameters. The parameter *in* is the address of the procedure's argument(s).

By default, the blocking I/O mode is used. See the [clnt_control\(3NSL\)](#) man page for more information on I/O modes.

The `clnt_send()` function does not check if the program version number supplied to `clnt_create()` is registered with the `rpcbind` service. Use `clnt_create_vers()` instead of `clnt_create()` to check on incorrect version number registration. `clnt_create_vers()` will return a valid handle to the client only if a version within the range supplied to `clnt_create_vers()` is supported by the server.

`RPC_SUCCESS` is returned when a request is successfully delivered to the transport layer. This does not mean that the request was received. If an error is returned, use the `clnt_getterr()` routine

	to find the failure status or the <code>clnt_perrno()</code> routine to translate the failure status into error messages.
<code>clnt_freeres()</code>	A function macro that frees any data allocated by the RPC/XDR system when it decoded the results of an RPC call. The parameter <i>out</i> is the address of the results, and <i>outproc</i> is the XDR routine describing the results. This routine returns 1 if the results were successfully freed; otherwise it returns 0.
<code>clnt_geterr()</code>	A function macro that copies the error structure out of the client handle to the structure at address <i>errp</i> .
<code>clnt_perrno()</code>	Prints a message to standard error corresponding to the condition indicated by <i>stat</i> . A newline is appended. It is normally used after a procedure call fails for a routine for which a client handle is not needed, for instance <code>rpc_call()</code>
<code>clnt_perror()</code>	Prints a message to the standard error indicating why an RPC call failed; <i>clnt</i> is the handle used to do the call. The message is prepended with string <i>s</i> and a colon. A newline is appended. This routine is normally used after a remote procedure call fails for a routine that requires a client handle, for instance <code>clnt_call()</code> .
<code>clnt_sperno()</code>	<p>Takes the same arguments as <code>clnt_perrno()</code>, but instead of sending a message to the standard error indicating why an RPC call failed, returns a pointer to a string that contains the message.</p> <p><code>clnt_sperno()</code> is normally used instead of <code>clnt_perrno()</code> when the program does not have a standard error, as a program running as a server quite likely does not. <code>clnt_sperno()</code> is also used if the programmer does not want the message to be output with <code>printf()</code>, or if a message format different than that supported by <code>clnt_perrno()</code> is to be used. See printf(3C). Unlike <code>clnt_spererror()</code> and <code>clnt_spcreatererror()</code>, <code>clnt_sperno()</code> does not return a pointer to static data. Therefore, the result is not overwritten on each call. See rpc_clnt_create(3NSL).</p>
<code>clnt_spererror()</code>	<p>Similar to <code>clnt_perror()</code>, except that like <code>clnt_sperno()</code>, it returns a string instead of printing to standard error. However, <code>clnt_spererror()</code> does not append a newline at the end of the message.</p> <p><code>clnt_spererror()</code> returns a pointer to a buffer that is overwritten on each call. In multithreaded applications, this buffer is implemented as thread-specific data.</p>

`rpc_broadcast()` Similar to `rpc_call()`, except that the call message is broadcast to all the connectionless transports specified by *nettype*. If *nettype* is NULL, it defaults to *netpath*. Each time it receives a response, this routine calls `eachresult()`, whose form is:

```
bool_t eachresult(caddr_t out, const struct netbuf *addr,
const struct netconfig *netconf);
```

where *out* is the same as *out* passed to `rpc_broadcast()`, except that the remote procedure's output is decoded there. *addr* points to the address of the machine that sent the results, and *netconf* is the *netconfig* structure of the transport on which the remote server responded. If `eachresult()` returns 0, `rpc_broadcast()` waits for more replies; otherwise, it returns with appropriate status.

The broadcast file descriptors are limited in size to the maximum transfer size of that transport. For Ethernet, this value is 1500 bytes. `rpc_broadcast()` uses AUTH_SYS credentials by default. See [rpc_clnt_auth\(3NSL\)](#).

`rpc_broadcast_exp()` Similar to `rpc_broadcast()`, except that the initial timeout, *inittime* and the maximum timeout, *waittime*, are specified in milliseconds.

inittime is the initial time that `rpc_broadcast_exp()` waits before resending the request. After the first resend, the retransmission interval increases exponentially until it exceeds *waittime*.

`rpc_call()` Calls the remote procedure associated with *prognum*, *versnum*, and *procnum* on the machine, *host*. The parameter *inproc* is used to encode the procedure's parameters, and *outproc* is used to decode the procedure's results. *in* is the address of the procedure's argument(s), and *out* is the address of where to place the result(s). *nettype* can be any of the values listed on [rpc\(3NSL\)](#). This routine returns RPC_SUCCESS if it succeeds, or it returns an appropriate status. Use the `clnt_perrno()` routine to translate failure status into error messages.

The `rpc_call()` function uses the first available transport belonging to the class *nettype* on which it can create a connection. You do not have control of timeouts or authentication using this routine.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Architecture	All
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Evolving
MT-Level	MT-Safe

See Also `printf(3C)`, `rpc(3NSL)`, `rpc_clnt_auth(3NSL)`, `rpc_clnt_create(3NSL)`, `attributes(5)`

Name `rpc_clnt_create`, `clnt_control`, `clnt_create`, `clnt_create_timed`, `clnt_create_vers`, `clnt_create_vers_timed`, `clnt_destroy`, `clnt_dg_create`, `clnt_pcreateerror`, `clnt_raw_create`, `clnt_screateerror`, `clnt_tli_create`, `clnt_tp_create`, `clnt_tp_create_timed`, `clnt_vc_create`, `rpc_createerr`, `clnt_door_create` – library routines for dealing with creation and manipulation of CLIENT handles

Synopsis `#include <rpc/rpc.h>`

```
bool_t clnt_control(CLIENT *clnt, const uint_t req, char *info);

CLIENT *clnt_create(const char *host, const rpcprog_t prognum,
    const rpcvers_t versnum, const char *nettype);

CLIENT *clnt_create_timed(const char *host, const rpcprog_t prognum,
    const rpcvers_t versnum, const nettype,
    const struct timeval *timetout);

CLIENT *clnt_create_vers (const char *host,
    rpcvers_t *const rpcprog_t prognum, vers_outp,
    const rpcvers_t vers_low, const rpcvers_t vers_high,
    char *nettype);

CLIENT *clnt_create_vers_timed(const char *host,
    const rpcprog_t prognum, rpcvers_t *vers_outp,
    const rpcvers_t vers_low, const rpcvers_t vers_high,
    char *nettype, const struct timeval *timeout);

void clnt_destroy(CLIENT *clnt);

CLIENT *clnt_dg_create(const int fildes,
    const struct netbuf *svcaddr, const rpcprog_t prognum,
    const rpcvers_t versnum, const uint_t sendsz,
    const uint_t recsz);

void clnt_pcreateerror(const char *s);

CLIENT *clnt_raw_create(const rpcprog_t prognum,
    const rpcvers_t versnum);

char *clnt_screateerror(const char *s);

CLIENT *clnt_tli_create(const int fildes,
    const struct netconfig *netconf, const struct netbuf *svcaddr,
    const rpcprog_t prognum, const rpcvers_t versnum,
    const uint_t sendsz, const uint_t recsz);

CLIENT *clnt_tp_create(const char *host,
    const rpcprog_t prognum, const rpcvers_t versnum,
    const struct netconfig *netconf);

CLIENT *clnt_tp_create_timed(const char *host,
    const rpcprog_t prognum, const rpcvers_t versnum,
    const struct netconfig *netconf, const struct timeval *timeout);
```

```

CLIENT *clnt_vc_create(const int filde,
    const struct netbuf *svcaddr, const rpcprog_t prognum,
    const rpcvers_t versnum, const uint_t sendsz,
    const uint_t recsz);

struct rpc_createerr rpc_createerr

CLIENT *clnt_door_create(const rpcprog_t prognum,
    const rpcvers_t versnum, const uint_t sendsz);

```

Description RPC library routines allow C language programs to make procedure calls on other machines across the network. First a CLIENT handle is created and then the client calls a procedure to send a request to the server. On receipt of the request, the server calls a dispatch routine to perform the requested service, and then sends a reply.

These routines are MT-Safe. In the case of multithreaded applications, the `-mt` option must be specified on the command line at compilation time. When the `-mt` option is specified, `rpc_createerr()` becomes a macro that enables each thread to have its own `rpc_createerr()`. See [threads\(5\)](#).

Routines See [rpc\(3NSL\)](#) for the definition of the CLIENT data structure.

`clnt_control()` A function macro to change or retrieve various information about a client object. *req* indicates the type of operation, and *info* is a pointer to the information. For both connectionless and connection-oriented transports, the supported values of *req* and their argument types and what they do are:

```

CLSET_TIMEOUT struct timeval * set total timeout
CLGET_TIMEOUT struct timeval * get total timeout

```

If the timeout is set using `clnt_control()`, the timeout argument passed by `clnt_call()` is ignored in all subsequent calls. If the timeout value is set to 0, `clnt_control()` immediately returns `RPC_TIMEDOUT`. Set the timeout parameter to 0 for batching calls.

```

CLGET_SERVER_ADDR struct netbuf * get server's address
CLGET_SVC_ADDR    struct netbuf * get server's address
CLGET_FD          int * get associated file descriptor
CLSET_FD_CLOSE    void close the file descriptor when
                    destroying the client handle
                    (see clnt_destroy())
CLSET_FD_NCLOSE   void do not close the file
                    descriptor when destroying the client handle
CLGET_VERS        rpcvers_t get the RPC program's version
                    number associated with the
                    client handle
CLSET_VERS        rpcvers_t set the RPC program's version
                    number associated with the

```

client handle. This assumes that the RPC server for this new version is still listening at the address of the previous version.

```

CLGET_XID    uint32_t    get the XID of the previous
                      remote procedure call
CLSET_XID    uint32_t    set the XID of the next
                      remote procedure call
CLGET_PROG   rpcprog_t   get program number
CLSET_PROG   rpcprog_t   set program number

```

The following operations are valid for connection-oriented transports only:

```

CLSET_IO_MODE rpciomode_t*    set the IO mode used
                              to send one-way requests. The argument for this operation
                              can be either:
- RPC_CL_BLOCKING    all sending operations block
                      until the underlying transport protocol has
                      accepted requests. If you specify this argument
                      you cannot use flush and getting and setting buffer
                      size is meaningless.
- RPC_CL_NONBLOCKING    sending operations do not
                      block and return as soon as requests enter the buffer.
                      You can now use non-blocking I/O. The requests in the
                      buffer are pending. The requests are sent to
                      the server as soon as a two-way request is sent
                      or a flush is done. You are responsible for flushing
                      the buffer. When you choose RPC_CL_NONBLOCKING argument
                      you have a choice of flush modes as specified by
                      CLSET_FLUSH_MODE.
CLGET_IO_MODE rpciomode_t*    get the current IO mode
CLSET_FLUSH_MODE rpcflushmode_t*    set the flush mode.
                              The flush mode can only be used in non-blocking I/O mode.
                              The argument can be either of the following:
- RPC_CL_BESTEFFORT_FLUSH: All flushes send requests
                              in the buffer until the transport end-point blocks.
                              If the transport connection is congested, the call
                              returns directly.
- RPC_CL_BLOCKING_FLUSH: Flush blocks until the
                              underlying transport protocol accepts all pending
                              requests into the queue.
CLGET_FLUSH_MODE rpcflushmode_t*    get the current flush mode.
CLFLUSH rpcflushmode_t    flush the pending requests.
                              This command can only be used in non-blocking I/O mode.
                              The flush policy depends on which of the following
                              parameters is specified:

```

- `RPC_CL_DEFAULT_FLUSH`, or `NULL`: The flush is done according to the current flush mode policy (see `CLSET_FLUSH_MODE` option).
- `RPC_CL_BESTEFFORT_FLUSH`: The flush tries to send pending requests without blocking; the call returns directly. If the transport connection is congested, this call could return without the request being sent.
- `RPC_CL_BLOCKING_FLUSH`: The flush sends all pending requests. This call will block until all the requests have been accepted by the transport layer.

`CLSET_CONNMAXREC_SIZE int*` set the buffer size.
It is not possible to dynamically resize the buffer if it contains data.
The default size of the buffer is 16 kilobytes.

`CLGET_CONNMAXREC_SIZE int*` get the current size of the buffer

`CLGET_CURRENT_REC_SIZE int*` get the size of the pending requests stored in the buffer. Use of this command is only recommended when you are in non-blocking I/O mode. The current size of the buffer is always zero when the handle is in blocking mode as the buffer is not used in this mode.

The following operations are valid for connectionless transports only:

`CLSET_RETRY_TIMEOUT struct timeval *` set the retry timeout
`CLGET_RETRY_TIMEOUT struct timeval *` get the retry timeout

The retry timeout is the time that RPC waits for the server to reply before retransmitting the request.

`clnt_control()` returns `TRUE` on success and `FALSE` on failure.

`clnt_create()`

Generic client creation routine for program *prognum* and version *versnum*. *host* identifies the name of the remote host where the server is located. *nettype* indicates the class of transport protocol to use. The transports are tried in left to right order in `NETPATH` variable or in top to bottom order in the netconfig database.

`clnt_create()` tries all the transports of the *nettype* class available from the `NETPATH` environment variable and the netconfig database, and chooses the first successful one. A default timeout is set and can be modified using

`clnt_control()`. This routine returns NULL if it fails. The `clnt_pcreateerror()` routine can be used to print the reason for failure.

Note that `clnt_create()` returns a valid client handle even if the particular version number supplied to `clnt_create()` is not registered with the `rpcbind` service. This mismatch will be discovered by a `clnt_call` later (see [rpc_clnt_calls\(3NSL\)](#)).

`clnt_create_timed()`

Generic client creation routine which is similar to `clnt_create()` but which also has the additional parameter *timeout* that specifies the maximum amount of time allowed for each transport class tried. In all other respects, the `clnt_create_timed()` call behaves exactly like the `clnt_create()` call.

`clnt_create_vers()`

Generic client creation routine which is similar to `clnt_create()` but which also checks for the version availability. *host* identifies the name of the remote host where the server is located. *nettype* indicates the class transport protocols to be used. If the routine is successful it returns a client handle created for the highest version between *vers_low* and *vers_high* that is supported by the server. *vers_outp* is set to this value. That is, after a successful return *vers_low* <= **vers_outp* <= *vers_high*. If no version between *vers_low* and *vers_high* is supported by the server then the routine fails and returns NULL. A default timeout is set and can be modified using `clnt_control()`. This routine returns NULL if it fails. The `clnt_pcreateerror()` routine can be used to print the reason for failure.

Note: `clnt_create()` returns a valid client handle even if the particular version number supplied to `clnt_create()` is not registered with the `rpcbind` service. This mismatch will be discovered by a `clnt_call` later (see [rpc_clnt_calls\(3NSL\)](#)). However, `clnt_create_vers()` does this for you and returns a valid handle only if a version within the range supplied is supported by the server.

`clnt_create_vers_timed()`

Generic client creation routine similar to `clnt_create_vers()` but with the additional parameter *timeout*, which specifies the maximum amount of time

	allowed for each transport class tried. In all other respects, the <code>clnt_create_vers_timed()</code> call behaves exactly like the <code>clnt_create_vers()</code> call.
<code>clnt_destroy()</code>	<p>A function macro that destroys the client's RPC handle. Destruction usually involves deallocation of private data structures, including <i>clnt</i> itself. Use of <i>clnt</i> is undefined after calling <code>clnt_destroy()</code>. If the RPC library opened the associated file descriptor, or <code>CLSET_FD_CLOSE</code> was set using <code>clnt_control()</code>, the file descriptor will be closed.</p> <p>The caller should call <code>auth_destroy(clnt->cl_auth)</code> (before calling <code>clnt_destroy()</code>) to destroy the associated AUTH structure (see rpc_clnt_auth(3NSL)).</p>
<code>clnt_dg_create()</code>	<p>This routine creates an RPC client for the remote program <i>prognum</i> and version <i>versnum</i>; the client uses a connectionless transport. The remote program is located at address <i>svcaddr</i>. The parameter <i>fildev</i> is an open and bound file descriptor. This routine will resend the call message in intervals of 15 seconds until a response is received or until the call times out. The total time for the call to time out is specified by <code>clnt_call()</code> (see <code>clnt_call()</code> in rpc_clnt_calls(3NSL)). The retry time out and the total time out periods can be changed using <code>clnt_control()</code>. The user may set the size of the send and receive buffers with the parameters <i>sendsz</i> and <i>recvsz</i>; values of 0 choose suitable defaults. This routine returns NULL if it fails.</p>
<code>clnt_pcreateerror()</code>	<p>Print a message to standard error indicating why a client RPC handle could not be created. The message is prepended with the string <i>s</i> and a colon, and appended with a newline.</p>
<code>clnt_raw_create()</code>	<p>This routine creates an RPC client handle for the remote program <i>prognum</i> and version <i>versnum</i>. The transport used to pass messages to the service is a buffer within the process's address space, so the corresponding RPC server should live in the same address space; (see <code>svc_raw_create()</code> in rpc_svc_create(3NSL)). This allows simulation of RPC and measurement of RPC overheads, such as round trip times, without any kernel or networking interference. This routine returns NULL if it fails.</p> <p><code>clnt_raw_create()</code> should be called after <code>svc_raw_create()</code>.</p>

<code>clnt_screateerror()</code>	<p>Like <code>clnt_pcreateerror()</code>, except that it returns a string instead of printing to the standard error. A newline is not appended to the message in this case.</p> <p>Warning: returns a pointer to a buffer that is overwritten on each call. In multithread applications, this buffer is implemented as thread-specific data.</p>
<code>clnt_tli_create()</code>	<p>This routine creates an RPC client handle for the remote program <i>prognum</i> and version <i>versnum</i>. The remote program is located at address <i>svcaddr</i>. If <i>svcaddr</i> is NULL and it is connection-oriented, it is assumed that the file descriptor is connected. For connectionless transports, if <i>svcaddr</i> is NULL, <code>RPC_UNKNOWADDR</code> error is set. <i>fildev</i> is a file descriptor which may be open, bound and connected. If it is <code>RPC_ANYFD</code>, it opens a file descriptor on the transport specified by <i>netconf</i>. If <i>fildev</i> is <code>RPC_ANYFD</code> and <i>netconf</i> is NULL, a <code>RPC_UNKNOWPROTO</code> error is set. If <i>fildev</i> is unbound, then it will attempt to bind the descriptor. The user may specify the size of the buffers with the parameters <i>sendsz</i> and <i>rcvsvsz</i>; values of 0 choose suitable defaults. Depending upon the type of the transport (connection-oriented or connectionless), <code>clnt_tli_create()</code> calls appropriate client creation routines. This routine returns NULL if it fails. The <code>clnt_pcreateerror()</code> routine can be used to print the reason for failure. The remote <code>rpcbind</code> service (see rpcbind(1M)) is not consulted for the address of the remote service.</p>
<code>clnt_tp_create()</code>	<p>Like <code>clnt_create()</code> except <code>clnt_tp_create()</code> tries only one transport specified through <i>netconf</i>.</p> <p><code>clnt_tp_create()</code> creates a client handle for the program <i>prognum</i>, the version <i>versnum</i>, and for the transport specified by <i>netconf</i>. Default options are set, which can be changed using <code>clnt_control()</code> calls. The remote <code>rpcbind</code> service on the host <i>host</i> is consulted for the address of the remote service. This routine returns NULL if it fails. The <code>clnt_pcreateerror()</code> routine can be used to print the reason for failure.</p>
<code>clnt_tp_create_timed()</code>	<p>Like <code>clnt_tp_create()</code> except <code>clnt_tp_create_timed()</code> has the extra parameter <i>timeout</i> which specifies the maximum time allowed for the creation attempt to succeed.</p>

	<p>In all other respects, the <code>clnt_tp_create_timed()</code> call behaves exactly like the <code>clnt_tp_create()</code> call.</p>
<code>clnt_vc_create()</code>	<p>This routine creates an RPC client for the remote program <i>prognum</i> and version <i>versnum</i>; the client uses a connection-oriented transport. The remote program is located at address <i>svcaddr</i>. The parameter <i>fildev</i> is an open and bound file descriptor. The user may specify the size of the send and receive buffers with the parameters <i>sendsz</i> and <i>recvsz</i>; values of 0 choose suitable defaults. This routine returns NULL if it fails.</p> <p>The address <i>svcaddr</i> should not be NULL and should point to the actual address of the remote program. <code>clnt_vc_create()</code> does not consult the remote rpcbind service for this information.</p>
<code>rpc_createerr()</code>	<p>A global variable whose value is set by any RPC client handle creation routine that fails. It is used by the routine <code>clnt_pcreateerror()</code> to print the reason for the failure.</p> <p>In multithreaded applications, <code>rpc_createerr</code> becomes a macro which enables each thread to have its own <code>rpc_createerr</code>.</p>
<code>clnt_door_create()</code>	<p>This routine creates an RPC client handle over doors for the given program <i>prognum</i> and version <i>versnum</i>. Doors is a transport mechanism that facilitates fast data transfer between processes on the same machine. The user may set the size of the send buffer with the parameter <i>sendsz</i>. If <i>sendsz</i> is 0, the corresponding default buffer size is 16 Kbyte. The <code>clnt_door_create()</code> routine returns NULL if it fails and sets a value for <code>rpc_createerr</code>.</p>

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Architecture	All
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Evolving
MT-Level	MT-Safe

See Also `rpcbind(1M)`, `rpc(3NSL)`, `rpc_clnt_auth(3NSL)`, `rpc_clnt_calls(3NSL)`,
`rpc_svc_create(3NSL)`, `svc_raw_create(3NSL)`, `threads(5)`, `attributes(5)`

Name `rpc_control` – library routine for manipulating global RPC attributes for client and server applications

Synopsis `bool_t rpc_control(int op, void *info);`

Description This RPC library routine allows applications to set and modify global RPC attributes that apply to clients as well as servers. At present, it supports only server side operations. This function allows applications to set and modify global attributes that apply to client as well as server functions. *op* indicates the type of operation, and *info* is a pointer to the operation specific information. The supported values of *op* and their argument types, and what they do are:

<code>RPC_SVC_MTMODE_SET</code>	<code>int *</code>	set multithread mode
<code>RPC_SVC_MTMODE_GET</code>	<code>int *</code>	get multithread mode
<code>RPC_SVC_THRMAX_SET</code>	<code>int *</code>	set maximum number of threads
<code>RPC_SVC_THRMAX_GET</code>	<code>int *</code>	get maximum number of threads
<code>RPC_SVC_THRTOTAL_GET</code>	<code>int *</code>	get number of active threads
<code>RPC_SVC_THRCREATES_GET</code>	<code>int *</code>	get number of threads created
<code>RPC_SVC_THRERRORS_GET</code>	<code>int *</code>	get number of thread create errors
<code>RPC_SVC_USE_POLLFD</code>	<code>int *</code>	set number of file descriptors to unlimited
<code>RPC_SVC_CONNMAXREC_SET</code>	<code>int *</code>	set non-blocking max rec size
<code>RPC_SVC_CONNMAXREC_GET</code>	<code>int *</code>	get non-blocking max rec size

There are three multithread (MT) modes. These are:

<code>RPC_SVC_MT_NONE</code>	Single threaded mode	(default)
<code>RPC_SVC_MT_AUTO</code>	Automatic MT mode	
<code>RPC_SVC_MT_USER</code>	User MT mode	

Unless the application sets the Automatic or User MT modes, it will stay in the default (single threaded) mode. See the *Network Interfaces Programmer's Guide* for the meanings of these modes and programming examples. Once a mode is set, it cannot be changed.

By default, the maximum number of threads that the server will create at any time is 16. This allows the service developer to put a bound on thread resources consumed by a server. If a server needs to process more than 16 client requests concurrently, the maximum number of threads must be set to the desired number. This parameter may be set at any time by the server.

Set and get operations will succeed even in modes where the operations don't apply. For example, you can set the maximum number of threads in any mode, even though it makes sense only for the Automatic MT mode. All of the get operations except `RPC_SVC_MTMODE_GET` apply only to the Automatic MT mode, so values returned in other modes may be undefined.

By default, RPC servers are limited to a maximum of 1024 file descriptors or connections due to limitations in the historical interfaces `svc_fdset(3NSL)` and `svc_getreqset(3NSL)`. Applications written to use the preferred interfaces of `svc_pollfd(3NSL)` and `svc_getreq_poll(3NSL)` can use an unlimited number of file descriptors. Setting *info* to point to a non-zero integer and *op* to `RPC_SVC_USE_POLLFD` removes the limitation.

Connection oriented RPC transports read RPC requests in blocking mode by default. Thus, they may be adversely affected by network delays and broken clients.

`RPC_SVC_CONNMAXREC_SET` enables non-blocking mode and establishes the maximum record size (in bytes) for RPC requests; RPC responses are not affected. Buffer space is allocated as needed up to the specified maximum, starting at the maximum or `RPC_MAXDATASIZE`, whichever is smaller.

The value established by `RPC_SVC_CONNMAXREC_SET` is used when a connection is created, and it remains in effect for that connection until it is closed. To change the value for existing connections on a per-connection basis, see [svc_control\(3NSL\)](#).

`RPC_SVC_CONNMAXREC_GET` retrieves the current maximum record size. A zero value means that no maximum is in effect, and that the connections are in blocking mode.

info is a pointer to an argument of type `int`. Non-connection RPC transports ignore `RPC_SVC_CONNMAXREC_SET` and `RPC_SVC_CONNMAXREC_GET`.

Return Values This routine returns `TRUE` if the operation was successful and returns `FALSE` otherwise.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [rpcbind\(1M\)](#), [rpc\(3NSL\)](#), [rpc_svc_calls\(3NSL\)](#), [attributes\(5\)](#)

Network Interfaces Programmer's Guide

Name `rpc_gss_getcred` – get credentials of client

Synopsis `#include <rpc/rpcsec_gss.h>`

```
bool_t rpc_gss_getcred(struct svc_req *req, rpc_gss_rawcred_t **rcred,  
    rpc_gss_ucred **ucred, void **cookie);
```

Description `rpc_gss_getcred()` is used by a server to fetch the credentials of a client. These credentials may either be network credentials (in the form of a `rpc_gss_rawcred_t` structure) or UNIX credentials.

For more information on RPCSEC_GSS data types, see the [rpcsec_gss\(3NSL\)](#) man page.

Parameters Essentially, `rpc_gss_getcred()` passes a pointer to a request (`svc_req`) as well as pointers to two credential structures and a user-defined cookie; if `rpc_gss_getcred()` is successful, at least one credential structure is "filled out" with values, as is, optionally, the cookie.

- req* Pointer to the received service request. `svc_req` is an RPC structure containing information on the context of an RPC invocation, such as program, version, and transport information.
- rcred* A pointer to an `rpc_gss_rawcred_t` structure pointer. This structure contains the version number of the RPCSEC_GSS protocol being used; the security mechanism and QOPs for this session (as strings); principal names for the client (as a `rpc_gss_principal_t` structure) and server (as a string); and the security service (integrity, privacy, etc., as an enum). If an application is not interested in these values, it may pass NULL for this parameter.
- ucred* The caller's UNIX credentials, in the form of a pointer to a pointer to a `rpc_gss_ucred_t` structure, which includes the client's uid and gids. If an application is not interested in these values, it may pass NULL for this parameter.
- cookie* A four-byte quantity that an application may use in any manner it wants to; RPC does not interpret it. (For example, a cookie may be a pointer or index to a structure that represents a context initiator.) See also [rpc_gss_set_callback\(3NSL\)](#).

Return Values `rpc_gss_getcred()` returns TRUE if it is successful; otherwise, use `rpc_gss_get_error()` to get the error associated with the failure.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe
Availability	SUNWrsgr (32-bit)
	SUNWrsgrx (64-bit)

See Also [rpc\(3NSL\)](#), [rpc_gss_set_callback\(3NSL\)](#), [rpc_gss_set_svc_name\(3NSL\)](#), [rpcsec_gss\(3NSL\)](#), [attributes\(5\)](#)

ONC+ Developer's Guide

Linn, J. *RFC 2078, Generic Security Service Application Program Interface, Version 2*. Network Working Group. January 1997.

Name `rpc_gss_get_error` – get error codes on failure

Synopsis `#include <rpc/rpcsec_gss.h>`

```
bool_t rpc_gss_get_error(rpc_gss_error_t*error);
```

Description `rpc_gss_get_error()` fetches an error code when an `RPCSEC_GSS` routine fails.

`rpc_gss_get_error()` uses a `rpc_gss_error_t` structure of the following form:

```
typedef struct {
    int    rpc_gss_error;      RPCSEC_GSS error
    int    system_error;      system error
} rpc_gss_error_t;
```

Currently the only error codes defined for this function are

```
#define RPC_GSS_ER_SUCCESS      0    /* no error */
#define RPC_GSS_ER_SYSTEMERROR  1    /* system error */
```

Parameters Information on `RPCSEC_GSS` data types for parameters may be found on the [rpcsec_gss\(3NSL\)](#) man page.

error A `rpc_gss_error_t` structure. If the `rpc_gss_error` field is equal to `RPC_GSS_ER_SYSTEMERROR`, the `system_error` field will be set to the value of `errno`.

Return Values Unless there is a failure indication from an invoked `RPCSEC_GSS` function, `rpc_gss_get_error()` does not set `error` to a meaningful value.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTETYPE	ATTRIBUTEVALUE
MT-Level	MT-Safe
Availability	SUNWrsg (32-bit)
	SUNWrsgx (64-bit)

See Also [perror\(3C\)](#), [rpc\(3NSL\)](#), [rpcsec_gss\(3NSL\)](#), [attributes\(5\)](#)

ONC+ Developer's Guide

Linn, J. *RFC 2078, Generic Security Service Application Program Interface, Version 2*. Network Working Group. January 1997.

Notes Only system errors are currently returned.

Name `rpc_gss_get_mechanisms`, `rpc_gss_get_mech_info`, `rpc_gss_get_versions`, `rpc_gss_is_installed` – get information on mechanisms and RPC version

Synopsis `#include <rpc/rpcsec_gss.h>`

```
char **rpc_gss_get_mechanisms();
char **rpc_gss_get_mech_info(char *mech, rpc_gss_service_t *service);
bool_t rpc_gss_get_versions(u_int *vers_hi, u_int *vers_lo);
bool_t rpc_gss_is_installed(char *mech);
```

Description These "convenience functions" return information on available security mechanisms and versions of RPCSEC_GSS.

<code>rpc_gss_get_mechanisms()</code>	Returns a list of supported security mechanisms as a null-terminated list of character strings.
<code>rpc_gss_get_mech_info()</code>	Takes two arguments: an ASCII string representing a mechanism type, for example, <code>kerberosv5</code> , and a pointer to a <code>rpc_gss_service_t</code> enum. <code>rpc_gss_get_mech_info()</code> will return NULL upon error or if no <code>/etc/gss/qop</code> file is present. Otherwise, it returns a null-terminated list of character strings of supported Quality of Protections (QOPs) for this mechanism. NULL or empty list implies only that the default QOP is available and can be specified to routines that need to take a QOP string parameter as NULL or as an empty string.
<code>rpc_gss_get_versions()</code>	Returns the highest and lowest versions of RPCSEC_GSS supported.
<code>rpc_gss_is_installed()</code>	Takes an ASCII string representing a mechanism, and returns TRUE if the mechanism is installed.

Parameters Information on RPCSEC_GSS data types for parameters may be found on the [rpcsec_gss\(3NSL\)](#) man page.

<i>mech</i>	An ASCII string representing the security mechanism in use. Valid strings may also be found in the <code>/etc/gss/mech</code> file.
<i>service</i>	A pointer to a <code>rpc_gss_service_t</code> enum, representing the current security service (privacy, integrity, or none).
<i>vers_hi</i>	
<i>vers_lo</i>	The highest and lowest versions of RPCSEC_GSS supported.

Files	<code>/etc/gss/mech</code>	File containing valid security mechanisms
	<code>/etc/gss/qop</code>	File containing valid QOP values

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe
Availability	SUNWrsg (32-bit)
	SUNWrsgx (64-bit)

See Also [rpc\(3NSL\)](#), [rpcsec_gss\(3NSL\)](#), [mech\(4\)](#), [qop\(4\)](#), [attributes\(5\)](#)

ONC+ Developer's Guide

Linn, J. *RFC 2743, Generic Security Service Application Program Interface Version 2, Update 1*.
Network Working Group. January 2000.

Notes This function will change in a future release.

Name `rpc_gss_get_principal_name` – Get principal names at server

Synopsis `#include <rpc/rpcsec_gss.h>`

```
bool_t rpc_gss_get_principal_name(rpc_gss_principal_ *principal,
                                  char *mech, char *name, char *node, char *domain);
```

Description Servers need to be able to operate on a client's principal name. Such a name is stored by the server as a `rpc_gss_principal_t` structure, an opaque byte string which can be used either directly in access control lists or as database indices which can be used to look up a UNIX credential. A server may, for example, need to compare a principal name it has received with the principal name of a known entity, and to do that, it must be able to generate `rpc_gss_principal_t` structures from known entities.

`rpc_gss_get_principal_name()` takes as input a security mechanism, a pointer to a `rpc_gss_principal_t` structure, and several parameters which uniquely identify an entity on a network: a user or service name, a node name, and a domain name. From these parameters it constructs a unique, mechanism-dependent principal name of the `rpc_gss_principal_t` structure type.

Parameters How many of the identifying parameters (*name*, *node*, and *domain*) are necessary to specify depends on the mechanism being used. For example, Kerberos V5 requires only a user name but can accept a node and domain name. An application can choose to set unneeded parameters to `NULL`.

Information on `RPCSEC_GSS` data types for parameters may be found on the [rpcsec_gss\(3NSL\)](#) man page.

<i>principal</i>	An opaque, mechanism-dependent structure representing the client's principal name.
<i>mech</i>	An ASCII string representing the security mechanism in use. Valid strings may be found in the <code>/etc/gss/mech</code> file, or by using <code>rpc_gss_get_mechanisms()</code> .
<i>name</i>	A UNIX login name (for example, 'gWashington') or service name, such as 'nfs'.
<i>node</i>	A node in a domain; typically, this would be a machine name (for example, 'valleyforge').
<i>domain</i>	A security domain; for example, a DNS, NIS, or NIS+ domain name ('eng.company.com').

Return Values `rpc_gss_get_principal_name()` returns `TRUE` if it is successful; otherwise, use `rpc_gss_get_error()` to get the error associated with the failure.

Files `/etc/gss/mech` File containing valid security mechanisms

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe
Availability	SUNWrsg (32-bit)
	SUNWrsgx (64-bit)

See Also [free\(3C\)](#), [rpc\(3NSL\)](#), [rpc_gss_get_mechanisms\(3NSL\)](#), [rpc_gss_set_svc_name\(3NSL\)](#), [rpcsec_gss\(3NSL\)](#), [mech\(4\)](#), [attributes\(5\)](#)

ONC+ Developer's Guide

Linn, J. *RFC 2078, Generic Security Service Application Program Interface, Version 2*. Network Working Group. January 1997.

Notes Principal names may be freed up by a call to [free\(3C\)](#). A principal name need only be freed in those instances where it was constructed by the application. (Values returned by other routines point to structures already existing in a context, and need not be freed.)

Name `rpc_gss_max_data_length`, `rpc_gss_svc_max_data_length` – get maximum data length for transmission

Synopsis `#include <rpc/rpcsec_gss.h>`

```
int rpc_gss_max_data_length(AUTH *handle, int max_tp_unit_len);
int rpc_gss_svc_max_data_length(struct svc_req *req, int max_tp_unit_len);
```

Description Performing a security transformation on a piece of data generally produces data with a different (usually greater) length. For some transports, such as UDP, there is a maximum length of data which can be sent out in one data unit. Applications need to know the maximum size a piece of data can be before it's transformed, so that the resulting data will still "fit" on the transport. These two functions return that maximum size.

`rpc_gss_max_data_length()` is the client-side version; `rpc_gss_svc_max_data_length()` is the server-side version.

Parameters

<i>handle</i>	An RPC context handle of type AUTH, returned when a context is created (for example, by <code>rpc_gss_seccreate()</code>). Security service and QOP are bound to this handle, eliminating any need to specify them.
<i>max_tp_unit_len</i>	The maximum size of a piece of data allowed by the transport.
<i>req</i>	A pointer to an RPC <code>svc_req</code> structure, containing information on the context (for example, program number and credentials).

Return Values Both functions return the maximum size of untransformed data allowed, as an `int`.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe
Availability	SUNWrsg (32-bit)
	SUNWrsgx (64-bit)

See Also [rpc\(3NSL\)](#), [rpcsec_gss\(3NSL\)](#), [attributes\(5\)](#)

ONC+ Developer's Guide

Linn, J. *RFC 2078, Generic Security Service Application Program Interface, Version 2*. Network Working Group. January 1997.

Name `rpc_gss_mech_to_oid`, `rpc_gss_qop_to_num` – map mechanism, QOP strings to non-string values

Synopsis `#include <rpc/rpcsec_gss.h>`

```
bool_t rpc_gss_mech_to_oid(charc*mech, rpc_gss_OIDc*oid);  
bool_t rpc_gss_qop_to_num(char *qop, char *mech, u_int *num);
```

Description Because in-kernel RPC routines use non-string values for mechanism and Quality of Protection (QOP), these routines exist to map strings for these attributes to their non-string counterparts. (The non-string values for QOP and mechanism are also found in the `/etc/gss/qop` and `/etc/gss/mech` files, respectively.) `rpc_gss_mech_to_oid()` takes a string representing a mechanism, as well as a pointer to a `rpc_gss_OID` object identifier structure. It then gives this structure values corresponding to the indicated mechanism, so that the application can now use the OID directly with RPC routines. `rpc_gss_qop_to_num()` does much the same thing, taking strings for QOP and mechanism and returning a number.

Parameters Information on `RPCSEC_GSS` data types for parameters may be found on the [rpcsec_gss\(3NSL\)](#) man page.

mech An ASCII string representing the security mechanism in use. Valid strings may be found in the `/etc/gss/mech` file.

oid An object identifier of type `rpc_gss_OID`, whose elements are usable by kernel-level RPC routines.

qop This is an ASCII string which sets the quality of protection (QOP) for the session. Appropriate values for this string may be found in the file `/etc/gss/qop`.

num The non-string value for the QOP.

Return Values Both functions return `TRUE` if they are successful, `FALSE` otherwise.

Files `/etc/gss/mech` File containing valid security mechanisms
`/etc/gss/qop` File containing valid QOP values

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe
Availability	SUNWrsg (32-bit)
	SUNWrsgx (64-bit)

See Also [rpc\(3NSL\)](#), [rpc_gss_get_error\(3NSL\)](#), [rpc_gss_get_mechanisms\(3NSL\)](#), [rpcsec_gss\(3NSL\)](#), [mech\(4\)](#), [qop\(4\)](#), [attributes\(5\)](#)

ONC+ Developer's Guide

Linn, J. *RFC 2078, Generic Security Service Application Program Interface, Version 2*. Network Working Group. January 1997.

Name `rpc_gss_seccreate` – create a security context using the RPCSEC_GSS protocol

Synopsis `#include <rpc/rpcsec_gss.h>`

```
AUTH *rpc_gss_seccreate(CLIENT *clnt, char *principal, char *mechanism,  
    rpc_gss_service_t service_type, char *qop,  
    rpc_gss_options_req_t *options_req,  
    rpc_gss_options_ret_t *options_ret);
```

Description `rpc_gss_seccreate()` is used by an application to create a security context using the RPCSEC_GSS protocol, making use of the underlying GSS-API network layer. `rpc_gss_seccreate()` allows an application to specify the type of security mechanism (for example, Kerberos v5), the type of service (for example, integrity checking), and the Quality of Protection (QOP) desired for transferring data.

Parameters Information on RPCSEC_GSS data types for parameters may be found on the [rpcsec_gss\(3NSL\)](#) man page.

<i>clnt</i>	This is the RPC client handle. <i>clnt</i> may be obtained, for example, from <code>clnt_create()</code> .
<i>principal</i>	This is the identity of the server principal, specified in the form <i>service@host</i> , where <i>service</i> is the name of the service the client wishes to access and <i>host</i> is the fully qualified name of the host where the service resides — for example, <code>nfs@mymachine.eng.company.com</code> .
<i>mechanism</i>	This is an ASCII string which indicates which security mechanism to use with this data. Appropriate mechanisms may be found in the file <code>/etc/gss/mech</code> ; additionally, <code>rpc_gss_get_mechanisms()</code> returns a list of supported security mechanisms (as null-terminated strings).
<i>service_type</i>	This sets the initial type of service for the session — privacy, integrity, authentication, or none.
<i>qop</i>	This is an ASCII string which sets the quality of protection (QOP) for the session. Appropriate values for this string may be found in the file <code>/etc/gss/qop</code> . Additionally, supported QOPs are returned (as null-terminated strings) by <code>rpc_gss_get_mech_info()</code> .
<i>options_req</i>	This structure contains options which are passed directly to the underlying GSS-API layer. If the caller specifies NULL for this parameter, defaults are used. (See NOTES, below.)
<i>options_ret</i>	These GSS-API options are returned to the caller. If the caller does not need to see these options, then it may specify NULL for this parameter. (See NOTES, below.)

Return Values `rpc_gss_seccreate()` returns a security context handle (an RPC authentication handle) of type AUTH. If `rpc_gss_seccreate()` cannot return successfully, the application can get an error number by calling `rpc_gss_get_error()`.

Files `/etc/gss/mech` File containing valid security mechanisms

`/etc/gss/qop` File containing valid QOP values.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTETYPE	ATTRIBUTEVALUE
MT-Level	MT-Safe
Availability	SUNWrsg (32-bits)
	SUNWrsgx (64-bits)

See Also [auth_destroy\(3NSL\)](#), [rpc\(3NSL\)](#), [rpc_gss_get_error\(3NSL\)](#), [rpc_gss_get_mechanisms\(3NSL\)](#), [rpcsec_gss\(3NSL\)](#), [mech\(4\)](#), [qop\(4\)](#), [attributes\(5\)](#)

ONC+ Developer's Guide

Linn, J. *RFC 2743, Generic Security Service Application Program Interface Version 2, Update 1*. Network Working Group. January 2000.

Notes Contexts may be destroyed normally, with `auth_destroy()`. See [auth_destroy\(3NSL\)](#)

Name `rpc_gss_set_callback` – specify callback for context

Synopsis `#include <rpc/rpcsec_gss.h>`

```
bool_t rpc_gss_set_callback(struct rpc_gss_callback_t *cb);
```

Description A server may want to specify a callback routine so that it knows when a context gets first used. This user-defined callback may be specified through the `rpc_gss_set_callback()` routine. The callback routine is invoked the first time a context is used for data exchanges, after the context is established for the specified program and version.

The user-defined callback routine should take the following form:

```
bool_t callback(struct svc_req *req, gss_cred_id_t deleg,
                gss_ctx_id_t gss_context, rpc_gss_lock_t *lock, void **cookie);
```

Parameters `rpc_gss_set_callback()` takes one argument: a pointer to a `rpc_gss_callback_t` structure. This structure contains the RPC program and version number as well as a pointer to a user-defined `callback()` routine. (For a description of `rpc_gss_callback_t` and other `RPCSEC_GSS` data types, see the [rpcsec_gss\(3NSL\)](#) man page.)

The user-defined `callback()` routine itself takes the following arguments:

<i>req</i>	Pointer to the received service request. <code>svc_req</code> is an RPC structure containing information on the context of an RPC invocation, such as program, version, and transport information.
<i>deleg</i>	Delegated credentials, if any. (See NOTES , below.)
<i>gss_context</i>	GSS context (allows server to do GSS operations on the context to test for acceptance criteria). See NOTES , below.
<i>lock</i>	This parameter is used to enforce a particular QOP and service for a session. This parameter points to a <code>RPCSEC_GSS rpc_gss_lock_t</code> structure. When the callback is invoked, the <code>rpc_gss_lock_t.locked</code> field is set to <code>TRUE</code> , thus locking the context. A locked context will reject all requests having different values for QOP or service than those specified by the <code>raw_cred</code> field of the <code>rpc_gss_lock_t</code> structure.
<i>cookie</i>	A four-byte quantity that an application may use in any manner it wants to — RPC does not interpret it. (For example, the cookie could be a pointer or index to a structure that represents a context initiator.) The cookie is returned, along with the caller's credentials, with each invocation of <code>rpc_gss_getcred()</code> .

Return Values `rpc_gss_set_callback()` returns `TRUE` if the use of the context is accepted; false otherwise.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe
Availability	SUNWrsg (32-bit)
	SUNWrsgx (64-bit)

See Also [rpc\(3NSL\)](#), [rpc_gss_getcred\(3NSL\)](#), [rpcsec_gss\(3NSL\)](#), [attributes\(5\)](#)

ONC+ Developer's Guide

Linn, J. *RFC 2078, Generic Security Service Application Program Interface, Version 2*. Network Working Group. January 1997.

Notes If a server does not specify a callback, all incoming contexts will be accepted.

Because the GSS-API is not currently exposed, the *deleg* and *gss_context* arguments are mentioned for informational purposes only, and the user-defined callback function may choose to do nothing with them.

Name `rpc_gss_set_defaults` – change service, QOP for a session

Synopsis `#include <rpc/rpcsec_gss.h>`

`bool_t rpc_gss_set_defaults(AUTH *auth, rpc_gss_service_t service, char *qop);`

Description `rpc_gss_set_defaults()` allows an application to change the service (privacy, integrity, authentication, or none) and Quality of Protection (QOP) for a transfer session. New values apply to the rest of the session (unless changed again).

Parameters Information on RPCSEC_GSS data types for parameters may be found on the [rpcsec_gss\(3NSL\)](#) man page.

- auth* An RPC authentication handle returned by `rpc_gss_seccreate()`.
- service* An enum of type `rpc_gss_service_t`, representing one of the following types of security service: authentication, privacy, integrity, or none.
- qop* A string representing Quality of Protection. Valid strings may be found in the file `/etc/gss/qop` or by using `rpc_gss_get_mech_info()`.

Return Values `rpc_gss_set_svc_name()` returns TRUE if it is successful; otherwise, use `rpc_gss_get_error()` to get the error associated with the failure.

Files `/etc/gss/qop` File containing valid QOPs

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe
Availability	SUNWrsg (32-bit)
	SUNWrsgx (64-bit)

See Also [rpc\(3NSL\)](#), [rpc_gss_get_mech_info\(3NSL\)](#), [rpcsec_gss\(3NSL\)](#), [qop\(4\)](#), [attributes\(5\)](#)

ONC+ Developer's Guide

Linn, J. RFC 2078, *Generic Security Service Application Program Interface, Version 2*. Network Working Group. January 1997.

Name `rpc_gss_set_svc_name` – send a principal name to a server

Synopsis `#include <rpc/rpcsec_gss.h>`

```
bool_t rpc_gss_set_svc_name(char *principal, char *mechanism,
                             u_int req_time, u_int program, u_int version);
```

Description `rpc_gss_set_svc_name()` sets the name of a principal the server is to represent. If a server is going to act as more than one principal, this procedure can be invoked for every such principal.

Parameters Information on RPCSEC_GSS data types for parameters may be found on the [rpcsec_gss\(3NSL\)](#) man page.

principal An ASCII string representing the server's principal name, given in the form of *service@host*.

mech An ASCII string representing the security mechanism in use. Valid strings may be found in the `/etc/gss/mech` file, or by using `rpc_gss_get_mechanisms()`.

req_time The time, in seconds, for which a credential should be valid. Note that the *req_time* is a hint to the underlying mechanism. The actual time that the credential will remain valid is mechanism dependent. In the case of kerberos the actual time will be `GSS_C_INDEFINITE`.

program The RPC program number for this service.

version The RPC version number for this service.

Return Values `rpc_gss_set_svc_name()` returns TRUE if it is successful; otherwise, use `rpc_gss_get_error()` to get the error associated with the failure.

Files `/etc/gss/mech` File containing valid security mechanisms

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe
Availability	SUNWrsg (32-bit)
	SUNWrsgx (64-bit)

See Also [rpc\(3NSL\)](#), [rpc_gss_get_mechanisms\(3NSL\)](#), [rpc_gss_get_principal_name\(3NSL\)](#), [rpcsec_gss\(3NSL\)](#), [mech\(4\)](#), [attributes\(5\)](#)

ONC+ Developer's Guide

Linn, J. RFC 2078, *Generic Security Service Application Program Interface, Version 2*. Network Working Group. January 1997.

Name rpcsec_gss – security flavor incorporating GSS-API protections

Synopsis `cc [flag...] file... -lnsl [library...]`
`#include <rpc/rpcsec_gss.h>`

Description RPCSEC_GSS is a security flavor which sits "on top" of the GSS-API (Generic Security Service API) for network transmissions. Applications using RPCSEC_GSS can take advantage of GSS-API security features; moreover, they can use any security mechanism (such as RSA public key or Kerberos) that works with the GSS-API.

The GSS-API offers two security services beyond the traditional authentication services (AUTH_DH, AUTH_SYS, and AUTH_KERB): integrity and privacy. With integrity, the system uses cryptographic checksumming to ensure the authenticity of a message (authenticity of originator, recipient, and data); privacy provides additional security by encrypting data. Applications using RPCSEC_GSS specify which service they wish to use. Type of security service is mechanism-independent.

Before exchanging data with a peer, an application must establish a context for the exchange. RPCSEC_GSS provides a single function for this purpose, `rpc_gss_seccreate()`, which allows the application to specify the security mechanism, Quality of Protection (QOP), and type of service at context creation. (The QOP parameter sets the cryptographic algorithms to be used with integrity or privacy, and is mechanism-dependent.) Once a context is established, applications can reset the QOP and type of service for each data unit exchanged, if desired.

Valid mechanisms and QOPs may be obtained from configuration files or from the name service. Each mechanism has a default QOP.

Contexts are destroyed with the usual RPC `auth_destroy()` call.

Data Structures Some of the data structures used by the RPCSEC_GSS package are shown below.

rpc_gss_service_t

This enum defines the types of security services the context may have. `rpc_gss_seccreate()` takes this as one argument when setting the service type for a session.

```
typedef enum {
    rpc_gss_svc_default = 0,
    rpc_gss_svc_none = 1,
    rpc_gss_svc_integrity = 2,
    rpc_gss_svc_privacy = 3
} rpc_gss_service_t ;
```

rpc_gss_options_req_t

Structure containing options passed directly through to the GSS-API. `rpc_gss_seccreate()` takes this as an argument when creating a context.

```
typedef struct {
    int    req_flags;           /*GSS request bits */
    int    time_req;           /*requested credential lifetime */
};
```



```

    gss_cred_id_t my_cred; /*GSS credential struct*/
    gss_channel_bindings_t;
    input_channel_bindings;
} rpc_gss_options_req_t ;

```

rpc_gss_OID

This data type is used by in-kernel RPC routines, and thus is mentioned here for informational purposes only.

```

typedef struct {
    u_int    length;
    void     *elements
} *rpc_gss_OID;

```

rpc_gss_options_ret_t

Structure containing GSS-API options returned to the calling function, `rpc_gss_seccreate()`. `MAX_GSS_MECH` is defined as 128.

```

typedef struct {
    int        major_status;
    int        minor_status;
    u_int      rpcsec_version           /*vers. of RPCSEC_GSS */
    int        ret_flags
    int        time_req
    gss_ctx_id_t gss_context;
    char       actual_mechanism[MAX_GSS_MECH]; /*mechanism used*/
} rpc_gss_options_ret_t;

```

rpc_gss_principal_t

The (mechanism-dependent, opaque) client principal type. Used as an argument to the `rpc_gss_get_principal_name()` function, and in the `gss_cred` table. Also referenced by the `rpc_gss_rawcred_t` structure for raw credentials (see below).

```

typedef struct {
    int len;
    char name[1];
} *rpc_gss_principal_t;

```

rpc_gss_rawcred_t

Structure for raw credentials. Used by `rpc_gss_getcred()` and `rpc_gss_set_callback()`.

```

typedef struct {
    u_int      version;           /*RPC version # */
    char       *mechanism;        /*security mechanism*/
    char       *qop;              /*Quality of Protection*/
    rpc_gss_principal_t client_principal; /*client name*/
    char       *svc_principal;    /*server name*/
    rpc_gss_service_t service;    /*service (integrity, etc.)*/
} rpc_gss_rawcred_t;

```

rpc_gss_ucred_t

Structure for UNIX credentials. Used by `rpc_gss_getcred()` as an alternative to `rpc_gss_rawcred_t`.

```
typedef struct {
    uid_t  uid;      /*user ID*/
    gid_t  gid;      /*group ID*/
    short  gidlen;
    git_t  *gidlist; /*list of groups*/
} rpc_gss_ucred_t;
```

rpc_gss_callback_t

Callback structure used by `rpc_gss_set_callback()`.

```
typedef struct {
    u_int  program;      /*RPC program #*/
    u_int  version;      /*RPC version #*/
    bool_t (*callback)(); /*user-defined callback routine*/
} rpc_gss_callback_t;
```

rpc_gss_lock_t

Structure used by a callback routine to enforce a particular QOP and service for a session. The `locked` field is normally set to `FALSE`; the server sets it to `TRUE` in order to lock the session. (A locked context will reject all requests having different QOP and service values than those found in the `raw_cred` structure.) For more information, see the [rpc_gss_set_callback\(3NSL\)](#) man page.

```
typedef struct {
    bool_t      locked;
    rpc_gss_rawcred_t *raw_cred;
} rpc_gss_lock_t;
```

rpc_gss_error_t

Structure used by `rpc_gss_get_error()` to fetch an error code when a `RPCSEC_GSS` routine fails.

```
typedef struct {
    int  rpc_gss_error;
    int  system_error; /*same as errno*/
} rpc_gss_error_t;
```

Index to Routines The following lists `RPCSEC_GSS` routines and the manual reference pages on which they are described. An (S) indicates it is a server-side function:

Routine (Manual Page)	Description
rpc_gss_seccreate(3NSL)	Create a secure <code>RPCSEC_GSS</code> context
rpc_gss_set_defaults(3NSL)	Switch service, QOP for a session

<code>rpc_gss_max_data_length(3NSL)</code>	Get maximum data length allowed by transport
<code>rpc_gss_set_svc_name(3NSL)</code>	Set server's principal name (S)
<code>rpc_gss_getcred(3NSL)</code>	Get credentials of caller (S)
<code>rpc_gss_set_callback(3NSL)</code>	Specify callback to see context use (S)
<code>rpc_gss_get_principal_name(3NSL)</code>	Get client principal name (S)
<code>rpc_gss_svc_max_data_length(3NSL)</code>	Get maximum data length allowed by transport (S)
<code>rpc_gss_get_error(3NSL)</code>	Get error number
<code>rpc_gss_get_mechanisms(3NSL)</code>	Get valid mechanism strings
<code>rpc_gss_get_mech_info(3NSL)</code>	Get valid QOP strings, current service
<code>rpc_gss_get_versions(3NSL)</code>	Get supported RPCSEC_GSS versions
<code>rpc_gss_is_installed(3NSL)</code>	Checks if a mechanism is installed
<code>rpc_gss_mech_to_oid(3NSL)</code>	Maps ASCII mechanism to OID representation
<code>rpc_gss_qop_to_num(3NSL)</code>	Maps ASCII QOP, mechansim to u_int number

Utilities The `gsscred` utility manages the `gsscred` table, which contains mappings of principal names between network and local credentials. See [gsscred\(1M\)](#).

Files `/etc/gss/mech` List of installed mechanisms
`/etc/gss/qop` List of valid QOPs

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe
Availability	SUNWrsg (32-bit)
	SUNWrsgx (64-bit)

See Also [gsscred\(1M\)](#), [rpc\(3NSL\)](#), [rpc_clnt_auth\(3NSL\)](#), [xdr\(3NSL\)](#), [attributes\(5\)](#), [environ\(5\)](#)

ONC+ Developer's Guide

Linn, J. *RFC 2743, Generic Security Service Application Program Interface Version 2, Update 1*. Network Working Group. January 2000.

Name `rpc_soc`, `authdes_create`, `authunix_create`, `authunix_create_default`, `callrpc`, `clnt_broadcast`, `clntraw_create`, `clnttcp_create`, `clntudp_bufcreate`, `clntudp_create`, `get_myaddress`, `getrpcport`, `pmap_getmaps`, `pmap_getport`, `pmap_rmtcall`, `pmap_set`, `pmap_unset`, `registerrpc`, `svc_fds`, `svc_getcaller`, `svc_getreq`, `svc_register`, `svc_unregister`, `svcfcd_create`, `svccraw_create`, `svctcp_create`, `svcudp_bufcreate`, `svcudp_create`, `xdr_authunix_parms` – obsolete library routines for RPC

Synopsis

```
#define PORTMAP
#include <rpc/rpc.h>

AUTH *authdes_create(char *name, uint_t window,
    struct sockaddr_in *syncaddr, des_block *ckey);

AUTH *authunix_create(char *host, uid_t uid, gid_t gid,
    int grouplen, gid_t *gidlist);

AUTH *authunix_create_default(void)

callrpc(char *host, rpcprog_t prognum, rpcvers_t versnum,
    rpcproc_t procnum, xdrproc_t inproc, char *in,
    xdrproc_t outproc, char *out);

enum clnt_stat clnt_broadcast(rpcprog_t prognum, rpcvers_t versnum,
    rpcproc_t procnum, xdrproc_t inproc, char *in,
    xdrproc_t outproc, char *out, resultproc_t result);

CLIENT *clntraw_create(rpcproc_t procnum, rpcvers_t versnum);

CLIENT *clnttcp_create(struct sockaddr_in *addr,
    rpcprog_t prognum, rpcvers_t versnum, int *fdp,
    uint_t sendz, uint_t recvsz);

CLIENT *clntudp_bufcreate(struct sockaddr_in *addr, rpcprog_t prognum,
    rpcvers_t versnum, struct timeval wait,
    int *fdp, uint_t sendz, uint_t recvsz);

CLIENT *clntudp_create(struct sockaddr_in *addr,
    rpcprog_t prognum, struct timeval wait, int *fdp);

void get_myaddress(struct sockaddr_in *addr);

ushort getrpcport(char *host, rpcprog_t prognum,
    rpcvers_t versnum, rpcprot_t proto);

struct pmaplist *pmap_getmaps(struct sockaddr_in *addr);

ushort pmap_getport(struct sockaddr_in *addr,
    rpcprog_t prognum, rpcvers_t versnum,
    rpcprot_t protocol);

enum clnt_stat pmap_rmtcall(struct sockaddr_in *addr,
    rpcprog_t prognum, rpcvers_t versnum,
    rpcproc_t procnum, caddr_t in, xdrproc_t inproc,
    caddr_t out, xdrproc_t outproc,
    struct timeval tout, rpcport_t *portp);
```

```

bool_t pmap_set(rpcprog_t prognum, rpcvers_t versnum,
               rpcprot_t protocol, u_short port);

bool_t pmap_unset(rpcprog_t prognum, rpcvers_t versnum);

int svc_fds;

struct sockaddr_in *svc_getcaller(SVCXPRT *xpirt);

void svc_getreq(int rdfs);

SVCXPRT *svcf_create(int fd, uint_t sendsz,
                    uint_t recvsz);

SVCXPRT *svccraw_create(void)

SVCXPRT *svctcp_create(int fd, uint_t sendsz,
                      uint_t recvsz);

SVCXPRT *svcudp_bufcreate(int fd, uint_t sendsz,
                          uint_t recvsz);

SVCXPRT *svcudp_create(int fd);

registerrpc(rpcprog_t prognum, rpcvers_t versnum, rpcproc_t procnum,
           char *(*procname)(), xdrproc_t inproc, xdrproc_t outproc);

bool_t svc_register(SVCXPRT *xpirt, rpcprog_t prognum, rpcvers_t versnum,
                   void (*dispatch)(), int protocol);

void svc_unregister(rpcprog_t prognum, rpcvers_t versnum);

bool_t xdr_authunix_parms(XDR *xdrs, struct authunix_parms *supp);

```

Description RPC routines allow C programs to make procedure calls on other machines across the network. First, the client calls a procedure to send a request to the server. Upon receipt of the request, the server calls a dispatch routine to perform the requested service, and then sends back a reply. Finally, the procedure call returns to the client.

The routines described in this manual page have been superseded by other routines. The preferred routine is given after the description of the routine. New programs should use the preferred routines, as support for the older interfaces may be dropped in future releases.

File Descriptors Transport independent RPC uses TLI as its transport interface instead of sockets.

Some of the routines described in this section (such as `clnttcp_create()`) take a pointer to a file descriptor as one of the parameters. If the user wants the file descriptor to be a socket, then the application will have to be linked with both `librpcsoc` and `libnsl`. If the user passed `RPC_ANYSOCK` as the file descriptor, and the application is linked with `libnsl` only, then the routine will return a TLI file descriptor and not a socket.

Routines The following routines require that the header `<rpc/rpc.h>` be included. The symbol `PORTMAP` should be defined so that the appropriate function declarations for the old interfaces are included through the header files.

`authdes_create()`

`authdes_create()` is the first of two routines which interface to the RPC secure authentication system, known as DES authentication. The second is `authdes_getcred()`, below. Note: the keyserver daemon [keyserv\(1M\)](#) must be running for the DES authentication system to work.

`authdes_create()`, used on the client side, returns an authentication handle that will enable the use of the secure authentication system. The first parameter *name* is the network name, or *netname*, of the owner of the server process. This field usually represents a hostname derived from the utility routine `host2netname()`, but could also represent a user name using `user2netname()`. See [secure_rpc\(3NSL\)](#). The second field is window on the validity of the client credential, given in seconds. A small window is more secure than a large one, but choosing too small of a window will increase the frequency of resynchronizations because of clock drift. The third parameter *syncaddr* is optional. If it is `NULL`, then the authentication system will assume that the local clock is always in sync with the server's clock, and will not attempt resynchronizations. If an address is supplied, however, then the system will use the address for consulting the remote time service whenever resynchronization is required. This parameter is usually the address of the RPC server itself. The final parameter *ckey* is also optional. If it is `NULL`, then the authentication system will generate a random DES key to be used for the encryption of credentials. If it is supplied, however, then it will be used instead.

This routine exists for backward compatibility only, and it is made obsolete by `authdes_seccreate()`. See [secure_rpc\(3NSL\)](#).

`authunix_create()`

Create and return an RPC authentication handle that contains .UX authentication information. The parameter *host* is the name of the machine on which the information was created; *uid* is the user's user ID; *gid* is the user's

current group ID; *grouplen* and *gidlistp* refer to a counted array of groups to which the user belongs.

It is not very difficult to impersonate a user.

This routine exists for backward compatibility only, and it is made obsolete by `authsys_create()`. See [rpc_clnt_auth\(3NSL\)](#).

`authunix_create_default()`

Call `authunix_create()` with the appropriate parameters.

This routine exists for backward compatibility only, and it is made obsolete by `authsys_create_default()`. See [rpc_clnt_auth\(3NSL\)](#).

`callrpc()`

Call the remote procedure associated with *prognum*, *versnum*, and *procnum* on the machine, *host*. The parameter *inproc* is used to encode the procedure's parameters, and *outproc* is used to decode the procedure's results; *in* is the address of the procedure's argument, and *out* is the address of where to place the result(s). This routine returns 0 if it succeeds, or the value of enum `clnt_stat` cast to an integer if it fails. The routine `clnt_perrno()` is handy for translating failure statuses into messages. See [rpc_clnt_calls\(3NSL\)](#).

You do not have control of timeouts or authentication using this routine. This routine exists for backward compatibility only, and is made obsolete by `rpc_call()`. See [rpc_clnt_calls\(3NSL\)](#).

`clnt_stat_clnt_broadcast()`

Like `callrpc()`, except the call message is broadcast to all locally connected broadcast nets. Each time the caller receives a response, this routine calls `eachresult()`, whose form is:

```
eachresult(char *out, struct sockaddr_in *addr);
```

where *out* is the same as *out* passed to `clnt_broadcast()`, except that the remote procedure's output is decoded there; *addr* points to the address of the machine that sent the results. If `eachresult()` returns 0, `clnt_broadcast()` waits for more replies; otherwise it returns with appropriate status. If `eachresult()` is NULL, `clnt_broadcast()` returns without waiting for any replies.

	<p>Broadcast packets are limited in size to the maximum transfer unit of the transports involved. For Ethernet, the callers argument size is approximately 1500 bytes. Since the call message is sent to all connected networks, it may potentially lead to broadcast storms. <code>clnt_broadcast()</code> uses SB AUTH_SYS credentials by default. See rpc_clnt_auth(3NSL). This routine exists for backward compatibility only, and is made obsolete by <code>rpc_broadcast()</code>. See rpc_clnt_calls(3NSL).</p>
<code>clntraw_create()</code>	<p>This routine creates an internal, memory-based RPC client for the remote program <i>prognum</i>, version <i>versnum</i>. The transport used to pass messages to the service is actually a buffer within the process's address space, so the corresponding RPC server should live in the same address space. See <code>svcrw_create()</code>. This allows simulation of RPC and acquisition of RPC overheads, such as round trip times, without any kernel interference. This routine returns NULL if it fails.</p> <p>This routine exists for backward compatibility only. It has the same functionality as <code>clnt_raw_create()</code>. See rpc_clnt_create(3NSL), which obsoletes it.</p>
<code>clnttcp_create()</code>	<p>This routine creates an RPC client for the remote program <i>prognum</i>, version <i>versnum</i>; the client uses TCP/IP as a transport. The remote program is located at Internet address <i>addr</i>. If <i>addr->sin_port</i> is 0, then it is set to the actual port that the remote program is listening on. The remote <code>rpcbind</code> service is consulted for this information. The parameter <i>*fdp</i> is a file descriptor, which may be open and bound; if it is <code>RPC_ANYSOCK</code>, then this routine opens a new one and sets <i>*fdp</i>. Refer to the File Descriptor section for more information. Since TCP-based RPC uses buffered I/O, the user may specify the size of the send and receive buffers with the parameters <i>sendsz</i> and <i>recvsz</i>. Values of 0 choose suitable defaults. This routine returns NULL if it fails.</p> <p>This routine exists for backward compatibility only. <code>clnt_create()</code>, <code>clnt_tli_create()</code>, or <code>clnt_vc_create()</code> should be used instead. See rpc_clnt_create(3NSL).</p>

`clntudp_bufcreate()`

Create a client handle for the remote program *prognum*, on *versnum*; the client uses UDP/IP as the transport. The remote program is located at the Internet address *addr*. If *addr->sin_port* is 0, it is set to port on which the remote program is listening on (the remote `rpcbind` service is consulted for this information). The parameter **fdp* is a file descriptor, which may be open and bound. If it is `RPC_ANYSOCK`, then this routine opens a new one and sets **fdp*. Refer to the File Descriptor section for more information. The UDP transport resends the call message in intervals of `wait` time until a response is received or until the call times out. The total time for the call to time out is specified by `clnt_call()`. See [rpc_clnt_calls\(3NSL\)](#). If successful it returns a client handle, otherwise it returns NULL. The error can be printed using the `clnt_pcreateerror()` routine. See [rpc_clnt_create\(3NSL\)](#).

The user can specify the maximum packet size for sending and receiving by using *sendsz* and *recvsz* arguments for UDP-based RPC messages.

If *addr->sin_port* is 0 and the requested version number *versnum* is not registered with the remote portmap service, it returns a handle if at least a version number for the given program number is registered. The version mismatch is discovered by a `clnt_call()` later (see [rpc_clnt_calls\(3NSL\)](#)).

This routine exists for backward compatibility only. `clnt_tli_create()` or `clnt_dg_create()` should be used instead. See [rpc_clnt_create\(3NSL\)](#).

`clntudp_create()`

This routine creates an RPC client handle for the remote program *prognum*, version *versnum*; the client uses UDP/IP as a transport. The remote program is located at Internet address *addr*. If *addr->sin_port* is 0, then it is set to actual port that the remote program is listening on. The remote `rpcbind` service is consulted for this information. The parameter **fdp* is a file descriptor, which may be open and bound; if it is `RPC_ANYSOCK`, then this routine opens a new one and sets **fdp*. Refer to the File Descriptor section for more information. The UDP transport resends the call message in intervals of `wait` time until a response is received or until the call times out. The total time for

the call to time out is specified by `clnt_call()`. See [rpc_clnt_calls\(3NSL\)](#). `clntudp_create()` returns a client handle on success, otherwise it returns NULL. The error can be printed using the `clnt_pcreateerror()` routine. See [rpc_clnt_create\(3NSL\)](#).

Since UDP-based RPC messages can only hold up to 8 Kbytes of encoded data, this transport cannot be used for procedures that take large arguments or return huge results.

This routine exists for backward compatibility only. `clnt_create()`, `clnt_tli_create()`, or `clnt_dg_create()` should be used instead. See [rpc_clnt_create\(3NSL\)](#).

`get_myaddress()`

Places the local system's IP address into **addr*, without consulting the library routines that deal with `/etc/hosts`. The port number is always set to `htons(PMAPPORT)`.

This routine is only intended for use with the RPC library. It returns the local system's address in a form compatible with the RPC library, and should not be taken as the system's actual IP address. In fact, the **addr* buffer's host address part is actually zeroed. This address may have only local significance and should not be assumed to be an address that can be used to connect to the local system by remote systems or processes.

This routine remains for backward compatibility only. The routine `netdir_getbyname()` should be used with the name `HOST_SELF` to retrieve the local system's network address as a *netbuf* structure. See [netdir\(3NSL\)](#).

`getrpcport()`

`getrpcport()` returns the port number for the version *versnum* of the RPC program *prognum* running on *host* and using protocol *proto*. `getrpcport()` returns 0 if the RPC system failed to contact the remote portmap service, the program associated with *prognum* is not registered, or there is no mapping between the program and a port.

This routine exists for backward compatibility only. Enhanced functionality is provided by `rpcb_getaddr()`. See [rpcbind\(3NSL\)](#).

<code>pmaplist()</code>	<p>A user interface to the portmap service, which returns a list of the current RPC program-to-port mappings on the host located at IP address <i>addr</i>. This routine can return <code>NULL</code>. The command <code>'rpcinfo -p'</code> uses this routine.</p> <p>This routine exists for backward compatibility only, enhanced functionality is provided by <code>rpcb_getmaps()</code>. See rpcbind(3NSL).</p>
<code>pmap_getport()</code>	<p>A user interface to the portmap service, which returns the port number on which waits a service that supports program <i>prognum</i>, version <i>versnum</i>, and speaks the transport protocol associated with <i>protocol</i>. The value of <i>protocol</i> is most likely <code>IPPROTO_UDP</code> or <code>IPPROTO_TCP</code>. A return value of <code>0</code> means that the mapping does not exist or that the RPC system failed to contact the remote portmap service. In the latter case, the global variable <code>rpc_createerr</code> contains the RPC status.</p> <p>This routine exists for backward compatibility only, enhanced functionality is provided by <code>rpcb_getaddr()</code>. See rpcbind(3NSL).</p>
<code>pmap_rmtcall()</code>	<p>Request that the portmap on the host at IP address <i>*addr</i> make an RPC on the behalf of the caller to a procedure on that host. <i>*portp</i> is modified to the program's port number if the procedure succeeds. The definitions of other parameters are discussed in <code>callrpc()</code> and <code>clnt_call()</code>. See rpc_clnt_calls(3NSL).</p> <p>This procedure is only available for the UDP transport.</p> <p>If the requested remote procedure is not registered with the remote portmap then no error response is returned and the call times out. Also, no authentication is done.</p> <p>This routine exists for backward compatibility only, enhanced functionality is provided by <code>rpcb_rmtcall()</code>. See rpcbind(3NSL).</p>
<code>pmap_set()</code>	<p>A user interface to the portmap service, that establishes a mapping between the triple [<i>prognum</i>, <i>versnum</i>, <i>protocol</i>] and <i>port</i> on the machine's portmap service. The value of <i>protocol</i> may be <code>IPPROTO_UDP</code> or <code>IPPROTO_TCP</code>. Formerly, the routine failed if the requested <i>port</i> was found to be in use. Now, the routine only fails if it finds that <i>port</i> is still</p>

bound. If *port* is not bound, the routine completes the requested registration. This routine returns 1 if it succeeds, 0 otherwise. Automatically done by `svc_register()`.

This routine exists for backward compatibility only, enhanced functionality is provided by `rpcb_set()`. See [rpcbind\(3NSL\)](#).

`pmap_unset()`

A user interface to the portmap service, which destroys all mapping between the triple [*prognum*, *versnum*, *all-protocols*] and *port* on the machine's portmap service. This routine returns one if it succeeds, 0 otherwise.

This routine exists for backward compatibility only, enhanced functionality is provided by `rpcb_unset()`. See [rpcbind\(3NSL\)](#).

`svc_fds()`

A global variable reflecting the RPC service side's read file descriptor bit mask; it is suitable as a parameter to the `select()` call. This is only of interest if a service implementor does not call `svc_run()`, but rather does his own asynchronous event processing. This variable is read-only, yet it may change after calls to `svc_getreq()` or any creation routines. Do not pass its address to `select()`! Similar to `svc_fdset`, but limited to 32 descriptors.

This interface is made obsolete by `svc_fdset`. See [rpc_svc_calls\(3NSL\)](#).

`svc_getcaller()`

This routine returns the network address, represented as a `struct sockaddr_in`, of the caller of a procedure associated with the RPC service transport handle, *xprt*.

This routine exists for backward compatibility only, and is obsolete. The preferred interface is `svc_getrpccaller()`. See [rpc_svc_reg\(3NSL\)](#), which returns the address as a `struct netbuf`.

`svc_getreq()`

This routine is only of interest if a service implementor does not call `svc_run()`, but instead implements custom asynchronous event processing. It is called when the `select()` call has determined that an RPC request has arrived on some RPC file descriptors; *rdfds* is the resultant read file descriptor bit mask. The routine returns when all

file descriptors associated with the value of *rdfds* have been serviced. This routine is similar to `svc_getreqset()` but is limited to 32 descriptors.

This interface is made obsolete by `svc_getreqset()`

`svcfld_create()`

Create a service on top of any open and bound descriptor. Typically, this descriptor is a connected file descriptor for a stream protocol. Refer to the File Descriptor section for more information. *sendsz* and *rcvysz* indicate sizes for the send and receive buffers. If they are 0, a reasonable default is chosen.

This interface is made obsolete by `svc_fd_create()` (see [rpc_svc_create\(3NSL\)](#)).

`svccraw_create()`

This routine creates an internal, memory-based RPC service transport, to which it returns a pointer. The transport is really a buffer within the process's address space, so the corresponding RPC client should live in the same address space; see `clntcrw_create()`. This routine allows simulation of RPC and acquisition of RPC overheads (such as round trip times), without any kernel interference. This routine returns NULL if it fails.

This routine exists for backward compatibility only, and has the same functionality of `svc_raw_create()`. See [rpc_svc_create\(3NSL\)](#), which obsoletes it.

`svctcp_create()`

This routine creates a TCP/IP-based RPC service transport, to which it returns a pointer. The transport is associated with the file descriptor *fd*, which may be `RPC_ANYSOCK`, in which case a new file descriptor is created. If the file descriptor is not bound to a local TCP port, then this routine binds it to an arbitrary port. Refer to the File Descriptor section for more information. Upon completion, *xprt->xp_fd* is the transport's file descriptor, and *xprt->xp_port* is the transport's port number. This routine returns NULL if it fails. Since TCP-based RPC uses buffered I/O, users may specify the size of buffers; values of 0 choose suitable defaults.

This routine exists for backward compatibility only. `svc_create()`, `svc_tli_create()`, or `svc_vc_create()` should be used instead. See [rpc_svc_create\(3NSL\)](#).

`svcudp_bufcreate()`

This routine creates a UDP/IP-based RPC service transport, to which it returns a pointer. The transport is associated with the file descriptor *fd*. If *fd* is `RPC_ANYSOCK` then a new file descriptor is created. If the file descriptor is not bound to a local UDP port, then this routine binds it to an arbitrary port. Upon completion, *xprt->xp_fd* is the transport's file descriptor, and *xprt->xp_port* is the transport's port number. Refer to the File Descriptor section for more information. This routine returns `NULL` if it fails.

The user specifies the maximum packet size for sending and receiving UDP-based RPC messages by using the *sendsz* and *recvsz* parameters.

This routine exists for backward compatibility only. `svc_tli_create()`, or `svc_dg_create()` should be used instead. See [rpc_svc_create\(3NSL\)](#).

`svcudp_create()`

This routine creates a UDP/IP-based RPC service transport, to which it returns a pointer. The transport is associated with the file descriptor *fd*, which may be `RPC_ANYSOCK`, in which case a new file descriptor is created. If the file descriptor is not bound to a local UDP port, then this routine binds it to an arbitrary port. Upon completion, *xprt->xp_fd* is the transport's file descriptor, and *xprt->xp_port* is the transport's port number. This routine returns `NULL` if it fails.

Since UDP-based RPC messages can only hold up to 8 Kbytes of encoded data, this transport cannot be used for procedures that take large arguments or return huge results.

This routine exists for backward compatibility only. `svc_create()`, `svc_tli_create()`, or `svc_dg_create()` should be used instead. See [rpc_svc_create\(3NSL\)](#).

`registerrpc()`

Register program *prognum*, procedure *procname*, and version *versnum* with the RPC service package. If a request arrives for program *prognum*, version *versnum*, and procedure *procnum*, *procname* is called with a pointer to its parameter(s). *procname* should return a pointer to its static result(s). *inproc* is used to decode the parameters

while *outproc* is used to encode the results. This routine returns 0 if the registration succeeded, -1 otherwise.

`svc_run()` must be called after all the services are registered.

This routine exists for backward compatibility only, and it is made obsolete by `rpc_reg()`.

svc_register()

Associates *prognum* and *versnum* with the service dispatch procedure, *dispatch*. If *protocol* is 0, the service is not registered with the portmap service. If *protocol* is non-zero, then a mapping of the triple [*prognum*, *versnum*, *protocol*] to *xprt*->*xp_port* is established with the local portmap service (generally *protocol* is 0, IPPROTO_UDP or IPPROTO_TCP). The procedure *dispatch* has the following form:

```
dispatch(struct svc_req *request, SVCXPRT *xprt);
```

The `svc_register()` routine returns one if it succeeds, and 0 otherwise.

This routine exists for backward compatibility only. Enhanced functionality is provided by `svc_reg()`.

svc_unregister()

Remove all mapping of the double [*prognum*, *versnum*] to dispatch routines, and of the triple [*prognum*, *versnum*, *all-protocols*] to port number from portmap.

This routine exists for backward compatibility. Enhanced functionality is provided by `svc_unreg()`.

xdr_authunix_parms()

Used for describing UNIX credentials. This routine is useful for users who wish to generate these credentials without using the RPC authentication package.

This routine exists for backward compatibility only, and is made obsolete by `xdr_authsys_parms()`. See [rpc_xdr\(3NSL\)](#).

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTETYPE	ATTRIBUTE VALUE
MT-Level	Unsafe

See Also [keyserv\(1M\)](#), [rpcbind\(1M\)](#), [rpcinfo\(1M\)](#), [netdir\(3NSL\)](#), [netdir_getbyname\(3NSL\)](#), [rpc\(3NSL\)](#), [rpc_clnt_auth\(3NSL\)](#), [rpc_clnt_calls\(3NSL\)](#), [rpc_clnt_create\(3NSL\)](#), [rpc_svc_calls\(3NSL\)](#), [rpc_svc_create\(3NSL\)](#), [rpc_svc_err\(3NSL\)](#), [rpc_svc_reg\(3NSL\)](#), [rpc_xdr\(3NSL\)](#), [rpcbind\(3NSL\)](#), [secure_rpc\(3NSL\)](#), [select\(3C\)](#), [xdr_authsys_parms\(3NSL\)](#), [libnsl\(3LIB\)](#), [librpcsoc\(3LIBUCB\)](#), [attributes\(5\)](#)

Notes These interfaces are unsafe in multithreaded applications. Unsafe interfaces should be called only from the main thread.

Name `rpc_svc_calls`, `svc_dg_enablecache`, `svc_done`, `svc_exit`, `svc_fdset`, `svc_freeargs`, `svc_getargs`, `svc_getreq_common`, `svc_getreq_poll`, `svc_getreqset`, `svc_getrpcaller`, `svc_max_pollfd`, `svc_pollfd`, `svc_run`, `svc_sendreply`, `svc_getcallerucred`, `svc_fd_negotiate_ucred` – library routines for RPC servers

Synopsis `cc [flag...] file... -lnsl [library...]`
`#include <rpc/rpc.h>`

```
int svc_dg_enablecache(SVCXPRT *xpirt, const uint_t cache_size);

int svc_done(SVCXPRT *xpirt);

void svc_exit(void);

void svc_fd_negotiate_ucred(int fd);

bool_t svc_freeargs(const SVCXPRT *xpirt, const txdrproc_t inproc,
                    caddr_t in);

bool_t svc_getargs(const SVCXPRT *xpirt, const xdrproc_t inproc,
                   caddr_t in);

int svc_getcallerucred(const SVCXPRT *xpirt, ucred_t **ucred);

void svc_getreq_common(const int fd);

void svc_getreqset(fd_set *rdfs);

void svc_getreq_poll(struct pollfd *pfdp, const int pollretval);

struct netbuf *svc_getrpcaller(const SVCXPRT *xpirt);

void svc_run(void);

bool_t svc_sendreply(const SVCXPRT *xpirt, const xdrproc_t outproc,
                    caddr_t outint svc_max_pollfd;
fd_set svc_fdset;
pollfd_t *svc_pollfd;
```

Description These routines are part of the RPC library which allows C language programs to make procedure calls on other machines across the network.

These routines are associated with the server side of the RPC mechanism. Some of them are called by the server side dispatch function. Others, such as `svc_run()`, are called when the server is initiated.

Because the service transport handle `SVCXPRT` contains a single data area for decoding arguments and encoding results, the structure cannot freely be shared between threads that call functions to decode arguments and encode results. When a server is operating in the Automatic or User MT modes, however, a copy of this structure is passed to the service dispatch procedure in order to enable concurrent request processing. Under these circumstances, some routines which would otherwise be Unsafe, become Safe. These are

marked as such. Also marked are routines that are Unsafe for multithreaded applications, and are not to be used by such applications. See [rpc\(3NSL\)](#) for the definition of the SVCXPRT data structure.

The `svc_dg_enablecache()` function allocates a duplicate request cache for the service endpoint *xprt*, large enough to hold *cache_size* entries. Once enabled, there is no way to disable caching. The function returns 1 if space necessary for a cache of the given size was successfully allocated, and 0 otherwise. This function is Safe in multithreaded applications.

The `svc_done()` function frees resources allocated to service a client request directed to the service endpoint *xprt*. This call pertains only to servers executing in the User MT mode. In the User MT mode, service procedures must invoke this call before returning, either after a client request has been serviced, or after an error or abnormal condition that prevents a reply from being sent. After `svc_done()` is invoked, the service endpoint *xprt* should not be referenced by the service procedure. Server multithreading modes and parameters can be set using the `rpc_control()` call. This function is Safe in multithreaded applications. It will have no effect if invoked in modes other than the User MT mode.

The `svc_exit()` function when called by any of the RPC server procedures or otherwise, destroys all services registered by the server and causes `svc_run()` to return. If RPC server activity is to be resumed, services must be reregistered with the RPC library either through one of the [rpc_svc_create\(3NSL\)](#) functions, or using [xprt_register\(3NSL\)](#). The `svc_exit()` function has global scope and ends all RPC server activity.

The `svc_freeargs()` function macro frees any data allocated by the RPC/XDR system when it decoded the arguments to a service procedure using `svc_getargs()`. This routine returns TRUE if the results were successfully freed, and FALSE otherwise. This function macro is Safe in multithreaded applications utilizing the Automatic or User MT modes.

The `svc_getargs()` function macro decodes the arguments of an RPC request associated with the RPC service transport handle *xprt*. The parameter *in* is the address where the arguments will be placed; *inproc* is the XDR routine used to decode the arguments. This routine returns TRUE if decoding succeeds, and FALSE otherwise. This function macro is Safe in multithreaded applications utilizing the Automatic or User MT modes.

The `svc_getreq_common()` function is called to handle a request on a file descriptor.

The `svc_getreq_poll()` function is only of interest if a service implementor does not call `svc_run()`, but instead implements custom asynchronous event processing. It is called when [poll\(2\)](#) has determined that an RPC request has arrived on some RPC file descriptors; *pollretval* is the return value from [poll\(2\)](#) and *pfdp* is the array of *pollfd* structures on which the [poll\(2\)](#) was done. It is assumed to be an array large enough to contain the maximal number of descriptors allowed. The `svc_getreq_poll()` function macro is Unsafe in multithreaded applications.

The `svc_getreqset()` function is only of interest if a service implementor does not call `svc_run()`, but instead implements custom asynchronous event processing. It is called when

`select(3C)` has determined that an RPC request has arrived on some RPC file descriptors; `rdfds` is the resultant read file descriptor bit mask. The routine returns when all file descriptors associated with the value of `rdfds` have been serviced. This function macro is Unsafe in multithreaded applications.

The `svc_getrpccaller()` function is the approved way of getting the network address of the caller of a procedure associated with the RPC service transport handle `xprt`. This function macro is Safe in multithreaded applications.

The `svc_run()` function never returns. In single-threaded mode, the function waits for RPC requests to arrive. When an RPC request arrives, the `svc_run()` function calls the appropriate service procedure. This procedure is usually waiting for the `poll(2)` library call to return.

Applications that execute in the Automatic or the User MT mode should invoke the `svc_run()` function exactly once. In the Automatic MT mode, the `svc_run()` function creates threads to service client requests. In the User MT mode, the function provides a framework for service developers to create and manage their own threads for servicing client requests.

The `svc_fdset` global variable reflects the RPC server's read file descriptor bit mask. This is only of interest if service implementors do not call `svc_run()`, but rather do their own asynchronous event processing. This variable is read-only may change after calls to `svc_getreqset()` or after any creation routine. Do not pass its address to `select(3C)`. Instead, pass the address of a copy. multithreaded applications executing in either the Automatic MT mode or the user MT mode should never read this variable. They should use auxiliary threads to do asynchronous event processing. The `svc_fdset` variable is limited to 1024 file descriptors and is considered obsolete. Use of `svc_pollfd` is recommended instead.

The `svc_pollfd` global variable points to an array of `pollfd_t` structures that reflect the RPC server's read file descriptor array. This is only of interest if service implementors do not call `svc_run()` but rather do their own asynchronous event processing. This variable is read-only, and it may change after calls to `svc_getreg_poll()` or any creation routines. Do not pass its address to `poll(2)`. Instead, pass the address of a copy. By default, `svc_pollfd` is limited to 1024 entries. Use `rpc_control(3NSL)` to remove this limitation. multithreaded applications executing in either the Automatic MT mode or the user MT mode should never be read this variable. They should use auxiliary threads to do asynchronous event processing.

The `svc_max_pollfd` global variable contains the maximum length of the `svc_pollfd` array. This variable is read-only, and it may change after calls to `svc_getreg_poll()` or any creation routines.

The `svc_sendreply()` function is called by an RPC service dispatch routine to send the results of a remote procedure call. The `xprt` parameter is the transport handle of the request. The `outproc` parameter is the XDR routine used to encode the results. The `out` parameter is the address of the results. This routine returns TRUE if it succeeds, FALSE otherwise. The `svc_sendreply()` function macro is Safe in multithreaded applications that use the Automatic or the User MT mode.

The `svc_fd_negotiate_ucred()` function is called by an RPC server to inform the underlying transport that the function wishes to receive `ucreds` for local calls, including those over IP transports.

The `svc_getcallerucred()` function attempts to retrieve the `ucred_t` associated with the caller. The function returns 0 when successful and -1 when not.

When successful, the `svc_getcallerucred()` function stores the pointer to a freshly allocated `ucred_t` in the memory location pointed to by the `ucred` argument if that memory location contains the null pointer. If the memory location is non-null, the function reuses the existing `ucred_t`. When `ucred` is no longer needed, a credential allocated by `svc_getcallerucred()` should be freed with `ucred_free(3C)`.

Attributes See [attributes\(5\)](#) for descriptions of attribute types and values.

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	See below.

The `svc_fd_negotiate_ucred()`, `svc_dg_enablecache()`, `svc_getrpccaller()`, and `svc_getcallerucred()` functions are Safe in multithreaded applications. The `svc_freeargs()`, `svc_getargs()`, and `svc_sendreply()` functions are Safe in multithreaded applications that use the Automatic or the User MT mode. The `svc_getreq_common()`, `svc_getreqset()`, and `svc_getreq_poll()` functions are Unsafe in multithreaded applications and should be called only from the main thread.

See Also [rpcgen\(1\)](#), [poll\(2\)](#), [getpeerucred\(3C\)](#), [rpc\(3NSL\)](#), [rpc_control\(3NSL\)](#), [rpc_svc_create\(3NSL\)](#), [rpc_svc_err\(3NSL\)](#), [rpc_svc_reg\(3NSL\)](#), [select\(3C\)](#), [ucred_free\(3C\)](#), [xpirt_register\(3NSL\)](#), [attributes\(5\)](#)

Name `rpc_svc_create`, `svc_control`, `svc_create`, `svc_destroy`, `svc_dg_create`, `svc_fd_create`, `svc_raw_create`, `svc_tli_create`, `svc_tp_create`, `svc_vc_create`, `svc_door_create` – library routines for the creation of server handles

Synopsis `#include <rpc/rpc.h>`

```
bool_t svc_control(SVCXPRT *svc, const uint_t req, void *info);

int svc_create(const void (*dispatch) const struct svc_req *,
               const SVCXPRT *), const rpcprog_t prognum, const rpcvers_t versnum,
               const char *nettype);

void svc_destroy(SVCXPRT *xpirt);

SVCXPRT *svc_dg_create(const int fildes, const uint_t sendsz,
                      const uint_t recvsz);

SVCXPRT *svc_fd_create(const int fildes, const uint_t sendsz,
                      const uint_t recvsz);

SVCXPRT *svc_raw_create(void)

SVCXPRT *svc_tli_create(const int fildes,
                       const struct netconfig *netconf, const struct t_bind *bind_addr,
                       const uint_t sendsz, const uint_t recvsz);

SVCXPRT *svc_tp_create(const void (*dispatch) const struct svc_req *,
                      const SVCXPRT *), const rpcprog_t prognum, const rpcvers_t versnum,
                      const struct netconfig *netconf);

SVCXPRT *svc_vc_create(const int fildes, const uint_t sendsz,
                      const uint_t recvsz);

SVCXPRT *svc_door_create(void (*dispatch)(struct svc_req *,
SVCXPRT *), const rpcprog_t prognum, const rpcvers_t versnum,
const uint_t sendsz);
```

Description These routines are part of the RPC library which allows C language programs to make procedure calls on servers across the network. These routines deal with the creation of service handles. Once the handle is created, the server can be invoked by calling `svc_run()`.

Routines See [rpc\(3NSL\)](#) for the definition of the SVCXPRT data structure.

`svc_control()`

A function to change or retrieve information about a service object. *req* indicates the type of operation and *info* is a pointer to the information. The supported values of *req*, their argument types, and what they do are:

`SVCGET_VERSQUIET`

If a request is received for a program number served by this server but the version number is outside the range

registered with the server, an `RPC_PROGVERSMISMATCH` error will normally be returned. *info* should be a pointer to an integer. Upon successful completion of the `SVCGET_VERSQUIET` request, **info* contains an integer which describes the server's current behavior: `0` indicates normal server behavior, that is, an `RPC_PROGVERSMISMATCH` error will be returned. `1` indicates that the out of range request will be silently ignored.

`SVCSET_VERSQUIET`

If a request is received for a program number served by this server but the version number is outside the range registered with the server, an `RPC_PROGVERSMISMATCH` error will normally be returned. It is sometimes desirable to change this behavior. *info* should be a pointer to an integer which is either `0`, indicating normal server behavior and an `RPC_PROGVERSMISMATCH` error will be returned, or `1`, indicating that the out of range request should be silently ignored.

`SVCGET_XID`

Returns the transaction ID of connection-oriented and connectionless transport service calls. The transaction ID assists in uniquely identifying client requests for a given RPC version, program number, procedure, and client. The transaction ID is extracted from the service transport handle *svc*. *info* must be a pointer to an unsigned long. Upon successful completion of the `SVCGET_XID` request, **info* contains the transaction ID. Note that rendezvous and raw service handles do not define a transaction ID. Thus, if the service handle is of rendezvous or raw type, and the request is of type `SVCGET_XID`, `svc_control()` will return `FALSE`. Note also that the transaction ID read by the server can be set by the client through the suboption `CLSET_XID` in `clnt_control()`. See [clnt_create\(3NSL\)](#)

`SVCSET_RECVERRHANDLER`

Attaches or detaches a disconnection handler to the service handle, *svc*, that will be called when a transport error arrives during the reception of a request or when the server is waiting for a request and the connection shuts down. This handler is only useful for a connection oriented service handle.

**info* contains the address of the error handler to attach, or NULL to detach a previously defined one. The error handler has two arguments. It has a pointer to the erroneous service handle. It also has an integer that indicates if the full service is closed (when equal to zero), or that only one connection on this service is closed (when not equal to zero).

```
void handler (const SVCXPRT *svc, const bool_t isAConnection);
```

With the service handle address, *svc*, the error handler is able to detect which connection has failed and to begin an error recovery process. The error handler can be called by multiple threads and should be implemented in an MT-safe way.

SVCGET_RECVERRHANDLER

Upon successful completion of the SVCGET_RECVERRHANDLER request, **info* contains the address of the handler for receiving errors. Upon failure, **info* contains NULL.

This routine returns TRUE if the operation was successful. Otherwise, it returns false.

```
svc_create()
```

svc_create() creates server handles for all the transports belonging to the class *nettype*.

nettype defines a class of transports which can be used for a particular application. The transports are tried in left to right order in NETPATH variable or in top to bottom order in the netconfig database. If *nettype* is NULL, it defaults to *netpath*.

svc_create() registers itself with the *rpcbind* service (see [rpcbind\(1M\)](#)). *dispatch* is called when there is a remote procedure call for the given *prognum* and *versnum*; this requires calling *svc_run()* (see *svc_run()* in [rpc_svc_reg\(3NSL\)](#)). If *svc_create()* succeeds, it returns the number of server handles it created, otherwise it returns 0 and an error message is logged.

```
svc_destroy()
```

A function macro that destroys the RPC service handle *xprt*. Destruction usually involves deallocation of private data structures, including *xprt* itself. Use of *xprt* is undefined after calling this routine.

```
svc_dg_create()
```

This routine creates a connectionless RPC service handle, and returns a pointer to it. This routine returns NULL if it

fails, and an error message is logged. *sendsz* and *recvsz* are parameters used to specify the size of the buffers. If they are 0, suitable defaults are chosen. The file descriptor *fildes* should be open and bound. The server is not registered with [rpcbind\(1M\)](#).

Warning: since connectionless-based RPC messages can only hold limited amount of encoded data, this transport cannot be used for procedures that take large arguments or return huge results.

`svc_fd_create()`

This routine creates a service on top of an open and bound file descriptor, and returns the handle to it. Typically, this descriptor is a connected file descriptor for a connection-oriented transport. *sendsz* and *recvsz* indicate sizes for the send and receive buffers. If they are 0, reasonable defaults are chosen. This routine returns NULL if it fails, and an error message is logged.

`svc_raw_create()`

This routine creates an RPC service handle and returns a pointer to it. The transport is really a buffer within the process's address space, so the corresponding RPC client should live in the same address space; (see `clnt_raw_create()` in [rpc_clnt_create\(3NSL\)](#)). This routine allows simulation of RPC and acquisition of RPC overheads (such as round trip times), without any kernel and networking interference. This routine returns NULL if it fails, and an error message is logged.

Note: `svc_run()` should not be called when the raw interface is being used.

`svc_tli_create()`

This routine creates an RPC server handle, and returns a pointer to it. *fildes* is the file descriptor on which the service is listening. If *fildes* is `RPC_ANYFD`, it opens a file descriptor on the transport specified by *netconf*. If the file descriptor is unbound and *bindaddr* is non-null *fildes* is bound to the address specified by *bindaddr*, otherwise *fildes* is bound to a default address chosen by the transport. In the case where the default address is chosen, the number of outstanding connect requests is set to 8 for connection-oriented transports. The user may specify the size of the send and receive buffers with the parameters *sendsz* and *recvsz*; values of 0 choose suitable defaults. This routine returns NULL if it

	fails, and an error message is logged. The server is not registered with the rpcbind(1M) service.
<code>svc_tp_create()</code>	<code>svc_tp_create()</code> creates a server handle for the network specified by <i>netconf</i> , and registers itself with the <i>rpcbind</i> service. <i>dispatch</i> is called when there is a remote procedure call for the given <i>prognum</i> and <i>versnum</i> ; this requires calling <code>svc_run()</code> . <code>svc_tp_create()</code> returns the service handle if it succeeds, otherwise a NULL is returned and an error message is logged.
<code>svc_vc_create()</code>	This routine creates a connection-oriented RPC service and returns a pointer to it. This routine returns NULL if it fails, and an error message is logged. The users may specify the size of the send and receive buffers with the parameters <i>sendsz</i> and <i>recvsz</i> ; values of 0 choose suitable defaults. The file descriptor <i>fildev</i> should be open and bound. The server is not registered with the rpcbind(1M) service.
<code>svc_door_create()</code>	This routine creates an RPC server handle over doors and returns a pointer to it. Doors is a transport mechanism that facilitates fast data transfer between processes on the same machine. for the given program The user may set the size of the send buffer with the parameter <i>sendsz</i> . If <i>sendsz</i> is 0, the corresponding default buffer size is 16 Kbyte. If successful, the <code>svc_door_create()</code> routine returns the service handle. Otherwise it returns NULL and sets a value for <code>rpc_createerr</code> . The server is not registered with rpcbind(1M) .

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Architecture	All
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [rpcbind\(1M\)](#), [rpc\(3NSL\)](#), [rpc_clnt_create\(3NSL\)](#), [rpc_svc_calls\(3NSL\)](#), [rpc_svc_err\(3NSL\)](#), [rpc_svc_reg\(3NSL\)](#), [attributes\(5\)](#)

Name `rpc_svc_err`, `svcerr_auth`, `svcerr_decode`, `svcerr_noproc`, `svcerr_noprog`, `svcerr_progvers`, `svcerr_systemerr`, `svcerr_weakauth` – library routines for server side remote procedure call errors

Description These routines are part of the RPC library which allows C language programs to make procedure calls on other machines across the network.

These routines can be called by the server side dispatch function if there is any error in the transaction with the client.

Routines See [rpc\(3NSL\)](#) for the definition of the SVCXPRT data structure.

```
#include <rpc/rpc.h>
```

```
void svcerr_auth(const SVCXPRT *xprt, const enum auth_stat why);
```

Called by a service dispatch routine that refuses to perform a remote procedure call due to an authentication error.

```
void svcerr_decode(const SVCXPRT *xprt);
```

Called by a service dispatch routine that cannot successfully decode the remote parameters (see `svc_getargs()` in [rpc_svc_reg\(3NSL\)](#)).

```
void svcerr_noproc(const SVCXPRT *xprt);
```

Called by a service dispatch routine that does not implement the procedure number that the caller requests.

```
void svcerr_noprog(const SVCXPRT *xprt);
```

Called when the desired program is not registered with the RPC package. Service implementors usually do not need this routine.

```
void svcerr_progvers(const SVCXPRT *xprt, const rpcvers_t low_vers, const rpcvers_t high_vers);
```

Called when the desired version of a program is not registered with the RPC package. *low_vers* is the lowest version number, and *high_vers* is the highest version number. Service implementors usually do not need this routine.

```
void svcerr_systemerr(const SVCXPRT *xprt);
```

Called by a service dispatch routine when it detects a system error not covered by any particular protocol. For example, if a service can no longer allocate storage, it may call this routine.

```
void svcerr_weakauth(const SVCXPRT *xprt);
```

Called by a service dispatch routine that refuses to perform a remote procedure call due to insufficient (but correct) authentication parameters. The routine calls `svcerr_auth(xprt, AUTH_TOOWEAK)`.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [rpc\(3NSL\)](#), [rpc_svc_calls\(3NSL\)](#), [rpc_svc_create\(3NSL\)](#), [rpc_svc_reg\(3NSL\)](#), [attributes\(5\)](#)

Name `rpc_svc_input`, `svc_add_input`, `svc_remove_input` – declare or remove a callback on a file descriptor

Synopsis `#include <rpc/rpc.h>`

```
typedef void (*svc_callback_t)(svc_input_id_t id, int fd,
    unsigned int events, void *cookie);

svc_input_id_t svc_add_input(int fd, unsigned int revents,
    svc_callback_t callback, void *cookie);

int svc_remove_input(svc_input_t id);
```

Description The following RPC routines are used to declare or remove a callback on a file descriptor.

Routines See [rpc\(3NSL\)](#) for the definition of the SVCXPRT data structure.

`svc_add_input()` This function is used to register a *callback* function on a file descriptor, *fd*. The file descriptor, *fd*, is the first parameter to be passed to `svc_add_input()`. This *callback* function will be automatically called if any of the events specified in the *events* parameter occur on this descriptor. The *events* parameter is used to specify when the callback is invoked. This parameter is a mask of poll events to which the user wants to listen. See [poll\(2\)](#) for further details of the events that can be specified.

The callback to be invoked is specified using the *callback* parameter. The *cookie* parameter can be used to pass any data to the *callback* function. This parameter is a user-defined value which is passed as an argument to the *callback* function, and it is not used by the Sun RPC library itself.

Several callbacks can be registered on the same file descriptor as long as each callback registration specifies a separate set of event flags.

The *callback* function is called with the registration *id*, the *fd* file descriptor, an *revents* value, which is a bitmask of all events concerning the file descriptor, and the *cookie* user-defined value.

Upon successful completion, the function returns a unique identifier for this registration, that can be used later to remove this callback. Upon failure, -1 is returned and `errno` is set to indicate the error.

The `svc_add_input()` function will fail if:

EINVAL The *fd* or *events* parameters are invalid.

EEXIST A callback is already registered to the file descriptor with one of the specified events.

ENOMEM Memory is exhausted.

svc_remove_input () This function is used to unregister a callback function on a file descriptor, *fd*. The *id* parameter specifies the registration to be removed.

Upon successful completion, the function returns zero. Upon failure, - 1 is returned and *errno* is set to indicate the error.

The `svc_remove_input ()` function will fail if:

EINVAL The *id* parameter is invalid.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Architecture	All
Availability	SUNWcsl (32-bit)
	SUNWcslx (64-bit)
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [poll\(2\)](#), [rpc\(3NSL\)](#), [attributes\(5\)](#)

Name `rpc_svc_reg`, `rpc_reg`, `svc_reg`, `svc_unreg`, `svc_auth_reg`, `xprt_register`, `xprt_unregister` – library routines for registering servers

Description These routines are a part of the RPC library which allows the RPC servers to register themselves with `rpcbind()` (see [rpcbind\(1M\)](#)), and associate the given program and version number with the dispatch function. When the RPC server receives a RPC request, the library invokes the dispatch routine with the appropriate arguments.

Routines See [rpc\(3NSL\)](#) for the definition of the SVCXPRT data structure.

```
#include <rpc/rpc.h>
```

```
bool_t rpc_reg(const rpcprog_t prognum, const rpcvers_t versnum, const rpcproc_t procnum,
char * (*procname)( ), const xdrproc_t inproc, const xdrproc_t outproc, const char *nettype);
```

Register program *prognum*, procedure *procname*, and version *versnum* with the RPC service package. If a request arrives for program *prognum*, version *versnum*, and procedure *procnum*, *procname* is called with a pointer to its parameter(s); *procname* should return a pointer to its static result(s). The *arg* parameter to *procname* is a pointer to the (decoded) procedure argument. *inproc* is the XDR function used to decode the parameters while *outproc* is the XDR function used to encode the results. Procedures are registered on all available transports of the class *nettype*. See [rpc\(3NSL\)](#). This routine returns 0 if the registration succeeded, -1 otherwise.

```
int svc_reg(const SVCXPRT *xprt, const rpcprog_t prognum, const rpcvers_t versnum, const
void (*dispatch)( ), const struct netconfig *netconf);
```

Associates *prognum* and *versnum* with the service dispatch procedure, *dispatch*. If *netconf* is NULL, the service is not registered with the `rpcbind` service. For example, if a service has already been registered using some other means, such as `inetd` (see [inetd\(1M\)](#)), it will not need to be registered again. If *netconf* is non-zero, then a mapping of the triple [*prognum*, *versnum*, *netconf*->] to *xprt*-> *xp_ltaddr* is established with the local `rpcbind` service.

The `svc_reg()` routine returns 1 if it succeeds, and 0 otherwise.

```
void svc_unreg(const rpcprog_t prognum, const rpcvers_t versnum);
```

Remove from the `rpcbind` service, all mappings of the triple [*prognum*, *versnum*, *all-transports*] to network address and all mappings within the RPC service package of the double [*prognum*, *versnum*] to dispatch routines.

```
int svc_auth_reg(const int cred_flavor, const enum auth_stat (*handler)( ));
```

Registers the service authentication routine *handler* with the dispatch mechanism so that it can be invoked to authenticate RPC requests received with authentication type *cred_flavor*. This interface allows developers to add new authentication types to their RPC applications without needing to modify the libraries. Service implementors usually do not need this routine.

Typical service application would call `svc_auth_reg()` after registering the service and prior to calling `svc_run()`. When needed to process an RPC credential of type *cred_flavor*, the *handler* procedure will be called with two parameters (`struct svc_req *rqst`, `struct`

rpc_msg *msg) and is expected to return a valid enum auth_stat value. There is no provision to change or delete an authentication handler once registered.

The svc_auth_reg () routine returns 0 if the registration is successful, 1 if cred_flavor already has an authentication handler registered for it, and -1 otherwise.

void xprt_register(const SVCXPRT *xprt);
 After RPC service transport handle xprt is created, it is registered with the RPC service package. This routine modifies the global variable svc_fdset (see rpc_svc_calls(3NSL)). Service implementors usually do not need this routine.

void xprt_unregister(const SVCXPRT *xprt);
 Before an RPC service transport handle xprt is destroyed, it unregisters itself with the RPC service package. This routine modifies the global variable svc_fdset (see rpc_svc_calls(3NSL)). Service implementors usually do not need this routine.

Attributes See attributes(5) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also inetd(1M), rpcbind(1M), rpc(3NSL), rpc_svc_calls(3NSL), rpc_svc_create(3NSL), rpc_svc_err(3NSL), rpcbind(3NSL), select(3C), attributes(5)

Name `rpc_xdr`, `xdr_accepted_reply`, `xdr_authsys_parms`, `xdr_callhdr`, `xdr_callmsg`, `xdr_opaque_auth`, `xdr_rejected_reply`, `xdr_replymsg` – XDR library routines for remote procedure calls

Synopsis

```
bool_t xdr_accepted_reply(XDR *xdrs, const struct accepted_reply *ar);

bool_t xdr_authsys_parms(XDR *xdrs, struct authsys_parms *aupp);

void xdr_callhdr(XDR *xdrs, struct rpc_msg *chdr);

bool_t xdr_callmsg(XDR *xdrs, struct rpc_msg *cmsg);

bool_t xdr_opaque_auth(XDR *xdrs, struct opaque_auth *ap);

bool_t xdr_rejected_reply(XDR *xdrs, const struct rejected_reply *rr);

bool_t xdr_replymsg(XDR *xdrs, const struct rpc_msg *rmsg);
```

Description These routines are used for describing the RPC messages in XDR language. They should normally be used by those who do not want to use the RPC package directly. These routines return TRUE if they succeed, FALSE otherwise.

Routines See [rpc\(3NSL\)](#) for the definition of the XDR data structure.

```
#include <rpc/rpc.h>
```

<code>xdr_accepted_reply()</code>	Used to translate between RPC reply messages and their external representation. It includes the status of the RPC call in the XDR language format. In the case of success, it also includes the call results.
<code>xdr_authsys_parms()</code>	Used for describing UNIX operating system credentials. It includes machine-name, uid, gid list, etc.
<code>xdr_callhdr()</code>	Used for describing RPC call header messages. It encodes the static part of the call message header in the XDR language format. It includes information such as transaction ID, RPC version number, program and version number.
<code>xdr_callmsg()</code>	Used for describing RPC call messages. This includes all the RPC call information such as transaction ID, RPC version number, program number, version number, authentication information, etc. This is normally used by servers to determine information about the client RPC call.
<code>xdr_opaque_auth()</code>	Used for describing RPC opaque authentication information messages.
<code>xdr_rejected_reply()</code>	Used for describing RPC reply messages. It encodes the rejected RPC message in the XDR language format. The message could be rejected either because of version number mis-match or because of authentication errors.

xdr_replymsg()

Used for describing RPC reply messages. It translates between the RPC reply message and its external representation. This reply could be either an acceptance, rejection or NULL.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Safe

See Also [rpc\(3NSL\)](#), [xdr\(3NSL\)](#), [attributes\(5\)](#)

Name rstat, havedisk – get performance data from remote kernel

Synopsis

```
cc [ flag ... ] file ... -lrpcsvc [ library ... ]
#include <rpc/rpc.h>
#include <rpcsvc/rstat.h>
```

```
enum clnt_stat rstat(char *host, struct statstime *statp);
int havedisk(char *host);
```

Protocol /usr/include/rpcsvc/rstat.x

Description These routines require that the [rpc.rstatd\(1M\)](#) daemon be configured and available on the remote system indicated by *host*. The `rstat()` protocol is used to gather statistics from remote kernel. Statistics will be available on items such as paging, swapping, and cpu utilization.

`rstat()` fills in the `statstime` structure *statp* for *host*. *statp* must point to an allocated `statstime` structure. `rstat()` returns `RPC_SUCCESS` if it was successful; otherwise a `enum clnt_stat` is returned which can be displayed using [clnt_perrno\(3NSL\)](#).

`havedisk()` returns 1 if *host* has disk, 0 if it does not, and -1 if this cannot be determined.

The following XDR routines are available in `librpcsvc`:

```
xdr_statstime
xdr_statsvar
```

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [rup\(1\)](#), [rpc.rstatd\(1M\)](#), [rpc_clnt_calls\(3NSL\)](#), [attributes\(5\)](#)

Name rusers, rnusers – return information about users on remote machines

Synopsis

```
cc [ flag ... ] file ... -lrpcsvc [ library ... ]
#include <rpc/rpc.h>
#include <rpcsvc/rusers.h>
```

```
enum clnt_stat rusers(char *host, struct utmpidlearr *up);
int rnusers(char *host);
```

Protocol /usr/include/rpcsvc/rusers.x

Description These routines require that the [rpc.rusersd\(1M\)](#) daemon be configured and available on the remote system indicated by *host*. The `rusers()` protocol is used to retrieve information about users logged in on the remote system.

`rusers()` fills the `utmpidlearr` structure with data about *host*, and returns 0 if successful. *up* must point to an allocated `utmpidlearr` structure. If `rusers()` returns successful it will have allocated data structures within the *up* structure, which should be freed with [xdr_free\(3NSL\)](#) when you no longer need them:

```
xdr_free(xdr_utmpidlearr, up);
```

On error, the returned value can be interpreted as an `enum clnt_stat` and can be displayed with [clnt_perror\(3NSL\)](#) or [clnt_sperrno\(3NSL\)](#).

See the header `<rpcsvc/rusers.h>` for a definition of `struct utmpidlearr`.

`rnusers()` returns the number of users logged on to *host* (–1 if it cannot determine that number).

The following XDR routines are available in `librpcsvc`:

```
xdr_utmpidlearr
```

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [rusers\(1\)](#), [rpc.rusersd\(1M\)](#), [rpc_clnt_calls\(3NSL\)](#), [xdr_free\(3NSL\)](#), [attributes\(5\)](#)

Name rwall – write to specified remote machines

Synopsis `cc [flag ...] file ... -lrpcsvc [library ...]`
`#include <rpc/rpc.h>`
`#include <rpcsvc/rwall.h>`

`enum clnt_stat rwall(char *host, char *msg);`

Protocol /usr/include/rpcsvc/rwall.x

Description These routines require that the [rpc.rwalld\(1M\)](#) daemon be configured and available on the remote system indicated by *host*.

`rwall()` executes [wall\(1M\)](#) on *host*. The `rpc.rwalld` process on *host* prints *msg* to all users logged on to that system. `rwall()` returns `RPC_SUCCESS` if it was successful; otherwise a `enum clnt_stat` is returned which can be displayed using [clnt_pererrno\(3NSL\)](#).

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [rpc.rwalld\(1M\)](#), [wall\(1M\)](#), [rpc_clnt_calls\(3NSL\)](#), [attributes\(5\)](#)

Name sasl_authorize_t – the SASL authorization callback

Synopsis

```
cc [ flag ... ] file ... -lsasl [ library ... ]
#include <sasl/sasl.h>

int sasl_authorize_t(sasl_conn_t *conn, const char *requested_user,
    unsigned alen, const char* auth_identity, unsigned rlen,
    const char *def_realm, unsigned urlen, struct propctx *propctx);
```

Description sasl_authorize_t() is a typedef function prototype that defines the interface associated with the SASL_CB_PROXY_POLICY callback.

Use the sasl_authorize_t() interface to check whether the authorized user *auth_identity* can act as the user *requested_user*. For example, the user root may want to authenticate with root's credentials but as the user tmartin, with all of tmartin's rights, not root's. A server application should be very careful when it determines which users may proxy as other users.

Parameters

<i>conn</i>	The SASL connection context.
<i>requested_user</i>	The identity or username to authorize. <i>requested_user</i> is null-terminated.
<i>rlen</i>	The length of <i>requested_user</i> .
<i>auth_identity</i>	The identity associated with the secret. <i>auth_identity</i> is null-terminated.
<i>alen</i>	The length of <i>auth_identity</i> .
<i>default_realm</i>	The default user realm as passed to sasl_server_new(3SASL) .
<i>ulren</i>	The length of the default realm
<i>propctx</i>	Auxiliary properties

Return Values Like other SASL callback functions, sasl_authorize_t() returns an integer that corresponds to a SASL error code. See <sasl.h> for a complete list of SASL error codes.

Errors SASL_OK The call to sasl_authorize_t() was successful.

See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [sasl_errors\(3SASL\)](#), [sasl_server_new\(3SASL\)](#), [attributes\(5\)](#)

Name `saslname, prop_new, prop_dup, prop_request, prop_get, prop_getnames, prop_clear, prop_erase, prop_dispose, prop_format, prop_set, prop_setvals` – SASL auxilliary properties

Synopsis `cc [flag ...] file ... -lsasl [library ...]`
`#include <sasl/prop.h>`

```
struct propctx *prop_new(unsigned estimate);

int prop_dup(struct propctx *src_ctx, struct propctx *dst_ctx);

int prop_request(struct propctx *ctx, const char **names);

const struct propval *prop_get(struct propctx *ctx);

int prop_getnames(struct propctx *ctx, const char **names,
                  struct propval *vals);

void prop_clear(struct propctx *ctx, int requests);

void prop_erase(struct propctx *ctx, const char *name);

void prop_dispose(struct propctx *ctx);

int prop_format(struct propctx *ctx, const char *sep, int seplen,
                char *outbuf, unsigned outmax, unsigned *outlen);

int prop_set(struct propctx *ctx, const char *name, const char *value,
             int vallen);

int prop_setvals(struct propctx *ctx, const char *name,
                 const char **values);
```

Description The SASL auxilliary properties are used to obtain properties from external sources during the authentication process. For example, a mechanism might need to query an LDAP server to obtain the authentication secret. The application probably needs other information from the LDAP server as well, such as the home directory of the UID. The auxilliary property interface allows the two to cooperate and results in only a single query against the property sources.

Property lookups take place directly after user canonicalization occurs. Therefore, all request should be registered with the context before user canonicalization occurs. Requests can also be registered by using the [saslname_request\(3SASL\)](#) function. Most of the auxilliary property functions require a property context that can be obtained by calling [saslname_getctx\(3SASL\)](#).

`prop_new()` The `prop_new()` function creates a new property context. It is unlikely that application developers will use this call.

`prop_dup()` The `prop_dup()` function duplicates a given property context.

`prop_request()` The `prop_request()` function adds properties to the request list of a given context.

`prop_get()` The `prop_get()` function returns a null-terminated array of `struct propval` from the given context.

`prop_getnames()` The `prop_getnames()` function fills in an array of `struct propval` based on a list of property names. The `vals` array is at least as long as the `names` array. The values that are filled in by this call persist until the next call on the context to `prop_request()`, `prop_clear()`, or `prop_dispose()`. If a name specified was never requested, then its associated values entry will be set to `NULL`.

The `prop_getnames()` function returns the number of matching properties that were found or a SASL error code.

`prop_clear()` The `prop_clear()` function clears *values* and *requests* from a property context. If the value of *requests* is 1, then *requests* is cleared. Otherwise, the value of *requests* is 0.

`prop_erase()` The `prop_erase()` function securely erases the value of a property. *name* is the name of the property to erase.

`prop_dispose()` The `prop_dispose()` function disposes of a property context and nullifies the pointer.

`prop_format()` The `prop_format()` function formats the requested property names into a string. The `prop_format()` function is not intended to be used by the application. The function is used only by auxprop plug-ins.

`prop_set()` The `prop_set()` functions adds a property value to the context. The `prop_set()` function is used only by auxprop plug-ins.

`prop_setvals()` The `prop_setvals()` function adds multiple values to a single property. The `prop_setvals()` function is used only by auxprop plug-ins.

Parameters	<i>conn</i>	The <code>sasl_conn_t</code> for which the request is being made
	<i>ctx</i>	The property context.
	<i>estimate</i>	The estimate of the total storage needed for requests and responses. The library default is implied by a value of 0.
	<i>names</i>	The null-terminated array of property names. <i>names</i> must persist until the requests are cleared or the context is disposed of with a call to <code>prop_dispose()</code> .
	<i>name</i>	The name of the property. For <code>prop_set()</code> , <i>name</i> is the named of the property to receive the new value, or <code>NULL</code> . The value will be added to the same property as the last call to either <code>prop_set()</code> or <code>prop_setvals()</code> .
	<i>outbuf</i>	The caller-allocated buffer of length <i>outmax</i> that the resulting string, including the <code>NULL</code> terminator, will be placed in.

<i>outlen</i>	If non-NULL, contains the length of the resulting sting, excluding the NULL terminator.
<i>outmax</i>	The maximum length of the output buffer, including the NULL terminator.
<i>requests</i>	The request list for a given context.
<i>sep</i>	The separator to use for the string.
<i>seplen</i>	The length of the separator. If the value is less than 0, then <code>strlen</code> will be used as <i>sep</i> .
<i>vallen</i>	The length of the property.
<i>vals</i>	The value string.
<i>value</i>	A value for the property of length <i>vallen</i> .
<i>values</i>	A null-terminated array of values to be added to the property.

Errors The `sas_l_auxprop()` functions that return an `int` will return a SASL error code. See [sas_l_errors\(3SASL\)](#). Those `sas_l_auxprop()` functions that return a pointer will return a valid pointer upon success and return NULL upon failure.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [sas_l_auxprop_getctx\(3SASL\)](#), [sas_l_auxprop_request\(3SASL\)](#), [sas_l_errors\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_auxprop_add_plugin – add a SASL auxiliary property plug-in

Synopsis cc [*flag* ...] *file* ... -lsasl [*library* ...]
#include <sasl/saslplug.h>

```
int sasl_auxprop_add_plugin(const char *plugname,  
                           sasl_auxprop_plug_init_t *cplugfunc);
```

Description Use the `sasl_auxprop_add_plugin()` interface to add a auxiliary property plug-in to the current list of auxiliary property plug-ins in the SASL library.

Parameters *plugname* The name of the auxiliary property plug-in.
cplugfunc The value of *cplugfunc* is filled in by the `sasl_auxprop_plug_init_t` structure.

Return Values `sasl_auxprop_add_plugin()` returns an integer that corresponds to a SASL error code.

Errors SASL_OK The call to `sasl_client_add_plugin()` was successful.
SASL_BADVERS Version mismatch with plug-in.
SASL_NOMEM Memory shortage failure.

See [sasl_errors\(3SASL\)](#) for information on other SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_auxprop_getctx – acquire an auxiliary property context

Synopsis `cc [flag ...] file ... -lsasl [library ...]
#include <sasl/sasl.h>`

```
struct propctx *sasl_auxprop_getctx(sasl_conn_t *conn);
```

Description The `sasl_auxprop_getctx()` interface returns an auxiliary property context for the given `sasl_conn_t` on which the sasl auxiliary property functions can operate. See [sasl_auxprop\(3SASL\)](#).

Parameters *conn* The `sasl_conn_t` for which the request is being made

Return Values `sasl_auxprop_getctx()` returns a pointer to the context, upon success.
`sasl_auxprop_getctx()` returns NULL upon failure.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	Safe

See Also [attributes\(5\)](#)

Name sasl_auxprop_request – request auxilliary properties from SASL

Synopsis cc [*flag* ...] *file* ... -lsasl [*library* ...]
#include <sasl/sasl.h>

```
int sasl_auxprop_request(sasl_conn_t *conn, const char **propnames);
```

Description The `sasl_auxprop_request()` interface requests that the SASL library obtain properties from any auxilliary property plugins that might be installed, for example, the user's home directory from an LDAP server. The lookup occurs just after username canonicalization is complete. Therefore, the request should be made before the call to [sasl_server_start\(3SASL\)](#), but after the call to [sasl_server_new\(3SASL\)](#).

Parameters *conn* The `sasl_conn_t` for which the request is being made
propnames A null-terminated array of property names to request. This array must persist until a call to [sasl_dispose\(3SASL\)](#) on the `sasl_conn_t`.

Errors `sasl_auxprop_request()` returns SASL_OK upon success. See [sasl_errors\(3SASL\)](#) for a discussion of other SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	Safe

See Also [sasl_dispose\(3SASL\)](#), [sasl_errors\(3SASL\)](#), [sasl_server_new\(3SASL\)](#), [sasl_server_start\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_canonuser_add_plugin – add a SASL user canonicalization plug-in

Synopsis cc [*flag* ...] *file* ... -lsasl [*library* ...]
#include <sasl/saslplug.h>

```
int sasl_canonuser_add_plugin(const char *plugname,  
                             sasl_canonuser_plug_init_t *cplugfunc);
```

Description Use the sasl_canonuser_add_plugin() interface to add a user canonicalization plug-in to the current list of user canonicalization plug-ins in the SASL library.

Parameters *plugname* The name of the user canonicalization plug-in.
cplugfunc The value of *cplugfunc* is filled in by the sasl_canonuser_plug_init_t structure.

Return Values sasl_server_add_plugin() returns an integer that corresponds to a SASL error code.

Errors SASL_OK The call to sasl_client_add_plugin() was successful.
SASL_BADVERS Version mismatch with plug-in.
SASL_NOMEM Memory shortage failure.

See [sasl_errors\(3SASL\)](#) for information on other SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_canon_user_t – the canon user callback

Synopsis cc [*flag* ...] *file* ... -lsasl [*library* ...]
#include <sasl/sasl.h>

```
int sasl_canon_user_t(sasl_conn_t *conn, void *context, const char *user,
    unsigned ulen, unsigned flags, const char *user_realm, char *out_user,
    unsigned *out_umat, unsigned *out_ulen);
```

Description The sasl_canon_user_t() interface is the callback function for an application-supplied user canonical function. This function is subject to the requirements of all canonical functions. It must copy the result into the output buffers, but the output buffers and the input buffers can be the same.

Parameters

<i>conn</i>	The SASL connection context.
<i>context</i>	The context from the callback record.
<i>user</i>	User name. The form of <i>user</i> is not canonical.
<i>ulen</i>	Length of <i>user</i> . The form of <i>ulen</i> is not canonical.
<i>flags</i>	One of the following values, or a bitwise OR of both: SASL_CU_AUTHID Indicates the authentication ID is canonical SASL_CU_AUTHZID Indicates the authorization ID is canonical
<i>user_realm</i>	Realm of authentication.
<i>out_user</i>	The output buffer for the user name.
<i>out_max</i>	The maximum length for the user name.
<i>out_len</i>	The actual length for the user name.

Return Values Like other SASL callback functions, sasl_canon_user_t() returns an integer that corresponds to a SASL error code. See <sasl.h> for a complete list of SASL error codes.

Errors SASL_OK The call to sasl_canon_user_t() was successful.

See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsas
Interface Stability	Evolving

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [sasl_errors\(3SASL\)](#), [sasl_server_new\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_chalprompt_t – prompt for input in response to a challenge

Synopsis

```
cc [ flag ... ] file ... -lsasl [ library ... ]
#include <sasl/sasl.h>
```

```
int sasl_chalprompt_t(void *context, int id, const char *challenge,
    const char *prompt, const char *defresult, const char **result,
    unsigned *len);
```

Description Use the sasl_chalprompt_t() callback interface to prompt for input in response to a server challenge.

Parameters

<i>context</i>	The context from the callback record.
<i>id</i>	The callback id. <i>id</i> can have a value of SASL_CB_ECHOPROMPT or SASL_CB_NOECHOPROMPT
<i>challenge</i>	The server's challenge.
<i>prompt</i>	A prompt for the user.
<i>defresult</i>	The default result. The value of <i>defresult</i> can be NULL
<i>result</i>	The user's response. <i>result</i> is a null-terminated string.
<i>len</i>	The length of the user's response.

Return Values Like other SASL callback functions, sasl_chalprompt_t() returns an integer that corresponds to a SASL error code. See <sasl.h> for a complete list of SASL error codes.

Errors SASL_OK The call to sasl_chalprompt_t() was successful.

See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [sasl_errors\(3SASL\)](#), [sasl_server_new\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_checkpop – check an APOP challenge or response

Synopsis cc [*flag* ...] *file* ... -lsasl [*library* ...]
#include <sasl/sasl.h>

```
int sasl_checkpop(sasl_conn_t *conn, const char *challenge,
                 unsigned challen, const char *response, unsigned resplen);
```

Description The sasl_checkpop() interface checks an APOP challenge or response. APOP is an option POP3 authentication command that uses a shared secret password. See RFC 1939.

If sasl_checkpop() is called with a NULL challenge, sasl_checkpop() will check to see if the APOP mechanism is enabled.

Parameters *conn* The sasl_conn_t for which the request is being made
challenge The challenge sent to the client
challen The length of *challenge*
response The client response
resplens The length of *response*

Return Values sasl_checkpop() returns an integer that corresponds to a SASL error code.

Errors SASL_OK Indicates that the authentication is complete

All other error codes indicate an error situation that must be handled, or the authentication session should be quit. See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	SUNWlibsasl
Interface Stability	Obsolete
MT-Level	Safe

See Also [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Meyers, J. and Rose, M. *RFC 1939, Post Office Protocol – Version 3*. Network Working Group. May 1996.

Name sasl_checkpass – check a plaintext password

Synopsis cc [*flag* ...] *file* ... -lsasl [*library* ...]
#include <sasl/sasl.h>

```
int sasl_checkpass(sasl_conn_t *conn, const char *user, unsigned userlen,  
                  const char *pass, unsigned passlen);
```

Description The sasl_checkpass() interface checks a plaintext password. The sasl_checkpass() interface is used for protocols that had a login method before SASL, for example, the LOGIN command in IMAP. The password is checked with the pwcheck_method.

The sasl_checkpass() interface is a server interface. You cannot use it to check passwords from a client.

The sasl_checkpass() interface checks the possible repositories until it succeeds or there are no more repositories. If sasl_server_userdb_checkpass_t is registered, sasl_checkpass() tries it first.

Use the pwcheck_method SASL option to specify which pwcheck methods to use.

The sasl_checkpass() interface supports the transition of passwords if the SASL option auto_transition is on.

If user is NULL, check is plaintext passwords are enabled.

Parameters conn The sasl_conn_t for which the request is being made
pass Plaintext password to check
passlen The length of pass
user User to query in current user_domain
userlen The length of username.

Return Values sasl_checkpass() returns an integer that corresponds to a SASL error code.

Errors SASL_OK Indicates that the authentication is complete

All other error codes indicate an error situation that must be handled, or the authentication session should be quit. See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Evolving
MT-Level	Safe

See Also [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_client_add_plugin – add a SASL client plug-in

Synopsis cc [*flag* ...] *file* ... -lsasl [*library* ...]
#include <sasl/saslplug.h>

int sasl_client_add_plugin(const char **plugname*,
sasl_client_plug_init_t **cplugfunc*);

Description Use the sasl_client_add_plugin() interface to add a client plug-in to the current list of client plug-ins in the SASL library.

Parameters *plugname* The name of the client plug-in.
cplugfunc The value of *cplugfunc* is filled in by the sasl_client_plug_init_t structure.

Return Values sasl_client_add_plugin() returns an integer that corresponds to a SASL error code.

Errors SASL_OK The call to sasl_client_add_plugin() was successful.
SASL_BADVERS Version mismatch with plug-in.
SASL_NOMEM Memory shortage failure.

See [sasl_errors\(3SASL\)](#) for information on other SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Name `sasldb_client_init` – initialize SASL client authentication

Synopsis `cc [flag ...] file ... -lsasl [library ...]
#include <sasl/sasl.h>`

```
int sasldb_client_init(const sasldb_callback_t *callbacks);
```

Description Use the `sasldb_client_init()` interface to initialize SASL. The `sasldb_client_init()` interface must be called before any calls to [sasldb_client_start\(3SASL\)](#). The call to `sasldb_client_init()` initializes all SASL client drivers, for example, authentication mechanisms. SASL client drivers are usually found in the `/usr/lib/sasl` directory.

Parameters `callbacks` Specifies the base callbacks for all client connections.

Return Values `sasldb_client_init()` returns an integer that corresponds to a SASL error code.

Errors	<code>SASL_OK</code>	The call to <code>sasldb_client_init()</code> was successful.
	<code>SASL_BADVERS</code>	There is a mismatch in the mechanism version.
	<code>SASL_BADPARAM</code>	There is an error in the configuration file.
	<code>SASL_NOMEM</code>	There is not enough memory to complete the operation.

All other error codes indicate an error situation that must be handled, or the authentication session should be quit. See [sasldb_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	Unsafe

See Also [sasldb_errors\(3SASL\)](#), [attributes\(5\)](#)

Notes While most of `libsasl` is MT-Safe, no other `libsasl` function should be called until this function completes.

Name sasl_client_new – create a new client authentication object

Synopsis cc [*flag ...*] *file ...* -lsasl [*library ...*]
#include <sasl/sasl.h>

```
int sasl_client_new(const char *service, const char *serverFQDN,
    const char *iplocalport, const char *ipremoteport,
    const sasl_callback_t *prompt_supp, unsigned flags,
    sasl_conn_t **pconn);
```

Description Use the sasl_client_new() interface to create a new SASL context. This SASL context will be used for all SASL calls for one connection. The context handles both authentication and the integrity and encryption layers after authentication.

Parameters *service* The registered name of the service that uses SASL, usually the protocol name, for example, IMAP.

serverFQDN The fully qualified domain name of the server, for example, serverhost.cmu.edu.

iplocalport

The IP and port of the local side of the connection, or NULL. If *iplocalport* is NULL, mechanisms that require IP address information are disabled. The *iplocalport* string must be in one of the following formats:

- a.b.c.d:port (IPv6)
- [e:f:g:h:i:j:k:l]:port (IPv6)
- [e:f:g:h:i:j:a.b.c.d]:port (IPv6)
- a.b.c.d;port (IPv4)
- e:f:g:h:i:j:k;l;port (IPv6)
- e:f:g:h:i:j:a.b.c.d;port (IPv6)

ipremoteport The IP and port of the remote side of the connection, or NULL.

prompt_supp A list of the client interactions supported that are unique to this connection. If this parameter is NULL, the global callbacks specified in [sasl_client_init\(3SASL\)](#) are used.

flags Usage flags. For clients, the flag SASL_NEED_PROXY is available.

pconn The connection context allocated by the library. The *pconn* structure is used for all future SASL calls for this connection.

Return Values sasl_client_new() returns an integer that corresponds to a SASL error code.

Errors SASL_OK The call to sasl_client_new() was successful.

SASL_NOMECH No mechanism meets the requested properties.

SASL_BADPARAM There is an error in the configuration file or passed parameters.

SASL_NOMEM There is not enough memory to complete the operation.

All other error codes indicate an error situation that must be handled, or the authentication session should be quit. See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	Safe

See Also [sasl_client_init\(3SASL\)](#), [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_client_plug_init_t – client plug-in entry point

Synopsis cc [*flag* ...] *file* ... -lsasl [*library* ...]
#include <sasl/saslplug.h>

```
int sasl_client_plug_init_t(const sasl_utils_t *utils, int max_version,  
    int *out_version, sasl_client_plug_t **pluglist, int *plugcount);
```

Description The sasl_client_plug_init_t() callback function is the client plug-in entry point.

Parameters

<i>utils</i>	The utility callback functions.
<i>max_version</i>	The highest client plug-in version supported.
<i>out_version</i>	The client plug-in version of the result..
<i>pluglist</i>	The list of client mechanism plug-ins.
<i>plugcount</i>	The number of client mechanism plug-ins.

Return Values Like other SASL callback functions, sasl_client_plug_init_t() returns an integer that corresponds to a SASL error code. See <sasl.h> for a complete list of SASL error codes.

Errors SASL_OK The call to sasl_client_plug_init_t() was successful.

See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_client_start – perform a step in the authentication negotiation

Synopsis `cc [flag ...] file ... -lsasl [library ...]`
`#include <sasl/sasl.h>`

```
int sasl_client_start(sasl_conn_t *conn, const char *mechlist,
                    sasl_interact_t **prompt_need, const char **clientout,
                    unsigned *clientoutlen, const char **mech);
```

Description Use the `sasl_client_start()` interface to select a mechanism for authentication and start the authentication session. The *mechlist* parameter holds the list of mechanisms that the client might like to use. The mechanisms in the list are not necessarily supported by the client, nor are the mechanisms necessarily valid. SASL determines which of the mechanisms to use based upon the security preferences specified earlier. The list of mechanisms is typically a list of mechanisms that the server supports, acquired from a capability request.

If `SASL_INTERACT` is returned, the library needs some values to be filled in before it can proceed. The *prompt_need* structure is filled in with requests. The application fulfills these requests and calls `sasl_client_start()` again with identical parameters. The *prompt_need* parameter is the same pointer as before, but it is filled in by the application.

Parameters	<i>conn</i>	The SASL connection context.
	<i>mechlist</i>	A list of mechanism that the server has available. Punctuation is ignored.
	<i>prompt_need</i>	A list of prompts that are needed to continue, if necessary.
	<i>clientout</i>	
	<i>clientoutlen</i>	<i>clientout</i> and <i>clientoutlen</i> are created. They contain the initial client response to send to the server. It is the job of the client to send them over the network to the server. Any protocol specific encoding that is necessary, for example base64 encoding, must be done by the client.
		If the protocol lacks client-send-first capability, then set <i>clientout</i> to NULL. If there is no initial client-send, then <i>*clientout</i> will be set to NULL on return.
	<i>mech</i>	Contains the name of the chosen SASL mechanism, upon success.

Return Values `sasl_client_start()` returns an integer that corresponds to a SASL error code.

Errors `SASL_CONTINUE` The call to `sasl_client_start()` was successful, and more steps are needed in the authentication.

All other error codes indicate an error situation that must be handled, or the authentication session should be quit. See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	Safe

See Also [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_client_step – acquire an auxiliary property context

Synopsis cc [*flag* ...] *file* ... -lsasl [*library* ...]
#include <sasl/sasl.h>

```
int sasl_client_step(sasl_conn_t *conn, const char *serverin,
                    sasl_interact_t **unsigned serverinlen, prompt_need,
                    const char **clientout, sasl_interact_t **unsigned *clientoutlen);
```

Description Use the sasl_client_step() interface performs a step in the authentication negotiation. sasl_client_step() returns SASL_OK if the complete negotiation is successful. If the negotiation on step is completed successfully, but at least one more step is required, sasl_client_step() returns SASL_CONTINUE. A client should not assume an authentication negotiaion is successful because the server signaled success through the protocol. For example, if the server signaled OK Authentication succeeded in IMAP, sasl_client_step() should be called one more time with a *serverinlen* of zero.

If a call to sasl_client_step() returns SASL_INTERACT, the library requires some values before sasl_client_step() can proceed. The *prompt_need* structure will be filled with the requests. The application should fulfull these requests and call sasl_client_step() again with identical parameters. The *prompt_need* parameter will be the same pointer as before, but it will have been filled in by the application.

Parameters	<i>conn</i>	The SASL connection context.
	<i>serverin</i>	The data given by the server. The data is decoded if the protocol encodes requests sent over the wire.
	<i>serverinlen</i>	The length of the <i>serverin</i> .
	<i>clientout</i> <i>clientoutlen</i>	<i>clientout</i> and <i>clientoutlen</i> are created. They contain the initial client response to send to the server. It is the job of the client to send them over the network to the server. Any protocol specific encodingthat is necessary, for example base64 encoding, must be done by the client.
	<i>prompt_need</i>	A list of prompts that are needed to continue, if necessary.

Return Values sasl_client_step() returns an integer that corresponds to a SASL error code.

Errors	SASL_OK	The call to sasl_client_start() was successful. Authentication is complete.
	SASL_CONTINUE	The call to sasl_client_start() was successful, but at least one more step is required for authentication.
	SASL_INTERACT	The library requires some values before sasl_client_step() can proceed.

All other error codes indicate an error situation that must be handled, or the authentication session should be quit. See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	Safe

See Also [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_decode – decode data received

Synopsis `cc [flag ...] file ... -lsasl [library ...]`
`#include <sasl/sasl.h>`

```
int sasl_decode(sasl_conn_t *conn, const char *input, unsigned inputlen,
               const char **output, unsigned *outputlen);
```

Description Use the `sasl_decode()` interface to decode data received. After authentication, call this function on all data received. The data is decoded from encrypted or signed form to plain data. If no security lay is negotiated, the output is identical to the input.

Do not give `sasl_decode()` more data than the negotiated `maxbufsize`. See [sasl_getprop\(3SASL\)](#).

`sasl_decode()` can complete successfully although the value of `outputlen` is zero. If this is the case, wait for more data and call `sasl_decode()` again.

Parameters

<i>conn</i>	The SASL connection context.
<i>input</i>	Data received.
<i>inputlen</i>	The length of <i>input</i>
<i>output</i>	The decoded data. <i>output</i> must be allocated or freed by the library.
<i>outputlen</i>	The length of <i>output</i> .

Return Values `sasl_decode()` returns an integer that corresponds to a SASL error code.

Errors SASL_OK The call to `sasl_decode()` was successful.

See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	Safe

See Also [sasl_errors\(3SASL\)](#), [sasl_getprop\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_decode64 – decode base64 string

Synopsis cc [*flag* ...] *file* ... -lsasl [*library* ...]
#include <sasl/saslutil.h>

```
int sasl_decode64(const char *in, unsigned inlen, char *out,  
                unsigned outmax, unsigned *outlen);
```

Description Use the sasl_decode64() interface to decode a base64 encoded buffer.

Parameters

<i>in</i>	Input data.
<i>inlen</i>	The length of the input data.
<i>out</i>	The output data. The value of <i>out</i> can be the same as <i>in</i> . However, there must be enough space.
<i>outlen</i>	The length of the actual output.
<i>outmax</i>	The maximum size of the output buffer.

Return Values sasl_decode64() returns an integer that corresponds to a SASL error code.

Errors SASL_OK The call to sasl_decode64() was successful.

See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_dispose – dispose of a SASL connection object

Synopsis

```
cc [ flag ... ] file ... -lsasl [ library ... ]  
#include <sasl/sasl.h>
```

```
void sasl_dispose(sasl_conn_t **pconn);
```

Description Use the `sasl_dispose()` interface when a SASL connection object is no longer needed. Generally, the SASL connection object is no longer needed when the protocol session is completed, not when authentication is completed, as a security layer may have been negotiated.

Parameters *pconn* The SASL connection context

Return Values `sasl_dispose()` has no return values.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	Safe

See Also [attributes\(5\)](#)

Name sasl_done – dispose of all SASL plug-ins

Synopsis `cc [flag ...] file ... -lsasl [library ...]`
`#include <sasl/sasl.h>`

`void sasl_encode(void)`

Description Make a call to the `sasl_done()` interface when the application is completely done with the SASL library. You must call [sasl_dispose\(3SASL\)](#) before you make a call to `sasl_done()`.

Return Values `sasl_done()` has no return values.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	Safe

See Also [sasl_dispose\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_encode, sasl_encodev – encode data for transport to an authenticated host

Synopsis `cc [flag ...] file ... -lsasl [library ...]`
`#include <sasl/sasl.h>`

```
int sasl_encode(sasl_conn_t *conn, const char *input, unsigned inputlen,
               const char **output, unsigned *outputlen);
```

```
int sasl_encodev(sasl_conn_t *conn, const struct iovec *invec,
                unsigned numiov, const char *outputlen);
```

Description The `sasl_encode()` interface encodes data to be sent to a remote host for which there has been a successful authentication session. If there is a negotiated security, the data is signed or encrypted, and the output is sent without modification to the remote host. If there is no security layer, the output is identical to the input.

The `sasl_encodev()` interface functions the same as the `sasl_encode()` interface, but operates on a `struct iovec` instead of a character buffer.

Parameters

<i>conn</i>	The SASL connection context.
<i>input</i>	Data.
<i>inputlen</i>	<i>input</i> length.
<i>output</i>	The encoded data. <i>output</i> must be allocated or freed by the library.
<i>outputlen</i>	The length of <i>output</i> .
<i>invec</i>	A pointer to set of <code>iovec</code> structures.
<i>numiov</i>	The number of <code>iovec</code> structures in the <i>invec</i> set.

Return Values `sasl_encode()` returns an integer that corresponds to a SASL error code.

Errors SASL_OK The call to `sasl_encode()` or `sasl_encodev()` was successful.

See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	Safe

See Also [attributes\(5\)](#)

Name sasl_encode64 – encode base64 string

Synopsis cc [*flag* ...] *file* ... -lsasl [*library* ...]
#include <sasl/saslutil.h>

```
int sasl_encode64(const char *in, unsigned inlen, char *out,  
                 unsigned outmax, unsigned *outlen);
```

Description Use the sasl_encode64() interface to convert an octet string into a base64 string. This routine is useful for SASL profiles that use base64, such as the IMAP (IMAP4) and POP (POP_AUTH) profiles. The output is null-terminated. If *outlen* is non-NULL, the length is placed in the *outlen*.

Parameters

<i>in</i>	Input data.
<i>inlen</i>	The length of the input data.
<i>out</i>	The output data. The value of <i>out</i> can be the same as <i>in</i> . However, there must be enough space.
<i>outlen</i>	The length of the actual output.
<i>outmax</i>	The maximum size of the output buffer.

Return Values sasl_encode64() returns an integer that corresponds to a SASL error code.

Errors

SASL_OK	The call to sasl_encode64() was successful.
SASL_BUFOVER	The output buffer was too small.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_erasebuffer – erase buffer

Synopsis cc [*flag* ...] *file* ... -lsasl [*library* ...]
#include <sasl/saslutil.h>

```
void sasl_erasebuffer(char *pass, unsigned len);
```

Description Use the sasl_erasebuffer() interface to erase a security sensitive buffer or password. The implementation may use recovery-resistant erase logic.

Parameters *pass* A password
len The length of the password

Return Values The sasl_erasebuffer() interface returns no return values.

Errors None.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [attributes\(5\)](#)

Name sasl_errdetail – retrieve detailed information about an error

Synopsis `cc [flag ...] file ... -lsasl [library ...]`
`#include <sasl/sasl.h>`

```
const char * sasl_errdetail(sasl_conn_t *conn);
```

Description The `sasl_errdetail()` interface returns an internationalized string that is a message that describes the error that occurred on a SASL connection. The `sasl_errdetail()` interface provides a more user friendly error message than the SASL error code returned when SASL indicates that an error has occurred on a connection. See [sasl_errors\(3SASL\)](#).

Parameters *conn* The SASL connection context for which the inquiry is made.

Return Values `sasl_errdetail()` returns the string that describes the error that occurred, or NULL, if there was an error retrieving it.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	Safe

See Also [sasl_errors\(3SASL\)](#), [sasl_seterror\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_errors – SASL error codes

Synopsis #include <sasl/sasl.h>

Description This man page describes the general error codes that may be returned by calls into the SASL library. The meaning of the error code may vary slightly based upon the context of the call from which it is returned.

Errors

Common Result Codes	SASL_OK	The call was successful.
	SASL_CONTINUE	Another step is required for authentication.
	SASL_FAILURE	Generic failure.
	SASL_NOMEM	Memory shortage failure.
	SASL_BUFOVER	Overflowed buffer.
	SASL_NOMECH	The mechanism was not supported, or no mechanisms matched the requirements.
	SASL_BADPROT	The protocol was bad, invalid or cancelled.
	SASL_NOT_DONE	Cannot request information. Not applicable until later in the exchange.
	SASL_BADPARAM	An invalid parameter was supplied.
	SASL_TRYAGAIN	Transient failure, for example, a weak key.
	SASL_BADMAC	Integrity check failed.
	SASL_NOTINIT	SASL library not initialized.
Client Only Result Codes	SASL_INTERACT	Needs user interaction.
	SASL_BADSERV	Server failed mutual authentication step.
	SASL_WRONGMECH	Mechanism does not support the requested feature.
Server Only Result Codes	SASL_BDAUTH	Authentication failure.
	SASL_NOAUTHZ	Authorization failure.
	SASL_TOOWEAK	The mechanism is too weak for this user.
	SASL_ENCRYPT	Encryption is needed to use this mechanism.
	SASL_TRANS	One time use of a plaintext password will enable requested mechanism for user.
	SASL_EXPIRED	The passphrase expired and must be reset.
	SASL_DISABLED	Account disabled.

Password Setting Result Codes	SASL_NOUSER	User not found.
	SASL_BADVERS	Version mismatch with plug-in.
	SASL_NOVERIFY	The user exists, but there is no verifier for the user.
	SASL_PWLOCK	Passphrase locked.
	SASL_NOCHANGE	The requested change was not needed.
	SASL_WEAKPASS	The passphrase is too weak for security policy.
	SASL_NOUSERPASS	User supplied passwords are not permitted.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTETYPE	ATTRIBUTEVALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	Safe

See Also [attributes\(5\)](#)

Name sasl_errstring – translate a SASL return code to a human-readable form

Synopsis cc [*flag* ...] *file* ... -lsasl [*library* ...]
#include <sasl/sasl.h>

```
const char * sasl_errstring(int saslerr, const char *langlist,
                           const char **outlang);
```

Description The sasl_errstring() interface is called to convert a SASL return code from an integer into a human readable string.

You should not used the sasl_errstring() interface to extract error code information from SASL. Applications should use [sasl_errdetail\(3SASL\)](#) instead, which contains this error information and more.

The sasl_errstring() interface supports only `i-default` and `i-local` at this time.

Parameters *saslerr* The error number to be translated.

langlist A comma-separated list of languages. See *RFC 1766*. If the *langlist* parameter has a NULL value, the default language, `i-default`, is used.

outlang The language actually used. The *outlang* parameter can be NULL. The returned error string is in UTF-8.

Return Values sasl_errstring() returns the string that describes the error that occurred, or NULL, if there was an error retrieving it.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	Safe

See Also [sasl_errors\(3SASL\)](#), [sasl_seterror\(3SASL\)](#), [attributes\(5\)](#)

Alvestrand, H. *RFC 1766, Tags for the Identification of Languages*. Network Working Group. November 1995.

Name sasl_getcallback_t – callback function to lookup a sasl_callback_t for a connection

Synopsis cc [*flag* ...] *file* ... -lsasl [*library* ...]
#include <sasl/saslplug.h>

```
int sasl_getcallback_t(sasl_conn_t *conn, unsigned long callbacknum,  
    int (**proc)( ), void **pcontext);
```

Description The sasl_getcallback_t() function is a callback to lookup a sasl_callback_t for a connection.

Parameters

<i>conn</i>	The connection to lookup a callback for.
<i>callbacknum</i>	The number of the callback.
<i>proc</i>	Pointer to the callback function. The value of <i>proc</i> is set to NULL upon failure.
<i>pcontext</i>	Pointer to the callback context. The value of <i>pcontext</i> is set to NULL upon failure.

Return Values Like other SASL callback functions, sasl_getcallback_t() returns an integer that corresponds to a SASL error code. See <sasl.h> for a complete list of SASL error codes.

Errors

SASL_OK	The call to sasl_getcallback_t() was successful.
SASL_FAIL	Unable to find a callback of the requested type.
SASL_INTERACT	The caller must use interaction to get data.

See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Name `sasl_getopt_t` – the SASL get option callback function

Synopsis `cc [flag ...] file ... -lsasl [library ...]`
`#include <sasl/sasl.h>`

```
int sasl_getopt_t(void *context, const char *plugin_name,
                 const char *option, const char **result, unsigned *len);
```

Description The `sasl_getopt_t()` function allows a SASL configuration to be encapsulated in the caller's configuration system. Some implementations may use default configuration file(s) if this function is omitted. Configuration items are arbitrary strings and are plug-in specific.

Parameters

<i>context</i>	The option context from the callback record.
<i>plugin_name</i>	The name of the plug-in. If the value of <i>plugin_name</i> is NULL, the the plug-in is a general SASL option.
<i>option</i>	The name of the option.
<i>result</i>	The value of <i>result</i> is set and persists until the next call to <code>sasl_getopt_t()</code> in the same thread. The value of <i>result</i> is unchanged if <i>option</i> is not found.
<i>len</i>	The length of <i>result</i> . The value of <i>result</i> can be NULL.

Return Values Like other SASL callback functions, `sasl_getopt_t()` returns an integer that corresponds to a SASL error code. See `<sasl.h>` for a complete list of SASL error codes.

Errors `SASL_OK` The call to `sasl_getopt_t()` was successful.

See [sas_l_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [sas_l_errors\(3SASL\)](#), [attributes\(5\)](#)

Name `sasl_getpath_t` – the SASL callback function to indicate location of the security mechanism drivers

Synopsis `cc [flag ...] file ... -lsasl [library ...]`
`#include <sasl/sasl.h>`

```
int sasl_getpath_t(void *context, char **path);
```

Description Use the `sasl_getpath_t()` function to enable the application to use a different location for the SASL security mechanism drivers, which are shared library files. If the `sasl_getpath_t()` callback is not used, SASL uses `/usr/lib/sasl` by default.

Parameters *context* The getpath context from the callback record
path The path(s) for the location of the SASL security mechanism drivers. The values for *path* are colon-separated.

Return Values Like other SASL callback functions, `sasl_getpath_t()` returns an integer that corresponds to a SASL error code. See `<sasl.h>` for a complete list of SASL error codes.

Errors `SASL_OK` The call to `sasl_getpath_t()` was successful.
See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_getprop – get a SASL property

Synopsis `cc [flag ...] file ... -lsasl [library ...]`
`#include <sasl/sasl.h>`

```
int sasl_getprop(sasl_conn_t *conn, int propnum, const void **pvalue);
```

Description Use the `sasl_getprop()` interface to get the value of a SASL property. For example, after successful authentication, a server may want to know the authorization name. Similarly, a client application may want to know the strength of the security level that was negotiated.

Parameters

<i>conn</i>	The SASL connection context.
<i>propnum</i>	The identifier for the property requested.
<i>pvalue</i>	The value of the SASL property. This value is filled in upon a successful call. Possible SASL values include:
SASL_USERNAME	A pointer to a null-terminated user name.
SASL_SSF	The security layer security strength factor. If the value of SASL_SSF is 0, a call to <code>sasl_encode()</code> or <code>sasl_decode()</code> is unnecessary.
SASL_MAXOUTBUF	The maximum size of output buffer returned by the selected security mechanism
SASL_DEFUSERREALM	Server authentication realm used.
SASL_GETOPTCTX	The context for <code>getopt()</code> callback.
SASL_IPLOCALPORT	Local address string.
SASL_IPREMOTEPORT	Remote address string.
SASL_SERVICE	Service passed on to <code>sasl_*_new()</code> .
SASL_SERVERFQDN	Server FQDN passed on to <code>sasl_*_new()</code> .
SASL_AUTHSOURCE	Name of authentication source last used. Useful for failed authentication tracking.
SASL_MECHNAME	Active mechanism name, if any.
SASL_PLUGERR	Similar to <code>sasl_errdetail()</code> .

Errors SASL_OK The call to `sasl_getprop()` was successful.

See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_getrealm_t – the realm acquisition callback function

Synopsis `cc [flag ...] file ... -lsasl [library ...]
#include <sasl/sasl.h>`

```
int sasl_getrealm_t(void *context, int id, const char **availrealms,  
                  const char **result);
```

Description Use the `sasl_getrealm_t()` function when there is an interaction with SASL_CB_GETREALM as the type.

If a mechanism would use this callback, but it is not present, then the first realm listed is automatically selected. A mechanism can still force the existence of a getrealm callback by SASL_CB_GETREALM to its `required_prompts` list.

Parameters

<i>context</i>	The context from the callback record
<i>id</i>	The callback ID (SASL_CB_GETREALM)
<i>availrealms</i>	A string list of the vailable realms. <i>availrealms</i> is a null-terminated sting that can be empty.
<i>result</i>	The chosen realm. <i>result</i> is a null-terminated string.

Return Values Like other SASL callback functions, `sasl_getrealm_t()` returns an integer that corresponds to a SASL error code. See `<sasl.h>` for a complete list of SASL error codes.

Errors SASL_OK The call to `sasl_getrealm_t()` was successful.

See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_getsecret_t – the SASL callback function for secrets (passwords)

Synopsis

```
cc [ flag ... ] file ... -lsasl [ library ... ]
#include <sasl/sasl.h>

int sasl_getsecret_t(sasl_conn_t *conn, void *context,
    int id, sasl_secret_t **psecret);
```

Description Use the `sasl_getsecret_t()` function to retrieve the secret from the application. Allocate a `sasl_secret_t` to length `sizeof(sasl_secret_t)+<length of secret>`. `sasl_secret_t` has two fields of `len` which contain the length of `secret` in bytes and the data contained in `secret`. The `secret` string does not need to be null-terminated.

Parameters

<i>conn</i>	The connection context
<i>context</i>	The context from the callback structure
<i>id</i>	The callback ID
<i>psecret</i>	To cancel, set the value of <i>psecret</i> to NULL. Otherwise, set the value to the password structure. The structure must persist until the next call to <code>sasl_getsecret_t()</code> in the same connection. Middleware erases password data when it is done with it.

Return Values Like other SASL callback functions, `sasl_getsecret_t()` returns an integer that corresponds to a SASL error code. See `<sasl.h>` for a complete list of SASL error codes.

Errors SASL_OK The call to `sasl_getsecret_t()` was successful.

See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_getsimple_t – the SASL callback function for username, authname and realm

Synopsis

```
cc [ flag ... ] file ... -lsasl [ library ... ]
#include <sasl/sasl.h>
```

```
int sasl_getsimple_t(void *context, int id, const char **result,
    unsigned *len);
```

Description Use the `sasl_getsimple_t()` callback function to retrieve simple data from the application such as the authentication name, the authorization name, and the realm. The *id* parameter indicates which value is requested.

Parameters

<i>context</i>	The context from the callback structure.								
<i>id</i>	The callback ID. Possible values for <i>id</i> include:								
	<table> <tr> <td>SASL_CB_USER</td> <td>Client user identity for login.</td> </tr> <tr> <td>SASL_CB_AUTHNAME</td> <td>Client authentication name.</td> </tr> <tr> <td>SASL_CB_LANGUAGE</td> <td>Comma-separated list of languages pursuant to <i>RFC 1766</i>.</td> </tr> <tr> <td>SASL_CB_CNONCE</td> <td>The client-nonce. This value is used primarily for testing.</td> </tr> </table>	SASL_CB_USER	Client user identity for login.	SASL_CB_AUTHNAME	Client authentication name.	SASL_CB_LANGUAGE	Comma-separated list of languages pursuant to <i>RFC 1766</i> .	SASL_CB_CNONCE	The client-nonce. This value is used primarily for testing.
SASL_CB_USER	Client user identity for login.								
SASL_CB_AUTHNAME	Client authentication name.								
SASL_CB_LANGUAGE	Comma-separated list of languages pursuant to <i>RFC 1766</i> .								
SASL_CB_CNONCE	The client-nonce. This value is used primarily for testing.								
<i>result</i>	To cancel user, set the value of <i>result</i> with a null-terminated string. If the value of <i>result</i> is NULL, then the user is cancelled.								
<i>len</i>	The length of <i>result</i> .								

Return Values Like other SASL callback functions, `sasl_getsimple_t()` returns an integer that corresponds to a SASL error code. See `<sasl.h>` for a complete list of SASL error codes.

Errors SASL_OK The call to `sasl_getsimple_t()` was successful.

See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Alvestrand, H. *RFC 1766, Tags for the Identification of Languages*. Network Working Group. November 1995.

Name sasl_global_listmech – retrieve a list of the supported SASL mechanisms

Synopsis cc [*flag* ...] *file* ... -lsasl [*library* ...]
#include <sasl/sasl.h>

```
const char ** sasl_global_listmech( );
```

Description The sasl_global_listmech() interface to returns a null-terminated array of strings that lists all of the mechanisms that are loaded by either the client or server side of the library.

Return Values A successful call to sasl_global_listmech() returns a pointer the array. On failure, NULL is returned. The SASL library is uninitialized.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Obsolete
MT-Level	MT-Safe

See Also [attributes\(5\)](#)

Name `sas_idle` – perform precalculations during an idle period

Synopsis `cc [flag ...] file ... -lsasl [library ...]`
`#include <sasl/sasl.h>`

```
int sas_idle(sasl_conn_t *conn);
```

Description Use the `sas_idle()` interface during an idle period to allow the SASL library or any mechanisms to perform any necessary precalculation.

Parameters *conn* The SASL connection context. The value of *conn* can be NULL in order to complete a precalculation before the connection takes place.

Return Values `sas_idle()` returns the following values:

- 1 Indicates action was taken
- 0 Indicates no action was taken

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [attributes\(5\)](#)

Name sasl_listmech – retrieve a list of the supported SASL mechanisms

Synopsis cc [*flag* ...] *file* ... -lsasl [*library* ...]
#include <sasl/sasl.h>

```
int sasl_listmech(sasl_conn_t *conn, const char *user, const char *prefix,  
                const char *sep, const char *suffix, const char **result,  
                unsigned *plen, int *pcount);
```

Description The sasl_listmech() interface returns a string listing the SASL names of all the mechanisms available to the specified user. This call is typically given to the client through a capability command or initial server response. Client applications need this list so that they know what mechanisms the server supports.

Parameters

<i>conn</i>	The SASL context for this connection user restricts the mechanism list to those mechanisms available to the user. This parameter is optional.
<i>user</i>	Restricts security mechanisms to those available to that user. The value of <i>user</i> may be NULL, and it is not used if called by the client application.
<i>prefix</i>	Appended to the beginning of <i>result</i> .
<i>sep</i>	Appended between mechanisms.
<i>suffix</i>	Appended to the end of <i>result</i> .
<i>result</i>	A null-terminated result string. <i>result</i> must be allocated or freed by the library.
<i>plen</i>	The length of the result filled in by the library. The value of <i>plen</i> may be NULL.
<i>pcount</i>	The number of mechanisms available. The value of <i>pcount</i> is filled in by the library. The value of <i>pcount</i> may be NULL

Return Values sasl_listmech() returns an integer that corresponds to a SASL error code.

Errors SASL_OK The call to sasl_listmech() was successful.
See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_log_t – the SASL logging callback function

Synopsis cc [*flag* ...] *file* ... -lsasl [*library* ...]
#include <sasl/sasl.h>

```
int sasl_log_t(void *context, int level, const char *message);
```

Description Use the sasl_log_t() function to log warning and error messages from the SASL library. [syslog\(3C\)](#) is used, unless another logging function is specified.

Parameters *context* The logging context from the callback record.

level The logging level. Possible values for *level* include:

SASL_LOG_NONE	Do not log anything.
SASL_LOG_ERR	Log unusual errors. This is the default log level.
SASL_LOG_FAIL	Log all authentication failures.
SASL_LOG_WARN	Log non-fatal warnings.
SASL_LOG_NOTE	Log non-fatal warnings (more verbose than SASL_LOG_WARN).
SASL_LOG_DEBUG	Log non-fatal warnings (more verbose than SASL_LOG_NOTE).
SASL_LOG_TRACE	Log traces of internal protocols.
SASL_LOG_PASS	Log traces of internal protocols, including passwords.

message The message to log

Return Values Like other SASL callback functions, sasl_log_t() returns an integer that corresponds to a SASL error code. See <sasl.h> for a complete list of SASL error codes.

Errors SASL_OK The call to sasl_log_t() was successful.

See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [sasl_errors\(3SASL\)](#), [syslog\(3C\)](#), [attributes\(5\)](#)

Name sasl_server_add_plugin – add a SASL server plug-in

Synopsis

```
cc [ flag ... ] file ... -lsasl [ library ... ]
#include <sasl/saslplug.h>

int sasl_server_add_plugin(const char *plugname,
    sasl_server_plug_init_t *cplugfunc);
```

Description Use the `sasl_server_add_plugin()` interface to add a server plug-in to the current list of client plug-ins in the SASL library.

Parameters *plugname* The name of the server plug-in.
cplugfunc The value of *cplugfunc* is filled in by the `sasl_server_plug_init_t` structure.

Return Values `sasl_server_add_plugin()` returns an integer that corresponds to a SASL error code.

Errors SASL_OK The call to `sasl_client_add_plugin()` was successful.
SASL_BADVERS Version mismatch with plug-in.
SASL_NOMEM Memory shortage failure.

See [sasl_errors\(3SASL\)](#) for information on other SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_server_init – SASL server authentication initialization

Synopsis `cc [flag ...] file ... -lsasl [library ...]`
`#include <sasl/sasl.h>`

```
int sasl_server_init(const sasl_callback *callbacks, const char *appname);
```

Description Use the `sasl_server_init()` interface to initialize SASL. You must call `sasl_server_init()` before you make a call to `sasl_server_start()`. `sasl_server_init()` may be called only once per process. A call to `sasl_server_init()` initializes all SASL mechanism drivers, that is, the authentication mechanisms. The SASL mechanism drivers are usually found in the `/usr/lib/sasl` directory.

Parameters *callbacks* Specifies the base callbacks for all client connections.
appname The name of the application for lower level logging. For example, the sendmail server calls *appname* this way:

```
sasl_server_init(srvcallbacks, "Sendmail")
```

Return Values `sasl_server_init()` returns an integer that corresponds to a SASL error code.

Errors SASL_OK The call to `sasl_server_init()` was successful.

All other error codes indicate an error situation that must be handled, or the authentication session should be quit. See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibasl
Interface Stability	Evolving
MT-Level	Unsafe

See Also [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Notes While most of `libasl` is MT-Safe, no other `libasl` function should be called until this function completes.

Name sasl_server_new – create a new server authentication object

Synopsis cc [*flag* ...] *file* ... -lsasl [*library* ...]
#include <sasl/sasl.h>

```
int sasl_server_new(const char *service, const char *serverFQDN,  
    const char *user_realm, const char *iplocalport,  
    const char *ipremoteport, const sasl_callback_t *callbacks,  
    unsigned flags, sasl_conn_t **pconn);
```

Description Use the sasl_server_new() interface to create a new SASL context. This context will be used for all SASL calls for one connection. The new SASL context handles both authentication and integrity or encryption layers after authentication.

Parameters	<p><i>service</i> The registered name of the service that uses SASL. The registered name is usually the protocol name, for example, IMAP.</p> <p><i>serverFQDN</i> The fully-qualified server domain name. If the value of <i>serverFQDN</i> is NULL, use gethostname(3C). The <i>serverFQDN</i> parameter is useful for multi-homed servers.</p> <p><i>user_realm</i> The domain of the user agent. The <i>user_realm</i> is usually not necessary. The default value of <i>user_realm</i> is NULL.</p> <p><i>iplocalport</i></p> <p style="margin-left: 40px;">The IP address and port of the local side of the connection. The value of <i>iplocalport</i> may be NULL. If <i>iplocalport</i> is NULL, mechanisms that require IP address information are disabled. The <i>iplocalport</i> string must be in one of the following formats:</p> <ul style="list-style-type: none">▪ a.b.c.d:port (IPv4)▪ [e:f:g:h:i:j:k:l]:port (IPv6)▪ [e:f:g:h:i:j:a.b.c.d]:port (IPv6) <p style="margin-left: 40px;">The following older formats are also supported:</p> <ul style="list-style-type: none">▪ a.b.c.d;port (IPv4)▪ e:f:g:h:i:j:k:l;port (IPv6)▪ e:f:g:h:i:j:a.b.c.d;port (IPv6) <p><i>ipremoteport</i> The IP address and port of the remote side of the connection. The value of <i>ipremoteport</i> may be NULL. See <i>iplocalport</i>.</p> <p><i>callbacks</i> Callbacks, for example: authorization, lang, and new getopt context.</p> <p><i>flags</i> Usage flags. For servers, the flags SASL_NEED_PROXY and SASL_SUCCESS_DATA are available.</p>
-------------------	---

pconn A pointer to the connection context allocated by the library. This structure will be used for all future SASL calls for this connection.

Return Values `sasl_server_new()` returns an integer that corresponds to a SASL error code.

Errors SASL_OK The call to `sasl_server_new()` was successful.

All other error codes indicate an error situation that must be handled, or the authentication session should be quit. See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [gethostname\(3C\)](#), [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_server_plug_init_t – server plug-in entry point

Synopsis

```
cc [ flag ... ] file ... -lsasl [ library ... ]
#include <sasl/saslplug.h>
```

```
int sasl_server_plug_init_t(const sasl_utils_t *utils, int max_version,
    int *out_version, sasl_client_plug_t **pluglist, int *plugcount);
```

Description The sasl_server_plug_init_t() callback function is the server plug-in entry point.

Parameters

<i>utils</i>	The utility callback functions.
<i>max_version</i>	The highest server plug-in version supported.
<i>out_version</i>	The server plug-in version of the result.
<i>pluglist</i>	The list of server mechanism plug-ins.
<i>plugcount</i>	The number of server mechanism plug-ins.

Return Values Like other SASL callback functions, sasl_server_plug_init_t() returns an integer that corresponds to a SASL error code. See <sasl.h> for a complete list of SASL error codes.

Errors SASL_OK The call to sasl_server_plug_init_t() was successful.
See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_server_start – create a new server authentication object

Synopsis

```
cc [ flag ... ] file ... -lsasl [ library ... ]
#include <sasl/sasl.h>
```

```
int sasl_server_start(sasl_conn_t *conn, const char *mech,
    const char *clientin, unsigned *clientinlen,
    const char **serverout, unsigned *serveroutlen);
```

Description The sasl_server_start() interface begins the authentication with the mechanism specified by the *mech* parameter. sasl_server_start() fails if the mechanism is not supported.

Parameters

<i>conn</i>	The SASL context for this connection.
<i>mech</i>	The mechanism name that the client requested.
<i>clientin</i>	The initial response from the client. The value of <i>clientin</i> is NULL if the protocol lacks support for the client-send-first or if the other end did not have an initial send. No initial client send is distinct from an initial send of a null string. The protocol must account for this difference.
<i>clientinlen</i>	The length of the initial response.
<i>serverout</i>	Created by the plugin library. The value of <i>serverout</i> is the initial server response to send to the client. <i>serverout</i> is allocated or freed by the library. It is the job of the client to send it over the network to the server. Protocol specific encoding, for example base64 encoding, must be done by the server.
<i>serveroutlen</i>	The length of the initial server challenge.

Return Values sasl_server_start() returns an integer that corresponds to a SASL error code.

Errors

SASL_OK	Authentication completed successfully.
SASL_CONTINUE	The call to sasl_server_start() was successful, and more steps are needed in the authentication.

All other error codes indicate an error situation that must be handled, or the authentication session should be quit. See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [gethostname\(3C\)](#), [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_server_step – perform a step in the server authentication negotiation

Synopsis

```
cc [ flag ... ] file ... -lsasl [ library ... ]
#include <sasl/sasl.h>

int sasl_server_step(sasl_conn_t *conn, const char *clientin,
    unsigned clientinlen, const char **serverout,
    unsigned *serveroutlen);
```

Description The sasl_server_step() performs a step in the authentication negotiation.

Parameters

<i>conn</i>	The SASL context for this connection.
<i>clientin</i>	The data given by the client. The data is decoded if the protocol encodes requests that are sent over the wire.
<i>clientinlen</i>	The length of <i>clientin</i> .
<i>serverout</i>	
<i>serveroutlen</i>	Set by the library and sent to the client.

Return Values sasl_server_step() returns an integer that corresponds to a SASL error code.

Errors

SASL_OK	The whole authentication completed successfully.
SASL_CONTINUE	The call to sasl_server_step() was successful, and at least one more step is needed for the authentication.

All other error codes indicate an error situation that you must handle, or you should quit the authentication session. See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_server_userdb_checkpass_t – plaintext password verification callback function

Synopsis `cc [flag ...] file ... -lsasl [library ...]`
`#include <sasl/sasl.h>`

```
int sasl_sasl_server_userdb_checkpass_t(sasl_conn_t *conn, void *context,  
    const char *user, const char *pass, unsigned passlen, struct propctx *propctx);
```

Description Use the `sasl_sasl_server_userdb_checkpass_t()` callback function to verify a plaintext password against the callback supplier's user database. Verification allows additional ways to encode the `userPassword` property.

Parameters

- conn* The SASL connection context.
- context* The context from the callback record.
- user* A null-terminated user name with `user@realm` syntax.
- pass* The password to check. This string cannot be null-terminated.
- passlen* The length of *pass*.
- propctx* The property context to fill in with `userPassword`.

Return Values Like other SASL callback functions, `sasl_server_userdb_checkpass_t()` returns an integer that corresponds to a SASL error code. See `<sasl.h>` for a complete list of SASL error codes.

Errors `SASL_OK` The call to `sasl_server_userdb_checkpass_t()` was successful.

See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Name

sasl_server_userdb_setpass_t – user database plaintext password setting callback function

Synopsis

```
cc [ flag ... ] file ... -lsasl    [ library ... ]
#include <sasl/sasl.h>

int sasl_server_userdb_setpass_t(sasl_conn_t *conn, void *context,
                                const char *user, const char *pass, unsigned passlen, struct propctx *propctx,
                                unsigned flags);
```

Description

Use the sasl_server_userdb_setpass_t() callback function to store or change a a plaintext password in the callback supplier's user database.

Parameters

conn

The SASL connection context.

context

The context from the callback record.

user

A null-terminated user name with user@realm syntax.

pass

The password to check. This string cannot be null-terminated.

passlen

The length of *pass*.

propctx

Auxiliary properties. The value of *propctx* is not stored.

flags

See [sasl_setpass\(3SASL\)](#). sasl_server_userdb_setpass_t() uses the same *flags* that are passed to sasl_setpass().

Return Values

Like other SASL callback functions, sasl_server_userdb_setpass_t() returns an integer that corresponds to a SASL error code. See <sasl.h> for a complete list of SASL error codes.

Errors

SASL_OK

The call to sasl_server_userdb_setpass_t() was successful.

See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes

See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also

[sasl_errors\(3SASL\)](#), [sasl_setpass\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_set_alloc – set the memory allocation functions used by the SASL library

Synopsis

```
cc [ flag ... ] file ... -lsasl [ library ... ]
#include <sasl/sasl.h>

void sasl_set_alloc(sasl_malloc_t *m, sasl_calloc_t *c, sasl_realloc_t *r,
    sasl_free_t *f);
```

Description Use the `sasl_set_alloc()` interface to set the memory allocation routines that the SASL library and plug-ins will use.

Parameters

- c* A pointer to a `calloc()` function
- f* A pointer to a `free()` function
- m* A pointer to an `amalloc()` function
- r* A pointer to a `realloc()` function

Return Values `sasl_set_alloc()` has no return values.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Obsolete
MT-Level	Unsafe

See Also [attributes\(5\)](#)

Notes While most of `libsasl` is MT-Safe, `sasl_set_*` modifies the global state and should be considered Unsafe.

Name sasl_seterror – set the error string

Synopsis

```
cc [ flag ... ] file ... -lsasl    [ library ... ]
#include <sasl/sasl.h>
```

```
void sasl_seterror(sasl_conn_t *conn, unsigned flags,
                  const char *fmt, ...);
```

Description The `sasl_seterror()` interface sets the error string that will be returned by [sasl_errdetail\(3SASL\)](#). Use [syslog\(3C\)](#) style formatting, that is, use `printf()`—style with `%m` as the most recent `errno` error.

The `sasl_seterror()` interface is primarily used by server callback functions and internal plug-ins, for example, with the `sasl_authorize_t` callback. The `sasl_seterror()` interface triggers a call to the SASL logging callback, if any, with a level of `SASL_LOG_FAIL`, unless the `SASL_NOLOG` flag is set.

Make the message string sensitive to the current language setting. If there is no `SASL_CB_LANGUAGE` callback, message strings must be `i-default`. Otherwise, UTF-8 is used. Use of *RFC 2482* for mixed-language text is encouraged.

If the value of `conn` is `NULL`, the `sasl_seterror()` interface fails.

Parameters *conn* The `sasl_conn_t` for which the call to `sasl_seterror()` applies.

flags If set to `SASL_NOLOG`, the call to `sasl_seterror()` is not logged.

fmt A [syslog\(3C\)](#) style format string.

Return Values `sasl_seterror()` has no return values.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [sasl_errdetail\(3SASL\)](#), [syslog\(3C\)](#), [attributes\(5\)](#)

Whistler, K. and Adams, G. *RFC 2482, Language Tagging in Unicode Plain Text*. Network Working Group. January 1999.

Name sasl_set_mutex – set the mutex lock functions used by the SASL library

Synopsis `cc [flag ...] file ... -lsasl [library ...]`
`#include <sasl/sasl.h>`

```
void sasl_set_mutex(sasl_mutex_alloc_t *a, sasl_mutex_lock_t *l,  
    sasl_mutex_unlock_t *u, sasl_mutex_free_t *f);
```

Description Use the `sasl_set_mutex()` interface to set the mutex lock routines that the SASL library and plug-ins will use.

Parameters *a* A pointer to the mutex lock allocation function
f A pointer to the mutex free or destroy function
l A pointer to the mutex lock function
u A pointer to the mutex unlock function

Return Values `sasl_set_mutex()` has no return values.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Obsolete
MT-Level	Unsafe

See Also [attributes\(5\)](#)

Notes While most of `libsasl` is MT-Safe, `sasl_set_*` modifies the global state and should be considered Unsafe.

Name sasl_setpass – set the password for a user

Synopsis `cc [flag ...] file ... -lsasl [library ...]`
`#include <sasl/sasl.h>`

```
int sasl_setpass(sasl_conn_t *conn, const char *user, const char *pass,
                unsigned passlen, const char *oldpass, unsigned oldpasslen,
                unsigned flags);
```

Description Use the `sasl_setpass()` interface to set passwords. `sasl_setpass()` uses the `SASL_CB_SERVER_USERDB_SETPASS` callback, if one is supplied. Additionally, if any server mechanism plugins supply a setpass callback, the setpass callback would be called. None of the server mechanism plugins currently supply a setpass callback.

Parameters

<i>conn</i>	The SASL connection context
<i>user</i>	The username for which the password is set
<i>pass</i>	The password to set
<i>passlen</i>	The length of <i>pass</i>
<i>oldpass</i>	The old password, which is optional
<i>oldpasslen</i>	The length of <i>oldpass</i> , which is optional
<i>flags</i>	Refers to flags, including, <code>SASL_SET_CREATE</code> and <code>SASL_SET_DISABLE</code> . Use these flags to create and disable accounts.

Return Values `sasl_setpass()` returns an integer that corresponds to a SASL error code.

Errors `SASL_OK` The call to `sasl_setpass()` was successful.

See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [sasl_errors\(3SASL\)](#), [sasl_getprop\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_setprop – set a SASL property

Synopsis `cc [flag ...] file ... -lsasl [library ...]`
`#include <sasl/sasl.h>`

```
int sasl_setprop(sasl_conn_t *conn, int propnum, const void *pvalue);
```

Description Use the `sasl_setprop()` interface to set the value of a SASL property. For example, an application can use `sasl_setprop()` to tell the SASL library about any external negotiated security layer like TLS.

`sasl_setprop()` uses the following flags.

SASL_AUTH_EXTERNAL	External authentication ID that is a pointer of type <code>const char</code>
SASL_SSF_EXTERNAL	External SSF active of type <code>sasl_ssf_t</code>
SASL_DEFUSERREALM	User realm that is a pointer of type <code>const char</code>
SASL_SEC_PROPS	<code>sasl_security_properties_t</code> , that can be freed after the call
SASL_IPLOCALPORT	A string that describes the local ip and port in the form <code>a.b.c.d:p</code> or <code>[e:f:g:h:i:j:k:l]:port</code> or one of the older forms, <code>a.b.c.d;p</code> or <code>e:f:g:j:i:j:k:l;port</code>
SASL_IPREMOTEPORT	A string that describes the remote ip and port in the form <code>a.b.c.d:p</code> or <code>[e:f:g:h:i:j:k:l]:port</code> or one of the older forms, <code>a.b.c.d;p</code> or <code>e:f:g:j:i:j:k:l;port</code>

Parameters

<i>conn</i>	The SASL connection context
<i>propnum</i>	The identifier for the property requested
<i>pvalue</i>	Contains a pointer to the data. The application must ensure that the data type is correct, or the application can crash.

Return Values `sasl_setprop()` returns an integer that corresponds to a SASL error code.

Errors SASL_OK The call to `sasl_setprop()` was successful.

See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_utf8verify – encode base64 string

Synopsis

```
cc [ flag ... ] file ... -lsasl  [ library ... ]
#include <sasl/saslutil.h>

int sasl_utf8verify(const char *str, unsigned len);
```

Description Use the `sasl_utf8verify()` interface to verify that a string is valid UTF-8 and does not contain NULL, a carriage return, or a linefeed. If `len == 0`, `strlen(str)` will be used.

Parameters *str* A string
len The length of the string

Return Values `sasl_utf8verify()` returns an integer that corresponds to a SASL error code.

Errors SASL_OK The call to `sasl_utf8verify()` was successful.
SASL_BADPROT There was invalid UTF-8, or an error was found.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [attributes\(5\)](#)

Name sasl_verifyfile_t – the SASL file verification callback function

Synopsis

```
cc [ flag ... ] file ... -lsasl    [ library ... ]
#include <sasl/sasl.h>
```

```
typedef enum {
    SASL_VRFY_PLUGIN,      /* a DLL/shared library plugin */
    SASL_VRFY_CONF,        /* a configuration file */
    SASL_VRFY_PASSWD,      /* a password storage file */
    SASL_VRFY_OTHER        /* some other file type */
} sasl_verify_ttype_t
```

```
int sasl_verifyfile_t(void *context, const char *file,
    sasl_verify_ttype_t type);
```

Description Use the sasl_verifyfile_t() callback function check whether a given file can be used by the SASL library. Applications use sasl_verifyfile_t() to check the environment to ensure that plugins or configuration files cannot be written to.

Parameters *context* The context from the callback record
file The full path of the file to verify
type The type of the file

Return Values Like other SASL callback functions, sasl_verifyfile_t() returns an integer that corresponds to a SASL error code. See <sasl.h> for a complete list of SASL error codes.

Errors SASL_OK The call to sasl_verifyfile_t() was successful.

See [sasl_errors\(3SASL\)](#) for information on SASL error codes.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [sasl_errors\(3SASL\)](#), [attributes\(5\)](#)

Name sasl_version – get SASL library version information

Synopsis

```
cc [ flag ... ] file ... -lsasl  [ library ... ]
#include <sasl/sasl.h>

void sasl_version(const char **implementation, int *version);
```

Description Use the sasl_version() interface to obtain the version of the SASL library.

Parameters *implementation* A vendor-defined string that describes the implementation. The value of *implementation* returned is Sun SASL.

version A vendor-defined representation of the version number.

Return Values The sasl_version() interface has no return values.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWlibsasl
Interface Stability	Evolving
MT-Level	MT-Safe

See Also [attributes\(5\)](#)

Name sctp_bindx – add or remove IP addresses to or from an SCTP socket

Synopsis

```
cc [ flag... ] file... -lsocket -lnsl -lsctp [ library... ]
#include <sys/types.h>
#include <sys/socket.h>
#include <netinet/sctp.h>
```

```
int sctp_bindx(int sock, void *addrs, int addrcnt, int flags);
```

Description The sctp_bindx() function adds or removes addresses to or from an SCTP socket. If *sock* is an Internet Protocol Version 4 (IPv4) socket, *addrs* should be an array of sockaddr_in structures containing IPv4 addresses. If *sock* is an Internet Protocol Version 6 (IPv6) socket, *addrs* should be an array of sockaddr_in6 structures containing IPv6 or IPv4-mapped IPv6 addresses. The *addrcnt* is the number of array elements in *addrs*. The family of the address type is used with *addrcnt* to determine the size of the array.

The *flags* parameter is a bitmask that indicates whether addresses are to be added or removed from a socket. The *flags* parameter is formed by bitwise OR of zero or more of the following flags:

SCTP_BINDX_ADD_ADDR	Indicates that addresses from <i>addrs</i> should be added to the SCTP socket.
SCTP_BINDX_REM_ADDR	Indicates that addresses from <i>addrs</i> should be removed from the SCTP socket.

These two flags are mutually exclusive. If *flags* is formed by a bitwise OR of both SCTP_BINDX_ADD_ADDR and SCTP_BINDX_REM_ADDR, the sctp_bindx() function will fail.

Prior to calling sctp_bindx() on an SCTP endpoint, the endpoint should be bound using [bind\(3SOCKET\)](#). On a listening socket, a special INADDR_ANY value for IP or an unspecified address of all zeros for IPv6 can be used in *addrs* to add all IPv4 or IPv6 addresses on the system to the socket. The sctp_bindx() function can also be used to add or remove addresses to or from an established association. In such a case, messages are exchanged between the SCTP endpoints to update the address lists for that association if both endpoints support dynamic address reconfiguration.

Return Values Upon successful completion, the sctp_bindx() function returns 0. Otherwise, the function returns -1 and sets errno to indicate the error.

Errors The sctp_bindx() call fails under the following conditions.

EBADF	The <i>sock</i> argument is an invalid file descriptor.
ENOTSOCK	The <i>sock</i> argument is not a socket.
EINVAL	One or more of the IPv4 or IPv6 addresses is invalid.
EINVAL	The endpoint is not bound.

EINVAL The last address is requested to be removed from an established association.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Evolving
MT-Level	Safe

See Also [bind\(3SOCKET\)](#), [in.h\(3HEAD\)](#), [libsctp\(3LIB\)](#), [listen\(3SOCKET\)](#),
[sctp_freeladdrs\(3SOCKET\)](#), [sctp_freepaddrs\(3SOCKET\)](#), [sctp_getladdrs\(3SOCKET\)](#),
[sctp_getpaddrs\(3SOCKET\)](#), [socket\(3SOCKET\)](#), [inet\(7P\)](#), [inet6\(7P\)](#), [ip\(7P\)](#), [ip6\(7P\)](#),
[sctp\(7P\)](#)

Name sctp_getladdr, sctp_freeladdr – returns all locally bound addresses on an SCTP socket

Synopsis

```
cc [ flag... ] file... -lsocket -lnsl -lsctp [ library... ]
#include <sys/types.h>
#include <sys/socket.h>
#include <netinet/sctp.h>
```

```
int sctp_getladdr(int sock, sctp_assoc_t id, void **addrs);
void sctp_freeladdr(void *addrs);
```

Description The sctp_getladdr() function queries addresses to which an SCTP socket is bound. The sctp_freeladdr() function releases resources that are allocated to hold the addresses.

The sctp_getladdr() function returns all the locally bound addresses on the SCTP socket *sock*. On completion *addrs* points to a dynamically allocated array of sockaddr_in structures for an Internet Protocol (IPv4) socket or an array of sockaddr_in6 structures for an Internet Protocol Version 6 (IPv6) socket. The *addrs* parameter must not be NULL. For an IPv4 SCTP socket, the addresses returned in the sockaddr_in structures are IPv4 addresses. For an IPv6 SCTP socket, the addresses in the sockaddr_in6 structures can be IPv6 addresses or IPv4-mapped IPv6 addresses.

If *sock* is a one-to-many style SCTP socket, *id* specifies the association of interest. A value of 0 to *id* returns locally-bound addresses regardless of a particular association. If *sock* is a one-to-one style SCTP socket, *id* is ignored.

The sctp_freeladdr() function frees the resources allocated by sctp_getladdr(). The *addrs* parameter is the array of addresses allocated by sctp_getladdr().

Return Values Upon successful completion, the sctp_getladdr() function returns the number of addresses in the *addrs* array. Otherwise, the function returns -1 and sets *errno* to indicate the error.

Errors The sctp_getladdr() call fails under the following conditions.

EBADF	The <i>sock</i> argument is an invalid file descriptor.
ENOTSOCK	The <i>sock</i> argument is not a socket.
EINVAL	The <i>addrs</i> argument is NULL.
EINVAL	The <i>id</i> argument is an invalid socket.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [bind\(3SOCKET\)](#), [in.h\(3HEAD\)](#), [libsctp\(3LIB\)](#), [sctp_freepaddrs\(3SOCKET\)](#), [sctp_getpaddrs\(3SOCKET\)](#), [socket\(3SOCKET\)](#), [attributes\(5\)](#), [inet\(7P\)](#), [inet6\(7P\)](#), [ip\(7P\)](#), [ip6\(7P\)](#), [sctp\(7P\)](#)

Name sctp_getpaddr, sctp_freepaddr – returns all peer addresses on an SCTP association

Synopsis

```
cc [ flag... ] file... -lsocket -lnsl -lsctp [ library... ]
#include <sys/types.h>
#include <sys/socket.h>
#include <netinet/sctp.h>
```

```
int sctp_getpaddr(int sock, sctp_assoc_t id, void **addrs);

void sctp_freepaddr(void *addrs);
```

Description The sctp_getpaddr() queries the peer addresses in an SCTP association. The sctp_freepaddr() function releases resources that are allocated to hold the addresses.

The sctp_getpaddr() function returns all the peer addresses in the SCTP association identified by *sock*. On completion *addrs* points to a dynamically allocated array of sockaddr_in structures for an Internet Protocol (IPv4) socket or an array of sockaddr_in6 structures for an Internet Protocol Version 6 (IPv6) socket. The *addrs* parameter must not be NULL. For an IPv4 SCTP socket, the addresses returned in the sockaddr_in structures are IPv4 addresses. For an IPv6 SCTP socket, the addresses in the sockaddr_in6 structures can be IPv6 addresses or IPv4-mapped IPv6 addresses.

If *sock* is a one-to-many style SCTP socket, *id* specifies the association of interest. If *sock* is a one-to-one style SCTP socket, *id* is ignored.

The sctp_freepaddr() function frees the resources allocated by sctp_getpaddr(). The *addrs* parameter is the array of addresses allocated by sctp_getpaddr().

Return Values Upon successful completion, the sctp_getpaddr() function returns the number of addresses in the *addrs* array. Otherwise, the function returns -1 and sets *errno* to indicate the error.

Errors The sctp_getpaddr() succeeds unless one of the following conditions exist.

EBADF	The <i>sock</i> argument is an invalid file descriptor.
ENOTSOCK	The <i>sock</i> argument is not a socket.
EINVAL	The <i>addrs</i> argument is NULL.
EINVAL	The <i>id</i> argument is an invalid association identifier for a one-to-many style STP socket.
ENOTCONN	The specified socket is not connected.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Committed

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Safe

See Also [bind\(3SOCKET\)](#), [in.h\(3HEAD\)](#), [libsctp\(3LIB\)](#), [sctp_freeladdrs\(3SOCKET\)](#), [sctp_getladdrs\(3SOCKET\)](#), [socket\(3SOCKET\)](#), [attributes\(5\)](#), [inet\(7P\)](#), [inet6\(7P\)](#), [ip\(7P\)](#), [ip6\(7P\)](#), [sctp\(7P\)](#)

Name sctp_opt_info – examine SCTP level options for an SCTP endpoint

Synopsis

```
cc [ flag... ] file... -lsocket -lnsl -lsctp [ library... ]
#include <sys/types.h>
#include <sys/socket.h>
#include <netinet/sctp.h>
```

```
int sctp_opt_info(int sock, sctp_assoc_t id, int opt, void *arg,
socklen_t *len);
```

Description The `sctp_opt_info()` returns SCTP level options associated with the SCTP socket *sock*. If *sock* is a one-to-many style socket, *id* refers to the association of interest. If *sock* is a one-to-one socket or if *sock* is a branched-off one-to-many style socket, *id* is ignored. The *opt* parameter specifies the SCTP option to get. The *arg* structure is an option-specific structure buffer allocated by the caller. The *len* parameter is the length of the option specified.

Following are the currently supported values for the *opt* parameter. When one of the options below specifies an association *id*, the *id* is relevant for only one-to-many style SCTP sockets. The association *id* can be ignored for one-to-one style or branched-off one-to-many style SCTP sockets.

SCTP_RTOINFO Returns the protocol parameters used to initialize and bind retransmission timeout (RTO) tunable. The following structure is used to access these parameters:

```
struct sctp_rtoinfo {
    sctp_assoc_t      srto_assoc_id;
    uint32_t          srto_initial;
    uint32_t          srto_max;
    uint32_t          srto_min;
};
```

where:	
srto_assoc_id	Association ID specified by the caller
srto_initial	Initial RTO value
srto_max	Maximum value for the RTO
srto_min	Minimum value for the RTO

SSCTP_ASSOCINFO Returns association-specific parameters. The following structure is used to access the parameters:

```
struct sctp_assocparams {
    sctp_assoc_t      sasoc_assoc_id;
    uint16_t          sasoc_asocmaxrxt;
    uint16_t          sasoc_number_peer_destinations;
    uint32_t          sasoc_peer_rwnd;
    uint32_t          sasoc_local_rwnd;
    uint32_t          sasoc_cookie_life;
};
```

where:

srto_assoc_id	Association ID specified by the caller
sasoc_asocmaxrxt	Maximum retransmission count for the association
sasoc_number_peer_destinations	Number of addresses the peer has
sasoc_peer_rwnd	Current value of the peer's receive window
sasoc_local_rwnd	Last reported receive window sent to the peer
sasoc_cookie_life	Association cookie lifetime used when issuing cookies

All parameters with time values are in milliseconds.

SCTP_DEFAULT_SEND_PARAM Returns the default set of parameters used by the `sendto()` function on this association. The following structure is used to access the parameters:

```
struct sctp_sndrcvinfo {
    uint16_t      sinfo_stream;
    uint16_t      sinfo_ssn;
    uint16_t      sinfo_flags;
    uint32_t      sinfo_ppid;
    uint32_t      sinfo_context;
    uint32_t      sinfo_timetolive;
    uint32_t      sinfo_tsn;
    uint32_t      sinfo_cumtsn;
    sctp_assoc_t  sinfo_assoc_id;
};
```

where:

sinfo_stream	Default stream for <code>sendmsg()</code>
sinfo_ssn	Always returned as 0
sinfo_flags	Default flags for <code>sendmsg()</code> that include the following: MSG_UNORDERED MSG_ADDR_OVER MSG_ABORT MSG_EOF MSG_PR_SCTP
sinfo_ppid	Default payload protocol identifier for <code>sendmsg()</code>
sinfo_context	Default context for <code>sendmsg()</code>
sinfo_timetolive	Time to live in milliseconds for a message on the sending side. The message expires if the sending side does not start the first transmission for the message within the specified time period. If the

	<p>sending side starts the first transmission before the time period expires, the message is sent as a normal reliable message. A value of 0 indicates that the message does not expire. When MSG_PR_SCTP is set in <code>sinfo_flags</code>, the message expires if it is not acknowledged within the time period.</p>
<code>sinfo_tsn</code>	Always returned as 0
<code>sinfo_cumtsn</code>	Always returned as 0
<code>sinfo_assoc_id</code>	Association ID specified by the caller
SCTP_PEER_ADDR_PARAMS	Returns the parameters for a specified peer address of the association. The following structure is used to access the parameters:
<pre> struct sctp_paddrparams { sctp_assoc_t spp_assoc_id; struct sockaddr_storage spp_address; uint32_t spp_hbinterval; uint16_t spp_pathmaxrxt; }; </pre>	
where:	
<code>spp_assoc_id</code>	Association ID specified by the caller
<code>spp_address</code>	Peer's address
<code>spp_hbinterval</code>	Heartbeat interval in milliseconds
<code>spp_pathmaxrxt</code>	Maximum number of retransmissions to an address before it is considered unreachable
SCTP_STATUS	Returns the current status information about the association. The following structure is used to access the parameters:
<pre> struct sctp_status { sctp_assoc_t sstat_assoc_id; int32_t sstat_state; uint32_t sstat_rwnd; uint16_t sstat_unackdata; uint16_t sstat_penddata; uint16_t sstat_instrms; uint16_t sstat_outstrms; uint16_t sstat_fragmentation_point; struct sctp_paddrinfo sstat_primary; }; </pre>	
where:	
<code>sstat_assoc_id</code>	Association ID specified by the caller
<code>sstat_state</code>	Current state of the association

which might be one of the following:

	SCTP_CLOSED
	SCTP_BOUND
	SCTP_LISTEN
	SCTP_COOKIE_WAIT
	SCTP_COOKIE_ECHOED
	SCTP_ESTABLISHED
	SCTP_SHUTDOWN_PENDING
	SCTP_SHUTDOWN_SENT
	SCTP_SHUTDOWN_RECEIVED
	SCTP_SHUTDOWN_ACK_SENT
sstat_rwnd	Current receive window of the association peer
sstat_unackdata	Number of unacked DATA chunks
sstat_penddata	Number of DATA chunks pending receipt
sstat_instrms	Number of inbound streams
sstat_outstrms	Number of outbound streams
sstat_fragmentation_point	Size at which SCTP fragmentation occurs
sstat_primary	Information about the primary peer address

sstat_primary has the following structure

```

struct sctp_paddrinfo {
    sctp_assoc_t      spinfo_assoc_id;
    struct sockaddr_storage spinfo_address;
    int32_t           spinfo_state;
    uint32_t          spinfo_cwnd;
    uint32_t          spinfo_srtt;
    uint32_t          spinfo_rto;
    uint32_t          spinfo_mtu;
};

```

where:

spinfo_assoc_id	Association ID specified by the caller
spinfo_address	Primary peer address
spinfo_state	State of the peer address: SCTP_ACTIVE or SCTP_INACTIVE
spinfo_cwnd	Congestion window of the peer address

<code>spinfo_srtt</code>	Smoothed round-trip time calculation of the peer address
<code>spinfo_rto</code>	Current retransmission timeout value of the peer address in milliseconds
<code>spinfo_mtu</code>	P-MTU of the address

Return Values Upon successful completion, the `sctp_opt_info()` function returns 0. Otherwise, the function returns -1 and sets `errno` to indicate the error.

Errors The `sctp_opt_info()` call fails under the following conditions.

EBADF	The <i>sock</i> argument is an invalid file descriptor.
ENOTSOCK	The <i>sock</i> argument is not a socket.
EINVAL	The association <i>id</i> is invalid for a one-to-many style SCTP socket.
EINVAL	The input buffer length is insufficient for the option specified.
EINVAL	The peer address is invalid or does not belong to the association.
EAFNOSUPPORT	The address family for the peer's address is other than <code>AF_INET</code> or <code>AF_INET6</code> .

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Evolving
MT-Level	Safe

See Also [in.h\(3HEAD\)](#), [libsctp\(3LIB\)](#), [getsockopt\(3SOCKET\)](#), [setsockopt\(3SOCKET\)](#), [socket\(3SOCKET\)](#), [inet\(7P\)](#), [inet6\(7P\)](#), [ip\(7P\)](#), [ip6\(7P\)](#), [sctp\(7P\)](#)

Name sctp_peeloff – branch off existing association from a one-to-many Sctp socket to create a one-to-one Stp socket

Synopsis

```
cc [ flag... ] file... -lsocket -lnsl -lsctp [ library... ]
#include <sys/types.h>
#include <sys/socket.h>
#include <netinet/sctp.h>

int sctp_peeloff(int sock, sctp_assoc_t id);
```

Description The sctp_peeloff() function branches off an existing association from a one-to-many style Sctp socket into a separate socket file descriptor. The resulting branched-off socket is a one-to-one style Sctp socket and is confined to operations allowed on a one-to-one style Sctp socket.

The *sock* argument is a one-to-many socket. The association specified by the *id* argument is branched off *sock*.

Return Values Upon successful completion, the sctp_peeloff() function returns the file descriptor that references the branched-off socket. The function returns -1 if an error occurs.

Errors The sctp_peeloff() function fails under the following conditions.

- EOPTNOTSUPP The *sock* argument is not a one-to-many style Sctp socket.
- EINVAL The *id* is 0 or greater than the maximum number of associations for *sock*.
- EMFILE Failure to create a new user file descriptor or file structure.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Evolving
MT-Level	Safe

See Also [in.h\(3HEAD\)](#), [libsctp\(3LIB\)](#), [socket\(3SOCKET\)](#), [sctp\(7P\)](#)

Name sctp_rcvmsg – receive message from an SCTP socket

Synopsis

```
cc [ flag... ] file... -lsocket -lnsl -lsctp [ library... ]
#include <sys/types.h>
#include <sys/socket.h>
#include <netinet/sctp.h>

ssize_t sctp_rcvmsg(int s, void *msg, size_t len, struct sockaddr *from,
    socklen_t *fromlen, struct sctp_sndrcvinfo *sinfo, int *msg_flags);
```

Description The sctp_rcvmsg() function receives a message from the SCTP endpoint *s*.

In addition to specifying the message buffer *msg* and the length *len* of the buffer, the following parameters can be set:

from Pointer to an address, filled in with the sender's address

fromlen Size of the buffer associated with the *from* parameter

sinfo Pointer to an sctp_sndrcvinfo structure, filled in upon the receipt of the message

msg_flags Message flags such as MSG_CTRUNC, MSG_NOTIFICATION, MSG_EOR

The *sinfo* parameter is filled in only when the caller has enabled sctp_data_io_events by calling setsockopt() with the socket option SCTP_EVENTS.

Return Values Upon successful completion, the sctp_rcvmsg() function returns the number of bytes received. The function returns -1 if an error occurs.

Errors The sctp_rcvmsg() function fails under the following conditions.

EBADF The *s* argument is an invalid file descriptor.

ENOTSOCK The *s* argument is not a socket.

EOPNOTSUPP MSG_OOB is set as a flag.

ENOTCONN There is no established association.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Evolving
MT-Level	Safe

See Also [accept\(3SOCKET\)](#), [bind\(3SOCKET\)](#), [connect\(3SOCKET\)](#), [in.h\(3HEAD\)](#), [libsctp\(3LIB\)](#), [listen\(3SOCKET\)](#), [rcvmsg\(3SOCKET\)](#), [sctp_opt_info\(3SOCKET\)](#), [setsockopt\(3SOCKET\)](#), [socket\(3SOCKET\)](#), [socket.h\(3HEAD\)](#), [sctp\(7P\)](#)

Name sctp_send – send message from an SCTP socket

Synopsis

```
cc [ flag... ] file... -lsocket -lnsl -lsctp [ library... ]  
#include <sys/types.h>  
#include <sys/socket.h>  
#include <netinet/sctp.h>
```

```
ssize_t sctp_send(int s, const void *msg, size_t *len,  
                 const struct sctp_sndrcvinfo *sinfo, int flags);
```

Description The sctp_send() function sends messages from one-to-one and one-to-many style SCTP endpoints. The following parameters can be set:

s Socket created by [socket\(3SOCKET\)](#)

msg Message to be sent

len Size of the message to be sent in bytes

The caller completes the *sinfo* parameter with values used to send a message. Such values might include the stream number, payload protocol identifier, time to live, and the SCTP message flag and context. For a one-to-many socket, the association ID can be specified in the *sinfo* parameter to send a message to the association represented in the ID.

Flags supported for sctp_send() are reserved for future use.

Return Values Upon successful completion, the sctp_send() function returns the number of bytes sent. The function returns -1 if an error occurs.

Errors The sctp_send() function fails under the following conditions.

EBADF The *s* argument is an invalid file descriptor.

ENOTSOCK The *s* argument is not a socket.

EOPNOTSUPP MSG_ABORT or MSG_EOF is set in the *sinfo_flags* field of *sinfo* for a one-to-one style SCTP socket.

EPIPE The socket is shutting down and no more writes are allowed.

EAGAIN The socket is non-blocking and the transmit queue is full.

ENOTCONN There is no established association.

EINVAL Control message length is incorrect.

EINVAL Specified destination address does not belong to the association.

EINVAL The *stream_no* is outside the number of outbound streams supported by the association.

EAFNOSUPPORT Address family of the specified destination address is other than AF_INET or AF_INET6.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Evolving
MT-Level	Safe

See Also [accept\(3SOCKET\)](#), [bind\(3SOCKET\)](#), [connect\(3SOCKET\)](#), [in.h\(3HEAD\)](#), [libsctp\(3LIB\)](#), [listen\(3SOCKET\)](#), [sctp_sendmsg\(3SOCKET\)](#), [sendmsg\(3SOCKET\)](#), [socket\(3SOCKET\)](#), [socket.h\(3HEAD\)](#), [sctp\(7P\)](#)

Name sctp_sendmsg – send message from an SCTP socket

Synopsis

```
cc [ flag... ] file... -lsocket -lnsl -lsctp [ library... ]  
#include <sys/types.h>  
#include <sys/socket.h>  
#include <netinet/sctp.h>  
  
ssize_t sctp_sendmsg(int s, const void *msg, size_t len,  
                    const struct sockaddr *to, socklen_t tolen, uint32_t ppid,  
                    uint32_t flags, uint16_t stream_no, uint32_t timetolive,  
                    uint32_t context);
```

Description The sctp_sendmsg() function sends a message from the SCTP endpoint *s*.

In addition to specifying *msg* as the message buffer and *len* as the length of the buffer, the following parameters can be set:

<i>to</i>	Destination address
<i>tolen</i>	Length of the destination address
<i>ppid</i>	Application-specified payload protocol identifier
<i>stream_no</i>	Target stream for the message
<i>timetolive</i>	Time period in milliseconds after which the message expires if transmission for the message has not been started. A value of 0 indicates that the message does not expire. When the MSG_PR_SCTP flag is set the message expires, even if transmission has started, unless the entire message is transmitted within the <i>timetolive</i> period.
<i>context</i>	Value returned when an error occurs in sending a message

The *flags* parameter is formed from the bitwise OR of zero or more of the following flags:

MSG_UNORDERED	This flag requests un-ordered delivery of the message. If this flag is clear the message is considered an ordered send.
MSG_ABORT	When set, this flag causes the specified association to abort by sending an ABORT to the peer. The flag is used only for one-to-many style SCTP socket associations.
MSG_EOF	When set, this flag invokes a graceful shutdown on a specified association. The flag is used only for one-to-many style SCTP socket associations.
MSG_PR_SCTP	This flag indicates that the message is treated as partially reliable. The message expires unless the entire message is successfully transmitted within the time period specified in the <i>timetolive</i> parameter.

MSG_PR_SCTP implements *timed reliability* service for SCTP messages. As yet, no common standard has been defined for the service and the interface is considered unstable.

The initial call to `sctp_sendmsg()` can be used to create an association, but it cannot be used subsequently on an existing association. Since `sctp_sendmsg()` always uses 0 internally as the association ID, it is not suitable for use on one-to-many sockets.

Return Values Upon successful completion, the `sctp_sendmsg()` function returns the number of bytes sent. The function returns -1 if an error occurs.

Errors The `sctp_sendmsg()` function will fail if:

EBADF	The <code>s</code> argument is an invalid file descriptor.
ENOTSOCK	The <code>s</code> argument is not a socket.
EOPNOTSUPP	MSG_OOB is set as a <i>flag</i> .
EOPNOTSUPP	MSG_ABORT or MSG_EOF is set on a one-to-one style SCTP socket.
EPIPE	The socket is shutting down and no more writes are allowed.
EAGAIN	The socket is non-blocking and the transmit queue is full.
ENOTCONN	There is no established association.
EINVAL	Control message length is incorrect.
EINVAL	Specified destination address does not belong to the association.
EAFNOSUPPORT	Address family of the specified destination address is other than AF_INET or AF_INET6.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also `accept(3SOCKET)`, `bind(3SOCKET)`, `connect(3SOCKET)`, `in.h(3HEAD)`, `libsctp(3LIB)`, `listen(3SOCKET)`, `sendmsg(3SOCKET)`, `socket(3SOCKET)`, `socket.h(3HEAD)`, [attributes\(5\)](#), [sctp\(7P\)](#)

Name sdp_add_origin, sdp_add_name, sdp_add_information, sdp_add_uri, sdp_add_email, sdp_add_phone, sdp_add_connection, sdp_add_bandwidth, sdp_add_repeat, sdp_add_time, sdp_add_zone, sdp_add_key, sdp_add_attribute, sdp_add_media – add specific SDP fields to the SDP session structure

Synopsis `cc [flag...] file... -lcommputil [library...]`
`#include <sdp.h>`

```
int sdp_add_origin(sdp_session_t *session, const char *name,
                  uint64_t id, uint64_t ver, const char *nettype,
                  const char *addrtype, const char *address);

int sdp_add_name(sdp_session_t *session, const char *name);

int sdp_add_information(char **information, const char *value);

int sdp_add_uri(sdp_session_t *session, const char *uri);

int sdp_add_email(sdp_session_t *session, const char *email);

int sdp_add_phone(sdp_session_t *session, const char *phone);

int sdp_add_connection(sdp_conn_t **conn, const char *nettype,
                      const char *addrtype, const char *address, uint8_t ttl,
                      int addrcount);

int sdp_add_bandwidth(sdp_bandwidth_t **bw, const char *type,
                     uint64_t value);

int sdp_add_repeat(sdp_time_t *time, uint64_t interval,
                  uint64_t duration, const char *offset);

int sdp_add_time(sdp_session_t *session, uint64_t starttime,
                uint64_t stoptime, sdp_time_t **time);

int sdp_add_zone(sdp_session_t *session, uint64_t time,
                const char *offset);

int sdp_add_key(sdp_key_t **key, const char *method,
               const char *enckey);

int sdp_add_attribute(sdp_attr_t **attr, const char *name,
                     const char *value);

int sdp_add_media(sdp_session_t *session, const char *name,
                 uint_t port, int portcount, const char *protocol,
                 const char *format, sdp_media_t **media);
```

Description The caller has to first call [sdp_new_session\(3COMMPUTIL\)](#) and get pointer to a session structure. Then that pointer is used as argument in the following functions and the session structure is constructed. Once the structure is built the caller converts it to a string representation using [sdp_session_to_str\(3COMMPUTIL\)](#).

The `sdp_add_origin()` function adds ORIGIN (o=) SDP field to the session structure (`sdp_session_t`) using *name*, *id*, *ver*, *nettype*, *addrtype*, and *address*.

The `sdp_add_name()` function adds NAME (s=) SDP field to the session structure (`sdp_session_t`) using *name*.

The `sdp_add_information()` function adds INFO (i=) SDP field to the session structure (`sdp_session_t`) or media structure (`sdp_media_t`) using *value*. Since this field can be either in the media section or the session section of an SDP description the caller has to pass `&session→s_info` or `&media→m_info` as the first argument.

The `sdp_add_uri()` function adds URI (u=) SDP field to the session structure (`sdp_session_t`) using *uri*.

The `sdp_add_email()` function adds EMAIL (e=) SDP field to the session structure (`sdp_session_t`) using *email*.

The `sdp_add_phone()` function adds PHONE (p=) SDP field to the session structure (`sdp_session_t`) using *phone*.

The `sdp_add_connection()` function adds CONNECTION (c=) SDP field to the session structure (`sdp_session_t`) or the media structure (`sdp_media_t`) using *nettype*, *addrtype*, *address*, *tll*, and *addrcount*. While adding an IP4 or IP6 unicast address the *tll* and *addrcount* should be set to 0. For multicast address the *tll* should be set a reasonable value (0 - 255) and *addrcount* cannot be 0. Also since this field can be either in the media section or the session section of an SDP description, the caller has to pass `&session→s_conn` or `&media→m_conn` as the first argument.

The `sdp_add_bandwidth()` function adds BANDWIDTH (b=) SDP field to the session structure (`sdp_session_t`) or the media structure (`sdp_media_t`) using *type* and *value*. Since this field can be either in the media section or the session section of an SDP description, the caller has to pass `&session→s_bw` or `&media→m_bw` as the first argument.

The `sdp_add_time()` function adds the TIME (t=) SDP field to the session structure using *starttime* and *stoptime*. The pointer to the newly created time structure is returned in *time*. This pointer is then used in `sdp_add_repeat()` function.

The `sdp_add_repeat()` function adds the REPEAT (r=) SDP field to the session structure using interval, duration and offset. Here, offset is a string holding one or more offset values, for example "60" or "60 1d 3h".

The `sdp_add_zone()` function adds the ZONE (z=) SDP field to the session structure using *time* and *offset*. To add multiple time and offset values in a single zone field, call this function once for each pair. See the example below.

The `sdp_add_key()` function adds the KEY (k=) SDP field to the session structure (`sdp_session_t`) or media structure (`sdp_media_t`) using *method* and *enckey*. Since this field can be either in the media section or the session section of an SDP description, the caller has to pass `&session→s_key` or `&media→m_key` as the first argument.

The `sdp_add_attribute()` function adds the ATTRIBUTE (a=) SDP field to the session structure (`sdp_session_t`) or media structure (`sdp_media_t`) using *name* and *value*. Since this field can be either in the media section or the session section of an SDP description, the caller has to pass `&session→s_attr` or `&media→m_attr` as the first argument.

The `sdp_add_media()` function adds the MEDIA (m=) SDP field to the session structure (`sdp_session_t`) using *name*, *port*, *portcount*, *protocol*, and *format*. Here, *format* is a string holding possibly more than one value, for example, "0 31 32 97". The pointer to the newly created media structure is returned in *media*. This pointer is then used to add SDP fields specific to that media section.

Return Values These functions return 0 on success and the appropriate error value on failure. The value of `errno` is not changed by these calls in the event of an error.

Errors These functions will fail if:

`EINVAL` Mandatory parameters are not provided (they are null).

`ENOMEM` The allocation of memory failed.

Examples **EXAMPLE 1** Build an SDP session structure

In the following example we see how to build an SDP session structure using the functions described on this manual page. We first get a pointer to `sdp_session_t` structure by calling `sdp_new_session()`. Then to this newly created structure we add various SDP fields. Once the structure is built we obtain a string representation of the structure using `sdp_session_to_str()` function. Since its caller responsibility to free the session we call `sdp_free_session()` towards the end.

```
/* SDP Message we will be building
"v=0\r\n\
o=Alice 2890844526 2890842807 IN IP4 10.47.16.5\r\n\
s=-\r\n\
i=A Seminar on the session description protocol\r\n\
u=http://www.example.com/seminars/sdp.pdf\r\n\
e=alice@example.com (Alice Smith)\r\n\
p=+1 911-345-1160\r\n\
c=IN IP4 10.47.16.5\r\n\
b=CT:1024\r\n\
t=2854678930 2854679000\r\n\
r=604800 3600 0 90000\r\n\
z=2882844526 -1h 2898848070 0h\r\n\
a=recvonly\r\n\
m=audio 49170 RTP/AVP 0\r\n\
i=audio media\r\n\
b=CT:1000\r\n\
k=prompt\r\n\
m=video 51372 RTP/AVP 99 90\r\n\
i=video media\r\n\
```

EXAMPLE 1 Build an SDP session structure *(Continued)*

```

a=rtpmap:99 h232-199/90000\r\n\
a=rtpmap:90 h263-1998/90000\r\n"
*/

#include stdio.h>
#include string.h>
#include errno.h>
#include sdp.h>

int main ()
{
    sdp_session_t      *my_sess;
    sdp_media_t        *my_media;
    sdp_time_t          *my_time;
    char *b_sdp;

    my_sess = sdp_new_session();
    if (my_sess == NULL) {
        return (ENOMEM);
    }
    my_sess->version = 0;
    if (sdp_add_name(my_sess, "-") != 0)
        goto err_ret;
    if (sdp_add_origin(my_sess, "Alice", 2890844526ULL, 2890842807ULL,
        "IN", "IP4", "10.47.16.5") != 0)
        goto err_ret;
    if (sdp_add_information(&my_sess->s_info, "A Seminar on the session"
        "description protocol") != 0)
        goto err_ret;
    if (sdp_add_uri (my_sess, "http://www.example.com/seminars/sdp.pdf")
        != 0)
        goto err_ret;
    if (sdp_add_email(my_sess, "alice@example.com (Alice smith)") != 0)
        goto err_ret;
    if (sdp_add_phone(my_sess, "+1 911-345-1160") != 0)
        goto err_ret;
    if (sdp_add_connection(&my_sess->s_conn, "IN", "IP4", "10.47.16.5",
        0, 0) != 0)
        goto err_ret;
    if (sdp_add_bandwidth(&my_sess->s_bw, "CT", 1024) != 0)
        goto err_ret;
    if (sdp_add_time(my_sess, 2854678930ULL, 2854679000ULL, &my_time)
        != 0)
        goto err_ret;
    if (sdp_add_repeat(my_time, 604800ULL, 3600ULL, "0 90000") != 0)

```

EXAMPLE 1 Build an SDP session structure *(Continued)*

```

        goto err_ret;
    if (sdp_add_zone(my_sess, 2882844526ULL, "-1h") != 0)
        goto err_ret;
    if (sdp_add_zone(my_sess, 2898848070ULL, "0h") != 0)
        goto err_ret;
    if (sdp_add_attribute(&my_sess->s_attr, "sendrecv", NULL) != 0)
        goto err_ret;
    if (sdp_add_media(my_sess, "audio", 49170, 1, "RTP/AVP",
                     "0", &my_media) != 0)
        goto err_ret;
    if (sdp_add_information(&my_media->m_info, "audio media") != 0)
        goto err_ret;
    if (sdp_add_bandwidth(&my_media->m_bw, "CT", 1000) != 0)
        goto err_ret;
    if (sdp_add_key(&my_media->m_key, "prompt", NULL) != 0)
        goto err_ret;
    if (sdp_add_media(my_sess, "video", 51732, 1, "RTP/AVP",
                     "99 90", &my_media) != 0)
        goto err_ret;
    if (sdp_add_information(&my_media->m_info, "video media") != 0)
        goto err_ret;
    if (sdp_add_attribute(&my_media->m_attr, "rtpmap",
                         "99 h232-199/90000") != 0)
        goto err_ret;
    if (sdp_add_attribute(&my_media->m_attr, "rtpmap",
                         "90 h263-1998/90000") != 0)
        goto err_ret;
    b_sdp = sdp_session_to_str(my_sess, &error);

    /*
     * b_sdp is the string representation of my_sess structure
     */

    free(b_sdp);
    sdp_free_session(my_sess);
    return (0);
err_ret:
    free(b_sdp);
    sdp_free_session(my_sess);
    return (1);
}

```

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [libcommputil\(3LIB\)](#), [sdp_new_session\(3COMMPUTIL\)](#), [sdp_parse\(3COMMPUTIL\)](#), [sdp_session_to_str\(3COMMPUTIL\)](#), [attributes\(5\)](#)

Name sdp_clone_session – clone an SDP session structure

Synopsis cc [*flag...*] *file...* -lcommputil [*library...*]
#include <sdp.h>

```
sdp_session_t *sdp_clone_session(const sdp_session_t *session);
```

Description The sdp_clone_session() function clones the input SDP session structure and returns the cloned structure. The resulting cloned structure has all the SDP fields from the input structure. The caller is responsible for freeing the returned cloned structure using sdp_free_session(), described on the [sdp_new_session\(3COMMPUTIL\)](#) manual page.

Return Values The sdp_clone_session() function returns the cloned structure on success and NULL on failure.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [libcommputil\(3LIB\)](#), [sdp_new_session\(3COMMPUTIL\)](#), [attributes\(5\)](#)

Name sdp_delete_all_field, sdp_delete_all_media_field – delete all SDP fields

Synopsis cc [*flag...*] *file...* -lcommputil [*library...*]
#include <sdp.h>

```
int sdp_delete_all_field(sdp_session_t *session,
                        const char field);

int sdp_delete_all_media_field(sdp_media_t *media,
                              const char field);
```

Description The sdp_delete_all_field() function deletes all the occurrences of the specified SDP field from the session structure. For example, if the session structure has 3 bandwidth (b=) fields, then when this function is called with SDP_BANDWIDTH_FIELD, all the three bandwidth fields are deleted from the session structure.

The sdp_delete_all_media_field() function deletes all the occurrences of the specified SDP field from the specified media structure. For example, if the caller wants to delete all the attribute fields in a media structure, calling this function with SDP_ATTRIBUTE_FIELD argument would delete all the attribute fields in the media structure.

Return Values Upon successful completion, these functions return 0. Otherwise, the appropriate error value is returned. The value of errno is not changed by these calls in the event of an error.

Errors These functions will fail if:

EINVAL The *session* or *media* argument is NULL or the field type is unknown.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTETYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [libcommputil\(3LIB\)](#), [attributes\(5\)](#)

Name sdp_delete_media, sdp_delete_attribute – delete the specified media or attribute from the appropriate list

Synopsis `cc [flag...] file... -lcommputil [library...]
#include <sdp.h>`

```
int sdp_delete_media(sdp_media_t **l_media, sdp_media_t *media);  
int sdp_delete_attribute(sdp_attr_t **l_attr, sdp_attr_t *attr);
```

Description The `sdp_delete_media()` function deletes the specified media from the media list. It is similar to deleting a node in a linked list. The function first finds the media that needs to be deleted using `sdp_find_media(3COMMPUTIL)`. The found media is then passed to `sdp_delete_media()` to delete it. The function frees the memory allocated to media structure after deleting it.

The `sdp_delete_attribute()` function deletes the specified attribute from the attribute list. It is similar to deleting a node in a linked list. The function first finds the attribute that needs to be deleted using `sdp_find_media_rtpmap(3COMMPUTIL)` or `sdp_find_attribute(3COMMPUTIL)`. The found attribute is then passed to `sdp_delete_attribute()` to delete it. The function frees the memory allocated to attribute structure after deleting it.

Return Values Upon successful completion, these functions return 0. Otherwise, the appropriate error value is returned. The value of `errno` is not changed by these calls in the event of an error.

Errors These functions will fail if:

EINVAL The mandatory input parameters are not provided or are NULL.

Attributes See `attributes(5)` for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also `libcommputil(3LIB)`, `sdp_find_attribute(3COMMPUTIL)`,
`sdp_find_media(3COMMPUTIL)`, `sdp_find_media_rtpmap(3COMMPUTIL)`,
`attributes(5)`

Name sdp_find_attribute – find the attribute from the attribute list

Synopsis cc [*flag...*] *file...* -lcommputil [*library...*]
#include <sdp.h>

```
sdp_attr_t *sdp_find_attribute(sdp_attr_t *attr, const char *name);
```

Description The sdp_find_attribute() function searches the attribute list *attr* for the specified attribute *name*. If the attribute is found it returns the pointer to that attribute. Otherwise it returns NULL.

Return Values The sdp_find_attribute() function returns the attribute (sdp_attr_t *) on success and NULL when the search fails or when mandatory input parameters are NULL.

Examples **EXAMPLE 1** An (incomplete) SDP description that contains one media section: audio.

```
m=audio 49170 RTP/AVP 0 8
a=rtpmap:0 PCMU/8000
a=rtpmap:8 PCMA/8000
a=sendonly
a=ptime:10000
a=maxptime:20000

/*
 * Assuming that above description is parsed using sdp_parse and that
 * the parsed structure is in "session" sdp_session_t structure.
 */

sdp_attr_t *ptime;
sdp_attr_t *max_ptime;
sdp_media_t *media = session->s_media;

if ((ptime = sdp_find_attribute(media->m_attr, "ptime")) == NULL)
    /* ptime attribute not present */
else if ((max_ptime = sdp_find_attribute(media->m_attr,
    "maxptime")) == NULL)
    /* max_ptime attribute not present */
```

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [libcommputil\(3LIB\)](#), [sdp_parse\(3COMMPUTIL\)](#), [attributes\(5\)](#)

Name sdp_find_media – find the specified media from the media list

Synopsis `cc [flag...] file... -lcommputil [library...]`
`#include <sdp.h>`

```
sdp_media_t *sdp_find_media(sdp_media_t *media, const char *name);
```

Description The `sdp_find_media()` function searches the media list for the media specified by *name*. If the media is found it returns the pointer to the media. Otherwise it returns NULL.

Return Values The `sdp_find_media()` function returns the media (`sdp_media_t *`) on success and NULL when the search fails or the mandatory input parameters are NULL.

Examples **EXAMPLE 1** An (incomplete) SDP description that contains two media sections: audio and video.

```
m=audio 49170 RTP/AVP 0 8
a=rtpmap:0 PCMU/8000
a=rtpmap:8 PCMA/8000
m=video 51372 RTP/AVP 31 32
a=rtpmap:31 H261/90000
a=rtpmap:32 MPV/90000

/*
 * Assuming that above description is parsed using sdp_parse() and that
 * the parsed structure is in "session" sdp_session_t structure.
 */

sdp_media_t      *my_media;
my_media = sdp_find_media(session->s_media, "video");

/*
 * my_media now points to the structure containg video media section
 * information
 */
```

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [libcommputil\(3LIB\)](#), [sdp_parse\(3COMMPUTIL\)](#), [attributes\(5\)](#)

Name sdp_find_media_rtpmap – find the rtpmap attribute in the specified media

Synopsis `cc [flag...] file... -lcommputil [library...]`
`#include <sdp.h>`

`sdp_attr_t *sdp_find_media_rtpmap(sdp_media_t *media,
const char *format);`

Description The sdp_find_media_rtpmap() function searches the attribute list of the specified media structure, *media*, for the specified *format*. If the search is successful a pointer to that *rtpmap* attribute is returned. Otherwise it returns NULL.

Return Values The sdp_find_media_rtpmap() function returns the attribute (sdp_attr_t *) on success and NULL when the search fails or the mandatory input parameters are NULL.

Examples **EXAMPLE 1** An (incomplete) SDP description that contains two media sections: audio and video.

```
m=audio 49170 RTP/AVP 0 8
a=rtpmap:0 PCMU/8000
a=rtpmap:8 PCMA/8000
m=video 51372 RTP/AVP 31 32
a=rtpmap:31 H261/90000
a=rtpmap:32 MPV/90000

/*
 * Assuming that above description is parsed using sdp_parse() and that
 * the parsed structure is in "session" sdp_session_t structure.
 */

sdp_media_t      *video;
sdp_attr_t       *mpv;

video = sdp_find_media(session->s_media, "video");
mpv = sdp_find_media_rtpmap(video, "32");

/*
 * Now the attribute structure sdp_attr_t, mpv will be having
 * values from the attribute field "a=rtpmap:32 MPV/90000"
 */
```

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [libcommputil\(3LIB\)](#), [sdp_parse\(3COMMPUTIL\)](#), [attributes\(5\)](#)

Name sdp_new_session, sdp_free_session – allocate a new SDP session structure

Synopsis cc [*flag...*] *file...* -lcommputil [*library...*]
#include <sdp.h>

```
sdp_session_t *sdp_new_session();  
  
void sdp_free_session(sdp_session_t *session);
```

Description The sdp_new_session() function allocates memory for an SDP session structure specified by *session*, assigns a version number to the session structure, and returns a new session structure. It is the responsibility of the user to free the memory allocated to the session structure using the sdp_free_session() function.

The sdp_free_session() function destroys the SDP session structure and frees the resources associated with it.

Return Values The sdp_new_session() function returns the newly allocated SDP session structure on success and NULL on failure.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [libcommputil\(3LIB\)](#), [attributes\(5\)](#)

Name sdp_parse – parse the SDP description

Synopsis `cc [flag...] file... -lcommputil [library...]
#include <sdp.h>`

```
int sdp_parse(const char *sdp_info, int len, int flags,  
             sdp_session_t **session, uint_t *p_error);
```

Description The `sdp_parse()` function parses the SDP description present in `sdp_info` and populates the `sdp_session_t` structure. The `len` argument specifies the length of the character buffer `sdp_info`. The `flags` argument is not used, but must be set to 0, otherwise the call fails with the error value of `EINVAL` and `*session` set to `NULL`. The function allocates the memory required for the `sdp_session_t` structure and hence the caller is responsible for freeing the parsed session structure (`sdp_session_t`) using `sdp_free_session()`, described on the [sdp_new_session\(3COMMPUTIL\)](#) manual page.

The `p_error` argument identifies any field that had a parsing error. It cannot be `NULL` and can take any of the following values:

<code>SDP_VERSION_ERROR</code>	<code>0x00000001</code>
<code>SDP_ORIGIN_ERROR</code>	<code>0x00000002</code>
<code>SDP_NAME_ERROR</code>	<code>0x00000004</code>
<code>SDP_INFO_ERROR</code>	<code>0x00000008</code>
<code>SDP_URI_ERROR</code>	<code>0x00000010</code>
<code>SDP_EMAIL_ERROR</code>	<code>0x00000020</code>
<code>SDP_PHONE_ERROR</code>	<code>0x00000040</code>
<code>SDP_CONNECTION_ERROR</code>	<code>0x00000080</code>
<code>SDP_BANDWIDTH_ERROR</code>	<code>0x00000100</code>
<code>SDP_TIME_ERROR</code>	<code>0x00000200</code>
<code>SDP_REPEAT_TIME_ERROR</code>	<code>0x00000400</code>
<code>SDP_ZONE_ERROR</code>	<code>0x00000800</code>
<code>SDP_KEY_ERROR</code>	<code>0x00001000</code>
<code>SDP_ATTRIBUTE_ERROR</code>	<code>0x00002000</code>
<code>SDP_MEDIA_ERROR</code>	<code>0x00004000</code>
<code>SDP_FIELDS_ORDER_ERROR</code>	<code>0x00008000</code>
<code>SDP_MISSING_FIELDS</code>	<code>0x00010000</code>

RFC 4566 states that the fields in the SDP description need to be in a strict order. If the fields are not in the order specified in the RFC, `SDP_FIELDS_ORDER_ERROR` will be set.

RFC 4566 mandates certain fields to be present in SDP description. If those fields are missing then `SDP_MISSING_FIELDS` will be set.

Applications can check for presence of parsing error using the bit-wise operators.

If there was an error on a particular field, that field information will not be in the `sdp_session_t` structure. Also, parsing continues even if there was a field with a parsing error.

The `sdp_session_t` structure is defined in the header file `<sdp.h>` and contains the following members:

```
typedef struct sdp_session {
    int            sdp_session_version; /* SDP session version */
    int            s_version;           /* SDP version field */
    sdp_origin_t   s_origin;            /* SDP origin field */
    char           s_name;              /* SDP name field */
    char           s_info;              /* SDP info field */
    char           s_uri;               /* SDP uri field */
    sdp_list_t     s_email;            /* SDP email field */
    sdp_list_t     s_phone;            /* SDP phone field */
    sdp_conn_t     s_conn;              /* SDP connection field */
    sdp_bandwidth_t s_bw;               /* SDP bandwidth field */
    sdp_time_t     s_time;              /* SDP time field */
    sdp_zone_t     s_zone;              /* SDP zone field */
    sdp_key_t      s_key;               /* SDP key field */
    sdp_attr_t     s_attr;              /* SDP attribute field */
    sdp_media_t    s_media;             /* SDP media field */
} sdp_session_t;
```

The `sdp_session_version` member is used to track the version of the structure. Initially it is set to `SDP_SESSION_VERSION_1` (= 1).

The `sdp_origin_t` structure contains the following members:

```
typedef struct sdp_origin {
    char           *o_username; /* username of the originating host */
    uint64_t       o_id;        /* session id */
    uint64_t       o_version;    /* version number of this session */
                                /* description */
    char           *o_nettype;   /* type of network */
    char           *o_addrtype;  /* type of the address */
    char           *o_address;   /* address of the machine from which */
                                /* session was created */
} sdp_origin_t;
```

The `sdp_conn_t` structure contains the following members:

```

typedef struct sdp_conn {
    char        *c_nettype; /* type of network */
    char        *c_addrtype; /* type of the address */
    char        *c_address; /* unicast-address or multicast */
                        /* address */
    int         c_addrcount; /* number of addresses (case of */
                        /* multicast address with layered */
                        /* encodings */
    struct sdp_conn *c_next; /* pointer to next connection */
                        /* structure; there could be several */
                        /* connection fields in SDP description */
    uint8_t     c_ttl; /* TTL value for IPV4 multicast address */
} sdp_conn_t;

```

The `sdp_bandwidth_t` structure contains the following members:

```

typedef struct sdp_bandwidth {
    char        *b_type; /* info needed to interpret b_value */
    uint64_t    b_value; /* bandwidth value */
    struct sdp_bandwidth *b_next; /* pointer to next bandwidth structure*/
                        /* (there could be several bandwidth */
                        /* fields in SDP description */
} sdp_bandwidth_t;

```

The `sdp_list_t` structure is a linked list of void pointers. This structure holds SDP fields like email and phone, in which case the void pointers point to character buffers. It to hold information in cases where the number of elements is not predefined (for example, offset (in repeat field) where void pointer holds integer values or format (in media field) where void pointers point to character buffers). The `sdp_list_t` structure is defined as:

```

typedef struct sdp_list {
    void        *value; /* string values in case of email, phone and */
                        /* format (in media field) or integer values */
                        /* in case of offset (in repeat field) */
    struct sdp_list *next; /* pointer to the next node in the list */
} sdp_list_t;

```

The `sdp_repeat_t` structure contains the following members:

```

typedef struct sdp_repeat {
    uint64_t    r_interval; /* repeat interval, e.g. 86400 seconds */
                        /* (1 day) */
    uint64_t    r_duration; /* duration of session, e.g. 3600 */
                        /* seconds (1 hour) */
    sdp_list_t  *r_offset; /* linked list of offset values; each */
                        /* represents offset from start-time */
                        /* in SDP time field */
    struct sdp_repeat *r_next; /* pointer to next repeat structure; */
                        /* there could be several repeat */
                        /* fields in SDP description */
} sdp_repeat_t;

```

The `sdp_repeat_t` structure will always be part of the time structure `sdp_time_t`, since the repeat field does not appear alone in SDP description and is always associated with the time field.

The `sdp_time_t` structure contains the following members:

```
typedef struct sdp_time {
    uint64_t      t_start; /* start-time for a session */
    uint64_t      t_stop;  /* end-time for a session */
    sdp_repeat_t  *t_repeat; /* points to the SDP repeat field */
    struct sdp_time *t_next; /* pointer to next time field; there */
                           /* could there could be several time */
                           /* fields in SDP description */
} sdp_time_t;
```

The `sdp_zone_t` structure contains the following members:

```
typedef struct sdp_zone {
    uint64_t      z_time; /* base time */
    char          *z_offset; /* offset added to z_time to determine */
                           /* session time; mainly used for daylight */
                           /* saving time conversions */
    struct sdp_zone *z_next; /* pointer to next zone field; there */
                           /* could be several <adjustment-time> */
                           /* <offset> pairs within a zone field */
} sdp_zone_t;
```

The `sdp_key_t` structure contains the following members:

```
typedef struct sdp_key {
    char *k_method; /* key type */
    char *k_enckey; /* encryption key */
} sdp_key_t;
```

The `sdp_attr_t` structure contains the following members:

```
typedef struct sdp_attr {
    char *a_name; /* name of the attribute */
    char *a_value; /* value of the attribute */
    struct sdp_attr *a_next; /* pointer to the next attribute */
                           /* structure; there could be several */
                           /* attribute fields within SDP description */
} sdp_attr_t;
```

The `sdp_media_t` structure contains the following members:

```
typedef struct sdp_media {
    char *m_name; /* name of the media such as "audio", */
                /* "video", "message" */
    uint_t m_port; /* transport layer port information */
    int m_portcount; /* number of ports in case of */
}
```

```

/* hierarchically encoded streams */
char      *m_proto; /* transport protocol */
sdp_list_t *m_format; /* media format description */
char      *m_info; /* media info field */
sdp_conn_t *m_conn; /* media connection field */
sdp_bandwidth_t *m_bw; /* media bandwidth field */
sdp_key_t *m_key; /* media key field */
sdp_attr_t *m_attr; /* media attribute field */
struct sdp_media *m_next; /* pointer to next media structure; */
/* there could be several media */
/* sections in SDP description */
sdp_session_t *m_session; /* pointer to the session structure */
} sdp_media_t;

```

Return Values The `sdp_parse()` function returns 0 on success and the appropriate error value on failure. The value of `errno` is not changed by these calls in the event of an error.

Errors The `sdp_parse()` function will fail if:

EINVAL Arguments to the function were invalid.

ENOMEM Memory allocation failed while parsing *sdp_info*.

Examples **EXAMPLE 1** `sdp_parse()` example

If the SDP description was

```

v=0\r\n
o=jdoe 23423423 234234234 IN IP4 192.168.1.1\r\n
s=SDP seminar\r\n
i=A seminar on the session description protocol\r\n
e=test@host.com
c=IN IP4 156.78.90.1\r\n
t=2873397496 2873404696\r\n

```

then after call to `sdp_parse()` function the `sdp_session_t` structure would be

```

session {
    sdp_session_version = 1
    s_version = 0
    s_origin {
        o_username = "jdoe"
        o_id = 23423423ULL
        o_version = 234234234ULL
        o_nettype = "IN"
        o_addrtype = "IP4"
        o_address = "192.168.1.1"
    }
    s_name = "SDP seminar"
    s_info = "A seminar on the session description protocol"
}

```

EXAMPLE 1 sdp_parse() example (Continued)

```
s_uri = (nil)
s_email {
    value = "test@host.com"
    next = (nil)
}
s_phone = (nil)
s_conn {
    c_nettype = "IN"
    c_addrtype = "IP4"
    c_address = "156.78.90.1"
    c_addrcount = 0
    c_ttl = 0
    c_next = (nil)
}
s_bw = (nil)
s_time {
    t_start = 2873397496ULL
    t_stop = 2873404696ULL
    t_repeat = (nil)
    t_next = (nil)
}
s_zone = (nil)
s_key = (nil)
s_attr = (nil)
s_media = (nil)
}
```

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [libcommputil\(3LIB\)](#), [sdp_new_session\(3COMMPUTIL\)](#), [attributes\(5\)](#)

Name sdp_session_to_str – return a string representation of a session structure

Synopsis

```
cc [ flag... ] file... -lcommputil [ library... ]
#include <sdp.h>

char *sdp_session_to_str(const sdp_session_t *session,
                        int *error);
```

Description The sdp_session_to_str() function returns the string representation of the SDP session structure *session*. The caller is responsible for freeing the returned string.

The function adds a CRLF at the end of each SDP field before appending that field to the string.

Return Values The sdp_session_to_str() function returns the relevant string on success and NULL otherwise.

If *error* is non-null, the location pointed by *error* is set to 0 on success or the error value on failure. The value of *errno* is not changed by these calls in the event of an error.

Errors The sdp_session_to_str() function will fail if:

EINVAL The input is null.

ENOMEM A memory allocation failure occurred.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe

See Also [libcommputil\(3LIB\)](#), [attributes\(5\)](#)

Name secure_rpc, authdes_getucrd, authdes_seccreate, getnetname, host2netname, key_decryptsession, key_encryptsession, key_gendes, key_setsecret, key_secretkey_is_set, netname2host, netname2user, user2netname – library routines for secure remote procedure calls

Synopsis `cc [flag...] file... -lnsl [library...]`
`#include <rpc/rpc.h>`
`#include <sys/types.h>`

```
int authdes_getucrd(const struct authdes_cred *adc, uid_t *uidp,
    gid_t *gidp, short *gidlenp, gid_t *gidlist);

AUTH *authdes_seccreate(const char *name, const uint_t window,
    const char *timehost, ckey);

int getnetname(char name [MAXNETNAMELEN+1]);

int host2netname(char name [MAXNETNAMELEN+1], const char *host,
    const char *domain);

int key_decryptsession(const char *remotename, des_block *deskey);

int key_encryptsession(const char *remotename, des_block *deskey);

int key_gendes(des_block *deskey);

int key_setsecret(const char *key);

int key_secretkey_is_set(void)

int netname2host(const char *name, char *host, const int hostlen);

int netname2user(const char *name, uid_t *uidp, gid_t *gidp, int *gidlenp,
    gid_t *gidlist [NGRPS]);

int user2netname(char name [MAXNETNAMELEN+1], const uid_t uid,
    const char *domain);
```

Description The RPC library functions allow C programs to make procedure calls on other machines across the network.

RPC supports various authentication flavors. Among them are:

AUTH_NONE	No authentication (none).
AUTH_SYS	Traditional UNIX-style authentication.
AUTH_DES	DES encryption-based authentication.

The `authdes_getucrd()` and `authdes_seccreate()` functions implement the AUTH_DES authentication style. The keyserver daemon [keyserv\(1M\)](#) must be running for the AUTH_DES authentication system to work and [keylogin\(1\)](#) must have been run. The AUTH_DES style of

authentication is discussed here. For information about the AUTH_NONE and AUTH_SYS flavors of authentication, refer to [rpc_clnt_auth\(3NSL\)](#). See [rpc\(3NSL\)](#) for the definition of the AUTH data structure.

The following functions documented on this page are MT-Safe. For the MT-levels of other authentication styles, see relevant man pages.

`authdes_getucred()` This is the first of two functions that interface to the RPC secure authentication system AUTH_DES. The second is the `authdes_seccreate()` function. The `authdes_getucred()` function is used on the server side to convert an AUTH_DES credential, which is operating system independent, to an AUTH_SYS credential. The `authdes_getucred()` function returns 1 if it succeeds, 0 if it fails.

The **uidp* parameter is set to the user's numerical ID associated with *adc*. The **gidp* parameter is set to the numerical ID of the user's group. The **gidlist* parameter contains the numerical IDs of the other groups to which the user belongs. The **gidlenp* parameter is set to the number of valid group ID entries specified by the **gidlist* parameter.

The `authdes_getucred()` function fails if the `authdes_cred` structure was created with the netname of a host. In such a case, `netname2host()` should be used to get the host name from the host netname in the `authdes_cred` structure.

`authdes_seccreate()` The second of two AUTH_DES authentication functions, the `authdes_seccreate()` function is used on the client side to return an authentication handle that enables the use of the secure authentication system. The first field, *name*, specifies the network name *netname* of the owner of the server process. The field usually represents a hostname derived from the `host2netname()` utility, but the field might also represent a user name converted with the `user2netname()` utility.

The second field, *window*, specifies the validity of the client credential in seconds. If the difference in time between the client's clock and the server's clock exceeds *window*, the server rejects the client's credentials and the clock will have to be resynchronized. A small window is more secure than a large one, but choosing too small a window increases the frequency of resynchronization due to clock drift.

The third parameter, *timehost*, is the host's name and is optional. If *timehost* is NULL, the authentication system

assumes that the local clock is always in sync with the *timehost* clock and does not attempt resynchronization. If a *timehost* is supplied, the system consults the remote time service whenever resynchronization is required. The *timehost* parameter is usually the name of the host on which the server is running.

The final parameter, *ckey*, is also optional. If *ckey* is `NULL`, the authentication system generates a random DES key to be used for the encryption of credentials. If *ckey* is supplied, it is used for encryption.

If `authdes_seccreate()` fails, it returns `NULL`.

`getnetname()`

This function returns the unique, operating system independent netname of the caller in the fixed-length array *name*. The function returns 1 if it succeeds and 0 if it fails.

`host2netname()`

This function converts a domain-specific hostname *host* to an operating system independent netname. The function returns 1 if it succeeds and 0 if it fails. The `host2netname()` function is the inverse of the `netname2host()` function. If the *domain* is `NULL`, `host2netname()` uses the default domain name of the machine. If *host* is `NULL`, it defaults to that machine itself. If *domain* is `NULL` and *host* is an NIS name such as `myhost.sun.example.com`, the `host2netname()` function uses the domain `sun.example.com` rather than the default domain name of the machine.

`key_decryptsession()`

This function is an interface to the keyserver daemon, which is associated with RPC's secure authentication system (`AUTH_DES` authentication). User programs rarely need to call `key_decryptsession()` or the associated functions `key_encryptsession()`, `key_gendes()`, and `key_setsecret()`.

The `key_decryptsession()` function takes a server netname *remotename* and a DES key *deskey*, and decrypts the key by using the the public key of the server and the secret key associated with the effective UID of the calling process. The `key_decryptsession()` function is the inverse of `key_encryptsession()` function.

`key_encryptsession()`

This function is a keyserver interface that takes a server netname *remotename* and a DES key *deskey*, and encrypts the key using the public key of the the server and the secret key

	<p>associated with the effective UID of the calling process. If the keyserver does not have a key registered for the UID, it falls back to using the secret key for the netname nobody unless this feature has been disabled. See keyserv(1M). The <code>key_encryptsession()</code> function is the inverse of <code>key_decryptsession()</code> function. The <code>key_encryptsession()</code> function returns 0 if it succeeds, -1 if it fails.</p>
<code>key_gendes()</code>	<p>This is a keyserver interface function used to ask the keyserver for a secure conversation key. Selecting a conversion key at random is generally not secure because the common ways of choosing random numbers are too easy to guess. The <code>key_gendes()</code> function returns 0 if it succeeds, -1 if it fails.</p>
<code>key_setsecret()</code>	<p>This is a keyserver interface function used to set the key for the effective UID of the calling process. This function returns 0 if it succeeds, -1 if it fails.</p>
<code>key_secretkey_is_set()</code>	<p>This is a keyserver interface function used to determine if a key has been set for the effective UID of the calling process. If the keyserver has a key stored for the effective UID of the calling process, the <code>key_secretkey_is_set()</code> function returns 1. Otherwise it returns 0.</p>
<code>netname2host()</code>	<p>This function converts an operating system independent netname <i>name</i> to a domain-specific hostname <i>host</i>. The <i>hostlen</i> parameter is the maximum size of <i>host</i>. The <code>netname2host()</code> function returns 1 if it succeeds and 0 if it fails. The function is the inverse of the <code>host2netname()</code> function.</p>
<code>netname2user()</code>	<p>This function converts an operating system independent netname to a domain-specific user ID. The <code>netname2user()</code> function returns 1 if it succeeds and 0 if it fails. The function is the inverse of the <code>user2netname()</code> function.</p> <p>The <i>*uidp</i> parameter is set to the user's numerical ID associated with <i>name</i>. The <i>*gidp</i> parameter is set to the numerical ID of the user's group. The <i>gidlist</i> parameter contains the numerical IDs of the other groups to which the user belongs. The <i>*gidlenp</i> parameter is set to the number of valid group ID entries specified by the <i>gidlist</i> parameter.</p>
<code>user2netname()</code>	<p>This function converts a domain-specific username to an operating system independent netname. The <code>user2netname()</code> function returns 1 if it succeeds and 0 if it fails. The function is</p>

the inverse of `netname2user()` function.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [chkey\(1\)](#), [keylogin\(1\)](#), [keyserv\(1M\)](#), [newkey\(1M\)](#), [rpc\(3NSL\)](#), [rpc_clnt_auth\(3NSL\)](#), [attributes\(5\)](#)

Name send, sendto, sendmsg – send a message from a socket

Synopsis cc [*flag...*] *file...* -lsocket -lnsl [*library...*]
 #include <sys/types.h>
 #include <sys/socket.h>

```
ssize_t send(int s, const void *msg, size_t len, int flags);

ssize_t sendto(int s, const void *msg, size_t len, int flags,
               const struct sockaddr *to, int tolen);

ssize_t sendmsg(int s, const struct msghdr *msg, int flags);
```

Description The send(), sendto(), and sendmsg() functions are used to transmit a message to another transport end-point. The send() function can be used only when the socket is in a connected state. See [connect\(3SOCKET\)](#). The sendto() and sendmsg() functions can be used at any time. The s socket is created with [socket\(3SOCKET\)](#).

The address of the target is supplied by to with a tolen parameter used to specify the size. The length of the message is supplied by the len parameter. For socket types such as SOCK_DGRAM and SOCK_RAW that require atomic messages, the error EMSGSIZE is returned and the message is not transmitted when it is too long to pass atomically through the underlying protocol. The same restrictions do not apply to SOCK_STREAM sockets.

A return value -1 indicates locally detected errors. It does not imply a delivery failure.

If the socket does not have enough buffer space available to hold a message, the send() function blocks the message, unless the socket has been placed in non-blocking I/O mode (see [fcntl\(2\)](#)). The [select\(3C\)](#) or [poll\(2\)](#) call can be used to determine when it is possible to send more data.

The flags parameter is formed from the bitwise OR of zero or more of the following:

MSG_OOB	Send <i>out-of-band</i> data on sockets that support this notion. The underlying protocol must also support <i>out-of-band</i> data. Only SOCK_STREAM sockets created in the AF_INET or the AF_INET6 address family support out-of-band data.
MSG_DONTROUTE	The SO_DONTROUTE option is turned on for the duration of the operation. It is used only by diagnostic or routing programs.

See [recv\(3SOCKET\)](#) for a description of the msghdr structure.

Return Values Upon successful completion, these functions return the number of bytes sent. Otherwise, they return -1 and set errno to indicate the error.

Errors The `send()`, `sendto()`, and `sendmsg()` functions return errors under the following conditions:

EBADF	<code>s</code> is not a valid file descriptor.
EINTR	The operation was interrupted by delivery of a signal before any data could be buffered to be sent.
EMSGSIZE	The socket requires that the message be sent atomically and the message is too long.
ENOMEM	Insufficient memory is available to complete the operation.
ENOSR	Insufficient STREAMS resources are available for the operation to complete.
ENOTSOCK	<code>s</code> is not a socket.
EWOULDBLOCK	The socket is marked non-blocking and the requested operation would block. <code>EWOULDBLOCK</code> is also returned when sufficient memory is not immediately available to allocate a suitable buffer. In such a case, the operation can be retried later.
ECONNREFUSED	The requested connection was refused by the peer. For connected IPv4 and IPv6 datagram sockets, this indicates that the system received an ICMP Destination Port Unreachable message from the peer in response to some prior transmission.

The `send()` and `sendto()` functions return errors under the following conditions:

EINVAL The `len` argument overflows a `ssize_t`.

The `sendto()` function returns errors under the following conditions:

EINVAL The value specified for the `tolen` parameter is not the size of a valid address for the specified address family.

EISCONN A destination address was specified and the socket is already connected.

The `sendmsg()` function returns errors under the following conditions:

EINVAL The `msg_iovlen` member of the `msg_hdr` structure pointed to by `msg` is less than or equal to 0, or the sum of the `iov_len` values in the `msg_iov` array overflows a `ssize_t`.

EINVAL One of the `iov_len` values in the `msg_iov` array member of the `msg_hdr` structure pointed to by `msg` is negative, or the sum of the `iov_len` values in the `msg_iov` array overflows a `ssize_t`.

The `send()` function returns errors under the following conditions:

EPIPE The socket is shut down for writing, or the socket is connection-mode and is no longer connected. In the latter case, if the socket is of type `SOCK_STREAM`, the `SIGPIPE` signal is generated to the calling thread.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	Safe

See Also [fcntl\(2\)](#), [poll\(2\)](#), [write\(2\)](#), [connect\(3SOCKET\)](#), [getsockopt\(3SOCKET\)](#), [recv\(3SOCKET\)](#), [select\(3C\)](#), [socket\(3SOCKET\)](#), [socket.h\(3HEAD\)](#), [attributes\(5\)](#)

Name send – send a message on a socket

Synopsis cc [*flag* ...] *file* ... -lxnet [*library* ...]
#include <sys/socket.h>

```
ssize_t send(int socket, const void *buffer, size_t length, int flags);
```

Parameters

<i>socket</i>	Specifies the socket file descriptor.
<i>buffer</i>	Points to the buffer containing the message to send.
<i>length</i>	Specifies the length of the message in bytes.
<i>flags</i>	Specifies the type of message transmission. Values of this argument are formed by logically OR'ing zero or more of the following flags:
MSG_EOR	Terminates a record (if supported by the protocol)
MSG_OOB	Sends out-of-band data on sockets that support out-of-band communications. The significance and semantics of out-of-band data are protocol-specific.

Description The `send()` function initiates transmission of a message from the specified socket to its peer. The `send()` function sends a message only when the socket is connected (including when the peer of a connectionless socket has been set via [connect\(3XNET\)](#)).

The length of the message to be sent is specified by the *length* argument. If the message is too long to pass through the underlying protocol, `send()` fails and no data is transmitted.

Successful completion of a call to `send()` does not guarantee delivery of the message. A return value of `-1` indicates only locally-detected errors.

If space is not available at the sending socket to hold the message to be transmitted and the socket file descriptor does not have `O_NONBLOCK` set, `send()` blocks until space is available. If space is not available at the sending socket to hold the message to be transmitted and the socket file descriptor does have `O_NONBLOCK` set, `send()` will fail. The [select\(3C\)](#) and [poll\(2\)](#) functions can be used to determine when it is possible to send more data.

The socket in use may require the process to have appropriate privileges to use the `send()` function.

Usage The `send()` function is identical to [sendto\(3XNET\)](#) with a null pointer *dest_len* argument, and to `write()` if no flags are used.

Return Values Upon successful completion, `send()` returns the number of bytes sent. Otherwise, `-1` is returned and `errno` is set to indicate the error.

Errors The `send()` function will fail if:

EAGAIN	
EWOULDBLOCK	The socket's file descriptor is marked <code>O_NONBLOCK</code> and the requested operation would block.
EBADF	The <i>socket</i> argument is not a valid file descriptor.
ECONNRESET	A connection was forcibly closed by a peer.
EDESTADDRREQ	The socket is not connection-mode and no peer address is set.
EFAULT	The <i>buffer</i> parameter can not be accessed.
EINTR	A signal interrupted <code>send()</code> before any data was transmitted.
EMSGSIZE	The message is too large be sent all at once, as the socket requires.
ENOTCONN	The socket is not connected or otherwise has not had the peer prespecified.
ENOTSOCK	The <i>socket</i> argument does not refer to a socket.
EOPNOTSUPP	The <i>socket</i> argument is associated with a socket that does not support one or more of the values set in <i>flags</i> .
EPIPE	The socket is shut down for writing, or the socket is connection-mode and is no longer connected. In the latter case, and if the socket is of type <code>SOCK_STREAM</code> , the <code>SIGPIPE</code> signal is generated to the calling thread.

The `send()` function may fail if:

EACCES	The calling process does not have the appropriate privileges.
EIO	An I/O error occurred while reading from or writing to the file system.
ENETDOWN	The local interface used to reach the destination is down.
ENETUNREACH	No route to the network is present.
ENOBUFS	Insufficient resources were available in the system to perform the operation.
ENOSR	There were insufficient STREAMS resources available for the operation to complete.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also `connect(3XNET)`, `getsockopt(3XNET)`, `poll(2)`, `recv(3XNET)`, `recvfrom(3XNET)`, `recvmsg(3XNET)`, `select(3C)`, `sendmsg(3XNET)`, `sendto(3XNET)`, `setsockopt(3XNET)`, `shutdown(3XNET)`, `socket(3XNET)`, `attributes(5)`, `standards(5)`

Name sendmsg – send a message on a socket using a message structure

Synopsis `cc [flag ...] file ... -lxnet [library ...]
#include <sys/socket.h>`

```
ssize_t sendmsg(int socket, const struct msghdr *message, int flags);
```

Parameters The function takes the following arguments:

<i>socket</i>	Specifies the socket file descriptor.
<i>message</i>	Points to a <code>msghdr</code> structure, containing both the destination address and the buffers for the outgoing message. The length and format of the address depend on the address family of the socket. The <code>msg_flags</code> member is ignored.
<i>flags</i>	Specifies the type of message transmission. The application may specify 0 or the following flag:
MSG_EOR	Terminates a record (if supported by the protocol)
MSG_OOB	Sends out-of-band data on sockets that support out-of-bound data. The significance and semantics of out-of-band data are protocol-specific.

Description The `sendmsg()` function sends a message through a connection-mode or connectionless-mode socket. If the socket is connectionless-mode, the message will be sent to the address specified by `msghdr`. If the socket is connection-mode, the destination address in `msghdr` is ignored.

The `msg_iov` and `msg_iovlen` fields of message specify zero or more buffers containing the data to be sent. `msg_iov` points to an array of `iovec` structures; `msg_iovlen` must be set to the dimension of this array. In each `iovec` structure, the `iov_base` field specifies a storage area and the `iov_len` field gives its size in bytes. Some of these sizes can be zero. The data from each storage area indicated by `msg_iov` is sent in turn.

Successful completion of a call to `sendmsg()` does not guarantee delivery of the message. A return value of `-1` indicates only locally-detected errors.

If space is not available at the sending socket to hold the message to be transmitted and the socket file descriptor does not have `O_NONBLOCK` set, `sendmsg()` function blocks until space is available. If space is not available at the sending socket to hold the message to be transmitted and the socket file descriptor does have `O_NONBLOCK` set, `sendmsg()` function will fail.

If the socket protocol supports broadcast and the specified address is a broadcast address for the socket protocol, `sendmsg()` will fail if the `SO_BROADCAST` option is not set for the socket.

The socket in use may require the process to have appropriate privileges to use the `sendmsg()` function.

Usage The `select(3C)` and `poll(2)` functions can be used to determine when it is possible to send more data.

Return Values Upon successful completion, `sendmsg()` function returns the number of bytes sent. Otherwise, `-1` is returned and `errno` is set to indicate the error.

Errors The `sendmsg()` function will fail if:

EAGAIN	
EWOULDBLOCK	The socket's file descriptor is marked <code>O_NONBLOCK</code> and the requested operation would block.
EAFNOSUPPORT	Addresses in the specified address family cannot be used with this socket.
EBADF	The <i>socket</i> argument is not a valid file descriptor.
ECONNRESET	A connection was forcibly closed by a peer.
EFAULT	The <i>message</i> parameter, or storage pointed to by the <i>msg_name</i> , <i>msg_control</i> or <i>msg_iov</i> fields of the <i>message</i> parameter, or storage pointed to by the <i>iovec</i> structures pointed to by the <i>msg_iov</i> field can not be accessed.
EINTR	A signal interrupted <code>sendmsg()</code> before any data was transmitted.
EINVAL	The sum of the <i>iov_len</i> values overflows an <code>ssize_t</code> .
EMSGSIZE	The message is too large to be sent all at once (as the socket requires), or the <i>msg_iovlen</i> member of the <i>msg_hdr</i> structure pointed to by <i>message</i> is less than or equal to 0 or is greater than <code>IOV_MAX</code> .
ENOTCONN	The socket is connection-mode but is not connected.
ENOTSOCK	The <i>socket</i> argument does not refer a socket.
EOPNOTSUPP	The <i>socket</i> argument is associated with a socket that does not support one or more of the values set in <i>flags</i> .
EPIPE	The socket is shut down for writing, or the socket is connection-mode and is no longer connected. In the latter case, and if the socket is of type <code>SOCK_STREAM</code> , the <code>SIGPIPE</code> signal is generated to the calling thread.

If the address family of the socket is `AF_UNIX`, then `sendmsg()` will fail if:

EIO	An I/O error occurred while reading from or writing to the file system.
ELOOP	Too many symbolic links were encountered in translating the pathname in the socket address.

ENAMETOOLONG	A component of a pathname exceeded NAME_MAX characters, or an entire pathname exceeded PATH_MAX characters.
ENOENT	A component of the pathname does not name an existing file or the pathname is an empty string.
ENOTDIR	A component of the path prefix of the pathname in the socket address is not a directory.
The sendmsg() function may fail if:	
EACCES	Search permission is denied for a component of the path prefix; or write access to the named socket is denied.
EDESTADDRREQ	The socket is not connection-mode and does not have its peer address set, and no destination address was specified.
EHOSTUNREACH	The destination host cannot be reached (probably because the host is down or a remote router cannot reach it).
EIO	An I/O error occurred while reading from or writing to the file system.
EISCONN	A destination address was specified and the socket is already connected.
ENETDOWN	The local interface used to reach the destination is down.
ENETUNREACH	No route to the network is present.
ENOBUFS	Insufficient resources were available in the system to perform the operation.
ENOMEM	Insufficient memory was available to fulfill the request.
ENOSR	There were insufficient STREAMS resources available for the operation to complete.

If the address family of the socket is AF_UNIX, then sendmsg() may fail if:

ENAMETOOLONG	Pathname resolution of a symbolic link produced an intermediate result whose length exceeds PATH_MAX.
--------------	---

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also [poll\(2\)](#), [getsockopt\(3XNET\)](#), [recv\(3XNET\)](#), [recvfrom\(3XNET\)](#), [recvmsg\(3XNET\)](#), [select\(3C\)](#), [send\(3XNET\)](#), [sendto\(3XNET\)](#), [setsockopt\(3XNET\)](#), [shutdown\(3XNET\)](#), [socket\(3XNET\)](#), [attributes\(5\)](#), [standards\(5\)](#)

Name sendto – send a message on a socket

Synopsis `cc [flag...] file... -lxnet [library ...]
#include <sys/socket.h>`

```
ssize_t sendto(int socket, const void *message, size_t length, int flags,  
               const struct sockaddr *dest_addr, socklen_t dest_len);
```

Description The `sendto()` function sends a message through a connection-mode or connectionless-mode socket. If the socket is connectionless-mode, the message will be sent to the address specified by `dest_addr`. If the socket is connection-mode, `dest_addr` is ignored.

If the socket protocol supports broadcast and the specified address is a broadcast address for the socket protocol, `sendto()` will fail if the `SO_BROADCAST` option is not set for the socket.

The `dest_addr` argument specifies the address of the target. The `length` argument specifies the length of the message.

Successful completion of a call to `sendto()` does not guarantee delivery of the message. A return value of `-1` indicates only locally-detected errors.

If space is not available at the sending socket to hold the message to be transmitted and the socket file descriptor does not have `O_NONBLOCK` set, `sendto()` blocks until space is available. If space is not available at the sending socket to hold the message to be transmitted and the socket file descriptor does have `O_NONBLOCK` set, `sendto()` will fail.

The socket in use may require the process to have appropriate privileges to use the `sendto()` function.

Parameters The function takes the following arguments:

<i>socket</i>	Specifies the socket file descriptor.				
<i>message</i>	Points to a buffer containing the message to be sent.				
<i>length</i>	Specifies the size of the message in bytes.				
<i>flags</i>	Specifies the type of message transmission. Values of this argument are formed by logically OR'ing zero or more of the following flags: <table data-bbox="511 1258 1336 1402"> <tr> <td>MSG_EOR</td><td>Terminates a record (if supported by the protocol)</td></tr> <tr> <td>MSG_OOB</td><td>Sends out-of-band data on sockets that support out-of-band data. The significance and semantics of out-of-band data are protocol-specific.</td></tr> </table>	MSG_EOR	Terminates a record (if supported by the protocol)	MSG_OOB	Sends out-of-band data on sockets that support out-of-band data. The significance and semantics of out-of-band data are protocol-specific.
MSG_EOR	Terminates a record (if supported by the protocol)				
MSG_OOB	Sends out-of-band data on sockets that support out-of-band data. The significance and semantics of out-of-band data are protocol-specific.				
<i>dest_addr</i>	Points to a <code>sockaddr</code> structure containing the destination address. The length and format of the address depend on the address family of the socket.				
<i>dest_len</i>	Specifies the length of the <code>sockaddr</code> structure pointed to by the <code>dest_addr</code> argument.				

Usage The `select(3C)` and `poll(2)` functions can be used to determine when it is possible to send more data.

Return Values Upon successful completion, `sendto()` returns the number of bytes sent. Otherwise, `-1` is returned and `errno` is set to indicate the error.

Errors The `sendto()` function will fail if:

EAFNOSUPPORT	Addresses in the specified address family cannot be used with this socket.
EAGAIN	
EWouldBlock	The socket's file descriptor is marked <code>O_NONBLOCK</code> and the requested operation would block.
EBADF	The <i>socket</i> argument is not a valid file descriptor.
ECONNRESET	A connection was forcibly closed by a peer.
EFAULT	The <i>message</i> or <i>destaddr</i> parameter cannot be accessed.
EINTR	A signal interrupted <code>sendto()</code> before any data was transmitted.
EMSGSIZE	The message is too large to be sent all at once, as the socket requires.
ENOTCONN	The socket is connection-mode but is not connected.
ENOTSOCK	The <i>socket</i> argument does not refer to a socket.
EOPNOTSUPP	The <i>socket</i> argument is associated with a socket that does not support one or more of the values set in <i>flags</i> .
EPIPE	The socket is shut down for writing, or the socket is connection-mode and is no longer connected. In the latter case, and if the socket is of type <code>SOCK_STREAM</code> , the <code>SIGPIPE</code> signal is generated to the calling thread.

If the address family of the socket is `AF_UNIX`, then `sendto()` will fail if:

EIO	An I/O error occurred while reading from or writing to the file system.
ELOOP	Too many symbolic links were encountered in translating the pathname in the socket address.
ENAMETOOLONG	A component of a pathname exceeded <code>NAME_MAX</code> characters, or an entire pathname exceeded <code>PATH_MAX</code> characters.
ENOENT	A component of the pathname does not name an existing file or the pathname is an empty string.
ENOTDIR	A component of the path prefix of the pathname in the socket address is not a directory.

The `sendto()` function may fail if:

EACCES	Search permission is denied for a component of the path prefix; or write access to the named socket is denied.
EDESTADDRREQ	The socket is not connection-mode and does not have its peer address set, and no destination address was specified.
EHOSTUNREACH	The destination host cannot be reached (probably because the host is down or a remote router cannot reach it).
EINVAL	The <i>dest_len</i> argument is not a valid length for the address family.
EIO	An I/O error occurred while reading from or writing to the file system.
EISCONN	A destination address was specified and the socket is already connected.
ENETDOWN	The local interface used to reach the destination is down.
ENETUNREACH	No route to the network is present.
ENOBUFS	Insufficient resources were available in the system to perform the operation.
ENOMEM	Insufficient memory was available to fulfill the request.
ENOSR	There were insufficient STREAMS resources available for the operation to complete.

If the address family of the socket is AF_UNIX, then `sendto()` may fail if:

ENAMETOOLONG	Pathname resolution of a symbolic link produced an intermediate result whose length exceeds PATH_MAX.
--------------	---

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also [poll\(2\)](#), [getsockopt\(3XNET\)](#), [recv\(3XNET\)](#), [recvfrom\(3XNET\)](#), [recvmsg\(3XNET\)](#), [select\(3C\)](#), [send\(3XNET\)](#), [sendmsg\(3XNET\)](#), [setsockopt\(3XNET\)](#), [shutdown\(3XNET\)](#), [socket\(3XNET\)](#), [attributes\(5\)](#), [standards\(5\)](#)

Name setsockopt – set the socket options

Synopsis `cc [flag...] file... -lxnet [library...]
#include <sys/socket.h>`

```
int setsockopt(int socket, int level, int option_name,  
               const void*option_value, socklen_t option_len);
```

Description The `setsockopt()` function sets the option specified by the *option_name* argument, at the protocol level specified by the *level* argument, to the value pointed to by the *option_value* argument for the socket associated with the file descriptor specified by the *socket* argument.

The *level* argument specifies the protocol level at which the option resides. To set options at the socket level, specify the *level* argument as `SOL_SOCKET`. To set options at other levels, supply the appropriate protocol number for the protocol controlling the option. For example, to indicate that an option will be interpreted by the TCP (Transport Control Protocol), set *level* to the protocol number of TCP, as defined in the `<netinet/in.h>` header, or as determined by using [getprotobyname\(3XNET\)](#).

The *option_name* argument specifies a single option to set. The *option_name* argument and any specified options are passed uninterpreted to the appropriate protocol module for interpretations. The `<sys/socket.h>` header defines the socket level options. The options are as follow

SO_DEBUG Turns on recording of debugging information. This option enables or disables debugging in the underlying protocol modules. This option takes an `int` value. This is a boolean option.

SO_BROADCAST Permits sending of broadcast messages, if this is supported by the protocol. This option takes an `int` value. This is a boolean option.

SO_REUSEADDR Specifies that the rules used in validating addresses supplied to [bind\(3XNET\)](#) should allow reuse of local addresses, if this is supported by the protocol. This option takes an `int` value. This is a boolean option.

SO_KEEPALIVE Keeps connections active by enabling the periodic transmission of messages, if this is supported by the protocol. This option takes an `int` value.

If the connected socket fails to respond to these messages, the connection is broken and threads writing to that socket are notified with a `SIGPIPE` signal.

This is a boolean option.

SO_LINGER Lingers on a [close\(2\)](#) if data is present. This option controls the action taken when unsent messages queue on a socket and [close\(2\)](#) is performed. If `SO_LINGER` is set, the system blocks the process during [close\(2\)](#) until it can transmit the data or until the time expires. If

	SO_LINGER is not specified, and <code>close(2)</code> is issued, the system handles the call in a way that allows the process to continue as quickly as possible. This option takes a <code>linger</code> structure, as defined in the <code><sys/socket.h></code> header, to specify the state of the option and linger interval.
SO_OOBINLINE	Leaves received out-of-band data (data marked urgent) in line. This option takes an <code>int</code> value. This is a boolean option.
SO_SNDBUF	Sets send buffer size. This option takes an <code>int</code> value.
SO_RCVBUF	Sets receive buffer size. This option takes an <code>int</code> value.
SO_DONTROUTE	Requests that outgoing messages bypass the standard routing facilities. The destination must be on a directly-connected network, and messages are directed to the appropriate network interface according to the destination address. The effect, if any, of this option depends on what protocol is in use. This option takes an <code>int</code> value. This is a boolean option.
SO_MAC_EXEMPT	Sets the mandatory access control on the socket. A socket that has this option enabled can communicate with an unlabeled peer if the socket is in the global zone or has a label that dominates the default label of the peer. Otherwise, the socket must have a label that is equal to the default label of the unlabeled peer. <code>SO_MAC_EXEMPT</code> is a boolean option that is available only when the system is configured with Trusted Extensions.
SO_ALLZONES	Bypasses zone boundaries (privileged). This option stores an <code>int</code> value. This is a boolean option.

The `SO_ALLZONES` option can be used to bypass zone boundaries between shared-IP zones. Normally, the system prevents a socket from being bound to an address that is not assigned to the current zone. It also prevents a socket that is bound to a wildcard address from receiving traffic for other zones. However, some daemons which run in the global zone might need to send and receive traffic using addresses that belong to other shared-IP zones. If set before a socket is bound, `SO_ALLZONES` causes the socket to ignore zone boundaries between shared-IP zones and permits the socket to be bound to any address assigned to the shared-IP zones. If the socket is bound to a wildcard address, it receives traffic intended for all shared-IP zones and behaves as if an equivalent socket were bound in each active shared-IP zone. Applications that use the `SO_ALLZONES` option to initiate connections or send datagram traffic should specify the source address for outbound traffic by binding to a specific address. There is no effect from setting this option in an exclusive-IP zone. Setting this option requires the `sys_net_config` privilege. See [zones\(5\)](#).

For boolean options, 0 indicates that the option is disabled and 1 indicates that the option is enabled.

Options at other protocol levels vary in format and name.

Usage The `setsockopt()` function provides an application program with the means to control socket behavior. An application program can use `setsockopt()` to allocate buffer space, control timeouts, or permit socket data broadcasts. The `<sys/socket.h>` header defines the socket-level options available to `setsockopt()`.

Options may exist at multiple protocol levels. The `SO_` options are always present at the uppermost socket level.

Return Values Upon successful completion, `setsockopt()` returns 0. Otherwise, -1 is returned and `errno` is set to indicate the error.

Errors The `setsockopt()` function will fail if:

- EBADF** The *socket* argument is not a valid file descriptor.
- EDOM** The send and receive timeout values are too big to fit into the timeout fields in the socket structure.
- EFAULT** The *option_value* parameter can not be accessed or written.
- EINVAL** The specified option is invalid at the specified socket level or the socket has been shut down.
- EISCONN** The socket is already connected, and a specified option can not be set while the socket is connected.
- ENOPROTOOPT** The option is not supported by the protocol.
- ENOTSOCK** The *socket* argument does not refer to a socket.

The `setsockopt()` function may fail if:

- ENOMEM** There was insufficient memory available for the operation to complete.
- ENOBUFS** Insufficient resources are available in the system to complete the call.
- ENOSR** There were insufficient STREAMS resources available for the operation to complete.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [bind\(3XNET\)](#), [endprotoent\(3XNET\)](#), [getsockopt\(3XNET\)](#), [socket\(3XNET\)](#), [attributes\(5\)](#), [standards\(5\)](#)

Name shutdown – shut down part of a full-duplex connection

Synopsis `cc [flag...] file... -lsocket -lnsl [library...]`
`#include <sys/socket.h>`

`int shutdown(int s, int how);`

Description The `shutdown()` call shuts down all or part of a full-duplex connection on the socket associated with *s*. If *how* is `SHUT_RD`, further receives are disallowed. If *how* is `SHUT_WR`, further sends are disallowed. If *how* is `SHUT_RDWR`, further sends and receives are disallowed.

The *how* values should be defined constants.

Return Values 0 is returned if the call succeeds.

−1 is returned if the call fails.

Errors The call succeeds unless one of the following conditions exists:

- `EBADF` The *s* value is not a valid file descriptor.
- `ENOMEM` Insufficient user memory is available for the operation to complete.
- `ENOSR` Insufficient STREAMS resources are available for the operation to complete.
- `ENOTCONN` The specified socket is not connected.
- `ENOTSOCK` The *s* value is not a socket.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Safe

See Also [connect\(3SOCKET\)](#), [socket\(3SOCKET\)](#), [socket.h\(3HEAD\)](#), [attributes\(5\)](#)

Name shutdown – shut down socket send and receive operations

Synopsis `cc [flag ...] file ... -lxnet [library ...]`
`#include <sys/socket.h>`

`int shutdown(int socket, int how);`

Description The `shutdown()` function disables subsequent `send()` and `receive()` operations on a socket, depending on the value of the *how* argument.

Parameters *how* Specifies the type of shutdown. The values are as follows:

SHUT_RD	Disables further receive operations.
SHUT_WR	Disables further send operations.
SHUT_RDWR	Disables further send and receive operations.

socket Specifies the file descriptor of the socket.

Return Values Upon successful completion, `shutdown()` returns 0. Otherwise, `-1` is returned and `errno` is set to indicate the error.

Errors The `shutdown()` function will fail if:

EBADF	The <i>socket</i> argument is not a valid file descriptor.
EINVAL	The <i>how</i> argument is invalid.
ENOTCONN	The socket is not connected.
ENOTSOCK	The <i>socket</i> argument does not refer to a socket.

The `shutdown()` function may fail if:

ENOBUFS	Insufficient resources were available in the system to perform the operation.
ENOSR	There were insufficient STREAMS resources available for the operation to complete.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also [getsockopt\(3XNET\)](#), [recv\(3XNET\)](#), [recvfrom\(3XNET\)](#), [recvmsg\(3XNET\)](#), [select\(3C\)](#), [send\(3XNET\)](#), [sendto\(3XNET\)](#), [setsockopt\(3XNET\)](#), [socket\(3XNET\)](#), [attributes\(5\)](#), [standards\(5\)](#)

Name sip_add_branchid_to_via – add a branch parameter to the topmost VIA header in the SIP message

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

```
int sip_add_branchid_to_via(sip_msg_t sip_msg, char *branchid);
```

Description The sip_add_branchid_to_via() function adds a branch *param* to the topmost VIA header in the SIP message *sip_msg*. Note that a new header is created as a result of adding the branch parameter and the old header is marked deleted. Applications with multiple threads working on the same VIA header need to take note of this.

Return Values These functions return 0 on success and the appropriate error value on failure.

Errors On failure, functions that return an error value may return one of the following:

EINVAL Mandatory parameters are not provided, i.e. null.

For sip_add_branchid_to_via(), the topmost VIA header already has a branch *param* or the SIP message does not have a VIA header.

EPERM The message cannot be modified.

ENOMEM There is an error allocating memory for creating headers/parameters.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_add_from, sip_add_to, sip_add_contact, sip_add_via, sip_add_maxforward, sip_add_callid, sip_add_cseq, sip_add_content_type, sip_add_content, sip_add_accept, sip_add_accept_enc, sip_add_accept_lang, sip_add_alert_info, sip_add_allow, sip_add_call_info, sip_add_content_disp, sip_add_content_enc, sip_add_content_lang, sip_add_date, sip_add_error_info, sip_add_expires, sip_add_in_reply_to, sip_add_mime_version, sip_add_min_expires, sip_add_org, sip_add_priority, sip_add_reply_to, sip_add_passertedid, sip_add_ppreferredid, sip_add_require, sip_add_retry_after, sip_add_route, sip_add_record_route, sip_add_server, sip_add_subject, sip_add_supported, sip_add_tstamp, sip_add_unsupported, sip_add_user_agent, sip_add_warning, sip_add_rseq, sip_add_privacy, sip_add_rack, sip_add_author, sip_add_authen_info, sip_add_proxy_authen, sip_add_proxy_author, sip_add_proxy_require, sip_add_www_authen, sip_add_allow_events, sip_add_event, sip_add_substate – add specific SIP headers to the SIP message

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

```
int sip_add_from(sip_msg_t sip_msg, char *display_name, char *from_uri,
                char *from_tag, boolean_t add_aquot, char *from_params);

int sip_add_to(sip_msg_t sip_msg, char *display_name, char *to_uri,
              char *to_tag, boolean_t add_aquot, char *to_params);

int sip_add_contact(sip_msg_t sip_msg, char *display_name,
                   char *contact_uri, boolean_t add_aquot, char *contact_params);

int sip_add_via(sip_msg_t sip_msg, char *sent_protocol_transport,
               char *sent_by_host, int sent_by_port, char *via_params);

int sip_add_maxforward(sip_msg_t sip_msg, uint_t maxforward);

int sip_add_callid(sip_msg_t sip_msg, char *callid);

int sip_add_cseq(sip_msg_t sip_msg, sip_method_t method, uint32_t cseq);

int sip_add_content_type(sip_msg_t sip_msg, char * type, char *subtype);

int sip_add_content(sip_msg_t sip_msg, char * content);

int sip_add_accept(sip_msg_t sip_msg, char *type, char *subtype,
                  char *media_param, char *accept_param);

int sip_add_accept_enc(sip_msg_t sip_msg, char *code,
                      char *param);

int sip_add_accept_lang(sip_msg_t sip_msg, char *lang,
                       char *param);

int sip_add_alert_info(sip_msg_t sip_msg, char *alert,
                      char *param);

int sip_add_allow(sip_msg_t sip_msg, sip_method_t method_name);
```

```
int sip_add_call_info(sip_msg_t sip_msg, char *uri,
                     char *param);

int sip_add_content_disp(sip_msg_t sip_msg, char *dis_type, char *param);

int sip_add_content_enc(sip_msg_t sip_msg, char *code);

int sip_add_content_lang(sip_msg_t sip_msg, char *lang);

int sip_add_date(sip_msg_t sip_msg, char *date);

int sip_add_error_info(sip_msg_t sip_msg, char *uri, char *param);

int sip_add_expires(sip_msg_t sip_msg, int secs);

int sip_add_in_reply_to(sip_msg_t sip_msg, char *reply_id);

int sip_add_mime_version(sip_msg_t sip_msg, char *version);

int sip_add_min_expires(sip_msg_t sip_msg, int secs);

int sip_add_org(sip_msg_t sip_msg, char *org);

int sip_add_priority(sip_msg_t sip_msg, char *prio);

int sip_add_reply_to(sip_msg_t sip_msg, char *display_name,
                    char *addr, char *param, boolean_t add_aquot);

int sip_add_passertedid(sip_msg_t sip_msg, char *display_name,
                       char *addr, boolean_t add_aqout);

int sip_add_ppreferredid(sip_msg_t sip_msg, char *display_name,
                        char *addr, boolean_t add_aquot);

int sip_add_require(sip_msg_t sip_msg, char *req);

int sip_add_retry_after(sip_msg_t sip_msg, int secs, char *cmt,
                       char *param);

int sip_add_route(sip_msg_t sip_msg, char *display_name, char *uri,
                  char *route_params);

int sip_add_record_route(sip_msg_t sip_msg, char *display_name,
                        char *uri, char *route_params);

int sip_add_server(sip_msg_t sip_msg, char *svr);

int sip_add_subject(sip_msg_t sip_msg, char *subject);

int sip_add_supported(sip_msg_t sip_msg, char *support);

int sip_add_tstamp(sip_msg_t sip_msg, char *time, char *delay);

int sip_add_unsupported(sip_msg_t sip_msg, char *unsupport);

int sip_add_user_agent(sip_msg_t sip_msg, char *usr);

int sip_add_warning(sip_msg_t sip_msg, int code, char *addr, char *msg);

int sip_add_privacy(sip_msg_t sip_msg, char *priv_val);
```

```

int sip_add_rseq(sip_msg_t sip_msg, int resp_num);

int sip_add Rack(sip_msg_t sip_msg, int resp_num, int cseq,
                 sip_method_t method);

int sip_add_author(sip_msg_t sip_msg, char *scheme, char *param);

int sip_add_authen_info(sip_msg_t sip_msg, char *ainfo);

int sip_add_proxy_authen(sip_msg_t sip_msg, char *pascheme,
                        char *param);

int sip_add_proxy_author(sip_msg_t sip_msg, char *pascheme,
                        char *param);

int sip_add_proxy_require(sip_msg_t sip_msg, char *opt);

int sip_add_www_authen(sip_msg_t sip_msg, char *wascheme,
                      char *param);

int sip_add_allow_events(sip_msg_t sip_msg, char *events);

int sip_add_event(sip_msg_t sip_msg, char *event, char *param);

int sip_add_substate(sip_msg_t sip_msg, char *sub, char *param);

```

Description For each of the following functions that add a header to a SIP message, the function adds a CRLF before appending the header to the SIP message.

The `sip_add_from()` and `sip_add_to()` functions append a FROM and TO header respectively to the SIP message `sip_msg`. The header is created using the `display_name`, if non-null, and the `uri` values. The `add_aquot` parameter is used to specify whether the `uri` should be enclosed within '<>'. If a `display_name` is provided then `add_aquot` cannot be B_FALSE. The `display_name` parameter, if provided, is enclosed within quotes before creating the SIP header. Tag value for the FROM/TO header can be specified which will be added to the SIP header by prefixing it with "TAG=". Any generic parameters can be specified as the last argument, which will be added, as is, to the SIP header.

Either the tag or the generic parameter can be specified not both, if both are specified, the resulting header contains only the tag parameter.

The `sip_add_contact()` function appends a CONTACT header to the SIP message `sip_msg` using the `display_name` and `contact_uri`. The `add_aquot` parameter has the same semantics as in `sip_add_from()/sip_add_to()`. Any contact parameters specified in `contact_param` is added to the CONTACT header before appending the header to the message.

The `sip_add_via()` function appends a VIA header to the SIP message `sip_msg`. The VIA header is constructed using `sent_protocol`, `transport`, `sent_by_host` and `sent_by_port`. A value of 0 for `sent_by_port` means that the port information is not present in the resulting VIA header. The VIA header that is created has the protocol set to "SIP" and version set to "2.0". Any parameters specific in `via_params` is added to the VIA header before appending the header to the SIP message.

The `sip_add_maxforward()` function appends a MAX-FORWARDS header to the SIP message *sip_msg* using the value in *maxforward*. The *maxforward* value is a positive integer.

The `sip_add_callid()` function appends a CALL-ID header to the SIP message *sip_msg* using the value in *callid*, if non-null. If *callid* is null, this function creates a CALL-ID header using a randomly generated value.

The `sip_add_cseq()` function appends a CSEQ header to the SIP message using the values in *method* and *cseq*. Permissible values for *method* include:

INVITE
ACK
OPTIONS
BYE
CANCEL
REGISTER
REFER
SUBSCRIBE
NOTIFY
PRACK
INFO

The *cseq* value is a positive integer.

The `sip_add_content_type()` function appends a CONTENT-TYPE to the SIP message *sip_msg*. The CONTENT-TYPE is created using the type and subtype, both should be non-null.

The `sip_add_content()` function adds a message body to the SIP message *sip_msg*. The message body is given by the null terminated string contents. Once the function returns, the caller may reuse or delete contents as `sip_add_content()` creates a new buffer and copies over contents for its use.

The `sip_add_accept()` function appends an ACCEPT header to the SIP message *sip_msg*. The ACCEPT header is created using type and subtype. If both type and subtype are null, then an empty ACCEPT header is added to the SIP message. If type is non-null, but subtype is null, then the ACCEPT header has the specified type and sets the subtype in the header to '*'. Any *accept_param* or *media_param*, if provided, are added to the ACCEPT header before appending the header to the SIP message.

The `sip_add_accept_enc()` function appends an ACCEPT-ENCODING header to the SIP message *sip_msg*. The ACCEPT-ENCODING is created using code. Any parameter specified in *param* is added to the ACCEPT-ENCODING header before appending the header to the SIP message.

The `sip_add_accept_lang()` function appends an ACCEPT - LANGUAGE header to the SIP message `sip_msg`. The ACCEPT - LANGUAGE header is created using `lang`. Any parameter specified in `param` is added to the ACCEPT - LANGUAGE header before appending the header to the SIP message.

The `sip_add_alert_info()` function appends an ALERT - INFO header to the SIP message `sip_msg`. The ALERT - INFO header is created using `alert`. Any parameter specified in `param` is added to the ALERT - INFO header before appending the header to the SIP message.

The `sip_add_allow()` function appends an ALLOW header to the SIP message `sip_msg`. The ALLOW header is created using `alert` and `method`. Permissible values for `method` include:

```
INVITE
ACK
OPTIONS
BYE
CANCEL
REGISTER
REFER
INFO
SUBSCRIBE
NOTIFY
PRACK
```

The `sip_add_call_info()` function appends a CALL - INFO header to the SIP message `sip_msg`. The CALL - INFO header is created using `uri`. Any parameter specified in `param` is added to the CALL - INFO before appending the header to the SIP message.

The `sip_add_content_disp()` function appends a CONTENT - DISPOSITION header to the SIP message `sip_msg`. The CONTENT - DISPOSITION header is created using `disp_type`. Any parameter specified in `param` is added to the CONTENT - DISPOSITION header before appending the header to the SIP message.

The `sip_add_content_enc()` function appends a CONTENT - ENCODING header to the SIP message `sip_msg`. The CONTENT - ENCODING header is created using `code`.

The `sip_add_content_lang()` function appends a CONTENT - LANGUAGE header to the SIP message `sip_msg`. The CONTENT - LANGUAGE header is created using `lang`.

The `sip_add_date()` appends a DATE header to the SIP message `sip_msg`. The DATE header is created using the date information specified in `date`. The semantics for the date string is given is RFC 3261, section 25.1.

The `sip_add_error_info()` function appends an ERROR - INFO header to the SIP message `sip_msg`. The ERROR - INFO header is created using `uri`. An parameters specified in `param` is added to the ERROR - INFO header before adding the header to the SIP message.

The `sip_add_expires()` function appends an EXPIRES header to the SIP message *sip_msg*. The EXPIRES header is created using the seconds specified in *secs*.

The `sip_add_in_reply_to()` function appends a IN-REPLY-TO header to the SIP message *sip_msg*. The IN-REPLY-TO header is created using the *call-id* value specified in *reply_id*.

The `sip_add_mime_version()` function appends a MIME-VERSION header to the SIP message *sip_msg*. The MIME-VERSION header is created using *version*.

The `sip_add_min_expires()` function appends a MIN-EXPIRES header to the SIP message *sip_msg*. The MIN-EXPIRES is created using the time in seconds specified in *secs*.

The `sip_add_org()` function appends a ORGANIZATION header to the SIP message *sip_msg*. The ORGANIZATION header is created using the information specified in *org*.

The `sip_add_priority()` function appends a PRIORITY header to the SIP message *sip_msg*. The PRIORITY header is created using the value specified in *prio*.

The `sip_add_reply_to()` function appends a REPLY-TO header to the SIP message *sip_msg*. The REPLY-TO header is created using the *display_name*, if provided, and *addr*. The *add_aquot* parameter has the same semantics as in `sip_add_from()/sip_add_to()`. Any parameters specified in *param* is added to the REPLY-TO header before appending the header to the SIP message.

The `sip_add_passertedid()` function appends a P-ASSERTED-IDENTITY header to the SIP message *sip_msg*. The P-ASSERTED-IDENTITY header is created using the *display_name*, if provided, and the *addr*. The *add_aquot* parameter has the same semantics as in `sip_add_from()/sip_add_to()`.

The `sip_add_ppreferredid()` function appends a P-PREFERRED-IDENTITY header to the SIP message *sip_msg*. The P-PREFERRED-IDENTITY header is created using the *display_name*, if provided, and the *addr*. The *add_aquot* parameter has the same semantics as in `sip_add_from()/sip_add_to()`.

The `sip_add_require()` function appends a REQUIRE header to the SIP message *sip_msg*. The REQUIRE header is created using the information in *req*.

The `sip_add_retry_after()` function appends a RETRY-AFTER header to the SIP message *sip_msg*. The RETRY-AFTER is created using the time in seconds specified in *secs* comments, if any, in *cmt*. Any parameters specified in *param*, if provided, is added to the RETRY-AFTER header before appending the header to the SIP message.

The `sip_add_route()` function appends a ROUTE header to the SIP message *sip_msg*. The ROUTE header is created using the *display_name*, if any, and the *uri*. The *uri* is enclosed in '<>' before adding to the header. Parameters specified in *route_params* are added to the ROUTE header before appending the header to the SIP message.

The `sip_add_record_route()` function appends a RECORD-ROUTE header to the SIP message *sip_msg*. The RECORD-ROUTE header is created using the *display_name*, if any, and the *uri*. The *uri* parameter is enclosed in '<>' before adding to the header. Any parameters specified in *route_params* is added to the ROUTE header before appending the header to the SIP message.

The `sip_add_server()` function appends a SERVER header to the SIP message *sip_msg*. The SERVER header is created using the information in *srv*.

The `sip_add_subject()` function appends a SUBJECT header to the SIP message *sip_msg*. The SUBJECT header is created using the information in *subject*.

The `sip_add_supported()` function appends a SUPPORTED header to the SIP message *sip_msg*. The SUPPORTED header is created using the information in *support*.

The `sip_add_tstamp()` function appends a TIMESTAMP header to the SIP message *sip_msg*. The TIMESTAMP header is created using the time value in *time* and the delay value, if provided, in *delay*.

The `sip_add_unsupported()` function appends an UNSUPPORTED header to the SIP message *sip_msg*. The UNSUPPORTED header is created using the *option-tag* value in *unsupport*.

The `sip_add_user_agent()` function appends an USER-AGENT header to the SIP message *sip_msg*. The USER-AGENT header is created using the *server-val* specified in *usr*.

The `sip_add_warning()` function appends a WARNING header to the SIP message *sip_msg*. The WARNING header is created using the *warn-code* in *code*, *warn-agent* in *addr* and *warn-test* in *msg*.

The `sip_add_privacy()` function appends a PRIVACY header to the SIP message *sip_msg*. The PRIVACY header is created using the privacy value specified in *priv_val*.

The `sip_add_rseq()` function appends a RSEQ header to the SIP message *sip_msg*. The RSEQ header is created using the sequence number specified in *resp_num*.

The `sip_add_rack()` function appends a RACK header to the SIP message *sip_msg*. The RACK header is created using the sequence number in *resp_num*, the SIP method in *method* and the CSEQ number in *cseq*. Permissible values for method include: INVITE, ACK, OPTIONS, BYE, CANCEL, REGISTER, REFER, INFO, SUBSCRIBE, NOTIFY, PRACK.

The `sip_add_author()` function appends an AUTHORIZATION header to the SIP message *sip_msg*. The AUTHORIZATION header is created using *scheme*. Any parameter specified in *param* is added to the AUTHORIZATION header before the header is appended to the SIP message.

The `sip_add_authen_info()` function appends an AUTHENTICATION-INFO() header to the SIP message *sip_msg*. The AUTHENTICATION-INFO header is created using the authentication information in *ainfo*.

The `sip_add_proxy_authen()` function appends a `PROXY-AUTHENTICATE` header to the SIP message `sip_msg`. The `PROXY-AUTHENTICATE` is created using the value specified in `pscheme`. Any parameter in `param` is added to the `PROXY-AUTHENTICATE` header before adding the header to the SIP message.

The `sip_add_proxy_author()` function appends a `PROXY-AUTHORIZATION` header to the SIP message `sip_msg`. The `PROXY-AUTHORIZATION` header is created using the value specified in `pscheme`. Any parameter in `param` is added to the `PROXY-AUTHORIZATION` header before adding the header to the SIP message.

The `sip_add_proxy_require()` function appends a `PROXY-REQUIRE` header to the SIP message `sip_msg`. The `PROXY-REQUIRE` header is created using the option-tag in `opt`.

The `sip_add_www_authen()` function appends a `WWW-AUTHENTICATE` header to the SIP message `sip_msg`. The `WWW-AUTHENTICATE` header is created using the challenge in `wascheme`. Any parameter in `param` is added to the `WWW-AUTHENTICATE` header before adding the header to the SIP message.

The `sip_add_allow_events()` function appends an `ALLOW-EVENTS` header to the SIP message. The `ALLOW-EVENTS` header is created using the event specified in `events`.

The `sip_add_event()` function appends an `EVENT` header to the SIP message. The `EVENT` header is created using the value specified in `event`. Any parameter in `param` is added to the `EVENT` header before appending the header to the SIP message.

The `sip_add_substate()` function appends a `SUBSCRIPTION-STATE` header to the SIP message. The `SUBSCRIPTION-STATE` header is created using the state specified in `sub`. Any parameter in `param` is added to the `SUBSCRIPTION-STATE` header before appending the header to the SIP message.

Return Values These functions return 0 on success and the appropriate error value on failure.

Errors On failure, functions that return an error value can return one of the following:

EINVAL Mandatory parameters are not provided, i.e. null.

For `sip_add_from()`, `sip_add_to()`, `sip_add_contact()`,
`sip_add_reply_to()`, `sip_add_passertedid()`, `sip_add_ppreferredid()` if
`display_name` is non-null and `add_aquot` is B_FALSE.

For `sip_add_branchid_to_via()` the topmost `VIA` header already has a branch
`param` or the SIP message does not have a `VIA` header.

EPERM The message cannot be modified.

ENOMEM There is an error allocating memory for creating headers/parameters.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_add_header – add a SIP header to the SIP message

Synopsis cc [*flag ...*] *file ...* -lsip [*library ...*]
#include <sip.h>

```
int sip_add_header(sip_msg_t sip_msg, char *header_string);
```

Description The sip_add_header() function takes the SIP header *header_string*, adds a CRLF (carriage return/line feed) and appends it to the SIP message *sip_msg*. The sip_add_header() function is typically used when adding a SIP header with multiple values.

Return Values The sip_add_header() function returns 0 on success and the appropriate error value on failure.

Errors On failure, the sip_add_header() function can return one of the following error values:

- EINVAL Mandatory parameters are not provided, i.e. null.
- EPERM The message cannot be modified.
- ENOMEM Error allocating memory for creating headers/parameters.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTETYPE	ATTRIBUTEVALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_add_param – add a parameter to the SIP header

Synopsis `cc [flag ...] file ... -lsip [library ...]`
`#include <sip.h>`

```

sip_header_t sip_add_param(sip_header_t sip_header, char *param,
                           int *error);

```

Description The `sip_add_param()` function adds the parameter provided in *param* to the SIP header *sip_header*. The function returns the header with the parameter added. A new header is created as a result of adding the parameter and the old header is marked deleted. Applications with multiple threads working on the same SIP header need to take note of this. If *error* is non-null, it (the location pointer by the variable) is set to 0 on success and the appropriate error value on error.

Return Values The `sip_add_param()` function returns the new header on success and null on failure. Further, if *error* is non-null, then on success the value in the location pointed by *error* is 0 and the appropriate error value on failure.

Errors On failure, functions that return an error value may return one of the following:

EINVAL Mandatory parameters are not provided, i.e. null.

For `sip_add_param()`, the header to be modified is marked deleted.

EPERM The message cannot be modified.

ENOMEM There is an error allocating memory for creating headers/parameters.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_add_request_line, sip_add_response_line – add a request/response line to a SIP message

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

```
int sip_add_request_line(sip_msg_t sip_request,  
                        sip_method_t method, char *request_uri);  
  
int sip_add_response_line(sip_msg_t sip_response,  
                        int response_code, char *response_phase);
```

Description The sip_add_request_line() function adds a request line to the SIP message *sip_request*. The request line is created using the SIP method specified in *method* and the URI in *request_uri*. The SIP method can be one of the following:

INVITE
ACK
OPTIONS
BYE
CANCEL
REGISTER
REFER
SUBSCRIBE
NOTIFY
PRACK
INFO

The resulting request line has the SIP-Version of “2.0”.

The sip_add_response_line() function adds a response line to the SIP message *sip_response*. The response line is created using the response code *response_code* and the phrase in *response_phrase*. If the *response_code* is one that is listed in RFC 3261, sip_get_resp_desc() can be used to get the response phase for the *response_code*. The resulting response line has the SIP-Version of “2.0”.

Return Values The sip_add_response_line() and sip_add_request_line() functions return 0 on success and the appropriate error value in case of failure.

The value of errno is not changed by these calls in the event of an error.

Errors On failure, the sip_add_response_line() and sip_add_request_line() functions could return one of the following errors:

EINVAL	If mandatory input is not provided or if the input is invalid.
ENOTSUP	If the input SIP message cannot be modified.
ENOMEM	If memory allocation fails when creating the request/response line or when creating headers in the ACK request.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_branchid – generate a RFC 3261 complaint branch ID

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

char *sip_branchid(sip_msg_t sip_msg);

Description The sip_branchid() function can be used to generate a value for the branch parameter for a VIA header. The returned string is prefixed with z9hG4bK to conform to RFC 3261. If *sip_msg* is null or *sip_msg* does not have a VIA header, a random value is generated. Otherwise, the value is generated using the MD5 hash of the VIA, FROM, CALL-ID, CSEQ headers and the URI from the request line. The caller is responsible for freeing the returned string.

Return Values The sip_branchid() function returns a string on success and NULL on failure.

The value of errno is not changed by these calls in the event of an error.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_clone_msg – clone a SIP message

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

sip_msg_t sip_clone_msg(sip_msg_t sip_msg);

Description The sip_clone_msg() function clones the input SIP message and returns the cloned message. The resulting cloned message has all the SIP headers and message body, if present, from the input message.

Return Values The sip_clone_msg() function returns the cloned message on success and NULL on failure.

The value of errno is not changed by these calls in the event of an error.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_copy_start_line, sip_copy_header, sip_copy_header_by_name, sip_copy_all_headers – copy headers from a SIP message

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

int sip_copy_start_line(sip_msg_t *from_msg*, sip_msg_t *to_msg*);
int sip_copy_header(sip_msg_t *sip_msg*, sip_header_t *sip_header*,
char **param*);
int sip_copy_header_by_name(sip_msg_t *from_msg*, sip_msg_t *to_msg*,
char **header_name*, char **param*);
int sip_copy_all_headers(sip_msg_t *from_msg*, sip_msg_t *to_msg*);

Description The sip_copy_start_line() function copies the start line, a request or a response line, from *from_msg* to *to_msg*.

The sip_copy_header() function copies the SIP header specified by *sip_header* to the SIP message *sip_msg*. A new SIP header is created from *sip_header* and *param*, and is appended to *sip_msg*. The *param* can be non-null.

The sip_copy_header_by_name() function copies the header specified by *header_name* (long or short form) from *from_msg* to *to_msg*. The new header is created using the header value from *from_msg* and *param*, if non-null, and appended to *to_msg*.

The sip_copy_all_headers() copies all the headers from *from_msg* to *to_msg*.

Return Values These functions return 0 on success and the appropriate error on failure.

The value of `errno` is not changed by these calls in the event of an error.

Errors These functions can return one of the following errors in case of failure:

- EINVAL
If the required input parameters are NULL or if the header being copied does not exist or is deleted in source SIP message.
- ENOMEM
Error while allocating memory for creating the new header.
- EPERM
If the input SIP message cannot be modified.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_create_dialog_req – create an in-dialog request

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

```
sip_msg_t sip_create_dialog_req(sip_method_t method,  
                               sip_dialog_t dialog, char *transport,  
                               char *sent_by, int sent_by_port,  
                               char *via_param, uint32_t smaxforward,  
                               int cseq)
```

Description The sip_create_dialog_req() function creates and returns a SIP request with the state information contained in *dialog*. The method in the resulting request is from *method*. The method can be one of the following:

INVITE
ACK
OPTIONS
BYE
CANCEL
REGISTER
REFER
INFO
SUBSCRIBE
NOTIFY
PRACK

The resulting request line in the SIP message has the SIP-Version of “2.0”. The URI in the request line is from the remote target in the *dialog* or from the route set in the *dialog*, if present. See RFC 3261 (section 12.2) for details. The FROM, TO, and CALL-ID headers are added from the *dialog*. The MAX-FORWARDS header is added using the value in *maxforward*. The CSEQ header is added using the SIP method in *method* and the sequence number value in *cseq*. If *cseq* is -1, the sequence number is obtained from the local sequence number in the *dialog*. The local sequence number in the *dialog* is incremented and is used in the CSEQ header. The VIA header added is created using the *transport*, *sent_by*, *sent_by_port* (if non-zero), and *via_param* (if any). If *dialog* has a non-empty route set, the resulting SIP request has the route set from the *dialog*.

Return Values The sip_create_dialog_req() function returns the resulting SIP message on success and NULL on failure.

The value of `errno` is not changed by these calls in the event of an error.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_create_OKack – create an ACK request for a final response

Synopsis cc [*flag ...*] *file ...* -lsip [*library ...*]
#include <sip.h>

```
int sip_create_OKack(sip_msg_t response,
                    sip_msg_t ack_msg, char *transport,
                    char *sent_by, int sent_by_port,
                    char *via_params);
```

Description The sip_create_OKack() function constructs an ACK request in *ack_msg* for the final 2XX SIP response. The request line is created using the URI in the CONTACT header from the *response*. The SIP-Version in the request line is “2.0”. The VIA header for the ACK request is created using *transport*, *sent_by*, *sent_by_port* (if non-zero), and *via_params* (if non-null). The following headers are copied to *ack_msg* from *response*:

FROM
TO
CALL-ID
MAX_FORWARDS

The CSEQ header is created using the method as ACK and the sequence number from the CSEQ header in *response*.

Return Values The sip_create_OKack() function returns 0 on success and the appropriate error value in case of failure.

The value of `errno` is not changed by these calls in the event of an error.

Errors On failure, the sip_create_OKack() function could return one of the following errors:

EINVAL If mandatory input is not provided or if the input is invalid.

The sip_create_OKack() function can return this error if it does not find a CONTACT header or if it is unable to obtain the URI from the CONTACT header for the request line.

ENOTSUP If the input SIP message cannot be modified.

ENOMEM If memory allocation fails when creating the request/response line or when creating headers in the ACK request.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_create_response – create a response for a SIP request

Synopsis cc [*flag ...*] *file ...* -lsip [*library ...*]
#include <sip.h>

```
sip_msg_t sip_create_response(sip_msg_t sip_request,  
                             int response_code, char *response_phrase,  
                             char *totag, char *contact_uri);
```

Description The sip_create_response() function creates and returns a SIP message in response to the SIP request *sip_request*. The response line in the resulting SIP message is created using the response code in *response_code* and the phrase in *response_phrase*. The response line has the SIP-Version of “2.0”. If a non-null *totag* is specified, the resulting SIP response has a TO header with a tag value from *totag*. If *totag* is null and the *response_code* is anything other than 100 (TRYING), sip_create_response() adds a TO header with a randomly generated tag value. If the *response_code* is 100 and *totag* is null, the SIP response has a TO header without a tag parameter. If *contact_uri* is non-null, a CONTACT header is added to the SIP response with the URI specified in *contact_uri*. The SIP response has the following headers copied from *sip_request*:

All VIA headers
FROM header
TO header (with tag added, if required, as stated above)
CALL-ID header
CSEQ header
All RECORD-ROUTE headers

Return Values The sip_create_response() function returns the resulting SIP message on success and NULL on failure.

The value of `errno` is not changed by these calls in the event of an error.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_delete_dialog – delete a dialog

Synopsis `cc [flag ...] file ... -lsip [library ...]`
`#include <sip.h>`

`void sip_delete_dialog(sip_dialog_t dialog);`

Description For functions that return a pointer of type `sip_str_t`, `sip_str_t` is supplied by:

```

typedef struct sip_str {
    char    *sip_str_ptr;
    int     sip_str_len;
}sip_str_t;

```

The *sip_str_ptr* parameter points to a specified value at the start of an input string. The *sip_str_len* supplies the length of the returned value starting from *sip_str_ptr*.

The `sip_delete_dialog()` function is used to delete the dialog specified in *dialog*. The dialog is not freed if it has outstanding references on it. When the last reference is released the dialog is freed.

Return Values The value of `errno` is not changed by these calls in the event of an error.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_delete_start_line, sip_delete_header, sip_delete_header_by_name, sip_delete_value – delete a SIP header or a header value

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

```

int sip_delete_start_line(sip_msg_t sip_msg);

int sip_delete_header(sip_msg_t sip_header);

int sip_delete_header_by_name(sip_msg_t msg,
    char *header_name);

int sip_delete_value(sip_header_t sip_header,
    sip_header_value_t sip_header_value);

```

Description The sip_delete_start_line() function deletes the start line, a request or a response line, from the SIP message *sip_msg*.

The sip_delete_header() function deletes the SIP header specified by *sip_header* from the associated SIP message *sip_msg*.

The sip_delete_header_by_name() function deletes the SIP header name specified by *header_name* (long or compact form) from the SIP message *sip_msg*.

The sip_delete_value() deletes the SIP header value specified by *sip_header_value* from the SIP header *sip_header*.

When a SIP header or value is deleted, the corresponding header or value is marked as deleted. Lookups ignore headers or values that are marked as deleted.

Return Values These functions return 0 on success and the appropriate error on failure.

The value of errno is not changed by these calls in the event of an error.

Errors On failure, the returned error could be one of the following:

- EINVAL If any of the required input is NULL.
- If the header or value to be deleted does not exist.
- If the header or value to be deleted has already been deleted.
- EPERM If the SIP message cannot be modified.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_enable_counters, sip_disable_counters, sip_get_counter_value – counter operations

Synopsis cc [*flag...*] *file...* -lsip [*library...*]
#include <sip.h>

```
int sip_enable_counters(int counter_group);  
int sip_disable_counters(int counter_group);  
int sip_get_counter_value(int group, int counter, void *counterval,  
                          size_t counterlen);
```

Description The sip_enable_counters() function enables the measurement and counting of the selected counter group. The only allowed value for the *counter_group* is SIP_TRAFFIC_COUNTERS, which is defined in <sip.h>. Once enabled, the SIP stack starts measuring end-to-end SIP traffic. The SIP stack keeps track of:

- the number of SIP requests sent and received (broken down by methods),
- the number of SIP responses sent and received (broken down by response codes), and
- the number of bytes sent and received.

The following counters are defined in <sip.h> for the SIP_TRAFFIC_COUNTERS group. These counter values are retrieved using the sip_get_counter_value() function.

```
SIP_TOTAL_BYTES_RCVD  
SIP_TOTAL_BYTES_SENT  
SIP_TOTAL_REQ_RCVD  
SIP_TOTAL_REQ_SENT  
SIP_TOTAL_RESP_RCVD  
SIP_TOTAL_RESP_SENT  
SIP_ACK_REQ_RCVD  
SIP_ACK_REQ_SENT  
SIP_BYE_REQ_RCVD  
SIP_BYE_REQ_SENT  
SIP_CANCEL_REQ_RCVD  
SIP_CANCEL_REQ_SENT  
SIP_INFO_REQ_RCVD  
SIP_INFO_REQ_SENT  
SIP_INVITE_REQ_RCVD  
SIP_INVITE_REQ_SENT  
SIP_NOTIFY_REQ_RCVD  
SIP_NOTIFY_REQ_SENT  
SIP_OPTIONS_REQ_RCVD  
SIP_OPTIONS_REQ_SENT  
SIP_PRACK_REQ_RCVD  
SIP_PRACK_REQ_SENT  
SIP_REFER_REQ_RCVD  
SIP_REFER_REQ_SENT  
SIP_REGISTER_REQ_RCVD
```

```

SIP_REGISTER_REQ_SENT
SIP_SUBSCRIBE_REQ_RCVD
SIP_SUBSCRIBE_REQ_SENT
SIP_UPDATE_REQ_RCVD
SIP_UPDATE_REQ_SENT
SIP_1XX_RESP_RCVD
SIP_1XX_RESP_SENT
SIP_2XX_RESP_RCVD
SIP_2XX_RESP_SENT
SIP_3XX_RESP_RCVD
SIP_3XX_RESP_SENT
SIP_4XX_RESP_RCVD
SIP_4XX_RESP_SENT
SIP_5XX_RESP_RCVD
SIP_5XX_RESP_SENT
SIP_6XX_RESP_RCVD
SIP_6xx_RESP_SENT
SIP_COUNTER_START_TIME /* records time when counting was enabled */
SIP_COUNTER_STOP_TIME  /* records time when counting was disabled */

```

All of the above counters are defined to be `uint64_t`, except for `SIP_COUNTER_START_TIME` and `SIP_COUNTER_STOP_TIME`, which are defined to be `time_t`.

The `sip_disable_counters()` function disables measurement and counting for the specified *counter_group*. When disabled, the counter values are not reset and are retained until the measurement is enabled again. Calling `sip_enable_counters()` again would reset all counter values to zero and counting would start afresh.

The `sip_get_counter_value()` function retrieves the value of the specified counter within the specified counter group. The value is copied to the user provided buffer, *counterval*, of length *counterlen*. For example, after the following call, *invite_rcvd* would have the correct value.

```

uint64_t invite_rcvd;

sip_get_counter_value(SIP_TRAFFIC_COUNTERS, SIP_INVITE_REQ_RCVD,
    &invite_rcvd, sizeof (uint64_t));

```

Return Values Upon successful completion, `sip_enable_counters()` and `sip_disable_counters()` return 0. They will return `EINVAL` if an incorrect group is specified.

Upon successful completion, `sip_get_counter_value()` returns 0. It returns `EINVAL` if an incorrect counter name or counter size is specified, or if *counterval* is `NULL`.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	MT-Safe

See Also
[attributes\(5\)](#)

Name sip_enable_trans_logging, sip_enable_dialog_logging, sip_disable_dialog_logging, sip_disable_trans_logging – transaction and dialog logging operations

Synopsis cc [*flag...*] *file...* -lsip [*library...*]
#include <sip.h>

```
int sip_enable_trans_logging(FILE *logfile, int flags);
int sip_enable_dialog_logging(FILE *logfile, int flags);
void sip_disable_dialog_logging();
void sip_disable_trans_logging();
```

Description The sip_enable_trans_logging() and sip_enable_dialog_logging() functions enable transaction and dialog logging respectively. The *logfile* argument points to a file to which the SIP messages are logged. The flags argument controls the amount of logging. The only flag defined in <sip.h> is SIP_DETAIL_LOGGING. Either transaction or dialog logging, or both, can be enabled at any time. For dialog logging to work, the SIP stack must be enabled to manage dialogs (using SIP_STACK_DIALOGS, see [sip_stack_init\(3SIP\)](#)) when the stack is initialized.

All the messages exchanged within a transaction/dialog is captured and later dumped to a log file when the transaction or dialog is deleted or terminated. Upon termination, each dialog writes to the file the messages that were processed in its context. Similarly, upon termination each transaction writes to the file the messages that were processed in its context.

The sip_disable_trans_logging() and sip_disable_dialog_logging() functions disable the transaction or dialog logging. These functions do not close the files. It is the responsibility of the application to close them.

The log contains the state of the transaction or dialog at the time the message was processed.

Return Values Upon successful completion, sip_enable_trans_logging() and sip_enable_dialog_logging() return 0. They return EINVAL if *logfile* is NULL or *flags* is unrecognized.

Examples EXAMPLE 1 Dialog logging

The following is an example of dialog logging.

```
FILE    *logfile;

logfile = fopen("/tmp/ApplicationA", "a+");
sip_enable_dialog_logging(logfile, SIP_DETAIL_LOGGING);

/* Application sends INVITE, receives 180 and 200 response and dialog is
   created. */
/* Application sends ACK request */
/* Application sends BYE and receives 200 response */
```

EXAMPLE 1 Dialog logging (Continued)

```
/* Application disables logging */
sip_disable_dialog_logging();
```

The log file will be of the following format.

```
***** Begin Dialog *****
Digest      : 43854 43825 26120 9475 5415 21595 25658 18538

-----
Dialog State      : SIP_DLG_NEW

Tue Nov 27 15:53:34 2007| Message - 1
INVITE sip:user@example.com SIP/2.0
From: "Me" < sip:me@mydomain.com > ; TAG=tag-from-01
To: "You" < sip:you@yourdomain.com >
Contact: < sip:myhome.host.com >
MAX-FORWARDS: 70
Call-ID: 1261K6A6492KF33549XM
CSeq: 111 INVITE
CONTENT-TYPE: application/sdp
Via: SIP/2.0/UDP 192.0.0.1 : 5060 ;branch=z9hG4bK-via-EVERYTHINGID0-05
Record-Route: <sip:server1.com;lr>
Record-Route: <sip:server2.com;lr>
CONTENT-LENGTH : 0

Tue Nov 27 15:53:34 2007| Message - 2
SIP/2.0 180 Ringing
Via: SIP/2.0/UDP 192.0.0.1 : 5060 ;branch=z9hG4bK-via-EVERYTHINGID0-05
From: "Me" < sip:me@mydomain.com > ; TAG=tag-from-01
To: "You" < sip:you@yourdomain.com >;tag=1
Call-ID: 1261K6A6492KF33549XM
CSeq: 111 INVITE
Contact: <sip:whitestar2-0.East.Sun.COM:5060;transport=UDP>
Record-Route: <sip:server1.com;lr>
Record-Route: <sip:server2.com;lr>
Content-Length: 0

-----
Dialog State      : SIP_DLG_EARLY

/* Entire 200 OK SIP Response */

-----
Dialog State      : SIP_DLG_CONFIRMED
```

EXAMPLE 1 Dialog logging *(Continued)*

```
/* Entire ACK Request */

/* Entire BYE Request */
/* Entire 200 OK Response */
-----
***** End Dialog *****
```

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	MT-Safe

See Also [sip_stack_init\(3SIP\)](#), [attributes\(5\)](#)

Name sip_get_contact_display_name, sip_get_from_display_name, sip_get_to_display_name, sip_get_from_tag, sip_get_to_tag, sip_get_callid, sip_get_callseq_num, sip_get_callseq_method, sip_get_via_sent_by_host, sip_get_via_sent_by_port, sip_get_via_sent_protocol_version, sip_get_via_sent_protocol_name, sip_get_via_sent_transport, sip_get_maxforward, sip_get_content_length, sip_get_content_type, sip_get_content_sub_type, sip_get_content, sip_get_accept_type, sip_get_accept_sub_type, sip_get_accept_enc, sip_get_accept_lang, sip_get_alert_info_uri, sip_get_allow_method, sip_get_min_expires, sip_get_mime_version, sip_get_org, sip_get_priority, sip_get_replyto_display_name, sip_get_replyto_uri_str, sip_get_date_time, sip_get_date_day, sip_get_date_month, sip_get_date_wkday, sip_get_date_year, sip_get_date_timezone, sip_get_content_disp, sip_get_content_enc, sip_get_error_info_uri, sip_get_expires, sip_get_require, sip_get_subject, sip_get_supported, sip_get_tstamp_delay, sip_get_unsupported, sip_get_server, sip_get_user_agent, sip_get_warning_code, sip_get_warning_agent, sip_get_warning_text, sip_get_call_info_uri, sip_get_in_reply_to, sip_get_retry_after_time, sip_get_retry_after_cmts, sip_get_rack_resp_num, sip_get_rack_cseq_num, sip_get_rack_method, sip_get_rseq_resp_num, sip_get_priv_value, sip_get_passertedid_display_name, sip_get_passertedid_uri_str, sip_get_pppreferredid_display_name, sip_get_pppreferredid_uri_str, sip_get_author_scheme, sip_get_author_param, sip_get_authen_info, sip_get_proxy_authen_scheme, sip_get_proxy_authen_param, sip_get_proxy_author_scheme, sip_get_proxy_author_param, sip_get_proxy_require, sip_get_www_authen_scheme, sip_get_www_authen_param, sip_get_allow_events, sip_get_event, sip_get_substate, sip_get_content_lang, sip_get_tstamp_value, sip_get_route_uri_str, sip_get_route_display_name, sip_get_contact_uri_str, sip_get_from_uri_str, sip_get_to_uri_str – obtain header specific attributes

Synopsis

```
cc [ flag ... ] file ... -lsip [ library ... ]
#include <sip.h>

const sip_str_t *sip_get_contact_display_name(sip_header_value_t value,
int *error);

const sip_str_t *sip_get_from_display_name(sip_msg_t sip_msg,
int *error);

const sip_str_t *sip_get_to_display_name(sip_msg_t sip_msg,
int *error);

const sip_str_t *sip_get_contact_uri_str(sip_header_value_t value,
int *error);

const sip_str_t *sip_get_from_uri_str(sip_msg_t sip_msg,
int *error);

const sip_str_t *sip_get_to_uri_str(sip_msg_t sip_msg,
int *error);

const sip_str_t *sip_get_from_tag(sip_msg_t sip_msg,
int *error);
```



```
const sip_str_t *sip_get_to_tag(sip_msg_t sip_msg,
                                int *error);

const sip_str_t *sip_get_callid(sip_msg_t sip_msg,
                                int *error);

int sip_get_callseq_num(sip_msg_t sip_msg,
                        int *error);

sip_method_t sip_get_callseq_method(sip_msg_t sip_msg,
                                    int *error);

const sip_str_t *sip_get_via_sent_by_host(sip_header_value_t value,
                                            int *error);

int sip_get_via_sent_by_port (sip_header_value_t value,
                              int *error);

const sip_str_t *sip_get_via_sent_protocol_version
(sip_header_value_t value, int *error);

const sip_str_t *sip_get_via_sent_transport(sip_header_value_t value,
                                             int *error);

int sip_get_maxforward(sip_msg_t sip_msg,
                       int *error);

int sip_get_content_length(sip_msg_t sip_msg,
                           int *error);

const sip_str_t *sip_get_content_type(sip_msg_t sip_msg,
                                       int *error);

const sip_str_t *sip_get_content_sub_type(sip_msg_t sip_msg,
                                           int *error);

char *sip_get_content(sip_msg_t sip_msg,
                      int *error);

const sip_str_t *sip_get_accept_type(sip_header_value_t value,
                                      int *error);

const sip_str_t *sip_get_accept_sub_type(sip_header_value_t value,
                                          int *error);

const sip_str_t *sip_get_accept_enc(sip_header_value_t value,
                                     int *error);

const sip_str_t *sip_get_accept_lang(sip_header_value_t value,
                                      int *error);

const sip_str_t *sip_get_alert_info_uri(sip_header_value_t value,
                                          int *error);

sip_method_t sip_get_allow_method(sip_header_value_t value,
                                  int *error);
```

```
int sip_get_min_expire(sip_msg_t sip_msg,
    int *error);

const sip_str_t *sip_get_mime_version(sip_msg_t sip_msg,
    int *error);

const sip_str_t *sip_get_org(sip_msg_t sip_msg,
    int *error);

const sip_str_t *sip_get_priority(sip_msg_t sip_msg,
    int *error);

const sip_str_t *sip_get_replyto_display_name(sip_msg_t sip_msg,
    int *error);

const sip_str_t *sip_get_replyto_uri_str(sip_msg_t sip_msg,
    int *error);

const sip_str_t *sip_get_date_time(sip_msg_t sip_msg,
    int *error);

int sip_get_date_day(sip_msg_t sip_msg,
    int *error);

const sip_str_t *sip_get_date_month(sip_msg_t sip_msg,
    int *error);

int sip_get_date_year(sip_msg_t sip_msg,
    int *error);

const sip_str_t *sip_get_date_wkday(sip_msg_t sip_msg,
    int *error);

const sip_str_t *sip_get_date_timezone(sip_msg_t sip_msg,
    int *error);

const sip_str_t *sip_get_content_disp(sip_msg_t sip_msg,
    int *error);

const sip_str_t *sip_get_content_enc(sip_header_value_t value,
    int *error);

const sip_str_t *sip_get_error_info_uri(sip_header_value_t value,
    int *error);

int sip_get_expires(sip_msg_t sip_msg,
    int *error);

const sip_str_t *sip_get_require(sip_header_value_t value,
    int *error);

const sip_str_t *sip_get_subject(sip_msg_t sip_msg,
    int *error);

const sip_str_t *sip_get_supported(sip_header_value_t value,
    int *error);
```

```

const sip_str_t *sip_get_tstamp_delay(sip_msg_t sip_msg,
    int *error);

const sip_str_t *sip_get_unsupported(sip_header_value_t value,
    int *error);

const sip_str_t *sip_get_server(sip_msg_t sip_msg,
    int *error);

const sip_str_t *sip_get_user_agent(sip_msg_t sip_msg,
    int *error);

int sip_get_warning_code(sip_header_value_t value,
    int *error);

const sip_str_t *sip_get_warning_agent(sip_header_value_t value,
    int *error);

const sip_str_t *sip_get_warning_text(sip_header_value_t value,
    int *error);

const sip_str_t *sip_get_call_info_uri(sip_header_value_t value,
    int *error);

const sip_str_t *sip_get_in_reply_to(sip_header_value_t value,
    int *error);

int sip_get_retry_after_time(sip_msg_t sip_msg,
    int *error);

const sip_str_t *sip_get_retry_after_cmts(sip_msg_t sip_msg,
    int *error);

const sip_str_t *sip_get_passertedid_display_name
    (sip_header_value_t value, int *error);

const sip_str_t *sip_get_passertedid_uri_str
    (sip_header_value_t value, int *error);

int sip_get_rack_resp_num(sip_msg_t sip_msg,
    int *error);

int sip_get_rack_cseq_num(sip_msg_t sip_msg, int *error);

sip_method_t sip_get_rack_method(sip_msg_t sip_msg, int *error);

int sip_get_rseq_resp_num(sip_msg_t sip_msg,
    int *error);

const sip_str_t *sip_get_priv_value(sip_header_value_t value,
    int *error);

const sip_str_t *sip_get_author_scheme(sip_msg_t sip_msg,
    int *error);

const sip_str_t *sip_get_author_param(sip_msg_t sip_msg,
    char *name, int *error);

```

```
const sip_str_t *sip_get_authen_info(sip_header_value_t value,
int *error);

const sip_str_t *sip_get_proxy_authen_scheme(sip_msg_t msg,
int *error);

const sip_str_t *sip_get_proxy_authen_param(sip_msg_t sip_msg,
char *name, int *error);

const sip_str_t *sip_get_proxy_author_scheme(sip_msg_t msg,
int *error);

const sip_str_t *sip_get_proxy_author_param(sip_msg_t sip_msg,
char *name, int *error);

const sip_str_t *sip_get_proxy_require(sip_header_value_t value,
int *error);

const sip_str_t *sip_get_www_authen_scheme(sip_msg_t msg,
int *error);

const sip_str_t *sip_get_www_authen_param(sip_msg_t sip_msg,
char *name, int *error);

const sip_str_t *sip_get_allow_events(sip_header_value_t value,
int *error);

const sip_str_t *sip_get_event(sip_msg_t sip_msg,
int *error);

const sip_str_t *sip_get_substate(sip_msg_t sip_msg,
int *error);

const sip_str_t *sip_get_content_lang(sip_header_value_t value,
int *error);

const sip_str_t *sip_get_tstamp_value(sip_msg_t sip_msg,
int *error);

const sip_str_t *sip_get_route_uri_str(sip_header_value_t value,
int *error);

const sip_str_t *sip_get_route_display_name(sip_header_value_t value,
int *error);
```

Description For functions that return a pointer of type `sip_str_t`, `sip_str_t` is supplied by:

```
typedef struct sip_str {
    char    *sip_str_ptr;
    int     sip_str_len;
}sip_str_t;
```

The *sip_str_ptr* parameter points to the start of the returned value and *sip_str_len* supplies the length of the returned value.

For example, given the following request line in a SIP message *sip_msg* that is input to *sip_get_request_uri_str()*:

```
FROM : <Alice sip:alice@atlanta.com>;tag=1928301774
```

the return is a pointer to *sip_str_t* with the *sip_str_ptr* member pointing to “A” of Alice and *sip_str_len* being set to 5, the length of Alice.

Access functions for headers that can have multiple values take the value as the input, while those that can have only one value take the SIP message *sip_msg* as the input.

The *sip_get_contact_display_name()*, *sip_get_from_display_name()*, and *sip_get_to_display_name()* functions will return the display name, if present, from the CONTACT header value, FROM and TO header respectively.

The *sip_get_contact_uri_str()*, *sip_get_from_uri_str()*, and *sip_get_to_uri_str()* functions will return the URI string from the CONTACT value, FROM and TO header respectively.

The *sip_get_from_tag()* and *sip_get_to_tag()* functions will return the TAG parameter value, if present, from the FROM and TO header, respectively, in the provided SIP message *sip_msg*.

The *sip_get_callid()* function will return the value from the CALL-ID header in the provided SIP message *sip_msg*.

The *sip_get_callseq_num()* function will return the call sequence number from the CSEQ header in the provided SIP message *sip_msg*.

The *sip_get_callseq_method()* function will return the method from the CSEQ header in the provided SIP message *sip_msg*. The method can be one of the following:

```
INVITE
ACK
OPTIONS
BYE
CANCEL
REGISTER
REFER
INFO
SUBSCRIBE
NOTIFY
PRACK
UNKNOWN
```

The *sip_get_via_sent_by_host()*, *sip_get_via_sent_by_port()*, *sip_get_via_sent_protocol_version()*, *sip_get_via_sent_protocol_name()*, and *sip_get_via_sent_transport()* functions will return the sent-by host, port (if present),

protocol version, protocol name and transport information from the provided VIA header value. Example, if the VIA value is given by SIP/2.0/UDP bobspc.biloxi.com:5060, then the sent-by host is “bobspc.biloxi.com”, protocol name is “SIP”, protocol version is “2.0”, port is 5060 and transport is UDP.

The `sip_get_maxforward()` function will return the value of the MAX-FORWARDS header in the provided SIP message *sip_msg*.

INVITE
ACK
OPTIONS
BYE
CANCEL
REGISTER
REFER
INFO
SUBSCRIBE
NOTIFY
PRACK
UNKNOWN

The `sip_get_content_length()` function will return the value of the CONTENT-LENGTH header in the provided SIP message *sip_msg*. The method can return one of the following:

The `sip_get_content_type()` and `sip_get_content_sub_type()` functions will return the value of the Type and Sub-Type field, respectively, from the CONTENT-TYPE header in the provided SIP message *sip_msg*.

The `sip_get_content()` function will return the message body from the provided SIP message *sip_msg*. The returned string is a copy of the message body and the caller is responsible for freeing the string after use.

The `sip_get_accept_type()` and `sip_get_accept_sub_type()` functions will return the value of the Type and Sub-Type field, respectively, from the provided ACCEPT header value.

The `sip_get_accept_enc()` function will return the content-coding from the provided ACCEPT-ENCODING header value.

The `sip_get_accept_lang()` function will return the language from the provided ACCEPT-LANGUAGE header value.

The `sip_get_alert_info_uri()` function will return the URI string from the provided ALERT-INFO header value.

The `sip_get_allow_method()` function will return the SIP method from the provided ALLOW header value. The method can return one of the following:

INVITE
 ACK
 OPTIONS
 BYE
 CANCEL
 REGISTER
 REFER
 INFO
 SUBSCRIBE
 NOTIFY
 PRACK
 UNKNOWN

The `sip_get_min_expire()` function will return the time in seconds from the MIN-EXPIRES header in the provided SIP message *sip_msg*.

The `sip_get_mime_version()` function will return the MIME version string from the MIME-VERSION header in the provided SIP message *sip_msg*.

The `sip_get_org()` function will return the organization string value from the ORGANIZATION header in the provided SIP message *sip_msg*.

The `sip_get_priority()` function will return the priority string value from the PRIORITY header in the provided SIP message *sip_msg*.

The `sip_get_replyto_display_name()` and `sip_get_replyto_uri_str()` functions will return the display name (if present) and the URI string, respectively, from the REPLY-TO header in the provided SIP message *sip_msg*.

The `sip_get_date_time()`, `sip_get_date_day()`, `sip_get_date_month()`, `sip_get_date_wkday()`, `sip_get_date_year()` and `sip_get_date_timezone()` functions will return the time, day, month, week day, year and timezone value from the DATE header in the provided SIP message *sip_msg*. Example, if the DATE header has the following value:

Sat, 13 Nov 2010 23:29:00 GMT

the time is “23:29:00”, week day is “Sat”, day is “13”, month is “Nov”, year is “2010”, timezone is “GMT”.

The `sip_get_content_disp()` function will return the content-disposition type from the CONTENT-DISPOSITION header in the provided SIP message *sip_msg*.

The `sip_get_content_enc()` function will return the content-coding value from the CONTENT-ENCODING header value.

The `sip_get_error_info_uri()` function will return the URI string from the provided ERROR-INFO header value.

The `sip_get_expires()` function will return the time in seconds from the EXPIRES header in the provided SIP message *sip_msg*.

The `sip_get_require()` function will return the option-tag value from the provided REQUIRE header value.

The `sip_get_subject()` function will return the value of the SUBJECT header in the provided SIP message *sip_msg*.

The `sip_get_supported()` function will return the extension value from the provided SUPPORTED header value.

The `sip_get_timestamp_delay()` function will return the value from the TIMESTAMP header in the provided SIP message *sip_msg*.

The `sip_get_unsupported()` function will return the extension value from the provided UNSUPPORTED header value.

The `sip_get_server()` function will return the value from the SERVER header in the provided SIP message *sip_msg*.

The `sip_get_user_agent()` function will return the value from the USER-AGENT header in the provided SIP message *sip_msg*.

The `sip_get_warning_code()`, `sip_get_warning_agent()`, and `sip_get_warning_text()` functions will return the value of the warn-code, warn-agent and warn-text, respectively, in the provided WARNING header value.

The `sip_get_call_info_uri()` function will return the URI string in the provided CALL-INFO header value.

The `sip_get_in_reply_to()` function will return the Call-Id value in the provided IN-REPLY-TO header value.

The `sip_get_retry_after_time()`, and `sip_get_retry_after_cmts()` functions return the time and comments (if any), respectively, from the RETRY-AFTER header in the provided SIP message *sip_msg*.

The `sip_get_passertedid_display_name()` and `sip_get_passertedid_uri_str()` functions will return the display name (if any) and the URI string, respectively, in the provided P-ASSERTED-IDENTITY header value.

The `sip_get_ppreferredid_display_name()` and `sip_get_ppreferredid_uri_str()` functions will return the display name (if any) and the URI string, respectively, in the provided P-PREFERRED-IDENTITY header value.

The `sip_get Rack_resp_num()`, `sip_get Rack_cseq_num()`, and `sip_get Rack_method()` functions will return the response-number, the CSEQ number and the SIP method from the RACK header in the provided SIP message *sip_msg*. The method can return one of the following:

INVITE
ACK
OPTIONS
BYE
CANCEL
REGISTER
REFER
INFO
SUBSCRIBE
NOTIFY
PRACK
UNKNOWN

The `sip_get_rseq_resp_num()` function will return the response-number, the RSEQ header in the provided SIP message *sip_msg*.

The `sip_get_priv_value()` function will return the priv-value in the provided PRIVACY header value.

The `sip_get_route_uri_str()` and `sip_get_route_display_name()` functions will return the URI string, and display name (if present) from the provided ROUTE or RECORD-ROUTE header value.

The `sip_get_author_scheme()` function will return the scheme from the AUTHORIZATION header in the provided SIP message *sip_msg*.

The `sip_get_author_param()` function will return the value of the parameter specified in name from the AUTHORIZATION header in the SIP message *sip_msg*.

The `sip_get_authen_info()` function will return the authentication information from the provided AUTHORIZATION-INFO header value.

The `sip_get_proxy_authen_scheme()` function will return the scheme from the PROXY-AUTHENTICATE header in the SIP message *sip_msg*.

The `sip_get_proxy_authen_param()` function will return the value of the parameter in name from the PROXY-AUTHENTICATE header in the SIP message *sip_msg*.

The `sip_get_proxy_author_scheme()` function will return the value of the scheme from the PROXY-AUTHORIZATION header in the SIP message *sip_msg*.

The `sip_get_proxy_author_param()` function will return the value of the parameter specified in name from the PROXY-AUTHORIZATION header in the SIP message *sip_msg*.

The `sip_get_proxy_require()` function will return the option-tag from the provided PROXY-REQUIRE header value.

The `sip_get_www_authen_scheme()` function will return the challenge from the WWW-AUTHENTICATE header in the SIP message *sip_msg*.

The `sip_get_www_authen_param()` function will return the value of the parameter specified in `name` from the WWW-AUTHENTICATE header in the SIP message `sip_msg`.

The `sip_get_allow_events()` function returns the value of the allowed event from the provided ALLOW-EVENTS header value.

The `sip_get_event()` function returns the event in the EVENT header in the SIP message `sip_msg`.

The `sip_get_substate()` function the subscription state from the SUBSCRIPTION-STATE header in the provided SIP message `sip_msg`.

The `sip_get_content_lang()` function will return the language from the provided CONTENT-LANGUAGE value.

The `sip_get_tstamp_value()` function will return the timestamp value from the TIMESTAMP header in the SIP message `sip_msg`.

Return Values For functions that return a pointer to `sip_str_t`, the return value is the specified value on success or NULL in case of error. For functions that return an integer, the return value is the specified value on success and -1 on error.

The value of `errno` is not changed by these calls in the event of an error.

Errors These functions take a pointer to an integer `error` as an argument. If the error is non-null, one of the following values is set:

EINVAL The input SIP message `sip_msg` or the header value is null; or the specified header/header value is deleted.

EPROTO The header value is not present or invalid. The parser could not parse it correctly.

ENOMEM There is an error allocating memory for the return value.

On success, the value of the location pointed to by `error` is set to 0.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_get_cseq, sip_get_rseq – get initial sequence number

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

uint32_t sip_get_cseq();
uint32_t sip_get_rseq();

Description The sip_get_cseq() and sip_get_rseq() functions can be used to generate an initial sequence number for the CSEQ and RSEQ headers.

Return Values The value of errno is not changed by these calls in the event of an error.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_get_dialog_state, sip_get_dialog_callid, sip_get_dialog_local_tag, sip_get_dialog_remote_tag, sip_get_dialog_local_uri, sip_get_dialog_remote_uri, sip_get_dialog_local_contact_uri, sip_get_dialog_remote_target_uri, sip_get_dialog_route_set, sip_get_dialog_local_cseq, sip_get_dialog_remote_cseq, sip_get_dialog_type, sip_get_dialog_method, sip_is_dialog_secure, sip_get_dialog_msgcnt – get dialog attributes

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

```
int sip_get_dialog_state(sip_dialog_t dialog, int *error);

const sip_str_t *sip_get_dialog_callid(sip_dialog_t dialog,
int *error);

const sip_str_t *sip_get_dialog_local_tag(sip_dialog_t dialog,
int *error);

const sip_str_t *sip_get_dialog_remote_tag(sip_dialog_t dialog,
int *error);

const struct sip_uri *sip_get_dialog_local_uri(sip_dialog_t dialog,
int *error);

const struct sip_uri *sip_get_dialog_remote_uri(sip_dialog_t dialog,
int *error);

const struct sip_uri *sip_get_dialog_local_contact_uri(
sip_dialog_t dialog, int *error);

const struct sip_uri *sip_get_dialog_remote_target_uri(
sip_dialog_t dialog, int *error);

const sip_str_t *sip_get_dialog_route_set(sip_dialog_t dialog,
int *error);

boolean_t sip_is_dialog_secure(sip_dialog_t dialog,
int *error);

uint32_t sip_get_dialog_local_cseq(sip_dialog_t dialog,
int *error);

uint32_t sip_get_dialog_remote_cseq(sip_dialog_t dialog,
int *error);

int sip_get_dialog_type(sip_dialog_t dialog, int *error);

int sip_get_dialog_method(sip_dialog_t dialog, int *error);

int sip_get_dialog_msgcnt(sip_dialog_t dialog, int *error);
```

Description For functions that return a pointer of type sip_str_t, sip_str_t is supplied by:

```
typedef struct sip_str {
    char    *sip_str_ptr;
```

```

        int    sip_str_len;
    }sip_str_t;

```

The *sip_str_ptr* parameter points to the start of the returned value and *sip_str_len* supplies the length of the returned value.

The `sip_get_dialog_state()` returns the state of the *dialog*. A *dialog* can be in one of the following states:

```

SIP_DLG_NEW
SIP_DLG_EARLY
SIP_DLG_CONFIRMED
SIP_DLG_DESTROYED

```

The `sip_get_dialog_callid()` function returns the call ID value maintained in the *dialog*.

The `sip_get_dialog_local_tag()` and `sip_get_dialog_remote_tag()` functions return the local and remote tag values, maintained in the *dialog*.

The `sip_get_dialog_local_uri()`, `sip_get_dialog_remote_uri()`, `sip_get_dialog_local_contact_uri()`, and `sip_get_dialog_remote_target_uri()` functions return the local, remote, local contract, and the remote target URIs, maintained in the *dialog*.

The `sip_get_dialog_route_set()` function returns the route set, if any, maintained in the *dialog*.

The `sip_get_dialog_local_cseq()` and `sip_get_dialog_remote_cseq()` functions return the local and remote CSEQ numbers maintained in the *dialog*.

The `sip_get_dialog_type()` function returns one of the following dialog types, depending on whether it is created by the client or the server.

```

SIP_UAC_DIALOG    created by client
SIP_UAS_DIALOG    created by server

```

The `sip_get_dialog_method()` function returns the SIP method, INVITE or SUBSCRIBE, of the request that created the dialog.

The `sip_is_dialog_secure()` function returns `B_TRUE` if the *dialog* is secure and `B_FALSE` otherwise.

The `sip_get_dialog_msgcnt()` function returns the number of SIP messages (requests and responses) that were sent and received within the context of the given dialog.

Return Values The `sip_get_dialog_state()`, `sip_get_dialog_local_cseq()`, `sip_get_dialog_remote_cseq()`, `sip_get_dialog_type()`, `sip_get_dialog_method()`, and `sip_get_dialog_msgcnt()` functions return the required value on success and -1 on failure.

The `sip_get_dialog_callid()`, `sip_get_dialog_local_tag()`, `sip_get_dialog_remote_tag()`, `sip_get_dialog_local_uri()`, `sip_get_dialog_remote_uri()`, `sip_get_dialog_local_contact_uri()`, `sip_get_dialog_remote_target_uri()`, and `sip_get_dialog_route_set()` functions return the required value on success and NULL on failure.

The value of `errno` is not changed by these calls in the event of an error.

Errors These functions take an *error* argument.

If the error is non-null, one of the following values is set:

EINVAL

The *dialog* is NULL or the stack is not configured to manage dialogs.

ENOTSUP

The input SIP message cannot be modified.

ENOMEM

The memory allocation fails when the request/response line or the headers in the ACK request are created.

On success, the value of the location pointed to by *error* is set to 0.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_get_header – get a SIP header from a message

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

```
const struct sip_header *sip_get_header(sip_msg_t sip_msg,
    char *header_name, sip_header_t old_header, int *error);
```

Description The sip_get_header() function returns the header specified by *header_name* (long or compact form) from the SIP message *sip_msg*. If *header_name* is NULL, the first header in the SIP message is returned. The *old_header*, if non-null, specifies the starting position in *sip_msg* from which the search is started. Otherwise, the search begins at the start of the SIP message. For example, to get the first VIA header from the SIP message *sip_msg*:

```
via_hdr = sip_get_header(sip_msg, "VIA", NULL, &error);
```

To get the next VIA header from *sip_msg*:

```
via_hdr = sip_get_header(sip_msg, "VIA", via_hdr, &error);
```

The sip_get_header() function ignores any header that is marked as deleted.

Return Values On success, the sip_get_header() function returns the queried header. On failure, it returns NULL.

The value of `errno` is not changed by these calls in the event of an error.

Errors The following value may be returned:

EINVAL The *header_name* specified in the SIP message is not present or has been deleted; or, the *header_name* is not specified and there are no “un-deleted” headers in the SIP message.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_get_header_value, sip_get_next_value – get a SIP header value

Synopsis cc [*flag ...*] file ... -lsip [*library ...*]
#include <sip.h>

```
const struct sip_value *sip_get_header_value
    (const struct sip_header *sip_header, int *error);

const struct sip_value *sip_get_next_value
    (sip_header_value_t old_value, int *error);
```

Description The sip_get_header_value() function returns the first valid value from SIP header *sip_header*.

The sip_get_next_value() function returns the next valid value following the SIP value *old_value*.

Return Values These functions return the queried value on success and NULL on failure.

The value of `errno` is not changed by these calls in the event of an error.

Errors If the error is non-null, one of the following values is set:

- EINVAL** If any of the required input is NULL or if the specified SIP header value is marked deleted.
- EPROTO** If the returned SIP header value is invalid (i.e. the parser encountered errors when parsing the value).

On success, the value of the location pointed to by *error* is set to 0.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name `sip_get_msg_len` – returns the length of the SIP message

Synopsis `cc [flag ...] file ... -lsip [library ...]`
`#include <sip.h>`

```
int sip_get_msg_len(sip_msg_t sip_msg,
                   int *error);
```

Description The `sip_get_msg_len()` function will return the length of the SIP message `sip_msg`.

Return Values For functions that return an integer, the return value is the specified value on success and -1 on error.

The value of `errno` is not changed by these calls in the event of an error.

Errors This function takes a pointer to an integer `error` as an argument. If the error is non-null, one of the following values is set:

EINVAL The input SIP message `sip_msg` or the header value is null; or the specified header/header value is deleted.

EPROTO The header value is not present or invalid. The parser could not parse it correctly.

ENOMEM There is an error allocating memory for the return value.

On success, the value of the location pointed to by `error` is set to 0.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_get_num_via, sip_get_branchid – get VIA header specific attributes

Synopsis cc [*flag ...*] *file ...* -lsip [*library ...*]
#include <sip.h>

```
int sip_get_num_via(sip_msg_t sip_msg,  
    int *error);  
  
char *sip_get_branchid(sip_msg_t sip_msg,  
    int *error);
```

Description The sip_get_num_via() function returns the number of VIA headers in the SIP message *sip_msg*.

The sip_get_branchid() function returns the branch ID value from the topmost VIA header. The caller is responsible for freeing the returned string.

Return Values The sip_get_num_via() function returns the number of VIA headers on success.

The sip_get_branchid() function returns the branch ID on success and NULL on failure.

The value of `errno` is not changed by these calls in the event of an error.

Errors If the error is non-null, one of the following values is set:

- EINVAL** The *sip_msg* is NULL.
- ENOENT** For the *sip_get_branchid* function, there is no VIA header or the VIA header has no branch parameter.
- EPROTO** For the *sip_sip_get_trans.3sipget_branchid* function, the VIA value is invalid. The parser encountered an error or errors while parsing the VIA header.
- ENOMEM** For the *sip_get_branchid* function, there is an error in allocating memory for the branch ID.

On success, the value of the location pointed to by *error* is set to 0.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_get_param_value, sip_get_params, sip_is_param_present – get parameter information for a SIP header value

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

```
const sip_str_t *sip_get_param_value
    (sip_header_value_t header_value, char *param_name, int *error);

const sip_param_t *sip_get_params
    (sip_header_value_t header_value, int *error);

boolean_t sip_is_param_present
    (const sip_param_t *param_list, char *param_name, int param_len);
```

Description The sip_get_param_value() function returns the value for the parameter name specified by *param_name* from the SIP header value *header_value*.

For functions that return a pointer of type sip_str_t, sip_str_t is supplied by:

```
typedef struct sip_str {
    char    *sip_str_ptr;
    int     sip_str_len;
}sip_str_t;
```

The *sip_str_ptr* parameter points to the start of the returned value and *sip_str_len* supplies the length of the returned value.

The sip_get_params() function returns the parameter list, if any, for the SIP header value *header_value*.

The sip_is_param_present() function returns B_TRUE if the parameter specified by *param_name* of length supplied in *param_len* is present in the parameter list, *param_list*. Otherwise, it returns B_FALSE.

Return Values With the exception of sip_is_param_present(), these functions return the queried value on success and NULL on failure.

The value of errno is not changed by these calls in the event of an error.

Errors If the error is non-null, one of the following values is set:

EINVAL	If any of the required input is NULL or if the specified SIP header value is marked deleted.
EPROTO	If the returned SIP header value is invalid (i.e. the parser encountered errors when parsing the value).

On success, the value of the location pointed to by *error* is set to 0.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_get_request_method, sip_get_response_code, sip_get_response_phrase, sip_get_sip_version – obtain attributes from the start line in a SIP message

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

```

sip_method_t sip_get_request_method(const sip_msg_t sip_msg,
    int *error);

int sip_get_response_code(sip_msg_t sip_msg,
    int *error);

const sip_str_t *sip_get_response_phrase(sip_msg_t sip_msg,
    int *error);

const sip_str_t *sip_get_sip_version(sip_msg_t sip_msg,
    int *error);

```

Description For functions that return a pointer of type sip_str_t, sip_str_t is supplied by:

```

typedef struct sip_str {
    char    *sip_str_ptr;
    int     sip_str_len;
} sip_str_t;

```

The *sip_str_ptr* parameter points to the start of the returned value and *sip_str_len* supplies the length of the returned value.

For example, given the following request line in a SIP message *sip_msg* that is input to sip_get_request_uri_str():

```
FROM : <Alice sip:alice@atlanta.com>;tag=1928301774
```

the return is a pointer to *sip_str_t* with the *sip_str_ptr* member pointing to “A” of Alice and *sip_str_len* being set to 5, the length of Alice.

Access functions for headers that can have multiple values take the value as the input, while those that can have only one value take the SIP message *sip_msg* as the input.

The sip_get_request_method() function will return the SIP method from the request line in the SIP message *sip_msg*. The method can be one of the following:

```

INVITE
ACK
OPTIONS
BYE
CANCEL
REGISTER
REFER
INFO

```

SUBSCRIBE
NOTIFY
PRACK
UNKNOWN

The `sip_get_response_code()` function will return the response code *response* from the request line in the SIP message *sip_msg*.

The `sip_get_response_phrase()` function will return the response phrase *response* from the request line in the SIP message *sip_msg*.

The `sip_get_sip_version()` function will return the version of the SIP protocol from the request or the response line in the SIP message *sip_msg*.

Return Values For functions that return a pointer to *sip_str_t*, the return value is the specified value on success or NULL in case of error. For functions that return an integer, the return value is the specified value on success and -1 on error.

The value of `errno` is not changed by these calls in the event of an error.

Errors These functions take a pointer to an integer *error* as an argument. If the error is non-null, one of the following values is set:

- EINVAL** The input SIP message *sip_msg* or the header value is null; or the specified header/header value is deleted.
- EPROTO** The header value is not present or invalid. The parser could not parse it correctly.
- ENOMEM** There is an error allocating memory for the return value.

On success, the value of the location pointed to by *error* is set to 0.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name

sip_get_request_uri_str – return request URI

Synopsis

```
cc [ flag ... ] file ... -lsip [ library ... ]
#include <sip.h>

const sip_str_t *sip_get_request_uri_str(sip_msg_t sip_msg,
int *error);
```

Description

For functions that return a pointer of type *sip_str_t*, *sip_str_t* is supplied by:

```
typedef struct sip_str {
    char *sip_str_ptr;
    int sip_str_len;
}sip_str_t;
```

The *sip_str_ptr* parameter points to the start of the returned value and *sip_str_len* supplies the length of the returned value.

For example, given the following request line in a SIP message input to *sip_get_request_uri_str()*:

```
INVITE sip:marconi@radio.org SIP/2.0
```

the return is a pointer to *sip_str_t* with the *sip_str_ptr* member pointing to “s” of *sip:marconi@radio.org* and *sip_str_len* being set to 21, the length of *sip:marconi@radio.org*.

The *sip_get_request_uri_str()* function returns the URI string from the request line in the SIP message *sip_msg*.

Return Values

The *sip_get_request_uri_str()* function returns the URI string. The function returns NULL on failure.

The value of *errno* is not changed by these calls in the event of an error.

Errors

If the error is non-null, one of the following values is set:

EINVAL For the *sip_get_request_uri_str()* function, there is no request line is in the SIP message.

EPROTO For *sip_get_request_uri_str*, the request URI is invalid.

On success, the value of the location pointed to by *error* is set to 0.

Attributes

See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_get_resp_desc – return the response phrase

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

```
char *sip_get_resp_desc(int *resp_code);
```

Description The sip_get_resp_desc() function returns the response phrase for the given response code in *resp_code*. The response code is not one that is listed in RFC 3261 (Section 21). The returned string is “UNKNOWN”.

Return Values The value of `errno` is not changed by these calls in the event of an error.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_get_trans – lookup a transaction

Synopsis

```
cc [ flag ... ] file ... -lsip [ library ... ]
#include <sip.h>

const struct sip_xaction *sip_get_trans(sip_msg_t sip_msg, int which,
int *error);
```

Description
The sip_get_trans() transaction for the SIP message *sip_msg*. A transaction is not freed if there are any references on it.

The transaction type should be specified as one of the following:

SIP_CLIENT_TRANSACTION - lookup a client transaction
SIP_SERVER_TRANSACTION - lookup a server transaction

The sip_get_trans() function matches a transaction to a message as specified in RFC 3261, sections 17.1.3 and 17.2.3. The sip_get_trans() function holds a reference to the returned transaction. The caller must release this reference after use.

Return Values
The sip_get_trans() function returns the required value on success or NULL on failure.

The value of `errno` is not changed by these calls in the event of an error.

Errors
On success, the value of the location pointed to by *error* is set to 0.

Attributes
See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also
[libsip\(3LIB\)](#)

Name sip_get_trans_method, sip_get_trans_state, sip_get_trans_orig_msg, sip_get_trans_conn_obj, sip_get_trans_resp_msg, sip_get_trans_branchid – get transaction attributes

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

```

sip_method_t sip_get_trans_method(sip_transaction_t sip_trans,
    int *error);

int sip_get_trans_state(sip_transaction_t trans, int *error);

const struct sip_message *sip_get_trans_orig_msg
    (sip_transaction_t sip_trans, int *error);

const struct sip_message *sip_get_trans_resp_msg
    (sip_transaction_t sip_trans, int *error);

const struct sip_conn_object *sip_get_trans_conn_obj
    (sip_transaction_t sip_trans, int *error);

char *sip_get_trans_branchid(sip_transaction_t trans, int *error);

```

Description The sip_get_trans_method() function returns the method the SIP message that created the transaction *sip_trans*.

The sip_get_trans_state() function returns the state of the transaction *sip_trans*.

A newly created transaction is in the state:

SIP_NEW_TRANSACTION

A client transaction could be in one of the following states:

SIP_CLNT_CALLING
 SIP_CLNT_INV_PROCEEDING
 SIP_CLNT_INV_TERMINATED
 SIP_CLNT_INV_COMPLETED
 SIP_CLNT_TRYING
 SIP_CLNT_NONINV_PROCEEDING
 SIP_CLNT_NONINV_TERMINATED
 SIP_CLNT_NONINV_COMPLETED

A server transaction could be in one of the following states:

SIP_SRV_INV_PROCEEDING
 SIP_SRV_INV_COMPLETED
 SIP_SRV_CONFIRMED

SIP_SRV_INV_TERMINATED
SIP_SRV_TRYING
SIP_SRV_NONINV_PROCEEDING
SIP_SRV_NONINV_COMPLETED
SIP_SRV_NONINV_TERMINATED

The `sip_get_trans_orig_msg()` function returns the message that created the transaction *sip_trans*. This could be a request on the client or a response on the server.

The `sip_get_trans_resp_msg()` function returns the last response that was sent on the transaction *sip_trans*. Typically, this response is used by the transaction layer for retransmissions for unreliable transports or for responding to retransmitted requests. A response that terminates a transaction is not returned.

The `sip_get_trans_conn_obj()` function returns the cached connection object, if any, in the transactions *sip_trans*.

The `sip_get_trans_branchid()` function returns the branch ID for the message that created the transactions *sip_trans*. The caller is responsible for freeing the returned string.

Return Values The `sip_get_trans_orig_msg()`, `sip_get_trans_resp_msg()`, `sip_get_trans_conn_obj()`, and `sip_get_trans_branchid()` functions return the required value on success or NULL on failure.

The `sip_get_trans_state()` and `sip_get_trans_method()` functions return the required value on success and -1 on failure.

The value of `errno` is not changed by these calls in the event of an error.

Errors If the error is non-null, one of the following values is set:

- EINVAL** The input transaction *sip_trans* is NULL.
- ENOMEM** For `sip_get_trans_branchid()` there is an error allocating memory for the branch ID string.

On success, the value of the location pointed to by *error* is set to 0.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_get_uri_parsed – return the parsed URI

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

const struct sip_uri *sip_get_uri_parsed(sip_header_value_t *value*,
int **error*);

Description The sip_get_uri_parsed() function returns the parsed URI *sip_uri* from the SIP header value specified in *value*.

Return Values The sip_get_uri_parsed() function returns the parsed URI *sip_uri* on success. The function returns NULL on failure.

The value of `errno` is not changed by these calls in the event of an error.

Errors If the error is non-null, following value is set:

- EINVAL** The SIP header value of the SIP message is NULL or there is no URI.

The input URI is null or the requested URI component is invalid. The error flag is set for the requested component.

The URI parameters or headers are requested from a non-SIP[S] URI; or the 'opaque', 'query', 'path', 'reg-name' components are requested from a SIP[S] URI.

On success, the value of the location pointed to by *error* is set to 0.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_guid – generate a random string

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

```
char *sip_guid();
```

Description The sip_guid() function can be used to generate a random string. The caller is responsible for freeing the returned string.

Return Values The sip_guid() function returns a string on success and NULL on failure.

The value of errno is not changed by these calls in the event of an error.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_hold_dialog, sip_release_dialog – hold/release reference on a dialog

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

void sip_hold_dialog(sip_dialog_t *dialog*);
void sip_release_dialog(sip_dialog_t *dialog*);

Description For functions that return a pointer of type sip_str_t, sip_str_t is supplied by:

typedef struct sip_str {
 char *sip_str_ptr;
 int sip_str_len;
}sip_str_t;

The *sip_str_ptr* parameter points to the start of the returned value and *sip_str_len* supplies the length of the returned value.

The sip_hold_dialog() function is used to hold a reference on the *dialog*. A dialog is not freed if there are any references on it.

The sip_release_dialog() function is used to release a reference in the *dialog*. If the reference in a dialog drops to 0 and it is in SIP_DLG_DESTROYED state, it is freed.

Return Values The value of errno is not changed by these calls in the event of an error.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_hold_msg, sip_free_msg – adds and removes a reference from a SIP message

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

```
void sip_hold_msg(sip_msg_t sip_msg);
```

```
void sip_free_msg(sip_msg_t sip_msg);
```

Description The sip_hold_msg() function adds a reference to the SIP message passed as the argument. The reference is used to prevent the SIP message from being freed when in use.

The sip_free_msg() function is used to remove an added reference on the SIP message passed as the argument. If this is the last reference on the SIP message (i.e. the number of references on the SIP message is 0), the SIP message is destroyed and associated resources freed. Freeing a SIP message does not set the sip_msg pointer to NULL. Applications should not expect the pointer to a freed SIP message to be NULL.

Return Values The value of errno is not changed by these calls in the event of an error.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_hold_trans, sip_release_trans – hold or release reference on a transaction

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

void sip_hold_trans(sip_transaction_t sip_trans);
void sip_release_trans(sip_transaction_t sip_trans);

Description The sip_hold_trans() function is used to hold a reference on the transaction *sip_trans*. A transaction is not freed if there are any references on it.

The sip_release_trans() function is used to release a reference on the transaction *sip_trans*. If the reference falls to 0 and the transaction is in a terminated state, the transaction is freed.

Return Values The value of errno is not changed by these calls in the event of an error.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_init_conn_object, sip_clear_stale_data, sip_conn_destroyed – connection object related functions

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

```
int sip_init_conn_object(sip_conn_object_t obj);
void sip_clear_stale_data(sip_conn_object_t obj);
void sip_conn_destroyed(sip_conn_object_t obj);
```

Description The sip_init_conn_object() function initializes the connection object *obj* for use by the stack. The first member of the connection object (a void *) is used by the stack to store connection object specific stack-private data.

The sip_clear_stale_data() function is used to clear any stack-private data in the connection object *obj*.

The sip_conn_destroyed() function is used to intimate the stack of the pending destruction of the connection object *obj*. The stack clean up any stack-private data in *obj* and also removes *obj* from any caches the stack maintains.

Return Values The sip_init_conn_object() function returns 0 on success and the appropriate error value on failure.

The value of `errno` is not changed by these calls in the event of an error.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_is_sip_uri, sip_get_uri_scheme, sip_get_uri_host, sip_get_uri_user, sip_get_uri_password, sip_get_uri_port, sip_get_uri_params, sip_get_uri_headers, sip_get_uri_opaque, sip_get_uri_query, sip_get_uri_path, sip_get_uri_regname, sip_is_uri_teluser, sip_get_uri_errflags, sip_uri_errflags_to_str – get URI related attributes

Synopsis cc [*flag* ...] file ... -lsip [*library* ...]
#include <sip.h>

```

boolean_t sip_is_sip_uri(const struct sip_uri *sip_uri);

const sip_str_t *sip_get_uri_scheme(const struct sip_uri *sip_uri,
    int *error);

const sip_str_t *sip_get_uri_user(const struct sip_uri *sip_uri,
    int *error);

const sip_str_t *sip_get_uri_password(const struct sip_uri *sip_uri,
    int *error);

const sip_str_t *sip_get_uri_host(const struct sip_uri *sip_uri,
    int *error);

int sip_get_uri_port(const struct sip_uri *sip_uri,
    int *error);

const sip_param_t *sip_get_uri_params(const struct sip_uri *sip_uri,
    int *error);

const sip_str_t *sip_get_uri_headers(const struct sip_uri *sip_uri,
    int *error);

const sip_str_t *sip_get_uri_opaque(const struct sip_uri *sip_uri,
    int *error);

const sip_str_t *sip_get_uri_query(const struct sip_uri *sip_uri,
    int *error);

const sip_str_t *sip_get_uri_path(const struct sip_uri *sip_uri,
    int *error);

const sip_str_t *sip_get_uri_regname(const struct sip_uri *sip_uri,
    int *error);

boolean_t sip_is_uri_teluser(const struct sip_uri *sip_uri);

int sip_get_uri_errflags(const struct sip_uri *sip_uri,
    int *error);

char *sip_uri_errflags_to_str(int uri_errflags);

```

Description For functions that return a pointer of type *sip_str_t*, *sip_str_t* is supplied by:

```

typedef struct sip_str {
    char *sip_str_ptr;
    int sip_str_len;
} sip_str_t;

```

The *sip_str_ptr* parameter points to the start of the returned value and *sip_str_len* supplies the length of the returned value.

For example, given the following request line in a SIP message input to `sip_get_request_uri_str()`:

```
INVITE sip:marconi@radio.org SIP/2.0
```

the return is a pointer to *sip_str_t* with the *sip_str_ptr* member pointing to “s” of `sip:marconi@radio.org` and *sip_str_len* being set to 21, the length of `sip:marconi@radio.org`.

The `sip_is_sip_uri()` function takes a parsed URI *sip_uri* and returns `B_TRUE` if it is a SIP[S] URI and `B_FALSE` if it is not. A URI is a SIP[S] URI if the scheme in the URI is either “sip” or “sips”.

The `sip_get_uri_user()` function takes a parsed URI *sip_uri* and returns the value of the “user” component, if present.

The `sip_get_uri_password()` function takes a parsed URI *sip_uri* and returns the value of the “password” component, if present.

The `sip_get_uri_host()` function takes a parsed URI *sip_uri* and returns the value of the “host” component, if present.

The `sip_get_uri_port()` function takes a parsed URI *sip_uri* and returns the value of the “port” component, if present.

The `sip_get_uri_params()` function takes a parsed URI *sip_uri* and returns the list of URI parameters, if present, from a SIP[S] URI.

The `sip_get_uri_headers()` function takes a parsed URI *sip_uri* and returns 'headers' from a SIP[S] URI.

The `sip_get_uri_query()` function takes a parsed URI *sip_uri* and returns the value of the 'query' component, if present.

The `sip_get_uri_path()` function takes a parsed URI *sip_uri* and returns the value of the 'path' component, if present.

The `sip_get_uri_regname()` function takes a parsed URI *sip_uri* and returns the value of the 'regname' component, if present.

The `sip_is_uri_teluser()` function returns `B_TRUE` if the user component is a telephone-subscriber. Otherwise, `B_FALSE` is returned.

The `sip_get_uri_errflags()` function returns the error flags from a parsed URI *sip_uri*. The returned value is a bitmask with the appropriate bit set when the parser, `sip_parse_uri()`, encounters an error. The following are the possible error values that could be set:

Bit value	Error	Comments
0x00000001	SIP_URIERR_SCHEME	invalid scheme
0x00000002	SIP_URIERR_USER	invalid user name
0x00000004	SIP_URIERR_PASS	invalid password
0x00000008	SIP_URIERR_HOST	invalid host
0x00000010	SIP_URIERR_PORT	invalid port number
0x00000020	SIP_URIERR_PARAM	invalid URI parameters
0x00000040	SIP_URIERR_HEADER	invalid URI headers
0x00000080	SIP_URIERR_OPAQUE	invalid opaque
0x00000100	SIP_URIERR_QUERY	invalid query
0x00000200	SIP_URIERR_PATH	invalid path
0x00000400	SIP_URIERR_REGNAME	invalid reg-name

The `sip_uri_errflags_to_str()` function takes the error flags from a parsed URI *sip_uri* and forms a string with all the error bits that are set. For example, if `SIP_URIERR_PASS` and `SIP_URIERR_PORT` are set in a parsed URI *sip_uri*, the `sip_uri_errflags_to_str()` function returns a string such as:

"Error(s) in PASSWORD, PORT part(s)"

The caller is responsible for freeing the returned string.

Return Values The `sip_get_uri_scheme()`, `sip_get_uri_user()`, `sip_get_uri_password()`, `sip_get_uri_host()`, `sip_get_uri_params()`, `sip_get_uri_headers()`, `sip_get_uri_opaque()`, `sip_get_uri_query()`, `sip_get_uri_path()`, `sip_get_uri_regname()`, and `sip_uri_errflags_to_str()` functions return the requested value on success and `NULL` on failure.

The `sip_get_uri_port()` function returns *port* from the URI or `0` if the port is not present. The returned port is in host byte order.

The value of `errno` is not changed by these calls in the event of an error.

Errors If the error is non-null, the following value is set:

- `EINVAL` The SIP header value of the SIP message is `NULL` or there is no URI.

The input URI is null or the requested URI component is invalid. The error flag is set for the requested component.

The URI parameters or headers are requested from a non-SIP[S] URI; or the 'opaque', 'query', 'path', 'reg-name' components are requested from a SIP[S] URI.

On success, the value of the location pointed to by *error* is set to `0`.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_msg_is_request, sip_message_is_response – determine if the SIP message is a request or a response

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

```
boolean_t sip_msg_is_request(const sip_msg_t sip_msg,  
                           int *error);  
  
boolean_t sip_msg_is_response(const sip_msg_t sip_msg,  
                             int *error);
```

Description The sip_msg_is_request() function returns B_TRUE if *sip_msg* is a request and B_FALSE otherwise.

The sip_msg_is_response() function returns B_TRUE if *sip_msg* is a response and B_FALSE otherwise.

Return Values For functions that return an integer, the return value is the specified value on success and -1 on error.

The value of `errno` is not changed by these calls in the event of an error.

Errors These functions take a pointer to an integer *error* as an argument. If the error is non-null, one of the following values is set:

- EINVAL** The input SIP message *sip_msg* or the header value is null; or the specified header/header value is deleted.
- EPROTO** The header value is not present or invalid. The parser could not parse it correctly.
- ENOMEM** There is an error allocating memory for the return value.

On success, the value of the location pointed to by *error* is set to 0.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_msg_to_str, sip_hdr_to_str, sip_reqline_to_str, sip_respline_to_str, sip_sent_by_to_str – return string representations

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

```
char *sip_msg_to_str(sip_msg_t sip_msg,
                    int *error);

char *sip_hdr_to_str(sip_header_t sip_header,
                    int *error);

char *sip_reqline_to_str(sip_msg_t sip_msg,
                        int *error);

char *sip_respline_to_str(sip_msg_t sip_msg,
                         int *error);

char *sip_sent_by_to_str(int *error);
```

Description The sip_msg_to_str() function returns the string representation of the SIP message *sip_msg*. Deleted headers are not included in the returned string. The caller is responsible for freeing the returned string.

The sip_hdr_to_str() function returns the string representation of the SIP header *sip_header*. The caller is responsible for freeing the returned string.

The sip_reqline_to_str() function returns the string representation of the request line from the SIP message *sip_msg*. The caller is responsible for freeing the returned string.

The sip_respline_to_str() function returns the string representation of the response line from the SIP message *sip_msg*. The caller is responsible for freeing the returned string.

The sip_sent_by_to_str() function can be used to retrieve the list of sent-by values registered with the stack. The returned string is a comma separated list of sent-by values. The caller is responsible for freeing the returned string.

Return Values The sip_msg_to_str(), sip_hdr_to_str(), sip_reqline_to_str(), sip_respline_to_str(), and sip_sent_by_to_str() functions return the relevant string on success and NULL on failure.

The value of `errno` is not changed by these calls in the event of an error.

Errors For the sip_msg_to_str(), sip_hdr_to_str(), sip_reqline_to_str(), and sip_respline_to_str(), one of the following values is set if the error is non-null:

EINVAL Input is null.

ENOMEM Memory allocation failure.

On success, the value of the location pointed to by *error* is set to 0.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_new_msg – allocates a new SIP message

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

```
sip_msg_t sip_new_msg();
```

Description The sip_new_msg() function allocates and returns a new SIP message.

Return Values The sip_new_msg() function returns the newly allocated SIP message on success and NULL on failure.

The value of `errno` is not changed by these calls in the event of an error.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_parse_uri, sip_free_parsed_uri – parse a URI and free a parsed URI

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

```
sip_uri_t sip_parse_uri(sip_str_t *uri_str,  
                        int *error);
```

```
void sip_free_parsed_uri(sip_uri_t sip_uri);
```

Description For functions that return a pointer of type *sip_str_t*, *sip_str_t* is supplied by:

```
typedef struct sip_str {  
    char *sip_str_ptr;  
    int sip_str_len;  
}sip_str_t;
```

The *sip_str_ptr* parameter points to the start of the returned value and *sip_str_len* supplies the length of the returned value.

For example, given the following request line in a SIP message input to *sip_get_request_uri_str()*:

```
INVITE sip:marconi@radio.org SIP/2.0
```

the return is a pointer to *sip_str_t* with the *sip_str_ptr* member pointing to “s” of *sip:marconi@radio.org* and *sip_str_len* being set to 21, the length of *sip:marconi@radio.org*.

The *sip_parse_uri()* function takes a URI string in the form *sip_str_t* and returns a parsed URI *sip_uri*. The syntax of the URI is as specified in RFC 3261, section 25.1. If the parser encounters an error when parsing a component, it sets the appropriate error bit in the error flags and proceeds to the next component, if present.

The *sip_free_parsed_uri()* function takes a parsed URI *sip_uri*, obtained from *sip_parse_uri()*, and frees any associated memory.

Return Values The *sip_parse_uri()* function returns the parsed URI *sip_uri* on success. It returns a NULL if memory cannot be allocated for the parsed URI.

The value of *errno* is not changed by these calls in the event of an error.

Errors If the error is non-null, the following values is set:

EINVAL The SIP header value of the SIP message is NULL or there is no URI.

The input URI is null or the requested URI component is invalid. The error flag is set for the requested component.

The URI parameters or headers are requested from a non-SIP[S] URI; or the 'opaque', 'query', 'path', 'reg-name' components are requested from a SIP[S] URI.

On success, the value of the location pointed to by *error* is set to 0.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_process_new_packet – send an inbound message to the SIP stack for processing

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

```
void sip_process_new_packet(sip_conn_object_t conn_object,  
    void *msgstr, size_t msgstr);
```

Description The sip_process_new_packet() function receives incoming message, creates a SIP message, processes it and passes it on to the application. For a byte-stream protocol like TCP sip_process_new_packet() also takes care of breaking the byte stream into message boundaries using the CONTENT-LENGTH header in the SIP message. If the SIP message arriving on TCP does not contain a CONTENT-LENGTH header, the behavior is unspecified. sip_process_new_packet() deletes the SIP message on return from the application's receive function, thus if the application wishes to retain the SIP message for future use, it must use sip_hod_msg() so that the message is not freed by sip_process_new_packet().

Return Values The value of errno is not changed by these calls in the event of an error.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_register_sent_by, sip_unregister_sent_by, sip_unregister_all_sent_by – allows registering and un-registering sent-by values

Synopsis cc [*flag ...*] *file ...* -lsip [*library ...*]
#include <sip.h>

```
int sip_register_sent_by(char *val);
void sip_unregister_sent_by(char *val);
void sip_unregister_all_sent_by(int *error);
```

Description The sip_register_sent_by() function can be used to register a list of hostnames or IP addresses that the application may add to the VIA headers. The *val* is a comma separated list of such sent-by values. If any value is registered using sip_register_sent_by(), the SIP stack validates incoming responses to check if the sent-by parameter in the topmost VIA header is part of the registered list. If the check fails, the response is dropped. If there are no sent-by values registered, there is no check done on incoming responses.

The sip_unregister_sent_by() and sip_unregister_all_sent_by() functions are used to un-register sent-by values. The *val* for sip_unregister_sent_by() is a comma separated list of sent-by values that need to be un-registered. sip_unregister_all_sent_by() un-registers all the values that have been registered.

Return Values The sip_register_sent_by() function returns 0 on success and the appropriate error value on failure.

The value of errno is not changed by these calls in the event of an error.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_sendmsg – send an outbound SIP message to the SIP stack for processing

Synopsis `cc [flag ...] file ... -lsip [library ...]`
`#include <sip.h>`

```
int sip_sendmsg(sip_conn_object_t obj, sip_msg_t sip_msg,
               sip_dialog_t dialog, uint32_t flags);
```

Description The `sip_sendmsg()` function is used to send an outbound SIP message *sip_msg* to the SIP stack on its way to the peer. The connection object for the SIP message is passed as *obj*. The caller also provides the dialog associated with the message, if one exists. The value of flags is the result of ORing the following, as required:

SIP_SEND_STATEFUL	Send the request or response statefully. This results in the stack creating and maintaining a transaction for this request/response. If this flag is not set transactions are not created for the request/response.
SIP_DIALOG_ON_FORK	When this flag is set, the stack may create multiple dialogs for a dialog completing response. This may result due to forking of the dialog creating request. If this flag is not set, the first response to a dialog creating request creates a dialog, but subsequent ones do not. It is only meaningful if the stack is configured to maintain dialogs.

Return Values The `sip_sendmsg()` function returns 0 on success and the appropriate error on failure.

The value of `errno` is not changed by these calls in the event of an error.

Errors The `sip_sendmsg()` function can return one of the following errors on failure:

EINVAL	If a message is being statefully sent and the <i>branchid</i> in the VIA header does not conform to RFC 3261 or when accessing CSEQ header while creating a transaction.
ENOENT	If a message is being statefully sent, error getting the CSEQ header while creating a transaction.
EPROTO	If a message is being statefully sent, error getting the CSEQ value while creating a transaction.
ENOMEM	If the message is being statefully sent, error allocating memory for creating or adding a transaction or during transaction related processing.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name sip_stack_init – initializes SIP stack

Synopsis cc [*flag* ...] *file* ... -lsip [*library* ...]
#include <sip.h>

```
int sip_stack_init(sip_stack_init_t * stack_val);
```

Description The sip_stack_init() function is used to initialize the SIP stack. The stack can be initialized by a process only once. Any shared library that is linked with a main program or another library that has already initialized the stack will encounter a failure when trying to initialize the stack.

The initialization structure is given by:

```
typedef struct sip_stack_init_s {
    int                sip_version;
    uint32_t           sip_stack_flags;
    sip_io_pointers_t   *sip_io_pointers;
    sip_ulp_pointers_t  *sip_ulp_pointers;
    sip_header_function_t *sip_function_table;
};
```

sip_version This must be set to SIP_STACK_VERSION.

sip_stack_flags If the application wants the SIP stack to maintain dialogs, this flag must be set to SIP_STACK_DIALOGS. Otherwise, it must be set to 0. If SIP_STACK_DIALOGS is not set, the stack does not deal with dialogs at all.

Upper Layer Registrations These include callbacks that are invoked to deliver incoming messages or error notification.

The callback functions should not create a thread and invoke a function that could recursively invoke the callback. For example, the callback function for a transition state change notification should not create a thread to send a SIP message that results in a change in the state of the transaction, which would again invoke the callback function.

The registration structure is supplied by:

```
typedef struct sip_ulp_pointers_s {
    void      (*sip_ulp_recv)(const sip_conn_object_t,
                             sip_msg_t, const sip_dialog_t);
    uint_t    (*sip_ulp_timeout)(void *,
                                void (*func)(void *),
                                struct timeval *);
    boolean_t (*sip_ulp_untimeout)(uint_t);
    int       (*sip_ulp_trans_error)
               (sip_transaction_t, int, void *);
    void      (*sip_ulp_dlg_del)(sip_dialog_t,
                                sip_msg_t, void *);
    void      (*sip_ulp_trans_state_cb)
               (sip_transaction_t, sip_msg_t,
```

```

        int, int);
void      (*sip_ulp_dlg_state_cb)(sip_dialog_t,
        sip_msg_t, int, int);
}sip_io_pointers_t;

```

`sip_ulp_recv`

This is a mandatory routine that the application registers for the stack to deliver an inbound SIP message. The SIP stack invokes the function with the connection object on which the message arrived, the SIP message, and any associated dialog.

The SIP message is freed once the function returns. If the application wishes to use the message beyond that, it has to hold a reference on the message using `sip_hold_msg()`. Similarly, if the application wishes to cache the dialog, it must hold a reference on the dialog using `sip_hold_dialog()`.

`sip_ulp_timeout`
`sip_ulp_untimeout`

An application can register these two routines to implement its own routines for the stack timers. Typically, an application should allow the stack to use its own built-in timer routines. The built-in timer routines are used only by the stack and are not available to applications. If the application registers one routine, it must also register the other.

These functions must be registered for single-threaded application. Otherwise, the timer thread provided by the stack could result in invoking a registered callback function.

`sip_ulp_trans_error`

The application can register this routine to be notified of a transaction error. An error can occur when the transaction layer tries to send a message using a cached connection object which results in a failure. If this routine is not registered the transaction is terminated on such a failure. The final argument is for future use. It is always set to NULL.

`sip_ulp_dlg_del`

An application can register this routine to be notified when a dialog is deleted. The dialog to be deleted is passed along with the SIP message which caused the dialog to be deleted. The final argument is for future use. It is always set to NULL.

`sip_ulp_trans_state_cb`
`sip_ulp_dlg_state_cb`

If these callback routines are registered, the stack invokes `sip_ulp_trans_state_cb` when a transaction changes states and `sip_ulp_dlg_state_cb` when a dialog changes states.

Connection Manager Interface

The connection manager interfaces must be registered by the application to provide I/O related functionality to the stack. These interfaces act on a connection object that is defined by the application. The application registers the interfaces for the stack to work with the connection object. The connection object is application defined, but the stack requires that the first member of the connection object is a void *, used by the stack to store connection object specific information which is private to the stack.

The connection manager structure is supplied by:

```
typedef struct sip_io_pointers_s {
    int      (*sip_conn_send)(const sip_conn_object_t, char *, int);
    void      (*sip_hold_conn_object)(sip_conn_object_t);
    void      (*sip_rel_conn_object)(sip_conn_object_t);
    boolean_t (*sip_conn_is_stream)(sip_conn_object_t);
    boolean_t (*sip_conn_is_reliable)(sip_conn_object_t);
    int      (*sip_conn_remote_address)(sip_conn_object_t, struct sockaddr *,
                                       socklen_t *);
    int      (*sip_conn_local_address)(sip_conn_object_t, struct sockaddr *,
                                       socklen_t *);
    int      (*sip_conn_transport)(sip_conn_object_t);
    int      (*sip_conn_timer1)(sip_conn_object_t);
    int      (*sip_conn_timer2)(sip_conn_object_t);
    int      (*sip_conn_timer4)(sip_conn_object_t);
    int      (*sip_conn_timerd)(sip_conn_object_t);
} sip_io_pointers_t;
```

sip_conn_send

This function is invoked by the stack after processing an outbound SIP message. This function is responsible for sending the SIP message to the peer. A return of 0 indicates success. The SIP message is passed to the function as a string, along with the length information and the associated connection object.

sip_hold_conn_object

sip_rel_conn_object

The application provides a mechanism for the stack to indicate that a connection object is in use by the stack and must not be freed. The stack uses `sip_hold_conn_object` to indicate that the connection object is in use and `sip_rel_conn_object` to indicate that it has been released. The connection object is passed as the argument to these functions. The stack expects that the application will not free the connection object if it is in use by the stack.

sip_conn_is_stream

The stack uses this to determine whether the connection object, passed as the argument, is byte-stream oriented. Byte-stream protocols include TCP while message-based protocols include SCTP and UDP.

<code>sip_conn_is_reliable</code>	The stack uses this to determine whether the connection object, passed as the argument, is reliable. Reliable protocols include TCP and SCTP. Unreliable protocols include UDP.
<code>sip_conn_local_address</code> <code>sip_conn_remote_address</code>	These two interfaces are used by the stack to obtain endpoint information for a connection object. The <code>sip_conn_local_address</code> provides the local address/port information. The <code>sip_conn_remote_address</code> provides the address/port information of the peer. The caller allocates the buffer and passes its associated length along with it. On return, the length is updated to reflect the actual length.
<code>sip_conn_transport</code>	The stack uses this to determine the transport used by the connection object, passed as the argument. The transport could be TCP, UDP, SCTP.
<code>sip_conn_timer1</code> <code>sip_conn_timer2</code> <code>sip_conn_timer4</code> <code>sip_conn_timerd</code>	<p>These four interfaces may be registered by an application to provide connection object specific timer information. If these are not registered the stack uses default values.</p> <p>The interfaces provide the timer values for Timer 1 (RTT estimate - default 500 msec), Timer 2 (maximum retransmit interval for non-INVITE request and INVITE response - default 4 secs), Timer 4 (maximum duration a message will remain in the network - default 5 secs) and Timer D (wait time for response retransmit interval - default 32 secs).</p>

Custom SIP headers In addition to the SIP headers supported by the stack, an application can optionally provide a table of custom headers and associated parsing functions. The table is an array with an entry for each header. If the table includes headers supported by the stack, parsing functions or other application-specific table entries take precedence over `libsip` supported headers. The header table structure is supplied by:

```
typedef struct header_function_table {
    char      *header_name;
    char      *header_short_name;
    int       (*header_parse_func)
              (struct sip_header *,
               struct sip_parsed_header **);
    boolean_t (*header_check_compliance)
              (struct sip_parsed_header *);
    boolean_t (*header_is_equal)
              (struct sip_parsed_header *,
```

	struct sip_parsed_header *);
void	(*header_free)
	(struct sip_parsed_header *);
}	
header_name	The full name of the header. The application must ensure that he name does not conflict with existing headers. If it does, the one registered by the application takes precedence.
header_short_name	Compact name, if any, for the header.
header_parse_func	The parsing function for the header. The parser will set the second argument to the resulting parsed structure. A return value of 0 indicates success.
header_free	The function that frees the parsed header
header_check_compliance	An application can optionally provide this function that will check if the header is compliant or not. The compliance for a custom header will be defined by the application.
header_is_equal	An application can optionally provide this function to determine whether two input headers are equivalent. The equivalence criteria is defined by the application.

Return Values On success `sip_stack_init()` returns 0. Otherwise, the function returns the error value.

The value of `errno` is not changed by these calls in the event of an error.

Errors On failure, the `sip_stack_init()` function returns the following error value:

EINVAL If the stack version is incorrect, or if any of the mandatory functions is missing.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Stable
MT-Level	MT-Safe

See Also [libsip\(3LIB\)](#)

Name	slp_api – Service Location Protocol Application Programming Interface
Synopsis	<pre>cc [flag ...] file ... -lslp [library ...] #include <slp.h></pre>
Description	<p>The <code>slp_api</code> is a C language binding that maps directly into the Service Location Protocol (“SLP”) defined by <i>RFC 2614</i>. This implementation requires minimal overhead. With the exception of the <code>SLPDereg()</code> and <code>SLPDeAttrs()</code> functions, which map into different uses of the SLP deregister request, there is one C language function per protocol request. Parameters are for the most part character buffers. Memory management is kept simple because the client allocates most memory and client callback functions are required to copy incoming parameters into memory allocated by the client code. Any memory returned directly from the API functions is deallocated using the <code>SLPFree()</code> function.</p> <p>To conform with standard C practice, all character strings passed to and returned through the API are null-terminated, even though the SLP protocol does not use null-terminated strings. Strings passed as parameters are UTF-8 but they may still be passed as a C string (a null-terminated sequence of bytes.) Escaped characters must be encoded by the API client as UTF-8. In the common case of US-ASCII, the usual one byte per character C strings work. API functions assist in escaping and unescaping strings.</p> <p>Unless otherwise noted, parameters to API functions and callbacks are non-NULL. Some parameters may have other restrictions. If any parameter fails to satisfy the restrictions on its value, the operation returns a <code>PARAMETER_BAD</code> error.</p>
Syntax for String Parameters	<p>Query strings, attribute registration lists, attribute deregistration lists, scope lists, and attribute selection lists follow the syntax described in <i>RFC 2608</i>. The API reflects the strings passed from clients directly into protocol requests, and reflects out strings returned from protocol replies directly to clients. As a consequence, clients are responsible for formatting request strings, including escaping and converting opaque values to escaped byte-encoded strings. Similarly, on output, clients are required to unescape strings and convert escaped string-encoded opaques to binary. The <code>SLPEscape()</code> and <code>SLPUnescape()</code> functions can be used for escaping SLP reserved characters, but they perform no opaque processing.</p> <p>Opaque values consist of a character buffer that contains a UTF-8-encoded string, the first characters of which are the non UTF-8 encoding “\ff”. Subsequent characters are the escaped values for the original bytes in the opaque. The escape convention is relatively simple. An escape consists of a backslash followed by the two hexadecimal digits encoding the byte. An example is “\2c” for the byte 0x2c. Clients handle opaque processing themselves, since the algorithm is relatively simple and uniform.</p>
System Properties	<p>The system properties established in <code>slp.conf(4)</code>, the configuration file, are accessible through the <code>SLPGetProperty()</code> and <code>SLPSetProperty()</code> functions. The <code>SLPSetProperty()</code> function modifies properties only in the running process, not in the configuration file. Errors are checked when the property is used and, as with parsing the configuration file, are logged at the <code>LOG_INFO</code> priority. Program execution continues without interruption by substituting the default for the erroneous parameter. In general, individual agents should rarely be required to</p>

override these properties, since they reflect properties of the SLP network that are not of concern to individual agents. If changes are required, system administrators should modify the configuration file.

Properties are global to the process, affecting all threads and all handles created with `SLPOpen()`.

Memory Management The only API functions that return memory specifically requiring deallocation on the part of the client are `SLPParseSrvURL()`, `SLPFindScope()`, `SLPEscape()`, and `SLPUnescape()`. Free this memory with `SLPFree()` when it is no longer needed. Do not free character strings returned by means of the `SLPGetProperty()` function.

Any memory passed to callbacks belongs to the library, and it must not be retained by the client code. Otherwise, crashes are possible. Clients must copy data out of the callback parameters. No other use of the memory in callback parameters is allowed.

Asynchronous and Incremental Return Semantics If a handle parameter to an API function is opened asynchronously, the API function calls on the handle to check the other parameters, opens the appropriate operation, and returns immediately. If an error occurs in the process of starting the operation, the error code is returned. If the handle parameter is opened synchronously, the function call is blocked until all results are available, and it returns only after the results are reported through the callback function. The return code indicates whether any errors occurred during the operation.

The callback function is called whenever the API library has results to report. The callback code is required to check the error code parameter before looking at the other parameters. If the error code is not `SLP_OK`, the other parameters may be `NULL` or otherwise invalid. The API library can terminate any outstanding operation on which an error occurs. The callback code can similarly indicate that the operation should be terminated by passing back `SLP_FALSE` to indicate that it is not interested in receiving more results. Callback functions are not permitted to recursively call into the API on the same `SLPHandle`. If an attempt is made to call into the API, the API function returns `SLP_HANDLE_IN_USE`. Prohibiting recursive callbacks on the same handle simplifies implementation of thread safe code, since locks held on the handle will not be in place during a second outcall on the handle.

The total number of results received can be controlled by setting the `net.slp.maxResults` parameter.

On the last call to a callback, whether asynchronous or synchronous, the status code passed to the callback has value `SLP_LAST_CALL`. There are four reasons why the call can terminate:

- | | |
|------------------------|---|
| DA reply received | A reply from a DA has been received and therefore nothing more is expected. |
| Multicast terminated | The multicast convergence time has elapsed and the API library multicast code is giving up. |
| Multicast null results | Nothing new has been received during multicast for awhile and the API library multicast code is giving up on that (as an optimization). |

- | | |
|---------------------|--|
| Maximum results | The user has set the <code>net.slp.maxResults</code> property and that number of replies has been collected and returned. |
| Configuration Files | The API library reads <code>slp.conf(4)</code> , the default configuration file, to obtain the operating parameters. You can specify the location of this file with the <code>SLP_CONF_FILE</code> environment variable. If you do not set this variable, or the file it refers to is invalid, the API will use the default configuration file at <code>/etc/inet/slp.conf</code> instead. |
| Data Structures | The data structures used by the SLP API are as follows: |

The URL Lifetime Type

```
typedef enum {
    SLP_LIFETIME_DEFAULT = 10800,
    SLP_LIFETIME_MAXIMUM = 65535
} SLPURLLifetime;
```

The enumeration `SLPURLLifetime` contains URL lifetime values, in seconds, that are frequently used. `SLP_LIFETIME_DEFAULT` is 3 hours, while `SLP_LIFETIME_MAXIMUM` is 18 hours, which corresponds to the maximum size of the `lifetime` field in SLP messages. Note that on registration `SLP_LIFETIME_MAXIMUM` causes the advertisement to be continually reregistered until the process exits.

The SLPBoolean Type

```
typedef enum {
    SLP_FALSE = 0,
    SLP_TRUE = 1
} SLPBoolean;
```

The enumeration `SLPBoolean` is used as a Boolean flag.

The Service URL Structure

```
typedef struct srvurl {
    char *s_pcSrvType;
    char *s_pcHost;
    int s_iPort;
    char *s_pcNetFamily;
    char *s_pcSrvPart;
} SLPsrvURL;
```

The `SLPsrvURL` structure is filled in by the `SLPParseSrvURL()` function with information parsed from a character buffer containing a service URL. The fields correspond to different parts of the URL, as follows:

- | | |
|--------------------------|---|
| <code>s_pcSrvType</code> | A pointer to a character string containing the service type name, including naming authority. |
|--------------------------|---|

<code>s_pchost</code>	A pointer to a character string containing the host identification information.
<code>s_iport</code>	The port number, or zero, if none. The port is only available if the transport is IP.
<code>s_pcnetfamily</code>	A pointer to a character string containing the network address family identifier. Possible values are "ipx" for the IPX family, "at" for the Appletalk family, and "", the empty string, for the IP address family.
<code>s_pcsrvpart</code>	<p>The remainder of the URL, after the host identification.</p> <p>The host and port should be sufficient to open a socket to the machine hosting the service; the remainder of the URL should allow further differentiation of the service.</p>

The SLPHandle

```
typedef void* SLPHandle;
```

The `SLPHandle` type is returned by `SLPOpen()` and is a parameter to all SLP functions. It serves as a handle for all resources allocated on behalf of the process by the SLP library. The type is opaque.

Callbacks Include a function pointer to a callback function specific to a particular API operation in the parameter list when the API function is invoked. The callback function is called with the results of the operation in both the synchronous and asynchronous cases. When the callback function is invoked, the memory included in the callback parameters is owned by the API library, and the client code in the callback must copy out the contents if it wants to maintain the information longer than the duration of the current callback call.

Each callback parameter list contains parameters for reporting the results of the operation, as well as an error code parameter and a cookie parameter. The error code parameter reports the error status of the ongoing (for asynchronous) or completed (for synchronous) operation. The cookie parameter allows the client code that starts the operation by invoking the API function to pass information down to the callback without using global variables. The callback returns an `SLPBoolean` to indicate whether the API library should continue processing the operation. If the value returned from the callback is `SLP_TRUE`, asynchronous operations are terminated. Synchronous operations ignore the return since the operation is already complete.

SLPRegReport()

```
typedef void SLPRegReport(SLPHandle hSLP,  
    SLPErr errCode,  
    void *pvCookie);
```

`SLPRegReport()` is the callback function to the `SLPReg()`, `SLPDereg()`, and `SLPDeLAttrs()` functions. The `SLPRegReport()` callback has the following parameters:

<i>hSLP</i>	The <code>SLPHandle()</code> used to initiate the operation.
<i>errCode</i>	An error code indicating if an error occurred during the operation.
<i>pvCookie</i>	Memory passed down from the client code that called the original API function, starting the operation. It may be <code>NULL</code> .

SLPSrvTypeCallback()

```
typedef SLPBoolean SLPSrvTypeCallback(SLPHandle hSLP,
    const char* pcSrvTypes,
    SLPErrCode errCode,
    void *pvCookie);
```

The `SLPSrvTypeCallback()` type is the type of the callback function parameter to the `SLPFindSrvTypes()` function. The results are collated when the *hSLP* handle is opened either synchronously or asynchronously. The `SLPSrvTypeCallback()` callback has the following parameters:

<i>hSLP</i>	The <code>SLPHandle</code> used to initiate the operation.
<i>pcSrvTypes</i>	A character buffer containing a comma-separated, null-terminated list of service types.
<i>errCode</i>	An error code indicating if an error occurred during the operation. The callback should check this error code before processing the parameters. If the error code is other than <code>SLP_OK</code> , then the API library may choose to terminate the outstanding operation.
<i>pvCookie</i>	Memory passed down from the client code that called the original API function, starting the operation. It can be <code>NULL</code> .

SLPSrvURLCallback

```
typedef SLPBoolean SLPSrvURLCallback(SLPHandle hSLP,
    const char* pcSrvURL,
    unsigned short usLifetime,
    SLPErrCode errCode,
    void *pvCookie);
```

The `SLPSrvURLCallback()` type is the type of the callback function parameter to the `SLPFindSrvs()` function. The results are collated, regardless of whether the *hSLP* was opened collated or uncollated. The `SLPSrvURLCallback()` callback has the following parameters:

<i>hSLP</i>	The <code>SLPHandle</code> used to initiate the operation.
<i>pcSrvURL</i>	A character buffer containing the returned service URL.
<i>usLifetime</i>	An unsigned short giving the life time of the service advertisement. The value must be an unsigned integer less than or equal to <code>SLP_LIFETIME_MAXIMUM</code> .

<i>errCode</i>	An error code indicating if an error occurred during the operation. The callback should check this error code before processing the parameters. If the error code is other than SLP_OK, then the API library may choose to terminate the outstanding operation.
<i>pvCookie</i>	Memory passed down from the client code that called the original API function, starting the operation. It can be NULL.

SLPAttrCallback

```
typedef SLPBoolean SLPAttrCallback(SLPHandle hSLP,  
    const char* pcAttrList,  
    SLPError errCode,  
    void *pvCookie);
```

The `SLPAttrCallback()` type is the type of the callback function parameter to the `SLPFindAttrs()` function.

The behavior of the callback differs depending upon whether the attribute request was by URL or by service type. If the `SLPFindAttrs()` operation was originally called with a URL, the callback is called once, in addition to the last call, regardless of whether the handle was opened asynchronously or synchronously. The *pcAttrList* parameter contains the requested attributes as a comma-separated list. It is empty if no attributes match the original tag list.

If the `SLPFindAttrs()` operation was originally called with a service type, the value of *pcAttrList* and the calling behavior depend upon whether the handle was opened asynchronously or synchronously. If the handle was opened asynchronously, the callback is called every time the API library has results from a remote agent. The *pcAttrList* parameter is collated between calls, and contains a comma-separated list of the results from the agent that immediately returned. If the handle was opened synchronously, the results are collated from all returning agents, the callback is called once, and the *pcAttrList* parameter is set to the collated result.

`SLPAttrCallback()` callback has the following parameters:

<i>hSLP</i>	The <code>SLPHandle</code> used to initiate the operation.
<i>pcAttrList</i>	A character buffer containing a comma-separated and null-terminated list of attribute id/value assignments, in SLP wire format.
<i>errCode</i>	An error code indicating if an error occurred during the operation. The callback should check this error code before processing the parameters. If the error code is other than SLP_OK, then the API library may choose to terminate the outstanding operation.
<i>pvCookie</i>	Memory passed down from the client code that called the original API function, starting the operation. It can be NULL.

Errors An interface that is part of the SLP API may return one of the following values.

SLP_LAST_CALL	The SLP_LAST_CALL code is passed to callback functions when the API library has no more data for them and therefore no further calls will be made to the callback on the currently outstanding operation. The callback uses this to signal the main body of the client code that no more data will be forthcoming on the operation, so that the main body of the client code can break out of data collection loops. On the last call of a callback during both a synchronous and asynchronous call, the error code parameter has value SLP_LAST_CALL, and the other parameters are all NULL. If no results are returned by an API operation, then only one call is made, with the error parameter set to SLP_LAST_CALL.
SLP_OK	The SLP_OK code indicates that the no error occurred during the operation.
SLP_LANGUAGE_NOT_SUPPORTED	No DA or SA has service advertisement information in the language requested, but at least one DA or SA might have information for that service in another language.
SLP_PARSE_ERROR	The SLP message was rejected by a remote SLP agent. The API returns this error only when no information was retrieved, and at least one SA or DA indicated a protocol error. The data supplied through the API may be malformed or damaged in transit.
SLP_INVALID_REGISTRATION	The API may return this error if an attempt to register a service was rejected by all DAs because of a malformed URL or attributes. SLP does not return the error if at least one DA accepts the registration.
SLP_SCOPE_NOT_SUPPORTED	The API returns this error if the UA or SA has been configured with the <code>net.slp.useScopes</code> list of scopes and the SA request did not specify one or more of these allowable scopes, and no others. It may also be returned by a DA if the scope included in a request is not supported by a DA.
SLP_AUTHENTICATION_ABSENT	This error arises when the UA or SA failed to send an authenticator for requests or registrations when security is enabled and thus required.
SLP_AUTHENTICATION_FAILED	This error arises when a authentication on an SLP message received from a remote SLP agent failed.

SLP_INVALID_UPDATE	An update for a nonexistent registration was issued, or the update includes a service type or scope different than that in the initial registration.
SLP_REFRESH_REJECTED	The SA attempted to refresh a registration more frequently than the minimum refresh interval. The SA should call the appropriate API function to obtain the minimum refresh interval to use.
SLP_NOT_IMPLEMENTED	An outgoing request overflowed the maximum network MTU size. The request should be reduced in size or broken into pieces and tried again.
SLP_BUFFER_OVERFLOW	An outgoing request overflowed the maximum network MTU size. The request should be reduced in size or broken into pieces and tried again.
SLP_NETWORK_TIMED_OUT	When no reply can be obtained in the time specified by the configured timeout interval, this error is returned.
SLP_NETWORK_INIT_FAILED	If the network cannot initialize properly, this error is returned.
SLP_MEMORY_ALLOC_FAILED	If the API fails to allocate memory, the operation is aborted and returns this.
SLP_PARAMETER_BAD	If a parameter passed into an interface is bad, this error is returned.
SLP_NETWORK_ERROR	The failure of networking during normal operations causes this error to be returned.
SLP_INTERNAL_SYSTEM_ERROR	A basic failure of the API causes this error to be returned. This occurs when a system call or library fails. The operation could not recover.
SLP_HANDLE_IN_USE	In the C API, callback functions are not permitted to recursively call into the API on the same <code>SLPHandle</code> , either directly or indirectly. If an attempt is made to do so, this error is returned from the called API function

List Of Routines	<code>SLPOpen()</code>	open an SLP handle
	<code>SLPClose()</code>	close an open SLP handle
	<code>SLPReg()</code>	register a service advertisement
	<code>SLPDereg()</code>	deregister a service advertisement
	<code>SLPDelAttrs()</code>	delete attributes

<code>SLPFindSrvTypes()</code>	return service types
<code>SLPFindSrvs()</code>	return service URLs
<code>SLPFindAttrs()</code>	return service attributes
<code>SLPGetRefreshInterval()</code>	return the maximum allowed refresh interval for SAs
<code>SLPFindScopes()</code>	return list of configured and discovered scopes
<code>SLPParseSrvURL()</code>	parse service URL
<code>SLPEscape()</code>	escape special characters
<code>SLPUnescape()</code>	translate escaped characters into UTF-8
<code>SLPGetProperty()</code>	return SLP configuration property
<code>SLPSetProperty()</code>	set an SLP configuration property
<code>slp_strerror()</code>	map SLP error code to message
<code>SLPFree()</code>	free memory

Environment Variables When `SLP_CONF_FILE` is set, use this file for configuration.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWslpu
CSI	CSI-enabled
Interface Stability	Standard
MT-Level	Safe

See Also [slpd\(1M\)](#), [slp.conf\(4\)](#), [slpd.reg\(4\)](#), [attributes\(5\)](#)

System Administration Guide: Network Services

Guttman, E., Perkins, C., Veizades, J., and Day, M. *RFC 2608, Service Location Protocol, Version 2*. The Internet Society. June 1999.

Kempf, J. and Guttman, E. *RFC 2614, An API for Service Location*. The Internet Society. June 1999.

Name SLPclose – close an open SLP handle

Synopsis `#include <slp.h>`

`void SLPclose(SLPHandle phSLP);`

Description The `SLPclose()` function frees all resources associated with the handle. If the handle is invalid, the function returns silently. Any outstanding synchronous or asynchronous operations are cancelled, so that their callback functions will not be called any further

Parameters `phSLP` An `SLPHandle` handle returned from a call to `SLPOpen()`.

Errors This function or its callback may return any SLP error code. See the ERRORS section in [slp_api\(3SLP\)](#).

Examples **EXAMPLE 1** Using `SLPclose()`

The following example will free all resources associated the handle:

```
SLPHandle hslp
    SLPclose(hslp);
```

Environment Variables `SLP_CONF_FILE` When set, use this file for configuration.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTETYPE	ATTRIBUTEVALUE
Availability	SUNWslpu

See Also [slpd\(1M\)](#), [slp_api\(3SLP\)](#), [slp.conf\(4\)](#), [slpd.reg\(4\)](#), [attributes\(5\)](#)

System Administration Guide: Network Services

Kempf, J. and Guttman, E. *RFC 2614, An API for Service Location*. The Internet Society. June 1999.

Name SLPDeAttrs – delete attributes

Synopsis `#include <slp.h>`

```
SLPError SLPDeAttrs(SLPHandle hSLP, const char *pcURL,
                    const char *pcAttrs, SLPRegReport *callback, void *pvCookie);
```

Description The SLPDeAttrs() function deletes the selected attributes in the locale of the SLPHandle. If no error occurs, the return value is 0. Otherwise, one of the SLPError codes is returned.

Parameters

<i>hSLP</i>	The language specific SLPHandle to use to delete attributes. It cannot be NULL.
<i>pcURL</i>	The URL of the advertisement from which the attributes should be deleted. It cannot be NULL.
<i>pcAttrs</i>	A comma-separated list of attribute ids for the attributes to deregister.
<i>callback</i>	A callback to report the operation's completion status. It cannot be NULL.
<i>pvCookie</i>	Memory passed to the callback code from the client. It cannot be NULL.

Errors This function or its callback may return any SLP error code. See the ERRORS section in [slp_api\(3SLP\)](#).

Examples **EXAMPLE 1** Deleting Attributes

Use the following example to delete the location and dpi attributes for the URL service:printer:lpr://serv/queue1

```
SLPHandle hSLP;
SLPError err;
SLPRegReport report;

err = SLPDeAttrs(hSLP, "service:printer:lpr://serv/queue1",
                 "location,dpi", report, NULL);
```

Environment Variables **SLP_CONF_FILE** When set, use this file for configuration.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWslpu

See Also [slpd\(1M\)](#), [slp_api\(3SLP\)](#), [slp.conf\(4\)](#), [slpd.reg\(4\)](#), [attributes\(5\)](#)

System Administration Guide: Network Services

Kempf, J. and Guttman, E. *RFC 2614, An API for Service Location*. The Internet Society. June 1999.

Name SLPDereg – deregister the SLP advertisement

Synopsis `#include <slp.h>`

```
SLPError SLPDereg(SLPHandle hSLP, const char *pcURL,
                  SLPRegReport callback, void *pvCookie);
```

Description The SLPDereg() function deregisters the advertisement for URL *pcURL* in all scopes where the service is registered and in all language locales, not just the locale of the SLPHandle. If no error occurs, the return value is 0. Otherwise, one of the SLPError codes is returned.

Parameters

- hSLP* The language specific SLPHandle to use for deregistering. *hSLP* cannot be NULL.
- pcURL* The URL to deregister. The value of *pcURL* cannot be NULL.
- callback* A callback to report the operation completion status. *callback* cannot be NULL.
- pvCookie* Memory passed to the callback code from the client. *pvCookie* can be NULL.

Errors This function or its callback may return any SLP error code. See the ERRORS section in [slp_api\(3SLP\)](#).

Examples **EXAMPLE 1** Using SLPDereg()

Use the following example to deregister the advertisement for the URL “service:ftp://csserver”:

```
SLPError err;
SLPHandle hSLP;
SLPRegReport regreport;

err = SLPDereg(hSLP, "service:ftp://csserver", regreport, NULL);
```

Environment Variables SLP_CONF_FILE When set, use this file for configuration.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWslpu

See Also [slpd\(1M\)](#), [slp_api\(3SLP\)](#), [slp.conf\(4\)](#), [slpd.reg\(4\)](#), [attributes\(5\)](#)

System Administration Guide: Network Services

Guttman, E., Perkins, C., Veizades, J., and Day, M. *RFC 2608, Service Location Protocol, Version 2*. The Internet Society. June 1999.

Kempf, J. and Guttman, E., *RFC 2614, An API for Service Location*, The Internet Society, June 1999.

Name SLPEscape – escapes SLP reserved characters

Synopsis #include <slp.h>

```
SLPError SLPEscape(const char *pcInBuf, char** ppcOutBuf,
                   SLPBoolean isTag);
```

Description The SLPEscape() function processes the input string in *pcInBuf* and escapes any SLP reserved characters. If the *isTag* parameter is SLPTtrue, it then looks for bad tag characters and signals an error if any are found by returning the SLP_PARSE_ERROR code. The results are put into a buffer allocated by the API library and returned in the *ppcOutBuf* parameter. This buffer should be deallocated using [SLPFree\(3SLP\)](#) when the memory is no longer needed.

Parameters

<i>pcInBuf</i>	Pointer to the input buffer to process for escape characters.
<i>ppcOutBuf</i>	Pointer to a pointer for the output buffer with the SLP reserved characters escaped. It must be freed using SLPFree() when the memory is no longer needed.
<i>isTag</i>	When true, checks the input buffer for bad tag characters.

Errors This function or its callback may return any SLP error code. See the ERRORS section in [slp_api\(3SLP\)](#).

Examples EXAMPLE 1 Converting Attribute Tags

The following example shows how to convert the attribute tag , tag-example, to on the wire format:

```
SLPError err;
char* escaped Chars;

err = SLPEscape(" , tag-example, ", &escapedChars, SLP_TRUE);
```

Environment Variables SLP_CONF_FILE When set, use this file for configuration.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWslpu

See Also [slpd\(1M\)](#), [slp_api\(3SLP\)](#), [SLPFree\(3SLP\)](#), [slp.conf\(4\)](#), [slpd.reg\(4\)](#), [attributes\(5\)](#)

System Administration Guide: Network Services

Guttman, E., Perkins, C., Veizades, J., and Day, M. *RFC 2608, Service Location Protocol, Version 2*. The Internet Society. June 1999.

Kempf, J. and Guttman, E. *RFC 2614, An API for Service Location*. The Internet Society. June 1999.

Name SLPFindAttrs – return service attributes

Synopsis #include <slp.h>

```
SLPError SLPFindAttrs(SLPHandle hSLP, const char *pcURL,
                     const char *pcScopeList, const char *pcAttrIds,
                     SLPAttrCallback *callback, void *pvCookie);
```

Description The SLPFindAttrs() function returns service attributes matching the attribute tags for the indicated full or partial URL. If *pcURL* is a complete URL, the attribute information returned is for that particular service in the language locale of the SLPHandle. If *pcURL* is a service type, then all attributes for the service type are returned, regardless of the language of registration. Results are returned through the *callback* parameter.

The result is filtered with an SLP attribute request filter string parameter, the syntax of which is described in *RFC 2608*. If the filter string is the empty string, "", all attributes are returned.

If an error occurs in starting the operation, one of the SLPError codes is returned.

Parameters	<i>hSLP</i>	The language-specific SLPHandle on which to search for attributes. It cannot be NULL.
	<i>pcURL</i>	The full or partial URL. See <i>RFC 2608</i> for partial URL syntax. It cannot be NULL.
	<i>pcScopeList</i>	A pointer to a char containing a comma-separated list of scope names. It cannot be NULL or an empty string, "".
	<i>pcAttrIds</i>	The filter string indicating which attribute values to return. Use empty string "" to indicate all values. Wildcards matching all attribute ids having a particular prefix or suffix are also possible. It cannot be NULL.
	<i>callback</i>	A callback function through which the results of the operation are reported. It cannot be NULL.
	<i>pvCookie</i>	Memory passed to the callback code from the client. It may be NULL.

Errors This function or its callback may return any SLP error code. See the ERRORS section in [slp_api\(3SLP\)](#).

Examples **EXAMPLE 1** Returning Service Attributes for a Specific URL

Use the following example to return the attributes “location” and “dpi” for the URL “service:printer:lpr://serv/queue1” through the callback attrReturn:

```
SLPHandle hSLP;
SLPAttrCallback attrReturn;
SLPError err;

err = SLPFindAttrs(hSLP "service:printer:lpr://serv/queue1",
                  "default", "location,dpi", attrReturn, err);
```

EXAMPLE 2 Returning Service Attributes for All URLs of a Specific Type

Use the following example to return the attributes “location” and “dpi” for all service URLs having type “service:printer:lpr”:

```
err = SLPFindAttrs(hSLP, "service:printer:lpr",
    "default", "location, pi",
    attrReturn, NULL);
```

- Environment Variables
- Attributes
- SLP_CONF_FILE
- When set, use this file for configuration.
- See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWslpu

See Also [slpd\(1M\)](#), [slp_api\(3SLP\)](#), [slp.conf\(4\)](#), [slpd.reg\(4\)](#), [attributes\(5\)](#)

System Administration Guide: Network Services

Kempf, J. and Guttman, E. *RFC 2614, An API for Service Location*. The Internet Society. June 1999.

Name SLPFindScopes – return list of configured and discovered scopes

Synopsis `#include <slp.h>`

```
SLPError SLPFindScopes(SLPHandle hSLP, char** ppcScopes);
```

Description The `SLPFindScopes()` function sets the `ppcScopes` parameter to a pointer to a comma-separated list including all available scope names. The list of scopes comes from a variety of sources: the configuration file, the `net.slp.useScopes` property and the `net.slp.DAAddresses` property, DHCP, or through the DA discovery process. If there is any order to the scopes, preferred scopes are listed before less desirable scopes. There is always at least one string in the array, the default scope, `DEFAULT`.

If no error occurs, `SLPFindScopes()` returns `SLP_OK`, otherwise, it returns the appropriate error code.

Parameters

<code>hSLP</code>	The <code>SLPHandle</code> on which to search for scopes. <code>hSLP</code> cannot be <code>NULL</code> .
<code>ppcScopes</code>	A pointer to a <code>char</code> pointer into which the buffer pointer is placed upon return. The buffer is null-terminated. The memory should be freed by calling <code>SLPFree()</code> . See SLPFree(3SLP)

Errors This function or its callback may return any SLP error code. See the ERRORS section in [slp_api\(3SLP\)](#).

Examples **EXAMPLE 1** Finding Configured or Discovered Scopes

Use the following example to find configured or discovered scopes:

```
SLPHandle hSLP;
char *ppcScopes;
SLPError err;

error = SLPFindScopes(hSLP, & ppcScopes);
```

Environment Variables `SLP_CONF_FILE` When set, use this file for configuration.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWslpu

See Also [slpd\(1M\)](#), [slp_api\(3SLP\)](#), [SLPFree\(3SLP\)](#), [slp.conf\(4\)](#), [slpd.reg\(4\)](#), [attributes\(5\)](#)

System Administration Guide: Network Services

Guttman, E., Perkins, C., Veizades, J., and Day, M. *RFC 2608, Service Location Protocol, Version 2*. The Internet Society. June 1999.

Kempf, J. and Guttman, E. *RFC 2614, An API for Service Location*. The Internet Society. June 1999.

Name SLPFindSrvs – return service URLs

Synopsis `#include <slp.h>`

```
SLPError SLPFindSrvs(SLPHandle hSLP, const char *pcServiceType,
                    const char *pcScopeList, const char *pcSearchFilter,
                    SLPsrvURLCallback *callback, void *pvCookie);
```

Description The SLPFindSrvs() function issues a request for SLP services. The query is for services on a language-specific SLPHandle. It returns the results through the *callback*. The parameters will determine the results.

If an error occurs in starting the operation, one of the SLPError codes is returned.

Parameters

<i>hSLP</i>	The language-specific SLPHandle on which to search for services. It cannot be NULL.
<i>pcServiceType</i>	The service type string for the request. The <i>pcServiceType</i> can be discovered by a call to SLPsrvTypes(). Examples of service type strings include "service:printer:lpr" or "service:nfs" <i>pcServiceType</i> cannot be NULL.
<i>pcScopeList</i>	A pointer to a char containing a comma-separated list of scope names. It cannot be NULL or an empty string, "".
<i>pcSearchFilter</i>	A query formulated of attribute pattern matching expressions in the form of a LDAPv3 search filter. See RFC 2254. If this filter is empty, "", all services of the requested type in the specified scopes are returned. It cannot be NULL.
<i>callback</i>	A callback through which the results of the operation are reported. It cannot be NULL.
<i>pvCookie</i>	Memory passed to the callback code from the client. It can be NULL.

Errors This function or its callback may return any SLP error code. See the ERRORS section in [slp_api\(3SLP\)](#).

Examples `EXAMPLE1 Using SLPFindSrvs()`

The following example finds all advertisements for printers supporting the LPR protocol with the dpi attribute 300 in the default scope:

```
SLPError err;
SLPHandle hSLP;
SLPSrvURLCallback srvngst;
```

EXAMPLE 1 Using SLPFindSrvs() (Continued)

```
err = SLPFindSrvs(hSLP,
                  "service:printer:lpr",
                  "default",
                  "(dpi=300)",
                  srvngst,
                  NULL);
```

Environment Variables SLP_CONF_FILE When set, use this file for configuration.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWslpu

See Also [slpd\(1M\)](#), [slp_api\(3SLP\)](#), [slp.conf\(4\)](#), [slpd.reg\(4\)](#), [attributes\(5\)](#)

System Administration Guide: Network Services

Howes, T. *RFC 2254, The String Representation of LDAP Search Filters*. The Internet Society. 1997.

Guttman, E., Perkins, C., Veizades, J., and Day, M. *RFC 2608, Service Location Protocol, Version 2*. The Internet Society. June 1999.

Kempf, J. and Guttman, E. *RFC 2614, An API for Service Location*. The Internet Society. June 1999.

Name SLPFindSrvTypes – find service types

Synopsis `#include <slp.h>`

```
SLPError SLPFindSrvTypes(SLPHandle hSLP, const char *pcNamingAuthority,
                        const char *pcScopeList, SLPsrvTypeCallback *callback, void *pvCookie);
```

Description The SLPFindSrvTypes() function issues an SLP service type request for service types in the scopes indicated by the pcScopeList. The results are returned through the callback parameter. The service types are independent of language locale, but only for services registered in one of the scopes and for the indicated naming authority.

If the naming authority is “*”, then results are returned for all naming authorities. If the naming authority is the empty string, “”, then the default naming authority, IANA, is used. IANA is not a valid naming authority name. The SLP_PARAMETER_BAD error code will be returned if you include it explicitly.

The service type names are returned with the naming authority included in the following format:

```
service-type "." naming-authority
```

unless the naming authority is the default, in which case, just the service type name is returned.

If an error occurs in starting the operation, one of the SLPError codes is returned.

Parameters	<i>hSLP</i>	The SLPHandle on which to search for types. It cannot be NULL.
	<i>pcNamingAuthority</i>	The naming authority to search. Use “*” to search all naming authorities; use the empty string “” to search the default naming authority. It cannot be NULL.
	<i>pcScopeList</i>	A pointer to a char containing a comma-separated list of scope names to search for service types. It cannot be NULL or an empty string, “”.
	<i>callback</i>	A callback through which the results of the operation are reported. It cannot be NULL.
	<i>pvCookie</i>	Memory passed to the callback code from the client. It can be NULL.

Errors This function or its callback may return any SLP error code. See the ERRORS section in [slp_api\(3SLP\)](#).

Examples **EXAMPLE 1** Using SLPFindSrvTypes()

The following example finds all service type names in the default scope and default naming authority:

EXAMPLE 1 Using SLPFindSrvTypes() (Continued)

```
SLPError err;
SLPHandle hSLP;
SLPSrvTypeCallback findsrvtypes;

err = SLPFindSrvTypes(hSLP, "", "default", findsrvtypes, NULL);
```

- Environment
- Variables
- Attributes
- SLP_CONF_FILE
- When set, use this file for configuration.
- See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWslpu

See Also [slpd\(1M\)](#), [slp_api\(3SLP\)](#), [slp.conf\(4\)](#), [slpd.reg\(4\)](#), [attributes\(5\)](#)

System Administration Guide: Network Services

Guttman, E., Perkins, C., Veizades, J., and Day, M. *RFC 2608, Service Location Protocol, Version 2*. The Internet Society. June 1999.

Howes, T. *RFC 2254, The String Representation of LDAP Search Filters*. The Internet Society. 1997.

Kempf, J. and Guttman, E. *RFC 2614, An API for Service Location*. The Internet Society. June 1999.

Name SLPFree – frees memory

Synopsis #include <slp.h>

```
SLPError SLPFree(void *pvMem);
```

Description The SLPFree() function frees memory returned from SLPParseSrvURL(), SLPFindScopes(), SLPEscape(), and SLPUnescape().

Parameters *pvMem* A pointer to the storage allocated by the SLPParseSrvURL(), SLPFindScopes(), SLPEscape(), and SLPUnescape() functions. *pvMem* is ignored if its value is NULL.

Errors This function or its callback may return any SLP error code. See the ERRORS section in [slp_api\(3SLP\)](#).

Examples **EXAMPLE 1** Using SLPFree()

The following example illustrates how to call SLPFree(). It assumes that SrvURL contains previously allocated memory.

```
SLPError err;

err = SLPFree((void*) SrvURL);
```

Environment Variables SLP_CONF_FILE When set, use this file for configuration.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWslpu

See Also [slpd\(1M\)](#), [SLPEscape\(3SLP\)](#), [SLPFindScopes\(3SLP\)](#), [SLPParseSrvURL\(3SLP\)](#), [SLPUnescape\(3SLP\)](#), [slp_api\(3SLP\)](#), [slp.conf\(4\)](#), [slpd.reg\(4\)](#), [attributes\(5\)](#)

System Administration Guide: Network Services

Guttman, E., Perkins, C., Veizades, J., and Day, M. *RFC 2608, Service Location Protocol, Version 2*. The Internet Society. June 1999.

Kempf, J. and Guttman, E. *RFC 2614, An API for Service Location*. The Internet Society. June 1999.

Name SLPGetProperty – return SLP configuration property

Synopsis `#include <slp.h>`

```
const char* SLPGetProperty(const char* pcName);
```

Description The SLPGetProperty() function returns the value of the corresponding SLP property name, or NULL, if none. If there is no error, SLPGetProperty() returns a pointer to the property value. If the property was not set, it returns the empty string, "". If an error occurs, SLPGetProperty() returns NULL. The returned string should not be freed.

Parameters *pcName* A null-terminated string with the property name. *pcName* cannot be NULL.

Errors This function or its callback may return any SLP error code. See the ERRORS section in [slp_api\(3SLP\)](#).

Examples **EXAMPLE 1** Using SLPGetProperty()

Use the following example to return a list of configured scopes:

```
const char* useScopes

useScopes = SLPGetProperty("net.slp.useScopes");
```

Environment Variables SLP_CONF_FILE When set, use this file for configuration.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWslpu

See Also [slpd\(1M\)](#), [slp_api\(3SLP\)](#), [slp.conf\(4\)](#), [slpd.reg\(4\)](#), [attributes\(5\)](#)

System Administration Guide: Network Services

Kempf, J. and Guttman, E. *RFC 2614, An API for Service Location*. The Internet Society. June 1999.

Name SLPGetRefreshInterval – return the maximum allowed refresh interval

Synopsis `#include <slp.h>`

```
int SLPGetRefreshInterval(void)
```

Description The SLPGetRefreshInterval() function returns the maximum across all DAs of the min-refresh-interval attribute. This value satisfies the advertised refresh interval bounds for all DAs. If this value is used by the SA, it assures that no refresh registration will be rejected. If no DA advertises a min-refresh-interval attribute, a value of 0 is returned. If an error occurs, an SLP error code is returned.

Errors This function or its callback may return any SLP error code. See the ERRORS section in [slp_api\(3SLP\)](#).

Examples **EXAMPLE 1** Using SLPGetRefreshInterval()

Use the following example to return the maximum valid refresh interval for SA:

```
int minrefresh  
  
minrefresh = SLPGetRefreshInterval( );
```

Environment Variables SLP_CONF_FILE When set, use this file for configuration.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWslpu

See Also [slpd\(1M\)](#), [slp_api\(3SLP\)](#), [slp.conf\(4\)](#), [slpd.reg\(4\)](#), [attributes\(5\)](#)

System Administration Guide: Network Services

Kempf, J. and Guttman, E. *RFC 2614, An API for Service Location*. The Internet Society. June 1999.

Name SLPOpen – open an SLP handle

Synopsis `#include <slp.h>`

`SLPError SLPOpen(const char *pcLang, SLPBoolean isAsync, SLPHandle *phSLP);`

Description The `SLPOpen()` function returns a `SLPHandle` handle in the *phSLP* parameter for the language locale passed in as the *pcLang* parameter. The client indicates if operations on the handle are to be synchronous or asynchronous through the *isAsync* parameter. The handle encapsulates the language locale for SLP requests issued through the handle, and any other resources required by the implementation. SLP properties are not encapsulated by the handle, they are global. The return value of the function is an `SLPError` code indicating the status of the operation. Upon failure, the *phSLP* parameter is `NULL`.

An `SLPHandle` can only be used for one SLP API operation at a time. If the original operation was started asynchronously, any attempt to start an additional operation on the handle while the original operation is pending results in the return of an `SLP_HANDLE_IN_USE` error from the API function. The `SLPClose()` function terminates any outstanding calls on the handle.

Parameters

<i>pcLang</i>	A pointer to an array of characters containing the language tag set forth in <i>RFC 1766</i> for the natural language locale of requests issued on the handle. This parameter cannot be <code>NULL</code> .
<i>isAsync</i>	An <code>SLPBoolean</code> indicating whether or not the <code>SLPHandle</code> should be opened for an asynchronous operation.
<i>phSLP</i>	A pointer to an <code>SLPHandle</code> in which the open <code>SLPHandle</code> is returned. If an error occurs, the value upon return is <code>NULL</code> .

Errors This function or its callback may return any SLP error code. See the **ERRORS** section in [slp_api\(3SLP\)](#).

Examples **EXAMPLE 1** Using `SLPOpen()`
Use the following example to open a synchronous handle for the German (“de”) locale:
`SLPHandle HSLP; SLPError err; err = SLPOpen("de", SLP_FALSE, &hSLP)`

Environment Variables `SLP_CONF_FILE` When set, use this file for configuration.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWslpu

See Also [slpd\(1M\)](#), [slp_api\(3SLP\)](#), [slp.conf\(4\)](#), [slpd.reg\(4\)](#), [attributes\(5\)](#)

System Administration Guide: Network Services

Alvestrand, H. *RFC 1766, Tags for the Identification of Languages*. Network Working Group. March 1995.

Kempf, J. and Guttman, E. *RFC 2614, An API for Service Location*. The Internet Society. June 1999.

Name SLPParseSrvURL – parse service URL

Synopsis #include <slp.h>

```
SLPError SLPParseSrvURL(const char *pcSrvURL, SLPSrvURL** ppSrvURL);
```

Description The SLPParseSrvURL () routine parses the URL passed in as the argument into a service URL structure and returns it in the *ppSrvURL* pointer. If a parser error occurs, returns SLP_PARSE_ERROR. The structure returned in *ppSrvURL* should be freed with SLPFree (). If the URL has no service part, the s_pcSrvPart string is the empty string, "", that is, it is not NULL. If *pcSrvURL* is not a service: URL, then the s_pcSrvType field in the returned data structure is the URL's scheme, which might not be the same as the service type under which the URL was registered. If the transport is IP, the s_pcNetFamily field is the empty string.

If no error occurs, the return value is the SLP_OK. Otherwise, if an error occurs, one of the SLPError codes is returned.

Parameters *pcSrvURL* A pointer to a character buffer containing the null terminated URL string to parse. It is destructively modified to produce the output structure. It may not be NULL.

ppSrvURL A pointer to a pointer for the SLPSrvURL structure to receive the parsed URL. It may not be NULL.

Errors This function or its callback may return any SLP error code. See the ERRORS section in [slp_api\(3SLP\)](#).

Examples **EXAMPLE 1** Using SLPParseSrvURL ()

The following example uses the SLPParseSrvURL () function to parse the service URL service:printer:lpr://serv/queue1:

```
SLPSrvURL* surl;
SLPError err;

err = SLPParseSrvURL("service:printer:lpr://serv/queue1", &surl);
```

Environment Variables SLP_CONF_FILE When set, use this file for configuration.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWslpu

See Also [slpd\(1M\)](#), [slp_api\(3SLP\)](#), [slp.conf\(4\)](#), [slpd.reg\(4\)](#), [attributes\(5\)](#)

System Administration Guide: Network Services

Guttman, E., Perkins, C., Veizades, J., and Day, M. *RFC 2608, Service Location Protocol, Version 2*. The Internet Society. June 1999.

Kempf, J. and Guttman, E. *RFC 2614, An API for Service Location*. The Internet Society. June 1999.

Name SLPReg – register an SLP advertisement

Synopsis `#include <slp.h>`

```
SLPError SLPReg(SLPHandle hSLP, const char *pcSrvURL,  
               const unsigned short usLifetime, const char *pcSrvType,  
               const char *pcAttrs, SLPBoolean fresh,  
               SLPRegReport callback, void *pvCookie);
```

Description The `SLPReg()` function registers the URL in *pcSrvURL* having the lifetime *usLifetime* with the attribute list in *pcAttrs*. The *pcAttrs* list is a comma-separated list of attribute assignments in on-the-wire format (including escaping of reserved characters). The *usLifetime* parameter must be nonzero and less than or equal to `SLP_LIFETIME_MAXIMUM`. If the *fresh* flag is `SLP_TRUE`, then the registration is new, the SLP protocol *fresh* flag is set, and the registration replaces any existing registrations.

The *pcSrvType* parameter is a service type name and can be included for service URLs that are not in the service: scheme. If the URL is in the service: scheme, the *pcSrvType* parameter is ignored. If the *fresh* flag is `SLP_FALSE`, then an existing registration is updated. Rules for new and updated registrations, and the format for *pcAttrs* and *pcScopeList*, can be found in *RFC 2608*. Registrations and updates take place in the language locale of the *hSLP* handle.

The API library is required to perform the operation in all scopes obtained through configuration.

Parameters	<i>hSLP</i>	The language specific <code>SLPHandle</code> on which to register the advertisement. <i>hSLP</i> cannot be <code>NULL</code> .
	<i>pcSrvURL</i>	The URL to register. The value of <i>pcSrvURL</i> cannot be <code>NULL</code> or the empty string.
	<i>usLifetime</i>	An unsigned short giving the life time of the service advertisement, in seconds. The value must be an unsigned integer less than or equal to <code>SLP_LIFETIME_MAXIMUM</code> .
	<i>pcSrvType</i>	The service type. If <i>pURL</i> is a service: URL, then this parameter is ignored. <i>pcSrvType</i> cannot be <code>NULL</code> .
	<i>pcAttrs</i>	A comma-separated list of attribute assignment expressions for the attributes of the advertisement. <i>pcAttrs</i> cannot be <code>NULL</code> . Use the empty string, "", to indicate no attributes.
	<i>fresh</i>	An <code>SLPBoolean</code> that is <code>SLP_TRUE</code> if the registration is new or <code>SLP_FALSE</code> if it is a reregistration.
	<i>callback</i>	A callback to report the operation completion status. <i>callback</i> cannot be <code>NULL</code> .
	<i>pvCookie</i>	Memory passed to the callback code from the client. <i>pvCookie</i> can be <code>NULL</code> .

Errors This function or its callback may return any SLP error code. See the ERRORS section in [slp_api\(3SLP\)](#).

Examples **EXAMPLE 1** An Initial Registration

The following example shows an initial registration for the “service:video://bldg15” camera service for three hours:

```
SLPError err;
SLPHandle hSLP;
SLPRegReport regreport;
err = SLPReg(hSLP, "service:video://bldg15",
            10800, "", "(location=B15-corridor),
            (scan-rate=100)", SLP_TRUE,
            regRpt, NULL);
```

Environment Variables **SLP_CONF_FILE** When set, use this file for configuration.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWslpu

See Also [slpd\(1M\)](#), [slp_api\(3SLP\)](#), [slp.conf\(4\)](#), [slpd.reg\(4\)](#), [attributes\(5\)](#)

System Administration Guide: Network Services

Guttman, E., Perkins, C., Veizades, J., and Day, M., *RFC 2608, Service Location Protocol, Version 2*. The Internet Society. June 1999.

Kempf, J. and Guttman, E. *RFC 2614, An API for Service Location*. The Internet Society. June 1999.

Name SLPsetProperty – set an SLP configuration property

Synopsis `#include <slp.h>`

`void SLPsetProperty(const char *pcName, const char *pcValue);`

Description The SLPsetProperty() function sets the value of the SLP property to the new value. The *pcValue* parameter contains the property value as a string.

Parameters *pcName* A null-terminated string with the property name. *pcName* cannot be NULL.
pcValue A null-terminated string with the property value. *pcValue* cannot be NULL

Errors This function or its callback may return any SLP error code. See the ERRORS section in [slp_api\(3SLP\)](#).

Examples **EXAMPLE 1** Setting a Configuration Property

The following example shows to set the property `net.slp.typeHint` to `service:ftp`:

```
SLPsetProperty ("net.slp.typeHint" "service:ftp");
```

Environment Variables `SLP_CONF_FILE` When set, use this file for configuration.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWslpu

See Also [slpd\(1M\)](#), [slp_api\(3SLP\)](#), [slp.conf\(4\)](#), [slpd.reg\(4\)](#), [attributes\(5\)](#)

System Administration Guide: Network Services

Kempf, J. and Guttman, E. *RFC 2614, An API for Service Location*. The Internet Society. June 1999.

Name `slp_strerror` – map SLP error codes to messages

Synopsis `#include <slp.h>`

```
const char* slp_strerror(SLError err_code);
```

Description The `slp_strerror()` function maps `err_code` to a string explanation of the error. The returned string is owned by the library and must not be freed.

Parameters `err_code` An SLP error code.

Errors This function or its callback may return any SLP error code. See the ERRORS section in [slp_api\(3SLP\)](#).

Examples **EXAMPLE 1** Using `slp_strerror()`

The following example returns the message that corresponds to the error code:

```
SError error;
const char* msg;
msg = slp_strerror(err);
```

Environment Variables `SLP_CONF_FILE` When set, use this file for configuration.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWslpu

See Also [slpd\(1M\)](#), [slp_api\(3SLP\)](#), [slp.conf\(4\)](#), [slpd.reg\(4\)](#), [attributes\(5\)](#)

System Administration Guide: Network Services

Kempf, J. and Guttman, E. *RFC 2614, An API for Service Location*. The Internet Society. June 1999.

Name SLPUnescape – translate escaped characters into UTF-8

Synopsis #include <slp.h>

```
SLPError SLPUnescape(const char *pcInBuf, char** ppcOutBuf,
                     SLPBoolean isTag);
```

Description The SLPUnescape() function processes the input string in *pcInBuf* and unescapes any SLP reserved characters. If the *isTag* parameter is `SLPTRUE`, then look for bad tag characters and signal an error if any are found with the `SLP_PARSE_ERROR` code. No transformation is performed if the input string is an opaque. The results are put into a buffer allocated by the API library and returned in the *ppcOutBuf* parameter. This buffer should be deallocated using [SLPFree\(3SLP\)](#) when the memory is no longer needed.

Parameters

<i>pcInBuf</i>	Pointer to the input buffer to process for escape characters.
<i>ppcOutBuf</i>	Pointer to a pointer for the output buffer with the SLP reserved characters escaped. Must be freed using SLPFree(3SLP) when the memory is no longer needed.
<i>isTag</i>	When true, the input buffer is checked for bad tag characters.

Errors This function or its callback may return any SLP error code. See the ERRORS section in [slp_api\(3SLP\)](#).

Examples **EXAMPLE 1** Using SLPUnescape()
The following example decodes the representation for “ , tag , ”:

```
char* pcOutBuf;
SLPError err;

err = SLPUnescape("\\2c tag\\2c", &pcOutbuf, SLP_TRUE);
```

Environment Variables `SLP_CONF_FILE` When set, use this file for configuration.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Availability	SUNWslpu

See Also [slpd\(1M\)](#), [SLPFree\(3SLP\)](#), [slp_api\(3SLP\)](#), [slp.conf\(4\)](#), [slpd.reg\(4\)](#), [attributes\(5\)](#)

System Administration Guide: Network Services

Guttman, E., Perkins, C., Veizades, J., and Day, M. *RFC 2608, Service Location Protocol, Version 2*. The Internet Society. June 1999.

Kempf, J. and Guttman, E. *RFC 2614, An API for Service Location*. The Internet Society. June 1999.

Name socketmark – determine whether a socket is at the out-of-band mark

Synopsis

```
cc [ flag ... ] file ... -lxnet [ library ... ]
#include <sys/socket.h>

int socketmark(int s);
```

Description The `socketmark()` function determines whether the socket specified by the descriptor `s` is at the out-of-band data mark. If the protocol for the socket supports out-of-band data by marking the stream with an out-of-band data mark, the `socketmark()` function returns 1 when all data preceding the mark has been read and the out-of-band data mark is the first element in the receive queue. The `socketmark()` function does not remove the mark from the stream.

Return Values Upon successful completion, the `socketmark()` function returns a value indicating whether the socket is at an out-of-band data mark. If the protocol has marked the data stream and all data preceding the mark has been read, the return value is 1. If there is no mark, or if data precedes the mark in the receive queue, the `socketmark()` function returns 0. Otherwise, it returns -1 and sets `errno` to indicate the error.

Errors The `socketmark()` function will fail if:

- EBADF** The `s` argument is not a valid file descriptor.
- ENOTTY** The `s` argument does not specify a descriptor for a socket.

Usage The use of this function between receive operations allows an application to determine which received data precedes the out-of-band data and which follows the out-of-band data.

There is an inherent race condition in the use of this function. On an empty receive queue, the current read of the location might well be at the "mark", but the system has no way of knowing that the next data segment that will arrive from the network will carry the mark, and `socketmark()` will return false, and the next read operation will silently consume the mark.

Hence, this function can only be used reliably when the application already knows that the out-of-band data has been seen by the system or that it is known that there is data waiting to be read at the socket, either by SIGURG or [select\(3C\)](#).

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	Safe

See Also `recv(3XNET)`, `recvmsg(3XNET)`, `select(3C)`, `attributes(5)`, `standards(5)`

Name socket – create an endpoint for communication

Synopsis

```
cc [ flag ... ] file ... -lsocket -lnsl [ library ... ]  
#include <sys/types.h>  
#include <sys/socket.h>
```

```
int socket(int domain, int type, int protocol);
```

Description The `socket()` function creates an endpoint for communication and returns a descriptor.

The *domain* parameter specifies a communications domain within which communication will take place; this selects the protocol family which should be used. The protocol family generally is the same as the address family for the addresses supplied in later operations on the socket. These families are defined in the include file `<sys/socket.h>`. There must be an entry in the [netconfig\(4\)](#) file for at least each protocol family and type required. If *protocol* has been specified, but no exact match for the tuple family, type, protocol is found, then the first entry containing the specified family and type with zero for protocol will be used. The currently understood formats are:

PF_UNIX	UNIX system internal protocols
PF_INET	Internet Protocol Version 4 (IPv4)
PF_INET6	Internet Protocol Version 6 (IPv6)
PF_NCA	Network Cache and Accelerator (NCA) protocols

The socket has the indicated type, which specifies the communication semantics. Currently defined types are:

```
SOCK_STREAM  
SOCK_DGRAM  
SOCK_RAW  
SOCK_SEQPACKET  
SOCK_RDM
```

A `SOCK_STREAM` type provides sequenced, reliable, two-way connection-based byte streams. An out-of-band data transmission mechanism may be supported. A `SOCK_DGRAM` socket supports datagrams (connectionless, unreliable messages of a fixed (typically small) maximum length). A `SOCK_SEQPACKET` socket may provide a sequenced, reliable, two-way connection-based data transmission path for datagrams of fixed maximum length; a consumer may be required to read an entire packet with each read system call. This facility is protocol specific, and presently not implemented for any protocol family. `SOCK_RAW` sockets provide access to internal network interfaces. The types `SOCK_RAW`, which is available only to a user with the `net_rawaccess` privilege, and `SOCK_RDM`, for which no implementation currently exists, are not described here.

The *protocol* parameter specifies a particular protocol to be used with the socket. Normally only a single protocol exists to support a particular socket type within a given protocol family. However, multiple protocols may exist, in which case a particular protocol must be specified in this manner. The protocol number to use is particular to the “communication domain” in which communication is to take place. If a protocol is specified by the caller, then it will be packaged into a socket level option request and sent to the underlying protocol layers.

Sockets of type `SOCK_STREAM` are full-duplex byte streams, similar to pipes. A stream socket must be in a *connected* state before any data may be sent or received on it. A connection to another socket is created with a `connect(3SOCKET)` call. Once connected, data may be transferred using `read(2)` and `write(2)` calls or some variant of the `send(3SOCKET)` and `recv(3SOCKET)` calls. When a session has been completed, a `close(2)` may be performed. Out-of-band data may also be transmitted as described on the `send(3SOCKET)` manual page and received as described on the `recv(3SOCKET)` manual page.

The communications protocols used to implement a `SOCK_STREAM` insure that data is not lost or duplicated. If a piece of data for which the peer protocol has buffer space cannot be successfully transmitted within a reasonable length of time, then the connection is considered broken and calls will indicate an error with `-1` returns and with `ETIMEDOUT` as the specific code in the global variable `errno`. The protocols optionally keep sockets “warm” by forcing transmissions roughly every minute in the absence of other activity. An error is then indicated if no response can be elicited on an otherwise idle connection for an extended period (for instance 5 minutes). A `SIGPIPE` signal is raised if a thread sends on a broken stream; this causes naive processes, which do not handle the signal, to exit.

`SOCK_SEQPACKET` sockets employ the same system calls as `SOCK_STREAM` sockets. The only difference is that `read(2)` calls will return only the amount of data requested, and any remaining in the arriving packet will be discarded.

`SOCK_DGRAM` and `SOCK_RAW` sockets allow datagrams to be sent to correspondents named in `sendto(3SOCKET)` calls. Datagrams are generally received with `recvfrom(3SOCKET)`, which returns the next datagram with its return address.

An `fcntl(2)` call can be used to specify a process group to receive a `SIGURG` signal when the out-of-band data arrives. It can also enable non-blocking I/O.

The operation of sockets is controlled by socket level *options*. These options are defined in the file `<sys/socket.h>`. `setsockopt(3SOCKET)` and `getsockopt(3SOCKET)` are used to set and get options, respectively.

Return Values Upon successful completion, a descriptor referencing the socket is returned. Otherwise, `-1` is returned and `errno` is set to indicate the error.

Errors The `socket()` function will fail if:

<code>EACCES</code>	Permission to create a socket of the specified type or protocol is denied.
---------------------	--

EAFNOSUPPORT	The specified address family is not supported by the protocol family.
EMFILE	The per-process descriptor table is full.
ENOMEM	Insufficient user memory is available.
ENOSR	There were insufficient STREAMS resources available to complete the operation.
EPFNOSUPPORT	The specified protocol family is not supported.
EPROTONOSUPPORT	The protocol type is not supported by the address family.
EPROTOTYPE	The socket type is not supported by the protocol.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTETYPE	ATTRIBUTEVALUE
MT-Level	Safe

See Also [nca\(1\)](#), [close\(2\)](#), [fcntl\(2\)](#), [ioctl\(2\)](#), [read\(2\)](#), [write\(2\)](#), [accept\(3SOCKET\)](#), [bind\(3SOCKET\)](#), [connect\(3SOCKET\)](#), [getsockname\(3SOCKET\)](#), [getsockopt\(3SOCKET\)](#), [in.h\(3HEAD\)](#), [listen\(3SOCKET\)](#), [recv\(3SOCKET\)](#), [setsockopt\(3SOCKET\)](#), [send\(3SOCKET\)](#), [shutdown\(3SOCKET\)](#), [socket.h\(3HEAD\)](#), [socketpair\(3SOCKET\)](#), [attributes\(5\)](#)

Name socket – create an endpoint for communication

Synopsis `cc [flag ...] file ... -lxnet [library ...]`
`#include <sys/socket.h>`

```
int socket(int domain, int type, int protocol);
```

Description The `socket()` function creates an unbound socket in a communications domain, and returns a file descriptor that can be used in later function calls that operate on sockets.

The `<sys/socket.h>` header defines at least the following values for the *domain* argument:

`AF_UNIX` File system pathnames.

`AF_INET` Internet Protocol version 4 (IPv4) address.

`AF_INET6` Internet Protocol version 6 (IPv6) address.

The *type* argument specifies the socket type, which determines the semantics of communication over the socket. The socket types supported by the system are implementation-dependent. Possible socket types include:

`SOCK_STREAM` Provides sequenced, reliable, bidirectional, connection-mode byte streams, and may provide a transmission mechanism for out-of-band data.

`SOCK_DGRAM` Provides datagrams, which are connectionless-mode, unreliable messages of fixed maximum length.

`SOCK_SEQPACKET` Provides sequenced, reliable, bidirectional, connection-mode transmission path for records. A record can be sent using one or more output operations and received using one or more input operations, but a single operation never transfers part of more than one record. Record boundaries are visible to the receiver via the `MSG_EOR` flag.

If the *protocol* argument is non-zero, it must specify a protocol that is supported by the address family. The protocols supported by the system are implementation-dependent.

The process may need to have appropriate privileges to use the `socket()` function or to create some sockets.

Parameters The function takes the following arguments:

domain Specifies the communications domain in which a socket is to be created.

type Specifies the type of socket to be created.

protocol Specifies a particular protocol to be used with the socket. Specifying a *protocol* of 0 causes `socket()` to use an unspecified default protocol appropriate for the requested socket type.

The *domain* argument specifies the address family used in the communications domain. The address families supported by the system are implementation-dependent.

Usage The documentation for specific address families specify which protocols each address family supports. The documentation for specific protocols specify which socket types each protocol supports.

The application can determine if an address family is supported by trying to create a socket with *domain* set to the protocol in question.

Return Values Upon successful completion, `socket ()` returns a nonnegative integer, the socket file descriptor. Otherwise a value of -1 is returned and `errno` is set to indicate the error.

Errors The `socket ()` function will fail if:

- EAFNOSUPPORT The implementation does not support the specified address family.
- EMFILE No more file descriptors are available for this process.
- ENFILE No more file descriptors are available for the system.
- EPROTONOSUPPORT The protocol is not supported by the address family, or the protocol is not supported by the implementation.
- EPROTOTYPE The socket type is not supported by the protocol.

The `socket ()` function may fail if:

- EACCES The process does not have appropriate privileges.
- ENOBUFS Insufficient resources were available in the system to perform the operation.
- ENOMEM Insufficient memory was available to fulfill the request.
- ENOSR There were insufficient STREAMS resources available for the operation to complete.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also [accept\(3XNET\)](#), [bind\(3XNET\)](#), [connect\(3XNET\)](#), [getsockname\(3XNET\)](#), [getsockopt\(3XNET\)](#), [listen\(3XNET\)](#), [recv\(3XNET\)](#), [recvfrom\(3XNET\)](#), [recvmsg\(3XNET\)](#), [send\(3XNET\)](#), [sendmsg\(3XNET\)](#), [setsockopt\(3XNET\)](#), [shutdown\(3XNET\)](#), [socketpair\(3XNET\)](#), [attributes\(5\)](#), [standards\(5\)](#)

Name socketpair – create a pair of connected sockets

Synopsis `cc [flag ...] file ... -lsocket -lnsl [library ...]`
`#include <sys/types.h>`
`#include <sys/socket.h>`

`int socketpair(int domain, int type, int protocol, int sv[2]);`

Description The `socketpair()` library call creates an unnamed pair of connected sockets in the specified address family *domain*, of the specified *type*, that uses the optionally specified *protocol*. The descriptors that are used in referencing the new sockets are returned in *sv*[0] and *sv*[1]. The two sockets are indistinguishable.

Return Values `socketpair()` returns `-1` on failure and `0` on success.

Errors The call succeeds unless:

- `EAFNOSUPPORT` The specified address family is not supported on this machine.
- `EMFILE` Too many descriptors are in use by this process.
- `ENOMEM` There was insufficient user memory for the operation to complete.
- `ENOSR` There were insufficient STREAMS resources for the operation to complete.
- `EOPNOTSUPP` The specified protocol does not support creation of socket pairs.
- `EPROTONOSUPPORT` The specified protocol is not supported on this machine.
- `EACCES` The process does not have appropriate privileges.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Safe

See Also [pipe\(2\)](#), [read\(2\)](#), [write\(2\)](#), [socket.h\(3HEAD\)](#), [attributes\(5\)](#)

Notes This call is currently implemented only for the `AF_UNIX` address family.

Name socketpair – create a pair of connected sockets

Synopsis `cc [flag ...] file ... -lxnet [library ...]
#include <sys/socket.h>`

```
int socketpair(int domain, int type, int protocol, int socket_vector[2]);
```

Description The `socketpair()` function creates an unbound pair of connected sockets in a specified *domain*, of a specified type, under the protocol optionally specified by the *protocol* argument. The two sockets are identical. The file descriptors used in referencing the created sockets are returned in *socket_vector*0 and *socket_vector*1.

The *type* argument specifies the socket type, which determines the semantics of communications over the socket. The socket types supported by the system are implementation-dependent. Possible socket types include:

SOCK_STREAM	Provides sequenced, reliable, bidirectional, connection-mode byte streams, and may provide a transmission mechanism for out-of-band data.
SOCK_DGRAM	Provides datagrams, which are connectionless-mode, unreliable messages of fixed maximum length.
SOCK_SEQPACKET	Provides sequenced, reliable, bidirectional, connection-mode transmission path for records. A record can be sent using one or more output operations and received using one or more input operations, but a single operation never transfers part of more than one record. Record boundaries are visible to the receiver via the MSG_EOR flag.

If the *protocol* argument is non-zero, it must specify a protocol that is supported by the address family. The protocols supported by the system are implementation-dependent.

The process may need to have appropriate privileges to use the `socketpair()` function or to create some sockets.

Parameters	<i>domain</i>	Specifies the communications domain in which the sockets are to be created.
	<i>type</i>	Specifies the type of sockets to be created.
	<i>protocol</i>	Specifies a particular protocol to be used with the sockets. Specifying a <i>protocol</i> of 0 causes <code>socketpair()</code> to use an unspecified default protocol appropriate for the requested socket type.
	<i>socket_vector</i>	Specifies a 2-integer array to hold the file descriptors of the created socket pair.

Usage The documentation for specific address families specifies which protocols each address family supports. The documentation for specific protocols specifies which socket types each protocol supports.

The `socketpair()` function is used primarily with UNIX domain sockets and need not be supported for other domains.

Return Values Upon successful completion, this function returns 0. Otherwise, `-1` is returned and `errno` is set to indicate the error.

Errors The `socketpair()` function will fail if:

<code>EAFNOSUPPORT</code>	The implementation does not support the specified address family.
<code>EMFILE</code>	No more file descriptors are available for this process.
<code>ENFILE</code>	No more file descriptors are available for the system.
<code>EOPNOTSUPP</code>	The specified protocol does not permit creation of socket pairs.
<code>EPROTONOSUPPORT</code>	The protocol is not supported by the address family, or the protocol is not supported by the implementation.
<code>EPROTOTYPE</code>	The socket type is not supported by the protocol.

The `socketpair()` function may fail if:

<code>EACCES</code>	The process does not have appropriate privileges.
<code>ENOBUFS</code>	Insufficient resources were available in the system to perform the operation.
<code>ENOMEM</code>	Insufficient memory was available to fulfill the request.
<code>ENOSR</code>	There were insufficient STREAMS resources available for the operation to complete.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Standard
MT-Level	MT-Safe

See Also [socket\(3XNET\)](#), [attributes\(5\)](#), [standards\(5\)](#)

Name spray – scatter data in order to test the network

Synopsis `cc [flag ...] file ... -lsocket -lnsl [library ...]`
`#include <rpcsvc/spray.h>`

```
bool_t xdr_sprayarr(XDR *xdrs, sprayarr *objp);
```

```
bool_t xdr_spraycumul(XDR *xdrs, spraycumul *objp);
```

Description The spray program sends packets to a given machine to test communications with that machine.

The spray program is not a C function interface, per se, but it can be accessed using the generic remote procedure calling interface `clnt_call()`. See [rpc_clnt_calls\(3NSL\)](#). The program sends a packet to the called host. The host acknowledges receipt of the packet. The program counts the number of acknowledgments and can return that count.

The spray program currently supports the following procedures, which should be called in the order given:

SPRAYPROC_CLEAR This procedure clears the counter.

SPRAYPROC_SPRAY This procedure sends the packet.

SPRAYPROC_GET This procedure returns the count and the amount of time since the last SPRAYPROC_CLEAR.

Examples **EXAMPLE 1** Using `spray()`

The following code fragment demonstrates how the spray program is used:

```
#include <rpc/rpc.h>
#include <rpcsvc/spray.h>
. . .
spraycumul    spray_result;
sprayarr      spray_data;
char          buf[100];          /* arbitrary data */
int           loop = 1000;
CLIENT        *clnt;
struct timeval timeout0 = {0, 0};
struct timeval timeout25 = {25, 0};
spray_data.sprayarr_len = (uint_t)100;
spray_data.sprayarr_val = buf;
clnt = clnt_create("somehost", SPRAYPROC, SPRAYVERS, "netpath");
if (clnt == (CLIENT *)NULL) {
    /* handle this error */
}
if (clnt_call(clnt, SPRAYPROC_CLEAR,
              xdr_void, NULL, xdr_void, NULL, timeout25)) {
```

EXAMPLE 1 Using `spray()` (Continued)

```

        /* handle this error */
    }
    while (loop- > 0) {
        if (clnt_call(clnt, SPRAYPROC_SPRAY,
                     xdr_sprayarr, &spray_data, xdr_void, NULL, timeout0)) {
            /* handle this error */
        }
    }
    if (clnt_call(clnt, SPRAYPROC_GET,
                 xdr_void, NULL, xdr_spraycumul, &spray_result, timeout25)) {
        /* handle this error */
    }
    printf("Acknowledged %ld of 1000 packets in %d secs %d usecs\n",
          spray_result.counter,
          spray_result.clock.sec,
          spray_result.clock.usec);

```

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Unsafe

See Also [spray\(1M\)](#), [rpc_clnt_calls\(3NSL\)](#), [attributes\(5\)](#)

Notes This interface is unsafe in multithreaded applications. Unsafe interfaces should be called only from the main thread.

A spray program is not useful as a networking benchmark as it uses unreliable connectionless transports, for example, udp. It can report a large number of packets dropped, when the drops were caused by the program sending packets faster than they can be buffered locally, that is, before the packets get to the network medium.

Name t_accept – accept a connection request

Synopsis #include <xti.h>

```
int t_accept(int fd, int resfd, const struct t_call *call);
```

Description This routine is part of the XTI interfaces that evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI routine that has the same name as an XTI routine, a different header file, `tiuser.h`, must be used. Refer to the TLI COMPATIBILITY section for a description of differences between the two interfaces.

This function is issued by a transport user to accept a connection request. The parameter *fd* identifies the local transport endpoint where the connection indication arrived; *resfd* specifies the local transport endpoint where the connection is to be established, and *call* contains information required by the transport provider to complete the connection. The parameter *call* points to a `t_call` structure which contains the following members:

```
struct netbuf addr;  
struct netbuf opt;  
struct netbuf udata;  
int sequence;
```

In *call*, *addr* is the protocol address of the calling transport user, *opt* indicates any options associated with the connection, *udata* points to any user data to be returned to the caller, and *sequence* is the value returned by `t_listen(3NSL)` that uniquely associates the response with a previously received connection indication. The address of the caller, *addr* may be null (length zero). Where *addr* is not null then it may optionally be checked by XTI.

A transport user may accept a connection on either the same, or on a different, local transport endpoint than the one on which the connection indication arrived. Before the connection can be accepted on the same endpoint (*resfd*==*fd*), the user must have responded to any previous connection indications received on that transport endpoint by means of `t_accept()` or `t_snddis(3NSL)`. Otherwise, `t_accept()` will fail and set `t_errno` to `TINDOUT`.

If a different transport endpoint is specified (*resfd*!=*fd*), then the user may or may not choose to bind the endpoint before the `t_accept()` is issued. If the endpoint is not bound prior to the `t_accept()`, the endpoint must be in the `T_UNBND` state before the `t_accept()` is issued, and the transport provider will automatically bind it to an address that is appropriate for the protocol concerned. If the transport user chooses to bind the endpoint it must be bound to a protocol address with a *qlen* of zero and must be in the `T_IDLE` state before the `t_accept()` is issued.

Responding endpoints should be supplied to `t_accept()` in the state `T_UNBND`.

The call to `t_accept()` may fail with `t_errno` set to `TLOOK` if there are indications (for example connect or disconnect) waiting to be received on endpoint *fd*. Applications should be prepared for such a failure.

The *udata* argument enables the called transport user to send user data to the caller and the amount of user data must not exceed the limits supported by the transport provider as returned in the *connect* field of the *info* argument of `t_open(3NSL)` or `t_getinfo(3NSL)`. If the *len* field of *udata* is zero, no data will be sent to the caller. All the *maxlen* fields are meaningless.

When the user does not indicate any option (*call*→*opt.len* = 0) the connection shall be accepted with the option values currently set for the responding endpoint *resfd*.

Return Values Upon successful completion, a value of 0 is returned. Otherwise, a value of -1 is returned and `t_errno` is set to indicate an error.

Valid States `fd`: `T_INCON`

`resfd` (`fd!=resfd`): `T_IDLE`, `T_UNBND`

Errors On failure, `t_errno` is set to one of the following:

TACCES	The user does not have permission to accept a connection on the responding transport endpoint or to use the specified options.
TBADADDR	The specified protocol address was in an incorrect format or contained illegal information.
TBADDATA	The amount of user data specified was not within the bounds allowed by the transport provider.
TBADFD	The file descriptor <i>fd</i> or <i>resfd</i> does not refer to a transport endpoint.
TBADOPT	The specified options were in an incorrect format or contained illegal information.
TBADSEQ	Either an invalid sequence number was specified, or a valid sequence number was specified but the connection request was aborted by the peer. In the latter case, its <code>T_DISCONNECT</code> event will be received on the listening endpoint.
TINDOUT	The function was called with <i>fd</i> == <i>resfd</i> but there are outstanding connection indications on the endpoint. Those other connection indications must be handled either by rejecting them by means of <code>t_snddis(3NSL)</code> or accepting them on a different endpoint by means of <code>t_accept</code> .
TLOOK	An asynchronous event has occurred on the transport endpoint referenced by <i>fd</i> and requires immediate attention.
TNOTSUPPORT	This function is not supported by the underlying transport provider.

TOUTSTATE	The communications endpoint referenced by <i>fd</i> or <i>resfd</i> is not in one of the states in which a call to this function is valid.
TPROTO	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<code>t_errno</code>).
TPROVMISMATCH	The file descriptors <i>fd</i> and <i>resfd</i> do not refer to the same transport provider.
TRESADDR	This transport provider requires both <i>fd</i> and <i>resfd</i> to be bound to the same address. This error results if they are not.
TRESQLEN	The endpoint referenced by <i>resfd</i> (where <i>resfd</i> != <i>fd</i>) was bound to a protocol address with a <i>qlen</i> that is greater than zero.
TSYSERR	A system error has occurred during execution of this function.

Tli Compatibility The XTI and TLI interface definitions have common names but use different header files. This, and other semantic differences between the two interfaces are described in the subsections below.

Interface Header The XTI interfaces use the header file, `xti.h`. TLI interfaces should *not* use this header. They should use the header:

```
#include <tiuser.h>
```

Error Description Values The `t_errno` values that can be set by the XTI interface and cannot be set by the TLI interface are:

TPROTO

TINDOUT

TPROVMISMATCH

TRESADDR

TRESQLEN

Option Buffer The format of the options in an `opt` buffer is dictated by the transport provider. Unlike the XTI interface, the TLI interface does not specify the buffer format.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [t_connect\(3NSL\)](#), [t_getinfo\(3NSL\)](#), [t_getstate\(3NSL\)](#), [t_listen\(3NSL\)](#), [t_open\(3NSL\)](#), [t_optmgmt\(3NSL\)](#), [t_rcvconnect\(3NSL\)](#), [t_snddis\(3NSL\)](#), [attributes\(5\)](#)

Warnings There may be transport provider-specific restrictions on address binding.

Some transport providers do not differentiate between a connection indication and the connection itself. If the connection has already been established after a successful return of [t_listen\(3NSL\)](#), `t_accept()` will assign the existing connection to the transport endpoint specified by *resfd*.

Name t_alloc – allocate a library structure

Synopsis #include <xti.h>

```
void *t_alloc(int fd, int struct_type, int fields);
```

Description This routine is part of the XTI interfaces which evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI routine that has the same name as an XTI routine, a different header file, `tiuser.h`, must be used. Refer to the section, TLI COMPATIBILITY, for a description of differences between the two interfaces.

The `t_alloc()` function dynamically allocates memory for the various transport function argument structures as specified below. This function will allocate memory for the specified structure, and will also allocate memory for buffers referenced by the structure.

The structure to allocate is specified by *struct_type* and must be one of the following:

T_BIND	struct	t_bind
T_CALL	struct	t_call
T_OPTMGMT	struct	t_optmgmt
T_DIS	struct	t_discon
T_UNITDATA	struct	t_unitdata
T_UDERROR	struct	t_uderr
T_INFO	struct	t_info

where each of these structures may subsequently be used as an argument to one or more transport functions.

Each of the above structures, except `T_INFO`, contains at least one field of type `struct netbuf`. For each field of this type, the user may specify that the buffer for that field should be allocated as well. The length of the buffer allocated will be equal to or greater than the appropriate size as returned in the *info* argument of `t_open(3NSL)` or `t_getinfo(3NSL)`. The relevant fields of the *info* argument are described in the following list. The *fields* argument specifies which buffers to allocate, where the argument is the bitwise-or of any of the following:

T_ADDR	The <i>addr</i> field of the <code>t_bind</code> , <code>t_call</code> , <code>t_unitdata</code> or <code>t_uderr</code> structures.
T_OPT	The <i>opt</i> field of the <code>t_optmgmt</code> , <code>t_call</code> , <code>t_unitdata</code> or <code>t_uderr</code> structures.
T_UDATA	The <i>udata</i> field of the <code>t_call</code> , <code>t_discon</code> or <code>t_unitdata</code> structures.
T_ALL	All relevant fields of the given structure. Fields which are not supported by the transport provider specified by <i>fd</i> will not be allocated.

For each relevant field specified in *fields*, `t_alloc()` will allocate memory for the buffer associated with the field, and initialize the *len* field to zero and the *buf* pointer and *maxlen* field

accordingly. Irrelevant or unknown values passed in fields are ignored. Since the length of the buffer allocated will be based on the same size information that is returned to the user on a call to `t_open(3NSL)` and `t_getinfo(3NSL)`, *fd* must refer to the transport endpoint through which the newly allocated structure will be passed. In the case where a `T_INFO` structure is to be allocated, *fd* may be set to any value. In this way the appropriate size information can be accessed. If the size value associated with any specified field is `T_INVALID`, `t_alloc()` will be unable to determine the size of the buffer to allocate and will fail, setting `t_errno` to `TSYSERR` and `errno` to `EINVAL`. See `t_open(3NSL)` or `t_getinfo(3NSL)`. If the size value associated with any specified field is `T_INFINITE`, then the behavior of `t_alloc()` is implementation-defined. For any field not specified in *fields*, *buf* will be set to the null pointer and *len* and *maxlen* will be set to zero. See `t_open(3NSL)` or `t_getinfo(3NSL)`.

The pointer returned if the allocation succeeds is suitably aligned so that it can be assigned to a pointer to any type of object and then used to access such an object or array of such objects in the space allocated.

Use of `t_alloc()` to allocate structures will help ensure the compatibility of user programs with future releases of the transport interface functions.

Return Values On successful completion, `t_alloc()` returns a pointer to the newly allocated structure. On failure, a null pointer is returned.

Valid States ALL - apart from `T_UNINIT`

Errors On failure, `t_errno` is set to one of the following:

TBADF	<code>struct_type</code> is other than <code>T_INFO</code> and the specified file descriptor does not refer to a transport endpoint.
TNOSTRUCTYPE	Unsupported <i>struct_type</i> requested. This can include a request for a structure type which is inconsistent with the transport provider type specified, that is, connection-mode or connectionless-mode.
TPROTO	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<code>t_errno</code>).
TSYSERR	A system error has occurred during execution of this function.

Tli Compatibility The XTI and TLI interface definitions have common names but use different header files. This, and other semantic differences between the two interfaces are described in the subsections below.

Interface Header The XTI interfaces use the header file, `xti.h`. TLI interfaces should *not* use this header. They should use the header:

```
#include <tiuser.h>
```

Error Description Values The `t_errno` values that can be set by the XTI interface and cannot be set by the TLI interface are:

```
TPROTO
TNOSTRUCTYPE
```

Special Buffer Sizes Assume that the value associated with any field of `struct t_info` (argument returned by `t_open()` or `t_getinfo()`) that describes buffer limits is `-1`. Then the underlying service provider can support a buffer of unlimited size. If this is the case, `t_alloc()` will allocate a buffer with the default size 1024 bytes, which may be handled as described in the next paragraph.

If the underlying service provider supports a buffer of unlimited size in the `netbuf` structure (see [t_connect\(3NSL\)](#)), `t_alloc()` will return a buffer of size 1024 bytes. If a larger size buffer is required, it will need to be allocated separately using a memory allocation routine such as [malloc\(3C\)](#). The `buf` and `maxlen` fields of the `netbuf` data structure can then be updated with the address of the new buffer and the 1024 byte buffer originally allocated by `t_alloc()` can be freed using [free\(3C\)](#).

Assume that the value associated with any field of `struct t_info` (argument returned by `t_open()` or `t_getinfo()`) that describes `nbuffer` limits is `-2`. Then `t_alloc()` will set the buffer pointer to `NULL` and the buffer maximum size to `0`, and then will return success (see [t_open\(3NSL\)](#) or [t_getinfo\(3NSL\)](#)).

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [free\(3C\)](#), [malloc\(3C\)](#), [t_connect\(3NSL\)](#), [t_free\(3NSL\)](#), [t_getinfo\(3NSL\)](#), [t_open\(3NSL\)](#), [attributes\(5\)](#)

Name t_bind – bind an address to a transport endpoint

Synopsis #include <xti.h>

```
int t_bind(int fd, const struct t_bind *req, struct t_bind *ret);
```

Description This routine is part of the XTI interfaces that evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI routine that has the same name as an XTI routine, the `tiuser.h` header file must be used. Refer to the TLI COMPATIBILITY section for a description of differences between the two interfaces.

This function associates a protocol address with the transport endpoint specified by *fd* and activates that transport endpoint. In connection mode, the transport provider may begin enqueueing incoming connect indications, or servicing a connection request on the transport endpoint. In connectionless-mode, the transport user may send or receive data units through the transport endpoint.

The *req* and *ret* arguments point to a `t_bind` structure containing the following members:

```
struct netbuf    addr;
unsigned        qlen;
```

The *addr* field of the `t_bind` structure specifies a protocol address, and the *qlen* field is used to indicate the maximum number of outstanding connection indications.

The parameter *req* is used to request that an address, represented by the `netbuf` structure, be bound to the given transport endpoint. The parameter *len* specifies the number of bytes in the address, and *buf* points to the address buffer. The parameter *maxlen* has no meaning for the *req* argument. On return, *ret* contains an encoding for the address that the transport provider actually bound to the transport endpoint; if an address was specified in *req*, this will be an encoding of the same address. In *ret*, the user specifies *maxlen*, which is the maximum size of the address buffer, and *buf* which points to the buffer where the address is to be placed. On return, *len* specifies the number of bytes in the bound address, and *buf* points to the bound address. If *maxlen* equals zero, no address is returned. If *maxlen* is greater than zero and less than the length of the address, `t_bind()` fails with `t_errno` set to `TBUFOVFLW`.

If the requested address is not available, `t_bind()` will return `-1` with `t_errno` set as appropriate. If no address is specified in *req* (the *len* field of *addr* in *req* is zero or *req* is `NULL`), the transport provider will assign an appropriate address to be bound, and will return that address in the *addr* field of *ret*. If the transport provider could not allocate an address, `t_bind()` will fail with `t_errno` set to `TNOADDR`.

The parameter *req* may be a null pointer if the user does not wish to specify an address to be bound. Here, the value of *qlen* is assumed to be zero, and the transport provider will assign an address to the transport endpoint. Similarly, *ret* may be a null pointer if the user does not care

what address was bound by the provider and is not interested in the negotiated value of *qlen*. It is valid to set *req* and *ret* to the null pointer for the same call, in which case the provider chooses the address to bind to the transport endpoint and does not return that information to the user.

The *qlen* field has meaning only when initializing a connection-mode service. It specifies the number of outstanding connection indications that the transport provider should support for the given transport endpoint. An outstanding connection indication is one that has been passed to the transport user by the transport provider but which has not been accepted or rejected. A value of *qlen* greater than zero is only meaningful when issued by a passive transport user that expects other users to call it. The value of *qlen* will be negotiated by the transport provider and may be changed if the transport provider cannot support the specified number of outstanding connection indications. However, this value of *qlen* will never be negotiated from a requested value greater than zero to zero. This is a requirement on transport providers; see WARNINGS below. On return, the *qlen* field in *ret* will contain the negotiated value.

If *fd* refers to a connection-mode service, this function allows more than one transport endpoint to be bound to the same protocol address, but it is not possible to bind more than one protocol address to the same transport endpoint. However, the transport provider must also support this capability. If a user binds more than one transport endpoint to the same protocol address, only one endpoint can be used to listen for connection indications associated with that protocol address. In other words, only one `t_bind()` for a given protocol address may specify a value of *qlen* greater than zero. In this way, the transport provider can identify which transport endpoint should be notified of an incoming connection indication. If a user attempts to bind a protocol address to a second transport endpoint with a value of *qlen* greater than zero, `t_bind()` will return `-1` and set `t_errno` to `TADDRBUSY`. When a user accepts a connection on the transport endpoint that is being used as the listening endpoint, the bound protocol address will be found to be busy for the duration of the connection, until a `t_unbind(3NSL)` or `t_close(3NSL)` call has been issued. No other transport endpoints may be bound for listening on that same protocol address while that initial listening endpoint is active (in the data transfer phase or in the `T_IDLE` state). This will prevent more than one transport endpoint bound to the same protocol address from accepting connection indications.

If *fd* refers to connectionless mode service, this function allows for more than one transport endpoint to be associated with a protocol address, where the underlying transport provider supports this capability (often in conjunction with value of a protocol-specific option). If a user attempts to bind a second transport endpoint to an already bound protocol address when such capability is not supported for a transport provider, `t_bind()` will return `-1` and set `t_errno` to `TADDRBUSY`.

Return Values Upon successful completion, a value of 0 is returned. Otherwise, a value of `-1` is returned and `t_errno` is set to indicate an error.

Valid States T_UNBND**Errors** On failure, `t_errno` is set to one of the following:

TACCES	The user does not have permission to use the specified address.
TADDRBUSY	The requested address is in use.
TBADADDR	The specified protocol address was in an incorrect format or contained illegal information.
TBADF	The specified file descriptor does not refer to a transport endpoint.
TBUFOVFLW	The number of bytes allowed for an incoming argument (<i>maxlen</i>) is greater than 0 but not sufficient to store the value of that argument. The provider's state will change to T_IDLE and the information to be returned in <i>ret</i> will be discarded.
TOUTSTATE	The communications endpoint referenced by <i>fd</i> is not in one of the states in which a call to this function is valid.
TNOADDR	The transport provider could not allocate an address.
TPROTO	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<code>t_errno</code>).
TSYSERR	A system error has occurred during execution of this function.

Tli Compatibility The XTI and TLI interface definitions have common names but use different header files. This, and other semantic differences between the two interfaces are described in the subsections below.

Interface Header The XTI interfaces use the header file, `xti.h`. TLI interfaces should *not* use this header. They should use the header:

```
#include <tiuser.h>
```

Address Bound The user can compare the addresses in *req* and *ret* to determine whether the transport provider bound the transport endpoint to a different address than that requested.

Error Description Values The `t_errno` values TPROTO and TADDRBUSY can be set by the XTI interface but cannot be set by the TLI interface.

A `t_errno` value that this routine can return under different circumstances than its XTI counterpart is TBUFOVFLW. It can be returned even when the *maxlen* field of the corresponding buffer has been set to zero.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [t_accept\(3NSL\)](#), [t_alloc\(3NSL\)](#), [t_close\(3NSL\)](#), [t_connect\(3NSL\)](#), [t_unbind\(3NSL\)](#), [attributes\(5\)](#)

Warnings The requirement that the value of *qlen* never be negotiated from a requested value greater than zero to zero implies that transport providers, rather than the XTI implementation itself, accept this restriction.

An implementation need not allow an application explicitly to bind more than one communications endpoint to a single protocol address, while permitting more than one connection to be accepted to the same protocol address. That means that although an attempt to bind a communications endpoint to some address with *qlen*=0 might be rejected with TADDRBUSY, the user may nevertheless use this (unbound) endpoint as a responding endpoint in a call to [t_accept\(3NSL\)](#). To become independent of such implementation differences, the user should supply unbound responding endpoints to [t_accept\(3NSL\)](#).

The local address bound to an endpoint may change as result of a [t_accept\(3NSL\)](#) or [t_connect\(3NSL\)](#) call. Such changes are not necessarily reversed when the connection is released.

Name t_close – close a transport endpoint

Synopsis #include <xti.h>

```
int t_close(int fd);
```

Description This routine is part of the XTI interfaces which evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI routine that has the same name as an XTI routine, the `tiuser.h` header file must be used. Refer to the TLI COMPATIBILITY section for a description of differences between the two interfaces.

The `t_close()` function informs the transport provider that the user is finished with the transport endpoint specified by `fd`, and frees any local library resources associated with the endpoint. In addition, `t_close()` closes the file associated with the transport endpoint.

The function `t_close()` should be called from the `T_UNBND` state. See [t_getstate\(3NSL\)](#). However, this function does not check state information, so it may be called from any state to close a transport endpoint. If this occurs, the local library resources associated with the endpoint will be freed automatically. In addition, [close\(2\)](#) will be issued for that file descriptor; if there are no other descriptors in this process or in another process which references the communication endpoint, any connection that may be associated with that endpoint is broken. The connection may be terminated in an orderly or abortive manner.

A `t_close()` issued on a connection endpoint may cause data previously sent, or data not yet received, to be lost. It is the responsibility of the transport user to ensure that data is received by the remote peer.

Return Values Upon successful completion, a value of 0 is returned. Otherwise, a value of -1 is returned and `t_errno` is set to indicate an error.

Valid States `T_UNBND`

Errors On failure, `t_errno` is set to the following:

TBADF	The specified file descriptor does not refer to a transport endpoint.
TPROTO	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<code>t_errno</code>).
TSYSERR	A system error has occurred during execution of this function.

- Tli Compatibility

The XTI and TLI interface definitions have common names but use different header files. This, and other semantic differences between the two interfaces are described in the subsections below.
- Interface Header

The XTI interfaces use the header file, `xti.h`. TLI interfaces should *not* use this header. They should use the header:

`#include <tiuser.h>`
- Error Description Values

The `t_errno` value that can be set by the XTI interface and cannot be set by the TLI interface is:

TPROTO
- Attributes

See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [close\(2\)](#), [t_getstate\(3NSL\)](#), [t_open\(3NSL\)](#), [t_unbind\(3NSL\)](#), [attributes\(5\)](#)

Name t_connect – establish a connection with another transport user

Synopsis #include <xti.h>

```
int t_connect(int fd, const struct t_call *sndcall,
              struct t_call *rcvcall);
```

Description This routine is part of the XTI interfaces which evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI routine that has the same name as an XTI routine, the `tiuser.h` header file must be used. Refer to the TLI COMPATIBILITY section for a description of differences between the two interfaces. This function enables a transport user to request a connection to the specified destination transport user.

This function can only be issued in the `T_IDLE` state. The parameter *fd* identifies the local transport endpoint where communication will be established, while *sndcall* and *rcvcall* point to a `t_call` structure which contains the following members:

```
struct netbuf addr;
struct netbuf opt;
struct netbuf udata;
int sequence;
```

The parameter *sndcall* specifies information needed by the transport provider to establish a connection and *rcvcall* specifies information that is associated with the newly established connection.

In *sndcall*, *addr* specifies the protocol address of the destination transport user, *opt* presents any protocol-specific information that might be needed by the transport provider, *udata* points to optional user data that may be passed to the destination transport user during connection establishment, and *sequence* has no meaning for this function.

On return, in *rcvcall*, *addr* contains the protocol address associated with the responding transport endpoint, *opt* represents any protocol-specific information associated with the connection, *udata* points to optional user data that may be returned by the destination transport user during connection establishment, and *sequence* has no meaning for this function.

The *opt* argument permits users to define the options that may be passed to the transport provider. The user may choose not to negotiate protocol options by setting the *len* field of *opt* to zero. In this case, the provider uses the option values currently set for the communications endpoint.

If used, *sndcall*→*opt.buf* must point to a buffer with the corresponding options, and *sndcall*→*opt.len* must specify its length. The *maxlen* and *buf* fields of the `netbuf` structure pointed by *rcvcall*→*addr* and *rcvcall*→*opt* must be set before the call.

The *udata* argument enables the caller to pass user data to the destination transport user and receive user data from the destination user during connection establishment. However, the amount of user data must not exceed the limits supported by the transport provider as returned in the *connect* field of the *info* argument of [t_open\(3NSL\)](#) or [t_getinfo\(3NSL\)](#). If the *len* of *udata* is zero in *sndcall*, no data will be sent to the destination transport user.

On return, the *addr*, *opt* and *udata* fields of *rcvcall* will be updated to reflect values associated with the connection. Thus, the *maxlen* field of each argument must be set before issuing this function to indicate the maximum size of the buffer for each. However, *maxlen* can be set to zero, in which case no information to this specific argument is given to the user on the return from `t_connect()`. If *maxlen* is greater than zero and less than the length of the value, `t_connect()` fails with `t_errno` set to `TBUFOVFLW`. If *rcvcall* is set to `NULL`, no information at all is returned.

By default, `t_connect()` executes in synchronous mode, and will wait for the destination user's response before returning control to the local user. A successful return (that is, return value of zero) indicates that the requested connection has been established. However, if `O_NONBLOCK` is set by means of [t_open\(3NSL\)](#) or [fcntl\(2\)](#), `t_connect()` executes in asynchronous mode. In this case, the call will not wait for the remote user's response, but will return control immediately to the local user and return `-1` with `t_errno` set to `TNODATA` to indicate that the connection has not yet been established. In this way, the function simply initiates the connection establishment procedure by sending a connection request to the destination transport user. The [t_rcvconnect\(3NSL\)](#) function is used in conjunction with `t_connect()` to determine the status of the requested connection.

When a synchronous `t_connect()` call is interrupted by the arrival of a signal, the state of the corresponding transport endpoint is `T_OUTCON`, allowing a further call to either [t_rcvconnect\(3NSL\)](#), [t_rcvdis\(3NSL\)](#) or [t_snddis\(3NSL\)](#). When an asynchronous `t_connect()` call is interrupted by the arrival of a signal, the state of the corresponding transport endpoint is `T_IDLE`.

Return Values Upon successful completion, a value of `0` is returned. Otherwise, a value of `-1` is returned and `t_errno` is set to indicate an error.

Valid States `T_IDLE`

Errors On failure, `t_errno` is set to one of the following:

<code>TACCES</code>	The user does not have permission to use the specified address or options.
<code>TADDRBUSY</code>	This transport provider does not support multiple connections with the same local and remote addresses. This error indicates that a connection already exists.
<code>TBADADDR</code>	The specified protocol address was in an incorrect format or contained illegal information.

TBADDATA	The amount of user data specified was not within the bounds allowed by the transport provider.
TBADF	The specified file descriptor does not refer to a transport endpoint.
TBADOPT	The specified protocol options were in an incorrect format or contained illegal information.
TBUFOVFLW	The number of bytes allocated for an incoming argument (<i>maxlen</i>) is greater than 0 but not sufficient to store the value of that argument. If executed in synchronous mode, the provider's state, as seen by the user, changes to T_DATAXFER, and the information to be returned in <i>rcvcall</i> is discarded.
TLOOK	An asynchronous event has occurred on this transport endpoint and requires immediate attention.
TNODATA	O_NONBLOCK was set, so the function successfully initiated the connection establishment procedure, but did not wait for a response from the remote user.
TNOTSUPPORT	This function is not supported by the underlying transport provider.
TOUTSTATE	The communications endpoint referenced by <i>fd</i> is not in one of the states in which a call to this function is valid.
TPROTO	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<i>t_errno</i>).
TSYSERR	A system error has occurred during execution of this function.

Tli Compatibility The XTI and TLI interface definitions have common names but use different header files. This, and other semantic differences between the two interfaces are described in the subsections below.

Interface Header The XTI interfaces use the header file, *xti.h*. TLI interfaces should *not* use this header. They should use the header:

```
#include <tiuser.h>
```

Error Description Values The TPROTO and TADDRBUSY *t_errno* values can be set by the XTI interface but not by the TLI interface.

A *t_errno* value that this routine can return under different circumstances than its XTI counterpart is TBUFOVFLW. It can be returned even when the *maxlen* field of the corresponding buffer has been set to zero.

Option Buffers The format of the options in an opt buffer is dictated by the transport provider. Unlike the XTI interface, the TLI interface does not fix the buffer format.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [fcntl\(2\)](#), [t_accept\(3NSL\)](#), [t_alloc\(3NSL\)](#), [t_getinfo\(3NSL\)](#), [t_listen\(3NSL\)](#), [t_open\(3NSL\)](#), [t_optmgmt\(3NSL\)](#), [t_rcvconnect\(3NSL\)](#), [t_rcvdis\(3NSL\)](#), [t_snddis\(3NSL\)](#), [attributes](#)

Name	t_errno – XTI error return value
Synopsis	<pre>#include <xti.h></pre>
Description	<p>This error return value is part of the XTI interfaces that evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI interface that has the same name as an XTI interfaces, a different headerfile, <tiuser.h>, must be used. Refer the the TLI COMPATIBILITY section for a description of differences between the two interfaces.</p> <p>t_errno is used by XTI functions to return error values.</p> <p>XTI functions provide an error number in t_errno which has type <i>int</i> and is defined in <xti.h>. The value of t_errno will be defined only after a call to a XTI function for which it is explicitly stated to be set and until it is changed by the next XTI function call. The value of t_errno should only be examined when it is indicated to be valid by a function's return value. Programs should obtain the definition of t_errno by the inclusion of <xti.h>. The practice of defining t_errno in program as <code>extern int t_errno</code> is obsolescent. No XTI function sets t_errno to 0 to indicate an error.</p> <p>It is unspecified whether t_errno is a macro or an identifier with external linkage. It represents a modifiable lvalue of type <i>int</i>. If a macro definition is suppressed in order to access an actual object or a program defines an identifier with name <i>t_errno</i>, the behavior is undefined.</p> <p>The symbolic values stored in t_errno by an XTI function are defined in the ERRORS sections in all relevant XTI function definition pages.</p>
Tli Compatibility	<p>t_errno is also used by TLI functions to return error values.</p> <p>The XTI and TLI interface definitions have common names but use different header files. This, and other semantic differences between the two interfaces are described in the subsections below.</p>
Interface Header	<p>The XTI interfaces use the header file, <xti.h>. TLI interfaces should <i>not</i> use this header. They should use the header:</p> <pre>#include <tiuser.h></pre>
Error Description Values	<p>The t_errno values that can be set by the XTI interface but cannot be set by the TLI interface are:</p> <pre>TNOSTRUCTYPE TBADNAME TBADQLEN TADDRBUSY</pre>

TINDOUT
TPROVMISMATCH
TRESADDR
TQFULL
TPROTO

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [attributes\(5\)](#)

Name t_error – produce error message

Synopsis #include <xti.h>

```
int t_error(const char *errmsg);
```

Description This routine is part of the XTI interfaces which evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI routine that has the same name as an XTI routine, the `tuser.h` header file must be used. Refer to the TLI COMPATIBILITY section for a description of differences between the two interfaces.

The `t_error()` function produces a message on the standard error output which describes the last error encountered during a call to a transport function. The argument string `errmsg` is a user-supplied error message that gives context to the error.

The error message is written as follows: first (if `errmsg` is not a null pointer and the character pointed to by `errmsg` is not the null character) the string pointed to by `errmsg` followed by a colon and a space; then a standard error message string for the current error defined in `t_errno`. If `t_errno` has a value different from `TSYSERR`, the standard error message string is followed by a newline character. If, however, `t_errno` is equal to `TSYSERR`, the `t_errno` string is followed by the standard error message string for the current error defined in `errno` followed by a newline.

The language for error message strings written by `t_error()` is that of the current locale. If it is English, the error message string describing the value in `t_errno` may be derived from the comments following the `t_errno` codes defined in `xti.h`. The contents of the error message strings describing the value in `errno` are the same as those returned by the [strerror\(3C\)](#) function with an argument of `errno`.

The error number, `t_errno`, is only set when an error occurs and it is not cleared on successful calls.

Examples If a [t_connect\(3NSL\)](#) function fails on transport endpoint `fd2` because a bad address was given, the following call might follow the failure:

```
t_error("t_connect failed on fd2");
```

The diagnostic message to be printed would look like:

```
t_connect failed on fd2: incorrect addr format
```

where *incorrect addr format* identifies the specific error that occurred, and *t_connect failed on fd2* tells the user which function failed on which transport endpoint.

Return Values Upon completion, a value of 0 is returned.

Valid States All - apart from T_UNINIT

Errors No errors are defined for the t_error() function.

Tli Compatibility The XTI and TLI interface definitions have common names but use different header files. This, and other semantic differences between the two interfaces are described in the subsections below.

Interface Header The XTI interfaces use the header file, xti.h. TLI interfaces should *not* use this header. They should use the header:

```
#include <tiuser.h>
```

Error Description Values The t_errno value that can be set by the XTI interface and cannot be set by the TLI interface is:

TPROTO

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [t_errno\(3NSL\)](#), [strerror\(3C\)](#), [attributes\(5\)](#)

Name t_free – free a library structure

Synopsis #include <xti.h>

```
int t_free(void *ptr, int struct_type);
```

Description This routine is part of the XTI interfaces which evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI routine that has the same name as an XTI routine, the `t_iuser.h` header file must be used. Refer to the TLI COMPATIBILITY section for a description of differences between the two interfaces.

The `t_free()` function frees memory previously allocated by `t_alloc(3NSL)`. This function will free memory for the specified structure, and will also free memory for buffers referenced by the structure.

The argument *ptr* points to one of the seven structure types described for `t_alloc(3NSL)`, and *struct_type* identifies the type of that structure which must be one of the following:

T_BIND	struct	t_bind
T_CALL	struct	t_call
T_OPTMGMT	struct	t_optmgmt
T_DIS	struct	t_discon
T_UNITDATA	struct	t_unitdata
T_UDERROR	struct	t_uderr
T_INFO	struct	t_info

where each of these structures is used as an argument to one or more transport functions.

The function `t_free()` will check the *addr*, *opt* and *udata* fields of the given structure, as appropriate, and free the buffers pointed to by the *buf* field of the netbuf structure. If *buf* is a null pointer, `t_free()` will not attempt to free memory. After all buffers are freed, `t_free()` will free the memory associated with the structure pointed to by *ptr*.

Undefined results will occur if *ptr* or any of the *buf* pointers points to a block of memory that was not previously allocated by `t_alloc(3NSL)`.

Return Values Upon successful completion, a value of 0 is returned. Otherwise, a value of -1 is returned and `t_errno` is set to indicate an error.

Valid States ALL - apart from T_UNINIT.

Errors On failure, `t_errno` is set to the following:

TNOSTRUCTYPE Unsupported *struct_type* requested.

- TPROTO

This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (*t_errno*).
- TSYSERR

A system error has occurred during execution of this function.

Tli Compatibility The XTI and TLI interface definitions have common names but use different header files. This, and other semantic differences between the two interfaces are described in the subsections below.

Interface Header

The XTI interfaces use the header file, `xti.h`. TLI interfaces should *not* use this header. They should use the header:

`#include <tiuser.h>`

Error Description Values

The `t_errno` value that can be set by the XTI interface and cannot be set by the TLI interface is:

TPROTO

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [t_alloc\(3NSL\)](#), [attributes\(5\)](#)

Name t_getinfo – get protocol-specific service information

Synopsis #include <xti.h>

```
int t_getinfo(int fd, struct t_info *info);
```

Description This routine is part of the XTI interfaces which evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI routine that has the same name as an XTI routine, the `tiuser.h` header file must be used. Refer to the TLI COMPATIBILITY section for a description of differences between the two interfaces.

This function returns the current characteristics of the underlying transport protocol and/or transport connection associated with file descriptor *fd*. The *info* pointer is used to return the same information returned by `t_open(3NSL)`, although not necessarily precisely the same values. This function enables a transport user to access this information during any phase of communication.

This argument points to a `t_info` structure which contains the following members:

```
t_scalar_t addr;      /*max size in octets of the transport protocol address*/
t_scalar_t options;   /*max number of bytes of protocol-specific options */
t_scalar_t tsdu;      /*max size in octets of a transport service data unit */
t_scalar_t etsdu;     /*max size in octets of an expedited transport service*/
                    /*data unit (ETSDU) */
t_scalar_t connect;   /*max number of octets allowed on connection */
                    /*establishment functions */
t_scalar_t discon;    /*max number of octets of data allowed on t_snddis() */
                    /*and t_rcvdis() functions */
t_scalar_t servtype;  /*service type supported by the transport provider */
t_scalar_t flags;     /*other info about the transport provider */
```

The values of the fields have the following meanings:

<i>addr</i>	A value greater than zero indicates the maximum size of a transport protocol address and a value of <code>T_INVALID</code> (-2) specifies that the transport provider does not provide user access to transport protocol addresses.
<i>options</i>	A value greater than zero indicates the maximum number of bytes of protocol-specific options supported by the provider, and a value of <code>T_INVALID</code> (-2) specifies that the transport provider does not support user-settable options.
<i>tsdu</i>	A value greater than zero specifies the maximum size in octets of a transport service data unit (TSDU); a value of <code>T_NULL</code> (zero) specifies that the transport provider does not support the concept of TSDU, although it does support the sending of a datastream with no logical boundaries preserved across a connection; a value of <code>T_INFINITE</code> (-1) specifies that there is no limit on the size

in octets of a TSDU; and a value of `T_INVALID` (−2) specifies that the transfer of normal data is not supported by the transport provider.

<i>etsdu</i>	A value greater than zero specifies the maximum size in octets of an expedited transport service data unit (ETSDU); a value of <code>T_NULL</code> (zero) specifies that the transport provider does not support the concept of ETSDU, although it does support the sending of an expedited data stream with no logical boundaries preserved across a connection; a value of <code>T_INFINITE</code> (−1) specifies that there is no limit on the size (in octets) of an ETSDU; and a value of <code>T_INVALID</code> (−2) specifies that the transfer of expedited data is not supported by the transport provider. Note that the semantics of expedited data may be quite different for different transport providers.
<i>connect</i>	A value greater than zero specifies the maximum number of octets that may be associated with connection establishment functions and a value of <code>T_INVALID</code> (−2) specifies that the transport provider does not allow data to be sent with connection establishment functions.
<i>discon</i>	If the <code>T_ORDRELDATA</code> bit in flags is clear, a value greater than zero specifies the maximum number of octets that may be associated with the <code>t_snddis(3NSL)</code> and <code>t_rcvdis(3NSL)</code> functions, and a value of <code>T_INVALID</code> (−2) specifies that the transport provider does not allow data to be sent with the abortive release functions. If the <code>T_ORDRELDATA</code> bit is set in flags, a value greater than zero specifies the maximum number of octets that may be associated with the <code>t_sndreldata()</code> , <code>t_rcvreldata()</code> , <code>t_snddis(3NSL)</code> and <code>t_rcvdis(3NSL)</code> functions.
<i>servtype</i>	This field specifies the service type supported by the transport provider, as described below.
<i>flags</i>	This is a bit field used to specify other information about the communications provider. If the <code>T_ORDRELDATA</code> bit is set, the communications provider supports sending user data with an orderly release. If the <code>T_SENDCZERO</code> bit is set in flags, this indicates that the underlying transport provider supports the sending of zero-length TSDUs.

If a transport user is concerned with protocol independence, the above sizes may be accessed to determine how large the buffers must be to hold each piece of information. Alternatively, the `t_alloc(3NSL)` function may be used to allocate these buffers. An error will result if a transport user exceeds the allowed data size on any function. The value of each field may change as a result of protocol option negotiation during connection establishment (the `t_optmgmt(3NSL)` call has no effect on the values returned by `t_getinfo()`). These values will only change from the values presented to `t_open(3NSL)` after the endpoint enters the `T_DATAXFER` state.

The *servtype* field of *info* specifies one of the following values on return:

T_COTS	The transport provider supports a connection-mode service but does not support the optional orderly release facility.
T_COTS_ORD	The transport provider supports a connection-mode service with the optional orderly release facility.
T_CLTS	The transport provider supports a connectionless-mode service. For this service type, t_open(3NSL) will return T_INVALID (−1) for <i>etsdu</i> , <i>connect</i> and <i>discon</i> .

Return Values Upon successful completion, a value of 0 is returned. Otherwise, a value of −1 is returned and `t_errno` is set to indicate an error.

Valid States ALL - apart from T_UNINIT.

Errors On failure, `t_errno` is set to one of the following:

TBADF	The specified file descriptor does not refer to a transport endpoint.
TPROTO	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<code>t_errno</code>).
TSYSERR	A system error has occurred during execution of this function.

Tli Compatibility The XTI and TLI interface definitions have common names but use different header files. This, and other semantic differences between the two interfaces are described in the subsections below.

Interface Header The XTI interfaces use the header file, `xti.h`. TLI interfaces should *not* use this header. They should use the header:

```
#include <tiuser.h>
```

Error Description Values The `t_errno` value TPROTO can be set by the XTI interface but not by the TLI interface.

The t_info Structure For TLI, the `t_info` structure referenced by *info* lacks the following structure member:

```
t_scalar_t flags;    /* other info about the transport provider */
```

This member was added to `struct t_info` in the XTI interfaces.

When a value of −1 is observed as the return value in various `t_info` structure members, it signifies that the transport provider can handle an infinite length buffer for a corresponding attribute, such as address data, option data, TSDU (octet size), ETSDU (octet size), connection data, and disconnection data. The corresponding structure members are `addr`, `options`, `tsdu`, `estdu`, `connect`, and `discon`, respectively.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [t_alloc\(3NSL\)](#), [t_open\(3NSL\)](#), [t_optmgmt\(3NSL\)](#), [t_rcvdis\(3NSL\)](#), [t_snddis\(3NSL\)](#), [attributes\(5\)](#)

Name t_getprotaddr – get the protocol addresses

Synopsis #include <xti.h>

```
int t_getprotaddr(int fd, struct t_bind *boundaddr,
                  struct t_bind *peeraddr);
```

Description This routine is part of the XTI interfaces which evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI routine that has the same name as an XTI routine, the `tiuser.h` header file must be used. Refer to the TLI COMPATIBILITY section for a description of differences between the two interfaces.

The `t_getprotaddr()` function returns local and remote protocol addresses currently associated with the transport endpoint specified by *fd*. In *boundaddr* and *peeraddr* the user specifies *maxlen*, which is the maximum size (in bytes) of the address buffer, and *buf* which points to the buffer where the address is to be placed. On return, the *buf* field of *boundaddr* points to the address, if any, currently bound to *fd*, and the *len* field specifies the length of the address. If the transport endpoint is in the `T_UNBND` state, zero is returned in the *len* field of *boundaddr*. The *buf* field of *peeraddr* points to the address, if any, currently connected to *fd*, and the *len* field specifies the length of the address. If the transport endpoint is not in the `T_DATAFER`, `T_INREL`, `T_OUTCON` or `T_OUTREL` states, zero is returned in the *len* field of *peeraddr*. If the *maxlen* field of *boundaddr* or *peeraddr* is set to zero, no address is returned.

Return Values Upon successful completion, a value of 0 is returned. Otherwise, a value of -1 is returned and `t_errno` is set to indicate the error.

Valid States ALL - apart from `T_UNINIT`.

Errors On failure, `t_errno` is set to one of the following:

TBADF	The specified file descriptor does not refer to a transport endpoint.
TBUFOVFLW	The number of bytes allocated for an incoming argument (<i>maxlen</i>) is greater than 0 but not sufficient to store the value of that argument.
TPROTO	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<code>t_errno</code>).
TSYSERR	A system error has occurred during execution of this function.

Tli Compatibility In the TLI interface definition, no counterpart of this routine was defined.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [t_bind\(3NSL\)](#), [attributes\(5\)](#)

Name t_getstate – get the current state

Synopsis #include <xti.h>

```
int t_getstate(int fd);
```

Description This routine is part of the XTI interfaces which evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI routine that has the same name as an XTI routine, the `tiuser.h` header file must be used. Refer to the TLI COMPATIBILITY section for a description of differences between the two interfaces.

The `t_getstate()` function returns the current state of the provider associated with the transport endpoint specified by *fd*.

Return Values State is returned upon successful completion. Otherwise, a value of `-1` is returned and `t_errno` is set to indicate an error. The current state is one of the following:

T_UNBND	Unbound.
T_IDLE	Idle.
T_OUTCON	Outgoing connection pending.
T_INCON	Incoming connection pending.
T_DATAXFER	Data transfer.
T_OUTREL	Outgoing direction orderly release sent.
T_INREL	Incoming direction orderly release received.

If the provider is undergoing a state transition when `t_getstate()` is called, the function will fail.

Errors On failure, `t_errno` is set to one of the following:

TBADF	The specified file descriptor does not refer to a transport endpoint.
TPROTO	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<code>t_errno</code>).
TSTATECHNG	The transport provider is undergoing a transient state change.
TSYSERR	A system error has occurred during execution of this function.

Tli Compatibility The XTI and TLI interface definitions have common names but use different header files. This, and other semantic differences between the two interfaces are described in the subsections below.

Interface Header The XTI interfaces use the header file, `xti.h`. TLI interfaces should *not* use this header. They should use the header:

```
#include <tiuser.h>
```

Error Description Values The `t_errno` value that can be set by the XTI interface and cannot be set by the TLI interface is:

TPROTO

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [t_open\(3NSL\)](#), [attributes\(5\)](#)

Name t_listen – listen for a connection indication

Synopsis #include <xti.h>

```
int t_listen(int fd, struct t_call *call);
```

Description This routine is part of the XTI interfaces which evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI routine that has the same name as an XTI routine, the `tiuser.h` header file must be used. Refer to the TLI COMPATIBILITY section for a description of differences between the two interfaces.

This function listens for a connection indication from a calling transport user. The argument *fd* identifies the local transport endpoint where connection indications arrive, and on return, *call* contains information describing the connection indication. The parameter *call* points to a `t_call` structure which contains the following members:

```
struct netbuf addr;
struct netbuf opt;
struct netbuf udata;
int sequence;
```

In *call*, *addr* returns the protocol address of the calling transport user. This address is in a format usable in future calls to `t_connect(3NSL)`. Note, however that `t_connect(3NSL)` may fail for other reasons, for example `TADDRBUSY`. *opt* returns options associated with the connection indication, *udata* returns any user data sent by the caller on the connection request, and *sequence* is a number that uniquely identifies the returned connection indication. The value of *sequence* enables the user to listen for multiple connection indications before responding to any of them.

Since this function returns values for the *addr*, *opt* and *udata* fields of *call*, the *maxlen* field of each must be set before issuing the `t_listen()` to indicate the maximum size of the buffer for each. If the *maxlen* field of *call*→*addr*, *call*→*opt* or *call*→*udata* is set to zero, no information is returned for this parameter.

By default, `t_listen()` executes in synchronous mode and waits for a connection indication to arrive before returning to the user. However, if `O_NONBLOCK` is set via `t_open(3NSL)` or `fcntl(2)`, `t_listen()` executes asynchronously, reducing to a poll for existing connection indications. If none are available, it returns `-1` and sets `t_errno` to `TNODATA`.

Return Values Upon successful completion, a value of 0 is returned. Otherwise, a value of `-1` is returned and `t_errno` is set to indicate an error.

Valid States `T_IDLE`, `T_INCON`

Errors On failure, `t_errno` is set to one of the following:

TBADF	The specified file descriptor does not refer to a transport endpoint.
TBADQLEN	The argument <i>qlen</i> of the endpoint referenced by <i>fd</i> is zero.
TBUFOVFLW	The number of bytes allocated for an incoming argument (<i>maxlen</i>) is greater than 0 but not sufficient to store the value of that argument. The provider's state, as seen by the user, changes to <code>T_INCON</code> , and the connection indication information to be returned in <i>call</i> is discarded. The value of <i>sequence</i> returned can be used to do a <code>t_snddis(3NSL)</code> .
TLOOK	An asynchronous event has occurred on this transport endpoint and requires immediate attention.
TNODATA	<code>O_NONBLOCK</code> was set, but no connection indications had been queued.
TNOTSUPPORT	This function is not supported by the underlying transport provider.
TOUTSTATE	The communications endpoint referenced by <i>fd</i> is not in one of the states in which a call to this function is valid.
TPROTO	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<code>t_errno</code>).
TQFULL	The maximum number of outstanding connection indications has been reached for the endpoint referenced by <i>fd</i> . Note that a subsequent call to <code>t_listen()</code> may block until another incoming connection indication is available. This can only occur if at least one of the outstanding connection indications becomes no longer outstanding, for example through a call to <code>t_accept(3NSL)</code> .
TSYSERR	A system error has occurred during execution of this function.

Tli Compatibility The XTI and TLI interface definitions have common names but use different header files. This, and other semantic differences between the two interfaces are described in the subsections below.

Interface Header	The XTI interfaces use the header file, <code>xti.h</code> . TLI interfaces should <i>not</i> use this header. They should use the header: <code>#include <tiuser.h></code>
Error Description Values	The <code>t_errno</code> values <code>TPROTO</code> , <code>TBADQLEN</code> , and <code>TQFULL</code> can be set by the XTI interface but not by the TLI interface. A <code>t_errno</code> value that this routine can return under different circumstances than its XTI counterpart is <code>TBUFOVFLW</code> . It can be returned even when the <i>maxlen</i> field of the corresponding buffer has been set to zero.

Option Buffers The format of the options in an opt buffer is dictated by the transport provider. Unlike the XTI interface, the TLI interface does not fix the buffer format.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [fcntl\(2\)](#), [t_accept\(3NSL\)](#), [t_alloc\(3NSL\)](#), [t_bind\(3NSL\)](#), [t_connect\(3NSL\)](#), [t_open\(3NSL\)](#), [t_optmgmt\(3NSL\)](#), [t_rcvconnect\(3NSL\)](#), [t_snddis\(3NSL\)](#), [attributes\(5\)](#)

Warnings Some transport providers do not differentiate between a connection indication and the connection itself. If this is the case, a successful return of `t_listen()` indicates an existing connection.

Name t_look – look at the current event on a transport endpoint

Synopsis #include <xti.h>

```
int t_look(int fd);
```

Description This routine is part of the XTI interfaces which evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI routine that has the same name as an XTI routine, the `tiuser.h` header file must be used. Refer to the TLI COMPATIBILITY section for a description of differences between the two interfaces.

This function returns the current event on the transport endpoint specified by *fd*. This function enables a transport provider to notify a transport user of an asynchronous event when the user is calling functions in synchronous mode. Certain events require immediate notification of the user and are indicated by a specific error, TLOOK, on the current or next function to be executed.

This function also enables a transport user to poll a transport endpoint periodically for asynchronous events.

Return Values Upon success, `t_look()` returns a value that indicates which of the allowable events has occurred, or returns zero if no event exists. One of the following events is returned:

T_LISTEN	Connection indication received.
T_CONNECT	Connect confirmation received.
T_DATA	Normal data received.
T_EXDATA	Expedited data received.
T_DISCONNECT	Disconnection received.
T_UDERR	Datagram error indication.
T_ORDREL	Orderly release indication.
T_GODATA	Flow control restrictions on normal data flow that led to a TFLOW error have been lifted. Normal data may be sent again.
T_GOEXDATA	Flow control restrictions on expedited data flow that led to a TFLOW error have been lifted. Expedited data may be sent again.

On failure, `-1` is returned and `t_errno` is set to indicate the error.

Valid States ALL - apart from T_UNINIT.

Errors On failure, `t_errno` is set to one of the following:

- TBADF** The specified file descriptor does not refer to a transport endpoint.
- TPROTO** This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (`t_errno`).
- TSYSERR** A system error has occurred during execution of this function.

Tli Compatibility The XTI and TLI interface definitions have common names but use different header files. This, and other semantic differences between the two interfaces are described in the subsections below.

Interface Header The XTI interfaces use the header file, `xti.h`. TLI interfaces should *not* use this header. They should use the header:

```
#include <tiuser.h>
```

Return Values The return values that are defined by the XTI interface and cannot be returned by the TLI interface are:

```
T_GODATA
T_GOEXDATA
```

Error Description Values The `t_errno` value that can be set by the XTI interface and cannot be set by the TLI interface is:

```
TPROTO
```

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [t_open\(3NSL\)](#), [t_snd\(3NSL\)](#), [t_sndudata\(3NSL\)](#), [attributes\(5\)](#)

Name t_open – establish a transport endpoint

Synopsis `#include <xti.h>`
`#include <fcntl.h>`

```
int t_open(const char *name, int oflag, struct t_info *info);
```

Description This routine is part of the XTI interfaces which evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI routine that has the same name as an XTI routine, the `t_iuser.h` header file must be used. Refer to the TLI COMPATIBILITY section for a description of differences between the two interfaces.

The `t_open()` function must be called as the first step in the initialization of a transport endpoint. This function establishes a transport endpoint by supplying a transport provider identifier that indicates a particular transport provider, that is, transport protocol, and returning a file descriptor that identifies that endpoint.

The argument *name* points to a transport provider identifier and *oflag* identifies any open flags, as in [open\(2\)](#). The argument *oflag* is constructed from `O_RDWR` optionally bitwise inclusive-OR'ed with `O_NONBLOCK`. These flags are defined by the header `<fcntl.h>`. The file descriptor returned by `t_open()` will be used by all subsequent functions to identify the particular local transport endpoint.

This function also returns various default characteristics of the underlying transport protocol by setting fields in the `t_info` structure. This argument points to a `t_info` which contains the following members:

```
t_scalar_t addr;          /* max size of the transport protocol address */
t_scalar_t options;       /* max number of bytes of */
                           /* protocol-specific options */
t_scalar_t tsdu;          /* max size of a transport service data */
                           /* unit (TSDU) */
t_scalar_t etsdu;         /* max size of an expedited transport */
                           /* service data unit (ETSDU) */
t_scalar_t connect;       /* max amount of data allowed on */
                           /* connection establishment functions */
t_scalar_t discon;        /* max amount of data allowed on */
                           /* t_snddis() and t_rcvdis() functions */
t_scalar_t servtype;      /* service type supported by the */
                           /* transport provider */
t_scalar_t flags;         /* other info about the transport provider */
```

The values of the fields have the following meanings:

<i>addr</i>	A value greater than zero (T_NULL) indicates the maximum size of a transport protocol address and a value of -2 (T_INVALID) specifies that the transport provider does not provide user access to transport protocol addresses.
<i>options</i>	A value greater than zero (T_NULL) indicates the maximum number of bytes of protocol-specific options supported by the provider, and a value of -2 (T_INVALID) specifies that the transport provider does not support user-settable options.
<i>tsdu</i>	A value greater than zero (T_NULL) specifies the maximum size of a transport service data unit (TSDU); a value of zero (T_NULL) specifies that the transport provider does not support the concept of TSDU, although it does support the sending of a data stream with no logical boundaries preserved across a connection; a value of -1 (T_INFINITE) specifies that there is no limit to the size of a TSDU; and a value of -2 (T_INVALID) specifies that the transfer of normal data is not supported by the transport provider.
<i>etsdu</i>	A value greater than zero (T_NULL) specifies the maximum size of an expedited transport service data unit (ETSDU); a value of zero (T_NULL) specifies that the transport provider does not support the concept of ETSDU, although it does support the sending of an expedited data stream with no logical boundaries preserved across a connection; a value of -1 (T_INFINITE) specifies that there is no limit on the size of an ETSDU; and a value of -2 (T_INVALID) specifies that the transfer of expedited data is not supported by the transport provider. Note that the semantics of expedited data may be quite different for different transport providers.
<i>connect</i>	A value greater than zero (T_NULL) specifies the maximum amount of data that may be associated with connection establishment functions, and a value of -2 (T_INVALID) specifies that the transport provider does not allow data to be sent with connection establishment functions.
<i>discon</i>	If the T_ORDRELDATA bit in flags is clear, a value greater than zero (T_NULL) specifies the maximum amount of data that may be associated with the t_snddis(3NSL) and t_rcvdis(3NSL) functions, and a value of -2 (T_INVALID) specifies that the transport provider does not allow data to be sent with the abortive release functions. If the T_ORDRELDATA bit is set in flags, a value greater than zero (T_NULL) specifies the maximum number of octets that may be associated with the t_sndreldata() , t_rcvreldata() , t_snddis(3NSL) and t_rcvdis(3NSL) functions.
<i>servtype</i>	This field specifies the service type supported by the transport provider, as described below.
<i>flags</i>	This is a bit field used to specify other information about the communications provider. If the T_ORDRELDATA bit is set, the communications provider supports user data to be sent with an orderly release. If the T_SENDZERO bit is set in flags,

this indicates the underlying transport provider supports the sending of zero-length TSDUs.

If a transport user is concerned with protocol independence, the above sizes may be accessed to determine how large the buffers must be to hold each piece of information. Alternatively, the `t_alloc(3NSL)` function may be used to allocate these buffers. An error will result if a transport user exceeds the allowed data size on any function.

The *servtype* field of *info* specifies one of the following values on return:

T_COTS	The transport provider supports a connection-mode service but does not support the optional orderly release facility.
T_COTS_ORD	The transport provider supports a connection-mode service with the optional orderly release facility.
T_CLTS	The transport provider supports a connectionless-mode service. For this service type, <code>t_open()</code> will return <code>-2 (T_INVALID)</code> for <i>etsdu</i> , <i>connect</i> and <i>discon</i> .

A single transport endpoint may support only one of the above services at one time.

If *info* is set to a null pointer by the transport user, no protocol information is returned by `t_open()`.

Return Values A valid file descriptor is returned upon successful completion. Otherwise, a value of `-1` is returned and `t_errno` is set to indicate an error.

Valid States T_UNINIT.

Errors On failure, `t_errno` is set to the following:

TBADFLAG	An invalid flag is specified.
TBADNAME	Invalid transport provider name.
TPROTO	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<code>t_errno</code>).
TSYSERR	A system error has occurred during execution of this function.

Tli Compatibility The XTI and TLI interface definitions have common names but use different header files. This and other semantic differences between the two interfaces are described in the subsections below.

Interface Header The XTI interfaces use the `xti.h` TLI interfaces should *not* use this header. They should use the header:

```
#include <tiuser.h>
```

Error Description Values The `t_errno` values `TPROTO` and `TBADNAME` can be set by the XTI interface but cannot be set by the TLI interface.

Notes For TLI, the `t_info` structure referenced by *info* lacks the following structure member:

```
t_scalar_t flags; /* other info about the transport provider */
```

This member was added to `struct t_info` in the XTI interfaces.

When a value of `-1` is observed as the return value in various `t_info` structure members, it signifies that the transport provider can handle an infinite length buffer for a corresponding attribute, such as address data, option data, TSDU (octet size), ETSDU (octet size), connection data, and disconnection data. The corresponding structure members are `addr`, `options`, `tsdu`, `estdu`, `connect`, and `discon`, respectively.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [open\(2\)](#), [attributes\(5\)](#)

Name t_optmgmt – manage options for a transport endpoint

Synopsis #include <xti.h>

```
int t_optmgmt(int fd, const struct t_optmgmt *req, struct t_optmgmt *ret);
```

Description This routine is part of the XTI interfaces which evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI routine that has the same name as an XTI routine, the `tiuser.h` header file must be used. Refer to the TLI COMPATIBILITY section for a description of differences between the two interfaces.

The `t_optmgmt()` function enables a transport user to retrieve, verify or negotiate protocol options with the transport provider. The argument *fd* identifies a transport endpoint.

The *req* and *ret* arguments point to a `t_optmgmt` structure containing the following members:

```
struct netbuf opt;  
t_scalar_t    flags;
```

The *opt* field identifies protocol options and the *flags* field is used to specify the action to take with those options.

The options are represented by a `netbuf` structure in a manner similar to the address in [t_bind\(3NSL\)](#). The argument *req* is used to request a specific action of the provider and to send options to the provider. The argument *len* specifies the number of bytes in the options, *buf* points to the options buffer, and *maxlen* has no meaning for the *req* argument. The transport provider may return options and flag values to the user through *ret*. For *ret*, *maxlen* specifies the maximum size of the options buffer and *buf* points to the buffer where the options are to be placed. If *maxlen* in *ret* is set to zero, no options values are returned. On return, *len* specifies the number of bytes of options returned. The value in *maxlen* has no meaning for the *req* argument, but must be set in the *ret* argument to specify the maximum number of bytes the options buffer can hold.

Each option in the options buffer is of the form `struct t_opthdr` possibly followed by an option value.

The *level* field of `struct t_opthdr` identifies the XTI level or a protocol of the transport provider. The *name* field identifies the option within the level, and *len* contains its total length; that is, the length of the option header `t_opthdr` plus the length of the option value. If `t_optmgmt()` is called with the action `T_NEGOTIATE` set, the *status* field of the returned options contains information about the success or failure of a negotiation.

Several options can be concatenated. The option user has, however to ensure that each options header and value part starts at a boundary appropriate for the architecture-specific alignment rules. The macros `T_OPT_FIRSTHDR(nbp)`, `T_OPT_NEXTHDR(nbp,tohp)`, `T_OPT_DATA(tohp)` are provided for that purpose.

<code>T_OPT_DATA(nhp)</code>	If argument is a pointer to a <code>t_opthdr</code> structure, this macro returns an unsigned character pointer to the data associated with the <code>t_opthdr</code> .
<code>T_OPT_NEXTHDR(nbp, tohp)</code>	If the first argument is a pointer to a netbuf structure associated with an option buffer and second argument is a pointer to a <code>t_opthdr</code> structure within that option buffer, this macro returns a pointer to the next <code>t_opthdr</code> structure or a null pointer if this <code>t_opthdr</code> is the last <code>t_opthdr</code> in the option buffer.
<code>T_OPT_FIRSTHDR(tohp)</code>	<p>If the argument is a pointer to a netbuf structure associated with an option buffer, this macro returns the pointer to the first <code>t_opthdr</code> structure in the associated option buffer, or a null pointer if there is no option buffer associated with this netbuf or if it is not possible or the associated option buffer is too small to accommodate even the first aligned option header.</p> <p><code>T_OPT_FIRSTHDR</code> is useful for finding an appropriately aligned start of the option buffer. <code>T_OPT_NEXTHDR</code> is useful for moving to the start of the next appropriately aligned option in the option buffer. Note that <code>OPT_NEXTHDR</code> is also available for backward compatibility requirements. <code>T_OPT_DATA</code> is useful for finding the start of the data part in the option buffer where the contents of its values start on an appropriately aligned boundary.</p> <p>If the transport user specifies several options on input, all options must address the same level.</p> <p>If any option in the options buffer does not indicate the same level as the first option, or the level specified is unsupported, then the <code>t_optmgmt()</code> request will fail with <code>TBADOPT</code>. If the error is detected, some options have possibly been successfully negotiated. The transport user can check the current status by calling <code>t_optmgmt()</code> with the <code>T_CURRENT</code> flag set.</p> <p>The <i>flags</i> field of <i>req</i> must specify one of the following actions:</p>
<code>T_NEGOTIATE</code>	This action enables the transport user to negotiate option values.

The user specifies the options of interest and their values in the buffer specified by *req*→*opt.buf* and *req*→*opt.len*. The negotiated option values are returned in the buffer pointed to by *ret*→*opt.buf*. The *status* field of each returned option is set to indicate the result of the negotiation. The value is `T_SUCCESS` if the proposed value was negotiated, `T_PARTSUCCESS` if a degraded value was negotiated, `T_FAILURE` if the negotiation failed (according to the negotiation rules), `T_NOTSUPPORT` if the transport provider does not support this option or illegally requests negotiation of a privileged option, and `T_READONLY` if modification of a read-only option was requested. If the status is `T_SUCCESS`, `T_FAILURE`, `T_NOTSUPPORT` or `T_READONLY`, the returned option value is the same as the one requested on input.

The overall result of the negotiation is returned in *ret*→*flags*.

This field contains the worst single result, whereby the rating is done according to the order `T_NOTSUPPORT`, `T_READONLY`, `T_FAILURE`, `T_PARTSUCCESS`, `T_SUCCESS`. The value `T_NOTSUPPORT` is the worst result and `T_SUCCESS` is the best.

For each level, the option `T_ALLOPT` can be requested on input. No value is given with this option; only the *t_opthdr* part is specified. This input requests to negotiate all supported options of this level to their default values. The result is returned option by option in *ret*→*opt.buf*. Note that depending on the state of the transport endpoint, not all requests to negotiate the default value may be successful.

T_CHECK

This action enables the user to verify whether the options specified in *req* are supported by the transport provider. If an option is specified with no option value (it consists only of a *t_opthdr* structure), the option is returned with its *status* field set to `T_SUCCESS` if it is supported, `T_NOTSUPPORT` if it is not or needs additional user privileges, and `T_READONLY` if it is read-only (in the current XTI state). No option value is returned.

If an option is specified with an option value, the *status* field of the returned option has the same value, as if the user had tried to negotiate this value with `T_NEGOTIATE`. If the status is `T_SUCCESS`, `T_FAILURE`, `T_NOTSUPPORT` or `T_READONLY`, the returned option value is the same as the one requested on input.

The overall result of the option checks is returned in *ret*→*flags*. This field contains the worst single result of the option checks, whereby the rating is the same as for T_NEGOTIATE.

Note that no negotiation takes place. All currently effective option values remain unchanged.

T_DEFAULT

This action enables the transport user to retrieve the default option values. The user specifies the options of interest in *req*→*opt.buf*. The option values are irrelevant and will be ignored; it is sufficient to specify the t_opthdr part of an option only. The default values are then returned in *ret*→*opt.buf*.

The *status* field returned is T_NOTSUPPORT if the protocol level does not support this option or the transport user illegally requested a privileged option, T_READONLY if the option is read-only, and set to T_SUCCESS in all other cases. The overall result of the request is returned in *ret*→*flags*. This field contains the worst single result, whereby the rating is the same as for T_NEGOTIATE.

For each level, the option T_ALLOPT can be requested on input. All supported options of this level with their default values are then returned. In this case, *ret*→*opt.maxlen* must be given at least the value *info*→*options* before the call. See [t_getinfo\(3NSL\)](#) and [t_open\(3NSL\)](#).

T_CURRENT

This action enables the transport user to retrieve the currently effective option values. The user specifies the options of interest in *req*→*opt.buf*. The option values are irrelevant and will be ignored; it is sufficient to specify the t_opthdr part of an option only. The currently effective values are then returned in *req*→*opt.buf*.

The *status* field returned is T_NOTSUPPORT if the protocol level does not support this option or the transport user illegally requested a privileged option, T_READONLY if the option is read-only, and set to T_SUCCESS in all other cases. The overall result of the request is returned in *ret*→*flags*. This field contains the worst single result, whereby the rating is the same as for T_NEGOTIATE.

For each level, the option T_ALLOPT can be requested on input. All supported options of this level with their currently effective values are then returned.

The option T_ALLOPT can only be used with t_optmgtmt () and the actions T_NEGOTIATE , T_DEFAULT and T_CURRENT . It can be used with any supported level and addresses all supported options of this level. The option has no value; it consists of a t_opthdr only. Since in a t_optmgtmt () call only options of one level may be addressed, this option should not be requested together with other options. The function returns as soon as this option has been processed.

Options are independently processed in the order they appear in the input option buffer. If an option is multiply input, it depends on the implementation whether it is multiply output or whether it is returned only once.

Transport providers may not be able to provide an interface capable of supporting T_NEGOTIATE and/or T_CHECK functionalities. When this is the case, the error TNOTSUPPORT is returned.

The function t_optmgtmt () may block under various circumstances and depending on the implementation. The function will block, for instance, if the protocol addressed by the call resides on a separate controller. It may also block due to flow control constraints; that is, if data sent previously across this transport endpoint has not yet been fully processed. If the function is interrupted by a signal, the option negotiations that have been done so far may remain valid. The behavior of the function is not changed if O_NONBLOCK is set.

Return Values Upon successful completion, a value of 0 is returned. Otherwise, a value of -1 is returned and t_errno is set to indicate an error.

Valid States ALL - apart from T_UNINIT.

Errors On failure, t_errno is set to one of the following:

- TBADF The specified file descriptor does not refer to a transport endpoint.
- TBADFLAG An invalid flag was specified.
- TBADOPT The specified options were in an incorrect format or contained illegal information.

	TBUFOVFLW	The number of bytes allowed for an incoming argument (<i>maxlen</i>) is greater than 0 but not sufficient to store the value of that argument. The information to be returned in <i>ret</i> will be discarded.
	TNOTSUPPORT	This action is not supported by the transport provider.
	TOUTSTATE	The communications endpoint referenced by <i>fd</i> is not in one of the states in which a call to this function is valid.
	TPROTO	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<i>t_errno</i>).
	TSYSERR	A system error has occurred during execution of this function.
Tli Compatibility	The XTI and TLI interface definitions have common names but use different header files. This, and other semantic differences between the two interfaces are described in the subsections below.	
Interface Header	The XTI interfaces use the header file, <code>xti.h</code> . TLI interfaces should <i>not</i> use this header. They should use the header: <code>#include <tiuser.h></code>	
Error Description Values	The <i>t_errno</i> value TPROTO can be set by the XTI interface but not by the TLI interface. The <i>t_errno</i> values that this routine can return under different circumstances than its XTI counterpart are TACCES and TBUFOVFLW.	
	TACCES	can be returned to indicate that the user does not have permission to negotiate the specified options.
	TBUFOVFLW	can be returned even when the <i>maxlen</i> field of the corresponding buffer has been set to zero.
Option Buffers	The format of the options in an <i>opt</i> buffer is dictated by the transport provider. Unlike the XTI interface, the TLI interface does not fix the buffer format. The macros <code>T_OPT_DATA</code> , <code>T_OPT_NEXTHDR</code> , and <code>T_OPT_FIRSTHDR</code> described for XTI are not available for use by TLI interfaces.	
Actions	The semantic meaning of various action values for the <i>flags</i> field of <i>req</i> differs between the TLI and XTI interfaces. TLI interface users should heed the following descriptions of the actions:	
	T_NEGOTIATE	This action enables the user to negotiate the values of the options specified in <i>req</i> with the transport provider. The provider will evaluate the requested options and negotiate the values, returning the negotiated values through <i>ret</i> .

- T_CHECK

This action enables the user to verify whether the options specified in *req* are supported by the transport provider. On return, the *flags* field of *ret* will have either `T_SUCCESS` or `T_FAILURE` set to indicate to the user whether the options are supported. These flags are only meaningful for the `T_CHECK` request.
- T_DEFAULT

This action enables a user to retrieve the default options supported by the transport provider into the *opt* field of *ret*. In *req*, the *len* field of *opt* must be zero and the *buf* field may be `NULL`.

Connectionless Mode If issued as part of the connectionless mode service, `t_optmgmt ()` may block due to flow control constraints. The function will not complete until the transport provider has processed all previously sent data units.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [close\(2\)](#), [poll\(2\)](#), [select\(3C\)](#), [t_accept\(3NSL\)](#), [t_alloc\(3NSL\)](#), [t_bind\(3NSL\)](#), [t_close\(3NSL\)](#), [t_connect\(3NSL\)](#), [t_getinfo\(3NSL\)](#), [t_listen\(3NSL\)](#), [t_open\(3NSL\)](#), [t_rcv\(3NSL\)](#), [t_rcvconnect\(3NSL\)](#), [t_rcvdata\(3NSL\)](#), [t_snddis\(3NSL\)](#), [attributes\(5\)](#)

Name t_rcv – receive data or expedited data sent over a connection

Synopsis #include <xti.h>

```
int t_rcv(int fd, void *buf, unsigned int nbytes, int *flags);
```

Description This function is part of the XTI interfaces which evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI function that has the same name as an XTI function, the `tiuser.h` header file must be used. Refer to the TLI COMPATIBILITY section for a description of differences between the two interfaces.

This function receives either normal or expedited data. The argument *fd* identifies the local transport endpoint through which data will arrive, *buf* points to a receive buffer where user data will be placed, and *nbytes* specifies the size of the receive buffer. The argument *flags* may be set on return from `t_rcv()` and specifies optional flags as described below.

By default, `t_rcv()` operates in synchronous mode and will wait for data to arrive if none is currently available. However, if `O_NONBLOCK` is set by means of `t_open(3NSL)` or `fcntl(2)`, `t_rcv()` will execute in asynchronous mode and will fail if no data is available. See `TNODATA` below.

On return from the call, if `T_MORE` is set in *flags*, this indicates that there is more data, and the current transport service data unit (TSDU) or expedited transport service data unit (ETSDU) must be received in multiple `t_rcv()` calls. In the asynchronous mode, or under unusual conditions (for example, the arrival of a signal or `T_EXDATA` event), the `T_MORE` flag may be set on return from the `t_rcv()` call even when the number of bytes received is less than the size of the receive buffer specified. Each `t_rcv()` with the `T_MORE` flag set indicates that another `t_rcv()` must follow to get more data for the current TSDU. The end of the TSDU is identified by the return of a `t_rcv()` call with the `T_MORE` flag not set. If the transport provider does not support the concept of a TSDU as indicated in the *info* argument on return from `t_open(3NSL)` or `t_getinfo(3NSL)`, the `T_MORE` flag is not meaningful and should be ignored. If *nbytes* is greater than zero on the call to `t_rcv()`, `t_rcv()` will return 0 only if the end of a TSDU is being returned to the user.

On return, the data is expedited if `T_EXPEDITED` is set in *flags*. If `T_MORE` is also set, it indicates that the number of expedited bytes exceeded *nbytes*, a signal has interrupted the call, or that an entire ETSDU was not available (only for transport protocols that support fragmentation of ETSDUs). The rest of the ETSDU will be returned by subsequent calls to `t_rcv()` which will return with `T_EXPEDITED` set in *flags*. The end of the ETSDU is identified by the return of a `t_rcv()` call with `T_EXPEDITED` set and `T_MORE` cleared. If the entire ETSDU is not available it is possible for normal data fragments to be returned between the initial and final fragments of an ETSDU.

If a signal arrives, `t_rcv()` returns, giving the user any data currently available. If no data is available, `t_rcv()` returns -1, sets `t_errno` to `TSYSERR` and `errno` to `EINTR`. If some data is available, `t_rcv()` returns the number of bytes received and `T_MORE` is set in *flags*.

In synchronous mode, the only way for the user to be notified of the arrival of normal or expedited data is to issue this function or check for the T_DATA or T_EXDATA events using the [t_look\(3NSL\)](#) function. Additionally, the process can arrange to be notified by means of the EM interface.

Return Values On successful completion, `t_rcv()` returns the number of bytes received. Otherwise, it returns `-1` on failure and `t_errno` is set to indicate the error.

Valid States T_DATAXFER, T_OUTREL.

Errors On failure, `t_errno` is set to one of the following:

TBADF	The specified file descriptor does not refer to a transport endpoint.
TLOOK	An asynchronous event has occurred on this transport endpoint and requires immediate attention.
TNODATA	O_NONBLOCK was set, but no data is currently available from the transport provider.
TNOTSUPPORT	This function is not supported by the underlying transport provider.
TOUTSTATE	The communications endpoint referenced by <i>fd</i> is not in one of the states in which a call to this function is valid.
TPROTO	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<code>t_errno</code>).
TSYSERR	A system error has occurred during execution of this function.

Tli Compatibility The XTI and TLI interface definitions have common names but use different header files. This, and other semantic differences between the two interfaces are described in the subsections below.

Interface Header The XTI interfaces use the header file, `xti.h`. TLI interfaces should *not* use this header. They should use the header:

```
#include <tiuser.h>
```

Error Description Values The `t_errno` value that can be set by the XTI interface and cannot be set by the TLI interface is:

TPROTO

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
Interface Stability	Committed
MT-Level	Safe
Standard	See standards(5) .

See Also [fcntl\(2\)](#), [t_getinfo\(3NSL\)](#), [t_look\(3NSL\)](#), [t_open\(3NSL\)](#), [t_snd\(3NSL\)](#), [attributes\(5\)](#), [standards\(5\)](#)

Name t_rcvconnect – receive the confirmation from a connection request

Synopsis #include <xti.h>

```
int t_rcvconnect(int fd, struct t_call *call);
```

Description This routine is part of the XTI interfaces which evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI routine that has the same name as an XTI routine, the `tiuser.h` header file must be used. Refer to the TLI COMPATIBILITY section for a description of differences between the two interfaces.

This function enables a calling transport user to determine the status of a previously sent connection request and is used in conjunction with `t_connect(3NSL)` to establish a connection in asynchronous mode, and to complete a synchronous `t_connect(3NSL)` call that was interrupted by a signal. The connection will be established on successful completion of this function.

The argument *fd* identifies the local transport endpoint where communication will be established, and *call* contains information associated with the newly established connection. The argument *call* points to a `t_call` structure which contains the following members:

```
struct netbuf addr;  
struct netbuf opt;  
struct netbuf udata;  
int sequence;
```

In *call*, *addr* returns the protocol address associated with the responding transport endpoint, *opt* presents any options associated with the connection, *udata* points to optional user data that may be returned by the destination transport user during connection establishment, and *sequence* has no meaning for this function.

The *maxlen* field of each argument must be set before issuing this function to indicate the maximum size of the buffer for each. However, *maxlen* can be set to zero, in which case no information to this specific argument is given to the user on the return from `t_rcvconnect()`. If *call* is set to `NULL`, no information at all is returned. By default, `t_rcvconnect()` executes in synchronous mode and waits for the connection to be established before returning. On return, the *addr*, *opt* and *udata* fields reflect values associated with the connection.

If `O_NONBLOCK` is set by means of `t_open(3NSL)` or `fcntl(2)`, `t_rcvconnect()` executes in asynchronous mode, and reduces to a poll for existing connection confirmations. If none are available, `t_rcvconnect()` fails and returns immediately without waiting for the connection to be established. See `TNODATA` below. In this case, `t_rcvconnect()` must be called again to complete the connection establishment phase and retrieve the information returned in *call*.

Return Values Upon successful completion, a value of 0 is returned. Otherwise, a value of -1 is returned and `t_errno` is set to indicate an error.

Valid States T_OUTCON.

Errors On failure, `t_errno` is set to one of the following:

TBADF	The specified file descriptor does not refer to a transport endpoint.
TBUFOVFLW	The number of bytes allocated for an incoming argument (<i>maxlen</i>) is greater than 0 but not sufficient to store the value of that argument, and the connection information to be returned in <i>call</i> will be discarded. The provider's state, as seen by the user, will be changed to T_DATAXFER.
TLOOK	An asynchronous event has occurred on this transport connection and requires immediate attention.
TNODATA	O_NONBLOCK was set, but a connection confirmation has not yet arrived.
TNOTSUPPORT	This function is not supported by the underlying transport provider.
TOUTSTATE	The communications endpoint referenced by <i>fd</i> is not in one of the states in which a call to this function is valid.
TPROTO	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<code>t_errno</code>).
TSYSERR	A system error has occurred during execution of this function.

Tli Compatibility The XTI and TLI interface definitions have common names but use different header files. This, and other semantic differences between the two interfaces are described in the subsections below.

Interface Header The XTI interfaces use the header file, `xti.h`. TLI interfaces should *not* use this header. They should use the header:

```
#include<tiuser.h>
```

Error Description Values The `t_errno` value TPROTO can be set by the XTI interface but not by the TLI interface. A `t_errno` value that this routine can return under different circumstances than its XTI counterpart is TBUFOVFLW. It can be returned even when the `maxlen` field of the corresponding buffer has been set to zero.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [fcntl\(2\)](#), [t_accept\(3NSL\)](#), [t_alloc\(3NSL\)](#), [t_bind\(3NSL\)](#), [t_connect\(3NSL\)](#), [t_listen\(3NSL\)](#), [t_open\(3NSL\)](#), [t_optmgmt\(3NSL\)](#), [attributes\(5\)](#)

Name t_rcvdis – retrieve information from disconnection

Synopsis #include <xti.h>

```
int t_rcvdis(int fd, struct t_discon *discon);
```

Description This routine is part of the XTI interfaces which evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI routine that has the same name as an XTI routine, the `tuser.h` header file must be used. Refer to the TLI COMPATIBILITY section for a description of differences between the two interfaces.

This function is used to identify the cause of a disconnection and to retrieve any user data sent with the disconnection. The argument *fd* identifies the local transport endpoint where the connection existed, and *discon* points to a `t_discon` structure containing the following members:

```
struct netbuf udata;
int reason;
int sequence;
```

The field *reason* specifies the reason for the disconnection through a protocol-dependent reason code, *udata* identifies any user data that was sent with the disconnection, and *sequence* may identify an outstanding connection indication with which the disconnection is associated. The field *sequence* is only meaningful when `t_rcvdis()` is issued by a passive transport user who has executed one or more `t_listen(3NSL)` functions and is processing the resulting connection indications. If a disconnection indication occurs, *sequence* can be used to identify which of the outstanding connection indications is associated with the disconnection.

The *maxlen* field of *udata* may be set to zero, if the user does not care about incoming data. If, in addition, the user does not need to know the value of *reason* or *sequence*, *discon* may be set to NULL and any user data associated with the disconnection indication shall be discarded. However, if a user has retrieved more than one outstanding connection indication by means of `t_listen(3NSL)`, and *discon* is a null pointer, the user will be unable to identify with which connection indication the disconnection is associated.

Return Values Upon successful completion, a value of 0 is returned. Otherwise, a value of -1 is returned and `t_errno` is set to indicate an error.

Valid States T_DATAXFER, T_OUTCON, T_OUTREL, T_INREL, T_INCON(`ocnt` > 0).

Errors On failure, `t_errno` is set to one of the following:

TBADF	The specified file descriptor does not refer to a transport endpoint.
TBUFOVFLW	The number of bytes allocated for incoming data (<i>maxlen</i>) is greater than 0 but not sufficient to store the data. If <i>fd</i> is a passive endpoint with <i>ocnt</i> > 1, it remains in state T_INCON; otherwise, the endpoint state is set to T_IDLE.

TNODIS	No disconnection indication currently exists on the specified transport endpoint.
TNOTSUPPORT	This function is not supported by the underlying transport provider.
TOUTSTATE	The communications endpoint referenced by <i>fd</i> is not in one of the states in which a call to this function is valid.
TPROTO	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<code>t_errno</code>).
TSYSERR	A system error has occurred during execution of this function.

Tli Compatibility The XTI and TLI interface definitions have common names but use different header files. This, and other semantic differences between the two interfaces are described in the subsections below.

Interface Header The XTI interfaces use the header file, `xti.h`. TLI interfaces should *not* use this header. They should use the header:

```
#include <tiuser.h>
```

Error Description Values The `t_errno` values `TPROTO` and `TOUTSTATE` can be set by the XTI interface but not by the TLI interface.

A failure return, and a `t_errno` value that this routine can set under different circumstances than its XTI counterpart is `TBUFOVFLW`. It can be returned even when the `maxlen` field of the corresponding buffer has been set to zero.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [t_alloc\(3NSL\)](#), [t_connect\(3NSL\)](#), [t_listen\(3NSL\)](#), [t_open\(3NSL\)](#), [t_snddis\(3NSL\)](#), [attributes\(5\)](#)

Name t_rcvrel – acknowledge receipt of an orderly release indication

Synopsis #include <xti.h>

```
int t_rcvrel(int fd);
```

Description This routine is part of the XTI interfaces which evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI routine that has the same name as an XTI routine, the `tiuser.h` header file must be used. Refer to the TLI COMPATIBILITY section for a description of differences between the two interfaces.

This function is used to receive an orderly release indication for the incoming direction of data transfer. The argument *fd* identifies the local transport endpoint where the connection exists. After receipt of this indication, the user may not attempt to receive more data by means of `t_rcv(3NSL)` or `t_rcvv()`. Such an attempt will fail with *t_error* set to TOUTSTATE. However, the user may continue to send data over the connection if `t_sndrel(3NSL)` has not been called by the user. This function is an optional service of the transport provider, and is only supported if the transport provider returned service type T_COTS_ORD on `t_open(3NSL)` or `t_getinfo(3NSL)`. Any user data that may be associated with the orderly release indication is discarded when `t_rcvrel()` is called.

Return Values Upon successful completion, a value of 0 is returned. Otherwise, a value of -1 is returned and *t_errno* is set to indicate an error.

Valid States T_DATAXFER, T_OUTREL.

Errors On failure, *t_errno* is set to one of the following:

TBADF	The specified file descriptor does not refer to a transport endpoint.
TLOOK	An asynchronous event has occurred on this transport endpoint and requires immediate attention.
TNOREL	No orderly release indication currently exists on the specified transport endpoint.
TNOTSUPPORT	This function is not supported by the underlying transport provider.
TOUTSTATE	The communications endpoint referenced by <i>fd</i> is not in one of the states in which a call to this function is valid.
TPROTO	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<i>t_errno</i>).
TSYSERR	A system error has occurred during execution of this function.

Tli Compatibility The XTI and TLI interface definitions have common names but use different header files. This, and other semantic differences between the two interfaces are described in the subsections below.

Interface Header The XTI interfaces use the header file, `xti.h`. TLI interfaces should *not* use this header. They should use the header:

```
#include<tiuser.h>
```

Error Description Values The `t_errno` values that can be set by the XTI interface and cannot be set by the TLI interface are:

```
TPROTO
TOUTSTATE
```

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [t_getinfo\(3NSL\)](#), [t_open\(3NSL\)](#), [t_sndrel\(3NSL\)](#), [attributes\(5\)](#)

Name t_rcvreldata – receive an orderly release indication or confirmation containing user data

Synopsis #include <xti.h>

```
int t_rcvreldata(int fd, struct t_discon *discon);
```

Description This function is used to receive an orderly release indication for the incoming direction of data transfer and to retrieve any user data sent with the release. The argument *fd* identifies the local transport endpoint where the connection exists, and *discon* points to a `t_discon` structure containing the following members:

```
struct netbuf udata;
int reason;
int sequence;
```

After receipt of this indication, the user may not attempt to receive more data by means of `t_rcv(3NSL)` or `t_rcvv(3NSL)`. Such an attempt will fail with *t_error* set to TOUTSTATE. However, the user may continue to send data over the connection if `t_sndrel(3NSL)` or `t_sndreldata(3N)` has not been called by the user.

The field *reason* specifies the reason for the disconnection through a protocol-dependent *reason code*, and *udata* identifies any user data that was sent with the disconnection; the field *sequence* is not used.

If a user does not care if there is incoming data and does not need to know the value of *reason*, *discon* may be a null pointer, and any user data associated with the disconnection will be discarded.

If *discon*→*udata.maxlen* is greater than zero and less than the length of the value, `t_rcvreldata()` fails with *t_errno* set to TBUFOVFLW.

This function is an optional service of the transport provider, only supported by providers of service type `T_COTS_ORD`. The flag `T_ORDRELDATA` in the *info*→*flag* field returned by `t_open(3NSL)` or `t_getinfo(3NSL)` indicates that the provider supports orderly release user data; when the flag is not set, this function behaves like `t_rcvre1(3NSL)` and no user data is returned.

This function may not be available on all systems.

Return Values Upon successful completion, a value of 0 is returned. Otherwise, a value of -1 is returned and *t_errno* is set to indicate an error.

Valid States `T_DATAXFER`, `T_OUTREL`.

Errors On failure, `t_errno` is set to one of the following:

TBADF	The specified file descriptor does not refer to a transport endpoint.
TBUFOVFLW	The number of bytes allocated for incoming data (<code>maxlen</code>) is greater than 0 but not sufficient to store the data, and the disconnection information to be returned in <i>discon</i> will be discarded. The provider state, as seen by the user, will be changed as if the data was successfully retrieved.
TLOOK	An asynchronous event has occurred on this transport endpoint and requires immediate attention.
TNOREL	No orderly release indication currently exists on the specified transport endpoint.
TNOTSUPPORT	Orderly release is not supported by the underlying transport provider.
TOUTSTATE	The communications endpoint referenced by <i>fd</i> is not in one of the states in which a call to this function is valid.
TPROTO	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<code>t_errno</code>).
TSYSERR	A system error has occurred during execution of this function.

Tli Compatibility In the TLI interface definition, no counterpart of this routine was defined.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [t_getinfo\(3NSL\)](#), [t_open\(3NSL\)](#), [t_sndreldata\(3NSL\)](#), [t_rcvrel\(3NSL\)](#), [t_sndrel\(3NSL\)](#), [attributes\(5\)](#)

Notes The interfaces [t_sndreldata\(3NSL\)](#) and `t_rcvreldata()` are only for use with a specific transport called “minimal OSI,” which is not available on the Solaris platform. These interfaces are not available for use in conjunction with Internet Transports (TCP or UDP).

Name t_rcvudata – receive a data unit

Synopsis #include <xti.h>

```
int t_rcvudata(int fd, struct t_unitdata *unitdata, int *flags);
```

Description This routine is part of the XTI interfaces which evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI routine that has the same name as an XTI routine, the `tiuser.h` header file must be used. Refer to the TLI COMPATIBILITY section for a description of differences between the two interfaces.

This function is used in connectionless-mode to receive a data unit from another transport user. The argument *fd* identifies the local transport endpoint through which data will be received, *unitdata* holds information associated with the received data unit, and *flags* is set on return to indicate that the complete data unit was not received. The argument *unitdata* points to a `t_unitdata` structure containing the following members:

```
struct netbuf addr;
struct netbuf opt;
struct netbuf udata;
```

The *maxlen* field of *addr*, *opt* and *udata* must be set before calling this function to indicate the maximum size of the buffer for each. If the *maxlen* field of *addr* or *opt* is set to zero, no information is returned in the *buf* field of this parameter.

On return from this call, *addr* specifies the protocol address of the sending user, *opt* identifies options that were associated with this data unit, and *udata* specifies the user data that was received.

By default, `t_rcvudata()` operates in synchronous mode and will wait for a data unit to arrive if none is currently available. However, if `O_NONBLOCK` is set by means of `t_open(3NSL)` or `fcntl(2)`, `t_rcvudata()` will execute in asynchronous mode and will fail if no data units are available.

If the buffer defined in the *udata* field of *unitdata* is not large enough to hold the current data unit, the buffer will be filled and `T_MORE` will be set in *flags* on return to indicate that another `t_rcvudata()` should be called to retrieve the rest of the data unit. Subsequent calls to `t_rcvudata()` will return zero for the length of the address and options until the full data unit has been received.

If the call is interrupted, `t_rcvudata()` will return `EINTR` and no datagrams will have been removed from the endpoint.

Return Values Upon successful completion, a value of 0 is returned. Otherwise, a value of -1 is returned and `t_errno` is set to indicate an error.

Valid States T_IDLE.

Errors On failure, `t_errno` is set to one of the following:

TBADF	The specified file descriptor does not refer to a transport endpoint.
TBUFOVFLW	The number of bytes allocated for the incoming protocol address or options (<i>maxlen</i>) is greater than 0 but not sufficient to store the information. The unit data information to be returned in <i>unitdata</i> will be discarded.
TLOOK	An asynchronous event has occurred on this transport endpoint and requires immediate attention.
TNODATA	O_NONBLOCK was set, but no data units are currently available from the transport provider.
TNOTSUPPORT	This function is not supported by the underlying transport provider.
TOUTSTATE	The communications endpoint referenced by <i>fd</i> is not in one of the states in which a call to this function is valid.
TPROTO	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<code>t_errno</code>).
TSYSERR	A system error has occurred during execution of this function.

Tli Compatibility The XTI and TLI interface definitions have common names but use different header files. This, and other semantic differences between the two interfaces are described in the subsections below.

Interface Header The XTI interfaces use the header file, `xti.h`. TLI interfaces should *not* use this header. They should use the header:

```
#include<tiuser.h>
```

Error Description Values The `t_errno` values that can be set by the XTI interface and cannot be set by the TLI interface are:

TPROTO
TOUTSTATE

A `t_errno` value that this routine can return under different circumstances than its XTI counterpart is TBUFOVFLW. It can be returned even when the `maxlen` field of the corresponding buffer has been set to zero.

Option Buffers The format of the options in an opt buffer is dictated by the transport provider. Unlike the XTI interface, the TLI interface does not fix the buffer format.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [fcntl\(2\)](#), [t_alloc\(3NSL\)](#), [t_open\(3NSL\)](#), [t_rcvuderr\(3NSL\)](#), [t_sndudata\(3NSL\)](#), [attributes\(5\)](#)

Name t_rcvuderr – receive a unit data error indication

Synopsis #include <xti.h>

```
int t_rcvuderr(int fd, struct t_uderr *uderr);
```

Description This routine is part of the XTI interfaces which evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI routine that has the same name as an XTI routine, the `tiuser.h` header file must be used. Refer to the TLI COMPATIBILITY section for a description of differences between the two interfaces.

This function is used in connectionless-mode to receive information concerning an error on a previously sent data unit, and should only be issued following a unit data error indication. It informs the transport user that a data unit with a specific destination address and protocol options produced an error. The argument *fd* identifies the local transport endpoint through which the error report will be received, and *uderr* points to a `t_uderr` structure containing the following members:

```
struct netbuf addr;  
struct netbuf opt;  
t_scalar_t error;
```

The *maxlen* field of *addr* and *opt* must be set before calling this function to indicate the maximum size of the buffer for each. If this field is set to zero for *addr* or *opt*, no information is returned in the *buf* field of this parameter.

On return from this call, the *addr* structure specifies the destination protocol address of the erroneous data unit, the *opt* structure identifies options that were associated with the data unit, and *error* specifies a protocol-dependent error code.

If the user does not care to identify the data unit that produced an error, *uderr* may be set to a null pointer, and `t_rcvuderr()` will simply clear the error indication without reporting any information to the user.

Return Values Upon successful completion, a value of 0 is returned. Otherwise, a value of -1 is returned and `t_errno` is set to indicate an error.

Valid States T_IDLE.

Errors On failure, `t_errno` is set to one of the following:

TBADF	The specified file descriptor does not refer to a transport endpoint.
TBUFOVFLW	The number of bytes allocated for the incoming protocol address or options (<i>maxlen</i>) is greater than 0 but not sufficient to store the information. The unit data error information to be returned in <i>uderr</i> will be discarded.

TNOTSUPPORT	This function is not supported by the underlying transport provider.
TNOUDERR	No unit data error indication currently exists on the specified transport endpoint.
TOUTSTATE	The communications endpoint referenced by <i>fd</i> is not in one of the states in which a call to this function is valid.
TPROTO	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<code>t_errno</code>).
TSYSERR	A system error has occurred during execution of this function.

Tli Compatibility	The XTI and TLI interface definitions have common names but use different header files. This, and other semantic differences between the two interfaces are described in the subsections below.
Interface Header	The XTI interfaces use the header file, <code>xti.h</code> . TLI interfaces should <i>not</i> use this header. They should use the header: <pre>#include <tiuser.h></pre>
Error Description Values	The <code>t_errno</code> values TPROTO and TOUTSTATE can be set by the XTI interface but not by the TLI interface. A <code>t_errno</code> value that this routine can return under different circumstances than its XTI counterpart is TBUFOVFLW. It can be returned even when the <code>maxlen</code> field of the corresponding buffer has been set to zero.
Option Buffers	The format of the options in an <code>opt</code> buffer is dictated by the transport provider. Unlike the XTI interface, the TLI interface does not fix the buffer format.
Attributes	See attributes(5) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [t_rcvudata\(3NSL\)](#), [t_sndudata\(3NSL\)](#), [attributes\(5\)](#)

Name t_rcvv – receive data or expedited data sent over a connection and put the data into one or more non-contiguous buffers

Synopsis #include <xti.h>

```
int t_rcvv(int fd, struct t_iovec *iov, unsigned int iovcount, int *flags);
```

Description This function receives either normal or expedited data. The argument *fd* identifies the local transport endpoint through which data will arrive, *iov* points to an array of buffer address/buffer size pairs (*iov_base*, *iov_len*). The `t_rcvv()` function receives data into the buffers specified by *iov*[0].*iov_base*, *iov*[1].*iov_base*, through *iov* [*iovcount*-1].*iov_base*, always filling one buffer before proceeding to the next.

Note that the limit on the total number of bytes available in all buffers passed:

```
iov(0).iov_len + . . . + iov(iovcount-1).iov_len)
```

may be constrained by implementation limits. If no other constraint applies, it will be limited by `INT_MAX`. In practice, the availability of memory to an application is likely to impose a lower limit on the amount of data that can be sent or received using scatter/gather functions.

The argument *iovcount* contains the number of buffers which is limited to `T_IOV_MAX`, which is an implementation-defined value of at least 16. If the limit is exceeded, the function will fail with `TBADDATA`.

The argument *flags* may be set on return from `t_rcvv()` and specifies optional flags as described below.

By default, `t_rcvv()` operates in synchronous mode and will wait for data to arrive if none is currently available. However, if `O_NONBLOCK` is set by means of `t_open(3NSL)` or `fcntl(2)`, `t_rcvv()` will execute in asynchronous mode and will fail if no data is available. See `TNODATA` below.

On return from the call, if `T_MORE` is set in *flags*, this indicates that there is more data, and the current transport service data unit (TSDU) or expedited transport service data unit (ETSDU) must be received in multiple `t_rcvv()` or `t_rcv(3NSL)` calls. In the asynchronous mode, or under unusual conditions (for example, the arrival of a signal or `T_EXDATA` event), the `T_MORE` flag may be set on return from the `t_rcvv()` call even when the number of bytes received is less than the total size of all the receive buffers. Each `t_rcvv()` with the `T_MORE` flag set indicates that another `t_rcvv()` must follow to get more data for the current TSDU. The end of the TSDU is identified by the return of a `t_rcvv()` call with the `T_MORE` flag not set. If the transport provider does not support the concept of a TSDU as indicated in the *info* argument on return from `t_open(3NSL)` or `t_getinfo(3NSL)`, the `T_MORE` flag is not meaningful and should be ignored. If the amount of buffer space passed in *iov* is greater than zero on the call to `t_rcvv()`, then `t_rcvv()` will return 0 only if the end of a TSDU is being returned to the user.

On return, the data is expedited if `T_EXPEDITED` is set in flags. If `T_MORE` is also set, it indicates that the number of expedited bytes exceeded `nbytes`, a signal has interrupted the call, or that an entire ETSDU was not available (only for transport protocols that support fragmentation of ETSDUs). The rest of the ETSDU will be returned by subsequent calls to `t_rcvv()` which will return with `T_EXPEDITED` set in flags. The end of the ETSDU is identified by the return of a `t_rcvv()` call with `T_EXPEDITED` set and `T_MORE` cleared. If the entire ETSDU is not available it is possible for normal data fragments to be returned between the initial and final fragments of an ETSDU.

If a signal arrives, `t_rcvv()` returns, giving the user any data currently available. If no data is available, `t_rcvv()` returns `-1`, sets `t_errno` to `TSYSERR` and `errno` to `EINTR`. If some data is available, `t_rcvv()` returns the number of bytes received and `T_MORE` is set in flags.

In synchronous mode, the only way for the user to be notified of the arrival of normal or expedited data is to issue this function or check for the `T_DATA` or `T_EXDATA` events using the [t_look\(3NSL\)](#) function. Additionally, the process can arrange to be notified via the EM interface.

Return Values On successful completion, `t_rcvv()` returns the number of bytes received. Otherwise, it returns `-1` on failure and `t_errno` is set to indicate the error.

Valid States `T_DATAXFER`, `T_OUTREL`.

Errors On failure, `t_errno` is set to one of the following:

<code>TBADDATA</code>	<i>iovcount</i> is greater than <code>T_IOV_MAX</code> .
<code>TBADF</code>	The specified file descriptor does not refer to a transport endpoint.
<code>TLOOK</code>	An asynchronous event has occurred on this transport endpoint and requires immediate attention.
<code>TNODATA</code>	<code>O_NONBLOCK</code> was set, but no data is currently available from the transport provider.
<code>TNOTSUPPORT</code>	This function is not supported by the underlying transport provider.
<code>TOUTSTATE</code>	The communications endpoint referenced by <i>fd</i> is not in one of the states in which a call to this function is valid.
<code>TPROTO</code>	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<code>t_errno</code>).
<code>TSYSERR</code>	A system error has occurred during execution of this function.

Tli Compatibility In the TLI interface definition, no counterpart of this routine was defined.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [fcntl\(2\)](#), [t_getinfo\(3NSL\)](#), [t_look\(3NSL\)](#), [t_open\(3NSL\)](#), [t_rcv\(3NSL\)](#), [t_snd\(3NSL\)](#), [t_sndv\(3NSL\)](#), [attributes\(5\)](#)

Name t_rcvvudata – receive a data unit into one or more noncontiguous buffers

Synopsis #include <xti.h>

```
int t_rcvvudata(int fd, struct t_unitdata *unitdata, struct t_iovec *iov,
               unsigned int iovcount, int *flags);
```

Description This function is used in connectionless mode to receive a data unit from another transport user. The argument *fd* identifies the local transport endpoint through which data will be received, *unitdata* holds information associated with the received data unit, *iovcount* contains the number of non-contiguous udata buffers which is limited to T_IOV_MAX, which is an implementation-defined value of at least 16, and *flags* is set on return to indicate that the complete data unit was not received. If the limit on *iovcount* is exceeded, the function fails with TBADDDATA. The argument *unitdata* points to a t_unitdata structure containing the following members:

```
struct netbuf addr;
struct netbuf opt;
struct netbuf udata;
```

The *maxlen* field of *addr* and *opt* must be set before calling this function to indicate the maximum size of the buffer for each. The *udata* field of t_unitdata is not used. The *iov_len* and *iov_base* fields of "iov0" through *iov[iovcount-1]* must be set before calling t_rcvvudata() to define the buffer where the userdata will be placed. If the maxlen field of *addr* or *opt* is set to zero then no information is returned in the *buf* field for this parameter.

On return from this call, *addr* specifies the protocol address of the sending user, *opt* identifies options that were associated with this data unit, and *iov[0].iov_base* through *iov[iovcount-1].iov_base* contains the user data that was received. The return value of t_rcvvudata() is the number of bytes of user data given to the user.

Note that the limit on the total number of bytes available in all buffers passed:

```
iov(0).iov_len + . . + iov(iovcount-1).iov_len)
```

may be constrained by implementation limits. If no other constraint applies, it will be limited by INT_MAX. In practice, the availability of memory to an application is likely to impose a lower limit on the amount of data that can be sent or received using scatter/gather functions.

By default, t_rcvvudata() operates in synchronous mode and waits for a data unit to arrive if none is currently available. However, if O_NONBLOCK is set by means of t_open(3NSL) or fcntl(2), t_rcvvudata() executes in asynchronous mode and fails if no data units are available.

If the buffers defined in the *iov[]* array are not large enough to hold the current data unit, the buffers will be filled and T_MORE will be set in flags on return to indicate that another

t_rcvvudata() should be called to retrieve the rest of the data unit. Subsequent calls to t_rcvvudata() will return zero for the length of the address and options, until the full data unit has been received.

Return Values On successful completion, t_rcvvudata() returns the number of bytes received. Otherwise, it returns -1 on failure and t_errno is set to indicate the error.

Valid States T_IDLE.

Errors On failure, t_errno is set to one of the following:

TBADDATA	iovcount is greater than T_IOV_MAX.
TBADF	The specified file descriptor does not refer to a transport endpoint.
TBUFOVFLW	The number of bytes allocated for the incoming protocol address or options (<i>maxlen</i>) is greater than 0 but not sufficient to store the information. The unit data information to be returned in <i>unitdata</i> will be discarded.
TLOOK	An asynchronous event has occurred on this transport endpoint and requires immediate attention.
TNODATA	O_NONBLOCK was set, but no data units are currently available from the transport provider.
TNOTSUPPORT	This function is not supported by the underlying transport provider.
TOUTSTATE	The communications endpoint referenced by <i>fd</i> is not in one of the states in which a call to this function is valid.
TPROTO	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (t_errno).
TSYSERR	A system error has occurred during execution of this function.

Tli Compatibility In the TLI interface definition, no counterpart of this routine was defined.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [fcntl\(2\)](#), [t_alloc\(3NSL\)](#), [t_open\(3NSL\)](#), [t_rcvvudata\(3NSL\)](#), [t_rcvuderr\(3NSL\)](#), [t_sndudata\(3NSL\)](#), [t_sndvudata\(3NSL\)](#), [attributes\(5\)](#)

Name t_snd – send data or expedited data over a connection

Synopsis #include <xti.h>

```
int t_snd(int fd, void *buf, unsigned int nbytes, int flags);
```

Description This routine is part of the XTI interfaces which evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI routine that has the same name as an XTI routine, the `tiuser.h` header file must be used. Refer to the TLI COMPATIBILITY section for a description of differences between the two interfaces.

This function is used to send either normal or expedited data. The argument *fd* identifies the local transport endpoint over which data should be sent, *buf* points to the user data, *nbytes* specifies the number of bytes of user data to be sent, and *flags* specifies any optional flags described below:

T_EXPEDITED If set in *flags*, the data will be sent as expedited data and will be subject to the interpretations of the transport provider.

T_MORE If set in *flags*, this indicates to the transport provider that the transport service data unit (TSDU) (or expedited transport service data unit - ETSDU) is being sent through multiple `t_snd()` calls. Each `t_snd()` with the **T_MORE** flag set indicates that another `t_snd()` will follow with more data for the current TSDU (or ETSDU).

The end of the TSDU (or ETSDU) is identified by a `t_snd()` call with the **T_MORE** flag not set. Use of **T_MORE** enables a user to break up large logical data units without losing the boundaries of those units at the other end of the connection. The flag implies nothing about how the data is packaged for transfer below the transport interface. If the transport provider does not support the concept of a TSDU as indicated in the *info* argument on return from `t_open(3NSL)` or `t_getinfo(3NSL)`, the **T_MORE** flag is not meaningful and will be ignored if set.

The sending of a zero-length fragment of a TSDU or ETSDU is only permitted where this is used to indicate the end of a TSDU or ETSDU; that is, when the **T_MORE** flag is not set. Some transport providers also forbid zero-length TSDUs and ETSDUs.

T_PUSH If set in *flags*, requests that the provider transmit all data that it has accumulated but not sent. The request is a local action on the provider and does not affect any similarly named protocol flag (for example, the TCP PUSH flag). This effect of setting this flag is protocol-dependent, and it may be ignored entirely by transport providers which do not support the use of

this feature.

Note that the communications provider is free to collect data in a send buffer until it accumulates a sufficient amount for transmission.

By default, `t_snd()` operates in synchronous mode and may wait if flow control restrictions prevent the data from being accepted by the local transport provider at the time the call is made. However, if `O_NONBLOCK` is set by means of `t_open(3NSL)` or `fcntl(2)`, `t_snd()` will execute in asynchronous mode, and will fail immediately if there are flow control restrictions. The process can arrange to be informed when the flow control restrictions are cleared by means of either `t_look(3NSL)` or the EM interface.

On successful completion, `t_snd()` returns the number of bytes (octets) accepted by the communications provider. Normally this will equal the number of octets specified in `nbytes`. However, if `O_NONBLOCK` is set or the function is interrupted by a signal, it is possible that only part of the data has actually been accepted by the communications provider. In this case, `t_snd()` returns a value that is less than the value of `nbytes`. If `t_snd()` is interrupted by a signal before it could transfer data to the communications provider, it returns `-1` with `t_errno` set to `TSYSERR` and `errno` set to `EINTR`.

If `nbytes` is zero and sending of zero bytes is not supported by the underlying communications service, `t_snd()` returns `-1` with `t_errno` set to `TBADDATA`.

The size of each TSDU or ETSDU must not exceed the limits of the transport provider as specified by the current values in the TSDU or ETSDU fields in the *info* argument returned by `t_getinfo(3NSL)`.

The error `TLLOOK` is returned for asynchronous events. It is required only for an incoming disconnect event but may be returned for other events.

Return Values On successful completion, `t_snd()` returns the number of bytes accepted by the transport provider. Otherwise, `-1` is returned on failure and `t_errno` is set to indicate the error.

Note that if the number of bytes accepted by the communications provider is less than the number of bytes requested, this may either indicate that `O_NONBLOCK` is set and the communications provider is blocked due to flow control, or that `O_NONBLOCK` is clear and the function was interrupted by a signal.

Errors On failure, `t_errno` is set to one of the following:

TBADDATA Illegal amount of data:

- A single send was attempted specifying a TSDU (ETSDU) or fragment TSDU (ETSDU) greater than that specified by the current values of the TSDU or ETSDU fields in the *info* argument.
- A send of a zero byte TSDU (ETSDU) or zero byte fragment of a TSDU (ETSDU) is not supported by the provider.

- Multiple sends were attempted resulting in a TSDU (ETSDU) larger than that specified by the current value of the TSDU or ETSDU fields in the *info* argument – the ability of an XTI implementation to detect such an error case is implementation-dependent. See WARNINGS, below.

TBADF	The specified file descriptor does not refer to a transport endpoint.
TBADFLAG	An invalid flag was specified.
TFLOW	O_NONBLOCK was set, but the flow control mechanism prevented the transport provider from accepting any data at this time.
TLOOK	An asynchronous event has occurred on this transport endpoint.
TNOTSUPPORT	This function is not supported by the underlying transport provider.
TOUTSTATE	The communications endpoint referenced by <i>fd</i> is not in one of the states in which a call to this function is valid.
TPROTO	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<code>t_errno</code>).
TSYSERR	A system error has occurred during execution of this function.

Tli Compatibility The XTI and TLI interface definitions have common names but use different header files. This, and other semantic differences between the two interfaces are described in the subsections below.

Interface Header The XTI interfaces use the header file, `xti.h`. TLI interfaces should *not* use this header. They should use the header:

```
#include <tiuser.h>
```

Error Description Values The `t_errno` values that can be set by the XTI interface and cannot be set by the TLI interface are:

```
TPROTO
TLOOK
TBADFLAG
TOUTSTATE
```

The `t_errno` values that this routine can return under different circumstances than its XTI counterpart are:

```
TBADDATA
```

In the TBADDATA error cases described above, TBADDATA is returned, only for illegal zero byte TSDU (ETSDU) send attempts.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [fcntl\(2\)](#), [t_getinfo\(3NSL\)](#), [t_look\(3NSL\)](#), [t_open\(3NSL\)](#), [t_rcv\(3NSL\)](#), [attributes\(5\)](#)

Warnings It is important to remember that the transport provider treats all users of a transport endpoint as a single user. Therefore if several processes issue concurrent `t_snd()` calls then the different data may be intermixed.

Multiple sends which exceed the maximum TSDU or ETSDU size may not be discovered by XTI. In this case an implementation-dependent error will result, generated by the transport provider, perhaps on a subsequent XTI call. This error may take the form of a connection abort, a TSYSErr, a TBADDATA or a TPROTO error.

If multiple sends which exceed the maximum TSDU or ETSDU size are detected by XTI, `t_snd()` fails with TBADDATA.

Name t_snddis – send user-initiated disconnection request

Synopsis #include <xti.h>

```
int t_snddis(int fd, const struct t_call *call);
```

Description This routine is part of the XTI interfaces which evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI routine that has the same name as an XTI routine, the `tuser.h` header file must be used. Refer to the [TLI COMPATIBILITY](#) section for a description of differences between the two interfaces.

This function is used to initiate an abortive release on an already established connection, or to reject a connection request. The argument *fd* identifies the local transport endpoint of the connection, and *call* specifies information associated with the abortive release. The argument *call* points to a `t_call` structure which contains the following members:

```
struct netbuf addr;
struct netbuf opt;
struct netbuf udata;
int sequence;
```

The values in *call* have different semantics, depending on the context of the call to `t_snddis()`. When rejecting a connection request, *call* must be non-null and contain a valid value of *sequence* to uniquely identify the rejected connection indication to the transport provider. The *sequence* field is only meaningful if the transport connection is in the `T_INCON` state. The *addr* and *opt* fields of *call* are ignored. In all other cases, *call* need only be used when data is being sent with the disconnection request. The *addr*, *opt* and *sequence* fields of the `t_call` structure are ignored. If the user does not wish to send data to the remote user, the value of *call* may be a null pointer.

The *udata* structure specifies the user data to be sent to the remote user. The amount of user data must not exceed the limits supported by the transport provider, as returned in the *discon* field, of the *info* argument of `t_open(3NSL)` or `t_getinfo(3NSL)`. If the *len* field of *udata* is zero, no data will be sent to the remote user.

Return Values Upon successful completion, a value of 0 is returned. Otherwise, a value of -1 is returned and `t_errno` is set to indicate an error.

Valid States `T_DATAXFER`, `T_OUTCON`, `T_OUTREL`, `T_INREL`, `T_INCON` (`ocnt > 0`).

Errors On failure, `t_errno` is set to one of the following:

TBADF	The specified file descriptor does not refer to a transport endpoint.
TBADDATA	The amount of user data specified was not within the bounds allowed by the transport provider.

TBADSEQ	An invalid sequence number was specified, or a null <i>call</i> pointer was specified, when rejecting a connection request.
TLOOK	An asynchronous event, which requires attention, has occurred.
TNOTSUPPORT	This function is not supported by the underlying transport provider.
TOUTSTATE	The communications endpoint referenced by <i>fd</i> is not in one of the states in which a call to this function is valid.
TPROTO	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<code>t_errno</code>).
TSYSERR	A system error has occurred during execution of this function.

Tli Compatibility The XTI and TLI interface definitions have common names but use different header files. This, and other semantic differences between the two interfaces are described in the subsections below.

Interface Header The XTI interfaces use the header file, `xti.h`. TLI interfaces should *not* use this header. They should use the header:

```
#include <tiuser.h>
```

ErrorDescription Values The `t_errno` value `TPROTO` can be set by the XTI interface but not by the TLI interface.

Option Buffers The format of the options in an `opt` buffer is dictated by the transport provider. Unlike the XTI interface, the TLI interface does not fix the buffer format.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [t_connect\(3NSL\)](#), [t_getinfo\(3NSL\)](#), [t_listen\(3NSL\)](#), [t_open\(3NSL\)](#), [t_snd\(3NSL\)](#), [attributes\(5\)](#)

Warnings `t_snddis()` is an abortive disconnection. Therefore a `t_snddis()` issued on a connection endpoint may cause data previously sent by means of [t_snd\(3NSL\)](#), or data not yet received, to be lost, even if an error is returned.

Name t_sndrel – initiate an orderly release

Synopsis #include <xti.h>

```
int t_sndrel(int fd);
```

Description This routine is part of the XTI interfaces which evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI routine that has the same name as an XTI routine, the `tiuser.h` header file must be used. Refer to the TLI COMPATIBILITY section for a description of differences between the two interfaces.

For transport providers of type `T_COTS_ORD`, this function is used to initiate an orderly release of the outgoing direction of data transfer and indicates to the transport provider that the transport user has no more data to send. The argument *fd* identifies the local transport endpoint where the connection exists. After calling `t_sndrel()`, the user may not send any more data over the connection. However, a user may continue to receive data if an orderly release indication has not been received. For transport providers of types other than `T_COTS_ORD`, this function fails with error `TNOTSUPPORT`.

Return Values Upon successful completion, a value of 0 is returned. Otherwise, a value of -1 is returned and `t_errno` is set to indicate an error.

Valid States `T_DATAXFER`, `T_INREL`.

Errors On failure, `t_errno` is set to one of the following:

TBADF	The specified file descriptor does not refer to a transport endpoint.
TFLOW	<code>O_NONBLOCK</code> was set, but the flow control mechanism prevented the transport provider from accepting the function at this time.
TLOOK	An asynchronous event has occurred on this transport endpoint and requires immediate attention.
TNOTSUPPORT	This function is not supported by the underlying transport provider.
TOUTSTATE	The communications endpoint referenced by <i>fd</i> is not in one of the states in which a call to this function is valid.
TPROTO	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<code>t_errno</code>).
TSYSERR	A system error has occurred during execution of this function.

Tli Compatibility The XTI and TLI interface definitions have common names but use different header files. This, and other semantic differences between the two interfaces are described in the subsections below.

Interface Header The XTI interfaces use the header file, `xti.h`. TLI interfaces should *not* use this header. They should use the header:

```
#include <tiuser.h>
```

Error Description Values The `t_errno` values that can be set by the XTI interface and cannot be set by the TLI interface are:

```
TPROTO
TLOOK
TOUTSTATE
```

Notes Whenever this function fails with `t_error` set to `TFLOW`, `O_NONBLOCK` must have been set.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [t_error\(3NSL\)](#), [t_getinfo\(3NSL\)](#), [t_open\(3NSL\)](#), [t_rcvrel\(3NSL\)](#), [attributes\(5\)](#)

Name t_sndreldata – initiate or respond to an orderly release with user data

Synopsis #include <xti.h>

```
int t_sndreldata(int fd, struct t_discon *discon);
```

Description This function is used to initiate an orderly release of the outgoing direction of data transfer and to send user data with the release. The argument *fd* identifies the local transport endpoint where the connection exists, and *discon* points to a *t_discon* structure containing the following members:

```
struct netbuf udata;
int reason;
int sequence;
```

After calling `t_sndreldata()`, the user may not send any more data over the connection. However, a user may continue to receive data if an orderly release indication has not been received.

The field *reason* specifies the reason for the disconnection through a protocol-dependent *reason code*, and *udata* identifies any user data that is sent with the disconnection; the field *sequence* is not used.

The *udata* structure specifies the user data to be sent to the remote user. The amount of user data must not exceed the limits supported by the transport provider, as returned in the *discon* field of the *info* argument of `t_open(3NSL)` or `t_getinfo(3NSL)`. If the *len* field of *udata* is zero or if the provider did not return `T_ORDRELDATA` in the `t_open(3NSL)` flags, no data will be sent to the remote user.

If a user does not wish to send data and reason code to the remote user, the value of *discon* may be a null pointer.

This function is an optional service of the transport provider, only supported by providers of service type `T_COTS_ORD`. The flag `T_ORDRELDATA` in the *info*→*flag* field returned by `t_open(3NSL)` or `t_getinfo(3NSL)` indicates that the provider supports orderly release user data.

This function may not be available on all systems.

Return Values Upon successful completion, a value of 0 is returned. Otherwise, a value of -1 is returned and `t_errno` is set to indicate an error.

Valid States `T_DATAXFER`, `T_INREL`.

Errors On failure, `t_errno` is set to one of the following:

TBADDATA	The amount of user data specified was not within the bounds allowed by the transport provider, or user data was supplied and the provider did not return <code>T_ORDRELDATA</code> in the <code>t_open(3NSL)</code> flags.
TBADF	The specified file descriptor does not refer to a transport endpoint.
TFLOW	<code>O_NONBLOCK</code> was set, but the flow control mechanism prevented the transport provider from accepting the function at this time.
TLOOK	An asynchronous event has occurred on this transport endpoint and requires immediate attention.
TNOTSUPPORT	Orderly release is not supported by the underlying transport provider.
TOUTSTATE	The communications endpoint referenced by <i>fd</i> is not in one of the states in which a call to this function is valid.
TPROTO	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<code>t_errno</code>).
TSYSERR	A system error has occurred during execution of this function.

Tli Compatibility In the TLI interface definition, no counterpart of this routine was defined.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [t_getinfo\(3NSL\)](#), [t_open\(3NSL\)](#), [t_rcvrel\(3NSL\)](#), [t_rcvreldata\(3NSL\)](#), [t_sndrel\(3NSL\)](#), [attributes\(5\)](#)

Notes The interfaces `t_sndreldata()` and [t_rcvreldata\(3NSL\)](#) are only for use with a specific transport called “minimal OSI,” which is not available on the Solaris platform. These interfaces are not available for use in conjunction with Internet Transports (TCP or UDP).

Name t_sndudata – send a data unit

Synopsis #include <xti.h>

```
int t_sndudata(int fd, const struct t_unitdata *unitdata);
```

Description This routine is part of the XTI interfaces which evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI routine that has the same name as an XTI routine, the `tiuser.h` header file must be used. Refer to the TLI COMPATIBILITY section for a description of differences between the two interfaces.

This function is used in connectionless-mode to send a data unit to another transport user. The argument *fd* identifies the local transport endpoint through which data will be sent, and *unitdata* points to a `t_unitdata` structure containing the following members:

```
struct netbuf addr;
struct netbuf opt;
struct netbuf udata;
```

In *unitdata*, *addr* specifies the protocol address of the destination user, *opt* identifies options that the user wants associated with this request, and *udata* specifies the user data to be sent. The user may choose not to specify what protocol options are associated with the transfer by setting the *len* field of *opt* to zero. In this case, the provider uses the option values currently set for the communications endpoint.

If the *len* field of *udata* is zero, and sending of zero octets is not supported by the underlying transport service, the `t_sndudata()` will return -1 with `t_errno` set to `TBADDATA`.

By default, `t_sndudata()` operates in synchronous mode and may wait if flow control restrictions prevent the data from being accepted by the local transport provider at the time the call is made. However, if `O_NONBLOCK` is set by means of `t_open(3NSL)` or `fcntl(2)`, `t_sndudata()` will execute in asynchronous mode and will fail under such conditions. The process can arrange to be notified of the clearance of a flow control restriction by means of either `t_look(3NSL)` or the EM interface.

If the amount of data specified in *udata* exceeds the TSDU size as returned in the *tsdu* field of the *info* argument of `t_open(3NSL)` or `t_getinfo(3NSL)`, a `TBADDATA` error will be generated. If `t_sndudata()` is called before the destination user has activated its transport endpoint (see `t_bind(3NSL)`), the data unit may be discarded.

If it is not possible for the transport provider to immediately detect the conditions that cause the errors `TBADDADDR` and `TBADOPT`, these errors will alternatively be returned by `t_rcvuderr`. Therefore, an application must be prepared to receive these errors in both of these ways.

If the call is interrupted, `t_sndudata()` will return `EINTR` and the datagram will not be sent.

Return Values Upon successful completion, a value of 0 is returned. Otherwise, a value of -1 is returned and `t_errno` is set to indicate an error.

Valid States `T_IDLE`.

Errors On failure, `t_errno` is set to one of the following:

TBADADDR	The specified protocol address was in an incorrect format or contained illegal information.
TBADDATA	Illegal amount of data. A single send was attempted specifying a TSDU greater than that specified in the <i>info</i> argument, or a send of a zero byte TSDU is not supported by the provider.
TBADF	The specified file descriptor does not refer to a transport endpoint.
TBADOPT	The specified options were in an incorrect format or contained illegal information.
TFLOW	<code>O_NONBLOCK</code> was set, but the flow control mechanism prevented the transport provider from accepting any data at this time.
TLOOK	An asynchronous event has occurred on this transport endpoint.
TNOTSUPPORT	This function is not supported by the underlying transport provider.
TOUTSTATE	The communications endpoint referenced by <i>fd</i> is not in one of the states in which a call to this function is valid.
TPROTO	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<code>t_errno</code>).
TSYSERR	A system error has occurred during execution of this function.

Tli Compatibility The XTI and TLI interface definitions have common names but use different header files. This, and other semantic differences between the two interfaces are described in the subsections below.

Interface Header The XTI interfaces use the header file, `xti.h`. TLI interfaces should *not* use this header. They should use the header:

```
#include <tiuser.h>
```

Error Description Values The `t_errno` values that can be set by the XTI interface and cannot be set by the TLI interface are:

- TPROTO
- TBADADDR

TBADOPT
TLOOK
TOUTSTATE

Notes Whenever this function fails with `t_error` set to `TFLOW`, `O_NONBLOCK` must have been set.

Option Buffers The format of the options in an `opt` buffer is dictated by the transport provider. Unlike the XTI interface, the TLI interface does not fix the buffer format.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [fcntl\(2\)](#), [t_alloc\(3NSL\)](#), [t_bind\(3NSL\)](#), [t_error\(3NSL\)](#), [t_getinfo\(3NSL\)](#), [t_look\(3NSL\)](#), [t_open\(3NSL\)](#), [t_rcvudata\(3NSL\)](#), [t_rcvuderr\(3NSL\)](#), [attributes\(5\)](#)

Name t_sndv – send data or expedited data, from one or more non-contiguous buffers, on a connection

Synopsis #include <xti.h>

```
int t_sndv(int fd, const struct t_iovec *iov, unsigned int iovcount, int flags);
```

Description This function is used to send either normal or expedited data. The argument *fd* identifies the local transport endpoint over which data should be sent, *iov* points to an array of buffer address/buffer length pairs. t_sndv() sends data contained in buffers *iov0*, *iov1*, through *iov* [*iovcount*-1]. *iovcount* contains the number of non-contiguous data buffers which is limited to T_IOV_MAX, an implementation-defined value of at least 16. If the limit is exceeded, the function fails with TBADDDATA.

iov(0).iov_len + . . + iov(iovcount-1).iov_len

Note that the limit on the total number of bytes available in all buffers passed:

may be constrained by implementation limits. If no other constraint applies, it will be limited by INT_MAX. In practice, the availability of memory to an application is likely to impose a lower limit on the amount of data that can be sent or received using scatter/gather functions.

The argument *flags* specifies any optional flags described below:

- | | |
|-------------|--|
| T_EXPEDITED | If set in <i>flags</i> , the data will be sent as expedited data and will be subject to the interpretations of the transport provider. |
| T_MORE | If set in <i>flags</i> , this indicates to the transport provider that the transport service data unit (TSDU) (or expedited transport service data unit – ETSDU) is being sent through multiple t_sndv() calls. Each t_sndv() with the T_MORE flag set indicates that another t_sndv() or t_snd(3NSL) will follow with more data for the current TSDU (or ETSDU). |

The end of the TSDU (or ETSDU) is identified by a t_sndv() call with the T_MORE flag not set. Use of T_MORE enables a user to break up large logical data units without losing the boundaries of those units at the other end of the connection. The flag implies nothing about how the data is packaged for transfer below the transport interface. If the transport provider does not support the concept of a TSDU as indicated in the *info* argument on return from t_open(3NSL) or t_getinfo(3NSL), the T_MORE flag is not meaningful and will be ignored if set.

The sending of a zero-length fragment of a TSDU or ETSDU is only permitted where this is used to indicate the end of a TSDU or ETSDU, that is, when the T_MORE flag is not set. Some transport providers also forbid zero-length TSDUs and ETSDUs.

If set in *flags*, requests that the provider transmit all data that it has accumulated but not sent. The request is a local action on the provider and does not affect any similarly named protocol flag (for example, the TCP PUSH flag). This effect of setting this flag is protocol-dependent, and it may be ignored entirely by transport providers which do not support the use of this feature.

The communications provider is free to collect data in a send buffer until it accumulates a sufficient amount for transmission.

By default, `t_sndv()` operates in synchronous mode and may wait if flow control restrictions prevent the data from being accepted by the local transport provider at the time the call is made. However, if `O_NONBLOCK` is set by means of `t_open(3NSL)` or `fcntl(2)`, `t_sndv()` executes in asynchronous mode, and will fail immediately if there are flow control restrictions. The process can arrange to be informed when the flow control restrictions are cleared via either `t_look(3NSL)` or the EM interface.

On successful completion, `t_sndv()` returns the number of bytes accepted by the transport provider. Normally this will equal the total number of bytes to be sent, that is,

```
(iov[0].iov_len + .. + iov[iovcount-1].iov_len)
```

However, the interface is constrained to send at most `INT_MAX` bytes in a single send. When `t_sndv()` has submitted `INT_MAX` (or lower constrained value, see the note above) bytes to the provider for a single call, this value is returned to the user. However, if `O_NONBLOCK` is set or the function is interrupted by a signal, it is possible that only part of the data has actually been accepted by the communications provider. In this case, `t_sndv()` returns a value that is less than the value of `nbytes`. If `t_sndv()` is interrupted by a signal before it could transfer data to the communications provider, it returns `-1` with `t_errno` set to `TSYSERR` and `errno` set to `EINTR`.

If the number of bytes of data in the *iov* array is zero and sending of zero octets is not supported by the underlying transport service, `t_sndv()` returns `-1` with `t_errno` set to `TBADDATA`.

The size of each TSDU or ETSDU must not exceed the limits of the transport provider as specified by the current values in the TSDU or ETSDU fields in the *info* argument returned by `t_getinfo(3NSL)`.

The error `TLOOK` is returned for asynchronous events. It is required only for an incoming disconnect event but may be returned for other events.

Return Values On successful completion, `t_sndv()` returns the number of bytes accepted by the transport provider. Otherwise, `-1` is returned on failure and `t_errno` is set to indicate the error.

Note that in synchronous mode, if more than `INT_MAX` bytes of data are passed in the *iov* array, only the first `INT_MAX` bytes will be passed to the provider.

If the number of bytes accepted by the communications provider is less than the number of bytes requested, this may either indicate that `O_NONBLOCK` is set and the communications provider is blocked due to flow control, or that `O_NONBLOCK` is clear and the function was interrupted by a signal.

Valid States `T_DATAXFER`, `T_INREL`.

Errors On failure, `t_errno` is set to one of the following:

<code>TBADDATA</code>	Illegal amount of data:
<code>TBADF</code>	The specified file descriptor does not refer to a transport endpoint. <ul style="list-style-type: none">▪ A single send was attempted specifying a TSDU (ETSDU) or fragment TSDU (ETSDU) greater than that specified by the current values of the TSDU or ETSDU fields in the <i>info</i> argument.▪ A send of a zero byte TSDU (ETSDU) or zero byte fragment of a TSDU (ETSDU) is not supported by the provider.▪ Multiple sends were attempted resulting in a TSDU (ETSDU) larger than that specified by the current value of the TSDU or ETSDU fields in the <i>info</i> argument – the ability of an XTI implementation to detect such an error case is implementation-dependent. See <code>WARNINGS</code>, below.▪ <i>iovcount</i> is greater than <code>T_IOV_MAX</code>.
<code>TBADFLAG</code>	An invalid flag was specified.
<code>TFLOW</code>	<code>O_NONBLOCK</code> was set, but the flow control mechanism prevented the transport provider from accepting any data at this time.
<code>TLOOK</code>	An asynchronous event has occurred on this transport endpoint.
<code>TNOTSUPPORT</code>	This function is not supported by the underlying transport provider.
<code>TOUTSTATE</code>	The communications endpoint referenced by <i>fd</i> is not in one of the states in which a call to this function is valid.
<code>TPROTO</code>	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<code>t_errno</code>).
<code>TSYSERR</code>	A system error has occurred during execution of this function.

Tli Compatibility In the TLI interface definition, no counterpart of this routine was defined.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [t_getinfo\(3NSL\)](#), [t_open\(3NSL\)](#), [t_rcvv\(3NSL\)](#) [t_rcv\(3NSL\)](#), [t_snd\(3NSL\)](#), [attributes\(5\)](#)

Warnings It is important to remember that the transport provider treats all users of a transport endpoint as a single user. Therefore if several processes issue concurrent [t_sndv\(\)](#) or [t_snd\(3NSL\)](#) calls, then the different data may be intermixed.

Multiple sends which exceed the maximum TSDU or ETSDU size may not be discovered by XTI. In this case an implementation-dependent error will result (generated by the transport provider), perhaps on a subsequent XTI call. This error may take the form of a connection abort, a TSYSERR, a TBADDDATA or a TPROTO error.

If multiple sends which exceed the maximum TSDU or ETSDU size are detected by XTI, [t_sndv\(\)](#) fails with TBADDDATA.

Name t_sndvudata – send a data unit from one or more noncontiguous buffers

Synopsis #include <xti.h>

```
int t_sndvudata(int fd, struct t_unitdata *unitdata, struct t_iovec *iov,
                unsigned int iovcount);
```

Description This function is used in connectionless mode to send a data unit to another transport user. The argument *fd* identifies the local transport endpoint through which data will be sent, *iovcount* contains the number of non-contiguous *udata* buffers and is limited to an implementation-defined value given by T_IOV_MAX which is at least 16, and *unitdata* points to a t_unitdata structure containing the following members:

```
struct netbuf addr;
struct netbuf opt;
struct netbuf udata;
```

If the limit on *iovcount* is exceeded, the function fails with TBADDDATA.

In *unitdata*, *addr* specifies the protocol address of the destination user, and *opt* identifies options that the user wants associated with this request. The *udata* field is not used. The user may choose not to specify what protocol options are associated with the transfer by setting the *len* field of *opt* to zero. In this case, the provider may use default options.

The data to be sent is identified by *iov[0]* through *iov[iovcount-1]*.

Note that the limit on the total number of bytes available in all buffers passed:

iov(0).iov_len + . . + iov(iovcount-1).iov_len

may be constrained by implementation limits. If no other constraint applies, it will be limited by INT_MAX. In practice, the availability of memory to an application is likely to impose a lower limit on the amount of data that can be sent or received using scatter/gather functions.

By default, t_sndvudata() operates in synchronous mode and may wait if flow control restrictions prevent the data from being accepted by the local transport provider at the time the call is made. However, if O_NONBLOCK is set by means of t_open(3NSL) or fcntl(2), t_sndvudata() executes in asynchronous mode and will fail under such conditions. The process can arrange to be notified of the clearance of a flow control restriction by means of either t_look(3NSL) or the EM interface.

If the amount of data specified in *iov0* through *iov[iovcount-1]* exceeds the TSDU size as returned in the *tsdu* field of the *info* argument of t_open(3NSL) or t_getinfo(3NSL), or is zero and sending of zero octets is not supported by the underlying transport service, a TBADDDATA error is generated. If t_sndvudata() is called before the destination user has activated its transport endpoint (see t_bind(3NSL)), the data unit may be discarded.

If it is not possible for the transport provider to immediately detect the conditions that cause the errors TBADADDR and TBADOPT, these errors will alternatively be returned by [t_rcvuderr\(3NSL\)](#). An application must therefore be prepared to receive these errors in both of these ways.

Return Values Upon successful completion, a value of 0 is returned. Otherwise, a value of -1 is returned and `t_errno` is set to indicate an error.

Valid States T_IDLE.

Errors On failure, `t_errno` is set to one of the following:

TBADADDR	The specified protocol address was in an incorrect format or contained illegal information.
TBADDATA	Illegal amount of data. <ul style="list-style-type: none"> ▪ A single send was attempted specifying a TSDU greater than that specified in the <i>info</i> argument, or a send of a zero byte TSDU is not supported by the provider. ▪ <i>iovcount</i> is greater than T_IOV_MAX.
TBADF	The specified file descriptor does not refer to a transport endpoint.
TBADOPT	The specified options were in an incorrect format or contained illegal information.
TFLOW	O_NONBLOCK i was set, but the flow control mechanism prevented the transport provider from accepting any data at this time.
TLOOK	An asynchronous event has occurred on this transport endpoint.
TNOTSUPPORT	This function is not supported by the underlying transport provider.
TOUTSTATE	The communications endpoint referenced by <i>fd</i> is not in one of the states in which a call to this function is valid.
TPROTO	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<code>t_errno</code>).
TSYSERR	A system error has occurred during execution of this function.

Tli Compatibility In the TLI interface definition, no counterpart of this routine was defined.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [fcntl\(2\)](#), [t_alloc\(3NSL\)](#), [t_open\(3NSL\)](#), [t_rcvudata\(3NSL\)](#), [t_rcvvudata\(3NSL\)](#),
[t_rcvuderr\(3NSL\)](#), [t_sndudata\(3NSL\)](#), [attributes\(5\)](#)

Name t_strerror – produce an error message string

Synopsis #include <xti.h>

```
const char *t_strerror(int errnum);
```

Description This routine is part of the XTI interfaces which evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI routine that has the same name as an XTI routine, the `tiuser.h` header file must be used. Refer to the TLI COMPATIBILITY section for a description of differences between the two interfaces.

The `t_strerror()` function maps the error number in `errnum` that corresponds to an XTI error to a language-dependent error message string and returns a pointer to the string. The string pointed to will not be modified by the program, but may be overwritten by a subsequent call to the `t_strerror` function. The string is not terminated by a newline character. The language for error message strings written by `t_strerror()` is that of the current locale. If it is English, the error message string describing the value in `t_errno` may be derived from the comments following the `t_errno` codes defined in <xti.h>. If an error code is unknown, and the language is English, `t_strerror()` returns the string:

```
"<error>: error unknown"
```

where <error> is the error number supplied as input. In other languages, an equivalent text is provided.

Valid States ALL - apart from T_UNINIT.

Return Values The function `t_strerror()` returns a pointer to the generated message string.

Tli Compatibility The XTI and TLI interface definitions have common names but use different header files. This, and other semantic differences between the two interfaces are described in the subsections below.

Interface Header The XTI interfaces use the header file, `xti.h`. TLI interfaces should *not* use this header. They should use the header:

```
#include <tiuser.h>
```

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [t_errno\(3NSL\)](#), [t_error\(3NSL\)](#), [attributes\(5\)](#)

Name t_sync – synchronize transport library

Synopsis #include <xti.h>

```
int t_sync(int fd);
```

Description This routine is part of the XTI interfaces which evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI routine that has the same name as an XTI routine, the `tiuser.h` header file must be used. Refer to the TLI COMPATIBILITY section for a description of differences between the two interfaces.

For the transport endpoint specified by *fd*, `t_sync()` synchronizes the data structures managed by the transport library with information from the underlying transport provider. In doing so, it can convert an uninitialized file descriptor (obtained by means of a `open(2)`, `dup(2)` or as a result of a `fork(2)` and `exec(2)`) to an initialized transport endpoint, assuming that the file descriptor referenced a transport endpoint, by updating and allocating the necessary library data structures. This function also allows two cooperating processes to synchronize their interaction with a transport provider.

For example, if a process forks a new process and issues an `exec(2)`, the new process must issue a `t_sync()` to build the private library data structure associated with a transport endpoint and to synchronize the data structure with the relevant provider information.

It is important to remember that the transport provider treats all users of a transport endpoint as a single user. If multiple processes are using the same endpoint, they should coordinate their activities so as not to violate the state of the transport endpoint. The function `t_sync()` returns the current state of the transport endpoint to the user, thereby enabling the user to verify the state before taking further action. This coordination is only valid among cooperating processes; it is possible that a process or an incoming event could change the endpoint's state *after* a `t_sync()` is issued.

If the transport endpoint is undergoing a state transition when `t_sync()` is called, the function will fail.

Return Values On successful completion, the state of the transport endpoint is returned. Otherwise, a value of `-1` is returned and `t_errno` is set to indicate an error. The state returned is one of the following:

T_UNBND	Unbound.
T_IDLE	Idle.
T_OUTCON	Outgoing connection pending.
T_INCON	Incoming connection pending.
T_DATAXFER	Data transfer.

- T_OUTREL Outgoing orderly release (waiting for an orderly release indication).
- T_INREL Incoming orderly release (waiting for an orderly release request).

Errors On failure, `t_errno` is set to one of the following:

- TBADF The specified file descriptor does not refer to a transport endpoint. This error may be returned when the *fd* has been previously closed or an erroneous number may have been passed to the call.
- TPROTO This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (`t_errno`).
- TSTATECHNG The transport endpoint is undergoing a state change.
- TSYSERR A system error has occurred during execution of this function.

Tli Compatibility The XTI and TLI interface definitions have common names but use different header files. This, and other semantic differences between the two interfaces are described in the subsections below.

Interface Header The XTI interfaces use the header file, `xti.h`. TLI interfaces should *not* use this header. They should use the header:

```
#include <tiuser.h>
```

Error Description Values The `t_errno` value that can be set by the XTI interface and cannot be set by the TLI interface is:

TPROTO

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT Level	Safe

See Also [dup\(2\)](#), [exec\(2\)](#), [fork\(2\)](#), [open\(2\)](#), [attributes\(5\)](#)

Name t_sysconf – get configurable XTI variables

Synopsis #include <xti.h>

```
int t_sysconf(intname);
```

Description The `t_sysconf()` function provides a method for the application to determine the current value of configurable and implementation-dependent XTI limits or options.

The *name* argument represents the XTI system variable to be queried. The following table lists the minimal set of XTI system variables from <xti.h> that can be returned by `t_sysconf()`, and the symbolic constants, defined in <xti.h> that are the corresponding values used for *name*.

Variable	Value of Name
T_IOV_MAX	_SC_T_IOV_MAX

Return Values If *name* is valid, `t_sysconf()` returns the value of the requested limit/option, which might be -1, and leaves `t_errno` unchanged. Otherwise, a value of -1 is returned and `t_errno` is set to indicate an error.

Valid States All.

Errors On failure, `t_errno` is set to the following:

TBADFLAG *name* has an invalid value.

Tli Compatibility In the TLI interface definition, no counterpart of this routine was defined.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [sysconf\(3C\)](#), [t_rcvv\(3NSL\)](#), [t_rcvvudata\(3NSL\)](#), [t_sndv\(3NSL\)](#), [t_sndvudata\(3NSL\)](#), [attributes\(5\)](#)

Name t_unbind – disable a transport endpoint

Synopsis #include <xti.h>

```
int t_unbind(int fd);
```

Description The This routine is part of the XTI interfaces which evolved from the TLI interfaces. XTI represents the future evolution of these interfaces. However, TLI interfaces are supported for compatibility. When using a TLI routine that has the same name as an XTI routine, the `tiuser.h` header file must be used. Refer to the TLI COMPATIBILITY section for a description of differences between the two interfaces.

`t_unbind()` function disables the transport endpoint specified by `fd` which was previously bound by `t_bind(3NSL)`. On completion of this call, no further data or events destined for this transport endpoint will be accepted by the transport provider. An endpoint which is disabled by using `t_unbind()` can be enabled by a subsequent call to `t_bind(3NSL)`.

Return Values Upon successful completion, a value of 0 is returned. Otherwise, a value of -1 is returned and `t_errno` is set to indicate an error.

Valid States T_IDLE.

Errors On failure, `t_errno` is set to one of the following:

TBADF	The specified file descriptor does not refer to a transport endpoint.
TLOOK	An asynchronous event has occurred on this transport endpoint.
TOUTSTATE	The communications endpoint referenced by <code>fd</code> is not in one of the states in which a call to this function is valid.
TPROTO	This error indicates that a communication problem has been detected between XTI and the transport provider for which there is no other suitable XTI error (<code>t_errno</code>).
TSYSERR	A system error has occurred during execution of this function.

Tli Compatibility The XTI and TLI interface definitions have common names but use different header files. This, and other semantic differences between the two interfaces are described in the subsections below.

Interface Header The XTI interfaces use the header file, `xti.h`. TLI interfaces should *not* use this header. They should use the header:

```
#include <tiuser.h>
```

Error Description The `t_errno` value that can be set by the XTI interface and cannot be set by the TLI interface
Values is:

TPROTO

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [t_bind\(3NSL\)](#), [attributes\(5\)](#)

Name xdr – library routines for external data representation

Description XDR routines allow C programmers to describe arbitrary data structures in a machine-independent fashion. Data for remote procedure calls (RPC) are transmitted using these routines.

Index to Routines The following table lists XDR routines and the manual reference pages on which they are described:

XDR Routine	Manual Reference Page
xdr_array	xdr_complex(3NSL)
xdr_bool	xdr_simple(3NSL)
xdr_bytes	xdr_complex(3NSL)
xdr_char	xdr_simple(3NSL)
xdr_control	xdr_admin(3NSL)
xdr_destroy	xdr_create(3NSL)
xdr_double	xdr_simple(3NSL)
xdr_enum	xdr_simple(3NSL)
xdr_float	xdr_simple(3NSL)
xdr_free	xdr_simple(3NSL)
xdr_getpos	xdr_admin(3NSL)
xdr_hyper	xdr_simple(3NSL)
xdr_inline	xdr_admin(3NSL)
xdr_int	xdr_simple(3NSL)
xdr_long	xdr_simple(3NSL)
xdr_longlong_t	xdr_simple(3NSL)
xdr_opaque	xdr_complex(3NSL)
xdr_pointer	xdr_complex(3NSL)
xdr_quadruple	xdr_simple(3NSL)
xdr_reference	xdr_complex(3NSL)
xdr_setpos	xdr_admin(3NSL)
xdr_short	xdr_simple(3NSL)
xdr_sizeof	xdr_admin(3NSL)

xdr_string	xdr_complex(3NSL)
xdr_u_char	xdr_simple(3NSL)
xdr_u_hyper	xdr_simple(3NSL)
xdr_u_int	xdr_simple(3NSL)
xdr_u_long	xdr_simple(3NSL)
xdr_u_longlong_t	xdr_simple(3NSL)
xdr_u_short	xdr_simple(3NSL)
xdr_union	xdr_complex(3NSL)
xdr_vector	xdr_complex(3NSL)
xdr_void	xdr_simple(3NSL)
xdr_wrapstring	xdr_complex(3NSL)
xdrmem_create	xdr_create(3NSL)
xdrrec_create	xdr_create(3NSL)
xdrrec_endofrecord	xdr_admin(3NSL)
xdrrec_eof	xdr_admin(3NSL)
xdrrec_readbytes	xdr_admin(3NSL)
xdrrec_skiprecord	xdr_admin(3NSL)
xdrstdio_create	xdr_create(3NSL)

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Safe

See Also [rpc\(3NSL\)](#), [xdr_admin\(3NSL\)](#), [xdr_complex\(3NSL\)](#), [xdr_create\(3NSL\)](#), [xdr_simple\(3NSL\)](#), [attributes\(5\)](#)

Name xdr_admin, xdr_control, xdr_getpos, xdr_inline, xdrrec_endofrecord, xdrrec_eof, xdrrec_readbytes, xdrrec_skiprecord, xdr_setpos, xdr_sizeof – library routines for external data representation

Description XDR library routines allow C programmers to describe arbitrary data structures in a machine-independent fashion. Protocols such as remote procedure calls (RPC) use these routines to describe the format of the data.

These routines deal specifically with the management of the XDR stream.

Routines See [rpc\(3NSL\)](#) for the definition of the XDR data structure. Note that any buffers passed to the XDR routines must be properly aligned. It is suggested either that [malloc\(3C\)](#) be used to allocate these buffers, or that the programmer insure that the buffer address is divisible evenly by four.

```
#include <rpc/xdr.h>
```

```
bool_t xdr_control( XDR *xdrs, int req, void *info);
```

A function macro to change or retrieve various information about an XDR stream. *req* indicates the type of operation and *info* is a pointer to the information. The supported values of *req* is XDR_GET_BYTES_AVAIL and its argument type is *xdr_bytesrec **. They return the number of bytes left unconsumed in the stream and a flag indicating whether or not this is the last fragment.

```
uint_t xdr_getpos(const XDR *xdrs);
```

A macro that invokes the get-position routine associated with the XDR stream, *xdrs*. The routine returns an unsigned integer, which indicates the position of the XDR byte stream. A desirable feature of XDR streams is that simple arithmetic works with this number, although the XDR stream instances need not guarantee this. Therefore, applications written for portability should not depend on this feature.

```
long *xdr_inline(XDR *xdrs, const int len);
```

A macro that invokes the in-line routine associated with the XDR stream, *xdrs*. The routine returns a pointer to a contiguous piece of the stream's buffer; *len* is the byte length of the desired buffer. Note: pointer is cast to *long **.

Warning: *xdr_inline()* may return NULL (0) if it cannot allocate a contiguous piece of a buffer. Therefore the behavior may vary among stream instances; it exists for the sake of efficiency, and applications written for portability should not depend on this feature.

```
bool_t xdrrec_endofrecord(XDR *xdrs, int sendnow);
```

This routine can be invoked only on streams created by *xdrrec_create()*. See [xdr_create\(3NSL\)](#). The data in the output buffer is marked as a completed record, and the output buffer is optionally written out if *sendnow* is non-zero. This routine returns TRUE if it succeeds, FALSE otherwise.


```
bool_t xdrrec_eof(XDR *xdrs);
```

This routine can be invoked only on streams created by `xdrrec_create()`. After consuming the rest of the current record in the stream, this routine returns `TRUE` if there is no more data in the stream's input buffer. It returns `FALSE` if there is additional data in the stream's input buffer.

```
int xdrrec_readbytes(XDR *xdrs, caddr_t addr, uint_t nbytes);
```

This routine can be invoked only on streams created by `xdrrec_create()`. It attempts to read *nbytes* bytes from the XDR stream into the buffer pointed to by *addr*. Upon success this routine returns the number of bytes read. Upon failure, it returns `-1`. A return value of `0` indicates an end of record.

```
bool_t xdrrec_skiprecord(XDR *xdrs);
```

This routine can be invoked only on streams created by `xdrrec_create()`. See [xdr_create\(3NSL\)](#). It tells the XDR implementation that the rest of the current record in the stream's input buffer should be discarded. This routine returns `TRUE` if it succeeds, `FALSE` otherwise.

```
bool_t xdr_setpos(XDR *xdrs, const uint_t pos);
```

A macro that invokes the set position routine associated with the XDR stream *xdrs*. The parameter *pos* is a position value obtained from `xdr_getpos()`. This routine returns `TRUE` if the XDR stream was repositioned, and `FALSE` otherwise.

Warning: it is difficult to reposition some types of XDR streams, so this routine may fail with one type of stream and succeed with another. Therefore, applications written for portability should not depend on this feature.

```
unsigned long xdr_sizeof(xdrproc_t func, void *data);
```

This routine returns the number of bytes required to encode *data* using the XDR filter function *func*, excluding potential overhead such as RPC headers or record markers. `0` is returned on error. This information might be used to select between transport protocols, or to determine the buffer size for various lower levels of RPC client and server creation routines, or to allocate storage when XDR is used outside of the RPC subsystem.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Safe

See Also [malloc\(3C\)](#), [rpc\(3NSL\)](#), [xdr_complex\(3NSL\)](#), [xdr_create\(3NSL\)](#), [xdr_simple\(3NSL\)](#), [attributes\(5\)](#)

Name xdr_complex, xdr_array, xdr_bytes, xdr_opaque, xdr_pointer, xdr_reference, xdr_string, xdr_union, xdr_vector, xdr_wrapstring – library routines for external data representation

Description XDR library routines allow C programmers to describe complex data structures in a machine-independent fashion. Protocols such as remote procedure calls (RPC) use these routines to describe the format of the data. These routines are the XDR library routines for complex data structures. They require the creation of XDR streams. See [xdr_create\(3NSL\)](#).

Routines See [rpc\(3NSL\)](#) for the definition of the XDR data structure. Note that any buffers passed to the XDR routines must be properly aligned. It is suggested either that `malloc()` be used to allocate these buffers, or that the programmer insure that the buffer address is divisible evenly by four.

```
#include <rpc/xdr.h>
```

```
bool_t xdr_array(XDR *xdrs, caddr_t *arrp, uint_t *sizep, const uint_t maxsize, const uint_t
    elsize, const xdrproc_t elproc);
```

`xdr_array()` translates between variable-length arrays and their corresponding external representations. The parameter *arrp* is the address of the pointer to the array, while *sizep* is the address of the element count of the array; this element count cannot exceed *maxsize*. The parameter *elsize* is the size of each of the array's elements, and *elproc* is an XDR routine that translates between the array elements' C form and their external representation. If **arrp* is NULL when decoding, `xdr_array()` allocates memory and **arrp* points to it. This routine returns TRUE if it succeeds, FALSE otherwise.

```
bool_t xdr_bytes(XDR *xdrs, char **sp, uint_t *sizep, const uint_t maxsize);
```

`xdr_bytes()` translates between counted byte strings and their external representations. The parameter *sp* is the address of the string pointer. The length of the string is located at address *sizep*; strings cannot be longer than *maxsize*. If **sp* is NULL when decoding, `xdr_bytes()` allocates memory and **sp* points to it. This routine returns TRUE if it succeeds, FALSE otherwise.

```
bool_t xdr_opaque(XDR *xdrs, caddr_t cp, const uint_t cnt);
```

`xdr_opaque()` translates between fixed size opaque data and its external representation. The parameter *cp* is the address of the opaque object, and *cnt* is its size in bytes. This routine returns TRUE if it succeeds, FALSE otherwise.

```
bool_t xdr_pointer(XDR *xdrs, char **objpp, uint_t objsize, const xdrproc_t xdrobj);
```

Like `xdr_reference()` except that it serializes null pointers, whereas `xdr_reference()` does not. Thus, `xdr_pointer()` can represent recursive data structures, such as binary trees or linked lists. If **objpp* is NULL when decoding, `xdr_pointer()` allocates memory and **objpp* points to it.

```
bool_t xdr_reference(XDR *xdrs, caddr_t *pp, uint_t size, const xdrproc_t proc);
```

`xdr_reference()` provides pointer chasing within structures. The parameter *pp* is the address of the pointer; *size* is the `sizeof` the structure that **pp* points to; and *proc* is an XDR procedure that translates the structure between its C form and its external representation. If **pp* is NULL when decoding, `xdr_reference()` allocates memory and **pp* points to it. This routine returns 1 if it succeeds, 0 otherwise.

Warning: this routine does not understand null pointers. Use `xdr_pointer()` instead.

`bool_t xdr_string(XDR *xdrs, char **sp, const uint_t maxsize);`
`xdr_string()` translates between C strings and their corresponding external representations. Strings cannot be longer than *maxsize*. Note: *sp* is the address of the string's pointer. If **sp* is NULL when decoding, `xdr_string()` allocates memory and **sp* points to it. This routine returns TRUE if it succeeds, FALSE otherwise. Note: `xdr_string()` can be used to send an empty string (" "), but not a null string.

`bool_t xdr_union(XDR *xdrs, enum_t *dscmp, char *unp, const struct xdr_discrim *choices, const xdrproc_t (*defaultarm));`

`xdr_union()` translates between a discriminated C union and its corresponding external representation. It first translates the discriminant of the union located at *dscmp*. This discriminant is always an `enum_t`. Next the union located at *unp* is translated. The parameter *choices* is a pointer to an array of `xdr_discrim` structures. Each structure contains an ordered pair of [*value*, *proc*]. If the union's discriminant is equal to the associated *value*, then the *proc* is called to translate the union. The end of the `xdr_discrim` structure array is denoted by a routine of value NULL. If the discriminant is not found in the *choices* array, then the *defaultarm* procedure is called (if it is not NULL). It returns TRUE if it succeeds, FALSE otherwise.

`bool_t xdr_vector(XDR *xdrs, char *arrp, const uint_t size, const uint_t elsize, const xdrproc_t elproc);`

`xdr_vector()` translates between fixed-length arrays and their corresponding external representations. The parameter *arrp* is the address of the pointer to the array, while *size* is the element count of the array. The parameter *elsize* is the `sizeof` each of the array's elements, and *elproc* is an XDR routine that translates between the array elements' C form and their external representation. This routine returns TRUE if it succeeds, FALSE otherwise.

`bool_t xdr_wrapstring(XDR *xdrs, char **sp);`

A routine that calls `xdr_string(xdrs, sp, maxuint)`; where *maxuint* is the maximum value of an unsigned integer.

Many routines, such as `xdr_array()`, `xdr_pointer()`, and `xdr_vector()` take a function pointer of type `xdrproc_t()`, which takes two arguments. `xdr_string()`, one of the most frequently used routines, requires three arguments, while `xdr_wrapstring()` only requires two. For these routines, `xdr_wrapstring()` is desirable. This routine returns TRUE if it succeeds, FALSE otherwise.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Safe

See Also [malloc\(3C\)](#), [rpc\(3NSL\)](#), [xdr_admin\(3NSL\)](#), [xdr_create\(3NSL\)](#), [xdr_simple\(3NSL\)](#), [attributes\(5\)](#)

Name xdr_create, xdr_destroy, xdrmem_create, xdrrec_create, xdrstdio_create – library routines for external data representation stream creation

Synopsis #include <rpc/xdr.h>

```
void xdr_destroy(XDR *xdrs);

void xdrmem_create(XDR *xdrs, const caddr_t addr, const uint_t size,
                  const enum xdr_op op);

void xdrrec_create(XDR *xdrs, const uint_t sendsz, const uint_t recvsz,
                  const caddr_t handle, const int (*readit) const void *read_handle,
                  char *buf, const int len, const int (*writeit)
                  const void *write_handle, const char *buf, const int len);

void xdrstdio_create(XDR *xdrs, FILE *
                    file, const enum xdr_op op);
```

Description The XDR library routines allow C programmers to describe arbitrary data structures in a machine-independent fashion. Protocols such as remote procedure calls (RPC) use these routines to describe the format of the data.

These routines deal with the creation of XDR streams, which must be created before any data can be translated into XDR format.

Routines See [rpc\(3NSL\)](#) for the definition of the XDR CLIENT and SVCXPRT data structures. Any buffers passed to the XDR routines must be properly aligned. Use [malloc\(3C\)](#) to allocate these buffers or be sure that the buffer address is divisible evenly by four.

xdr_destroy()	A macro that invokes the destroy routine associated with the XDR stream, <i>xdrs</i> . Private data structures associated with the stream are freed. Using <i>xdrs</i> after xdr_destroy() is invoked is undefined.
xdrmem_create()	This routine initializes the XDR stream object pointed to by <i>xdrs</i> . The stream's data is written to or read from a chunk of memory at location <i>addr</i> whose length is no less than <i>size</i> bytes long. The <i>op</i> determines the direction of the XDR stream. The value of <i>op</i> can be either XDR_ENCODE, XDR_DECODE, or XDR_FREE.
xdrrec_create()	This routine initializes the read-oriented XDR stream object pointed to by <i>xdrs</i> . The stream's data is written to a buffer of size <i>sendsz</i> . A value of 0 indicates the system should use a suitable default. The stream's data is read from a buffer of size <i>recvsz</i> . It too can be set to a suitable default by passing a 0 value. When a stream's output buffer is full, <i>writeit</i> is called. Similarly, when a stream's input buffer is empty, xdrrec_create() calls <i>readit</i> . The behavior of these two routines is similar to the system calls read() and write(), except that an appropriate handle, <i>read_handle</i> or <i>write_handle</i> , is passed to the

former routines as the first parameter instead of a file descriptor. See [read\(2\)](#) and [write\(2\)](#), respectively. The XDR stream's *op* field must be set by the caller.

This XDR stream implements an intermediate record stream. Therefore, additional bytes in the stream are provided for record boundary information.

`xdrstdio_create()` This routine initializes the XDR stream object pointed to by *xdrs*. The XDR stream data is written to or read from the standard I/O stream *file*. The parameter *op* determines the direction of the XDR stream. The value of *op* can be either `XDR_ENCODE`, `XDR_DECODE`, or `XDR_FREE`.

The destroy routine associated with XDR streams calls `fflush()` on the *file* stream, but never `fclose()`. See [fclose\(3C\)](#).

A failure of any of these functions can be detected by first initializing the *x_ops* field in the XDR structure (*xdrs*->*x_ops*) to `NULL` before calling the `xdr*_create()` function. If the *x_ops* field is still `NULL`, after the return from the `xdr*_create()` function, the call has failed. If the *x_ops* field contains some other value, assume that the call has succeeded.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	MT-Safe

See Also [read\(2\)](#), [write\(2\)](#), [fclose\(3C\)](#), [malloc\(3C\)](#), [rpc\(3NSL\)](#), [xdr_admin\(3NSL\)](#), [xdr_complex\(3NSL\)](#), [xdr_simple\(3NSL\)](#), [attributes\(5\)](#)

Name xdr_simple, xdr_bool, xdr_char, xdr_double, xdr_enum, xdr_float, xdr_free, xdr_hyper, xdr_int, xdr_long, xdr_longlong_t, xdr_quadruple, xdr_short, xdr_u_char, xdr_u_hyper, xdr_u_int, xdr_u_long, xdr_u_longlong_t, xdr_u_short, xdr_void – library routines for external data representation

Synopsis #include <rpc/xdr.h>

```
bool_t xdr_bool(XDR *xdrs, bool_t *bp);
bool_t xdr_char(XDR *xdrs, char *cp);
bool_t xdr_double(XDR *xdrs, double *dp);
bool_t xdr_enum(XDR *xdrs, enum_t *ep);
bool_t xdr_float(XDR *xdrs, float *fp);
void xdr_free(xdrproc_t proc, char *objp);
bool_t xdr_hyper(XDR *xdrs, longlong_t *llp);
bool_t xdr_int(XDR *xdrs, int *ip);
bool_t xdr_long(XDR *xdrs, longt *lp);
bool_t xdr_longlong_t(XDR *xdrs, longlong_t *llp);
bool_t xdr_quadruple(XDR *xdrs, long double *pq);
bool_t xdr_short(XDR *xdrs, short *sp);
bool_t xdr_u_char(XDR *xdrs, unsigned char *ucp);
bool_t xdr_u_hyper(XDR *xdrs, u_longlong_t *ullp);
bool_t xdr_u_int(XDR *xdrs, unsigned *up);
bool_t xdr_u_long(XDR *xdrs, unsigned long *ulp);
bool_t xdr_u_longlong_t(XDR *xdrs, u_longlong_t *ullp);
bool_t xdr_u_short(XDR *xdrs, unsigned short *usp);
bool_t xdr_void(void)
```

Description The XDR library routines allow C programmers to describe simple data structures in a machine-independent fashion. Protocols such as remote procedure calls (RPC) use these routines to describe the format of the data.

These routines require the creation of XDR streams (see [xdr_create\(3NSL\)](#)).

Routines See [rpc\(3NSL\)](#) for the definition of the XDR data structure. Note that any buffers passed to the XDR routines must be properly aligned. It is suggested that [malloc\(3C\)](#) be used to allocate these buffers or that the programmer insure that the buffer address is divisible evenly by four.

<code>xdr_bool()</code>	<code>xdr_bool()</code> translates between booleans (C integers) and their external representations. When encoding data, this filter produces values of either 1 or 0. This routine returns TRUE if it succeeds, FALSE otherwise.
<code>xdr_char()</code>	<code>xdr_char()</code> translates between C characters and their external representations. This routine returns TRUE if it succeeds, FALSE otherwise. Note: encoded characters are not packed, and occupy 4 bytes each. For arrays of characters, it is worthwhile to consider <code>xdr_bytes()</code> , <code>xdr_opaque()</code> , or <code>xdr_string()</code> (see xdr_complex(3NSL)).
<code>xdr_double()</code>	<code>xdr_double()</code> translates between C double precision numbers and their external representations. This routine returns TRUE if it succeeds, FALSE otherwise.
<code>xdr_enum()</code>	<code>xdr_enum()</code> translates between C enums (actually integers) and their external representations. This routine returns TRUE if it succeeds, FALSE otherwise.
<code>xdr_float()</code>	<code>xdr_float()</code> translates between C floats and their external representations. This routine returns TRUE if it succeeds, FALSE otherwise.
<code>xdr_free()</code>	Generic freeing routine. The first argument is the XDR routine for the object being freed. The second argument is a pointer to the object itself. Note: the pointer passed to this routine is not freed, but what it points to is freed (recursively, depending on the XDR routine).
<code>xdr_hyper()</code>	<code>xdr_hyper()</code> translates between ANSI C long long integers and their external representations. This routine returns TRUE if it succeeds, FALSE otherwise.
<code>xdr_int()</code>	<code>xdr_int()</code> translates between C integers and their external representations. This routine returns TRUE if it succeeds, FALSE otherwise.
<code>xdr_long()</code>	<code>xdr_long()</code> translates between C long integers and their external representations. This routine returns TRUE if it succeeds, FALSE otherwise.

In a 64-bit environment, this routine returns an error if the value of `lp` is outside the range `[INT32_MIN, INT32_MAX]`. The `xdr_int()` routine is recommended in place of this routine.

<code>xdr_longlong_t()</code>	<code>xdr_longlong_t()</code> translates between ANSI C long long integers and their external representations. This routine returns TRUE if it succeeds, FALSE otherwise. This routine is identical to <code>xdr_hyper()</code> .
<code>xdr_quadruple()</code>	<code>xdr_quadruple()</code> translates between IEEE quadruple precision floating point numbers and their external representations. This routine returns TRUE if it succeeds, FALSE otherwise.
<code>xdr_short()</code>	<code>xdr_short()</code> translates between C short integers and their external representations. This routine returns TRUE if it succeeds, FALSE otherwise.
<code>xdr_u_char()</code>	<code>xdr_u_char()</code> translates between unsigned C characters and their external representations. This routine returns TRUE if it succeeds, FALSE otherwise.
<code>xdr_u_hyper()</code>	<code>xdr_u_hyper()</code> translates between unsigned ANSI C long long integers and their external representations. This routine returns TRUE if it succeeds, FALSE otherwise.
<code>xdr_u_int()</code>	A filter primitive that translates between a C unsigned integer and its external representation. This routine returns TRUE if it succeeds, FALSE otherwise.
<code>xdr_u_long()</code>	<code>xdr_u_long()</code> translates between C unsigned long integers and their external representations. This routine returns TRUE if it succeeds, FALSE otherwise. In a 64-bit environment, this routine returns an error if the value of <i>ulp</i> is outside the range <code>[0, UINT32_MAX]</code> . The <code>xdr_u_int()</code> routine is recommended in place of this routine.
<code>xdr_u_longlong_t()</code>	<code>xdr_u_longlong_t()</code> translates between unsigned ANSI C long long integers and their external representations. This routine returns TRUE if it succeeds, FALSE otherwise. This routine is identical to <code>xdr_u_hyper()</code> .
<code>xdr_u_short()</code>	<code>xdr_u_short()</code> translates between C unsigned short integers and their external representations. This routine returns TRUE if it succeeds, FALSE otherwise.
<code>xdr_void()</code>	This routine always returns TRUE. It may be passed to RPC routines that require a function parameter, where nothing is to be done.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Safe

See Also [malloc\(3C\)](#), [rpc\(3NSL\)](#), [xdr_admin\(3NSL\)](#), [xdr_complex\(3NSL\)](#), [xdr_create\(3NSL\)](#), [attributes\(5\)](#)

Name ypclnt, yp_get_default_domain, yp_bind, yp_unbind, yp_match, yp_first, yp_next, yp_all, yp_order, yp_master, yperr_string, ypprot_err – NIS Version 2 client interface

Synopsis cc [-flag...] file... -lnsl [library...]
 #include <rpcsvc/ypclnt.h>
 #include <rpcsvc/yp_prot.h>

```
int yp_bind(char *indomain);

void yp_unbind (char *indomain);

int yp_get_default_domain(char **outdomain);

int yp_match(char *indomain, char *inmap, char *inkey, int inkeylen,
             char *char **outval, int *outvallen);

int yp_first(char *indomain, char *inmap, char **outkey, int *outkeylen,
             char **outval, int *outvallen);

int yp_next(char *indomain, char *inmap, char *inkey, int *inkeylen,
            char **outkey, int *outkeylen, char **outval,
            int *outvallen);

int yp_all(char *indomain, char *inmap, struct ypall_callback *incallback);

int yp_order(char *indomain, char *inmap, unsigned long *outorder);

int yp_master(char *indomain, char *inmap, char **outname);

char *yperr_string(int incode);

int ypprot_err(char *domain);
```

Description This package of functions provides an interface to NIS, Network Information Service Version 2, formerly referred to as YP. In this version of SunOS, NIS version 2 is supported only for compatibility with previous versions. The recommended enterprise level information service is NIS+ or NIS version 3. See [NIS+\(1\)](#). The current SunOS supports only the client interface to NIS version 2. This client interface will in turn be served either by an existing ypserve process running on another machine on the network that has an earlier version of SunOS, or by a NIS+ server running in “YP-compatibility mode”. See [rpc.nisd\(1M\)](#). The NOTES section in [ypfiles\(4\)](#) discusses the implications of being an NIS client of an NIS+ server in *YP-compatibility mode*. For commands used to access NIS from a client machine, see [ypbind\(1M\)](#), [ypwhich\(1\)](#), [ypmatch\(1\)](#), and [ypcat\(1\)](#). The package can be loaded from the standard library, /usr/lib/libnsl.so.1.

All input parameter names begin with *in*. Output parameters begin with *out*. Output parameters of type char ** should be addresses of uninitialized character pointers. Memory is allocated by the NIS client package using [malloc\(3C\)](#) and can be freed by the user code if it has no continuing need for it. For each *outkey* and *outval*, two extra bytes of memory are allocated at the end that contain NEWLINE and null, respectively, but these two bytes are not reflected

in *outkeylen* or *outvallen*. The *indomain* and *inmap* strings must be non-null and null-terminated. String parameters that are accompanied by a count parameter may not be null, but they may point to null strings, with the count parameter indicating this. Counted strings need not be null-terminated.

All functions in this package of type *int* return 0 if they succeed. Otherwise, they return a failure code (YPERR_XXX). Failure codes are described in the ERRORS section.

Routines `yp_bind()`

To use the NIS name services, the client process must be “bound” to an NIS server that serves the appropriate domain using `yp_bind()`. Binding need not be done explicitly by user code. Binding is done automatically whenever an NIS lookup function is called. The `yp_bind()` function can be called directly for processes that make use of a backup strategy, for example, a local file in cases when NIS services are not available. A process should call `yp_unbind()` when it is finished using NIS in order to free up resources.

`yp_unbind()`

Each binding allocates or uses up one client process socket descriptor. Each bound domain costs one socket descriptor. However, multiple requests to the same domain use that same descriptor. The `yp_unbind()` function is available at the client interface for processes that explicitly manage their socket descriptors while accessing multiple domains. The call to `yp_unbind()` makes the domain *unbound*, and frees all per-process and per-node resources used to bind it.

If an RPC failure results upon use of a binding, that domain will be unbound automatically. At that point, the `ypclnt()` layer will retry a few more times or until the operation succeeds, provided that `rpcbind(1M)` and `ypbind(1M)` are running, and either:

- The client process cannot bind a server for the proper domain; or
- RPC requests to the server fail.

Under the following circumstances, the `ypclnt` layer will return control to the user code, with either an error or success code and the results:

- If an error is not RPC-related.
- If `rpcbind` is not running.
- If `ypbind` is not running.
- If a bound `ypserv` process returns any answer (success or failure).

<code>yp_get_default_domain()</code>	NIS lookup calls require a map name and a domain name, at minimum. The client process should know the name of the map of interest. Client processes fetch the node's default domain by calling <code>yp_get_default_domain()</code> and use the returned <i>outdomain</i> as the <i>indomain</i> parameter to successive NIS name service calls. The domain returned is the same as that returned using the <code>SI_SRPC_DOMAIN</code> command to the sysinfo(2) system call. The value returned in <i>outdomain</i> should not be freed.
<code>yp_match()</code>	The <code>yp_match()</code> function returns the value associated with a passed key. This key must be exact because no pattern matching is available. <code>yp_match()</code> requires a full YP map name, such as <code>hosts.byname</code> , instead of the nickname <code>hosts</code> .
<code>yp_first()</code>	The <code>yp_first()</code> function returns the first key-value pair from the named map in the named domain.
<code>yp_next()</code>	The <code>yp_next()</code> function returns the next key-value pair in a named map. The <i>inkey</i> parameter must be the <i>outkey</i> returned from an initial call to <code>yp_first()</code> (to get the second key-value pair) or the one returned from the <i>n</i> th call to <code>yp_next()</code> (to get the <i>n</i> th + second key-value pair). Similarly, the <i>inkeylen</i> parameter must be the <i>outkeylen</i> returned from the earlier <code>yp_first()</code> or <code>yp_next()</code> call.

The concept of first and next is particular to the structure of the NIS map being processed. Retrieval order is not related to either the lexical order within any original (non-NIS name service) data base, or to any obvious numerical sorting order on the keys, values, or key-value pairs. The only ordering guarantee is that if the `yp_first()` function is called on a particular map, and then the `yp_next()` function is repeatedly called on the same map at the same server until the call fails with a reason of `YPERR_NOMORE`, every entry in the data base is seen exactly once. Further, if the same sequence of operations is performed on the same map at the same server, the entries are seen in the same order.

Under conditions of heavy server load or server failure, the domain can become unbound, then bound once again (perhaps to a different server) while a client is running. This binding can cause a break in one of the enumeration rules. Specific entries may be seen twice by the client, or not at all. This approach protects the client from error messages that

would otherwise be returned in the midst of the enumeration. For a better solution to enumerating all entries in a map, see `yp_all()`.

`yp_all()`

The `yp_all()` function provides a way to transfer an entire map from server to client in a single request using TCP (rather than UDP as with other functions in this package). The entire transaction takes place as a single RPC request and response. The `yp_all()` function can be used just like any other NIS name service procedure to identify the map in the normal manner and to supply the name of a function that will be called to process each key-value pair within the map. The call to `yp_all()` returns only when the transaction is completed (successfully or unsuccessfully), or the `foreach()` function decides that it does not want to see any more key-value pairs.

The third parameter to `yp_all()` is:

```
struct ypall_callback *incallback {
    int (*foreach)( );
    char *data;
};
```

The function `foreach()` is called:

```
foreach(int instatus, char *inkey,
int inkeylen, char *inval,
int invallen, char *indata);
```

The *instatus* parameter holds one of the return status values defined in `<rpcsvc/yp_prot.h>`, either `YP_TRUE` or an error code. See `ypprot_err()`, for a function that converts an NIS name service protocol error code to a `ypclnt` layer error code.

The key and value parameters are somewhat different than defined in the synopsis section above. First, the memory pointed to by the *inkey* and *inval* parameters is private to the `yp_all()` function, and is overwritten with the arrival of each new key-value pair. The `foreach()` function must do something useful with the contents of that memory, but it does not own the memory itself. Key and value objects presented to the `foreach()` function look exactly as they do in the server's map. If they were not NEWLINE-terminated or null-terminated in the map, they would not be here either.

The *indata* parameter is the contents of the *incallback->data* element passed to `yp_all()`. The data element of the callback structure can be used to share state information between the `foreach()` function and the mainline code. Its use is optional, and no part of the NIS client package inspects its contents; cast it to something useful, or ignore it. The `foreach()` function is Boolean. It should return 0 to indicate that it wants to be called again for further received key-value pairs, or non-zero to stop the flow of key-value pairs. If `foreach()` returns a non-zero value, it is not called again. The functional value of `yp_all()` is then 0.

<code>yp_order()</code>	The <code>yp_order()</code> function returns the order number for a map. The function is not supported if the <code>ypbind</code> process on the client's system is bound to an NIS+ server running in "YP-compatibility mode".
<code>yp_master()</code>	The <code>yp_master()</code> function returns the machine name of the master NIS server for a map.
<code>yperr_string()</code>	The <code>yperr_string()</code> function returns a pointer to an error message string that is null-terminated but contains no period or NEWLINE.
<code>ypprot_err()</code>	The <code>ypprot_err()</code> function takes an NIS name service protocol error code as input, and returns a <code>ypclnt()</code> layer error code, which can be used as an input to <code>yperr_string()</code> .

Return Values All integer functions return 0 if the requested operation is successful, or one of the following errors if the operation fails:

<code>YPERR_ACCESS</code>	Access violation.
<code>YPERR_BADARGS</code>	The arguments to the function are bad.
<code>YPERR_BADDDB</code>	The YP database is bad.
<code>YPERR_BUSY</code>	The database is busy.
<code>YPERR_DOMAIN</code>	Cannot bind to server on this domain.
<code>YPERR_KEY</code>	No such key in map.
<code>YPERR_MAP</code>	No such map in server's domain.
<code>YPERR_NODOM</code>	Local domain name not set.
<code>YPERR_NOMORE</code>	No more records in map database.
<code>YPERR_PMAP</code>	Cannot communicate with <code>rpcbind</code> .

YPERR_RESRC	Resource allocation failure.
YPERR_RPC	RPC failure; domain has been unbound.
YPERR_YPBIND	Cannot communicate with ypbind.
YPERR_YPERR	Internal YP server or client error.
YPERR_YPSESV	Cannot communicate with ypserv.
YPERR_VERS	YP version mismatch.

Files /usr/lib/libnsl.so.1

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Safe

See Also [NIS+\(1\)](#), [ypcat\(1\)](#), [ypmatch\(1\)](#), [ypwhich\(1\)](#), [rpc.nisd\(1M\)](#), [rpcbind\(1M\)](#), [ypbind\(1M\)](#), [ypserv\(1M\)](#), [sysinfo\(2\)](#), [malloc\(3C\)](#), [ypfiles\(4\)](#), [attributes\(5\)](#)

Name yp_update – change NIS information

Synopsis #include <rpcsvc/ypclnt.h>

```
int yp_update(char *domain, char *map, unsigned ypop, char *key,
              char *int keylen, char *data, int datalen);
```

Description yp_update() is used to make changes to the NIS database. The syntax is the same as that of yp_match() except for the extra parameter *ypop* which may take on one of four values. If it is POP_CHANGE then the data associated with the key will be changed to the new value. If the key is not found in the database, then yp_update() will return YPERR_KEY. If *ypop* has the value YPOP_INSERT then the key-value pair will be inserted into the database. The error YPERR_KEY is returned if the key already exists in the database. To store an item into the database without concern for whether it exists already or not, pass *ypop* as YPOP_STORE and no error will be returned if the key already or does not exist. To delete an entry, the value of *ypop* should be YPOP_DELETE.

This routine depends upon secure RPC, and will not work unless the network is running secure RPC.

Return Values If the value of *ypop* is POP_CHANGE, yp_update() returns the error YPERR_KEY if the key is not found in the database.

If the value of *ypop* is POP_INSERT, yp_update() returns the error YPERR_KEY if the key already exists in the database.

Attributes See [attributes\(5\)](#) for descriptions of the following attributes:

ATTRIBUTE TYPE	ATTRIBUTE VALUE
MT-Level	Unsafe

See Also [secure_rpc\(3NSL\)](#), [ypclnt\(3NSL\)](#), [attributes\(5\)](#)

Notes This interface is unsafe in multithreaded applications. Unsafe interfaces should be called only from the main thread.

