

Trusted Extensions Developer's Guide

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT END USERS. Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Ce logiciel et la documentation qui l'accompagne sont protégés par les lois sur la propriété intellectuelle. Ils sont concédés sous licence et soumis à des restrictions d'utilisation et de divulgation. Sauf disposition de votre contrat de licence ou de la loi, vous ne pouvez pas copier, reproduire, traduire, diffuser, modifier, breveter, transmettre, distribuer, exposer, exécuter, publier ou afficher le logiciel, même partiellement, sous quelque forme et par quelque procédé que ce soit. Par ailleurs, il est interdit de procéder à toute ingénierie inverse du logiciel, de le désassembler ou de le décompiler, excepté à des fins d'interopérabilité avec des logiciels tiers ou tel que prescrit par la loi.

Les informations fournies dans ce document sont susceptibles de modification sans préavis. Par ailleurs, Oracle Corporation ne garantit pas qu'elles soient exemptes d'erreurs et vous invite, le cas échéant, à lui en faire part par écrit.

Si ce logiciel, ou la documentation qui l'accompagne, est concédé sous licence au Gouvernement des Etats-Unis, ou à toute entité qui délivre la licence de ce logiciel ou l'utilise pour le compte du Gouvernement des Etats-Unis, la notice suivante s'applique:

U.S. GOVERNMENT END USERS. Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

Ce logiciel ou matériel a été développé pour un usage général dans le cadre d'applications de gestion des informations. Ce logiciel ou matériel n'est pas conçu ni n'est destiné à être utilisé dans des applications à risque, notamment dans des applications pouvant causer des dommages corporels. Si vous utilisez ce logiciel ou matériel dans le cadre d'applications dangereuses, il est de votre responsabilité de prendre toutes les mesures de secours, de sauvegarde, de redondance et autres mesures nécessaires à son utilisation dans des conditions optimales de sécurité. Oracle Corporation et ses affiliés déclinent toute responsabilité quant aux dommages causés par l'utilisation de ce logiciel ou matériel pour ce type d'applications.

Oracle et Java sont des marques déposées d'Oracle Corporation et/ou de ses affiliés. Tout autre nom mentionné peut correspondre à des marques appartenant à d'autres propriétaires qu'Oracle.

Intel et Intel Xeon sont des marques ou des marques déposées d'Intel Corporation. Toutes les marques SPARC sont utilisées sous licence et sont des marques ou des marques déposées de SPARC International, Inc. AMD, Opteron, le logo AMD et le logo AMD Opteron sont des marques ou des marques déposées d'Advanced Micro Devices. UNIX est une marque déposée d'The Open Group.

Ce logiciel ou matériel et la documentation qui l'accompagne peuvent fournir des informations ou des liens donnant accès à des contenus, des produits et des services émanant de tiers. Oracle Corporation et ses affiliés déclinent toute responsabilité ou garantie expresse quant aux contenus, produits ou services émanant de tiers. En aucun cas, Oracle Corporation et ses affiliés ne sauraient être tenus pour responsables des pertes subies, des coûts occasionnés ou des dommages causés par l'accès à des contenus, produits ou services tiers, ou à leur utilisation.

Contents

Preface	9
1 Trusted Extensions APIs and Security Policy	13
Understanding Labels	13
Label Types	14
Label Ranges	14
Label Components	15
Label Relationships	15
Trusted Extensions APIs	17
Label APIs	18
Trusted X Window System APIs	20
Label Builder APIs	21
Trusted Extensions Security Policy	21
Multilevel Operations	22
Zones and Labels	25
2 Labels and Clearances	27
Privileged Operations and Labels	27
Label APIs	29
Detecting a Trusted Extensions System	29
Accessing the Process Sensitivity Label	30
Allocating and Freeing Memory for Labels	30
Obtaining and Setting the Label of a File	31
Obtaining Label Ranges	32
Accessing Labels in Zones	32
Obtaining the Remote Host Type	34
Translating Between Labels and Strings	34

Comparing Labels	35
Acquiring a Sensitivity Label	37
3 Label Code Examples	41
Obtaining a Process Label	41
Obtaining a File Label	42
Setting a File Sensitivity Label	43
Determining the Relationship Between Two Labels	44
Obtaining the Color Names of Labels	45
Obtaining Printer Banner Information	46
4 Printing and the Label APIs	49
Printing Labeled Output	49
Designing a Label-Aware Application	50
Understanding the Multilevel Printing Service	50
get_peer_label() Label-Aware Function	51
Determining Whether the Printing Service Is Running in a Labeled Environment	52
Understanding the Remote Host Credential	53
Obtaining the Credential and Remote Host Label	53
Using the label_to_str() Function	53
Handling Memory Management	54
Using the Returned Label String	55
Validating the Label Request Against the Printer's Label Range	55
5 Interprocess Communications	59
Multilevel Port Information	59
Communication Endpoints	60
Berkeley Sockets and TLI	61
RPC Mechanism	62
Using Multilevel Ports With UDP	63
6 Trusted X Window System	67
Trusted X Window System Environment	67
Trusted X Window System Security Attributes	68

Trusted X Window System Security Policy	69
Root Window	70
Client Windows	70
Override-Redirect Windows	70
Keyboard, Pointer, and Server Control	70
Selection Manager	70
Default Window Resources	71
Moving Data Between Windows	71
Privileged Operations and the Trusted X Window System	71
Trusted Extensions X Window System APIs	72
Data Types for X11	73
Accessing Attributes	73
Accessing and Setting a Window Label	74
Accessing and Setting a Window User ID	74
Accessing and Setting a Window Property Label	74
Accessing and Setting a Window Property User ID	75
Accessing and Setting a Workstation Owner ID	75
Setting the X Window Server Clearance and Minimum Label	75
Working With the Trusted Path Window	76
Accessing and Setting the Screen Stripe Height	76
Setting Window Polyinstantiation Information	77
Working With the X11 Label-Clipping Interface	77
Using Trusted X Window System Interfaces	77
Obtaining Window Attributes	78
Translating the Window Label With the Font List	78
Obtaining a Window Label	79
Setting a Window Label	79
Obtaining the Window User ID	80
Obtaining the X Window Server Workstation Owner ID	80
7 Label Builder APIs	81
APIs for Label Builder GUIs	81
Creating an Interactive User Interface	82
Label Builder Behavior	85
Application-Specific Functionality for Label Builder	86

Privileged Operations and Label Builder	87
tsol_lbuild_create() Routine	87
Extended Label Builder Operations	88
ModLabelData Structure	89
Online Help for Label Builder	90
8 Trusted Web Guard Prototype	91
Administrative Web Guard Prototype	91
Modifying the label_encodings File	93
Configuring Trusted Networking	95
Configuring the Apache Web Servers	97
Running the Trusted Web Guard Demonstration	98
Accessing Lower-Level Untrusted Servers	98
9 Experimental Java Bindings for the Solaris Trusted Extensions Label APIs	101
Java Bindings Overview	101
Structure of the Experimental Java Label Interfaces	102
SolarisLabel Abstract Class	102
Range Class	104
Java Bindings	104
Detecting a Trusted Extensions System	105
Accessing the Process Sensitivity Label	105
Allocating and Freeing Memory for Label Objects	105
Obtaining and Setting the Label of a File	105
Obtaining Label Range Objects	107
Accessing Labels in Zones	108
Obtaining the Remote Host Type	109
Translating Between Labels and Strings	109
Comparing Label Objects	112
A Programmer's Reference	115
Header File Locations	115
Abbreviations Used in Interface Names and Data Structure Names	116
Developing, Testing, and Debugging an Application	117

Releasing an Application	117
Creating a CDE Action	118
Creating a Software Package	118
B Trusted Extensions API Reference	119
Process Security Attribute Flags APIs	119
Label APIs	119
Label-Clipping APIs	121
RPC APIs	121
Label Builder APIs	121
Trusted X Window System APIs	121
Oracle Solaris Library Routines and System Calls That Use Trusted Extensions Parameters ..	122
System Calls and Library Routines in Trusted Extensions	123
Index	127

Preface

The *Trusted Extensions Developer's Guide* describes how to use the application programming interfaces (APIs) to write new trusted applications for systems that are configured with the Trusted Extensions feature of the Oracle Solaris OS. Readers must be familiar with UNIX programming and understand security policy concepts.

Note – This Oracle Solaris release supports systems that use the SPARC and x86 families of processor architectures. The supported systems appear in the *Oracle Solaris OS: Hardware Compatibility Lists*. This document cites any implementation differences between the platform types.

In this document, these x86 related terms mean the following:

- x86 refers to the larger family of 64-bit and 32-bit x86 compatible products.
- x64 relates specifically to 64-bit x86 compatible CPUs.
- "32-bit x86" points out specific 32-bit information about x86 based systems.

For supported systems, see the *Oracle Solaris OS: Hardware Compatibility Lists*.

Note that the example programs in this book focus on the APIs being shown and do not perform error checking. Your applications should perform the appropriate error checking.

How the Trusted Extensions Books Are Organized

The Trusted Extensions documentation set supplements the documentation for the Oracle Solaris release. Review both sets of documentation for a more complete understanding of Trusted Extensions. The Trusted Extensions documentation set consists of the following books.

Book Title	Topics	Audience
<i>Solaris Trusted Extensions Transition Guide</i>	Obsolete. Provides an overview of the differences between Trusted Solaris 8 software, Oracle Solaris software, and Trusted Extensions software. For this release, the <i>What's New</i> document for the Oracle Solaris OS provides an overview of Trusted Extensions changes.	All
<i>Solaris Trusted Extensions Reference Manual</i>	Obsolete. Provides Trusted Extensions man pages for the Solaris 10 11/06 and Solaris 10 8/07 releases of Trusted Extensions. For this release, Trusted Extensions man pages are included with the Oracle Solaris man pages.	All
<i>Trusted Extensions User's Guide</i>	Describes the basic features of Trusted Extensions. This book contains a glossary.	End users, administrators, developers
<i>Trusted Extensions Configuration Guide</i>	Starting with the Solaris 10 5/08 release, describes how to enable and initially configure Trusted Extensions. Replaces <i>Solaris Trusted Extensions Installation and Configuration</i> .	Administrators, developers
<i>Trusted Extensions Administrator's Procedures</i>	Shows how to perform specific administration tasks.	Administrators, developers
<i>Trusted Extensions Developer's Guide</i>	Describes how to develop applications with Trusted Extensions.	Developers, administrators
<i>Trusted Extensions Label Administration</i>	Provides information about how to specify label components in the label encodings file.	Administrators
<i>Compartmented Mode Workstation Labeling: Encodings Format</i>	Describes the syntax used in the label encodings file. The syntax enforces the various rules for well-formed labels for a system.	Administrators

How This Book Is Organized

[Chapter 1, “Trusted Extensions APIs and Security Policy,”](#) provides an overview of the Trusted Extensions APIs and describes how the security policy is enforced within the system.

[Chapter 2, “Labels and Clearances,”](#) describes the data types and the APIs for managing labels on processes and on device objects. This chapter also describes clearances, how a process acquires a sensitivity label, and when label operations require privileges. Guidelines for handling labels are also provided.

[Chapter 3, “Label Code Examples,”](#) provides sample code that uses the APIs for labels.

[Chapter 4, “Printing and the Label APIs,”](#) uses the Trusted Extensions multilevel printing service as an example of using the label APIs.

Chapter 5, “Interprocess Communications,” provides an overview of how the security policy is applied to process-to-process communications within the same workstation and across the network.

Chapter 6, “Trusted X Window System,” describes the data types and the APIs that enable administrative applications to access and modify security-related X Window System information. This chapter has a section of code examples.

Chapter 7, “Label Builder APIs,” describes the data types and the APIs for creating a graphical user interface (GUI) for building labels and clearances. This chapter has a section of code examples.

Chapter 8, “Trusted Web Guard Prototype,” provides an example of a safe web browsing prototype that isolates a web server and its web content from an Internet attack.

Chapter 9, “Experimental Java Bindings for the Solaris Trusted Extensions Label APIs,” describes an experimental set of Java classes and methods that mirror the label APIs that are provided with the Trusted Extensions software. This chapter also includes a pointer to the source code and build instructions, so you can use these APIs to create label-aware applications.

Appendix A, “Programmer’s Reference,” provides information about Trusted Extensions man pages, shared libraries, header files, and abbreviations used in data type names and in interface names. This appendix also provides information about preparing an application for release.

Appendix B, “Trusted Extensions API Reference,” provides programming interface listings, including parameter and return value declarations.

Access to Oracle Support

Oracle customers have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Typographic Conventions

The following table describes the typographic conventions that are used in this book.

TABLE P-1 Typographic Conventions

Typeface	Description	Example
AaBbCc123	The names of commands, files, and directories, and onscreen computer output	Edit your <code>.login</code> file. Use <code>ls -a</code> to list all files. <code>machine_name% you have mail.</code>

TABLE P-1 Typographic Conventions (Continued)

Typeface	Description	Example
AaBbCc123	What you type, contrasted with onscreen computer output	machine_name% su Password:
<i>aabbcc123</i>	Placeholder: replace with a real name or value	The command to remove a file is <i>rm filename</i> .
<i>AaBbCc123</i>	Book titles, new terms, and terms to be emphasized	Read Chapter 6 in the <i>User's Guide</i> . <i>A cache</i> is a copy that is stored locally. Do <i>not</i> save the file. Note: Some emphasized items appear bold online.

Shell Prompts in Command Examples

The following table shows UNIX system prompts and superuser prompts for shells that are included in the Oracle Solaris OS. In command examples, the shell prompt indicates whether the command should be executed by a regular user or a user with privileges.

TABLE P-2 Shell Prompts

Shell	Prompt
Bash shell, Korn shell, and Bourne shell	\$
Bash shell, Korn shell, and Bourne shell for superuser	#
C shell	machine_name%
C shell for superuser	machine_name#

Trusted Extensions APIs and Security Policy

The Trusted Extensions feature of the Oracle Solaris OS (Trusted Extensions) provides application programming interfaces (APIs) that enable you to write applications that access and handle labels. This chapter summarizes the API functionality and introduces you to the Trusted Extensions security policy.

For Trusted Extensions term definitions, see the glossary in the *Trusted Extensions User's Guide*.

This chapter covers the following topics:

- “Understanding Labels” on page 13
- “Trusted Extensions APIs” on page 17
- “Trusted Extensions Security Policy” on page 21

Understanding Labels

The Trusted Extensions software provides a set of policies and services to extend the security features of the Oracle Solaris OS. These *extensions* provide access control that is based on label relationships.

Labels control access to data and maintain the classification of data. The labels are attributes that are interpreted by the system security policy. The *system security policy* is the set of rules that is enforced by system software to protect information that is being processed on the system. The term *security policy* can refer to the policy itself or to the implementation of the policy. For more information, see “Trusted Extensions Security Policy” on page 21.

This section includes overview information about label types, ranges, components, and relationships.

Label Types

The Trusted Extensions software defines two types of labels: sensitivity labels and clearance labels. A *sensitivity label* indicates the security level of an entity and is usually referred to as a *label*. A *clearance label* defines the upper boundary of a label range and is usually referred to as a *clearance*.

Sensitivity Labels

The Trusted Extensions software uses zones to contain classified information at various levels. Each level is associated with its own zone that has a sensitivity label. The sensitivity label specifies the sensitivity of the information in that zone and is applied to all of the subjects and objects in that zone. A label might be something like CONFIDENTIAL, SECRET, or TOP SECRET. A *subject* is an active entity, such as a process, that causes information to flow among objects or changes a system's state. An *object* is a passive entity that contains or receives data, such as a file or device. All processes that run in a zone, all files that are contained in a zone, and so on, have the same sensitivity label as their zone. All processes and objects have a sensitivity label that is used in mandatory access control (MAC) decisions. By default, sensitivity labels are visible in the windowing system.

Clearance Labels

The security administrator assigns a clearance to each user. A clearance is a label that defines the upper boundary of a label range. For example, if you have a clearance of SECRET, you can access information that is classified at this level or lower, but not information that is classified at a higher level. A *user clearance* is assigned by the security administrator. It is the highest label at which a user can access files and initiate processes during a session. In other words, a user clearance is the upper boundary of a user's account label range. At login, a user selects his session clearance. The *session clearance* determines which labels a user can access. The session clearance sets the *least upper bound* at which the user can access files and initiate processes during that login session. The session clearance is dominated by the user clearance.

Label Ranges

The security administrator defines label ranges and label sets to enforce *mandatory access control* (MAC) policy. A *label range* is a set of labels that is bounded at the upper end by a clearance or a limit and at the lower end by a minimum label. A *label limit* is the upper bound of a label range. A *label set* contains one or more discrete labels that might be disjoint from one another. Labels in a label set do not dominate one another.

Label Components

A label contains a hierarchical classification and a set of zero or more nonhierarchical compartments. A classification is also referred to as a *level* or a security level. A *classification* represents a single level within a hierarchy of labels, for example, TOP SECRET or UNCLASSIFIED. A *compartment* is associated with a classification and represents a distinct, nonhierarchical area of information in a system, such as private information for a human resources (HR) group or a sales group. A compartment limits access only to users who need to know the information in a particular area. For example, a user with a SECRET classification only has access to the secret information that is specified by the associated list of compartments, not to any other secret information. The classification and compartments together represent the label of the zone and the resources within that zone.

The textual format of a classification is specified in the `label_encodings` file and appears similar to this:

```
CLASSIFICATIONS:
name= CONFIDENTIAL; sname= C; value= 4; initial compartments= 4-5 190-239;
name= REGISTERED; sname= REG; value= 6; initial compartments= 4-5 190-239;
```

The textual format of a compartment is specified in the `label_encodings` file and appears similar to this:

```
WORDS:
name= HR; minclass= C; compartments= 0;
```

For more information about label definitions and label formats, see [Trusted Extensions Label Administration](#) and [Compartmented Mode Workstation Labeling: Encodings Format](#). For information about the label APIs, see [Chapter 2, “Labels and Clearances.”](#)

Label Relationships

Comparing labels means that the label of a process is compared to the label of a target, which might be a sensitivity label or a clearance label. Based on the result of the comparison, the process is either granted access or denied access to the object. Access is granted only when the label of the process dominates the label of the target. Label relationships and dominance are described later in this section. For examples, see [“Determining the Relationship Between Two Labels” on page 44.](#)

A *security level* is a numerical classification. A label indicates the security level of an entity and might include zero or more compartments. An entity is something that can be labeled, such as a process, zone, file, or device.

Labels are of the following types and relate to each other in these ways:

- - **Equal** – When one label is equal to another label, both of these statements are true:
 - The label's classification is numerically *equal to* the other label's classification.
 - The label has exactly the same compartments as the other label.
- - **Dominant** – When one label dominates another label, both of these statements are true:
 - The label's classification is numerically *greater than or equal to* the other label's classification.
 - The label has exactly the same compartments as the other label.
- - **Strictly dominant** – When one label strictly dominates another label, both of these statements are true:
 - The label's classification is numerically *greater than or equal to* the other label's classification.
 - The label has all the compartments that the other label has and at least one other compartment.
- - **Disjoint** – When one label is disjoint with another label, both of these statements are true:
 - The labels are not equal.
 - Neither label dominates the other label.

The `label_encodings` file is used to specify the classifications and compartments for labels. See the [label_encodings\(4\)](#) man page.

When any type of label has a security level that is equal to or greater than the security level of a second label, the first label is said to *dominate* the second label. This comparison of security levels is based on classifications and compartments in the labels. The classification of the dominant label must be equal to or greater than the classification of the second label. Additionally, the dominant label must include all the compartments in the second label. Two equal labels are said to dominate each other.

In the following sample excerpt of the `label_encodings` file, the REGISTERED (REG) label dominates the CONFIDENTIAL (C) label. The comparison is based on the value of each label's `value` keyword. The value of the REG label's `value` keyword is numerically greater than or equal to the value of the C label's `value` keyword. Both labels dominate the PUBLIC (P) label.

The value of the `initial` `compartments` keyword shows the list of compartments that are initially associated with the classification. Each number in the `initial` `compartments` keyword is a *compartment bit*, each of which represents a particular compartment.


```

CLASSIFICATIONS:
name= PUBLIC; sname= P; value= 1;
name= CONFIDENTIAL; sname= C; value= 4; initial compartments= 4-5 190-239;
name= REGISTERED; sname= REG; value= 6; initial compartments= 4-5 190-239;

```

The following `label_encodings` excerpt shows that the REG HR label (Human Resources) dominates the REG label. The REG HR label has the REGISTERED classification and the HR compartment. The `compartments` keyword for the HR compartment sets the 0 compartment bit, so the REG HR classification has compartments 0, 4–5, and 190–239 set, which is more than the compartments set by the REG classification.

```

CLASSIFICATIONS:
name= REGISTERED; sname= REG; value= 6; initial compartments= 4-5 190-239;
...
WORDS:
name= HR; minclass= C; compartments= 0;

```

Sometimes, strict dominance is required to access an object. In the previous examples, the REG label strictly dominates the P label, and the REG HR label strictly dominates the REG label. When comparing labels, a REG label dominates another REG label.

Labels that do not dominate each other are said to be disjoint. A *disjoint* label might be used to separate departments in a company. In the following example, the REG HR label (Human Resources) is defined as being disjoint from the REG Sales label. These labels are disjoint because each compartment sets a different compartment bit.

```

CLASSIFICATIONS:
name= REGISTERED; sname= REG; value= 6; initial compartments= 4-5 190-239;
...
WORDS:
name= HR; minclass= C; compartments= 0;
name= Sales; minclass= C; compartments= 1;

```

For information about label APIs, see [“Sensitivity Label APIs” on page 19](#).

Trusted Extensions APIs

This section introduces the following Trusted Extensions APIs that are described in this book:

- Label APIs
- Trusted X Window System APIs
- Label Builder APIs

In addition to these Trusted Extensions APIs, you can use the security APIs that are available with the Oracle Solaris OS. An application that runs on Trusted Extensions might require the manipulation of other security attributes. For example, the user and profile databases contain information about users, roles, authorizations, and profiles. These databases can restrict who can run a program. Privileges are coded into various Oracle Solaris programs and can also be coded into third-party applications.

For more information about these Oracle Solaris OS security APIs, see [Chapter 2, “Developing Privileged Applications,”](#) in *Developer’s Guide to Oracle Solaris 10 Security*.

The Oracle Solaris OS provides *discretionary access control* (DAC), in which the owner of the data determines who is permitted access to the data. The Trusted Extensions software provides additional access control, which is called mandatory access control (MAC). In MAC, ordinary users cannot specify or override the *security policy*. The security administrator sets the security policy.

Applications use Trusted Extensions APIs to obtain labels for hosts, zones, users, and roles. Where the security policy permits, the APIs enable you to set labels on user processes or on role processes. Setting a label on a zone or on a host is an administrative procedure, not a programmatic procedure.

You can write applications to customize window labels. The Trusted Extensions software provides Motif based programming interfaces for adding a basic label-building user interface to an application. The label-building interface enables a user to interactively build valid sensitivity labels and valid clearances.

The label APIs operate on opaque labels. In an *opaque label*, the internal structure of the label is not exposed. Using an opaque label enables existing programs that are created with the APIs to function even if the internal structure of the label changes. For example, you cannot use the label APIs to locate particular bits in a label. The label APIs enable you to obtain labels and to set labels. You can only set labels if you are permitted to do so by the security policy.

Label APIs

Labels, label ranges, and a label limit determine who can access information on a system that is configured with Trusted Extensions.

The label APIs are used to access, convert, and perform comparisons for labels, label ranges and limits, and the relationship between labels. A label can dominate another label, or a label can be disjoint from another label.

The `label_encodings` file defines the sensitivity labels, clearance labels, label ranges, and label relationships that pertain to your Trusted Extensions environment. This file also controls the appearance of labels. The security administrator is responsible for creating and maintaining the `label_encodings` file. See the [label_encodings\(4\)](#) man page.

The label of a process is determined by the zone in which the process executes.

All objects are associated with a label or sometimes with a label range. An object can be accessed at a particular label within the defined label range. The objects that are associated with a label range include the following:

- All users and all roles
- All hosts with which communications are permitted
- Zone interfaces and network interfaces
- Allocatable devices, such as tape drives, diskette drives, CD-ROM devices, and audio devices
- Other devices that are not allocatable, such as printers and workstations

Workstation access is controlled by the label range that is set for the frame buffer or video display device. The security administrator sets this range by using the Device Manager GUI. By default, devices have a range from ADMIN_LOW to ADMIN_HIGH.

For more information about labels, see [“Label Types” on page 14](#).

How Labels Are Used in Access Control Decisions

MAC compares the label of the process that is running an application with the label or the label range of any object that the process tries to access. MAC permits a process to read down to a lower label and permits a process to write to an equal label.

`Label[Process] >= Label[Object]`

A process bound to a multilevel port (MLP) can listen for requests at multiple labels and send replies to the originator of the request. In Trusted Extensions, such replies are write-equal.

`Label[Process] = Label[Object]`

Types of Label APIs

Sensitivity Label APIs

Sensitivity label APIs can be used to do the following:

- Obtain a process label
- Initialize labels
- Find the greatest lower bound or the least upper bound between two labels
- Compare labels for dominance and equality
- Check and set label types
- Convert labels to a readable format
- Obtain information from the `label_encodings` file
- Check that a sensitivity label is valid and within the system range

For a description of these APIs, see [Chapter 2, “Labels and Clearances.”](#)

Clearance Label APIs

Users, devices, and network interfaces have label ranges. The upper bound of the range is effectively the clearance. If the upper bound of the range and the lower bound of the range are equal, the range is a single label.

Clearance label APIs can be used to do the following:

- Find the greatest lower bound or the least upper bound between two labels
- Compare labels for dominance and equality
- Convert clearances between the internal format and the hexadecimal format

For a description of these APIs, see [Chapter 2, “Labels and Clearances.”](#)

Label Range APIs

A label range is used to set limits on the following:

- The labels at which hosts can send and receive information
- The labels at which processes acting on behalf of users and roles can work on the system
- The labels at which users can allocate devices

This use of a label range restricts the labels at which files can be written to storage media on these devices.

Label ranges are assigned administratively. Label ranges can apply to users, roles, hosts, zones, network interfaces, printers, and other objects.

You can use the following methods to obtain information about label ranges:

- `getuserrange()` obtains the user's label range.
- `getdevicerange()` obtains the label range of a device.
- `tninfo -t template-name` shows the label range of a template that is associated with a network interface.

For a description of these APIs, see [Chapter 2, “Labels and Clearances.”](#)

Trusted X Window System APIs

The Trusted X Window System, Version 11, server starts at login. The server handles the workstation windowing system by using a trusted interprocess communication (IPC) path. Windows, properties, selections, and ToolTalk sessions are created at multiple sensitivity labels as separate and distinct objects. The creation of distinct objects at multiple sensitivity labels is called *polyinstantiation*. Applications that are created with Motif widgets, Xt Intrinsics, Xlib, and desktop interfaces run within the constraints of the security policy. These constraints are enforced by extensions to the X11 protocols.

[Chapter 6, “Trusted X Window System,”](#) describes the programming interfaces that can access the security attribute information described in [“Trusted Extensions Security Policy” on page 21](#). These programming interfaces can also be used to translate the labels and clearances to text. The text can be constrained by a specified width and font list for display in the Trusted X Window System.

The Trusted X Window System stores the following security attributes:

Audit ID	Trusted Path flag
Group ID	Trusted Path window
Internet address	User ID
Process ID	X Window Server owner ID
Sensitivity label	X Window Server clearance
Session ID	X Window Server minimum label

The Trusted Path flag identifies a window as a Trusted Path window. The Trusted Path window protects the system from being accessed by untrusted programs. This window is always the toplevel window, such as the screen stripe or login window.

[Appendix B, “Trusted Extensions API Reference,”](#) lists the extensions that you can use to create an X11 trusted IPC path.

Label Builder APIs

The Trusted Extensions software provides a label builder API that enables you to create a graphical user interface (GUI) for your application. The GUI takes user input and builds a valid label from that input.

A system that is configured with Trusted Extensions provides Motif-based programming interfaces for adding a basic label-building user interface to an application. The label-building interface enables a user to interactively build valid sensitivity labels and valid clearances. For information about these programming interfaces, see [Chapter 7, “Label Builder APIs.”](#)

Trusted Extensions Security Policy

Sensitivity labels control access to data and maintain the classification of data. All processes and objects have a sensitivity label that is used in MAC decisions. The labels are attributes that are interpreted by the system security policy. The *system security policy* is the set of rules that is enforced by system software to protect information being processed on the system.

The following sections describe how the Trusted Extensions security policy affects multilevel operations, zones, and labels.

Multilevel Operations

When you create an operation that runs at multiple security levels, you must consider the following issues:

- Write-down policy in the global zone
- Default security attributes
- Default network policy
- Multilevel ports
- MAC-exempt sockets

Operations that run at multiple security levels are controlled by the global zone because only processes in the global zone can initiate processes at specified labels.

Write-Down Policy in the Global Zone

The ability of a subject, such as a process, to write an object whose label it dominates is referred to as *writing down*. The write-down policy in the global zone is specified administratively. Because global zone processes run at the ADMIN_HIGH label, certain file systems that are associated with other labels can be mounted read-write in the global zone. However, these special file system mounts must be administratively specified in automount maps, and they must be mounted by the global zone automounter. These mounts must have mount points within the zone path of the zone that has the same label as the exported file system. However, these mount points must not be visible from within the labeled zone.

For example, if the PUBLIC zone has a zone path of /zone/public, a writable mount point of /zone/public/home/mydir is permitted. However, a writable mount point of /zone/public/root/home/mydir is not permitted because it can be accessed by the labeled zone and *not* by the global zone. No cross-zone NFS mounts are permitted, which means that the NFS-mounted files can only be accessed by processes that run in the zone that mounted the file system. Global zone processes can write down to such files, subject to the standard discretionary access control (DAC) policy.

Local file systems associated with zones are protected from access by global zone processes by DAC, which uses file *permissions* and access control lists (ACLs). The parent directory of each zone's root (/) directory is only accessible by root processes or by processes that assert the file_dac_search privilege.

In general, the ability to write down from the global zone is restricted. Typically, writing down is used only when a file is reclassified by using the setflabel() interface or when privileged users drag and drop files between File Manager applications in different zones.

Default Security Attributes

Default security attributes are assigned to messages that arrive on Trusted Extensions hosts from other *host types*. The attributes are assigned according to settings in the network database

files. For information about host types, their supported security attributes, and network database file defaults, see *Trusted Extensions Administrator's Procedures*.

Default Network Policy

For network operations that send or receive data, the default policy is that the local process and the remote peer must have the same label. This policy applies to all zones, including the global zone, whose network label is ADMIN_LOW. However, the default network policy is more flexible than the policy for mounting file systems. Trusted Extensions provides administrative interfaces and programmatic interfaces for overriding the default network policy. For example, a system administrator can create an MLP in the global zone or in a labeled zone to enable listening at different labels.

Multilevel Ports



Caution – Use extreme caution when using a multilevel port to violate MAC policy. When you must use this mechanism, ensure that your server application enforces MAC policy.

Multilevel ports (MLPs) are listed in the `tnzonecfg` administrative database. Processes within the zone can bind to MLPs if these processes assert the `net_bindmlp` privilege. If the port number is less than 1024, the `net_privaddr` privilege must also be asserted. Such bindings allow a process to accept connections at all labels that are associated with the IP addresses to which the process is bound. The labels that are associated with a network interface are specified in the `tnrddb` database and the `tnrhtp` database. The labels can be specified by a range, by a set of explicit enumerated labels, or by a combination of both.

When a privileged process that is bound to an MLP receives a TCP request, the reply is automatically sent with the label of the requester. For UDP datagrams, the reply is sent with the label that is specified by the `SO_RECVUCRED` option.

The privileged process can implement a more restrictive MAC policy by comparing the label of the request to other parameters. For example, a web server could compare the label of the requesting process with the label of the file specified in the URL. The remote label can be determined by using the `getpeerucred()` function, which returns the credentials of the remote peer. If the peer is running in a zone on the same host, the `ucred_get()` library routine returns a full set of credentials. Regardless of whether the peer is local or remote, the label of the peer is accessible from the `ucred` data structure by using the `ucred_getlabel()` function. This label can be compared with other labels by using functions such as `bl dominates()`.

A zone can have single-level ports and multilevel ports. See “[Multilevel Port Information](#)” on page 59.

MAC-Exempt Sockets

The Trusted Extensions software provides an explicit socket option, `SO_MAC_EXEMPT`, to specify that the socket can be used to communicate with an endpoint at a lower label.



Caution – The `SO_MAC_EXEMPT` socket option must *never* be used unintentionally. Use extreme caution when using this socket option to disable MAC policy. When you must use this mechanism, ensure that your client application enforces MAC policy.

The Trusted Extensions software restricts the use of the `SO_MAC_EXEMPT` option in these ways:

- To explicitly set the socket option, a process must assert the `net_mac_aware` privilege.
- To further restrict the use of this socket option, the `net_mac_aware` privilege can be removed from the limit set for ordinary users.

See the [user_attr\(4\)](#) man page for details.

Sometimes, explicitly setting the socket option is not practical, such as when the socket is managed by a library. In such circumstances, the socket option can be set implicitly. The `setpflags()` system call enables you to set the `NET_MAC_AWARE` process flag. Setting this process flag also requires the `net_mac_aware` privilege. All sockets that are opened while the process flag is enabled automatically have the `SO_MAC_EXEMPT` socket option set. See the [setpflags\(2\)](#) and [getpflags\(2\)](#) man pages.

For applications that cannot be modified or recompiled, use the `ppriv -M` command to pass the `net_mac_aware` process flag to the application. In this case, all sockets that are opened by the application have the `SO_MAC_EXEMPT` option set. However, child processes of the application do not have this process flag or the related privilege.

Whenever you can, scrutinize and modify the source code of an application when you need to use the `SO_MAC_EXEMPT` socket option. If you *cannot* make such modifications to the code or if a safer method is not available to you, you may use the `ppriv -M` command.

The `SO_MAC_EXEMPT` socket option has been used sparingly by the Oracle Solaris OS. This option has been used by the NFS client. An NFS client might need to communicate with an NFS server that runs at a different label on an untrusted operating system. The NFS client enforces MAC policy to ensure that inappropriate requests are not granted.

In the Oracle Solaris OS, both the NFS server and client code include and enforce MAC policy so that communications between the Oracle Solaris client or server and an untrusted client or server has MAC policy enabled. To enable an untrusted host to communicate with a system that runs Trusted Extensions, the untrusted host must have an entry in the `tnrhdb` database. For more information, see “[Configuring Trusted Network Databases \(Task Map\)](#)” in *Trusted Extensions Administrator’s Procedures*.

Zones and Labels

All objects on a system configured with Trusted Extensions are associated with a zone. Such zones are called *labeled zones*. A labeled zone is a non-global zone and is accessible to ordinary users. A user who is cleared at more than one label is permitted access to a zone at each of those labels.

The *global zone* is a special zone that contains files and processes that control the security policy of the system. Files in the global zone can only be accessed by roles and by privileged processes.

Labels in the Global Zone

The global zone is assigned a range of labels. The range is from ADMIN_LOW to ADMIN_HIGH. ADMIN_HIGH and ADMIN_LOW are *administrative labels*.

Objects in the global zone that are shared with other zones are assigned the ADMIN_LOW label. For example, files in the /usr, /sbin, and /lib directories are assigned the ADMIN_LOW label. These directories and their contents are shared by all zones. These files and directories are typically installed from packages and are generally not modified, except during packaging or patching procedures. To modify ADMIN_LOW files, a process must typically be run by superuser or by someone who has all privileges.

Information that is private to the global zone is assigned the label ADMIN_HIGH. For example, all processes in the global zone and all administrative files in the /etc directory are assigned the ADMIN_HIGH label. Home directories that are associated with roles are assigned the ADMIN_HIGH label. Multilevel information that is associated with users is also assigned the ADMIN_HIGH label. See [“Multilevel Operations” on page 22](#). Access to the global zone is restricted. Only system services and administrative roles can execute processes in the global zone.

Labeled Zones

Non-global zones are called *labeled zones*. Each labeled zone has a unique label. All objects within a labeled zone have the same label. For example, all processes that run in a labeled zone have the same label. All files that are writable in a labeled zone have the same label. A user who is cleared for more than one label has access to a labeled zone at each label.

Trusted Extensions defines a set of label APIs for zones. These APIs obtain the labels that are associated with labeled zones and the path names within those zones:

- `getpathbylabel()`
- `getzoneidbylabel()`
- `getzonelabelbyid()`
- `getzonelabelbyname()`
- `getzonerootbyid()`
- `getzonerootbylabel()`
- `getzonerootbyname()`

For more information about these APIs, see [“Accessing Labels in Zones” on page 32](#).

The label of a file is based on the label of the zone or of the host that owns the file. Therefore, when you relabel a file, the file must be moved to the appropriate labeled zone or to the appropriate labeled host. This process of relabeling a file is also referred to as *reclassifying* a file. The `setflabel()` library routine can relabel a file by moving the file. To relabel a file, a process must assert the `file_upgrade_sl` privilege or the `file_downgrade_sl` privilege. See the [`getlabel\(2\)`](#) and [`setflabel\(3TSOL\)`](#) man pages.

For more information about setting privileges, see [Chapter 2, “Developing Privileged Applications,” in *Developer’s Guide to Oracle Solaris 10 Security*](#).

Labels and Clearances

This chapter describes the Trusted Extensions APIs for performing basic label operations such as initializing labels, and comparing labels and clearances. This chapter also describes the APIs for accessing the label of a process.

This chapter covers the following topics:

- “Privileged Operations and Labels” on page 27
- “Label APIs” on page 29
- “Acquiring a Sensitivity Label” on page 37

Chapter 3, “Label Code Examples,” provides code examples for the programming interfaces that are described in this chapter.

Privileged Operations and Labels

When an operation can bypass or override the security policy, the operation requires special privileges in its effective set.

Privileges are added to the effective set programmatically or administratively in these ways:

- If the executable file is owned by `root` and has the set user ID permission bit set, it starts with all privileges in its effective set. For example, the CDE File Manager starts with all privileges in its effective set. Then, File Manager programmatically relinquishes most of its privileges to retain only the ones it needs to perform drag-and-drop operations across labels.
- The administrator can specify privileges in manifest files for SMF services or in the RBAC database `exec_attr` file for general commands. For more information about this file, see the [exec_attr\(4\)](#) man page.

The operation needs special privileges when translating binary labels and when upgrading or downgrading sensitivity labels.

Users and roles can run operations with special privileges. These privileges can be specified by using *rights profiles*. Applications can be written to run certain functions with certain privileges, as well. When you write an application that must assume special privileges, make sure that you enable the privilege only while running the function that needs it and that you remove the privilege when the function completes. This practice is referred to as *privilege bracketing*. For more information, see [Developer's Guide to Oracle Solaris 10 Security](#).

- **Translating binary labels** – You can translate a label between its internal representation and a string. If the label being translated is not dominated by the label of the process, the calling process requires the `sys_trans_label` privilege to perform the translation.
- **Upgrading or downgrading sensitivity labels** – You can *downgrade* or *upgrade* the sensitivity label on a file. If the file is not owned by the calling process, the calling process requires the `file_owner` privilege in its effective set. For more information, see the [setflabel\(3TSOL\)](#) man page.

A process can set the sensitivity label on a file system object to a new sensitivity label that does not dominate the object's existing sensitivity label with the `file_downgrade_sl` privilege in its effective set. The `file_downgrade_sl` privilege also allows a file to be relabeled to a disjoint label.

A process can set the sensitivity label on a file system object to a new sensitivity label that dominates the object's existing sensitivity label with the `file_upgrade_sl` privilege in its effective set.

Most applications do not use privileges to bypass access controls because the applications operate in one of the following ways:

- The application is launched at one sensitivity label and accesses data in objects at that same sensitivity label.
- The application is launched at one sensitivity label and accesses data in objects at other sensitivity labels, but the mandatory access operations are permitted by the system security policy. For example, read-down is allowed by MAC.

If an application tries to access data at sensitivity labels other than the sensitivity label of its process and access is denied, the process needs privileges to gain access. *Privileges* enable an application to bypass MAC or DAC. For example, the `file_dac_read`, `file_dac_write`, and `file_dac_search` privileges bypass DAC. The `file_upgrade_sl` and `file_downgrade_sl` privileges bypass MAC. No matter how access is obtained, the application design must not compromise the classification of the data that is accessed.

When your application changes its own sensitivity label or the sensitivity label of another object, be sure to close all file descriptors. An open file descriptor might leak sensitive data to other processes.

Label APIs

This section describes the APIs that are available for basic label operations. To use these APIs, you must include the following header file:

```
#include <tsol/label.h>
```

The label APIs compile with the `-ltsol` library option.

The Trusted Extensions APIs include data types for the following:

- **Sensitivity label** – The `m_label_t` type definition represents a sensitivity label. The `m_label_t` structure is opaque.
Interfaces accept a variable of type `m_label_t` as a parameter. Interfaces can return sensitivity labels in a variable of type `m_label_t`. The `m_label_t` type definition is compatible with the `blevel_t` structure.
- **Sensitivity label range** – The `brange_t` data structure represents a range of sensitivity labels. The structure holds a minimum label and a maximum label. The structure fields are referred to as `variable.lower_bound` and `variable.upper_bound`.

The APIs for the following operations are described in this section:

- Detecting a Trusted Extensions system
- Accessing the process sensitivity label
- Allocating and freeing memory for labels
- Obtaining and setting the label of a file
- Obtaining label ranges
- Accessing labels in zones
- Obtaining the remote host type
- Translating between labels and strings
- Comparing labels

Detecting a Trusted Extensions System

The `is_system_labeled()` routine is used to determine whether you are running on a Trusted Extensions system. The following routine description includes the prototype declaration for each routine:

```
int is_system_labeled(void);
```

The `is_system_labeled()` routine returns `TRUE` (1) if the Trusted Extensions software is installed and active. Otherwise, it returns `FALSE` (0).

See the [is_system_labeled\(3C\)](#) man page. For an example of this routine's use, see “[get_peer_label\(\) Label-Aware Function](#)” on [page 51](#).

You can also use these other interfaces to determine whether the system is labeled:

- **X client.** If you are writing an X client that depends on multilevel functionality, use the `XQueryExtension()` routine to query the X server for the `SUN_TSQL` extension.
- **Shell script.** If you are writing a shell script that will determine whether the system is labeled, use the `plabel` command. See the [plabel\(1\)](#) man page.

The following example shows the `smf_is_system_labeled()` function used by the `/lib/svc/share/smf_include.sh` script:

```
#
# Returns zero (success) if system is labeled (aka Trusted Extensions).
# 1 otherwise.
#
smf_is_system_labeled() {
    [ ! -x /bin/plabel ] && return 1
    /bin/plabel > /dev/null 2>&1
    return $?
}
```

Accessing the Process Sensitivity Label

The `getlabel()` and `ucred_getlabel()` routines are used to access the sensitivity label of a process. The following routine descriptions include the prototype declaration for each routine:

```
int getlabel(m_label_t *label_p);
```

The `getlabel()` routine obtains the process label of the calling process.

See the [getlabel\(3TSOL\)](#) man page.

```
m_label_t *ucred_getlabel(const ucred_t *uc);
```

The `ucred_getlabel()` routine obtains the label in the credential of the remote process.

See the [ucred_getlabel\(3C\)](#) man page. For an example of this routine's use, see [“get_peer_label\(\) Label-Aware Function” on page 51](#).

Allocating and Freeing Memory for Labels

The `m_label_alloc()`, `m_label_dup()`, and `m_label_free()` routines are used to allocate and free memory for labels. The following routine descriptions include the prototype declaration for each routine:

```
m_label_t *m_label_alloc(const m_label_type_t label_type);
```

The `m_label_alloc()` routine allocates a label in an `m_label_t` data structure on the heap. Labels must be allocated before calling routines such as `getlabel()` and `fgetlabel()`. Some routines, such as `str_to_label()`, automatically allocate an `m_label_t` structure.

When you create a label by using the `m_label_alloc()` routine, you can set the label type to be a sensitivity label or a clearance label.

```
int m_label_dup(m_label_t **dst, const m_label_t *src);
```

The `m_label_dup()` routine duplicates a label.

```
void m_label_free(m_label_t *label);
```

The `m_label_free()` routine frees the memory that was allocated for a label.

When you allocate an `m_label_t` structure or when you call another routine that automatically allocates an `m_label_t` structure, you are responsible for freeing the allocated memory. The `m_label_free()` routine frees the allocated memory.

See the [m_label\(3TSOL\)](#) man page.

Obtaining and Setting the Label of a File

The `setflabel()` routine, the `getlabel()` system call, and the `fgetlabel()` system call are used to obtain and set the label of a file. The following descriptions include the prototype declarations for the routine and the system calls:

```
int setflabel(const char *path, const m_label_t *label_p);
```

The `setflabel()` routine changes the sensitivity label of a file. When the sensitivity label of a file changes, the file is moved to a zone that corresponds to the new label. The file is moved to a new path name that is relative to the root of the other zone.

See the [setflabel\(3TSOL\)](#) man page.

For example, if you use the `setflabel()` routine to change the label of the file `/zone/internal/documents/designdoc.odt` from `INTERNAL` to `RESTRICTED`, the new path of the file will be `/zone/restricted/documents/designdoc.odt`. Note that if the destination directory does not exist, the file is not moved.

When you change the sensitivity label of a file, the original file is deleted. The only exception occurs when the source and destination file systems are loopback-mounted from the same underlying file system. In this case, the file is renamed.

When a process creates an object, the object inherits the sensitivity label of its calling process. The `setflabel()` routine programmatically sets the sensitivity label of a file system object.

The File Manager application and the `setlabel` command permit an authorized user to move an existing file to a different sensitivity label. See the [setlabel\(1\)](#) man page.

```
int getlabel(const char *path, m_label_t *label_p);
```

The `getlabel()` system call obtains the label of a file that is specified by *path*. The label is stored in an `m_label_t` structure that you allocate.

See the [getlabel\(2\)](#) man page.

```
int fgetlabel(int fd, m_label_t *label_p);
```

The `fgetlabel()` system call obtains the label of an open file by specifying a file descriptor.

When you allocate an `m_label_t` structure, you are responsible for freeing the allocated memory by using the `m_label_free()` routine. See the [m_label\(3TSOL\)](#) man page.

Obtaining Label Ranges

The `getuserrange()` and `getdevicerange()` routines are used to obtain the label range of a user and a device, respectively. The following routine descriptions include the prototype declaration for each routine:

```
m_range_t *getuserrange(const char *username);
```

The `getuserrange()` routine obtains the label range of the specified user. The lower bound in the range is used as the initial workspace label when a user logs in to a multilevel desktop. The upper bound, or clearance, is used as an upper limit to the available labels that a user can assign to labeled workspaces.

The default value for a user's label range is specified in the `label_encodings` file. The value can be overridden by the `user_attr` file.

See the [setflabel\(3TSOL\)](#), [label_encodings\(4\)](#), and [user_attr\(4\)](#) man pages.

```
bl_range_t *getdevicerange(const char *device);
```

The `getdevicerange()` routine obtains the label range of a user-allocatable device. If no label range is specified for the device, the default range has an upper bound of `ADMIN_HIGH` and a lower bound of `ADMIN_LOW`.

You can use the `list_devices` command to show the label range for a device.

See the [list_devices\(1\)](#) man page.

Accessing Labels in Zones

These functions obtain label information from objects in zones. The following routine descriptions include the prototype declaration for each routine:

```
char *getpathbylabel(const char *path, char *resolved_path, size_t bufsize,  
const m_label_t *sl);
```

The `getpathbylabel()` routine expands all symbolic links and resolves references to `./`, `../`, removes extra slash (`/`) characters, and stores the zone path name in the buffer named by `resolved_path`. The `bufsize` variable specifies the size in bytes of this buffer. The resulting path does not have any symbolic link components or any `./`, `../`. This function can only be called from the global zone.

The zone path name is relative to the sensitivity label, `sl`. To specify a sensitivity label for a zone name that does not exist, the process must assert either the `priv_file_upgrade_sl` or the `priv_file_downgrade_sl` privilege, depending on whether the specified sensitivity label dominates or does not dominate the process sensitivity label.

See the [getpathbylabel\(3TSOL\)](#) man page.

```
m_label_t *getzoneidbylabel(const m_label_t *label);
```

The `getzoneidbylabel()` routine returns the zone ID of the zone whose label is *label*. This routine requires that the specified zone's state is at least `ZONE_IS_READY`. The zone of the calling process must dominate the specified zone's label, or the calling process must be in the global zone.

See the [getzoneidbylabel\(3TSOL\)](#) man page.

```
m_label_t *getzonelabelbyid(zoneid_t zoneid);
```

The `getzonelabelbyid()` routine returns the MAC label of *zoneid*. This routine requires that the specified zone's state is at least `ZONE_IS_READY`. The zone of the calling process must dominate the specified zone's label, or the calling process must be in the global zone.

See the [getzonelabelbyid\(3TSOL\)](#) man page.

```
m_label_t *getzonelabelbyname(const char *zonename);
```

The `getzonelabelbyname()` routine returns the MAC label of the zone whose name is *zonename*. This routine requires that the specified zone's state is at least `ZONE_IS_READY`. The zone of the calling process must dominate the specified zone's label, or the calling process must be in the global zone.

See the [getzonelabelbyname\(3TSOL\)](#) man page.

```
m_label_t *getzonerootbyid(zoneid_t zoneid);
```

The `getzonerootbyid()` routine returns the root path name of *zoneid*. This routine requires that the specified zone's state is at least `ZONE_IS_READY`. The zone of the calling process must dominate the specified zone's label, or the calling process must be in the global zone. The returned path name is relative to the root path of the caller's zone.

See the [getzonerootbyid\(3TSOL\)](#) man page.

```
m_label_t *getzonerootbylabel(const m_label_t *label);
```

The `getzonerootbylabel()` routine returns the root path name of the zone whose label is *label*. This routine requires that the specified zone's state is at least `ZONE_IS_READY`. The zone of the calling process must dominate the specified zone's label, or the calling process must be in the global zone. The returned path name is relative to the root path of the caller's zone.

See the [getzonerootbylabel\(3TSOL\)](#) man page.

```
m_label_t *getzonerootbyname(const char *zonename);
```

The `getzonerootbyname()` routine returns the root path name of *zonename*. This routine requires that the specified zone's state is at least `ZONE_IS_READY`. The zone of the calling process must dominate the specified zone's label, or the calling process must be in the global zone. The returned path name is relative to the root path of the caller's zone.

See the [getzonerootbyname\(3TSOL\)](#) man page.

Obtaining the Remote Host Type

This routine determines the remote host type. The following routine description includes the prototype declaration:

```
tsol_host_type_t tsol_getrhtype(char *hostname);
```

The `tsol_getrhtype()` routine queries the kernel-level network information to determine the host type that is associated with the specified host name. *hostname* can be a regular host name, an IP address, or a network wildcard address. The returned value is one of the enumerated types that is defined in the `tsol_host_type_t` structure. Currently, these types are `UNLABELED` and `SUN_CIPSO`.

See the [tsol_getrhtype\(3TSOL\)](#) man page.

Translating Between Labels and Strings

The `label_to_str()` and `str_to_label()` routines are used to translate between labels and strings. The following routine descriptions include the prototype declaration for each routine:

```
int label_to_str(const m_label_t *label, char **string, const m_label_str_t  
conversion_type, uint_t flags);
```

The `label_to_str()` routine translates a label, `m_label_t`, to a string. You can use this routine to translate a label into a string that hides the classification name. This format is suitable for storing in public objects. The calling process must dominate the label to be translated, or the process must have the `sys_trans_label` privilege.

See the [label_to_str\(3TSOL\)](#) man page.

The `label_to_str()` routine allocates memory for the translated string. The caller must free this memory by calling the `free()` routine.

See the [free\(3C\)](#) man page.

```
int str_to_label(const char *string, m_label_t **label, const m_label_type_t  
label_type, uint_t flags, int *error);
```

The `str_to_label()` routine translates a label string to a label, `m_label_t`. When you allocate an `m_label_t` structure, you must free the allocated memory by using the `m_label_free()` routine.

When you create a label by using the `str_to_label()` routine, you can set the label type to be a sensitivity label or a clearance label.

See the [str_to_label\(3TSOL\)](#) and [m_label\(3TSOL\)](#) man pages.

Readable Versions of Labels

The `label_to_str()` routine provides readable versions of labels. The `M_LABEL` conversion type returns a string that is classified at that label. The `M_INTERNAL` conversion type returns a string that is unclassified. The classified string version is typically used for displays, as in windows. The classified string might not be suitable for storage. Several conversion types are offered for printing purposes. All printing types show a readable string that is classified at the label that the string shows.

The `conversion_type` parameter controls the type of label conversion. The following are valid values for `conversion_type`, although not all types of conversion are valid for both level types:

- `M_LABEL` is a string of the label that is based on the type of label: sensitivity or clearance. This label string is classified at the level of the label and is therefore not safe for storing in a public object. For example, an `M_LABEL` string such as `CONFIDENTIAL` is not safe for storing in a public directory because the words in the label are often classified.
- `M_INTERNAL` is a string of an unclassified representation of the label. This string is safe for storing in a public object. For example, an `M_INTERNAL` string such as `0x0002-04-48` is safe for storing in an LDAP database.
- `M_COLOR` is a string that represents the color that the security administrator has associated with the label. The association between the label and the color is stored in the `LOCAL DEFINITIONS` section of the `label_encodings` file.
- `PRINTER_TOP_BOTTOM` is a string used as the top and the bottom label of banner and trailer pages.
- `PRINTER_LABEL` is a string used as the downgrade warning on the banner page.
- `PRINTER_CAVEATS` is a string used in the caveats section on the banner page.
- `PRINTER_CHANNEL` is a string used as the handling channels on the banner page.

Label Encodings File

The `label_to_str()` routine uses the label definitions in the `label_encodings` file. The encodings file is a text file that is maintained by the security administrator. The file contains site-specific label definitions and constraints. This file is kept in `/etc/security/tso1/label_encodings`. For information about the `label_encodings` file, see [Trusted Extensions Label Administration, Compartmented Mode Workstation Labeling: Encodings Format](#), and the `label_encodings(4)` man page.

Comparing Labels

The `blequal()`, `bldominates()`, and `blstrictdom()` routines are used to compare labels. The `blinrange()` routine is used to determine whether a label is within a specified label range. In these routines, a *level* refers to a classification and a set of compartments in a sensitivity label or in a clearance label.

```
int blequal(const blevel_t *level1, const blevel_t *level2);
```

The `blequal()` routine compares two labels to determine whether *level1* equals *level2*.

```
int bldominates(const m_label_t *level1, const m_label_t *level2);
```

The `bldominates()` routine compares two labels to determine whether *level1* dominates *level2*.

```
int blstrictdom(const m_label_t *level1, const m_label_t *level2);
```

The `blstrictdom()` routine compares two labels to determine whether *level1* strictly dominates *level2*.

```
int blinrange(const m_label_t *level, const brange_t *range);
```

The `blinrange()` routine determines whether the label, *level*, is within the specified range, *range*.

These routines return a nonzero value when the comparison is true and a value of 0 when the comparison is false. For more information about these routines, see the [blcompare\(3TSOL\)](#) man page. For examples of how these routines are used in the multilevel printing application, see “[Validating the Label Request Against the Printer's Label Range](#)” on page 55.

For more information about label relationships, see “[Label Relationships](#)” on page 15.

The `blmaximum()` and `blminimum()` routines are used to determine the upper and lower bounds of the specified label range.

```
void blmaximum(m_label_t *maximum_label, const m_label_t *bounding_label);
```

The `blmaximum()` routine compares two labels to find the least upper bound of the range.

The *least upper bound* is the lower of two clearances, which is used to determine whether you have access to a system of a particular clearance.

For instance, use this routine to determine the label to use when creating a new labeled object that combines information from two other labeled objects. The label of the new object will dominate both of the original labeled objects.

See the [blminmax\(3TSOL\)](#) man page.

```
void blminimum(m_label_t *minimum_label, const m_label_t *bounding_label);
```

The `blminimum()` routine compares two labels to find the label that represents the greatest lower bound of the range that is bounded by the two levels. The *greatest lower bound* is the

higher of two labels, which is also used to determine whether you have access to a system of a particular clearance.

See the [blminmax\(3TSOL\)](#) man page.

Acquiring a Sensitivity Label

Sensitivity labels are acquired from labeled zones and from other processes. A user can start a process only at the current sensitivity label of the current zone.

When a process creates an object, the object inherits the sensitivity label of its calling process. You can use the `setLabel` command or the `setflabel()` routine to set the sensitivity label of a file system object. See the [setLabel\(1\)](#) and [setflabel\(3TSOL\)](#) man pages.

The following script, `runwlabel`, runs a program that you specify in the labeled zone that you specify. You must run this script from the global zone.

EXAMPLE 2-1 `runwlabel` Script

The `runwlabel` script must first acquire the sensitivity label of the labeled zone in which you want to run the specified program. This script uses the `getzonepath` command to obtain the zone path from the label that you specify on the command line. See the [getzonepath\(1\)](#) man page.

Next, the `runwlabel` script uses the `zoneadm` command to find the zone name associated with the zone path, which was acquired by the `getzonepath` command. See the [zoneadm\(1M\)](#) man page.

Finally, the `runwlabel` script uses the `zlogin` command to run the program that you specify in the zone associated with the label you specified. See the [zlogin\(1\)](#) man page.

To run the `zonename` command in the zone associated with the Confidential: Internal Use Only label, run the `runwlabel` script from the global zone. For example:

```
machine1% runwlabel "Confidential : Internal Use Only" zonename
```

The following shows the source of the `runwlabel` script:

```
#!/sbin/sh
#
# Usage:
# runwlabel "my-label" my-program
#
[ ! -x /usr/sbin/zoneadm ] && exit 0    # SUNWzoneu not installed

PATH=/usr/sbin:/usr/bin; export PATH

# Get the zone path associated with the "my-label" zone
# Remove the trailing "/root"
zonepath=$(getzonepath "$1" | sed -e 's/\s/root$//')
programe="$2"

# Find the zone name that is associated with this zone path
for zone in $(zoneadm list -pi | nawk -F: -v zonepath=${zonepath} '{
    if ($4 == zonepath) {
        print $2
```

EXAMPLE 2-1 runwlabel Script (Continued)

```
    }  
  }'; do  
  
    # Run the specified command in the matching zone  
    zlogin ${zone} ${programe}  
  done  
exit
```

The following script, `runinzone`, runs a program in a zone that you specify even if the zone is not booted. You must run this script from the global zone.

EXAMPLE 2-2 runinzone Script

The script first boots the zone you specified, and then it uses the `zlogin` command to run the `waitforzone` script in the specified zone.

The `waitforzone` script waits for the local zone automounter to come up, and then it runs the program you specified as the user you specified.

To run the `/usr/bin/xclock` command in the public zone, run the following from the global zone:

```
machine1% runinzone public terry /usr/bin/xclock
```

The following shows the source of the `runinzone` script:

```
#!/sbin/ksh  
zonename=$1  
user=$2  
program=$3  
  
# Boot the specified zone  
zoneadm -z ${zonename} boot  
  
# Run the command in the specified zone  
zlogin ${zonename} /bin/demo/waitforzone ${user} ${program} ${DISPLAY}
```

The `runinzone` script calls the following script, `waitforzone`:

```
#!/bin/ksh  
user=$1  
program=$2  
display=$3  
  
# Wait for the local zone automounter to come up  
# by checking for the auto_home trigger being loaded  
  
while [ ! -d /home/${user} ]; do  
  sleep 1  
done
```

EXAMPLE 2-2 runinzone Script *(Continued)*

```
# Now, run the command you specified as the specified user  
su - ${user} -c "${program} -display ${display}"
```


Label Code Examples

This chapter contains several code examples that show how to use the label APIs that are described in [Chapter 2](#), “Labels and Clearances.”

This chapter covers the following topics:

- “Obtaining a Process Label” on page 41
- “Obtaining a File Label” on page 42
- “Setting a File Sensitivity Label” on page 43
- “Determining the Relationship Between Two Labels” on page 44
- “Obtaining the Color Names of Labels” on page 45
- “Obtaining Printer Banner Information” on page 46

Obtaining a Process Label

This code example shows how to obtain and print the sensitivity label of the zone in which this program is run.

```
#include <tsol/label.h>

main()
{
    m_label_t* pl;
    char *plabel = NULL;
    int retval;

    /* allocate an m_label_t for the process sensitivity label */
    pl = m_label_alloc(MAC_LABEL);
    /* get the process sensitivity label */
    if ((retval = getplabel(pl)) != 0) {
        perror("getplabel(pl) failed");
        exit(1);
    }

    /* Translate the process sensitivity label to text and print */
```

```
if ((retval = label_to_str(pl, &plabel, M_LABEL, LONG_NAMES)) != 0) {
    perror("label_to_str(M_LABEL, LONG_NAMES) failed");
    exit(1);
}
printf("Process label = %s\n", plabel);

/* free allocated memory */
m_label_free(pl);
free(plabel);
}
```

The `printf()` statement prints the sensitivity label. The sensitivity label is inherited from the zone in which the program is run. The following shows the text output of this example program:

```
Process label = ADMIN_LOW
```

The text output depends on the specifications in the `label_encodings` file.

Obtaining a File Label

You can obtain a file's sensitivity label and perform operations on that label.

This code example uses the `getlabel()` routine to obtain the file's label. The `fgetlabel()` routine can be used in the same way, but it operates on a file descriptor.

```
#include <tsol/label.h>

main()
{
    m_label_t* docLabel;
    const char* path = "/zone/restricted/documents/designdoc.odt";
    int retval;
    char* label_string;

    /* allocate label and get the file label specified by path */
    docLabel = m_label_alloc(MAC_LABEL);
    retval = getlabel(path, docLabel);

    /* translate the file's label to a string and print the string */
    retval = label_to_str(docLabel, &label_string, M_LABEL, LONG_NAMES);
    printf("The file's label = %s\n", label_string);

    /* free allocated memory */
    m_label_free(docLabel);
    free(label_string);
}
```

When you run this program, the output might look similar to this:

```
The file's label = CONFIDENTIAL : INTERNAL USE ONLY
```

Setting a File Sensitivity Label

When you change the sensitivity label of a file, the file is moved to a new zone that matches the file's new label.

In this code example, the process is running at the CONFIDENTIAL label. The user who is running the process has a TOP SECRET clearance. The TOP SECRET label dominates the CONFIDENTIAL label. The process upgrades the sensitivity label to TOP SECRET. The user needs the Upgrade File Label RBAC authorization to successfully perform the upgrade.

The following program is called `upgrade-afile`.

```
#include <tsol/label.h>

main()
{
    int retval, error;
    m_label_t *fsenslabel;
    char *string = "TOP SECRET";
    *string1 = "TOP SECRET";

    /* Create new sensitivity label value */
    if ((retval = str_to_label(string, &fsenslabel, MAC_LABEL, L_DEFAULT, &err)) != 0) {
        perror("str_to_label(MAC_LABEL, L_DEFAULT) failed");
        exit(1);
    }

    /* Set file label to new value */
    if ((retval = setflabel("/export/home/zelda/afile", &fsenslabel)) != 0) {
        perror("setflabel("/export/home/zelda/afile") failed");
        exit(1);
    }

    m_label_free(fsenslabel);
}
```

The result of running this program depends on the process's label, relative to the label of the file that was passed to the process.

Before and after you run this program, you use the `getlabel` command to verify the file's label. As the following shows, before the program runs, the label for `afile` is CONFIDENTIAL. After the program runs, the label for `afile` is TOP SECRET.

```
% pwd
/export/home/zelda
% getlabel afile
afile: CONFIDENTIAL
% update-afile
% getlabel afile
afile: TOP SECRET
```

If you run the `getlabel` command from a window labeled CONFIDENTIAL after you reclassified the file, it is no longer visible. If you run the `getlabel` command in a window labeled TOP SECRET, you can see the reclassified file.

Determining the Relationship Between Two Labels

If your application accesses data at different sensitivity labels, perform checks in your code to ensure that the process label has the correct relationship to the data label before you permit an access operation to occur. You check the sensitivity label of the object that is being accessed to determine whether access is permitted by the system.

The following code example shows how to test two sensitivity labels for equality, dominance, and strict dominance. The program checks whether a file's label is dominated by or is equal to the process's label.

```
#include <stdio.h>
#include <stdlib.h>

#include <tsol/label.h>

main(int argc, char *argv[])
{
    m_label_t *plabel;
    m_label_t *flabel;

    plabel = m_label_alloc(MAC_LABEL);
    flabel = m_label_alloc(MAC_LABEL);

    if (getlabel(plabel) == -1) {
        perror("getlabel");
        exit(1);
    }
    if (getlabel(argv[1], flabel) == -1) {
        perror("getlabel");
        exit(1);
    }

    if (blequal(plabel, flabel)) {
        printf("Labels are equal\n");
    }
    if (bldominates(plabel, flabel)) {
        printf("Process label dominates file label\n");
    }
    if (blstrictdom(plabel, flabel)) {
        printf("Process label strictly dominates file label\n");
    }

    m_label_free(plabel);
    m_label_free(flabel);

    return (0);
}
```

The text output of this program depends on the process's label, relative to the label of the file that was passed to the process, as follows:

- Because “dominates” includes “equal,” when the labels are equal, the output is the following:

```
Labels are equal
Process label dominates file label
```

- If the process's label strictly dominates the file's label, the output is the following:

Process label strictly dominates file label

Obtaining the Color Names of Labels

This code example uses the `label_to_str()` function to obtain the color name of a label. The mappings between color names and labels are defined in the `label_encodings` file.

```
#include <stdlib.h>
#include <stdio.h>

#include <tsol/label.h>

int
main()
{
    m_label_t *plabel;
    char *label = NULL;
    char *color = NULL;

    plabel = m_label_alloc(MAC_LABEL);

    if (getlabel(plabel) == -1) {
        perror("getlabel");
        exit(1);
    }

    if (label_to_str(plabel, &color, M_COLOR, 0) != 0) {
        perror("label_to_string(M_COLOR)");
        exit(1);
    }
    if (label_to_str(plabel, &label, M_LABEL, DEF_NAMES) != 0) {
        perror("label_to_str(M_LABEL)");
        exit(1);
    }

    printf("The color for the \"%s\" label is \"%s\".\n", label, color);

    m_label_free(plabel);

    return (0);
}
```

If the `label_encodings` file maps the color blue to the label `CONFIDENTIAL`, the program prints the following:

The color for the "CONFIDENTIAL" label is "BLUE".

In the following code example, the `label_to_str()` routine converts a label to strings, such as the header and footer, a caveats section, and handling channels. This routine is used internally by the Trusted Extensions print system, as shown in [Chapter 4, “Printing and the Label APIs.”](#)

Trusted Extensions Developer's Guide • August 2013

```
m_label_free(plabel);  
  
    return (0);  
}
```

For a process label of TS SA SB, the text output might be the following:

```
"TOP SECRET"
```

Unless manually reviewed and downgraded, this output must be protected at the following label:

```
"TOP SECRET A B SA SB"
```

```
"(FULL SB NAME) (FULL SA NAME)"  
"HANDLE VIA (CH B)/(CH A) CHANNELS JOINTLY"
```

```
"TOP SECRET"
```

For more information, see the [label_encodings\(4\)](#) man page, *Compartmented Mode Workstation Labeling: Encodings Format*, and *Trusted Extensions Label Administration*.

Printing and the Label APIs

Printing is one type of service that needs to be label-aware. This chapter introduces the Trusted Extensions label APIs by using as an example the multilevel printing service that was developed for Trusted Extensions.

This chapter covers the following topics:

- “Printing Labeled Output” on page 49
- “Designing a Label-Aware Application” on page 50
- “Understanding the Multilevel Printing Service” on page 50
- “`get_peer_label()` Label-Aware Function” on page 51
- “Validating the Label Request Against the Printer's Label Range” on page 55

Printing Labeled Output

Typically, printers are shared resources. Multilevel printing allows users who are operating at different security levels to share a printer, subject to the restrictions of the security policy. The printing service is also label-aware so that labels can be clearly marked on printed documents.

You can assume the System Administrator role in role-based access control (RBAC) to configure a printer so that the output is labeled. The session label at which the print job is initiated is printed on the banner and trailer pages. The label of the session is also added to the header and footer of every printed page. The labels can be printed because of a printing adapter. The Trusted Extensions printing adapter determines the host label or the zone label at which the print request was initiated. The adapter passes along this label information with the print job to enable the printed output to be labeled.

Designing a Label-Aware Application

Most applications do not need to be label-aware. Therefore, most Oracle Solaris software applications run under Trusted Extensions without modification. The Trusted Extensions label-based access restriction is designed to operate in a way that is consistent with Oracle Solaris OS standards. Generally, any process that you bind to a multilevel port needs to be label-aware because it receives data at multiple labels and is trusted to enforce the security policy.

For example, an application might not be able to access a resource because the application is running at a label that is lower than the required resource. However, an attempt to access that resource does not result in a special error condition. Instead, the application might issue a `File not found` error. Or, an application might attempt to access information that has a higher label than the application is allowed to access. However, the security policy dictates that without sufficient privileges, an application cannot be aware of the existence of a resource with a higher label. Therefore, if an application attempts to access a resource with a label that is higher than the application's label, the resulting error condition is not label-specific. The error message is the same as the error message that is returned to an application that tries to access a resource that does not exist. The lack of “special error conditions” helps to enforce security principles.

In Trusted Extensions, the operating system, *not* the application, enforces the security policy. This security policy is called the *mandatory access control (MAC) policy*. For example, an application does not determine if a protected resource is accessible. Ultimately, the operating system enforces the MAC policy. If an application does not have sufficient privileges to access a resource, the resource is not available to the application. Thus, an application does not need to know anything about labels to access labeled resources.

Similarly, most label-aware applications must be designed so that they can operate in a consistent manner with applications that are not label-aware. Label-aware applications must behave in essentially the same way in environments that involve only a single label, in environments that are unlabeled, and in environments that involve multiple labels. An example of a single-label environment is when a user session with a given label mounts a device at the same label. In an *unlabeled environment*, a label is not explicitly set, but a default label is specified in the `tnrhdb` database. See the `smtnrhdb(1M)` man page.

Understanding the Multilevel Printing Service

Because the printing service accepts requests from processes that operate at different labels, printing must be label-aware. Ordinarily, MAC allows access only to resources that are at the same labels at which the user is operating. Even when print requests are issued only at the same label, printing should be label-aware to enable the printed output to display labels on the printed page.

To handle labels, the printing service must perform these essential functions:

- Determine if the host on which the print process is running is labeled or unlabeled
- If the printing process is running in a labeled environment, obtain the credential of the network connection from which the print request originates (the credential contains the label for that process)
- Extract the label from the network credential
- Obtain the printer's label range, that is, the range of labels for which the printer can accept requests
- Determine if the user's label falls within the acceptable range of labels for the specified printer

get_peer_label() Label-Aware Function

The `get_peer_label()` function in the `lp/lib/lp/tx.c` file implements the logic of multilevel printing in Trusted Extensions. The following sections describe this function and step you through its implementation.

In Trusted Extensions software, much of the logic for handling labels in the printing service is in the `get_peer_label()` function. This function obtains the credential of the remote process in a `ucred_t` data structure and extracts the label from the credential.

The following shows the `get_peer_label()` code.

```
int
get_peer_label(int fd, char **slabel)
{
    if (is_system_labeled()) {
        ucred_t *uc = NULL;
        m_label_t *sl;
        char *pslabel = NULL; /* peer's slabel */

        if ((fd < 0) || (slabel == NULL)) {
            errno = EINVAL;
            return (-1);
        }

        if (getpeerucred(fd, &uc) == -1)
            return (-1);

        sl = ucred_getlabel(uc);
        if (label_to_str(sl, &pslabel, M_INTERNAL, DEF_NAMES) != 0)
            syslog(LOG_WARNING, "label_to_str(): %m");
        ucred_free(uc);

        if (pslabel != NULL) {
            syslog(LOG_DEBUG, "get_peer_label(%d, %s): becomes %s",
                fd, (*slabel ? *slabel : "NULL"), pslabel);
            if (*slabel != NULL)
```

```
        free(*slabel);
        *slabel = strdup(pslabel);
    }
}

return (0);
}
```

Determining Whether the Printing Service Is Running in a Labeled Environment

The printing service is designed to work in labeled and unlabeled environments. Therefore, the printing application must determine when the label of a remote host should be requested and whether the label should be applied. The printing process first checks its own environment. Is the process running in a label-aware environment?

Note that the application does not first determine whether the remote request is labeled. Instead, the printing application determines if its own environment is labeled. If the application is not running on a labeled host, the MAC policy prevents the printing application from receiving labeled requests.

The printing service uses the `is_system_labeled()` function to determine whether the process is running in a labeled environment. For information about this function, see the [is_system_labeled\(3C\)](#) man page.

This code excerpt shows how to determine whether the application is running in a labeled environment:

```
if (is_system_labeled()) {
    ucred_t *uc = NULL;
    m_label_t *sl;
    char *pslabel = NULL; /* peer's slabel */

    if ((fd < 0) || (slabel == NULL)) {
        errno = EINVAL;
        return (-1);
    }
}
```

If the printing adapter process is running on a system configured with Trusted Extensions, the `is_system_labeled()` function obtains the `ucred_t` credential abstraction from the remote process. The `ucred_t` data structure for the remote process and the peer's label are then set to NULL. The functions that return values for the credential and the peer's label fill the data structures. These data structures are discussed in the following sections.

See “[get_peer_label\(\) Label-Aware Function](#)” on [page 51](#) to view the source of the entire `get_peer_label()` routine.

Understanding the Remote Host Credential

The Oracle Solaris OS network API provides an abstraction of a process's credentials. This credentials data is available through a network connection. The credentials are represented by the `ucred_t` data structure. This structure can include the label of a process.

The `ucred` API provides functions for obtaining the `ucred_t` data structure from a remote process. This API also provides functions for extracting the label from the `ucred_t` data structure.

Obtaining the Credential and Remote Host Label

Obtaining the label of a remote process is a two-step procedure. First, you must obtain the credential. Then, you must obtain the label from this credential.

The credential is in the `ucred_t` data structure of the remote process. The label is in the `m_label_t` data structure in the credential. After obtaining the credential of the remote process, you extract the label information from that credential.

The `getpeerucred()` function obtains the `ucred_t` credential data structure from the remote process. The `ucred_getlabel()` function extracts the label from the `ucred_t` data structure. In the `get_peer_label()` function, the two-step procedure is coded as follows:

```
if (getpeerucred(fd, &uc) == -1)
    return (-1);

sl = ucred_getlabel(uc);
```

See [“get_peer_label\(\) Label-Aware Function” on page 51](#) to view the source of the entire `get_peer_label()` routine.

For information about the two functions, see the [getpeerucred\(3C\)](#) and [ucred_getlabel\(3C\)](#) man pages.

In addition to obtaining a remote host's label, you can obtain a remote host's type. To obtain the remote host type, use the `tsol_getrhtype()` routine. See [“Obtaining the Remote Host Type” on page 34](#).

Using the label_to_str() Function

After obtaining the credential and remote host label, an application can call `label_to_str()` to convert the label data structure into a string. The string form of the label data structure can be used by the application.

Note that in the Trusted Extensions printing service, the label is returned as a string. The `get_peer_label()` function returns the string that is obtained by calling `label_to_str()` on the `m_label_t` data structure. This string value is returned in the `slabel` parameter of the `get_peer_label()` function, `char** slabel`.

The following code excerpt shows how the `label_to_str()` function is used:

```
sl = ucred_getlabel(uc);
if (label_to_str(sl, &pslabel, M_INTERNAL, DEF_NAMES) != 0)
    syslog(LOG_WARNING, "label_to_str(): %m");
ucred_free(uc);

if (pslabel != NULL) {
    syslog(LOG_DEBUG, "get_peer_label(%d, %s): becomes %s",
        fd, (*slabel ? *slabel : "NULL"), pslabel);
    if (*slabel != NULL)
        free(*slabel);
    *slabel = strdup(pslabel);
}
```

See [“get_peer_label\(\) Label-Aware Function” on page 51](#) to view the source of the entire `get_peer_label()` routine.

Handling Memory Management

As shown in [“get_peer_label\(\) Label-Aware Function” on page 51](#), labels are often dynamically allocated. The functions `str_to_label()`, `label_to_str()`, `getdevicerange()`, and other functions allocate memory that must be freed by the caller. The following man pages for these functions describe the memory allocation requirements:

- [label_to_str\(3TSOL\)](#)
- [m_label\(3TSOL\)](#)
- [str_to_label\(3TSOL\)](#)

Using the Returned Label String

The `get_peer_label()` function extracts the label from a remote host and returns that label as a string. The printing application, as is typical of label-aware applications, uses the label for the following purposes:

- To make sure that information associated with a label is clearly marked with the correct label. The banner and trailer pages, as well as the header and footer, are marked with the label of the document being printed.
- To validate that the label of a resource permits a given operation to be performed by another labeled resource. That is, the label of the requesting process permits this printer to accept a request from that requesting process. This permission is based on the range of labels that this printer is assigned.

Validating the Label Request Against the Printer's Label Range

In the printing application, the code for validating the label is contained in the `lp/cmd/lpsched/validate.c` file.

Some types of applications need to compare two given labels. For example, an application might need to determine if one label strictly dominates another label. These applications use API functions that compare one label to another label.

The printing application, however, is based on a range of labels. A printer is configured to accept printing requests from a range of different labels. Therefore, the printing application uses API functions that check a label against a range. The application checks that the label from the remote host falls within the range of labels that the printer allows.

In the `validate.c` file, the printing application uses the `blinrange()` function to check the remote host's label against the label range of the printer. This check is made within the `tsol_check_printer_label_range()` function, as shown here:

```
static int
tsol_check_printer_label_range(char *slabel, const char *printer)
{
    int            in_range = 0;
    int            err = 0;
    blrange_t      *range;
    m_label_t      *sl = NULL;

    if (slabel == NULL)
        return (0);

    if ((err =
         (str_to_label(slabel, &sl, USER_CLEAR, L_NO_CORRECTION, &in_range)))
```

```
    == -1) {
        /* str_to_label error on printer max label */
        return (0);
    }
    if ((range = getdevicerange(printer)) == NULL) {
        m_label_free(sl);
        return (0);
    }

    /* blinrange returns true (1) if in range, false (0) if not */
    in_range = blinrange(sl, range);

    m_label_free(sl);
    m_label_free(range->lower_bound);
    m_label_free(range->upper_bound);
    free(range);

    return (in_range);
}
```

The `tsol_check_printer_label_range()` function takes as parameters the label returned by the `get_peer_label()` function and the name of the printer.

Before comparing the labels, `tsol_check_printer_label_range()` converts the string into a label by using the `str_to_label()` function.

The label type is set to `USER_CLEAR`, which produces the clearance label of the associated object. The clearance label ensures that the appropriate level of label is used in the range check that the `blinrange()` function performs.

The `sl` label that is obtained from `str_to_label()` is checked to determine whether the remote host's label, `slabel`, is within the range of the requested device, that is, the printer. This label is tested against the printer's label. The printer's range is obtained by calling the `getdevicerange()` function for the selected printer. The range is returned as a `blrange_t` data structure.

The printer's label range in the `blrange_t` data structure is passed into the `blinrange()` function, along with the clearance label of the requester. See the [blinrange\(3TSOL\)](#) man page.

The following code excerpt shows the `_validate()` function in the `validate.c` file. This function is used to find a printer to handle a printing request. This code compares the user ID and the label associated with the request against the set of allowed users and the label range that is associated with each printer.

```
/*
 * If a single printer was named, check the request against it.
 * Do the accept/reject check late so that we give the most
 * useful information to the user.
 */
if (pps) {
    (pc = &single)->pps = pps;
```



```
/* Does the printer allow access to the user? */
if (!CHKU(prs, pps)) {
    ret = MDENYDEST;
    goto Return;
}

/* Check printer label range */
if (is_system_labeled() && prs->secure->slabel != NULL) {
    if (tsol_check_printer_label_range(prs->secure->slabel,
        pps->printer->name) == 0) {
        ret = MDENYDEST;
        goto Return;
    }
}
```


Interprocess Communications

A system that is configured with Trusted Extensions enforces mandatory access control (MAC) and discretionary access control (DAC). Access control is enforced between communicating processes on the same host and across the network. This chapter summarizes the interprocess communication (IPC) mechanisms that are available in a system configured with Trusted Extensions. This chapter also discusses how access controls apply.

This chapter covers the following topics:

- [“Multilevel Port Information” on page 59](#)
- [“Communication Endpoints” on page 60](#)

Multilevel Port Information

A system that is configured with Trusted Extensions supports single-level and multilevel ports. These ports are used to create connections between applications. A multilevel port can receive data within the range of sensitivity labels that is defined for that port. A single-level port can receive data at a designated sensitivity label only.

- **Single-level port** – A communication channel is established between two unprivileged applications. The sensitivity label of the communication endpoints must be equal.
- **Multilevel port** – A communication channel is established between an application with the `net_bindmtp` privilege in its effective set and any number of unprivileged applications that run at different sensitivity labels. The application with the `net_bindmtp` privilege in the effective set of its process can receive all data from the applications, regardless of the receiving application's sensitivity label.

A multilevel port is a server-side mechanism to establish a connection between two Trusted Extensions applications that are running at different labels. If you want a Trusted Extensions client application to communicate with a service that runs on an untrusted operating system at a different label, you might be able to use the `SO_MAC_EXEMPT` socket option. For more information, see [“MAC-Exempt Sockets” on page 24](#).



Caution – If a connection is multilevel, ensure that the application does not make a connection at one sensitivity label, and then send or receive data at another sensitivity label. Such a configuration would cause data to reach an unauthorized destination.

The Trusted Network library provides an interface to retrieve the label from a packet. The programmatic manipulation of network packets is not needed. Specifically, you cannot change the security attributes of a message before it is sent. Also, you cannot change the security attributes on the communication endpoint over which the message is sent. You can read the label of a packet, just as you read other security information of a packet. The `ucred_getlabel()` function is used to retrieve label information.

If your application requires the use of a multilevel port, that port cannot be created programmatically. Rather, you must tell the system administrator to create a multilevel port for the application.

For more information about multilevel ports, see the following:

- “Zones and Multilevel Ports” in *Trusted Extensions Administrator’s Procedures*
- “How to Create a Multilevel Port for a Zone” in *Trusted Extensions Administrator’s Procedures*
- “How to Configure a Multilevel Print Server and Its Printers” in *Trusted Extensions Administrator’s Procedures*

Communication Endpoints

The Trusted Extensions software supports IPC over communication endpoints by using the following socket-based mechanisms:

- Berkeley sockets
- Transport Layer Interface (TLI)
- Remote procedure calls (RPC)

This section summarizes the socket communication mechanisms and the related security policy. See the appropriate man page for specific information about the security policy and applicable privileges.

In addition to these mechanisms, Trusted Extensions also supports multilevel ports. See “Multilevel Port Information” on page 59.

Berkeley Sockets and TLI

The Trusted Extensions software supports network communication by using Berkeley sockets and the TLI over single-level ports and multilevel ports. The `AF_UNIX` family of system calls establishes interprocess connections in the same labeled zone by means of a special file that is specified by using a fully resolved path name. The `AF_INET` family of system calls establishes interprocess connections across the network by using IP addresses and port numbers.

AF_UNIX Family

In the `AF_UNIX` family of interfaces, only one server bind can be established to a single special file, which is a UNIX domain socket. The `AF_UNIX` family does not support multilevel ports.

Like UNIX domain sockets, doors and named pipes use special files for rendezvous purposes.

The default policy for all Trusted Extensions IPC mechanisms is that they are all constrained to work within a single labeled zone. The following are exceptions to this policy:

- The global zone administrator can make a named pipe (FIFO) available to a zone whose label dominates the owning zone. The administrator does this by loopback-mounting the directory that contains the FIFO.

A process that runs in the higher-level zone is permitted to open the FIFO in read-only mode. A process is not permitted to use the FIFO to write down.

- A labeled zone can access global zone door servers if the global zone rendezvous file is loopback-mounted into the labeled zone.

The Trusted Extensions software depends on the door policy to support the `labeld` and `nscd` doors-based services. The default `zonecfg` template specifies that the `/var/tsol/doors` directory in the global zone is loopback-mounted into each labeled zone.

AF_INET Family

In the `AF_INET` family, the process can establish a single-label connection or a multilabel connection to privileged or unprivileged port numbers. To connect to privileged port numbers, the `net_priv_addr` privilege is required. If a multilevel port connection is sought, the `net_bindmlp` privilege is also required.

The server process needs the `net_bindmlp` privilege in its effective set for a multilevel port connection. If a single-level port connection is made instead, the server process needs mandatory read-equal access to the socket, and the client process needs mandatory write-equal access. Both processes need mandatory and discretionary access to the file. If access to the file is denied, any process that is denied access needs the appropriate file privilege in its effective set to gain access.

The following code example shows how a multilevel server can obtain the labels of its connected clients. The standard C library function `getpeerucred()` obtains a connected socket or a STREAM peer's credentials. In the context of Trusted Extensions, when the listening socket of a

multilevel port server accepts a connection request, the first argument is typically a client socket file descriptor. The Trusted Extensions application uses the `getpeerucred()` function in exactly the same way a normal application program does. The Trusted Extensions addition is `ucred_getlabel()`, which returns a label. For more information, see the [ucred_get\(3C\)](#) man page.

```
/*
 * This example shows how a multilevel server can
 * get the label of its connected clients.
 */
void
remote_client_label(int svr_fd)
{
    ucred_t *uc = NULL;
    m_label_t *sl;
    struct sockaddr_in6 remote_addr;

    bzero((void *)&remote_addr, sizeof (struct sockaddr_in6));

    while (1) {
        int clnt_fd;
        clnt_fd = accept(svr_fd, (struct sockaddr *)&remote_addr,
                        &sizeof (struct sockaddr_in6));

        /*
         * Get client attributes from the socket
         */
        if (getpeerucred(clnt_fd, &uc) == -1) {
            return;
        }

        /*
         * Extract individual fields from the ucred structure
         */

        sl = ucred_getlabel(uc);

        /*
         * Security label usage here
         * .....
         */

        ucred_free(uc);
        close(clnt_fd);
    }
}
```

RPC Mechanism

The Trusted Extensions software provides multilevel port support for remote procedure calls (RPCs). A client application can send inquiries to a server's PORTMAPPER service (port 111) whether or not a particular service is available. If the requested service is registered with the PORTMAPPER on the server, the server will dynamically allocate an anonymous port and return this port to the client.

On a Trusted Extensions system, an administrator can configure the PORTMAPPER port as a multilevel port so that multiple single-level applications can use this service. If the PORTMAPPER port is made a multilevel port, all anonymous ports allocated by the PORTMAPPER service are also multilevel ports. There are no other programmable interfaces or administrative interfaces to control anonymous multilevel ports.

Using Multilevel Ports With UDP

The PORTMAPPER service described in the previous section is implemented by using UDP. Unlike TCP, UDP sockets are not connection oriented, so some ambiguity might arise about which credentials to use when replying to a client on a multilevel port. Therefore, the client's request socket must be explicitly associated with the server's reply packet. To make this association, use the `SO_RECVUCRED` socket option.

When `SO_RECVUCRED` is set on a UDP socket, the kernel UDP module can pass a label in a `ucred` structure as ancillary data to an application. The `level` and `type` values of the `ucred` are `SOL_SOCKET` and `SCM_UCRED`, respectively.

An application can handle this `ucred` structure in one of these ways:

- Copy this `ucred` structure from the receiving buffer to the send buffer
- Reuse the receiving buffer as the send buffer and leave the `ucred` structure in the receiving buffer

The following code excerpt shows the reuse case.

```
/*
 * Find the SCM_UCRED in src and place a pointer to that
 * option alone in dest. Note that these two 'netbuf'
 * structures might be the same one, so the code has to
 * be careful about referring to src after changing dest.
 */
static void
extract_cred(const struct netbuf *src, struct netbuf *dest)
{
    char *cp = src->buf;
    unsigned int len = src->len;
    const struct T_opthdr *opt;
    unsigned int olen;

    while (len >= sizeof (*opt)) {
        /* LINTED: pointer alignment */
        opt = (const struct T_opthdr *)cp;
        olen = opt->len;
        if (olen > len || olen < sizeof (*opt) ||
            !IS_P2ALIGNED(olen, sizeof (t_uscalar_t)))
            break;
        if (opt->level == SOL_SOCKET &&
            opt->name == SCM_UCRED) {
            dest->buf = cp;
        }
    }
}
```

```
        dest->len = olen;
        return;
    }
    cp += olen;
    len -= olen;
}
dest->len = 0;
}
```

The following code excerpt shows how to access the user credential from the receiving buffer:

```
void
examine_udp_label()
{
    struct msghdr  recv_msg;
    struct cmsghdr *cmsgp;
    char message[MAX_MSGLEN+1];
    char inmsg[MAX_MSGLEN+1];
    int on = 1;

    setsockopt(sockfd, SOL_SOCKET, SO_RECVUCRED, (void *)&on,
               sizeof (int));

    [...]

    while (1) {
        if (recvmsg(sockfd, &recv_msg, 0) < 0) {
            (void) fprintf(stderr, "recvmsg_errno:  %d\n", errno);
            exit(1);
        }

        /*
         * Check ucred in ancillary data
         */
        ucred = NULL;

        for (cmsgp = CMSG_FIRSTHDR(&recv_msg); cmsgp;
             cmsgp = CMSG_NXTHDR(&recv_msg, cmsgp)) {
            if (cmsgp->cmsg_level == SOL_SOCKET &&
                cmsgp->cmsg_type == SCM_UCRED) {
                ucred = (ucred_t *)CMSG_DATA(cmsgp);
                break;
            }

            if (ucred == NULL) {
                (void) sprintf(&message[0],
                              "No ucred info in ancillary data with UDP");
            } else {
                /*
                 * You might want to extract the label from the
                 * ucred by using ucred_getlabel(3C) here.
                 */
            }
        }

        [...]
    }
}
```



```
        if (message != NULL)
            (void) strncpy(&inmsg[0], message, MAX_MSGLEN);
        /*
         * Use the received message so that it will contain
         * the correct label
         */
        iov.iov_len = strlen(inmsg);
        ret = sendmsg(sockfd, &recv_msg, 0);
    }
}
```


Trusted X Window System

This chapter describes the Trusted Extensions X Window System APIs. This chapter also includes a short Motif application that is used to describe the Trusted X Window System security policy and the Trusted Extensions interfaces.

This chapter covers the following topics:

- “Trusted X Window System Environment” on page 67
- “Trusted X Window System Security Attributes” on page 68
- “Trusted X Window System Security Policy” on page 69
- “Privileged Operations and the Trusted X Window System” on page 71
- “Trusted Extensions X Window System APIs” on page 72
- “Using Trusted X Window System Interfaces” on page 77

Trusted X Window System Environment

A system that is configured with Trusted Extensions uses the Trusted Extensions CDE (CDE), which is an enhanced version of the Common Desktop Environment (CDE). The Trusted Extensions CDE (CDE) uses the Trusted Extensions X Window System. The Trusted Extensions X Window System includes protocol extensions to support mandatory access control (MAC), discretionary access control (DAC), and the use of privileges.

Data transfer sessions are *polyinstantiated*, meaning that they are instantiated at different sensitivity labels and user IDs. Polyinstantiation ensures that data in an unprivileged client at one sensitivity label or user ID is not transferred to another client at another sensitivity label or user ID. Such a transfer might violate the Trusted X Window System DAC policies and the MAC policies of write-equal and read-down.

The Trusted Extensions X Window System APIs enable you to obtain and set security-related attribute information. These APIs also enable you to translate labels to strings by using a font list and width to apply a style to the text string output. For example, the font might be 14-point,

bold Helvetica. These interfaces are usually called by administrative applications that are written with Motif widgets, Xt Intrinsics, Xlib, and CDE interfaces.

- **Obtaining security-related information** – These interfaces operate at the Xlib level where X protocol requests are made. Use Xlib interfaces to obtain data for the input parameter values.
- **Translating labels to strings** – These interfaces operate at the Motif level. The input parameters are the label, a font list that specifies the appearance of the text string output, and the desired width. A compound string of the specified style and width is returned.

For declarations of these routines, see [“Trusted Extensions X Window System APIs” on page 72](#).

Trusted X Window System Security Attributes

The Trusted X Window System interfaces manage security-related attribute information for various X Window System objects. You can choose to create a GUI application with Motif only. The Motif application should use XToolkit routines to retrieve the Xlib object IDs underlying the Motif widgets to handle security attribute information for an Xlib object.

The X Window System objects for which security attribute information can be retrieved by the Trusted X Window System interfaces are window, property, X Window Server, and the connection between the client and the X Window Server. Xlib provides calls to retrieve the window, property, display, and client connection IDs.

A window displays output to the user and accepts input from clients.

A property is an arbitrary collection of data that is accessed by the property name. Property names and property types can be referenced by an *atom*, which is a unique, 32-bit identifier and a character name string.

The security attributes for windows, properties, and client connections consist of ownership IDs and sensitivity label information. For information about the structures for capturing some of these attributes, see [“Data Types for X11” on page 73](#). For information about the interfaces that obtain and set security attribute information, see [“Trusted Extensions X Window System APIs” on page 72](#).

Trusted X Window System Security Policy

Window, property, and pixmap objects have a user ID, a client ID, and a sensitivity label. Graphic contexts, fonts, and cursors have a client ID only. The connection between the client and the X Window Server has a user ID, an X Window Server ID, and a sensitivity label.

The *user ID* is the ID of the client that created the object. The *client ID* is related to the connection number to which the client that creates the object is connected.

The DAC policy requires a client to own an object to perform any operations on that object. A client owns an object when the client's user ID equals the object's ID. For a connection request, the user ID of the client must be in the access control list (ACL) of the owner of the X Window Server workstation. Or, the client must assert the Trusted Path attribute.

The MAC policy is write-equal for windows and pixmaps, and read-equal for naming windows. The MAC policy is read-down for properties. The sensitivity label is set to the sensitivity label of the creating client. The following shows the MAC policy for these actions:

- **Modify, create, or delete** – The sensitivity label of the client must equal the object's sensitivity label.
- **Name, read, or retrieve** – The client's sensitivity label must dominate the object's sensitivity label.
- **Connection request** – The sensitivity label of the client must be dominated by the session clearance of the owner of the X Window Server workstation, or the client must assert the Trusted Path attribute.

Windows can have properties that contain information to be shared among clients. Window properties are created at the sensitivity label at which the application is running, so access to the property data is segregated by its sensitivity label. Clients can create properties, store data in a property on a window, and retrieve the data from a property subject to MAC and DAC restrictions. To specify properties that are not polyinstantiated, update the `TrustedExtensionsPolicy` file.

The `TrustedExtensionsPolicy` file is supported for the Xsun server and the Xorg server:

- SPARC: For Xsun, the file is in `/usr/openwin/server/etc`.
- x86: For Xorg, the file is in `/usr/X11/lib/X11/xserver`.

These sections describe the security policy for the following:

- Root window
- Client windows
- Override-redirect windows
- Keyboard, pointer, and server control
- Selection Manager
- Default window resources
- Moving data between windows

Root Window

The root window is at the top of the window hierarchy. The root window is a public object that does not belong to any client, but it has data that must be protected. The root window attributes are protected at ADMIN_LOW.

Client Windows

A client usually has at least one top-level client window that descends from the root window and additional windows nested within the top-level window. All windows that descend from the client's top-level window have the same sensitivity label.

Override-Redirect Windows

Override-redirect windows, such as menus and certain dialog boxes, cannot take the input focus away from another client. This prevents the input focus from accepting input into a file at the wrong sensitivity label. Override-redirect windows are owned by the creating client and cannot be used by other clients to access data at another sensitivity label.

Keyboard, Pointer, and Server Control

A client needs MAC and DAC to gain control of the keyboard, pointer, and server. To reset the focus, a client must own the focus or have the win_devices privilege in its effective set.

To warp a pointer, the client needs pointer control and MAC and DAC to the destination window. X and Y coordinate information can be obtained for events that involve explicit user action.

Selection Manager

The Selection Manager application arbitrates user-level interwindow data moves, such as cut and paste or drag and drop, where information is transferred between untrusted windows. When a transfer is attempted, the Selection Manager captures the transfer, verifies the controlling user's authorization, and requests confirmation and labeling information from the user. Any time the user attempts a data move, the Selection Manager automatically appears. You do not need to update your application code to get the Selection Manager to appear.

The administrator can set automatic confirmation for some transfer types, in which case the Selection Manager does not appear. If the transfer meets the MAC and DAC policies, the data transfer completes. The File Manager and the window manager also act as selection agents for their private drop sites. See the /usr/openwin/server/etc/TrustedExtensionsPolicy file to specify selection targets that are polyinstantiated. See the /usr/dt/config/sel_config file to determine which selection targets are automatically confirmed.

Default Window Resources

Resources that are not created by clients are default resources that are protected at ADMIN_LOW. Only clients that run at ADMIN_LOW or with the appropriate privileges can modify default resources.

The following are window resources:

- **Root window attributes** – All clients have read and create access, but only privileged clients have write or modify access. See [“Privileged Operations and the Trusted X Window System” on page 71](#).
- **Default cursor** – Clients are free to reference the default cursor in protocol requests.
- **Predefined atoms** – The TrustedExtensionsPolicy file contains a read-only list of predefined atoms.

Moving Data Between Windows

A client needs the win_selection privilege in its effective set to move data between one window and another window without going through the Selection Manager. See [“Selection Manager” on page 70](#).

Privileged Operations and the Trusted X Window System

Library routines that access a window, property, or atom name without user involvement require MAC and DAC. Library routines that access frame buffer graphic contexts, fonts, and cursors require discretionary access and might also require additional privileges for special tasks.

The client might need one or more of the following privileges in its effective set if access to the object is denied: win_dac_read, win_dac_write, win_mac_read, or win_mac_write. See the TrustedExtensionsPolicy file to enable or disable these privileges.

This list shows the privileges needed to perform the following tasks:

- **Configuring and destroying window resources** – A client process needs the win_config privilege in its effective set to configure or destroy windows or properties that are permanently retained by the X Window Server. The screen saver timeout is an example of such a resource.
- **Using window input devices** – A client process needs the win_devices privilege in its effective set to obtain and set keyboard and pointer controls, or to modify pointer button mappings and key mappings.
- **Using direct graphics access** – A client process needs the win_dga privilege in its effective set to use the direct graphics access (DGA) X protocol extension.

- **Downgrading window labels** – A client process needs the `win_downgrade_sl` privilege in its effective set to change the sensitivity label of a window, pixmap, or property to a new label that does not dominate the existing label.
- **Upgrading window labels** – A client process needs the `win_upgrade_sl` privilege in its effective set to change the sensitivity label of a window, pixmap, or property to a new label that dominates the existing label.
- **Setting a font path on a window** – A client process needs the `win_fontpath` privilege in its effective set to modify the font path.

Trusted Extensions X Window System APIs

To use the Trusted X11 APIs, you need the following header file:

```
#include <X11/extensions/Xtsol.h>
```

The Trusted X11 examples compile with the `-lXtsol` and `-ltsol` library options.

To use the X11 label-clipping APIs, you need the following header file:

```
#include <Dt/label_clipping.h>
```

The label-clipping examples compile with the `-lDtTsol` and `-ltsol` library options.

The following sections provide data types and declarations for the Trusted X11 interfaces and the X11 label-clipping interfaces:

- Data types for X11
- Accessing attributes
- Accessing and setting a window label
- Accessing and setting a window user ID
- Accessing and setting a window property label
- Accessing and setting a window property user ID
- Accessing and setting a workstation owner ID
- Setting the X Window Server clearance and minimum label
- Working with the Trusted Path window
- Accessing and setting the screen stripe height
- Setting window polyinstantiation information
- Working with the X11 label-clipping interface

Data Types for X11

The following data types are defined in `X11/extensions/Xtsol.h` and are used for the Trusted Extensions X Window System APIs:

- **Object type for X11** – The `ResourceType` definition indicates the type of resource to be handled. The value can be `IsWindow`, `IsPixmap`, or `IsColormap`.

`ResourceType` is a type definition to represent a clearance. Interfaces accept a structure of type `m_label_t` as parameters and return clearances in a structure of the same type.

- **Object attributes for X11** – The `XTsolResAttributes` structure contains these resource attributes:

```
typedef struct _XTsolResAttributes {
    CARD32    ousid;    /* owner uid */
    CARD32    uid;      /* uid of the window */
    m_label_t *sl;      /* sensitivity label */
} XTsolResAttributes;
```

- **Property attributes for X11** – The `XTsolPropAttributes` structure contains these property attributes:

```
typedef struct _XTsolPropAttributes {
    CARD32    uid;      /* uid of the property */
    m_label_t *sl;      /* sensitivity label */
} XTsolPropAttributes;
```

- **Client attributes for X11** – The `XTsolClientAttributes` structure contains these client attributes:

```
typedef struct _XTsolClientAttributes {
    int        trustflag; /* true if client masked as trusted */
    uid_t      uid;        /* owner uid who started the client */
    gid_t      gid;        /* group id */
    pid_t      pid;        /* process id */
    u_long     sessionid;  /* session id */
    au_id_t    auditid;    /* audit id */
    u_long     iaddr;      /* internet addr of host where client is running */
} XTsolClientAttributes;
```

Accessing Attributes

The following routines are used to access resource, property, and client attributes:

Status `XTSOLgetResAttributes(Display *display, XID object, ResourceType type, XTsolResAttributes *winattrp);`

This routine returns the resource attributes for a window ID in *winattrp*. See the [XTSOLgetResAttributes\(3XTSOL\)](#) man page.

Status `XTSOLgetPropAttributes(Display *display, Window window, Atom property, XTsolPropAttributes *propattrp);`

This routine returns the property attributes for a property hanging on a window ID in *propattrp*. See the [XTSOLgetPropAttributes\(3XTSOL\)](#) man page.

```
Status XTSOLgetClientAttributes(Display *display, XID windowid,  
XTSOLClientAttributes *clientattrp);
```

This routine returns the client attributes in *clientattrp*. See the [XTSOLgetClientAttributes\(3XTSOL\)](#) man page.

Accessing and Setting a Window Label

The `XTSOLgetResLabel()` and `XTSOLsetResLabel()` routines are used to obtain and set the sensitivity label of a window.

```
Status XTSOLgetResLabel(Display *display, XID object, ResourceType type,  
m_label_t *sl);
```

This routine obtains the sensitivity label of a window. See the [XTSOLgetResLabel\(3XTSOL\)](#) man page.

```
Status XTSOLsetResLabel(Display *display, XID object, ResourceType type,  
m_label_t *sl);
```

This routine sets the sensitivity label of a window. See the [XTSOLsetResLabel\(3XTSOL\)](#) man page.

Accessing and Setting a Window User ID

The `XTSOLgetResUID()` and `XTSOLsetResUID()` routines are used to obtain and set the user ID of a window.

```
Status XTSOLgetResUID(Display *display, XID object, ResourceType type, uid_t  
*uidp);
```

This routine obtains the user ID of a window. See the [XTSOLgetResUID\(3XTSOL\)](#) man page.

```
Status XTSOLsetResUID(Display *display, XID object, ResourceType type, uid_t  
*uidp);
```

This routine sets the user ID of a window. See the [XTSOLsetResUID\(3XTSOL\)](#) man page.

Accessing and Setting a Window Property Label

The `XTSOLgetPropLabel()` and `XTSOLsetPropLabel()` routines are used to obtain and set the sensitivity label of a property hanging on a window ID.

```
Status XTSOLgetPropLabel(Display *display, Window window, Atom property,  
m_label_t *sl);
```

This routine obtains the sensitivity label of a property hanging on a window ID. See the [XTSOLgetPropLabel\(3XTSOL\)](#) man page.

```
Status XTSOLsetPropLabel(Display *display, Window window, Atom property,
m_label_t *sl);
```

This routine sets the sensitivity label of a property hanging on a window ID. See the [XTSOLsetPropLabel\(3XTSOL\)](#) man page.

Accessing and Setting a Window Property User ID

The `XTSOLgetPropUID()` and `XTSOLsetPropUID()` routines are used to obtain and set the user ID of a property hanging on a window ID.

```
Status XTSOLgetPropUID(Display *display, Window window, Atom property, uid_t
*uidp);
```

This routine obtains the user ID of a property hanging on a window ID. See the [XTSOLgetPropUID\(3XTSOL\)](#) man page.

```
Status XTSOLsetPropUID(Display *display, Window window, Atom property, uid_t
*uidp);
```

This routine sets the user ID of a property hanging on a window ID. See the [XTSOLsetPropUID\(3XTSOL\)](#) man page.

Accessing and Setting a Workstation Owner ID

The `XTSOLgetWorkstationOwner()` and `XTSOLsetWorkstationOwner()` routines are used to obtain and set the user ID of the owner of the workstation server.

Note – The `XTSOLsetWorkstationOwner()` routine should only be used by the window manager.

```
Status XTSOLgetWorkstationOwner(Display *display, uid_t *uidp);
```

This routine obtains the user ID of the owner of the workstation server. See the [XTSOLgetWorkstationOwner\(3XTSOL\)](#) man page

```
Status XTSOLsetWorkstationOwner(Display *display, uid_t *uidp);
```

This routine sets the user ID of the owner of the workstation server. See the [XTSOLsetWorkstationOwner\(3XTSOL\)](#) man page.

Setting the X Window Server Clearance and Minimum Label

The `XTSOLsetSessionHI()` and `XTSOLsetSessionLO()` routines are used to set the session high clearance and the session low minimum label for the X Window Server. Session high can be selected from the Label Builder GUI and must be within the user's range. Session low is the same as the user's minimum label for the multilevel session.

Note – These interfaces should only be used by the window manager.

Status `XTSOLsetSessionHI(Display *display, m_label_t *sl);`

The session high clearance is set from the workstation owner's clearance at login. The session high clearance must be dominated by the owner's clearance and by the upper bound of the machine monitor's label range. Once changed, connection requests from clients that run at a sensitivity label higher than the window server clearance are rejected unless they have privileges. See the [XTSOLsetSessionHI\(3XTSOL\)](#) man page.

Status `XTSOLsetSessionLO(Display *display, m_label_t *sl);`

The session low minimum label is set from the workstation owner's minimum label at login. The session low minimum label must be greater than the user's administratively set minimum label and the lower bound of the machine monitor's label range. When this setting is changed, connection requests from clients that run at a sensitivity label lower than the window server sensitivity label are rejected unless they have privileges. See the [XTSOLsetSessionLO\(3XTSOL\)](#) man page.

Working With the Trusted Path Window

The `XTSOLMakeTPWindow()` and `XTSOLIsWindowTrusted()` routines are used to make the specified window the Trusted Path window and to test whether the specified window is the Trusted Path window.

Status `XTSOLMakeTPWindow(Display *display, Window *w);`

This routine makes the specified window the Trusted Path window. See the [XTSOLMakeTPWindow\(3XTSOL\)](#) man page.

Bool `XTSOLIsWindowTrusted(Display *display, Window *window);`

This routine tests whether the specified window is the Trusted Path window. See the [XTSOLIsWindowTrusted\(3XTSOL\)](#) man page.

Accessing and Setting the Screen Stripe Height

The `XTSOLgetSSHeight()` and `XTSOLsetSSHeight()` routines are used to obtain and set the screen stripe height.

Note – These interfaces should only be used by the window manager.

Status `XTSOLgetSSHeight(Display *display, int screen_num, int *newHeight);`

This routine obtains the screen stripe height. See the [XTSOLgetSSHeight\(3XTSOL\)](#) man page.

```
Status XTSOLsetSSHeight(Display *display, int screen_num, int newHeight);
```

This routine sets the screen stripe height. Be careful that you do not end up without a screen stripe or with a very large screen stripe. See the [XTSOLsetSSHeight\(3XTSOL\)](#) man page.

Setting Window Polyinstantiation Information

```
Status XTSOLsetPolyInstInfo(Display *display, m_label_t sl, uid_t *uidp, int enabled);
```

The `XTSOLsetPolyInstInfo()` routine enables a client to obtain property information from a property at a different sensitivity label than the client. In the first call, you specify the desired sensitivity label and the user ID, and set the enabled property to True. Then, you call `XTSOLgetPropAttributes()`, `XTSOLgetPropLabel()`, or `XTSOLgetPropUID()`. To finish, you call the `XTSOLsetPolyInstInfo()` routine again with the enabled property set to False. See the [XTSOLsetPolyInstInfo\(3XTSOL\)](#) man page.

Working With the X11 Label-Clipping Interface

```
int label_to_str(const m_label_t *label, char **string, const m_label_str_t conversion_type, uint_t flags);
```

The `label_to_str()` routine translates a sensitivity label or clearance to a string. See the [label_to_str\(3TSOL\)](#) man page.

Using Trusted X Window System Interfaces

The following sections provide example code excerpts that use Trusted Extensions interface calls. These calls handle security attributes and translate a label to a string. The excerpts focus on handling window security attributes, the most commonly managed attributes in application programs. Often, a client retrieves security attributes by using the appropriate privileges for an object that was created by another application. The client then checks the attributes to determine whether an operation on the object is permitted by the system's security policy. The security policy covers DAC policies and the MAC write-equal and read-down policies. If access is denied, the application generates an error or uses privileges, as appropriate. See “[Privileged Operations and the Trusted X Window System](#)” on page 71 for a discussion about when privileges are needed.

You must create an object before you can retrieve its ID to pass to the Trusted Extensions APIs.

Obtaining Window Attributes

The `XTSOLgetResAttributes()` routine returns security-related attributes for a window. You supply the following:

- Display ID
- Window ID
- Flag to indicate that the object for which you want security attributes is a window
- `XtsolResAttributes` structure to receive the returned attributes

Because the client is obtaining the security attributes for a window that the client created, no privileges are required.

Note that the example programs in this book focus on the APIs being shown and do not perform error checking. Your applications should perform the appropriate error checking.

```
/* Retrieve underlying window and display IDs with Xlib calls */
window = XtWindow(topLevel);
display = XtDisplay(topLevel);

/* Retrieve window security attributes */
retval = XTSOLgetResAttributes(display, window, IsWindow, &winattrs);

/* Translate labels to strings */
retval = label_to_str(&winattrs.sl, &label, M_LABEL, LONG_NAMES);

/* Print security attribute information */
printf("Workstation Owner ID = %d\nUser ID = %d\nLabel = %s\n",
       winattrs.oid, winattrs.uid, string1);
```

The `printf` statement prints the following:

```
Workstation Owner ID = 29378
User ID = 29378
Label = CONFIDENTIAL
```

Translating the Window Label With the Font List

This example shows how to obtain the process sensitivity label and translate it to a string by using a font list and the pixel width. A label widget is created with the string for its label. The process sensitivity label equals the window sensitivity label. Therefore, no privileges are required.

When the final string is longer than the width, the string is clipped and the clipped indicator is used. Note that the X Window System label-translation interfaces clip to the specified number of pixels, while the label-clipping interfaces clip to the number of characters.

Note – If your site uses a `label_encodings` file in a language other than English, the translation might not work on accent characters in the ISO standard above 128. The following example does not work for the Asian character set.

```

        retval = getlabel(&senslabel);

/* Create the font list and translate the label using it */
        italic = XLoadQueryFont(XtDisplay(topLevel),
            "-adobe-times-medium-i-*-*14-*-*-*iso8859-1");
        fontlist = XmFontListCreate(italic, "italic");
        xmstr = Xbsltos(XtDisplay(topLevel), &senslabel, width, fontlist,
            LONG_WORDS);
/* Create a label widget using the font list and label text*/
        i=0;
        XtSetArg(args[i], XmNfontList, fontlist); i++;
        XtSetArg(args[i], XmNlabelString, xmstr); i++;
        label = XtCreateManagedWidget("label", xmLabelWidgetClass,
            form, args, i);

```

Obtaining a Window Label

This example shows how to obtain the sensitivity label for a window. The process sensitivity label equals the window sensitivity label. Therefore, no privileges are required.

```

/* Retrieve window label */
        retval = XTSOLgetResLabel(display, window, IsWindow, &senslabel);

/* Translate labels to string and print */
        retval = label_to_str(label, &string, M_LABEL, LONG_NAMES);
        printf("Label = %s\n", string);

```

The `printf` statement, for example, prints the following:

```
Label = PUBLIC
```

Setting a Window Label

This example shows how to set the sensitivity label on a window. The new sensitivity label dominates the sensitivity label of the window and the process. The client needs the `sys_trans_label` privilege in its effective set to translate a label that the client does not dominate. The client also needs the `win_upgrade_sl` privilege to change the window's sensitivity label.

For more information about using privileges, see [Developer's Guide to Oracle Solaris 10 Security](#).

```

/* Translate text string to sensitivity label */
        retval = label_to_str(string4, &label, M_LABEL, L_NO_CORRECTION, &error);

```

```
/* Set sensitivity label with new value */  
retval = XTSOLsetResLabel(display, window, IsWindow, label);
```

Obtaining the Window User ID

This example shows how to obtain the window user ID. The process owns the window resource and is running at the same sensitivity label. Therefore, no privileges are required.

```
/* Get the user ID of the window */  
retval = XTSOLgetResUID(display, window, IsWindow, &uid);
```

Obtaining the X Window Server Workstation Owner ID

This example shows how to obtain the ID of the user who is logged in to the X Window Server. The process sensitivity label equals the window sensitivity label. Therefore, no privileges are required.

```
/* Get the user ID of the window */  
retval = XTSOLgetWorkstationOwner(display, &uid);
```


Label Builder APIs

Trusted Extensions provides a set of Motif based APIs. You can use these interfaces to create an interactive GUI to build valid sensitivity labels or clearances from user input. These interfaces are called the *Label Builder APIs*. These APIs are most often called from within administrative applications.

The Label Builder GUIs are used in a system that is configured with Trusted Extensions. The *Trusted Extensions User's Guide* describes these interfaces from the end user's point of view, as well as the functionality that is provided by the Label Builder library routines.

This chapter covers the following topics:

- “APIs for Label Builder GUIs” on page 81
- “Creating an Interactive User Interface” on page 82
- “Online Help for Label Builder” on page 90

APIs for Label Builder GUIs

To use the APIs that are described in this section, you need to include the following header file:

```
#include <Dt/ModLabel.h>
```

The Label Builder examples compile with the `-lDtTsol` and `-ltsol` library options.

The following APIs are available for building label GUIs. The data types and parameter lists are described in “[Creating an Interactive User Interface](#)” on page 82.

```
ModLabelData *tsol_lbuild_create(Widget widget, void (*event_handler)()
ok_callback, lbuild_attributes extended_operation, ..., NULL);
```

The `tsol_lbuild_create()` routine creates the GUI and returns a pointer variable of type `ModLabelData`, which contains information about the user interface. This information is a

combination of values passed in the `tsol_lbuild_create()` input parameter list, default values for information not provided, and information about the widgets that the Label Builder uses to create the user interface.

The `LBUILD_WORK_SL` and `LBUILD_WORK_CLR` operation values are not valid for `tsol_lbuild_create()` because these values are set from input that is supplied by the user.

You can use the `tsol_lbuild_get()` and `tsol_lbuild_set()` routines to obtain and set extended operations and values. However, these routines cannot be used for widget information, which is accessed directly by referencing fields in the `ModLabelData` structure. See the [labelbuilder\(3TSOL\)](#) man page.

```
void tsol_lbuild_destroy(ModLabelData *lbdata);
```

The `tsol_lbuild_destroy()` routine destroys the `ModLabelData` structure that is returned by the `tsol_lbuild_create()` routine.

```
void *tsol_lbuild_get(ModLabelData *lbdata, lbuild_attributes  
extended_operation);
```

The `tsol_lbuild_get()` routine accesses the user interface information that is created by `tsol_lbuild_create()` and stored in the `ModLabelData` structure.


```
void tsol_lbuild_set(ModLabelData *lbdata, lbuild_attributes  
extended_operation, ..., NULL);
```

The `tsol_lbuild_set()` routine changes the user interface information that is created by `tsol_lbuild_create()` and stored in the `ModLabelData` structure. The `LBUILD_WORK_SL` and `LBUILD_WORK_CLR` operation values are not valid for `tsol_lbuild_set()` because these values are set from input that is supplied by the user.

Creating an Interactive User Interface

The following figure shows a GUI similar to the one created by the code that follows the figure. The main program creates a parent form (*form*) with one button (*display*). The button callback shows the Label Builder dialog box that is created by the call to the `tsol_lbuild_create()` routine. See the [tsol_lbuild_create\(3TSOL\)](#) man page.

FIGURE 7-1 Label Building Interface



The Label Builder dialog box appears when you click the Show button in the parent form. The callouts indicate where the parameters passed to the `tsol_lbuild_create()` routine appear in the Label Builder dialog box. See the [tsol_lbuild_create\(3TSOL\)](#) man page.

The following code creates a GUI something like that shown by the figure.

```
#include <X11/Intrinsic.h>
#include <X11/StringDefs.h>
#include <Xm/Xm.h>
#include <Xm/PushButton.h>
#include <Xm/Form.h>
#include <Dt/ModLabel.h>
```

```
ModLabelData *data;
```

```
/* Callback passed to tsol_lbuild_create() */
void callback_function()
{
    char *title, *userval;
    char *string = (char *)0;
    char *string1 = (char *)0;
    int mode, view;
    Boolean show;
    m_label_t *sl_label, *work_sl_label;
    Position x, y;

    /* Your application-specific implementation goes here */
    printf("OK button called\n");

    /* Query settings */
    mode = (int)tsol_lbuild_get(data, LBUILD_MODE);
    title = (String)tsol_lbuild_get(data, LBUILD_TITLE);
    sl_label = (m_label_t*) tsol_lbuild_get(data, LBUILD_VALUE_SL);
    work_sl_label = (m_label_t*) tsol_lbuild_get(data, LBUILD_WORK_SL);
    view = (int)tsol_lbuild_get(data, LBUILD_VIEW);
    x = (Position ) tsol_lbuild_get(data, LBUILD_X);
    y = (Position ) tsol_lbuild_get(data, LBUILD_Y);
    userval = (char *)tsol_lbuild_get(data, LBUILD_USERFIELD);
    show = (Boolean )tsol_lbuild_get(data, LBUILD_SHOW);

    label_to_str(sl_label, &string, M_LABEL, LONG_NAMES);
    label_to_str(work_sl_label, &string1, M_LABEL, LONG_NAMES);
    printf("Mode = %d, Title = %s, SL = %s, WorkSL = %s, View = %d, ",
           mode, title, string, string1, view);
    printf("X = %d, Y = %d, Userval = %s, Show = %d\n",
           x, y, userval, show);
}

/* Callback to display dialog box upon button press */
void Show(Widget display, caddr_t client_data, caddr_t call_data)
{
    tsol_lbuild_set(data, LBUILD_SHOW, TRUE, NULL);
}

main(int argc, char **argv)
{
    Widget      form, topLevel, display;
    Arg args[9];
    int i = 0, error, retval;
    char *sl_string = "CNF";
    m_label_t * sl_label;

    topLevel = XtInitialize(argv[0], "XMcmds1", NULL, 0, &argc, argv);
    form = XtCreateManagedWidget("form",
                                   xmFormWidgetClass, topLevel, NULL, 0);

    retval = str_to_label(sl_string, &sl_label, MAC_LABEL, L_NO_CORRECTION, NULL);
    printf("Retval = %d\n", retval);

    data = tsol_lbuild_create( form, callback_function,
                               LBUILD_MODE, LBUILD_MODE_SL,
                               LBUILD_TITLE, "Building Sensitivity Label",
```

```

        LBUILD_VALUE_SL, sl_label,
        LBUILD_VIEW, LBUILD_VIEW_EXTERNAL,
        LBUILD_X, 200,
        LBUILD_Y, 200,
        LBUILD_USERFIELD, "/export/home/zelda",
        LBUILD_SHOW, FALSE,
        NULL);

    i = 0;
    XtSetArg(args[i], XmNtopAttachment, XmATTACH_FORM); i++;
    XtSetArg(args[i], XmNleftAttachment, XmATTACH_FORM); i++;
    XtSetArg(args[i], XmNrightAttachment, XmATTACH_FORM); i++;
    XtSetArg(args[i], XmNbottomAttachment, XmATTACH_FORM); i++;
    display = XtCreateManagedWidget("Show",
        xmPushButtonWidgetClass, form, args, i);
    XtAddCallback(display, XmNactivateCallback, Show, 0);
    XtRealizeWidget(topLevel);

    XtMainLoop();

    tsol_lbuild_destroy(data);
}

```

When run, the program produces the following output:

```

OK button called
Mode = 12, Title = Building Sensitivity label,
Label = CNF, WorkSL = SECRET,
View = 1, X = 200, Y = 200,
Userval = /export/home/zelda,
Show = 1

```

The following sections cover these topics:

- Label Builder behavior
- Application-specific functionality for Label Builder
- Privileged operations and Label Builder
- `tsol_lbuild_create()` routine
- Extended Label Builder operations
- `ModLabelData` structure

Label Builder Behavior

The Label Builder dialog box prompts the end user for information and generates a valid sensitivity label from the input. Label Builder ensures that a valid label or clearance is built. The labels and clearances are defined in the `label_encodings` file for the system.

Label Builder provides default behavior for the OK, Reset, Cancel, and Update buttons. The callback passed to the `tsol_lbuild_create()` routine is mapped to the OK button to provide application-specific behavior.

Keyboard Entry and Update Button

The Update button takes the text the user types in the Update With field and checks that the string is a valid label or clearance as defined in the `label_encodings` file.

- If the input is not valid, Label Builder generates an error for the user.
- If the input is valid, Label Builder updates the text in the Label field and stores the value in the appropriate working label field of the `ModLabelData` variable that is returned by the `tsol_lbuild_create()` routine. See [“ModLabelData Structure” on page 89](#).

When the user clicks OK, the user-built value is handled according to the OK button callback implementation.

Radio Button Options

The Label Settings radio button options enable you to build a sensitivity label or clearance from classifications and compartments. These options also enable you to build an information label from classifications, compartments, and markings. Depending on the mode, one of these buttons might be grayed out. This approach is independent of the keyboard entry and Update button method described in the previous section.

The information about the classifications, compartments, and markings is specified in the `label_encodings` file for the system. The combinations and constraints that are specified in the `label_encodings` file are enforced by graying out invalid combinations. The Label field is updated and the value is stored in the appropriate working label field of the `ModLabelData` variable that is returned by the `tsol_lbuild_create()` routine when the user chooses options. The user can build a sensitivity label or a clearance by selecting radio buttons in the classification (CLASS) and compartment (COMPS) lists.

When the user clicks OK, the user-built value is handled according to the OK button callback implementation.

Reset Button

The Reset button sets the text in the Label field to what its value was when the application started.

Cancel Button

The Cancel button exits the application without saving any changes.

Application-Specific Functionality for Label Builder

The Label Builder GUI generates a valid label or clearance. You must also add application-specific callbacks, error handling, and other functionality that is associated with that label or clearance.

Privileged Operations and Label Builder

Label Builder shows the user only those classifications and related compartments that are dominated by the workspace sensitivity label. If the executable has the `sys_trans_label` privilege in its effective set, more classifications and compartments might be shown.

Your application-specific implementation for the OK button callback might require privileges.

If the user does not have the authorization to upgrade or downgrade labels, the OK and Reset buttons are grayed out. The same is true if the user-built label is out of the user's range. The grayed-out buttons prevent the user from completing the task. No privileges can override these restrictions.

tsol_lbuild_create() Routine

The `tsol_lbuild_create()` routine accepts any widget, a callback function, and a null-terminated series of name and value pairs. The name represents an operation. The routine returns a variable of type `ModLabelData`.

The following describes the information accepted by the `tsol_lbuild_create()` routine:

- **Widget** – Label Builder can build the dialog box from any widget.
- **Callback function** – The callback function activates when the OK button is clicked. This callback function provides application-specific behavior.
- **Name and value pairs** – The name (left) side of the pair specifies an extended operation (see [“Extended Label Builder Operations” on page 88](#)) and the value (right) side specifies the value. In some cases, the value is an enumerated constant. In other cases, you provide a value. The pairs can be specified in any order, but every operation you specify requires a valid value.

The return value is a data structure that contains information about the dialog box that was just created. The information comes from the `tsol_lbuild_create()` input parameters and user activities during execution. Label Builder provides default values for some fields where no values have been specified.

Use the `tsol_lbuild_get()` routine and the `tsol_lbuild_set()` routine to programmatically access and change the information in these name and value pairs. The data structure is described in [“ModLabelData Structure” on page 89](#).

The following shows a sample call to the `tsol_lbuild_create()` routine:

```
data= tsol_lbuild_create(form, callback_function,
    LBUILD_MODE, LBUILD_MODE_SL,
    LBUILD_TITLE, "Building a Label",
    LBUILD_VALUE_SL, sl_label,
    LBUILD_VIEW, LBUILD_VIEW_EXTERNAL,
    LBUILD_X, 200,
    LBUILD_Y, 200,
```

```
LBUILD_USERFIELD "/export/home/zelda",  
LBUILD_SHOW, FALSE,  
NULL);
```

Extended Label Builder Operations

This section describes the extended operations and valid values that you can pass to the `tsol_lbuild_create()`, `tsol_lbuild_get()`, and `tsol_lbuild_set()` routines. The values that are passed to `tsol_lbuild_create()` are stored in its return value. The return value is of type `ModLabelData`. The values returned in the parameters can be accessed by calls to `tsol_lbuild_get()` and `tsol_lbuild_set()`. The `ModLabelData` structure is described in [“ModLabelData Structure” on page 89](#). See the [`tsol_lbuild_create\(3TSOL\)`](#), [`tsol_lbuild_get\(3TSOL\)`](#), and [`tsol_lbuild_set\(3TSOL\)`](#) man pages.

All extended operations are valid to pass to `tsol_lbuild_get()`. However, the `LBUILD_WORK_SL` and `LBUILD_WORK_CLR` operations are not valid to pass to `tsol_lbuild_set()` or `tsol_lbuild_create()` because these values are set by Label Builder based on user input. These exceptions are noted in the following operation descriptions:

- `LBUILD_MODE` – You can instruct `tsol_lbuild_create()` to create a user interface to build sensitivity labels or clearances. The default value is `LBUILD_MODE_SL`.
 - `LBUILD_MODE_SL` – Builds a sensitivity label.
 - `LBUILD_MODE_CLR` – Builds a clearance.
- `LBUILD_VALUE_SL` – The starting sensitivity label that is shown in the Label field when the mode is `LBUILD_MODE_SL`. The default value is `ADMIN_LOW`.
- `LBUILD_VALUE_CLR` – The starting clearance that is shown in the Label field when the mode is `LBUILD_MODE_CLR`. The default value is `ADMIN_LOW`.
- `LBUILD_USERFIELD` – A character string prompt that appears at the top of the Label Builder dialog box. The default value is `NULL`.
- `LBUILD_SHOW` – Shows or hides the Label Builder dialog box. The default value is `FALSE`.
 - `TRUE` – Shows the Label Builder dialog box.
 - `FALSE` – Hides the Label Builder dialog box.
- `LBUILD_TITLE` – A character string title that appears at the top of the Label Builder dialog box. The default value is `NULL`.
- `LBUILD_WORK_SL` – The sensitivity label that the user is building. This value is updated based on the user's input when the user selects the Update button or interactively chooses an option. The default value is `ADMIN_LOW`, which is not valid if an extended operation is specified with `tsol_lbuild_set()` or `tsol_lbuild_create()`.
- `LBUILD_WORK_CLR` – The clearance that the user is building. This value is updated based on the user's input when the user selects the Update button or interactively chooses an option. The default value is `ADMIN_LOW`, which is not valid if an extended operation is specified with `tsol_lbuild_set()` or `tsol_lbuild_create()`.

- **LBUILD_X** – The X offset in pixels from the upper left corner of the Label Builder dialog box in relation to the upper left corner of the screen. By default, the Label Builder dialog box is positioned in the middle of the screen.
- **LBUILD_Y** – The Y offset in pixels from the upper left corner of the Label Builder dialog box in relation to the upper left corner of the screen. By default, the Label Builder dialog box is positioned in the middle of the screen.
- **LBUILD_UPPER_BOUND** – The highest classification, and related compartments and markings, that are available to the user as radio buttons. These buttons are used to interactively build a label or a clearance. A value you supply must be within the user's range. If no value is supplied, this value is the user's workspace sensitivity label. Or, if the executable has the `sys_trans_label` privilege, this value is the user's clearance.
- **LBUILD_LOWER_BOUND** – The lowest classification, and related compartments and markings, that are available to the user as radio buttons. These buttons are used to interactively build a label or a clearance. This value is the user's minimum label. If no value is specified, the value is based on the default specified by the user's attributes.
- **LBUILD_CHECK_AR** – Checks whether the user-built label is within the user's range. A value of 1 means “check,” and a value of 0 means “do not check.” If the label is out of range, an error message is displayed to the user. The default value is 1.
- **LBUILD_VIEW** – Determines whether to use the internal or the external label representation. The default value is **LBUILD_VIEW_EXTERNAL**.
 - **LBUILD_VIEW_INTERNAL** – Uses the internal names for the highest and lowest labels in the system, `ADMIN_HIGH` and `ADMIN_LOW`.
 - **LBUILD_VIEW_EXTERNAL** – Promotes an `ADMIN_LOW` label to the next lowest label and demotes an `ADMIN_HIGH` label to the next highest label.

ModLabelData Structure

The `ModLabelData` structure contains information about the state of the Label Builder interface that is created by the call to the `tsol_lbbuild_create()` routine. The following table describes the `ModLabelData` fields. All fields, except for the widgets and the callbacks, are accessible by specifying the associated extended operation and a valid value in a call to `tsol_lbbuild_set()` or `tsol_lbbuild_get()`. For descriptions of the extended operations, see [“Extended Label Builder Operations” on page 88](#).

TABLE 7-1 ModLabelData Structure

Extended Operation or Description	Data Type	Field	Comments
<code>LBUILD_CHECK_AR</code>	<code>int</code>	<code>check_ar</code>	
<code>LBUILD_MODE</code>	<code>int</code>	<code>mode</code>	
<code>LBUILD_SHOW</code>	<code>Bool</code>	<code>show</code>	

TABLE 7-1 ModLabelData Structure (Continued)

Extended Operation or Description	Data Type	Field	Comments
LBUILD_TITLE	char	*lbuild_title	
LBUILD_UPPER_BOUND, LBUILD_LOWER_BOUND	brange_t	range	
LBUILD_USERFIELD	char	*userfield	
LBUILD_VALUE_CLR	bclear_t	*clr	
LBUILD_VALUE_SL	m_label_t	*sl	
LBUILD_VIEW	int	view	
LBUILD_WORK_CLR	bclear_t	*clr_work	Not valid for tsol_lbuild_set() or tsol_lbuild_create()
LBUILD_WORK_SL	m_label_t	*sl_work	Not valid for tsol_lbuild_set() or tsol_lbuild_create()
LBUILD_X	Position	x	
LBUILD_Y	Position	y	
Callback passed to tsol_lbuild_create()	void	(*event_handler)()	
Cancel button	Widget	cancel	
Help button	Widget	help	
Label Builder dialog box	Widget	lbuild_dialog	
OK button	Widget	ok	
Reset button	Widget	reset	
Update button	Widget	update	

Online Help for Label Builder

The Help button and other widgets that are used in the user interface can be accessed directly from your application code through the lbl_shell field in the ModLabelData structure. To add online help to your application, follow the procedures and guidelines in the *Common Desktop Environment: Help System Author's and Programmer's Guide*.

Trusted Web Guard Prototype

This chapter describes the configuration of a safe web browsing prototype called Web Guard. Web Guard is configured to isolate a web server and its web content to prevent attacks from the Internet.

The Web Guard prototype described in this chapter is not a complete solution. Rather, the prototype is intended to demonstrate how multilevel ports can be used to proxy URL requests across label boundaries. A more complete solution would include authentication, data filtering, auditing, and so on.

The primary implementation of the prototype is administrative. The prototype uses multilevel ports, trusted networking, and Apache web server configuration to set up Web Guard. In addition to the administrative example, you can use some programmatic methods to set up the safe web browsing prototype.

This chapter covers the following topics:


- [“Administrative Web Guard Prototype” on page 91](#)
- [“Accessing Lower-Level Untrusted Servers” on page 98](#)

Administrative Web Guard Prototype

This section provides an example of a safe web browsing prototype that isolates a web server and its web content to prevent attacks from the Internet. This Web Guard prototype takes advantage of administrative trusted networking features to configure a two-stage filter that restricts access to a protected web server and web content. This prototype was implemented solely by administrative means. No programming was required.

The following figure shows the configuration of the Web Guard prototype in a multilevel environment. The label relationships are shown by how the labels are positioned in the figure. Vertical relationships represent label dominance, while horizontal relationships represent disjoint labels.

FIGURE 8-1 Web Guard Configuration



Web requests come in to the web server that is configured in the public zone and are passed to the web server that is configured in the restricted zone.

The restricted zone uses a multilevel port (MLP) to listen for requests at port 8080 of the public zone. This web server passes the requests to the webservice labeled zone.

The webservice zone also uses an MLP to listen for requests at port 80 of the restricted zone and reads content from the webcontent labeled zone.

The webcontent zone is in the ready state and has its web content stored in the /export/home file system, which is automatically mounted in all other labeled zones. When a zone is in the ready state, no processes run in that zone. Thus, the zone is essentially a disk drive attached directly to the webservice zone.

You configure the Web Guard prototype by performing these high-level tasks:

1. Modifying the `label_encodings` file to configure the labels in your safe web browsing environment

The default `label_encodings` file is updated to configure two new labels: WEB GUARD SERVICE and WEB GUARD CONTENT. See [“Modifying the label_encodings File” on page 93](#).

2. Configuring trusted networking

The private IP addresses and MLPs are configured on the restricted and webservice labeled zones. See [“Configuring Trusted Networking” on page 95](#).

3. Configuring the Apache web servers

The public, restricted, and webservice zones all have web servers configured. In this example, the web server used is Apache. See [“Configuring the Apache Web Servers” on page 97](#).

Modifying the label_encodings File

The default label_encodings file is updated to configure two new labels: WEB GUARD SERVICE and WEB GUARD CONTENT. The SANDBOX label, which is part of the default file, is modified to serve as the WEB GUARD CONTENT label. The WEB GUARD SERVICE label is added.

You must install the label_encodings file in the /etc/security/tsol directory. You can install this file on top of an existing Trusted Extensions installation.

After you install the updated file in the /etc/security/tsol directory, activate the new label_encodings file:

```
# svcadm restart svc:/system/labeld
```

The following shows the label_encodings file used in this Web Guard prototype.

```
* ident      "@(#)label_encodings.simple    5.15    05/08/09 SMI"
*
* Copyright 2005 Sun Microsystems, Inc. All rights reserved.
* Use is subject to license terms.
*
* This example shows how to specify labels that meet an actual
* site's legal information protection requirements for
* labeling email and printer output. These labels may also
* be used to enforce mandatory access control checks based on user
* clearance labels and sensitivity labels on files and directories.

VERSION= Sun Microsystems, Inc. Example Version - 6.0. 2/15/05

CLASSIFICATIONS:

name= PUBLIC; sname= PUB; value= 2; initial compartments= 4;
name= CONFIDENTIAL; sname= CNF; value= 4; initial compartments= 4;
name= WEB GUARD; sname= WEB; value= 5; initial compartments= 0;
name= MAX LABEL; sname= MAX; value= 10; initial compartments= 0 4 5;

INFORMATION LABELS:

WORDS:

name= ;; prefix;

name= INTERNAL USE ONLY; sname= INTERNAL; compartments= 1 ~2; minclass= CNF;
name= NEED TO KNOW; sname= NEED TO KNOW; compartments= 1-2 ~3; minclass= CNF;
name= RESTRICTED; compartments= 1-3; minclass= CNF;
name= CONTENT; compartments= 0 ~1 ~2 ~3; minclass= WEB;
```

```

name= SERVICE; compartments= 5; minclass= WEB;

REQUIRED COMBINATIONS:

COMBINATION CONSTRAINTS:

SENSITIVITY LABELS:

WORDS:

name= ;; prefix;

name= INTERNAL USE ONLY; sname= INTERNAL; compartments= 1 ~2; minclass= CNF;
prefix= :

name= NEED TO KNOW; sname= NEED TO KNOW; compartments= 1-2 ~3; minclass= CNF;
prefix= :

name= RESTRICTED; compartments= 1-3; minclass= CNF; prefix= :

name= CONTENT; compartments= 0 ~1 ~2 ~3; minclass= WEB;

name= SERVICE; compartments= 5; minclass= WEB;

REQUIRED COMBINATIONS:

COMBINATION CONSTRAINTS:

CLEARANCES:

WORDS:

name= INTERNAL USE ONLY; sname= INTERNAL; compartments= 1 ~2; minclass= CNF;
name= NEED TO KNOW; sname= NEED TO KNOW; compartments= 1-2 ~3; minclass= CNF;
name= RESTRICTED; sname= RESTRICTED; compartments= 1-3; minclass= CNF;
name= CONTENT; compartments= 0 ~1 ~2 ~3; minclass= WEB;
name= SERVICE; compartments= 5; minclass= WEB;

REQUIRED COMBINATIONS:

COMBINATION CONSTRAINTS:

CHANNELS:

WORDS:

PRINTER BANNERS:

WORDS:

ACCREDITATION RANGE:

classification= PUB; all compartment combinations valid;
classification= WEB; all compartment combinations valid;
classification= CNF; all compartment combinations valid except: CNF

minimum clearance= PUB;
minimum sensitivity label= PUB;
minimum protect as classification= PUB;

```

* Local site definitions and locally configurable options.

LOCAL DEFINITIONS:

default flags= 0x0;
forced flags= 0x0;

Default Label View is Internal;

Classification Name= Classification;
Compartments Name= Sensitivity;

Default User Sensitivity Label= PUB;
Default User Clearance= CNF NEED TO KNOW;

COLOR NAMES:

```
label= Admin_Low;           color= #bdbdbd;

label= PUB;                  color= blue violet;
label= WEB SERVICE;         color= yellow;
label= CNF;                  color= navy blue;
label= CNF : INTERNAL USE ONLY; color= blue;
label= CNF : NEED TO KNOW;  color= #00bfff;
label= CNF : RESTRICTED;    color= #87ceff;

label= Admin_High;          color= #636363;
```

* End of local site definitions

For more information about the label_encodings file, see [Trusted Extensions Label Administration](#).

Configuring Trusted Networking

The restricted and webservice zones are assigned a private IP address in addition to the IP address that they already share. Each private IP address has a multilevel port configured and is associated with a restricted label set.

The following table shows the network configuration for each of the labeled zones.

Zone Name	Zone Label	Local IP Address	Host Name	Multilevel Port	Security Label Set
restricted	CONFIDENTIAL : RESTRICTED	10.4.5.6	proxy	8080/tcp	PUBLIC
webservice	WEB GUARD SERVICE	10.1.2.3	webservice	80/tcp	CONFIDENTIAL : RESTRICTED
webcontent	WEB GUARD CONTENT	None			

First, you must create the new zones. You can clone an existing zone, such as the `public` zone. After these zones are created, use the `zonecfg` command to add a network (with the address specified in the table) and your local interface name.

For example, the following command associates the `10.4.5.6` IP address and the `bge0` interface with the `restricted` zone:

```
# zonecfg -z restricted
add net
set address=10.4.5.6
set physical=bge0
end
exit
```

After you specify the IP address and network interface for each labeled zone, you use the Solaris Management Console to configure the remaining values in the table. When using this tool, make sure that you select the tool box with `Scope=Files` and `Policy=TSOL`.

Follow these steps to finish the zone configuration:

1. Start the Solaris Management Console as superuser.

```
# smc &
```
2. From the Navigation panel, select This Computer, and then click the System Configuration icon.
3. Click the Computers and Network icon.
4. Click the Computers icon, and then choose Add Computer from the Action menu.
5. Add the host names and IP addresses for the proxy host and the webservice host.
6. From the Navigation panel, select Trusted Network Zones.

You might need to expand the columns. If the zone names do not appear in the list, choose Add Zone Configuration from the Action menu.

7. Assign each zone its label and specify the appropriate port and protocol in the MLP Configuration for Local IP Addresses field.
8. From the Navigation panel, click the Security Families icon and choose Add Template from the Action menu.

Add templates for the proxy host name and the webservices host name based on the information in the table.

- a. Specify the corresponding host name for the template name.
- b. Specify CIPSO in the Host Type field.
- c. Specify the corresponding zone label in the Minimum Label and Maximum Label fields.
- d. Specify the corresponding security label in the Security Label Set field.
- e. Click the Hosts Explicitly Assigned tab.
- f. In the Add an Entry section, add the corresponding local IP address to each template.

9. Exit the Solaris Management Console.

After you exit the Solaris Management Console, start or restart the affected zones. In the global zone, add routes for the new addresses, where *shared-IP-addr* is the shared IP address.

```
# route add proxy shared-IP-addr
# route add webservice shared-IP-addr
```

Configuring the Apache Web Servers

An instance of the Apache web server runs in the public zone, the restricted zone, and the webservice zone. The `/etc/apache/httpd.conf` file is updated in each of the zones as follows:

- **public zone** – Specify the IP address or host name of the server for the `ServerName` keyword, and update the proxy configuration as follows:

```
ServerName myserver

ProxyRequests Off
ProxyPass /demo http://proxy:8080/demo
ProxyPassReverse /demo http://proxy:8080/demo
```

- **restricted zone** – Specify the listen proxy port and the port. Then, specify the IP address or host name of this zone for the `ServerName` keyword, and update the proxy configuration as follows:

```
Listen proxy:8080
Port 8080

ServerName proxy

ProxyRequests Off
ProxyPass /demo http://webservice
ProxyPassReverse /demo http://webservice
```

You might also want to set up some filtering of the web requests, such as dirty word filters, or other filters to restrict the types of requests for web content.

- **webservice zone** – Specify the IP address or host name of this zone for the `ServerName` keyword, and point to the location of the web content directory in the `DocumentRoot` keyword and the `<Directory>` element as follows:

```
ServerName webservice

DocumentRoot "/zone/webcontent/export/home/www/htdocs"
<Directory "/zone/webcontent/export/home/www/htdocs">
```

After you have updated the Apache web server configuration files for each labeled zone, store your web content in the `/export/home/www/htdocs` directory of the webcontent zone.

Create the demo directory in the `/export/home/www/htdocs` directory, and then create an `index.html` file in the demo directory to use for testing.

The `/export/home` directory is automatically mounted by using `lofs` into the `webservice` zone when it is booted. The `webcontent` zone only needs to be brought up to the ready state.

```
# zoneadm -z webcontent ready
```

When a zone is in the ready state, no processes are running in that zone. The zone's file system can be mounted read-only by the `webservice` zone. Accessing the web content in this way ensures that the content cannot be changed.

Running the Trusted Web Guard Demonstration

From your browser in the `public` zone or from a remote browser running at the `PUBLIC` label, type the following URL:

```
http://server-name/demo
```

The browser should show the default `index.html` file from the `webcontent` zone.

Note that the Web Guard flow cannot be bypassed. The web server in the `webservice` zone cannot receive packets from the `public` zone or from any remote host. The web content cannot be changed because the `webcontent` zone is in the ready state.

Accessing Lower-Level Untrusted Servers

Sometimes a client needs to be able to access a server on an unlabeled system. An *unlabeled system* is a system that does not run the Trusted Extensions software. In such a case, you cannot use multilevel ports because they are restricted to privileged servers that run in the global zone or in labeled zones.

For example, suppose your browser is running in the `INTERNAL` zone. You want to access a web server that runs on a single-level network that has been assigned the `PUBLIC` sensitivity label by means of the `tnrhdb` database. Such access is not permitted by default. However, you could write a privileged proxy server to forward the HTTP request to the `PUBLIC` web server. The proxy should use a special Trusted Extensions socket option called `SO_MAC_EXEMPT`. This socket option permits a request to be sent to an untrusted lower-level service, and permits the reply from that service to be returned to the requester.

Note – The use of the `SO_MAC_EXEMPT` option represents an unprotected downgrade channel and should be used *very carefully*. The `SO_MAC_EXEMPT` option cannot be set unless the calling process has the `PRIV_NET_MAC_AWARE` privilege in its effective set. Such a process must enforce its own data filtering policy to prevent leaking higher-level data to the lower-level service. For example, the proxy should sanitize URLs to restrict words from being used as values.

The following code excerpt demonstrates the use of `SO_MAC_EXEMPT` in a modified version of the `wget` command's `connect_to_ip()` routine in `connect.c`. The call to `setsockopt()` has been added to show how to set the `SO_MAC_EXEMPT` option.

```
int
connect_to_ip (const ip_address *ip, int port, const char *print)
{
    struct sockaddr_storage ss;
    struct sockaddr *sa = (struct sockaddr *)&ss;
    int sock;
    int on = 1;

    /* If PRINT is non-NULL, print the "Connecting to..." line, with
       PRINT being the host name we're connecting to. */
    if (print)
    {
        const char *txt_addr = pretty_print_address (ip);
        if (print && 0 != strcmp (print, txt_addr))
            logprintf (LOG_VERBOSE, _("Connecting to %s|%s|:%d... "),
                      escnonprint (print), txt_addr, port);
        else
            logprintf (LOG_VERBOSE, _("Connecting to %s:%d... "), txt_addr, port);
    }

    /* Store the sockaddr info to SA. */
    sockaddr_set_data (sa, ip, port);

    /* Create the socket of the family appropriate for the address. */
    sock = socket (sa->sa_family, SOCK_STREAM, 0);
    if (sock < 0)
        goto err;

    if (setsockopt (sock, SOL_SOCKET, SO_MAC_EXEMPT, &on, sizeof (on)) == -1) {
        perror("setsockopt SO_MAC_EXEMPT");
    }

#ifdef ENABLE_IPV6 && defined(IPV6_V6ONLY)
    if (opt.ipv6_only) {
        /* In case of error, we will go on anyway... */
        int err = setsockopt (sock, IPPROTO_IPV6, IPV6_V6ONLY, &on, sizeof (on));
    }
#endif
}
```


Experimental Java Bindings for the Solaris Trusted Extensions Label APIs

This chapter describes an experimental set of Java classes and methods that mirror the label application programming interfaces (APIs) that are provided with the Trusted Extensions software. The Java implementation of the Trusted Extensions label APIs is intended to be used to create label-aware applications. As a result, all of the label APIs provided by Trusted Extensions are not part of the Java implementation.

The presentation of these experimental Java APIs (Java bindings) demonstrate how the Trusted Extensions features can be expanded into the Java development environment.



Caution – These experimental Java bindings are *not* a supported part of the Trusted Extensions software.

This chapter covers the following topics:

- [“Java Bindings Overview” on page 101](#)
- [“Structure of the Experimental Java Label Interfaces” on page 102](#)
- [“Java Bindings” on page 104](#)

Java Bindings Overview

The Java language is an untapped resource for creating label-aware applications that run in secure, multilevel arenas. These experimental Java bindings provide a foundation on which to develop more applications, such as system audit log generation and system resource controls.

Adding platform services to the Java environment will enable Java applications to handle sensitive multilevel data.

Trusted Extensions provides label services through the label daemon, `labeld`. This daemon is available to processes that run in the global zone and in labeled zones.

The Java bindings described in this chapter are Java Native Interface (JNI) implementations of some of the Trusted Extensions label APIs. The experimental JNI code calls the Trusted Extensions label library functions to extend some of the label functionality to the Java language. Constructors and methods in these Java classes call private JNI interfaces, written in C, that in turn call the Trusted Extensions APIs. For example, the `SolarisLabel.dominates` method calls a private JNI interface written in C that calls the `blDominates()` routine. These experimental Java bindings have been developed using Java 2 Platform, Standard Edition 5.0. For more information about JNI, see [Java Native Interface Documentation \(http://download.oracle.com/javase/1.5.0/docs/guide/jni/\)](http://download.oracle.com/javase/1.5.0/docs/guide/jni/).

Structure of the Experimental Java Label Interfaces

The JNI implementation of the Trusted Extensions label APIs introduces several label-related classes that relate to each other in this way:

- `SolarisLabel` abstract class
 - `ClearanceLabel` subclass
 - `SensitivityLabel` subclass
- `Range` class

`SolarisLabel` Abstract Class

The `SolarisLabel` abstract class provides the foundation for common and native methods related to Trusted Extensions labels. The `SensitivityLabel` and `ClearanceLabel` subclasses inherit members from this abstract class. Static factories for creating sensitivity labels and clearance labels are also provided by the abstract class.

Static factories and methods throw exceptions when errors are encountered to ensure that no mandatory access control-related errors occur silently.

This abstract class defines the following general-purpose methods that are used to compare labels and to translate labels to strings:

- `dominates`
- `equals`
- `setFileLabel`
- `strictlyDominates`
- `toColor`
- `toInternal`
- `toRootPath`
- `toString`
- `toText`
- `toTextLong`

- `toTextShort`

The `equals`, `dominates`, and `strictlyDominates` methods are analogous to the `blequal()`, `bldominates()`, and `blstrictdom()` label APIs currently available with Trusted Extensions. The `setFileLabel` method is analogous to the `setflabel()` routine currently available with Trusted Extensions.

The rest of the methods (such as `toText`, `toInternal`, and `toColor`) are related in function to the `label_to_str()` routine that is currently available with Trusted Extensions. These methods enable you to translate a label to a particular type of string. Depending on the label relationship of the process and the object, you might need privileges in your effective set to translate a label to a human-readable form. For instance, the Java Virtual Machine (JVM) process must be running with the `sys_trans_label` privilege to translate labels that it does not dominate.

The `SolarisLabel` abstract class also includes the following static factories:

- `getClearanceLabel`
- `getFileLabel`
- `getSensitivityLabel`
- `getSocketPeer`

The string that you pass as a label to `getSensitivityLabel` or `getClearanceLabel` can be in one of the following forms:

- Human-readable form of the label, such as `PUBLIC`
- Internal form of the label, such as `0x0002-08-08`

Only the internal form of the label is suitable for storage and for transmission over a network connection, as the internal form does not reveal the actual label. For more information, see [“Readable Versions of Labels” on page 35](#).

The `ClearanceLabel` and `SensitivityLabel` subclasses extend the `SolarisLabel` abstract class. These subclasses each inherit the common methods provided by the `SolarisLabel` abstract class.

ClearanceLabel Subclass

The `ClearanceLabel` subclass extends the `SolarisLabel` abstract class and defines the `getMaximum` and `getMinimum` methods, which return the `ClearanceLabel` object that represents the least upper bound and the greatest lower bound, respectively.

SensitivityLabel Subclass

The `SensitivityLabel` subclass extends the `SolarisLabel` abstract class and defines the `getMaximum` and `getMinimum` methods, which return the `SensitivityLabel` object that represents the least upper bound and the greatest lower bound, respectively.

The `SensitivityLabel` subclass introduces the following methods that provide information suitable for labeled printer banner pages:

- `toCaveats`
- `toChannels`
- `toFooter`
- `toHeader`
- `toProtectAs`

Range Class

The `Range` class represents a Java version of a Trusted Extensions label range.

This class defines the following general-purpose methods that are used to obtain the upper and lower labels in a label range and to determine whether a label is within a specified label range:

- `getLower`
- `getUpper`
- `inRange`

The `Range` class also includes the following static factories that create range objects:

- `getDeviceRange`
- `getLabelRange`
- `getUserRange`

The `getDeviceRange` and `getUserRange` static factories create range objects based on the range for the specified device and the specified user, respectively. The `getLabelRange` static factory enables you to create a label range where you specify the upper and lower bounds for the range.

Java Bindings

The Java implementation of the Trusted Extensions label APIs is intended to be used to create label-aware applications. As a result, not all of the label APIs provided by Trusted Extensions are part of the Java implementation.

The Java classes and methods that are presented in this chapter mimic the following general label functionality shown in [“Label APIs” on page 29](#):

- Detecting a Trusted Extensions system
- Accessing the process sensitivity label
- Allocating and freeing memory for label objects
- Obtaining and setting the label of a file
- Obtaining label range objects
- Accessing labels in zones

- Obtaining the remote host type
- Translating between labels and strings
- Comparing label objects

Detecting a Trusted Extensions System

These Java bindings do not include methods to determine whether a system is labeled. Rather, the library will fail to load if Trusted Extensions is not enabled.

Accessing the Process Sensitivity Label

These Java bindings do not include methods to obtain the label of a process. In Trusted Extensions, a process that runs in a labeled zone has the same label as the zone.

Allocating and Freeing Memory for Label Objects

These Java bindings take advantage of the Java “garbage-collection” functionality. As a result, you do not need to explicitly free the memory used by label objects as you do for the label APIs described in [“Obtaining and Setting the Label of a File” on page 31](#).

Obtaining and Setting the Label of a File

These Java bindings use the Java `File` object to obtain and set file labels. Use the `getFileLabel` static factory to obtain the label from the file's `File` object. To set a file label to another specified label, use the `setFileLabel` method on the file's `File` object.

In addition to obtaining the sensitivity label of a file, the `getSocketPeer` static factory enables you to obtain the sensitivity label for the peer endpoint of a socket.

The `getFileLabel` static factory and the `setFileLabel` method correspond to the `getlabel()` system call and the `setflabel()` routine, respectively. For more information, see [“Obtaining and Setting the Label of a File” on page 31](#) and the `getlabel(2)` and `setflabel(3TSOL)` man pages.

The following descriptions include the prototype declarations for the static factories and the method:

```
public static SensitivityLabel getFileLabel(java.io.File file)
```

The `getFileLabel` static factory obtains the label of a Java `File` object that is specified by *file*.

```
public static SensitivityLabel getSocketPeer(java.net.Socket socket)
```

The `getSocketPeer` static factory obtains a sensitivity label object from the specified socket, *socket*.

The following code fragment obtains the sensitivity label object of the socket, *s*:

```
SensitivityLabel sl = SolarisLabel.getSocketPeer(s);
```

The following example code shows how to create a server socket on port 9090 and then obtain the sensitivity label of the peer end of the accepted connection. This code example also outputs the internal and human-readable forms, the color, and the root path of the obtained socket peer label.

```
import java.io.*;
import java.net.*;
import solarismac.*;

public class ServerSocketTest
{
    public static void main (String args[]) {

        System.out.println("ServerSocketTest Start");

        CreateListner();

        System.out.println("ServerSocketTest End");

    }

    /*
     * Listen for connections on port then print the peer connection label.
     * You can use telnet host 9090 to create a client connection.
     */
    private static void CreateListner() {
        int port = 9090;

        ServerSocket acceptSocket;
        Socket s;
        try {
            System.out.println("Creating ServerSocket on port " + port);

            acceptSocket = new ServerSocket(port);

            System.out.println("ServerSocket created, waiting for connection");

            s = acceptSocket.accept();

            /*
             * Get the Sensitivity Label for the peer end of the socket.
             */
            SensitivityLabel socksl = SolarisLabel.getSocketPeer(s);

            System.out.println("Client connected...");
            System.out.println(" toInternal: " + socksl.toInternal());
            System.out.println(" toText: " + socksl.toText());
            System.out.println(" toString: " + socksl.toString());
            System.out.println(" toColor: " + socksl.toColor());
            System.out.println(" toRootPath: " + socksl.toRootPath());
        } catch (Exception e) {
            e.printStackTrace();
        }
    }
}
```

```

    }
}

public static void setFileLabel(java.io.File file, SensitivityLabel label)
    The setFileLabel method changes the sensitivity label of the specified file to the specified
    label. When the sensitivity label of a file changes, the file is moved to the zone that
    corresponds to the new label. The file is moved to a new path name that is relative to the root
    of the other zone.

```

For example, if you use the setFileLabel method to change the label of the file /zone/internal/documents/designdoc.odt from INTERNAL to RESTRICTED, the new path of the file will be /zone/restricted/documents/designdoc.odt. Note that if the destination directory does not exist, the file is not moved.

The following code fragment shows how you might change the label of the file:

```

SolarisLabel.setFileLabel(new File("/zone/internal/documents/designdoc.odt"),
    SolarisLabel.getSensitivityLabel("RESTRICTED"));

```

When you change the sensitivity label of a file, the original file is deleted. The only exception occurs when the source and destination file systems are loopback-mounted from the same underlying file system. In this case, the file is renamed.

The Java virtual machine must be running with the appropriate privilege (file_upgrade_sl or file_downgrade_sl) to relabel a file.

See also the [setflabel\(3TSOL\)](#) man page.

Obtaining Label Range Objects

The getLabelRange static factory creates a label range object. The getUserRange and getDeviceRange static factories obtain label range objects for a user and a device, respectively. The getUpper and getLower methods are used to obtain the upper and lower labels of the range, respectively. In addition, the inRange method determines whether the specified label is in a range. For more information about the inRange method, see [“Comparing Label Objects” on page 112](#).

The getUserRange and getDeviceRange static factories correspond to the getuserrange() and getdevicerange() routines. For more information, see [“Obtaining Label Ranges” on page 32](#).

The following constructor and method descriptions include the prototype declaration for each constructor:

```

public static Range getDeviceRange(java.lang.String device)
    The getDeviceRange static factory obtains the label range of a user-allocatable device. If no
    label range is specified for the device, the default range has an upper bound of ADMIN_HIGH
    and a lower bound of ADMIN_LOW.

```

You can use the `list_devices` command to show the label range for a device. See the [list_devices\(1\)](#) man page.

```
public static <L extends SolarisLabel, U extends SolarisLabel> Range  
getLabelRange(L lower, U upper)
```

The `getLabelRange` static factory creates a label range. The static factory takes the lower bound value in the range and the upper bound, or clearance, as parameters. An exception is thrown if *upper* does not dominate *lower*.

```
public L getLower()
```

The `getLower` method returns the lower portion of the range.

```
public U getUpper()
```

The `getUpper` method returns the upper portion of the range.

```
public static Range getUserRange(java.lang.String user)
```

The `getUserRange` static factory obtains the label range of the specified user. The lower bound in the range is used as the initial workspace label when a user logs in to a multilevel desktop. The upper bound, or clearance, is used as an upper limit to the available labels that a user can assign to labeled workspaces.

The default value for a user's label range is specified in the `label_encodings` file. The value can be overridden by the `user_attr` file.

For more information, see the [getuserrange\(3TSOL\)](#) man page.

Accessing Labels in Zones

The following description includes the prototype declaration for the method:

```
public final java.lang.String toRootPath()
```

This method returns the root path name of the zone for the specified sensitivity label.

The following code excerpt shows how to obtain the root path for the `PUBLIC` sensitivity label:

```
SensitivityLabel sl = SolarisLabel.getSensitivityLabel("PUBLIC");  
System.out.println("toRootPath: " + sl.toRootPath());
```

This method throws a `java.io.IOException` if an invalid label is specified or if no zone is configured for the specified label.

This method mimics the `getzonerootbylabel()` routine. See the [getzonerootbylabel\(3TSOL\)](#) man page. See also “[Accessing Labels in Zones](#)” on page 32.

Obtaining the Remote Host Type

The Java implementation of the Trusted Extensions label APIs does not include interfaces for obtaining the remote host type.

Translating Between Labels and Strings

The `SolarisLabel` abstract class includes methods for translating between labels and strings, which are inherited by its subclasses.

These methods translate the internal representation of a label (`m_label_t`) to `String` objects.

You can use the `toInternal` method to translate a label into a string that hides the classification name. This format is suitable for storing labels in public objects.

The running Java virtual machine must dominate the label to be translated, or it must have the `sys_trans_label` privilege. See the [label_to_str\(3TSOL\)](#) man page.

Some of the label values are based on data in the `label_encodings` file.

The following methods mimic the `label_to_str()` routine. See the [label_to_str\(3TSOL\)](#) man page.

```
public final java.lang.String toColor()
```

This method returns the color of the `SolarisLabel` object. The value is suitable for use by HTML.

```
public final java.lang.String toInternal()
```

This method returns the internal representation of the label that is safe for storing in a public object. An internal conversion can later be parsed to its same value. This is the same as using the `toString` method.

These two methods differ in the way that they handle errors. If the `toInternal` method encounters an error, it returns a `java.io.IOException`. However, if the `toString` method encounters an error, it returns a null.

```
public java.lang.String toString()
```

This method returns the internal hexadecimal version of the label in string form, which is the same as using the `toInternal` method.

These two methods differ in the way that they handle errors. If the `toString` method encounters an error, it returns a null. However, if the `toInternal` method encounters an error, it returns a `java.io.IOException`.

```
public java.lang.String toText()
```

This method returns a human-readable text string of the `SolarisLabel` object.

```
public java.lang.String toTextLong()
```

This method returns the long human-readable text string of the `SolarisLabel` object.

```
public java.lang.String toTextShort()
```

This method returns the short human-readable text string of the `SolarisLabel` object.

The following methods perform label translations that are suitable for creating multilevel printer banner pages. These methods mimic some of the functionality of the `label_to_str()` routine. See the [label_to_str\(3TSOL\)](#) and [m_label\(3TSOL\)](#) man pages.

```
public java.lang.String toCaveats()
```

This method returns a human-readable text string that is suitable for the caveats section of the banner page.

This method is only available for `SensitivityLabel` objects, not for `ClearanceLabel` objects.

```
public java.lang.String toChannels()
```

This method returns a human-readable text string that is suitable for the handling channels section of the banner page.

This method is only available for `SensitivityLabel` objects, not for `ClearanceLabel` objects.

```
public java.lang.String toFooter()
```

This method returns a human-readable text string that is appropriate for use as the sensitivity label. This sensitivity label appears at the bottom of banner and trailing pages.

This method is only available for `SensitivityLabel` objects, not for `ClearanceLabel` objects.

```
public java.lang.String toHeader()
```

This method returns a human-readable text string that is appropriate for use as the sensitivity label. This sensitivity label appears at the top of banner and trailing pages.

This method is only available for `SensitivityLabel` objects, not for `ClearanceLabel` objects.

```
public java.lang.String toProtectAs()
```

This method returns a human-readable text string that is suitable for the page downgrade section of the banner page.

This method is only available for `SensitivityLabel` objects, not for `ClearanceLabel` objects.

EXAMPLE 9-1 Using the Java Bindings to Create a Banner Page

The following example code shows how to use the Java bindings to create a banner page similar to the one described in [“Obtaining Printer Banner Information” on page 46](#).

```
import solarismac.*;
import java.io.*;
```

EXAMPLE 9-1 Using the Java Bindings to Create a Banner Page *(Continued)*

```

/*
 * Banner page example
 */
public class PrintTest1
{
    public static void main (String args[]) {
        try {
            // Pick a valid label using the label_encodings.example
            SensitivityLabel sl = SolarisLabel.getSensitivityLabel("TOP SECRET A B SA");

            // "Protect as classification"
            System.out.println(sl.toHeader());
            System.out.println();

            // "Protect as classification plus compartments"
            System.out.println("This output must be protected as:");
            System.out.println(sl.toProtectAs());
            System.out.println("unless manually reviewed and downgraded.");
            System.out.println();

            // Handling instructions specified in PRINTER BANNERS
            System.out.println(sl.toCaveats());
            System.out.println();

            // Handling instructions specified in CHANNELS
            System.out.println(sl.toChannels());
            System.out.println();

            // "Protect as classification"
            System.out.println(sl.toFooter());
            System.out.println();

        } catch (Exception e) {
            e.printStackTrace();
        }
    }
}

```

For a process label of TOP SECRET A B SA, the text output might be the following:

```

TOP SECRET

This output must be protected as:

TOP SECRET A B SA

unless manually reviewed and downgraded.

(FULL SA NAME)
HANDLE VIA (CH B)/(CH A) CHANNELS JOINTLY

TOP SECRET

```

Methods such as `toText`, `toInternal`, and `toColor` do not translate from a string to a label. To translate a string to a sensitivity label or to a clearance label, you must call the `getSensitivityLabel` or `getClearanceLabel` static factories, respectively. The following static factories mimic the `str_to_label()` routine. See the [str_to_label\(3TSOL\)](#) and [m_label\(3TSOL\)](#) man pages.

```
public static ClearanceLabel getClearanceLabel(java.lang.String label)
```

This static factory creates a clearance label from the specified string. The following examples create new clearance labels based on a label name and the internal hexadecimal name of a label:

```
ClearanceLabel cl = SolarisLabel.getClearanceLabel("PUBLIC");  
ClearanceLabel cl = SolarisLabel.getClearanceLabel("0x0002-08-08");
```

```
public static SensitivityLabel getSensitivityLabel(java.lang.String label)
```

This static factory creates a sensitivity label from the specified string. The following examples create new sensitivity labels based on a label name and the internal hexadecimal name of a label:

```
SensitivityLabel sl = SolarisLabel.getSensitivityLabel("PUBLIC");  
SensitivityLabel sl = SolarisLabel.getSensitivityLabel("0x0002-08-08");
```

Comparing Label Objects

The following `equals`, `dominates`, and `strictlyDominates` methods are used to compare labels, and correspond to the `blequal()`, `bldominate()`, and `blstrictdom()` routines. The `inRange` method is used to determine whether a label is within a specified label range, and corresponds to the `blinrange()` routine. In these methods, a *label* refers to a classification and a set of compartments in a sensitivity label or in a clearance label. For more information, see [“Comparing Labels” on page 35](#) and the [blcompare\(3TSOL\)](#) man page.

```
public boolean dominates(SolarisLabel label)
```

The `dominates` method compares two labels to determine whether one label dominates the other.

The following example code shows how you can make the comparison. The `CNF : INTERNAL` label is being compared to check its dominance over the `PUBLIC` label.

```
SensitivityLabel sl = SolarisLabel.getSensitivityLabel("CNF : INTERNAL");  
boolean isDominant = sl.dominates(SolarisLabel.getSensitivityLabel("PUBLIC"));
```

```
public boolean equals(java.lang.Object obj)
```

The `equals` method compares two labels to determine whether they are equal.

The following example code shows how you can make the comparison:

```
SensitivityLabel sl = SolarisLabel.getSensitivityLabel("CNF : INTERNAL");  
boolean isSame = sl.equals(SolarisLabel.getSensitivityLabel("PUBLIC"));
```



```
public boolean Range inRange(SensitivityLabel label)
```

The `inRange` method determines whether the specified label is within the range. This method belongs to the `Range` class.

The following code fragment shows how you can verify that a file is within a user's clearance range:

```
import solarismac.*;
import java.io.*;

public class Example1
{
    public static void main (String args[]) {
        try {
            Range range;

            range = Range.getUserRange("jweeks");
            SensitivityLabel fsl =
                SolarisLabel.getFileLabel(new File("/etc/passwd"));
            boolean isInRange;

            isInRange = Range.inRange(fsl);

            if (isInRange)
                System.out.println("File is within user's range");
            else
                System.out.println("File is not within user's range");
        }
        catch (Exception e) {
            e.printStackTrace();
        }
    }
}
```

```
public boolean strictlyDominates(SolarisLabel label)
```

The `strictlyDominates` method compares two labels to determine whether one label strictly dominates the other. When a label strictly dominates another, it dominates the other label, but is not equal to the other label.

The following example code shows how you can make the comparison. The `CNF : INTERNAL` label is being compared to check its strict dominance over the `PUBLIC` label.

```
SensitivityLabel sl = SolarisLabel.getSensitivityLabel("CNF : INTERNAL");
boolean isStrictlyDominant =
    sl.strictlyDominates(SolarisLabel.getSensitivityLabel("PUBLIC"));
```

For more information about label relationships, see [“Label Relationships” on page 15](#).

The `getMaximum` and `getMinimum` methods are used to determine the least upper bound and the greatest lower bound of the specified label range, respectively. These methods mirror the functionality of the `blmaximum()` and `blminimum()` routines. For more information, see [“Comparing Labels” on page 35](#) and the `blminmax(3TSOL)` man page.

For instance, use the `getMaximum` method to determine the label to use when creating a new labeled object that combines information from two other labeled objects. The label of the new object will dominate both of the original labeled objects. Each method is defined by the `ClearanceLabel` and `SensitivityLabel` subclasses.

```
public ClearanceLabel getMaximum(ClearanceLabel bounding)
```

The `getMaximum` method creates a new clearance label object that is the lowest label that can dominate two label objects you specify. The resulting object is the least upper bound of the range. `getMaximum` returns an object in the internal form of the clearance label.

```
public ClearanceLabel getMinimum(ClearanceLabel bounding)
```

The `getMinimum` method creates a new clearance label object that is the highest label that is dominated by two labels you specify. The resulting object is the greatest lower bound of the range. `getMinimum` returns an object in the internal form of the clearance label.

```
public SensitivityLabel getMaximum(SensitivityLabel bounding)
```

The `getMaximum` method creates a new sensitivity label object that is the lowest label that can dominate two label objects you specify. The resulting object is the least upper bound of the range. `getMaximum` returns an object in the internal form of the sensitivity label.

```
public SensitivityLabel getMinimum(SensitivityLabel bounding)
```

The `getMinimum` method creates a new sensitivity label object that is the highest label that is dominated by two labels you specify. The resulting object is the greatest lower bound of the range. `getMinimum` returns an object in the internal form of the sensitivity label.

The following table shows label input and output from the `getMaximum` and `getMinimum` methods.

TABLE 9-1 Using the `getMinimum` and `getMaximum` Methods

Input Labels	getMinimum Output	getMaximum Output
SECRET A B TOP SECRET A B SA SB CC	SECRET A B	TOP SECRET A B SA SB CC
SECRET A B TOP SECRET A SA CC	SECRET A	TOP SECRET A B SA CC
SECRET A B TOP SECRET	SECRET	TOP SECRET A B
SECRET A TOP SECRET B	SECRET	TOP SECRET A B

Programmer's Reference

This appendix explains where to find information about developing, testing, and releasing label-aware applications to an environment that uses the Trusted Extensions software.

This appendix covers the following topics:

- “Header File Locations” on page 115
- “Abbreviations Used in Interface Names and Data Structure Names” on page 116
- “Developing, Testing, and Debugging an Application” on page 117
- “Releasing an Application” on page 117

Header File Locations

Most Trusted Extensions header files are located in the `/usr/include/tsol` directory and in the `/usr/include/sys/tsol` directory. The locations of other header files are shown in the following table.

Header File and Its Location	Category of Interface
<code>/usr/dt/include/Dt/label_clipping.h</code>	X11 label translation and label clipping with font list
<code>/usr/dt/include/Dt/ModLabel.h</code>	Label Builder
<code>/usr/openwin/include/X11/extensions/Xtsol.h</code>	X Window System
<code>/usr/include/libtsnet.h</code>	Trusted network library
<code>/usr/include/bsm/libbsm.h</code>	Audit library

Abbreviations Used in Interface Names and Data Structure Names

Many of the Trusted Extensions interface names and data structure names use the following short abbreviations. Knowing the abbreviations of these names will help you recognize the purpose of an interface or structure.

TABLE A-1 Name Abbreviations Used by Trusted Extensions APIs

Abbreviation	Name
attr	Attribute
b	Binary
clear	Clearance
ent	Entry
f	File
fs	File system
h	Hexadecimal
l	Level, label, or symbolic link
lbuild	Label Builder
prop	Properties
r	Re-entrant
res	Resource
s	String
sec	Security
sl	Sensitivity label
tp	Trusted Path
tsol	Trusted Extensions
xtsol	Trusted X11 Server

Developing, Testing, and Debugging an Application

You must develop, test, and debug an application on an isolated development system to prevent software bugs and incomplete code from compromising the security policy on the main system.

Follow these guidelines:

- Remove extra debugging code, especially code that provides undocumented features and code that bypasses security checks.
 - Make application data manipulation easy to follow so that the manipulation can be inspected for security problems by an administrator before installation.
 - Test return codes for all programming interfaces. An unsuccessful call can have unpredictable results. When an unexpected error condition occurs, the application must always terminate.
 - Test all functionality by running the application at all sensitivity labels and from all roles that you expect will run the application.
 - If the program is run by an ordinary user and not by a role, start the program from the command line at the labels where the program is intended to run.
 - If the program is run by a role, start the program from the command line in the global zone or from the user role at the labels where the program is intended to run.
 - Test all functionality under privilege debugging mode so that you know whether the application has all the privileges it needs. This type of testing also determines whether the application is attempting to perform privileged tasks that it should not be performing.
 - Know the security implications of using privileges. Ensure that the application does not compromise system security by its use of privileges.
 - Know and follow good privilege bracketing practices.
- See *Developer's Guide to Oracle Solaris 10 Security*.
- If you use the SUNWsprow debugger or the dbx command to test a privileged application, start the debugger *before* you attach it to a running process. You cannot start the debugger with the command name as an argument.

Releasing an Application

You submit a fully tested and debugged application to the system administrator for application integration. The application can be submitted as a CDE action or as a software package. If the application uses privileges, the system administrator must evaluate the application source code and the security information that you supply. This evaluation verifies that your use of privileges does not compromise system security.



Caution – Notify the system administrator of new auditing events, audit classes, or X Window System properties that your application uses. The system administrator *must* place these items into the correct files. For more information, see [Chapter 6, “Trusted X Window System.”](#)

Creating a CDE Action

A CDE action is started from the workspace by a user or a role. The action inherits the privileges assigned to the profile of that user or role. A *CDE action* is a set of instructions that work like application macros or APIs to automate desktop tasks such as running applications and opening data files. On a system configured with Trusted Extensions, applications are started from the workspace as CDE actions. Instructions on how to create a CDE action are provided in the *Solaris Common Desktop Environment: Advanced User's and System Administrator's Guide*.

Note – When you create a CDE action, create an `f.action`, not an `f.exec`. An `f.exec` executes the program as superuser with all privileges.

The system administrator puts the CDE action into the appropriate profiles and assigns any necessary privileges to the CDE action. You must list the privileges that the program uses, indicate the labels at which the application is intended to run, and supply any required effective user or group IDs. The system administrator assigns privileges as well as effective user and group IDs to the CDE action in the profile.

Creating a Software Package

To create a software package, see the *Application Packaging Developer's Guide*. To debug package installation issues, see [Chapter 14, “Troubleshooting Software Problems \(Overview\),”](#) in *System Administration Guide: Advanced Administration*.

Trusted Extensions API Reference

This appendix provides application programming interface (API) listings and cross-references to their use. Declarations are grouped by security topic.

This appendix covers the following topics:

- “Process Security Attribute Flags APIs” on page 119
- “Label APIs” on page 119
- “Label-Clipping APIs” on page 121
- “RPC APIs” on page 121
- “Label Builder APIs” on page 121
- “Trusted X Window System APIs” on page 121
- “Oracle Solaris Library Routines and System Calls That Use Trusted Extensions Parameters” on page 122
- “System Calls and Library Routines in Trusted Extensions” on page 123

Process Security Attribute Flags APIs

The following Oracle Solaris APIs accept Trusted Extensions parameters:

- `uint_t getpflags(uint_t flag);`
- `int setpflags(uint_t flag, uint_t value);`

Label APIs

The label APIs are introduced in [Chapter 2, “Labels and Clearances.”](#) Sample code is provided in [Chapter 3, “Label Code Examples.”](#) A fully described example is provided in [Chapter 4, “Printing and the Label APIs.”](#)

The following lists the types of label-related APIs and shows the prototype declarations of the routines and system calls for each type:

- **Accessing the `label_encodings` file**
 - `m_label_t *m_label_alloc(const m_label_type_t label_type);`
 - `int m_label_dup(m_label_t **dst, const m_label_t *src);`
 - `void m_label_free(m_label_t *label);`
 - `int label_to_str(const m_label_t *label, char **string, const m_label_str_t conversion_type, uint_t flags);`
- **Comparing level relationships**
 - `int blequal(const m_label_t *level1, const m_label_t *level2);`
 - `int bldominates(const m_label_t *level1, const m_label_t *level2);`
 - `int blstrictdom(const m_label_t *level1, const m_label_t *level2);`
 - `int blinrange(const m_label_t *level, const brange_t *range);`
 - `void blmaximum(m_label_t *maximum_label, const m_label_t *bounding_label);`
 - `void blminimum(m_label_t *minimum_label, const m_label_t *bounding_label);`
- **Accessing label ranges**
 - `m_range_t *getuserange(const char *username);`
 - `blrange_t *getdevicerange(const char *device);`
- **Accessing labels in zones**
 - `char *getpathbylabel(const char *path, char *resolved_path, size_t bufsize, const m_label_t *sl);`
 - `m_label_t *getzonelabelbyid(zoneid_t zoneid);`
 - `m_label_t *getzonelabelbyname(const char *zonename);`
 - `zoneid_t *getzoneidbylabel(const m_label_t *label);`
 - `char *getzonerootbyid(zoneid_t zoneid);`
 - `char *getzonerootbylabel(const m_label_t *label);`
 - `char *getzonerootbyname(const char *zonename);`
- **Obtaining the remote host type**
 - `tsol_host_type_t tsol_getrhtype(char *hostname);`
- **Accessing and modifying sensitivity labels**
 - `int fgetlabel(int fd, m_label_t *label_p);`
 - `int getlabel(const char *path, m_label_t *label_p);`
 - `int setflabel(const char *path, const m_label_t *label_p);`
 - `int getplabel(m_label_t *label_p);`

- `int label_to_str(const m_label_t *label, char **string, const m_label_str_t conversion_type, uint_t flags);`
- `int str_to_label(const char *string, m_label_t **label, const m_label_type_t label_type, uint_t flags, int *error);`

Label-Clipping APIs

For information about this label-clipping API, see [Chapter 6, “Trusted X Window System.”](#)

```
int label_to_str(const m_label_t *label, char **string,
                const m_label_str_t conversion_type, uint_t flags);
```

RPC APIs

Trusted Extensions does not provide interfaces for remote procedure calls (RPC). RPC interfaces have been modified to work with Trusted Extensions. For conceptual information, see [Chapter 5, “Interprocess Communications.”](#) For an example that uses the `getpeercred()` and `ucred_getlabel()` routines, see [Chapter 4, “Printing and the Label APIs.”](#)

Label Builder APIs

For information about the Label Builder user interface, see [Chapter 7, “Label Builder APIs.”](#)

- `ModLabelData *tsol_lbuild_create(Widget widget, void (*event_handler)() ok_callback, lbuild_attributes extended_operation, ..., NULL);`
- `void tsol_lbuild_destroy(ModLabelData *lbdata);`
- `void *tsol_lbuild_get(ModLabelData *lbdata, lbuild_attributes extended_operation);`
- `void tsol_lbuild_set(ModLabelData *lbdata, lbuild_attributes extended_operation, ..., NULL);`

Trusted X Window System APIs

For information about the Trusted X Window System APIs, see [Chapter 6, “Trusted X Window System.”](#)

- `Status XTSOLgetResAttributes(Display *display, XID object, ResourceType type, XTSOLResAttributes *winattrp);`
- `Status XTSOLgetPropAttributes(Display *display, Window window, Atom property, XTSOLPropAttributes *propattrp);`

- `Status XTSOLgetClientAttributes(Display *display, XID windowid, XTsolClientAttributes *clientattrp);`
- `Status XTSOLgetResLabel(Display *display, XID object, ResourceType type, m_label_t *sl);`
- `Status XTSOLsetResLabel(Display *display, XID object, ResourceType type, m_label_t *sl);`
- `Status XTSOLgetResUID(Display *display, XID object, ResourceType type, uid_t *uidp);`
- `Status XTSOLsetResUID(Display *display, XID object, ResourceType type, uid_t *uidp);`
- `Status XTSOLgetPropLabel(Display *display, Window window, Atom property, m_label_t *sl);`
- `Status XTSOLsetPropLabel(Display *display, Window window, Atom property, m_label_t *sl);`
- `Status XTSOLgetPropUID(Display *display, Window window, Atom property, uid_t *uidp);`
- `Status XTSOLsetPropUID(Display *display, Window window, Atom property, uid_t *uidp);`
- `Status XTSOLgetWorkstationOwner(Display *display, uid_t *uidp);`
- `Status XTSOLsetWorkstationOwner(Display *display, uid_t *uidp);`
- `Status XTSOLsetSessionHI(Display *display, m_label_t *sl);`
- `Status XTSOLsetSessionLO(Display *display, m_label_t *sl);`
- `Status XTSOLMakeTPWindow(Display *display, Window *w);`
- `Bool XTSOLIsWindowTrusted(Display *display, Window *window);`
- `Status XTSOLgetSSHheight(Display *display, int screen_num, int *newheight);`
- `Status XTSOLsetSSHheight(Display *display, int screen_num, int newheight);`
- `Status XTSOLsetPolyInstInfo(Display *display, m_label_t sl, uid_t *uidp, int enabled);`

Oracle Solaris Library Routines and System Calls That Use Trusted Extensions Parameters

The following Oracle Solaris interfaces either include Trusted Extensions parameters or are used in this guide with Trusted Extensions interfaces:

- `int auditon(int cmd, caddr_t data, int length);`
- `void free(void *ptr);`

- `int getpeerucred(int fd, ucred_t **ucred);`
- `uint_t getpflags(uint_t flag);`
- `int is_system_labeled(void);`
- `int setpflags(uint_t flag, uint_t value);`
- `int getsockopt(int s, int level, int optname, void *optval, int *optlen);`
- `int setsockopt(int s, int level, int optname, const void *optval, int optlen);`
- `int socket(int domain, int type, int protocol);`
- `ucred_t *ucred_get(pid_t pid);`
- `m_label_t *ucred_getlabel(const ucred_t *uc);`

System Calls and Library Routines in Trusted Extensions

The following table lists the Trusted Extensions system calls and routines. The table also provides references to descriptions and declarations of the interface and to examples of the interface that appear in this guide. The man page section is included as part of the name of each system call and routine.

TABLE B-1 System Calls and Library Routines That Are Used in Trusted Extensions

System Call or Library Routine	Cross-Reference to Description	Cross-Reference to Example
<code>bldominates(3TSOL)</code>	“Label Relationships” on page 15 “Comparing Labels” on page 35	“Determining the Relationship Between Two Labels” on page 44
<code>blequal(3TSOL)</code>	“Comparing Labels” on page 35	“Determining the Relationship Between Two Labels” on page 44
<code>blinrange(3TSOL)</code>	“Label Relationships” on page 15	“Validating the Label Request Against the Printer’s Label Range” on page 55
<code>blmaximum(3TSOL)</code>	“Comparing Labels” on page 35	
<code>blminimum(3TSOL)</code>	“Comparing Labels” on page 35	
<code>blstrictdom(3TSOL)</code>	“Comparing Labels” on page 35	
<code>fgetlabel(2)</code>	“Labeled Zones” on page 25 “Obtaining and Setting the Label of a File” on page 31	
<code>free(3C)</code>	“Translating Between Labels and Strings” on page 34	
<code>getlabel(2)</code>	“Labeled Zones” on page 25 “Obtaining and Setting the Label of a File” on page 31	“Obtaining a File Label” on page 42

TABLE B-1 System Calls and Library Routines That Are Used in Trusted Extensions (Continued)

System Call or Library Routine	Cross-Reference to Description	Cross-Reference to Example
getpathbylabel(3TSOL)	“Accessing Labels in Zones” on page 32	
getpeerucred(3C)	“get_peer_label() Label-Aware Function” on page 51	“Obtaining the Credential and Remote Host Label” on page 53
getpflags(2)	“MAC-Exempt Sockets” on page 24	
getplabel(3TSOL)	“Accessing the Process Sensitivity Label” on page 30	“Translating the Window Label With the Font List” on page 78
getuserange(3TSOL)	“Obtaining Label Ranges” on page 32	
getzoneidbylabel(3TSOL)	“Accessing Labels in Zones” on page 32	
getzonelabelbyid(3TSOL)	“Accessing Labels in Zones” on page 32	
getzonelabelbyname(3TSOL)	“Accessing Labels in Zones” on page 32	
getzonerootbyid(3TSOL)	“Accessing Labels in Zones” on page 32	
getzonerootbylabel(3TSOL)	“Accessing Labels in Zones” on page 32	
getzonerootbyname(3TSOL)	“Accessing Labels in Zones” on page 32	
is_system_labeled(3C)	“get_peer_label() Label-Aware Function” on page 51 “Detecting a Trusted Extensions System” on page 29	“Determining Whether the Printing Service Is Running in a Labeled Environment” on page 52
labelbuilder(3TSOL)	Chapter 7, “Label Builder APIs”	“Creating an Interactive User Interface” on page 82
label_to_str(3TSOL)	“Translating Between Labels and Strings” on page 34	“Obtaining a Process Label” on page 41
m_label_alloc(3TSOL)	“Allocating and Freeing Memory for Labels” on page 30	“Obtaining a Process Label” on page 41 “Obtaining a File Label” on page 42
m_label_dup(3TSOL)	“Allocating and Freeing Memory for Labels” on page 30	
m_label_free(3TSOL)	“Allocating and Freeing Memory for Labels” on page 30	“Validating the Label Request Against the Printer’s Label Range” on page 55 “Obtaining a Process Label” on page 41

TABLE B-1 System Calls and Library Routines That Are Used in Trusted Extensions (Continued)

System Call or Library Routine	Cross-Reference to Description	Cross-Reference to Example
setflabel(3TSOL)	“Obtaining and Setting the Label of a File” on page 31	
	“Obtaining and Setting the Label of a File” on page 31	
setpflags(2)	“MAC-Exempt Sockets” on page 24	
str_to_label(3TSOL)	“Translating Between Labels and Strings” on page 34	“Validating the Label Request Against the Printer’s Label Range” on page 55
		“Obtaining a File Label” on page 42
tsol_getrhtype(3TSOL)	“Obtaining the Remote Host Type” on page 34	
ucred_get(3C)	“Multilevel Ports” on page 23	
ucred_getlabel(3C)	“Multilevel Ports” on page 23	
XTSOLgetClientAttributes(3XTSOL)	“Accessing Attributes” on page 73	
XTSOLgetPropAttributes(3XTSOL)	“Accessing Attributes” on page 73	
XTSOLgetPropLabel(3XTSOL)	“Accessing and Setting a Window Property Label” on page 74	
XTSOLgetPropUID(3XTSOL)	“Accessing and Setting a Window Property Label” on page 74	
XTSOLgetResAttributes(3XTSOL)	“Obtaining Window Attributes” on page 78	
XTSOLgetResLabel(3XTSOL)	“Obtaining a Window Label” on page 79	
XTSOLgetResUID(3XTSOL)	“Obtaining the Window User ID” on page 80	
	“Accessing and Setting a Window User ID” on page 74	
XTSOLgetSSHeight(3XTSOL)	“Accessing and Setting the Screen Stripe Height” on page 76	
XTSOLgetWorkstationOwner(3XTSOL)	“Accessing and Setting a Workstation Owner ID” on page 75	
XTSOLIsWindowTrusted(3XTSOL)	“Working With the Trusted Path Window” on page 76	
XTSOLMakeTPWindow(3XTSOL)	“Working With the Trusted Path Window” on page 76	
XTSOLsetPolyInstInfo(3XTSOL)	Chapter 6, “Trusted X Window System”	

TABLE B-1 System Calls and Library Routines That Are Used in Trusted Extensions (Continued)

System Call or Library Routine	Cross-Reference to Description	Cross-Reference to Example
<code>XTSOLsetPropLabel(3XTSOL)</code>	“Accessing and Setting a Window Property Label” on page 74	
<code>XTSOLsetPropUID(3XTSOL)</code>	“Accessing and Setting a Window Property Label” on page 74	
<code>XTSOLsetResLabel(3XTSOL)</code>	“Setting a Window Label” on page 79	
<code>XTSOLsetResUID(3XTSOL)</code>	“Accessing and Setting a Window User ID” on page 74	
<code>XTSOLsetSessionHI(3XTSOL)</code>	“Setting the X Window Server Clearance and Minimum Label” on page 75	
<code>XTSOLsetSessionLO(3XTSOL)</code>	“Setting the X Window Server Clearance and Minimum Label” on page 75	
<code>XTSOLsetSSHeight(3XTSOL)</code>	“Accessing and Setting the Screen Stripe Height” on page 76	
<code>XTSOLsetWorkstationOwner(3XTSOL)</code>	“Accessing and Setting a Workstation Owner ID” on page 75	

Index

A

abbreviations used in interface names, 116

access

checks for

network, 60–65

sockets, 61

Trusted X Window System, 69

file labels, 27–28

guidelines for labels, 28

multilevel port connections, 59–60

ADMIN_HIGH label, 25

ADMIN_LOW label, 25

APIs

clearance label, 20

declarations, 119–126

examples of Trusted Extensions in Oracle
Solaris, 13

introduction to, 14

Label Builder, 81, 121

label clipping, 121

label range, 20

labels, 29–36, 41, 119–121

for Oracle Solaris that use Trusted Extensions
parameters, 122–123

process security attribute flags, 119

RPC, 121

security APIs from Oracle Solaris OS, 17

sensitivity label, 19

Trusted X Window System, 20–21, 67–80, 121–122

for zone labels and zone paths, 25

applications

integrating, 117–118

applications (*Continued*)

releasing, 117–118

testing and debugging, 117

atoms, predefined in X Window System, 71

auditid field, 73

authorizations, Label Builder, 87

B

bldominates() routine

code example, 44

declaration, 35–36

blequal() routine

code example, 44

declaration, 35–36

blinrange() routine

declaration, 35–36, 36

blmaximum() routine, declaration, 36

blminimum() routine, declaration, 36

blstrictdom() routine

code example, 44

declaration, 35–36

brange_t type, 29

builders, API declarations for GUI, 121

C

CDE actions

assigning inheritable privileges, 118

creating, 118

classifications

- clearance component, 14
- disjoint, 16
- dominant, 16
- equal, 16
- label component, 14
- strictly dominant, 16

clearance labels, 14

ClearanceLabel subclass, 103

clearances

- disjoint labels, 16
- dominant labels, 16
- equal labels, 16
- session, 14
- strictly dominant labels, 16
- user, 14

code examples

file systems

- obtaining label, 42

getSocketPeer static factory

- obtaining socket peer label, 106

Label Builder, 83

label_encodings file

- creating printer banner, 46–47, 110–111
- obtaining character-coded color names, 45

label relationships, 44

labels

- obtaining on file system, 42
 - obtaining on window, 79
 - obtaining process label, 41
 - setting on window, 79–80
- obtain socket peer label, 106
- printer banner, 46–47, 110–111
- set file sensitivity label, 43
- Trusted X Window System, 77–80
- obtaining window attributes, 78
 - obtaining window label, 79
 - obtaining window user ID, 80
 - obtaining workstation owner, 80
 - setting window label, 79–80
 - translating with font list, 78–79

communication endpoints

- access checks, 60–65
- connections described, 61–62

compartments

- clearance component, 14
- disjoint, 16
- dominant, 16
- equal, 16
- label component, 14
- strictly dominant, 16

compile

- Label Builder libraries, 81–82
- label libraries, 29–36
- Trusted X Window System libraries, 72

connection requests

- security attributes, 68
- security policy, 69

D

DAC (discretionary access control), 59, 67

data types

- label APIs, 29
- Label Builder APIs
 - ModLabelData structure, 89–90
 - tsol_lbbuild_create() routine, 87–88
- Trusted X Window System APIs, 72

debugging, applications, 117

definitions of terms, 13

detecting a Trusted Extensions system, 105

determining whether a system is labeled, example, 30

devices, input device privileges, 71

DGA (direct graphics access), privileges, 71

disjoint labels, 16

dominant labels, 16

dominates method, declaration, 112–114

downgrading labels

- guidelines, 28
- privileges needed, 28
- Trusted X Window System, 72

E

equal labels, 16

equals method, declaration, 112–114

examples of Trusted Extensions APIs in Oracle
Solaris, 13
extended operations, 88–89

F

`fcntl_label()` system call, declaration, 31–32
`file_dac_search` privilege, overriding access to parent
directory of zone's root directory, 22
`file_downgrade_sl` privilege, 28
`file_owner` privilege, 28
files, label privileges, 28
fonts
font list translation, 78–79
font path privileges, 72

G

`get_peer_label()` function, 51–55
`getClearanceLabel` static factory, declaration, 112
`getdevicerange()` routine, declaration, 32
`getDeviceRange` static factory, declaration, 107–108
`getFileLabel` static factory
declaration, 105–107
`getlabel` command, 43
code example, 44
`getlabel()` system call
code example, 42
declaration, 31–32
`getLabelRange` static factory, declaration, 107–108
`getLower` method, declaration, 107–108
`getMaximum` method
declaration, 113, 114
`getMinimum` method
declaration, 113, 114
`getpathbylabel()` routine, declaration, 32–33
`getplabel()` routine
code example, 41, 44, 45
declaration, 30
`getSensitivityLabel` static factory
code example, 110–111
declaration, 112

`getSocketPeer` static factory
code example, 106
declaration, 105–107
`getUpper` method, declaration, 107–108
`getuserrange()` routine, declaration, 32
`getUserRange` static factory, declaration, 107–108
`getzoneidbylabel()` routine, declaration, 32–33
`getzoneidbylabelbyid()` routine, declaration, 32–33
`getzoneidbylabelbyname()` routine, declaration, 32–33
`getzonerootbyid()` routine, declaration, 32–33
`getzonerootbylabel()` routine, declaration, 32–33
`getzonerootbylabelbyname()` routine, declaration, 32–33
`gid` field, 73
global zone
controlling multilevel operations, 22–24
labels in, 25
mounts in, 22
GUIs
Label Builder, 81
Xlib objects, 68

H

header files
label APIs, 29–36
Label Builder APIs, 81–82
locations, list of, 115
Trusted X Window System APIs, 72

I

`iaddr` field, 73
`inRange` method
declaration, 112–114
integrating an application, 117–118
interface names, abbreviations used in, 116
IPC (interprocess communication), 59
`is_system_labeled()` routine
declaration, 29–30
example, 52

J

Java bindings

- classes, 102–104
- ClearanceLabel subclass, 103
- Range class, 104
- SensitivityLabel subclass, 103–104
- SolarisLabel abstract class, 102–104

Java methods

- dominates, 112–114
- equals, 112–114
- getLower, 107–108
- getMaximum, 113, 114
- getMinimum, 113, 114
- getUpper, 107–108
- inRange, 112–114
- setFileLabel, 105–107
- strictlyDominates, 112–114
- toCaveats, 110
- toChannels, 110
- toColor, 109
- toFooter, 110
- toHeader, 110
- toInternal, 109
- toProtectAs, 110
- toRootPath, 108
- toString, 109
- toText, 109
- toTextLong, 109
- toTextShort, 110

Java static factories

- getClearanceLabel, 112
- getDeviceRange, 107–108
- getFileLabel, 105–107
- getLabelRange, 107–108
- getSensitivityLabel, 112
- getSocketPeer, 105–107
- getUserRange, 107–108

L

label APIs, 29–36

- introduction to, 14
- Label Builder, 81, 121
- label clipping, 121

label APIs (*Continued*)

labels

- code examples, 41
- list of, 119–121
- RPC, 121
- Trusted X Window System, 67–80, 121–122
- windows, 20–21, 21
- for zone labels and zone paths, 25

Label Builder

- APIs, 81–82
- authorizations, 87
- Cancel button, 86
- declarations, 81–82
- description of, 21
- functionality, 85–86
- header files, 81–82
- label radio buttons, 86
- libraries, 81–82
- ModLabelData structure, 89–90
- online help, 90
- privileged tasks, 87
- Reset button, 86
- tsol_lbuild_create() routine, 87–88
- Update button, 85

label clipping

- API declaration, 77, 121
- translating with font list, 78–79

label data types

- label ranges, 29
- sensitivity labels, 29

label_encodings file

- API declarations, 120
- color names, 45
- Label Builder, 85–86
- non-English, 79

label ranges, 14

- file systems
- data structure, 29
- overview, 19

label_to_str() routine

- code example, 45, 46–47, 78–79
- declaration, 77

labeled zones, 25–26

labels

- acquiring, 37–39
- ADMIN_HIGH, 25
- ADMIN_LOW, 25
- API declarations, 120
 - label clipping, 121
 - label_encodings file, 120
 - labels, 120
 - levels, 120
 - network databases, 120
 - ranges, 120
 - zones, 120
- components of, 14
- definition of, 15
- disjoint, 17
- dominant, 16
- downgrading guidelines, 28
- in global zone, 25
- objects, 31, 37–39, 107
- privileged tasks, 27–28
- privileges
 - downgrading labels, 28
 - upgrading labels, 28
- ranges, 20, 29
- relationships, 15, 44
- strictly dominant, 17
- types
 - clearance, 14
 - sensitivity, 14
- upgrading guidelines, 28
- user processes, 37–39
- LBUILD_CHECK_AR operation, 89
- LBUILD_LOWER_BOUND operation, 89
- LBUILD_MODE_CLR value, 88
- LBUILD_MODE operation, 88
- LBUILD_MODE_SL value, 88
- LBUILD_SHOW operation, 88
- LBUILD_TITLE operation, 88
- LBUILD_UPPER_BOUND operation, 89
- LBUILD_USERFIELD operation, 88
- LBUILD_VALUE_CLR operation, 88
- LBUILD_VALUE_SL operation, 88
- LBUILD_VIEW_EXTERNAL value, 89
- LBUILD_VIEW_INTERNAL value, 89

- LBUILD_VIEW operation, 89
- LBUILD_WORK_CLR operation, 88
- LBUILD_WORK_SL operation, 88
- LBUILD_X operation, 89
- LBUILD_Y operation, 89
- libraries, Trusted X Window System APIs, 72
- libraries, compile
 - label APIs, 29–36
 - Label Builder APIs, 81–82
- library routines
 - API declarations, 123–126
 - bldominates(), 35–36
 - blequal(), 35–36
 - blinrange(), 35–36, 36
 - blmaximum(), 36
 - blminimum(), 36
 - blstrictdom(), 35–36
 - getdevicerange(), 32
 - getpathbylabel(), 32–33
 - getplabel(), 30
 - getuserrange(), 32
 - getzoneidbylabel(), 32–33
 - getzonelabelbyid(), 32–33
 - getzonelabelbyname(), 32–33
 - getzonerootbyid(), 32–33
 - getzonerootbylabel(), 32–33
 - getzonerootbyname(), 32–33
 - is_system_labeled(), 29–30
 - label_to_str(), 34, 35, 77
 - m_label_alloc(), 30–31
 - m_label_dup(), 30–31
 - m_label_free(), 30–31
 - setflabel(), 31–32
 - str_to_label(), 34
 - tsol_getrhtype(), 34
 - tsol_lbuid_create(), 81–82
 - tsol_lbuid_destroy(), 81–82
 - tsol_lbuid_get(), 81–82
 - tsol_lbuid_set(), 81–82
 - ucred_getlabel(), 30
 - XQueryExtension(), 30
 - XTSOLgetClientAttributes(), 74
 - XTSOLgetPropAttributes(), 73
 - XTSOLgetPropLabel(), 74–75

library routines (*Continued*)

- XTSOLgetPropUID(), 75
- XTSOLgetResAttributes(), 73
- XTSOLgetResLabel(), 74
- XTSOLgetResUID(), 74
- XTSOLgetSSHheight(), 76–77
- XTSOLgetWorkstationOwner(), 75
- XTSOLIsWindowTrusted(), 76
- XTSOLmakeTPWindow(), 76
- XTSOLsetPolyInstInfo(), 77
- XTSOLsetPropLabel(), 74–75
- XTSOLsetPropUID(), 75
- XTSOLsetResLabel(), 74
- XTSOLsetResUID(), 74
- XTSOLsetSessionHI(), 75–76
- XTSOLsetSessionLO(), 75–76
- XTSOLsetSSHheight(), 76–77
- XTSOLsetWorkstationOwner(), 75

M

- `m_label_alloc()` routine
 - code example, 44
 - declaration, 30–31
- `m_label_dup()` routine, declaration, 30–31
- `m_label_free()` routine, declaration, 30–31
- `m_label_t` type, 29
- MAC (mandatory access control), 59, 67
 - making socket exempt from, 24
- ModLabelData structure, 89–90
- Motif application
 - Label Builder widgets, 89–90
 - online help, 90
- multilevel operations, security policy for, 22–24
- multilevel ports
 - description of, 23, 59–60
 - using with UDP, 63–65

N

- `net_bindmlp` privilege, 59
- `net_mac_aware` privilege, 24
- network security policy, default, 23

- networks, security attributes, 23
- non-global zones, 25–26

O

- online help, Label Builder, 90
- operations, extended, *See* `LBUILD_CHECK_AR` operation
- Oracle Solaris
 - examples of Trusted Extensions APIs, 13
 - interfaces, API declarations, 122–123
- oid field, 73

P

- `PAF_SELAGENT` flag, 71
- pid field, 73
- `plabel` command, 30
- polyinstantiation, description of, 67
- PORTMAPPER service, 62
- ports
 - multilevel, 59
 - single-level, 59
- printer banner page
 - label translation, 46–47, 110–111
- printing
 - banner page, 49
 - `get_peer_label()` function, 51–55
 - label API and, 49
 - labeled output, 49
 - multilevel, 49
- privileged tasks
 - Label Builder, 87
 - labels, 27–28
 - multilevel port connections, 59–60
 - Trusted X Window System, 71–72
- privileges
 - `file_dac_read`, 28
 - `file_dac_search`, 22, 28
 - `file_dac_write`, 28
 - `file_downgrade_sl`, 26, 28
 - `file_owner`, 28
 - `file_upgrade_sl`, 26, 28
 - `net_bindmlp`, 23, 59, 61

privileges (*Continued*)

- net_mac_aware, 24
- sys_trans_label, 28, 79, 87, 89
- win_config, 71
- win_dac_read, 71
- win_dac_write, 71
- win_devices, 70, 71
- win_dga, 71
- win_downgrade_sl, 72
- win_fontpath, 72
- win_selection, 71
- win_upgrade_sl, 72, 79

process clearances, labels defined, 15

processes

- binding to multilevel ports, 23
- in labeled zones, 25–26
- multilevel initiated in global zone, 22–24
- writing down from global zone, 22

properties

- description of, 68, 69
- privileges, 71

R

Range class

- description of, 104
- methods and static factories, 104

relationships between labels, 15

releasing an application, 117–118

remote host

- credential, 51–55
- label, 53
- type, 34

ResourceType structure, 73

RPC (remote procedure call), 62

S

SCM_UCRED, 63

security attribute flags, API declarations, 119

security attributes

- accessing labels, 27–28
- labels from remote hosts, 23

security attributes (*Continued*)

Trusted X Window System

- contrast with Oracle Solaris, 21
- description of, 68

security policy

- CDE actions, 118
- communication endpoints, 60–65
- definition of, 13
- global zone, 25
- label guidelines, 27–28
- labels, 27–28
- multilevel operations, 22–24
- multilevel ports, 59–60
- network, 23
- sockets, 61
- translating labels, 28
- Trusted X Window System, 69–71
- write-down in global zone, 22

Selection Manager

- bypassing with flag, 71
- security policy, 70

sensitivity labels, 14

SensitivityLabel subclass

- code example, 110–111
- description of, 103–104
- methods, 104

sessionid field, 73

setFileLabel method, declaration, 105–107

setflabel() routine

- code example, 43
- declaration, 31–32

setpflags() system call, 24

single-level ports, description of, 59

sl field, 73

SO_MAC_EXEMPT option, 24

SO_RECVUCRED option, 23

sockets

- access checks, 60–65
- exempt from MAC, 24
- software packages, creating, 118

SOL_SOCKET, 63

SolarisLabel abstract class

- description of, 102–104
- methods and static factories, 102

`str_to_label()` routine, code example, 43
strictly dominant labels, 16
`strictlyDominates` method, declaration, 112–114
`sys_trans_label` privilege, 28, 87
system calls
 API declarations, 123–126
 `fgetlabel()` routine, 31–32
 `getlabel()` routine, 31–32

T

terms, definitions of, 13
testing and debugging applications, 117
text, color names, 45
`toCaveats` method
 code example, 110–111
 declaration, 110
`toChannels` method
 code example, 110–111
 declaration, 110
`toColor` method, declaration, 109
`toFooter` method
 code example, 110–111
 declaration, 110
`toHeader` method
 code example, 110–111
 declaration, 110
`toInternal` method, declaration, 109
`toProtectAs` method
 code example, 110–111
 declaration, 110
`toRootPath` method, declaration, 108
`toString` method, declaration, 109
`toText` method, declaration, 109
`toTextLong` method, declaration, 109
`toTextShort` method, declaration, 110
translation
 labels with font list, 78–79
 privileges needed, 28
Trusted Extensions APIs, Oracle Solaris examples, 13
Trusted Extensions system, detecting, 105
Trusted Path window, definition of, 21
Trusted X Window System
 API declarations, 72–77, 121–122

Trusted X Window System (*Continued*)

 client attributes structure, 73
 defaults, 71
 description of, 20–21
 input devices, 70
 label-clipping API declaration, 121
 object attribute structure, 73
 object type definition, 73
 objects, 68
 override-redirect, 70
 predefined atoms, 71
 privileged tasks, 71–72
 properties, 69
 property attribute structure, 73
 protocol extensions, 67–80
 root window, 70
 security attributes
 contrast with Oracle Solaris, 21
 description of, 68
 security policy, 69–71
 Selection Manager, 70
 server control, 70
 Trusted Path window, 21
 using interfaces, 77–80
`tsol_getrhtype()` routine, declaration, 34
`tsol_lbuild_create()` routine
 code example, 83
 declaration, 81–82
 description of, 87–88
`tsol_lbuild_destroy()` routine, declaration, 81–82
`tsol_lbuild_get()` routine
 code example, 83
 declaration, 81–82
`tsol_lbuild_set()` routine
 code example, 83
 declaration, 81–82

U

`ucred_getlabel()` routine, declaration, 30
`ucred_t` data structure, 51–55
uid field, 73
upgrading labels
 guidelines, 28

upgrading labels (*Continued*)
 privileges needed, 28
 Trusted X Window System, 72
 user IDs
 obtaining on window, 79–80
 obtaining on workstation, 80

W

Web Guard prototype, 91
 win_config privilege, 71
 win_dac_read privilege, 71
 win_dac_write privilege, 71
 win_devices privilege, 71
 win_dga privilege, 71
 win_downgrade_sl privilege, 72
 win_fontpath privilege, 72
 win_mac_read privilege, 71
 win_mac_write privilege, 71
 win_upgrade_sl privilege, 72
 windows
 client, security policy, 70
 defaults, 71
 description of, 68
 override-redirect, security policy, 70
 privileges, 71
 root, security policy, 70
 security policy, 69

X

X Window System, *See* Trusted X Window System
 Xlib
 API declarations, 72–77
 objects, 68
 XTsolClientAttributes structure, 73
 XTSOLgetClientAttributes() routine,
 declaration, 74
 XTSOLgetPropAttributes() routine, declaration, 73
 XTSOLgetPropLabel() routine, declaration, 74–75
 XTSOLgetPropUID() routine, declaration, 75
 XTSOLgetResAttributes() routine
 code example, 78

XTSOLgetResAttributes() routine (*Continued*)
 declaration, 73
 XTSOLgetResLabel() routine
 code example, 79
 declaration, 74
 XTSOLgetResUID() routine
 code example, 80
 declaration, 74
 XTSOLgetSSHheight() routine, declaration, 76–77
 XTSOLgetWorkstationOwner() routine
 code example, 80
 declaration, 75
 XTSOLIsWindowTrusted() routine, declaration, 76
 XTSOLmakeTPWindow() routine, declaration, 76
 XTsolPropAttributes structure, 73
 XTsolResAttributes structure, 73
 XTSOLsetPolyInstInfo() routine, declaration, 77
 XTSOLsetPropLabel() routine, declaration, 74–75
 XTSOLsetPropUID() routine, declaration, 75
 XTSOLsetResLabel() routine
 code example, 79–80
 declaration, 74
 XTSOLsetResUID() routine, declaration, 74
 XTSOLsetSessionHI() routine, declaration, 75–76
 XTSOLsetSessionLO() routine, declaration, 75–76
 XTSOLsetSSHheight() routine, declaration, 76–77
 XTSOLsetWorkstationOwner() routine,
 declaration, 75

Z

zones
 APIs for zone labels and zone paths, 25
 labeled, 25–26
 mounts and the global zone, 22
 multilevel ports, 23
 in Trusted Extensions, 25–26

