



How Products Become Profits™

Agile® e6.0

# **Upgrade Tool 3.1.14 for Agile e6.0.3**

Upgrade Manual

**Part Number: UGP-603B**

## Copyrights and Trademarks

Copyright © 1992-2007

Agile Software Corporation. All rights reserved.

You shall not create any derivative works of this publication nor shall any part of this publication be copied, reproduced, distributed, published, licensed, sold, stored in a retrieval system or transmitted in any form or by any means: electronic, mechanical, photocopying, or otherwise, without the prior written consent of Agile Software Corporation, 6373 San Ignacio Avenue, San Jose, California 95119-1200 U.S.A.; Telephone 408.284.4000, Facsimile 408.284.4002, or <<http://www.agile.com/>>.

The material in this document is for information only and is subject to change without notice. While reasonable efforts have been made in the preparation of this document to ensure its accuracy, Agile Software Corporation assumes no liability resulting from errors or omissions in this document or from the use of the information contained herein. Agile Software Corporation reserves the right to make changes in the product design without reservation and without notification to its users.

Agile Software is a registered trademark and Agile, Agile Product Collaboration, Agile Product Cost Management, Agile Product Service & Improvement, Agile Program Execution, Agile Product Interchange, AgileMD, and the Agile Logo are trademarks of Agile Software Corporation in the U.S. and/or other countries. Guaranteed Business Results is a service mark of Agile Software Corporation. All other brands or product names are trademarks or registered trademarks of their respective holders.

Java and Solaris are registered trademarks of Sun Corporation.

Microsoft, Microsoft Windows, Microsoft Word, Microsoft Excel, Internet Explorer and SQL Server are registered trademarks of Microsoft Corporation.

Oracle and Oracle8i are registered trademarks of Oracle Corporation.

### NOTICE OF RESTRICTED RIGHTS:

The Software is a “commercial item,” as that term is defined at 48 C.F.R. 2.101 (OCT 1995), consisting of “commercial computer software” and “commercial computer software documentation” as such terms are used in 48 C.F.R. 12.212 (SEPT 1995) and when provided to the U. S. Government, is provided (a) for acquisition by or on behalf of civilian agencies, consistent with the policy set forth in 48 C.F.R. 12.212; or (b) for acquisition by or on behalf of units of the Department of Defense, consistent with the policies set forth in 48 C.F.R. 227.7202-1 (JUN 1995) and 227.7202-4 (JUN 1995).

January 29, 2007

# REVISIONS

---

Revision	Date	Pages Effected	Description
A	12/04/2006	All	Initial document
B	29/01/2007	All	- Upgrade package for Agile e6.0.3 - Upgrade tool version is now included in the document - Chown_mssql.cmd command file description has been added

# CONTENTS

---

<b>Chapter 1 Introduction</b>	<b>1</b>
Overview	1
Prerequisites	1
How it Works	2
<b>Chapter 2 Installation and Configuration</b>	<b>4</b>
ApplicationParameter.xml Template	4
Database Settings in Oracle	4
Oracle Parameters	4
SQL Net Configuration.	4
Global Database Name	5
Service Name	5
listener.ora	5
sqlnet.ora	6
Database Settings in Microsoft SQL Server	6
Tablespaces / File Groups	6
Oracle	6
SQL Server	6
Pre-Activities on the Original Production Environment	7
Import Dumps	7
Import Source Reference Dump	8
Import Customer Dump	8
Create Statistics for all Involved Database Schemas	9
Run Upgrade Tool	9
Configure the Upgrade Tool	10
Configure New Database Environment Connections	10
Configure Production Dump Connection	11
Setting Upgrade Tool Parameters	12
Save Configuration	14
<b>Chapter 3 Perform the Upgrade</b>	<b>15</b>
Perform the Upgrade in Interactive Mode	15
Step 1: run pre-action-scripts	15
Step 2: DTV-upgrade	15
Step 3: run before-sync-scripts	16
Step 4: Synchronize_Repository	16
Analyze	17
Configure special.xml for Synchronizing Repository	17
Synchronize	19

Step 5: run after-sync-script	19
Step 6: run before-common-scripts	20
Step 7: EDB-upgrade (Configuration)	20
Step 8: BRW-upgrade (Browser)	20
Step 9: DODE-upgrade (Print Studio)	20
Step 10: LGV-upgrade (LogiView)	20
Step 11: WFL-upgrade (Workflow)	21
Step 12: CHG-upgrade (Change Management)	21
Step 13: GTM-upgrade (Classification)	21
Step 14: GDM-upgrade (Office Suite)	22
Step 15: RMT-upgrade (Requirement Management Traceability)	22
Step 16: run after-common-scripts	22
Step 17: Upgrading Classification (optional)	22
Step 18: Classification attribute inheritance	23
Step 19: Special replace	23
Specific Dump Changes	23
Perform Upgrade in Batch Mode	23
Import DataView Repository with DTV.BLD	25
Convert XML Files to HTML	25
Takeover Production Data	25
Pre-Action on Microsoft SQL Server	26
Define Reference Tables	26
Edit Production Table List	26
Perform Transfer	27
Taking Over Number Server Values	27
Post-Action Scripts	27
Classification (Stage 2)	28
Manual Dump Changes	28
LogiView	28
STEP	28
Customer Specific Changes	28
Post-Actions on Microsoft SQL Server	28
<b>Chapter 4 Additional Information</b>	<b>30</b>
Browser Upgrade	30
Cleanup BVB_ARTIKEL	30
STA_LUT	30
Project References in Processes	30
BVB_ARTMEH Upgrade	31
Favorites Upgrade	31
Classification	31
Workflow Takeover	33
<b>Chapter 5 Appendix</b>	<b>34</b>
Appendix A: CMD Scripts	34

Appendix B: Configuration Files in /conf/	37
Appendix C: Contents of the Folder “upgrade/conf/template”	37
Appendix D: SQL Scripts	38
Appendix E: Directories	40
Appendix F: Migration Rules	41
Standard Rules for Delete	41
Standard Rules for Update	41
Standard Rules for Insert	41
Special Rules	42

# Chapter 1

## Introduction

### Overview

This guide is intended as a manual for upgrading earlier versions of the Agile e-series products to Agile e6.0.3 with the Agile Upgrade Tool.

The Upgrade tool allows a direct upgrade to Agile e6.0.3 from one of the following product versions:

- CADIM/EDB 2.3.2 or higher
- axalant 2000 SPx
- Eigner PLM 5.x
- Agile e6.x

### Prerequisites


- Do not use the software in any situation where significant damage to property or business could occur from a software error. In no event will AGILE or any other party who has been involved in the creation, production or delivery of the software be liable for special, direct, indirect, incidental, punitive or consequential damages, including loss of profits, revenue, business, goodwill, data or computer programs, or inability to use the software, however, caused and regardless of the theory of liability even if AGILE or such other party has been advised of the possibility of such damages.
- The Upgrade Tool addresses experienced project engineers and PLM administrators with customizing and database experience. Do not use the tool without the necessary knowledge. Read the complete manual in order to get all necessary information.
- Do not attach to, or even change the production system. Always work on a copy of the production database dump. Avoid working on production computers to exclude any influence on the system. Never insert database connections of production database users in any configuration file or script except for exporting the dump or a source for copying tables (Production Database).
- You should always be able to restart the old PLM version (CADIM/EDB, axalant or Eigner PLM 5.x) as a fallback strategy.
- The best performance is reached when installing the upgrade tool on your database server. It is also possible to work on any machine in the LAN.
- Dump upgrade takes up to 8 hours runtime per each environment - please have patience.
- Upgrade tool is running on Windows 2003 Server and all UNIX platforms officially supported for Agile e6 series.
- At least JRE 1.4.2\_08 should be installed on the machine and configured in the environment (JAVA\_HOME must be set – this can be done in upg\_env.cmd resp. upg\_env.sh script).
- SQLCMD.EXE should be installed.

- ❑ Database versions supported in this upgrade tool are Oracle 10.1.0.4 / Oracle 10.2.0.2 and Microsoft SQL Server 2005 SP1 (English/German).
- ❑ For production database link (step Takeover production data) Oracle 8.1.7 / 9.2.0.4 and Microsoft SQL Server 2000 SP4 can be used.
- ❑ ORACLE\_HOME variable must be set for “system V” operating system – Unix/Linux etc. This can be done in upg\_env.cmd (upg\_env.sh) script.
- ❑ SQL\*PLUS must be installed on the machine.
- ❑ At least 250 MB hard disk space must be available for the software and generated log and data files on the local hard disk where the tool is installed.
- ❑ At least 512 MB free RAM must be available to run a dump upgrade.
- ❑ Sufficient disc space must be available to store copies of your production database and reference dumps on the machine / within the database.

For additional information and most up-to-date upgrade information, check the Agile Support page at <http://eignersupport.agilesoft.com/index.asp> (you will need a password to enter the support website).

## How it Works

The upgrade tool is implemented in Java. The tool accesses the databases directly using a JDBC connection. The configuration of all upgrade steps is stored in a set of xml control files. In addition SQL scripts are used for special steps.



The upgrade process is organized in following phases:

- ❑ Pre-actions on the original production environment
- ❑ Customizing Upgrade  
In this step the customization and configuration stored in the database is updated to Agile e6. The minimum passing time will be 4-5 hours (depending on the system. Main parameter is memory!). Make a copy of your production database dump. Do not attach your production system. Always work on a copy of your data.
- ❑ Customizing / Test phase  
The upgrade tool will create a dump on which you can run Agile e6. All



functionalities must be tested to run correctly, including the whole customer-specific functionality. This dump is not error free. You have to check all functionalities and clear out the errors caused by setting up the upgrade tool.

- Take over production data  
All tables containing production data, like document and item master data, are copied from the production system to your new Agile e6 dump. They will be adapted so that you can work on this data within Agile e6.

Log files are created and stored in the log/ directory. After the dump upgrade is done, these files have to be reviewed, especially the errors.log file, to make sure there are no errors, otherwise manual dump changes have to be made. Further “synchronize step” log files placed in data/sync have to be reviewed. Please control log files after each upgrade step and correct occurred errors manually before proceeding with upgrade.

# Chapter 2

## Installation and Configuration

### ApplicationParameter.xml Template

The upgrade tool is preconfigured for an upgrade of an oracle database dump. Before proceeding with upgrade on Microsoft SQL Server, please copy the file `conf/template/ApplicationParameter.xml` to `conf/ApplicationParameter.xml`.

### Database Settings in Oracle

The upgrade tool needs a well-configured database to provide a good performance. The Oracle standard database settings are not sufficient to run the program within the stated time.

### Oracle Parameters

Check the Oracle parameters and verify that at least the following minimum values are set in your database instance:

- `db_cache_size`  $\geq$  200,000,000 (200MB)
- `shared_pool_size`  $\geq$  100,000,000 (100MB)
- `log_buffer`  $\geq$  163,840 (3\*64 Kbytes)

If the database memory consumption is too small, adapt the values.

If you use the server parameter file spfile (like in the Agile e6 standard installation), execute the following commands to change the values of the initialization parameters.

- Login into Sql\*Plus as user sys

```
C:\> Sqlplus /nolog
SQL>CONNECT <sys>@<db_service> as sysdba
SQL>ALTER SYSTEM SET <parameter name>=<Value> SCOPE=BOTH
```

**Note:** Do not change the values of production systems. Make a copy of the initialization file and adapt the values.

- Also read the Oracle online manuals and the Oracle10.1 installation manual from Agile.

Oracle needs physical memory. If the system starts swapping or paging, the Oracle performance degrades or causes errors. Examine your free physical memory and prevent the OS from swapping.

Some Unix systems have maximum values for shared memory. Refer to the installation instructions before changing any value.

### SQL Net Configuration.

The network domain is part of different oracle settings. Please check if the domain is consistently used for the following settings:

- Global Database
- Service name
- Listener.ora
- Default domain name

### Global Database Name

1. Login into Sql\*Plus as user sys and check the global database name.

The name should contain the network domain. Here is an example:

```
sqlplus <system>/<db_password>@<db_service>
SQL>select * from global_name;
GLOBAL_NAME -----
PLM.WORLD
```

The example uses the default network domain in world. Also possible are values like agile.agilesoft.com.

2. Change the global database name login to Sql\*Plus and execute the following commands:

```
SQL>alter database global name plm.agile.agilesoft.com
```

### Service Name

The service name in the SQL net configuration file tnsnames.ora in the directory \$ORACLE\_HOME/network/admin must include the network domain.

1. Change to the directory \$ORACLE\_HOME/network/admin
2. Open the file tnsnames.ora and check if the service name is fully defined.

That means the name contains the same network domain as the global database name.

```
PLM.WORLD =
(DESCRIPTION =
  (ADDRESS_LIST =
    (ADDRESS = (PROTOCOL = TCP)(HOST = localhost)(PORT = 1521))
  )
  (CONNECT_DATA =
    (SERVICE_NAME = PLM.WORLD)
  )
)
```

### listener.ora

1. Check if the global database name in the section SID\_List of the listener configuration file contains also the same fully qualified global database name.

```
SID_LIST_LISTENER_PLM =
(SID_LIST =
  (SID_DESC =
    (GLOBAL_DBNAME = PLM.WORLD)
    (SID_NAME = plm)
  )
)
```

```
LISTENER_PLM =  
  (DESCRIPTION =  
    (ADDRESS = (PROTOCOL = TCP)(HOST = localhost)(PORT = 1521))  
  )
```

### **sqlnet.ora**

The default setting for the network domain in the sqlnet.ora file should be the same. Change to the directory \$ORACLE\_HOME/network/admin and open the file sqlnet.ora and check the default domain settings.

```
names.default_domain = world
```

## **Database Settings in Microsoft SQL Server**

The memory consumption of an SQL Server is dynamic. The actual memory settings on the new database server have to be controlled.

1. Start the Enterprise Manager.
2. Select the server name and choose SQL-Server Properties in the Extra Menu.
3. Select folder “memory” in the new window and adjust the values

## **Tablespaces / File Groups**

Check if the following table spaces (Oracle) or file groups (SQL Server) exist in your database.

- edb\_tmp
- edb\_tmpidx
- edb\_lob
- edb\_tmp
- edb\_tmpidx

**Note:** If one of them does not exist they have to be created!

### **Oracle**

1. Change to the directory upgrade/ora/sql.
2. Adapt file names, paths, and file size in the script cre\_plm\_tbs.sql.
3. Login as user system to Sql\*Plus and execute cre\_axa\_tbs.sql.

```
sqlplus system/<password>@PLM60  
SQL> @cre_plm_tbs.sql
```

### **SQL Server**

1. Check if the following file groups exist in your database:

```
edb, edb_idx, edb_lob, edb_tmp, edb_tmpidx
```

2. Call the script missing\_f.cmd for the customer dump to create the missing file groups.

Example how to call missing\_f.cmd in the command line:

```
missing_f.cmd1 sa2 password3 ceqell\axa4 edbprod5 d:\mssql\data6 d:\mssql\data7 d:\mssql\data8
```

Parameters:

- 1 script name to be executed
- 2 Database administrator login
- 3 Database administrator password
- 4 Instance name (e.g. <hostname>\axa)
- 5 Database name
- 6 Path where edb\_lob file group will be placed
- 7 Path where edb\_tmp file group will be placed
- 8 Path where edb\_tmpidx file group will be placed

## Pre-Activities on the Original Production Environment

Since Eigner PLM 5.0 UIC  $\leq 1000$  and GIC  $\leq 1000$  are reserved for the standard development, existing users or groups using such C\_IC / C\_GIC must be migrated to a higher value.

This action must be executed only on production dump with PLM version older than Eigner PLM 5.0. This migration must be executed before you start any other upgrade activity.

**Note:** It can be very time consuming!

In a big customer dump it takes 1h/6 users. To solve the time conflict, break down the update into different subsets and try to run it in parallel.

To do this, adapt the following statement in the SQL script:

```
INSERT INTO TEMP_U (OLD_U) SELECT C_IC FROM T_USER a
WHERE
C_IC > 200 AND C_IC < 1000 AND C_NAME NOT LIKE 'EDB%' AND
C_NAME NOT LIKE 'DEMOEP%';
```

To execute the UIC/GIC Migration run following commands:

```
sqlplus <user>/<password>@PLM
SQL> @update_customers_UIC.sql
```

On Microsoft SQL Server run following:

```
cmd> sqlcmd.exe -x -S <server> -U <user> -P <password>
-i ..\mssql\sql\update_customers_UIC.sql
-o ..\log\update_customers_UIC.log
```

## Import Dumps

Three dumps need to be imported into the new database environment:

- Source reference dump
- Target reference dump

- ❑ Customer dump

For importing the dumps, do not change the tablespace names because the created table statements on tables containing a blob clause will fail if the original table spaces like EDB, EDB\_IDX and EDB\_LOB do not exist

To import dumps into the database you have to be familiar with your database environment and Oracle / SQL Server import utilities as well. Alternatively, a batch script called `imp_dmp.cmd` can be used for automated imports (Oracle only). This script uses dumps located in the directory `upgrade/dumps`.

## Import Source Reference Dump

1. Download appropriate source reference dump from <http://eignersupport.agilesoft.com/index.asp> and import it into the new database environment.

Example: import `plm50upgref.dmp` into a user named `PLM50UPGREF`

2. Import target reference dump
3. Download the latest target reference dump from <http://eignersupport.agilesoft.com/index.asp> and import it into the new database environment.

Example: import `plm601upgref.dmp` into a user named `PLM601UPGREF`.

**Note:** Agile upgrade tool supports the latest Agile e-series version only!

## Import Customer Dump

1. Export the current production environment into a dump file and import it in the new environment.

**Note:** Always work on this customer dump. Do not attach production dump during the upgrade process except for take over step described below.

This dump will be the new production dump after the upgrade is completed.

2. Give the new environment an expressive name.

**Note:** Change the database owner and (re-)create login/password account for each restored SQL Server database with the command file `upgrade/cmd/chown_mssql.cmd` delivered with upgrade tool. Run `chown_mssql.cmd` and provide the following information into the shell screen:

- ❑ server: [localhost] - name of the SQL Server
- ❑ server: [localhost] - name of the SQL Server
- ❑ database name: [plm60] - name of the database
- ❑ new password: - password for the new account
- ❑ DB administrator: [sa] – database administrator
- ❑ password: – administrator’s password
- ❑ old schema name: – schema name, where objects are currently stored ('plm' for e6 SQL Server databases). In most cases it is a schema, which owns the most objects

**Note:** On SQL server set recovery model to “simple” for customer database, which prevents an unlimited growth of database log files. Run following statement to set the recovery model:

```
ALTER DATABASE <database> SET RECOVERY SIMPLE WITH NO_WAIT
GO
ALTER DATABASE <database> set READ_COMMITTED_SNAPSHOT OFF
GO
```

## Create Statistics for all Involved Database Schemas

### 1. Check Language settings

Because of an Oracle bug the setting for the environment variable NLS\_LANG must be AMERICAN\_AMERICA.WE8ISO8859P15. Otherwise, statistics will not be computed correctly.

### 2. Login in Sql\*Plus as user sys with sysdba privilege and perform analyzing.

```
SQL> EXECUTE DBMS_STATS.GATHER_SCHEMA_STATS(<DBUSER>,CASCADE =>true);
```

## Run Upgrade Tool

### 1. Set a DISPLAY variable on UNIX

### 2. Control the NLS\_LANG setting in upg\_env.sh (upg\_env.cmd on windows) which specifies the client character set. “AMERICAN\_AMERICA.WE8ISO8859P15” is a default setting for upgrade reference dumps.

### 3. Adapt the following environment definitions in upg\_env.sh on UNIX:

- JAVA\_HOME - at least JRE 1.4.2 is required by the upgrade tool. In the standard configuration of the file the JRE of the Agile e6 installation is used for that.
- ORACLE\_HOME - make sure that Oracle 10.1.4 environment is set before proceeding with upgrade. To check the environment for UNIX, execute the following commands:

```
user@host:~> env|grep ORA
```

The output should look like this:

```
/usr/oracle> env|grep NLS
NLS_LANG=AMERICAN_AMERICA.WE8ISO8859P15
ORA_NLS33=/usr/oracle/product/10g_db/ocommon/nls/admin/data
/usr/oracle> env|grep ORA
ORACLE_BASE=/usr/oracle
ORACLE_HOME=/usr/oracle/product/10g_db
ORACLE_SID=TITAN
ORACLE_DOC=/usr/oracle/product/10g_db/doc
ORACLE_TERM=xterm
ORA_NLS33=/usr/oracle/product/10g_db/ocommon/nls/admin/data
/usr/oracle>
```

## Configure the Upgrade Tool

### Configure New Database Environment Connections

1. Run start\_upg.cmd (start\_upg.sh on UNIX) and enter the following information for dumps in your new database environment.

Each database connection can be tested with a “TEST” button on an appropriate tab.

**Note:** Press return after every change in a field. The color turns back from red to black. Otherwise the changes will be lost.

Use file group names in Tablespace fields for Microsoft SQL Server. These are case sensitive; therefore, you have to use lower case.

If you want to connect to a Microsoft SQL Server named instance, please specify a correct servername\instancename in the field “server” as well as the corresponding TCP port number. You can find the appropriate port configuration within the Configuration Manager.



Parameter	Description
Host	Host name of database server
Port	Port number of Oracle listener (default 1521 ) or SQL Server port number (default 1433)



Parameter	Description
SID	Oracle_SID (uppercase) or database name for SQL Server (lowercase)
User	Database user name
Password	Password of database user
Connection String	Service name which is used to run SQL*PLUS commands on the machine the upgrade tool is installed on. Use fully qualified name including the network domain, i.e. plm60.agile.agilesoft.com Note: the service name cannot be tested in the current version of upgrade tool

Adapt tablespace names for each database connection since they are used, e.g. for creation of new database objects or running SQL scripts:

Table	Default EDB <sup>*</sup>
Index	Default EDB_IDX <sup>*</sup>
LOB	Default EDB_LOB <sup>*</sup>
Temporary table	Default EDB_TMP <sup>*</sup> (edb on SQL Server until axalant 2000 SP3 )
Temporary index	EDB_TMPIDX <sup>*</sup> (edb_idx on SQL Server until axalant 2000 Sp3)

**Note:** Lower case for SQL Server, upper case for Oracle.

## Configure Production Dump Connection

1. Enter a database connection for the current production dump.

This connection will be used at the end of the upgrade process in the “Take over” phase. The definition of this connection is different, because it is implemented as a database link, which is temporary created in your new customer dump. Creation of the database link can be tested with the “TEST” button.

This connection will not be used until the takeover phase of the upgrade process.

**Note:** Press return after every change in a field. The color turns back from red to black. Otherwise, the changes will be lost.

A named instance can also be used for a production environment connection. Please enter “servername\instancename” in the Server field in this case.

For testing this connection, grant access to currently production environment for the customer database user running these statements as Microsoft SQL Server Administrator like SA.

<login\_name> is the customer database login.

```
GRANT ALTER ANY LOGIN TO <login_name>
GO
GRANT ALTER ANY LINKED SERVER TO <login_name>
GO
```



Parameter	Description
Service Name	Oracle service name including network domain, i.e. AGILE.AGILESOFT.COM. Service name must be defined in tnsnames.ora.
SID	Oracle_SID (uppercase) or database name for SQL Server (lowercase).
User	Database user name.
Password	Password of database user.

### Setting Upgrade Tool Parameters

Review and correct the entries if necessary and check the following table for valid entries. The correct values can be determined with the Compute button. Always check the computed values.

**Note:** Press return after every change in a field. The color turns back from red to black. Otherwise, the changes will be lost.



PLM-Version	<p>The customer dump version (before Agile e6 upgrade process). Following values are valid:</p> <ul style="list-style-type: none"> <li>1 = CADIB/EDB 2.3.x</li> <li>2 = AXALANT SP1</li> <li>3 = AXALANT SP2</li> <li>4 = AXALANT SP3</li> <li>5 = PLM 5.0</li> <li>6 = e6.0 LA</li> <li>7 = e6.0 GA</li> <li>8 = e6.0.1</li> <li>9 = e6.0.2</li> </ul>
LogiView Timestamp	<p>All LogiView items with a change date after this time point will be deleted. You can adapt this value manually. Following values are possible:</p> <ul style="list-style-type: none"> <li>CADIM/EDB 2.3.2 – 19990329094555</li> <li>CADIM/EDB 2.3#3 – 19990707174038</li> <li>CADIM/EDB 2.3#4 – 19990707174038</li> <li>CADIM/EDB 2.3#5 – 20000329161725</li> <li>axalant2000 SP1 – 20001109140557</li> <li>axalant2000 SP2 – 20010723102350</li> <li>axalant2000 SP3 – 20011113092600</li> <li>axa2000 SP3 PA1 – 20020808110309</li> <li>Eigner PLM 5.0.1 - 20020830153411</li> <li>Agile e6.0 LA - 20050414160530</li> <li>Agile e6.0 GA - 20050615170000</li> <li>Agile e6.0.1 - 20051111135800</li> <li>Agile e6.0.2 - 20060630200000</li> </ul>

Classification – Control file	<p>A file name of the control file for the customer dump in the present case. Valid entries are:</p> <p>cla_ctl.xml          cla_ctl_with_multi_lang.xml          cla_ctl_with_multi_lang_repl.xml          cla_ctl_with_repl.xml</p>
Database Language	<p>Language for the database dump. This influences the migration of the classification date.</p> <p>Values: German, English          Default: German</p>
Level	<p>Status that is set during classification upgrade for records in the tables T_CLA_DAT (pool attributes), T_GROUP_DAT (classes)</p>
Replication server	<p>The valid name of the database server, in case of an implemented database replication to the environment, should be migrated.</p>

### Save Configuration


1. Save the current configuration by selecting File / Save parameter.

# Chapter 3

## Perform the Upgrade

### Perform the Upgrade in Interactive Mode

This chapter describes how the customizing upgrade is executed interactively. There are different steps available for selection on the ACTION tab, which should be executed in the respective order.



#### Step 1: run pre-action-scripts

The command script upg03\_preaction\_sql.cmd will be executed. This script executes a couple of SQL scripts (depending on the customer dump version). Log files created in this step in the upgrade/log directory have to be reviewed manually before proceeding with upgrade.

A complete list of SQL / LOG files created in this step can be found in the Appendix.

#### Step 2: DTV-upgrade

This step upgrades the DataView repository and is generally split into two steps:

- ❑ Compares the data sets from the different dumps and stores the changes in an XML file for the three possible operations: delete, insert and update:  
dtv\_del.xml, dtv\_ins.xml, dtv\_upd.xml  
The upgrade tool selects each row from the source and the target reference dumps,

compares the data sets from both dumps to identify the differences and checks if the customer has modified these data. The upgrade action (Insert, Update, and Delete) is determined for each record and the information is stored in a set of XML files. The migration rules are listed in the Appendix.

**Note:** This step takes around 10 min - 4 hours.

- ❑ Performing operations. The upgrade tool reads the XML files created during the previous operation and performs the corresponding SQL-statements. This step takes about 15 - 40 min. During the performing an error log file `data/dtv/dtv_err.xml` is created and should be checked for possible errors.

**Note:** A `dtv_customizing.log` is created in the directory `data/dtv/` also. It contains conflicts, which occurred during the DTV-upgrade. This log file must be reviewed.

Check log files in the directory `upgrade\data\dtv`. If an error occurs, check the error description in `upgrade\log\errordetails.log`.

**Note:** The upgrade tool is only able to compare tables with the same table structure. Therefore, the DataView tables in the reference dumps (`edb234upgref ...`) have an Agile e6 structure.

**Note:** For a better readability, it is possible to create HTML files from the XML log files (see `Convert XML files to HTML`).

### Step 3: run before-sync-scripts

The command script `upg07_sync_update.cmd / upg07_sync_update.sh` is executed. This script executes a SQL script (depending on the customer dump version). Log files created in this step in the `upgrade/log` directory have to be reviewed manually before proceeding with the upgrade.

A complete list of SQL / LOG files created in this step can be found in the Appendix.

### Step 4: Synchronize\_Repository

During this step the table definition in DataView within the customer dump is compared to the physical table structure in the database. SQL statements to create and alter database objects are generated and executed automatically. The adaptation of the physical data structure will consist of the following steps:

- ❑ Analyze phase  
In this phase you can see which statements the program will perform. It creates also a control file named `conf/special.xml` for field values and special tasks. This step takes about 1-6 min.
- ❑ Review and edit the control file `conf/special.xml`
- ❑ Synchronize phase  
In this step, database structure is converted according to the new DataView repository. This step takes about 1 min – 4 h.

The data and log files are placed in the `data\sync` directory. A detailed description of the errors can be found in `log\errordetail.log`.

**Note:** If the program terminates the process and releases the connection because of a server error, drop the `special.xml` file in `conf/` directory and copy the

preconfigured template from conf/template into the conf/ directory. Restart the process.

## Analyze

In this step, a proposal special.xml file is written to the conf/ directory.

### Configure special.xml for Synchronizing Repository

The delivery package contains a preconfigured special.xml, which defines standard settings for all expected cases. Very often the customer dump contains inconsistencies so that in the analyze mode the tool will add entries to the special.xml file. In this case you need to review and adapt following configuration subsets:

**Note:** Do not change or delete the default settings.

- ❑ Static default values for columns changed from null to not null.  
In the following example the column T\_TRE\_DAT.CUR\_FLAG is set to 'n'.

```
<FieldDefault>
  <FieldName>T_TRE_DAT.CUR_FLAG</FieldName>
  <FieldType>S</FieldType>
  <FieldSize>1</FieldSize>
  <DefaultValue>
    <Value>n</Value>
  </DefaultValue>
</FieldDefault>
```

- ❑ Dynamic default values.  
The field values can be computed dynamically based on a Java function / SQL Statement. Preconfigured function are available to use the number server to set values. Here an example for an SQL statement and JAVA generated field default:

```
<FieldDefault>
  <FieldName>T_CTX_DAT.EDB_SEQ</FieldName>
  <FieldType>I</FieldType>
  <FieldSize>4</FieldSize>
  <DefaultValue>
    <Select>
      DISTINCT (SELECT COUNT(*) FROM T_CTX_DAT T WHERE T.C_ID &lt;= thisRec.C_ID)*10
    </Select>
    <Where>C_ID &gt; 0</Where>
  </DefaultValue>
</FieldDefault>
```

```
<FieldDefault>
  <FieldName>T_MASTER_DOC.EDB_ID</FieldName>
  <FieldType>I</FieldType>
  <FieldSize>10</FieldSize>
  <DefaultValue>
    <Function>GetNewEDBID(EDBEDBID)</Function>
  </DefaultValue>
</FieldDefault>
```

- ❑ Rename tables.  
If you have used DFM already, the following tables must be renamed (for upgrade from CADIM to Agile 6 only).
  - T\_EER\_SIT
  - T\_EER\_SIT\_STR
  - T\_EER\_SIT\_MED

```
<RenameTable>
  <TableName>T_EER_SIT</TableName>
  <NewTableName>T_DDM_SIT</NewTableName>
</RenameTable>
<RenameTable>
  <TableName>T_EER_SIT_STR</TableName>
  <NewTableName>T_DDM_SIT_STR</NewTableName>
</RenameTable>
```

- ❑ Move fields.  
This option allows to move a column of a table inclusive stored values to a new location. To move a field you have to specify:
  - Source field (<table\_name>.<column\_name>)
  - Target field (<table\_name>.<column\_name>)and
  - Path (join condition between old and new table)

The following sample configuration files show 3 different possibilities to move field values to a new location.

```
<!-- Example transfer from typetable to entitytable. -->
<MoveField>
  <SourceField>T_DOC_DRW.CRE_USER</SourceField>
  <Path>T_DOC_DRW.C_ID_2</Path>
  <Path>T_DOC_DAT.C_ID</Path>
  <DestField>T_DOC_DAT.CAX_CRE_SYSTEM</DestField>
</MoveField>
```

```
<!-- Example transfer from entitytable to entitytable via relevationtable. -->
<MoveField>
  <SourceField>T_MASTER_DAT.PART_ID</SourceField>
  <Path>T_MASTER_DAT.C_ID</Path>
  <Path>T_MASTER_DOC.C_ID_1</Path>
  <Path>T_MASTER_DOC.C_ID_2</Path>
  <Path>T_DOC_DAT.C_ID</Path>
  <DestField>T_DOC_DAT.CAX_CRE_SYSTEM</DestField>
</MoveField>
```

```
<!-- Example transfer in table. -->
<MoveField>
  <SourceField>T_MASTER_DAT.PART_ID</SourceField>
  <DestField>T_MASTER_DAT.EDB_ICON</DestField>
</MoveField>
```



If you have a CAX interface already installed, please check if one of the columns used to store CAX specific information is defined as a document-type-table-column. These columns are now part of the standard data-model and included in the document master table T\_DOC\_DAT (migration from CADIM to Agile e6).

An example configuration file special\_move.xml containing definition of moved fields is stored in the template directory conf/template/

- Change data type of a field  
The upgrade tool allows changing the type definition of columns like integer to string. If the value of a column for all records is null then also incompatible data type changes can be executed (e.g. string to integer). Cutting a string field is only possible if no record contains a longer value. Please check max length of stored values directly within Sql\*Plus.

You have to replace “false” by “true” to confirm such critical changes. The type definition “oldType” comes from the database; “newType” is the DataView definition (stored in T\_FIELD. C\_FORMAT).

```
<FieldChange>
<FieldName>T_DOC_DAT.FOO</FieldName>
<ConfirmChange oldType="S80.0" newType="S40.0">false</ConfirmChange>
</FieldChange>
```

### Synchronize

In this step, dump structure are adapted to DataView repository using the special.xml entries to fill NOT NULL fields.

### Step 5: run after-sync-script

The command script upg08\_postactions is executed. This script executes a set of SQL scripts. Check the results in the log files named log/08\_\*.log. For a complete list of log files please refer to the Appendix.

During this upgrade step a valid reference to T\_STA\_LUT is established with values in EDB\_STA\_REF for each entry in T\_CHK\_STA. Additionally, EDB\_LEVEL within the table T\_STA\_LUT is filled.

**Note:** The values of the table T\_STA\_LUT have to be reviewed after the customizing upgrade.

Additionally, BVB\_ARTIKEL clean up step is executed. For more information please refer to 0 Cleanup BVB\_ARTIKEL.

**Note:** PLM5 and older favorites are migrated in this upgrade step as well. For more information please refer to 14.5 Favorites upgrade.

**Note:** The favorite migration can be performed after the first takeover execution because it needs standard browser entries, which are inserted later within the step BRW-upgrade.

And finally, the T\_PRC\_DAT.EDB\_PRO\_REF column is filled during this upgrade step. For more information please refer to 0 Project references in processes.

### Step 6: run before-common-scripts

The command script upg09\_common\_get is executed. This script starts the SQL script to save and delete standard LogiView models. Check log files named log\09%.log

### Step 7: EDB-upgrade (Configuration)

During this step the content of the common Agile configuration tables are upgraded. The appropriate xml files are stored in data/edb/ directory.

1. Click on the button "create files".

XML files edb\_ins.xml, edb\_del.xml, and edb\_upd.xml are created. They can be reviewed before performing these actions on the database dump.

2. Click on the button "Perform delete, insert, update".

XML files created in the previous step are read and executed. Errors occurred during these actions are stored in edb\_err.xml – please control this file.

**Note:** If an error occurs, check the error description in upgrade\log\errorrdetails.log.

### Step 8: BRW-upgrade (Browser)

During this step the content of the browser configuration tables is upgraded. The appropriate xml files are stored in the data/brw/ directory.

1. Click on the button "create files".

XML files brw\_ins.xml, brw\_del.xml, and brw\_upd.xml are created. They can be reviewed before performing these actions on the database dump.

2. Click on the button "Perform delete, insert, update".

XML files created in the previous step are read and executed. Errors occurred during these actions are stored in brw\_err.xml – please control this file.

**Note:** If an error occurs, check the error description in upgrade\log\errorrdetails.log.

### Step 9: DODE-upgrade (Print Studio)

During this step the content of the Print Studio configuration tables will be upgraded. The appropriate xml files are stored in data/dode/ directory.

1. Click on the button "create files".

XML files dode\_ins.xml, dode\_del.xml, and dode\_upd.xml are created. They can be reviewed before performing these actions on the database dump.

2. Click on the button "Perform delete, insert, update".

XML files created in the previous step are read and executed. Errors occurred during these actions are stored in dode\_err.xml – please control this file.

**Note:** If an error occurs, check the error description in upgrade\log\errorrdetails.log.

### Step 10: LGV-upgrade (LogiView)

Several standard LogiView procedures are changed in every new Agile PLM software release. All LogiView logic models are deleted – if they are identical to new ones respectively saved if they were changed. Next, all new logical models are re-inserted. After the upgrade all LogiView changes made by customer must be made again.

Additionally standard LogiView variables, constants, and system variables are upgraded in the usual manner.

The appropriate xml files are stored in data/lgv/ directory.

1. Click on the button "create files".

XML files lgv\_ins.xml, lgv\_del.xml, and lgv\_upd.xml are created. They can be reviewed before performing these actions on the database dump.

2. Click on the button "Perform delete, insert, update".

XML files created in the previous step are read and executed. Errors occurred during these actions are stored in lgv\_err.xml – please control this file.

**Note:** If an error occurs, check the error description in upgrade\log\errorrdetails.log.

### Step 11: WFL-upgrade (Workflow)

During this step the content of the workflow configuration tables is upgraded. The appropriate xml files are stored in the data/wfl/ directory.

1. Click on the button "create files".

XML files wfl\_ins.xml, wfl\_del.xml, and wfl\_upd.xml are created. They can be reviewed before performing these actions on the database dump.

2. Click on the button "Perform delete, insert, update".

XML files created in the previous step are read and executed. Errors occurred during these actions will be stored in wfl\_err.xml – please control this file.

**Note:** If an error occurs, check the error description in upgrade\log\errorrdetails.log.

### Step 12: CHG-upgrade (Change Management)

During this step the content of the change management configuration tables is upgraded. The appropriate xml files are stored in the data/chg/ directory.

1. Click on the button "create files".

XML files chg\_ins.xml, chg\_del.xml, and chg\_upd.xml are created. They can be reviewed before performing these actions on the database dump.

2. Click on the button "Perform delete, insert, update".

XML files created in the previous step are read and executed. Errors occurred during these actions are stored in chg\_err.xml – please control this file.

**Note:** If an error occurs, check the error description in upgrade\log\errorrdetails.log.

### Step 13: GTM-upgrade (Classification)

During this step the content of the classification configuration tables is upgraded. The appropriate xml files are stored in the data/gtm/ directory.

1. Click on the button "create files".

XML files gtm\_ins.xml, gtm\_del.xml, and gtm\_upd.xml are created. They can be reviewed before performing these actions on the database dump.

2. Click on the button "Perform delete,insert,update".

XML files created in the previous step are read and executed. Errors occurred during these actions are stored in gtm\_err.xml – please control this file.

**Note:** If an error occurs, check the error description in upgrade\log\errorrdetails.log.

### Step 14: GDM-upgrade (Office Suite)

During this step the content of the Office Suite configuration tables is upgraded. The appropriate xml files are stored in the data/gtm/ directory.

1. Click on the button "create files".

XML files gdm\_ins.xml, gdm\_del.xml, and gdm\_upd.xml are created. They can be reviewed before performing these actions on the database dump.

2. Click on the button "Perform delete, insert, update".

XML files created in the previous step are read and executed. Errors occurred during these actions are stored in gdm\_err.xml – please control this file.

**Note:** If an error occurs, check the error description in upgrade\log\errorrdetails.log.

### Step 15: RMT-upgrade (Requirement Management Traceability)

During this step the content of the RMT-module configuration tables is upgraded. The appropriate xml files are stored in the data/rmt/ directory.

1. Click on the button "create files".

XML files rmt\_ins.xml, rmt\_del.xml, and rmt\_upd.xml are created. They can be reviewed before performing these actions on the database dump.

2. Click on the button "Perform delete, insert, update".

XML files created in the previous step are read and executed. Errors occurred during these actions are stored in gdm\_err.xml – please control this file.

**Note:** If an error occurs, check the error description in upgrade\log\errorrdetails.log.

### Step 16: run after-common-scripts

The command script upg10\_common\_update is executed. This script executes an SQL script to migrate non-standard browser entries to the new Agile e6 browser based on new database tables having a prefix T\_EXP\_\*. Check the results in the log files named log/10\_\*.log. For a complete list of log files please refer to the Appendix.

This step can be skipped if you are migrating from Agile e6.0 or newer.

### Step 17: Upgrading Classification (optional)

In Eigner PLM 5.0 a new concept – Attribute pool was introduced. This step converts attributes within the customer dump to this new concept. This step must be skipped, if you are migrating from PLM5.x version or newer.

1. Click on “Determine merge condition”.

A special xml control file data/cla/cla\_merge\_ctl.xml is created. It describes how attributes are moved into a global attribute pool and contains so-called merge groups. All attributes mapped onto the same pool attribute are in the same merge group. Please review it and adapt if changes are necessary. This mapping file is used at the end of the takeover phase to migrate current production data to existing attribute pool

## 2. Click on “Perform mapping”.

This will build the attribute pool and perform mapping to item, to documents, etc.

**Note:** Please check log files located in the data/cla/ directory. For more information please refer to Chapter 4, Classification.

### Step 18: Classification attribute inheritance

Since Agile e6.0 a new attribute inheritance concept was introduced. To convert existing class attributes, this upgrade step has to be executed.

**Note:** It is not necessary if you are migrating from Agile e6.0 or newer.

### Step 19: Special replace

This optional upgrade step allows a string replacement within table content.

This configuration file conf/specialreplace.xml contains an example definition for migrating from CADIM 2.3.x of substrings, which should be replaced by another string.

Example: Update the strings ‘T\_EER\_SIT’ with ‘T\_DDM\_SIT’ in LogiView procedures

```
<?xml version="1.0" encoding="UTF-8"?>
<special>
  <replace>
    <table>LV_DT_PRC</table>
    <field>MAIN</field>
    <example>T_EER_SIT</example>
    <replacewith>T_DDM_SIT</replacewith>
  </replace>
</special>
```

### Specific Dump Changes

Recreate customer specific indexes, views, packages, procedures and triggers, database constraints like field defaults, etc.

### Perform Upgrade in Batch Mode

After the upgrade is tested completely in the interactive mode, it can be used in batch mode. UNIX scripts for batch mode execution are available too. These have the .sh extension (instead of .cmd for Windows).

**Note:** Batch mode is intended for experienced upgrade users. Many upgrade steps are compressed in few batch scripts, so that they possibly need to be adapted manually.

The batch mode can be used in the following manner:

- Do an upgrade in interactive mode
- Re-import customer dump
- Start start\_upg.cmd and control the configuration
- Clean the log directory by executing upg01\_pre\_cleanlog.cmd
- Run the following scripts:
  - upg03\_preaction\_sql.cmd
  - upg05\_dtv\_update.cmd
  - upg07\_sync\_update.cmd
  - upg08\_postaction.cmd
  - upg10\_common\_update.cmd
  - upg11\_cla.cmd
- Control log files
- Take over production data by executing upg13\_prod1\_takeover.cmd
- Run post-action scripts by executing upg14\_prod2\_rep\_update.cmd.

Alternatively, a whole upgrade process may be performed in the batch mode:

- Import customer dump
- Start start\_upg.cmd and configure the upgrade tool.
- Run following scripts:
  - upg03\_preaction\_sql.cmd
  - upg04\_dtv\_get.cmd
  - upg05\_dtv\_update.cmd
  - upg06\_sync\_get.cmd
- Adapt special.xml
- Run following scripts:
  - upg07\_sync\_update.cmd
  - upg08\_postaction.cmd
  - upg09\_common\_get.cmd
  - upg10\_common\_update.cmd
  - upg11\_cla.cmd
- Control log files
- Take over production data by executing upg13\_prod1\_takeover.cmd
- Run post-action scripts by executing upg14\_prod2\_rep\_update.cmd

## Import DataView Repository with DTV.BLD

Even though the DataView internal repository entries are handled by the upgrade tool, it is sometimes useful to import it from a DTV.BLD file. This is possible with the script `imp_dtv.cmd` / `imp_dtv.sh`.

Some parameters respective to the current application server configuration must be adapted in the script before proceeding with the import.

**Note:** Since the `dtv.bld` file has to be located on the application server machine and there is no `dtv.bld` file available in the standard installation, this script can be executed on this machine only.

## Convert XML Files to HTML

You can convert XML files to HTML and view them with a browser. The batch file `xml2html.bat` creates HTML files for insert, update, and delete. This function is available on Windows platforms only.

Execute `xml2html.cmd` with one of the following parameter values, which specify the HTML file to be created for modules:

- All – HTML files for all modules are created
- Module name - HTML files only for specified modules are created, possible values are:  
`dtv edb brw dode lgv wfl chg gdm rmt gtm`

**Note:** You need memory for approximately six times the XML file size! The batch job will run several hours. The Java Runtime Environment allocates 512MB of memory. You can adjust the memory allocation by editing the file `Upgrade\cmd\upg_env.cmd`

## Takeover Production Data

The next step is to transfer reference data from the production system. This phase is necessary, because during the upgrade and customizing of the new environment new reference data (all tables except customized tables) is available in the old production dump.

Takeover phase is separated in several tasks:

- Generate a relevant table list using a database connection to current production dump. This database connection is used as source for the tables copied into the new environment. No changes are made in the production database.
- Edit the list of tables, which should be copied during the takeover step.
- Takeover: drop tables in the new dump and copy them from the current production dump.
- Takeover the latest number server values.
- Make the dump up-to-date again by executing the step “Synchronize\_repository” and appropriate post-actions.
- Perform a test in the new environment. Test all functionalities, maybe during training of the user. If errors occur, remove them via customizing. Not everything might be done automatically. During the test period a lot of new data is created in the

production system. Therefore, the last two steps can be repeated till the new environment is error-free.

- If testing does not raise any errors you can switch the production database to the new one. Takeover your data from the production system (and the files!) again and the new environment is your production system. Shut down your old system.

## Pre-Action on Microsoft SQL Server

Grant access to the current production environment for the customer database user running these statements as Microsoft SQL Server Administrator (e.g. SA).

<login\_name> is the customer database login.

```
GRANT ALTER ANY LOGIN TO <login_name>
GO
GRANT ALTER ANY LINKED SERVER TO <login_name>
GO
```


## Define Reference Tables

Select the folder Takeover in the upgrade tool and press the button Create Ref File. The upgrade tool will connect to the production database, identify all tables and synchronize the information with the predefined list (ref\_tables.xml). Only tables with data will be written to the file.

## Edit Production Table List

To adapt the list, press Edit ref. File. For each table you have to define if it is a reference table. (ref\_data = y.) Such reference tables will be dropped to the customer dump and copied from the production system using the connection to the production DB.

Select OK to save the XML file (conf/ref\_tables.xml).





**Note:** On SQL server set recovery model to “simple” for customer database, which prevents an unlimited growth of database log files. Run following statement to set the recovery model:

```
ALTER DATABASE <database> SET RECOVERY SIMPLE WITH NO_WAIT
GO
ALTER DATABASE <database> set READ_COMMITTED_SNAPSHOT OFF
GO
```

**Note:** Because of a special BVB\_ARTMEH upgrade functionality BVB\_ARTIKEL, BVB\_ARTMEH, and BVB\_ARTMEHUFK tables have to be specified as production tables. Other BVB tables are treated as configuration tables. Otherwise an error can occur during execution of SQL scripts artmeh\_1.sql / artmeh\_2.sql.

**Note:** If you have createe new users and / or groups since the date when the dump was exported form production system the following DataView tables must be migrated. Attention: new users like EDB-WFL, EDB-DFM, EDB-DDM, EDB-GDM, EDB-EER, DODEKERNEL will get lost. Export these users first with the binary loader and reload them after the upgrade.

- T\_USER
- T\_GROUP
- T\_GRP\_USR
- T\_PROFILE
- Related tables of the PLM – person management

**Note:** Table T\_DEFAULT should be migrated by the loader (import/overload) otherwise, new defaults will be missing.

## Perform Transfer

Backup your customer Agile e6 dump and press the Takeover button. The tables containing non-repository information are dropped in your customers dump. The tables will be copied from the defined production environment into your customer dump.

**Note:** Check the log file log/errordetails.log

**Note:** After copying production database tables, a special upgrade step will be automatically executed – Takeover Workflow Masks. This step is described later in this document.

## Taking Over Number Server Values

Since number server is used during the step “Synchronize\_repository”, the newest values have to be transferred to the new environment. This is done by executing the step “AFTER TAKEOVER: takeover number server values”. Please control log files 14\_01\_get\_numvalue.log and 14\_02\_set\_numvalue.log.

## Post-Action Scripts

Tables just copied from the current production environment have an old table structure and must be upgraded. This is done with the following steps:

- ❑ Step “AFTER TAKEOVER: run before-sync-scripts”  
The command script upg07\_sync\_update.cmd will be executed.  
Check log files upg07%.log in the upgrade\log directory.
- ❑ Step “AFTER TAKEOVER: Synchronize\_repository”  
Execute “Synchronize” and control log/errors.log, control log files in data\sync.
- ❑ Step “AFTER TAKEOVER > Run after-sync scripts”  
The command script upg15\_prod3\_postaction.cmd will be executed.  
Check log files log/upg15%.log. The complete list of SQL scripts is described in the Appendix.

## Classification (Stage 2)

It is required that the attributes are already migrated and only the classification lists is updated. Click Perform mapping.

**Note:** If the customer has created new classes and attributes in the production system, after the customization upgrade classes, attributes, and domain values must also be copied and migrated.

## Manual Dump Changes

### LogiView

After the upgrade all LogiView changes made by customers in the standard must be made again. The previous changed standard procedures can be found within the S<timestamp> LogiView models.

### STEP

After the upgrade or productive takeover you have to check the defaults "EDB-STP-DEF-NO-REF" and "EDB-STP-DEF-ORG-REF". During the upgrade to Agile e6 the values of these defaults were changed from "EP" to "NN". If the values of these defaults in your productive environment are already set "NN", nothing needs to be done.

These defaults are used as field defaults in several fields (<TABLE>.STEP\_NO\_REF, <TABLE>.STEP\_ORG\_REF).

This upgrade tool provides a default scripts (ora\sql\upg\_org\_ref\_default.sql, ora\mssql\upg\_org\_ref\_default.sql), which changes all values of these fields in the standard tables from "EP" to "NN".

Please review the script according to your customizing. If you have not done any changes to your customizing regarding STEP\_ORG\_REF,STEP\_NO\_REF you can run the scripts without changes.

If you do not run the script it is possible to, e.g. duplicate PART\_ID's in T\_MASTER\_DAT, because these two fields are used in the unique key constraint of T\_MASTER\_DAT.

### Customer Specific Changes

Recreate customer specific views, packages, procedures and triggers, database constraints like field defaults, etc.

### Post-Actions on Microsoft SQL Server

Before switching the production system to the new database, some changes must be performed on the Microsoft SQL Server database.

Set recovery model and isolation level for customer database. These statements must be executed from an administrative account - like SA.

```
ALTER DATABASE <database> SET RECOVERY FULL WITH NO_WAIT  
GO  
ALTER DATABASE <database> set READ_COMMITTED_SNAPSHOT ON  
GO
```

And finally revoke access rights to old production database for the customer database user. These statements must be executed from an administrative account – e.g. as user SA.

<login\_name> is the customer database login.

```
REVOKE ALTER ANY LOGIN TO <login_name>  
GO  
REVOKE ALTER ANY LINKED SERVER TO <login_name>  
GO
```

# Chapter 4

## Additional Information

Following special handling modules are integrated into the upgrade tool. Therefore, no additional actions are required to migrate the involved content. The steps described below are already integrated in the upgrade process and will be executed automatically.

### Browser Upgrade

With Agile e6.0 release a new browser was introduced. It is based on new database tables having a prefix T\_EXP\_\*.

During the upgrade, standard content of these new tables is inserted. In addition, non-standard entries from the “old” browser are migrated.

### Cleanup BVB\_ARTIKEL

Some inconsistencies in the existing item data structure are eliminated during this specific upgrade step. Here a list of executed activities:

- Redundant BVB\_ARTIKEL entries are dropped.
- All BVB\_ARTIKEL records without corresponding T\_MASTER\_DAT entries are deleted.
- Missing BVB\_ARTIKEL records are inserted.
- Missing values of T\_MASTER\_DAT.UNIT are inserted into BVB\_MASSEH.

### STA\_LUT

For each entry in T\_CHK\_STA a valid reference to T\_STA\_LUT is established with values in T\_CHK\_STA.EDB\_STA\_REF. Additionally, EDB\_LEVEL is filled within the table T\_STA\_LUT.

**Note:** The values of the table T\_STA\_LUT must be reviewed after the customizing upgrade.

### Project References in Processes

There is a known problem existing within the projects workflow in Agile e6.0. In case of creation of a relation between process and project, which has several versions, several entries are shown in the list because the PROJ\_ID (kind of project name shortcut) is not unique over the stored versions. For this reason a new DB field is added: T\_PRC\_DAT.EDB\_PRO\_REF.

If necessary this field was filled with values during the upgrade step upg08\_postaction.

## BVB\_ARTMEH Upgrade

During this step, an upgrade of BVB\_ARTMEH\* tables is performed. SQL script artmeh\_1.sql and artmeh\_2.sql is executed within the upg08\_postaction step.

## Favorites Upgrade

The upgrade tool inserts several data into browser tables to make favorites and stored queries visible in the Agile e6 client browser window.

## Classification

Overview attribute concept (old):

- Attributes are defined class specific in the ATT concept.
- Domain values for an attribute are defined in static menus.
- No release procedures and status management for classes and attributes.

Overview new pool concept:


- Attributes can be defined class independent.
- Pool attributes can be assigned to more than one class.
- Domain values for a pool attribute can be stored in special domain tables.
- For every class it can be specified which domain value is valid.

The migration includes:

- Merge attribute definitions. Attributes are considered as identical if the following values are identical:
  - C\_LETTER
  - C\_TITLE
  - C\_TYPE

If you have defined C-LETTER and C\_TITLE as multi-lingual fields (standard since axalant 2000), then you have to define with the Parameter “DB language” which language is used as standard for the merge.

- Initial load of the attribute value pool including the activation of the attributes for special classes.
- Update classification lists.
- Update used field name.
- Set of attribute ATT\_VAL\_REF in the classification lists.
- Update field and mask definition (if you have defined own forms for classes).



**Note:** If possible, do not create or modify basic definitions of classes and attributes between customization upgrade and takeover data from production system. This influences the migration steps which must be executed after the takeover process.

- ❑ No new classes and attributes are created. Only classification list tables must be defined as reference table.
  - T\_GRP\_ART
  - T\_GRP\_DOC
  - T\_GRP\_ORD
  - T\_GRP\_PRO
- ❑ Customers have created new classes and attributes in the production system after the customization upgrade. In addition to the classification list table classes, attributes, and domain values must be copied and migrated.
  - T\_GROUP\_DAT
  - T\_GROUP\_STR
  - T\_GRP\_FLD

## Workflow Takeover

Since upgrade tool version 3.1.11 (upgrade to Agile e6.0.2) special generic workflow masks are copied during the takeover phase.

After taking over of the common tables, workflow masks are deleted, which are currently presented in the customer dump. Generic workflow masks are copied from the production database. Following tables are involved in this procedure:

- ❑ T\_MASK
- ❑ T\_MAS\_FLD
- ❑ T\_FIELD
- ❑ T\_MENU
- ❑ T\_MEN\_SEL

Workflow masks have a special naming convention: EDB-WFL-<CID\_OF\_ACTIVITY>

Entries within T\_FIELD follow naming rule EDB-DEC<CID\_OF\_ACTIVITY>

- ❑ T\_MEN\_SEL entries contain names like EDB-SEL-<CID> and EDB-NSEL-<CID>
- ❑ T\_MENU entries of C\_BUT\_EDT / C\_BUT\_SEL / C\_BUT\_NOS are considered only for this action.

During the takeover phase, all statements will be generated and executed within the upgrade tool and additionally written to full.log file.

# Chapter 5

## Appendix

### Appendix A: CMD Scripts

Here is a short description of all shell scripts included in the upgrade download package.

Shell script	Description	Called SQL scripts
chown_mssql.cmd	(Re-) create a Login/User for an Microsoft SQL Server database	-
convert_it.cmd	Convert XML data file for a single table to HTML files. This script is called from xml2html.cmd.	--
exp_dmp.cmd	This script helps you to export oracle database to a dump file.	--
imp_dmp.cmd	This script helps you to create database users and import oracle dump files.	--
imp_dtv.cmd	Imports the DataView repository. Please adapt parameters within before running this script	DEL_DTV.SQL > DEL_DTV.LOG
missing_f.cmd	Create missing file groups in MS SQL Server.	--
preaction_template.cmd	This file is for upgrade internal use only! It is used as a template for creating the file preaction.cmd, which is needed if all upgrade steps are executed in batch mode.	--
start_upg.cmd	Start upgrade user interface.	--
upg01_pre_cleanup.cmd	Cleanup all log files within current upgrade project.	--
upg03_preaction_sql.cmd	Run several SQL scripts depending on source, target and customer product versions. Called SQL scripts are saved in the file 03_preaction_sql.log	source: CRE_REP_EDB.SQL > 03_01_CRE_REP_EDB.LOG  source: TRUNC_LVTABS.SQL > 03_TRUNC_LVTABS.LOG  source: GRANT_SELECT_T_CONSTRAINT.SQL > 03_16_GRANT_SELECT_T_CONSTRAINT. LOG  target: GRANT_SELECT_T_CONSTRAINT.SQL >



Shell script	Description	Called SQL scripts
		03_15_GRANT_SELECT_T_CONSTRAINT.LOG CRE_REP_EDB.SQL > 03_15_CRE_REP_EDB.LOG CLEANUP_C_ID_NULL.SQL > 03_03_CLEANUP_C_ID_NULL.LOG ANA_LV.SQL > 03_04_ANA_LV.LOG <=CADIM: ORA3-4.SQL > 03_05_ORA3-4.LOG <=AXA SP 1: PST10P2TOP3.SQL > 03_06_PST10P2TOP3.LOG <=AXA SP 1: ORA403-404.SQL > 03_07_ORA403-404.LOG <=AXA SP 1: AXASP1_TO_SP2.SQL > 03_08_AXASP1_TO_SP2.LOG <=AXA SP 3: DTV405-406.SQL > 03_10_DTV405-406.LOG <=AXA SP 3: UPD_T_SELECTION.SQL > 03_11_UPD_T_SELECTION.LOG <=e6 LA: DTV406-407.SQL > 03_12_DTV406-407.LOG <=e6 GA: DTV407-430.SQL > 03_13_DTV407-430.LOG <= e6.0.1: DTV430-431.SQL > 03_14_DTV430-431.LOG CUSTOMER_DATABASE_TASKS.SQL > 03_17_CUSTOMER_DATABASE_TASKS.L OG
upg04_dtv_get.cmd	Get XML files for the step “DTV-Upgrade” in shell mode.	--
upg05_dtv_update.cmd	Proceed XML files for the step “DTV-Upgrade” in shell mode.	--
upg06_sync_get.cmd	Run the step “Analyze repository” in shell mode.	
upg07_sync_update.cmd	Run the step “Synchronize repository” in shell mode. Called SQL scripts are saved in the file 07_sync_update.log	<= PLM5.x: before_sync.sql > 07_01_before_sync.log
upg08_postaction.cmd	Run some SQL scripts, which are necessary after performing “Synchronize repository” upgrade step. Called SQL scripts are saved in the file 08_postaction.log	cre_rep_edb.sql > 08_01_cre_rep_edb.log cleanup.sql > 08_02_cleanup.log db_defaults.sql > 08_03_db_defaults.log artmeh_1.sql > 08_04_artmeh_1.sql update_defartmehr.sql > 08_05_update_defartmehr.log artmeh_2.sql > 08_06_artmeh_2.sql

Shell script	Description	Called SQL scripts
		special602.sql > 08_07_special602.log get_compile_all.sql > compile_all.sql compile_all.sql > 08_08_compile_all.log invalid_objects.sql > 08_09_invalid_objects.log
upg09_common_get.cmd	Generate XML files for several upgrade steps, one for each common PLM module. Called SQL scripts are saved in the file 09_common_get.log	del_and_save_lvmodel.sql > 09_01_del_and_save_lvmodel.log
upg10_common_update.cmd	Proceed common PLM modules XML files. Called SQL scripts are saved in the file 10_common_update.log	compare_lgv.sql > 10_01_compare_lgv.log <=PLM5.x: edb_explorer.sql > 10_02_edb_explorer.log
upg11_cla.cmd	Upgrade PLM Classification.	--
upg13_prod1_takeover.cmd	Start a user interface to proceed with "Takeover production data". Scripts upg14_prod2_rep_update and upg15_prod3_postaction have to be executed after that.	--
upg14_prod2_rep_update.cmd	Synchronize repository (this script includes all necessary pre-action and post-action calls).	SQL Files of upg07_sync_update.cmd and upg08_postaction.cmd are called again get_numvalue.sql > 14_01_get_numvalue.log set_numvalue.sql > 14_02_set_numvalue.log cre_rep_edb.sql > 14_03_cre_rep_edb.log
upg_env.cmd	Common upgrade settings, like Java, JRE, Path, etc.	--
xml2drop.cmd	Generates ora/ref_data_tab.par and ora/ref_data_tab_drop.sql files for manually import/export of production tables. You have to configure which tables are relevant for the takeover step before.	--
xml2html.cmd	Converts generated XML files to HTML format for a module. Example: "xml2html.cmd dtv" Or "xml2html.cmd all"	Possible module names ('all' for all modules):  dtv edb brw dode lgv wfl chg gdm rmt gtm

## Appendix B: Configuration Files in /conf/

- ❑ ApplicationParameter.xml - Global application configuration file
- ❑ brwDD.xml - Configuration file for upgrade module BRW (Explorer)
- ❑ chgDD.xml - Configuration file for upgrade module CHG (Change Management)
- ❑ wflDD.xml - Configuration file for upgrade module WFL (Workflow)
- ❑ dodeDD.xml - Configuration file for upgrade module DODE (Print Studio)
- ❑ dtvDD.xml - Configuration file for upgrade module DTV (DataView Repository)
- ❑ edbDD.xml - Configuration file for upgrade module EDB (Agile PLM configuration)
- ❑ gdmDD.xml - Configuration file for upgrade module GDM (Office integration)
- ❑ gtmDD.xml - Configuration file for upgrade module GTM (Classification)
- ❑ lgvDD.xml - Configuration file for upgrade module LGV (LogiView)
- ❑ rmtDD.xml - Configuration file for upgrade module RMT (Requirement Management)
- ❑ special.xml - Configuration file for the step “Synchronize Repository”
- ❑ specialreplace.xml - A sample configuration file for special replace cases
- ❑ ref\_tables.xml - Configuration file for the upgrade step “Takeover production data”
- ❑ wfl\_ctl.xml - Configuration file for Workflow mapping
- ❑ cla\_ctl.xml - Configuration file for Classification Upgrade (PLM5.x to Agile e6)
- ❑ cla\_post\_ctl.xml - Configuration file for Classification Upgrade (PLM5.x to Agile e6)
- ❑ insert.xsl, delete.xsl, update.xsl, upgrade.xsl - XSL-style sheet for converting XML control files to HTML, used by xml2html.cmd script
- ❑ ref\_data\_tab\_drop.xsl - XSL-style sheet for generating SQL script, which drops production data tables in the customer dump. This style sheet is used by xml2drop.cmd
- ❑ ref\_data\_tab\_par.xsl - XSL-style sheet for generating table list clause for oracle EXP command, which can be used alternatively to transfer production data tables from production database. This style sheet is used by xml2drop.cmd
- ❑ cla\_stl.xsl - XSL-style sheet for configuration file for classification upgrade (Axalant 2000 to PLM5.x), which generates a HTML output of performed mapping operations
- ❑ dtv\_dd.dtd - Document type definition file for module control files

## Appendix C: Contents of the Folder “upgrade/conf/template”

- ❑ ApplicationParameterORACLE.xml - Upgrade tool settings file with standard values for an ORACLE database. Copy this file to upgrade/conf to reset the application settings.
- ❑ ApplicationParameterMSSQL.xml - Upgrade tool settings file with standard values for a Microsoft SQL Server database. Copy this file to upgrade/conf to reset the application settings.
- ❑ cla\_ctl\_with\_multi\_lang.xml - Example for the classification control file (with multi-lingual definition of the attributes).

- ❑ cla\_ctl\_with\_multi\_lang\_repl.xml - Example for the classification control file (with multi-lingual definition of the attributes and additional fields for database replication).
- ❑ cla\_ctl\_with\_repl.xml - Example for the classification control file (with additional fields for database replication).
- ❑ ref\_tables.xml – This configuration file is used during the takeover phase for read only reasons. Based on settings in this file, a ref\_table.xml file is created in the CONF directory during the “Create ref. File” step.
- ❑ special\_move.xml - Examples for the special case with table field moving.
- ❑ special\_rename.xml - Examples for the special case with table field renaming.
- ❑ Special.xml - Default template.
- ❑ specialreplace.xml - Examples for special replace cases.

## Appendix D: SQL Scripts

Here is a short description of SQL scripts delivered with the Agile upgrade tool. All script executions create a log file in the log/ directory which are named like the script itself with a prefix like 08.

SQL Script	Description
mssql/sql/after_restore.sql	This script is used by chown_mssql.cmd to setup the user/schema and default options within a just restored mssql database.
ana_lv.sql	Analyze LogiView content in the customer dump. Please control the log file of this script as described in the manual.
artmeh_1.sql	Conversion of BVB_ARTMEH* tables, for PLM version <= Eigner PLM 5.x (Part 1).
artmeh_2.sql	Conversion of BVB_ARTMEH* tables, for PLM version <= Eigner PLM 5.x (Part 2).
axasp1_to_sp2.sql	Upgrade axalant sp1 to axalant sp2.
before_sync.sql	This script has to be executed before running the step “Synchronize Repository”. It is done by default with the standard upgrade configuration. It prepares the table T_STA_LUT and drops triggers, because otherwise it is impossible to insert rows in the involved tables.
cleanup.sql	This script cleans up some dump content and is executed automatically after the step “Synchronize Repository”.
cleanup_c_id_null.sql	This script cleans up some inconsistencies in the customer dump (like rows with negative C_ID values). It must be executed before DTV-upgrade.
Compare_lgv.sql	This script compares LogiView procedures in reference dump / customer dump. It is executed after the LogiView upgrade.
customer_database_tasks.sql	This script executes some cleanup statements to get rid of common dump inconsistencies.

SQL Script	Description
cre_plm_tbs.sql	Creates missing Oracle tablespaces.
cre_plm_usr.sql	Create a database user. This script needs 2 parameters: username and password.
cre_rep_edb.sql	Create all schema objects (tables, views, indexes, packages, triggers, sequences, etc.) and insert number server rows, most of them already exist, so a lot of errors will be logged after executing this script.
db_defaults.sql	This script overwrites default constraints on the database level, since they are different to DataView default definitions. It is executed automatically after the step "Synchronize_repository".
del_and_save_lvmodel.sql	Delete standard LogiView content and save customized models with a prefix "SAVE-".
del_dtv.sql	Truncate all DataView internal entries in DTV-tables.
mssql/sql/ dropall.sql	This script can be used to drop all objects within an existing mssql database.
dtv405-406.sql	Pre-action script has to be executed before DTV-upgrade for customer dump version <= axalant SP3.
dtv406-407.sql	Pre-action script has to be executed before DTV-upgrade for customer dump version <= Agile e6.0 LA.
dtv407-430.sql	Pre-action script has to be executed before DTV-upgrade for customer dump version <= Agile e6.0 GA.
Dtv430-431.sql	Pre-action script has to be executed before DTV-upgrade for customer dump version <= Agile e6.0.1.
edb_explorer.sql	Converts DTV explorer to Agile e6 EDB-explorer. This step is executed once after common modules upgrade.
getoradrop.sql	Get script "dropall.sql" which cleans up a complete database schema.
get_compile_all.sql	Generates a script to recompile all db objects.
get_numvalue.sql	This script is executed in the production database and generates a file named "set_numvalue.sql" after takeover step. This file updates number server values in the customer database.
get_rebuildidx.sql	This script generates a file named "rebuildidx.sql" to rebuild all indexes in a right tablespace of a schema. It has 5 parameters for tablespaces: EDB EDB_IDX EDB_LOB EDB_TMP EDB_TMPIDX
grant_select_t_constraint.sql	This script grants a selection on table T_CONSTRAINT for the customer database. This permission is needed for constraint conversions.
Invalid_objects.sql	Lists all objects still invalid in the dump.
levind_in_stalut.sql	This script is called automatically after "Synchronize Repository" and

SQL Script	Description
	converts records in the table T_STA_LUT. It is needed only for upgrades form <= Eigner PLM to >= Agile e6.
ora3-4.sql	This pre-action-script is called automatically if the customer dump is a CADIM dump.
ora403-404.sql	Pre-action script has to be executed before DTV-upgrade for customer dump version <= axalant SP1.
Pst10P2ToP3.sql	Pre-action script has to be executed before DTV-upgrade for customer dump version <= axalant SP1.
mssql/sql/show_default_constraints.sql	This script can be used to examine default values within a mssql database.
special602.sql	Special data modifications for upgrade to 6.0.2
trunc_lvtab.sql	Truncate all LogiView tables. This script is executed on reference dumps only!
update_customers_UIC.sql	This script has to be executed on the customer dump before proceeding with upgrade.
upd_t_selection.sql	This script is a workaround for incompatible changes for table T_SELECTION in Eigner PLM5.0 This script is already executed on all reference dumps delivered with Agile upgrade tool. It will automatically executed IDs that are necessary in the step “preaction-scripts”.
update_defartmehr.sql	Fills DEFARTMEHR.BVB_ARTIKEL field during the CLEANUP_BVB phase of the step “Postaction”.
mssql/sql/user_indexes.sql	Creates a USER_INDEXES view (ORACLE-like) in a mssql database. This script is executed during the pre-action phase of an upgrade
upg_org_ref_default.sql	A sample update script for existing STEP_NO_REF and STEP_ORG_REF values.

## Appendix E: Directories

Directory	Description
cmd	Windows 2000 shell scripts of the upgrade tool.
conf	Configuration xml files.
conf/template	Some templates of xml configuration files. The upgrade tool does not use these files. The only exception is the file ref_tables.xml. It will be read by the tool to recreate /conf/ref_tables.xml.
data	This directory contains several subdirectories, each for a module – like BRW, EDB, etc. For each module delete, insert, and update xml files are created. After performing of these operations on the customer database, error xml file is written. Additionally, html files generated for a module are saved here. A file customizing.log in this directory contains conflicts caused by customizing of the original dump

data\dtv	DataView upgrade files as described above are stored here. Please read carefully the file customizing.log because it contains user-exit conflicts.
data\sync	Log files of the synchronize repository upgrade step are stored in this directory.
data\cla	Log files of the classification upgrade step are stored in this directory.
doc	Upgrade tool documentation.
dumps	Database dumps can be stored here. Dumps, which are imported / exported by shell scripts imp_dmp.cmd and exp_dmp.cmd, have to be stored in this directory.
lib	Upgrade tool java executables.
log	Log files of all sql scripts and common application log files.
mssql\sql	MS SQL server SQL-scripts.
ora\sql	Oracle SQL-scripts.
scripts	Unix / Linux shell scripts of the upgrade tool.

## Appendix F: Migration Rules

Standard rules are available for insert, update, and delete and these rules are verified during the comparison of the table contents. They can be overwritten by special definitions.

### Standard Rules for Delete

Data records deleted in the standard are also deleted in the customer dump.

Customer-specific dump	Source master	Target master	Action
+	+	-	Delete

### Standard Rules for Update

Data records existing in source master dump that were deleted in the customer dump are not re-created. Existing data records are updated. The standard changes overwrite the customer changes. Special rules apply on field level to protect customer-specific changes.

Customer-specific dump	Source master	Target master	Action
+	+	+	Update

### Standard Rules for Insert

Data records not existing in source master dump or in the customer dump are added.

Customer-specific dump	Source master	Target master	Action
-	-	+	Insert

## **Special Rules**

Customer changes that will not be overwritten by standard changes are:

- Field defaults and check strings.
- Customizing hints for fields containing userexits .
- Special handling for mask components.
- Replacements of strings (-> specialreplace.xml).