

```

<?xml version="1.0" encoding="ISO-8859-1"?>

<xsl:stylesheet version="1.0"
xmlns:xsl="http://www.w3.org/1999/XSL/Transform">
  <xsl:output method="xml"
    indent="yes"
    doctype-public="-//Sun Microsystems Inc.//DTD Application Server
9.1 Domain//EN"
    doctype-system="http://www.sun.com/software/appserver/dtds/sun-
domain_1_3.dtd">
  </xsl:output>

  <xsl:template match="/">
    <xsl:apply-templates select="node()|@*" />
  </xsl:template>
  <xsl:template match="node()|@">
    <xsl:copy>
      <xsl:apply-templates select="node()|@" />
    </xsl:copy>
  </xsl:template>

  <xsl:template match="http-service">
    <xsl:copy>
      <xsl:apply-templates select="node()|@" />
      <xsl:element name="property">
        <xsl:attribute name="name">accessLoggingEnabled</xsl:attribute>
        <xsl:attribute name="value">>false</xsl:attribute>
      </xsl:element>
    </xsl:copy>
  </xsl:template>

  <xsl:template match="http-listener">
    <xsl:copy>
      <xsl:copy-of select="@*" />
    </xsl:copy>
  </xsl:template>

  <xsl:template match="http-listener[@security-enabled='false']">
    <xsl:copy>
      <xsl:copy-of select="@*" />
      <xsl:element name="property">
        <xsl:attribute name="name">proxiedProtocols</xsl:attribute>
        <xsl:attribute name="value">ws/tcp</xsl:attribute>
      </xsl:element>
    </xsl:copy>
  </xsl:template>

  <xsl:template match="http-listener[@security-enabled='true']">
    <xsl:copy>
      <xsl:copy-of select="@*" />
    </xsl:copy>
  </xsl:template>

```

```

    <xsl:element name="ssl">
      <xsl:attribute name="cert-nickname">s1as</xsl:attribute>
    </xsl:element>
  </xsl:copy>
</xsl:template>

<xsl:template match="http-listener[@id='admin-listener']">
  <xsl:copy>
    <xsl:copy-of select="@*" />
  </xsl:copy>
</xsl:template>

<xsl:template match="http-file-cache">
  <xsl:copy>
    <xsl:copy-of select="@*" />
    <xsl:attribute name="globally-enabled">>false</xsl:attribute>
    <xsl:attribute name="file-caching-enabled">>false</xsl:attribute>
  </xsl:copy>
</xsl:template>

<xsl:template match="virtual-server">
  <xsl:copy>
    <xsl:apply-templates select="node()|@" />
    <xsl:element name="property">
      <xsl:attribute name="name">sso-enabled</xsl:attribute>
      <xsl:attribute name="value">>false</xsl:attribute>
    </xsl:element>
  </xsl:copy>
</xsl:template>

<xsl:template match="jmx-connector">
  <xsl:copy>
    <xsl:copy-of select="@*" />
    <xsl:element name="ssl">
      <xsl:attribute name="cert-nickname">s1as</xsl:attribute>
    </xsl:element>
  </xsl:copy>
</xsl:template>

<xsl:template match="java-config">
  <xsl:copy>
    <xsl:apply-templates select="node()|@" />
    <xsl:comment>
      Use the following jvm-options element to disable the quick startup:
      com.sun.enterprise.server.ss.ASQuickStartup=false
    </xsl:comment>
  </xsl:copy>
</xsl:template>

```

</xsl:stylesheet>