

Name	stop-domain– Stops the Domain Administration Server of the specified domain
Synopsis	<pre>stop-domain [--terse={false true}] [--echo ={false true}] [--user <i>admin_user</i>] [--passwordfile <i>filename</i>] [--domaindir <i>domain-dir</i>] [--help] <i>domain_name</i></pre>
Description	Use the stop-domain command to stop the Domain Administration Server of the specified domain. The stop-domain command can be run in the local mode only.
Options	<p>-t --terse Indicates that any output data must be very concise, typically avoiding human-friendly sentences and favoring well-formatted data for consumption by a script. Default is false.</p> <p>-e --echo Setting to true will echo the command line statement on to the standard output. Default is false.</p> <p>-u --user The user name of the authorized administrative user of the domain administration server.</p> <p>If you have authenticated to a domain by using the <code>asadmin login</code> command, you need not specify the <code>--user</code> option for subsequent operations on the domain.</p> <p>--passwordfile Specifies the name, including the full path, of a file that contains the password entries in a specific format.</p> <p>The entry for a password must have the <code>AS_ADMIN_</code> prefix followed by the password name in uppercase letters. For example, to specify the password for the domain administration server, use an entry with the following format:</p> <pre>AS_ADMIN_PASSWORD=<i>password</i></pre> <p>In this example, <i>password</i> is the actual administrator password.</p> <p>The following other passwords can also be specified:</p> <ul style="list-style-type: none"> ▪ <code>AS_ADMIN_MAPPEDPASSWORD</code> ▪ <code>AS_ADMIN_USERPASSWORD</code> ▪ <code>AS_ADMIN_ALIASPASSWORD</code> <p>All remote commands must specify the administration password to authenticate to the domain administration server. The password can be specified by one of the following means:</p> <ul style="list-style-type: none"> ▪ Through the <code>--passwordfile</code> option ▪ Through the <code>asadmin login</code> command ▪ Interactively at the command prompt <p>The <code>asadmin login</code> command can be used only to specify the administration password. For other passwords that remote commands require, use the <code>--passwordfile</code> option or specify them at the command prompt.</p>

After authenticating to a domain by using the `asadmin login` command, you need not specify the administration password through the `--passwordfile` option for subsequent operations on the domain. However, only the `AS_ADMIN_PASSWORD` option is not required. You still must provide the other passwords, for example, `AS_ADMIN_USERPASSWORD`, when required by individual commands, such as `update-file-user`.

For security reasons, a password that is specified as an environment variable is not read by the `asadmin` command.

The default value for `AS_ADMIN_MASTERPASSWORD` is `changeit`.

`--domaindir`

The directory where the domain is to be stopped. If specified, the path must be accessible in the filesystem. If not specified, the domain in the default `as-install/domains` directory is stopped.

`--help`

Displays the help text for the command.

Operands *domain_name* This is the name of the domain to stop.

Examples EXAMPLE 1 Using the `stop-domain` Command

```
asadmin> stop-domain sampleDomain
Domain sampleDomain stopped
```

Exit Status 0 command executed successfully
1 error in executing the command

See Also `delete-domain(1)`, `list-domains(1)`, `restart-domain(1)`, `start-domain(1)`

