

# Retek<sup>®</sup> Distribution Management<sup>™</sup> 10.1.6

## Installation Guide



The software described in this documentation is furnished under a license agreement and may be used only in accordance with the terms of the agreement.

No part of this documentation may be reproduced or transmitted in any form or by any means without the express written permission of Retek Inc., Retek on the Mall, 950 Nicollet Mall, Minneapolis, MN 55403.

Information in this documentation is subject to change without notice.

Retek provides product documentation in a read-only-format to ensure content integrity. Retek Customer Support cannot support documentation that has been changed without Retek authorization.

**Corporate Headquarters:**

Retek Inc.  
Retek on the Mall  
950 Nicollet Mall  
Minneapolis, MN 55403  
888.61.RETEK (toll free US)  
+1 612 587 5000

Retek® Distribution Management™ is a trademark of Retek Inc.

Retek and the Retek logo are registered trademarks of Retek Inc.

©2004 Retek Inc. All rights reserved.

All other product names mentioned are trademarks or registered trademarks of their respective owners and should be treated as such.

Printed in the United States of America.

**European Headquarters:**

Retek  
110 Wigmore Street  
London  
W1U 3RW  
United Kingdom  
Switchboard:  
+44 (0)20 7563 4600  
Sales Enquiries:  
+44 (0)20 7563 46 46  
Fax: +44 (0)20 7563 46 10

## ***Customer Support***

### **Customer Support hours**

Customer Support is available 7x24x365 via e-mail, phone, and Web access.

Depending on the Support option chosen by a particular client (Standard, Plus, or Premium), the times that certain services are delivered may be restricted.

Severity 1 (Critical) issues are addressed on a 7x24 basis and receive continuous attention until resolved, for all clients on active maintenance. Retek customers on active maintenance agreements may contact a global Customer Support representative in accordance with contract terms in one of the following ways.

<b>Contact Method</b>	<b>Contact Information</b>
<b>E-mail</b>	support@retек.com
<b>Internet (ROCS)</b>	<a href="http://rocs.retek.com">rocs.retek.com</a> Retek's secure client Web site to update and view issues
<b>Phone</b>	1 612 587 5800

Toll free alternatives are also available in various regions of the world:

Australia	1 800 555 923 (AU-Telstra) or 1 800 000 562 (AU-Optus)
France	0800 90 91 66
United Kingdom	0800 917 2863
United States	1 800 61 RETEK or 800 617 3835
<b>Mail</b>	Retek Customer Support Retek on the Mall 950 Nicollet Mall Minneapolis, MN 55403

### **When contacting Customer Support, please provide:**

- Product version and program/module name.
- Functional and technical description of the problem (include business impact).
- Detailed step by step instructions to recreate.
- Exact error message received.
- Screen shots of each step you take.



# Contents

## **Chapter 1 – Database server installation instructions ..... 1**

Mount CD-ROM on the database server ..... 1

Update packages, stored procedures, and functions ..... 1

## **Chapter 2 – Application Server installation instructions .... 3**

UNIX Application Server installation instructions ..... 3



# Chapter 1 – Database server installation instructions

Before you apply the RDM 10.1.6 patch:

- Make a backup of all your objects and database schema.
- Check that RDM 10.1.5 is installed.

Before copying over any files:

- Note whether customizations have been made to the module. If so, then the customizations must be reapplied over the new version of the module (or the fix may need to be applied to the custom version of the code).
- Copy the original files to a different directory before copying over them in case they need to be referred to at a later date.

**Note:** These instructions refer to `rdmdev10` as the Oracle owning schema.

## Mount CD-ROM on the database server

- 1 Mount the CD-ROM on your database server.
- 2 Copy the `rdm1016dbpatch.tar.z` file from the `CD/dbserverunix` directory to a newly created staging directory on your UNIX server.
- 3 Log in to UNIX.
- 4 Change directories to the staging directory.

**Note:** The tar file must have a `.Z` extension.

- 5 If the tar file has a “z” in lowercase, change it by typing:  
`mv rdm1016dbpatch.tar.z rdm1016dbpatch.tar.Z`
- 6 Uncompress the tar file by entering:  
`uncompress rdm1016dbpatch.tar.Z`
- 7 Untar the tar file by entering:  
`tar xvf rdm1016dbpatch.tar`

## Update packages, stored procedures, and functions

- 1 On the server, change directories to `<staging area>/db_objects`.
- 2 Log in to SQLPLUS as `rdmdev10`.
- 3 Enter the following command to update packages, procedures, and functions:  
`SQL> @startall.sql`
- 4 Exit SQLPlus.
- 5 View the spool file `startall.log` when finished to verify that no errors were found.
- 6 After you have compiled all these objects, validate any objects that may have become invalid. You can do this by using the Oracle utility `dbms_utility.compile_schema`.





## Chapter 2 – Application Server installation instructions

**Note:** If you have modified any forms, menus, or reports make a backup copy so that you can reapply any custom modifications.

### UNIX Application Server installation instructions

- 1 Mount the CD-ROM on your UNIX Application Server.
- 2 Change directories to /appserverunix.
- 3 Copy the rdm1016apppatch.tar.Z file from the CD /appserverunix directory to a newly created staging directory on your UNIX Application server.
- 4 Log in to UNIX.
- 5 Change directories to the staging directory.

**Note:** The tar file must have a .Z extension.

- 6 If the tar file has a Z in lowercase, change it by typing:  

```
mv rdm1016apppatch.tar.z rdm1016apppatch.tar.Z
```
- 7 Uncompress the tar file by entering:  

```
uncompress rdm1016apppatch.tar.Z
```
- 8 Untar the tar file by entering:  

```
tar xvf rdm1016apppatch.tar
```
- 9 Make sure your UNIX environment is set up properly to compile Oracle Forms (see the RDM 10.1 installation guide for more information).

#### Compile forms (\*.fmb)

- 1 Change directories to <staging area>/forms/src.
- 2 Copy all the \*.fmb's to <INSTALL\_DIR>/rdm/forms/src.
- 3 Change directories to <INSTALL\_DIR>/rdm/forms/src.
- 4 Use the fmb2fmx script located in that directory to compile and generate the executable forms (fmx).  

```
> chmod 755 fmb2fmx (if necessary)
```

```
> ./fmb2fmx
```
- 5 Check to make sure each .fmb file has a corresponding .fmx file. If a form fails to compile (there is no .fmx file), you may have to manually compile the form by launching the form builder tool.(f60desm&)
- 6 All resulting .fmx files need to be moved to the <INSTALL\_DIR>/rdm/forms/bin directory. From the <INSTALL\_DIR>/rdm/forms/src directory, issue the following command:  

```
> mv *.fmx ../bin
```