

Oracle Insurance

**Insbridge Rating and
Underwriting
SoftRater for JBoss
Reference Guide**

Release 3.13

December 2009

Copyright © 2005, 2009, Oracle and/or its affiliates. All rights reserved.

Oracle Insurance Insbridge Rating and Underwriting SoftRater for JBoss Reference Guide

Release 3.13

Part # E16316-01

Library # E16330-01

December 2009

Primary Authors: Mary Elizabeth Wiger

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS

Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure the safe use of this software. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software in dangerous applications.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

This software and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Where an Oracle offering includes third party content or software, we may be required to include related notices. For information on third party notices and the software and related documentation in connection with which they need to be included, please contact the attorney from the Development and Strategic Initiatives Legal Group that supports the development team for the Oracle offering. Contact information can be found on the Attorney Contact Chart.

The information contained in this document is for informational sharing purposes only and should be considered in your capacity as a customer advisory board member or pursuant to your beta trial agreement only. It is not a commitment to deliver any material, code, or functionality, and should not be relied upon in making purchasing decisions. The development, release, and timing of any features or functionality described in this document remains at the sole discretion of Oracle.

This document in any form, software or printed matter, contains proprietary information that is the exclusive property of Oracle. Your access to and use of this confidential material is subject to the terms and conditions of your Oracle Software License and Service Agreement, which has been executed and with which you agree to comply. This document and information contained herein may not be disclosed, copied, reproduced, or distributed to anyone outside Oracle without prior written consent of Oracle. This document is not part of your license agreement nor can it be incorporated into any contractual agreement with Oracle or its subsidiaries or affiliates.

CONTENTS

	UPGRADE NOTICE FOR RELEASE 03.13.00	III
	PREFACE	IV
	Audience	iv
	Related Documents	iv
	Conventions	iv
	System Requirements.....	v
	Manual History	v
CHAPTER 1		
	CONCEPT DIAGRAM.....	6
CHAPTER 2		
	SOFTWARE INTEGRATION	7
CHAPTER 3		
	RATING ARGUMENTS	9
CHAPTER 4		
	INSBRIDGE.XML	10
	Insbridge.XML Request Format	10
	Insbridge.XML Result Format	13
	Examples	18
SUPPORT		
	CONTACTING SUPPORT	21
	TTY Access to Oracle Support Services	21
INDEX		
	INDEX	22

UPGRADE NOTICE FOR RELEASE 03.13.00

This notice is for customers currently running a SoftRater for Java engine Release 3.12 or lower. This includes:

- **SoftRater for WebLogic**
- **SoftRater for WebSphere**
- **SoftRater for JBoss**

Necessary updates have been made to the SoftRater for Java engines. This includes:

- **SoftRater for WebSphere has been updated to SOAP version 1.1.**
- **SoftRater for WebLogic has been updated to SOAP version 1.2.**
- **SoftRater for JBoss has been updated to SOAP version 1.2.**

These changes mean that the WSDLs for the SoftRater for Java engines have been modified. Updated WSDL documents will need to be incorporated into any client calling application that communicates with SoftRater. If upgrades are done to the SoftRater for Java engines without updating the calling applications, the calling application will fail.

Please update a test environment prior to deploying to production. Install the .EAR file in a test environment to obtain the WSDL. Update your calling application and then test. When testing is complete, you can upgrade your other environments.

NOTE: *Customers running a Windows only environment, without a Java component, will not be affected.*

These updates are for the 3.13 release of SoftRater for Java engines only.

PREFACE

Welcome to the *Oracle Insurance Insbridge Rating and Underwriting SoftRater for JBoss Reference Guide*. This guide describes the concepts and requirements of SoftRater for Red Hat JBoss. It provides a reference for developers to properly interact with the Insbridge SoftRater Engine either through SOAP, POST Web Services Interface (WSI) or Direct EJB Interfacing.

AUDIENCE

This guide is intended for SoftRater system administrators who are tasked with administering SoftRater. Readers of this guide should be familiar with XML, HTTP.

RELATED DOCUMENTS

For more information, refer to the following Oracle resources:

The Oracle Insurance Insbridge Rating and Underwriting RateManager User Guide.

The Oracle Insurance Insbridge Rating and Underwriting SoftRater User Guide.

You can view these guides in-line at this address:

<http://www.oracle.com/technology/documentation/insurance.html>

CONVENTIONS

The following text conventions are used in this document:

Convention	Description
bold	Boldface type indicates graphical user interface elements associated with an action.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
<code>monospace</code>	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

SYSTEM REQUIREMENTS

For minimum operating system and hardware requirements, please see the Hardware Software requirements guide.

Manual History

New editions incorporate any updates issued since the previous edition.

Edition	Publication Number	Product Version	Publication Date	Comment
1 st Edition	P01-770-01	V 3.11	December 2008	Initial Version
2 nd Edition	P01-770-02	V 3.12	July 2009	Update Version
3 rd Edition	P01-770-03	V 3.13	December 2009	Update Version

CONCEPT DIAGRAM

The diagram below shows the high level interaction between the client application and the SoftRater system. The SoftRater instance is responsible for all rating & underwriting processing. The basic functionality of SoftRater system is demonstrated below. Input data is sent to the SoftRater instance, processed and output data is returned.




Figure 1 Concept Diagram

SoftRater for WebLogic supports the following:

- Red Hat JBoss Application Server Versions 4.2.3

Version: 4.2.3.GA (build: SVNTag=JBoss_4_2_3_GA date=200807181418)

Version Name: Trinity

Built on: July 18 200

SOFTWARE INTEGRATION

SoftRater is an EJB component hosted in the JBoss Application Server and accessible through the following software integration methods.

Port 8080 may change depending on your server configuration.

1. HTTP SOAP Proxy – SoftRater Web Service – WSDL documents are included in the installation of the EJB component. From them, proxy classes can be generated to communicate with the installed SoftRater instance. The SoftRater Web Service WSDL should be located at the following URL:
<http://<yourserver>:8080/IBSS/wsdl/com/insbridge/sofrater/SoftRaterService.wsdl>

Also included is a sample SoftRater SOAP proxy class instance along with the java file. They are located in the installation directory under integration.

Whether the sample SoftRaterProxy class is used or a new one is generated from the WSDL interface the integrating application must call the ([setEndPoint](#)) method to set the target hosting URL for the SoftRater instance. The target URLs should be the following:
<http://localhost:8080/IBSS/SoftRaterWS> and <http://localhost:8080/IBSS/SoftDataWS>

If you are submitting Insbridge XML, it is recommended that you use HTTP POST instead of SOAP. The SOAP should only be used when rating custom XML. If you must use SOAP, remove <MappedRateRequest> section from the SOAP header.

Currently, when rating custom XML, the engine only supports stateful rating. The SoftRater WSI will add the contents of the rating results to the document that was submitted for rating. This is an important consideration when constructing XSLT (mapping) files.

2. HTTP POST – A lite weight Web Service Interface JSP page is provided as an interface for clients with just web form POST abilities. CustomXml cannot be submitted from this interface.

The URL to the POST interface should be the following
<http://<yourserver>:8080/IBSS/sofrater/lwsi/RateBase.jsp>

The Boolean rating arguments can be provided (optionally) as URL query string arguments for example:
<http://<yourserver>:8080/IBSS/sofrater/lwsi/RateBase.jsp?addinputs=true&addroot=true;>

The lists of available URL arguments are the standard rating arguments provided through all SoftRater interfaces.

- addinputs=true
- addroot=true
- addheading=true
- addresultdesc=true
- addresultempty=true
- doinXSL=true

3. EJB – Direct JNDI interfacing.

The EJB interfaces for creating service clients, which create SoftRater instances.

Typical JNDI Path – [ejb/com/insbridge/sofrater/SoftRaterHome](#)

Target JAR – [SoftRaterEJB.jar](#) is part of the [Insbridge Application Framework.EAR](#) file containing the following standard EJB 2.0 interface files.

Typical JNDI Path – [ejb/com/insbridge/sofrater/SoftRaterHome](#)

Interface Example:

```
package com.insbridge.sofrater;
import java.rmi.RemoteException;

/**
 * Remote interface for Enterprise Bean: SoftRater
 */
public interface SoftRater extends javax.ejb.EJBObject
{
    public String ProcessIB(                final String XMLInputs,
                                           final boolean AddRootNode,
                                           final boolean AddInputsNode,
                                           final boolean AddHeadingNode,
                                           final boolean AddResultDesc,
                                           final boolean AddResultThatAreEmpty,
                                           final boolean DoInStyle,
                                           final boolean DoDebugOutput
                                           )

    throws RemoteException;

    public boolean ResetPackageCache( ) throws RemoteException;

    public void ResetConfigInfo( ) throws RemoteException;

    public String QueryAvailableEnvironments( ) throws RemoteException;

    public String getVersion( ) throws RemoteException;

    public String getErrorMessage( ) throws RemoteException;

    public String getDefaultPath() throws RemoteException;
}
```

RATING ARGUMENTS

The SoftRater engine rating arguments control the handling of XML data out of the system. Rating arguments are optional. For optimal performance, use the following arguments for your rating integration.

- **Add Root Node** (Use default – False) – If submitting multiple rate request documents, this option is typically set to true to make the result document a valid XML document.
- **Add Inputs** (Use default – False) – When set to true, the full request Insbridge.XML document is returned in the result Insbridge.XML document making the XML document much larger than normal.
- **Add Heading** (Use default – False) – When set to true, the program name description information is returned in the result XML also.
- **Add Result Descriptions** (Use default – False) – When set to true each result item includes the RateManager variable result name along with the result id and value. Making the result XML much larger. Typically, most integration operates on the result IDs and descriptions are not needed when building an automated system.
- **Add Empty Results** (Use default – False) – When set to true, a defined result item, whose value is empty (i.e. blank), is still created and returned blank in the resulting Insbridge.XML. If your program design requires a number of optional results, you could have blank results items in your XML.
- **Debug Output** (Use default – False) – When set to false, no debug report will be issued. Set to true if you would like a debug report.
- **EnvRef** (Use default – blank) – When left blank, the default environment defined in setup will be used. To specifically define an environment, enter in the environment name.

If no arguments are sent, the default values will be used. Default values are defined in setup. If using SoftRater Server, see Submit Insbridge XML.

INSBRIDGE.XML

XML is the primary data exchange mechanism used by Insbridge to import/export data and to communicate information electronically with external and internal software systems. XML provides a clean, readable, self-validating way to exchange data and is quickly becoming (or possibly already is) the data exchange standard.

Insbridge's rating request input XML is designed to be flexible and efficient. It allows for single or multiple rate requests to be submitted via one input XML document. The rate requests embedded in this single document can be targeted to multiple states and/or multiple lines of business. Multiple versions of a rating package also can be targeted in a single rate request document.

The rating request response XML is also streamlined to present all the results to the various request methods, described above, in a single output XML document.

INSBRIDGE.XML REQUEST FORMAT

The following is an example of an Insbridge rate request XML document:

```
<rate lob="2" tracking_attribute="" env_def="">
  <heading>
    <program parent_id="700" tiering_id="" program_id="24" program_ver="1"/>
  </heading>
  <c i="0" desc="Policy">
    <m i="1086" n="PackageDiscInd" v=""/>
    <m i="1094" n="RenewalRetentionCreditInd" v=""/>
    <m i="1157" n="CompanyCode" v=""/>
    <m i="1212" n="Eff_Date" v=""/>
    <m i="1214" n="PrimInsuredAge" v=""/>
    <m i="1215" n="SecInsuredAge" v=""/>
    <m i="1222" n="RenewalInd" v=""/>
    <c i="5" desc="Home">
      <m i="1083" n="TerritoryCode" v=""/>
      <m i="1084" n="ResidenceType" v=""/>
      <m i="1087" n="ProtectionClass" v=""/>
      <m i="1095" n="Wood/Tile/SlateRoofType" v=""/>
      <m i="1096" n="HomeDeductible" v=""/>
      <m i="1098" n="WindstormOrHailDeductible" v=""/>
      <m i="1100" n="CentralStationFireAlarmInd" v=""/>
      <m i="1101" n="CentralStationBurglarAlarmInd" v=""/>
    </c>
    <c i="8" desc="Coverage">
      <m i="1204" n="CovCd" v=""/>
      <m i="1205" n="CovLimit" v=""/>
      <m i="1207" n="CovEff_Date" v=""/>
    </c>
    <c i="9" desc="Endorsement">
      <m i="1181" n="EndorCd" v=""/>
      <m i="1182" n="EndorRateInd" v=""/>
      <m i="1190" n="EndorEff_Date" v=""/>
    </c>
  </c>
</rate>
```

```

        <m i="1191" n="Parm5" v=""/>
      </c>
    </c>
  </c>
</rate>

```

<rate> Node

The <rate> node marks the beginning of a rate request for a specific line of business. Accordingly, this node has the required attribute, “lob”, which identifies the “line of business” for the request. In the following example, the lob attribute is set to “2” which represents “Home” insurance according to the Insbridge standard line of business mappings (see User Guide). The rate node attributes are defined as follows:

lob	- line of business indicator per Insbridge standard lob codes (Required)
env_def	- rating environment indicator per Insbridge Framework Administrator (Optional)
renc	- SoftRater can encode XML characters, in the result XML, that are not considered valid XML characters. These characters are the ampersand (&), the less than sign (<), the greater than sign (>), double quotation marks (") and the single quotation mark ('). For example, the ampersand will be encoded as &. To have SoftRater encode the results, set the renc attribute value to one. (renc="1"). The default setting is zero. (No encoding)

As an optional feature, all other attributes provided on the <rate> node are collected as tracking attributes to be returned in the result XML document as attributes in the <result> node. This allows the original rate request to be uniquely tracked with its result XML document by any identification elements available to the calling subsystem. In the example below, the “policyId='A1206' ” attribute value pair would be mirrored on the <result> node of the resulting output XML.

Example:

```
<rate lob="2" policyId="A1206">
```

This rate request may be targeted to one or more rating logic instances based on what is found in the <heading> node (described) next.

<heading> Node

The <heading> node serves only as a container for <program> nodes and has no attributes. If multiple <program> nodes are found in the heading node, then rating is performed for each node, if possible, and appropriate results are generated in the output XML.

Example:

```

<heading>
  <program parent_id="700" tiering_id="" program_id="24"
    program_ver="1"/>
  <program parent_id="700" tiering_id="" program_id="22"
    program_ver="1"/>
</heading>

```

<program> Node

The <program> node specifies a specific SoftRater Package (rating engine logic instance) to run this rate request against. A program typically represents rating logic for a particular State and line of business (e.g.: Texas Auto insurance, California Home insurance). The program node attributes are defined as follows:

parent_id	- Insbridge identifier typically assigned to a carrier for database lookup purposes (Required)
program_id	- Insbridge identifier assigned to a program (rating engine logic instance) which represent the rating rules necessary to generate a quote. (Optional)
program_ver	- A particular version of a program. Each version may have different rating rules, inputs, outputs, etc. (Optional)
tiering_id	- Insbridge identifier specifying which tier to use within a program. (Optional/Required)

Attribute requirement rules:

1. If the [tiering_id](#) is provided then the [program_ver](#) value is required and is used to select a tiering program version to be processed against the source XML.
Example: `<program parent_id="100" tiering_id="20" ver="1"/>`
2. If the [program_id](#) is provided then the version [program_ver](#) value is used to select a program version to be processed against the source XML.
Example: `<program parent_id="100" program_id="100" ver="3"/>`
3. If the [program_id](#) is provided and the [program_ver](#) is not the version selection rules for the program, identified by program_id, are used to select the program version to be processed against the source XML.
Example: `<program parent_id="100" program_id="100" />`

The <program> node allows mapped input overrides to be specified for a specific program in a multi-program (or multi-state) rate request. See Multiple Rate Requests below for more details.

<c> Node

The <c> (category) node marks the beginning of input data for a specific category of information (i.e.: home, car, driver, policy, etc). It has the following attributes:

i	- identifier. Zero always indicates "Policy" level inputs, other categories are user definable. (Required)
desc	- description of category (Optional)

Example:
`<c i="0" desc="Policy">`

The "Policy" category is always a direct child of the <rate> node, except for overrides in the <program> node (described later). It is also the top-level category node. The Policy category node typically has an ID of zero (i.e.: i="0"). Item level categories are nested under the Policy category node.

For example:

```
<c i="0" desc="Policy">
  <m i="1212" n="Eff_Date" v="" />
```

```

    <m i="1214" n="PrimInsuredAge" v="" />
    <m i="1215" n="SecInsuredAge" v="" />
    <c i="5" desc="Home">
      ....
      <c i="7" desc="Scheduled Property">
        ....
      </c>
    </c>
    <c i="5" desc="Home">
      ....
    </c>
  </c>
</c>

```

<m> Node

The <m> (map) node represents an individual attribute-value pair mapped for a specific SoftRater Package hosted by SoftRater. In the input case, it identifies an input attribute recognized by the SoftRater Package (or Packages) listed in the <heading> node, and its associated value. The <m> node's attributes are defined as follows:

i	- input identifier (Required)
n	- name, description of input (Optional)
v	- value of input (Required)

The <m> node is always a child of a <c> (category) node and is an attribute-value pair for that specific category instance (see the Policy category example above).

INSBRIDGE.XML RESULT FORMAT

The following is an example of an Insbridge rate request result XML document. As you can see the result XML very similar to the input XML format.

```

<result lob="2" st="6" gen_date="2/19/2009 1:55:32 PM">
  <program parent_id="900" program_id="1" program_ver="1" status="PASS">
    <c i="5">
      <m i="Dwelling_1" v="640"/>
      <m i="Dwelling_3" v="0"/>
      <m i="Dwelling_5" v="0"/>
      <m i="replcc" v="0"/>
      <m i="COV Replacement Cost Contents" v="0"/>
      <m i="COV Mortgage Payment" v="0"/>
      <m i="Dwelling_10" v="0"/>
      <m i="Dwelling_11" v="34"/>
      <m i="COV Replacement Cost - Dwelling" v="0"/>
      <m i="Dwelling_13" v="0"/>
      <m i="Dwelling_13" v="674"/>
      <m i="COV Business Pursuits" v="0"/>
      <m i="COV Permitted Incidental Occupancies" v="0"/>
      <m i="COV Personal Injury" v="0"/>
      <m i="Dwelling_17" v="0.02"/>
    </c>
  </program>
</result>

```

```
<m i="Dwelling_18" v="0"/>
<m i="Dwelling_19" v="0"/>
<m i="CREDIT Multi Policy Discount" v="0"/>
<m i="CREDIT Neighborhood Watch" v="0"/>
<m i="CREDIT New Home" v="0.20"/>
<m i="CREDIT New Loan" v="0.10"/>
<m i="CREDIT Protective Devices" v="0.020000000"/>
<m i="Dwelling_25" v="0"/>
<m i="SEC_I C. Personal Property" v="213500"/>
<m i="SEC_I D. Loss of Use" v="122000"/>
<m i="SEC_I A. Dwelling" v="305000"/>
<m i="SEC_II Personal Liability Each Occurrence" v="500000"/>
<m i="SEC_II Medical Payments Each Person" v="2000"/>
<m i="SEC_I B. Other Structures" v="30500"/>
<m i="Total Annual Premium" v="674"/>
<m i="DED Standard Deductible" v="1000"/>
<m i="COV Replacement Cost Comp" v="1"/>
<m i="Total Earthquake Annual Prem" v="0"/>
<m i="EQ Loss of Use" v="25000"/>
<m i="EQ Personal Property" v="152500"/>
<m i="EQ Dwelling Limit" v="305000"/>
<m i="DED Earthquake Deductible" v="30500"/>
</c>
<c i="0">
  <m i="SELECTED_TEIR" v="SPECIAL"/>
  <m i="Total Policy Premium" v="674"/> </c>
</program>
</result>
```

The same nodes are present in the output XML as were found in the input XML, however their meanings are slightly different. The following sections describe how to interpret the output XML.

<result> Node

The <result> node marks the beginning of a rate request result. There is a one-to-one correspondence between <rate> nodes in the request XML to <result> nodes in the response XML. The result node attributes are defined as follows:

lob	- line of business indicator corresponding to the <rate> request nodes lob attribute
gen_date	- server creation timestamp indicating when this response was created.

As described previously, tracking attributes on the <rate> node are returned in the result XML document as attributes in the <result> node.

Example:

```
<rate lob="2" policyId="A1206" gen_date="2/9/2009 1:50:31 PM">
```

<program> Node

The result <program> node provides an XML envelope containing all of the formatted data, setup in the RateManager application as output results for the program. There can be (1-N) <program> node groups based on (1-N) program node groups requested in the input <rate> XML document. If the original <rate> request contained a tiering selection, each program version located during tiering execution will generate a <program> node in the result data. The result XML program node attributes are defined as follows:

parent_id	- Parent or Insbridge Company Identifier	(available by default)
program_id	- Selected Program Identifier	(available by default)
ver	- Selected Program Version Identifier	(available by default)
Status	- Status of program rate request	(available by default)
company_nm	- Parent Corporate name	(with AddHeading request option)
program_nm	- Program name	(with AddHeading request option)
version_nm	- Version name	(with AddHeading request option)
rating	- Program Rating	(with AddHeading request option)
logo	- Company Logo	(with AddHeading request option)
site	- Company Website	(with AddHeading request option)

Example base:

```
<program parent_id='500' program_id='3' ver='2' status='PASS'>
```

Example with add heading option requested:

```
<program parent_id='200' program_id='32' ver='4' company_nm='NewCo Mutual'
program_nm='Texas 6 Month' ver_nm='Performance' rating='A++' logo='newco.jpg'
site='www.newco.com' status='PASS'>
```

<c> Node

The <c> (category) node marks the beginning of output data for a specific category of information (i.e.: home, car, driver, policy, etc). It has the following attributes:

i	- identifier. Zero always indicates “Policy” level inputs, other categories are user defined. (available by default)
d	- description of category (with AddResultDesc request option)

Example:

```
<c i="0" d="Policy">
```

The “Policy” category is always a direct child of the <program> node. It is also typically the top level category node. The Policy category node typically has an ID of zero (i.e.: i="0"). Item level (user defined) categories are nested under the Policy category node.

For example:

```
<c i="0">
  <m i="SELECTED_TEIR" v="SPECIAL"/>
  <m i="Total Policy Premium" v="674"/>
  <c i="5">
    <m i="Dwelling_1" v="640"/>
    <m i="Dwelling_3" v="0"/>
    <m i="Dwelling_5" v="0"/>
    <m i="SEC_II Personal Liability Each Occurrence" v="500000"/>
    <m i="SEC_II Medical Payments Each Person" v="2000"/>
  </c>
</c>
```


<m> Node

The <m> (map) node represents an individual attribute-value pair mapped for a specific SoftRater Package hosted by SoftRater. In the output case, it identifies an output attribute as defined in the SoftRater Package (represented by the <program> node) and its associated value. The <m> node's attributes are defined as follows:

i	- output identifier	(available by default)
n	- (name) description of output	(with AddResultDesc request option)
v	- value of output	(available by default)

The <m> node is always a child of a <c> (category) node and is an attribute-value pair for that specific category instance (see the category example above).

<input> Node

The <input> node is optional. When the rate request is issued with the "AddInputs" option, this node is returned in the result XML document. It includes the full input rate request document that was used to generate the rate result document.

Example:

```
<result lob="1" policyId="ABC1234-AUTO" gen_date="7/9/2008 1:50:31 PM">
  <inputs>
    <rate policyId="ABC1234-AUTO">
      ....
    </rate>
  </inputs>
  ...
</result>
```

Input Overrides

By specifying input values in the <program> node within the <header> section of the input XML, those values will be used for that program when it is processed by SoftRater, regardless of whether those values are present in the body of the XML request. This allows each program found in the <header> to use the common set of inputs provided in the rate request body, and either provide additional inputs that are relevant only to that program, or provide overriding inputs values to ones found in the body, for use during rating.

Example:

```
<rate lob="1">
  <heading>
    <program parent_id="2" program_id="1" program_ver="3.00">
      <c i="0" d="Policy">
        <m i="11" n="Policy Program Specific Something " v="1029"/>
        <m i="12" n="Custom Question 1" v="XYZ"/>
      </c>
      <c i="3" d="driver">
        <m i="2" n="gender" v="Female"/>
      </c>
    </program>
  </heading>
  ...
</rate>
```

```

        <m i="3" n="Custom Driver Question 1" v="ABC"/>
      </c>
    </c>
  </program>
  <program parent_id="2" program_id="7" program_ver="3.00">
</heading>
<c i="0" d="Policy">
  <m i="11" n="Policy Program Specific Something " v="5000"/>
  <c i="3" d="driver">
    <m i="3" n="Custom Driver Question 1" v="DEF"/>
    ....
  </rate>

```

Time Statistics

By enabling the time tracking statistics from the Insbridge SoftRater for JBossAdministrative system (see SoftRater for JBoss Installation), the following node segment will be included in the Insbridge Response XML document returned from the engine.

Example:

```

<stats>
  <start_time>12/O6/2008 04:25:35:0280 PM</start_time>
  <stop_time>12/O6/2008 04:25:35:0316 PM</stop_time>
  <running_time>36</running_time>
</stats>

```

<start_time>

The <start_time> is the internal system tracking time from the just before the SoftRaterEJB engine starts any processing, parsing or any manipulation of the Insbridge XML Request but after the XML payload has been marshaled from the integrate client to the SoftRaterEJB system.

<stop_time>

The <stop_time> is the internal system tracking time after all program execution and just before the SoftRaterEJB engine closes the Insbridge Response XML document which will be marshaled back to the integrating client.

<running_time>

The <running_time> is the different (in Milliseconds) from the <start_time> and <stop_time>. It represents the transactional duration of the program processing the request.

Examples

Single Rate Request

See Insbridge.XML Request Format and Insbridge.XML Result Format above.

Multiple Rate Requests in a Single XML Document

It is possible to request several rates from a single XML document. These can be rates on different lines of business, across different states, and/or different SoftRater Package versions.

This simple way to do this is to combine multiple <rate> request nodes in one single root node, and submit it for rating. The root node can be anything, however in the WSI call it is always <ibdoc>.

Multiple <rate> nodes

This request XML:

```
<ibdoc>
  <rate> ... </rate>
  <rate> ... </rate>
</ibdoc>
```

...will produce this result XML:

```
<ibdoc>
  <result> ... </result>
  <result> ... </result>
</ibdoc>
```

The root node is not returned in the result XML automatically. It must be specified in the call using the “AddRoot” attribute.

Multiple <program> nodes

This request XML:

```
<ibdoc>
  <rate>
    <heading>
      <program> ... </program>
      <program> ... </program>
    </heading>
    <c>...</c>
  </rate>
</ibdoc>
```

...will produce this result XML:

```

<ibdoc>
  <result>
    <program>
      <c>...</c>
    </program>
    <program>
      <c>...</c>
    </program>
  </result>
</ibdoc>

```

Multi - State Request

To rate against multiple states using one request XML document, it is recommended to follow the “Multiple <program> nodes” request model. In the following example, we are targeting two Auto programs for rating. A program typically represents a State for a specific line of business. In this example we will assume CA=“21” and TX=“41”. As discussed earlier in Input Overrides, each program entry can specify input values to be used for that particular program.

This rate request XML:

```

<ibdoc>
  <rate lob="1">
    <heading>
      <program parent_id="2" program_id="21"> ... </program>
      <program parent_id="2" program_id="41"> ... </program>
    </heading>
    <c>...</c>
  </rate>
</ibdoc>


```

... will produce this result XML:

```

<ibdoc>
  <result lob="1" gen_date="2/9/2008 1:50:31 PM">
    <program parent_id="2" program_id="21">
      <c>...</c>
    </program>
    <program parent_id="2" program_id="41">
      <c>...</c>
    </program>
  </result>
</ibdoc>

```



The diagram shows two green boxes on the right. The top box is labeled "Results for CA" and has an arrow pointing to the <program parent_id="2" program_id="21"> node in the XML. The bottom box is labeled "Results for TX" and has an arrow pointing to the <program parent_id="2" program_id="41"> node in the XML.

Multi - Line of Business Request

To rate against multiple lines of business using one request XML document, it is recommended to follow the “Multiple <rate> nodes” request model. In the following example, we are targeting two lines of business for rating, Auto and Home. The “lob” attribute in the <rate> node signifies which line of business will be rated against.

This rate request XML:

```
<ibdoc>
  <rate lob="1" > ... </rate>
  <rate lob="2" > ... </rate>
</ibdoc>
```

...will produce this result XML:

```
<ibdoc>
  <result lob="1" gen_date="2/9/2008 1:50:31 PM"> ... </result>
  <result lob="2" gen_date="2/9/2008 1:50:45 PM"> ... </result>
</ibdoc>
```

Results for Auto

Results for Home

CONTACTING SUPPORT

If you need assistance with an Oracle Insurance Insbridge Rating and Underwriting System product, please log a Service Request using My Oracle Support at <https://support.oracle.com/>.

Address any additional inquiries to:

Oracle Corporation
World Headquarters
500 Oracle Parkway
Redwood Shores, CA 94065
U.S.A.

Worldwide Inquiries:
Phone: +1.650.506.7000
Fax: +1.650.506.7200
oracle.com

TTY ACCESS TO ORACLE SUPPORT SERVICES

Oracle provides dedicated Text Telephone (TTY) access to Oracle Support Services within the United States of America 24 hours a day, seven days a week. For TTY support, call 800.446.2398.

INDEX

(

(1-N) <program> node Groups, 14
(setEndPoint) Method
 Called by Application, 7

<

<c> Node, 12, 15
<heading> Node, 11
<input> Node, 16
<m> Node, 13, 16
<program> Node, 12, 14
 Specifying Input Values, 16
<rate> Node, 11
<result> Node, 14
<running_time> Node, 17
<start_time> Node, 17
<stop_time> Node, 17

A

Add Empty Results
 Options, 9
Add Heading
 Options, 9
Add Inputs
 Options, 9
Add Result Descriptions
 Options, 9
Add Root Node
 Options, 9
AddInputs Option, 16
AddRoot
 Attribute, 18
Applications
 Supported by Insbridge, 6
Attribute
 Rules, 12
Attributes
 AddRoot, 18
 c Node, 12, 15
 company_nm, 15
 d, 15
 desc, 12
 env_def, 11
 gen_date, 14
 i, 12, 13, 15, 16
 Line of Business, 11
 lob, 11, 14
 logo, 15
 m Node, 13
 n, 13, 16
 parent_id, 12, 15

Program Node, 12, 14
program_id, 12, 15
program_ver, 12
Rate Node, 11
rating, 15
renc, 11
Results Node, 14
site, 15
Status, 15
tiering_id, 12
Tracking, 11
v, 13, 16
ver, 15
version_nm, 15
Attribute-value Pair, 13

B

Boolean Rating Arguments
 URL Query String Arguments, 7

C

Category Node
 Example, 12, 15
 Top Level, 12, 15
Category Node Nested
 Example, 12, 15
Children
 Category Node, 13, 16
 Rate Node, 12, 15
company_nm
 Attributes, 15
Concept Diagram, 6
CustomXml
 Submitting, 7

D

d
 Attribute, 15
Data
 Handling Out of System, 9
 SoftRater Interaction, 6
desc
 Attribute, 12
Diagram
 Concept, 6
Direct JNDI interfacing, 8

E

Edition Notice, 2
EJB 2.0 Interface Files, 8
EJB Interface, 8

- env_def
 - Attributes, 11
- Example
 - Category Node, 12, 15
 - Category Node Nested, 12, 15
 - Heading Node, 11
 - Input Node, 16
 - Input Overrides, 16
 - Insbridge Rate Request Result XML Document, 13
 - Interface, 8
 - Multiple <rate> Nodes, 18
 - Multiple Line of Business Request, 19
 - Multiple Program Nodes, 18
 - Multiple Rate Request, 18
 - Multiple State Request, 19
 - Program Node, 15
 - Program Node w/Heading Option Request, 15
 - program_id, 12
 - Rate Node, 11
 - Result Node, 14
 - Single Rate Request, 18
 - Time Statistics, 17
 - XML Document, 10

G

- gen_date
 - Attributes, 14

H

- Heading Node
 - Example, 11
 - Program Nodes, 11
- HTTP POST, 7
- HTTP SOAP Proxy, 7

I

- i
 - Attribute, 12, 13, 15, 16
- identifier
 - Attribute, 12
- Input Data
 - Marking Beginning, 12
- Input Node
 - Example, 16
- Input Overrides
 - Example, 16
- Input Values
 - Specifying, 16
- Insbridge Application Framework.EAR
 - Target JAR, 8
- Insbridge Rate Request
 - XML Document, 10
- Insbridge Rate Request Result XML Document
 - Example, 13
- Insbridge.XML, 10
- Installation Directory
 - SAOP Proxy Class Instance, 7
- Integration
 - Software, 7

- Interface
 - EJB, 8
 - Example, 8
 - URL to POST, 7
- Item level
 - Categories, 12, 15

J

- JBoss
 - EJB component, 7
- JNDI Path
 - Typical, 8
- JSP Page
 - Web Service Interface, 7

L

- Line of Business
 - Attribute, 11
- Linux
 - SoftRater, 6
- lob
 - Attributes, 11, 14
- logo
 - Attributes, 15

M

- Map Node
 - Children, 13, 16
- Microsoft Windows 2003
 - SoftRater, 6
- Multiple <rate> Nodes, 19
 - Example, 18
- Multiple Line of Business Request
 - Example, 19
- Multiple Program Nodes
 - Example, 18
- Multiple Rate Request
 - Example, 18
- Multiple State Request
 - Example, 19

N

- n
 - Attribute, 13, 16
- Node
 - Category, 12, 15
 - Heading, 11
 - Input, 16
 - Map, 13, 16
 - Program, 12, 14
 - Rate, 11
 - Result, 14
 - Running Time, 17
 - Start Time**, 17
 - Stop Time, 17

O

- Options
 - Rating Integration, 9
- Output Data
 - Marking Beginning, 15
- Output XML Document, 10

P

- parent_id
 - Attributes, 12, 15
- Policy Category
 - Children, 12, 15
- Program Node
 - Example, 15
- Program Node w/Heading Option Request
 - Example, 15
- Program Nodes
 - In Header, 11
- program_id
 - Attributes, 12, 15
 - Example, 12
 - Rules, 12
- program_ver
 - Attributes, 12
- Proxy Classes
 - Generating, 7

R

- Rate Node
 - Example, 11
- Rate Request
 - Node to Mark Beginning, 11
- Rate Request Document, 10
- Rate Request Result
 - Marking Beginning, 14
- rating
 - Attributes, 15
- Rating
 - Multiple Lines of Business, 19
 - Multiple States, 19
- Rating Arguments, 9
- Rating Integration
 - Options, 9
- Rating Request Response XML, 10
- renc
 - Attributes, 11
- Request XML
 - Result Nodes, 14
- Requirements
 - Rate Node, 11
- Result Documents
 - Setting Options, 9
- Result Node
 - Example, 14
 - Output XML, 11
- Rules
 - Attribute, 12

S

- Sample
 - SOAP Proxy Class, 7
- Setting
 - Target Hosting, 7
- Setting Options
 - Result Documents, 9
- Several Rates
 - Requesting, 18
- Single Rate Request
 - Example, 18
- site
 - Attributes, 15
- SOAP Proxy Class
 - Sample, 7
- SoftRater
 - Basic Functionality, 6
 - Engine Perform, 6
 - Input Overrides, 16
- SoftRater Engine
 - Rating Arguments, 9
- SoftRaterEJB Engine
 - Start Processing, 17
 - Stop Processing, 17
- SoftRaterEJB.jar
 - Target JAR, 8
- SoftRaterProxy Class, 7
- Software
 - Integration, 7
- Status
 - Attributes, 15
- Submitting
 - Rate Requests via XML, 10
- Sun Solaris
 - SoftRater, 6

T

- Target Hosting
 - Setting, 7
- Target JAR, 8
- Tiering Selection, 14
- tiering_id
 - Attributes, 12
 - Rules, 12
- Time Statistics, 17
 - Example, 17
- Tracking
 - Attributes, 11

U

- UNIX
 - SoftRater, 6
- URL Arguments
 - Available, 7

V

- v
 - Attribute, 13, 16

ver
 Attributes, 15
version_nm
 Attributes, 15

W

Web Service Interface JSP Page, 7
WSDL Documents, 7

X

XML
 Usage in SoftRater, 10
XML Data
 Out of System, 9
XML Document
 Example, 10
 Multiple Rate Requests, 18
 Returned, 17
XML Envelope, 14