



Sun Java™ System

# Application Server 7 Error Message Reference

---

2004Q2

Sun Microsystems, Inc.  
4150 Network Circle  
Santa Clara, CA 95054  
U.S.A.

Part No: 817-5056

Copyright © 2004 Sun Microsystems, Inc., 4150 Network Circle, Santa Clara, California 95054, U.S.A. All rights reserved.

Sun Microsystems, Inc. has intellectual property rights relating to technology embodied in the product that is described in this document. In particular, and without limitation, these intellectual property rights may include one or more of the U.S. patents listed at <http://www.sun.com/patents> and one or more additional patents or pending patent applications in the U.S. and in other countries.

THIS PRODUCT CONTAINS CONFIDENTIAL INFORMATION AND TRADE SECRETS OF SUN MICROSYSTEMS, INC. USE, DISCLOSURE OR REPRODUCTION IS PROHIBITED WITHOUT THE PRIOR EXPRESS WRITTEN PERMISSION OF SUN MICROSYSTEMS, INC.

U.S. Government Rights - Commercial software. Government users are subject to the Sun Microsystems, Inc. standard license agreement and applicable provisions of the FAR and its supplements.

Use is subject to license terms. This distribution may include materials developed by third parties.

Sun, Sun Microsystems, the Sun logo, Java, Solaris, Sun™ ONE, Sun™ ONE Studio, iPlanet, J2EE, J2SE, Enterprise JavaBeans, EJB, JavaServer Pages, JSP, JDBC, JDK, JVM, Java Naming and Directory Interface, JavaMail, and the Java Coffee Cup logo are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries.

All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. in the U.S. and other countries. Products bearing SPARC trademarks are based upon architecture developed by Sun Microsystems, Inc.

UNIX is a registered trademark in the U.S. and in other countries, exclusively licensed through X/Open Company, Ltd.

This product is covered and controlled by U.S. Export Control laws and may be subject to the export or import laws in other countries. Nuclear, missile, chemical biological weapons or nuclear maritime end uses or end users, whether direct or indirect, are strictly prohibited. Export or reexport to countries subject to U.S. embargo or to entities identified on U.S. export exclusion lists, including, but not limited to, the denied persons and specially designated nationals lists is strictly prohibited.

DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID.

---

Copyright © 2004 Sun Microsystems, Inc., 4150 Network Circle, Santa Clara, California 95054, Etats-Unis. Tous droits réservés.

Sun Microsystems, Inc. détient les droits de propriété intellectuelle relatifs à la technologie incorporée dans le produit qui est décrit dans ce document. En particulier, et ce sans limitation, ces droits de propriété intellectuelle peuvent inclure un ou plus des brevets américains listés à l'adresse <http://www.sun.com/patents> et un ou les brevets supplémentaires ou les applications de brevet en attente aux Etats-Unis et dans les autres pays.

CE PRODUIT CONTIENT DES INFORMATIONS CONFIDENTIELLES ET DES SECRETS COMMERCIAUX DE SUN MICROSYSTEMS, INC. SON UTILISATION, SA DIVULGATION ET SA REPRODUCTION SONT INTERDITES SANS L'AUTORISATION EXPRESSE, ECRITE ET PREALABLE DE SUN MICROSYSTEMS, INC.

L'utilisation est soumise aux termes de la Licence. Cette distribution peut comprendre des composants développés par des tierces parties.

Sun, Sun Microsystems, le logo Sun, Java, Solaris, Sun™ ONE, Sun™ ONE Studio, iPlanet, J2EE, J2SE, Enterprise JavaBeans, EJB, JavaServer Pages, JSP, JDBC, JDK, JVM, Java Naming and Directory Interface, JavaMail, et le logo Java Coffee Cup sont des marques de fabrique ou des marques déposées de Sun Microsystems, Inc. aux Etats-Unis et dans d'autres pays.

Toutes les marques SPARC sont utilisées sous licence et sont des marques de fabrique ou des marques déposées de SPARC International, Inc. aux Etats-Unis et dans d'autres pays. Les produits portant les marques SPARC sont basés sur une architecture développée par Sun Microsystems, Inc.

UNIX est une marque déposée aux Etats-Unis et dans d'autres pays et licenciée exclusivement par X/Open Company, Ltd.

Ce produit est soumis à la législation américaine en matière de contrôle des exportations et peut être soumis à la réglementation en vigueur dans d'autres pays dans le domaine des exportations et importations. Les utilisations, ou utilisateurs finaux, pour des armes nucléaires, des missiles, des armes biologiques et chimiques ou du nucléaire maritime, directement ou indirectement, sont strictement interdites. Les exportations ou réexportations vers les pays sous embargo américain, ou vers des entités figurant sur les listes d'exclusion d'exportation américaines, y compris, mais de manière non exhaustive, la liste de personnes qui font objet d'un ordre de ne pas participer, d'une façon directe ou indirecte, aux exportations des produits ou des services qui sont régis par la législation américaine en matière de contrôle des exportations et la liste de ressortissants spécifiquement désignés, sont rigoureusement interdites.

LA DOCUMENTATION EST FOURNIE "EN L'ETAT" ET TOUTES AUTRES CONDITIONS, DECLARATIONS ET GARANTIES EXPRESSES OU TACITES SONT FORMELLEMENT EXCLUES, DANS LA MESURE AUTORISEE PAR LA LOI APPLICABLE, Y COMPRIS NOTAMMENT TOUTE GARANTIE IMPLICITE RELATIVE A LA QUALITE MARCHANDE, A L'APTITUDE A UNE UTILISATION PARTICULIERE OU A L'ABSENCE DE CONTREFAÇON.

<b>About This Guide</b>	<b>7</b>
Who Should Use This Guide	7
Using the Documentation	8
How This Guide Is Organized	10
Documentation Conventions	11
General Conventions	12
Conventions Referring to Directories	13
Contacting Sun	13
Give Us Feedback	13
Obtain Training	14
Contact Product Support	14
 <b>Chapter 4 Unexpected Errors</b>	 <b>15</b>
Analyze the System	15
 <b>Chapter 5 ADMIN</b>	 <b>17</b>
ADM	17
 <b>Chapter 6 Application Client Container</b>	 <b>31</b>
ACC	31
 <b>Chapter 7 Configuration</b>	 <b>35</b>
CNFG	35
 <b>Chapter 8 Core Services</b>	 <b>39</b>
CORE	39
 <b>Chapter 9 Dynamic Configuration</b>	 <b>55</b>
DCONF	55
 <b>Chapter 10 Deployment</b>	 <b>57</b>
DPL	57
 <b>Chapter 11 Java Transaction API</b>	 <b>71</b>
DTX	71
 <b>Chapter 12 Enterprise Java Beans</b>	 <b>73</b>
EJB	73

<b>Chapter 13 Failover Group</b> .....	<b>83</b>
FGRP .....	83
 <b>Chapter 14 High-Availability Database</b> .....	 <b>85</b>
HADB .....	85
 <b>Chapter 15 Health Checker</b> .....	 <b>161</b>
HLCK .....	161
 <b>Chapter 16 Install Services</b> .....	 <b>163</b>
INSTALL .....	163
 <b>Chapter 17 Inter ORB Protocol</b> .....	 <b>173</b>
IOP .....	173
 <b>Chapter 18 Java Message Service</b> .....	 <b>189</b>
JMS .....	189
 <b>Chapter 19 Java Transaction Services</b> .....	 <b>197</b>
JTS .....	197
 <b>Chapter 20 Load Balancer Runtime</b> .....	 <b>209</b>
LBRT .....	209
 <b>Chapter 21 Lifecycle Module</b> .....	 <b>211</b>
LCM .....	211
 <b>Chapter 22 Class Loader</b> .....	 <b>215</b>
LDR .....	215
 <b>Chapter 23 Message Driven Bean Container</b> .....	 <b>221</b>
MDB .....	221
 <b>Chapter 24 Resource Adapter</b> .....	 <b>233</b>
RAR .....	233
 <b>Chapter 25 Runtime</b> .....	 <b>243</b>
RNTM .....	243

<b>Chapter 26 Router</b> .....	<b>247</b>
ROUT .....	247
 <b>Chapter 27 Security Services</b> .....	 <b>249</b>
SEC .....	249
 <b>Chapter 28 UTIL Services</b> .....	 <b>257</b>
UTIL .....	257
 <b>Chapter 29 Verifier Tool</b> .....	 <b>263</b>
VRFY .....	263
 <b>Chapter 30 Web Container</b> .....	 <b>265</b>
WEB .....	265



# About This Guide

This guide describes error messages in the Sun Java™ System Application Server Standard and Enterprise Edition 7 environment.

This preface addresses the following topics:

- [Who Should Use This Guide](#)
- [Using the Documentation](#)
- [How This Guide Is Organized](#)
- [Documentation Conventions](#)
- [Contacting Sun](#)

## Who Should Use This Guide

The intended audience for this guide is the person who develops, assembles, and deploys beans in a corporate enterprise.

This guide assumes you are familiar with the following topics:

- Java APIs as defined in the Java™ Servlet, JavaServer Pages™ (JSP™), Enterprise JavaBeans™ (EJB™), and Java™ Database Connectivity (JDBC™) specifications
- The SQL structured database query languages
- Relational database concepts

# Using the Documentation

The Sun Java System Application Server Standard and Enterprise Edition manuals are available as online files in Portable Document Format (PDF) and Hypertext Markup Language (HTML).

The following table lists tasks and concepts described in the Sun Java System Application Server manuals. The manuals marked *(updated for 7 2004Q2)* have been updated for the Sun Java System Application Server Standard and Enterprise Edition 7 2004Q2 release. The manuals not marked in this way have not been updated since the version 7 Enterprise Edition release.

**Table 1** Sun Java System Application Server Documentation Roadmap

For information about	See the following
<i>(Updated for 7 2004Q2)</i> Late-breaking information about the software and the documentation. Includes a comprehensive, table-based summary of supported hardware, operating system, JDK, and JDBC/RDBMS.	<i>Release Notes</i>
Sun Java System Application Server 7 overview, including the features available with each product edition.	<i>Product Overview</i>
Diagrams and descriptions of server architecture and the benefits of the Sun Java System Application Server architectural approach.	<i>Server Architecture</i>
<i>(Updated for 7 2004Q2)</i> How to get started with the Sun Java System Application Server product. Includes a sample application tutorial. There are two guides, one for Standard Edition and one for Enterprise Edition.	<i>Getting Started Guide</i>
<i>(Updated for 7 2004Q2)</i> Installing the Sun Java System Application Server Standard Edition and Enterprise Edition software and its components, such as sample applications and the Administration interface. For the Enterprise Edition software, instructions are provided for implementing the high-availability configuration.	<i>Installation Guide</i>
<i>(Updated for 7 2004Q2)</i> Evaluating your system needs and enterprise to ensure that you deploy Sun Java System Application Server in a manner that best suits your site. General issues and concerns that you must be aware of when deploying an application server are also discussed.	<i>System Deployment Guide</i>
Creating and implementing Java™ 2 Platform, Enterprise Edition (J2EE™ platform) applications intended to run on the Sun Java System Application Server that follow the open Java standards model for J2EE components such as servlets, Enterprise JavaBeans™ (EJBs™), and JavaServer Pages™ (JSPs™). Includes general information about application design, developer tools, security, assembly, deployment, debugging, and creating lifecycle modules. A comprehensive Sun Java System Application Server glossary is included.	<i>Developer's Guide</i>



**Table 1** Sun Java System Application Server Documentation Roadmap (*Continued*)

<b>For information about</b>	<b>See the following</b>
( <i>Updated for 7 2004Q2</i> ) Creating and implementing J2EE web applications that follow the Java™ Servlet and JavaServer Pages (JSP) specifications on the Sun Java System Application Server. Discusses web application programming concepts and tasks, and provides sample code, implementation tips, and reference material. Topics include results caching, JSP precompilation, session management, security, deployment, SHTML, and CGI.	<i>Developer's Guide to Web Applications</i>
( <i>Updated for 7 2004Q2</i> ) Creating and implementing J2EE applications that follow the open Java standards model for enterprise beans on the Sun Java System Application Server. Discusses Enterprise JavaBeans (EJB) programming concepts and tasks, and provides sample code, implementation tips, and reference material. Topics include container-managed persistence, read-only beans, and the XML and DTD files associated with enterprise beans.	<i>Developer's Guide to Enterprise JavaBeans Technology</i>
( <i>Updated for 7 2004Q2</i> ) Creating Application Client Container (ACC) clients that access J2EE applications on the Sun Java System Application Server.	<i>Developer's Guide to Clients</i>
Creating web services in the Sun Java System Application Server environment.	<i>Developer's Guide to Web Services</i>
( <i>Updated for 7 2004Q2</i> ) Java™ Database Connectivity (JDBC™), transaction, Java Naming and Directory Interface™ (JNDI), Java™ Message Service (JMS), and JavaMail™ APIs.	<i>Developer's Guide to J2EE Services and APIs</i>
Creating custom NSAPI plug-ins.	<i>Developer's Guide to NSAPI</i>
( <i>Updated for 7 2004Q2</i> ) Information and instructions on the configuration, management, and deployment of the Sun Java System Application Server subsystems and components, from both the Administration interface and the command-line interface. Topics include cluster management, the high-availability database, load balancing, and session persistence. A comprehensive Sun Java System Application Server glossary is included.	<i>Administration Guide</i>
( <i>Updated for 7 2004Q2</i> ) Editing Sun Java System Application Server configuration files, such as the <code>server.xml</code> file.	<i>Administrator's Configuration File Reference</i>
Configuring and administering security for the Sun Java System Application Server operational environment. Includes information on general security, certificates, and SSL/TLS encryption. HTTP server-based security is also addressed.	<i>Administrator's Guide to Security</i>
Configuring and administering service provider implementation for J2EE™ Connector Architecture (CA) connectors for the Sun Java System Application Server. Topics include the Administration Tool, Pooling Monitor, deploying a JCA connector, and sample connectors and sample applications.	<i>J2EE CA Service Provider Implementation Administrator's Guide</i>
( <i>Updated for 7 2004Q2</i> ) Migrating your applications to the new Sun Java System Application Server programming model, specifically from iPlanet Application Server 6.x and Sun ONE Application Server 7.0. Includes a sample migration.	<i>Migrating and Redeploying Server Applications Guide</i>
( <i>Updated for 7 2004Q2</i> ) How and why to tune your Sun Java System Application Server to improve performance.	<i>Performance Tuning Guide</i>

**Table 1** Sun Java System Application Server Documentation Roadmap (Continued)

For information about	See the following
(Updated for 7 2004Q2) Information on solving Sun Java System Application Server problems.	<i>Troubleshooting Guide</i>
(Updated for 7 2004Q2) Information on solving Sun Java System Application Server error messages.	<i>Error Message Reference</i>
(Updated for 7 2004Q2) Utility commands available with the Sun Java System Application Server; written in manpage style.	<i>Utility Reference Manual</i>
Using the Sun™ Java System Message Queue 3.5 software.	The Sun Java System Message Queue documentation at: <a href="http://docs.sun.com/db?p=prod/sl.slmsgqu">http://docs.sun.com/db?p=prod/sl.slmsgqu</a>

# How This Guide Is Organized

This guide is a compilation of messages that you may encounter while running the Application Server. Each message begins with a message ID, which has a format like the following:

<Subsystem><4CharacterIntegerId>.

The subsystem is identified by the initial characters in the message ID. For example, in JMS0001, the subsystem is JMS.

The error messages in this guide are divided into chapters based on the subsystem prefix:

Prefix	Chapter
ADM	<a href="#">Chapter 5, “ADMIN” on page 17</a>
ACC	<a href="#">Chapter 6, “Application Client Container” on page 31</a>
CORE	<a href="#">Chapter 8, “Core Services” on page 39</a>
DPL	<a href="#">Chapter 10, “Deployment” on page 57</a>
DTX	<a href="#">Chapter 11, “Java Transaction API” on page 71</a>
EJB	<a href="#">Chapter 12, “Enterprise Java Beans” on page 73</a>
HADB	<a href="#">Chapter 14, “High-Availability Database” on page 85</a>
INSTALL	<a href="#">Chapter 16, “Install Services” on page 163</a>

Prefix	Chapter
IOP	<a href="#">Chapter 17, “Inter ORB Protocol” on page 173</a>
JMS	<a href="#">Chapter 18, “Java Message Service” on page 189</a>
JTS	<a href="#">Chapter 19, “Java Transaction Services” on page 197</a>
LCM	<a href="#">Chapter 21, “Lifecycle Module” on page 211</a>
LDR	<a href="#">Chapter 22, “Class Loader” on page 215</a>
MDB	<a href="#">Chapter 23, “Message Driven Bean Container” on page 221</a>
RAR	<a href="#">Chapter 24, “Resource Adapter” on page 233</a>
SEC	<a href="#">Chapter 27, “Security Services” on page 249</a>
UTIL	<a href="#">Chapter 28, “UTIL Services” on page 257</a>
VERFY	<a href="#">Chapter 29, “Verifier Tool” on page 263</a>
WEB	<a href="#">Chapter 30, “Web Container” on page 265</a>

The messages defined in this reference guide also include the following information:

- **Severity:** Messages are assigned a severity level ranging from FINEST to FATAL. However, in this document all messages with a log level less than INFO (FINEST, FINER, FINE, CONFIG, and INFO) are *not* listed. For a description of what these log levels mean, see the *Administrator’s Guide*, “Using Logging”.
- **Description:** Meaning and likely cause of the message.
- **Action:** Instructions on how to address the condition that caused the message to be generated.
- **See Also:** Pointer to a relevant document or guide, where applicable.

## Documentation Conventions

This section describes the types of conventions used throughout this guide:

- [General Conventions](#)
- [Conventions Referring to Directories](#)

# General Conventions

The following general conventions are used in this guide:

- **File and directory paths** are given in UNIX<sup>®</sup> format (with forward slashes separating directory names). For Windows versions, the directory paths are the same, except that backslashes are used to separate directories.

- **URLs** are given in the format:

`http://server.domain/path/file.html`

In these URLs, *server* is the server name where applications are run; *domain* is your Internet domain name; *path* is the server's directory structure; and *file* is an individual filename. Italic items in URLs are placeholders.

- **Font conventions** include:
  - The monospace font is used for sample code and code listings, API and language elements (such as function names and class names), file names, pathnames, directory names, and HTML tags.
  - *Italic* type is used for code variables.
  - *Italic* type is also used for book titles, emphasis, variables and placeholders, and words used in the literal sense.
  - **Bold** type is used as either a paragraph lead-in or to indicate words used in the literal sense.
- **Installation root directories** for most platforms are indicated by *install\_dir* in this document. Exceptions are noted in [“Conventions Referring to Directories” on page 13](#).

By default, the location of *install\_dir* on **most** platforms is:

- Solaris and Linux file-based installations:

*user's home directory*/sun/appserver7

- Windows, all installations:

*system drive*: \Sun\AppServer7

For the platforms listed above, *default\_config\_dir* and *install\_config\_dir* are identical to *install\_dir*. See [“Conventions Referring to Directories” on page 13](#) for exceptions and additional information.

- **Instance root directories** are indicated by *instance\_dir* in this document, which is an abbreviation for the following:

*default\_config\_dir/domains/domain/instance*

- **UNIX-specific descriptions** throughout this manual apply to the Linux operating system as well, except where Linux is specifically mentioned.

## Conventions Referring to Directories

By default, when using the Solaris package-based or Linux RPM-based installation, the application server files are spread across several root directories. This guide uses the following document conventions to correspond to the various default installation directories provided:

- *install\_dir* refers to `/opt/SUNWappserver7`, which contains the static portion of the installation image. All utilities, executables, and libraries that make up the application server reside in this location.
- *default\_config\_dir* refers to `/var/opt/SUNWappserver7/domains`, which is the default location for any domains that are created.
- *install\_config\_dir* refers to `/etc/opt/SUNWappserver7/config`, which contains installation-wide configuration information such as licenses and the master list of administrative domains configured for this installation.

## Contacting Sun

You might want to contact Sun Microsystems in order to:

- [Give Us Feedback](#)
- [Obtain Training](#)
- [Contact Product Support](#)

## Give Us Feedback

If you have general feedback on the product or documentation, please send this to:

<http://www.sun.com/hwdocs/feedback/>

## Obtain Training

Application Server training courses are available at:

[http://training.sun.com/US/catalog/enterprise/web\\_application.html/](http://training.sun.com/US/catalog/enterprise/web_application.html/)

Visit this site often for new course availability on the Sun Java System Application Server.

## Contact Product Support

If you have problems with your system, contact customer support using one of the following mechanisms:

- The online support web site at:  
<http://www.sun.com/supporttraining/>
- The telephone dispatch number associated with your maintenance contract

Please have the following information available prior to contacting support. This helps to ensure that our support staff can best assist you in resolving problems:

- Description of the problem, including the situation where the problem occurs and its impact on your operation
- Machine type, operating system version, and product version, including any patches and other software that might be affecting the problem. Here are some of the commonly used commands:
  - **Solaris:** `pkginfo, showrev`
  - **Linux:** `rpm`
  - **All:** `asadmin version --verbose`
- Detailed steps on the methods you have used to reproduce the problem
- Any error logs or core dumps
- Configuration files such as:
  - `instance_dir/config/server.xml`
  - a web application's `web.xml` file, when a web application is involved in the problem
- For an application, whether the problem appears when it is running in a cluster or standalone

# Unexpected Errors

This chapter provides general advice to help you deal with unexpected errors.

## Analyze the System

Unexpected errors generally result from problems in the configuration (system configuration, JVM configuration, server configuration or application-level configuration). They can also occur when the system runs out of memory, or when there is a system crash, hardware failure, or power failure.

To find cases in which the error has been reported, search for occurrences of the error code (for example, `HADB99999`) at <http://www.sunsolve.sun.com>.

In the event of a general system failure, the error message can generally be ignored, because the error is unlikely to reoccur when the system is working properly.

If system memory is an issue, consult the *Performance Tuning Guide* for suggestions on optimizing your configuration. (Consider taking other actions to remedy the problem as well, such as adding memory or decreasing system load.)

When the system is not the cause, the problem may be due to the configuration settings. If you have recently made changes, consider backing them out.

When all else fails, you may need help analyzing your configuration. In that case, gather the following information and [Contact Product Support](#) as described on [page 14](#):

- Detailed information from the body of the message
- Stack trace information
- System logs

Analyze the System



# ADMIN

This chapter lists error messages that originate from the Admin subsystem.

## ADM

### ADM0003

Severity	SEVERE/WARNING
Description	<p>MBeanServer initialization failed.</p> <p>If this error message occurs in an admin instance, it has a SEVERE level, otherwise it is a WARNING message. This error occurs when the system <code>mbeans</code> could not be registered during system start-up and as a result the server does not start.</p>
Action	<p><a href="#">Analyze the System</a>, as described on <a href="#">page 15</a>.</p>

### ADM0006

Severity	WARNING
Description	<p>Timestamp files could not be created.</p> <p>This error message occurs when Write access permission is <i>not</i> granted to the directory.</p>

**Action** See the detailed message that follows this error message. It may provide details of what occurred when the time-stamp files were created.

Make sure you have Write access permission to the directory. If not, grant Write access permission to the config directory located in, (*<install-dir>/domains/<domain-name>/<server-name>/config*) and the backup directory located in, (*<install-dir>/domains/<domain-name>/<server-name>/config/backup*).

### ADM0008

**Severity** WARNING

**Description** The Admin Server could not create the temporary folder for internal purposes in the temporary directory location. This may cause problems during deployment.

**Action** Grant appropriate file permissions to enable writing to the file. Make sure that there is sufficient space for writing to the file in the temporary directory location.

### ADM0011

**Severity** WARNING

**Description** Unable to re-register `HttpListener` with `DomainRegistry`.

During the admin server instance startup, http-listeners associated with the server are registered in the domain registry. The domain registry is used to keep the domain-specific information, so that the admin server can be contacted by other domain's admin servers. This error can occur if the domain registry is missing, that is the `domains.bin` file is missing from *<Install\_root/config>* location.

**Action** Restart the server.

*ADM0014*

<b>Severity</b>	WARNING
<b>Description</b>	The temporary folder required by the Administrator interface could not be created in the specified location. This poses some problems while trying to deploy archives from the console. Some space can be freed at this location without restarting the administrative server to correct this problem.
<b>Action</b>	Free some space at the specified location so that the file can be created at this location, without restarting the admin server. Make sure that the directory has Write access permissions.

*ADM0101*

<b>Severity</b>	WARNING
<b>Description</b>	An error occurred while getting manual changes.  This message occurs when there is a problem in the thread that tracks the manual changes performed in the configuration file, <code>server.xml</code> .
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*ADM1002*

<b>Severity</b>	WARNING
<b>Description</b>	Create instance failed.  This error message occurs when the user is trying to create an instance, and the instance creation fails. See the accompanying detailed message to determine the actual reason for this failure. Two reasons may be: <ul style="list-style-type: none"> <li>• No space to create the instance.</li> <li>• No permission to create the files in the designated directory.</li> </ul>
<b>Action</b>	The detailed message in the log file helps determine the action to be taken.

*ADM1004*

<b>Severity</b>	WARNING
-----------------	---------

<b>Description</b>	Delete instance failed. This error message is reported when the deletion of a server instance fails to execute properly. The above message is followed by detailed error message that can help determine the actual reason for this failure.
<b>Action</b>	The detailed message in the log file helps determine the action to be taken.

### *ADM1008*

<b>Severity</b>	WARNING
<b>Description</b>	Upload failed for the file at the specified location. This error message occurs when the output stream could not be closed when the server upload for deployment throws some exception.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *ADM1022*

<b>Severity</b>	SEVERE
<b>Description</b>	The deployment procedure failed.
<b>Action</b>	See the exception stack trace for information on why the deployment failed.

### *ADM1024*

<b>Severity</b>	SEVERE
<b>Description</b>	The undeployment procedure failed.
<b>Action</b>	See the exception stack trace for information on why the undeployment failed.

### *ADM1025*

<b>Severity</b>	SEVERE
<b>Description</b>	The redeployment procedure failed.
<b>Action</b>	See the exception stack trace for information on why the redeployment failed.

### *ADM1026*

<b>Severity</b>	SEVERE
<b>Description</b>	Redeployment failed.
<b>Action</b>	See the exception stack trace for information on why the redeployment failed.

### *ADM1028*

<b>Severity</b>	WARNING
<b>Description</b>	List operation failed. This error message occurs when the admin server is unable to get a list of deployed applications, web-modules, resources or connectors.
<b>Action</b>	See the exception stack trace for information on why the list operation failed and how to fix the error.

### *ADM1030*

<b>Severity</b>	WARNING
<b>Description</b>	Resource creation failed. This error message is logged when the creation of any resource, for example, jdbc-resource, jndi-resource, java-mail-resource, fails during execution.
<b>Action</b>	See the exception stack trace for information on why the resource creation failed and how to fix the error.

### *ADM1032*

<b>Severity</b>	WARNING
<b>Description</b>	Resource deletion failed. This error message is logged when the deletion of any resource, for example, jdbc-resource, jndi-resource, java-mail-resource, fails during execution.
<b>Action</b>	See the exception stack trace for information on why the resource deletion failed and how to fix the error.

*ADM1034*

<b>Severity</b>	WARNING
<b>Description</b>	Deletion of connection pool failed. This error message occurs when the deletion of the chosen JDBC connection pool fails.
<b>Action</b>	See the exception stack trace for information on why the operation failed and how to fix the error.

*ADM1037*

<b>Severity</b>	WARNING
<b>Description</b>	Lifecycle module creation failed. This error message occurs when the lifecycle module could not be created successfully.
<b>Action</b>	See the exception stack trace for information on why the operation failed and how to fix the error.

*ADM1039*

<b>Severity</b>	WARNING
<b>Description</b>	Lifecycle module deletion failed. This error message occurs when the deletion of lifecycle module does not succeed.
<b>Action</b>	See the exception stack trace for information on why the operation failed and how to fix the error.

*ADM1044*

<b>Severity</b>	SEVERE
<b>Description</b>	The specified event will not be applied. This was applied as part of a prior event.
<b>Action</b>	No action to be taken.

*ADM1046*

<b>Severity</b>	WARNING
<b>Description</b>	Notification failed. This error message occurs when the admin server fails to notify the instances that are running of any changes made in the configuration of the server.
<b>Action</b>	Restart the server. If the problem persists, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*ADM1047*

<b>Severity</b>	WARNING
<b>Description</b>	Setting JVM debug options in configuration file failed. This error message occurs when the server starts up in debug mode and fails.
<b>Action</b>	Make sure the server starts up normally. Make sure this port is free and restart the server.

*ADM1050*

<b>Severity</b>	SEVERE
<b>Description</b>	The specified starting instance failed. See instance logs for more details.
<b>Action</b>	See the <a href="#">ADM1069</a> message and instance level log file. The exact nature of failure can be determined and appropriate action can be taken.

*ADM1059*

<b>Severity</b>	WARNING
<b>Description</b>	Security check failed. This error message occurs when the authentication check fails during server instance startup.
<b>Action</b>	Make sure the <code>init.conf</code> file exists in the config directory. If the file exists, make sure the security value is correct.

### *ADM1060*

<b>Severity</b>	WARNING
<b>Description</b>	<code>isDebug</code> check failed. This error message occurs while starting a server instance either in debug or normal mode. This means that the debug check for server start failed.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *ADM1069*

<b>Severity</b>	WARNING
<b>Description</b>	The server instance startup failed. This error message occurs during server instance startup. See the detailed message to understand why the startup failed.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *ADM5002*

<b>Severity</b>	WARNING
<b>Description</b>	Attempt to register a non-compliant monitoring <code>mbean</code> . This exception occurred while trying to register an <code>Mbean</code> in the <code>MBean</code> server that is not a JMX-compliant <code>Mbean</code> .
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *ADM5003*

<b>Severity</b>	WARNING
<b>Description</b>	<p>MBean server initialization for monitoring failed.</p> <p>This error message occurs while trying to get the MBean server for registering or de-registering monitor <code>mbeans</code>.</p>
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .



*ADM5004*

<b>Severity</b>	WARNING
<b>Description</b>	<p>Monitoring channel initialization error occurred and hence monitoring is disabled.</p> <p>This error message occurs when the monitoring event listener is initialized. As a result of this, if a component has its monitoring enabled, it may be ignored, and the user may not be able to get the monitoring data. This error message should be read in conjunction with <a href="#">ADM5005</a> to determine the components that may not be monitored.</p>
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*ADM5005*

<b>Severity</b>	WARNING
<b>Description</b>	<p>Initialization of monitoring failed for the specified component.</p> <p>For a component to be monitored its monitoring enabled state should be initialized.</p>
<b>Action</b>	Lookup components in the <code>server.xml</code> and ensure the specified component is not missing.

### *ADM5603*

<b>Severity</b>	WARNING
<b>Description</b>	This is a generic error message that appears during deployment, or when configuration changes are made and also while monitoring the event handling process.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *ADM5609*

<b>Severity</b>	SEVERE
<b>Description</b>	Unable to set the config context from the event multicast.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *ADM5801*

<b>Severity</b>	WARNING
<b>Description</b>	This error occurs while creating communication channel between the admin server and the administered instance during server startup.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *ADM5802*

<b>Severity</b>	WARNING
<b>Description</b>	This error occurs while creating communication channel between the admin server and the administered instance during server startup. The reason why this error occurred is due to an IO exception that occurred while reading one of the server system files.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *ADM5803*

<b>Severity</b>	WARNING
-----------------	---------

**Description** This error occurs while creating communication channel between the admin server and the administered instance during server startup. The cause for this is an IO exception while writing one of the server system files.

**Action** [Analyze the System](#), as described on [page 15](#).

### *ADM5804*

**Severity** WARNING

**Description** This error occurs when the Admin server tries to check the client access and the address of client is null.

**Action** [Analyze the System](#), as described on [page 15](#).

### *ADM5805*

**Severity** WARNING

**Description** Local access to admin server channel.

**Action** [Analyze the System](#), as described on [page 15](#).

### *ADM5807*

**Severity** WARNING

**Description** Unable to determine the local host. This error occurs when the IP address of the local host where the server is running could not be determined.

**Action** Make sure your machine has a valid IP address.

### *ADM5810*

**Severity** WARNING

**Description** As part of establishing a communication link between the admin server and the administered instances, the admin channel client is created. If this creation fails, this error occurs.

**Action** [Analyze the System](#), as described on [page 15](#).

*ADM5811*

<b>Severity</b>	WARNING
<b>Description</b>	The admin channel auto refresh thread was interrupted.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*ADM5812*

<b>Severity</b>	WARNING
<b>Description</b>	An event notification failed. This error occurs while sending an event notification over the admin channel from the admin server to the admin client. This event notification may be for deployment, monitoring, or config changes.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*ADM5813*

<b>Severity</b>	WARNING
<b>Description</b>	If the event notification fails and the server stub file status is changed, a refresh operation is performed to get the stub file. It then retries for event notification and if it fails this error occurs.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*ADM5814*

<b>Severity</b>	WARNING
<b>Description</b>	The stub file does not exist or cannot be read.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*ADM5815*

<b>Severity</b>	WARNING
-----------------	---------

<b>Description</b>	An error occurred while initializing the admin channel client. An IO exception occurred while reading the stub from the stub file for the client in the admin channel.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*ADM6004*

<b>Severity</b>	WARNING
<b>Description</b>	This error occurs when a command is sent to an Mbean from the Mbean server and the invocation fails.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*ADM6006*

<b>Severity</b>	WARNING
<b>Description</b>	The <code>Get</code> attribute failed. An error occurred while getting the specified attribute of an Mbean from the MbeanServer.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*ADM6008*

<b>Severity</b>	WARNING
<b>Description</b>	The <code>Set</code> attribute failed. An error occurred while setting the specified attribute of an Mbean from the Mbean server.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*ADM7003*

<b>Severity</b>	WARNING
<b>Description</b>	JAVA_HOME value cannot be derived from the admin server's configuration file, and therefore an instance cannot be created.
<b>Action</b>	Make sure the JAVA_HOME is set in the admin server's <code>server.xml</code> .

*ADM7004*

<b>Severity</b>	WARNING
<b>Description</b>	This error occurs when an instance is started, stopped or restarted through a subprocess and the subprocess gives an error or terminates abruptly.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*ADM7006*

<b>Severity</b>	SEVERE
<b>Description</b>	The process of finding a free port on this system failed. The admin server tries to proceed by using default ports. See <code>dtcd/manuals</code> for default port assignments.
<b>Action</b>	Contact the system administrator.

# Application Client Container

This chapter lists error messages that originate from the Application Client Container subsystem.

## ACC

The Application Client Container (ACC) includes a set of Java classes, libraries, and other files that are distributed along with Java client programs that execute on their own Java Virtual machine. The ACC provides system services that enable a Java client program to execute. It communicates with the Application Server using RMI/IIOP and manages communication of RMI/IIOP using the client ORB bundled with it. The ACC is specific to the EJB container and is often provided by the same vendor.

This chapter contains error messages that occur in the ACC system.

### ACC002

Severity	WARNING
Description	The client container XML was not found. The default <code>sun-acc.xml</code> will be used.
Action	Ensure that the client container XML file exists and has Read access permission. By default, the application client container uses <code>sun-acc.xml</code> . Ensure that <code>sun-acc.xml</code> exists and has Read access permission. You can also add <code>-xml</code> option while running the application client script. Use the following command: <pre>appclient -client client_jar [-xml] absolute_location/sun-acc.xml</pre>

*ACC003*

<b>Severity</b>	WARNING
<b>Description</b>	An exception occurred in the client application.
<b>Action</b>	Fix the client application.

*ACC005*

<b>Severity</b>	WARNING
<b>Description</b>	Failed to load the application client descriptors and hence the client application did not build correctly.
<b>Action</b>	Fix the client application, and make sure that the <code>application-client.xml</code> and <code>sun-application-client.xml</code> files exist. Ensure that the <code>&lt;display-name&gt;</code> in <code>application-client.xml</code> matches the option, <code>-name</code> . However, if <code>-classname</code> option is used, make sure that the name used matches the client application class that contains the <code>main()</code> method.

*ACC006*

<b>Severity</b>	WARNING
<b>Description</b>	The application client descriptor is not defined for the client application.
<b>Action</b>	Fix the client application, and make sure that the <code>application-client.xml</code> and <code>sun-application-client.xml</code> files exist and have Read access permission.

*ACC010*

<b>Severity</b>	WARNING
<b>Description</b>	The server port is not disabled and the server has an invalid name.
<b>Action</b>	Check the application server to make sure the server is running. Check the server name and port number in <code>sun-acc.xml</code> , or the XML file used.



*ACC011*

<b>Severity</b>	WARNING
<b>Description</b>	A duplicate display name appears in multiple applications.
<b>Action</b>	The client application JAR contains multiple applications with <code>main()</code> method. Change the client application name.

*ACC012*

<b>Severity</b>	WARNING
<b>Description</b>	The client application JAR contains multiple applications.
<b>Action</b>	For multiple applications, you must specify the main class name or display name using <code>-mainclass &lt;appClass-name&gt;</code> or <code>-name &lt;display name&gt;</code> option. Add <code>-mainclass</code> option and specify the application class with <code>main()</code> method that should be running.

*ACC015*

<b>Severity</b>	WARNING
<b>Description</b>	An error occurred in the XML file.
<b>Action</b>	Make sure that the DTD file specified in the XML file exists and the XML file matches the DTD file.

*ACC016*

<b>Severity</b>	WARNING
<b>Description</b>	Unable to find or read the client container XML file.
<b>Action</b>	<p>Ensure that the client container XML file exists and has Read access permission. By default, the application client container uses <code>sun-acc.xml</code>. Make sure that <code>sun-acc.xml</code> file exists and has Read access permission. You can also add <code>-xml</code> option while running the application client script. Use the following command:</p> <pre>appclient -client client_jar -xml absolute_location/sun-acc.xml</pre>

ACC

# Configuration

This chapter lists error messages that originate during Load Balancer configuration.

## CNFG

### *CNFG1004*

<b>Severity</b>	WARNING
<b>Description</b>	During dynamic reconfiguration, the xml parser failed to parse loadbalancer.xml
<b>Action</b>	Check loadbalancer.xml for errors.

### *CNFG1005*

<b>Severity</b>	SEVERE
<b>Description</b>	Health Checker thread could not be created.
<b>Action</b>	Check the health checker configuration. Restart the server.

### *CNFG1006*

<b>Severity</b>	SEVERE
<b>Description</b>	Internal error
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*CNFG1007*

<b>Severity</b>	SEVERE
<b>Description</b>	Internal error
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*CNFG1008*

<b>Severity</b>	SEVERE
<b>Description</b>	Two instances are having the same name which is not allowed.
<b>Action</b>	Check the loadbalancer.xml for duplicate instance names and correct it.

*CNFG1009*

<b>Severity</b>	SEVERE
<b>Description</b>	A cluster could not be added to the configuration.
<b>Action</b>	Check if there are duplicate clusters in loadbalancer.xml

*CNFG1010*

<b>Severity</b>	SEVERE
<b>Description</b>	Two clusters have the same name.
<b>Action</b>	Check for duplicate clusters in loadbalancer.xml

*CNFG1011*

<b>Severity</b>	WARNING
<b>Description</b>	Loadbalancer dynamic reconfiguration thread could not read the loadbalancer.xml
<b>Action</b>	Check the permissions of loadbalancer.xml and whether it exists. The webserver may be running as another user which may not have sufficient permission.

*CNFG1012*

<b>Severity</b>	WARNING
<b>Description</b>	Dynamic reconfiguration thread could not be created.
<b>Action</b>	Restart the server.

*CNFG1020*

<b>Severity</b>	WARNING
<b>Description</b>	While loading the new configuration , an error was detected.
<b>Action</b>	Check the logs for additional error messages.

*CNFG1021*

<b>Severity</b>	SEVERE
<b>Description</b>	Duplicate context roots are present in loadbalancer.xml
<b>Action</b>	Correct the loadbalancer.xml and remove duplicate context roots.

*CNFG1022*

<b>Severity</b>	SEVERE
<b>Description</b>	loadbalancer dtd is not in sync with the xml file.
<b>Action</b>	Check the sun-loadbalancer_1_1.dtd file and the loadbalancer.xml. Make sure the xml points to correct dtd.

*CNFG1024*

<b>Severity</b>	SEVERE
<b>Description</b>	Duplicated idempotent URL entries detected in loadbalancer.xml
<b>Action</b>	Correct the loadbalancer.xml and remove duplicate entries for idempotent url.

*CNFG1026*

<b>Severity</b>	WARNING
<b>Description</b>	Error URL does not end with ".html".
<b>Action</b>	Correct the loadbalancer.xml and point the error-url attribute to either a valid html file ending with ".html" or to an URL starting with "http://" or "https://"

*CNFG1028*

<b>Severity</b>	WARNING
<b>Description</b>	Idempotent url pattern does not match any characters.
<b>Action</b>	Correct the idempotent-url-pattern attribute.

# Core Services

This chapter lists error messages that originate from the Core services.

## CORE

### *CORE3283*

<b>Severity</b>	ERROR
<b>Description</b>	An IOException occurred.
<b>Action</b>	This error has been seen when trying to connect to HADB.

### *CORE4001*

<b>Severity</b>	WARNING
<b>Description</b>	An error occurred when a request processing thread tried to connect to the Java Virtual Machine.
<b>Action</b>	Restart the server. If the problem persists, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *CORE4002*

<b>Severity</b>	WARNING
<b>Description</b>	An error occurred when a request processing thread tried to disconnect from the Java Virtual Machine.

**Action** Restart the server. If the problem persists, [Analyze the System](#), as described on [page 15](#).

### CORE4003

**Severity** WARNING

**Description** No name has been specified for the `<profiler>` element in `server.xml`.

**Action** Specify a name for the `<profiler>` element in `server.xml` and restart the server.

**See Also**

- *Developer's Guide*, chapter "Debugging J2EE Applications".
- *Administrator's Configuration File Reference*, chapter "Server Configuration Files".

### CORE4005

**Severity** WARNING

**Description** An error occurred while creating the embedded Java Virtual Machine. The server will not start if this error occurs.

**Action** Ensure that the JDK configuration in the `java-config` element in `server.xml` points to a valid JDK. In particular, ensure that the JDK is installed in the directory path as specified in the `java-home` attribute. Restart the server.

**See Also** *Administrator's Configuration File Reference*, chapter "Server Configuration Files".

### CORE4007

**Severity** WARNING

**Description** A generic exception report occurred.

**Action** Refer to the messages logged along with this message to determine the cause of the error.



**CORE4008**

<b>Severity</b>	WARNING
<b>Description</b>	An error occurred while trying to load the <code>Throwable</code> class. As a result of this, context information about exceptions is not logged to the server log file.
<b>Action</b>	If the problem persists, restart the server instance.

**CORE4009**

<b>Severity</b>	WARNING
<b>Description</b>	An error occurred while loading the embedded Java Virtual Machine. The server will not start if this error occurs.
<b>Action</b>	Ensure that the JDK configuration of the <code>java-config</code> element in <code>server.xml</code> points to a valid JDK. In particular, ensure that the directory pointed by the <code>java-home</code> attribute is the directory path where JDK is installed. Restart the server.
<b>See Also</b>	<i>Administrator's Configuration File Reference</i> , chapter "Server Configuration Files".

**CORE4011**

<b>Severity</b>	WARNING
<b>Description</b>	An error occurred during initialization of the Java subsystem in the server. The server will not start if this error occurs.
<b>Action</b>	Ensure that the <code>server-classpath</code> configuration of the <code>java-config</code> element in <code>server.xml</code> has not changed and does not contain any errors. Restart the server.
<b>See Also</b>	<i>Administrator's Configuration File Reference</i> , chapter "Server Configuration Files".

**CORE4012**

<b>Severity</b>	WARNING
<b>Description</b>	An error occurred during initialization of the Java subsystem in the server. The server will not start if this error occurs.

<b>Action</b>	Ensure that the <code>server-classpath</code> configuration of the <code>java-config</code> element in <code>server.xml</code> has not changed and does not contain any errors. Restart the server.
<b>See Also</b>	<i>Administrator's Configuration File Reference</i> , chapter "Server Configuration Files".

### CORE4013

<b>Severity</b>	WARNING
<b>Description</b>	An error occurred during initialization of the Java subsystem in the server. The server will not start if this error occurs.
<b>Action</b>	Ensure that the <code>server-classpath</code> configuration of the <code>java-config</code> element in <code>server.xml</code> has not changed and does not contain any errors. Restart the server.
<b>See Also</b>	<i>Administrator's Configuration File Reference</i> , chapter "Server Configuration Files".

### CORE4014

<b>Severity</b>	WARNING
<b>Description</b>	This error occurs when the Java subsystem is incorrectly configured in <code>init.conf</code> and <code>obj.conf</code> .
<b>Action</b>	Ensure that the <code>init-j2ee</code> , <code>ntrans-j2ee</code> and <code>error-j2ee</code> server application functions are configured correctly. Restart the server.
<b>See Also</b>	<i>Developer's Guide to NSAPI</i> , chapter "Predefined SAFs and the Request Handling Process". <i>Developer's Guide to NSAPI</i> , chapter "SAFs in the <code>init.conf</code> file"

### CORE4015

<b>Severity</b>	WARNING
<b>Description</b>	This error indicates insufficient memory allocation during the initialization of the Java subsystem.
<b>Action</b>	Ensure that the system has sufficient memory and then restart the server.
<b>See Also</b>	<i>Release Notes</i> , section "Software and Hardware Requirements".

*CORE5001*

<b>Severity</b>	SEVERE
<b>Description</b>	An internal error occurred.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information

*CORE5005*

<b>Severity</b>	SEVERE
<b>Description</b>	An internal error occurred during dynamic resource deployment.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

*CORE5007*

<b>Severity</b>	SEVERE
<b>Description</b>	An internal error occurred during dynamic resource un-deployment.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

*CORE5009*

<b>Severity</b>	SEVERE
<b>Description</b>	An internal error occurred during dynamic resource re-deployment.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

*CORE5011*

<b>Severity</b>	SEVERE
<b>Description</b>	An internal error occurred while enabling the dynamic resource.

**Action** [Analyze the System](#), as described on [page 15](#) with the stack trace information.

### *CORE5013*

**Severity** SEVERE

**Description** An internal error occurred while disabling the dynamic resource.

**Action** [Analyze the System](#), as described on [page 15](#) with the stack trace information.

### *CORE5014*

**Severity** WARNING

**Description** An internal configuration error occurred.

**Action** Restart the server. If the problem persists, [Analyze the System](#), as described on [page 15](#) with the stack trace information.

### *CORE5015*

**Severity** WARNING

**Description** An internal configuration error occurred.

**Action** Restart the server. If the problem persists, [Analyze the System](#), as described on [page 15](#) with the stack trace information.

### *CORE5016*

**Severity** WARNING

**Description** An internal error occurred. For example, a null pointer exception occurred while loading the application.

**Action** Restart the server. If the problem persists, [Analyze the System](#), as described on [page 15](#) with the stack trace information.

### CORE5017

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while redeploying the application.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

### CORE5018

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred during dynamic deployment of a connector module.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with stack trace information.

### CORE5019

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred during dynamic reload of an application.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

### CORE5020

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred during dynamic deployment of the EJB module.
<b>Action</b>	Add all the necessary resources used by this EJB module and restart the server. If the problem persists, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

### CORE5021

<b>Severity</b>	SEVERE
<b>Description</b>	The application was not loaded during server startup or during dynamic deployment.

**Action** This is due to missing resources (JDBC, JMS, and so on). If the problem persists, [Analyze the System](#), as described on [page 15](#) with stack trace information.

### *CORE5028*

**Severity** WARNING

**Description** An exception occurred while creating the time stamp for MIME types.

**Action** See the messages logged along with this message to determine how to fix the error.

### *CORE5029*

**Severity** WARNING

**Description** An IO error occurred while setting the value of time stamp in a new file.

**Action** See the messages logged along with this message to determine how to fix the error.

### *CORE5030*

**Severity** WARNING

**Description** Unsupported Javac option found in server configuration.

**Action** User configured invalid Javac option. Check the `javac-options` of `java-config` element in `server.xml`.

### *CORE5031*

**Severity** SEVERE

**Description** An exception occurred while loading the license.

**Action** [Analyze the System](#), as described on [page 15](#).

### *CORE5032*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred because the license file is invalid.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *CORE5033*

<b>Severity</b>	SEVERE
<b>Description</b>	The evaluation license for the Application Server has expired.
<b>Action</b>	Contact the Sun Microsystems representative to obtain the software.
<b>See Also</b>	The Sun Microsystems product upgrade site at <a href="http://www.sun.com/as7upgrade">http://www.sun.com/as7upgrade</a> for Application Server product information and downloads.

### *CORE5034*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while assigning remote permissions.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *CORE5035*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while setting up the instance limit.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *CORE5036*

<b>Severity</b>	SEVERE
<b>Description</b>	This error indicates that the license is invalid.
<b>Action</b>	Contact the Sun Microsystems representative to obtain an upgrade.

**See Also** The Sun Microsystems product upgrade site at <http://www.sun.com/as7upgrade> for Application Server product information and downloads.

### *CORE5037*

**Severity** SEVERE

**Description** The error indicates that the evaluation license is about to expire.

**Action** Contact the Sun Microsystems representative to obtain the software.

**See Also** The Sun Microsystems product site at <http://www.sun.com/as7upgrade>, for Application Server product information and downloads.

### *CORE5038*

**Severity** SEVERE

**Description** This error indicates that the evaluation license has expired.

**Action** Contact the Sun Microsystems representative to obtain the software.

**See Also** The Sun Microsystems product site at <http://www.sun.com/as7upgrade>, for Application Server product information and downloads.

### *CORE5046*

**Severity** SEVERE

**Description** An error occurred while loading the applications during server startup time.

**Action** [Analyze the System](#), as described on [page 15](#) with the stack trace information

### *CORE5047*

**Severity** SEVERE

**Description** A configuration exception occurred while loading the applications during server startup time.



**Action** [Analyze the System](#), as described on [page 15](#) with the stack trace information

### *CORE5048*

**Severity** SEVERE

**Description** A configuration exception occurred while retrieving the value of the `dynamic reload enabled` flag defined in `server.xml`.

**Action** [Analyze the System](#), as described on [page 15](#) with the stack trace information.

### *CORE5049*

**Severity** SEVERE

**Description** An error occurred while shutting down applications.

**Action** [Analyze the System](#), as described on [page 15](#) with the stack trace information.

### *CORE5053*

**Severity** SEVERE

**Description** An error occurred while terminating applications during server shutdown.

**Action** [Analyze the System](#), as described on [page 15](#) with the stack trace information.

### *CORE5054*

**Severity** SEVERE

**Description** An error occurred while calling `onReady` state of the application life cycle.

**Action** Make sure the steady pools for the EJBs are created properly during server startup.

### *CORE5060*

<b>Severity</b>	WARNING
<b>Description</b>	An error occurred while constructing a URL path for the classloader.
<b>Action</b>	Check the classpath in <code>server.xml</code> . Verify if the files and directories you have specified are valid.

### *CORE5061*

<b>Severity</b>	WARNING
<b>Description</b>	A generic exception occurred.
<b>Action</b>	Refer to the exception data to understand the context of this log message. See the other log messages reported along with this message.

### *CORE5070*

<b>Severity</b>	SEVERE
<b>Description</b>	Server context could not be created.
<b>Action</b>	Refer to the exception data to understand the context of this log message. See the other log messages reported along with this message.

### *CORE5071*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred during initialization of the application server.
<b>Action</b>	Refer to the exception data to understand the context of this log message. See the other log messages reported along with this message.

### *CORE5072*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred either during startup or while reconfiguring the application server.

**Action** Refer to the exception data to understand the context of this log message. See the other log messages reported along with this message.

### *CORE5074*

**Severity** SEVERE

**Description** An error occurred while application server was shutting down.

**Action** Refer to exception data. to understand the context of this log message. See the other log messages reported along with this message.

### *CORE5075*

**Severity** SEVERE

**Description** An error occurred because the license file is invalid.

**Action** Obtain a valid license. Contact the Sun Microsystems representative to obtain the software.

### *CORE5080*

**Severity** SEVERE

**Description** An exception occurred while resolving the initial reference of ORB. The lookup for `RootPOA` failed for the ORB started in the server.

**Action** The ORB was not created in the server. [Analyze the System](#), as described on [page 15](#) with the complete stack trace.

### *CORE5081*

**Severity** SEVERE

**Description** The ORB was not created in the server.

**Action** Check the ORB properties in the `server.xml` file or check if the ORB listener port is already in use. If the problem persists, [Analyze the System](#), as described on [page 15](#) with the complete stack trace information.

### *CORE5082*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while running the J2EE services.
<b>Action</b>	Server startup failed. <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

### *CORE5084*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while creating or binding the server object in the naming service.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

### *CORE5089*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while initializing the <code>realmmanager</code> and registering with the naming service.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information

### *CORE5090*

<b>Severity</b>	SEVERE
<b>Description</b>	Unable to write to the <code>seed</code> <sup>1</sup> file, for fast startup. The next startup is likely to be slow.
<b>Action</b>	Refer to the exception data to understand the context of this log message. See the other log messages reported along with this message.

1. A file used to store a random secure number. The application server stores this number in the file and accesses it whenever the server restarts.

*CORE5091*

<b>Severity</b>	SEVERE
<b>Description</b>	The J2EE server startup failed.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

*CORE5092*

<b>Severity</b>	SEVERE
<b>Description</b>	The J2EE server reported an error.
<b>Action</b>	See the description of the error. <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with stack trace information.

*CORE5093*

<b>Severity</b>	SEVERE
<b>Description</b>	The J2EE server startup failed.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

*CORE5094*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while looking up the server object during shutdown.
<b>Action</b>	Refer to exception data to understand the context of this log message. See the other log messages reported along with this message.

*CORE5095*

<b>Severity</b>	SEVERE
<b>Description</b>	Unable to shutdown the J2EE server.

**Action** Refer to exception data to understand the context of this log message. See the other log messages reported along with this message.

### *CORE5096*

**Severity** WARNING

**Description** Relative pathname is specified for transaction log directory.

**Action** Check the `tx-log-dir` attribute of `transaction-service` element in `server.xml`.

# Dynamic Configuration

This chapter lists error messages that originate during dynamic configuration of the Load Balancer.

## DCONF

### *DCONF3000*

<b>Severity</b>	ERROR
<b>Description</b>	Failure to create the instance quiescing thread.
<b>Action</b>	Restart the server.

### *DCONF3004*

<b>Severity</b>	ERROR
<b>Description</b>	Failure to create the application quiescing thread.
<b>Action</b>	Restart the server.

DCONF



# Deployment

This chapter lists error messages that originate from the Deployment subsystem.

## DPL

### *DPL5001*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while loading all the classes within the JAR.
<b>Action</b>	See the stack trace for more information and make sure the corresponding JAR file exists.

### *DPL5002*

<b>Severity</b>	SEVERE
<b>Description</b>	Unable to add an icon.
<b>Action</b>	See the stack trace for more information and make sure the icon file is available in the JAR file.

### *DPL5003*

<b>Severity</b>	WARNING
<b>Description</b>	SAX Parser cannot validate. This error or warning message is sent either from the XML parser or the application.

**Action** See the stack trace for more information. If it is an XML parser error, [Analyze the System](#), as described on [page 15](#). If the error is from the application, make sure the XML file is valid.

*DPL5004*

**Severity** WARNING

**Description** Cannot add JAR to output stream.

**Action** Make sure the user has appropriate access permission to the temporary directory, `tmp`, and there is sufficient space in the `tmp` directory.

*DPL5005*

**Severity** WARNING

**Description** An IO exception occurred. This error occurs when deployment backend tries to create a file in the specified directory.

**Action** Make sure the user has appropriate access permission to the temporary directory, `tmp`, and there is sufficient space in the `tmp` directory.

*DPL5006*

**Severity** WARNING

**Description** An error occurred while reading the `connector.xml` file. This error occurs while converting the XML subtree representing connector information into a connector descriptor object.

**Action** See the stack trace for more information and see if the supplied `connector.xml` file exists and is valid.

*DPL5007*

**Severity** SEVERE

**Description** An error occurred while loading the class, `EjbDescriptor.getMethods()`.

**Action** See the stack trace for more information and see if the class exists in the classpath.

### *DPL5008*

**Severity** SEVERE

**Description** An error occurred while loading the class.

**Action** See the stack trace for more information and see if the class exists in the classpath.

### *DPL5009*

**Severity** SEVERE

**Description** An error occurred while loading the EJB class, in `getFields` on `EjbDescriptor`.

**Action** See the stack trace for more information and see if the EJB class is available.

### *DPL5010*

**Severity** SEVERE

**Description** An error occurred while loading the EJB class in `getFields` on `EjbDescriptor`.

**Action** See the stack trace for more information and see if the EJB class is available.

### *DPL5011*

**Severity** SEVERE

**Description** An error occurred while loading the EJB class in `getFieldForName` on `EjbDescriptor`.

**Action** See the stack trace for more information and see if the EJB class is available.

*DPL5012*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while loading the EJB class in <code>getFieldForName</code> on <code>EjbDescriptor</code> .
<b>Action</b>	See the stack trace for more information and see if the EJB class is available.

*DPL5013*

<b>Severity</b>	SEVERE
<b>Description</b>	A mail configuration exception occurred while loading the configuration information from the mail resource node in <code>server.xml</code> for the JavaMail session object.
<b>Action</b>	See the stack trace for more information.

*DPL5014*

<b>Severity</b>	SEVERE
<b>Description</b>	A method not found in <code>ejbDescriptor</code> .
<b>Action</b>	See the stack trace for more information and make sure the EJB bean contains this method.

*DPL5015*

<b>Severity</b>	SEVERE
<b>Description</b>	The method was not found.
<b>Action</b>	See the stack trace for more information and make sure the EJB bean contains this method.

*DPL5016*

<b>Severity</b>	WARNING
<b>Description</b>	Unable to instantiate implementation of interface. This is a configuration error.

**Action** [Analyze the System](#), as described on [page 15](#).

### *DPL5017*

**Severity** WARNING

**Description** Unable to instantiate implementation. This is a configuration error.

**Action** [Analyze the System](#), as described on [page 15](#).

### *DPL5018*

**Severity** WARNING

**Description** An error occurred while parsing. This error occurs while translating an input stream containing the XML document into the implementation object for Taglib.

**Action** See the stack trace for more information and make sure the XML file is valid.

### *DPL5019*

**Severity** WARNING

**Description** Illegal argument(s). This warning occurs while constructing the application object from the XML tree (`application.xml`).

**Action** Make sure the `application.xml` of a particular EAR file is valid.

*DPL5020*

<b>Severity</b>	SEVERE
<b>Description</b>	SAX Parser cannot parse given stream. This message is sent from the XML parser or the application.
<b>Action</b>	Make sure the <code>application.xml</code> file is valid. If the error occurred from the XML Parser, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*DPL5021*

<b>Severity</b>	SEVERE
<b>Description</b>	No method found for XML query element. This error occurs when the tags in the <code>ejb-jar.xml</code> file does not have respective query methods.
<b>Action</b>	Make sure the <code>ejb-jar.xml</code> file tags are valid.

*DPL5022*

<b>Severity</b>	WARNING
<b>Description</b>	Supplied external descriptors are incorrect. This error occurs while adding the EJB JAR file into the application using the given descriptor entry name.
<b>Action</b>	See the stack trace and make sure the specified descriptor entry name ( <code>ejb-jar.xml</code> ) is available.

*DPL5023*

<b>Severity</b>	WARNING
<b>Description</b>	Unable to find the class.
<b>Action</b>	See the stack trace for more information.

*DPL5024*

<b>Severity</b>	WARNING
<b>Description</b>	Unable to expand JAR archive.

**Action** Make sure there is sufficient disk space and that the user has access permission to the directory.

### *DPL5025*

**Severity** WARNING

**Description** An error occurred in the SAX parser configuration.

**Action** [Analyze the System](#), as described on [page 15](#).

### *DPL5026*

**Severity** WARNING

**Description** An exception occurred in the SAX parser. This warning message is sent from either the XML parser or the application.

**Action** Make sure the archive (ear / jar) XML files are valid. See the stack trace for more information. If the problem persists, [Analyze the System](#), as described on [page 15](#).

### *DPL5028*

**Severity** SEVERE

**Description** An exception occurred in `MethodDescriptor.getMethod()`. This error occurs while getting the method from `EjbDescriptor` which contains the meta-information describing EJBs.

**Action** See the stack trace for more information. Make sure the method name exists in the EJB.

### *DPL5029*

**Severity** WARNING

**Description** Unable to read runtime descriptor nodes (XML file for runtime bindings for a J2EE application) from the input stream.

**Action** [Analyze the System](#), as described on [page 15](#).

*DPL5030*

<b>Severity</b>	WARNING
<b>Description</b>	Unable to read EJB nodes from the input stream (containing the <code>ejb-jar.xml</code> file).
<b>Action</b>	Make sure the <code>ejb-jar.xml</code> content is valid.

*DPL5031*

<b>Severity</b>	WARNING
<b>Description</b>	Unable to read the method descriptor nodes (XML format of a method element) from the input stream representing XML.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*DPL5032*

<b>Severity</b>	WARNING
<b>Description</b>	An authentication method was not defined in the <code>web.xml</code> descriptor and is therefore using the default, BASIC, for login configuration.
<b>Action</b>	Make sure the <code>web.xml</code> file, <code>login-config</code> element contains the value for <code>auth-method</code> .



*DPL5034*

<b>Severity</b>	WARNING
<b>Description</b>	An error in the deployment and consequently Rollback failed.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*DPL5035*

<b>Severity</b>	WARNING
<b>Description</b>	An error occurred while deploying the EJB module and generating <code>clientStubs</code> .
<b>Action</b>	See the stack trace for more information.

*DPL5036*

<b>Severity</b>	WARNING
<b>Description</b>	A duplicate entry exists in the JAR archive. This error occurs when two files with the same name are added into the JAR archive while creating the client JAR archive.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*DPL5100*

<b>Severity</b>	SEVERE
<b>Description</b>	Unable to generate new source. This error occurs while generating the Java files ( <code>EJBHome/EJBObject</code> ).
<b>Action</b>	See the stack trace for more information. If you are unable to fix the error, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*DPL5101*

<b>Severity</b>	SEVERE
<b>Description</b>	Unable to invoke <code>rmic</code> .
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*DPL5102*

<b>Severity</b>	SEVERE
<b>Description</b>	This error is sent by the <code>rmic</code> compiler while generating stub or skeletons from <code>EJBHome/EJBRemote</code> .
<b>Action</b>	See the stack trace for more information. <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*DPL5103*

<b>Severity</b>	SEVERE
<b>Description</b>	EJBC compilation failed. This error occurs during the compilation of generated Java files ( <code>EJBHome/Remote/stub/skeletons</code> ).
<b>Action</b>	See the stack trace for more information. <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*DPL5104*

<b>Severity</b>	WARNING
<b>Description</b>	The EJBC code gen required <i>check error</i> . This error occurs when EAR or JAR files are redeployed. The deployment backend checks if the EAR/JAR file and the new EAR/JAR file to be deployed are similar, to determine if deployment backend must regenerate Home/Remote implementation code for an EJB.
<b>Action</b>	Make sure both the new and old <code>ear/jar</code> file exists.

*DPL5200*

<b>Severity</b>	SEVERE
<b>Description</b>	Unable to invoke <code>rmic</code> . This error occurs when the deployment backend is not able to invoke the <code>rmic</code> .
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*DPL5201*

<b>Severity</b>	SEVERE
<b>Description</b>	The <code>rmic</code> compilation failed. This error occurs when the generated Java files ( <code>EJBHome/Remote</code> ) are sent to the <code>rmic</code> for generating stubs/skeletons.
<b>Action</b>	See the stack trace for more information. <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*DPL5202*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while compiling the EJB. This error occurs when compiling the generated Java files ( <code>EJBHome/EJBRemote</code> ).
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*DPL5203*

<b>Severity</b>	WARNING
<b>Description</b>	The output JAR file already exists. This error occurs while generating the <code>jar</code> for this application and the JAR file with the same name exists.
<b>Action</b>	Check if the application <code>Cooked.jar</code> exists where the <code>GeneratorDriver</code> is running.

*DPL5204*

<b>Severity</b>	WARNING
-----------------	---------

<b>Description</b>	An exception occurred while loading the class. This exception occurs while loading the stubs/skeletons of home/interface classes in EAR.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *DPL5205*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while generating EJB. This error occurs while running <code>rmic</code> on generated Java (EJBHome/EJBRemote)files.
<b>Action</b>	See the stack trace for more information.

### *DPL5206*

<b>Severity</b>	SEVERE
<b>Description</b>	This error occurs either while loading the bean implementation class or while loading the stubs for all the EJBHome/EJBRemote classes in the JAR.
<b>Action</b>	Make sure the bean implementation class is present in the JAR. If the problem persists, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *DPL5207*

<b>Severity</b>	SEVERE
<b>Description</b>	An IO exception occurred. This error occurs when the deployment backend (GeneratorDriver) tries to get an application object representing the EAR file.
<b>Action</b>	Make sure the <code>application.xml</code> file is present in ear file.

### *DPL5208*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred.
<b>Action</b>	See the stack trace for more information.

### *DPL5209*

<b>Severity</b>	WARNING
<b>Description</b>	This exception occurs when the deployment backend adds generated files (EJBHome/EJBObject) to the generated file list.
<b>Action</b>	See the stack trace for more information.

### *DPL5210*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while generating code. This error occurs when the deployment backend runs the generator to generates files for EJBHome/EJBObject.
<b>Action</b>	See the stack trace for more information.

### *DPL5211*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while setting the message status. This error occurs when the deployment client (remote/local) sends a request to the deployment backend and the backend sends a message to the client requesting the status. This is a communication related exception that occurs during the execution of remote method call.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *DPL5212*

<b>Severity</b>	WARNING
<b>Description</b>	This error occurs when the deployment client (remote/local) sends a request to the deployment backend and the backend sends a notification event to the client. This is a communication related exception that occurs during the execution of remote method call.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

DPL

# Java Transaction API

This chapter lists error messages that originate from the Java transaction APIs.

## DTX

Transaction processing in J2EE involves the following five participants: Transaction Manager, Application Server, Resource Manager(s), Resource Adapter(s) and the User Application. Each of these entities contribute to reliable transaction processing, by implementing different APIs and functionalities.

This chapter contains error messages that occur in the DTX system.

### *DTX5001*

<b>Severity</b>	SEVERE
<b>Description</b>	An internal error occurred while enlisting a resource with the transaction.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *DTX5002*

<b>Severity</b>	SEVERE
<b>Description</b>	An internal error occurred while delisting a resource with the transaction.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*DTX5003*

<b>Severity</b>	SEVERE
<b>Description</b>	An internal error occurred while registering synchronization with the transaction.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*DTX5004*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while trying to start the transaction.
<b>Action</b>	See the exception data for more details. Make sure the application is not trying to start a transaction when an active transaction is already running.

*DTX5005*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while trying to <i>commit</i> the transaction.
<b>Action</b>	See the exception data for more information on the exception.

*DTX5006*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while trying to <i>rollback</i> the transaction.
<b>Action</b>	See the exception data for more details.



# Enterprise Java Beans

This chapter lists error messages that originate from the enterprise java bean subsystem.

## EJB

An enterprise java bean (EJB) is a server-side component that encapsulates the business logic of an application. The business logic is the code that fulfills the purpose of the application.

### *EJB5013*

<b>Severity</b>	SEVERE
<b>Description</b>	An internal EJB exception occurred.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

### *EJB5014*

<b>Severity</b>	SEVERE
<b>Description</b>	An internal exception occurred while resolving an object.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

### *EJB5016*

<b>Severity</b>	SEVERE
<b>Description</b>	<p>An exception occurred while creating <code>BaseContainer</code>. Possible reasons are:</p> <ul style="list-style-type: none"><li>• The <code>ejbObject</code> class/home interface, or class/remote interface class could not be loaded.</li><li>• An exception occurred while trying to bind the objects into the Naming manager.</li></ul>
<b>Action</b>	More information on the exception can be obtained from the log file. Correct the problem and redeploy the application.

### *EJB5017*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while running <code>preinvoke</code> .
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

### *EJB5020*

<b>Severity</b>	WARNING
<b>Description</b>	An exception occurred while unregistering <code>monitormbean</code> . This exception occurs if the <code>MBean</code> is not registered for a particular EJB. Another reason may be incorrectly unregistering from the <code>MBean</code> server.
<b>Action</b>	Make sure that the <code>MBean</code> is not registered for a particular EJB. Ensure that you unregister from the <code>MBean</code> server correctly.

### *EJB5021*

<b>Severity</b>	SEVERE
<b>Description</b>	The session bean transaction is incomplete.
<b>Action</b>	A transaction started within a method of the stateless session bean must be completed before leaving the method. Check the application code and correct the problem.

### *EJB5022*

<b>Severity</b>	SEVERE
<b>Description</b>	Message driven bean transaction is incomplete.
<b>Action</b>	A transaction started within a method of a Message Driven Bean must be completed before leaving the method. Check the application code and correct the problem.

### *EJB5023*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while registering <code>monitormbean</code> .
<b>Action</b>	An <code>MBean</code> with a similar configuration is already registered or an error occurred while registering the bean with the <code>MBean</code> server.

### *EJB5024*

<b>Severity</b>	WARNING
<b>Description</b>	An exception occurred while registering child <code>monitormbean</code> in the pool/cache to the monitoring bean.
<b>Action</b>	Refer the stack trace for details. If you are unable to fix the error, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

### *EJB5025*

<b>Severity</b>	WARNING
<b>Description</b>	An internal exception occurred while releasing EJB context back to the pool.
<b>Action</b>	Refer the stack trace for details on how to correct the problem. If you are unable to fix the error, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

*EJB5026*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while removing the EJB local object. When the <code>ejbRemove()</code> method of the bean was called, the method sent a <code>RemoveException</code> .
<b>Action</b>	Check the application code.

*EJB5027*

<b>Severity</b>	SEVERE
<b>Description</b>	<p>An exception occurred while removing the EJB.</p> <p>When the <code>ejbRemove()</code> method of the bean was called, the method sent an exception.</p>
<b>Action</b>	Check the stack trace information to correct the problem. If you still get the error, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

*EJB5028*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while getting the EJB local object. Possible reason could be, an EJB object instance could not be created.
<b>Action</b>	Make sure that the bean class is defined as public and has a default constructor.

*EJB5029*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while getting the EJB context. Possible reasons could be, an EJB object instance could not be created.
<b>Action</b>	Make sure that the bean class is defined as public and has a default constructor.

*EJB5030*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while comparing homes and primary keys of two EJBs.
<b>Action</b>	Make sure that the <code>EJBObject</code> passed as parameter to the <code>isIdentical</code> method is not null.

*EJB5031*

<b>Severity</b>	SEVERE
<b>Description</b>	A remote exception occurred while refreshing a Read Only bean or the bean name was incorrectly specified.
<b>Action</b>	Make sure the bean is not a remote object or a Read Only bean. Check the code to specify the correct bean name. If the bean does not provide a remote interface, use the <code>getReadOnlyBeanLocalNotifier</code> to refresh the local Read Only bean. Otherwise, set the <code>is-read-only-bean</code> to <code>true</code> in the <code>sun-ejb-jar.xml</code> file.

*EJB5032*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while creating a new bean. Possible reason could be, a bean instance could not be created.
<b>Action</b>	Make sure the bean class is defined as public and has a default constructor.

*EJB5058*

<b>Severity</b>	SEVERE
<b>Description</b>	The passivation directory could not be created. This occurs if you do not have Write access permission to the directory pointed by the <code>session-store</code> element in the <code>server.xml</code> of the server instance.
<b>Action</b>	Make sure you have Write access permission to the directory pointed by the <code>session-store</code> element in the <code>server.xml</code> of the server instance

*EJB5059*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while creating a new bean. Possible reason could be, a bean instance that could not be created.
<b>Action</b>	Make sure the bean class is defined as public and has a default constructor.

*EJB5060*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while creating a new bean. Possible reason could be, a bean instance that could not be created.
<b>Action</b>	Make sure the bean class is defined as public and has a default constructor.

*EJB5061*

<b>Severity</b>	SEVERE
<b>Description</b>	Unable to call <code>remove</code> on the <code>statefulsession</code> bean. The bean may be removed due to time-out.
<b>Action</b>	Set higher values for <code>removal-timeout</code> in <code>server.xml</code> . If you still get this error, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the server log and stack trace information.

*EJB5062*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while removing the bean.
<b>Action</b>	Set higher values for <code>removal-timeout</code> in <code>server.xml</code> . If you still get this error, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the server log and stack trace information.

*EJB5063*

<b>Severity</b>	SEVERE
<b>Description</b>	Unable to call <code>remove</code> on the stateful session bean. The bean may be removed due to time-out.
<b>Action</b>	Set higher values for <code>removal-timeout</code> in <code>server.xml</code> . If you still get this error, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the server log and stack trace information.

*EJB5064*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred in the code implementing the <code>afterCompletion</code> method of the <code>SessionSynchronization</code> interface.
<b>Action</b>	Look at the <code>afterCompletion</code> code in your session bean that implements the <code>SessionSynchronization</code> interface.

*EJB5066*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred in the <code>ejbRemove()</code> method of the <code>Stateful</code> session bean, other than <code>EJBException</code> or <code>EJBRemoveException</code> .
<b>Action</b>	See the log file that contains the stack trace describing the cause of the exception. If you still get this error, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

*EJB5069*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred getting the <code>ejbcreate()</code> method.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

*EJB5070*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while creating stateless session bean.
<b>Action</b>	See the log file that contains the stack trace describing the cause of the exception. If this error occurs again, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*EJB5071*

<b>Severity</b>	SEVERE
<b>Description</b>	A remote or transactional roll back exception occurred when the container attempted to commit or rollback the transaction. Typically, a database failure (like database server crash) causes this failure.
<b>Action</b>	See the stack trace for more information.

*EJB5103*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred in <code>releaseContext</code> .
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

*EJB5105*

<b>Severity</b>	WARNING
-----------------	---------



<b>Description</b>	An exception occurred in <code>createContainer</code> .
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

### *EJB5106*

<b>Severity</b>	WARNING
<b>Description</b>	An exception occurred in <code>EntityContainer</code> .
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

EJB

# Failover Group

This chapter lists error messages that originate in a cluster failover group.

## FGRP

### *FGRP1001*

<b>Severity</b>	WARNING
<b>Description</b>	Two instances are having the same name which is not allowed.
<b>Action</b>	Check the loadbalancer.xml for duplicate instance names and correct it.

### *FGRP1002*

<b>Severity</b>	SEVERE
<b>Description</b>	Internal error
<b>Action</b>	Restart the server.

### *FGRP1004*

<b>Severity</b>	WARNING
<b>Description</b>	Internal error
<b>Action</b>	Restart the server.

*FGRP1005*

<b>Severity</b>	SEVERE
<b>Description</b>	Internal error
<b>Action</b>	Restart the server.

*FGRP1007*

<b>Severity</b>	SEVERE
<b>Description</b>	Internal error
<b>Action</b>	Restart the server.

*FGRP1008*

<b>Severity</b>	SEVERE
<b>Description</b>	Internal error
<b>Action</b>	Restart the server.

# High-Availability Database

This chapter lists error messages that originate from the HADB.

## HADB

### *HADB00000*

<b>Description</b>	Operation completed successfully.
<b>Action</b>	None.

### *HADB00208*

<b>Description</b>	An operation within the current transaction failed and the transaction was aborted.
<b>Action</b>	Retry the transaction.

### *HADB00216*

<b>Description</b>	A request to abort transaction arrived. An error occurred on one of the processing nodes, that caused the transaction to abort.
<b>Action</b>	Retry the transaction.

*HADB00224*

<b>Description</b>	The operation timed out. The transaction controller did not receive a reply on time, from one or more of the participating nodes.
<b>Action</b>	The possible reasons for this could be: <ul style="list-style-type: none"><li>• Lock contention</li><li>• High load</li><li>• Node is inactive</li><li>• Lack of resources for executing the operation.</li></ul>

*HADB00208*

<b>Description</b>	The transaction was aborted.
<b>Action</b>	Look in the SQL Guide for your database to get an explanation, and retry the transaction.

*HADB00216*

<b>Description</b>	An error occurred on one of the processing nodes, that caused the transaction to rollback.
<b>Action</b>	Retry the transaction.

*HADB00224*

<b>Description</b>	SQL operation timed out. .
<b>Action</b>	Look in the SQL Guide for your database to get an explanation.

*HADB00512*

<b>Description</b>	When starting or restarting a node, the Node Supervisor (NUSP) attempted to start a process, but there are indications that this process is already running. The most common occurrence of this is that the UDP port assigned to the process is occupied.
--------------------	---

**Action** Check the offending computer for processes that own the UDP port. If the process that cannot be started is running, stop it manually.

### *HADB00560*

**Description** Illegal internet address format. Error when connecting to the network address of a server process. This may be caused by an invalid network address or non-existing hostname.

**Action** Verify that the network addresses being used when creating a database exists.

### *HADB00582*

**Description** Failed to free message information object. This is an internal consistency message. The process attempted to free a pool of objects for information about communication messages, but there are allocated objects in the pool.

**Action** If this message occurs during shutdown of a node or database, it can be ignored. Otherwise, [Analyze the System](#), as described on [page 15](#).

### *HADB00583*

**Description** Out of Message Descriptor objects for sending messages. This error may occur when a server process attempts to allocate more than 100000 message descriptors.

**Action** [Analyze the System](#), as described on [page 15](#).. It is very unlikely that a process will allocate this many message descriptors during normal operation.

### *HADB00584*

**Description** Failed to free Message Descriptor object. Internal consistency message. The process attempted to free a pool of descriptor objects for communication messages, but there are allocated objects in the pool.

**Action** If this message occurs during shutdown of a node or database, it can be ignored. Otherwise, [Analyze the System](#), as described on [page 15](#)..

### *HADB00624*

- Description** Too many ports used. Server process has exhausted its pool of network port objects. This is typically caused by the server process attempting to create too many network connections over a short period of time. This occurs when a large number of SQL client connections arrives almost simultaneously.
- Action** Try to decrease the arrival rate of SQL client connections, or distribute the load over more database nodes. If this is not possible, [Analyze the System](#), as described on [page 15](#)..

### *HADB00832*

- Description** Message out of sequence with respect to the current state has been received by a server or client process.
- Action** Spurious errors can be safely ignored. If numerous errors occur during a short interval, [Analyze the System](#), as described on [page 15](#)..

### *HADB00848*

- Description** This message is reported when you attempt to run server processes belonging to different versions of HADB software to support one database. Client programs running a software version different from the server versions is usually safe, unless specified in the release notes.
- Action** Upgrade all server software for a database to run the same software version.

### *HADB00916*

- Description** This is an internal message that is used to synchronize internal processing of SQL commands. Due to some unresolved error, this error message will occasionally be sent to an application client, instead of a more specific user error. This problem will be resolved in future releases of HADB.
- Action** Retry the operation.



*HADB01040*

<b>Description</b>	This error may occur when an application attempts to retrieve data from a table while the table is being refragmented.
<b>Action</b>	Rollback the transaction and retry.

*HADB01521*

<b>Description</b>	No space left on the device. The database was unable to allocate more space on a storage device.
<b>Action</b>	Check the available device space on the offending database node and determine the device that lacks space. Reclaim free space on the device, if possible. If you determine that you need to upgrade the node with more storage space, follow the procedure documented in the <i>Administrator's Guide</i> . Note that because most HADB instances are configured so that storage space is allocated evenly and distributed over the nodes, it is likely that other nodes will report the same error.

*HADB01536*

<b>Severity</b>	
<b>Description</b>	Unknown error during asynchronous operation. Attempting to read data from or write data to a file failed. An operating system specific error code is usually also displayed in an adjacent message. A normal reason is damaged storage devices.
<b>Action</b>	Replace damaged storage devices, if any. Follow procedures in the <i>Administrator's Guide</i> in order to reconstruct missing configurations and data.

*HADB01552*

<b>Description</b>	Too many active transaction objects allocated at this node. Each active session may have an active transaction object. In addition, the transaction controller keeps a number of objects corresponding to transactions that have committed but not yet terminated due to incomplete slave cleanup work.
<b>Action</b>	Increase the maximum number of sessions allowed per node. This will also cause a corresponding increase in the number of available transaction objects.

### *HADB01600*

<b>Description</b>	Log buffer full. This error may occur if the tuple log buffer or node-internal log buffer is too small for the applied load. When this occurs, the history files should contain information messages containing the text "HIGH LOAD" that gives a more precise description of the resource problem.
<b>Action</b>	Refer to the <i>Troubleshooting Guide</i> for information on how to tune the system to avoid resource problems.

### *HADB01616*

<b>Description</b>	This error may occur during repair or refragmentation operation if the node has a regular node that fills the log faster than the repair/refragmentation operation can process. You are likely to see HIGH LOAD messages in the history files, meaning that the internal resource control attempts to reduce the regular node.
<b>Action</b>	If this happens during a refragmentation operation, retry the operations, preferably at a time with less regular database load. If this happens during a repair, the repair is automatically retried. If the repair fails repeatedly, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> ..

### *HADB01664*

<b>Description</b>	No checkpoint log record found. The node recovery procedure failed because it was unable to find a valid checkpoint in either the node-internal log or the tuple log on that node. This may happen if the node fails very early after it started.
<b>Action</b>	No action to be taken. The node supervisor catches this error and automatically initiates a repair from the mirror node.

### *HADB01696*

<b>Description</b>	<p>Too many replicas. The pool of replica descriptors on the processing node has been exhausted. Generally, the maximum number of replicas can be calculated as the sum of replicas for each table in the database.</p> <p>For a table, the number of replicas is two multiplied by the number of nodes the table is fragmented over. The maximum number of replicas is currently fixed to 8800. Note that the required number of replicas increases when new nodes are added to a database.</p>
--------------------	--

**Action** Remove unused tables from the database. If the error occurs again, [Analyze the System](#), as described on [page 15](#)..

### *HADB01920*

**Description** Inconsistent B-tree. This error indicates an inconsistency in one of the table fragments stored at the node.

**Action** This error usually causes the node to abort, which eventually causes a repair of all data from the mirror node. Hence, no action is usually required.

### *HADB02000*

**Description** Requested fragment not found. No replicas were found for some of the fragments of a table. This indicates a pair node failure, and disaster recovery is probably needed.

**Action** See the *Administrator's Guide* for information on how to recover from session data corruption.

### *HADB02016*

**Description** No replicas were found for one or more of the fragments of a table. This indicates a pair node failure, and disaster recovery is probably needed.

**Action** See the *Administrator's Guide* for information on how to recover from session data corruption.

### *HADB02064*

**Description** One fragment replica has changed the role during operation, probably from primary to hot-standby. This may occur when the mirror node is restarted during the operation, reclaiming the primary replica of the fragment. The transaction is rolled back.

**Action** Retry the transaction.

*HADB02078*

<b>Description</b>	Wrong dictionary version number. The dictionary version that the client views is too old compared to the current global dictionary. This can be a problem for long transactions when other clients perform repeated dictionary-changing operations.
<b>Action</b>	Rollback the current transaction and retry.

*HADB02079*

<b>Description</b>	Version limit test failed. Version check performed on computing slave detected a transient mismatch between the global state of the dictionary and the state of a fragment at that particular slave. This may happen in rare circumstances when applying modifications to a table or creating or dropping indexes for a table.
<b>Action</b>	Rollback the current transaction and retry.

*HADB02080*

<b>Description</b>	Too many locks set, out of request objects.
<b>Action</b>	Increase the maximum number of concurrent locks by modifying the hadbm variable, <code>NumberOfLocks</code> . Modify the application so that it sets fewer concurrent locks. For example, split a session into more transactions, or by reduce the transaction isolation level from Repeatable Read to Read Committed.

*HADB02096*

<b>Description</b>	Too many locks held concurrently.
<b>Action</b>	Increase the maximum number of concurrent locks by modifying the hadbm variable, <code>NumberOfLocks</code> . Modify the application so that it sets fewer concurrent locks. For example, split a session into more transactions, or by reduce the transaction isolation level from Repeatable Read to Read Committed.

*HADB02097*

<b>Description</b>	Upgrade from shared to exclusive lock failed. An update to a record failed because the updating transaction was not the only transaction holding a shared lock on the record.
--------------------	---

**Action** Rollback the transaction and retry. In severe cases, you may try to run conflicting applications at different times of day, or reprogram applications so that they access and lock data so that no lock upgrades are required.

### *HADB02168*

**Description** Execution terminated at slave involved in takeover. Transaction failed because a node takeover operation has occurred during transaction execution. A node takeover operation means that one or more replicas at one of the involved node changed role from primary to hot-standby, or vice versa. This error may also occur if a transaction is attempting to access a table that is being refragmented by another transaction. The transaction is automatically rolled back.

**Action** Retry the transaction.

### *HADB02272*

**Description** Too many clients. Attempted to start too many database sessions at this transaction controller.

**Action** Try to connect to another transaction controller (you may have to replace the connect string), or increase the size of the hadbm variable, `NumberOfSessions`.

### *HADB02304*

**Description** Session has been disconnected. The transaction controller has decided to assign the session object that was allocated to your session, to another client. A session object may be reused if there is no activity within 60 seconds, and another client requests a new database session.

**Action** The immediate action should be to reconnect with the database and retry the transaction. If this problem occurs often, you should increase the size of the hadbm variable, `NumberOfSessions`.

### *HADB02320*

**Description** TCON does not accept clients. The database node has not completed initial start or restart.

**Action** Wait a short while and retry to connect to the database. If this situation persists, the offending database node has entered an invalid state. Manually restarting the node using `hadbm restartnode` may help to resolve the problem.

### *HADB02464*

**Description** Amnesia. The process has run out of virtual or physical memory. This is similar to the error, [HADB04096](#).

**Action** Increase the available memory by adding swap size or more physical memory to the computer. You may also decrease the memory consumption on the computer by moving services to another computer or decreasing the sizes of the memory buffers, for example, `DataBufferPoolSize` or `LogbufferSize`.

### *HADB03072*

**Description** Bad or missing server address or key. This error indicates that a HADB utility program has failed when connecting to the database. The HADB utility programs use the `hadbm` configuration file when deciding the parameters used to connect to the database. If this file is inconsistent with respect to the configuration files stored at each database node.

**Action** Make sure that the configuration files used by `hadbm` and those stored at the database nodes are identical. In particular, make sure that the value for the variable `clientkey` are equal and that all the lines starting with `node` are equal.

### *HADB03104*

**Description** Bad slave. This error means that one of the slave nodes involved in the transaction has failed during the transaction execution. The transaction is rolled back.

**Action** Retry the transaction.

### *HADB03504*

**Description** Node involved in current operation failed. This error means that one of the slave nodes involved in the transaction has failed during the transaction execution. The transaction is rolled back.

**Action**            Retry the transaction. You may have to investigate the cause of node failure, in case the node is not automatically restarted. This will probably involve reading history log files on the database node.

### *HADB03505*

**Description**      A relational algebra server process that was involved in the processing of a relational algebra query has failed. This error should be detected by the node supervisor, which will immediately restart a new relational algebra server.

**Action**            Retry the operation. If the error persists, [Analyze the System](#), as described on [page 15](#)..

### *HADB03508*

**Description**      All relational algebra server processes defined for the database have failed, and the request cannot be processed.

**Action**            You may retry the operation at a later time, but a more likely action is to investigate why all relational algebra server processes have failed simultaneously. This will probably involve reading history log files on the database nodes, or [Analyze the System](#), as described on [page 15](#)..

### *HADB03840*

**Description**      No replicas were found for one of the fragments of a table. This indicates a pair node failure, and disaster recovery is probably needed.

**Action**            See the *Administrator's Guide* for description of how to recover from session data corruption, for possible actions.

### *HADB04096*

**Description**      Out of space. The process has run out of virtual or physical memory. This is similar to error [HADB02464](#).

**Action**            Increase the available memory by adding swap size or more physical memory to the computer. You may also decrease the memory consumption on the computer by moving services to another computer or decreasing the sizes of the memory buffers. For example, `DataBufferPoolSize` or `LogbufferSize`.

*HADB04362*

<b>Description</b>	Too many tables. The maximum number of tables that can be created in the database dictionary has been reached.
<b>Action</b>	Increase the value of the hadbm variable, <code>MaxTables</code> , or remove unused existing tables, before retrying the create table operation.

*HADB04576*

<b>Description</b>	Client held transaction open for too long. The transaction controller has rolled back the transaction because it was idle a too long time.
<b>Action</b>	You can specify a longer transaction idle time from the client. In the JDBC, set the property <code>maxtransidle</code> . In the ODBC, set the ODBC ini string <code>maxtransidle</code> . In <code>Clusql</code> , use the SQL command <code>SET TRANSACTION IDLETIME</code> . A likely cause of this error may be that the previous transaction was not committed.

*HADB04592*

<b>Description</b>	No free blocks on data devices. The data device(s) of one or more nodes involved in the operation has no more free blocks. This is a critical operational error that calls for immediate action.
<b>Action</b>	<p>You must always locate node(s) having no free blocks. Use the command <code>hadbm deviceinfo</code> and look for nodes that have a low number of free blocks. Note that because HADB tries to spread data evenly across all active nodes, it is likely that all nodes will reach critical storage space situation almost simultaneously. To resolve the problem, try one or more of the following procedures:</p> <ul style="list-style-type: none"> <li>• Reclaim storage space by removing unused tables.</li> <li>• Extend existing devices by increasing the value of the hadbm variable <code>TotalDatadeviceSizePerNode</code>. (You need to verify that the disk devices have sufficient free space before executing this procedure).</li> </ul>

*HADB04593*

<b>Description</b>	No unreserved blocks on data devices. The data device(s) of one or more nodes involved in the operation has no more unreserved blocks. To a user, this error is similar to error <a href="#">HADB04592</a> . This is a critical operational error that calls for immediate action.
--------------------	--



- Action** You must always locate node(s) having no free blocks. Use the command `hadbm deviceinfo` and look for nodes that have a low number of free blocks. Note that because HADB tries to spread data evenly across all active nodes, it is likely that all nodes will reach critical storage space situation almost simultaneously. To resolve the problem, try one or more of the following procedures:
- Reclaim storage space by removing unused tables.
  - Extend existing devices by increasing the value of the `hadbm` variable `TotalDataDeviceSizePerNode`. (You need to verify that the disk devices have sufficient free space before executing this procedure).

### *HADB04640*

- Description** Refrag table requires all nodes to be up and running. A refragmentation requires that all the nodes involved in the operation (both in the old and the new node group) are running.
- Action** Make sure that all nodes are active and retry the operation, or refragment to a set of nodes that are running.

### *HADB04656*

- Description** A backup or restore operation, or a table creation, deletion or modification operation cannot be started when a backup operation is active inside the database.
- Action** Wait until the current backup operation is finished.

### *HADB04672*

- Description** A backup or restore operation cannot be started when a restore operation is already active inside the database.
- Action** Wait until the current backup operation is finished.

### *HADB04688*

- Description** Node-internal log buffer too small. The database node failed to start because the node-internal log buffer is too small.

**Action** Set the size of the node-internal log buffer (hadbm variable `InternalLogBufferSize`) as outlined in the *Administrator's Guide*.

### *HADB04752*

**Description** Too many fragment replicas at one node. When creating a table, you cannot specify more fragments than the number of nodes it is created over. It is not allowed to create more than one primary fragment per node.

**Action** Reduce the number of fragments in the create table statement so that it is not greater than the number of nodes in the nodegroup.

### *HADB04768*

**Description** No backup service available at node. The backup or restore operation cannot be started because there is no backup service available at the specified node.

**Action** Start the operation where a backup service is active.

### *HADB05500*

**Description** An attempt to open or create a file failed. The error message includes the name of the file and an operating system-specific error code. Normal reasons for this error are file not found or permission denied, and these reasons indicate misconfigurations or damaged storage devices.

**Action** A misconfiguration must be resolved by following procedures documented in the *Administrator's Guide*, possibly by re-applying the offending command with the correct file name(s).

### *HADB05501*

**Description** An attempt to close a file failed. The error message includes an operating system-specific error code.

**Action** [Analyze the System](#), as described on [page 15](#)..

*HADB05502*

<b>Description</b>	An attempt to read a file failed. The error message includes an operating system-specific error code. Normal reasons for this error are damaged storage devices.
<b>Action</b>	You need to replace possible damaged storage devices. Follow procedures in the <i>Administrator's Guide</i> to reconstruct missing configurations and data.

*HADB05503*

<b>Description</b>	An attempt to write data to a file failed. The error message includes an operating system-specific error code. Normal reasons for this error are damaged storage devices.
<b>Action</b>	You need to replace possible damaged storage devices. Follow procedures in the <i>Administrator's Guide</i> to reconstruct missing configurations and data.

*HADB05504*

<b>Description</b>	A control operation on an open file failed. The error message includes an operating system-specific error code. Possible reasons for this error are unavailable remote storage devices.
<b>Action</b>	Try to resolve this problem using the operating system documentation. If you are unable to do so, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*HADB05505*

<b>Description</b>	An attempt to execute a file failed. The Node Supervisor (NSUP) attempted to create a new server process, but failed to execute a new program image. The error message includes the name of the file and an operating system-specific error code. The most likely causes for this error are lack of physical or virtual memory or an incorrect path to the executable program.
<b>Action</b>	Install more physical memory on the computer. Increase the swap space available for the computer. Reduce the load on the computer, such as by moving HADB nodes or other computing services to other computers. Check that the path to the executable program that NSUP tries to start is valid.

### *HADB05506*

- Description** An attempt to perform an asynchronous operation on a file failed. The error message includes an operating system-specific error code. Normal reasons for this error are damaged storage devices.
- Action** You need to replace possible damaged storage devices. Follow procedures in the *Administrator's Guide* to reconstruct missing configurations and data.

### *HADB05510*

- Description** Creating or getting access to an existing shared memory segment failed. The error message includes an operating system-specific error code. Possible problems include: the segment already exists (if a previous instance was not completely cleaned up, or another application uses the same shared memory key), access problems (also if the segment already exists), lack of memory (that is, there is not sufficient virtual or physical memory to create the segment), or maximum shared memory segment size is configured too small for the requested segment size.
- Action** Make sure that old instances have been properly cleaned up. Make sure that other applications does not use the same shared memory key. Use the command `ipcs(1)` to list the existing shared memory segments. You may have to define a different shared memory segment key for HADB nodes (see *Administrator's Guide*). You may have to add physical or virtual memory to the computer, or move HADB instances to other computers. You may have to increase the maximum shared memory size for the computer (see the *Installation Guide*).

### *HADB05511*

- Description** A control operation on a shared memory segment, such as retrieving the size of the segment or removing the segment, failed. The error message includes an operating system-specific error code.
- Action** Consult the operating system documentation for information on how to resolve this problem.

### *HADB05512*

- Description** Attaching a process to a shared memory segment failed. The error message includes an operating system-specific error code. This error may indicate that there is not enough physical or virtual memory to map the memory segment.

**Action** Consult the operating system documentation for information on how to resolve this problem. You may have to increase the physical memory on the computer, or increase the swap space. You may also work around the problem by reducing the HADB data or log buffer sizes.

### *HADB05513*

**Description** Detaching a process from a shared memory segment failed. The error message includes an operating system-specific error code. There are no common reasons for this error.

**Action** Consult the operating system documentation for information on how to resolve this problem.

### *HADB05514*

**Description** A control operation on a shared memory segment failed. The error message includes an operating system-specific error code. There are no common reasons for this error.

**Action** Consult the operating system documentation for information on how to resolve this problem.

### *HADB05520*

**Description** Creating a semaphore failed. The error message includes an operating system-specific error code. The error code may indicate a lack of semaphore resources or that you tried to create a semaphore that already exists.

**Action** You may have to increase the number of semaphore resources on your computer. Instructions are provided in the *Installation Guide*. Otherwise, consult the operating system documentation for information on how to resolve this problem.

### *HADB05521*

**Description** An operation on a semaphore, such as obtaining the status of a semaphore or acquiring or releasing a semaphore, failed. The error message includes an operating system-specific error code. This error code may indicate a lack of semaphore resources.

**Action** You may have to increase the number of semaphore resources on your computer. Instructions are provided in the *Installation Guide*. Otherwise, consult the operating system documentation for information on how to resolve this problem.

### *HADB05522*

**Description** Removing a semaphore failed. The error message includes an operating system-specific error code.

**Action** Consult the operating system documentation for information on how to resolve this problem.

### *HADB05530*

**Description** Creating a socket failed. The operating system error code associated with this error indicates the problem. Most likely this is a resource problem, such as the pool of socket descriptors is full.

**Action** The operating system error code determines the action to take.

### *HADB05531*

**Description** A control operation on a socket failed. The operating system error code associated with this error indicates the problem.

**Action** The operating system error code determines the action to take.

### *HADB05532*

**Description** Removing a socket failed. The operating system error code associated with this error indicates the problem.

**Action** The operating system error code determines the action to take.

### *HADB05533*

- Description** An attempt to receive data on a UDP port failed. The error message displays an operating system-specific error code.
- Action** Check the operating system-specific error code for information about the error.

### *HADB05534*

- Description** An attempt to send data on a UDP port failed. The error message displays an operating system-specific error code.
- Action** Check the operating system-specific error code for specific information about the error.

### *HADB05540*

- Description** Creating a message queue failed. The error message displays an operating system-specific error code, which may indicate insufficient message queue resources or you tried to create a message queue with a key that already in use.
- Action** You may have to increase the number of message queue resources on your computer. Instructions are provided in the *Installation Guide*. Otherwise, consult the operating system documentation for information on how to resolve this problem.

### *HADB05541*

- Description** Removing a message queue failed. The error message displays an operating system-specific error code.
- Action** Consult the operating system documentation for information on how to resolve this problem.

### *HADB05542*

- Description** Sending a message to a message queue failed. The error message displays an operating system-specific error code.

**Action** Consult the operating system documentation for information on how to resolve this problem.

### *HADB05543*

**Description** Receiving a message from a message queue failed. The error message displays an operating system-specific error code.

**Action** Consult the operating system documentation for information on how to resolve this problem.

### *HADB05544*

**Description** A control operation on a message queue failed. The error message displays an operating system-specific error code.

**Action** Consult the operating system documentation for information on how to resolve this problem.

### *HADB05550*

**Description** A call to an operating system routine failed. The error message displays the name of the routine as well as the operating system error code.

**Action** Consult the operating system documentation for information on how to resolve this problem.

### *HADB05551*

**Description** Creating a process failed. The Node Supervisor (NUSP) attempted to create a new server process, but failed to fork a new process. The most likely errors are lack of process slots and lack of physical or virtual memory.

**Action** Increase the number of processes and reboot the system. Install more physical memory on the computer. Increase the swap space available for the computer. Reduce the load on the computer, such as by moving HADB nodes or other computing services to other computers.



*HADB05552*

<b>Description</b>	Looking up the address of an Internet resource specified with Internet address and port number failed. The error message displays an operating system-specific error code.
<b>Action</b>	Consult the operating system documentation for information on how to resolve this problem.

*HADB05570*

<b>Description</b>	Creating a thread inside a multi-threaded process failed. The error message displays an operating system-specific error code.
<b>Action</b>	Consult the operating system documentation for information on how to resolve this problem.

*HADB05571*

<b>Description</b>	Destroying a thread inside a multi-threaded process failed. The error message displays an operating system-specific error code.
<b>Action</b>	Consult the operating system documentation for information on how to resolve this problem.

*HADB05572*

<b>Description</b>	A synchronization operation on a thread inside a multi-threaded process failed. The error message displays an operating system-specific error code.
<b>Action</b>	Consult the operating system documentation for information on how to resolve this problem.

*HADB05573*

<b>Description</b>	Sending a continuation signal to a thread inside a multi-threaded process failed. The error message displays an operating system-specific error code.
<b>Action</b>	Consult the operating system documentation for information on how to resolve this problem.

*HADB05580*

<b>Description</b>	Allocating a segment of memory failed. The error message displays an operating system-specific error code.
<b>Action</b>	You may have to increase the physical memory or swap space associated with the computer.

*HADB11110*

<b>Description</b>	Sequential file is damaged. The sequential file being read is unreadable. This may occur if the file being read is assumed to be a text file but is actually a binary file, if the file has been truncated in the middle of a logical record, and so on.
<b>Action</b>	The file that you are trying to read is not usable. You need to find the appropriate file or reconstruct the file from other sources.

*HADB11112*

<b>Description</b>	The file or file system containing the relational algebra temporary storage device is full, and no more blocks can be allocated from it. You may move the storage device to a larger disk.
<b>Action</b>	You must create a larger file for the relational algebra temporary storage device. You may need to allocate a larger storage device, if the currently allocated space is insufficient.

*HADB11304*

<b>Description</b>	Key is too large. The row to be inserted or updated is greater than 8080 bytes.
<b>Action</b>	If you have control over the database schema, consider to split the offending table in two, or convert some large character or binary columns into CLOB or BLOB columns. If you do not have control over the database schema, consider truncating some of the variable-sized fields in the row, or inform the application provider of this problem.

### *HADB11309*

- Description** Too many statement handles allocated. The database session attempted to allocate more than 8000 statement handles.
- Action** Make sure that you close the statement handles when they are no longer used.

### *HADB11311*

- Description** Unique index could not be created. There are duplicate values in columns specified in a `CREATE UNIQUE INDEX` statement. The index could not be created.
- Action** Remove duplicate values from the table. Create a non-unique index instead of a unique index.

### *HADB11320*

- Description** Key is too large. The row to be inserted or updated has a primary key that is greater than 1024 bytes, or the secondary key fields of the row (for any secondary index), are greater than 1024 bytes.
- Action** If you have control over the database schema, consider to use a different primary key definition, or remove secondary indexes created over very large columns. If you do not have control over the database schema, consider truncating some of the variable-sized fields in the row, or inform the application provider of this problem.

### *HADB11402*

- Description** String not terminated. A string must be enclosed in single quotes. A delimited identifier must be enclosed in double quotes. The last quote is missing in the current statement.
- Action** Make sure that the string is terminated with a single quote or double quote character.

*HADB11403*

- Description** Illegal special character. The specified character cannot be used in this context. Apart from alphabetic and numeric characters, the following characters are allowed outside of character strings in the SQL syntax: '\_', '#', '<', '>', '=', ':', ',', ';', ':', '"', "'", '!', '?', '+', '-', '\*', '/', '%', '|', '\', '(', ')', '[, ]', space character.
- Action** Make sure that your SQL string contains only valid special characters.

*HADB11404*

- Description** Specified string argument is too long. The string argument supplied is longer than 32000 characters.
- Action** Make sure that the string argument is not longer than the limit.

*HADB11405*

- Description** String is too long.
- Action** A string specified in the statement is longer than the allowed maximum size. Filenames can be maximum 256 characters wide.

*HADB11406*

- Description** Syntax error in symbol specification. A syntactical error was found in the supplied text argument. A hexadecimal constant value was not terminated with a quote character.
- Action** Make sure that the symbol has proper syntax.

*HADB11407*

- Description** Non-delimiter token must be followed by a delimiter token or separator. The statement contains two consecutive non-delimiter tokens which must have an intermittent separator, such as a space character or a line break.
- Action** Insert appropriate separators between non-delimiter tokens.

*HADB11521*

<b>Description</b>	Table definition has changed, prepared statement invalid. The SQL server was not able to automatically re-prepare a statement. The layout of one or more tables that are part of the statement has changed, and, when preparing the statement, it was found that the types of columns selected from the tables had changed.
<b>Action</b>	You must terminate and restart the application.

*HADB11601*

<b>Description</b>	Invalid user password. Login not accepted because user name or password is incorrect.
<b>Action</b>	Add the missing user name and password to the database, or use the correct user name and password combination.

*HADB11602*

<b>Description</b>	An operation that requires auto commit mode was attempted in the manual commit mode. Operations that require auto commit mode are: <ul style="list-style-type: none"> <li>• create/drop index</li> <li>• table refragmentation</li> </ul>
<b>Action</b>	Set the connection to <code>autocommit</code> mode, and retry the operation.

*HADB11608*

<b>Description</b>	Too many users, login rejected The defined maximum number of users are already logged in to the database. Wait some time before trying a new login. Contact the database administrator (DBA) if this situation persists. You may need to increase the configuration file parameter <code>nsessions</code> .
<b>Action</b>	Reconfigure the HADB to allow more user connections. Ensure that all clients disconnect from the HADB properly before terminating. A client which exits without closing the connection to HADB occupies resources until HADB decides to time-out the connection. The default timeout is 30 minutes of idle time.

*HADB11619*

<b>Description</b>	Too many global table descriptors. Space is exhausted in the shared memory segment used for SQL dictionary cache. The SQL query cannot be prepared or executed. Note that this memory segment is shared between all connections on a given HADB node.
<b>Action</b>	Change the application(s) to use fewer tables, or increase the size of the dictionary cache.

*HADB11646*

<b>Description</b>	The maximum total line length has been exceeded. The maximum length is 32000 characters. Note that in order to have lines longer than 255 characters, you need to split them up into several lines no longer than 255 characters and terminate the last line with a semicolon.
<b>Action</b>	Rewrite the SQL query.

*HADB11657*

<b>Description</b>	Reported by <code>clsql</code> if it reaches end-of-file before reading the SQL query termination token “;”. Query will not be prepared or executed.
<b>Action</b>	Terminate all queries with “;”.

*HADB11662*

<b>Description</b>	Invalid transaction state.  An attempt was made to perform an INSERT, UPDATE or DELETE operation on a permanent table, and the current transaction is in read only mode. Also a transaction may be active when the SET TRANSACTION command is executed.
<b>Action</b>	Set the connection in read-write mode if transactions need to modify the database.

*HADB11666*

- Description** This error is reported by `clusql` if `control-c` is entered at the SQL: prompt. The application is terminated. Note that queries that have been submitted, cannot be canceled (by `control-c` or by other means).
- Action** Use `quit` or `exit` to terminate `clusql`.

*HADB11701*

- Description** Table not found.  
No table or view with the given name exists in the database.
- Action** Ensure that current schema is correct, and that the table name is correct.

*HADB11703*

- Description** Table type not found.  
The table type with the specified name does not exist in the database.
- Action** If you have used the `create tabletype ...` and `create table <table name> tabletype <table type>`, then verify that the names used are correct. If the problem persists, [Analyze the System](#), as described on [page 15](#)..

*HADB11704*

- Description** Column not found.  
Column does not exist within the tables, views, or table types specified in the current command.
- Action** Check the spelling of the column names.

*HADB11707*

- Description** A table type cannot be altered or dropped because at least one table is using the type.
- Action** Drop tables using the table type.

*HADB11708*

**Description** Table name is not recognized as a schema.

**Action** Check the table name. Create the missing schema.

*HADB11709*

**Description** Schema is not empty.  
The schema cannot be dropped because there is at least one table or view in it.

**Action** Drop the contents of the schema before dropping the schema.

*HADB11711*

**Description** Table exists already  
A table or view with the supplied name exists already. Supply a unique name when creating or modifying a table.

**Action** Supply a unique name when creating or modifying a table.

*HADB11713*

**Description** Insufficient privilege for attempted operation.  
Operation cannot be performed with existing user privilege and access rights.

**Action** Grant access rights to the current user, or connect as a different user with appropriate rights.

*HADB11714*

**Description** Double declaration in dictionary definition.  
The definition portion of a Data Dictionary creation or modification command contains a double declaration.

**Action** Each declaration in a dictionary command (such as OWNER) can be specified only once.



*HADB11715*

- Description** No table type was specified in a CREATE TABLE command and the table specification does not include a column definition list.  
A table type name and a column definition list must be specified when creating a table.
- Action** Create the table type first, or create the table with a column definition list.

*HADB11716*

- Description** Illegal organization of table.  
Table must be organized as INDEXED or SEQUENTIAL.
- Action** Table organization must be specified as indexed or sequential. Only indexed tables are supported. Although sequential is accepted it is ignored.

*HADB11717*

- Description** Illegal fill level specified.  
Fill level must be greater than 0% and less than or equal to 100%.
- Action** Fill level must be greater than 0% and less than or equal to 100%.

*HADB11718*

- Description** User cannot be owner of resource.  
A user needs System or Total privilege to become the owner of an index, a table, view, table type, application or nodegroup.
- Action** Grant appropriate access rights, or connect as a different user.

*HADB11721*

- Description** Table type exists already.  
The table type name cannot be used because a table type with this name already exists in the database.

**Action** Supply a unique name when creating or modifying a table type.

### *HADB11723*

**Description** No primary key specified.  
A table created with INDEXED organization (implicitly or explicitly) must contain a primary key.

**Action** All tables stored in HADB must have a primary key.

### *HADB11725*

**Description** Sequence, column, or group cannot be a key.  
A column of this type cannot be a primary or secondary key column.

**Action** Columns of type decimal or real cannot be indexed. Use other columns as primary or secondary keys.

### *HADB11726*

**Description** Illegal to add, change or remove key column.  
A column which is part of the primary key of a table cannot be altered or dropped. It is also illegal to add new columns to the primary key definition. It is, however, legal to rename a key column.

**Action** Drop and recreate the table with the new column definitions.

### *HADB11727*

**Description** It is illegal to change a column's basic type, for example, a numeric column cannot be changed into a character column. It is, however legal to change between any data type and the data type byte of the same size, for example, from integer to byte (4) and vice versa. In this case, no actual data conversion is performed.

**Action** The cast function can be used for data conversion in many cases.

*HADB11733*

- Description** Column and field names cannot be used twice when declaring the column list of a table type.
- Action** Supply a unique name when creating or modifying a table.

*HADB11734*

- Description** Illegal length, precision or scale.
- The length of CHAR, VARCHAR, BINARY and VARBINARY columns must be greater than 0 and less or equal to 8000 characters (bytes). The precision of a DECIMAL column must be greater than 0 and less than or equal to 31 digits. The scale of a DECIMAL column cannot be greater than the precision. The binary precision of a real column cannot be greater than the implementation-defined maximum precision of a 64 bit floating point datum. (The IEEE standard specifies this as 52).
- The seconds precision of a TIME or TIMESTAMP column cannot be greater than six. The leading precision and seconds precision of an INTERVAL column cannot be greater than six.
- Action** Rewrite your table definition to comply with the rules described.

*HADB11735*

- Description** Illegal data type specified in column definition.
- Action** Use only supported data types in table definitions and in cast/convert queries.

*HADB11736*

- Description** Too many columns in key.
- A primary or secondary key consisting of more than 16 columns cannot be defined.
- Action** Rewrite your table definition.

*HADB11738*

<b>Description</b>	Too many columns. Number of columns within the table type exceeds 255.
<b>Action</b>	Re-write your table definition.

*HADB11740*

<b>Description</b>	A system table (a table with a table ID less than 1000) cannot be deleted.
<b>Action</b>	No action to be taken.

*HADB11742*

<b>Description</b>	The specified user name is already defined in the database.
<b>Action</b>	Supply a unique name when creating or modifying users.

*HADB11743*

<b>Description</b>	The specified user name does not exist in the database.
<b>Action</b>	Make sure you enter the correct user name.

*HADB11744*

<b>Description</b>	During an attempt to create or modify a user, the user definition contained a syntax error.
<b>Action</b>	No action to be taken.

*HADB11745*

<b>Description</b>	Attempt to drop system defined user. The system defined user created with the name SYSTEM when a database is initialized cannot be removed from the database.
<b>Action</b>	No action to be taken.

*HADB11747*

<b>Description</b>	Nodegroup exists already.
<b>Action</b>	Supply a unique name when creating new node groups.

*HADB11748*

<b>Description</b>	The nodegroup name given cannot be found.
<b>Action</b>	Ensure that the supplied node group name is correct.

*HADB11751*

<b>Description</b>	The schema could not be created because a schema with the same name exists already.
<b>Action</b>	Supply a unique name when creating a new schema.

*HADB11755*

<b>Description</b>	No schema with the given name exists in the database.
<b>Action</b>	Ensure that the schema name is correct.

*HADB11757*

<b>Description</b>	An attempt was made to delete a schema which is essential for operation of the database.
--------------------	--

**Action** No action to be taken.

### *HADB11759*

**Description** When attempting to change the layout of a table, and the change is not cosmetic (for example, rename a column), the table type must be used by this table.

**Action** If several tables use the same table type, you must create a new table type and then convert the table to the new table type with the statement. `ALTER TABLE t type = new_type.`

### *HADB11761*

**Description** The specified index does not exist.

**Action** Ensure that current schema is correct, and that the index name is correct.

### *HADB11762*

**Description** An attempt was made to create an index with a name that already exists.

**Action** Supply a unique name when creating an index.

### *HADB11763*

**Description** The name of an index is required in this operation. The specified name does not refer to an index.

**Action** Ensure that current schema is correct, and that the index name is correct.

### *HADB11768*

**Description** An attempt was made to revoke several privileges from a user, but some or all of the privileges could not be revoked. This is probably because not all of the revoked privileges were granted to the user originally.

**Action** Privileges defined for a user can be obtained from `DatabaseMetaData.getColumnPrivileges()` and `DatabaseMetaData.getTablePrivileges()` in the JDBC.

### *HADB11770*

**Description** You do not have the privileges necessary to grant some or all of the specified privileges. Only those privileges that you are granted 'with grant option' have been granted.

**Action** Privileges defined for a user can be obtained from `DatabaseMetaData.getColumnPrivileges()` and `DatabaseMetaData.getTablePrivileges()` in the JDBC.

### *HADB11773*

**Description** The user to whom you granted the privilege(s) has passed them on to another user.

**Action** Use `revoke` with the `cascade` clause to revoke the whole chain of privileges that has resulted from your original grant statement.

### *HADB11775*

**Description** You can specify `with check option` only when creating a view that can be updated.

**Action** Views involving more than one table cannot be updated in HADB. Note that the `with check option` is not currently enforced.

### *HADB11776*

**Description** The specified table, view or column cannot be dropped because there are other views or restrictions that depend on the specified resource.

**Action** Use the `cascade` option to drop the table, view or column and all dependent views and restrictions.

*HADB11778*

- Description** Only one primary key constraint is allowed.
- Action** You can specify the primary key option for only one column, or once with a list of columns specified within parentheses.

*HADB11779*

- Description** The specified revoke statement would cause some privileges implicitly granted by a 'create view' statement to be revoked.
- Action** Using revoke with the cascade option will force the privileges to be revoked, and may cause the views to be dropped because they are no longer visible.

*HADB11782*

- Description** No view with the given name exists in the database (in the current schema).
- Action** Ensure that current schema is correct, and that the view name is correct.

*HADB11783*

- Description** A view with the supplied name exists already.
- Action** Supply a unique name when creating a view.

*HADB11784*

- Description** You specified an operation that required a table, but the name that you specified refers to a view or a schema.
- Action** Ensure that the current schema is correct, and that the table name is correct.

*HADB11787*

- Description** It is not legal to drop a user who owns schemas, tables or table types.



**Action** Drop the entities owned by the user before dropping the user.

### *HADB11790*

**Description** Columns of 'interval' data type cannot have default values.

**Action** Rewrite your table definition.

### *HADB11796*

**Description** An illegal access priority was specified for create table or alter table.

**Action** Use one of the legal values.

### *HADB11798*

**Description** Too many nodes specified in a `create nodegroup` statement.

**Action** Do not specify more than the actual number of running nodes.

### *HADB11901*

**Description** Table is too large for operation. The result of a 'group by' operation is too large to fit in main memory buffers.

**Action** Increase the value of the config variable `relalg_workspace_size`, and restart `clu_relalg_srv` on all nodes.

### *HADB11903*

**Description** Trim character must be a single character. The `trim()` function was called with a `<trim character>` string with length different from 1.

**Action** Use a string with a single character.

*HADB11905*

**Description** Substring length is negative. The `substring( )` function was called with a `<start position>` value that was less than 1.

**Action** Rewrite your SQL query.

*HADB11907*

**Description** Overflow in string field. A string concatenation, conversion or assignment caused a result string that exceeded the maximum length expected for the target string.

**Action** Rewrite your SQL query, or alter the table(s) involved.

*HADB11908*

**Description** Numeric value out of range. An arithmetic operation or a conversion into a numeric data type created a value that was outside the range of the data type of the result of the operation.

**Action** Rewrite your SQL query, or alter the table(s) involved.

*HADB11909*

**Description** An attempt to divide a number by zero was made.

**Action** Check your data or rewrite your query so that division by zero cannot occur.

*HADB11910*

**Description** Invalid character value for cast. Conversion from a character field to a numeric field failed because an invalid character was found in the character field.

**Action** Check your data.

### *HADB11914*

<b>Description</b>	The specified date and time field (date, time or timestamp) was not valid. Possible reason may be because a date field specified a month value greater than 12.
<b>Action</b>	Check your data.

### *HADB11915*

<b>Description</b>	The specified interval field was not valid. Possible reason may be because an <code>interval hour to second</code> field specified a minute or second value greater than 59.
<b>Action</b>	Check your data.

### *HADB11916*

<b>Description</b>	A time zone interval value expression specified in a datetime expression with the <code>at time zone</code> construct, or in a <code>set time zone</code> command, must be greater than or equal to -12:59 and less than or equal to +13:00.
<b>Action</b>	Check your data or command.

### *HADB11917*

<b>Description</b>	A null value was attempted to be assigned to a column that was defined with a <code>Not Null</code> constraint.
<b>Action</b>	Check your data.

### *HADB11918*

<b>Description</b>	A dynamic parameter that was required for the execution of this query was not supplied.
<b>Action</b>	Check your client application.

### *HADB11919*

<b>Description</b>	A conversion to a date, time or timestamp field from a string expression failed because the string expression was not in the correct datetime format. This may occur in a cast expression or when converting from a user-defined character field to a data time field.
<b>Action</b>	Check your data.

### *HADB11920*

<b>Description</b>	A source string was retrieved into a target string that was smaller than the size of the source string. The source string was right truncated so that it fit into the size of the target string.
<b>Action</b>	Check your data.

### *HADB11921*

<b>Description</b>	A set function (count, min, max, sum, avg) was executed and one or more value expressions contained in the set function specification evaluated to NULL and was eliminated before applying the set function.
<b>Action</b>	Check your data.

### *HADB11924*

<b>Description</b>	An SQL query containing a scalar subquery was performed, but the scalar subquery returned more than one row.
<b>Action</b>	Check your data and/or client application. You need to specify a scalar subquery that returns a maximum of one row.

### *HADB11927*

<b>Description</b>	A conversion to an interval field from a string expression failed because the string expression was not in the correct interval format. This may occur in a cast expression or when converting from a user-defined character field to an interval field.
--------------------	--

**Action** Check your data.

### *HADB11939*

**Description** An attempt was made to insert a row with a primary key which already was in use by another row.

**Action** Use unique values for primary keys.

### *HADB12001*

**Description** HADB was unable to allocate more virtual memory from the operating system.

**Action** Decrease the load on the host(s) where HADB is running. Extend physical and/or virtual memory on the host(s). Use unique values for primary keys.

### *HADB12002*

**Description** Expressions can be nested up to 256 levels.

**Action** Rewrite your SQL query.

### *HADB12003*

**Description** Space is exhausted in the shared memory segment used for SQL dictionary cache. The SQL query cannot be prepared or executed. Note that this memory segment is shared between all connections at a given HADB node.

**Action** Change the application(s) to use fewer tables, or increase the size of the dictionary cache.

### *HADB12004*

**Description** An internal error has occurred while allocating memory.

**Action** [Analyze the System](#), as described on [page 15](#).

*HADB12005*

**Description** An error has occurred while trying to allocate memory from the operating system. An operating system specific error code is usually also displayed in an adjacent message.

**Action** [Analyze the System](#), as described on [page 15](#).

*HADB12006*

**Description** An internal error has occurred while allocating memory.

**Action** [Analyze the System](#), as described on [page 15](#).

*HADB12301*

**Description** Import of table contents from file (bulk load) failed because of inconsistent input data.

**Action** Verify the contents of the input file.

*HADB12302*

**Description** Import of table contents from file (bulk load) failed because of inconsistent input data.

**Action** Verify the contents of the input file.

*HADB12303*

**Description** Import of table contents from file (bulk load) failed because of inconsistent input data.

**Action** Verify the contents of the input file.

*HADB12304*

<b>Description</b>	Import of table contents from file (bulk load) failed because of inconsistent input data.
<b>Action</b>	Verify the contents of the input file.

*HADB12305*

<b>Description</b>	Import of table contents from file (bulk load) failed because of inconsistent input data.
<b>Action</b>	Verify the contents of the input file.

*HADB12306*

<b>Description</b>	Import of table contents from file (bulk load) failed because of inconsistent input data.
<b>Action</b>	Verify the contents of the input file.

*HADB12307*

<b>Description</b>	Import of table contents from file (bulk load) failed because of inconsistent input data. The bulk load operation was terminated.
<b>Action</b>	Verify the contents of the input file.

*HADB12317*

<b>Description</b>	The table import/export was successfully completed, with some warnings about data conversion errors.
<b>Action</b>	Verify the contents of the input/output file.

*HADB12319*

**Description** Invalid import or export specification.  
**Action** Verify your import/export command.

*HADB12320*

**Description** Import of table contents from file (bulk load) failed because of inconsistent input data.  
**Action** Verify the contents of the input file.

*HADB12321*

**Description** Import of table contents from file (bulk load) failed because of inconsistent input data.  
**Action** Verify the contents of the input file.

*HADB12322*

**Description** Invalid import or export specification.  
**Action** Verify your import/export command.

*HADB12323*

**Description** Invalid import or export specification.  
**Action** Verify your import/export command.

*HADB12324*

**Description** The parameters supplied for a prepared query occupies more than 32000 bytes.  
**Action** Rewrite the client application.



### *HADB12401*

- Description** The operands in this expression do not have compatible data types. Integers cannot be compared with character strings, and so on.
- Action** Sometimes you can get around this problem by using the cast or convert function. For example, a character string that contains all numeric characters can be cast into an integer.

### *HADB12402*

- Description** The current SQL statement contains a syntax error.
- Action** Verify your SQL statement.

### *HADB12403*

- Description** The number of values specified in an `insert into` statement must conform to the number of columns of the table to insert into.
- Action** Verify your SQL statement.

### *HADB12404*

- Description** An SQL query was submitted in an illegal context, for example in JDBC: `statement.executeUpdate("select * from t")`.
- Action** Verify your client application.

### *HADB12406*

- Description** The specified column was found in more than one table.
- Action** Prefix the column name with the name of the correct table and a period (.).

### *HADB12407*

- Description** An expression in an `order by` list must be a number greater than 0 and less or equal to the number of columns selected, or a valid expression containing columns present in the select list.
- Action** Verify your client application.

### *HADB12408*

- Description** An aggregate expression is used in the wrong context. For example, `select sum(i) from t where sum(i)>0`.
- Action** Verify your client application.

### *HADB12411*

- Description** A subquery is contained in one of the branches of an `or` clause, or inside the `<join specification>` of a joined table clause.
- Action** Rewrite your SQL query.

### *HADB12412*

- Description** The expression is too complex to be evaluated, due to limitations in HADB SQL.
- Action** Rewrite your SQL query.

### *HADB12413*

- Description** When aggregated expressions are specified in a `select` statement, the grouping columns are the only individual columns that can be retrieved in the result, in addition to the aggregated expressions.
- Action** Verify your client application.

### *HADB12416*

- Description** An attempt was made to exceed an implementation defined limit. HADB cannot handle more than 100 users in a single GRANT or REVOKE statement.
- Action** Rewrite your SQL grant/revoke command.

### *HADB12422*

- Description** The same column name was used more than once when a unique name was required. This can occur inside a view definition, update clause or column alias list.
- Action** Verify your SQL statement.

### *HADB12423*

- Description** The number of column aliases in an alias list does not match the number of columns in the corresponding table expression.
- Action** Verify your SQL statement.

### *HADB12424*

- Description** A column that is found in both tables specified in a join expression and is used as a join column cannot be referenced with a table alias prefix. Such a column must be referenced with column name alone, without any table alias.
- Action** Verify your SQL statement.

### *HADB12427*

- Description** When specifying a table set operation (UNION, INTERSECT or EXCEPT), the select list of both select statements must contain the same number of expressions.
- Action** Verify your SQL statement.

*HADB12428*

**Description** When using the CORRESPONDING BY clause in a table set operation, the corresponding column(s) must be part of the select list from both SELECT statements participating in the set operation.

**Action** Verify your SQL statement.

*HADB12430*

**Description** When using the CORRESPONDING BY clause in a table set operation, the select lists of the two SELECT statements involved must contain at least one column with the same name.

**Action** Verify your SQL statement.

*HADB12432*

**Description** You are attempting to grant or revoke table privileges on a non-table entity, or you are attempting to grant or revoke USAGE privileges on a table entity.

**Action** Verify your SQL statement.

*HADB12433*

**Description** You can delete, insert or update rows in a view only if the view can be updated.

**Action** Views involving more than one table cannot be updated in HADB. Verify your SQL statement.

*HADB12434*

**Description** When creating a view, a view column list is required if referenced columns have system-generated names. This occurs if referenced column is an expression or if two or more referenced columns have equal names.

**Action** Verify your SQL statement.

*HADB12435*

- Description** When using a table subquery as part of a comparison clause, the table subquery must contain the same number of expressions in its select list as there are expressions in the list being compared with.
- Action** Verify your SQL statement.

*HADB12437*

- Description** Aggregate functions cannot be nested. For example, it is illegal to specify `sum(sum(column))`. Aggregate functions cannot contain subqueries or grouped columns.
- Action** Verify your SQL statement.

*HADB12440*

- Description** The internal definition of the view that was referenced in your query is corrupt.
- Action** The view must be dropped and recreated.

*HADB12442*

- Description** The specified dynamic SQL statement contains an expression involving a dynamic parameter marker whose data type cannot be determined. You are not allowed to specify an expression consisting of a single parameter marker, parameter markers on both sides of a dyadic operator, a parameter marker in a set function argument, and so on.
- Action** Verify your SQL statement.

*HADB12443*

- Description** You cannot specify a parameter marker in the SELECT statement part of a CREATE VIEW statement.
- Action** Verify your SQL statement.

*HADB12444*

**Description** You cannot create a view that references a temporary table. Only permanent tables and other views can be referenced.

**Action** Verify your SQL statement.

*HADB12445*

**Description** Subtracting two DATE, TIME or TIMESTAMP expressions to form an INTERVAL requires the interval type for the result to be specified.

**Action** Verify your SQL statement.

*HADB12446*

**Description** System maintained columns (for example, log sequence number: LSN) cannot be updated.

**Action** Verify your SQL statement.

*HADB12447*

**Description** DEFAULT values cannot be used inside general expressions.

**Action** Verify your SQL statement.

*HADB12448*

**Description** A dynamic SQL statement contains an invalid usage of a parameter. For example, `select ? from t.`

**Action** Verify your SQL statement.

*HADB12449*

- Description** An `INSERT INTO` may contain a list of values representing rows to be inserted. The rows must be of the same degree, that is have the same number of fields. An example of an illegal statement is, `insert into t values (1),(1,2);`
- Action** Verify your SQL statement.

*HADB12450*

- Description** An `'INSERT INTO'` may contain a list of values representing rows to be inserted. The values to be inserted must have the correct number of elements. For example, if table `t` has a single column, the following statement is illegal. `insert into t values(1,2);`
- Action** Verify your SQL statement.

*HADB12451*

- Description** A `NULL` value is used in an incorrect way. For example, `select NULL from t;`
- Action** Verify your SQL statement. A correct example is as follows:  
`select cast(NULL as int) from t;`

*HADB12452*

- Description** A `NULL` value is used in an ill-defined manner. For example, `insert into temporary.t values(NULL);`
- Action** Verify your SQL statement. You can use the `cast ( )` construct to specify correct type.

*HADB12454*

- Description** An SQL query can reference a maximum of 32 tables, including tables which are included when expanding views.
- Action** Rewrite the SQL query.

*HADB12455*

**Description** The expression is too complex to be evaluated, due to limitations in HADB SQL.

**Action** Rewrite the SQL query.

*HADB12456*

**Description** The expression is too complex to be evaluated, due to limitations in HADB SQL.

**Action** Rewrite your SQL query.

*HADB12457*

**Description** The number of parameters for a dynamic SQL query exceeds 255.

**Action** Rewrite the client application.

*HADB12458*

**Description** Due to limitations in HADB SQL, the expression is too complex to be evaluated. The number of statements is limited to 1023. This is relevant for batched SQL statements.

**Action** Rewrite your SQL query.

*HADB12459*

**Description** Row value lists are not supported in all expression contexts. An example of an illegal query is as follows:

```
select * from t2 where (i,j) > (0,0)
```

**Action** Rewrite your SQL query.



*HADB12460*

- Description** If columns have been renamed by an alias in a query, the alias names must be used in the select list.
- Action** Rewrite your SQL query.

*HADB12461*

- Description** When performing a natural join with the `using ( )` construct, the select list cannot qualify the (common) join columns with a table name. This is according to the SQL standard.
- Action** Rewrite your SQL query.

*HADB12522*

- Description** You tried to send one receive statement through the client/server interface without establishing a network connection.
- Action** Try to reconnect to the server.

*HADB12523*

- Description** The HADB node to which your client tries to connect does not have the necessary capabilities to handle client requests.
- Action** Connect to a different HADB node, or re-try the connection at a later time.

*HADB12528*

- Description** The connection has been aborted by HADB. The HADB node to which you were connected has most likely stopped, or has crashed.
- Action** Re-connect to HADB.

*HADB12530*

<b>Description</b>	The client and servers has initiated a connection, but lose contact before a proper connection has been established.
<b>Action</b>	Re-connect to HADB on a different node.

*HADB12539*

<b>Description</b>	There is a mismatch in the client/server protocol. You are possibly using a new ODBC/JDBC driver to connect to an old version of HADB, or vice versa.
<b>Action</b>	Change to the driver appropriate for your HADB version.

*HADB20001*

<b>Description</b>	A internal error occurred in the JDBC driver.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*HADB20002*

<b>Description</b>	The feature used is optional in the JDBC standard, and is not supported by the HADB.
<b>Action</b>	User code should be rewritten not to use this feature.

*HADB20003*

<b>Description</b>	The specified transaction isolation level is not supported.
<b>Action</b>	Use either TRANSACTION_READ_COMMITTED, TRANSACTION_READ_UNCOMMITTED or TRANSACTION_REPEATABLE_READ.

*HADB20004*

**Description** The JDBC Connection is closed, so no more operations are allowed on it.

**Action** Re-connect to the database.

*HADB20005*

**Description** An invalid data type conversion. One typical cause is to use `setString(colno, value)` on an integer column.

**Action** Check data type and use the correct accessor procedure.

*HADB20006*

**Description** Invalid characters were detected in the string.

**Action** Correct the input string.

*HADB20008*

**Description** A numeric conversion resulting in an overflow was attempted.

**Action** Check value range and data types.

*HADB20009*

**Description** Cursor positioning is not allowed on forward-only cursors.

**Action** Do not use cursor positioning methods.

*HADB20010*

**Description** An attempt was made to set a column to a NULL value when the column cannot be set to NULL in the database.

**Action** Either change the database schema to allow null values, or set a non-null value on the column.

### *HADB20011*

- Description** An attempt was made to retrieve data from a `ResultSet` and the `ResultSet` is not positioned on a row.
- Action** When a result set is retrieved for a query, it is positioned before the first row. Use `ResultSet.next()` to position on the first row.

### *HADB20012*

- Description** It is not permissible to retrieve values from the result set after it is closed.
- Action** Close the result set after reading from it.

### *HADB20013*

- Description** An attempt was made to retrieve a column that does not exist in the result set.
- Action** Check column index value.

### *HADB20014*

- Description** An attempt was made to set a query parameter that does not exist.
- Action** Check query parameter index value.

### *HADB20015*

- Description** The query returned values with a data type not known to the JDBC driver.
- Action** [Analyze the System](#), as described on [page 15](#).

### *HADB20016*

- Description** The column name does not exist in the result set.
- Action** Check the column name.

*HADB20020*

- Description** The requested result set type is not supported.
- Action** The result set type may only be TYPE\_FORWARD\_ONLY:  
TYPE\_SCROLL\_INSENSITIVE or TYPE\_SCROLL\_SENSITIVE.

*HADB20021*

- Description** The `executeQuery()` and `executeUpdate()` on a `PreparedStatement` may not accept any parameters.
- Action**

*HADB20022*

- Description** The requested result set concurrency level is not supported
- Action** Only CONCUR\_READ\_ONLY is supported.

*HADB20024*

- Description** The `executeUpdate()` method was used to execute a SELECT-type query.
- Action** Use either the `executeQuery()` or the `execute()` method when executing SELECT-type queries.

*HADB20025*

- Description** The `executeQuery()` method was used to execute an INSERT/UPDATE/DELETE-type query.
- Action** Use either `executeUpdate()` or `execute()` to execute an INSERT/UPDATE/DELETE-type query.

*HADB20026*

**Description** A statement may not include variable parameters.

**Action** Use `PreparedStatement` when using variable parameters.

*HADB20027*

**Description** The parameter to `setMaxFieldSize()` can not be negative.

**Action** Use a positive value.

*HADB20028*

**Description** The parameter to `setMaxRows()` can not be negative.

**Action** Use a positive value.

*HADB20029*

**Description** The time-out value cannot be negative.

**Action** Use a positive value.

*HADB20030*

**Description** The statement is closed. No further operations are allowed.

**Action** Do not close the statement until completing it.

*HADB20033*

**Description** The date-time format is incorrect, or out of range.

**Action** Check the JDBC documentation for the correct format.

*HADB20034*

- Description** The interval value was out of range.
- Action** See the JDBC documentation for information on legal ranges of interval columns.

*HADB20035*

- Description** A character used is not allowed in the current character code set.
- Action** Use valid characters.

*HADB20036*

- Description** Only `FETCH_FORWARD` is allowed as fetch direction on a `TYPE_FORWARD_ONLY` result set.
- Action** Use `FETCH_FORWARD` as the fetch direction.

*HADB20037*

- Description** The fetch size value may not be a negative value.
- Action** Use a positive value for the fetch size.

*HADB20038*

- Description** The suggested fetch direction is not allowed.
- Action** See the JDBC documentation for information on allowed values.

*HADB20039*

- Description** The fetch size must be less or equal to the value set using `setMaxRows()`.
- Action** Use a lower value.

*HADB20040*

- Description** The PreparedStatement does not have any parameters, so any call to `setXXX( )` fails.
- Action** Do not call `setXXX( )` methods in a PreparedStatement with no parameters.

*HADB20041*

- Description** The PreparedStatement has one or more parameters that need to be set before calling `executeQuery/executeUpdate`, since they access columns that may not be NULL.
- Action** Set all parameters that access non-NULL columns.

*HADB20043*

- Description** The requested server information item array was not found.
- Action** [Analyze the System](#), as described on [page 15](#).

*HADB20044*

- Description** A user name is required to log on to the database.
- Action** Provide a user name

*HADB20045*

- Description** A user password is required to log on to the database.
- Action** Provide a password.



*HADB20046*

- Description** None of the hosts in the connection URL could be found. This is usually due to misspelling or problems with the Domain Name Service (DNS).
- Action** Check host names and the DNS setup.

*HADB20050*

- Description** The `executeUpdate()` or `executeQuery()` was used to execute batched statements.
- Action** Use `executeBatch()` to execute batched statements.

*HADB20051*

- Description** None of the hosts in the connection URL could be found. This is usually due to misspelling or problems with the Domain Name Service (DNS).
- Action** Check host names and the DNS setup.

*HADB20052*

- Description** The requested hold is not supported.
- Action** Only `CLOSE_CURSORS_AT_COMMIT` is supported.

*HADB20053*

- Description** SQL save points are not supported in this version of HADB.
- Action** Rewrite code so that use of savepoints are not required.

*HADB20054*

- Description** The LOB table specified in the LOB descriptor does not exist in this schema.
- Action** Check if the right database schema is used.

*HADB20055*

**Description** Batched statements are not allowed in LOB queries.

**Action** Execute each query by itself.

*HADB20056*

**Description** The requested data type conversion is not allowed on a BLOB/CLOB column.

**Action** See the conversion table in the JDBC documentation for conversions that are allowed.

*HADB20057*

**Description** The requested operation is not supported when operating on LOBs.

**Action** See the *Administrator's Guide* for information on operations that are allowed.

*HADB20059*

**Description** An internal inconsistency has occurred.

**Action** [Analyze the System](#), as described on [page 15](#).

*HADB20060*

**Description** The connection is in an invalid state for executing LOB operations.

**Action** The transaction isolation level must be `REPEATABLE_READ` or higher, and the auto commit mode must be set to OFF.

*HADB20061*

**Description** Only SELECT-type queries are allowed when using `executeQuery()`.

**Action** Use `executeUpdate` to execute INSERT/UPDATE/DELETE-type queries and DML updates.

*HADB20062*

<b>Description</b>	The <code>executeUpdate</code> may not be used for SELECT-type operations.
<b>Action</b>	Use <code>executeQuery( )</code> to execute SELECT-type queries.

*HADB22002*

<b>Description</b>	Database specified does not exist.
<b>Action</b>	Retry the command with appropriate parameters

*HADB22003*

<b>Description</b>	Node number specified does not exist.
<b>Action</b>	Retry the command with appropriate parameters.

*HADB22005*

<b>Description</b>	Invalid password.
<b>Action</b>	Retry the command with appropriate parameters

*HADB22125*

<b>Description</b>	An exception propagated from mgt API or <code>cladm</code> .
<b>Action</b>	<p>Check the exception code mapped in the message.</p> <p>Example 1: "Internal Error: [ Cladm command failed : CLADM-E-27:failed to start database".</p> <ul style="list-style-type: none"> <li>In this case, the history files must be analyzed to find the reason the system could not start the database.</li> </ul> <p>Example 2: Internal Error: [ "localhost" not allowed in the host list (21042) ]</p> <ul style="list-style-type: none"> <li>Do not use localhost in the hostlist</li> </ul>

*HADB22021*

- Description** This error message was generated by the `create` command. A database with the specified name already exists.
- Action** Create a database with another name.

*HADB22022*

- Description** This error message was generated by the `create/add nodes` command. Specified path does not exist on a host.
- Action** Create the path on the host, or specify another path.

*HADB22023*

- Description** This error message was generated by the `create/addnodes` command. Specified path on a host does not have `Write` permissions.
- Action** Provide `Write` permission to the path, or specify another path.

*HADB22024*

- Description** This error message was generated by the `create/addnodes` command. Specified hosts are not reachable.
- Action** Verify that the host can be reached by pinging the host. Verify the `ssh/rsh` setup.

*HADB22025*

- Description** This error message was generated by the `create/addnodes` command. Length of host list must be greater than one and should be even.
- Action** Retry the command with appropriate parameters.

*HADB22026*

<b>Description</b>	This error message was generated by the <code>create</code> command. Specified database name is not valid.
<b>Action</b>	Retry the command with appropriate parameters.

*HADB22027*

<b>Description</b>	This error message was generated by the <code>create</code> command. Port base number is not valid or is already in use.
<b>Action</b>	Make sure no other HADB instance/program uses the port. Retry the command with appropriate parameters

*HADB22028*

<b>Description</b>	This error message was generated by the <code>create</code> command. Specified number of data devices cannot be supported.
<b>Action</b>	Retry the command with appropriate parameters

*HADB22029*

<b>Description</b>	This error message was generated by the <code>create</code> command. Specified device size cannot be supported.
<b>Action</b>	Retry the command with appropriate parameters

*HADB22030*

<b>Description</b>	This error message was generated by the <code>create/addnodes</code> command. Specified number of spares could not be allocated.
<b>Action</b>	Retry the command with appropriate parameters

*HADB22031*

- Description** This error message was generated by the `create/set` command. Attributes that are to be set are not recognized: [ {0} ].
- Action** Retry the command with appropriate parameters.

*HADB22032*

- Description** This error message was generated by the `create/clear` command. Password string is invalid. It should have a minimum length of eight.
- Action** Retry the command with appropriate parameters.

*HADB22033*

- Description** This error message was generated by the `create` command. Invalid values have been set for attributes. Following are the attributes which have been specified with invalid values: [ {0} ]
- Action** Retry the command with appropriate parameters.

*HADB22034*

- Description** This error message was generated by the `create/addnodes` command. Invalid directory specified for `inetd` setup files.
- Action** Retry the command with appropriate parameters.

*HADB22041*

- Description** This error message was generated by the `addnodes` command. Database has to be in `HAFaultTolerant` or `FaultTolerant` states.
- Action** Start the database, or start the nodes which are not running before running the `addnodes` command. In case of double node failure (mirror nodes), stop and delete the hadb instance and recreate it after including the new nodes.

*HADB22201*

- Description** This error message was generated by the `addnodes` command. Database was not refragmented.
- Action** Refragment the database with the `refragment` command.

*HADB22042*

- Description** This error message was generated by the `addnodes/refragment` command. Database could not be refragmented.
- Action** Make sure there is enough disk space for refragment. If there is not enough space, increment the `TotalDataDeviceSizePerNode` attribute. If this fails, delete and recreate the `hadb` instance, and retry the command.

*HADB22043*

- Description** This error message was generated by the `addnodes/create` command. Specified number of spares could not be allocated. Number of spares should be a positive number less than or equal to length of host list.
- Action** Retry the command with appropriate parameters.

*HADB22044*

- Description** This error message was generated by the `addnodes` command. Path configured for the original database is not existing on the new hosts: [ {0} {1} ].
- Action** Create the path on the new hosts.

*HADB22045*

- Description** This error message was generated by the `addnodes` command. Path configured for the original database does not have `write` permissions on the new host.
- Action** Set `write` permissions for the path on the new host.

*HADB22046*

<b>Description</b>	This error message was generated by the <code>addnodes</code> command. Database state has deteriorated. Original and current states of the database are: [ {0} {1} ]
<b>Action</b>	Check the nodes that have failed with the <code>hadbm status --nodes</code> command. Then check the history files for the nodes for error messages/warning messages. If some nodes have stopped, try to start them one by one with the <code>hadbm startnodes</code> command.

*HADB22047*

<b>Description</b>	This error message was generated by the <code>refragment</code> command. Refragmentation cannot be done in this operation as the database is running under <code>inetd</code> . Use <code>-r   --no-refragment</code> option and re-run the command to turn off refragmentation.
<b>Action</b>	Retry the command with appropriate parameters.

*HADB22203*

<b>Description</b>	Info message from the <code>addnodes</code> command. Nodes successfully added to the database without refragmenting data. Use the <code>inetd</code> setup files to configure and restart <code>inetd</code> and then run <code>refragment</code> command.
<b>Action</b>	No action to be taken.

*HADB22061*

<b>Description</b>	This error message was generated by the <code>clear</code> command.
<b>Action</b>	Check the history files for error messages. Retry the <code>clear</code> command, or delete and recreate the HADB instance.

*HADB22065*

<b>Description</b>	This error message was generated by the <code>delete</code> command. Database is not in the stop state.
<b>Action</b>	Stop the database by using the <code>stop</code> command and rerun the command.



### *HADB22066*

<b>Description</b>	Database could not be deleted: [ {0} ]
<b>Action</b>	None

### *HADB22071*

<b>Description</b>	This error message was generated by the <code>get/set</code> command. Attributes are not recognized.
<b>Action</b>	Retry the command with appropriate parameters.

### *HADB22072*

<b>Description</b>	This error message was generated by the <code>set</code> command. Some or all of the attributes cannot be set on an existing database.
<b>Action</b>	The attributes are static for the HADB instance. Change, delete and recreate the HADB instance with the new attribute values.

### *HADB22073*

<b>Description</b>	This error message was generated by the <code>get</code> command. The <code>get</code> command failed to get the attributes from the database.
<b>Action</b>	Retry the operation.

### *HADB22081*

<b>Description</b>	This error message was generated by the <code>startnode</code> command. Expected node state of stopped, but node state is running.
<b>Action</b>	The node is already running, so do not run the <code>startnode</code> command. Check the status of the node by using the <code>hadbm status --nodes</code> command.

*HADB22082*

<b>Description</b>	This error message was generated by the <code>startnode</code> command.
<b>Action</b>	Retry the command with appropriate parameters.

*HADB22083*

<b>Description</b>	This error message was generated by the <code>startnode</code> command. Node could not be started.
<b>Action</b>	Check the history files for HADB.

*HADB22085*

<b>Description</b>	This error message was generated by the <code>stopnode</code> command. Database has to be in <code>HAFaultTolerant</code> state for repair. No spare node is available. Node has not been stopped. Node number: [ {0} ].
<b>Action</b>	The node can be stopped with the <code>--no-repair</code> option.

*HADB22086*

<b>Description</b>	This error message was generated by the <code>stopnode</code> command. Node could not be stopped. Node number: [ {0} ]
<b>Action</b>	Retry the command. Check hadb history files for error and warning messages.

*HADB22087*

<b>Description</b>	This error message was generated by the <code>stopnode</code> command. Mirror node is not up. Node is not stopped. Node number and its mirror node number are: [ {0} {1} ]
<b>Action</b>	None. Do not try to stop a node and a mirror node, the database will become non-operational. To stop all nodes, use the <code>stop</code> command for the database ( <code>hadbm stop</code> ).

### *HADB22088*

<b>Description</b>	This error message was generated by the <code>stopnode</code> command. Node should not be in stop state. Node state found is stopped. Node could not be stopped. Node number: [ {0} ]
<b>Action</b>	None. The node is already stopped.

### *HADB22091*

<b>Description</b>	This error message was generated by the <code>restartnode</code> command. Node could not be restarted. Node number: [ {0} ]
<b>Action</b>	Retry the command. Check the hadb history files for error and warning messages.

### *HADB22095*

<b>Description</b>	This error message was generated by the <code>start</code> command. Database could not be started: [ {0} ]
<b>Action</b>	Check the HADB history files for error and warning messages. If the history files are not available, check for error and warning messages in <code>syslog</code> . The messages are prefixed with HADB, by default.

### *HADB22096*

<b>Description</b>	This error message was generated by the <code>start</code> command. Database is already running: [ {0} ]
<b>Action</b>	None. The database is already running, so there is no need to run the start command.

### *HADB22097*

<b>Description</b>	This error message was generated by the <code>start</code> command. Database only partially started.
<b>Action</b>	Retry the command, check hadb history files for error messages and warning messages.

*HADB22101*

<b>Description</b>	This error message was generated by the <code>stop</code> command. Database could not be stopped.
<b>Action</b>	Retry the command. Check hadb history files for error and warning messages.

*HADB22102*

<b>Description</b>	This error message was generated by the <code>stop</code> command. Database is already in a stopped state.
<b>Action</b>	None

*HADB22105*

<b>Description</b>	This error message was generated by the <code>restart</code> command. Database is not running. Database name: [ {0} ]
<b>Action</b>	Start the database with the <code>hadbm start</code> command.

*HADB22106*

<b>Description</b>	This error message was generated by the <code>restart</code> command. Database could not be restarted. Database name: [ {0} ]
<b>Action</b>	Retry the command. Check HADB history files for error and warning messages.

*HADB22107*

<b>Description</b>	This error message was generated by the <code>restart</code> command. Restart failed to return the database to original state or better.
<b>Action</b>	Check HADB history files for error and warning messages. Start nodes which are not running.

### *HADB22108*

<b>Description</b>	This error message was generated by the <code>restart</code> command. Database has to be in <code>HAFaultTolerant</code> or <code>FaultTolerant</code> states for rolling restart.
<b>Action</b>	Use no-rolling option to restart the database

### *HADB22111*

<b>Description</b>	This error message was generated by the <code>clearhistory</code> command. Directory to which history files are to be saved does not exist.
<b>Action</b>	Retry the command with appropriate parameters.

### *HADB22112*

<b>Description</b>	This error message was generated by the <code>clearhistory</code> command. Specified location to save the history files is not a directory.
<b>Action</b>	Retry the command with appropriate parameters.

### *HADB22113*

<b>Description</b>	This error message was generated by the <code>clearhistory</code> command. Directory to which history files are to be saved does not have write permissions.
<b>Action</b>	Retry the command with appropriate parameters.

### *HADB22114*

<b>Description</b>	This error message was generated by the <code>clearhistory</code> command. History files could not be cleared and saved.
<b>Action</b>	Enable logging in the CLI by modifying the <code>hadbmlogging.properties</code> file in the <code>lib</code> directory. Retry the command. If it fails, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*HADB21006*

<b>Description</b>	The value for a configuration attribute is invalid.
<b>Action</b>	Retry command with appropriate parameters.

*HADB21022*

<b>Description</b>	The <code>cladm</code> command failed. There will be a linked message from <code>cladm</code> with error code and description as part of this error message.
<b>Action</b>	Analyze the message from <code>cladm</code> .

*HADB21024*

<b>Description</b>	No reply received in response to the dialog message for one of the server processes.
<b>Action</b>	Verify that the nodes are running, retry the command.

*HADB21042*

<b>Description</b>	Prevents the user from adding nodes with <code>localhost</code> as hostname.
<b>Action</b>	You must supply the qualified hostname, preferably the IP address.

*HADB21035*

<b>Description</b>	Device size is too small for logstore and data. A part of the data device is reserved for logstore. Totally $4 * \text{logbuffersize}$ is reserved for logstore per node. This exception ( $4 * \text{logbuffersize} + 16$ ) occurs if the data devices can not hold the log store.
<b>Action</b>	Increase the size of the data devices, or decrease the size of the <code>logbuffersize</code> .

*HADB21023*

<b>Description</b>	The <code>cladm</code> command could not be invoked.
<b>Action</b>	Check permissions for the <code>cladm</code> script, located in the <code>bin</code> directory.

*HADB25005*

<b>Description</b>	The communication RPC layer is closed.
<b>Action</b>	Reconnect to the database.

*HADB25010*

<b>Description</b>	The query string is too large.
<b>Action</b>	Shorten the query, and if possible execute the query using multiple queries.

*HADB25012*

<b>Description</b>	The connection to the database failed.
<b>Action</b>	Check if the database is running, and that the correct host name and port numbers are used. Reconnect to the database.

*HADB25017*

<b>Description</b>	The database server node serving the query is not currently available. The database connection is still valid, but the transaction must be retried.
<b>Action</b>	Retry the transaction.

*HADB25018*

<b>Description</b>	There has been a time-out in the call to the database server. The connection is still valid, but the transaction must be retried.
<b>Action</b>	Retry the transaction.

### *HADB25020*

- Description** The JDBC driver and the database server is not compatible. This is usually due to using a JDBC driver that is either too old or too new compared to the database server.
- Action** Use the correct JDBC driver version.

### *HADB25022*

- Description** The transaction was rolled back due to an error in the commit cycle. The transaction must be retried.
- Action** Retry the transaction.



# Health Checker

This chapter lists error messages that originate from the Health Checker.

## HLCK

### *HLCK3002*

<b>Severity</b>	WARNING
<b>Description</b>	Could not create the health checker thread
<b>Action</b>	Restart the server.

### *HLCK3003*

<b>Severity</b>	WARNING
<b>Description</b>	The application server instance is still down.
<b>Action</b>	Check the application server instance, and bring it up.

### *HLCK3007*

<b>Severity</b>	WARNING
<b>Description</b>	Could not create the health check stop thread.
<b>Action</b>	Restart the server.

HLCK

# Install Services

This chapter lists error messages that originate from the Installer subsystem.

## INSTALL

### *INSTALL2001*

<b>Severity</b>	FATAL
<b>Description</b>	A shell-specific character in your server ID was used.
<b>Action</b>	Retry with a non-shell specific character in the server ID.

### *INSTALL2002*

<b>Severity</b>	FATAL
<b>Description</b>	The <code>mkdir</code> command failed.
<b>Action</b>	Check the disk space and directory permissions. Refer to exception data to get more information on the directory.

### *INSTALL2003*

<b>Severity</b>	FATAL
<b>Description</b>	Unable to get system information about user.
<b>Action</b>	Refer to exception data to get more information on user.

*INSTALL2004*

<b>Severity</b>	FATAL
<b>Description</b>	Unable to open the file for reading.
<b>Action</b>	Make sure the file exists and has the Right access permissions.

*INSTALL2005*

<b>Severity</b>	FATAL
<b>Description</b>	Unable to open file for writing.
<b>Action</b>	Make sure the file exists and has Write access permissions.

*INSTALL2006*

<b>Severity</b>	FATAL
<b>Description</b>	Unable to read file.
<b>Action</b>	Make sure the file exists and has Read access permissions.

*INSTALL2007*

<b>Severity</b>	FATAL
<b>Description</b>	An error occurred while writing to a file from the source.
<b>Action</b>	Refer to the exception data to get more information on why the Write operation failed.

*INSTALL2008*

<b>Severity</b>	FATAL
<b>Description</b>	Unable to create the file.
<b>Action</b>	Refer to the exception data to get more information on the file that could not be created. The command to create this file may have failed.

*INSTALL2009*

<b>Severity</b>	FATAL
<b>Description</b>	Unable to write to the file.
<b>Action</b>	Refer to the exception data to get more information on why the Write operation failed.

*INSTALL2010*

<b>Severity</b>	FATAL
<b>Description</b>	Unable to change the ownership of the file.
<b>Action</b>	Refer to exception data to get more information on the reason the change ownership failed.

*INSTALL2011*

<b>Severity</b>	FATAL
<b>Description</b>	The server was unable to find user.
<b>Action</b>	Create user and retry.

*INSTALL2012*

<b>Severity</b>	FATAL
<b>Description</b>	Unauthorized user.
<b>Action</b>	Select or create another user. Refer to exception data to get more information on the reason the change of ownership failed.

*INSTALL2013*

<b>Severity</b>	FATAL
<b>Description</b>	The file is not a regular file.
<b>Action</b>	The source file is not a regular UNIX file that can be copied to another file.

*INSTALL2014*

<b>Severity</b>	FATAL
<b>Description</b>	Problem creating or opening the <code>dbswitch.conf</code> config file.
<b>Action</b>	Make sure the file exists.

*INSTALL2015*

<b>Severity</b>	FATAL
<b>Description</b>	Document root must be an absolute path.
<b>Action</b>	Make sure that the document root is an absolute path.

*INSTALL2016*

<b>Severity</b>	FATAL
<b>Description</b>	Problem creating <code>/bin/startserv</code> .
<b>Action</b>	Refer to exception data to get more information on why the <code>startserv</code> script creation failed.

*INSTALL2017*

<b>Severity</b>	FATAL
<b>Description</b>	Problem creating <code>/bin/stopserv</code> .
<b>Action</b>	Refer to exception data to get more information on why the <code>stopserv</code> script creation failed.

*INSTALL2018*

<b>Severity</b>	FATAL
<b>Description</b>	Problem creating <code>/bin/restartserv</code> .
<b>Action</b>	Refer to exception data to get more information on why the <code>restartserv</code> script creation failed.

*INSTALL2019*

<b>Severity</b>	FATAL
<b>Description</b>	Problem creating <code>admpw</code> file.
<b>Action</b>	Make sure that the <code>admpw</code> file exists.

*INSTALL2020*

<b>Severity</b>	FATAL
<b>Description</b>	Unable to create the backup tree.
<b>Action</b>	Refer to exception data to get more information on why the creation of the backup tree failed.

*INSTALL2021*

<b>Severity</b>	FATAL
<b>Description</b>	Unable to create backup for <code>keyfile</code> .
<b>Action</b>	Refer to exception data to get more information on why the <code>keyfile</code> backup failed.

*INSTALL2022*

<b>Severity</b>	FATAL
<b>Description</b>	Unable to create backup for <code>mime.types</code> .
<b>Action</b>	Refer to exception data to get more information on the reason <code>mime.types</code> backup failed

*INSTALL2023*

<b>Severity</b>	FATAL
<b>Description</b>	Unable to execute <code>chmod</code> command for the <code>config</code> directory.

<b>Action</b>	Possible reasons for the <code>chmod</code> command to fail could be: <ul style="list-style-type: none"><li>• Lack of appropriate permission</li><li>• Object is a symbolic link that points to a non-existent file.</li></ul>
---------------	--

### *INSTALL2024*

<b>Severity</b>	FATAL
<b>Description</b>	Could not execute <code>chmod</code> command for <code>config/alias</code> directory.
<b>Action</b>	Possible reasons for the <code>chmod</code> command to fail could be due to lack of appropriate permission or the object is a symbolic link that points to a non-existent file.

### *INSTALL2025*

<b>Severity</b>	FATAL
<b>Description</b>	File mapping creation failed.
<b>Action</b>	Refer to exception data to get more information on why the creation of file mapping failed.

### *INSTALL2026*

<b>Severity</b>	FATAL
<b>Description</b>	Unable to map files.
<b>Action</b>	Refer to exception data to get more information on why the creation of file mapping failed.

### *INSTALL2027*

<b>Severity</b>	FATAL
-----------------	-------



<b>Description</b>	Unable to create the registry key due to one of the following reasons: <ul style="list-style-type: none"> <li>• Registry key may already exist</li> <li>• Path does not exist</li> <li>• Only the Administrator has privileges to create the registry key.</li> </ul>
<b>Action</b>	Make sure the registry key and the path exist.

### *INSTALL2028*

<b>Severity</b>	FATAL
<b>Description</b>	Unable to set registry key.
<b>Action</b>	Make sure the registry key exists.

### *INSTALL2029*

<b>Severity</b>	FATAL
<b>Description</b>	While installing the service, the NT Service Manager reported an error.
<b>Action</b>	Refer to exception data for more information.

### *INSTALL2030*

<b>Severity</b>	FATAL
<b>Description</b>	Server instance already exists within the given domain.
<b>Action</b>	Please choose a different server name.

### *INSTALL2031*

<b>Severity</b>	FATAL
<b>Description</b>	Problem creating the file.
<b>Action</b>	Refer to exception data for more information.

*INSTALL2032*

<b>Severity</b>	FATAL
<b>Description</b>	Problem setting registry key.
<b>Action</b>	Make sure the registry key exists.

*INSTALL2033*

<b>Severity</b>	FATAL
<b>Description</b>	Exceeded token limit.
<b>Action</b>	Change the source and rebuild.

*INSTALL2034*

<b>Severity</b>	FATAL
<b>Description</b>	The token name is NULL.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*INSTALL2035*

<b>Severity</b>	FATAL
<b>Description</b>	Null or empty delimiter.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*INSTALL2036*

<b>Severity</b>	FATAL
<b>Description</b>	NULL template file name
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*INSTALL2037*

<b>Severity</b>	FATAL
<b>Description</b>	Unable to open the template file for reading.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*INSTALL2038*

<b>Severity</b>	FATAL
<b>Description</b>	Unable to open the template file for reading.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*INSTALL2039*

<b>Severity</b>	FATAL
<b>Description</b>	Unable to chmod file.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

INSTALL

# Inter ORB Protocol

This chapter lists error messages that originate from the Internet Inter-ORB Protocol.

## IOP

Internet Inter-ORB Protocol is a transport-level protocol used by both Remote Method Invocation (RMI) over IIOP and Common Object Request Broker Architecture (CORBA).

This chapter contains error messages that occur in the IOP system.

### *IOP5001*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while creating the security mechanism list based on the deployer-specified configuration information.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *IOP5002*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while initializing the IIOP SSL socket factory in the server.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*IOP5003*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while initializing the IOP SSL socket factory in the application client.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*IOP5004*

<b>Severity</b>	SEVERE
<b>Description</b>	This error could occur due to one of the following reasons: <ul style="list-style-type: none"><li>• Unable to set SSL cipher suites after connecting to the server.</li><li>• Unable to set server socket for client authentication.</li></ul>
<b>Action</b>	Check SSL settings for the listener.

*IOP5006*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while creating an SSL socket connection.
<b>Action</b>	Check the host and port settings.

*IOP5007*

<b>Severity</b>	SEVERE
<b>Description</b>	An IO exception occurred while reading the <code>security.properties</code> file. There may be a problem with setup.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*IOP5009*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while initializing the transaction service on the server.

**Action** [Analyze the System](#), as described on [page 15](#).

### *IOP5010*

**Severity** SEVERE

**Description** An exception occurred while creating a portable object adapter (POA) on the server.

**Action** [Analyze the System](#), as described on [page 15](#).

### *IOP5011*

**Severity** SEVERE

**Description** A request arrived for an EJB object that does not exist. It may have been removed.

**Action** Ensure that the `removal-timeout-in-seconds` element in the `sun-ejb-jar.xml` file is a stateful session bean.

**See Also** *EJB Developers Guide*.

### *IOP5012*

**Severity** SEVERE

**Description** A runtime exception occurred during server execution.

**Action** [Analyze the System](#), as described on [page 15](#).

### *IOP5013*

**Severity** SEVERE

**Description** An exception occurred while creating a CORBA reference to `EJBHome` or `EJBObject`.

**Action** [Analyze the System](#), as described on [page 15](#).

## *IOP5015*

<b>Severity</b>	SEVERE
<b>Description</b>	A runtime exception occurred while setting a system property.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

## *IOP5016*

<b>Severity</b>	SEVERE
<b>Description</b>	The security service is unregistered and therefore exists at interception point.
<b>Action</b>	You may be using Common Secure Interoperability version 2 (CSIV2) <sup>1</sup> features via RMI-IIOP client. However, this is not supported. Use the application client container for CSIV2 features.

1. It is a protocol used to address the requirements of CORBA security for interoperable authentication, delegation and privileges.

## *IOP5017*

<b>Severity</b>	WARNING
<b>Description</b>	Security service is not registered and therefore the status is not set.
<b>Action</b>	You may be using Common Secure Interoperability version 2 (CSIV2) <sup>1</sup> features via RMI-IIOP client. However, this is not supported. Use the application client container for CSIV2 feature.
<b>See Also</b>	Message ID <a href="#">IOP5016</a> .

1. It is a protocol used to address the requirements of CORBA security for interoperable authentication, delegation and privileges.

## *IOP5018*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while importing the user name. Server fails while trying to create Generic Security Service Username Password (GSSUP), API-GSSUPName, from an exported user name sent by the client.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the exception stack trace information.



**See Also** Message ID [IOP5019](#).

### *IOP5019*

**Severity** SEVERE

**Description** An exception occurred while creating an exported user name. The server or client fails while creating an exported user name as an array of one or more UTF-8 characters.

**Action** [Analyze the System](#), as described on [page 15](#) with the exception stack trace information.

**See Also** Message ID [IOP5018](#).

### *IOP5020*

**Severity** SEVERE

**Description** An exception occurred while getting the password. This occurs while extracting the user name and password from `PasswordCredential` and converting the string to UTF-8 format.

**Action** Make sure the user name or password specified is not `null`. If the problem persists, [Analyze the System](#), as described on [page 15](#) with the exception stack trace information.

### *IOP5021*

**Severity** SEVERE

**Description** An exception occurred while encoding. The token that contains the user name and password is encoded in CDR format.

**Action** Make sure the server or client user name and password are correct. If the problem persists, [Analyze the System](#), as described on [page 15](#) with exception stack trace.

### *IOP5022*

**Severity** SEVERE

<b>Description</b>	An exception occurred while decoding. This exception occurs when a CDR stream is decoded to create an object that contains the user name and password.
<b>Action</b>	Make sure the user name and password specified in the client or server are correct. If the problem persists, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the exception stack trace information.

### *IOP5023*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while getting user name and password.
<b>Action</b>	The specified user name or password is either null or not in UTF-8 format. Verify the user name and password.

### *IOP5024*

<b>Severity</b>	SEVERE
<b>Description</b>	An IO exception occurred in IIOP. This exception occurs when the <code>security.properties</code> file is not present in the classpath of the application server or application client container.
<b>Action</b>	Verify and add the <code>security.properties</code> file in the classpath of the application server or application client container.

*IOP5026*

<b>Severity</b>	SEVERE
<b>Description</b>	More than one credential is specified. You may be using an unsupported feature by using CSIV2 <sup>1</sup> via RMI-IIOP client.
<b>Action</b>	Use application client container.

1. It is a protocol used to address the requirements of CORBA security for interoperable authentication, delegation and privileges.

*IOP5027*

<b>Severity</b>	SEVERE
<b>Description</b>	An invalid security mechanism occurred. The client does not conform to the target bean's configured security policies.
<b>Action</b>	Verify the <code>sun-ejb-jar.xml</code> and <code>sun-acc.xml</code> files and validate the data.

*IOP5029*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while creating authentication token – Generic Security Service Username Password (GSSUP) from the specified credential.
<b>Action</b>	Make sure the user name and password specified is not null. If the problem persists, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the exception stack trace information.

*IOP5030*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while creating and adding the CDR encoded client identity token to the service context field.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the exception stack trace information.

### *IOP5031*

<b>Severity</b>	SEVERE
<b>Description</b>	A service context exception occurred.
<b>Action</b>	Refer to the stack trace in the exception. This indicates the reason that the service context on the client was not extracted from the message. <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the exception stack trace information.

### *IOP5032*

<b>Severity</b>	SEVERE
<b>Description</b>	Reply message not <code>CompleteEstablishContext</code> or <code>ContextError</code> . An illegal message was sent from the client while establishing a context with the client.
<b>Action</b>	Refer to <code>SecurityException</code> in the log that follows this message for a better description of possible reasons. <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the exception stack trace information.

### *IOP5033*

<b>Severity</b>	SEVERE
<b>Description</b>	Unknown identity assertion type. An error occurred while creating an identity in the security context for a user on the server.
<b>Action</b>	Refer to the <code>SecurityException</code> in the log that follows this message, and correct the security identity token.

### *IOP5034*

<b>Severity</b>	SEVERE
<b>Description</b>	The message received is not an <code>EstablishContext</code> message. An illegal message was sent from the client while establishing a context with the client.
<b>Action</b>	Check the implementation on the client ORB to find possible issues with the protocol version mismatch, for example, in <i>sequence messages</i> . If you are using the Sun Java System client and server ORBs, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the exception stack trace information.

### *IOP5035*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while creating a JAAS subject credential. This error occurs when the message from the client contained an authentication token and JAAS was unable to create an authentication or subject credential.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the exception stack trace information.

### *IOP5036*

<b>Severity</b>	SEVERE
<b>Description</b>	A security exception occurred in IIOP. The system was unable to create an identity credential because the message from the client contained an identity token.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the exception stack trace information.

### *IOP5037*

<b>Severity</b>	SEVERE
<b>Description</b>	A generic exception occurred in IIOP during the creation of identity credential.
<b>Action</b>	Refer to the <code>SecurityException</code> in the log following this exception. <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the exception stack trace information.

*IOP5038*

<b>Severity</b>	SEVERE
<b>Description</b>	Could not propagate user name or password required by target when using <code>run</code> as identity. There was no client authentication token found in the security context and an exception, <code>SecurityMechanismException</code> occurred.
<b>Action</b>	A client authentication on the server is required. Send a client authentication to the server.

*IOP5039*

<b>Severity</b>	SEVERE
<b>Description</b>	The specified mechanism type sent by the client for identification is not supported.
<b>Action</b>	See documentation for server and client security mechanisms.

*IOP5040*

<b>Severity</b>	SEVERE
<b>Description</b>	Could not lookup the domain name of the specified IP address.
<b>Action</b>	Verify the network and configuration settings. Check the IP address and domain information. The client's domain may not be supported.

*IOP5041*

<b>Severity</b>	SEVERE
<b>Description</b>	Cannot find <code>principal</code> information in the subject. The security mechanisms are trying to extract the <code>principal</code> from the subject.
<b>Action</b>	Check client authentication token propagated. Also refer to security documentation for supported security mechanisms.

*IOP5042*

<b>Severity</b>	SEVERE
-----------------	--------

<b>Description</b>	Cannot find credential information in subject. While authenticating the client and getting its identity, the security mechanism on the server was able to extract the principal from the subject. However, it could not determine any credential from the subject.
<b>Action</b>	Check the client authentication token that is propagated.
<b>See Also</b>	Message ID <a href="#">IOP5041</a> . Also see the <i>Administrator's Guide to Security</i> for supported security mechanisms.

### *IOP5043*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while creating <code>ASContext</code> . The client authentication does not conform to the security policies set on the server.
<b>Action</b>	Check the application security configuration and make sure the client meets the minimum security required.

### *IOP5044*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while getting the peer certificate chain. The user and the server are using an SSL connection. However, the server security mechanism is unable to retrieve the certificate from the user to evaluate <i>trust</i> .
<b>Action</b>	Ensure that the client certificate is available on the client and meets the security requirements as per the server requirements.

### *IOP5045*

<b>Severity</b>	SEVERE
<b>Description</b>	An invalid security mechanism exception occurred.
<b>Action</b>	See the exceptions reported along with this message for solution. If the problem persists, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*IOP5046*

<b>Severity</b>	SEVERE
<b>Description</b>	An invalid ID token is sent.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*IOP5047*

<b>Severity</b>	SEVERE
<b>Description</b>	A security exception occurred. The client does not conform to the target bean's configured security policies.
<b>Action</b>	Verify the <code>sun-ejb-jar.xml</code> and <code>sun-acc.xml</code> files. Validate the security information and roles assigned in the XML files.

*IOP5048*

<b>Severity</b>	SEVERE
<b>Description</b>	An authentication exception occurred. The client authentication does not conform to the security policies set on the server.
<b>Action</b>	Check the application's security configuration and make sure the client meets the minimum security required.

*IOP5049*

<b>Severity</b>	SEVERE
<b>Description</b>	A login exception occurred. An attempt to login to the server by authenticating the client with the specified subject and credential failed.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the exception stack trace information.

*IOP5050*

<b>Severity</b>	SEVERE
-----------------	--------



<b>Description</b>	An unknown message type exception occurred.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *IOP5051*

<b>Severity</b>	SEVERE
<b>Description</b>	More than one TAG_CSI_SEC_MECH_LIST tagged component was found. The client has sent more than one security mechanism. However, only one mechanism can be specified.
<b>Action</b>	Specify only one security mechanism.

### *IOP5052*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while starting <code>bootserver</code> .
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *IOP5054*

<b>Severity</b>	WARNING
<b>Description</b>	A request arrived on a disabled connection. The IIOP listener port is disabled in <code>server.xml</code> . A regular CORBA request message sent by the client is rejected.
<b>Action</b>	If the IIOP listener port was disabled on purpose, then no action is required. However, if it was not disabled on purpose, enable the IIOP listener port in <code>server.xml</code> .

### *IOP5055*

<b>Severity</b>	SEVERE
<b>Description</b>	Could not create listener on the specified port and host.

**Action** Validate host and port settings in `server.xml`. Also verify if there is a process listening on that port. If yes, then change the `iiop-listener` element in `server.xml` to a different port and restart the server. If the problem persists, [Analyze the System](#), as described on [page 15](#) with the stack trace information.

### *IOP5056*

**Severity** SEVERE

**Description** An exception occurred while creating the listener.

**Action** Check host and port settings. If the problem persists, [Analyze the System](#), as described on [page 15](#) with the stack trace information.

**See Also** Message ID [IOP5055](#).

### *IOP5057*

**Severity** SEVERE

**Description** An unknown host present and hence could not create a listener.

**Action** Make sure the host used in `server.xml` has a valid hostname/IP address. If the problem persists, [Analyze the System](#), as described on [page 15](#) with the exception stack trace information.

### *IOP5058*

**Severity** SEVERE

**Description** An unknown host present.

**Action** Check host settings. The host name may be incorrect.

**See Also** Message ID [IOP5057](#).

### *IOP5071*

**Severity** WARNING

**Description** This exception can occur during the `findPOA()` call in the ORB.

**Action** Restart the server. If restart option is not available, [Analyze the System](#), as described on [page 15](#) with the exception stack trace information.

### *IOP5073*

**Severity** WARNING

**Description** The port specified in the `iiop-listener` element in `server.xml` is not a number between 1 and 65535.

**Action** Make sure the `iiop-listener` element in `server.xml` is a number in the range specified. Modify the `server.xml` and restart the server.

### *IOP5074*

**Severity** WARNING

**Description** The port specified in the `iiop-listener` element in `server.xml` is not a number between 1 and 65535, even though the listener is disabled.

**Action** Make sure that all the disabled `iiop-listener` elements in `server.xml` is a number in the range specified above. Modify the `server.xml` and restart the server.

### *IOP5075*

**Severity** WARNING

**Description** The `steady-thread-pool-size` specified in the ORB element in `server.xml` is *not* a positive number (greater than or equal to 1).

**Action** Make sure that `steady-thread-pool-size` specified in the ORB element in `server.xml` is *not* a positive number. Modify the value in `server.xml` and restart the server.

### *IOP5076*

**Severity** WARNING

**Description** The `max-thread-pool-size` specified in the ORB element in `server.xml` is *not* a positive number (greater than or equal to 1).

**Action** Make sure that `max-thread-pool-size` specified in the ORB element in `server.xml` is *not* a positive number. Modify the value in `server.xml` and restart the server.

### *IOP5077*

**Severity** WARNING

**Description** This exception can occur if the `idle-thread-timeout-in-seconds` specified in the ORB element in `server.xml` is *not* a positive number.

**Action** Make sure that `idle-thread-timeout-in-seconds` specified in the ORB element in `server.xml` is *not* a positive number. Modify the value in `server.xml` and restart the server.

# Java Message Service

This chapter lists error messages that originate from the Java messaging service.

## JMS

Java Message Service is a standard set of interfaces and semantics that define how a JMS client accesses the facilities of a JMS message service. These interfaces provide a standard way for Java programs to create, send, receive, and read messages.

This chapter contains error messages that occur in the JMS system.

### *JMS5004*

<b>Severity</b>	SEVERE
<b>Description</b>	The session could not be closed.
<b>Action</b>	See exception message and stack trace for information on why the session could not be closed.

### *JMS5005*

<b>Severity</b>	SEVERE
<b>Description</b>	Resource handle could not be created.
<b>Action</b>	See exception message and stack trace for information on why the resource handle could not be created.

*JMS5006*

<b>Severity</b>	SEVERE
<b>Description</b>	Resource handle could not be registered.
<b>Action</b>	See exception message and stack trace for information on why the resource handle could not be registered.

*JMS5007*

<b>Severity</b>	SEVERE
<b>Description</b>	An illegal access to the connection factory was performed. J2EE components must access JMS connection factories through a <code>resource-ref</code> in <code>java:comp/env</code> subcontext.
<b>Action</b>	Make sure that the correct application accesses <code>resource-ref</code> in <code>java:comp/env</code> subcontext.

*JMS5008*

<b>Severity</b>	WARNING
<b>Description</b>	The <code>resource-reference</code> for JMS connection factory specifies container authorization but no user name and password is available.
<b>Action</b>	Specifying <code>default-resource-principal</code> for the JMS <code>resource-reference</code> removes this warning message. If you intend to use the resource sign-on information configured in the JMS connection factory resource, then you may ignore this warning message.

*JMS5009*

<b>Severity</b>	WARNING
<b>Description</b>	Calling <code>createQueueConnection()</code> on <code>resource-ref</code> with <code>APPLICATION</code> authentication.
<b>Action</b>	Use <code>createQueueConnection(username, password)</code> instead.

*JMS5010*

<b>Severity</b>	WARNING
<b>Description</b>	JMS connection with container authentication cannot programmatically set user name and password.
<b>Action</b>	Correct the application to use the no-argument JMS connection creation method.

*JMS5011*

<b>Severity</b>	WARNING
<b>Description</b>	Calling <code>createTopicConnection()</code> on resource-ref with APPLICATION authentication.
<b>Action</b>	Use <code>createTopicConnection(username, password)</code> instead.

*JMS5012*

<b>Severity</b>	SEVERE
<b>Description</b>	The connection factory could not be found.
<b>Action</b>	Check the stack trace following this error message for reason.

*JMS5014*

<b>Severity</b>	SEVERE
<b>Description</b>	A pooling exception occurred while creating resource. The <code>create resource handle</code> failed.
<b>Action</b>	See the stack trace for more information on why it failed.

*JMS5016*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while installing JMS resources.

<b>Action</b>	See the error message for reason. Check the stack trace following this error message for more information.
---------------	--

### *JMS5018*

<b>Severity</b>	SEVERE
-----------------	--------

<b>Description</b>	An error occurred while deleting a JMS connection factory resource.
--------------------	---

<b>Action</b>	See the error message and the stack trace following this error message for information on how to fix this error.
---------------	--

### *JMS5020*

<b>Severity</b>	SEVERE
-----------------	--------

<b>Description</b>	An error occurred while deleting a JMS destination administered object.
--------------------	---

<b>Action</b>	See the error message and the stack trace following this error message for reason.
---------------	--

### *JMS5022*

<b>Severity</b>	SEVERE
-----------------	--------

<b>Description</b>	This message can occur during application server initialization and the application server aborts. It indicates conflicting configuration of JMS port number.
--------------------	---

<b>Action</b>	Assign an unused port number to the application server's JMS service and restart the application server.
---------------	--

### *JMS5024*

<b>Severity</b>	SEVERE
-----------------	--------

<b>Description</b>	The message queue broker startup failed for an unknown reason. Consequently, the application server aborts.
--------------------	---



**Action** Check the application server's JMS service configuration. See the exception stack trace following this message. If it does not provide sufficient information, lower the application server's log level and try again. See the message queue broker log file also. Start the message queue broker manually to narrow down the cause of failure.

### *JMS5027*

**Severity** SEVERE

**Description** An exception occurred while creating JMS destination administered object.

**Action** See the exception message and the stack trace following this error message for reason.

### *JMS5028*

**Severity** SEVERE

**Description** An exception occurred while creating JMS connection factory resource.

**Action** See the exception message and the stack trace following this error message for reason.

### *JMS5031*

**Severity** SEVERE

**Description** An exception occurred while creating JMS connection factory resource.

**Action** See the exception message and the stack trace following this error message for reason.

### *JMS5033*

**Severity** INFO

<b>Description</b>	Unable to attach to an existing JMS service broker process. This message occurs during application server initialization. It precedes a SEVERE error and causes the application server to abort. It indicates a problem in the application server's JMS service configuration. For instance, JMS service port number may already be used by another server application.
<b>Action</b>	Check the JMS service configuration. Assign an unused port number to the JMS service and restart the application server.

### *JMS5034*

<b>Severity</b>	INFO
<b>Description</b>	Unable to start the JMS service broker process. This message can occur during application server initialization. It precedes a SEVERE error and causes the application server to abort. It indicates the application server's inability to spawn the message queue broker process. This can happen due to a variety of reasons such as, improper installation (missing message queue broker packages), or lack of system resources such as, swap space, and so on.
<b>Action</b>	Examine the Java exception details following this message. Ensure that the system has sufficient swap space. You may also want to verify if the message queue broker can be started manually.

### *JMS5035*

<b>Severity</b>	INFO
<b>Description</b>	This message can occur during application server initialization. It precedes a SEVERE error and causes the application server to abort. It indicates that the application server tried to start the message queue broker but could not establish communication with it.
<b>Action</b>	Make sure that the message queue broker started. If you have a large number of persistent messages pending, the message queue broker may take a long time to start. If this is the case, you may want to check the application server's JMS service configuration and increase the initialization timeout value. If the message queue broker is not running, check the log file.

### *JMS5036*

<b>Severity</b>	INFO
-----------------	------

<b>Description</b>	This message can occur during the application server initialization. It precedes a SEVERE error and causes the application server to abort. It indicates that the message queue broker runs as a separate process and generates a separate log file. So in order to isolate the initialization problem, it may be necessary to check both the application server log file and the message queue broker log file.
<b>Action</b>	See the message queue broker log file for the error messages specific to the JMS service.



# Java Transaction Services

This chapter lists error messages that originate from the Java transaction services.

## JTS

Java Transaction Service is a Java service for processing transactions.

### *JTS5001*

<b>Severity</b>	SEVERE
<b>Description</b>	An internal error occurred while creating a control object.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *JTS5002*

<b>Severity</b>	WARNING
<b>Description</b>	Unable to locate the servant for the object listed in the message.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *JTS5003*

<b>Severity</b>	WARNING
<b>Description</b>	An error occurred while destroying an internal object.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*JTS5004*

<b>Severity</b>	SEVERE
<b>Description</b>	An internal error occurred while creating a coordinator object.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*JTS5005*

<b>Severity</b>	WARNING
<b>Description</b>	An internal error occurred.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*JTS5006*

<b>Severity</b>	SEVERE
<b>Description</b>	An internal error occurred during recovery.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*JTS5007*

<b>Severity</b>	SEVERE
<b>Description</b>	The initialization of distributed transaction logs failed.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*JTS5008*

<b>Severity</b>	SEVERE
<b>Description</b>	The distributed transaction logs could not be opened.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*JTS5009*

<b>Severity</b>	SEVERE
<b>Description</b>	An internal error occurred while creating the <code>CoordinatorResource</code> object.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*JTS5010*

<b>Severity</b>	SEVERE
<b>Description</b>	An internal error occurred while creating the <code>CoordinatorSynchronization</code> object.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*JTS5011*

<b>Severity</b>	SEVERE
<b>Description</b>	An internal error occurred. No coordinator available for the transaction.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*JTS5012*

<b>Severity</b>	SEVERE
<b>Description</b>	An internal error occurred at the beginning of the transaction.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*JTS5013*

<b>Severity</b>	WARNING
<b>Description</b>	An internal error occurred while creating a subordinate.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *JTS5015*

<b>Severity</b>	WARNING
<b>Description</b>	An internal error occurred while creating portable object adapters (POA).
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *JTS5016*

<b>Severity</b>	WARNING
<b>Description</b>	An internal error occurred while creating the Current object.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *JTS5017*

<b>Severity</b>	WARNING
<b>Description</b>	The ORB is not running.
<b>Action</b>	Make sure the instance's ORB port is not in use. If the port is in use, change the ORB port through the Administrator Interface or by changing <code>server.xml</code> . If the problem persists, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *JTS5018*

<b>Severity</b>	WARNING
<b>Description</b>	Could not register <code>TransactionFactory</code> with ORB.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *JTS5020*

<b>Severity</b>	WARNING
<b>Description</b>	Invalid distributed transactions log path.



**Action** Make sure the `tx-log-dir` attribute in the `transaction-service` element in the `server.xml` is valid. If the problem persists, [Analyze the System](#), as described on [page 15](#).

### *JTS5021*

**Severity** WARNING

**Description** Invalid default distributed transactions log path.

**Action** Make sure the `tx-log-dir` attribute in the `transaction-service` element in the `server.xml` is valid. If the problem persists, [Analyze the System](#), as described on [page 15](#).

### *JTS5022*

**Severity** SEVERE

**Description** An error occurred while operating with distributed transaction logs.

**Action** [Analyze the System](#), as described on [page 15](#).

### *JTS5023*

**Severity** WARNING

**Description** A heuristic exception occurred during roll-back of a transaction as part of `resync` operation.

**Action** [Analyze the System](#), as described on [page 15](#).

### *JTS5024*

**Severity** SEVERE

**Description** An internal error occurred while creating a `recoverycoordinator` object.

**Action** [Analyze the System](#), as described on [page 15](#).

*JTS5026*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while recovering the <code>in-doubt</code> transactions.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*JTS5027*

<b>Severity</b>	WARNING
<b>Description</b>	An exception occurred while performing the <code>resync</code> operation.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*JTS5028*

<b>Severity</b>	WARNING
<b>Description</b>	An exception occurred while performing recovery on XA resources.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*JTS5029*

<b>Severity</b>	WARNING
<b>Description</b>	An exception occurred while performing the <code>resync</code> operation.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*JTS5030*

<b>Severity</b>	WARNING
<b>Description</b>	An exception occurred while writing the restart record in the distributed transaction logs.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*JTS5031*

<b>Severity</b>	WARNING
<b>Description</b>	An exception occurred while performing an operation on the resource.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*JTS5033*

<b>Severity</b>	WARNING
<b>Description</b>	An exception occurred while performing synchronization.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*JTS5035*

<b>Severity</b>	WARNING
<b>Description</b>	Unable to identify the communication manager.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*JTS5036*

<b>Severity</b>	SEVERE
<b>Description</b>	An internal error occurred while transitioning from one state to another.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*JTS5037*

<b>Severity</b>	SEVERE
<b>Description</b>	An internal error occurred while creating a <code>Terminator</code> object.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*JTS5040*

<b>Severity</b>	SEVERE
<b>Description</b>	An internal error occurred while creating a <code>TransactionFactory</code> object.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*JTS5041*

<b>Severity</b>	WARNING
<b>Description</b>	The resource manager is working outside a global transaction. This error occurs if an <code>XAConnection</code> is used outside the <code>pf</code> transactional context and if the connection is reused within a transaction. ( <code>XAConnection</code> may be reused because of Connection Pooling also).
<b>Action</b>	Change the application logic in such a way that an <code>XAConnection</code> is not used outside the transactional context. <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> for a workaround.

*JTS5042*

<b>Severity</b>	WARNING
<b>Description</b>	An error occurred while getting the transaction status.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*JTS5043*

<b>Severity</b>	SEVERE
<b>Description</b>	Failed to create <code>TransactionManager</code> instance.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*JTS5044*

<b>Severity</b>	WARNING
<b>Description</b>	An error occurred in getting or creating transaction state.

**Action** [Analyze the System](#), as described on [page 15](#).

### *JTS5045*

**Severity** WARNING

**Description** An error occurred in `beforeCompletion`.

**Action** [Analyze the System](#), as described on [page 15](#).

### *JTS5046*

**Severity** WARNING

**Description** The transaction is not active when the resource is trying to enlist the transaction.

**Action** [Analyze the System](#), as described on [page 15](#).

### *JTS5047*

**Severity** WARNING

**Description** The transaction object is unavailable when the resource is trying to enlist the transaction.

**Action** [Analyze the System](#), as described on [page 15](#).

### *JTS5049*

**Severity** SEVERE

**Description** Not able to activate XA Resource in the portable object adapters (POA).

**Action** [Analyze the System](#), as described on [page 15](#).

### *JTS5050*

**Severity** SEVERE

<b>Description</b>	Transaction timeout is negative.
<b>Action</b>	If the transaction timeout is set programmatically, make sure you set it to zero or any positive value. If it is set in the <code>server.xml</code> , go to the <code>transaction-service</code> element in the <code>server.xml</code> and change the <code>timeout-in-seconds</code> attribute value to zero or a positive value.

### *JTS5053*

<b>Severity</b>	SEVERE
<b>Description</b>	An internal occurred while reading distributed transaction log data.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *JTS5054*

<b>Severity</b>	WARNING
<b>Description</b>	An error occurred in <code>afterCompletion</code> .
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *JTS5055*

<b>Severity</b>	SEVERE
<b>Description</b>	Failed to get a CORBA reference for synchronization object.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### *JTS5059*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while recovering an <code>in-doubt</code> coordinator.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*JTS5062*

<b>Severity</b>	WARNING
<b>Description</b>	An error occurred while setting time-out on XA Resource
<b>Action</b>	Make sure XA Resource time-out is set correctly in the <code>server.xml</code> .

*JTS5063*

<b>Severity</b>	WARNING
<b>Description</b>	An XA exception occurred in <code>beforecompletion</code> .
<b>Action</b>	See the exception data for more details. Also see the XA error code and error message.





# Load Balancer Runtime

This chapter lists error messages that originate from the Load Balancer at runtime.

## LBRT

### *LBRT1004*

<b>Severity</b>	ERROR
<b>Description</b>	Internal error
<b>Action</b>	Restart the server.

LBRT

# Lifecycle Module

This chapter lists error messages that originate from the lifecycle module.

## LCM

The lifecycle module listens and performs tasks in response to events in the server life cycle. These modules are automatically initiated at server startup and are notified at various phases of the server life cycle.

### *LCM0101*

<b>Severity</b>	FATAL
<b>Description</b>	An error occurred while loading the server's life cycle listener module.
<b>Action</b>	Make sure that the life cycle module is in the server classpath. The classpath for the life cycle modules is configurable via the <code>server-classpath</code> attribute or the classpath of the <code>lifecycle-module</code> element.  You can also place the JAR file classes in the <code>&lt;install-root&gt;/domains/server1/lib/</code> or the classes in <code>&lt;install-root&gt;/domains/server1/classes</code> .
<b>See also</b>	<i>Developer's Guide</i> , chapter "Developing Lifecycle Listeners".

### *LCM0103*

<b>Severity</b>	FATAL
<b>Description</b>	The server is not able to startup due to an error loading a life cycle module. This occurs when the <code>is-failure-fatal</code> attribute is set to <code>true</code> and there is an error loading the module.

<b>Action</b>	Fix the error and restart the server. You can also set the <code>is-failure-fatal</code> attribute in <code>server.xml</code> to <code>false</code> . The server then ignores the error and continues the initialization and startup.
<b>See also</b>	<i>Developer's Guide</i> , chapter "Developing Lifecycle Listeners".

### LCM0105

<b>Severity</b>	FATAL
<b>Description</b>	An exception occurred when the server was setting up the life cycle module environment prior to invoking the module. This exception occurs due to an internal error.
<b>Action</b>	Refer to the stack trace in the exception. This indicates the reason why the internal error occurred. Restart the server instance. If the problem persists, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

### LCM0107

<b>Severity</b>	FATAL
<b>Description</b>	An exception occurred when the server was resetting the life cycle module environment after invoking the module. The exception occurs due to an internal error.
<b>Action</b>	Examine the exception stack and restart the server instance. If the problem persists, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

### LCM0201

<b>Severity</b>	WARNING
<b>Description</b>	A general exception occurred while running the life cycle module.
<b>Action</b>	Examine the exception stack and rectify the life cycle module code or the root cause of the exception.

*LCM0203*

<b>Severity</b>	WARNING
<b>Description</b>	An exception, <code>ServerLifecycleException</code> occurred while running the life cycle module.
<b>Action</b>	Examine the exception stack and rectify the root cause of the exception.

*LCM0205*

<b>Severity</b>	FATAL
<b>Description</b>	The server is about to shutdown while executing the life cycle modules. An exception stack trace may appear before this message.
<b>Action</b>	<ol style="list-style-type: none"><li>1. If the exception stack trace is available, examine the exception stack and rectify the root cause of the exception.</li><li>2. Examine the <code>is-failure-fatal</code> attribute in <code>server.xml</code> to see if the server can continue with these exceptions.</li></ol>



# Class Loader

This chapter lists error messages that originate from the class loader.

## LDR

A class loader is a Java component responsible for loading Java classes according to specific rules.

### *LDR5001*

<b>Severity</b>	WARNING
<b>Description</b>	The classloader failed to convert the path (as indicated in the error message) into a URL.
<b>Action</b>	Verify if the specified file path is valid and exists, and retry.

### *LDR5002*

<b>Severity</b>	WARNING
<b>Description</b>	An error occurred while undeploying an EJB.
<b>Action</b>	Refer to the exception data for more information.

*LDR5003*

<b>Severity</b>	SEVERE
<b>Description</b>	The unique ID specified in the EJB descriptor is automatically generated and updated during deployment or redeployment. The error occurs when it conflicts with an ID assigned to another EJB.
<b>Action</b>	Redploy the EJB, thereby forcing the unique ID to be regenerated.

*LDR5004*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while creating the EJB container.
<b>Action</b>	Refer to the exception data for information on how to fix this error.

*LDR5005*

<b>Severity</b>	WARNING
<b>Description</b>	An error occurred while unloading a Resource Adapter Reference (RAR).
<b>Action</b>	Refer to the exception data for information on how to fix this error.

*LDR5006*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while loading the application's deployment descriptor.
<b>Action</b>	Refer to the exception data for information on how to fix this error.



*LDR5007*

<b>Severity</b>	WARNING
<b>Description</b>	This error is caused by <a href="#">LDR5001</a> .
<b>Action</b>	Verify that the specified file path is valid and exists.

*LDR5008*

<b>Severity</b>	WARNING
<b>Description</b>	An error occurred while getting the deployment location of the deployed connector module.
<b>Action</b>	Refer to the exception data for details.

*LDR5009*

<b>Severity</b>	WARNING
<b>Description</b>	An error occurred while creating the URL.
<b>Action</b>	Make sure the filename and path is correct.

*LDR5011*

<b>Severity</b>	WARNING
<b>Description</b>	The class specified under the <code>&lt;ejb-class&gt;</code> element of the EJB deployment descriptor could not be found.
<b>Action</b>	Make sure the class exists in the deployment directory or the generated directory of the server instance.

*LDR5012*

<b>Severity</b>	SEVERE
<b>Description</b>	The JNDI name you assigned to the bean is already in use by another bean.
<b>Action</b>	Assign a different JNDI name to the bean.

*LDR5013*

<b>Severity</b>	SEVERE
<b>Description</b>	This is the actual exception caused by <a href="#">LDR5012</a> .
<b>Action</b>	Assign a different JNDI name to the bean.

*LDR5100*

<b>Severity</b>	SEVERE
<b>Description</b>	A configuration exception occurred.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*LDR5101*

<b>Severity</b>	SEVERE
<b>Description</b>	The META-INF/application.xml file could not be read, parsed or loaded.
<b>Action</b>	Verify that the META-INF/application.xml exists in the application's deployment directory and is formatted correctly.

*LDR5200*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception, <code>java.io.IOException</code> occurred while trying to access the application deployment directory.
<b>Action</b>	Ensure that the application deployment directory exists.

*LDR5201*

<b>Severity</b>	WARNING
<b>Description</b>	The environment property, <code>com.sun.aas.installRoot</code> is not set. Therefore, the location of the EJB class loader's <code>CodeSource</code> is set to the current working directory.
<b>Action</b>	This system property is set internally. <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*LDR5202*

<b>Severity</b>	WARNING
<b>Description</b>	An exception <code>java.io.IOException</code> occurred while trying to read the resource file from disk.
<b>Action</b>	Refer to the exception data for details.

LDR

# Message Driven Bean Container

This chapter lists error messages that originate from the message driven bean container.

## MDB

Message-driven beans are persistent objects that are likely to call a full range of JDBC interfaces, much like entity beans. However, message-driven beans have no local or remote interfaces as do other EJB components, and they differ from entity beans in how they are accessed.

A message-driven bean is a message listener that can reliably consume messages from a queue or a durable subscription. The messages may be sent by any J2EE component—from an application client, another EJB component, or a Web component—or from an application or a system that does not use J2EE technology.

### *MDB0002*

<b>Severity</b>	SEVERE
<b>Description</b>	Could not get server session. The message-driven bean's, <code>ejbCreate</code> method may have failed.
<b>Action</b>	Check the stack trace following this error message for reason.

### *MDB0004*

<b>Severity</b>	SEVERE
-----------------	--------

<b>Description</b>	The <code>getSession()</code> call failed while the session was still in use. It is likely that the JMS provider re-used the old <code>ServerSession</code> object instead of getting one from the <code>ServerSessionPool</code> .
<b>Action</b>	Lower the server's log level to get more information about the error and try again. If the problem persists, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*MDB0005*

<b>Severity</b>	SEVERE
<b>Description</b>	The <code>getSession()</code> call failed after the session was destroyed. It is likely that the JMS provider re-used an old <code>ServerSession</code> object that was destroyed instead of getting one from the <code>ServerSessionPool</code> .
<b>Action</b>	Lower the server's log level to get more information about the error and try again. If the problem persists, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*MDB0006*

<b>Severity</b>	SEVERE
<b>Description</b>	The <code>Get</code> session failed. There are several reasons for this failure. For example, creation of JMS Session or the message-driven bean <code>ejbCreate</code> method may have failed.
<b>Action</b>	Check the stack trace following this error message for reason or check the other error messages in the server log.

*MDB0008*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred in <code>Session.run()</code> .
<b>Action</b>	Check the server log for more information and check any runtime errors with the message-driven bean's <code>onMessage</code> method.

*MDB00010*

<b>Severity</b>	SEVERE
-----------------	--------

<b>Description</b>	An exception occurred while cleaning up <code>ServerSession</code> . The message-driven bean's <code>ejbRemove</code> method may have failed.
<b>Action</b>	Check the stack trace following this error message and other error messages in the server log for more information.

*MDB00012*

<b>Severity</b>	SEVERE
<b>Description</b>	<code>ServerSession.getSession()</code> must be called first before calling <code>ServerSession.start()</code> . It is likely that the JMS provider called the <code>ServerSession</code> methods in an incorrect sequence.
<b>Action</b>	Lower the server's log level to get more information about the error and try again. If the problem persists, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*MDB00013*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while creating <code>ServerSession</code> .
<b>Action</b>	Check the stack trace following this error message and other error messages in the server log.

*MDB00015*

<b>Severity</b>	SEVERE
<b>Description</b>	Message-driven bean's destination name not found.
<b>Action</b>	Check the stack trace following this error message for information on why this exception occurred.

*MDB00017*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while creating message-driven bean container.

**Action** See the stack trace following this error message for information on why this exception occurred.

### *MDB00020*

**Severity** SEVERE

**Description** An exception occurred while closing message-driven bean container.

**Action** See the exception in the error message. Lower the server's log level to get more information about the error and try again. If the problem persists, [Analyze the System](#), as described on [page 15](#).

### *MDB00021*

**Severity** SEVERE

**Description** Message-driven bean container's destination has a type mismatch.

**Action** See the error message for details. Check the message-driven bean's deployment descriptors and the `type` of the JMS destination that the message-driven bean listens and correct the type mismatch.

### *MDB00023*

**Severity** WARNING

**Description** The message-driven bean's deployment descriptor element, `jms-max-messages-load` has an invalid value.

**Action** Correct the invalid `jms-max-messages-load` value in the message-driven bean's deployment descriptor element.

### *MDB00024*

**Severity** SEVERE

**Description** Message-driven bean container's connection factory not found.

**Action** Check the JMS connection factory resource configuration for the message-driven bean container. Check the stack trace information following this error message for information on why the error occurred.



*MDB00025*

<b>Severity</b>	SEVERE
<b>Description</b>	Message-driven bean container's connection factory has a type mismatch.
<b>Action</b>	See the error message for detail. Check the message-driven bean's deployment descriptors and the type of the JMS connection factory for the message-driven bean container and correct the type mismatch.

*MDB00026*

<b>Severity</b>	SEVERE
<b>Description</b>	Unable to start the message-driven bean container connection.
<b>Action</b>	See the error message for reason. Check the stack trace following this error message.

*MDB00027*

<b>Severity</b>	SEVERE
<b>Description</b>	A connection exception event occurred.
<b>Action</b>	See the error message for details. The message-driven bean container's connection to the JMS provider is broken. Check the stack trace following this error message. Check if the JMS provider's message server is still running.

*MDB00029*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while registering the bean-pool monitor for a message-driven bean.
<b>Action</b>	See the error message for reason. Lower the server's log level to get more information about the error and try again. If the problem persists, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*MDB00030*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while setting up the message-driven bean container.
<b>Action</b>	See the error message and other error messages in the server log for reason.

*MDB00031*

<b>Severity</b>	WARNING
<b>Description</b>	Message-driven bean container's connection factory not found. The default connection factory which connects to the built-in Sun Java System Message Queue server will be used instead.
<b>Action</b>	Check the configuration of the JMS connection factory resource for the message-driven bean container.

*MDB00032*

<b>Severity</b>	WARNING
<b>Description</b>	Message-driven bean container's connection factory not found. The default connection factory which connects to the built-in Sun Java System Message Queue server will be used instead.
<b>Action</b>	If you are using the default JMS connection factory, and it is not intended for the message-driven bean, add the <code>mdb-connection-factory</code> to the message-driven bean deployment descriptor and redeploy the application.

*MDB00035*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred after closing the message-driven bean pool.
<b>Action</b>	See the error message and the stack trace following this error message for reason.

*MDB00036*

<b>Severity</b>	SEVERE
<b>Description</b>	Pre-invocation of message-driven bean failed.
<b>Action</b>	See the stack trace following this error message and other error messages in the server log for more information.

*MDB00037*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred during message-driven bean invocation.
<b>Action</b>	The message-driven bean container pre-invocation failed. See the error message for reason. Check the stack trace following this error message and other error messages in the server log for more information.

*MDB00038*

<b>Severity</b>	SEVERE
<b>Description</b>	No message-driven bean context in message listener.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*MDB00039*

<b>Severity</b>	SEVERE
<b>Description</b>	Message sent to a destroyed message-driven bean.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

*MDB00041*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred in the message-driven bean's <code>onMessage</code> method.

**Action** See the error message for reason. Lower the server's log level to get more information about the error and try again. If the problem persists, [Analyze the System](#), as described on [page 15](#).

### *MDB00042*

**Severity** SEVERE  
**Description** No invocation for message.  
**Action** See other error messages in the server log for more information.

### *MDB00043*

**Severity** WARNING  
**Description** An exception occurred while reading the `mdb-container` configuration.  
**Action** See the error message for reason. Check valid values in the `mdb-container` element in `server.xml`.

### *MDB00046*

**Severity** SEVERE  
**Description** The message-driven bean's `onMessage` method threw a run time exception.  
**Action** Check the message-driven bean's `onMessage` method for abnormal runtime behavior. Lowering the server's log level may give more information.

### *MDB00047*

**Severity** SEVERE  
**Description** Some application or unchecked exception occurred.  
**Action** See the error message and other error messages in the server log for more information.

*MDB00048*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred in the message-driven bean's pre-invocation.
<b>Action</b>	See the error message for reason. Check other error messages and stack traces in the server log for more information.

*MDB00049*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred in the message-driven bean's post-invocation.
<b>Action</b>	See the error message for reason. Check the stack trace following this error message and other error messages in the server log for more information.

*MDB00050*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while creating message-driven bean.
<b>Action</b>	See the error message and the stack trace following this error message for reason.

*MDB00051*

<b>Severity</b>	SEVERE
<b>Description</b>	The message-driven bean container pre-invocation of <code>ejbRemove</code> method or <code>ejbRemove</code> method may have failed.
<b>Action</b>	Check the error message and the stack trace following this error message for more information.

*MDB00052*

<b>Severity</b>	SEVERE
<b>Description</b>	Start message delivery for the message-driven bean container failed.

**Action** See the error message and the stack trace following this error message for information.

### *MDB00053*

**Severity** SEVERE

**Description** Message-driven bean container has a cleanup exception.

**Action** See the error message and the stack trace following this error message for more information.

### *MDB00054*

**Severity** SEVERE

**Description** An exception occurred while setting message-driven bean context.

**Action** See the error message and the stack trace following this error message for reason.

### *MDB00055*

**Severity** SEVERE

**Description** An exception occurred while closing message-driven bean container's `ConnectionConsumer`.

**Action** See the error message and the stack trace following this error message for reason.

### *MDB00058*

**Severity** SEVERE

**Description** The message-driven bean container's JMS connection threw an exception during server shutdown.

**Action** See the error message for the connection exception.

*MDB00060*

<b>Severity</b>	SEVERE
<b>Description</b>	An invalid or inconsistent attribute value was found in the mdb-container element in server.xml value.
<b>Action</b>	Check valid values in mdb-container element in server.xml.

MDB



# Resource Adapter

This chapter lists error messages that originate from the resource adapter.

## RAR

### *RAR5001*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while returning an object to the pool. This error occurred while closing a <code>ManagedConnection</code> from the resource adapter.
<b>Action</b>	Contact the vendor of the resource adapter for support.

### *RAR5002*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred in the monitoring pool size. This error occurs while closing a <code>ManagedConnection</code> from the resource adapter.
<b>Action</b>	Contact the vendor of the resource adapter for support.

### *RAR5003*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while loading the <code>server.xml</code> .
<b>Action</b>	Make sure you have access to <code>server.xml</code> file.

*RAR5004*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred during the XA recovery process.
<b>Action</b>	See the transaction log for more information on the recovery process.

*RAR5005*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred during the XA recovery process.
<b>Action</b>	See the transaction log for more information on the recovery process.

*RAR5007*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while creating a data source object.
<b>Action</b>	Enable the debugger to get more information on why this error occurred.

*RAR5008*

<b>Severity</b>	SEVERE
<b>Description</b>	A generic exception occurred while creating a custom resource.
<b>Action</b>	Make sure that the custom resource that are installed are correct.

*RAR5009*

<b>Severity</b>	WARNING
<b>Description</b>	Unable to load external-jndi-resource factory-class.
<b>Action</b>	See the <code>InitialContextFactory</code> class for the external resource and make sure that it is available in the server classpath.

*RAR5010*

<b>Severity</b>	WARNING
<b>Description</b>	The external-jndi-resource factory-class must be of type <code>javax.naming.spi.InitialContextFactory</code> .
<b>Action</b>	Ensure that the <code>InitialContextFactory</code> class provided is an instance of <code>javax.naming.spi.InitialContextFactory</code> .

*RAR5011*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while creating the initial context for the external JNDI factory.
<b>Action</b>	The loading of <code>InitialContextFactory</code> was successful. However, make sure that the other properties of the resource being installed are correct.

*RAR5012*

<b>Severity</b>	SEVERE
<b>Description</b>	Unable to create an external-jndi-resource factory-class.
<b>Action</b>	The loading of <code>InitialContextFactory</code> was successful. However, make sure that the other properties of the resource being installed are correct.

*RAR5015*

<b>Severity</b>	SEVERE
-----------------	--------

<b>Description</b>	An exception occurred while loading the class.
<b>Action</b>	Make sure the classpath of <code>InitialContextFactory</code> class is correct.

### *RAR5016*

<b>Severity</b>	WARNING
<b>Description</b>	While uninstalling the resource adapter, the <code>server.xml</code> could not be changed and an exception occurred.
<b>Action</b>	Make sure you have access to the <code>server.xml</code> file.

### *RAR5017*

<b>Severity</b>	SEVERE
<b>Description</b>	Unable to locate the connection descriptor name.
<b>Action</b>	Make sure the <code>DeploymentDescriptor</code> of the resource adapter being installed is correct.

### *RAR5018*

<b>Severity</b>	SEVERE
<b>Description</b>	Unable to create connection factory.
<b>Action</b>	Make sure all the properties related to the connection factory are correct.

### *RAR5019*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while loading the JAR file during inspection.
<b>Action</b>	Make sure you have proper access permissions to the <code>.jar</code> file.

*RAR5024*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while adding a resource to the configuration file.
<b>Action</b>	Make sure there is sufficient disk space and that the user has appropriate directory access permission.

*RAR5025*

<b>Severity</b>	WARNING
<b>Description</b>	An error occurred while removing the J2EE resource.
<b>Action</b>	Make sure there is sufficient disk space and that the user has appropriate directory access permission.

*RAR5026*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred due to an incomplete transaction.
<b>Action</b>	See the exception message that appears along with this message and the transaction manager error logs for information on why this error occurred.

*RAR5027*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred in resource pooling.
<b>Action</b>	See the exception message that appears along with this message for information on why this error occurred.

*RAR5028*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred in the number formatting.

<b>Action</b>	Ensure that the <code>idle.resource.threshold</code> value in the configuration file is a numeric value.
---------------	--

### *RAR5029*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while registering the component.
<b>Action</b>	See the transaction logs for more information.

### *RAR5030*

<b>Severity</b>	WARNING
<b>Description</b>	An exception occurred while registering the synchronization.
<b>Action</b>	See the exception message that appears along with this message for information on why the error occurred.

### *RAR5031*

<b>Severity</b>	WARNING
<b>Description</b>	A system exception occurred while unregistering a resource. There may be an error in the resource.
<b>Action</b>	See the server log files for more information.

### *RAR5032*

<b>Severity</b>	WARNING
<b>Description</b>	An exception occurred while returning the resource to the pool.
<b>Action</b>	See the accompanying exception message for more information on why this error occurred.

*RAR5034*

<b>Severity</b>	SEVERE
<b>Description</b>	Unable to resize pools.
<b>Action</b>	Modify the size of the pool quantity and try again.

*RAR5035*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while closing a resource (JDBC/JMS/Connector).
<b>Action</b>	See the exception message for more information on why this error occurred.

*RAR5040*

<b>Severity</b>	SEVERE
<b>Description</b>	Unable to get local connection.
<b>Action</b>	See the accompanying exception message for more information.

*RAR5041*

<b>Severity</b>	SEVERE
<b>Description</b>	Unable to get JDBC connection.
<b>Action</b>	See the accompanying exception message for more information.

*RAR5042*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while accessing the XA resource for recovery.
<b>Action</b>	See the transaction log for more information on the recovery process.

*RAR5043*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while creating the data source object.
<b>Action</b>	Enable the debugger to get information on how to correct this error.

*RAR5045*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while creating a naming reference for custom resource.
<b>Action</b>	Make sure that the custom resource being installed are correct.

*RAR5046*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while the classloader was loading the class.
<b>Action</b>	Make sure the classpath of <code>InitialContextFactory</code> class supplied is correct.

*RAR5047*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while creating initial context for external JNDI factory.
<b>Action</b>	The loading of <code>InitialContextFactory</code> was successful. However, make sure that the other properties of the resource that are installed are correct.

*RAR5049*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while publishing JDBC connection pool resource.



**Action** Make sure that the connection pool properties in the `server.xml` are correct.

### *RAR5050*

**Severity** WARNING

**Description** JDBC connection pool has an invalid validation type. The default is set to *false*.

**Action** Make sure that the connection validation type is correct.

### *RAR5051*

**Severity** SEVERE

**Description** The JDBC pool monitoring bean registration failed.

**Action** See the accompanying exception message for more information.

### *RAR5055*

**Severity** SEVERE

**Description** Missing parameter in properties file.

**Action** Ensure that `IASIndiNames.properties` has all the values required.

### *RAR5056*

**Severity** SEVERE

**Description** Failed to parse the XML deployment descriptor.

**Action** Make sure that deployment descriptor is correct.

### *RAR5057*

**Severity** SEVERE

<b>Description</b>	Failed to parse the XML deployment descriptor.
<b>Action</b>	Make sure that deployment descriptor is correct.

### *RAR5058*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while resizing the pool.
<b>Action</b>	See the accompanying exception message for more information.

# Runtime

This chapter lists error messages that originate at runtime.

## RNTM

### *RNTM2024*

<b>Severity</b>	WARNING
<b>Description</b>	Application server instance is detected to be unhealthy.
<b>Action</b>	Check the application server instance, and bring it up.

### *RNTM2029*

<b>Severity</b>	WARNING
<b>Description</b>	Application server instance may be rejecting connections because of saturation.
<b>Action</b>	Check the health of the application server instance, and check the network traffic between the loadbalancer and the application server instance.

### *RNTM2030*

<b>Severity</b>	WARNING
<b>Description</b>	Application server instance may be down.
<b>Action</b>	Check the health of the application server instance.

*RNTM3000*

<b>Severity</b>	ERROR
<b>Description</b>	Internal error
<b>Action</b>	Restart the server.

*RNTM3001*

<b>Severity</b>	ERROR
<b>Description</b>	Application server instance listener url has an error.
<b>Action</b>	Check the loadbalancer.xml for any errors in the listeners attribute of instance element. Check the DNS configuration for any errors.

*RNTM3002*

<b>Severity</b>	ERROR
<b>Description</b>	Two listeners are having the same value which is not allowed.
<b>Action</b>	Check the loadbalancer.xml for any duplicate entries for listeners.

*RNTM3003*

<b>Severity</b>	ERROR
<b>Description</b>	Internal error while disabling instance or application.
<b>Action</b>	Restart the server.

*RNTM3005*

<b>Severity</b>	ERROR
<b>Description</b>	Failed to initialize load balancing subsystem.
<b>Action</b>	Check the loadbalancer.xml file and the path to it.

*RNTM3007*

<b>Severity</b>	WARNING
<b>Description</b>	Invalid error file.
<b>Action</b>	Check the loadbalancer.xml and the error-url attribute of web-module element.

RNTM

# Router

This chapter lists error messages that originate from the router.

## ROUT

### *ROUT1014*

<b>Severity</b>	WARNING
<b>Description</b>	An error happened while servicing the request. As the URL is not idempotent, it cannot be retried.
<b>Action</b>	Check the health of the application server instance and the response-timeout-in-seconds parameter in loadbalancer.xml. Increase the timeout and try again.

ROUT



# Security Services

This chapter lists error messages that originate from the security services.

## SEC

### *SEC1000*

<b>Severity</b>	WARNING
<b>Description</b>	Generic exception information report.
<b>Action</b>	Refer to exception data. To understand the context of this log message, see the other log messages reported along with this message.

### *SEC1050*

<b>Severity</b>	WARNING
<b>Description</b>	Certificate realm is not configured properly.
<b>Action</b>	If an application is using certificate client authentication, set the realm name to <code>certificate</code> in the <code>server.xml</code> file.
<b>See Also</b>	<i>Developer's Guide</i> , chapter "Securing J2EE Applications".

## SEC1100

<b>Severity</b>	WARNING
<b>Description</b>	Realm configuration had a fatal error and is therefore disabled.
<b>Action</b>	To understand the context of this log message, see the other log messages reported along with this message. Correct the realm configuration and restart the server.
<b>See Also</b>	<i>Developer's Guide</i> , chapter "Securing J2EE Applications".

## SEC1101

<b>Severity</b>	SEVERE
<b>Description</b>	All configured realms are invalid. Application Server requires at least one valid realm to run.
<b>Action</b>	Verify and fix the configuration of <code>auth-realm</code> entries in <code>server.xml</code> .
<b>See Also</b>	<i>Developer's Guide</i> , chapter "Securing J2EE Applications".

## SEC1102

<b>Severity</b>	WARNING
<b>Description</b>	The configuration for this realm lacks a JAAS context property.
<b>Action</b>	Verify and fix the <code>jaas-context</code> property of the realm configuration in <code>server.xml</code> .
<b>See Also</b>	<i>Developer's Guide</i> , chapter "Securing J2EE Applications".

## SEC1103

<b>Severity</b>	WARNING
<b>Description</b>	A non-existent authentication handler has been requested.
<b>Action</b>	<p>If you are using a realm provided in the Application Server, <a href="#">Analyze the System</a>, as described on <a href="#">page 15</a>.</p> <p>If you are using a custom or third-party realm, contact the vendor for support.</p>

## SEC1104

<b>Severity</b>	WARNING
<b>Description</b>	A non-existent credential has been requested.
<b>Action</b>	See exception for more details. If you are using a realm provided in the Application Server, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> . If you are using a custom or third-party realm, contact the vendor for support.

## SEC1105

<b>Severity</b>	WARNING
<b>Description</b>	A non-existent password credential has been requested.
<b>Action</b>	See exception for more details. If you are using a realm provided in the Application Server, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> . If you are using a custom or third-party realm, contact the vendor adapter for support.

## SEC1106

<b>Severity</b>	WARNING
<b>Description</b>	LDAP server returned an error during search operation.
<b>Action</b>	See the server log for search query details. Also refer the LDAP server logs, which may contain more information about the failure of search operation.

## SEC1108

<b>Severity</b>	WARNING
<b>Description</b>	An error occurred while writing to the realm data file. Updates to the data file were most likely lost.
<b>Action</b>	Verify and fix the contents of the realm data file. See exception for error details.

## SEC1109

<b>Severity</b>	WARNING
<b>Description</b>	Server was unable to read the realm data file.
<b>Action</b>	See exception for error details. Verify that the file exists, and if it does, make sure it is readable and the data is not corrupt.

## SEC1110

<b>Severity</b>	WARNING
<b>Description</b>	Certificate realm has been queried for JAAS context, indicating a misconfiguration.
<b>Action</b>	Fix the configuration of <code>auth-realm</code> entries in <code>server.xml</code> .
<b>See Also</b>	<i>Developer's Guide</i> , chapter "Securing J2EE Applications".

## SEC1120

<b>Severity</b>	WARNING
<b>Description</b>	Configuration error in <code>audit-enabled</code> option in <code>server.xml</code> .
<b>Action</b>	Fix the <code>audit-enabled</code> option in <code>server.xml</code> , in the <code>security-service</code> element.

## SEC1130

<b>Severity</b>	WARNING
<b>Description</b>	Application code does not have permission to invoke programmatic login.
<b>Action</b>	Grant required permissions to your application.
<b>See Also</b>	<i>Developer's Guide</i> , chapter "Securing J2EE Applications".

## SEC1132

<b>Severity</b>	WARNING
-----------------	---------

<b>Description</b>	An internal error occurred while processing programmatic login.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### SEC1133

<b>Severity</b>	WARNING
<b>Description</b>	Illegal access of internal interfaces.
<b>Action</b>	Contact the vendor of the application for support.

### SEC5022

<b>Severity</b>	WARNING
<b>Description</b>	Error reading <code>anonymous-role</code> option in <code>server.xml</code> .
<b>Action</b>	Fix the <code>anonymous-role</code> option of the <code>security-service</code> element in <code>server.xml</code> .
<b>See Also</b>	<i>Developer's Guide</i> , chapter "Securing J2EE Applications".

### SEC5023

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred while querying group membership for <code>principal</code> .
<b>Action</b>	See exception for more details. If you are using a realm provided in the Application Server, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> . If you are using a custom or third-party realm, contact the vendor for support.

### SEC5024

<b>Severity</b>	SEVERE
<b>Description</b>	Internal error processing credentials.
<b>Action</b>	See exception for more details. If you are using a realm provided in the Application Server, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> . If you are using a custom or third-party realm, contact the vendor for support.

SEC5037

Severity	WARNING
Description	Error reading default-principal attribute from server.xml.
Action	Check server.xml for default-principal attribute in security-service. This is an optional attribute and should <i>not</i> be specified.

SEC5038

Severity	WARNING
Description	Internal error establishing default security context.
Action	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

SEC5041

Severity	SEVERE
Description	Error loading or initializing a realm.
Action	See exception for more details. Verify realm configuration in server.xml. If you are using a custom or third-party realm, contact the vendor for support.

SEC5042

Severity	SEVERE
Description	Error creating a realm instance.
Action	See exception for more details. Verify the realm configuration in server.xml. If you are using a realm provided in the Application Server, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> . If you are using a custom or third-party realm, contact the vendor for support.

SEC5043

Severity	SEVERE
----------	--------

<b>Description</b>	An internal error occurred while processing authentication.
<b>Action</b>	See exception for more details. If you are using a realm provided in the Application Server, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> . If you are using a custom or third-party realm, contact the vendor for support.

### *SEC5044*

<b>Severity</b>	SEVERE
<b>Description</b>	An internal error occurred while processing authentication.
<b>Action</b>	See exception for more details. If you are using a realm provided in the Application Server, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> . If you are using a custom or third-party realm, contact the vendor for support.

### *SEC5100*

<b>Severity</b>	WARNING
<b>Description</b>	An internal error has occurred.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .





# UTIL Services

This chapter lists error messages that originate from the Utility services.

## UTIL

### *UTIL6003*

<b>Severity</b>	SEVERE
<b>Description</b>	A malformed URL exception occurred in <code>ConnectorClassLoader</code> while trying to add a resource adapter.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

### *UTIL6004*

<b>Severity</b>	SEVERE
<b>Description</b>	An IO exception occurred while loading the properties from <code>cis.properties</code> file.
<b>Action</b>	Ensure that the formatting of entries in the properties file is correct.

### *UTIL6005*

<b>Severity</b>	SEVERE
<b>Description</b>	A malformed URL exception occurred in <code>com/sun/enterprise/util/EJBClassLoader</code> .

**Action** [Analyze the System](#), as described on [page 15](#) with the stack trace information.

### *UTIL6007*

**Severity** SEVERE

**Description** An exception occurred while creating a new ZIP file from a group of entries. One of the entries is invalid.

**Action** [Analyze the System](#), as described on [page 15](#) with the stack trace information.

### *UTIL6009*

**Severity** SEVERE

**Description** A config exception occurred in the ORB Manager. Some errors occurred while getting the IIOP service and the IIOP listener associated values from `server.xml`.

**Action** See if the values for the IIOP service and IIOP listener in `server.xml` are correct and properly formatted.

### *UTIL6017*

**Severity** SEVERE

**Description** An internal error occurred.

**Action** [Analyze the System](#), as described on [page 15](#) with the server log information.

### *UTIL6018*

**Severity** SEVERE

**Description** An internal error occurred.

**Action** [Analyze the System](#), as described on [page 15](#) with the server log information.

*UTIL6021*

<b>Severity</b>	SEVERE
<b>Description</b>	When an invalid number of arguments are passed to this JAR utility, an error message is logged in <code>server.log</code> .
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the server log information.

*UTIL6024*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred in <code>FileUtil.CountWords()</code> .
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

*UTIL6027*

<b>Severity</b>	SEVERE
<b>Description</b>	An exception occurred in <code>invokeApplicationMain</code> .
<b>Action</b>	Make sure that <code>invokeApplicationMain</code> is present in the specified class.

*UTIL6028*

<b>Severity</b>	WARNING
<b>Description</b>	This exception occurs if you are running a test for equality of two JAR entry fails.
<b>Action</b>	No action required.

*UTIL6031*

<b>Severity</b>	WARNING
<b>Description</b>	There was an error in the format of a numeric quantity in <code>server.xml</code> .
<b>Action</b>	See the stack trace information to locate the erroneous numeric quantity.

*UTIL6032*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while initializing the monitoring mechanism for ORB connections.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

*UTIL6033*

<b>Severity</b>	SEVERE
<b>Description</b>	Problem initializing monitoring for the ORB threadpool.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the full stack trace information.

*UTIL6034*

<b>Severity</b>	SEVERE
<b>Description</b>	A generic error occurred while initializing the ORB monitoring mechanism.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

*UTIL6035*

<b>Severity</b>	WARNING
<b>Description</b>	The numeric format of the ORB message fragment size is incorrect.
<b>Action</b>	Correct the numeric format of the ORB message fragment size attribute in <code>server.xml</code> . The default value was used.

*UTIL6045*

<b>Severity</b>	WARNING
<b>Description</b>	Could not create the default reporter.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

### UTIL6545

<b>Severity</b>	WARNING
<b>Description</b>	An internal error occurred in the reporter. Unable to find/make default reporter.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

### UTIL6548

<b>Severity</b>	SEVERE
<b>Description</b>	An internal exception occurred.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

### UTIL6549

<b>Severity</b>	SEVERE
<b>Description</b>	An IO exception occurred.
<b>Action</b>	Make sure you have Write access permission to create the file in the directory specified.

### UTIL6550

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred in the local string manager. The resource bundle may be missing.
<b>Action</b>	Make sure you have specified the correct package name.

### UTIL6551

<b>Severity</b>	SEVERE
<b>Description</b>	An internal error occurred while storing the local string manager into a hash table. The package name or the string manager may be null.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the stack trace information.

### *UTIL6552*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while constructing the local string manager object.
<b>Action</b>	<p>Possible reasons and action to be taken to correct this error are:</p> <ul style="list-style-type: none"><li>• No resource bundle properties file found. Make sure you have specified a correct package name.</li><li>• An internal error occurred. <a href="#">Analyze the System</a>, as described on <a href="#">page 15</a> with the stack trace information.</li></ul>

### *UTIL6553*

<b>Severity</b>	WARNING
<b>Description</b>	An error occurred while formatting the local string.
<b>Action</b>	An internal error occurred while trying to format the error message. <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> with the detailed stack trace.

### *UTIL8050*

<b>Severity</b>	WARNING
<b>Description</b>	Maximum entries in the cache is specified as 0 or less than 0.
<b>Action</b>	Check the configuration of the cache. Set the maximum entries to a value greater than 0.
<b>See Also</b>	<a href="#">UTIL8051</a>

### *UTIL8051*

<b>Severity</b>	WARNING
<b>Description</b>	Maximum entries in the cache is specified as 0 or less than 0.
<b>Action</b>	Check the configuration of the cache. Set the maximum entries to a value greater than 0.

# Verifier Tool

This chapter lists error messages that originate from the verifier tool.

## VRFY

The verifier tool validates both J2EE and Application Server specific deployment descriptors against their corresponding DTD files and gives errors and warnings if a module or application is not J2EE and Application Server compliant. You can verify deployment descriptors in EAR, WAR, RAR, and JAR files.

The verifier tool is not simply an XML syntax verifier. Rules and interdependencies between various elements in the deployment descriptors are verified. Where needed, user application classes are introspected to apply validation rules.

### *VRFY5001*

<b>Severity</b>	SEVERE
<b>Description</b>	The specified class could not be instantiated.
<b>Action</b>	Make sure the class to be instantiated is not an interface or an abstract class.

### *VRFY5002*

<b>Severity</b>	SEVERE
<b>Description</b>	The specified class was not found.
<b>Action</b>	Make sure the specified class is in the classpath.

### VRFY5003

<b>Severity</b>	SEVERE
<b>Description</b>	The class could not be accessed.
<b>Action</b>	Make sure you have access to the class. The method or class called does not have the specified access.

### VRFY5101

<b>Severity</b>	WARNING
<b>Description</b>	There was an IO exception reading and parsing the <code>ServerTestList.xml</code> file.
<b>Action</b>	The <code>ServerTestList.xml</code> file resides in the <code>&lt;install-root&gt;/lib</code> directory. Make sure this file exists and has Read permissions. Do <i>not</i> modify this file manually.

### VRFY5102

<b>Severity</b>	WARNING
<b>Description</b>	A parser configuration exception occurred while instantiating the parser.
<b>Action</b>	Make sure the correct parser is in the server classpath. This error occurs only when the server has been configured to use another parser other than the default parser bundled with JDK1.4.

### VRFY5103

<b>Severity</b>	WARNING
<b>Description</b>	An error occurred while parsing the <code>ServerTestList.xml</code> file due to a <code>SAXParseException</code> .
<b>Action</b>	The <code>ServerTestList.xml</code> file resides in the <code>&lt;install-root&gt;/lib</code> directory. Make sure this file has Read permissions and is a valid XML document. This exception occurs only when the <code>ServerTestList.xml</code> file has been manually edited and saved, or the file is not a valid XML document. Do <i>not</i> modify this file manually.



# Web Container

This chapter lists error messages that originate from the web container.

## WEB

### *WEB0101*

<b>Severity</b>	SEVERE
<b>Description</b>	A generic exception occurred while loading a web application.
<b>Action</b>	Refer to exception data to determine the cause of the problem. Correct the errors, and redeploy or reload the application.

### *WEB0102*

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred that prevents the web container from functioning correctly.
<b>Action</b>	Restart the server instance. If the problem persists, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

**WEB0103**

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred that prevents the web container from functioning correctly.
<b>Action</b>	Restart the server instance. If the problem persists, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

**WEB0104**

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred that prevents the web container from functioning correctly.
<b>Action</b>	Restart the server instance. If the problem persists, then <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

**WEB0105**

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred during web container startup.
<b>Action</b>	Refer to exception data to determine the cause of the problem. Correct the errors, and redeploy or reload the application.

**WEB0106**

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while stopping the web container. All the web applications may not have shutdown properly. Loss of session data might occur even if the session is configured for <i>persistence</i> .
<b>Action</b>	Refer to exception data to determine the cause of the problem.

**WEB0107**

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred in the configuration specified in <code>server.xml</code> .

<b>Action</b>	Refer to exception data to determine the cause of the configuration error. Correct the errors and reconfigure the server.
<b>See Also</b>	<i>Configuration File Reference.</i>

## WEB0108

<b>Severity</b>	SEVERE
<b>Description</b>	The path specified in the <code>extra-class-path</code> attribute of the <code>class-loader</code> element in <code>sun-web.xml</code> does not exist.
<b>Action</b>	Ensure that the correct path separator (":" for UNIX and ";" for Windows) is used to separate the path components of the <code>extra-class-path</code> attribute. Ensure that the file and directory specified in this error message exists. Correct the errors and redeploy or reload the application.
<b>See Also</b>	<i>Developer's Guide to Web Applications</i> , chapter "Assembling and Deploying Web Modules".

## WEB0112

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while loading the specified web application.
<b>Action</b>	To understand the context of this log message, refer the other log messages reported along with this message. Correct the errors and redeploy the application.

## WEB0113

<b>Severity</b>	SEVERE
<b>Description</b>	The context-root of the specified web application is already in use by another web application.
<b>Action</b>	Change the context-root from where the specified web application is deployed. Redeploy or reload the application.

- See Also**
- *Developer's Guide to Web Applications*, chapter “Assembling and Deploying Web Modules”.
  - *Java 2 Platform Enterprise Edition Specification 1.3*, chapter “Application Assembly and Deployment - J2EE”.
  - *Administrator's Configuration File Reference*, chapter “Server Configuration Files”.

## WEB0202

- Severity** SEVERE
- Description** An error occurred in the `server.xml` configuration of the specified `<virtual-server>` element.
- Action** Ensure that `<virtual-server>` element exists in `server.xml` corresponding to the virtual server specified in this error message.  
Correct the errors and redeploy or reload the application.
- See Also** *Administrator's Configuration File Reference*, chapter “Server Configuration Files”.

## WEB0203

- Severity** SEVERE
- Description** An error occurred that indicates that there is no web-module information in `server.xml` corresponding to the name used in the `default-web-module` attribute of the specified `virtual-server` element.
- Action** Ensure that the value used in the `default-web-module` attribute corresponds to a value specified in one of the web-module's “name” attribute in `server.xml`. Correct the errors and redeploy or reload the application.
- See Also**
- *Administrator's Configuration File Reference*, chapter “Server Configuration Files”.
  - *Administrator's Configuration File Reference*, chapter “Server Configuration Files”.

## WEB0204

- Severity** SEVERE

<b>Description</b>	The web module specified by the <code>default-web-module</code> attribute of the virtual server has been disabled in <code>server.xml</code> . As a result, the system default web module is deployed as the default web module for this virtual server.
<b>Action</b>	Enable the web module and reconfigure the instance by applying the changes.
<b>See Also</b>	<i>Administrator's Guide</i> , chapter "Deploying Applications".

### WEB1001

<b>Severity</b>	SEVERE
<b>Description</b>	An invalid character encoding was used to decode parameters in the request.
<b>Action</b>	Ensure that any character encoding specified in <code>sun-web.xml</code> is one of the supported encodings. Redeploy or reload the application.
<b>See Also</b>	<ul style="list-style-type: none"> <li>• <i>Java Servlet Specification Version 2.3</i>, chapter "SRV.4.9 Request data encoding".</li> <li>• <i>Developer's Guide to Web Applications</i> chapter "Assembling and Deploying Web Modules".</li> </ul>

### WEB1002

<b>Severity</b>	SEVERE
<b>Description</b>	Indicates an input or output error while reading form POST data.
<b>Action</b>	Resubmit the form.

### WEB2001

<b>Severity</b>	SEVERE
<b>Description</b>	Generic message when an error occurs while processing a web application request.
<b>Action</b>	To understand the context of this error message, refer the other log messages reported along with this message.

### *WEB4002*

<b>Severity</b>	SEVERE
<b>Description</b>	Indicates an irrecoverable error while initializing the specified virtual server.
<b>Action</b>	<p>Refer to the messages logged along with this message to determine the cause of the error.</p> <p>If this error occurs during startup the server startup fails and the errors must be fixed before the server can successfully start. If the server is already running this error does not affect the server that is running. Correct the errors and apply the changes to the server.</p>

### *WEB5002*

<b>Severity</b>	SEVERE
<b>Description</b>	A generic message when an error occurs while processing a web application request.
<b>Action</b>	To understand the context of this error message, refer the other log messages reported along with this message.

### *WEB5003*

<b>Severity</b>	SEVERE
<b>Description</b>	A generic message when an error occurs while processing a web application request.
<b>Action</b>	To understand the context of this error message, refer the other log messages reported along with this message.

### *WEB5004*

<b>Severity</b>	SEVERE
<b>Description</b>	Generic message when an error occurs while processing a web application request.
<b>Action</b>	To understand the context of this error message, refer the other log messages reported along with this message.

### WEB5005

<b>Severity</b>	SEVERE
<b>Description</b>	Generic message when an error occurs while processing a web application request.
<b>Action</b>	To understand the context of this error message, refer the other log messages reported along with this message.

### WEB6000

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred that prevents the web container from functioning correctly.
<b>Action</b>	Restart the server instance. If the problem persists, <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### WEB6001

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred when creating or configuring the servlet caching subsystem. Does not affect other web applications.
<b>Action</b>	To understand the context of this error message, refer the other log messages reported along with this message. Correct the errors in the servlet cache configuration in <code>sun-web.xml</code> and redeploy or reload the application.
<b>See Also</b>	<ul style="list-style-type: none"> <li>• <i>Developer's Guide to Web Applications</i>, chapter “Using Servlets”.</li> <li>• <i>Developer's Guide to Web Applications</i>, chapter “Assembling and Deploying Web Modules”.</li> </ul>

### WEB8001

<b>Severity</b>	SEVERE
<b>Description</b>	An error occurred while creating or configuring the servlet caching subsystem of a web application.

<b>Action</b>	To understand the context of this error message, refer the other log messages reported along with this message. Correct the errors in the servlet cache configuration in <code>sun-web.xml</code> . Redeploy or reload the application.  This error does not affect other web applications.
<b>See Also</b>	<ul style="list-style-type: none"><li>• <i>Developer's Guide to Web Applications</i>, chapter “Using Servlets”.</li><li>• <i>Developer's Guide to Web Applications</i>, chapter “Assembling and Deploying Web Modules”.</li></ul>

## WEB8002

<b>Severity</b>	SEVERE
<b>Description</b>	Indicates an error during initialization of the <code>CacheHelper</code> class of the caching subsystem of a web application.
<b>Action</b>	Refer the other log messages reported along with this message and correct the cache helper implementation accordingly. Redeploy or reload the application.  This error does not affect other web applications.
<b>See Also</b>	<ul style="list-style-type: none"><li>• <i>Developer's Guide to Web Applications</i>, chapter “Using Servlets”.</li><li>• <i>Developer's Guide to Web Applications</i>, chapter “Assembling and Deploying Web Modules”.</li></ul>

## WEB8020

<b>Severity</b>	SEVERE
<b>Description</b>	The value of the specified scope attribute is incorrect. This may prevent the servlet caching subsystem for the web application from functioning correctly. This error does not affect other web applications.
<b>Action</b>	Correct the “scope” setting in the <code>&lt;cache-mapping&gt;</code> element in <code>sun-web.xml</code> and redeploy or reload the application.
<b>See Also</b>	<ul style="list-style-type: none"><li>• <i>Developer's Guide to Web Applications</i>, chapter “Assembling and Deploying Web Modules”.</li></ul>

## WEB8021

<b>Severity</b>	SEVERE
-----------------	--------



<b>Description</b>	<p>An error occurred in the value specified in the <code>constraint-field</code> subelement of the caching configuration in <code>sun-web.xml</code>.</p> <p>This may prevent the servlet caching subsystem for the web application from functioning correctly. This error does not affect other web applications.</p>
<b>Action</b>	Specify a numeric value and redeploy or reload the application.
<b>See Also</b>	<ul style="list-style-type: none"> <li>• <i>Developer's Guide to Web Applications</i>, chapter “Assembling and Deploying Web Modules”.</li> </ul>

## WEB8022

<b>Severity</b>	SEVERE
<b>Description</b>	<p>Indicates an error in the value specified in a <code>constraint-field</code> subelement of the caching configuration in <code>sun-web.xml</code>.</p> <p>This may prevent the servlet caching subsystem for the web application from functioning correctly. This error does not affect other web applications.</p>
<b>Action</b>	Specify a numeric value and redeploy or reload the application.
<b>See Also</b>	<ul style="list-style-type: none"> <li>• <i>Developer's Guide to Web Applications</i>, chapter “Assembling and Deploying Web Modules”.</li> </ul>

## WEB8023

<b>Severity</b>	SEVERE
<b>Description</b>	<p>Indicates an invalid value in the “<code>match-expr</code>” attribute of a <code>constraint-field</code>'s <code>&lt;value&gt;</code> element of the caching configuration in <code>sun-web.xml</code>.</p> <p>This may prevent the servlet caching subsystem of the web application from functioning correctly. This error does not affect other web applications.</p>
<b>Action</b>	Use one of the values allowed for <code>match-expr</code> and redeploy or reload the application.
<b>See Also</b>	<ul style="list-style-type: none"> <li>• <i>Developer's Guide to Web Applications</i>, chapter “Assembling and Deploying Web Modules”.</li> </ul>

## WEB8024

<b>Severity</b>	SEVERE
-----------------	--------

<b>Description</b>	<p>Indicates an incorrect specification of numerical range in a constraint-field that specifies <code>match-expr= 'in-range '</code> (which is part of the caching configuration in <code>sun-web.xml</code>).</p> <p>This may prevent the servlet caching subsystem of the web application from functioning correctly. This error does not affect other web applications.</p>
<b>Action</b>	Specify a numerical range using the format <code>xx-yy</code> . For example, 50-55
<b>See Also</b>	<ul style="list-style-type: none"><li>• <i>Developer's Guide to Web Applications</i>, chapter “Assembling and Deploying Web Modules”.</li></ul>

## WEB8025

<b>Severity</b>	SEVERE
<b>Description</b>	<p>Indicates a missing hyphen (-) in a numerical range specification in a constraint-field that specifies <code>match-expr= 'in-range '</code> (which is part of the caching configuration in <code>sun-web.xml</code>).</p> <p>This may prevent the servlet caching subsystem of the web application from functioning correctly. This error does not affect other web applications.</p>
<b>Action</b>	Specify a numerical range using the format <code>xx-yy</code> . For example, 50-55.
<b>See Also</b>	<ul style="list-style-type: none"><li>• <i>Developer's Guide to Web Applications</i>, chapter “Assembling and Deploying Web Modules”.</li></ul>

## WEB8026

<b>Severity</b>	SEVERE
<b>Description</b>	<p>Indicates a missing hyphen(-) in a numerical range specification in a constraint-field that specifies <code>match-expr= 'in-range '</code> (which is part of the caching configuration in <code>sun-web.xml</code>).</p> <p>This may prevent the servlet caching subsystem for the web application from functioning correctly. This error does not affect other web applications.</p>
<b>Action</b>	Specify a numerical range using the format <code>xx-yy</code> . For example, 50-55.
<b>See Also</b>	<ul style="list-style-type: none"><li>• <i>Developer's Guide to Web Applications</i>, chapter “Assembling and Deploying Web Modules”.</li></ul>

## WEB8027

<b>Severity</b>	SEVERE
-----------------	--------

<b>Description</b>	<p>Indicates a missing hyphen(-) in a numerical range specification in a constraint-field that specifies match-expr='in-range' (which is part of the caching configuration in <code>sun-web.xml</code>).</p> <p>This may prevent the servlet caching subsystem for the web application from functioning correctly. This error does not affect other web applications.</p>
<b>Action</b>	<p>Specify a numerical range using the format xx-yy. For example, 50-55.</p>
<b>See Also</b>	<ul style="list-style-type: none"><li>• <i>Developer's Guide to Web Applications</i>, chapter "Assembling and Deploying Web Modules".</li></ul>

**WEB8028**

<b>Severity</b>	SEVERE
<b>Description</b>	<p>Indicates a missing hyphen(-) in a numerical range specification in a constraint-field that specifies match-expr='in-range' (which is part of the caching configuration in <code>sun-web.xml</code>).</p> <p>This may prevent the servlet caching subsystem for the web application from functioning correctly. This error does not affect other web applications.</p>
<b>Action</b>	Specify a numerical range using the format xx-yy. For example, 50-55.
<b>See Also</b>	<ul style="list-style-type: none"><li>• <i>Developer's Guide to Web Applications</i>, chapter "Assembling and Deploying Web Modules".</li></ul>

**WEB8074**

<b>Severity</b>	SEVERE
<b>Description</b>	Generic exception information report when an error occurs while gathering monitoring data.
<b>Action</b>	Refer to exception data to determine the cause of the problem.

### WEB8075

<b>Severity</b>	SEVERE
<b>Description</b>	Indicates an error during initialization of the web monitoring subsystem.
<b>Action</b>	Refer to exception data to determine the cause of the problem. Restart the server instance. If the problem persists, then <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### WEB8076

<b>Severity</b>	SEVERE
<b>Description</b>	Indicates an error while gathering monitoring data.
<b>Action</b>	Refer to exception data to determine the cause of the problem.

### WEB8077

<b>Severity</b>	SEVERE
<b>Description</b>	Indicates an error during initialization of the web monitoring subsystem.
<b>Action</b>	Refer to exception data to determine the cause of the problem. Restart the server instance. If the problem persists, then <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### WEB8078

<b>Severity</b>	SEVERE
<b>Description</b>	Indicates an error while gathering monitoring data.
<b>Action</b>	<a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

### WEB8079

<b>Severity</b>	SEVERE
<b>Description</b>	Indicates that the specified attribute name is not monitored.

<b>Action</b>	Check the <code>asadmin</code> command line and ensure that the attribute name specification has valid values.
<b>See Also</b>	<i>Administrator's Guide</i> , chapter "Monitoring the Application Server".

### *WEB9001*

<b>Severity</b>	SEVERE
<b>Description</b>	<p>Indicates an error that prevents the caching subsystem of the web application from functioning correctly.</p> <p>This error does not affect other web applications.</p>
<b>Action</b>	Restart the server instance. If the problem persists, then <a href="#">Analyze the System</a> , as described on <a href="#">page 15</a> .

# Index

## A

ACC002	31
ACC003	32
ACC005	32
ACC006	32
ACC010	32
ACC011	33
ACC012	33
ACC015	33
ACC016	33
ADM0003	17
ADM0006	17
ADM0008	18
ADM0011	18
ADM0014	19
ADM0101	19
ADM1002	19
ADM1004	19
ADM1034	22
ADM1037	22
ADM1039	22
ADM1044	22
ADM1046	23
ADM1047	23
ADM1050	23
ADM1059	23
ADM1060	24
ADM1069	24
ADM5002	24
ADM5003	24
ADM5004	25
ADM5005	25
ADM5603	26
ADM5609	26
ADM5801	26
ADM5802	26
ADM5803	26
ADM5804	27
ADM5805	27
ADM5807	27
ADM5810	27
ADM5811	28
ADM5812	28
ADM5813	28
ADM5814	28
ADM5815	28
ADM6004	29
ADM6006	29
ADM6008	29
ADM7003	29
ADM7004	30
ADM7006	30
admin	17

application client container [31](#)

## C

class loader [215](#)

core [39](#)

CORE3283 [39](#)

CORE4001 [39](#)

CORE4002 [39](#)

CORE4003 [40](#)

CORE4005 [40](#)

CORE4007 [40](#)

CORE4008 [41](#)

CORE4009 [41](#)

CORE4011 [41](#)

CORE4012 [41](#)

CORE4013 [42](#)

CORE4014 [42](#)

CORE4015 [42](#)

CORE5001 [43](#)

CORE5005 [43](#)

CORE5007 [43](#)

CORE5009 [43](#)

CORE5011 [43](#)

CORE5013 [44](#)

CORE5037 [48](#)

CORE5038 [48](#)

CORE5046 [48](#)

CORE5047 [48](#)

CORE5048 [49](#)

CORE5049 [49](#)

CORE5053 [49](#)

CORE5054 [49](#)

CORE5060 [50](#)

CORE5061 [50](#)

CORE5070 [50](#)

CORE5071 [50](#)

CORE5072 [50](#)

CORE5074 [51](#)

CORE5075 [51](#)

CORE5080 [51](#)

CORE5081 [51](#)

CORE5082 [52](#)

CORE5084 [52](#)

CORE5089 [52](#)

CORE5090 [52](#)

CORE5091 [53](#)

CORE5092 [53](#)

CORE5093 [53](#)

CORE5094 [53](#)

CORE5095 [53](#)

CORE5096 [54](#)

## D

deployment [57](#)

DPL5001 [57](#)

DPL5002 [57](#)

DPL5003 [57](#)

DPL5004 [58](#)

DPL5005 [58](#)

DPL5006 [58](#)

DPL5007 [58](#)

DPL5008 [59](#)

DPL5009 [59](#)

DPL5010 [59](#)

DPL5011 [59](#)

DPL5012 [60](#)

DPL5013 [60](#)

DPL5014 [60](#)

DPL5015 [60](#)

DPL5016 [60](#)

DPL5017 [61](#)

DPL5018 [61](#)

DPL5019 [61](#)

DPL5020 [62](#)

DPL5021 [62](#)

DPL5022 [62](#)

DPL5023 [62](#)

DPL5024 [62](#)



DPL5025 [63](#)  
DPL5026 [63](#)  
DPL5028 [63](#)  
DPL5029 [63](#)  
DPL5030 [64](#)  
DPL5031 [64](#)  
DPL5032 [64](#)  
DPL5034 [65](#)  
DPL5035 [65](#)  
DPL5036 [65](#)  
DPL5100 [65](#)  
DPL5101 [66](#)  
DPL5102 [66](#)  
DPL5103 [66](#)  
DPL5104 [66](#)  
DPL5200 [67](#)  
DPL5201 [67](#)  
DPL5202 [67](#)  
DPL5203 [67](#)  
DPL5204 [67](#)  
DPL5205 [68](#)  
DPL5206 [68](#)  
DPL5207 [68](#)  
DPL5208 [68](#)  
DPL5209 [69](#)  
DPL5210 [69](#)  
DPL5211 [69](#)  
DPL5212 [69](#)  
DTX5001 [71](#)  
DTX5002 [71](#)  
DTX5003 [72](#)  
DTX5004 [72](#)  
DTX5005 [72](#)  
DTX5006 [72](#)

## E

EJB5013 [73](#)  
EJB5014 [73](#)  
EJB5016 [74](#)

EJB5017 [74](#)  
EJB5020 [74](#)  
EJB5021 [74](#)  
EJB5022 [75](#)  
EJB5023 [75](#)  
EJB5024 [75](#)  
EJB5025 [75](#)  
EJB5026 [76](#)  
EJB5027 [76](#)  
EJB5028 [76](#)  
EJB5029 [77](#)  
EJB5030 [77](#)  
EJB5031 [77](#)  
EJB5032 [77](#)  
EJB5058 [78](#)  
EJB5059 [78](#)  
EJB5060 [78](#)  
EJB5061 [78](#)  
EJB5062 [79](#)  
EJB5063 [79](#)  
EJB5064 [79](#)  
EJB5066 [79](#)  
EJB5069 [80](#)  
EJB5070 [80](#)  
EJB5071 [80](#)  
EJB5103 [80](#)  
EJB5105 [80](#)  
EJB5106 [81](#)  
enterprise java bean [73](#)

## H

HADB [85](#)  
HADB00208 [85](#)  
HADB00216 [85](#)  
HADB00224 [86](#)  
HADB00512 [86](#)  
HADB00560 [87](#)  
HADB00582 [87](#)  
HADB00583 [87](#)

HADB00584	87	HADB11112	106
HADB00624	88	HADB11304	106
HADB00832	88	HADB11309	107
HADB00848	88	HADB11311	107
HADB00916	88	HADB11320	107
HADB01040	89	HADB11402	107
HADB01521	89	HADB11403	108
HADB01536	89	HADB11404	108
HADB01552	89	HADB11405	108
HADB01600	90	HADB11406	108
HADB01616	90	HADB11407	108
HADB01664	90	HADB11521	109
HADB01696	90	HADB11601	109
HADB01920	91	HADB11602	109
HADB02000	91	HADB11608	109
HADB02016	91	HADB11619	110
HADB02064	91	HADB11646	110
HADB02078	92	HADB11657	110
HADB02079	92	HADB11662	110
HADB02080	92	HADB11666	111
HADB02096	92	HADB11701	111
HADB02097	92	HADB11703	111
HADB02168	93	HADB11704	111
HADB02272	93	HADB11707	111
HADB02304	93	HADB11708	112
HADB02320	93	HADB11709	112
HADB02464	94	HADB11711	112
HADB03072	94	HADB11713	112
HADB03505	95	HADB11714	112
HADB03508	95	HADB11715	113
HADB04096	95	HADB11716	113
HADB04362	96	HADB11717	113
HADB04576	96	HADB11718	113
HADB04592	96	HADB11721	113
HADB04593	96	HADB11723	114
HADB04640	97	HADB11725	114
HADB04656	97	HADB11726	114
HADB04672	97	HADB11727	114
HADB04688	97	HADB11733	115
HADB04752	98	HADB11734	115
HADB04768	98	HADB11735	115
HADB11110	106	HADB11736	115

HADB11738	116	HADB11920	124
HADB11740	116	HADB11921	124
HADB11742	116	HADB11924	124
HADB11743	116	HADB11927	124
HADB11744	116	HADB11939	125
HADB11745	117	HADB12001	125
HADB11747	117	HADB12002	125
HADB11748	117	HADB12003	125
HADB11751	117	HADB12004	125
HADB11755	117	HADB12005	126
HADB11757	117	HADB12006	126
HADB11759	118	HADB12301	126
HADB11761	118	HADB12302	126
HADB11762	118	HADB12303	126
HADB11763	118	HADB12304	127
HADB11768	118	HADB12305	127
HADB11770	119	HADB12306	127
HADB11773	119	HADB12307	127
HADB11775	119	HADB12317	127
HADB11776	119	HADB12319	128
HADB11778	120	HADB12320	128
HADB11779	120	HADB12321	128
HADB11782	120	HADB12322	128
HADB11783	120	HADB12323	128
HADB11784	120	HADB12324	128
HADB11787	120	HADB12401	129
HADB11790	121	HADB12402	129
HADB11796	121	HADB12403	129
HADB11798	121	HADB12404	129
HADB11901	121	HADB12406	129
HADB11903	121	HADB12407	130
HADB11905	122	HADB12408	130
HADB11907	122	HADB12411	130
HADB11908	122	HADB12412	130
HADB11909	122	HADB12413	130
HADB11910	122	HADB12416	131
HADB11914	123	HADB12422	131
HADB11915	123	HADB12423	131
HADB11916	123	HADB12424	131
HADB11917	123	HADB12427	131
HADB11918	123	HADB12428	132
HADB11919	124	HADB12430	132

HADB12432	132	HADB20014	140
HADB12433	132	HADB20015	140
HADB12434	132	HADB20016	140
HADB12435	133	HADB20020	141
HADB12437	133	HADB20021	141
HADB12440	133	HADB20022	141
HADB12442	133	HADB20024	141
HADB12443	133	HADB20025	141
HADB12444	134	HADB20026	142
HADB12445	134	HADB20027	142
HADB12446	134	HADB20028	142
HADB12447	134	HADB20029	142
HADB12448	134	HADB20030	142
HADB12449	135	HADB20033	142
HADB12450	135	HADB20034	143
HADB12451	135	HADB20035	143
HADB12452	135	HADB20036	143
HADB12454	135	HADB20037	143
HADB12455	136	HADB20038	143
HADB12456	136	HADB20039	143
HADB12457	136	HADB20040	144
HADB12458	136	HADB20041	144
HADB12459	136	HADB20044	144
HADB12460	137	HADB20045	144
HADB12461	137	HADB20046	145
HADB12522	137	HADB20050	145
HADB12523	137	HADB20051	145
HADB12528	137	HADB20052	145
HADB12530	138	HADB20053	145
HADB12539	138	HADB20054	145
HADB20001	138	HADB20055	146
HADB20002	138	HADB20056	146
HADB20003	138	HADB20057	146
HADB20004	139	HADB20059	146
HADB20005	139	HADB20060	146
HADB20006	139	HADB20061	146
HADB20008	139	HADB20062	147
HADB20009	139	HADB21006	158
HADB20010	139	HADB21022	158
HADB20011	140	HADB21023	159
HADB20012	140	HADB21024	158
HADB20013	140	HADB21035	158

HADB21042 158  
 HADB22002 147  
 HADB22003 147  
 HADB22005 147  
 HADB22021 148  
 HADB22022 148  
 HADB22023 148  
 HADB22024 148  
 HADB22025 148  
 HADB22026 149  
 HADB22027 149  
 HADB22028 149  
 HADB22029 149  
 HADB22030 149  
 HADB22031 150  
 HADB22032 150  
 HADB22033 150  
 HADB22034 150  
 HADB22041 150  
 HADB22042 151  
 HADB22043 151  
 HADB22044 151  
 HADB22045 151  
 HADB22046 152  
 HADB22047 152  
 HADB22061 152  
 HADB22065 152  
 HADB22066 153  
 HADB22071 153  
 HADB22072 153  
 HADB22073 153  
 HADB22081 153  
 HADB22082 154  
 HADB22083 154  
 HADB22085 154  
 HADB22086 154  
 HADB22087 154  
 HADB22088 155  
 HADB22091 155  
 HADB22095 155  
 HADB22096 155  
 HADB22097 155

HADB22101 156  
 HADB22102 156  
 HADB22105 156  
 HADB22106 156  
 HADB22107 156  
 HADB22108 157  
 HADB22111 157  
 HADB22112 157  
 HADB22113 157  
 HADB22114 157  
 HADB22125 147  
 HADB22201 151  
 HADB22203 152  
 HADB25005 159  
 HADB25010 159  
 HADB25012 159  
 HADB25017 159  
 HADB25018 159  
 HADB25020 160  
 HADB25022 160

## I

INSTALL2001 163  
 INSTALL2002 163  
 INSTALL2003 163  
 INSTALL2004 164  
 INSTALL2005 164  
 INSTALL2006 164  
 INSTALL2007 164  
 INSTALL2008 164  
 INSTALL2009 165  
 INSTALL2010 165  
 INSTALL2011 165  
 INSTALL2012 165  
 INSTALL2013 165  
 INSTALL2014 166  
 INSTALL2015 166  
 INSTALL2016 166  
 INSTALL2017 166

INSTALL2018 [166](#)  
INSTALL2019 [167](#)  
INSTALL2020 [167](#)  
INSTALL2021 [167](#)  
INSTALL2022 [167](#)  
INSTALL2023 [167](#)  
INSTALL2024 [168](#)  
INSTALL2025 [168](#)  
INSTALL2026 [168](#)  
INSTALL2027 [168](#)  
INSTALL2028 [169](#)  
INSTALL2029 [169](#)  
INSTALL2030 [169](#)  
INSTALL2031 [169](#)  
INSTALL2032 [170](#)  
INSTALL2033 [170](#)  
INSTALL2034 [170](#)  
INSTALL2035 [170](#)  
INSTALL2036 [170](#)  
INSTALL2037 [171](#)  
INSTALL2038 [171](#)  
INSTALL2039 [171](#)  
installer [163](#)  
Internet Inter-ORB Protocol [173](#)  
IOP5001 [173](#)  
IOP5002 [173](#)  
IOP5003 [174](#)  
IOP5004 [174](#)  
IOP5006 [174](#)  
IOP5007 [174](#)  
IOP5009 [174](#)  
IOP5010 [175](#)  
IOP5011 [175](#)  
IOP5012 [175](#)  
IOP5013 [175](#)  
IOP5015 [176](#)  
IOP5016 [176](#)  
IOP5017 [176](#)  
IOP5018 [176](#)  
IOP5019 [177](#)  
IOP5020 [177](#)  
IOP5021 [177](#)

IOP5022 [177](#)  
IOP5023 [178](#)  
IOP5024 [178](#)  
IOP5026 [179](#)  
IOP5027 [179](#)  
IOP5029 [179](#)  
IOP5030 [179](#)  
IOP5031 [180](#)  
IOP5039 [182](#)  
IOP5040 [182](#)  
IOP5047 [184](#)  
IOP5048 [184](#)  
IOP5049 [184](#)  
IOP5050 [184](#)  
IOP5051 [185](#)  
IOP5052 [185](#)  
IOP5054 [185](#)

## J

java message service [189](#)  
java transaction APIs [71](#)  
java transaction services [197](#)  
JMS5004 [189](#)  
JMS5005 [189](#)  
JMS5006 [190](#)  
JMS5007 [190](#)  
JMS5008 [190](#)  
JMS5009 [190](#)  
JMS5010 [191](#)  
JMS5011 [191](#)  
JMS5012 [191](#)  
JMS5014 [191](#)  
JMS5016 [191](#)  
JMS5018 [192](#)  
JMS5020 [192](#)  
JMS5022 [192](#)  
JMS5024 [192](#)  
JMS5027 [193](#)  
JMS5028 [193](#)

JMS5031 [193](#)  
JMS5033 [193](#)  
JMS5034 [194](#)  
JMS5035 [194](#)  
JMS5036 [194](#)  
JTS5001 [197](#)  
JTS5002 [197](#)  
JTS5003 [197](#)  
JTS5004 [198](#)  
JTS5005 [198](#)  
JTS5006 [198](#)  
JTS5007 [198](#)  
JTS5008 [198](#)  
JTS5009 [199](#)  
JTS5010 [199](#)  
JTS5011 [199](#)  
JTS5012 [199](#)  
JTS5013 [199](#)  
JTS5015 [200](#)  
JTS5016 [200](#)  
JTS5017 [200](#)  
JTS5018 [200](#)  
JTS5020 [200](#)  
JTS5021 [201](#)  
JTS5022 [201](#)  
JTS5023 [201](#)  
JTS5024 [201](#)  
JTS5026 [202](#)  
JTS5027 [202](#)  
JTS5028 [202](#)  
JTS5029 [202](#)  
JTS5030 [202](#)  
JTS5031 [203](#)  
JTS5033 [203](#)  
JTS5035 [203](#)  
JTS5036 [203](#)  
JTS5037 [203](#)  
JTS5040 [204](#)  
JTS5041 [204](#)  
JTS5042 [204](#)  
JTS5043 [204](#)  
JTS5044 [204](#)

JTS5045 [205](#)  
JTS5046 [205](#)  
JTS5047 [205](#)  
JTS5049 [205](#)  
JTS5050 [205](#)  
JTS5053 [206](#)  
JTS5054 [206](#)  
JTS5055 [206](#)  
JTS5059 [206](#)  
JTS5062 [207](#)  
JTS5063 [207](#)

## L

LCM0101 [211](#)  
LCM0103 [211](#)  
LCM0105 [212](#)  
LCM0107 [212](#)  
LCM0201 [212](#)  
LCM0203 [213](#)  
LCM0205 [213](#)  
LDR5001 [215](#)  
LDR5002 [215](#)  
LDR5003 [216](#)  
LDR5004 [216](#)  
LDR5005 [216](#)  
LDR5006 [216](#)  
LDR5007 [217](#)  
LDR5008 [217](#)  
LDR5009 [217](#)  
LDR5011 [217](#)  
lifecycle module [211](#)

## M

MDB00010 [222](#)  
MDB00012 [223](#)  
MDB00013 [223](#)

MDB00015 [223](#)  
MDB00017 [223](#)  
MDB0002 [221](#)  
MDB00020 [224](#)  
MDB00021 [224](#)  
MDB00023 [224](#)  
MDB00024 [224](#)  
MDB00025 [225](#)  
MDB00026 [225](#)  
MDB00027 [225](#)  
MDB00029 [225](#)  
MDB00030 [226](#)  
MDB00031 [226](#)  
MDB00032 [226](#)  
MDB00035 [226](#)  
MDB00036 [227](#)  
MDB00037 [227](#)  
MDB00038 [227](#)  
MDB00039 [227](#)  
MDB0004 [221](#)  
MDB00041 [227](#)  
MDB00042 [228](#)  
MDB00043 [228](#)  
MDB00046 [228](#)  
MDB00047 [228](#)  
MDB00048 [229](#)  
MDB00049 [229](#)  
MDB0005 [222](#)  
MDB00050 [229](#)  
MDB00051 [229](#)  
MDB00052 [229](#)  
MDB00053 [230](#)  
MDB00054 [230](#)  
MDB00055 [230](#)  
MDB00058 [230](#)  
MDB0006 [222](#)  
MDB00060 [231](#)  
MDB0008 [222](#)  
message driven bean container [221](#)  
message-driven beans [221](#)

## R

RAR5001 [233](#)  
RAR5002 [233](#)  
RAR5003 [233](#)  
RAR5004 [234](#)  
RAR5005 [234](#)  
RAR5007 [234](#)  
RAR5008 [234](#)  
RAR5009 [235](#)  
RAR5010 [235](#)  
RAR5011 [235](#)  
RAR5012 [235](#)  
RAR5025 [237](#)  
RAR5026 [237](#)  
RAR5027 [237](#)  
RAR5028 [237](#)  
RAR5029 [238](#)  
RAR5030 [238](#)  
RAR5031 [238](#)  
RAR5032 [238](#)  
RAR5034 [239](#)  
RAR5035 [239](#)  
RAR5040 [239](#)  
RAR5041 [239](#)  
RAR5042 [239](#)  
RAR5043 [240](#)  
RAR5045 [240](#)  
RAR5046 [240](#)  
RAR5047 [240](#)  
RAR5049 [240](#)  
RAR5050 [241](#)  
RAR5051 [241](#)  
RAR5055 [241](#)  
RAR5056 [241](#)  
RAR5057 [241](#)  
RAR5058 [242](#)  
resource adapter [233](#)  
rpm [14](#)



## S

SEC1000 [249](#)  
 SEC1050 [249](#)  
 SEC1100 [250](#)  
 SEC1101 [250](#)  
 SEC1102 [250](#)  
 SEC1103 [250](#)  
 SEC1104 [251](#)  
 SEC1105 [251](#)  
 SEC1106 [251](#)  
 SEC1108 [251](#)  
 SEC1109 [252](#)  
 SEC1110 [252](#)  
 SEC1120 [252](#)  
 SEC1130 [252](#)  
 SEC1132 [252](#)  
 SEC1133 [253](#)  
 SEC5022 [253](#)  
 SEC5023 [253](#)  
 SEC5024 [253](#)  
 SEC5037 [254](#)  
 SEC5038 [254](#)  
 SEC5041 [254](#)  
 SEC5042 [254](#)  
 SEC5043 [254](#)  
 SEC5044 [255](#)  
 SEC5100 [255](#)  
 security services [249](#)  
 showrev [14](#)  
 Sun customer support [14](#)

## U

UTIL6003 [257](#)  
 UTIL6004 [257](#)  
 UTIL6005 [257](#)  
 UTIL6007 [258](#)  
 UTIL6009 [258](#)  
 UTIL6027 [259](#)

UTIL6028 [259](#)  
 UTIL6031 [259](#)  
 UTIL6032 [260](#)  
 UTIL6033 [260](#)  
 UTIL6034 [260](#)  
 UTIL6035 [260](#)  
 UTIL6545 [261](#)  
 UTIL6548 [261](#)  
 UTIL6549 [261](#)  
 UTIL6550 [261](#)  
 UTIL6551 [261](#)  
 UTIL6552 [262](#)  
 UTIL6553 [262](#)  
 UTIL8071 [262](#)  
 utility services [257](#)

## V

verifier [263](#)  
 VRFY5001 [263](#)  
 VRFY5002 [263](#)  
 VRFY5003 [264](#)  
 VRFY5101 [264](#)  
 VRFY5102 [264](#)  
 VRFY5103 [264](#)

## W

web container [265](#)  
 WEB0101 [265](#)  
 WEB0102 [265](#)  
 WEB0103 [266](#)  
 WEB0104 [266](#)  
 WEB0105 [266](#)  
 WEB0106 [266](#)  
 WEB0107 [266](#)  
 WEB0108 [267](#)  
 WEB0112 [267](#)

WEB0113	<a href="#">267</a>
WEB0202	<a href="#">268</a>
WEB0203	<a href="#">268</a>
WEB0204	<a href="#">268</a>
WEB1001	<a href="#">269</a>
WEB1002	<a href="#">269</a>
WEB2001	<a href="#">269</a>
WEB4002	<a href="#">270</a>
WEB5002	<a href="#">270</a>
WEB5003	<a href="#">270</a>
WEB5004	<a href="#">270</a>
WEB5005	<a href="#">271</a>
WEB6000	<a href="#">271</a>
WEB6001	<a href="#">271</a>
WEB8001	<a href="#">271</a>
WEB8002	<a href="#">272</a>
WEB8020	<a href="#">272</a>
WEB8021	<a href="#">272</a>
WEB8022	<a href="#">273</a>
WEB8023	<a href="#">273</a>
WEB8024	<a href="#">273</a>
WEB8025	<a href="#">274</a>
WEB8026	<a href="#">274</a>
WEB8027	<a href="#">274</a>
WEB8028	<a href="#">276</a>
WEB8074	<a href="#">276</a>
WEB8075	<a href="#">277</a>
WEB8076	<a href="#">277</a>
WEB8077	<a href="#">277</a>
WEB8078	<a href="#">277</a>
WEB8079	<a href="#">277</a>
WEB9001	<a href="#">278</a>