

Oracle Utilities Energy Information Platform

Installation Guide

Release 1.6.1.17 for Windows

E18199-18

February 2014

Oracle Utilities Energy Information Platform/Energy Information Platform Installation Guide, Volume 1,
Release 1.6.1.17 for Windows

E18199-18

Copyright © 1999, 2012 Oracle. All rights reserved.

Primary Author: Lou Prosperi

Contributor: Steve Pratt

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are “commercial computer software” pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

NOTIFICATION OF THIRD-PARTY LICENSES

Oracle Utilities software contains third party, open source components as identified below. Third-party license terms and other third-party required notices are provided below.

License: Apache 1.1

Module: Crimson v1.1.1, Xalan J2

Copyright © 1999-2000 The Apache Software Foundation. All rights reserved.

Use of Crimson 1.1.1 and Xalan J2 within the product is governed by the following (Apache 1.1):

(1) Redistributions of source code must retain the above copyright notice, this list of conditions and the disclaimer below. (2) Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the disclaimer below in the documentation and/or other materials provided with the distribution. (3) The end-user documentation included with the redistribution, if any, must include the following acknowledgment: "This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>). " Alternately, this acknowledgment may appear in the software itself, if and wherever such third-party acknowledgments normally appear. (4) Neither the component name nor Apache Software Foundation may be used to endorse or promote products derived from the software without specific prior written permission. (5) Products derived from the software may not be called "Apache", nor may "Apache" appear in their name, without prior written permission.

THIS SOFTWARE IS PROVIDED "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

License: CoolServlets.com

Module: CS CodeViewer v1.0 (Sun JRE Component)

Copyright © 1999 by CoolServlets.com

Use of this module within the product is governed by the following:

(1) Redistributions of source code must retain the above copyright notice, this list of conditions and the disclaimer below. (2) Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the disclaimer below in the documentation and/or other materials provided with the distribution. (3) Neither the component name nor Coolservlets.com may be used to endorse or promote products derived from the software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY COOLSERVLETS.COM AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE."

License: Justin Frankel, justin@nullsoft.com

Module: NSIS 1.0j (Sun JRE Component)

Use of this module within the product is governed by the following:

(1) The origin of the module must not be misrepresented, and Oracle may not claim that it wrote the original software. If Oracle uses this module in a product, an acknowledgment in the product documentation is appreciated but not required. (2) Altered source versions of the module must be plainly marked as such, and

must not be misrepresented as being the original software. (3) The following notice may not be removed or altered from any source distribution: "Justin Frankel justin@nullsoft.com".

License: ICU4j License

Module: ICU4j

Copyright © 1995-2001 International Business Machines Corporation and others. All rights reserved.

Oracle may use the software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, and/or sell copies of the software, and to permit persons to whom the software is furnished to do so, provided that the above copyright notice and the permission notice appear in all copies of the software and that both the above copyright notice and the permission notice appear in supporting documentation.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OF THIRD PARTY RIGHTS. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR HOLDERS INCLUDED IN THIS NOTICE BE LIABLE FOR ANY CLAIM, OR ANY SPECIAL INDIRECT OR CONSEQUENTIAL DAMAGES, OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

License: Info-ZIP

Module: INFO-ZIP ZIP32.DLL (Binary Form)

Copyright (c) 1990-2005 Info-ZIP. All rights reserved

Use of this dll within the product is governed by the following:

(1) Redistributions of source code must retain the above copyright notice, this list of conditions and the definition and disclaimer below. (2) Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the definition and disclaimer below in the documentation and/or other materials provided with the distribution. The sole exception to this condition is redistribution of a standard UnZipSFX binary (including SFXWiz) as part of a self-extracting archive; that is permitted without inclusion of this license, as long as the normal SFX banner has not been removed from the binary or disabled. (3) Altered versions--including, but not limited to, ports to new operating systems, existing ports with new graphical interfaces, and dynamic, shared, or static library versions--must be plainly marked as such and must not be misrepresented as being the original source. Such altered versions also must not be misrepresented as being Info-ZIP releases--including, but not limited to, labeling of the altered versions with the names "Info-ZIP" (or any variation thereof, including, but not limited to, different capitalizations), "Pocket UnZip," "WiZ" or "MacZip" without the explicit permission of Info-ZIP. Such altered versions are further prohibited from misrepresentative use of the Zip-Bugs or Info-ZIP e-mail addresses or of the Info-ZIP URL(s). (4) Info-ZIP retains the right to use the names "Info-ZIP," "Zip," "UnZip," "UnZipSFX," "WiZ," "Pocket UnZip," "Pocket Zip," and "MacZip" for its own source and binary releases.

[Definition]: For the purposes of this copyright and license, "Info-ZIP" is defined as the following set of individuals:

Mark Adler, John Bush, Karl Davis, Harald Denker, Jean-Michel Dubois, Jean-loup Gailly, Hunter Goatley, Ed Gordon, Ian Gorman, Chris Herborth, Dirk Haase, Greg Hartwig, Robert Heath, Jonathan Hudson, Paul Kienitz, David Kirschbaum, Johnny Lee, Onno van der Linden, Igor Mandrichenko, Steve P. Miller, Sergio Monesi, Keith Owens, George Petrov, Greg Roelofs, Kai Uwe Rommel, Steve Salisbury, Dave Smith, Steven M. Schweda, Christian Spieler, Cosmin Truta, Antoine Verheijen, Paul von Behren, Rich Wales, Mike White

[Disclaimer]: "This software is provided "as is," without warranty of any kind, express or implied. In no event shall Info-ZIP or its contributors be held liable for any direct, indirect, incidental, special or consequential damages arising out of the use of or inability to use this software."

License: Paul Johnston

Modules: md5.js

Copyright (C) Paul Johnston 1999 - 2002

Use of these modules within the product is governed by the following:

(1) Redistributions of source code must retain the above copyright notice, this list of conditions and the disclaimer below. (2) Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the disclaimer below in the documentation and/or other materials provided with the distribution. (3) Neither the component name nor the names of the copyright holders and contributors may be used to endorse or promote products derived from the software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

License: Jef Poskanzer

Modules: DES, 3xDES (Sun JRE Components)

Copyright © 2000 by Jef Poskanzer <jef@acme.com>. All rights reserved

Use of these modules within the product is governed by the following:

(1) Redistributions of source code must retain the above copyright notice, this list of conditions and the disclaimer below. (2) Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the disclaimer below in the documentation and/or other materials provided with the distribution. (3) Neither the component name nor the name of Jef Poskanzer may be used to endorse or promote products derived from the software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

License: Sun Microsystems, Inc.

Modules: Sun Swing Tutorials

Copyright© 1995-2006 Sun Microsystems, Inc. All Rights Reserved.

Use of these modules within the product is governed by the following:

(1) Redistributions of source code must retain the above copyright notice, this list of conditions and the disclaimer below. (2) Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the disclaimer below in the documentation and/or other materials provided with the distribution. (3) Neither the component name nor the name of Sun Microsystems, Inc. and contributors may be used to endorse or promote products derived from the software without specific prior written permission. (4) Oracle must acknowledge that the software is not designed, licensed or intended for use in the design, construction, operation or maintenance of any nuclear facility.

THIS SOFTWARE IS PROVIDED "AS IS," WITHOUT A WARRANTY OF ANY KIND. ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE HEREBY EXCLUDED. SUN MICROSYSTEMS, INC. ("SUN") AND ITS LICENSORS SHALL NOT BE LIABLE FOR ANY DAMAGES SUFFERED BY LICENSEE AS A RESULT OF USING, MODIFYING OR DISTRIBUTING THIS SOFTWARE OR ITS DERIVATIVES. IN NO EVENT WILL SUN OR ITS LICENSORS BE LIABLE FOR ANY LOST REVENUE, PROFIT OR DATA, OR FOR DIRECT, INDIRECT, SPECIAL, CONSEQUENTIAL, INCIDENTAL OR

PUNITIVE DAMAGES, HOWEVER CAUSED AND REGARDLESS OF THE THEORY OF LIABILITY, ARISING OUT OF THE USE OF OR INABILITY TO USE THIS SOFTWARE, EVEN IF SUN HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

License: Tom Wu

Module: jsbn library

Copyright © 2003-2005 Tom Wu. All rights reserved

Use of this module within the product is governed by the following:

(1) Redistributions of source code must retain the above copyright notice, this list of conditions and the disclaimer below. (2) Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the disclaimer below in the documentation and/or other materials provided with the distribution.

THE SOFTWARE IS PROVIDED "AS-IS" AND WITHOUT WARRANTY OF ANY KIND, EXPRESS, IMPLIED OR OTHERWISE, INCLUDING WITHOUT LIMITATION, ANY WARRANTY OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. IN NO EVENT SHALL TOM WU BE LIABLE FOR ANY SPECIAL, INCIDENTAL, INDIRECT OR CONSEQUENTIAL DAMAGES OF ANY KIND, OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER OR NOT ADVISED OF THE POSSIBILITY OF DAMAGE, AND ON ANY THEORY OF LIABILITY, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

Contents

What's New

New Features in the Oracle Utilities Energy Information Platform Installation Guide	1-i
New Features for Release 1.6.0.0	1-i

Chapter 1

Overview.....	1-1
Installation Overview	1-2
What is this book?	1-3
The Oracle Utilities Energy Information Platform Installation Package	1-4

Chapter 2

Setting Up the Network Environment.....	2-1
Oracle Utilities Platform Components Specifications	2-2
Client Workstation - C/S.....	2-3
Client Workstation - Web.....	2-4
Database Server.....	2-5
Application/Batch Processing Server	2-6
Web Server(s).....	2-7
Sample Platform Configurations.....	2-8
Oracle Utilities Billing Component, Oracle Utilities Rate Management	2-8
Oracle Utilities Billing Component with Oracle Utilities Receivables Component	2-8
Oracle Utilities Billing Component Web, Oracle Utilities Quotations Management (web).....	2-8
Application and Web Service Configuration.....	2-9
Configuration Steps for Windows 2003	2-9
Configuration Steps for Windows 2008	2-9
Installing Relational Database Management System Software	2-10
Setting Up the Relational Database Connection.....	2-10
Oracle Database Connectivity.....	2-11
Specifying the Time Zone for Oracle Database Servers (optional)	2-12
Oracle Real Application Cluster (RAC).....	2-13
MS SQL Server 2008 Configuration	2-16
Installing and Configuring Reporting Software	2-18
Installing Oracle Business Intelligence Publisher	2-18
Configuring Oracle BI Publisher.....	2-19
Installing Crystal Reports 2008	2-22
Configuring Application and Web Servers for Crystal Reports 2008.....	2-22

Chapter 3

Oracle Utilities Data Repository Schema Creation	3-1
Accessing the Database Creation Scripts.....	3-2
Product-Specific Database Scripts.....	3-2
Schema Creation for Oracle 10g and 11g.....	3-3
Schema Creation	3-3
Data Loading	3-6
Number of Open Cursors on Oracle Server	3-6

ODBC Data Source Options	3-7
Schema Creation for MS SQL Server 2008.....	3-8
Schema Creation	3-8
Data Loading	3-10
Temp DB	3-10
Upgrading the Oracle Utilities Energy Information Platform Database Schema	3-11
Upgrading Oracle Utilities Energy Information Platform Schema.....	3-11
Updating the Reporting Framework for Oracle Business Intelligence Publisher	3-12
Oracle Utilities Energy Information Platform Reports	3-12
Verification - Energy Information Platform Reports.....	3-12
Base Database Tables	3-13
Optional Schemas.....	3-20
Security Schema.....	3-20
Updating the LSGlobal Table.....	3-21

Chapter 4

Installing the Oracle Utilities Application Software.....	4-1
Before you Begin.....	4-1
Important Notes	4-2
Installing Oracle Utilities Energy Information Platform Software.....	4-3
Install the Oracle Utilities Application Software.....	4-3
Install Oracle Utilities Language Packs (Optional)	4-5
Configuring Oracle Utilities Energy Information Platform Software.....	4-6
Configuring an Application Server.....	4-6
Configuring a Client Workstation	4-9
Configuring a Web Server	4-12
Verifying the Installation	4-18
Verifying Security Access.....	4-18
Verifying the Reporting Framework	4-19
Verifying the Report Scheduler.....	4-20
Upgrading Your Software	4-21
Upgrading RDBMS and Interval Data Database Software	4-21
Upgrading Oracle Utilities Software	4-21

Index

What's New

New Features in the Oracle Utilities Energy Information Platform Installation Guide

This chapter outlines the new features of the 1.6.0.0 release of the Oracle Utilities Energy Information Platform that are documented in this guide.

New Features for Release 1.6.0.0

Feature	Description	For more information, refer to...
Support for Oracle Business Intelligence Publisher	This release includes support for publishing reports using Oracle Business Intelligence Publisher version 10.1.3.4 or 11.1.1 (as of v1.6.1.7).	Installing Oracle Business Intelligence Publisher on page 2-18 Configuring Oracle BI Publisher on page 2-19
Support Oracle 10g RAC	This release includes support for the use of Oracle Real Application Clusters (RAC) with database servers.	Oracle Real Application Cluster (RAC) on page 2-13

Chapter 1

Overview

This chapter provides an overview of the installation of the Oracle Utilities Energy Information Platform, including:

- **Installation Overview**
- **What is this book?**
- **The Oracle Utilities Energy Information Platform Installation Package**

Installation Overview

Installing the Oracle Utilities Energy Information Platform involves the following steps:

- Setup the Energy Information Platform Network Environment and the Oracle Utilities Data Repository as described in **Chapter 2: Setting Up the Network Environment** and **Chapter 3: Oracle Utilities Data Repository Schema Creation** of the *Oracle Utilities Energy Information Platform Installation and Configuration Guide*.
- Install workstation and application server applications used by the Energy Information Platform on server and client machines as described in **Chapter 4: Installing the Oracle Utilities Application Software**.
- Install Energy Information Platform web components on web server as described in **Chapter 4: Installing the Oracle Utilities Application Software**.

What is this book?

This book describes how to install the Oracle Utilities Energy Information Platform, including the following:

- **Chapter 1: Overview** (this chapter) provides an overview of the Energy Information Platform installation and configuration process
- **Chapter 2: Setting Up the Network Environment** describes the hardware components used by Energy Information Platform.
- **Chapter 3: Oracle Utilities Data Repository Schema Creation** describes how to create the Oracle Utilities Data Repository database schema.
- **Chapter 4: Installing the Oracle Utilities Application Software** describes how to install Energy Information Platform application software on an application server, on a web server, and on client machines.

The Oracle Utilities Energy Information Platform Installation Package

There is a separate installation package for the Oracle Utilities Energy Information Platform and for each related product. The table below provides the installation package file names for the Oracle Utilities Energy Information Platform and for each related product.

Product	Installation File Name
Oracle Utilities Energy Information Platform	01.06.10.xx.00.EIP.zip
Oracle Utilities Billing Component	01.06.10.xx.00.BC.zip
Oracle Utilities Load Profiling and Settlement	01.06.10.xx.00.LPS.zip
Oracle Utilities Meter Data Management	01.06.10.xx.00.MDM.zip
Oracle Utilities Quotations Management	01.06.10.xx.00.QM.zip
Oracle Utilities Rate Management	01.06.10.xx.00.RM.zip
Oracle Utilities Transaction Management	01.06.10.xx.00.TM.zip

The Oracle Utilities Energy Information Platform installation package contains the following folders:

- **Install:** Contains the installation program for the Oracle Utilities Energy Information Platform, including:
 - Oracle Utilities EIP 01.06.01.xx.00.msi
 - setup.exe
- **DBScripts:** Contains database creation scripts for the Oracle Utilities Energy Information Platform, including:
 - Buildora.cmd
 - Other database script files
- **Documentation:** Contains documentation for the Oracle Utilities Energy Information Platform, including:
 - Oracle Utilities Energy Information Platform Installation Guide
 - Oracle Utilities Energy Information Platform Configuration Guide
 - Oracle Utilities Energy Information Platform User's Guide
 - Data Manager User's Guide
 - Oracle Utilities Rules Language User's Guide
 - Oracle Utilities Rules Language Reference Guide

Chapter 2

Setting Up the Network Environment

This chapter describes how to set up and configure the network environment in which the Oracle Utilities software will be installed. This includes:

- **Oracle Utilities Platform Components Specifications**
- **Sample Platform Configurations**
- **Application and Web Service Configuration**
- **Installing Relational Database Management System Software**
- **Installing and Configuring Reporting Software**

Oracle Utilities Platform Components Specifications

This section contains options for hardware and software specifications for implementation of the Oracle Utilities Energy Information Platform and related products, including:

- Oracle Utilities Billing Component
- Oracle Utilities Load Analysis
- Oracle Utilities Load Profiling and Settlement
- Oracle Utilities Meter Data Management
- Oracle Utilities Quotations Management
- Oracle Utilities Rate Management
- Oracle Utilities Transaction Management

The Energy Information Platform application architecture comprises all of the components typically found in any n-tier enterprise architecture, including client machines, servers, and the supporting network infrastructure.

The Oracle Utilities Energy Information Platform uses five primary types of systems components. Suggested hardware specifications and required software for each component are listed below.

Before installing Oracle Utilities software you should consult with Oracle Utilities Consulting. They will make suggestions for your hardware and network architecture based on your business requirements. You should also consult with Oracle Utilities Consulting if your business requirements change, if your database grows significantly, or if you plan on migrating to a different version of Oracle Utilities software.

Note: Supported software versions are subject to change. Please refer to the Release Notes shipped with the software for the latest supported versions.

Client Workstation - C/S

These are workstations used when running the client/server (C/S) versions of Oracle Utilities applications, such as Data Manager.

Hardware	Minimum Requirements
CPU	Intel® Pentium® series (2 core per CPU, 1.6 GHz minimum)
Memory	2GB or higher
Disk Drive	80GB SATA 7200RPM
Network	100 MB/s or higher

Software for Client Workstation - C/S:

- Supported Operating Systems
 - Microsoft Windows XP Professional with Service Pack 3 (SP3) or higher
 - Microsoft Windows Vista Business with Service Pack 1 (SP1)
 - Microsoft Windows 7
- Supported Web Browsers
 - Microsoft Internet Explorer 7 with latest security updates
 - Microsoft Internet Explorer 8 with latest security updates
 - Microsoft Internet Explorer 9 with latest security updates
- Relational Database Management System (RDBMS) client with applicable ODBC driver and Data Provider for .NET

Note: The Oracle 11gR2 SP1 (11.02.00.01) client requires patch 7 (or later).

Note: When using 64-bit operating systems, the 32-bit version of the database client is required.
- Oracle Utilities Energy Information Platform software
- Microsoft .NET Framework 3.5
- Microsoft Data Access Component (MDAC) 2.8 or higher
- Microsoft XML Core Services (MSXML) 4.0 SP2 or higher

Client Workstation - Web

These are workstations used when running the web-enabled versions of Oracle Utilities applications only.

Hardware	Minimum Requirements
CPU	Intel® Celeron® series (2 core per CPU, 1.6 GHz minimum)
Memory	1GB or higher
Disk Drive	80GB SATA 7200RPM
Network	100 MB/s

Software for Client Workstation - Web:

- Supported Operating Systems
 - Microsoft Windows XP Professional with Service Pack 3 (SP3) or higher
 - Microsoft Windows Vista Business with Service Pack 1 (SP1)
 - Microsoft Windows 7
- Supported Web Browsers
 - Microsoft Internet Explorer 7 with latest security updates
 - Microsoft Internet Explorer 8 with latest security updates
 - Microsoft Internet Explorer 9 with latest security updates

Note: For users that require access to both client/server and web browser-based applications, please refer to the requirements listed for "Client Workstations - Thick Client."

Database Server

The database server houses the Oracle Utilities Data Repository. The hardware platform for the database server may be Windows/Intel or UNIX/RISC.

Hardware	Minimum Requirements
CPU	2 x Intel® Xeon® 5000 series or RISC based (2 core per CPU, 2.0 GHz minimum)
Memory	16GB or higher
Disk Drive	2 x 72GB 15k rpm SCSI or better (system disk)
Data Storage	External Network Storage
Disk Controller	RAID
Network	2 x Gigabit Ethernet or higher

Software for Database Server:

- Supported Operating Systems
 - Microsoft Windows Server 2003, Microsoft Windows Server 2008, LINUX (UNIX/Intel), Sun Microsystems Solaris, HP-UX, or IBM AIX (UNIX/RISC) software
- RDBMS server - Oracle or Microsoft SQL Server

Database Platforms:

- Oracle 10g, Release 2 (10.2.0.4)
- Oracle 11g, Release 1 (11.1.0.7)
- Oracle 11g, Release 2 (11.2.0.3)
- Microsoft® SQL Server 2008*

Note: Supported database versions and drivers are subject to change. Please refer to the Oracle Release Notes shipped with the software for the latest compatibility matrix.

*Oracle Utilities Load Analysis, Oracle Utilities Portfolio Management, and Oracle Utilities Transaction Management are not supported on Microsoft SQL Server database.

Application/Batch Processing Server

Application servers are used when running Windows Services, such as those employed by the Reporting Framework and Adapter components. The application server(s) can also perform batch processes such as meter data upload and validation as well as batch billing and settlements.

Hardware	Minimum Requirements
CPU	2 x Intel® Xeon® 3000 series (2 core per CPU, 2.0 GHz minimum)
Memory	8GB or higher
Disk Drive	2 x 72 GB 10k rpm SCSI or better
Disk Controller	RAID
Network	2x Gigabit Ethernet or higher

Software for the Application/Batch Server:

- Supported Operating Systems
 - Windows 2003 Enterprise Server R2 with Service Pack 2 (SP2) or higher (32-bit and 64-bit)
 - Windows 2008 Enterprise Server with Service Pack 2 (SP2) (64-bit)
 - Windows 2008 Enterprise Server R2 (64-bit)
- Supported Web Browsers
 - Microsoft Internet Explorer 7 with latest security updates
 - Microsoft Internet Explorer 8 with latest security updates
 - Microsoft Internet Explorer 9 with latest security updates
- RDBMS client with applicable ODBC driver and Data Provider for .NET

Note: The Oracle 11gR2 SP1 (11.02.00.01) client requires patch 7 (or later).

Note: When using 64-bit operating systems, the 32-bit version of the database client is required.
- Oracle Utilities Energy Information Platform software
- Microsoft .NET Framework 3.5
- Microsoft Data Access Component (MDAC) 2.8 or higher
- Microsoft XML Core Services (MSXML) 4.0 SP2 or higher
- Java Development Kit (JDK) 1.7.0_45 or later (for application servers that will be running the Adapter)

Web Server(s)

Web servers run Microsoft Internet Information Service (IIS). These servers may be combined with the application server(s) for combination Web and Application servers.

Hardware	Minimum Requirements
CPU	2 x Intel® Xeon® 3000 series (2 core per CPU, 2.0 GHz minimum)
Memory	8GB or higher
Disk Drive	2 x 72 GB 10k rpm SCSI or better
Disk Controller	RAID
Network	2x Gigabit Ethernet or higher

Software for Web Server(s):

- Supported Operating Systems
 - Windows 2003 Enterprise Server R2 with Service Pack 2 (SP2) or higher (32-bit and 64-bit) with Microsoft Internet Information Service (IIS) 6.0
 - Windows 2008 Enterprise Server with Service Pack 2 (SP2) (64-bit) with Microsoft Internet Information Service (IIS) 7.0
 - Windows 2008 Enterprise Server R2 (64-bit) with Microsoft Internet Information Service (IIS) 7.0

Note: The IIS6 Management Capability option (including IIS6 Metabase Compatibility, IIS6 WMI Compatibility, IIS6 Scripting Tools, and IIS6 Management Console) must be installed when using IIS on Windows 2008.
- Supported Web Browsers
 - Microsoft Internet Explorer 7 with latest security updates
 - Microsoft Internet Explorer 8 with latest security updates
 - Microsoft Internet Explorer 9 with latest security updates
- RDBMS client with applicable ODBC driver and Data Provider for .NET

Note: The Oracle 11gR2 SP1 (11.02.00.01) client requires patch 7 (or later).

Note: When using 64-bit operating systems, the 32-bit version of the database client is required.
- Oracle Utilities Energy Information Platform software
- Microsoft .NET Framework 3.5
- Microsoft Data Access Component (MDAC) 2.8 or higher
- Microsoft XML Core Services (MSXML) 4.0 SP2 or higher

Sample Platform Configurations

This section outlines sample platform configurations for several different Oracle Utilities products. Each configuration comprises different sets of the Oracle Utilities system components described above. Note that these are provided as examples only. Listings of client workstations are followed by the types of users expected to use the workstation. This includes End Users and System and Security Administrators.

Oracle Utilities Billing Component, Oracle Utilities Rate Management

This configuration applies to the C/S versions of Oracle Utilities Billing Component or Oracle Utilities Rate Management. It includes only C/S applications, and consists of the following components:

- Database Server
- Application/Batch Processing Server
- One or more Client workstations (C/S) [End users and System Administration]

Oracle Utilities Billing Component with Oracle Utilities Receivables Component

This configuration includes using the C/S version of Oracle Utilities Billing Component with the Oracle Utilities Receivables Component, and consists of the following components:

- Database Server
- Application/Batch Processing Server
- Web Server
- One or more Client workstations (C/S) [End users and System Administrators]
- One or more Client workstations (Web) [End users and Security Administrators]

Oracle Utilities Billing Component Web, Oracle Utilities Quotations Management (web)

This configuration includes primarily web applications, and consists of the following components:

- Database Server
- Application/Batch Processing Server
- Web Server
- One or more Client workstations (Web) [End Users and Security Administrators]
- One or more Client workstations (C/S) [System Administrators]

Application and Web Service Configuration

This section outlines a number of configuration steps that must be performed on application and web servers prior to installing the Oracle Utilities software.

Configuration Steps for Windows 2003

When installing on Windows 2003, the version of ASP.NET must be set to 2.0.5.0727. Use the following procedure to set this version of ASP.NET.

1. Select **Start→Administrative Tools→Internet Information Services (IIS) Manager**.
2. Click on the plus (+) sign next to your server to expand your server.
3. Expand **Web Sites** by clicking on the plus (+) sign.
4. Right-click **Default Web Site** and select **Properties**.
5. Select the **ASP.NET** tab.
6. Select **2.0.50727** on the ASP.NET version drop-down list.
7. Click **Apply**.
8. Restart the IIS service.

Configuration Steps for Windows 2008

When installing on Windows 2008 (64-bit), you must configure the server to run the Oracle Utilities software in 32-bit mode.

Use the following procedure to perform this configuration.

1. Select **Start→Administrative Tools→Internet Information Services (IIS) Manager**.
2. Click on the plus (+) sign next to your server to expand your server.
3. Expand **Web Sites** by clicking on the plus (+) sign.
4. Select **Default Web Site**.
5. Click **Basic Settings** in the **Actions** box in the upper right of the page.
The **Edit Site** dialog opens.
6. Click **Select**.
The **Select Application Pool** dialog opens.
7. Select **Classic .NET AppPool** from the Application Pool drop-down list.
8. Click OK to close the **Select Application Pool** dialog.
9. Click OK to close the **Edit Site** dialog.
10. Select **Application Pools** on the Internet Information Services Manager screen (under your server).
11. Select **Classic .NET AppPool** from the list of application pools in the center of the screen.
12. Click **Advanced Settings** in the **Edit Application Pool** box in the upper right of the page.
The **Advanced Settings** dialog opens.
13. Set **Enable 32-bit Applications** to **True** (in the General section of the dialog).
14. Click OK to close the **Advanced Settings** dialog.
15. Exit the Internet Information Services (IIS) Manager.

Installing Relational Database Management System Software

This section describes installation and setup of Relational Database Management System (RDBMS) application software on the database server, application server, and client machine(s), including:

- **Setting Up the Relational Database Connection**
- **Oracle Database Connectivity**
- **Specifying the Time Zone for Oracle Database Servers (optional)**
- **Oracle Real Application Cluster (RAC)**
- **MS SQL Server 2008 Configuration**

The Oracle Utilities Energy Information Platform supports the following RDBMS:

- Oracle 10gR2 (10.2.0.4), 11gR1 (11.1.0.7), 11gR2 (11.2.0.3)
- MS SQL Server 2008

Later versions of these RDBMS are generally supported when proven stable through Quality Assurance testing at Oracle. Please contact technical support for information on which RDBMS versions are currently supported.

Setting Up the Relational Database Connection

Before the Oracle Utilities application software can be installed, a relational database connection must be established between the database server and the application server and client machines. This section explains how to set up this connection.

Important Note!

Setting up the relational database connection is a critical step in installing and implementing Oracle Utilities software. Without a working database connection, the software cannot function properly. **Consult with your IT department and Database Administrator (DBA) when performing the following steps.**

How to set up a relational database connection for Oracle Utilities software:

1. Install the appropriate RDBMS server software on the database server. Refer to installation information for your RDBMS for more information.
2. Install the RDBMS client software on the application server and client machines.

Note: When using 64-bit operating systems, the 32-bit version of the database client is required.

3. Create a database connection between the database server and a client machine using RDBMS client software.
4. Create the Oracle Utilities Data Repository schema on the database server. See **Chapter 3: Oracle Utilities Data Repository Schema Creation** for more information.
5. Create user IDs for each client you need in the database, and assign PWRLINE_USER roles to each.

Note: The PWRLINE_USER role is created when you create the Oracle Utilities schema on the database server.

6. Create Data Source Names (DSNs) for the Oracle Utilities Data Repository schema on each machine and test the connection to the server.

Oracle Database Connectivity

This release uses both Oracle Data Provider (ODP) and ODBC for database connectivity.

- ODBC is required when running database creation and/or upgrade scripts, and when using Business Objects® Crystal Reports® reporting software.
- ODP is required for all other database connectivity.

Oracle Data Provider (ODP) Information

This release requires Oracle Data Provider for .NET 3.5. The specific version for each Oracle version is as follows:

Oracle Database Version	Oracle Data Provider for .NET Version	Oracle Data Access Version
10gR2 (10.2.0.4)	10.2.0.4.0	2.102.4.0
11gR1 (11.1.0.7)	11.1.0.7.20	2.111.7.2
11gR2 (11.2.0.3)	11.2.0.3.0	2.112.3.0

When installing Oracle 10g database software, use the following procedure:

- Install the 10.2.0.1 client
- Install ODP 2.0 10.2.0.2.20 (or 10.2.0.2.21 on Vista)
- Install the 10.2.0.4 patch, which also patches the ODP

ODBC Driver Information

Below is a matrix of the ODBC driver versions, database versions and the operating systems supported by the Oracle Utilities products included in this release:

Oracle Database Version	ODBC Version
10gR2 (10.2.0.4)	10.2.0.4
11gR1 (11.1.0.7)	11.1.0.7
11gR2 (11.2.0.3)	11.2.0.3

ODBC Driver Configuration

ODBC Data Source names must match the name defined in the tnsnames.ora file *exactly*.

To properly configure your Oracle ODBC driver, open the Data Sources (ODBC) Control Panel, select the System DSN tab, and double-click on the appropriate data source (DSN). Select the Application tab, see to it that "Enable Query Timeout" is not selected.

Note: ODBC drivers must be configured using the 32-bit obdcad32.exe program. This is usually located in the ..\windows\sysWOW64 folder.

Specifying the Time Zone for Oracle Database Servers (optional)

Oracle database servers can be configured to specify the time zone used by the applications. This can be used in situations where users are located in a different time zone than the application and database servers.

When using this feature, dates/times calculated by the system will reflect the time zone specified for the database and application servers.

Note: This feature is available for Oracle databases only, and should ONLY be used when ALL users are located in the same time zone, and the application and database servers are located in a different time zone.

When using this feature, the time zones specified on the database server should also be specified on **ALL** application and web servers that will access the database server.

To specify the time zone used by the Oracle database server, you must define the time zone for the Oracler user used by the Energy Information Platform applications to access the database.

For Oracle databases run on Linux, this is done by changing the TZ variable in the **.bash_profile** file. The syntax for this is as follows:

```
TZ='<TIMEZONE>' ; export TZ
```

where:

- **<TIMEZONE>** is the time zone you wish to specify for the database user and server.

Example:

```
TZ='GMT+2' ; export TZ
```

Note: Log files display date and time information based on the server/operating system time zone, and will ignore the time specified for the Oracle user.

Oracle Real Application Cluster (RAC)

This release supports the use of Oracle Real Application Clusters (RAC) with the database servers running Oracle 10g Release 2 (10gR2) or Oracle 11g Release 2 (11gR2). This section outlines specific steps involved in configuring your environment to work with Oracle RAC.

Installing Oracle RAC

Install the Oracle RAC software as described in the *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Installation Guide* (for 10g Release 2 or 11g Release 2).

Application/Web Server Configuration for Oracle RAC

This section outlines application/web server configuration tasks required when using Oracle RAC.

TNS Names File

The TNS Names file (tnsnames.ora) on each application server, web server, and client workstation must specify the RAC node names within the TNS entry being referenced by the Energy Information Platform software. Specifically, the HOST attributes (within the ADDRESS attributes) must be set to the machine name of the nodes (database servers) in the cluster. The following example illustrates how you might specify the node names for 2 nodes in a cluster (node1 and node2).

```
racdb =
  (DESCRIPTION =
    (LOAD_BALANCE = ON)
    (ADDRESS = (PROTOCOL = TCP) (HOST = node1-vip) (PORT = 1521))
    (ADDRESS = (PROTOCOL = TCP) (HOST = node2-vip) (PORT = 1521))
    (CONNECT_DATA =
      (SERVER = DEDICATED)
      (SERVICE_NAME = racdb)
    )
  )
```

In addition, a “failover” entry with the same SERVICE_NAME attribute must also be included in the TNS Names file. The following example illustrates how you specify the node names for 2 nodes in a cluster (node1 and node2) in the “failover” entry.

```
failover =
  (DESCRIPTION =
    (enable=broken)
    (LOAD_BALANCE = ON)
    (ADDRESS = (PROTOCOL = TCP) (HOST = node1-vip) (PORT = 1521))
    (ADDRESS = (PROTOCOL = TCP) (HOST = node2-vip) (PORT = 1521))
    (CONNECT_DATA =
      (SERVER = DEDICATED)
      (SERVICE_NAME = racdb)
      (failover_mode=(type=select) (method=basic))
    )
  )
```

Hosts File

The Hosts file on each application server, web server, and client workstation must be edited to specify the RAC node names. This file is located in the C:\Windows\System32\drivers\etc directory. Each node should be listed in the following format at the bottom of the file:

```
<virtual_ip> <node_name>-vip
```

where:

- **<virtual_ip>** is the virtual IP address of the node, as defined in the RAC installation
- **<node_name>** is the name of the node (database server) in the cluster that are to be accessed by the Adapter.

The following example illustrates how node names for 2 nodes in a cluster (node1 and node2) might be listed in this file.

```
# Copyright (c) 1993-1999 Microsoft Corp.
#
# This is a sample HOSTS file used by Microsoft TCP/IP for Windows.
#
# This file contains the mappings of IP addresses to host names. Each
# entry should be kept on an individual line. The IP address should
# be placed in the first column followed by the corresponding host name.
# The IP address and the host name should be separated by at least one
# space.
#
# Additionally, comments (such as these) may be inserted on individual
# lines or following the machine name denoted by a '#' symbol.
#
# For example:
#
#       102.54.94.97       rhino.acme.com           # source server
#       38.25.63.10       x.acme.com               # x client host

```



```
127.0.0.1       localhost
10.159.172.22   node1-vip
10.159.172.23   node2-vip
```

Energy Information Platform Configuration for Oracle RAC

This section outlines Energy Information Platform configuration tasks required when using Oracle RAC.

LTMH.CFG.XML Configuration File

The LTMH.CFG.XML configuration file on each application server and web server that will be running the Energy Information Platform Adapter must be edited to specify the TNS entry for the RAC connection in the JDBC connection section. The following example illustrates the specific elements and attributes that must be populated.

```
<LTMH JMSENABLED="false">
...
  <!-- Connection for an Oracle database -->
  <JDBC URL="jdbc:oracle:thin:@(DESCRIPTION = (LOAD_BALANCE =
ON) (ADDRESS = (PROTOCOL = TCP) (HOST = <HOST_NAME>) (PORT = <PORT>)) (ADDRESS =
(PROTOCOL = TCP) (HOST = <HOST_NAME>) (PORT = <PORT>)) (CONNECT_DATA =
(SERVICE_NAME = racdb)))">
    <DRIVER TYPE="ORACLE">oracle.jdbc.OracleDriver</DRIVER>
    <QUALIFIER>tr450</QUALIFIER>
    <USERNAME>tr450</USERNAME>
    <PASSWORD>password</PASSWORD>
  </JDBC>
...
</LTMH>
```

where:

- **<HOST_NAME>**: is the name of the node (database server) in the cluster that are to be accessed by the Adapter.
- **<PORT>** is the port the database connection will use. Default is 1521.

See **LTMH.CFG.XML** on page 2-46 in the *Oracle Utilities Energy Information Platform Configuration Guide* for more information about this configuration file.

LSReportMonitor.CFG.XML Configuration File

The LSReportMonitor.CFG.XML configuration file on each application server and web server that will be running Crystal Reports or BI Publisher reports must be edited to specify the TNS entry for the RAC connection in the Alternate database connection section. The following example illustrates the specific elements and attributes that must be populated.

```
<LSREPORTMONITOR>
  <DATASOURCE>
    <NAME>QA Only</NAME>
    <CONNECTSTRING>Data Source=racdb;User
ID=ls106d;Password=lodestar;LSProvider=ODP;</CONNECTSTRING>
    <QUALIFIER>ls106d</QUALIFIER>
  </DATASOURCE>
  <ALTERNATES>
    <CONNECTSTRING NAME="QA Only" REPORTTYPE="BIPublisher">(DESCRIPTION =
(Load_Balance = ON) (Address = (Protocol = TCP) (Host = <HOST_NAME>) (Port =
<PORT>)) (Address = (Protocol = TCP) (Host = <HOST_NAME>) (Port =
<PORT>)) (CONNECT_DATA = (Server = Dedicated) (Service_Name = racdb)))</
CONNECTSTRING>
  </ALTERNATES>
  ...
</LSREPORTMONITOR>
```

where:

- **<HOST_NAME>**: is the name of the node (database server) in the cluster that are to be accessed by Crystal Reports.
- **<PORT>** is the port the database connection will use. Default is 1521.

See **LSREPORTMONITOR.CFG.XML** on page 2-35 in the *Oracle Utilities Energy Information Platform Configuration Guide* for more information about this configuration file.

Oracle BI Publisher Configuration for Oracle RAC

This section outlines Oracle BI Publisher configuration tasks required when using Oracle RAC.

Data Source Connection String

The Connection String of the Data Source must specify the TNS entry for the RAC connection. The following example illustrates the correct syntax for the Connection String:

```
jdbc:oracle:thin:@(DESCRIPTION = (LOAD_BALANCE = ON) (ADDRESS = (PROTOCOL =
TCP) (HOST = <HOST_NAME>) (PORT = <PORT>)) (ADDRESS = (PROTOCOL = TCP) (HOST =
<HOST_NAME>) (PORT = <PORT>)) (CONNECT_DATA = (SERVICE_NAME = racdb)))
```

where:

- **<HOST_NAME>** is the name of the node(s) (database servers) in the cluster that are to be accessed by the Adapter.
- **<PORT>** is the port the database connection will use. Default is 1521.

MS SQL Server 2008 Configuration

This section outlines configuration tasks that must be performed when using MS SQL Server 2008, including:

- **Edit WEB.CONFIG Configuration File**
- **Install MS SQL Server JDBC Driver**

Edit WEB.CONFIG Configuration File

When using MS SQL Server 2008, you must edit the WEB.CONFIG configuration file on each web server that will be running the Energy Information Platform Adapter. To edit this file, use the following procedure:

1. Locate the web.config file in the **c:\lodestar\web** directory on the web server.
2. Remove the following line from this file:

```
<add assembly="Oracle.DataAccess, Version=2.102.2.20,
Culture=neutral, PublicKeyToken=89B483F429C47342"></add>
```

3. Save the file.

Note: This file will be replaced when upgrading to a new release or service pack version. Make a back-up copy of this file and keep it with back-ups of your other configuration files (LODESTAR.CFG, LSSECURE.CFG.XML, etc.).

Install MS SQL Server JDBC Driver

When using MS SQL Server 2008, you must install a Java Database Connectivity (JDBC) 2.0 driver on each application server and web server that will be running the Energy Information Platform Adapter. The driver **MUST** be JDBC 2.0 compliant.

Energy Information Platform Configuration

This section outlines configuration tasks required when using a non-Oracle JDBC driver.

Adapter - System Properties

The System Properties records for all Adapter servers must be updated to reflect the JDBC driver being used. Specifically, the Class Path of each System Properties record must be edited to include the .jar file of the JDBC driver. The following example highlights the Class Path of the Oracle JDBC driver:

```
.\portal.jar;.\lthm.jar;.\lsice.jar;.\CustomerBusinessRules.jar;.\lib\jms.jar;
.\lib\tibjms.jar;.\lib\com.ibm.mq.jar;.\lib\com.ibm.mqjms.jar;.\lib\xercesImpl
.jar;.\lib\xalan.jar;.\lib\xml-
apis.jar;.\lib\ojdbc14.jar;.\lib\fscontext.jar;.\lib\providerutil.jar;.\lib\co
mmons-cli-1.0.jar;.\lib\commons-lang-2.0.jar
```

See **System Properties** on page 11-12 in the *Oracle Utilities Energy Information Platform User's Guide* for more information about editing System Properties records.

LTMH.CFG.XML Configuration File

The LTMH.CFG.XML configuration file on each application server and web server that will be running the Energy Information Platform Adapter must be edited to specify the JDBC driver. The JDBC Oracle section should be commented out or removed from the file, and the JDBC SQL Server section must be populated. The following example illustrates the specific elements and attributes that must be populated.

```
<LTMH JMSENABLED="false">
...
  <!-- Connection for a SQL Server database -->
  <!-- A SQL Server JDBC driver can be obtained from http://
jtds.sourceforge.net -->
  <JDBC URL="{DRIVER_URL}://{SERVERNAME}/{DATABASE}">
```

```
<DRIVER TYPE="SQLSERVER">{DRIVER_CLASS_PATH}</DRIVER>
<USERNAME>{DATABASE_USERNAME}</USERNAME>
<PASSWORD>{DATABASE_PASSWORD}</PASSWORD>
</JDBC>
...
</LTMH>
```

where:

- **{DRIVER_URL}** is the URL of the JDBC driver. Consult your driver's documentation for proper composition.
- **{DRIVER_CLASS_PATH}** is the full classpath of the JDBC driver.

See **LTMH.CFG.XML** on page 2-46 in the *Oracle Utilities Energy Information Platform Configuration Guide* for more information about this configuration file.

Installing and Configuring Reporting Software

This release of the Energy Information Platform provides reporting capabilities through Crystal Reports 2008 (Service Pack 2) and Oracle Business Intelligence Publisher version 10.1.3.4 or 11.1.1. This section provides information related to installing and configuring these reporting packages to work with the Energy Information Platform, including:

- **Installing Oracle Business Intelligence Publisher**
- **Configuring Oracle BI Publisher**
- **Installing Crystal Reports 2008**
- **Configuring Application and Web Servers for Crystal Reports 2008**

Installing Oracle Business Intelligence Publisher

When using Oracle Business Intelligence Publisher (Oracle BI Publisher), you install the Oracle BI Publisher software on a single application server. The Energy Information Platform application and web servers that will be used to generate reports are configured to communicate with the report server.

Note: The Oracle BI Publisher application can be installed either on an Energy Information Platform application or web server, or on a “stand-alone” server.

Oracle BI Publisher Installation

Download the Oracle BI Publisher installation program and documentation from the Oracle eDelivery website (<http://edelivery.oracle.com>).

Note: Oracle Business Intelligence Publisher must be licensed separately.

Install the Oracle BI Publisher software as described in the *Oracle Business Intelligence Publisher Installation Guide* (for the version being used, 10.1.3.4 or 11.1.1).

During the installation:

- Make a note of the name and path of the directory where the application is installed.
For example: BIPHome1 / c:\OraHome_1
- Select the “Basic” installation type.
- Set your OC4J Administrator (oc4jadmin) password. Passwords must be a minimum of 5 characters, maximum of 30 characters, and include at least one digit.

Example: Lodestar1

- Review your installation summary information:
 - Install Directory: c:\OraHome_1
 - Install Type: Oracle BI Publisher Basic
 - Installed Components: Oracle BI Publisher
 - Administrator Username: oc4jadmin
- Make a note of the URL used to access the Oracle BI Publisher application.

Example: <http://MADEV2K3ORVM01:9704/xmlpserver>

Configuring Oracle BI Publisher

This section outlines Oracle Business Intelligence Publisher configuration tasks required to enable Oracle Business Intelligence Publisher to generate and display reports run through the Energy Information Platform, including:

- **Start the Oracle BI Publisher Software**
- **Log In to the Oracle BI Publisher Software**
- **Create User for Reporting Framework**
- **Set Report Path**
- **Create Data Source for Oracle Utilities Data Repository**

Note: if installing Oracle BI Publisher on the same machine as the Energy Information Platform application server or web server software, install the Energy Information Platform software before proceeding with the following tasks.

Start the Oracle BI Publisher Software

The first step in configuring the Oracle BI Publisher software is to start the application.

To start the application, select **Start->All Programs->Oracle-BIPHome1->Start BI Publisher**.

A console (DOS) window opens on the desktop. Leave this window open in the background.

Log In to the Oracle BI Publisher Software

Once the Oracle BI Publisher software is running, you must log in to the application to continue the configuration tasks.

1. Launch the BI Publisher application using one of the following methods:

From the Start menu, select **Start->All Programs->Oracle - <ORACLE_HOME_NAME> ->BI Publisher Server**

where:

- **<ORACLE_HOME_NAME>** is the name you gave the Oracle Home where you installed Oracle BI Publisher.

From your browser, open your browser to `http://<hostname>:<port>/xmlpserver`

where:

- **<hostname>** is the name of the server
- **<port>** is the port where you installed Oracle BI Publisher

For example:

`http://localhost:9704/xmlpserver`

2. Log in to the Oracle BI Publisher server using the default administrator user name and password:
 - User Name: Administrator
 - Password: Administrator

Create User for Reporting Framework

You must create a BI Publisher administrator user on the Oracle BI Publisher server that the Reporting Framework will use to connect to the BI Publisher server when users create, run, and view BI Publisher reports.

To create a user, use the following procedure:

1. Navigate to the Admin tab, and click **Users** (under Security Center).
The User tab of the Security Center screen opens.
2. Click **Create User**.
The Create User screen opens.
3. Enter the User ID and Password for the user and click **Apply**.
The User tab of the Security Center screen now displays the new user.
4. Click the **Assign Roles** icon.
The Assign Roles screen opens.
5. Select **BI Publisher Administrator** in the Available Roles box, and click **Move**.
The BI Publisher Administrator role now appears in the Assigned Roles box.
6. Click **Apply**.

Refer to the Oracle BI Publisher documentation for more information about users and roles.

The User ID and Password for this user should be specified in the BI_PUBLISHER/CONNECTSTRING element in the LSReportMonitor.cfg.xml configuration file on each application or web server on which the Reporting Framework will generate Oracle BI Publisher reports.

Set Report Path

You must set the path to the directory where the report template files are stored on the server.

To set the report path, use the following procedure:

1. Identify the report templates folder on the Oracle BI Publisher server.
 - If the Energy Information Platform (and related products) is installed on this machine, this is “C:\lodestar\bip.”
 - If Oracle BI Publisher is installed on a stand-alone server (a server where the Energy Information Platform is NOT installed), create a directory for the report templates, and copy the contents of the “C:\lodestar\bip” directory from an application server or web server to the directory you created.
2. Navigate to the Admin tab, and click **Report Repository** (under System Maintenance).
The Report Repository tab of the System Maintenance screen opens.
3. Select **File System** from the Repository Type drop-down list.
4. Enter the path to the directory where the report templates are located (defined in Step 1 above).

Create Data Source for Oracle Utilities Data Repository

You must also create a JDBC data source on the Oracle BI Publisher to allow a connection to the Oracle Utilities Data Repository. This is used when designing and testing reports.

To create a JDBC data source, use the following procedure:

1. Navigate to the Admin tab, and click **JDBC Connection** (under Data Sources).
The JDBC tab of the Data Sources screen opens.
2. Click **Add Data Source**.
The Add Data Source screen opens.
3. Enter the following for the new data source:

- **Data Source Name:** The name of the data source
- **Driver Type:** Select the driver type from the drop-down list. Applicable driver types include:
 - Oracle 11g
 - Oracle 10g
 - Microsoft SQL Server 2005
- **Database Driver Class:** the driver class for the data source. Should be one of the following:
 - Oracle: “oracle.jdbc.OracleDriver.”
 - MS SQL Server: “net.sourceforge.jtds.jdbc.Driver” or full classpath of JDBC driver
- **Connection String:** the connection string for the data source in one of the following formats:

For Oracle data sources:

```
jdbc:oracle:thin:@<ServerName>:<Port>:<YourDatabaseName>
```

where:

- **<ServerName>** is the machine name of the database server.
- **<Port>** is the port the database connection will use. Default is 1521.
- **<YourDatabaseName>** is the TNS service name used by the database’s ODBC connection.

Note: If using Oracle 10g RAC, the connection string must specify the TNS entry for the RAC connection. See **Oracle BI Publisher Configuration for Oracle RAC** on page 2-15 in the *Oracle Utilities Energy Information Platform Installation Guide* for more information.

For MS SQL Server data sources:

```
<DRIVER_URL>://<ServerName>/<Database>
```

where:

- **<Driver_URL>** is the URL of the JDBC driver
- **<ServerName>** is the machine name of the database server.
- **<Database>** is the database name.
- **User ID:** the user ID for the database connection
- **Password:** the password for the supplied user ID

4. Click **Apply**.

The new data source appears on the JDBC tab of the Data Source screen.

Installing Crystal Reports 2008

When using Crystal Reports 2008, you install the Crystal Reports software on each Energy Information Platform application and web server that will be used to generate reports.

Note: The Crystal Reports software should be installed **before** the Energy Information Platform software.

Crystal Reports 2008 Installation

Download the Crystal Reports 2008 (Service Pack 2) software and documentation from the SAP website. The specific installation program required for use with the Energy Information Platform is **Crystal Reports Service Pack 2 - Click Once**.

Note: Crystal Reports must be licensed separately.

Install the Crystal Reports software as described in the Crystal Reports installation documentation.

Configuring Application and Web Servers for Crystal Reports 2008


This section outlines application and web server configuration tasks required to enable Crystal Reports 2008 to generate and display reports run through the Energy Information Platform, including:

- **Configuration for Windows 2003**
- **Configuration for Windows 2008**

Configuration for Windows 2003

Configuring Windows 2003 application and web services involves the following:


- Grant **Read** and **Write** permissions for the “C:\windows\temp” folder to the **NETWORK SERVICE** user.



Configuration for Windows 2008

Configuring Windows 2008 application and web services involves the following:

- Grant **Full Control** permissions for the “C:\windows\temp” folder to the **NETWORK SERVICE** user.



Note: If the NETWORK SERVICE user does not exist, you must create this user.

- Copy the **libpng10.dll** file from the Crystal Reports directory: “C:\Program Files (x86)\Business Objects\Business Objects Enterprise 12.0\win32_x86” to the “C:\LODESTAR\Bin” folder on the server.

Chapter 3

Oracle Utilities Data Repository Schema Creation

This chapter explains how to create the Oracle Utilities Data Repository schema, including:

- Accessing the Database Creation Scripts
- Schema Creation for Oracle 10g and 11g
- Schema Creation for MS SQL Server 2008
- Upgrading the Oracle Utilities Energy Information Platform Database Schema
- Updating the Reporting Framework for Oracle Business Intelligence Publisher
- Base Database Tables
- Optional Schemas
- Updating the LSGlobal Table

Later versions of the above RDBMS are generally supported when proven stable through Quality Assurance testing at Oracle. Please contact technical support for information on which RDBMS versions are currently supported. If your facility uses another type of database software, contact Oracle.

Accessing the Database Creation Scripts

The database creation scripts you will use to create the Oracle Utilities Data Repository database schema are included in the Energy Information Platform installation package (01.06.00.xx.00.EIP.zip). When the contents of the installation package have been extracted, the database scripts are located in one of the following directories:

- ..\DBScripts\EIP\Oracle\ (for Oracle databases)
- ..\DBScripts\EIP\MSSQL\ (for MS SQL Server databases)

Product-Specific Database Scripts

Some product require additional database tables in the Oracle Utilities Data Repository. These are added via product-specific database scripts. These scripts are included in the product-specific installation programs.

After being extracted from the installation package, the database scripts can be found using the following path:

..\<PRODUCT>\<DB_TYPE>\<SCRIPT_TYPE>

where:

<PRODUCT> is the abbreviation for the product you are installing.

<DB_TYPE> is the type of database platform you are using, Oracle or MS SQL Server

<SCRIPT_TYPE> is the type of database script you wish to access, Install or Upgrade

For example, to add the Oracle Utilities Meter Data Management database schema to the Oracle Utilities Data Repository, you would first extract the contents of the **01.06.00.xx.00.MDM.zip** file. The database scripts are located in one of the following directories:

- ..\DBScripts\MDM\Oracle\ (for Oracle databases)
- ..\DBScripts\MDM\MSSQL\ (for MS SQL Server databases)

Schema Creation for Oracle 10g and 11g

This section describes the steps required to create a Oracle Utilities Schema for Oracle 10g and 11g. These steps create the necessary tables for the Oracle Utilities Data Repository, as well as load initial data. This section includes:

- **Schema Creation**
- **Data Loading**
- **Number of Open Cursors on Oracle Server**
- **ODBC Data Source Options**

Schema Creation

The base database schema consists of 180 tables, each of which has one or more constraints, and possibly one or more indexes. The BUILDORA.CMD file included with your Oracle Utilities installation is the top-level script used to initially create these tables. The syntax for this tool is:

```
buildora -l <userid/password|/> [-d <database>] [-own <owner name>]
-opw <owner password> [-security]
```

Parameter	Description
<userid/password>	The userID and password for a user with system administrator privileges (a '/' can be used here if OS-authentication is supported)
<database>	The service name given to the instance as specified in the TNSNAMES.ORA file. and the ODBC DSN name of the same database instance. This parameter is optional and if not specified, the script will connect to the default Oracle database.
<owner name>	The name of the user which will own the database objects. This parameter is optional. If not specified, the default user PWRLINE will own the database objects.
<owner password>	The chosen password for the PWRLINE schema owner.

Note: Database scripts must be run from either a client workstation, application/batch server, or web server with all required software previously installed. See **Oracle Utilities Platform Components Specifications** on page 2-2 for more information about the software required on each of these types of system components.

The optional **-security** parameter specifies that the Security schema be installed as a stand-alone schema. See **Security Schema** on page 3-20 for more information about this schema.

A log file named BUILDORA.LOG is created when the BUILDORA script is run. You should check this log file for possible errors after running the script.

Note: When running database scripts from a 64-bit machine, the scripts must be run via the 32-bit version of the cmd.exe program, normally located in the ..\windows\sysWOW64 folder.

Schema Creation in Advance Storage Mode

By default, the buildora.cmd script runs in basic storage mode. In basic storage mode tables, indexes, and LOB segments placed in the default tablespace of the user that will own the database objects.

You also can run the buildora.cmd script in advanced storage mode. In advanced storage mode tables, indexes, and LOB segments will be placed in 3 different tablespaces. By default, the names of these tablespaces are LSTAR_DATA, LSTAR_INDEX and LSTAR_LOB respectively.

How to run the buildora.cmd script in advanced storage mode:

1. Right-click on buildora.cmd and click EDIT. At the top of script you will see following lines:

```
rem *****
rem Valid values for STORAGE_MODE are BASIC and ADVANCED
rem *****

set STORAGE_MODE=BASIC
set TAB_TBLSPACE=LSTAR_DATA
set IND_TBLSPACE=LSTAR_INDEX
set LOB_TBLSPACE=LSTAR_LOB

rem *****
```

2. Change the STORAGE_MODE line from “BASIC” to “ADVANCED”
3. The default tablespace for tables is “LSTAR_DATA”. To change this, change the TAB_TBLSPACE line from “LSTAR_DATA” to the desired name.
4. The default tablespace for indexes is “LSTAR_INDEX”. To change this, change the IND_TBLSPACE line from “LSTAR_INDEX” to the desired name.
5. The default tablespace for LOB segments is “LSTAR_LOB”. To change this, change the LOB_TBLSPACE line from “LSTAR_LOB” to the desired name.
6. Save the changes and run the script.

Note: The buildora.cmd script does not create tablespaces for you. If you going to run the buildora.cmd script in advanced storage mode, you should create proper tablespaces before running the script.

Notes:

1. The name of the database objects owner must be 7 or less characters.
2. If your database objects owner is not PWRLINE, then you have to use the -q <owner name> parameter in the command line for Oracle Utilities applications, where <owner name> is your database objects owner.

The script consists of the phases described below.

Phase 1: Schema Owner Creation

The BUILDORA script first creates the PWRLINE (or other user if specified in the **-own** parameter) user with DBA privileges. The PWRLINE user is the owner of all of the database tables. The script assumes that the name of the tablespace used to contain all data is USERS and that there also exists a tablespace named TEMP which is used for temporary storage of data required for sorting, index creation, and other functions. **If this is not the case then this script must be edited prior to schema creation to reflect the proper names of these two tablespaces.**

Note: The advisable storage space for testing databases recommended is 100 MB on USERS and 50MB on TEMP.

Phase 2: PWRLINE_USER and LSSEC_ADMIN Role Creation

The BUILDORA script next creates two database role named PWRLINE_USER and LSSEC_ADMIN.

The PWRLINE_USER role is granted read and write access to all of the tables. Any database users who are subsequently created should be granted this role so that they too have read and write access to the tables. However, the PWRLINE_USER role does NOT have permissions to work with security database tables.

The LSSEC_ADMIN role is granted read and write access to the tables in the Security schema. However, this role does NOT have permissions to work with other tables.

Phase 3: Base Schema Table Creation

The BUILDORA script next creates each of the 180 base database tables along with any declarative constraints. The parent tables of all referential integrity constraints are created before their respective dependent tables. See **Base Database Tables** on page 3-13 for the order in which the tables are created.

All database tables are created in the default data tablespace of the PWRLINE (or other user if specified in the **-own** parameter) user with default Oracle sizing parameters. If you decide that these defaults are not appropriate for your database installation, the table creation script should be edited prior to schema creation.

Phase 4: Loading Initial Required (Generic) Data

Oracle Utilities provides some lookup codes, as well as the base metadata required to initially populate the database. This includes data for the following tables:

- Units of Measure (UOM)
- UOM Rate Quantities (UOMRATEQUANTITY)
- Bill Determinants (BILLDETERMINANT)
- Note Types (ACCTNOTETYPE)
- MV90 Status Code Map (MV90STATUSCODEMAP)
- Report Lists (REPORTLIST)
- Type Metadata (TYPEMETADATA)
- Domain Metadata (DOMAINMETADATA)
- Table Metadata (TABLEMETADATA)
- Column Metadata (COLUMNMETADATA)
- Reference Metadata (REFERENCEMETADATA & KEYCOLUMNMETADATA)
- LODESTAR DB Version (LSDBVERSION)
- Versioning Status (VERSIONINGSTATUS)

Phase 5: Schema Index Creation

The next phase of schema creation is the creation of additional indexes used to improve query performance of various functions. Like the database tables, these indexes are also created in the default tablespace of the PWRLINE user with default sizing parameters. If these defaults are required to be changed then the script may be edited.

Phase 6: Loading LSGLOBAL dictionary

The next phase of schema creation is the loading of the LSGLOBAL dictionary. The LSGLOBAL table holds the visible names of tables, references, and data types in xml format, and is required for international support in Oracle Utilities applications. You **must** update the LSGlobal table

whenever metadata changes are made to the database. See **Updating the LSGlobal Table** on page 3-21 for more information about updating the LSGLOBAL table.

Phase 7: Loading pre-defined Report Templates

The last phase of schema creation is the loading of pre-defined report templates used by the Oracle Utilities Reporting Framework. See **Chapter 13: Energy Information Platform Reporting Framework** for more information about report templates and the Reporting Framework.

Data Loading

The Data Manager application provides graphical interfaces to add, edit, and delete data in the Oracle Utilities Data Repository. It also provides access to the Import utility for bulk loading of data from comma delimited, ASCII files. See the *Data Manager User's Guide* for more information.

The RSTATORA.CMD file included with your Oracle Utilities installation is the script used to update statistics. After every major data load (approximately 20K records), run this script to update statistics for optimal performance. The syntax for this script is:

```
rstatora [-d <database>] [-own <owner name>] -opw <owner password>
```

Parameter	Description
<database>	The name given to the instance as specified in the TNSNAMES.ORA file. This parameter is optional and if not specified, the script will connect to the default Oracle database.
<owner name>	The name of the user which will own the database objects. This parameter is optional. If not specified, the default user PWRLINE will own database objects.
<owner password>	The chosen password for the PWRLINE schema owner.

A log file named RSTATORA.LOG is created when the RSTATORA script is run. You should check this log file for possible errors after running the script.

Note: When running database scripts from a 64-bit machine, the scripts must be run via the 32-bit version of the cmd.exe program, normally located in the ..\windows\sysWOW64 folder.

Number of Open Cursors on Oracle Server

The following setting is needed in the init<sid>.ora (startup file):


```
Open_cursors = 1000
```

The above setting is a minimum. It can be more than 1000 if enough physical memory is available.


ODBC Data Source Options

The following settings are needed in ODBC Data Source options on each client machine:

- Enable LOBs = TRUE (checkbox is checked)



- Enable Query Timeout = FALSE (checkbox is unchecked)



Schema Creation for MS SQL Server 2008

This section describes the various steps required to create a Schema for MS SQL Server 2008. These steps create the necessary tables for the Oracle Utilities Data Repository, as well as load initial data.

Schema Creation

The base database schema currently consists of 180 tables, each of which has one or more constraints, and possibly one or more indexes. The BUILDSQL.CMD file included with your Oracle Utilities installation is the top-level script used to initially create these tables. The syntax for this tool is:

```
buildsql -d <dbname> -u <admin userid> -p <admin password>
[-s <server>] [-own <owner name>] -opw <owner password>
[-crdb <TRUE|FALSE>] [-dn1 <device1 number>] [-dn2 <device2 number>]
```

Parameter	Description
<dbname>	The name given to the database in the SQL server instance
<admin userid>	The userid for a user with system administrator privileges.
<admin password>	The password for a user with system administrator privileges.
<server>	The name of the SQL server. By default this is the name of the NT server.
<owner name>	The chosen username for the database schema owner.
<owner password>	The chosen password for the database schema owner.
<-crdb>	<p>If set to TRUE, the script will create a new database on the sybase server with name specified in <dbname> parameter and using values from the <-dn1> and <-dn2> parameters like device numbers for new database devices for this database.</p> <p>If set to FALSE, the script will not create new database. The script will connect to an existing database with a name specified in <dbname> parameter and ignore values in the <-dn1> and <-dn2> parameters.</p>

A log file named BUILDSQL.LOG is created when the BUILDSQL script is run. You should check this log file for possible errors after running the script.

Note: When running database scripts from a 64-bit machine, the scripts must be run via the 32-bit version of the cmd.exe program, normally located in the ..\windows\sysWOW64 folder.

Notes:

1. The name of the database objects owner can be 7 or less characters.
2. If your database objects owner is not PWRLINE, then you have to use the -q <owner name> parameter in the command line for Oracle Utilities applications, where <owner name> is your database objects owner.

The schema creation consists of five phases which are described below.

Phase 1: Schema Owner Creation

The BUILDSQL script first creates the PWRLINE user with DBO privileges. The PWRLINE user is the owner of all of the database tables. The script assumes enough space on drive containing the X:\Mssql\Data directory. If this is not the case, the script must be edited prior to schema creation to reflect the proper Drive specification.

Phase 2: PWRLINE_USER Role Creation

The BUILDSQL script next creates a database role named PWRLINE_USER. This role is granted read and write access to all of the tables. Any database users who are subsequently created should be granted this role so that they have read and write access to the tables.

Phase 3: Base Schema Table Creation

The BUILDSQL script next creates each of the 180 base database tables along with any declarative constraints. The parent tables of all referential integrity constraints are created before their respective dependent tables. See **Base Database Tables** on page 3-13 for the order in which the tables are created.

All database tables are created in the default data tablespace of the PWRLINE (or other user if specified in the **-own** parameter) user with default Sqlcle sizing parameters. If you decide that these defaults are not appropriate for your database installation, the table creation script should be edited prior to schema creation.

Phase 4: Loading Initial Required (Generic) Data

Oracle Utilities provides some lookup codes, as well as the base metadata required to initially populate the database. This includes data for the following tables:

- Units of Measure (UOM)
- UOM Rate Quantities (UOMRATEQUANTITY)
- Bill Determinants (BILLDETERMINANT)
- Note Types (ACCTNOTETYPE)
- MV90 Status Code Map (MV90STATUSCODEMAP)
- Report Lists (REPORTLIST)
- Type Metadata (TYPEMETADATA)
- Domain Metadata (DOMAINMETADATA)
- Table Metadata (TABLEMETADATA)
- Column Metadata (COLUMNMETADATA)
- Reference Metadata (REFERENCEMETADATA & KEYCOLUMNMETADATA)
- LODESTAR DB Version (LSDBVERSION)
- Versioning Status (VERSIONINGSTATUS)

Phase 5: Schema Index Creation

The final phase of schema creation is the creation of additional indexes used to improve query performance of various functions. Like the database tables, these indexes are also created in the default tablespace of the PWRLINE (or other user if specified in **-own** parameter) user with default sizing parameters. If these defaults are required to be changed, the script may be edited.

Data Loading

The Data Manager application provides graphical interfaces to add, edit, and delete data in the Oracle Utilities Data Repository. It also provides access to the Import utility for bulk loading of data from comma delimited, ASCII files. See the *Data Manager User's Guide* for more information.

The RSTATSQL.CMD file included with your Oracle Utilities installation is the script used to update statistics. After every major data load (approximately 20K records), run this script to update statistics for optimal performance. The syntax for this script is:

```
rstatsql -d <dbname> [-own <owner name>] -opw <owner password> -s  
<server>]
```

Parameter	Description
<dbname>	The name given to the database in the SQL server instance.
<owner name>	The chosen user name for the schema owner.
<owner password>	The chosen password for the schema owner.
<server>	The name of the SQL sever. By default this is the name of the NT server.

A log file named RSTATSQL.LOG is created when the RSTATSQL script is run. You should check this log file for possible errors after running the script.

Note: When running database scripts from a 64-bit machine, the scripts must be run via the 32-bit version of the cmd.exe program, normally located in the ..\windows\sysWOW64 folder.

Temp DB

Temp db is required to store temporary database query results as well results of multiple sorts etc. Make sure temp db is large enough to do the above process.

Temp db should be at least 50MB, either in RAM or on disk. Check with your system administrator or SQL Server DBA for more information.

Note: Do not use initial 2MB of temp db on master device.

Upgrading the Oracle Utilities Energy Information Platform Database Schema

If you are upgrading Oracle Utilities Energy Information Platform from a previous version, you must upgrade Energy Information Platform database schema. The following database upgrade scripts are included in the Energy Information Platform installation package.

- The **updateEIP.cmd** file. This database script updates the tables and data used by Oracle Utilities Energy Information Platform in the Oracle Utilities Data Repository. This script can only be used when upgrading the following schema version.

v1.6 Schema Version	v1.6.1 Schema Version
v1.6.0.0.0	v1.6.1.15.0

If you are upgrading from a different schema version, contact Oracle Global Customer Support.

Upgrading Oracle Utilities Energy Information Platform Schema

Open a command prompt and run the updateEIP.CMD script. This script uses the following syntax:

```
updateEIP [-d <database>] [-own <owner name>] -opw <owner password>
```

Parameter	Description
<database>	The name given to the instance as specified in the TNSNAMES.ORA file. This parameter is optional and if not specified, the script will connect to the default Oracle database.
<owner name>	The name of the user which will own Oracle Utilities database objects. This parameter is optional. If not specified, the default Oracle Utilities user PWRLINE will own database objects.
<owner password>	The chosen password for the PWRLINE schema owner.

Updating the Reporting Framework for Oracle Business Intelligence Publisher

If you are using Oracle Business Intelligence Publisher for reporting, you must update the pre-defined reports in Reporting Framework database tables. The following database scripts are included in the Energy Information Platform installation package for this purpose.

- The **BIPEIP.cmd** file. This script changes the pre-defined Energy Information Platform reports from Crystal Reports to Oracle Business Intelligence Publisher.

Oracle Utilities Energy Information Platform Reports

Open a command prompt and run the BIPEIP.CMD script. This script uses the following syntax:

BIPEIP [-d <database>] [-own <owner name>] -opw <owner password>

Parameter	Description
<database>	The name given to the instance as specified in the TNSNAMES.ORA file. This parameter is optional and if not specified, the script will connect to the default Oracle database.
<owner name>	The name of the user which will own Oracle Utilities database objects. This parameter is optional. If not specified, the default Oracle Utilities user PWRLINE will own database objects.
<owner password>	The chosen password for the PWRLINE schema owner.

Verification - Energy Information Platform Reports

To verify that the Energy Information Platform reports have been updated, use the following procedure:

1. Log into the database using the PWRLINE user (Password =password).
2. Verify that the following records exist in the Report Instance table:

Report Name	Description	Report Type
WQAging	Work Queue Aging	BIPublisher
WQOpenByUser	Work Queue Open Items	
WQProductivity	Work Queue Productivity	BIPublisher

Base Database Tables

The scripts used to build the database schema create the tables in the order listed below. These tables are available when using Oracle.

- ACCOUNT
- ACCOUNTHISTORY
- ACCOUNTNOTE
- ACCOUNTSTATUS
- ACCTBILLDETUSE
- ACCTDIRECTORY
- ACCTFACTORHIST
- ACCTNAMEOVERHIST
- ACCTNOTETYPE
- ACCTOVERRIDEHIST
- ACCTOVERRIDEREDY
- ACCTOVERRIDEUSE
- ACCTRATECODEHIST
- ACCTRIDERHIST
- ADDRESS
- AGGREGATIONGROUP
- AGSERVGRPHIST
- BILLCODE
- BILLDETERMINANT
- BILLFREQUENCY
- BILLFREQUENCYDATA
- BILLHISTORY
- BILLHISTORYVALUE
- BILLHISTORYEDIT
- BILLHISTORYEDITVAL
- BILLHISTORYPROBLEM
- BILLINGCYCLE
- BILLINGCYCLEDATE
- BLOCK
- BLOCKING
- BUDGETPLAN
- BUDGETTYPE
- CHANNEL
- CHANNELGROUP
- CHANNELHISTORY

- CHANSERVICEHIST
- CUSTOMER
- CUSTDIRECTORY
- DESKTOP
- DIRECTORY
- ENDUSE
- ENTINT
- ENTPURPOSE
- FACTOR
- FACTORVALUE
- GROUPCATEGORY
- HOLIDAY
- HOLIDAYLIST
- INDUSTRIALCLASSIFICATION
- INTERROGATION
- INTERSCHEDMAP
- JURISDICTION
- LASTUID
- LIST
- LISTQUERY
- LISTSTATUS
- LISTRESULTS
- LSACCOUNTTYPE
- LSBREAKPOINT
- LSCDVERSION
- LSCONTACTTYPE
- LSCURRENCY
- LSCHANNELCUTDATA
- LSCHANNELCUTHEADER
- LSCHANNELCUTVMSG
- LSCHVERSION
- LSDBAUDIT
- LSDBAUDITCLOBS
- LSDBAUDITUSERS
- LSDBVERSION
- LSFROMEMAIL
- LSGLOBAL
- LSINTDSTAGING

- LSINTDSOURCES
- LSINTDVERCONTROL
- LSPRODUCT
- LSSPLASHMESSAGE
- LSSPLASHMESSAGEEVENT
- LSSESSIONINFO
- LSTOUPERIODNAME
- METER
- METERHISTORY
- METERREAD
- METERVALUE
- MV90STATUSCODEMAP
- OPERATINGCOMPANY
- OVERRIDE
- PHYSICALRECORDER
- PLANNINGAREA
- PREMISE
- RATECODE
- RATEFORM
- RATEFORMVERSION
- RATEFORMVERTEXT
- REBILLREASON
- RECORDER
- REGION
- REPORTSETTINGS
- REVENUECODE
- RECORDERHISTORY
- REPORT
- REPORTLIST
- REVENUE
- REVENUEADEQUACY
- REVENUESUMMARY
- REVFORECAST
- REVFORECASTITEM
- SEASONDATE
- SEASONPERIOD
- SEASONSCHEDULE
- SERVICE

- SERVICEPLAN
- SERVICETYPE
- SIC
- SUBSTATION
- TIMEZONE
- TOUSCHEDULE
- TOUPERIOD
- TRANSFORMERLOC
- TRANSFORMER
- UOM
- UOMRATEQUANTITY
- USDAY
- USDAYLIST
- VERSION
- VERSIONINGSTATUS

Meta-Data Tables

- CATEGORYMETADATA
- COLUMNMETADATA
- DOMAINMETADATA
- KEYCOLUMNMETADATA
- REFERENCEMETADATA
- TABLECATEGORYMETADATA
- TABLEMETADATA
- TYPEMETADATA

Security Tables

- LSDATASOURCE
- LSGROUP
- LSGROUPPROFILE
- LSGROUPTOKEN
- LSPROFILE
- LSPROFILETOKEN
- LSSESSION
- LSUSER
- LSUSERACTIVITY

Report Framework Tables

- LSRFBUSINESSUNIT
- LSRFINTDHEADER
- LSRFINTDVALUES

- LSRFRPTCATEGORY
- LSRFRPTINSTANCE
- LSRFRPTTEMPLATE
- LSRFRPTTEMPLATEPRODUCT
- LSRFRPTUNIT
- LSRFRPTYPE

Messaging Tables

- BUSINESSCALENDAR
- BUSINESSDAY
- MESSAGEQUEUE
- MESSAGE TYPE
- MESSAGE TYPE QUEUE
- SCHEDULEDMESSAGE

Work Queues Tables

- LSPROCESS
- LSWQAPPRLEVEL
- LSWQAPPRPROC
- LSWQAPPRSTEP
- LSWQCLOSEDACTION
- LSWQCLOSEDITEM
- LSWQCUSTPARAM
- LSWQHINT
- LSWQOPENACTION
- LSWQOPENITEM
- LSWQQUEUE
- LSWQTYPE
- LSWQTYPEHINT
- LSWQTYPEPARAM

Interval Data Manager Tables

- LSCEDITTRAILS
- LSCHANNELCUTDATAA
- LSCHANNELCUTHEADERA
- LSIECDWSET
- LSIECEDITWSET
- LSIECHWSET
- LSIECVMSGWSET

Adapter Tables

- BAGFVERSION
- BAGGLOBALFUNCTION
- BARDLVERSION
- BARULEDESCLANG
- BARULERDL
- BATYPE
- COMOBJECT
- COMOBJTYPE
- HUBEXCEPTION
- HUBINBOUND
- HUBINBOUNDEXCEPTION
- HUBMAP
- HUBMAPVER
- HUBQUEUE
- HUBROWLOCK
- HUBRULE
- HUBRULETYPE
- HUBSERVER
- HUBSERVERSERVICE
- HUBSERVICE
- HUBSERVICETYPE
- HUBSEVERITY
- HUBSYSPROPS
- HUBSYSTEM
- ICEPAYLOAD
- ICEPAYLOADEXT
- ICEPAYLOADTYPE
- ICESTATUS
- JMSSERVER
- XMLMAPSTORAGE

Service Point Tables

- LSACCOUNTREL
- LSACCOUNTRELTYPE
- LSADDRESS
- LSADDRESSFORMAT
- LSCONTACT
- LSCONTACTADDRESS

- LSCONTACTGROUP
- LSCONTACTGROUPITEM
- LSCONTACTPURPOSE
- LSCONTACTMETHODTYPE
- LSCONTACTMETHOD
- LSMARKET
- LSMARKETATTR
- LSMARKETATTRTYPE
- LSMARKETPARTICIPANT
- LSMARKETPARTREL
- LSMARKETPARTRELTYPE
- LSMARKETPARTTYPE
- LSMDBDVALUESP
- LSORGANIZATION
- LSORGCONTACT
- LSORGCONTACTPURPOSE
- LSPARTICIPANTTYPE
- LSPREMISE
- LSPREMISECONTACT
- LSPREMISECONTACTPURP
- LSSERVICEPOINT
- LSSERVICETYPE
- LSSRVCPTACCT
- LSSRVCPTCONTACT
- LSSRVCPTINVDDETAIL
- LSSRVCPTINVOICE
- LSSRVCPTCONTACTPURP
- LSSRVCPTMARKETATTR
- LSSRVCPTMARKETPART

Optional Schemas

After the creation of the base schema you can add the following schema objects to the Oracle Utilities Data Repository:

- **Security Schema**

Security Schema

The Security schema includes tables that store records used by the security functionality of the Customer Choice Suite. See **Chapter 12: Energy Information Platform Security** for more information. This schema is automatically included with the base schema, but can also be installed as a stand-alone schema. The “-security” switch is included in the buildora.cmd command line to support this option.

Note: If the -security switch is present in command line and <owner name> is not PWRLINE or specified by <owner name>, then the default user PWRLINE will be ignored and the default security user LSSEC will own this schema (security database objects only). The “-audit” switch has no effect if the “-security” switch is present in the command line.

Note: When installing the Security schema as a stand-alone schema, be sure to specify the correct data source and qualifier containing the Security schema in the LSSECURE.CFG.XML file instead of the data source that contains the base schema. See **LSSECURE.CFG.XML** on page 2-42 in the *Oracle Utilities Energy Information Platform Configuration Guide* for more information.

Updating the LSGlobal Table

The LSGlobal table holds the visible names of tables, references, and data types in xml format, and is required for international support in Oracle Utilities applications.


How to add/update LSGlobal table:

1. Locate the addLSG.wsf script (included with your Oracle Utilities installation) located in the **C:\LODESTAR\DB\Base** directory created when you installed the Oracle Utilities application software.

Note: Windows script host version 5.6 or above is required to run this script.

2. Double click the script.

The addLSG dialog opens.




3. Enter Data Source Name, User ID and Password for the appropriate database schema in the following format:

DSN=<database>;UID=<owner name>;PWD=<owner password>;

Parameter	Description
<database>	The name given to the instance as specified in the TNSNAMES.ORA file. This parameter is optional and if not specified, the script will connect to the default Oracle database.
<owner name>	The name of the user which will own the database objects. This parameter is optional. If not specified, the default user PWRLINE will own database objects.
<owner password>	The chosen password for the PWRLINE schema owner.

4. Click **OK**.

The addLSG dialog prompts you to specify whether you want to create and load the LSGlobal XML, or just create it.



5. Enter 1 to create and load XML file into the database, or 0 to just create XML file.
 - If you entered 1, to load XML file into database, you will see a dialog displaying “updating LSGlobal”. Click **OK**.
 - If you entered 0 the dialog will **Done**.

Maintaining the LSGlobal Table

You **must** update the LSGlobal table whenever meta-data changes are made to the database.

Multiple Language Support

Updating the LSGlobal table only creates English labels. Updating the LSGlobal table for other languages must be performed as a separate manual process.

First, the English xml file has to be generated using the addLSG.wsf script. Then the xml file is edited for local language support and loaded to the LSGlobal table. Any meta-data changes after this point must be added as a separate xml record in the LSGlobal table. Oracle recommends the use of a source control application to track files added to the LSGlobal table.

Chapter 4

Installing the Oracle Utilities Application Software

This chapter describes installing the Oracle Utilities application software on an application server, client workstation machines, and web servers, and includes:

- **Installing Oracle Utilities Energy Information Platform Software**
- **Configuring Oracle Utilities Energy Information Platform Software**
- **Upgrading Your Software**

Note

The installation of Oracle Utilities Billing Component and the Oracle Utilities Receivables Component used here is for purposes of example only. The specific products that appear on your installation screens may differ from those shown here.

Before you Begin

Before you install your Oracle Utilities software, be sure that the following steps have been taken:

- The Oracle Utilities Data Repository schema has been installed on the database server. Make a note of the following information:
 - Data Source Name (DSN) for the database
 - A valid User ID and Password for the database
 - A valid Qualifier for the database
 - The Oracle database service name (if using Oracle)
 - The IP address or Host Name of the database server (if using MS SQL Server)

You will need this information when configuring your software to connect to the database.

- RDBMS software has been installed on the application server and client workstation(s) where you plan to install the software,
- A database connection has been set up between the database server and the application server and client workstation(s).
- Verify the ODBC / ODP driver installed on the web server is supported for the version of the software being installed. See **Oracle Data Provider (ODP) Information** on page 2-11 and **ODBC Driver Information** on page 2-11 for more information about supported drivers.

See **Chapter 2: Setting Up the Network Environment** and **Chapter 3: Oracle Utilities Data Repository Schema Creation** for more information about performing the above steps.

Important Notes

The following are suggested practices for successful installation:

- **DO NOT use Terminal Services to install software:** Use of Terminal Services to install software is NOT supported (by Microsoft or Oracle Utilities). Installing Oracle Utilities software using Terminal Services will result in errors. If remote installation is required, Remote Desktop Connection can be used, under the following conditions:
 - The server/workstation where the software is to be installed is running Windows 2003.
 - The Remote Desktop client machine be running either Windows 2003, and must have the latest version of the Remote Desktop Connection client software installed.
 - The client Remote Desktop Connection application must be launched with the “/console” parameter on the command line.
- **Install directly on the server, with Full Administrative Rights:** When installing web software, ALWAYS install directly on the web server, with Full Administrative Rights, not from another computer using console services. Doing otherwise can result in errors.
- **Use Default IIS Settings (no Security):** When installing web software, make sure that IIS is set to default security settings (i.e. NO security). Changing default IIS security settings may result in errors. If IIS security must be applied, apply any security settings AFTER the Oracle Utilities web software has been installed, configured, and tested.
- **DO NOT use Oracle names for user authentication:** Oracle does not support Oracle names with IIS. Use local TNS names only.
- Stop Internet Information Services (IIS) prior to installing Oracle Utilities web-enabled applications.
- If using Crystal Reports, the Crystal Reports software should be installed **before** the Energy Information Platform software.

Installing Oracle Utilities Energy Information Platform Software

The following section details the steps involved in installing Oracle Utilities Energy Information Platform application software on application servers, client workstations, or web servers, including:

- **Install the Oracle Utilities Application Software**
- **Install Oracle Utilities Language Packs (Optional)**

Install the Oracle Utilities Application Software

To install the Oracle Utilities application software, use the following procedure:

1. Navigate to the Install folder created from the Energy Information Platform installation package (1.6.1.xx.0.EIP.zip). This folder contains the following files:

- Oracle Utilities EIP 1.6.1.xx.0.msi
- setup.exe

Note: If you wish to install other Oracle Utilities applications in conjunction with the Energy Information Platform, expand the ZIP files for the applications you wish to install and move the corresponding MSI files into the same directory as the Energy Information Platform files. For example, if installing Oracle Utilities Billing Component along with the Energy Information Platform, expand the "1.6.1.xx.00.BC.zip" file and move the "Oracle Utilities BC 1.6.1.xx.0.msi" file in to the same directory as the Energy Information Platform installation files.

Note: Stop Internet Information Services (IIS) prior to installing Oracle Utilities web-enabled applications.

2. Double-click the setup.exe file.

A dialog opens asking you to confirm the products you wish to install. Click **Yes** to continue with the installation. Click **No** to cancel the installation.

3. When the Welcome screen appears, click **Next**.
4. The **System Utilities Update Warning** screen appears. This version of Oracle Utilities software requires version 2.8 of Microsoft Data Access Components (MDAC).

To install the update of MDAC, select **Yes, I want to install Microsoft Data Access Components (MDAC) v2.8** and click **Next**. To return to the previous screen, click **Back**. To cancel the installation, select **No, I do not want to install Microsoft Data Access Components (MDAC) v2.8** and click **Next**, or click **Cancel**.

Note: The **System Utilities Update Warning** screen only appears if MDAC 2.8 is not installed on the application server. If MDAC 2.7 is installed, the setup skips this screen.

5. The **Customer Information** screen appears. This screen allows you to enter your user name and organization. You also specify whether the software can be used by all users, or just the user entered.

The user name and organization will be populated automatically. Select the appropriate users under **Install this application for:** or select **Anyone who uses this computer** (recommended) and click **Next**. To go back to the previous screen, click **Back**. To cancel the installation, click **Cancel**.

6. The **Destination Folder** screen appears. This screen allows you to specify where the software is installed on the machine.

To install the software in the default directory (C:\LODESTAR), click **Next**. To change the destination folder for the installation, click **Change**. The **Change Current Destination Folder** screen appears.

Use the Browse button to navigate to the desired destination folder and click **OK**. This returns you to the **Destination Folder** screen. Click **Next** to continue the installation. To go back to the previous screen, click **Back**. To cancel the installation, click **Cancel**.

Select the type of installation you wish to perform. Available options include:

- **Web Server:** All features will be installed, including web components
- **Configuration Client or Application Server:** All features except web components will be installed.

7. The **Ready to Install the Program** screen appears.

To install continue with the installation, click **Install**. To go back to the previous screen, click **Back**. To cancel the installation, click **Cancel**.

8. The **Setup Status** screen will appear.

9. When the installation is complete, the **Installation Completed** screen will appear.

Click **Finish**.

10. After the installation is complete, you must restart your machine.

Directory Structure and Contents

The installation installs the files in the following directory:

C:\LODESTAR\

Once installed, the Oracle Utilities application directory contains the a number of subdirectories which contain the following files:

- **BIN:** Contains all files the Oracle Utilities application software needs to run, including executables and .DLLs.
- **BIP:** Contains report templates and other files used by Oracle Business Intelligence Publisher.
- **BPEL:** Contains files (jar files, XML files, and other files) used by BPEL web services used by Oracle Utilities Meter Data Management.

Note: This directory is only installed if Oracle Utilities Meter Data Management was installed.

- **CFG:** Contains configuration files. When installed, this directory is empty, but sample configuration files can be found in the C:\LODESTAR\CFG\Examples\CFG directory.
- **FMEReports:** This directory contains reports created through the Oracle Utilities Receivables Component Reports feature. See **Chapter 10: Reports** in the *Oracle Utilities Billing Component Installation and Configuration Guide, Volume II* for more information.

Note: This directory is only installed if Oracle Utilities Billing Component was installed.

- **LOG:** Default location for all logging and error reports generated by the Logging Framework.
- **LTMH:** Contains files (executables, batch files, and .DLLs) used by the Oracle Utilities Adapter.
- **RCDATA:** Contains rate schedule and query files created by users.
- **USER:** Contains various reports generated by the user.

- **WEB:** This directory contains the directories and files that comprise the Oracle Utilities Energy Information Platform web user interface and other web-based applications.

Install Oracle Utilities Language Packs (Optional)

This section describes the installation of language packs for localized versions of Oracle Utilities applications. Language packs must be downloaded separately.

Pre-Requisites

Before installing a language pack, please make sure the following pre-requisite items are fulfilled.

1. Make sure all Oracle Utilities products have been installed on the appropriate machines (application servers, web servers, and client workstations).
2. Make sure an ODBC connection has been setup correctly and can access the database.
3. Make sure the user has administration (read and write) permission to access the Oracle Utilities installation file folders. This is typically "C:\lodestar."
4. Set the default script host to CScript by calling CScript //H:CScript.
5. Extract all files from the language pack zip file to a local (and accessible) folder.

Installation

The InstallLangPack script is used to install the language pack. This script is run from a command prompt. To install the language pack, open a command prompt from the folder where language pack files have been extracted and run the script.

The syntax for this script is as follows:

InstallLangpack <dsn> <own> <opw> <LangCode> [<OUAppPath>]

where:

Parameter	Description
<dsn>	is the DSN for the Oracle Utilities Data Repository
<own>	is the user ID for the database connection
<opw>	is the password for the supplied user ID
<LangCode>	is the Language Code. FRA - French, RUS - Russian, ITA - Italy, ARA - Arabic, etc.
<OUAppPath>	<i>Optional.</i> Oracle Utilities application root folder. The default is "C:\LODESTAR". If you installed the software in a different folder or drive, please specify full path.

Example: Install the Russian language pack, connecting to a data source name called "local."

```
InstallLangPack local tr105 password RUS
```

Configuring Oracle Utilities Energy Information Platform Software

After installing the Oracle Utilities software, the software must be configured to run properly. This section describes the steps required for basic configuration of the Oracle Utilities Energy Information Platform software, including:

- **Configuring an Application Server**
- **Configuring a Client Workstation**
- **Configuring a Web Server**

Refer to the *Oracle Utilities Energy Information Platform Configuration Guide* for more information about configuring the Oracle Utilities software.

Configuring an Application Server

After installing Oracle Utilities software on an application server, perform the following steps, as needed.

Set Up Configuration Files on the Server

Oracle Utilities application servers use the following configuration files.

LODESTAR.CFG

The LODESTAR.CFG file is a text file used to customize the working environment of the Oracle Utilities application software. See **LODESTAR.CFG** on page 2-2 for more information about setting up this file. A sample of this file can be found in the

C:\LODESTAR\CFG\Examples\CFG directory on each of the client workstations.

When configuring the software for use in a shared client-server configuration, copy the client CFG file created when you installed the software on the application server to the LODESTAR\CFG directory of each of the client machines.

LTMH.CFG.XML (optional)

The LTMH.CFG.XML file is a text file used to specify the database connection used by the Oracle Utilities Adapter and Oracle Utilities Transaction Management. This file is required if the server will be used to run the Adapter or Oracle Utilities Transaction Management. See

LTMH.CFG.XML on page 2-46 of the *Oracle Utilities Energy Information Platform Installation and Configuration Guide* for more information about setting up this file.

LSRELAY.CFG.XML (optional)

The LSRELAY.CFG.XML file identifies the machine running an SMTP service used to send email messages from the Oracle Utilities Energy Information Platform. This file is required only if the email functions are used. The LSRELAY.CFG.XML file must be installed in the

C:\LODESTAR\CFG directory on each client workstation machine intended to execute the EMAILCLIENT Rules Language function (see **EMAILCLIENT Function** on page 13-111 in the *Oracle Utilities Rules Language Reference Guide* for more information). See **LSRELAY.CFG.XML** on page 2-34 for more information about setting up this file. A sample of this file can be found in the **C:\LODESTAR\CFG\Examples\CFG** directory on the web server.

LSREPORTMONITOR.CFG.XML (optional)

The LSREPORTMONITOR.CFG.XML file specifies where report data is stored and how reports are processed through the web-enabled Energy Information Platform and related products. The LSREPORTMONITOR.CFG.XML must be installed in the

C:\LODESTAR\CFG directory on all application and web servers. See **LSREPORTMONITOR.CFG.XML** on page 2-35 for more information about setting up this file. A sample of this file can be found in the **C:\LODESTAR\CFG\Examples\CFG** directory on the web server.

Example:

```

<LSREPORTMONITOR>
  <DATASOURCE>
    <NAME>DatabaseName</NAME>
    <CONNECTSTRING>Data Source=TS92;User
ID=ls470bx;Password=password;LSProvider=ODP</CONNECTSTRING>
    <QUALIFIER>DatabaseQualifier</QUALIFIER>
  </DATASOURCE>
  <PROCESS_POOL_SIZE>5</PROCESS_POOL_SIZE>
  <LOOP_TIMEOUT>5000</LOOP_TIMEOUT>
  <REPORT_TYPES>
    <REPORT_TYPE NAME="PLBX" PATH="C:\LODESTAR\BIN\lsreport.exe"/>
    <REPORT_TYPE NAME="Crystal" PATH="C:\LODESTAR\BIN\crgenreport.exe"/>
    <REPORT_TYPE NAME="LSIMPORT" PATH="C:\LODESTAR\BIN\lsimport.exe"/>
  </REPORT_TYPES>
</LSREPORTMONITOR>

```

Note: If an application server and web server are installed on different machines, the LSREPORTMONITOR.CFG.XML file must be installed in the C:\LODESTAR\CFG directory on both servers.

Sharing the LODESTAR Directory (optional)

Share portions of the LODESTAR directory with the client machine(s) that will use the Oracle Utilities software.

- To share the LODESTAR directory with all intended users of the Oracle Utilities software (i.e. client machines), set the shared access to Full Control.
- Modify the Share Name of the LODESTAR\RCDATA directory with an extension of this directory matching the ODBC data source name, for example RCDATA.TEST2000.

Note: This step is applicable only when configuring the software for use in a shared client-server configuration. These steps are NOT required when using web-based products.

Modify the LODESTAR.CFG File (optional)

When running Oracle Utilities software in a server/client configuration there are two distinct.CFG files used: the Server CFG file and the Client CFG file. For more information concerning modification of the LODESTAR.CFG file and other configuration files, see **Chapter Six: Configuration Files**.

Note: While this and other manuals refer to this file as the 'LODESTAR.CFG' file (the default name of the configuration file), the actual name of the file can be changed to match the name of the specific ODBC data source that will be shared between the server and client(s).

Note: This step is applicable only when configuring the software for use in a shared client-server configuration. These steps are NOT required when using web-based products.

Server CFG File

Copy the LODESTAR.CFG file from the C:\LODESTAR\Cfg\examples\Cfg directory to the C:\LODESTAR\Cfg directory, and edit it to add the following lines:

```
RCDATADIR=<DRIVE LETTER>:\LODESTAR\RCDATA.TEST2000
```

This configuration file is used by the server only.

Client CFG File

Create a copy of LODESTAR.CFG and modify the line RCDATADIR line as follows:

```
RCDATADIR=\\<MACHINE_NAME>\<RESOURCE>\Lodestar\RCDATA.TEST2000
```

Note: MACHINE_NAME is the name of the server where the LODESTAR.CFG file is located.

This file is used by all client machines.

Create a CISFORMT.TXT File (optional)

The next (optional) step is to create a file named CISFORMT.TXT file in the C:\LODESTAR\CFG directory on the application server. This text file specifies the output format of transaction records created by Oracle Utilities Billing Component and other Oracle Utilities applications. See **Chapter 9: Creating a CIS Transaction Record Output File** for more information about setting up this file.

Install Interval Database Software (optional)

The last (and optional) step in setting up the Oracle Utilities software is to install Interval Database software on the interval database server. The currently supported version of Interval Database software is Pervasive.SQL 8.0. Refer to the Pervasive.SQL installation documentation when installing this software.

Note: When using Pervasive.SQL, interval database files **must** reside on the interval database server.

Specify the Time Zone for the Application Server (optional)

Energy Information Platform application servers can be configured to specify the time zone used by the applications. This can be used in situations where users are located in a different time zone than the application and database servers.

When using this feature, dates/times calculated by the system will reflect the time zone specified for the database and application servers.

Note: This feature should **ONLY** be used when **ALL** users are located in the same time zone, and the application and database servers are located in a different time zone.

When using this feature, the time zone specified on the database server should also be specified on **ALL** application and web servers that will access the database server.

To specify the time zone used by the application server, you must define the following two environment variables as follows:

- **LSTZ_ENABLED=TRUE** (this variable enables the time zone feature on the server)
- **TZ=TIMEZONE** (this variable specifies the time zone for the server)

The syntax for the TZ environment variable is as follows:

TZ=<tzn>[+ | -]hh[:mm[:ss]]][<dzn>]

where:

- **<tzn>**: The three-letter time-zone name, such as PST. You must specify the correct offset from local time to UTC.
- **hh**: The difference in hours between UTC and local time. The plus sign (+) is optional for positive values.
- **mm**: Minutes. Separated from <hh> by a colon (:).
- **ss**: Seconds. Separated from <mm> by a colon (:).
- **<dzn>** = Three-letter daylight-saving-time zone such as PDT. If daylight saving time is never in effect in the locale, set TZ without a value for dzn. The application assumes the United States' rules for implementing the calculation of daylight saving time (DST).

Example:

TZ=CET-1CEST

The above example would set the time zone for Berlin, Germany.

Note: Environment variables are defined on the **Advanced** tab of the **System Properties** dialog.

Note: Log files display date and time information based on the server/operating system time zone, and will ignore the time specified for the Oracle user.

Configuring a Client Workstation

After installing Oracle Utilities software on a client workstation, perform the following steps to configure the software.

Set Up Configuration Files on the Workstation

Client workstations use the following configuration files.

LODESTAR.CFG

The LODESTAR.CFG file is a text file used to customize the working environment of the Oracle Utilities application software. See **LODESTAR.CFG** on page 2-2 for more information about setting up this file. A sample of this file can be found in the

C:\LODESTAR\CFG\Examples\CFG directory on each of the client workstations.

When configuring the software for use in a shared client-server configuration, copy the client CFG file created when you installed the software on the application server to the LODESTAR\CFG directory of each of the client machines.

LSRELAY.CFG.XML (optional)

The LSRELAY.CFG.XML file identifies the machine running an SMTP service used to send email messages from the Oracle Utilities Energy Information Platform. This file is required only if the email functions are used. The LSRELAY.CFG.XML file must be installed in the

C:\LODESTAR\CFG directory on each client workstation machine intended to execute the EMAILCLIENT Rules Language function (see **EMAILCLIENT Function** on page 13-111 in the *Oracle Utilities Rules Language Reference Guide* for more information). See **LSRELAY.CFG.XML** on page 2-34 for more information about setting up this file. A sample of this file can be found in the **C:\LODESTAR\CFG\Examples\CFG** directory on the web server.

Example:

```
<LSRELAY>
  <EMAIL>
    <EMAIL_SERVER>bxqasrv5</EMAIL_SERVER>
    <EMAIL_PORT>25</EMAIL_PORT>
    <EMAIL_AUTH>LOGIN</EMAIL_AUTH>
    <EMAIL_USER>Administrator</EMAIL_USER>
    <EMAIL_PASS>lodestar</EMAIL_PASS>
  </EMAIL>
</LSRELAY>
```

Set Up Shortcuts to the Oracle Utilities Applications

The next step is set up shortcuts to the Oracle Utilities applications. You'll want to set up a shortcut for each Oracle Utilities application you have installed on each machine. At a minimum this includes Data Manager, but may also include other Oracle Utilities products, such as Oracle Utilities Billing Component or Oracle Utilities Rate Management.

Note: These instructions assume you are setting up shortcuts on the desktop. If you wish, you can also modify the shortcuts on the Start Menu in the same manner.

You should set up shortcuts for each Oracle Utilities application on both the server and each client machine.

1. Create a folder on the desktop. Create a shortcut in the folder and select DATAMGR.EXE from the C:\LODESTAR\BIN directory. This is the shortcut to the Data Manager application.
2. Modify the command line to include the following parameters (see Oracle Utilities Application Command Line Parameters, below, for more information):
DATAMGR.EXE -l -cTEST2000 -fC:\LODESTAR\CFG\LODESTAR.CFG (or server-specific CFG file).

Note: The first parameter is lower case 'l', not numeric 1.

3. Double-click the Data Manager shortcut to open the program.
4. In Data Manager, select **File->Browse->Customer Database** to verify the database (in this case, TEST2000) is visible by the application.
5. Select **Tools->Options**, and use the **Interval Data Source** tab to select an interval data database file. Then select **File->Browse->Interval Data Database**, and expand the Recorder\Channel tree until you see a meter symbol. Click on any meter symbol to display the load shape for that cut of data.
6. Copy the Data Manager icon to create shortcuts for any other Oracle Utilities products you have installed, such as Oracle Utilities Billing Component or Oracle Utilities Rate Management. Then click the *right* mouse button and select **Properties**. Change DATAMGR.EXE to the name of the program you are installing (for example, PLBX.EXE for Oracle Utilities Billing Component, RATEXPRT.EXE for Oracle Utilities Rate Management).
7. Test each of these shortcuts by double-clicking on them to open the applications.

Oracle Utilities Application Command Line Parameters

Client/server applications use specific parameters to connect to the Oracle Utilities Data Repository and other options. These parameters do not apply to web-based applications.

Command line parameters include:

-c <connectstring> Specifies Data Source connection information, in one of the following formats:

For Oracle databases:

```
"Data Source=<data_source>;User
Id=<user_id>;Password=<password>;LSProvider=ODP;"
```

For Microsoft SQL databases:

```
"Data Source=<address>;Initial Catalog=<SQL_database>;User
Id=<user_id>;Password=<password>;MultipleActiveResultSets=True;LSProvider=MSSQL;"
```

where:

- <data_source> is the Oracle TNS Name for the data source, from the TNS_NAMES.ora file (typically located in the \\<machine>\oracle\network\admin directory)

- <user_id> is the user ID for the database connection
- <password> is the password for the supplied user ID.
- <address> is the IP address or Hostname of the MS SQL Server database server
- <SQL_database> is the name of the MS SQL Server database

-q <qualifier> Specifies the database table qualifier (default is PWRLINE). If you supply this parameter, it overrides the value specified for PLDBQUAL in the LODESTAR.CFG file. See **LODESTAR.CFG** on page 2-2 of the *Oracle Utilities Energy Information Platform Configuration Guide* for more information.

Note: All qualifiers used in the database must be uppercase.

-f <configfile> Configfile is the path and file name of a user-specific configuration file (TEST2000C.CFG in the above example). The default file is LODESTAR.CFG. See **LODESTAR.CFG** on page 2-2 for more information about this file.

-l Display the Log On dialog before connecting to the database. The Log On dialog is also displayed if there are PLDBQUALIFIERS in the LODESTAR.CFG file and the -q parameter is not used.

Note: This is the letter L preceded by a dash (not the number 1). If you do not supply this parameter, the logon dialog box does not appear.

-1 Run this application as a new instance, regardless of whether another one is running. Used to connect to two different databases at the same time.

Note: This is the numeral 1 preceded by a dash (not the letter L).

-lxxx Specifies the language displayed by the application. The parameter (xxx) is a three letter language abbreviation. Supported languages include DEU (German), ENU (American English), FRA (French), and ITA (Italian).

-g If you supply this parameter, the program starts in debug mode (debug parameter is ON). Default is debug parameter OFF. See **LODESTAR.CFG** on page 2-2 of the *Oracle Utilities Energy Information Platform Configuration Guide* for more information.

-nc If you supply this parameter, the program turns off catching fatal errors and displaying Windows error messages. See **LODESTAR.CFG** on page 2-2 of the *Oracle Utilities Energy Information Platform Configuration Guide* for more information.

Example:

```
C:\LODESTAR\Bin\datamgr.exe -c "Data Source=TS92;User
ID=LS470BX;Password=password;LSProvider=ODP;" -q LS470BX -1
```

Note: Each user of Oracle Utilities applications should have a unique user ID. Oracle Utilities recommends that only one instance of each Oracle Utilities application run on a workstation at a time.

Using User-specified Configuration Files

Each Oracle Utilities application can be set to use other, user-specified configuration files. For instance, you might want to change some configuration settings from the original CFG file. To do this, edit the command line to refer to the specific application and/or configuration file you wish to use, such as:

For path and file name: C:\LODESTAR\BIN\xxx.EXE

Optional Parameters: -fC:\LODESTAR\CFG\MYOWN.CFG

If you do this, it's best to rename the file with a meaningful name (such as USERNAME.CFG) to help you keep track of each CFG file.

If a configuration file is not passed to the application software at startup, it will search for a file named **LODESTAR.CFG** in the **CFG** directory. See **Chapter Six: Configuration Files** for information about the use and customization of the configuration file.

Create a **CISFORMAT.TXT** File (optional)

The next (optional) step is to create a file named **CISFORMAT.TXT** file in the **C:\LODESTAR\CFG** directory on the workstation. This text file specifies the output format of transaction records created by Oracle Utilities Billing Component and other Oracle Utilities applications. See **Chapter 9: Creating a CIS Transaction Record Output File** for more information about setting up this file.

Install Interval Data Database software on the client

The last (and optional) step is to install Interval Database software on the client machine(s). The currently supported version of Interval Database software is Pervasive.SQL 8.0. Refer to the Pervasive.SQL installation documentation when installing this software.

Configuring a Web Server

After installing Oracle Utilities software on a web server, perform the following steps to configure the software.

Set Up Configuration Files on the Web Server

Oracle Utilities web applications use the following configuration files.

LODESTAR.CFG

The **LODESTAR.CFG** file is a text file used to customize the working environment of the Oracle Utilities application software. See **LODESTAR.CFG** on page 2-2 for more information about setting up this file. A sample of this file can be found in the **C:\LODESTAR\CFG\Examples\CFG** directory on the web server.

Note: This file **MUST** be named **LODESTAR.CFG** on the web server.

LSSECURE.CFG.XML

The **LSSECURE.CFG.XML** file specifies the data source used by the Security functionality and is required in order to run Oracle Utilities web-enabled applications. The **LSSECURE.CFG.XML** must be installed in the **C:\LODESTAR\CFG** directory. See **LSSECURE.CFG.XML** on page 2-42 for more information about setting up this file. A sample of this file can be found in the **C:\LODESTAR\CFG\Examples\CFG** directory on the web server.

Example:

```
<LSSECURE>
  <DATASOURCE>
    <NAME>DatabaseName</NAME>
    <CONNECTSTRING>Data Source=TS92;User
ID=ls470bx;Password=password;LSProvider=ODP</CONNECTSTRING>
    <QUALIFIER>DatabaseQualifier</QUALIFIER>
  </DATASOURCE>
  <EXPIRETIME>60</EXPIRETIME>
</LSSECURE>
```

Note: If an application server and web server are installed on different machines, the **LSSECURE.CFG.XML** file is installed in the **C:\LODESTAR\CFG** directory with the web Server components.

LSREPORTMONITOR.CFG.XML (optional)

The **LSREPORTMONITOR.CFG.XML** file specifies where report data is stored and how reports are processed through the web-enabled Energy Information Platform and related products. The **LSREPORTMONITOR.CFG.XML** must be installed in the

C:\LODESTAR\CFG directory on all application and web servers. See **LSREPORTMONITOR.CFG.XML** on page 2-35 for more information about setting up this file. A sample of this file can be found in the **C:\LODESTAR\CFG\Examples\CFG** directory on the web server.

Example:

```
<LSREPORTMONITOR>
  <DATASOURCE>
    <NAME>DatabaseName</NAME>
    <CONNECTSTRING>Data Source=TS92;User
ID=ls470bx;Password=password;LSProvider=ODP</CONNECTSTRING>
    <QUALIFIER>DatabaseQualifier</QUALIFIER>
  </DATASOURCE>
  <PROCESS_POOL_SIZE>5</PROCESS_POOL_SIZE>
  <LOOP_TIMEOUT>5000</LOOP_TIMEOUT>
  <REPORT_TYPES>
    <REPORT_TYPE NAME="PLBX" PATH="C:\LODESTAR\BIN\lsreport.exe"/>
    <REPORT_TYPE NAME="Crystal" PATH="C:\LODESTAR\BIN\crgenreport.exe"/>
    <REPORT_TYPE NAME="LSIMPORT" PATH="C:\LODESTAR\BIN\lsimport.exe"/>
  </REPORT_TYPES>
</LSREPORTMONITOR>
```

Note: If an application server and web server are installed on different machines, the LSREPORTMONITOR.CFG.XML file must be installed in the C:\LODESTAR\CFG directory on both servers.

LSLOGGER.CFG.XML (optional)

The LSLOGGER.CFG.XML file defines how log files are generated by Oracle Utilities applications. Each Oracle Utilities component can be configured to write messages to a specified log file or an Event Log. The LSLOGGER.CFG.XML must be installed in the **C:\LODESTAR\CFG** directory. See **LSLOGGER.CFG.XML** on page 2-27 for more information about setting up this file. A sample of this file can be found in the **C:\LODESTAR\CFG\Examples\CFG** directory on the web server.

Note: If an application server and web server are installed on different machines, the LSLOGGER.CFG.XML file is installed in the C:\LODESTAR\CFG directory on both machines.

LSSCHDLR.CFG.XML (optional)

The LSSCHDLR.CFG.XML file defines the data source(s) monitored by the Oracle Utilities Schedule Service (LSSCHDLR.exe). This service monitors the Scheduled Message (SCHEDULEDMESSAGE) table in each data source specified in this file. This file is required if the Oracle Utilities Schedule Service is used. The LSSCHDLR.CFG.XML must be installed in the **C:\LODESTAR\CFG** directory. See **LSSCHDLR.CFG.XML** on page 2-41 for more information about setting up this file. A sample of this file can be found in the **C:\LODESTAR\CFG\Examples\CFG** directory on the web server.

Example

```
<LSSCHDLR>
  <DATASOURCE>
    <NAME>DatabaseName</NAME>
    <CONNECTSTRING>Data Source=TS92;User
ID=ls470bx;Password=password;LSProvider=ODP</CONNECTSTRING>
    <QUALIFIER>DatabaseQualifier</QUALIFIER>
  </DATASOURCE>
  <LOOP_TIMEOUT>5000</LOOP_TIMEOUT>
</LSSCHDLR>
```

Note: If an application server and web server are installed on different machines, the LSSCHDLR.CFG.XML file is installed in the C:\LODESTAR\CFG directory on both machines.

LSRELAY.CFG.XML (optional)

The LSRELAY.CFG.XML file identifies the machine running an SMTP service used to send email messages from the Oracle Utilities Energy Information Platform. This file is required only if the email functions are used. The LSRELAY.CFG.XML file must be installed in the **C:\LODESTAR\CFG** directory on the web server. See **LSRELAY.CFG.XML** on page 2-34 for more information about setting up this file. A sample of this file can be found in the **C:\LODESTAR\CFG\Examples\CFG** directory on the web server.

Example:

```
<LSRELAY>
  <EMAIL>
    <EMAIL_SERVER>bxqasrv5</EMAIL_SERVER>
    <EMAIL_PORT>25</EMAIL_PORT>
    <EMAIL_AUTH>LOGIN</EMAIL_AUTH>
    <EMAIL_USER>Administrator</EMAIL_USER>
    <EMAIL_PASS>lodestar</EMAIL_PASS>
  </EMAIL>
</LSRELAY>
```

LTMH.CFG.XML (optional)

The LTMH.CFG file is a text file used to specify the database connection used by the Oracle Utilities Adapter and Oracle Utilities Transaction Management. This file is required if the server will be used to run the Adapter or Oracle Utilities Transaction Management. See **LTMH.CFG.XML** on page 2-46 of the *Oracle Utilities Energy Information Platform Installation and Configuration Guide* for more information about setting up this file.

LOCALES.CFG.XML

The LOCALES.CFG.XML file specifies the regional locales available to Oracle Utilities web-enabled applications. The LOCALES.CFG.XML file must be installed in the **C:\LODESTAR\Web\CCS** directory. A sample of this file can be found in the **C:\LODESTAR\CFG\Examples\CFG** directory on the web server. See **LOCALES.CFG.XML** on page 2-22 for more information about this file.

Note: If the Report Server and Web Server are installed on different machines, the LOCALES.CFG.XML file is installed in the C:\LODESTAR\Web\ccs directory with the Web Server components.

Set Administration Login Password

Before logging on to the Oracle Utilities application, the administrator password must be set using the LSsecureInit.exe command line program. This program must be run on the web/application server where the Oracle Utilities applications are installed. The syntax for this program is as follows:

```
LSsecureInit -d <set_pw>
```

where:

Parameter	Description
-d	<set_pw> prompts the user to set a password for administrator login (using the “admin” user ID) is to be set. The user is prompted to enter and re-enter the password.

Create a CISFORMT.TXT File (optional)

The next (optional) step is to create a file named CISFORMT.TXT file in the **C:\LODESTAR\CFG** directory on the web server. This text file specifies the output format of transaction records created by Oracle Utilities Billing Component and other Oracle Utilities applications. See **Chapter 9: Creating a CIS Transaction Record Output File** for more information about setting up this file.

Install Interval Data Database software on the server (Optional)

The last (and optional) step is to install Interval Database software on the web server. The currently supported version of Interval Database software is Pervasive.SQL 8.0. Refer to the Pervasive.SQL installation documentation when installing this software.

Specify the Time Zone for the Web Server (optional)

Energy Information Platform web servers can be configured to specify the time zone used by the applications. This can be used in situations where users are located in a different time zone than the web/application and database servers.

When using this feature, dates/times calculated by the system will reflect the time zone specified for the database and application servers.

Note: This feature should ONLY be used when ALL users are located in the same time zone, and the web/application and database servers are located in a different time zone.

When using this feature, the time zone specified on the database server should also be specified on **ALL** application and web servers that will access the database server.

To specify the time zone used by the web server, you must define the following two environment variables as follows:

- **LSTZ_ENABLED=TRUE** (this variable enables the time zone feature on the server)
- **TZ=TIMEZONE** (this variable specifies the time zone for the server)

The syntax for the TZ environment variable is as follows:

TZ=<tzn>[+ | -]hh[:mm[:ss]]][<dzn>]

where:

- **<tzn>**: The three-letter time-zone name, such as PST. You must specify the correct offset from local time to UTC.
- **hh**: The difference in hours between UTC and local time. The plus sign (+) is optional for positive values.
- **mm**: Minutes. Separated from <hh> by a colon (:).
- **ss**: Seconds. Separated from <mm> by a colon (:).
- **<dzn>** = Three-letter daylight-saving-time zone such as PDT. If daylight saving time is never in effect in the locale, set TZ without a value for dzn. The application assumes the United States' rules for implementing the calculation of daylight saving time (DST).

Example:

TZ=CET-1CEST

The above example would set the time zone for Berlin, Germany.

Note: Environment variables are defined on the **Advanced** tab of the **System Properties** dialog.

Note: Log files display date and time information based on the server/operating system time zone, and will ignore the time specified for the Oracle user.

Configuring an SMTP Email Server (Optional)

Use of the **EMAILCLIENT** Rules Language function and the **Send Email** function on the View Reports screen of the Oracle Utilities Energy Information Platform web user interface requires an SMTP (Simple Mail Transfer Protocol) server be set up and accessible by the machine executing the email function. This is either an application server or client workstation executing

the EMAILCLIENT Rules Language function, or a web server. See **Oracle Utilities Platform Components Specifications** on page 2-2 for hardware/software requirements for each type of machine.

The connection between the executing machine and the SMTP server is defined in the LSRELAY.CFG.XML configuration file, which must be properly configured and present in the C:\LODESTAR\CFG directory of the executing machine. See **LSRELAY.CFG.XML** on page 2-34 for more information about this file.

Installing the Microsoft IIS SMTP Service

The Microsoft IIS SMTP service is a component of Microsoft Internet Information Services (IIS), and is available with Windows 2003 Server. If you wish to use this service as your SMTP email server and this service is not installed on the web server (or client workstation) you must install it.

How to install the SMTP service:

1. Select **Start->Settings->Control Panel**.
2. Select **Add/Remove Programs**.
3. Select **Add/Remove Windows Components**.
The **Windows Components Wizard** dialog opens.
4. Check **Internet Information Services (IIS)** and click the **Details** button.
The **Internet Information Services (IIS)** dialog opens.
5. Check **SMTP Service** and click **OK**.
6. Click **Next** on the **Windows Components Wizard** dialog, and follow the instructions on the wizard to complete the installation.

Configuring the Microsoft IIS SMTP Service for Basic Authentication and Relaying

The next step in setting up the IIS SMTP email server is to configure the server for Basic Authentication and Relaying.

1. On the Desktop, right-click the **My Computer** icon and select **Manage**.
The **Computer Management** window opens.
2. In the Tree pane, expand **Services and Applications** and **Internet Information Services**.
3. Right-click **Default SMTP Virtual Service** and select **Properties**.
The **Default SMTP Virtual Server Properties** window opens. Select the **Access** tab.
4. Click the **Authentication** button.
The **Authentication** window opens.
5. Check the **Basic authentication** checkbox, and click **OK**.
6. Click the **Relay** button.
The **Relay Restrictions** window opens.
7. To specify a list of servers that can relay messages to the SMTP server, select **Only the list below** and add the web server to the Computers list (see step 9, below).
8. To allow any server except a specific set of servers to relay messages to the SMTP server, select **All except the list below** and add the servers you wish to exclude to the Computers list (see step 9, below).
9. To add a computer to the Computers list, click **Add**.
The **Computer** window opens.

To add a single computer, select **Single Computer** and enter the IP address of the computer to be added, or click **DNS Lookup** to select the computer by its machine name.

To add a group of computers, select **Group of Computers** and enter the subnet address and subnet mask for the group.

To add a domain, select **Domain** and enter the domain name.

Click **OK**. The specified computers will appear in the Computers list on the Relay Restrictions window.

10. To allow all computers that successfully authenticate to relay messages to the SMTP server, check the **Allow all computers that successfully authenticate to relay, regardless of the list above** checkbox.
11. Click **OK** to save your settings.
12. Click OK on the **Default SMTP Virtual Server Properties** window.

SMTP Error Messages

Possible error messages related to the security access to the SMTP server are described below.

MSGRELAY0002: Unable to connect to the mail server. 535 5.7.3 Authentication unsuccessful.

- **Cause of Error:** This error describes an attempt by the user to connect to the SMTP server using the LOGIN security mechanism, but without a valid user name and/or password.
- **Resolution:** Verify the user name and password in the LSRELAY.CFG.XML file, or create a new user and password to the server's user account list.

MSGRELAY0003L: Unable to send the email. 530 5.7.3 Client was not authenticated.

- **Cause of Error:** This error describes an attempt by the user to send a email, without using any authentication, on a SMTP server that requires this authentication before sending the email.
- **Resolution:** Provide a LOGIN authentication with a valid user name and password in the LSRELAY.CFG.XML file.

Note: If users encounter problems emailing from a specific email server, keep in mind that email servers can be configured to exclude users, domains or IP addresses from relaying email messages on the server.

Verifying the Installation

After the software has been installed and configured, you can verify the installation by following the procedures outlined below, including:

- **Verifying Security Access**
- **Verifying the Reporting Framework**
- **Verifying the Report Scheduler**

Verifying Security Access

Verifying security access involves testing that the Oracle Utilities web software can access security data (data sources, users, groups, etc.) in the Oracle Utilities Data Repository. To verify security access, use the following procedure:

1. Configure the LSSECURE.CFG.XML configuration file.

This file specifies the data source used by the Security functionality and is required in order to run Oracle Utilities web-enabled applications. The LSSECURE.CFG.XML must be installed in the **C:\LODESTAR\CFG** directory. See **LSSECURE.CFG.XML** on page 2-42 in the *Oracle Utilities Energy Information Platform Configuration Guide* for more information about setting up this file. A sample of this file can be found in the **C:\LODESTAR\CFG\Examples\CFG** directory on the web server.

2. Login to the Oracle Utilities Energy Information Platform.

Open Microsoft Internet Explorer and enter the following address in the Address field:

http://<MACHINE_NAME>/lodestar/ccs

where:

- <MACHINE_NAME> is the name of the web server where the Oracle Utilities web application server software is installed.

Enter the following credentials (case-sensitive):

User ID: admin

Password: lodestar

The Oracle Utilities Energy Information Platform welcome screen should open.

If the screen does not open, or if you see an error, verify the settings in the LSSECURE.CFG.XML file. See **Oracle Utilities Energy Information Platform Diagnostics** on page 14-6 in the *Oracle Utilities Energy Information Platform Configuration Guide* for additional information about troubleshooting issues related to logging into the Oracle Utilities web software.

3. On the Left Menu, select **Tools and Utilities>Security Admin**.

The Security Administration screen should open.

Do the following on the Security Administration screen:

- Create a Data Source record. See **Data Sources** on page 7-21 in the *Oracle Utilities Energy Information Platform User's Guide* for more information about Data Sources.
- Create a User record. See **Users** on page 7-37 in the *Oracle Utilities Energy Information Platform User's Guide* for more information about Users.
- Grant all feature privileges to the User you just created for the Data Source you just created. See **Applying Function-Level Security** on page 12-7 in the *Oracle Utilities Energy Information Platform Configuration Guide* for more information about granting feature privileges.

- b. Click the Logout icon to log out of the software.
3. Login to the Oracle Utilities Energy Information Platform using the new user you created.
All options on the Left Menu should be active and available.

Verifying the Reporting Framework

Verifying the reporting framework involves testing that reports can be run and viewed through the reporting framework.

Note: Verifying the reporting framework requires that the correct reporting software has been installed. See **Installing and Configuring Reporting Software** on page 2-18 for more information.

To verify the reporting framework, use the following procedure:

1. Configure the LSREPORTMONITOR.CFG.XML configuration file. This file specifies where report data is stored and how reports are processed through the web-enabled Customer Choice Suite. The LSREPORTMONITOR.CFG.XML must be installed in the **C:\LODESTAR\CFG** directory. See **LSREPORTMONITOR.CFG.XML** on page 2-35 in the *Oracle Utilities Energy Information Platform Configuration Guide* for more information about setting up this file. A sample of this file can be found in the **C:\LODESTAR\CFG\Examples\CFG** directory on the web server.

2. Login to the Oracle Utilities Energy Information Platform.

Open Microsoft Internet Explorer and enter the following address in the Address field:

http://<MACHINE_NAME>/lodestar/ccs

where:

- <MACHINE_NAME> is the name of the web server where the Oracle Utilities web application server software is installed.

Enter the user ID and Password for the user you created in **Verifying Security Access** on page 4-18.

The Oracle Utilities Energy Information Platform welcome screen should open.

3. Run the Work Queues Aging Report.
 - a. On the Left Menu, select **Work Queues>Run Reports**.

The Run Reports screen should open, displaying three reports:

- WQAging
- WQOpenByUser
- WQProductivity

- b. Click **WQAging**. The **Report “WQAging”** screen should open.

- b. Click **Run** (do not enter report parameters).

The report should open in Adobe Acrobat Reader.

If the report does not run, verify that the Report Monitor service is running. See **Energy Information Platform Report Monitor** on page 11-23 in the *Oracle Utilities Energy Information Platform Configuration Guide* for more information about the Report Monitor service.

Verifying the Report Scheduler

Verifying the report scheduler involves testing that reports can be scheduled for execution and recurrence. To verify the report scheduler, use the following procedure:

1. Configure the LSSCHDLR.CFG.XML configuration file. This file defines the data source(s) monitored by the Oracle Utilities Schedule Service (LSSCHDLR.exe). This service monitors the Scheduled Message (SCHEDULEDMESSAGE) table in each data source specified in this file. This file is required if the Oracle Utilities Schedule Service is used. The LSSCHDLR.CFG.XML must be installed in the **C:\LODESTAR\CFG** directory. See **LSSCHDLR.CFG.XML** on page 2-41 in the *Oracle Utilities Energy Information Platform Configuration Guide* for more information about setting up this file. A sample of this file can be found in the **C:\LODESTAR\CFG\Examples\CFG** directory on the web server.

2. Log in to the Oracle Utilities Energy Information Platform.

Open Microsoft Internet Explorer and enter the following address in the Address field:

http://<MACHINE_NAME>/lodestar/ccs

where:

- <MACHINE_NAME> is the name of the web server where the LODESTAR web application server software is installed.

Enter the user ID and Password for the user you created in **Verifying Security Access** on page 4-18.

The Oracle Utilities Energy Information Platform welcome screen should open.

3. Run/schedule the Work Queues Aging Report.

- a. On the Left Menu, select **Work Queues>Run Reports**.

The Run Reports screen should open, displaying three reports:

- WQAging
- WQOpenByUser
- WQProductivity

- b. Click **WQAging**. The **Report “WQAging”** screen should open.

- b. Click **Schedule Report** (do not enter report parameters).

The **Schedule Process: WQAging** screen should open.

- b. Enter the scheduled time for the report at 1 minute past the current time, displayed as Server Time on the Schedule Process screen.

- b. Click **Schedule**. The View Reports screen should open (the WQAging report you ran in **Verifying the Reporting Framework** on page 4-19 should be listed on the screen).

- b. Check the **Show Scheduled Reports** checkbox. The WQAging report you just scheduled should appear on the View Reports screen.

- b. Check the **Refresh Periodically** checkbox.

The report should run and open in Adobe Acrobat Reader.

If the report does not run, verify that the Report Monitor and Workflow Scheduler services are both running. See **Energy Information Platform Report Monitor** on page 11-23 and **Energy Information Platform Report Scheduler** on page 11-24 in the *Oracle Utilities Energy Information Platform Configuration Guide* for more information about these services.

Upgrading Your Software

As new versions of Oracle Utilities, RDBMS, and Btrieve/Pervasive.SQL software become available, you may want to upgrade to take full advantage of any new features or improved performance offered. This section explains some of the issues associated with upgrading.

Upgrading RDBMS and Interval Data Database Software

Before upgrading your RDBMS software, be sure to check with Oracle to ensure that your Oracle Utilities application software will work properly with the new version of your RDBMS. Later versions of these RDBMS are generally supported when proven stable.

Before upgrading your interval data database software, check with Oracle to ensure that your Oracle Utilities application software will function properly with the new version of Pervasive software.

Upgrading Oracle Utilities Software

Oracle releases software upgrades regularly. Customers are encouraged to upgrade to the newest versions of our software after proper testing in their specific environments.

The following are some key points to keep in mind when installing an upgrade of Oracle Utilities software:

- Install the new software in a Test Environment. **DO NOT INSTALL NEW SOFTWARE OVER YOUR EXISTING PRODUCTION SOFTWARE.** The Test Environment can be established on a separate server/clients network (the preferred approach), or in different directories on the same server/clients (for instance, C:\LODESTARTEST).
- Create duplicate versions of your Oracle Utilities Data Repository for use in the Test Environment, and rename them to clearly identify them as test versions of your data. This will allow you to test the new software on valid data without affecting your production data. Be sure to change the command lines on the new application shortcuts to point to the test versions of your data.

Index

Numerics

1 4-11

I

Installing

Customer Database schema 3-1

L

Log On

Defining whether dialog is displayed 4-11

O

Oracle

Customer Database schema creation 3-3

Oracle Utilities Data Repository 1-2

