
PeopleSoft HCM 9.2: Global Payroll for France

March 2013

PeopleSoft HCM 9.2: Global Payroll for France
CDSKU hcm92pbr0
Copyright © 1988-2013, Oracle and/or its affiliates. All rights reserved.

Trademark Notice

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

License Restrictions Warranty/Consequential Damages Disclaimer

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

Warranty Disclaimer

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

Restricted Rights Notice

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

Hazardous Applications Notice

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Third Party Content, Products, and Services Disclaimer

This software or hardware and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Alpha and Beta Draft Documentation Notice

If this document is in preproduction status:

This documentation is in preproduction status and is intended for demonstration and preliminary use only. It may not be specific to the hardware on which you are using the software. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to this documentation and will not be responsible for any loss, costs, or damages incurred due to the use of this documentation.

Contents

Preface.....	xvii
Understanding the PeopleSoft Online Help and PeopleBooks.....	xvii
PeopleSoft Hosted Documentation.....	xvii
Locally Installed Help.....	xvii
Downloadable PeopleBook PDF Files.....	xvii
Common Help Documentation.....	xvii
Field and Control Definitions.....	xviii
Typographical Conventions.....	xviii
ISO Country and Currency Codes.....	xix
Region and Industry Identifiers.....	xix
Access to Oracle Support.....	xx
Documentation Accessibility.....	xx
Using and Managing the PeopleSoft Online Help.....	xx
PeopleSoft HCM Related Links.....	xx
Contact Us.....	xxi
Follow Us.....	xxi
Chapter 1: Getting Started with Global Payroll for France.....	23
Global Payroll for France Overview.....	23
Global Payroll for France Business Processes.....	23
Global Payroll for France Integrations.....	24
Global Payroll for France Implementation.....	24
Chapter 2: Understanding Global Payroll for France.....	27
Global Payroll for France Business Processes.....	27
Delivered Elements for France.....	30
Delivered Element Creation.....	30
Element Ownership and Maintenance.....	30
Element Naming Convention for France.....	34
Archiving Data for Global Payroll for France.....	41
Additional Archiving Considerations.....	41
Viewing Delivered Elements for France.....	41
Chapter 3: Setting Up Country Data.....	43
Understanding Country Setup.....	43
Pay Process Flow.....	43
Variables and Categories.....	45
Rounding Rules.....	46
Understanding Contribution Rates and Limits.....	46
PeopleSoft-Delivered Contribution Rates and Ceilings.....	46
Contribution Calculations.....	46
Reviewing and Updating Contribution Rates and Limits.....	49
Pages Used to View and Update Rates, Limits, and Ceilings.....	49
Rates And Elements Page.....	49
Limits Page.....	50
Ceilings FRA Page.....	51
Reviewing Garnishment Brackets.....	53
Page Used to Update Salary Ceilings for Garnishments.....	53
Bracket FRA Page.....	53
Understanding Net Guarantee Processing.....	55

Managing the Net Guarantee.....	55
Adding Deductions to the Net Guarantee Calculation.....	58
Viewing the Delivered Net Guarantee Deduction.....	59
Understanding the Seniority Calculation.....	60
Seniority Effective at the Segment End Date.....	60
Seniority Prorated After a Period of Part-Time Work.....	61
Seniority Calculated at the Beginning of the Notice Period.....	61
Elements Used in Seniority Calculation.....	61
Understanding SMIC Control.....	64
Understanding Hours Calculations.....	65
Understanding Net-to-Pay Management.....	66
Understanding Trigger Setup for France.....	66
Generate Triggers PeopleCode for Dependent Beneficiary and Other French Records.....	66
Segmentation Triggers with Earning and Deduction Assignments.....	67
Offset Days for Retro Triggers.....	68
Chapter 4: Setting Up Absence Rules.....	71
Understanding Absence Setup.....	71
Understanding Absence Rules for Paid Vacation.....	72
Absence Elements for Paid Vacation.....	72
Absence Entitlement Rules for Paid Vacation.....	72
Understanding Absence Rules for Illness, Maternity, and Work Accidents.....	81
Absence Elements for Illness.....	82
Absence Elements for Maternity Leave.....	82
Absence Elements for Work Accidents.....	82
Modifying Absence Rules for Illness, Maternity, and Work Accidents.....	83
Understanding Rules for Other Absences.....	90
Absence Elements for Family Leave and Other Personal Leave.....	90
Absence Elements for Unpaid Absence.....	91
Absence Elements for Work Council, Union, and Staff Representative Absence.....	91
Modifying Absence Rules for Other Absences.....	91
Understanding User-Defined (TAKE CONFIG) Fields.....	98
Calculating Worked Days.....	99
Pages Used to Calculate Worked Days.....	99
Understanding the Build Worked Days by Week Process.....	99
Build Worked Days Page.....	100
Maintain Work Day Weights FRA Page.....	100
Assigning Absence Elements to Payees and Process Lists.....	101
Associating Absence Elements with Payees.....	101
Associating Absence Elements with Process Lists.....	102
Chapter 5: Defining URSSAF Contributions.....	105
Understanding URSSAF Contributions.....	105
Bases.....	105
Rates.....	107
Ceilings.....	107
Contribution Classes.....	107
Understanding URSSAF Deductions.....	108
Understanding URSSAF and Retroactive Processing.....	109
Understanding Fillon Reductions to URSSAF Contributions.....	109
Defining URSSAF Rates and Additional Parameters.....	110
Pages Used to Define URSSAF Rates and Additional Parameters.....	110
Understanding URSSAF Rates and Ceilings.....	111

URSSAF Rates Page.....	111
URSSAF Additional Setup Page.....	113
Defining Rates for Accidents at Work.....	114
Pages Used to Define Work Accident Rates.....	114
Understanding Work Accident Rates.....	115
Reporting URSSAF Data.....	117
Creating the TRC Annual Report (without Application Framework).....	118
Viewing the TRC Declaration Type.....	118
Creating a TRC Declaration Definition.....	118
Setting Up TRC Data Extraction.....	119
Generating the TRC Report File.....	119
Creating the TRC Annual Report (with Application Framework).....	119
Viewing the TRC Declaration Type.....	119
Creating a TRC Declaration Definition.....	120
Setting Up TRC Data Extraction.....	120
Generating the TRC Report File.....	120
Reviewing Delivered URSSAF Deductions.....	120
Chapter 6: Defining ASSEDIC Contributions.....	123
Understanding ASSEDIC Rates, Limits, and Ceilings.....	123
Understanding Funding Bases.....	123
Funding Bases A, B, and A+B.....	123
Contributions at Age 65.....	124
Contribution Exceptions.....	125
Understanding ASSEDIC and Retroactive Processing.....	125
Setting up Rates and Ceilings for ASSEDIC Contributions.....	125
Page Used to Set up Rates for ASSEDIC Contributions.....	125
Understanding ASSEDIC Rates and Ceilings.....	125
ASSEDIC Rates FRA Page.....	126
Creating the BDA Report.....	128
Viewing the BDA Declaration Type.....	128
Creating a BDA Declaration Definition.....	128
Setting up BDA Data Extraction.....	128
Generating the BDA Report File.....	129
Viewing Delivered ASSEDIC Deductions.....	129
Chapter 7: Defining ARRCO, AGIRC, and Contingency Fund Contributions.....	131
Understanding ARRCO, AGIRC, and Contingency Fund Contributions.....	131
ARRCO, AGIRC, and Contingency Fund Contributions.....	131
Rates, Limits, and Ceilings.....	132
Contribution Exception Limits.....	132
Tax and Limits.....	133
Viewing and Maintaining ARRCO and AGIRC Rates.....	134
Pages Used to View and Maintain ARRCO and AGIRC Rates.....	135
ARRCO Rates Page.....	135
AGIRC Rates Page.....	137
APEC Page.....	139
AGFF Rates Page.....	141
Viewing Delivered ARRCO and AGIRC Deductions.....	142
ARRCO Deductions.....	142
AGIRC Deductions.....	142
APEC Deductions.....	143
AGFF Deductions.....	144

Setting Up Contingency Fund Contributions.....	144
Understanding Contingency Fund Calculations.....	144
Setting Up Contingency Funds for Contribution Calculation.....	146
Viewing Delivered Contingency Fund Deductions.....	147
Contingency Fund Deductions.....	147
Chapter 8: Defining Levies.....	149
Understanding Levies.....	149
Steps to View and Adjust Ceilings and Rates for Levies.....	151
Establishing Levy Rates.....	152
Pages Used to Establish Levy Rates.....	152
General Rates 1 Page.....	153
General Rates 2 Page.....	154
Establishing Levy Rates on Salaries.....	156
Special VAT-Exempt Element Group.....	158
Reviewing Delivered Levy Deductions.....	158
Chapter 9: Setting Up DUCS Reporting.....	161
Understanding DUCS Reporting.....	161
Understanding Global Payroll Rules for DUCS.....	161
Setting Up DUCS Information Without Application Framework.....	162
Pages Used to Set Up DUCS Information.....	162
Understanding DUCS Setup.....	164
DUCS Types FRA Page.....	165
Identifier Code Page.....	166
Declaration Type Page.....	167
Contributions Page.....	168
Amounts Types Page.....	169
Pay Informations Page.....	170
DUCS Contributions FRA Page.....	171
Address Mapping FRA Page.....	173
Contact Definition Page.....	174
Address and Phone Page.....	176
DUCS Definitions FRA Page.....	177
DUCS Override Rates FRA page.....	179
Setting Up DUCS Information Using Application Framework.....	180
Pages Used to Set Up DUCS Information.....	180
Understanding DUCS Setup.....	182
DUCS Types FRA Page.....	182
Identifier Code Page.....	183
Declaration Type Page.....	184
Contributions Page.....	186
Amounts Types Page.....	186
Pay Informations Page.....	188
AF-DUCS Contributions FRA Page.....	188
Contact Definition Page.....	189
Address and Phonem Page.....	191
DUCS Definitions Page.....	192
Chapter 10: Setting Up DADS Reporting.....	195
Understanding DADS Reporting.....	195
Understanding Global Payroll Rules for DADS.....	195
Writable Arrays Used to Support DADS.....	195
Understanding DADS Data Structures.....	196

Setting Up DADS Extraction.....	196
Pages Used to Set Up DADS Extraction.....	197
DADS Data Types Page.....	199
DADS Situations FRA Page.....	200
Reporting Estabs FRA Page.....	201
DADS Sending References FRA Page.....	203
Chapter 11: Understanding Overtime Payments.....	207
Understanding Overtime Payments.....	207
Understanding Paid Overtime.....	207
Understanding Time Off in Lieu of Pay.....	208
Delivered Overtime Elements.....	209
Earnings.....	209
Other elements.....	211
Chapter 12: Understanding Allowances.....	215
Understanding Allowance Types.....	215
Understanding Allowance Calculation.....	216
Compensation in Lieu of Paid Holidays Not Taken.....	216
Severance Allowance.....	217
End of Fixed-Term Contract Allowance.....	218
Retirement Allowance.....	218
Transportation Allowances.....	219
Independent Transportation Allowance.....	220
Benefits in Kind.....	222
Meal Allowances.....	224
Meal Tickets.....	226
Understanding Allowance Brackets.....	227
IND BR FIN CONT (End of Contract Entitlements).....	228
IND BR DT SPEC (Contract Type Specific Entitlements).....	230
IND BR IND LIC (Severance Allowance Entitlements).....	232
IND BR DEP RET (Retirement Allowance Entitlements).....	234
IND BR C ORANGE (Paris Transportation Allowance).....	236
IND BR TIT REST (Meal Tickets).....	236
Understanding Allowance Earnings and Deductions.....	237
Chapter 13: Understanding AFB Rules.....	241
The AFB Process Section.....	241
AFB Compensation Elements.....	241
AFB Earning Elements.....	241
The AFB Thirteenth Payment.....	242
The AFB Diploma Premium.....	243
AFB Transport Allowances.....	243
Transport Allowance Amounts.....	243
Other Transport Benefits.....	244
AFB End of Contract Allowances.....	244
Severance Allowance Entitlement.....	244
Severance Allowance Calculation.....	245
Seniority and 2002.....	249
AFB Retirement Allowances.....	249
Retirement Allowance Entitlement.....	250
Retirement Allowance Calculation.....	250
Chapter 14: Understanding Specific Contracts.....	253
Understanding Specific Contracts.....	253

Professionalization Contracts.....	253
Overview of Professionalization Contract.....	253
Elements Used to Define Professionalization Contract Rules.....	254
Apprentices.....	256
Apprentice Contracts.....	256
Apprenticeship Period.....	257
URSSAF Contributions.....	257
ASSEDIC Contributions.....	258
Levies.....	258
ARRCO/AGIRC Contributions.....	258
Contingency Funds.....	258
Counting Employees.....	258
Trainees.....	259
Trainee Contracts.....	259
Earnings.....	259
Social Security Contributions.....	260
Trainee Examples.....	261
Work Initiative Contracts(Contrat Initiative Emploi).....	262
Work Initiative Contracts.....	262
CIE and Return-to-Work Contracts(Contrat de Retour à l'Emploi).....	262
Fixed and Unfixed Term Contracts.....	263
Contributions.....	263
Counting Employees.....	263
Fixed-Term Contracts.....	264
Fixed-Term Contracts.....	264
Fixed-Term Contracts for Students.....	264
Seasonal and Custom Contracts.....	265
Specific Categories of Payees.....	265
Payees Under 18.....	265
Assignees.....	265
Organization Managers or Officials.....	266
Doctors.....	266
Brackets for Specific Contracts.....	267
Brackets for Professionalization Contract Minimum Wage (SMIC) Controls.....	267
Bracket for Specific Contract Compensation Scale.....	268
Bracket for Specific Contract Contribution Bases.....	268
SIT FM Formulas.....	269
Chapter 15: Understanding Vacation Accruals.....	271
Accruals.....	271
Paid Vacation Accruals Calculations.....	271
Chapter 16: Understanding Integration with Learning Management Applications.....	273
Understanding Integration with Administer Training and Enterprise Learning Management.....	273
Integration Between the Administer Training Business Process and Global Payroll for France.....	273
Integration Between PeopleSoft Learning Management and Global Payroll for France.....	274
Processing DIF and Skills Development Training Hours.....	275
Understanding How Global Payroll for France Processes Training Hours.....	275
Calculating DIF and DIF in Advance Balances.....	276
Making Training Data Available for the 2483 Report.....	277
The FOR WA 2483 Writable Array.....	278
Chapter 17: Understanding Retroactive Processing.....	281

Standard Retro Setup In Global Payroll for France.....	281
Gross Salary Changes.....	281
Managing Gross Salary Changes in the Current Year.....	282
Gross Salary Calculation Steps and Elements.....	283
Controlling Retro Calculations.....	287
Variations on Standard Retro Processing.....	288
Gross Salary Changes with a Change of Establishment or Company.....	289
Ceiling Changes.....	290
Funding Base Exemption Changes.....	290
Changes in the Lump Sum Funding Base for Apprentices.....	290
Contribution Calculations for Finalized Years.....	290
Net Guarantee.....	291
Contribution Eligibility.....	291
Hiring and Departure.....	299
Isolated Amounts.....	301
Inactive Segments.....	302
Loans and Garnishments.....	302
Reporting and Retroactivity.....	303
Delivered Retro Triggers.....	305
Collective Changes to Contribution Calculation Elements.....	306
Chapter 18: Setting Up Termination Processing.....	307
Understanding The Termination Process.....	307
Termination Process Setup Steps.....	307
Segmentation and Retro Triggers for Termination Processing.....	309
Elements Used to Identify Payees For Data Extraction.....	311
ASSEDIC Report Generation for Transfers.....	312
Setting Up Terminations.....	314
Pages Used to Set Up Terminations.....	315
Extraction Setup Page.....	315
Assedic Reasons Page.....	316
Elements Mapping Codes FRA Page.....	318
Chapter 19: Administering Garnishments.....	319
Understanding Garnishments.....	319
Garnishment Types and Priorities.....	319
Attachable and Unattachable Earnings.....	319
Garnishments and Retroactive Processing.....	320
Prerequisite.....	320
Entering Garnishments.....	321
Page Used to Enter Garnishments.....	321
Assign Garnishments FRA page.....	321
Specifying Recipients for a Garnishment.....	324
Stopping, Removing, and Deleting Garnishments.....	324
Changing a Garnishment Balance.....	324
Setting Maximum Amounts for Garnishments.....	326
Generating a Garnishment Report.....	327
Chapter 20: Administering Loans and Advances.....	329
Understanding Loans and Advances.....	329
Understanding Reimbursement Terms.....	329
Reimbursement of Loans and Salary Advances (Avances).....	329
Reimbursement of Permanent Salary Advances.....	330
Reimbursement of Advances on Salary (Acomptes).....	330

Loan and Advance Processing Relative to Garnishment Processing.....	330
Understanding Loans and Retroactive Processing.....	330
Setting Up Loans and Advances.....	331
Pages Used to Set Up Loans and Advances.....	331
Understanding The Setup of Loans and Advances.....	331
Request Advances/Loans FRA Page.....	334
One Time (Positive Input) Page.....	338
Positive Input - Details Page.....	338
Generating a Loans Report.....	339
Viewing Delivered Loan and Advance Deductions.....	340
Chapter 21: Entering Absences.....	341
Understanding Absence Calculations.....	341
Understanding Absence Take Elements.....	342
Elements for Miscellaneous Absence.....	343
Elements for Work Accidents.....	345
Elements for Paid Vacation.....	351
Elements for Family Events.....	351
Elements for Illness Absence.....	354
Elements for Maternity Absence.....	358
Elements for Staff Representative Absence.....	361
Entering Absences.....	362
Pages Used to Enter Absences.....	363
Entering Absences Due to Illness.....	363
Entering Absences Due to Work Accidents.....	364
Entering Absences Due to a Relapse.....	364
Entering Absences for Pathological Leave.....	365
Entering Absences for Maternity and Adoption.....	365
Entering Absences That Occur During Public Holidays.....	366
Entering Absences for Anticipated Paid Vacation.....	366
Entering Absences That Require Manager Approval.....	366
Selecting the Half Day Box.....	367
Chapter 22: Setting Up and Generating Wage Certificates.....	369
Understanding the Wage Certificates Process.....	369
Common Elements Used to Set Up and Generate Wage Certificates.....	369
Updating Elements for Wage Certificates.....	370
Page Used to Update Elements for Wage Certificates.....	370
Element Mapping Codes FRA Page.....	371
Maintaining Absence Codes for Wage Certificates.....	371
Pages Used to Maintain Absence Codes for Wage Certificates.....	371
Understanding Absence Codes.....	372
Element Group Members Page.....	372
Define List Set Page.....	373
Element Group Attributes Page.....	374
Entering Absences.....	375
Retrieving Data for Wage Certificates.....	376
Pages Used to Retrieve Data for Wage Certificates.....	376
Extract Certificates Data FRA Page.....	376
Certification Page.....	378
Viewing and Updating Data for Illness and Maternity Certificates.....	379
Pages Used to View or Update Data for Illness and Maternity Certificates.....	380
Understanding the Illness and Maternity Certificates.....	380

Administrative Information Page.....	381
Right Study Page.....	382
Reference Salaries Page.....	384
Subrogation Page.....	387
Term Illness Page.....	388
Viewing and Updating Data for Work Accidents and Occupational Illness Certificates.....	390
Pages Used for Work Accidents and Occupational Illness Certificates.....	390
Admin Information Page.....	391
Frames A and B Page.....	392
Frames C and D Page.....	395
Subrogation and Certification Page.....	397
Printing Wage Certificates.....	399
Page Used to Generate Wage Certificates.....	400
Chapter 23: Working with Payslips.....	401
Understanding Payslip Layout.....	401
Setting up Payslips.....	403
Pages Used to Set up Payslips.....	403
Understanding Payslip Setup.....	403
Payslip/PayGroup Page.....	404
Payslip Sort keys Page.....	405
Payslip Lines Page.....	406
Payslip Totals Page.....	411
Adding Payslip Comments.....	412
Page Used to Add Payslip Comments.....	413
Messages FRA Page.....	413
Printing Payslips.....	415
Page Used to Print Payslips.....	415
Create/Print Payslips Page.....	415
Setting Up and Viewing Payslips Online.....	416
Pages Used to Set Up and View Payslips Online.....	416
Understanding the Online Payslip View.....	417
Common Elements Used in This Section.....	417
Admin Payslip/Results FRA Page.....	418
Summary Page.....	418
Body Page.....	419
Supporting Elements Page.....	420
Earnings Deductions Page.....	421
Accumulator Page.....	422
Absences Page.....	423
Positive Inputs Page.....	424
Chapter 24: Setting Up and Running the Banking Processes.....	427
Understanding Banking Setup and Processing for France.....	427
Understanding How to Set Up the Banking Process for France.....	427
Understanding How To Run the Banking Process for France.....	429
Running the Payment Preparation Process.....	431
Page Used to Run the Payment Preparation Process for France.....	431
Run Payment Prep Process FRA Page.....	431
Creating the EFT Payment File.....	431
Page Used to Create an EFT Payment File.....	432
Create EFT Payment File FRA Page.....	432
Creating Net Payment and Exceptions Reports.....	433

Page Used to Generate Net Payment and Exceptions Reports.....	433
Understanding Net Payment and Exceptions Reports.....	433
Net Payment Report FRA Page.....	434
Processing SEPA Payments for France.....	436
Setting Up SEPA Processing.....	436
Processing SEPA Payments.....	436
Sending SEPA Payments to PeopleSoft Financial Gateway.....	437
Chapter 25: Processing Terminations.....	439
Understanding Termination Processing.....	439
Prerequisites.....	442
Creating an Off-Cycle Group for Processing Terminated Payees.....	442
Pages Used to Create an Off-Cycle Group for Processing Terminated Payees.....	442
Termination Group Page.....	443
Terminated Employees page.....	444
Off-cycle Calendar Group Page.....	447
Calculating and Finalizing the Off-Cycle Termination Group.....	448
Page Used to Calculate and Finalize Off-Cycle Termination Groups.....	449
Extracting Data for Terminated Employees.....	449
Page Used to Extract Data for Terminated Employees.....	449
Understanding the Data Extraction Process.....	449
Prerequisites.....	450
Extract Termination Data FRA Page.....	451
Reviewing and Updating Retrieved Employee Data.....	452
Pages Used to Review and Update Retrieved Employee Data.....	453
ASSEDIC Certificate 1 Page.....	454
2 and 3 Page.....	456
4 Page.....	458
4 (end) Page.....	459
5 and 6 Page.....	461
7.1 Page.....	462
7.2 and 7.3 Page.....	463
7.3 Page.....	465
8 and 9 Page.....	467
Work Certificate Page.....	468
Last Payment Receipt Page.....	469
Certification Page.....	469
Printing Termination Certificates.....	470
Page Used to Run Termination Reports.....	471
Prerequisite.....	471
Termination Reports Page.....	471
Chapter 26: Managing Off-Cycle Payments.....	473
Understanding Off-Cycle Processing.....	473
Off-Cycle Processing.....	473
Types of Off-Cycle Transactions.....	473
Manual Payments.....	474
Reversals and Corrections.....	474
Unscheduled Payments.....	474
Advance Payments.....	475
Understanding Advance Payments.....	475
Chapter 27: Generating DUCS.....	477
Understanding DUCS Processing.....	477

Prerequisites.....	477
Producing DUCS Files and Reports Without Application Framework.....	477
Pages Used to Produce DUCS Files and Reports.....	478
Understanding DUCS Processing Without Application Framework.....	478
Create DUCS Data FRA Page.....	478
Update DUCS Data FRA Page.....	480
Create DUCS/TRC/DRA File FRA Page.....	481
Extracting DUCS Data Using Application Framework.....	482
Pages Used to Extract DUCS Data.....	482
Define Extraction Data Page.....	483
Parameters Page.....	484
Run Extraction FRA Page.....	484
Viewing and Updating Extracted DUCS Data Using Application Framework.....	487
Pages Used to View and Update DUCS Data.....	487
Understanding Viewing and Updating Extracted DUCS Data.....	487
Node/Attr Filter Page.....	488
Other Filters Page.....	488
Updating Data Page.....	489
Generating DUCS Files Using Application Framework.....	491
Page Used to Generate DUCS files.....	491
Create File FRA Page.....	491
Chapter 28: Counting Employees.....	493
Understanding Employee Counts.....	493
Viewing Headcounts by Company.....	494
Page Used to View Headcounts by Company.....	494
Update Company Headcount FRA Page.....	494
Adjusting DUCS Headcounts (without Application Framework).....	495
Page Used to Adjust DUCS Headcounts.....	495
Adjust DUCS Headcount FRA Page.....	495
Chapter 29: Generating DADS.....	497
Extracting DADS Data.....	497
Pages Used to Extract DADS Data.....	497
Define Extraction Data Page.....	497
Parameters page.....	498
Run Extraction FRA Page.....	499
Viewing and Updating Extracted DADS Data.....	502
Pages Used to View and Update DADS Data.....	502
Understanding Viewing and Updating Extracted DADS Data.....	502
Node/Attr Filter Page.....	503
Other Filters Page.....	503
Updating Data Page.....	504
Generating DADS Files.....	506
Page Used to Generate DADS files.....	506
Create File FRA Page.....	506
Appendix A: Global Payroll for France Reports.....	509
Global Payroll for France Reports: A to Z.....	509

Preface

Understanding the PeopleSoft Online Help and PeopleBooks

The PeopleSoft Online Help is a website that enables you to view all help content for PeopleSoft Applications and PeopleTools. The help provides standard navigation and full-text searching, as well as context-sensitive online help for PeopleSoft users.

PeopleSoft Hosted Documentation

You access the PeopleSoft Online Help on Oracle's PeopleSoft Hosted Documentation website, which enables you to access the full help website and context-sensitive help directly from an Oracle hosted server. The hosted documentation is updated on a regular schedule, ensuring that you have access to the most current documentation. This reduces the need to view separate documentation posts for application maintenance on My Oracle Support, because that documentation is now incorporated into the hosted website content. The Hosted Documentation website is available in English only.

Locally Installed Help

If your organization has firewall restrictions that prevent you from using the Hosted Documentation website, you can install the PeopleSoft Online Help locally. If you install the help locally, you have more control over which documents users can access and you can include links to your organization's custom documentation on help pages.

In addition, if you locally install the PeopleSoft Online Help, you can use any search engine for full-text searching. Your installation documentation includes instructions about how to set up Oracle Secure Enterprise Search for full-text searching.

See *PeopleTools 8.53 Installation* for your database platform, "Installing PeopleSoft Online Help." If you do not use Secure Enterprise Search, see the documentation for your chosen search engine.

Note: Before users can access the search engine on a locally installed help website, you must enable the Search portlet and link. Click the Help link on any page in the PeopleSoft Online Help for instructions.

Downloadable PeopleBook PDF Files

You can access downloadable PDF versions of the help content in the traditional PeopleBook format. The content in the PeopleBook PDFs is the same as the content in the PeopleSoft Online Help, but it has a different structure and it does not include the interactive navigation features that are available in the online help.

Common Help Documentation

Common help documentation contains information that applies to multiple applications. The two main types of common help are:

- Application Fundamentals

- Using PeopleSoft Applications

Most product lines provide a set of application fundamentals help topics that discuss essential information about the setup and design of your system. This information applies to many or all applications in the PeopleSoft product line. Whether you are implementing a single application, some combination of applications within the product line, or the entire product line, you should be familiar with the contents of the appropriate application fundamentals help. They provide the starting points for fundamental implementation tasks.

In addition, the *PeopleTools: PeopleSoft Applications User's Guide* introduces you to the various elements of the PeopleSoft Pure Internet Architecture. It also explains how to use the navigational hierarchy, components, and pages to perform basic functions as you navigate through the system. While your application or implementation may differ, the topics in this user's guide provide general information about using PeopleSoft Applications.

Field and Control Definitions

PeopleSoft documentation includes definitions for most fields and controls that appear on application pages. These definitions describe how to use a field or control, where populated values come from, the effects of selecting certain values, and so on. If a field or control is not defined, then it either requires no additional explanation or is documented in a common elements section earlier in the documentation. For example, the Date field rarely requires additional explanation and may not be defined in the documentation for some pages.

Typographical Conventions

The following table describes the typographical conventions that are used in the online help.

<i>Typographical Convention</i>	<i>Description</i>
Bold	Highlights PeopleCode function names, business function names, event names, system function names, method names, language constructs, and PeopleCode reserved words that must be included literally in the function call.
<i>Italics</i>	Highlights field values, emphasis, and PeopleSoft or other book-length publication titles. In PeopleCode syntax, italic items are placeholders for arguments that your program must supply. Italics also highlight references to words or letters, as in the following example: Enter the letter <i>O</i> .
Key+Key	Indicates a key combination action. For example, a plus sign (+) between keys means that you must hold down the first key while you press the second key. For Alt+W, hold down the Alt key while you press the W key.
Monospace font	Highlights a PeopleCode program or other code example.
... (ellipses)	Indicate that the preceding item or series can be repeated any number of times in PeopleCode syntax.

<i>Typographical Convention</i>	<i>Description</i>
{ } (curly braces)	Indicate a choice between two options in PeopleCode syntax. Options are separated by a pipe ().
[] (square brackets)	Indicate optional items in PeopleCode syntax.
& (ampersand)	When placed before a parameter in PeopleCode syntax, an ampersand indicates that the parameter is an already instantiated object. Ampersands also precede all PeopleCode variables.
⇒	This continuation character has been inserted at the end of a line of code that has been wrapped at the page margin. The code should be viewed or entered as a single, continuous line of code without the continuation character.

ISO Country and Currency Codes

PeopleSoft Online Help topics use International Organization for Standardization (ISO) country and currency codes to identify country-specific information and monetary amounts.

ISO country codes may appear as country identifiers, and ISO currency codes may appear as currency identifiers in your PeopleSoft documentation. Reference to an ISO country code in your documentation does not imply that your application includes every ISO country code. The following example is a country-specific heading: "(FRA) Hiring an Employee."

The PeopleSoft Currency Code table (CURRENCY_CD_TBL) contains sample currency code data. The Currency Code table is based on ISO Standard 4217, "Codes for the representation of currencies," and also relies on ISO country codes in the Country table (COUNTRY_TBL). The navigation to the pages where you maintain currency code and country information depends on which PeopleSoft applications you are using. To access the pages for maintaining the Currency Code and Country tables, consult the online help for your applications for more information.

Region and Industry Identifiers

Information that applies only to a specific region or industry is preceded by a standard identifier in parentheses. This identifier typically appears at the beginning of a section heading, but it may also appear at the beginning of a note or other text.

Example of a region-specific heading: "(Latin America) Setting Up Depreciation"

Region Identifiers

Regions are identified by the region name. The following region identifiers may appear in the PeopleSoft Online Help:

- Asia Pacific
- Europe
- Latin America

- North America

Industry Identifiers

Industries are identified by the industry name or by an abbreviation for that industry. The following industry identifiers may appear in the PeopleSoft Online Help:

- USF (U.S. Federal)
- E&G (Education and Government)

Access to Oracle Support

Oracle customers have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Using and Managing the PeopleSoft Online Help

Click the Help link in the universal navigation header of any page in the PeopleSoft Online Help to see information on the following topics:

- What's new in the PeopleSoft Online Help.
- PeopleSoft Online Help accessibility.
- Accessing, navigating, and searching the PeopleSoft Online Help.
- Managing a locally installed PeopleSoft Online Help website.

PeopleSoft HCM Related Links

[PeopleSoft Information Portal on Oracle.com](#)

[My Oracle Support](#)

[PeopleSoft Training from Oracle University](#)

[PeopleSoft Video Feature Overviews on YouTube](#)

[HCM Abbreviations](#)

Contact Us

Send us your suggestions Please include release numbers for the PeopleTools and applications that you are using.

Follow Us



Get the latest PeopleSoft updates on [Facebook](#).



Follow PeopleSoft on [Twitter@PeopleSoft_Info](#).

Chapter 1

Getting Started with Global Payroll for France

Global Payroll for France Overview

PeopleSoft Global Payroll for France delivers elements, rules, pages, processes, and reports that work with the PeopleSoft Global Payroll core application to form a complete payroll package for France.

Related Links

[Global Payroll for France Business Processes](#)

Global Payroll for France Business Processes

Global Payroll for France supports these business processes:

- Overtime.
- URSSAF contributions.
- ASSEDIC contributions.
- ARRCO and AGIRC contributions.
- Contingency Funds contributions.
- Allowances.
- Absence processing.
- Levies.
- Garnishments.
- Loans and advances.
- Net guarantee.
- Accruals.
- Specific contracts.
- Payslips.
- Banking.

- Termination processing.
- DUCS generation.
- DADS reporting.
- Wage certificates.
- Retroactive processing.
- DIF and training allocation calculation.

We discuss these business processes in the business process topics.

Global Payroll for France Integrations

PeopleSoft Global Payroll for France integrates with these applications through the core Global Payroll application:

- PeopleSoft Human Resources (HR).
- PeopleSoft Time and Labor.
- PeopleSoft General Ledger.

We discuss integration considerations in the core Global Payroll . Supplemental information about third-party application integrations is located on the PeopleSoft My Oracle Support website.

Related Links

"Understanding Payee Data (*PeopleSoft HCM 9.2: Global Payroll*)"

"Running a Payroll with Time and Labor Data (*PeopleSoft HCM 9.2: Global Payroll*)"

"Understanding the General Ledger Interface (*PeopleSoft HCM 9.2: Global Payroll*)"

Global Payroll for France Implementation

PeopleSoft Setup Manager enables you to generate a list of setup tasks for your organization based on the features that you are implementing. The setup tasks include the components that you must set up, listed in the order in which you must enter data into the component tables, and links to the corresponding documentation.

Global Payroll for France also provides component interfaces to help you load data from the existing system into Global Payroll for France tables. Use the Excel to Component Interface utility with the component interfaces to populate the tables.

Component	Component Interface	References
GPFR_DA_DATTYP	CI_GPFR_DA_DATTYP	See Setting Up DADS Extraction .
GPFR_DA_SIT	CI_GPFR_DA_SIT	See Setting Up DADS Extraction .

Component	Component Interface	References
GPFR_AF_UPG_SETUP	CI_GPFR_AF_APPL	See Setting Up DADS Extraction .
GPFR_AF_UPG_SETUP	CI_GPFR_AF_SQL_ENTITY	See Setting Up DADS Extraction .
GPFR_AF_UPG_SETUP	CI_GPFR_AF_MAPCODE	See Setting Up DADS Extraction .
GPFR_AF_UPG_SETUP	CI_GPFR_AF_DON	See Setting Up DADS Extraction .
GPFR_AF_UPG_SETUP	CI_GPFR_AF_NODE	See Setting Up DADS Extraction .
GPFR_AF_UPG_SETUP	CI_GPFR_AF_ATTR_DEFN	See Setting Up DADS Extraction .
GPFR_AF_UPG_SETUP	CI_GPFR_AF_ATTR_PARM	See Setting Up DADS Extraction .
GPFR_AF_UPG_SETUP	CI_GPFR_AF_NDSET_DTL	See Setting Up DADS Extraction .

Other Sources of Information

In the planning phase of your implementation, take advantage of all PeopleSoft sources of information, including the installation guides, table-loading sequences, data models, and business process maps.

See the product documentation for *PeopleTools: PeopleSoft Setup Manager* *PeopleTools: PeopleSoft Component Interfaces*

Related Links

"Understanding Application Diagnostics (*PeopleSoft HCM 9.2: Application Fundamentals*)"

Understanding Global Payroll for France

Global Payroll for France Business Processes

PeopleSoft Global Payroll for France supports the following business processes:

- Overtime.

PeopleSoft Global Payroll for France enables you to process overtime hours. The number of overtime hours is calculated outside of the payroll system and passed to PeopleSoft Global Payroll for France, which provides the functionality to calculate and pay the overtime. Specific elements are delivered to manage TEPA overtime hours.

- URSSAF Contributions.

PeopleSoft Global Payroll for France enables you to manage URSSAF contributions that are paid by both the payee and employer to cover retirement, sickness, workplace accidents, family benefits, widows' benefits, and FNAL. We deliver the rates for several URSSAF schemes (*régimes*), including the general scheme 100, Alsace-Moselle General Scheme 101, and other URSSAF schemes.

- ASSEDIC Contributions.

ASSEDIC (or GARP in Paris) contributions are paid to the state unemployment fund, *Pôle Emploi*, which finances unemployment insurance (*Régime d'Assurance Chomage* or RAC) and salary guarantees (*Fond National de Garantie des Salaires* or FNGS). PeopleSoft Global Payroll for France enables you to enter and maintain ASSEDIC contribution rates, create regulatory reports, make payments to collector institutions, and create ASSEDIC certificates upon employee termination.

- ARRCO and AGIRC Contributions.

PeopleSoft Global Payroll for France enables you to manage ARRCO and AGIRC contributions for pension funds.

- Contingency Funds Contributions.

PeopleSoft Global Payroll for France enables you to manage contributions for contingency funds.

- Allowances.

A payee may be entitled to a variety of allowances, paid in addition to the regular salary. PeopleSoft Global Payroll for France enables you to calculate and manage payment of allowances relating to contract termination, transportation allowances, benefits in kind, and meal and travel allowances.

- Absence Processing.

PeopleSoft delivers predefined rules for processing absences due to vacation, illness, maternity, work accidents, and other reasons. We've designed these rules in accordance with French statutory

requirements. You can easily modify many of these rules to reflect absence policies that are specific to your organization or to collective agreements that may be in force for your employees.

- Levies.

Levies are deductions that don't fall into obvious categories, such as URSSAF, ASSEDIC, and retirement funds. Levies are paid to several organizations with different funding bases, different conditions, and on different dates. PeopleSoft Global Payroll for France manages levies for:

- Professional training.
- Transportation.
- Participation of the Construction Effort levy.
- Apprenticeships.
- CSG and CRDS.
- Levy on salaries.
- Works councils.

- Garnishments.

PeopleSoft Global Payroll for France enables you to process garnishment deductions for alimony and various types of debt. Garnishments are taken every month, according to national guidelines.

- Loans and Advances.

Employers who agree to pay salary advances or provide employee loans can use PeopleSoft Global Payroll for France to define and manage these loans and advances automatically.

- Net Guarantee.

Employers may be required to pay a guaranteed percentage of a payee's gross salary during the time that the payee is on sick leave. PeopleSoft Global Payroll for France provides rules to manage the net guarantee calculation.

- Accruals.

PeopleSoft Global Payroll for France manages three accruals: the 2483 Annual Training report, the Employee Survey report, and paid vacation. For the 2483 Annual Training report, PeopleSoft Global Payroll for France provides a writable array to retrieve the required payroll indicators such as salary, training full time gross salary, and paid hours. For the Employee Survey report, PeopleSoft Global Payroll for France provides writable arrays to retrieve payroll and absence indicators such as salary, the number of working hours, the number of leaves of absence, and so on. PeopleSoft HR subsequently retrieves the values in the writable arrays to create the reports. In addition, PeopleSoft Global Payroll for France calculates two paid vacation accruals: the paid vacation accruals of the current accounting year and the accruals of the balance paid vacation of past accounting years.

- Specific Contracts.

Specific contracts provide exemptions on contributions. Usually they are set up between an employer and a government department or between an employer and payee, subject to controls from the DDTE

(regional government organization responsible for employment laws). PeopleSoft delivers rules for some common exemptions for fixed-term contracts, specific exempted contracts, and specific categories of payees.

- AFB Rules.

PeopleSoft Global Payroll for France provides specific elements for banking organizations that are members of the *Association Française des Banques* (AFB).

- Payslips.

The PeopleSoft payslip functionality enables you to define the elements that you want to print on the payslip, such as earnings, deductions, absence hours, and current and year-to-date totals, as well as a daily record. With our payslip process, you can print payslips for all payees, or a group of payees.

- Banking.

PeopleSoft Global Payroll for France includes an optional banking process that enables you to create a bank transfer file with details of payments to be made to each payee.

- Terminations.

PeopleSoft Global Payroll for France enables you to identify and retrieve online any employees that have been terminated in a defined period. Using the terminations functionality, you can create an off-cycle group, associate the terminated employees with this group, and process the employees in an off-cycle calendar. Or you can process the terminated employees as part of a regular, on-cycle calendar. This transaction enables you to specify the payment method for terminated employees (for example, manual payment or EFT).

- DUCS Generation.

PeopleSoft provides the ability to create DUCS files for submitting social security contribution information to government agencies for URSSAF, ASSEDIC, and ARRCO/AGIRC contributions.

- DADS Generation.

With PeopleSoft Global Payroll for France, you can extract DADS data from your database, review and update the extracted information, and create the DADS report conforming to the DADS-U norm.

- Wage Certificates.

PeopleSoft Global Payroll for France enables you to generate wage certificates for your payees. These certificates provide proof that a payee is entitled to receive social security payments for sick leave, maternity leave, paternity leave, work accidents, or occupational illness.

- Retroactive Processing.

Every customer must record retroactive updates that affect payroll. These retroactive updates can affect gross pay as well as deductions. PeopleSoft Global Payroll for France provides the following retroactivity functionality:

- Retroactivity standard setup.
- Support for retroactivity in reporting.

- Calculation of inactive segments.
- DIF and Training Allocation.

Global Payroll for France integrates with both the Administer Training business process and with Enterprise Learning Management to enable users to track DIF balances and compensate learners for DIF training and other training completed outside of the normal work schedule.

Delivered Elements for France

PeopleSoft Global Payroll for France defines each business process for France in terms of delivered elements and rules that are needed to run a French payroll. Some of these elements and rules are specifically designed to meet legal requirements, while others support common or customary payroll practices.

This section discusses:

- Delivered element creation.
- Element ownership and maintenance.
- Element naming convention for France.

Delivered Element Creation

All of the elements that are delivered with your country extension were created using the core application.

The core application:

- Consists of a payroll rules engine.

The rules engine is a flexible tool that enables you to define new payroll elements and run payroll and absence calculations using the delivered elements. PeopleSoft Global Payroll for France does not embed payroll computations in application code. Instead, it specifies all business application logic (such as earnings, deductions, absences, and accumulators) in terms of payroll rules. PeopleSoft Global Payroll for France enables you to enter and maintain payroll rules through a set of pages and offers comprehensive features that enable you to work in your preferred language or currency.

- Provides a payroll processing framework.

The payroll processing framework provides a flexible way to define and run payroll and absence processing flows (such as calendars, run types, pay periods, and process lists).

Element Ownership and Maintenance

This section describes PeopleSoft's approach to element ownership and what this means for the maintenance of French payroll rules.

Understanding Ownership in Global Payroll

PeopleSoft Global Payroll for France provides five types of element ownership:

PS Delivered/Maintained	Elements that are delivered and maintained on an ongoing basis by PeopleSoft.
PS Delivered/Not Maintained	Elements that are delivered by PeopleSoft that must be maintained by the customer. This type of element ownership consists primarily of either customary (nonstatutory) rules or statutory elements that customers may want to define according to a different interpretation of the rules. Although PeopleSoft occasionally updates elements that are defined as PS Delivered/Not Maintained, you are not required to apply these updates.
Customer Maintained	Elements that are created and maintained by your organization. PeopleSoft does not deliver rules that are defined as Customer Maintained.
PS Delivered/Customer Modified	Elements that were originally PS Delivered/Maintained elements over which the customer has decided to take control (this change is irreversible).
PS Delivered / Maintained / Secure	Delivered elements that the customer can never modify or control.

Understanding Ownership in Global Payroll for France

Of the five ownership types that are described here, two are used to define French elements:

- PS Delivered/Maintained.

PeopleSoft Global Payroll for France uses the ownership category PS Delivered/Maintained to prevent the modification of elements that are designed to comply with legal or statutory requirements.

- PS Delivered/Not Maintained.

Some elements, such as contribution rates and SMIC values, are defined as PS Delivered/Not Maintained. This enables you to modify these elements without waiting for the tax updates that are delivered by PeopleSoft.

Note: Before applying tax updates or other enhancements, determine whether the elements being upgraded have already been modified by your organization.

Element Type	Ownership	Exceptions
Earning	PS Delivered/Maintained	Base Salary and Base Salary for AFB.
Deduction	PS Delivered/Maintained	Work Council Tax is delivered as sample data.
Variable	PS Delivered/Not Maintained	Values that cannot be changed without affecting the calculation.

<i>Element Type</i>	<i>Ownership</i>	<i>Exceptions</i>
Bracket	PS Delivered/Not Maintained	If values are not to be changed by the customer, they are defined as PS Delivered/Maintained.
Accumulator	PS Delivered/Not Maintained for segment accumulators. PS Delivered/Maintained otherwise.	<p>In general, PeopleSoft maintains the nonsegment base accumulators because customers can modify the funding base segment accumulators. However, the following nonsegment accumulators are not PS Delivered/Maintained:</p> <ul style="list-style-type: none"> • Accumulators for loans and garnishments. • Generic accumulators. • Accumulators for benefits in kind.
Element Group	PS Delivered/Not Maintained	None.
Process List	PS Delivered/Not Maintained	None.
Section	PS Delivered/Not Maintained	None.

Element Type	Ownership	Exceptions
Formula	PS Delivered/Maintained	<p>Some exceptions apply if the rule is not strictly legal:</p> <p>Formulas that are used to create conditional sections in a process list and generation control formulas are not maintained.</p> <hr/> <p>Note: To enable you to decide when and how elements are triggered, generation control formulas and formulas that are used to create conditional sections are defined as PS Delivered/Not Maintained.</p> <hr/> <p>Situation formulas are used to manage specific contracts and are not maintained.</p> <hr/> <p>Note: Situation formulas are used to control how HR fields are used in payroll processing. To enable you to decide how these fields should be used, situation formulas are defined as PS Delivered/Not Maintained.</p> <hr/> <p>Most generic formulas are not PeopleSoft-maintained (except legal rules and specific process formulas).</p> <hr/> <p>Note: Generic formulas are developed as part of the country setup feature and carry the prefix GEN.</p> <hr/>
Array	PS Delivered/Maintained	None.
Generation Control	PS Delivered/Not Maintained	None. Generation control formulas have been defined as PS Delivered/Not Maintained to enable you to decide when and how elements are triggered.

Note: The owner field is used by the Element Upgrader to identify which elements PeopleSoft has delivered and which ones you have created.

Related Links

"Defining Element Names (*PeopleSoft HCM 9.2: Global Payroll*)"

[Understanding Specific Contracts](#)

[Understanding Specific Contracts](#)

Element Naming Convention for France

Understanding the naming convention that is used for PeopleSoft-delivered elements can help you determine how an element is used, its element type, and even the functional area that it serves.

This section discusses:

- Naming convention for supporting elements.
- Naming convention for primary elements.
- Naming convention for other elements.
- Additional clues to the use of French elements.
- Functional area codes.
- Element type codes (PIN_TYPE).

Naming Convention for Supporting Elements

For supporting elements such as variables, formulas, dates, durations, and so forth, PeopleSoft uses the following naming convention: FFF TT NAME.

- FFF: Functional Area Code (see Functional Area Codes for more information).
- TT: Type of Supporting Element (see List of Element Type Codes (PIN_TYPE) for more information).
- NAME: The name is based on a term in French and provides a further means of identifying the element.

For example, in the name of the variable URS VR TX VEUV S, URS represents the functional area, VR represents the element type, and TX VEUV S provides a further means of identifying the element.

Note: This naming convention applies to the following element types: arrays, brackets, counts, dates, durations, formulas, rate codes, variables, historical rules, fictitious calculation rules, proration rules, rounding rules, and generation control conditions.

Naming Convention for Primary Elements

Primary elements such as earnings, deductions, absence take, and absence entitlement elements do not always contain functional area codes in their names. This is because primary elements have names, based on French terms, that identify their function and element type without the use of additional codes. For example, the absence take and absence entitlement elements for seniority paid vacation have names that identify their use in the system:

Absence Reason	Take Element	Entitlement Element
Seniority paid vacation	CPT ANCIENTE	CPE ANCIENTE

The key to understanding how these elements are used is found in the abbreviations CPT and CPE. CPT represents paid vacation take (*prise congés payés*), and CPE represents paid vacation entitlement (*droits*

congés payés). In addition, the abbreviation ANCIENTE (*ancienneté* or seniority) indicates that the purpose of these elements is to calculate seniority paid vacation.

Note: PeopleSoft Global Payroll for France uses numerous abbreviations to signify how elements are used and the functional area they serve. Additional information about these abbreviations can be found in the section "Additional Clues to the Use of French Elements."

Naming Convention for Other Elements

For accumulators, sections, and element groups, PeopleSoft uses the following naming convention: FFF TT NAME.

- FFF: Functional Area Code (see Functional Area Codes for more information).
- TT: Type of Supporting Element (see List of Element Type Codes (PIN_TYPE) for more information).
- NAME: The name is based on a term in French and provides a further means of identifying the element.

For example, a section in a process list for France might be URS SE COTISATIONS, where URS is a functional area code, SE represents the element type, and COTISATIONS provides a means of uniquely identifying the element.

Additional Clues to the Use of French Elements

Many French elements contain abbreviations that provide additional clues to their use in the system (beyond those that are provided by the Functional Area Codes or List of Element Type Codes (PIN_TYPE)). For example, URS MAL S is a deduction with a calculation rule of *base x percent*. The *percentage* is contained in the variable URS VR TX MAL S, and the *base* is calculated by the formula URS FM BRUT ABAT. While the code URS (URSSAF) in the name of the deduction indicates the functional area that is served by the element, the abbreviations MAL and S provide additional useful information about the deduction. The abbreviation MAL (*maladie* or illness) indicates that the deduction applies to the URSSAF illness contribution, and the S (*salarie* or payee) signifies that the deduction is part of the payee's contribution. The TX (*taux* or rate) in the variable URS VR TX MAL indicates that the variable stores a contribution rate. And in the formula representing the base, the abbreviation ABAT (*abattement*) signifies that the formula determines a reduction (in this case a reduction of the gross salary). As you become more familiar with the elements that are created for a functional area, these abbreviations will help you to further identify and understand the role that is played by each element.

Abbreviations used in Global Payroll for France	French	English
ABAT(T)	<i>Abattu</i>	Reduced
ABT	<i>Abattement</i>	Reduction
ALIM	<i>Alimentation</i>	Feeding
AN	<i>Annuel</i>	Annual
AN	<i>Avantage en Nature</i>	Benefits in kind

Abbreviations used in Global Payroll for France	French	English
ANC	<i>Ancienneté</i>	Seniority
ATRV or AT	<i>Accident du Travail</i>	Work accident
AUB	<i>Aubry</i>	Aubry
CALC	<i>Calcul</i>	Calculation
CAR	<i>Carence</i>	Waiting period
CC	<i>Convention Collective</i>	Labor agreement
CO	<i>Carte Orange</i>	Paris transportation Orange Card
COND	<i>Conditionnel</i>	Conditional
COT	<i>Cotisations</i>	Contributions
CP or CPA	<i>Congés Payés</i>	Paid vacation
CPE	<i>Droits Congés Payés</i>	Paid vacation entitlements
CPT	<i>Prise Congés Payés</i>	Paid vacation take
DEB	<i>Début</i>	Beginning
DEC	<i>Décès</i>	Death
DECL	<i>Déclenchement</i>	Triggering
DED	<i>Déduction</i>	Deduction
DEP RET or D RET	<i>Départ à la retraite</i>	Voluntary retirement leave
DRT or DRTS or DTS	<i>Droits</i>	Entitlements
DT	<i>Droits ou Date</i>	Entitlements or date
DU	<i>DUCS (Déclaration Unifiée des Cotisations Sociales)</i>	Declaration of Social Contributions
E	<i>Employeur</i>	Employer
ENF	<i>Enfant</i>	Child
ETP	<i>Equivalent Temps Plein</i>	Full-time equivalent

Abbreviations used in Global Payroll for France	French	English
EVE	<i>Droits évènement familial</i>	Family event entitlements
EVF	<i>Evènement Familial</i>	Family event
EVT	<i>Prise évènement familial</i>	Family event takes
FF	<i>Forfaitaire</i>	Lump sum
FORM	<i>Formation</i>	Training/education
HOR	<i>Horaire</i>	Hourly
HR or HRS	<i>Heures</i>	Hours
ICCP	<i>Indemnités compensatrices de congés payés</i>	Paid vacation in lieu of allowances
IJ	(shorter term for IJSS) <i>Indemnités Journalières</i>	Daily allowances
IJSS	<i>Indemnités Journalières de Sécurité Sociale</i>	Social Security daily allowances
IND	<i>Indemnités</i>	Allowance
JC	<i>Jours Calendaires</i>	Calendar days
JO	<i>Jours Ouvrés</i>	Business days
JR or J	<i>Jour</i>	Day
LIC	<i>Licenciement</i>	Lay off
LIM	<i>Limite</i>	Limit
MAL	<i>Maladie</i>	Illness
MAP	<i>Mise à Pied</i>	Protective motive
MNT	<i>Montant</i>	Amount
MO	<i>Mois</i>	Month
NB or NBR	<i>Nombre</i>	Number
OBD	<i>Date d'origine de l'absence</i>	Original begin date

Abbreviations used in Global Payroll for France	French	English
OUV	<i>Ouvert/Ouverture</i>	Opened/opening
PL or PLAF	<i>Plafond/Plafonné</i>	Ceiling
PRD	<i>Période</i>	Period
PRM	<i>Primes</i>	Premiums
REE	<i>Droits Représentant du Personnel</i>	Entitlements for staff representatives
REM	<i>Rémunération</i>	Compensation
REP	<i>Rapport ou prise Représentant du Personnel</i>	Report or takes for staff representatives
RET	<i>Retenue</i>	Deduction
S	<i>Salarié</i>	Employee
SAL	<i>Salaire</i>	Salary
SG	<i>Segment</i>	Segment
SLD	<i>Solde</i>	Balance
STG	<i>Stagiaire</i>	Trainee
THEO	<i>Théorique</i>	Theoretical
TRAV or TRV	<i>Travail</i>	Work
TX	<i>Taux</i>	Rate

Functional Area Codes

Functional Area	Description
ABS	Absence
AFB	AFB Collective Agreement
AGI	AGIRC
APP	Apprentices
ARC	ARRCO

Functional Area	Description
ASS	ASSEDIC
ATR	Work Accident
BSO	<i>Bilan Social</i>
CP and CPA	Paid Vacation
EVE	Other Absences
EVT	Other Absences
FOR	2483 Training Report DIF Training Allocation
GEN	Country Setup
HRS	Overtime
IND	Allowances - Premiums
MAL	Illness
MAT	Maternity
PRE	Loans
PRO	Liability
PRV	Contingency
REE	Work Council
REP	Reports
RTO	Retroactivity
SAI	Garnishments
SIT	Situations
STG	Trainees
TAX	Levies
URS	URSSAF

Element Type Codes (PIN_TYPE)

<i>Element type</i>	<i>Description</i>
AE	Absence Entitlement
AT	Absence Take
AC	Accumulator
AR	Array
AA	Auto Assigned
BR	Bracket
CT	Count
DT	Date
DD	Deduction
DR	Duration
ER	Earning
EG	Element Group
EM	Error Message
FC	Fictitious Calculation
FM	Formula
GC	Generation Control
PP	Previous Period Rule
PR	Process
PO	Proration Rule
RC	Rate Code
RR	Rounding Rule
SE	Section
SY	System Element
VR	Variable

Related Links

"Understanding Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

Archiving Data for Global Payroll for France

PeopleSoft Global Payroll for France generates a large amount of result data which you may need to maintain for auditing or regulatory purposes, and which should periodically be archived. To facilitate this requirement, PeopleSoft PeopleTools delivers an archiving tool called the Data Archive Manager. To aid in archiving your data, PeopleSoft Global Payroll for France delivers a predefined archive object (GPFR_RSLT_ARCHIVE) and an archive template (GPFRRSLT) created using the Data Archive Manager. The archive template uses queries to select and store data by calendar group ID from calculation, banking, and other tables.

Note: Please use extreme caution when making changes to delivered archive objects, queries, or templates. Any modifications can result in the loss of important data.

See "Absence Processing (*PeopleSoft HCM 9.2: Global Payroll*)".

Additional Archiving Considerations

Result Data Type	Data Location
DUCS COT Results	GPFR_DUCS_CONTS table

If you want to archive this data, you can set up new archive objects, queries, and templates using the Data Archive Manager, or you can use your own archiving solution.

See the product documentation for *PeopleTools: Data Management*

Viewing Delivered Elements for France

The PeopleSoft system delivers a query that you can run to view the names of all delivered elements that are designed for France. Instructions for running the query are provided in the *PeopleSoft Global Payroll*

Related Links

"Understanding How to View Delivered Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

Setting Up Country Data

Understanding Country Setup


This section discusses:

- Pay process flow.
- Variables and categories.
- Rounding rules.

Pay Process Flow

Image: The pay process flow in Global Payroll for France

This diagram illustrates the pay process flow in Global Payroll for France



The following steps describe the pay process in Global Payroll for France:

1. Initialization.

The system executes formulas, arrays, dates, durations, and earnings in order to populate elements such as variables, accumulators, and formulas. These elements are needed by most of the other processes.

2. The system processes the Gross, which is made up of numerous earnings and deductions (compensation, premiums, overtime pay, absences, and allowances).

3. The system processes contributions, which are types of deductions (ARRCO/AGIRC, contingency funds, social contributions exemption limits, URSSAF, taxable exemption limits, ASSEDIC, and levies).

4. The system processes miscellaneous earnings and deductions that are not subject to income taxes, such as allowances, loans, garnishments, accruals, and DIF earnings.

A specific section manages the negative net-to-pay. This section is placed just before the accruals section. Other sections also appear at the end of the process list. Some sections are used to fill writable arrays, while others perform calculations to generate data for the absence process.

5. At the end of the calculation, several processes are completed to prepare data for different reports and processes.

These processes and reports include:

- The DUCS preparation (by populating the writable array (REP WA DU CONTS).
- The DADS preparation (by populating several payroll elements like variable or accumulators and the writable array DAS WA SITUAT S41).
- The ASSEDIC certificate preparation (by populating the writable array REP WA AA ELMT).
- The 2483 report preparation (by populating the writable array FOR WA 2483).
- The employee survey report preparation (by populating the writable array BSO WE PAIE).

See [Global Payroll for France Reports: A to Z](#).

Note: Set up the pay process in the order described so that the system processes the steps sequentially. If you stray from this order, the system may not function correctly.

Note: The pay process flow described here focuses only on the pay process and not on the absence process. For the absence process, different steps are followed and are described in the absence topic.

See "Understanding Absence Setup and Management Tasks (*PeopleSoft HCM 9.2: Global Payroll*)" [Updating Elements for Wage Certificates](#)

Variables and Categories

Global Payroll for France enables you to update many of the delivered variables on the Variables by Category page. You can also define your own variables, assign them to a category, and update them, if necessary, on the Variables by Category page.

Category	Description
A36	Article 36 Employee
A4	Article 4/4 bis Managers
ASS	ASSEDIC
CPA	Paid Vacation
EMPL	Employee
GEN	Country Setup Generic Variable
HRS	Additional and Overtime Hours
IND	Allowances
LEV	Levies
PRV	Contingency Funds
RET	ARRCO/AGIRC
SAI	Garnishments
URS	URSSAF
RTO	Retro- Elements retrieved in array

- The EMPL, A36, and A4 categories apply only to ARRCO/AGIRC deductions. During processing, they populate the variable ARC VR CATEGORIE, which is an accumulator key on most of the ARRCO/AGIRC accumulators. The deductions associated with the EMPL category are ARC T1 NC S, ARC T1 NC E, ARC T2 NC S, and ARC T2 NC E. When these deductions are processed, the category is retrieved and is used as an accumulator key.
- Many of these categories are used to group variables on the Variables by Category page. You can adjust these variables on the individual contributions or directly in the Variables by Category page. For example, you can update the value of an URSSAF variable on the URSSAF Rates page or on the Variables by Category page.

Related Links

[Understanding ARRCO, AGIRC, and Contingency Fund Contributions](#)

"Understanding Accumulators (*PeopleSoft HCM 9.2: Global Payroll*)"

"Defining Variable Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

Rounding Rules

Earnings and deductions provided by Global Payroll France have their *results* rounded using the rounding rule GP ROUND NEAR 2DEC. For the component elements (unit, base, rate, percent) of the earnings and deductions, the rounding rules applied are the pay group default rounding rules.

Understanding Contribution Rates and Limits

This section discusses:

- PeopleSoft-delivered contribution rates and ceilings.
- Contribution calculations.

PeopleSoft-Delivered Contribution Rates and Ceilings

PeopleSoft defines the contribution rates for URSSAF, ASSEDIC, ARRCO/AGIRC, and contingency funds as *variables*. Although PeopleSoft populates these variables with the correct rates for each type of contribution, and defines the ceilings that apply to the bases used to calculate these contributions, you can adjust the rates and ceiling values to comply with changing laws.

For example, there are 17 variables for the ARRCO rates. Each variable represents a single ARRCO contribution rate. On the ARRCO Rates page, the first variable contains the rate for the non-managers, Slice 1 (T1), payee contribution. The second variable contains the rate for the non-managers, Slice 1 (T1), employer contribution, and so on.

Many contributions, such as those for URSSAF and ASSEDIC, are based on earnings limits, or ceilings, defined by the government.

Ceilings are the earnings limits that define the different contribution rates for organizations such as URSSAF and ASSEDIC. The Limits page contains ceiling definitions. The monetary values of the ceilings appear on the Ceilings page.

You use the Contract Data page in PeopleSoft HR to assign limits to the earnings ceilings and enter complementary HR information specific to France. This information relates to the payee's regime and any related contribution deductions. Any payee eligible for an URSSAF contribution must be associated with a contribution class code (social security code or regime).

Contribution Calculations

This section discusses how the contribution calculations change in specific situations.

Progressive Regularization of Contributions

Some contribution types have limit ceilings. For these contributions, Global Payroll for France applies a progressive regularization of the contributions. This means that in each segment, the system calculates the limited funding base based on the annual amounts and obtains the funding month for the segment. The funding base is calculated as follows:

Calculation of the annual funding base limited to a ceiling – annual funding base on which the payee has already contributed = segment funding base limited to a ceiling

The annual funding base is calculated by the GEN FM CALC LIMIT formula. To process this formula correctly, the following variables must be populated: GEN VR BRUT (annual base amount), GEN VR MAXI (upper ceiling limit), and GEN VR MINI (lower ceiling limit).

Ceiling Proration Based on the Number of Segment Days

The ceilings entered on the Ceilings page are monthly ceilings for the URSSAF, ASSEDIC, ARRCO/AGIRC, and Contingency funds contributions. In the case of segmentation, these ceilings are prorated according to the number of days in the current segment being processed. The proration is calculated by the GEN FM NB JR 30IEM formula, based on 30 days per month (*trentième*) for all months of the year (as required by French law).

To override the number of days in the current segment retrieved by the GEN FM NB JR 30IEM formula, use the variable GEN VR 30EME FORCE and enter the new value on the Supporting Element Overrides page. The new value will be used for the calculation of the prorated ceilings. All ceilings calculated by PeopleSoft are affected by this override.

Ceiling Reduction for Payees with Multiple Employers

For payees with multiple employers, enter a multiple employer rate on the Contract Data page. The ceiling reduction is calculated using the value entered in the Multiple Employer Rate field.

Ceiling Proration for Part-Time Payees

You can apply proration to the ceiling for part-time payees. If these payees work less than the company standard hours, this proration is applied. This proration does not apply if the payee has multiple employers because the law indicates that only one proration can be used. The ceiling reduction first applies for the multiple employer rate and is never processed for part-time payees if it has been applied for multiple employers.

Gross Reduction Percentage for Specific Job Categories

You can enter a gross reduction value for specific job categories on the Contract Data page. The generic formula GEN FM ABATT BASE is used to calculate the funding base after reduction with the limitation previously defined.

Overriding Ceiling Values

Several variables can be used to override the ceiling values calculated by the application. The ceilings must be overridden individually.

Variable	Function
URS VR PLAF A FORC	Overrides the URSSAF A ceiling.
ASS VR PLAF A FORC	Overrides the ASSEDIC A ceiling.
ASS VR PLAF B FORC	Overrides the ASSEDIC B ceiling.
ASS VR PLAF AB FORC	Overrides the ASSEDIC AB ceiling.
ARC VR PLAF A FORC	Overrides the ARRCO A ceiling.

Variable	Function
ARC VR PLAF 1 FORC	Overrides the ARRCO 1 ceiling.
ARC VR PLAF 2 FORC	Overrides the ARRCO 2 ceiling.
AGI VR PLAF A FORC	Overrides the AGIRC A ceiling.
AGI VR PLAF B FORC	Overrides the AGIRC B ceiling.
AGI VR PLAF C FORC	Overrides the URSSAF C ceiling.
AGI VR PL ABC FORC	Overrides the AGIRC ABC ceiling.
AGI VR PL GMP FORC	Overrides the AGIRC GMP ceiling.
PRV VR PLAF A FORC	Overrides the Contingency Funds A ceiling.

Long Term Absences

There are three types of long-term absences considered by Global Payroll for France:

- Unpaid Absence During An Entire Month.

In the case of an unpaid absence during a whole month, the ceilings are considered equal to 0. In order to manage this case, the payee status must be equal to *Leave with Pay* during the whole month.

If the payee status is equal to *Leave with Pay*, the URSSAF, ASSEDIC, and Contingency ceilings and the ARRCO ceiling for payees are set equal to 0.

If you want to avoid setting ceilings equal to 0, override the variable GEN VR ANNUL PLAF at the Supporting Element Overrides level with the value 0. Then, even if the status is equal to *Leave with Pay* for the whole month, the ceilings won't be set equal to 0.

- Uninterrupted Absence that Overlaps Two Calendar Year with A Status of *Leave with Pay*.

In this situation, if there is a payment of back pay salaries for the previous year, the system retrieves the last ceiling values for the payee and uses these ceilings to calculate the contributions of the segment.

- Uninterrupted Absence that Overlaps Two Calendar Year with A Status of *Leave without Pay*.

When the payee comes back (and when his status is no longer equal to *Leave with Pay*), then all the ceilings are set to 0. This means that the system does not use the ceilings if they have been retrieved as described in the previous case.

Related Links

[Understanding URSSAF Contributions](#)

[Setting up Rates and Ceilings for ASSEDIC Contributions](#)

[Understanding ARRCO, AGIRC, and Contingency Fund Contributions](#)

Reviewing and Updating Contribution Rates and Limits

To update contribution rates and ceilings, use the Ceilings FRA (GPFR_CEILINGS) and Rates/Elements/Limits FRA (GPFR_RATE_PANELS) components.

This section discusses how to:

- View groups of rates for contributions.
- View limits associated with variables.
- View and update ceilings.

Pages Used to View and Update Rates, Limits, and Ceilings

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Rates And Elements	GPFR_RATE_PANELS	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Addl Rates, Ceilings, Values, Rates/Elements/Limits FRA, Rates And Elements	View the variables containing the rates for the different types of contributions, such as ARRCO or AGIRC. The data on the Rates and Elements page is delivered by PeopleSoft but is not maintained by PeopleSoft.
Limits	GPFR_LIM_PANELS	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Addl Rates, Ceilings, Values, Rates/Elements/Limits FRA, Limits	View the limits or ceilings associated with the rate variables displayed on the Rates and Elements page. The values on the Limits page are delivered by PeopleSoft but not maintained by PeopleSoft. You can change the ceilings for a variable here.
Ceilings FRA	GPFR_CEILINGS	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Addl Rates, Ceilings, Values, Ceilings FRA	View the different ceiling values used to calculate the funding bases for the URSSAF, ASSEDIC, AGIRC/ARRCO, and contingency funds contributions. You can change the values of the ceilings here to comply with changing laws.

Related Links

[ARRCO Rates Page](#)

[Element Ownership and Maintenance](#)

Rates And Elements Page

Use the Rates And Elements page (GPFR_RATE_PANELS) to view the variables containing the rates for the different types of contributions, such as ARRCO or AGIRC.

The data on the Rates and Elements page is delivered by PeopleSoft but is not maintained by PeopleSoft.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Addl Rates, Ceilings, Values, Rates/Elements/Limits FRA, Rates And Elements

Image: Rates And Elements page

This example illustrates the fields and controls on the Rates And Elements page. You can find definitions for the fields and controls later on this page.

Entry Type	Element	Name		
1 Variable	ASS VR TX RAC TA S	Rate RAC bracket A payee	+	-
2 Variable	ASS VR TX RAC TA E	Rate RAC bracket A employer	+	-
3 Variable	ASS VR TX RAC TB S	Rate RAC bracket B payee	+	-
4 Variable	ASS VR TX RAC TB E	Rate RAC bracket B employer	+	-
5 Variable	ASS VR TX FNGS	Rate FNGS employer	+	-

Component Name

Displays the name of the component that contains the variables.

Elements

Entry Type

Select the entry type: *Accumulatr* (accumulator), *Deduction*, *Section*, and *Variable*.

Element Name

Displays the names of the variables containing the rates for the different types of contributions, such as ARRCO or AGIRC. Variable names are coded according to the contribution type. For example, *ARC VR TX T1 NC S* is the variable that contains the value of the ARRCO contribution rate for a payee on earning base T1.

Limits Page

Use the Limits page (GPFR_LIM_PANELS) to view the limits or ceilings associated with the rate variables displayed on the Rates and Elements page.

The values on the Limits page are delivered by PeopleSoft but not maintained by PeopleSoft. You can change the ceilings for a variable here.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Addl Rates, Ceilings, Values, Rates/Elements/Limits FRA, Limits

Image: Limits page

This example illustrates the fields and controls on the Limits page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'Limits' page in the Oracle HCM system. The page has a tabbed interface with 'Rates And Elements' and 'Limits'. The 'Limits' tab is active, displaying a table with three rows of limits. Each row has a 'From Ceiling' and a 'To Ceiling' dropdown menu, and buttons to add or remove rows. The component name is GPFR_ASS_RATES and the description is ASSEDIC Rates and Limits.

Limits		Customize Find View All First 1-3 of 3 Last	
	From Ceiling	To Ceiling	
1	Zero	A Ceiling	+ -
2	A Ceiling	B Ceiling	+ -
3	Zero	B Ceiling	+ -

Component Name Displays the name of the component that contains the variables.

Limits

From Ceiling Select the minimum salary base for the set of limits that you are defining.

To Ceiling Select the maximum salary base for the set of limits that you are defining.

Ceilings FRA Page

Use the Ceilings FRA page (GPFR_CEILINGS) to view the different ceiling values used to calculate the funding bases for the URSSAF, ASSEDIC, AGIRC/ARRCO, and contingency funds contributions.

You can change the values of the ceilings here to comply with changing laws.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Addl Rates, Ceilings, Values, Ceilings FRA

Image: Ceilings FRA page

This example illustrates the fields and controls on the Ceilings FRA page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'Ceilings FRA' page. At the top, there is a header bar with 'Ceilings' and navigation links: 'Find | View All | First | 1 of 10 | Last'. Below the header, there are two input fields: '*Effective Date:' with a date picker set to '01/01/2009' and 'Status:' with a dropdown menu set to 'Active'. To the right of these fields are '+' and '-' buttons. Below this is a table titled 'Ceilings' with two columns: 'Ceilings' and 'Amount'.

Ceilings	Amount
A Ceiling	2859.000
B Ceiling	11436.000
C Ceiling	22872.000
GMP Ceiling	305.420
Ceiling 2 (A Ceiling x 3)	8577.000
Tax on Salaries Ceiling 1	7461.000
Tax on Salaries Ceiling 2	14901.000

The ceiling name appears in the column on the left. The current monetary values of each ceiling appear in the Amount column. The amounts for the ceilings are monthly amounts in euros.

Defining Ceilings for Amounts That Are Not Monthly

If a payee works only one week during the month, the payee has a segment period equal to one week in the month. You can prorate the ceiling using the number of days of the segment compared to the number of days in the monthly period.

Determining When a Ceiling Has Been Reached

The calculation of the slice is a monthly calculation. This means that you add the gross for the year and compare this sum to the sum of all the monthly ceilings. If the sum of the gross is more than the sum of the ceilings, the annual funding base of the ceiling is limited. The funding base of the previous month on which the payee has already contributed is deducted and the monthly funding base is obtained. A generic formula called GEN FM CALC LIMIT is used for calculating this monthly funding base limited to a ceiling.

Reviewing Garnishment Brackets

To review garnishment brackets, use the Bracket FRA (GPFR_GAR_RATES) component.

Garnishment calculations are based on a payee's net taxable earnings. The attachable portion is calculated as a fraction of net taxable earnings and is adjusted if the payee has dependents. The government sets annual ceilings each year, which appear on the Garnishment Bracket page. PeopleSoft delivers the values in the garnishment bracket.

Note: To see the name of the variables that store the values in the garnishment bracket, access the Rates and Elements page using the component name GPFR_GAR_RATES.

Page Used to Update Salary Ceilings for Garnishments

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Bracket FRA	GPFR_GAR_RATES	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Garnishments/Court Orders, Bracket FRA, Bracket FRA	View and update the salary ceilings for garnishments.

Bracket FRA Page

Use the Bracket FRA page (GPFR_GAR_RATES) to view and update the salary ceilings for garnishments.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Garnishments/Court Orders, Bracket FRA, Bracket FRA

Image: Bracket FRA page

This example illustrates the fields and controls on the Bracket FRA page. You can find definitions for the fields and controls later on this page.

Bracket FRA

Rates Find | View All First 1 of 10 Last

*Effective Date: 01/01/2009 31 Status: Active + -

Salary Slice (Ceilings)	
	Amount
1/20	3460.000
1/10	6790.000
1/5	10160.000
1/4	13490.000
1/3	16830.000
2/3	20220.000

Other	
	Amount
Increase per dependant person	1310.000
Monthly unattachable portion ("RMI")	454.630

Salary Slice (Ceilings)

The fraction of a payee's salary that is attachable varies according to the salary limits set by the government. The fraction that corresponds to each salary limit is listed under Salary Slice (Ceilings). To the right, the corresponding salary limit appears in euros.

Other

Increase per dependant person

Displays the statutory increase in the salary slice, or range, for each dependent person. If a payee has one dependent, for example, the bottom salary slice increases by the amount in this field. If the payee has three dependents, the slice increases by three times the amount in this field.

Note: The system counts only those dependents for whom the Garnishment check box is selected on the Dependent Information - Personal Profile page in Workforce Administration.

Monthly unattachable portion ("RMI")

Displays the monthly unattachable portion of salary.

Related Links

"Dependent Information - Name Page (*PeopleSoft HCM 9.2: Human Resources Administer Workforce*)"

Understanding Net Guarantee Processing

This section provides an overview of the net guarantee, and discusses:

- Managing the net guarantee calculation.
- Adding deductions to the net guarantee calculation.
- Viewing the delivered net guarantee deduction.

Managing the Net Guarantee

French law requires employers to pay a guaranteed percentage of a payee's gross salary during the time that the payee is on sick leave, subject to certain conditions. Alternatively, some collective agreements stipulate a guaranteed percentage of a payee's net salary during a payee's sick leave.

Many collective agreements stipulate that the allowance paid to a payee during the payee's illness, after deduction of the social security daily allowances, cannot result in the payee's net salary exceeding the net salary earned when the payee is not on sick leave. This is called the guarantee on the net salary (*garantie sur le net*).

The law stipulates a guarantee on the gross salary. For companies not bound by a collective agreement, the guarantee on the net salary does not have to be applied. However, most companies in France are bound by a collective agreement. Also, most companies apply the net guarantee rule because it is generally considered a fair way to do business. However, in some cases, such as with small companies without a collective agreement or a collective agreement without any reference to the net guarantee, the net guarantee does not have to be considered.

Global Payroll for France provides rules to manage the net guarantee calculation.

Note: Most elements created specifically for the net guarantee calculation are named with a prefix of GEN or a suffix of GN. This enables you to easily identify the relevant elements.

The Net Guarantee Calculation

The net guarantee calculation is managed through a sub-process section (GEN SE GARANTI NET) and the following are the steps in the calculation:

1. The net guarantee sub-process section is triggered if there are social security daily allowances (*Indemnités Journalières de Sécurité Sociale* or "IJSS")—that is, if the accumulator GEN AC IJSS GN SG is over zero. The condition formula GEN FM COND NET GA is used to trigger the sub-process section.

2. The formula GEN FM INIT initializes the sub-process section. The formula populates the variable GEN VR IERE ITERAT to indicate that the system is processing the first loop.
3. The processing loop begins. The formula GEN FM NB ITERAT is processed at the beginning of each loop. This formula populates the variable GEN VR NB ITERAT with the value of the number of iterations (for example, GEN VR NB ITERAT will be equal to five during the fifth iteration). To exit the loop, the variable GEN VR EXIT, used in the condition formula GEN FM EXIT, must be equal to FALSE.
4. The net guarantee section GEN SE IJSS AJUST is triggered. This section stores the adjustments that are being calculated iteratively. The section GEN SE IJSS AJUST includes the deduction IJSS AJUST. This section and this deduction are also used during "normal" processing (that is, outside the sub-process section) and IJSS AJUST is equal to the adjustment calculated in the sub-process section.
5. During the first iteration of processing, the modification of the gross salary is calculated. The formula GEN FM MODIF BRUT populates a variable with the amount of the IJSS, and this variable is a member of the accumulator GEN AC BRUT SG. Then the net salary, without the impact of the IJSS, is calculated. This produces a target net salary.
6. The various sections created specifically for the net guarantee calculation are triggered using the same condition formula and in the same order as the regular contributions sections in the process list.
7. The formula GEN FM RAZ VR GN is resolved, and the indicator variables are set to zero. If you create a formula using the same logic as GEN FM RAZ VR GN, the formula must resolve to set the indicator variable to zero. Your new formula must be inserted into the sub-process section immediately after the formula GEN FM RAZ VR GN.

If you create any formulas using the same logic as the one described in the section *Understanding Net Guarantee Formulas*, the indicator variables you create must be set to zero. Such a formula must have the same goal as GEN FM RAZ VR NG (that is, to set the indicator variables equal to zero). Your new formula must be inserted into the sub-process section immediately after the formula GEN FM RAZ VR GN.

8. The target net salary is calculated during the first iteration. The formula GEN FM NET GARANT calculates the target net salary and stores the result in the variable GEN VR NET A PAYER. The target net to pay is equal to net salary calculated during the first iteration (that is, gross salary, without impact of the IJSS, minus the contributions). This net salary is reduced by the amount of the net IJSS, which is the IJSS reduced by the CSG and CRDS.
9. The IJSS adjustment is calculated. The formula GEN FM GARANTI NET calculates the IJSS adjustment if there is still more than one cent of difference between the net salary and the target net salary. The adjustment calculated during each iteration is equal to the difference between the net salary and the target net salary multiplied by a contribution rate stored in the variable GEN VR TAUX FIXE. This amount is added to the previous value of the IJSS adjustment. If the difference between the net salary and the target net salary is lower than the value stored in the variable GEN VR DELTA NET, the variable used as an indicator of the last iteration (GEN VR DERN ITERAT) and the variable used to exit the loop (GEN VR EXIT) is populated.
10. The IJSS adjustment is limited so that the IJSS plus the IJSS adjustment are not greater than the appropriate salary upholding for the month.
11. The sub-process section is stopped, and the normal process list continues processing.

The maximum number of iterations for this process is 15. If the difference between the net salary and the target net salary is higher than the value of GEN VR DELTA NET after the fifteenth iteration, the

processing loop is stopped, the IJSS adjustment is set equal to the last amount calculated, and a warning message appears letting you know that the calculation of the IJSS adjustment is inaccurate.

The variable GEN VR CALC GN is used in the condition formula GEN FM COND NET GA to trigger the calculation of the net guarantee sub-process section. By default, GEN VR CALC GN is equal to True (1), which means that the net guarantee is processed when the accumulator GEN AC IJSS GN SG is over zero.

Note: If you want to avoid the calculation of the net guarantee and want to directly enter an amount for the IJSS adjustment, override the variable GEN VR CALC GN to False (0) and enter the value of the adjustment in the variable GEN VR AJUSTEMENT.

If your organization does not want to use the calculation of the net guarantee, there are several possible solutions, some of which are:

- Override the variable GEN VR CALC GN to false (0) at the payee level if you just want to avoid the calculation for one specific payee.
- Override the variable GEN VR CALC GN to false at the pay entity level. Then, the adjustment will not be calculated for organizations where the adjustment does not need to be calculated (for example, when following a collective agreement).
- Create a process list without the sub-process section GEN SE GARANTI NET and use this process list for organizations where the net guarantee does not need to be performed.
- Modify the condition formula GEN FM COND NET GA. This formula is PeopleSoft delivered, but not maintained. Create your own logic to trigger, or not trigger, the net guarantee calculation according to your needs.

Note: PeopleSoft strongly recommends that you define the pay entity equal to *Company* when using the delivered rules for France.

See "Setting Up Sections (*PeopleSoft HCM 9.2: Global Payroll*)", "Setting Up Process Lists (*PeopleSoft HCM 9.2: Global Payroll*)".

Net Guarantee Formulas

PeopleSoft designed the net guarantee rules to allow the recalculation of elements in the sub-process section without excessive degradation of the system's performance.

The goal of the sub-process section is to create processing loops (or iterations) for some elements. During each loop, some of the elements have another value and must be recalculated. These elements are therefore defined to always recalculate. The rules use logic that maximizes performance during each processing loop. When formulas are used several times in the process or in the sub-process, their results are stored in variables.

When using these formulas, the system follows these steps:

1. Test if the variable indicator is equal to *True* or *False*.
2. If the variable indicator is equal to *False*, the formula is triggered and its result is stored in a variable.
3. If the variable indicator is equal to *True*, the system does not trigger the formula because the system knows the formulas has already been calculated and the result has already been stored in a variable.

4. The system uses the result stored in the variable (and not the formula itself).
5. At the end of the sub-process section, the variable indicators are set to zero by the formula GEN FM RAZ VR GN and are then ready to be recalculated during a new iteration.

For example, the formula ARC FM BRUT ABAT is used to determine the gross salary, after reduction for specific jobs, used in the ARRCO contributions calculation. This formula needs to be recalculated during each iteration, but is used by the formulas ARC FM CALC BASE A, ARC FM CALC BASE 1, and ARC FM CALC BASE 2. The result of the formula ARC FM BRUT ABAT is stored in the variable ARC VR BRUT ABAT, and the variable indicator ARC VR BRUT ABA DC stores the value *True (1)* when the formula ARC FM BRUT ABAT is calculated.

When Global Payroll for France needs the gross salary for ARRCO contributions in the formula ARC FM CALC BASE A, for example, the system firsts tests the value of the variable indicator. If this variable is equal to *False*, the system triggers the calculation of the formula ARC FM BRUT ABAT and then uses the result stored in the variable ARC VR BRUT ABAT. If the variable ARC VR BRUT ABA DC retrieves the value *True*, the system does not trigger the formula ARC FM BRUT ABAT and can instead use the result already stored in the variable.

Formula Name	Variable Result	Variable Indicator
AGI FM BRUT ABAT	AGI VR BRUT ABAT	AGI VR BRUT ABA DC
AGI FM CALC BASE B	AGI VR CALC BASE B	AGI VR CAL BA B DC
ARC FM BRUT ABAT	ARC VR BRUT ABAT	ARC VR BRUT ABA DC
URS FM BASE A	URS VR BASE A	URS VR BASE A DC
URS FM BRUT ABAT	URS VR BRUT ABA 2	URS VR BRUT ABA DC

Adding Deductions to the Net Guarantee Calculation

This section discusses how you add deductions to the net guarantee calculation.

Creating Deductions

If you create any deductions that need to be included in the net guarantee calculation and need to use formulas triggered several times in the process, apply the same logic (explained in the previous section) as the PeopleSoft-delivered elements.

If you need to use the results of the formulas AGI FM BRUT ABAT, AGI FM CALC BASE B, ARC FM BRUT ABAT, URS FM BASE A, and URS FM BRUT ABAT, use the logic developed by PeopleSoft.

If you create new deductions and have formulas that must be recalculated during each iteration, but that are used several times, you can use the delivered PeopleSoft logic. But if you need to create a formula with the same function as the formula GEN FM RAZ VR GN (that is, to set the variable indicator equal to zero), insert the new formula in the sub-process section after the formula GEN FM RAZ VR GN.

Creating Sections

You can create your own sections referencing your deductions and then include them in the sub-process section. The deductions that need to be included in the sub-process section are the deductions that impact the net to pay salary. This is the case for a payee's contributions. But this is also the case for some employer's contributions and particularly the deductions used to calculate the contributions exemption limits.

Creating or Updating the Sub-Process Section

The setup of the sub-process section must reflect the process list you define. The sub-process section provided by PeopleSoft is based on the process list REGLEMENTAIRE PAIE. In the sub-process section, the system uses certain sections (with the suffix GN) patterned after the sections used in the normal process list. The system also uses the same conditional formulas.

If you have a process list with some differences in the order of the sections, in the sections themselves, and/or in the conditional formulas, update the sub-process section provided by PeopleSoft or create your own sub-process section. If your company has its own unique process list, create sub-process sections that correspond to your own unique process list.

Note: For example, PeopleSoft provides some specific sections to manage the contributions due for the different categories for the retirement and contingency contributions. There are two ways of managing the triggering of the deductions depending on the payee's category (employee, Article 36, or Article 4&4bis). This can be done through eligibility groups or through sections.

The process list REGLEMENTAIRE PAYE provided by PeopleSoft uses eligibility group management of the deductions triggering. For companies that choose to manage the triggering through sections, those companies need to create sub-process sections that follow the same logic as their process lists.

The calculation of some benefits in kind (meal and lodging) depends on the value of the gross salary. Because the gross salary varies during the iterative calculation, if the benefits in kind calculation were included in the net guarantee sub-process section, this could cause instability in the adjustment calculation. To avoid this, PeopleSoft has placed the benefit in kind section IND SE AVT NATURE after the IJSS section GEN SE IJSS but before the net guarantee sections GEN SE GARANTIN NET and GEN SE IJSS AJUST.

Related Links

[Understanding ARRCO, AGIRC, and Contingency Fund Contributions](#)

[Understanding Allowance Calculation](#)

Viewing the Delivered Net Guarantee Deduction

PeopleSoft delivers and maintains the deduction element IJSS AJUSTEM to accommodate the net guarantee calculation. This deduction stores the value of the adjustment calculated in the sub-process section. To find out the specifics of an element's definition, use the Global Payroll core application online element definition pages to display the element's definition.

Note: PeopleSoft delivers a query that you can run to view the names of all delivered elements that are designed for France.

Related Links

"Understanding Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

"Understanding Earning and Deduction Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

Understanding the Seniority Calculation

Global Payroll for France delivers three types of seniority calculation. This section discusses:

- Seniority effective at the segment end date.
- Seniority prorated after a period of part-time work.
- Seniority calculated at the beginning of the notice period.
- Elements used in seniority calculation.

Seniority Effective at the Segment End Date

The seniority effective at the segment end date is calculated from the number of days worked by a payee. The number of days worked is stored in the GEN AC JOUR ANC accumulator. The GEN AC JOUR ANC accumulator is calculated as follows:

GEN AC JOUR ANC = number of days of the segment – the number of absence days + the number of absence days counted as days worked by law + the number of absence days counted as days worked by the collective agreement

Seniority is calculated as follows:

Seniority = segment end date – number of days of seniority

The following variables return these corresponding values:

- The GEN VR AN ANC variable returns the value for the number of years.
- The GEN VR MOIS ANC variable returns the value for the additional seniority in months.
- The GEN VR JOUR ANC variable returns the value for the additional seniority in days.

Global Payroll for France takes into account both leap years and non-leap years in calculating seniority. If the segment end date is December 31, and the number of days of seniority is 365 days, the seniority in years is equal to 1 for a non-leap year and 0 for a leap year. In other words, for a non-leap year, the system returns a value of 1, and for a leap year, the system returns a value of 0.

The seniority calculation is expressed in years plus months plus days.

Example

Segment end date = December 31, 2001 (a non-leap year)

Number of days of seniority for a payee = 401

Seniority = 1 year, 1 month, and 5 days

Note: Global Payroll for France does not express seniority in different formats, such as 1 year, 13 months, or 401 days.

Seniority Prorated After a Period of Part-Time Work

For seniority that is prorated after a period of part-time work, the GEN AC JR ANC PRO accumulator stores the number of days of seniority that are prorated. The results are stored using the same logic as the variables used for seniority at the segment end day.

The following variables return these corresponding values:

- The GEN VR AN ANC PRO variable returns the value for the number of years.
- The GEN VR MOIS ANC PR variable returns the value for the number of months.
- The GEN VR JOUR ANC PR variable returns the value for the number of days.

Seniority Calculated at the Beginning of the Notice Period

Global Payroll for France also provides a seniority type calculated at the begin date of the notice period. The number of days of seniority is stored in the GEN AC JOUR ANC LI accumulator.

The results are stored in the following accumulators:

- GEN AC AN ANC LIC for the years.
- GEN AC MOIS ANC LI for the months.
- GEN AC JOUR ANC LI for the days.

This seniority is calculated only when the date of the beginning of the notice period is included in the segment period. The results are stored in custom accumulators. This means that the result of these accumulators should be calculated only once and that the result is stored and can be retrieved in future pay periods.

Note: When you first set up Global Payroll for France, you must populate the GEN AC JOUR ANC, GEN AC JR ANC PRO, and GEN AC JOUR ANC LI accumulators with the number of days of seniority.

Elements Used in Seniority Calculation

This section discusses:

- Accumulators
- Formulas
- Brackets

Accumulators

Global Payroll for France uses the following rules to populate the GEN AC JOUR ANC, GEN AC JR ANC PRO, and GEN AC JOUR ANC LI accumulators.

Note: The following example illustrates the rules for the GEN AC JOUR ANC accumulator, but the logic is the same for the other accumulators.

The GEN AC JOUR ANC accumulator has four members:

- GEN AC JOUR CAL is added and retrieves the number of calendar days of the segment. This accumulator is populated in the pay process.
- GEN AC ABSENCE is subtracted and retrieves the number of absence days of the segment. This accumulator is populated in the absence process and is used to deduct the seniority from the days of absence.
- GEN AC ABS ASS LOI is added and retrieves the number of absence days of the segment counted as days worked by the law. This accumulator is populated in the absence process and is used to decrease the number of absence days when the law indicates that some specific absences are counted as days worked and do not then decrease the seniority.
- GEN AC ABS ASS CC is added and retrieves the number of absence days of the segment counted as days worked by the collective agreement. This accumulator is populated in the absence process and is used to decrease the number of absence days when the collective agreement indicates that some specific absence is counted as days worked and does not then decrease the seniority. Of course, what is counted as days worked is exclusive between the law and the collective agreement.

Formulas

The accumulators populated by the absence process are updated by three formulas:

- The GEN FM ABS CAL formula populates the GEN AC ABSENCE accumulator. This formula is processed in a day formula for all absences.
- The GEN FM ABS ASS CAL formula populates the GEN AC ABS ASS LOI accumulator. This formula is processed in a day formula only for absences that are counted as days worked by law.
- The GEN FM ABS ASS CC formula populates the GEN AC ABS ASS CC accumulator. This formula is processed in a day formula only for absences that are counted as days worked by the collective agreement.

Brackets

The formulas GEN FM ABS ASS CAL and GEN FM ABS ASS CC are triggered by the brackets ABS BR ANC-ABS LOI and ABS BR ANC-ABS CC.

<i>ABS BR ANC-ABS LOI</i>	<i>Key: TAKE CONFIG2</i>
<p>Indicates how to process an absence for the seniority calculation.</p> <p>Values in the bracket result column:</p> <p><i>1</i> means that the absence is considered to be effective work by law.</p> <p><i>0</i> means the absence is considered to be an absence by law.</p>	<p>Return column:</p> <p>ABS BR ANC-ABS LOI</p>

TAKE CONFIG2	ABS BR ANC-ABS LOI
MAL	0
AT	1
ATRCH	0
MAT	1
ADOPT	0
THERP	0
EVF	0

ABS BR ANC-ABS CC	Keys: TAKE CONFIG2, COLLECTIVE AGREEMENT
<p>Indicates how to process an absence when calculating seniority under a collective agreement.</p> <p>Values in the bracket result column:</p> <p><i>1</i> means that the absence is considered to be effective work by the collective agreement.</p> <p><i>0</i> means that the absence is considered to be an absence by the collective agreement.</p> <p>Values in the ABS VR J PAYES CC column result:</p> <p><i>1</i> means the absence has to be paid to be treated as effective work by the collective agreement (the variable can only be equal to <i>1</i> if the bracket returns <i>1</i>).</p> <p><i>0</i> means the absence is considered to be an absence by the collective agreement.</p>	<p>Return columns:</p> <p>ABS BR ANC-ABS CC</p> <p>ABS VR J PAYES CC</p>

TAKE CONFIG2	COLLECTIVE AGREEMENT	ABS BR ANC-ABS CC	ABS VR J PAYES CC
MAL	AFB	1	1
AT	AFB	1	0
ATRCH	AFB	0	0
MAT	AFB	1	0
MTSUP	AFB	0	0

TAKE CONFIG2	COLLECTIVE AGREEMENT	ABS BR ANC-ABS CC	ABS VR J PAYES CC
ADOPT	AFB	0	0
THERP	AFB	0	0
DIV	AFB	0	0
EVF	AFB	0	0

Global Payroll for France uses the formula ABS FM ALIM AC ABS (applied to each absence take calculation) to trigger either the formula GEN FM ABS ASS CAL or the formula GEN FM ABS ASS CC based on the values returned by the brackets. For example, if the bracket ABS BR ANC-ABS LOI identifies an absence as an absence by law that should subtract from the number of seniority days, the formula ABS FM ALIM AC ABS triggers the formula GEN FM ABS ASS CAL.

Understanding SMIC Control

The *Salaire Minimum Interprofessionnel de Croissance* (SMIC) is the minimum salary defined by law. Global Payroll for France includes a control to check that the salary paid is greater than or equal to the SMIC. If the salary paid is less than the SMIC, the system increases the funding base used for the contributions because this funding base cannot be less than the SMIC.

Global Payroll for France uses the GEN FM CTRL SMIC formula to process different calculations and controls, including the control for the SMIC. If the salary paid is less than the SMIC, this formula generates a warning message. View this message on the Payee Messages page in the core application.

The SMIC is calculated as follows:

SMIC = the number of hours paid × the hourly SMIC value

The control is applied to the segment and the month that the system controls if the sum of the different salaries paid during the month is more than the sum of the segment SMICs.

The SIT FM PAYM HRS situation formula is used to indicate whether the payment of the salary is based on the hours and if the SMIC control can be done.

If the payment is a lump sum and the number of hours cannot be estimated, then you must override the SIT FM PAYM HRS formula with the GP FALSE value, and no SMIC control is applied. By default, the SIT FM PAYM HRS formula is equal to GP TRUE, which means that the control is normally processed.

This control is not checked for a company officer or payees who have the SIT FM MANDATAIRE situation formula equal to TRUE. For the SMIC calculation, the system applies the reduction for specific categories of payees, such as for people under 18 and for specific contracts.

Regarding the modification of the funding base, the system calculates the difference between the SMIC and the salary paid. If the salary paid is less than the SMIC, the system adds the difference to the funding base used for the calculation of the contributions. Moreover, the salary compared to the SMIC is the salary after the reductions for professional expenses because these expenses do not count as contributions to a salary that is less than the SMIC.

Related Links

[Understanding Specific Contracts](#)

Understanding Hours Calculations

PeopleSoft calculates different hours for a segment, such as hours paid and hours worked.

You must first indicate the base hour for the payee in PeopleSoft HR. You must populate the Paid Hours and the Paid FTE fields. If you don't populate these fields, the process errors when the system needs this information.

Note: The only frequencies that Global Payroll accepts for the Paid Worked Period field are *A* (annual), *M* (monthly), and *W* (weekly).

When you enter paid hours, the process converts these hours to hours per month. If the paid hours are defined as *monthly*, the variable GEN VR HOR SAL MO retrieves the input value directly. If the paid hours are defined as *weekly*, the variable GEN VR HOR SAL MO retrieves the result of the weekly hours input multiplied by 52 and divided by 12. If the paid hours are defined as *annual*, the variable GEN VR HOR SAL MO retrieves the annual input divided by 12.

The different hours are calculated as follows:

- GEN VR HOR CONV retrieves the monthly standard hour of the company (and is equal to Paid Hours Fra divided by the paid FTE).
- GEN VR HOR SAL MO retrieves the monthly theoretical hour of the payee.
- GEN VR HOR LEG MO retrieves the monthly legal hour applied to the company. This hour comes from the GEN VR HR LEG variable where users can enter the weekly legal hour. If this variable is not populated, this hour is considered equal to the monthly standard hour of the payee GEN VR HOR CONV.
- GEN VR HRS TRAV retrieves the hours effectively worked during the segment. This is calculated as the theoretical hour + additional and overtime hours – absence hours.
- GEN VR HRS PAYE retrieves the paid hours of the segment.
- GEN VR HRS PAYE CO retrieves the paid hours of the segment except for the overtime hours that are not added to this variable result.
- GEN AC HRS SMIC SG retrieves the paid hours of the segment, surcharge for additional hours included, and decrease for absence hours included. For example, 1 overtime hour paid at 125 percent counts as 1,25 paid hour. One absence hour paid at only 66 percent counts as 0,66 paid hour.
- GEN VR HRS TRAV-HS retrieves the worked hours limited to the additional hours. This means that the system does not count the overtime hours.

Regarding the calculation of GEN VR HRS PAYE, GEN VR HRS PAYE CO, and GEN AC HRS SMIC SG, these elements are equal to the standard hours of the segment plus the hours over the standard hours (additional and overtime hours) minus the absence hours. The system calculates these hours as follows:

- Standard Hours are calculated through the formula GEN FM PROR HRS. You maintain this formula and can modify it according to your needs.
- Overtime hours are retrieved by three segment accumulators. GEN AC HRS PLUS SG is used to calculate GEN VR HRS PAYE, GEN AC HRS COMP SG is used to calculate GEN VR HRS PAYE CO, and GEN AC HR CP+SP SG is used to calculate GEN AC HRS SMIC SG.
- Absence hours are calculated using the accumulators EGN AC HRS NPAY MO (to calculate GEN VR HRS PAYE and GEN VR HRS PAYE CO) and GEN AC HNPA VAL MO (to calculate GEN AC HRS SMIC SG). These accumulator values are prorated using the Customer Maintained formula GEN FM PROR ABS.

Note: Some of the elements that retrieve hours are rounded to two decimal places, while some are not rounded. Be sure to use the correct rounding rule.

Understanding Net-to-Pay Management

In Global Payroll for France, a special earning and a special deduction have been created to manage cases in which the net salary is negative.

The NET NEG AVAN earning receives an amount equal to the net negative amount, so that the final net salary is equal to 0 on the minimum. The NET NEG REPR deduction recovers the advanced amount of the previous month.

The GEN AC NET NEG accumulator stores the salary advance balance to cover the negative net.

The GEN EG NET NEG element group must be placed in the eligibility groups that you defined in order to process this calculation. The GEN SE NET NEG section must be placed in the process list after the last section that can impact the net salary. This means that you should place the GEN SE NET NEG section after the loans section on the process list provided by PeopleSoft.

Understanding Trigger Setup for France

This section discusses:

- Generate Triggers PeopleCode for dependent beneficiary and other French records.
- Segmentation triggers with earning and deduction assignments.
- Offset days for retro triggers.

Generate Triggers PeopleCode for Dependent Beneficiary and Other French Records

Global Payroll for France delivers the DEP_BENEF_FRA record with the standard Generate Triggers PeopleCode attached. This is to enable you to set up iterative, segmentation, and retro triggers for this record and to initiate iterative, segmentation, and retroactive processing in response to changes to benefits data.

The standard Generate Triggers PeopleCode follows this general format:

```
Declare Function Generate_Triggers PeopleCode FUNCLIB_GP.TRGR_FUNCTIONS FieldFormul⇒
a;

Local date &L_DT;

/*****
/*      Begin:  Generate Triggers for Global Payroll      */
*****/

Generate_Triggers(RECORD_NAME.EMPLID, &L_DT);

/*****
/*      End:    Generate Triggers for Global Payroll      */
*****/
```

For example, the Generate Triggers PeopleCode for the DEP_BENEF_FRA record is constructed as follows:

```
Declare Function Generate_Triggers PeopleCode FUNCLIB_GP.TRGR_FUNCTIONS FieldFormul⇒
a;

Local date &L_DT;

If %Component = Component.DEPEND_BENEF Then
    Generate_Triggers(DEP_BENEF_FRA.EMPLID, &L_DT);
End-If;
```

Note: Global Payroll for France does not deliver trigger definitions for the DEP_BENEF_FRA record. The Generate Triggers PeopleCode associated with this record prepares the system to respond correctly to any trigger definitions you create yourself using the Trigger Definitions (GP_TRGR_SETUP) component.

You can add the Generate Triggers PeopleCode to other French-specific records as needed and then set up your trigger definitions using the trigger definition pages in the core Global Payroll application.

Related Links

"Implementing Triggers (*PeopleSoft HCM 9.2: Global Payroll*)"

Segmentation Triggers with Earning and Deduction Assignments

In Global Payroll you can define segmentation triggers only for *effective dated* records, with one exception: you can define segmentation triggers for the *begin and end dated* earning and deduction assignment record GP_PYE_OVRD. This exception enables you to assign an earning or deduction to a payee on the Element Assignment by Payee (GP_ED_PYE) or Payee Assignment by Element (GP_ED_ELEM) components, and segment—and prorate—the element when the assignment *begin* date comes after the pay period begin date, and/or the assignment *end* date comes before the period end date.

Global Payroll for France has set up the following earnings so that they are automatically segmented and prorated (using the proration factor defined on the earning definition pages) when the assignment period covers only a portion of the pay period:

Element Name	Type	Description
SALAIRE BASE	Earning	Base Salary.
IND KILOMETR	Earning	Mileage Allowance.

Element Name	Type	Description
AN NOURRITUR	Earning	Meal Benefit in Kind.
AN AUTRES	Earning	Other Benefits in Kind.
AN VEHIC REG	Earning	Car Benefit in Kind Regular.
AN AUTRE REG	Earning	Other Benefit in Kind Regular.
PANIER J I	Earning	Day Meal Allowance.
PANIER N I	Earning	Night Meal Allowance Liable to Contributions.
AN VEHICULE	Earning	Car Benefit in Kind.
STG OBL AT	Earning	Mandatory Training Allowance.
STG OBL NAT	Earning	Mandatory Training Allowance.
STG NOBL	Earning	Non-Mandatory Training Allowance.
AFB SAL 12M	Earning	Base Salary—12 Months.
AFB SAL 13M	Earning	Base Salary—13 Months.

If you want to set up additional earnings and deductions to trigger segmentation and proration when they are assigned to payees and the assignment period covers only a portion of the pay period, access the Trigger Definitions component and add these elements to the segmentation trigger definition for the GP_PYE_OVRD record.

Related Links

"Payee Overrides and Segmentation (*PeopleSoft HCM 9.2: Global Payroll*)"

"Setting Up Trigger Definitions (*PeopleSoft HCM 9.2: Global Payroll*)"

Offset Days for Retro Triggers

When you define retro triggers on the Trigger Definitions-Field Values page, you can enter a positive or negative number in the Offset Days field to increase or decrease the retro trigger effective date in relation to the date of a field value change. For example, if you enter -1 in the Offset Days field for one of the values listed in the Field Values group box, and you retroactively enter that value into the database with an effective date of January 1, 2000, the system automatically adjusts the trigger effective date to December 31, 1999 (one day earlier). The system then processes pay periods going back to December 1999 rather than January 2000.

Global Payroll for France uses the offset days feature to define the triggers for retroactive terminations entered in the JOB record using the Action field:

Image: Trigger Definitions-Field Values page showing JOB actions that trigger retroactive termination processing for France

Trigger Definitions-Field Values page showing JOB actions that trigger retroactive termination processing for France

Trigger Definitions

Field Values

Country: FRA France

Record (Table) Name: JOB

Field Name: ACTION

Field Values			
*Sequence	*Character Value		
10	HIR	+	-
20	REH	+	-
30	PSF	+	-
40	TER	+	-

No Match on Field Value Option

☒ Do Not Trigger
☐ Trigger

Note that the offset for the termination triggers is -1.

The reason for this offset is that the PeopleSoft system considers the effective date of a termination entered in the Action field in JOB to be the first day that a payee is no longer working (in other words, the day before the termination is the last day the payee is considered active); however, the effective date of the trigger generated in response to this termination is identical to the termination date. This can create problems when the termination date in the JOB record is equal to the pay period begin date (meaning, the last day worked is the last day of the prior pay period). For example, assume that you enter a termination in JOB on February 1 after processing and closing the January calendar. In this situation, the system generates a trigger with an effective date of February 1, which is within the current period—a period in which the payee is *inactive* and is not picked up for processing. Because there is no trigger in the prior, closed period (January), this period will not be recalculated and any rules set up to generate termination payments will not be processed. To avoid this problem, Global Payroll for France sets the offset days for the *TER*, *RET*, *XFR*, and *TWP* action values in the JOB record equal to -1.

Important! If you define additional action values to trigger retroactive termination payments, you should set the offset days to -1.

Related Links

[Segmentation and Retro Triggers for Termination Processing](#)

"Trigger Definitions - Field Values Page (*PeopleSoft HCM 9.2: Global Payroll*)"

Chapter 4

Setting Up Absence Rules

Understanding Absence Setup

Before you can enter and process absences, you must complete various setup tasks. Refer to the *PeopleSoft Global Payroll* for the general setup steps. This topic describes the specific steps applicable to Global Payroll for France.

To set up absences:

1. Define work schedules and assign a schedule to each payee.
2. Define holiday schedules.
3. Run the Build Work Days by Week process to count the working days in each week.
4. Modify the delivered absence take and absence entitlement elements or create new absence elements, as needed.

A complete list of the absence take and absence entitlement elements delivered with Global Payroll for France appears at the end of this section. PeopleSoft deliver sample values for many of these elements. Most likely, you'll want to replace at least some of these values with data that is specific to your organization. This section explains how to do this.

In most cases, modifying a delivered absence rule involves updating variable or bracket elements the system uses to resolve the absence entitlement or take rules. The Variables by Category page offers a quick way to update several variable elements at the same time. To update bracket elements, use the Bracket component described in the *PeopleSoft Global Payroll*.

If you plan to create your own absence rules, use any of the supporting elements described in this section.

5. Assign absence elements to payees and process lists.

As with all primary elements, assign absence entitlement and take elements to payees and include the elements in the process lists that you use when you run the absence processes. (This step is not necessary for per-absence entitlement elements.)

PeopleSoft delivers predefined sections and process lists for absence processing. Use these, modify them, or create your own.

Related Links

[Calculating Worked Days](#)

Understanding Absence Rules for Paid Vacation

This section discusses:

- Absence elements for paid vacation.
- Absence entitlement rules for paid vacation.

Absence Elements for Paid Vacation

This table lists the absence entitlement and absence take elements that PeopleSoft delivers for paid vacation:

Absence Reason	Take Element	Entitlement Element
Standard paid vacation	CPT CG PAYES	CPE CG PAYES
Split vacation days	CPT FRACTMT	CPE FRACTMT
Seniority paid vacation	CPT ANCIENTE	CPE ANCIENTE
Anticipated paid vacation	CPT CG ANTICIP	CPE CG PAYES
Other paid vacations	CPT AUTRES	CPE AUTRES

Absence Entitlement Rules for Paid Vacation

This table lists the variables (and variable category) and brackets that you can update for paid vacation, along with the sample values that PeopleSoft delivers:

Element Name	Use	Delivered Value	Category
CPA VR MOIS DEB REF	Reference period. Stores the number of the starting month of the reference period.	6	CPA
CPA VR MAX PD DAYS	Maximum entitlement. Stores the maximum number of paid vacation days that an employee can accumulate during the reference period. The value of this variable should be consistent with the value entered for CPA VR JRS/1 SEM described later in this table.	30 (working days)	CPA
CPA VR GEST FRACT	Split vacation days (<i>conges payes pour fractionnement</i>). Specifies whether the system should track split vacation days. (1 = yes; 0 = no)	1	CPA

Element Name	Use	Delivered Value	Category
CPA VR JRS/1 SEM	Day weight. Stores the number of days to be decreased when an employee takes one week of vacation. This enables you to specify if you want to use business days or working days as the basis for counting paid vacation days.	6 working days	CPA
CPA VR J JNE MERE	Extra paid vacation days. Specifies the number of extra days of paid vacation available to employees (for example, young mothers).	0	CPA
CPA VR C 1/10	Comparison of 1/10 rule to salary upholding. Tells the system when to perform the comparison. 1 = compare at each take; 2 = compare at the last take (when all entitlement has been taken).	1	CPA
CPA VR 4 SEM	Tells the system how to consider the periods of four worked weeks for the calculation of paid vacation entitlements: either in calendar days or in business days.	JO	CPA
CPA BR DRTS	Stores the number of days of paid vacation to which an employee is entitled for a number of periods of four worked weeks.	2,5 working days and 2,08 business days for each period of 4 weeks	Not applicable
ABS BR ASS TRV LOI ABS BR ASS TRAV CC	Identifies the types of absences that are considered as effective work days when calculating entitlement and the period of time that a payee must work before eligible to accrue entitlement.	See Effective Work Days (ABS BR ASS TRV LOI, ABS BR ASS TRAV CC)	Not applicable
CPA BR JRS ANCIEN	Seniority. Stores the number of days of paid vacation to which an employee is entitled according to years of seniority.	See Extra Paid Vacation Days for Seniority (CPA BR JRS ANCIEN)	Not applicable

Element Name	Use	Delivered Value	Category
ABS BR ANC_ABS LOI ABS BR ANC_ABS CC	Identifies which types of absences are considered as effective work days when calculating seniority.	See Effective Work Days for Seniority Accrual (ABS BR ANC_ABS LOI, ABS BR ANC_ABS CC) and Effective Work Days (ABS BR ASS TRV LOI, ABS BR ASS TRAV CC)	Not applicable

Paid Vacation Reference Period (CPA VR MOIS DEB REF)

Entitlement for paid vacation is based on a *reference* year. The reference year, usually June 1 to May 31, represents the 12 previous, consecutive months during which an employee accumulates entitlement to paid vacation. Employees can use the accrued entitlement only after completing the reference year.

When you receive Global Payroll for France, the reference year is set to 6 to represent June 1, the legal begin date that applies in most cases. If you want to change the reference year, update the value of the CPA VR MOIS DEB REF variable element.

Maximum Entitlement for Paid Vacation (CPA VR MAX PD DAYS)

You can specify the maximum number of paid vacation days an employee can accumulate during the reference period. When entitlement exceeds the limit, the system rounds entitlement to the maximum value.

The maximum entitlement value is set to 30 when Global Payroll for France is delivered. To change this number, update the value of the variable element CPA VR MAX PD DAYS.

Note: The values stored by CPA VR MAX PD DAYS and CPA VR JRS/1 SEM should represent the same type of days—business days or working days.

Split Vacation Days (CPA VR GEST FRACT)

Employees may be eligible for up to two extra days of paid vacation or split vacation days (*conges payes pour fractionnement*), when they split their principal paid vacation and take some vacation days after the end of the legal vacation period (May 1 and October 31). To be granted the split vacation days, a person must take more than 12 and less than 24 consecutive paid vacation days during the legal vacation period.

If you want the system to calculate extra days of vacation for employees who qualify for split vacation entitlement, set the value of the CPA VR GEST FRACT variable to 1. Otherwise, set the value to 0. (You must also assign the entitlement element CPE FRACTMT to eligible payees.)

The entitlements for Split Vacation Days (CPE FRACTMT) is either triggered in November, or if the payee is not included in the November payroll run, it is triggered in the payee's next payroll run.

The Day Weight Factor (CPA VR JRS/1 SEM)

When a payee takes one week of paid vacation, the system can decrease entitlement by six working days (*jours ouvrables*) or five business days (*jours ouvrés*), depending on the value of the variable element CPA VR JRS/1 SEM. The delivered variable is set to 6.

The system uses the value of CPA VR JRS/1 SEM as a weighting factor so that it can correctly reduce paid vacation entitlement for both full-time and part-time employees. It also uses CPA VR JRS/1 SEM

to determine the denominator for the rate it applies when calculating positive input for the earnings and deductions associated with the absence. For example, if CPA VR JRS/1 SEM is set to 5 (for business days), the system calculates the payee's earnings for each paid vacation day by dividing the monthly base salary by the number of business days in the month. If you enter 6, the valuation is in working days.

The values stored by CPA VR JRS/1 SEM and CPA VR MAX PD DAYS should represent the same type of days—business days or working days.

Note: When a paid vacation day falls on a holiday that is normally a work day, the system first adds the weighted value to the paid days and also adds the weighted value of the vacation day to the entitlement balance.

Warning! You can choose between business days or working days only once. If you change your selection later, the consequences may be unpredictable. In addition, if you transfer entitlement accumulators from one company to another within your organization and the companies use different calculation methods for paid vacation, the entitlement results will not be accurate.

Here are two examples of the weighting factor calculations:

- Example 1: Company counts paid vacation in working days (CPA VR JRS/1 SEM = 6).

Assume that a payee normally works two days per week. The weighting for each day is three (or 6/2). Each time that the payee takes one vacation day, the system deducts three days (the weighting factor of 3 x 1 absent day).
- Example 2: Company counts paid vacation in business days (CPA VR JRS/1 SEM = 5).

Assume that a payee normally works one day a week. The weighting factor for each worked day for the payee is 5/1 or 5. When the payee takes one day of paid vacation, the system deducts five days of entitlement (5 x 1 day).

If the entitlement balance is greater than 0 and the absence take weight exceeds the balance, the system replaces the take weight with the balance accumulator. In other words, if the take exceeds the entitlement balance, the system reduces the balance to 0. For example, if the entitlement balance is 0.85 days and the payee takes a vacation day with a weight of 1.66, the balance replaces the absence weight. The balance accumulator value after this absence is then equal to 0.

Extra Paid Vacation Days (CPA VR J JNE MERE)

If you want to grant extra days of paid vacation to employees, use the variable element CPA VR J JNE MERE to specify the number of extra days. Use the element to define extra days of paid vacation for young mothers, or to grant extra paid vacation for any other reason.

CPA VR J JNE MERE returns the entitlement amount for CPE AUTRES, the entitlement element that you use to record other paid vacation take. The value of CPA VR J JNE MERE is set to 0 when you receive Global Payroll for France.

Unused entitlement for extra days of paid vacation is not carried forward at year-end.

Note: If you enter a value for CPA VR J JNE MERE, every person to whom the entitlement element CPE AUTRES is assigned accrues entitlement regardless of the person's age or gender.

The 1/10 Rule and Salary Upholding Rule (CPA VR C 1/10)

The allowance for paid vacation is determined by comparing two calculations: the 1/10 rule and the salary upholding rule. For the 1/10 rule, the basis for calculating paid vacation is one-tenth of the payee's earnings in the previous year. For the salary upholding rule, the basis is the payee's current year earnings.

Use the variable element CPA VR C 1/10 to specify whether you want the system to compare the two calculation methods for each absence take or for the last take only—the take that reduces the entitlement balance to 0.

- Set CPA VR C 1/10 to 1 to compare the calculation methods for each take and to apply the most favorable outcome to the payee. This is the delivered value.
- Set CPA VR C 1/10 to 2 to do the comparison only when the last absence occurs.

Four-Week Period Day Count (CPA VR 4 SEM)

By law, employees are entitled to 2,5 working days (*jours ouvrables*) or 2,08 business days of paid vacation for each period of four weeks of work. Working days include all weekdays except the legal day off, usually Sunday.

Determine how you want to consider the four weeks period count in days through the variable element CPA VR 4 SEM. Set this variable element to JC to calculate the period and the absence days in calendar days. Selecting JO, the system's default, forces the system to calculate the period in business days. Also, when you choose JO, each absence business day is multiplied by 28/20/FTE (full time equivalent). The number of worked days during the reference period is then divided by 28.

Entitlement for Four-Week Periods (CPA BR DRTS)

Store entitlement values for paid vacation in the bracket element CPA BR DRTS. The keys to this bracket are CPA FM CALC DRTS and LABOR AGREEMENT. For each combination of these two keys, the bracket returns the number of working days of entitlement (in the bracket, itself) and the number of business days of entitlement (in the variable CPA VR DRT OUVRES).

Note: The value of CPA VR JRS/1 SEM determines whether the system retrieves entitlement in working days (CPA VR JRS/1 SEM = 6) or business days (CPA VR JRS/1 SEM = 5).

You can update the bracket with the values for each valid combination of keys in your organization. The entitlement values that you enter should represent four-week periods. For example: 1 period of 4 weeks = 2,5 working days or 2,08 business days; 2 periods of 4 weeks = 5 days working days and 4,16 business days, and so on, up to 30 working days or 25 business days (depending on the value of the variable CPA VR MAX PD DAYS).

This table lists the sample values that PeopleSoft delivers with CPA BR DRTS:

CPA FM CALC DRTS <i>(key)</i>	LABOR AGREEMENT <i>(key)</i>	CPA BR DRTS <i>(return column for working days)</i>	CPA VR DRT OUVRES <i>(return column for business days)</i>
1		2,5	2,08
2		5	4,16

CPA FM CALC DRTS <i>(key)</i>	LABOR AGREEMENT <i>(key)</i>	CPA BR DRTS <i>(return column for working days)</i>	CPA VR DRT OUVRES <i>(return column for business days)</i>
3		7,5	6,24

The system uses proration to calculate the exact number of paid vacation days to which the payee is entitled at the end of the reference year and when an employee leaves your organization.

Effective Work Days (ABS BR ASS TRV LOI, ABS BR ASS TRAV CC)

Two periods of time affect entitlement for paid vacation:

- The period of time that an employee must work (four weeks) before he can begin to accumulate entitlement. This period is also referred to as the *opening* of entitlement.
- The reference period upon which entitlement calculations are based.

These two periods of time do not use the same definition of working days. For example, certain absences that are treated as effective work days when calculating entitlement are not considered effective work days when determining whether the four-week period has been met.

PeopleSoft delivers these bracket elements that you can update, if necessary, to specify which absences the system should interpret as effective workdays in each of these cases:

- ABS BR ASS TRV LOI specifies which absences the system should interpret as effective workdays according to the law.

The key for the bracket is TAKE CONFIG2. For each value of TAKE CONFIG2, the bracket returns two values: one for the bracket itself and one for the variable element ABS VR CP OUV LOI (0 = count as effective working day; 1 = do not count as an effective work day). The first value returned for the bracket tells the system how to interpret absences for entitlement calculations (0 = count as effective work day). The second value tells the system how to interpret absences for the opening of entitlement (the 28 day period). For the list of valid TAKE CONFIG2 values, see Understanding the User-Defined (TAKE CONFIG) Fields.

- ABS BR ASS TRAV CC specifies which absences the system should interpret as effective work days according to collective agreements.

The keys for this bracket are TAKE CONFIG2 and LABOR AGREEMENT. For each combination of these keys, the bracket returns two values: one for the bracket itself and one for the variable element ABS VR CP OUV CC. The first value returned for the bracket tells the system how to interpret absences for entitlement calculations. The second value tells the system how to interpret absences for the opening of entitlement (the 28 day period). For example, suppose that you want to interpret sick days as effective working days when calculating the opening of entitlement for collective agreement XYZ. In this case, access the bracket element ABS BR ASS TRAV CC, and for the combination of the keys TAKE CONFIG2 = MAL and Labor Agreement = XYZ, set the value returned in the variable ABS VR CP OUV CC to 0.

TAKE CONFIG2 (key)	ABS BR ASS TRV LOI (return column for entitlement calculations)	ABS VR OUV CP LOI (return column for opening of entitlement)
MAL	1	1
AT	0	1
ATRCH	1	1

TAKE CONFIG2 (key)	LABOR AGREEMENT (key)	ABS BR ASS TRAV CC (return column for entitlement calculations)	ABS VR OUV CP CC (return column for opening of entitlement)
MAL	AFB	1	1
ATRCH	AFB	1	1
AT	AFB	0	1

Extra Paid Vacation Days for Seniority (CPA BR JRS ANCIEN)

The entitlement element CPE ANCIENTE defines rules for granting extra days of paid vacation to payees based on seniority (*conges payes anciennete*). The bracket element CPA BR JRS ANCIEN returns the appropriate entitlement value for CPE ANCIENTE.

CPA BR JRS ANCIEN has the following keys:

- ABS AC RECUP ANC, an accumulator element that stores years of service.
- LABOR AGREEMENT, a system element that identifies the collective agreement.

For each combination of these keys, the bracket returns the number of business days of entitlement (in the bracket itself).

The following table shows the sample entitlement values PeopleSoft delivers with CPA BR JRS ANCIEN. You can change these values and specify seniority entitlement by collective agreement, if applicable.

ABS AC RECUP ANC (Key: Years of Seniority)	LABOR AGREEMENT (Key: Labor Agreement)	CPA BR JRS ANCIEN (Return column: Entitlement)
2		2
3		3
6		6

Note: When calculating entitlement, the system refers to the payee's years of service as of the first day of the absence. If the payee crosses a seniority boundary during his absence, the system does not increase entitlement for that absence.

Effective Work Days for Seniority Accrual (ABS BR ANC_ABS LOI, ABS BR ANC_ABS CC)

Two bracket elements define how the system should consider a payee's absences when calculating years of seniority. One bracket (ABS BR ANC_ABS LOI) specifies the legal requirements; the second (ABS BR ANC_ABS CC) specifies the requirements by collective agreement.

ABS BR ANC_ABS LOI uses the system element TAKE CONFIG2 as the key. The bracket returns one of the following values:

- 0 if the absence is not considered an effective work day.
- 1 if the absence is considered an effective work day.
- Or 0,5 if only half of the absent days are considered as effective work days (designed for a specific leave of absence).

TAKE CONFIG2 (key)	ABS BR ANC-ABS LOI (return column)
MAL	0
AT	1
ATRCH	0

ABS BR ANC_ABS CC uses the system elements TAKE CONFIG2 and LABOR AGREEMENT as keys. For each combination of these two values it returns one value for the bracket element itself (0 or 1) and one value for the variable ABS VR J PAYES CC (0 or 1).

Possible values returned by the bracket element:

- 1 if the absence is considered as effective work by the collective agreement.
- 0 if the absence is not considered as effective work by the collective agreement.

The value returned by ABS VR J PAYES CC is relevant only when the bracket returns a value of 1. Valid values returned by ABS VR J PAYES CC:

- 1 if the absence is considered as an effective work day only if it is paid.
- 0 if the absence is considered an effective work day regardless of whether it is paid.

TAKE CONFIG2 (key)	LABOR AGREEMENT (key)	ABS BR ANC-ABS CC (return column)	ABS VR J PAYES CC (return column)
MAL	AFB	1	1
AT	AFB	1	1

TAKE CONFIG2 (key)	LABOR AGREEMENT (key)	ABS BR ANC-ABS CC (return column)	ABS VR J PAYES CC (return column)
ATRCH	AFB	1	1

The Minimum Work Period

Legally, the minimum work period required before a payee can begin to earn entitlement for paid vacation is one month or four weeks of work. This is equivalent to 28 calendar days, the number that the system uses to determine when a payee meets the minimum work period. This number is stored in the element CPA VR OUV DTS; do not change it.

Fixed-Term Contracts


The delivered entitlement rules for paid vacation take into account the requirements specific to persons with fixed-term contracts (CDD). The system identifies these employees through the contract information maintained in PeopleSoft HR.

Accumulation Periods for Paid Vacation (CPE CG PAYES)

Period	Period Name	Comments
Current reference period	A+1	Current period of accumulation.
Current period (for taking vacation).	A	Entitlement calculated in A+1 is transferred to A each 31 May or 1 June.
The period before the previous period.	A-1	The balance for the current period is transferred to A-1 each 31 May or 1 June.
The period before A-1.	A-2	The balance for A-1 is transferred to A-2 each 31 May or 1 June.

Image: The four accumulation periods for paid vacation entitlement

Example: Assume today is 5 October 2000. If the reference period is 1 June to 31 May, then the relevant accumulation periods appear in the following diagram:



Global Payroll for France tracks four totals for each accumulation period: entitlement earned, entitlement balance, take, and adjustments. For each, the accumulation period is set to *Year To Date*. By default, the

Begin Option date is 1 June, meaning that the accumulation period runs from 1 June to 31 May of the following year.

Change the beginning month of the reference period by updating the variable CPA VR MOIS DEB REF. The Begin Option field refers to CPA VR MOIS DEB REF for the month. So, if the variable is set to 1, the accumulation period begins in January; if it is set to 5, the period begins in May, and so on.

Note: If you change the reference year by updating the variable element CPA VR MOIS DEB REF, the system automatically updates the accumulator periods for CPE CG PAYES.

Paid Vacation In-Lieu Allowance: Upon leaving a company, a payee is entitled to compensation in-lieu of any unused paid vacation days. Global Payroll for France automatically calculates the correct earnings for terminated payees, generating earnings for each day of unused paid vacation, seniority paid vacation, split vacation days, and other paid vacation days for which the employee is entitled to receive compensation.

Generation control triggers the calculation of allowances for paid vacation in-lieu. The system can generate up to four earnings for each period of paid vacation (if any days remain in the previous periods): A-2, A-1, A, and A+1. (The four accumulation periods are described in the previous topic.)

The system does not pay entitlement earned during the current reference period (A+1) when you select *Termination* in the Action/Reason field in Job Data, and then select misconduct (*CON*) or gross misconduct (*GMI*).

Understanding Absence Rules for Illness, Maternity, and Work Accidents

PeopleSoft delivers absence entitlement and absence take rules for illness, maternity, and work accidents. You can modify some of these absence rules by updating the variables and brackets described in this section. Entitlement for the elements discussed in this section is calculated per absence—that is, at the time of each absence event, not at a regular frequency.

This section discusses:

- Absence elements for illness.
- Absence elements for maternity leave.
- Absence elements for work accidents.
- Modifying absence rules for illness, maternity, and work accidents.

Note: The following tables present a partial list of the take elements and corresponding entitlement elements delivered for illness, maternity, and work accidents. The tables list only those take elements that you enter on the Absence Event Entry page. When required, the system uses the mapping and negative entitlement features of Global Payroll to trigger the resolution of other take rules during processing. For example, if you enter the absence take element MLT MALADIE to record sick time, once entitlement for this element has been depleted, the system automatically uses the entitlement for MLT MALADIE 2, which contains the appropriate compensation rate for the second absence period. When entitlement for MLT MALADIE 2 is depleted, the system uses the entitlement associated with MLT MALADIE 3, and so on.

See [Understanding Absence Take Elements](#).

Absence Elements for Illness

<i>Absence Reason</i>	<i>Take Element</i>	<i>Entitlement Element</i>
Illness take 1	MLT MALADIE	MLE MALADIE
Therapeutic part time	MLT MT THERP	MLE MT THERP
Authorized unpaid therapeutic	MLT MT THER N P	None
Long period illness	MLT LG MALADIE	MLE LG MALAD
Unpaid course of treatment	MLT CURE NP	None
Paid course of treatment 1	MLT CURE PAYEE	MLE CURE

Absence Elements for Maternity Leave

<i>Absence Reason</i>	<i>Take Element</i>	<i>Entitlement Element</i>
Paid maternity	MTT MATERN PAYEE	MTE MAT PAY
Unpaid maternity	MTT MATERN NON PAY	None
Paid adoption	MTT ADOPTION	MTE ADOPTION
Unpaid adoption	MTT ADOPTION NON PAY	None
Pathological leave 1	MTT PATHOLOGIQ	MLE MALADIE
Pathological leave before maternity 1	MTT PATHO AV	MLE MALADIE
Additional maternity absence	MTT CG SUP	MTE CG SUP
Paternity Leave	MTT PATERNITE	MTE PATERN

Absence Elements for Work Accidents

<i>Absence Reason</i>	<i>Take Element</i>	<i>Entitlement Element</i>
Work accident - take 1	ATT TRAVAIL	ATE TRAVAIL
Accident on way to work 1	ATT TRAJET	ATE TRAJET
Work accident relapse 1	ATT RECHUTE TRAV	ATE TRAVAIL
Accident on way to work: relapse 1	ATT RECHUTE TRAJ	ATE TRAJET
Professional disease 1	MLT PROFESSL	MLE PROFESSL

Absence Reason	Take Element	Entitlement Element
Relapse of professional disease 1	MLT PRO RECHUTE	MLE PROFESSL

Modifying Absence Rules for Illness, Maternity, and Work Accidents

Element Name	Use	Category	Related Information
ABS BR ABS VALO	Specifies whether to generate positive input for earnings and deductions in hours, business days, or calendar days.	Not applicable	See Units for Earning and Deduction Calculations
ABS BR IJSS DTS/TX, ABS BR IJSS MN/MX	IJSS entitlement. Returns entitlement values for IJSS calculations and specifies the minimum and maximum entitlement rate or amount.	Not applicable	See IJSS Entitlement and Percent Calculation
ABS VR ENF LIM IJ	Illness – IJSS entitlement calculation. Specifies the number of children that triggers a change in entitlement and rates for IJSS calculation. Works with the Dependent Data page in PeopleSoft HR.	MAL	
MAL VR CARENCE IJ	Illness waiting period. Specifies the waiting period for social security daily allowance in the event of illness.	MAL	
MAL VR CARENCE MT	Illness waiting period. Specifies the waiting period for salary upholding because of illness.	MAL	
ATR VR CARENCE IJ	Work accident waiting period. Specifies the waiting period for social security daily allowance in the event of a work accident.	ATR	
ATR VR CARENCE MT	Work accident waiting period. Specifies the waiting period for salary upholding in the event of a work accident.	ATR	
ABS BR MT SAL LOI	Salary upholding. Specifies the legal salary upholding rates for illness and work accidents.	Not applicable	See Entitlement for Salary Upholding

Element Name	Use	Category	Related Information
ABS BR MT SAL AFB	Salary upholding for AFB. Specifies the AFB salary upholding rates for illness and work accidents.	Not applicable	See Defining Entitlement for Salary Upholding
MAL VR CARENCE AFB	Illness. Specifies the maximum number of absences due to illness without a waiting period for salary upholding. For AFB only.	MAL	
ABS VR ENF LIM AFB	Illness – entitlement calculation for AFB. Specifies the number of children that triggers a change in entitlement. Works with the Dependent Data page in PeopleSoft HR. Only dependents for which the Status 9 check box is selected are counted as children.	MAL	
ABS VR PENS INVALI	Long-term illness (IJSS amount). The annual amount for the disability pension.	ABS	
ABS VR DTS MATERN	Maternity. Specifies the number of days of paid time off to which payees are entitled for maternity. Enter the value via a supporting element override.	MAT	See Entering Absences for Maternity and Adoption
MAT VR DTS ADOPT	Maternity. Specifies the number of days of paid time off to which payees are entitled for adoption.	MAT	
MAT VR DTS IJ	Maternity. Specifies the number of days of social security daily allowances for maternity.	MAT	
ATR AC SAL BASE	Work accident certificates. Specifies which earning elements contribute to the accumulator for the base salary that the system uses to produce work accident certificates.	Not applicable	Accumulator members: SAL BASE AFB SAL 12M AFB SAL 13M

Element Name	Use	Category	Related Information
ATR AC AV NAT	Work accident certificate. Identifies the earning elements that contribute to the payments-in-kind amount that the system uses when preparing work accident certificates. This amount appears in the Adv Kind & Tips field on the Frames A and B page (Salary Accessories tab). You can change the elements that are members of the accumulator.	Not applicable	Accumulator members: AN NOURRITUR AN LOGEMENT AN VEHICULE AN AUTRES
ATR AC PRIMES ATR AC FP SOUMIS ATR AC RAPPELS ATR AC PRIME TRIM ATR AC PRIME AN	Work accident certificate. Identifies the earning or deduction elements that contribute to the allowances amount (including premiums and gratuities) that the system uses when preparing work accident certificates. This amount appears in the Allowances field on the Frames A and B page (Salary Accessories tab). You can select the members of the accumulator.	Not applicable	PeopleSoft does not deliver any earning or deduction elements for allowances.

Units for Earning and Deduction Calculations (ABS BR ABS VALO)

When you run the Take process, the system creates positive input for the earning or deduction elements associated with the absence take element that was used to record the payee's absence. Although the absence event is stored in units of days or hours, you can instruct the system to use hours, business days, or calendar days when generating the positive input. For each type of absence, use the ABS BR ABS VALO bracket to define the type of units that you want to use for earnings and deductions. (The unit type must be the same for earnings and deductions.)

The key to ABS BR ABS VALO is the system element TAKE CONFIG2, which identifies the absence type (for example MAL for illness, AT for work accident, and so on).

The return columns for the bracket:

- ABS VR VALO HEURES: hours.
- ABS VR VALO JO: business days.
- ABS VR VALO JC: calendar days.

To select the units that you want the system to use, set the value of corresponding variable to 1. Set the value of the other two variables to 0.

TAKE CONFIG2 (key)	ABS VR VALO HEURES (return column)	ABS VR VALO JO (return column)	ABS VR VALO JC (return column)
MAL			1
AT			1
ATRCH			1

Note: When you enter a value of 0 in a return column, the field appears empty. For this reason, zeros are not shown in the previous table.

IJSS and Salary Upholding

When an employee is eligible to receive a daily IJSS allowance during an absence, the employer must *uphold* the employee's salary—that is, the employer must pay the current salary minus the amount of the allowance.

The take elements that PeopleSoft delivers for illness, work accidents, and maternity are all mapped to take elements that automatically trigger IJSS calculations, when appropriate. When you record the absence on the Absence Event Entry page, the system checks to see whether the payee meets the requirements for receiving an IJSS allowance. If the payee does meet the requirements, the system applies salary upholding.

The system calculates a payee's eligibility for IJSS entitlement only once, at the original begin date of the absence. If a payee is not eligible for IJSS, the system does not calculate IJSS, nor does it uphold the employee's salary.

Should you need to, you can manually update the opening of entitlement for employees by entering a supporting element override that sets the formula that triggers the opening of IJSS (ABS FM TEST OUV IJ) to 1.

The system calculates a payee's daily allowance for IJSS until entitlement for salary upholding is depleted.

Some employers can choose to receive an employee's daily social security allowance and then pay the allowance to the payee with the payee's salary. The term *subrogation* is used to refer to this method of paying IJSS. Global Payroll for France does not manage subrogation of IJSS allowances.

The system uses two bracket elements for IJSS calculations, ABS BR IJSS DTS/TX and ABS BR IJSS MN/MX.

The ABS BR IJSS DTS/TX bracket stores the number of days of entitlement due to an employee based on the type of absence and the number of children the employee has. One of the two keys for this bracket is the variable ABS VR NOM PRISE, which is populated by a formula and stores the name of the absence that's being processed (MALADIE for illness, LG MALADIE for long term illness, TRAVAIL for work accident, CURE for course of treatment, PATHOAV for pathological leave before maternity, and PATHOAP for pathological leave after maternity). The other key is the formula ABS FM ENF BR IJ, which returns either 0 or 3 (entitlement changes when a payee has over three children). For each combination of the two keys, the bracket returns the number of days of entitlement and the appropriate percent to apply. It can store up to three entitlement amounts and three percentages for each combination of keys. The return columns for the bracket are as follows:

- ABS BR IJSS DTS/TX (the bracket itself): the number of days of entitlement for the first rate applicable to IJSS.
- ABS VR IJ TX1: the first rate.
- ABS VR IJ DTS2: the number of days of entitlements for the second rate.
- ABS VR IJ TX2: the second rate.
- ABS VR IJ DTS3: the number of days of entitlements for the third rate.
- ABS VR IJ TX3: the third rate.

The ABS BR IJSS MN/MX uses the same keys as ABS BR IJSS DTS/TX, but returns for each combination of these keys the maximum and minimum limits to apply to the daily allowance. Limits are stated as rates or amounts, as defined by law. The return columns for the bracket are as follows:

- ABS BR IJSS MN/MX (the bracket itself): the minimum rate for the first entitlement rate applicable to IJSS.
- ABS BR IJ MAXI1: the maximum for the first entitlement rate (it calculates the daily allowance as follows: ABS BR IJ MAXI1 x theoretical A ceiling x 12).
- ABS VR IJ MINI2: the minimum for the second entitlement rate.
- ABS VR IJ MAXI2: the maximum for the second entitlement rate (it calculates the daily allowance as follows: ABS BR IJ MAXI2 x theoretical A ceiling x 12).
- ABS VR IJ MINI3: the minimum for the third entitlement rate (a monetary variable).
- ABS VR IJ MAXI3: the maximum for the third entitlement rate (it calculates the daily allowance as follows: ABS BR IJ MAXI3 x theoretical A ceiling x 12).

IJSS allowances are based, in part, on the number of children that are dependent on the payee. A child is considered a dependent until age 16 (age 18 if the child is an apprentice, age 20 if the child is a student).

Use the Dependent Information - Personal Profile page to indicate which children qualifies as a dependent. If you update dependent information during the time that a payee is absent, the system automatically adjusts the calculation for the IJSS allowance.

To identify dependent children who meet the criteria for IJSS entitlement:

1. Access the Dependent Information - Personal Profile page in PeopleSoft HR.

The navigation to this page is Workforce Administration, Personal Information, Dependent Information.

2. Select the French flag at the bottom of the page to display additional fields for France.
3. Select the IJSS Calc check box.

The variable element ABS VR ENF LIM IJ specifies the number of dependent children that triggers a change in the calculations for IJSS entitlement. The variable is set to 3 when delivered. You can update the number if the legal limit changes.

In most cases, separate waiting periods must be met before IJSS allowances are paid and salary upholding begins. PeopleSoft uses variable elements to define the waiting periods. The delivered values are shown

in the table at the beginning of the section entitled Modifying Absence Rules for Illness, Maternity, and Work Accidents. You can update the values if the legal limits change.

PeopleSoft delivers two bracket elements that define the rates that apply, by seniority, to salary upholding for illness and work accidents: ABS BR MT SAL LOI, which identifies the legal requirements, and ABS BR MT SAL AFB, which specifies the AFB requirements. These elements are not maintained by PeopleSoft, so you can update either one, if necessary.

If you have additional collective agreements, you can create new brackets, using the delivered brackets as models. Name each bracket ABS BR MT SAL XXX (where XXX represents the code for your collective agreement). Use the same return columns as those used by the ABS BR MT SAL LOI and ABS BR MT SAL AFB:

- ABS BR MT SAL XXX (XXX represents your collective agreement): stores the number of days of entitlement for the first applicable percent for salary upholding.
- ABS VR MAINT %1: stores the first applicable percent for salary upholding.
- ABS VR MAINT JRS2: stores the number of days of entitlement for the second applicable percent for salary upholding.
- ABS VR MAINT %2: stores the second applicable percent for salary upholding.
- ABS VR MAINT JRS3: stores the number of days of entitlement for the third applicable percent for salary upholding.
- ABS VR MAINT %3: stores the third applicable percent for salary upholding.
- ABS VR MAINT JRS4: stores the number of days of entitlement for the fourth applicable percent for salary upholding.
- ABS VR MAINT %4: stores the fourth applicable percent for salary upholding.

ABS VR NOM PRISE (Key)	GEN VR AN ANC (Key)	ABS BR MT SAL LOI	ABS VR MAINT %1	ABS VR MAINT JRS2	ABS VR MAINT %2
MALADIE	0	0	90	0	66,66
MALADIE	3	30	90	30	66,66
MALADIE	8	40	90	40	66,66

Note: No sample data is delivered for ABS VR MAINT JRS3, ABS VR MAINT %3, ABS VR MAINT JRS4, or ABS VR MAINT %4.

ABS VR NOM PRISE (Key)	ABS VR ENF<16 (Key)	GEN VR AN ANC (Key)	ABS BR MT LAL LOI	ABS VR MAINT %1	ABS VR MAINT JRS2	ABS VR MAINT %2
MALADIE			0	100	0	50
MALADIE		1	60	100	60	50

ABS VR NOM PRISE (Key)	ABS VR ENF<16 (Key)	GEN VR AN ANC (Key)	ABS BR MT LAL LOI	ABS VR MAINT %1	ABS VR MAINT JRS2	ABS VR MAINT %2
MALADIE		5	90	100	90	50
MALADIE	1	0	0	100	0	50
MALADIE	1	1	60	100	150	50
MALADIE	1	5	90	100	180	50

Note: No sample data is delivered for ABS VR MAINT JRS3, ABS VR MAINT %3, ABS VR MAINT JRS4, or ABS VR MAINT %4.

Global Payroll for France delivers (but does not maintain) the formula element ABS FM BRACK DTS, which enables you to tell the system which bracket should return the upholding rates for the collective agreement. To update the formula, add the following rows to the end of it:

```
IF LABOR AGREEMENT = XXX (where XXX equals the code for the collective agreement) THEN
ABS BR MT SAL XXX >> ABS FM BRACK DTS ELSE ABS BR MT SAL LOI >> ABS FM BRACK
DTS END IF
```

After a payee receives an IJSS allowance for six consecutive months, Social Security requires some additional information from the employer to determine if the payee remains eligible for payments. Provide this information by producing a certificate for Social Security.

If CPAM reclassifies an illness leave as long term, use the Absence Event Entry page to change the end date of the first absence event to the date before the start of the long-term illness period. Enter the long-term illness with the correct begin date and end date (if already known), which triggers retroactive processing when you run the payroll process for the affected payroll periods.

AFB Rules

This topic applies only if your organization is a member of the *Association Française des Banques* (AFB). It describes absence rules specific to the AFB collective agreement that Global Payroll for France supports.

According to the AFB collective agreement, a payee becomes subject to a waiting period for absences due to illness only after reporting a certain number of absence events. The variable MAL VR CARENCE AFB identifies this number and is set to 3 when delivered. You can update this number if the legal limit changes.

Use the Dependent Information - Personal Profile page to indicate which children qualify as dependents according to AFB rules.

To identify dependent children who meet the criteria for AFB entitlements:

1. Access the Dependent Information - Personal Profile page in PeopleSoft HR.

The navigation to this page is Workforce Administration, Personal Information, Dependent Information.

2. Enter the correct birthdate.

3. Select the French flag at the bottom of the page to display additional fields for France.
4. Select the Collective Agmt check box.

The AFB collective agreement institutes an additional paid leave after the maternity leave. The additional leave is equal to 45 days upheld at 100 percent of the base salary or to 90 days upheld at 50 percent. Use the take element MTT CG SUP to record the absence on the Absence Event Entry page. Once entitlement for the 45 days has been used, the system automatically uses the entitlement balance for the take element MTT CG SUP2.

Related Links

"Defining Formula Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

[Printing Wage Certificates](#)

Understanding Rules for Other Absences

This topic describes the absence entitlement and take elements that PeopleSoft delivers for absences due to special family leaves, unpaid absences, public holidays, AFB absences, time-off entitlements for staff representatives, and other absences.

This section discusses:

- Absence elements for family leave and other personal leave.
- Absence elements for unpaid absence.
- Absence elements for work council, union, and staff representative absence.
- Modifying absence rules for other absences.

Absence Elements for Family Leave and Other Personal Leave

Absence Reason	Take Element	Entitlement Element
Birth leave	EVT NAIS/ADOP	EVE NAIS/ADO
Payee's marriage	EVT MAR SAL	EVE MAR SAL
Marriage of payee's child	EVT MAR ENF	EVE MAR ENF
Death of child	EVT DEC ENFANT	EVE DEC ENFA
Death of husband or wife	EVT DEC CONJOINT	EVE DEC CONJ
Death of parent	EVT DEC PARENT	EVE DEC PARE
Death of brother or sister	EVT DEC COLLATERAU	EVE DEC FRER
Death of step parent	EVT DEC BEAUX PARE	EVE DEC BPA
Child illness	EVT ENF MAL	EVE ENF MALA

Absence Reason	Take Element	Entitlement Element
Child illness AFB	EVT ENF MAL AFB	EVE EML AFB
Breast feeding	EVT ALLAITEMENT	EVE ALLAITEM
Moving	EVT DEMENAGEMENT	EVE DEMENAGE
Unpaid sabbatical training	ABT CIF NONPAYE	None

Absence Elements for Unpaid Absence

Absence Reason	Take Element	Entitlement Element
Unauthorized unpaid absence	ABT AB N AUT N PAY	None
Authorized unpaid leave (<i>conge sans solde</i>)	ABT AUT NON PAYEE	None
Suspension for protective reason (<i>mise a pied conservatoire</i>)	ABT MAP CONSER	None
Suspension for disciplinary reason (<i>mise a pied disciplinaire</i>)	ABT MAP DISCIPLI	None
Strike	ABT GREVE	None
Parental childcare - unpaid	ABT CONGE PARENTAL	None
Adoption	ABT ADOPTION	None

Absence Elements for Work Council, Union, and Staff Representative Absence

Absence Reason	Take Element	Entitlement Element
Work council without entitlement	REP CE SS DT	None
Work council time off	REP CE	REE CE
Staff representative hours	REP DELEGUE PERSON	REE DELEGUE
CHSCT member hours	REP CHSCT	REE CHSCT
Trade union representative hours	REP DEL SYNDICAL	REE DEL SYND

Modifying Absence Rules for Other Absences

In some cases, you can modify the rules that PeopleSoft delivers for other time off.

<i>Element Name</i>	<i>Use</i>	<i>Delivered Values</i>	<i>Category</i>
GEN AC JOUR ANC	Enables you to adjust a payee's seniority for absences recorded in PeopleSoft HR.	None	Not applicable
ABS BR C.FAMIL1	Specifies days of entitlement for death of a family member, by collective agreement.	See Family Leave and Personal Leave	Not applicable
ABS BR C.FAMIL2	Specifies days of entitlement for births, weddings, and other family-related events by collective agreement.	See Family Leave and Personal Leave	Not applicable
EVE VR DEC ASCENDA	Specifies the legal minimum days of entitlement for death of a parent.	1	ABS
EVE VR DEC B,PAREN	Specifies the legal minimum days of entitlement for death of a step-parent.	1	ABS
EVE VR DEC CONJOIN	Specifies the legal minimum days of entitlement for death of a spouse.	2	ABS
EVE VR DEC ENFANT	Specifies the legal minimum days of entitlement for death of a child.	2	ABS
EVE VR DEC FRERE	Specifies the legal minimum days of entitlement for death of a brother or sister.	1	ABS
EVE VR MAR SAL	Specifies the legal minimum days of entitlement for payee's wedding.	4	ABS
EVE VR MAR ENF	Specifies the legal minimum days of entitlement for wedding of payee's son or daughter.	1	ABS
EVE VR NAIS/ADOP	Specifies the legal minimum days of entitlement for birth or adoption.	3	ABS
EVE VR EVE MAL DN	Specifies the legal minimum standard days of entitlement for child's illness.	3	ABS
EVE VR EVE MAL DM	Specifies additional days of entitlement for child's illness.	5	ABS
EVE VR DEMENAGEMEN	Specifies days of entitlement for moving.	0	ABS

<i>Element Name</i>	<i>Use</i>	<i>Delivered Values</i>	<i>Category</i>
REE VR CE	Specifies the number of paid hours allowed for work council obligations.	20	ABS
REE VR CHSCT	Specifies the number of paid hours allowed for CHSCT obligations.	10	ABS
REE VR DEL SYNDICA	Specifies the number of paid hours allowed for trade union representative obligations.	20	ABS
REE VR DELEGUE PER	Specifies the number of paid hours allowed for staff representative obligations.	15	ABS

Adjusting Seniority for Absences Entered in PeopleSoft HR (GEN AC JOUR ANC)

Entitlement for certain types of absences covered in this section is based on a payee's seniority. When the system determines a payee's seniority, it does not take into account any absences that you enter only through PeopleSoft HR, such as leave with pay. If you want the system to adjust seniority to reflect these absences, adjust the accumulator GEN AC JOUR ANC, which stores the number of days that a payee is present during a segment.

Family Leave and Personal Leave (ABS BR C.FAMIL1 and ABS BR C.FAMIL2)

PeopleSoft delivers two bracket elements that store entitlement values, by collective agreement, for family events, such as births, adoptions, weddings, and deaths: ABS BR C.FAMIL1 and ABS BR C.FAMIL2. The key to these brackets is LABOR AGREEMENT.

The sample entitlement values delivered with the brackets represent AFB requirements. AFB entitlement applies only to payees who have completed at least one year of service. Employees with less than one year of service accrue the minimum legal entitlement that is defined by the variables (that begin with EVE VR) listed in the previous table. Use the Variables by Category page to adjust the legal values if they change.

When it retrieves entitlement for a family-related absence event, the system checks to see if the AFB collective agreement applies. If it applies, the system triggers the appropriate bracket listed above, which overrides the existing values of the variables. If there is no AFB collective agreement, the system retrieves the existing value of the same variable (for example, EVE VR MAR SAL).

Add entitlement values for other collective agreements, as needed.

ABS BR C.FAMIL1 returns entitlement values for death of a family member:

- EVE VR DEC ASCENDA: death of a parent.
- EVE VR DEC B.PAREN: death of a mother-in-law or father-in-law.
- EVE VR DEC CONJOIN: death of spouse.
- EVE VR DEC ENFANT: death of a son or daughter.

- EVE VR DEC FRERE: death of a brother or sister.

:

LABOR AGREEMENT (key)	EVE VR DEC ASCENDA (return column)	EVE VR DEC B. PAREN (return column)	EVE VR DEC CONJOIN (return column)	EVE VR DEC ENFANT (return column)	EVE VR DEC FRERE (return column)
AFB	3	3	5	5	2

ABS BR C.FAMIL2 returns entitlement values for births, marriage, moving, and child illness:

- EVE VR MAR SAL: payee's wedding.
- EVE VR MAR ENF: wedding of payee's son or daughter.
- EVE VR NAIS/ADOP: birth or adoption.
- EVE VR ENF MAL DN: standard entitlement for child's illness (AFB specific).
- EVE VR ENF MAL DM: increased entitlement for child's illness (AFB specific).
- EVE VR DEMENAGEMEN: moving.

LABOR AGREEMENT (key)	EVE VR MAR SAL (return column)	EVE VR MAR ENF (return column)	EVE VR NAIS/ADOP (return column)	EVE VR ENF MAL DN (return column)	EVE VR ENF MAL DM (return column)	EVE VR DEMENAGEMEN (return column)
AFB	5	2	3	3		2

Note: The system does not check whether payees meet the three-month seniority requirement for paid time off due to the death of a brother, sister, or in-law.

The entitlement for absences related to children is as follows:

- Child's Illness.

Parents are entitled to one unpaid absence leave per calendar year to take care of sick children. Entitlement is as follows:

- 3 days for employees who have 1 dependant child under age 14.
- 6 days for employees who have 2 dependant children under age 14.
- 9 days for employees who have 3 or more dependant children under age 14.

- Hospitalization of Child (AFB).

Two additional paid days are granted during the calendar year if a dependant child under age 14 is hospitalized. Before recording the absence, use the Supporting Element Overrides page to enter the value for EVE VR ENF MAL HOS. Use the take element EVT ENF MAL AFB to enter this absence.

- Breast-feeding period (*période d'allaitement*).

Young mothers who breast feed a child up to one year after the child's birth are eligible for one paid hour per worked day for breastfeeding. Use the take element EVT ALLAITEMENT to record paid time off taken for breastfeeding.

Unpaid Leave

PeopleSoft delivers these absence rules for unpaid leave:

- Childcare Leave (*congé parental d'éducation*).

Employees with more than one year of seniority at the birth or adoption of their children are eligible for unpaid parental childcare leave, which is granted until the child's third birthday. When you use the absence take ABT CONGE PARENTAL to record the absence, the system generates positive input for the parental deduction PAR DED JC, PAR DED JO, or PAR DED H (depending on the units you selected for valuation).

During childcare leave, the payee acquires half of his absence period as entitlement for the seniority calculation.

During childcare leave, half of the payee's absence period is considered as effective work time when determining entitlement for seniority.

- Adoption Leave.

Parents who adopt children who are over age 3 may be eligible for unpaid parental adoption leave. Use the absence take element ABT ADOPTION to enter these absences. The system generates positive input for the authorized unpaid leave deduction CSS RET XX (where XX represents JC, JO, or H, depending on whether you are using calendar days, working days, or hours as units).

The system does not verify the child's age; however, it does require that you select the Manager Approved check box when entering the absence on the Absence Event Entry page.

- Authorized Unpaid Absences.

Use the ABT AUT NON PAYEE take element to record the following types of unpaid absences:

- Jury duty (*juré d'assises*).
- Ability assessment (*bilan de compétence*).
- Councilor of the employees (*conseiller des salariés*).
- Absence for company creation (*absence création d'entreprise*).
- Absence for being with an end-life patient (*congé d'accompagnement fin de vie*).

Work Council, Union, and Staff Representative Obligations (REE VR CE, REE VR CHSCT, REE VR DEL SYNDICA, REE VR DELEGUE PER)

Staff representatives (*delegates du personnel*), members of the work council (*comite d'entreprise*), trade union representatives (*délégués syndicaux*), and members of the CHSCT are entitled to some paid hours for executing their mandates. PeopleSoft identifies these hours on the subsidiary payslip, but not on the payslip itself.

If the number of hours taken exceeds entitlement, a regularization earning element (RPP VAL RG H) calculates the complement. This earning does not appear on the payslip, but does appear on the supplementary payslip.

You can update the entitlement hours for work council (REE VR CE), CHSCT (REE VR CHSCT), trade union representative (REE VR DEL SYNDICA), or staff representative (REE VR DELEGUE PER), if necessary.

Travel time (*délai de route*) and specific meetings do not decrease entitlement. The Take Config1 field is populated in the event take with *DL* for journey duration and specific meetings.

Given that few employees have that kind of mandate, in the element group ABS EG AUTRES, all the entitlements and takes related to those absences have been set to the By Payee element assignment.

Entitlements	Takes
	REP CE SS DT
REE CE	REP CE
REE DEL PERS	REP DELEGUE PERSO
REE CHSCT	REP CHSCT
REE DEL SYND	REP DEL SYNDICAL

For those employees who have one of those mandates, assign the correct element and entitlement (if any) corresponding to the desired mandate to allow their calculations by the system. This assignment is done on the Entitlement/Take Assignment page. Use the date of the mandate as the begin and end dates.

Note: In case of an absence leave, also enter your absence take in the Absence Event Entry page.

Other Absences

Descriptions of other absence rules delivered with Global Payroll for France:

- Authorized Paid Leave.

When you cannot or do not want to identify the reason for a paid absence, use the absence take element ABT AUT ABS PAYEE. The entitlement element ABE AUT ABS PAYEE retrieves 1 for each day of the absence so that each day is paid.

- Sabbatical Leave (*congé sabbatique*).

Payees with more than three years seniority in their company and more than six years of professional activity are eligible for unpaid sabbatical leave. Sabbatical leave cannot be less than 6 months or over 11 months. Use the absence take element ABT SABBATIQ to enter these absences. The system generates positive input for the Authorized Unpaid Leave deduction; however, it does not check to see whether the payee meets the requirements for years of seniority or professional activity, nor does it monitor the length of the sabbatical.

Payees do not earn entitlement for the seniority calculation during a sabbatical leave.

- Sabbatical Training (*congé individuel de formation*).

During a sabbatical taken for training, a payee receives some compensation from his employer, who is then reimbursed by the FONGECIF. The payee is entitled to paid vacation during the sabbatical training and his seniority is not reduced by the amount of time spent on sabbatical.

If the FONGECIF compensates only part of the payee's salary, part of the absence may be unpaid. In this case, you may want to create a second employee record number for the payee. For the first record number, set up a part-time schedule for the payee; for the second employee record number, set up a part-time schedule for sabbatical training.

Enter the take for sabbatical training using the employee record number dedicated to sabbatical training. Then, when the employee takes a paid vacation, enter the vacation take using the employee record number dedicated to the regular part-time schedule.

- Time Off in Lieu of Compensation.

When an eligible payee works more than a standard number of hours per week, employers are obligated to pay overtime on the extra time worked. If the extra time exceeds a second limit, the employer may have to give the payee time off in lieu of payment (*repos compensateur*).

The entitlement element ABE REP COMP, which stores the bonus hours that an employee can recover in time off rather than pay, is populated automatically by the accumulator HRS AC RCOMP EX PP, which stores days and not hours. The accumulator is first fed, the entitlement is equal to the value in the accumulator. Then when additional days are added to the accumulator, only the difference between the previous value and the new value is triggered as the new entitlements.

Employees can take time off in lieu in increments of half days or full days.

Use the take element ABT REP COMP to record time off on the Absence Event Entry page. Select the Half Day check box when reporting half-day absences; otherwise, entitlement is reduced by one day.

In case of termination, the payment of the unused completed and uncompleted hours is automatically triggered. The earning element RCL VAL JO is used in this allowance.

Note: The system does not manage the loss of entitlement if a payee does not take time off in lieu of compensation during the two months following the acquisition of the entitlement. You can use adjustments to manage this point.

Notice Period Not Worked

During a notice period, employers can pay an employee for time that is not worked. During this period, the employee continues to accrue entitlement for paid vacation, seniority calculation, and other time off. Premiums and allowances that depend on the payee's presence, such as transportation premiums and meal tickets (ticket restaurant), are not given to the payee during the non-worked period. To record a notice not worked absence, use the absence take element ABT PREAV N F.

Related Links

[Understanding Overtime Payments](#)

Understanding User-Defined (TAKE CONFIG) Fields

The Calculation page that you use to define take elements includes four user-defined fields, which populate the system elements TAKE CONFIG1 through TAKE CONFIG4. The TAKE CONFIG fields provide additional instructions to the system during the Absence process.

Although you should not modify the user-defined fields for the take elements delivered with Global Payroll for France, you may want to follow the same usage conventions if you define your own take elements:

- TAKE CONFIG1 identifies the type of take followed by the sequence number of the take if other takes are used when the entitlement balance reaches 0 (the Take with Other Absence field on the take element's Negative page identifies these take elements). For example, the first take element for illness, MLT MALADIE, has the code MAL1.

The TAKE CONFIG1 field works in conjunction with the offset formula identified on the Day Formula page. The offset formula decreases the beginning entitlement balance by the number of units that have already been paid for the same type of absence. For example, suppose that a payee who is entitled to 30 paid days for illness is ill for 15 days. He uses 15 days of entitlement. Two months later, the payee is out sick again for 20 days. When the system processes the second absence, it retrieves the 30 days of entitlement, then decreases it by the number of days that have already been paid for illness during the past 12 months. (It does not decrease entitlement for absences due to work accidents, family events, or any reason other than illness.) It determines the number of days to decrease entitlement by looking for absence takes where the TAKE CONFIG1 field is set to *MAL1*.

- TAKE CONFIG2 identifies the absence type (*MAL* for illness, *AT* for work accident, *MAT* for maternity, and so on). These codes are used in several brackets related to seniority calculations (ABS BR ANC-ABS LOI and ABS BR ANC-ABS CC) and paid vacation calculations (ABS BR ASS TRV LOI and ABS BR ASS TRAV CC). They are also used within ABS BR ABS VAL, the bracket that designates the units you want the system to use when generating positive input for earnings and deductions.
- TAKE CONFIG3 identifies which absence take the system is processing: the first in a sequence, the last in a sequence, or a single take, if there is only one.

For example, Global Payroll for France delivers a sequence of four absence take elements for illness. The first take, MLT MALADIE, has a TAKE CONFIG3 code of *1* and the last take, MLT MALADIE4, has a code of *DER*. As another example, take element EVT MAR SAL has a code of *IDER* to indicate that it is the only take element for this type of absence.

The formula ABS FM ALIM AC ABS uses the value in the TAKE CONFIG3 field to trigger other formulas. For example, if TAKE CONFIG3 equals *1* or *IDER*, the formula ABS FM ALIM AC NTR is triggered. This formula calculates the unworked units (hours, business days, and calendar days) and stores the units in accumulators.

If TAKE CONFIG3 equals *DER* or *IDER*, the formula ABS FM ALIM AC NPA is triggered. This formula calculates the unpaid units (hours, business days, and calendar days) and stores them in accumulators.

Related Links

[Understanding Absence Take Elements](#)

Calculating Worked Days

To set up calculation of worked days, use the Maintain Work Day Weights FRA (GPFR_WORKED_DAYS) and Weigh Weekly Work Days FRA (GPFR_WRK_RUNCNTL) components.

This section provides an overview of the Build Worked Days by Week process and discusses how to:

- Launch the Build Worked Days by Week process.
- View number of worked days.

Pages Used to Calculate Worked Days

Page Name	Definition Name	Navigation	Usage
Build Worked Days	GPFR_WRK_RUNCTL	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Schedules, Weigh Weekly Work Days FRA, Build Worked Days	Launch the GPFR_WRK_AE process that determines the number of worked days in each week for the period of time that you specify.
Maintain Work Day Weights FRA	GPFR_WORKED_DAYS	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Schedules, Maintain Work Day Weights FRA, Maintain Work Day Weights FRA	View the number of worked days for the period that you selected to run the Build Worked Days by Week process.

Understanding the Build Worked Days by Week Process

The Build Worked Days by Week Application Engine process (GPFR_WRK_AE) calculates the number of business days for each week that falls within the dates that you specify. The system considers that a day has been worked if the number of scheduled hours is greater than zero. The paid vacation absence process uses the number of business days per week to calculate the day weight used to process paid vacation take.

Before you can run this process, you must create schedules in Global Payroll or PeopleSoft Time and Labor and run the Build Schedule Calendar process.

Typically, you run this process only after you run the Build Schedule Calendar process. For example, if you build schedule calendars at the beginning of the year for January 1 to December 31, you should run the Build Worked Days by Week process for the same period. If you update schedules during the year and rebuild the calendars, run the Build Worked Days by Week process again so that the system always has an accurate description of all work days.

Run the Build Worked Days by Week process for every schedule.

Related Links

"Understanding Work Schedules (*PeopleSoft HCM 9.2: Time and Labor*)"

Build Worked Days Page

Use the Build Worked Days page (GPFR_WRK_RUNCTL) to launch the GPFR_WRK_AE process that determines the number of worked days in each week for the period of time that you specify.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Schedules, Weigh Weekly Work Days FRA, Build Worked Days

Image: Build Worked Days page

This example illustrates the fields and controls on the Build Worked Days page. You can find definitions for the fields and controls later on this page.

Schedule ID

Enter the schedule that you want the system to read when calculating the number of worked days per week.

From date

Enter the date of the first Monday that you want the system to include in the count of worked days.

To date

Enter the date of the last Monday that you want the system to include in the count of worked days.

Maintain Work Day Weights FRA Page

Use the Maintain Work Day Weights FRA page (GPFR_WORKED_DAYS) to view the number of worked days for the period that you selected to run the Build Worked Days by Week process.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Schedules, Maintain Work Day Weights FRA, Maintain Work Day Weights FRA

Image: Maintain Work Day Weights FRA page

This example illustrates the fields and controls on the Maintain Work Day Weights FRA page. You can find definitions for the fields and controls later on this page.

Effective Date

Enter the effective date for the schedule. This is start of the week for which work days were counted. The Effective Date must fall on a Monday.

Note: You see one row of data if each week within the schedule has the same number of work days. If the schedule includes work weeks of varying lengths (such as a three-day work week followed by a five-day work week), a separate row of data appears whenever the length of the work week changes.

Worked Days of the Week

Enter the number of work days for the week indicated.

Changing the number of worked days in this field may cause unintended results.

Assigning Absence Elements to Payees and Process Lists

To resolve absence elements during processing, you must associate absence elements with payees and the process lists you use to run the absence process. This section discusses how to:

- Associate absence elements with payees.
- Associate absence elements with process lists.

Associating Absence Elements with Payees

With the exception of entitlement elements that are resolved per absence, you must individually assign the delivered take and entitlement elements to payees using the Entitlement/Take Assignment page, or assign element groups that contain the absence elements to the eligibility groups that are associated with payees' pay groups.

PeopleSoft delivers, but does not maintain, three element groups for absences. Use these groups as they are delivered or modify them to meet your needs. To view a list of the elements within each element group, use the Element Groups component.

Element Groups for Absences

:

Description of Element Group	Name
Paid vacation	CPA EG CG PAYES
Illness, work accident, and maternity	ABS EG MAL/AT/MAT
Other absences	ABS EG AUTRES

Note: The element group GEN EG IJSS includes the deduction elements used for calculating IJSS allowances and should be assigned to payees that are eligible to receive IJSS allowances for absences.

General Guidelines for Assigning Absence Elements

The following guidelines apply:

- Senior executives (*mandataires sociaux*) that do not have working contracts are not entitled to paid vacation. Do not assign these individuals to an eligibility group that includes entitlement elements for paid vacations.
- Employees that work in discontinuous jobs may not be eligible for the standard rules for paid vacation if they receive entitlement for paid vacation through certain funds (*caisses de congés payés*). Do not assign these payees to an eligibility group that includes entitlement elements for paid vacation. PeopleSoft does not deliver rules to manage contributions to *caisses de congés payés*.

Associating Absence Elements with Process Lists

PeopleSoft delivers a process list named ABS PROCESS LIST that you can use to run the absence process. The delivered process list combines the entitlement and take processes.

Use ABS PROCESS LIST as is, modify the list to meet your needs, or create your own process lists for absence processing.

Purpose	Section Name
Initialization	AB SE INT
Paid vacation	CPA SE CG PAYES
Paid vacation - positive input	CPA SE CG PAYES PI
Illness, work accident, maternity	ABS SE MAL/AT/MAT
Illness, work accident, maternity - positive input	ABS SE MAL/AT/MT PI

<i>Purpose</i>	<i>Section Name</i>
Other absences	ABS SE AUTRES
Other absences - positive input	ABS SE AUT PI

Note: The section ABS SE RET VAL, which is included in the delivered payroll process list REGLEMENTAIRE PAIE, includes the earning and deduction elements associated with the delivered absence take elements. The section IND SE FIN CONTR includes the earning elements for paid vacation that are resolved when a payee is terminated.

Defining URSSAF Contributions

Understanding URSSAF Contributions

URSSAF are regular contributions paid by both the payee and employer to cover retirement, sickness, workplace accidents, family benefits, old age benefits, solidarity, and FNAL. Most URSSAF contributions are calculated as a percentage of a *funding base* (calculation rule = percentage x base). In some cases, contributions may apply to a reduced base, and some contribution classes may qualify for reduced rates or exemption from paying contributions.

This section discusses:

- Bases.
- Rates.
- Ceilings.
- Contribution classes.

Bases

The funding base for URSSAF deductions is derived from the gross pay accumulator URS AC BRUT SG. However, the funding base is defined not as an accumulator but as a formula or variable and may differ in value from the gross pay accumulator. For example, in the case of journalists, the formula used to calculate URSSAF contributions can reduce the funding base below the amount of the gross pay accumulator. And in cases where deductions are limited to a ceiling, formulas can be used to limit the funding base to the ceiling.

This section discusses:

- Funding bases limited to a ceiling.
- Funding base for payees moving from a non-standard class to a standard class.
- Lump sum bases.

Funding Bases Limited to a Ceiling

Some funding bases are limited to a ceiling—in other words, contributions are calculated as a percentage of a limited funding base, rather than applying to the entire base. The calculation used to determine when the ceiling has been reached is a monthly calculation. The system adds all the gross of the year and compares this sum to the sum of all the monthly ceilings. If the sum of the gross is greater than the sum of the ceilings, the system limits the annual funding base to the ceiling. The system then deducts the funding base of the previous month on which the payee has already contributed to obtain the monthly funding base.

Global Payroll for France uses a generic formula GEN FM CALC LIMIT to calculate monthly funding bases limited to a ceiling.

Funding Bases for Payees Moving From a Non-Standard Class to a Standard Class

In the case of certain contracts, when payees' earnings exceed a predefined limit, they may no longer be eligible for the special URSSAF rate assigned to their class. When these limits are broken, they pay another rate, assigned to a different contribution class. This new class is referred to as the *standard class* because it does not contain the exempted rates of the original class but the *normal* rates of the standard *régimes*.

To calculate the maximum payees can make and still remain within their normal *régime*, Global Payroll for France uses the variable GEN VR SMIC L VG P. To calculate the earning ceiling, the system multiplies the value of this variable (which is equal to the hourly SMIC) by the number of paid hours. If earnings go over this amount, a change in *régime* is triggered. The payee then moves to the standard *régime* and deductions are made at the new rate for earnings over the ceiling.

Note: When payees move into a standard class from a non-standard class, the funding base for the new, standard class is not the complete salary base, but only the amount over the limit.

Note: The value of the variable GEN VR SMIC L VG P appears in the Upper Limit field of the URSSAF Additional Setup page.

Social Security Code	Description
914	Qualification contract
915	Qualification contract AM
944	CRE: unlimited exemption
945	CRE unlimited exception Alsace-Moselle
956	CIE general case
957	CIE general case Alsace-Moselle
960	CIE more than 50
961	CIE more than 50 years Alsace-Moselle
963	Prof contract with AT
965	Prof contract with AT in AM

Lump Sum Bases

Some specific categories of employees contribute to URSSAF based on lump-sum bases. For example, this applies to instructors in vacation centers, apprentices, trainees, taxi drivers, and some other categories of employees.

Important! PeopleSoft manages only lump-sum bases in the case of apprentices and trainees. It does not manage other cases.

See [Understanding Specific Contracts](#).

Rates

The contribution rates for URSSAF vary according to the contribution class and are defined as variables. Although PeopleSoft delivers these variables with predefined values, you must maintain these variables on the URSSAF Rates page.

See [Defining URSSAF Rates and Additional Parameters](#).

Ceilings

Some URSSAF contributions are based only on the portion of a payee's salary that falls within a limit referred to as a *ceiling*. In other words, these contributions are calculated using a reduced base so that if a salary is over the ceiling, the contribution is calculated only on the ceiling.

Note: To view the ceilings for the different contribution classes, use the URSSAF Rates page. To modify a ceiling level, use the Ceilings page described in the Country Data topic.

See [Understanding Contribution Rates and Limits](#).

Contribution Classes

The contribution class for each payee is determined by such factors as where the payee works, what type of work is being done, and the employee's age. The different contribution classes for payees are identified in Global Payroll for France by a set of codes defined by URSSAF. Except in a few cases (such as for trainees), any payee who is eligible for URSSAF must be associated with a contribution class code (or social security code) on the Contract page. Use these codes to access the URSSAF Rates and URSSAF Additional Setup pages described in this section.

Social Security Code	Description
100	<i>General régime</i>
101	<i>General régime Alsace-Moselle</i>
102	<i>General régime</i> without AT contribution
103	<i>General régime</i> without AT AM
104	<i>General régime</i> without payee contribution
106	<i>Régime</i> without payee contribution and AT
128	Apprentice
129	Apprentice Alsace-Moselle

Social Security Code	Description
336	Doctors
337	Doctors Alsace-Moselle
456	Prof contract without AT
457	Prof contract without AT in AM
705	Apprentice contract with AT
707	Apprentice contract with AT in AM
914	Qualification contract
915	Qualification contract AM
944	CRE: unlimited exemption
945	CRE unlimited exception Alsace-Moselle
956	CIE general case
957	CIE general case Alsace-Moselle
960	CIE more than 50
961	CIE more than 50 years Alsace-Moselle
963	Prof contract with AT
965	Prof contract with AT in AM

Note: You can create classes that are not managed by PeopleSoft. If you do so, ensure that the URSSAF contributions are correctly calculated.

Understanding URSSAF Deductions

To trigger URSSAF deductions for a payee, specify the payee's social security code on the Contract Type/ Clauses page in PeopleSoft HR. Global Payroll for France uses the variable URS VR REGIME to retrieve the value of the social security code and trigger deduction processing. If you do not enter a social security code, the variable is not populated and the system does not process URSSAF contributions.

Note: You do not have to specify a social security code for trainees. The system determines the correct code for trainees based on the kind of training they receive and their salary level.

Related Links

[Understanding Specific Contracts](#)

Understanding URSSAF and Retroactive Processing

Global Payroll for France delivers processing rules to manage retroactive changes that affect the calculation of URSSAF contributions.

Understanding Fillon Reductions to URSSAF Contributions

In addition to reduced rates that apply to some contribution classes as a whole, certain employees within a class may qualify for Fillon reductions.

Supporting Element	Description
HRS VR AVT RTT	<p>This variable is defined as <i>PeopleSoft Delivered/Not Maintained</i> in order to allow updates.</p> <p>This variable stores the weekly work hours that were in effect at a company (if different from 39) before the Aubry law reduced the legal hours to 35.</p> <p>By default, this variable contains a value of 39.</p> <p>If the work hours before Aubry were different from 39, this variable needs to be updated to reflect the standard work hours at each company or establishment. This variable can be overridden at all levels (positive input, rules, pay entity, and so on).</p> <hr/> <p>Note: This variable is used in the bracket URS BR GMR2 MOIS, which retrieves the GMR2 (<i>Garantie Mensuelle de Rémunération 2</i>). The GMR2 is used in the calculation of the Fillon reduction for employers benefiting from the Aubry II reduction as of June 30, 2003.</p>
URS VR FILL MAJO	<p>This variable is defined as <i>PeopleSoft Delivered/Not Maintained</i> in order to allow updates.</p> <p>This variable contains the possible increase percentage for certain situations defined by the law.</p> <p>By default, this variable stores no increase rate. To define a 10% increase, enter a value of .10 in the variable.</p> <p>This variable can be overridden at all levels (positive input, rules, pay entity, and so on).</p>

Supporting Element	Description
URS BR GMR2 MOIS	<p>This bracket is defined as <i>PeopleSoft Delivered/Not Maintained</i>.</p> <p>The bracket is defined as not maintained to enable users to enter the correct values if they are unable to apply PeopleSoft tax updates.</p> <p>This bracket stores the different values of the GMR2 (<i>Garantie Mensuelle de Rémunération 2</i>). The value of GMR2 depends on the hours in effect at the company before the hourly reduction was applied.</p> <p>The search key of the bracket is the variable HRS VR AVT RTT (see above).</p>

Related Links

[Understanding Country Setup](#)

Defining URSSAF Rates and Additional Parameters

To define URSSAF rates and additional parameters, use the URSSAF Rates FRA (GPFR_URS_RATES) component.

This section provides an overview of URSSAF rates and ceilings and discusses how to:

- Define URSSAF rates.
- View and modify additional URSSAF parameters.

Pages Used to Define URSSAF Rates and Additional Parameters

Page Name	Definition Name	Navigation	Usage
URSSAF Rates	GPFR_URS_RATES	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, URSSAF Rates FRA, URSSAF Rates	<p>Review the URSSAF rates for illness, old age, family benefits, FNAL Employer, and Retirement rates</p> <p>PeopleSoft delivers the rates that appear on the URSSAF Rates page. However, you can adjust them if necessary to meet legal requirements.</p>
URSSAF Additional Setup	GPFR_URS_GENERAL	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, URSSAF Rates FRA, URSSAF Additional Setup	View (and if necessary, modify) additional URSSAF parameters.

Understanding URSSAF Rates and Ceilings

Global Payroll for France uses variables to define the rates for the different URSSAF contributions. Although PeopleSoft populates these variables with the correct rates, you can update them on the URSSAF Rates page to comply with changing laws and regulations. In addition, you can update the ceilings that apply to the bases used to calculate these contributions. This section explains how to view the delivered rates and ceilings for URSSAF. It also explains how you can adjust rate and ceiling values if necessary.

To view and adjust rates and ceilings:

1. View the ceilings for URSSAF rates.

Use the Limits page to view the ceilings that apply to the URSSAF rates. The ceilings that appear on this page (URSSAF uses only Ceiling A) also appear on the URSSAF Rates page with the actual ceiling values.

Note: The Limits page is documented in the topic on setting up country data.

See [Reviewing and Updating Contribution Rates and Limits](#).

2. View and maintain the ceilings for the URSSAF contribution rates.

Many URSSAF contribution rates apply only to a portion of an employee's funding base—in other words, they apply to the portion of the funding base that falls within a limit or ceiling. PeopleSoft has defined a specific variable to store the ceiling used in URSSAF: Ceiling A. Use the Ceilings page to update the value of this variable.

Note: This page is documented in the topic on setting up country data.

See [Reviewing and Updating Contribution Rates and Limits](#).

3. View and maintain the rates for the different contribution classes.

After reviewing and (if necessary) adjusting the ceilings used for URSSAF, go to the URSSAF Rates page to view and adjust the contribution rates for the different contribution classes. The ceilings that appear on this page are dynamically displayed based on the values on the Ceilings page. For example, if you enter a new ceiling on the Ceilings page, the ceiling data also changes on the URSSAF Rates page.

See [URSSAF Rates Page](#).

Note: PeopleSoft maintains the rates and ceilings for URSSAF; however, you can adjust the rates and ceilings without having to wait for PeopleSoft to issue updates when there are statutory changes.

4. Define additional URSSAF parameters on the URSSAF Additional Setup page. This page is discussed in detail in the subsequent topic on viewing and modifying URSSAF parameters.

URSSAF Rates Page

Use the URSSAF Rates page (GPFR_URS_RATES) to .

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, URSSAF Rates FRA, URSSAF Rates

Image: URSSAF Rates page

This example illustrates the fields and controls on the URSSAF Rates page. You can find definitions for the fields and controls later on this page.

Social Security Code: 100									
Rates									
*Effective Date:	*Status:								
01/01/2006	Active								
*Description: General "Regime"									
<table border="1"> <thead> <tr> <th colspan="2">Illness Rate</th> </tr> <tr> <th></th> <th>Payee Employer</th> </tr> </thead> <tbody> <tr> <td>No limit</td> <td>0.750 12.800</td> </tr> </tbody> </table>		Illness Rate			Payee Employer	No limit	0.750 12.800		
Illness Rate									
	Payee Employer								
No limit	0.750 12.800								
<table border="1"> <thead> <tr> <th colspan="2">Family Allowance</th> </tr> <tr> <th></th> <th>Employer</th> </tr> </thead> <tbody> <tr> <td>No limit</td> <td>5.400</td> </tr> </tbody> </table>		Family Allowance			Employer	No limit	5.400		
Family Allowance									
	Employer								
No limit	5.400								
<table border="1"> <thead> <tr> <th colspan="2">Retirement Rate</th> </tr> <tr> <th></th> <th>Payee Employer</th> </tr> </thead> <tbody> <tr> <td>No limit</td> <td>1.600</td> </tr> <tr> <td>From 0 To 2589</td> <td>6.650 8.300</td> </tr> </tbody> </table>		Retirement Rate			Payee Employer	No limit	1.600	From 0 To 2589	6.650 8.300
Retirement Rate									
	Payee Employer								
No limit	1.600								
From 0 To 2589	6.650 8.300								
<table border="1"> <thead> <tr> <th colspan="2">Oldness Rate</th> </tr> <tr> <th></th> <th>Payee</th> </tr> </thead> <tbody> <tr> <td>No limit</td> <td>0.100</td> </tr> </tbody> </table>		Oldness Rate			Payee	No limit	0.100		
Oldness Rate									
	Payee								
No limit	0.100								
<table border="1"> <thead> <tr> <th colspan="2">FNAL Employer Rate</th> </tr> <tr> <th></th> <th>Employer</th> </tr> </thead> <tbody> <tr> <td>From 0 To 2589</td> <td>0.100</td> </tr> </tbody> </table>		FNAL Employer Rate			Employer	From 0 To 2589	0.100		
FNAL Employer Rate									
	Employer								
From 0 To 2589	0.100								
<table border="1"> <thead> <tr> <th colspan="2">Solidarity Employer Rate</th> </tr> <tr> <th></th> <th>Employer</th> </tr> </thead> <tbody> <tr> <td>No limit</td> <td>0.300</td> </tr> </tbody> </table>		Solidarity Employer Rate			Employer	No limit	0.300		
Solidarity Employer Rate									
	Employer								
No limit	0.300								

Illness Rate

Displays the illness contribution rates for Payee and Employer.

Family Allowance

Displays the rate for family allowance.

Retirement Rate

Displays the two contributions towards the retirement rate.

The employer pays a rate based on the entire funding base. This is displayed opposite No Limit.

The second contribution, paid by both payee and employer, is applied to a funding base limited to Ceiling A.

Oldness Rate

Displays the contribution rate for old age benefits.

FNAL Employer Rate

Displays the rate that applies to a funding base limited to Ceiling A.

Note: FNAL contributions not limited to Ceiling A are maintained on the Variables By Category page. Only FNAL contributions limited to Ceiling A are maintained on the URSSAF Rates page.

Solidarity Employer Rate

Displays the solidarity contribution rate.

Note: Several of the contribution sections on this page display the comment No limit. This means that the contributions for each section are not based on an earning ceiling. They are calculated from the entire funding base, with no limit.

Related Links

[Defining URSSAF Rates and Additional Parameters](#)

URSSAF Additional Setup Page

Use the URSSAF Additional Setup page (GPFR_URS_GENERAL) to view (and if necessary, modify) additional URSSAF parameters.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, URSSAF Rates FRA, URSSAF Additional Setup

Image: URSSAF Additional Setup page

This example illustrates the fields and controls on the URSSAF Additional Setup page. You can find definitions for the fields and controls later on this page.

Social Security Code

Displays the payees' existing contribution class—not that of the standard class.

AT Reduction

Displays the percentage amount of the reduction in the work accident rate if the contribution class (*régime*) qualifies for a reduction. You can adjust this amount if necessary.

Low Salary Reduction

Select this check box to trigger the Fillon reduction if the payee earns a low salary.

Standard Class

Displays the standard class to which payees are assigned if they become ineligible for their original class. For example, payees in some contribution classes contribute using the rates for their

class if their monthly salary is less than or equal to the SMIC (minimum monthly salary). When payees belonging to one of these classes earn more than the SMIC, they automatically begin contributing using the rates in effect for the standard class. These rates apply only to the portion of the salary that exceeds the earning limit.

Upper Limit

Displays the value of the variable GEN VR SMIC L VG P that stores the hourly SMIC rate. To calculate the maximum payees can earn and remain within their normal *régime*, Global Payroll for France multiplies the value of this variable by the number of paid hours. If earnings go over this amount, a change in *régime* is triggered. The payee then moves to the rates for the contribution class specified in the Standard Class field and deductions are made at the new rate for earnings over the limit.

Related Links

[Defining Rates for Accidents at Work](#)

[Defining URSSAF Rates and Additional Parameters](#)

Defining Rates for Accidents at Work

This section provides an overview of work accident rates and discusses how to define work accident rates.

Pages Used to Define Work Accident Rates

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Establishment Address	ESTAB_TBL1_GBL	Set Up HCM, Foundation Tables, Organization, Establishment, Establishment Address	Define risk codes, AT sections, and corresponding rates.
Department Profile	DEPARTMENT_TBL_GBL	Set Up HCM, Foundation Tables, Organization, Departments, Department Profile	Define the risk code and AT section for an establishment.

Page Name	Definition Name	Navigation	Usage
Supporting Elements	GP_PAYEE_SOVR	Global Payroll & Absence Mgmt, Payee Data, Create Overrides, Supporting Elements, Supporting Elements	<ul style="list-style-type: none"> Enter the risk code that applies to a payee in the variable URS VR CODE RISK E. Enter the correct AT section for a payee in the variable URS VR AT SEC E. <p>Override the standard risk code and AT section on the Supporting Elements page only if the standard work accident risk doesn't reflect the payee's true risk.</p>

Related Links

"Setting Up Person of Interest Types (*PeopleSoft HCM 9.2: Application Fundamentals*)"

Understanding Work Accident Rates

The work accident (AT) contribution is based on the URSSAF funding base and is calculated using a rate corresponding to the amount of risk in the workplace.

To define the risk on which this contribution is based:

1. (Required) For each establishment defined in PeopleSoft HR, specify risk codes, AT sections, and associated contribution rates.

Do this on the Establishment Address page.

Note that there can be multiple risk codes for the same establishment, and that a single risk code can be associated with multiple AT sections, each linked to a different AT contribution rate. For example, you could define the contribution rates for different levels of risk as follows:

Risk Code	AT Section	AT Rate
724CA	01	1.5
724CA	02	2.5
724CA	03	2.15
518CA	01	2.3

Note: This example shows that within an establishment there can be different risk codes, and that the same risk code can have multiple AT sections corresponding to the different levels of risk within the organization. In other words, different departments or "sections" within a single establishment may pay different rates if the level of risk varies from department to department.

2. (Optional) For each department within an establishment, select the appropriate risk code and AT section from the list of valid values defined on the Establishment Address page in step 1.

Do this on the Department Profile page.

Define risk codes and AT sections at the department level if there are multiple risk codes and AT sections, or a single risk code with more than one AT section, specified on the Establishment Address page, and you want the system to use the contribution rate associated with *one* of these risk codes/sections to process payees in a specific department.

3. (Optional) Override the standard risk code and AT section at the payee level.

If a payee is associated with a department, but the standard work accident risk doesn't reflect the payee's true risk, you can override the standard risk at the payee level. To do this, enter the risk code that applies to the payee in the variable URS VR CODE RISK E, and enter the correct AT section in the variable URS VR AT SEC E. Enter these override values using the Create Overrides—Supporting Elements (GP_PAYEE_SOVR) component.

Note: You must specify a value for the risk code variable (URS VR CODE RISK E) to create a payee level override. You do not need to specify a value for the AT section variable (URS VR AT SEC E); however, if there are multiple AT sections associated with the same risk code, and you want to control which of these to apply to a payee, you should specify the AT section. If you override only the AT section variable (URS VR AT SEC E) and not the risk code variable (URS VR CODE RISK E), the system issues an error message.

Examples: Understanding Risk Logic

Depending on the level at which you specify risk data in the system as well as the complexity of the data, the system follows the path described here to determine the correct contribution rate for a given payee:

- The system first checks to see whether the risk code is specified at the payee level (using the variable URS VR CODE RISK E). If so, the system retrieves the AT section linked to this risk code on the Establishment Address page, and then uses the contribution rate associated with this AT section. If there are multiple AT sections linked to the same payee-level risk code, the system selects the AT section with the lowest number for the specified risk code and applies the associated contribution rate to the payee.

Note: This example assumes that only the risk code is specified at the payee level. If both the risk code and the AT section are specified, the system does not need to search for the section with the lowest number as described here, but instead simply selects the rate associated with the specified section.

- If there is no risk code specified at the payee level, the system checks to see whether the risk code and AT section are defined at the department level. If this is the case, the system retrieves the contribution rate associated with this risk code and AT section on the Establishment Address page, and applies it to the payee.

Note: You can specify a risk code at the department level without entering an AT section. If you do this, the system retrieves the AT section linked to this risk code on the Establishment Address page, and then uses the contribution rate associated with this AT section. However, if there are multiple AT sections linked to the same risk code, the system selects the AT section with the lowest number for the specified risk code and applies the associated contribution rate to the payee.

- If there is no risk code or AT section defined at either the payee level *or* the department level, the correct AT rates are retrieved in two steps:
 1. First, the system selects the risk code entered in the first row on the Establishment Address page and applies it to any payee linked to that establishment on the JOB table.
 2. If the risk code in this row has only *one* associated AT section, the system automatically applies the AT rate associated with this section to the payee.
 3. However, if there are *multiple* AT sections for the risk code selected in step 1, the system selects the AT section with the lowest number and applies the AT rate for that section to any payee linked to the establishment on the JOB table.

For example, consider a case in which the following risk codes and AT sections are defined at the establishment level:

<i>Row Number</i>	<i>Risk Code</i>	<i>AT Section</i>	<i>AT Rate</i>
1	724CA	01	1.5
2	724CA	02	2.5
3	518CA	01	2.3
4	518CA	02	2.6

In this example, there is no risk data defined at either the payee or the department level. To determine the correct AT rate to apply to a payee, the system takes the first risk code in row 1 on the Establishment Address page, which is 724CA. There are two AT sections associated with this risk code—01 and 02. The system selects AT section 01, because it has the lowest number. This section is associated with an AT rate of 1.5. This means that for any payee in the establishment for which these rates are defined, the system applies a rate of 1.5.

Note: When you define risk codes, the risk code in row #1 on the Establishment Address page should contain the most current AT rate that applies without overrides. This is because the risk code in this row contains the rate that applies by default when the risk is not defined at lower levels (department level or payee level).

Reporting URSSAF Data

Reports available for URSSAF are:

- DUCS reports.
- Tax Reduction for Low Salaries report (generic report FRPAY006).

Related Links

[Understanding DADS Reporting](#)

[Global Payroll for France Reports: A to Z](#)

Creating the TRC Annual Report (without Application Framework)

The *Tableau Récapitulatif des Cotisations* (TRC) summarizes the previous year's URSSAF contributions. The report is organized by establishment, and enables URSSAF to recalculate the annual contributions and acknowledge any over- or underpayments.

Because most of the data needed for this report is produced in the DUCS process, you use the DUCS Declaration Type and DUCS Definition pages to create the report and update the data extracted on the Update DUCS Data FRA page. Then use the DUCS Run Control and Create DUCS/TRC/DRA File FRA pages to run the TRC report.

This section discusses how to:

- View the TRC declaration type.
- Create a TRC declaration definition.
- Set up TRC data extraction.
- Generate the TRC report file.

Viewing the TRC Declaration Type

Access the Declaration Type page.

This page allows you to view the TRC file types that are used to generate TRC data through the DUCS process.

File Type

Select *915* for TRC for one establishment, or *916* if the TRC is for several establishments.

Related Links

[Declaration Type Page](#)

Creating a TRC Declaration Definition

Access the DUCS Definition page.

This page allows you to create a specific DUCS declaration definition for TRC processing. Reproduce the setup created for monthly URSSAF DUCS, ignoring the payment type and source bank fields.

Establishment List

Enter the DUCS Establishment List data. These are the establishments you want to declare through your DUCS definition.

Related Links

[DUCS Definitions FRA Page](#)

Setting Up TRC Data Extraction

Access the DUCS Preparation Run Control page.

This page allows you to establish which data is extracted for the TRC report.

Period Format Select *Yearly Qualifier*.

Related Links

[Create DUCS Data FRA Page](#)

Generating the TRC Report File

Access the Create DUCS/TRC/DRA File FRA page.

Output Select *Report*. The system can prepare the TRC DUCS file, but it is not currently accepted by URSSAF.

Related Links

[Create DUCS/TRC/DRA File FRA Page](#)

Creating the TRC Annual Report (with Application Framework)

The *Tableau Récapitulatif des Cotisations* (TRC) summarizes the previous year's URSSAF contributions. The report is organized by establishment, and enables URSSAF to recalculate the annual contributions and acknowledge any over- or underpayments.

This section discusses how to:

- View the TRC declaration type.
- Create a TRC declaration definition.
- Set up TRC data extraction.
- Generate the TRC report file.

Viewing the TRC Declaration Type

Access the Declaration Type page (Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Parameters FRA, Declaration Type).

This page allows you to view the TRC file types that are used to generate TRC data through the DUCS process.

File Type Select *915* for TRC for one establishment, or *916* if the TRC is for several establishments.

Related Links

[Declaration Type Page](#)

Creating a TRC Declaration Definition

Access the DUCS Definition page.

This page allows you to create a specific DUCS declaration definition for TRC processing. Reproduce the setup created for monthly URSSAF DUCS, ignoring the payment type and source bank fields.

Establishment List

Enter the DUCS Establishment List data. These are the establishments you want to declare through your DUCS definition.

Related Links

[DUCS Definitions FRA Page](#)

Setting Up TRC Data Extraction

Access the Node Set Nodes page (Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, Define Node Set Details FRA).

The TRC is managed as a specific Node Set of the DUCS 4.2 Application in Application Framework. You can see the list of node sets that were defined in the Define Application / Node Set component, on the Node Set Definition page, and the list of structures associated with each node set. A link on each structure's row, leads to the list of records associated with the structure.

Related Links

[Setting Up DADS Extraction](#)

Generating the TRC Report File

Generating the TRC report file uses the same process you use to generate a DADS file.

Related Links

[Generating DADS Files](#)

Reviewing Delivered URSSAF Deductions

This section discusses these groups of URSSAF deductions:

- Deductions for standard classes.
- Deductions for classes carrying rate exemptions.
- Deductions for the fillon reductions.

Deductions for Standard Classes

<i>Deduction</i>	<i>Description</i>
URS MAL S	Illness without ceiling - Payee.
URS MAL E	Illness without ceiling - Employer
URS VEUV S	Widow - Payee. <hr/> Note: URS VEUV S becomes inactive in July 2004. <hr/>
URS AT E	Work Accident - Employer.
URS AF E	Family Allowance - Employer.
URS VIE TA S	Old age with ceiling - Payee.
URS VIE TA E	Old age with ceiling - Employer.
URS VIE DP E	Old age without ceiling - Employer.
URS VIE DP S	Old age without ceiling - Payee. <hr/> Note: This deduction becomes effective in July 2004. <hr/>
URS VIE EX S	Old age without ceiling - Payee. <hr/> Note: This deduction becomes effective in July 2004. <hr/>
URS FNAL A E	FNAL with ceiling - Employer.
URS FNAL D E	FNAL without ceiling - Employer.
URS SOLID E	Solidarity - Employer. <hr/> Note: This deduction becomes effective in July 2004. <hr/>

Deductions for Classes Carrying Rate Exemptions

<i>Deduction</i>	<i>Description</i>
URS MAL EX S	Illness without ceiling - Associated Régime - Payee.
URS MAL EX E	Illness - Associated Régime - Employer.

Deduction	Description
URS VEU EX S	Widow - Associated Régime - Payee. <hr/> Note: URS VEU EX S becomes inactive in July 2004. <hr/>
URS AT EX E	Work Accident - Associate Régime - Employer.
URS AF EX E	Family Allowance - Associate Régime - Employer.
URS V A EX S	Old age with ceiling - Associated Régime - Payee.
URS V A EX E	Old age - Associated Régime - Employer.
URS VIEEX E	Old age without ceiling - Employer.
URS FNP EX E	FNAL with ceiling - Associate Régime - Employer.
URS FND EX E	FNAL without ceiling - Associate Régime - Employer.
URS SOLID EX	Solidarity - Employer. <hr/> Note: URS SOLID EX becomes inactive in July 2004. <hr/>

Note: PeopleSoft delivers a query that you can run to view the names of all delivered elements designed for France. Instructions for running the query are provided in the *PeopleSoft Global Payroll* .

Related Links

"Understanding How to View Delivered Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

[URSSAF Additional Setup Page](#)

"Understanding Earning and Deduction Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

Chapter 6

Defining ASSEDIC Contributions

Understanding ASSEDIC Rates, Limits, and Ceilings

ASSEDIC (or GARP in Paris) contributions are paid to the state unemployment fund, *Pôle Emploi*, which finances unemployment insurance *Régime d'Assurance Chômage* (RAC) and salary guarantee *Fond National de Garantie des Salaires* (FNGS). Global Payroll for France offers complete ASSEDIC functionality, enabling you to:

- Enter and maintain rates using the ASSEDIC Rates component.
- Create regulatory reports and make payments to collector institutions using the DUCS component.
- Create ASSEDIC certificates upon employee termination in three steps using three components (ASSEDIC Data Retrieval, ASSEDIC Certificate, and ASSEDIC Printing Process).

PeopleSoft delivers current contribution rate percentages for RAC and FNGS contributions on the ASSEDIC Rates (GPFR_ASS_RATES) component, but you must update and maintain this information yourself as the government issues new rate changes. The contribution percentages vary depending on gross monthly salary as reflected in government-mandated ceilings, which you enter on the Ceilings FRA (GPFR_CEILINGS) component.

The fields on the ASSEDIC Rates component are dynamically displayed based on these ceilings. For example, if you enter a new ceiling, the data changes when you view ASSEDIC rates.

In addition to ceilings, Global Payroll for France also uses rates and limits to determine ASSEDIC contributions. PeopleSoft delivers this data, but you should verify it before proceeding with ASSEDIC processing.

See [Reviewing and Updating Contribution Rates and Limits](#), [Setting up Rates and Ceilings for ASSEDIC Contributions](#).

Understanding Funding Bases

This section discusses:

- Funding bases A, B, and A+B.
- Contributions at age 65.
- Contribution exceptions.

Funding Bases A, B, and A+B

The funding bases for ASSEDIC contributions are:

- Base A: Gross salary limited to Ceiling A as defined on the Ceilings component.

For ASSEDIC contributions limited to Ceiling A (such as RAC), the contribution is calculated based only on Ceiling A if the gross salary is more than Ceiling A. If the gross salary is less than Ceiling A, the contribution is calculated based on the gross salary.

- Base B: Part of the gross salary between Ceiling A and Ceiling A x 3.

For ASSEDIC contributions limited to Ceiling B (such as RAC), the contribution is calculated only on the difference between the gross salary and Ceiling A if the gross salary is more than Ceiling A but less than Ceiling B. If the gross salary is more than Ceiling B, the contribution is calculated based on the portion between Ceilings A and B. If the gross salary is less than Ceiling A, no contribution on base B is required.

Note: As of the January 1, 2001, the RAC contributions on Base A and on Base B have the same rate. The contributions could be calculated on only one slice (slice A + B), however, PeopleSoft will continue to split the contributions on the two slices (A and B) in case rates differ again in the future.

- Base A+B: Part of the gross salary included between Ceiling A and Ceiling A x 4.

For the ASSEDIC contribution limited to Ceiling A+B (such as AGS), the contribution is calculated based on only Ceiling B if the gross salary is more than Ceiling B. If the gross salary is less than Ceiling B, the contribution is calculated based on the gross salary. The upper limit is Ceiling B.

These calculations are done on a monthly basis, but the comparisons are based on annual amounts. An annual gross salary is calculated from the monthly salary, and annual ceilings are calculated from the monthly ceilings. The system also produces a monthly report, detailing the contributions for the period. You can create and produce all required regulatory reports through the DUCS components in Global Payroll for France.

Ceilings A and B are prorated by the number of calendar days in the period to take into consideration hires and terminations during that period, the part-time rate (calculated in the payroll process), and the multiple employer rate. Payees who have multiple employers are not considered part-time, so only one proration is calculated.

Note: The rules concerning funding base calculation for ASSEDIC are identical to those for URSSAF. URSSAF actually determines these rules and, generally, ASSEDIC also follows them.

Related Links

[Understanding Country Setup](#)

[Understanding URSSAF Contributions](#)

[Generating DUCS Files Using Application Framework](#)

Contributions at Age 65

Payees turning 65 during a pay period pay a prorated ASSEDIC contribution only for the period of time before their 65th birthday. This is accomplished by triggering the section ASSEDIC if the payee isn't 65 years old at the beginning of the calendar period. The system prorates the ASSEDIC funding base if the payee turns 65 before the end date of the calendar period. The proration is equal to the amount of time the payee is still 64 years old within the calendar period divided by the calendar period duration. Ceilings

A and B are not prorated; only the funding base is prorated. After a payee's 65th birthday, if the birthday does not occur during the current calculated segment period, ASSEDIC contributions are no longer paid.

Contribution Exceptions

There are exceptions to ASSEDIC contributions depending on the classification of the payee or a payee's specific contract.

There are some additional exceptions that affect specific contributions. Global Payroll for France uses generation control to trigger the appropriate contributions in these special cases.

Related Links

[Understanding Specific Contracts](#)

Understanding ASSEDIC and Retroactive Processing

Global Payroll for France delivers processing rules to manage retroactive changes that affect the calculation of ASSEDIC contributions.

Setting up Rates and Ceilings for ASSEDIC Contributions

To set up rates for ASSEDIC contributions, use the ASSEDIC Rates FRA (GPFR_ASS_RATES) component.

This section provides an overview of ASSEDIC rates and ceilings, and discusses how to set up ASSEDIC rates for ASSEDIC contributions.

Page Used to Set up Rates for ASSEDIC Contributions

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
ASSEDIC Rates FRA	GPFR_ASS_RATES	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Addl Rates, Ceilings, Values, ASSEDIC Rates FRA, ASSEDIC Rates FRA	Set up rates for ASSEDIC contributions. PeopleSoft delivers these rates, but you can maintain them when the government issues updates.

Understanding ASSEDIC Rates and Ceilings

Global Payroll for France uses variables to define the rates for ASSEDIC contributions. Although PeopleSoft populates these variables with the correct rates, you can update them on the ASSEDIC Rates page to comply with changing laws and regulations. In addition, you can update the ceilings that apply to the bases used to calculate ASSEDIC contributions. This section explains how to view the delivered rates and ceilings for ASSEDIC. It also explains how you can adjust rate and ceiling values if necessary.

To view and adjust rates and ceilings:

1. View the variables containing the ASSEDIC rates.

Do this on the Rates and Elements page.

Note: The Rates and Elements page is documented in the topic on setting up country data.

See [Rates And Elements Page](#).

2. View the ceilings for ASSEDIC rates.

Use the Limits page to view the ceilings associated with the ASSEDIC rate variables.

Note: The Limits page is documented in the topic on setting up country data.

See [Limits Page](#).

3. View and maintain the ceilings for the ASSEDIC contribution rates.

The different ASSEDIC contribution rates apply only to a portion of an employee's funding base—in other words, they apply to the portion of the funding base that falls within a limit or ceiling. You can update the values of the ASSEDIC ceilings on the Ceilings page.

Note: This page is documented in the topic on setting up country data.

See [Ceilings FRA Page](#).

4. View and maintain ASSEDIC rates.

After reviewing and (if necessary) adjusting the ceilings used for ASSEDIC, access the ASSEDIC Rates page to view and adjust the contribution rates.

The ceilings that appear on the ASSEDIC Rates page are dynamically displayed based on the values on the Ceilings page. For example, if you enter a new ceiling on the Ceilings page, the ceiling data also changes on the ASSEDIC Rates page.

See [ASSEDIC Rates FRA Page](#).

Note: PeopleSoft maintains the rates and ceilings for ASSEDIC; however, you can adjust the rates and ceilings without having to wait for PeopleSoft to issue updates when there are statutory changes.

ASSEDIC Rates FRA Page

Use the ASSEDIC Rates FRA page (GPFR_ASS_RATES) to set up rates for ASSEDIC contributions.

PeopleSoft delivers these rates, but you can maintain them when the government issues updates.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Addl Rates, Ceilings, Values, ASSEDIC Rates FRA, ASSEDIC Rates FRA

Image: ASSEDIC Rates FRA page

This example illustrates the fields and controls on the ASSEDIC Rates FRA page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'ASSEDIC Rates FRA' page. At the top, there is a 'Rates' header with navigation links: 'Find', 'View All', 'First', '1 of 14', and 'Last'. Below this, there are two main fields: '*Effective Date:' with a date picker set to '04/01/2009' and a calendar icon, and 'Status:' with a dropdown menu set to 'Active' and '+' '-' buttons. The main content area is divided into two sections. The first section is 'Unemployment Insurance Contrib' and contains a table with two columns: 'Payee' and 'Employer'. It has two rows of data: 'From 0 To 2859' with values 2.400 and 4.000, and 'From 2859 To 11436' with values 2.400 and 4.000. The second section is 'Salary Guarantee Association' and contains a table with one column: 'Employer'. It has one row of data: 'From 0 To 11436' with a value of 0.200.

Unemployment Insurance Contrib		
	Payee	Employer
From 0 To 2859	2.400	4.000
From 2859 To 11436	2.400	4.000

Salary Guarantee Association	
	Employer
From 0 To 11436	0.200

Unemployment Insurance Contrib (unemployment insurance contributions)

The fields in this region display the Payee and Employer contribution percentages for the portion of gross salary below the A ceiling and Payee and Employer contribution percentages for the portion of gross salary below the B ceiling but above the A ceiling.

Note: The field names in this region are dynamically displayed based on the values entered on the Ceilings page. These values change each year

Salary Guarantee Association

The field in this region displays the Employer contribution percentage for FNGS.

Note: There is only an employer contribution percentage for FNGS, not for payees. This rate is based on the B ceiling, which is displayed dynamically. If the gross salary is over this limit, the contribution is still based on the B ceiling.

Creating the BDA Report

The *Bordereau de Déclaration Annuelle* (BDA) summarizes the previous year's ASSEDIC contributions. Use the DUCS pages to set up the BDA reporting process, generate BDA data, and create the BDA report.

This section discusses how to:

- View the BDA declaration type.
- Create a BDA declaration definition.
- Set up BDA data extraction.
- Generate the BDA report file.

Viewing the BDA Declaration Type

Access the Declaration Type page.

This page allows you to view the BDA file type used to generate BDA data through the DUCS process.

File Type Select 922 for BDA for one establishment, or 923 for BDA for several establishments.

Related Links

[Declaration Type Page](#)

Creating a BDA Declaration Definition

Access the DUCS Definition page.

This page allows you to create a specific DUCS declaration definition for BDA processing. Reproduce the setup created for monthly ASSEDIC DUCS, ignoring the payment type and source bank fields.

Establishment List Enter the DUCS Establishment list data. These are the establishments you want to declare through your DUCS definition.

Related Links

[DUCS Definitions FRA Page](#)

Setting up BDA Data Extraction

Access the DUCS Preparation Run Control page.

This page allows you to establish which data is extracted for the BDA report.

Period Format Select *Yearly Qualifier*.

Related Links

[Create DUCS Data FRA Page](#)

Generating the BDA Report File

Access the Create DUCS/TRC/DRA File FRA page.

Output

Select *Report*. The system can prepare the BDA DUCS file, but it is not currently accepted by URSSAF. Use the report to complete the original BDA form.

Related Links

[Create DUCS/TRC/DRA File FRA Page](#)

Viewing Delivered ASSEDIC Deductions

<i>Deduction</i>	<i>Description</i>
ASS RAC TA S	RAC on Ceiling A, payee.
ASS RAC TA E	RAC on Ceiling A, employer.
ASS RAC TB S	RAC on Ceiling B, payee.
ASS RAC TB E	RAC on Ceiling B, employer.
ASS ASF TA S	ASF on Ceiling A, payee. This deduction is inactive as of the 1st of January 2001.
ASS ASF TA E	ASF on Ceiling A, employer. This deduction is inactive as of the 1st of January 2001.
ASS ASF TB S	ASF on Ceiling B, payee. This deduction is inactive as of the 1st of January 2001.
ASS ASF TB E	ASF on Ceiling B, employer. This deduction is inactive as of the 1st of January 2001.
ASS FNGS	FNGS.

Note: The PeopleSoft system delivers a query that you can run to view the names of all delivered elements designed for France. Instructions for running the query are provided in the *PeopleSoft Global Payroll*.

Related Links

"Understanding How to View Delivered Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

Chapter 7

Defining ARRCO, AGIRC, and Contingency Fund Contributions

Understanding ARRCO, AGIRC, and Contingency Fund Contributions

This section discusses:

- ARRCO, AGIRC, and contingency fund contributions.
- Rates, limits, and ceilings.
- Contribution exception limits.
- Tax and limits.

ARRCO, AGIRC, and Contingency Fund Contributions

Both the ARRCO and AGIRC manage pension funds. Each comprises employer and payee contributions. Most payees, except for apprentices and trainees, for example, are liable for contributions to ARRCO or AGIRC funds.

Contributions to ARRCO and AGIRC are based on the same funding bases as for URSSAF and ASSEDIC, with one difference. If the employer contributions for retirement and contingency submitted to URSSAF exceed 85 percent of the social security ceiling A (or 19 percent for the contingency only contributions), the part of the contributions over the ceiling is included in the URSSAF funding base but is not included in the ARRCO and AGIRC funding bases.

Because contributions paid to the *Association Pour l'Emploi des Cadres* (APEC) are first paid to AGIRC and then paid to APEC, they are managed with the other AGIRC contributions. These include lump sum APEC contributions and the APEC contribution base on slice B.

Because *Contribution Exceptionnelle Temporaire* (CET) and AGFF contributions are paid to AGIRC, it is also managed with the other AGIRC contributions.

Contingency funds supplement the standard social security (URSSAF) payments. There is a single mandatory payment, paid by all companies, for employees categorized in *Article 36* or *Article 4/4 bis*. All other payments are voluntary. Each organization deals with contingency contributions in its own way and needs to set up its own rules to handle its calculations.

Related Links

[Contribution Exception Limits](#)

[Understanding URSSAF Contributions](#)

[Setting up Rates and Ceilings for ASSEDIC Contributions](#)

Rates, Limits, and Ceilings

Global Payroll for France uses rates, limits, and ceilings to determine ARRCO, AGIRC, and contingency contributions. PeopleSoft delivers this data, but you should verify it before proceeding with ARRCO, AGIRC, and contingency processing. You should:

- Use the Rates/Elements/Limits FRA component to view the variables and limits used to calculate the contributions to these funds.
- Use the Ceilings FRA component to view the monetary value of these limits, which the system uses to calculate the funding bases for ARRCO, AGIRC, and contingency contributions.
- Use the ARRCO/AGIRC Rt FRA component to enter the numeric values for the various ARRCO and AGIRC contribution rates.

The ceilings appearing on this page are dynamically displayed based on the values on the Ceilings page. For example, if you enter a new ceiling on the Ceilings page, the ceiling data also changes on the AARRCO/AGIRC Rt FRA component.

- Use the Pension/Contingency Contract page in the HR application to enter contribution rates for contingency funds directly in the contingency contract.

Related Links

[Understanding Country Setup](#)

Contribution Exception Limits

The government sets the annual social security contribution ceiling. If the employer contributions to contingency funds and additional pension funds (ARRCO and AGIRC) are less than 85 percent of the annual social security ceiling, then these contributions are exempted from social security contributions. If the employer contribution to contingency funds is less than 19 percent of the social security ceiling, these are also exempt from contributions. If both the 85 percent limit and the 19 percent limit are exceeded, the largest excess amount is added to the URSSAF and ASSEDIC accumulators and reintegrated into the social security base. This has no impact on the pension fund contribution.

Three calculations are required to determine the limits:

- Contributions to contingency funds and additional pension funds are checked against the limit of 85 percent of the annual social security ceiling.

Any excess is paid into the social security base.

- Contributions to contingency funds only are compared to 19 percent of the total funding base.

Any excess is added to the social security and ASSEDIC funding base.

Note: If both the 19 and 85 percent limits are exceeded, only the largest excess amount is reintegrated into the social security and ASSEDIC base.

These calculations are performed by the PRV FM REINT SOCIA formula, which is triggered by the PRV SE SOCIAL section. This formula performs the calculation for departing employees or during the month of December.

Tax and Limits

For a temporary period (for years beginning on 1 January 2004), two methods must be used to calculate taxes on contingency and additional pension funds. The method that calculates the smallest amount is the one accepted as the true calculation, and the smallest amount is the one reinstated in the taxable salary.

Note: PeopleSoft doesn't deliver the taxable exemption rules for additional retirement funds.

- The first method calculates the exemption limit once a year, in the case of departure, or in December. It is triggered at the same time as the 19 and 85 percent exemptions.
- The second method:
 - Calculates a ceiling equal to 7% of the annual social security ceiling plus 3% of the payee's yearly compensation. This ceiling is limited to 3% of 8 times the annual social security ceiling.
 - Compares the yearly contributions to the contingency funds to this ceiling. The amount of contributions over the ceiling is the amount to be reinstated.

The smallest amount calculated by these methods is the amount reinstated.

Note: The calculations of these tax limits is done by the formula PRV FM REINT FISCA, which is a member of the PRV SE FISCAL section. The contingency contributions used in these calculations are stored in the accumulator PRV AC COT RFIS SG.

Voluntary Contributions to Contingency Funds and Additional Pension Funds

In the case of voluntary contributions, both the payee and employer contributions are liable to tax. The payee contributions are not deducted from the taxable net salary and the employer contributions are added to the taxable net salary. The PeopleSoft system does not manage voluntary contributions; you must update the accumulators.

Mandatory Contributions

If contributions are mandatory, they are not subject to tax if they are below the legal limits. There are two limits: one for contingency and pension funds and one for contingency funds only. The first limit is for contributions to contingency funds and pension funds. If the contributions from payee and employer do not exceed 19 percent of the annual social security ceiling multiplied by 8, they are not liable to tax. The second limit is for contributions to contingency funds only. If the payee and employer contributions do not exceed 3 percent of the annual social security ceiling multiplied by 8, they are not liable to contributions. If contributions exceed either limit, the surplus is reintegrated back into the taxable base and is liable for tax. If contributions exceed both limits, the largest surplus is added to the net salary. The PeopleSoft system provides the PRV AC 19% FIS SG accumulator and the PRV AC 3% FIS SG accumulator to calculate these limits in the PRV FM REINT FISCA formula. It is your responsibility to update these accumulators.

There are two retirement contribution rates: the contractual rate and the calling rate. The difference between these two rates relates to contributions that do not give entitlements for pension points. For the reinstatement of retirement contributions over the tax limits, the system uses the calling rate to compare the retirement contribution to the limits. The contributions are reinstated in the taxable salary depending on their contractual rate. This is because contributions that do not give entitlements to pension points are not reinstated in the taxable salary.

The employer contributions to contingency and retirement that are over the 3 or 19 percent limit are also included in the levy on salary funding base. The amount that is added to the levy on salary funding base is calculated in the following manner:

- If the limit is only exceeded by the contingency contributions (3 percent limit), the amount over the limit is prorated and is calculated depending on the employer's and payee's contingency contributions.

The calculation is:

$(\text{amount over the limit}) \times (\text{employer's contingency contributions}) \div (\text{employer's} + \text{payee's contingency contributions})$

- If the limit is only exceeded by the contingency plus retirement contributions (19 percent limit), the amount over the limit is prorated depending on the employer's and payee's retirement contributions.

The calculation is:

$(\text{amount over the limit}) \times (\text{employer's retirement contribution}) \div (\text{employer's} + \text{payee's retirement contributions})$

- If both of the limits (3 and 19 percent) are exceeded, the highest amount over the limits is prorated depending on the total contributions to contingency and retirement funds.

The calculation is:

$(\text{highest amount over the limit}) \times (\text{employer's contingency} + \text{retirement contributions}) \div (\text{employer's and payee's contingency} + \text{retirement contributions})$

Related Links

[Establishing Levy Rates on Salaries](#)

Viewing and Maintaining ARRCO and AGIRC Rates

To view and maintain ARRCO, AGIRC, and Contingency Fund rates, use the ARRCO/AGIRC Rt FRA (GPFR_ARC_RATES) component.

This section discusses how to:

- View contribution rates for ARRCO.
- View contribution rates for AGIRC and CET.
- View APEC rates and flat amount for managers.
- View AGFF rates.

Pages Used to View and Maintain ARRCO and AGIRC Rates

Page Name	Definition Name	Navigation	Usage
ARRCO Rates	GPFR_ARC_RATES	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Addl Rates, Ceilings, Values, ARRCO/ AGIRC Rt FRA, ARRCO Rates	View the contribution rates for ARRCO. The PeopleSoft system is delivered with these rates, but you must maintain them when the government makes changes.
AGIRC Rates	GPFR_AGI_RATES	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Addl Rates, Ceilings, Values, ARRCO/ AGIRC Rt FRA, AGIRC Rates	View the contribution rates for AGIRC, CET, and APEC. AGIRC contributions are for the non-management pension fund, CET contributions are paid into a special AGIRC fund, and APEC contributions are paid into a managers' unemployment benefit fund. The PeopleSoft system is delivered with these rates, but you must maintain them when the government makes changes.
APEC	GPFR_APEC	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Addl Rates, Ceilings, Values, ARRCO/ AGIRC Rt FRA, APEC	View the APEC flat amount for managers. The PeopleSoft system is delivered with these rates, but you must maintain them when the government makes changes.
AGFF Rates	GPFR_AGFF_RATES	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Addl Rates, Ceilings, Values, ARRCO/ AGIRC Rt FRA, AGFF Rates	View the AGFF rates for employees (based on slices 1 and 2), and for <i>Article 36</i> and managers (based on slices A and B).

ARRCO Rates Page

Use the ARRCO Rates page (GPFR_ARC_RATES) to view the contribution rates for ARRCO.

The PeopleSoft system is delivered with these rates, but you must maintain them when the government makes changes.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Addl Rates, Ceilings, Values, ARRCO/AGIRC Rt FRA, ARRCO Rates

Image: ARRCO Rates page

This example illustrates the fields and controls on the ARRCO Rates page. You can find definitions for the fields and controls later on this page.

Rates		
Find View All First 1 of 11 Last		
*Effective Date:	01/01/2009	Status: Active
Non Managers Slice 1		
From 0 To 2859	Payee 3.000	Employer 4.500
Non Managers Slice 2		
From 2859 To 8577	Payee 8.000	Employer 12.000
Article 36 & 4/4bis Slice A		
From 0 To 2859	Payee 3.000	Employer 4.500

Non-Managers Slice 1

Displays the contribution rates for the pension fund for both employer and payee. The rates are expressed as a percentage of the payee's funding base.

The non-managers slice 1 rate is applied to funding bases below the A ceiling. The A ceiling is populated from the Ceiling page.

Non-Managers Slice 2

Displays the second rate of the pension fund contribution that is applied to non-management payees when the gross salary is between the A ceiling and the A ceiling multiplied by three, known as slice 2.

Article 36 and 4/4bis Slice A

Displays the contribution rates for slice A that is paid to ARRCO by those payees categorized by *Article 36* and *Article 4/4 bis*. This rate also applies to payees with salaries below the A ceiling.

Note: The fields From <lower limit> to <upper limit> dynamically appear based on the values entered on the Ceilings page. Ceiling values are in euros. The ceilings shown are current as of January 1, 2004.

Related Links

[Limits Page](#)

[Ceilings FRA Page](#)

AGIRC Rates Page

Use the AGIRC Rates page (GPFR_AGI_RATES) to view the contribution rates for AGIRC, CET, and APEC.

AGIRC contributions are for the non-management pension fund, CET contributions are paid into a special AGIRC fund, and APEC contributions are paid into a managers' unemployment benefit fund. The PeopleSoft system is delivered with these rates, but you must maintain them when the government makes changes.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Addl Rates, Ceilings, Values, ARRCO/AGIRC Rt FRA, AGIRC Rates

Image: AGIRC Rates page

This example illustrates the fields and controls on the AGIRC Rates page. You can find definitions for the fields and controls later on this page.

Rates			
*Effective Date:		01/01/2009	Status: Active
Find View All First 1 of 11 Last			
Slice B+GMP+Isolated Amounts			
From 2859 To 11436	Payee:	7.700	Employer: 12.600
Slice C+Isolated Amounts			
From 11436 To 22872	Payee:	7.700	Employer: 12.600
C.E.T. Slice ABC			
From 0 To 22872	Payee:	0.130	Employer: 0.220

Slice B+GMP+Isolated Amounts
(slice B + garantie minimum de points + isolated amounts)

Displays the AGIRC contribution rates for both employer and payee, for those payees with earnings between the A and B ceilings or on the specific GMP slice. The rates are expressed as a percentage of the payee's funding base.

These rates apply to payees classified by *Article 36* and *Article 4/4 bis*.

Note: GMP contributions are for the minimum guarantee of points. Payees earning below the GMP limit pay a minimum contribution as if they were earning the same as the limit.

Although the GMP contribution is based on an annual amount, the PeopleSoft system performs the calculation monthly and adjusts the contributions accordingly. The GMP ceiling is defined on the Ceilings page. The calculation of the GMP base is done by the base formula of the GMP deduction.

Isolated amounts are payments in lieu of a payee leaving a company. They are isolated from the funding base and do not accumulate contribution points towards the payee's retirement fund. They are liable for contributions, regardless of upper and lower limits. They include compensation in lieu of paid vacation; retirement allowance for an amount exceeding their legal exemption limit; and salary, premium, or bonus payments paid after departure.

Slice C+Isolated Amounts

Displays the AGIRC contribution rates for both payee and employer, for payees with a gross funding base between slice B and slice C.

These rates apply to payees classified by *Article 36* and *Article 4/4 bis*.

C.E.T. Slice ABC

Displays the CET contribution for payees and employers on a gross funding base up to the C ceiling.

These rates apply to payees classified by *Article 36* and *Article 4/4 bis*.

Related Links

[Limits Page](#)

APEC Page

Use the APEC page (GPFR_APEC) to view the APEC flat amount for managers.

The PeopleSoft system is delivered with these rates, but you must maintain them when the government makes changes.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Addl Rates, Ceilings, Values, ARRCO/AGIRC Rt FRA, APEC

Image: APEC page

This example illustrates the fields and controls on the APEC page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'APEC' tab selected. The 'Rates' section has a search bar with 'Find | View All' and pagination 'First 1 of 11 Last'. Below this, there are two tables. The first table is titled 'APEC for Managers Slice B' and has columns for 'Payee' and 'Employer'. The 'Payee' column shows '0.024' and the 'Employer' column shows '0.036'. The second table is titled 'APEC Flat Amount for Managers' and also has columns for 'Payee' and 'Employer'. The 'Payee' column shows '8.230' and the 'Employer' column shows '12.350'.

APEC for Managers Slice B

Displays the payee and employer contributions for managers with a funding base between the A and B ceilings. These contributions are paid monthly.

These rates apply to payees classified by *Article 4/4 bis*.

Note: The field names From <lower limit> to <upper limit> dynamically appear based on the values entered on the Ceilings page.

APEC Flat Amount for Managers

Displays the fixed, annual contribution paid every March by employer and payee for those payees in employment during that month.

Related Links

[Ceilings FRA Page](#)

AGFF Rates Page

Use the AGFF Rates page (GPFR_AGFF_RATES) to view the AGFF rates for employees (based on slices 1 and 2), and for Article 36 and managers (based on slices A and B).

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Addl Rates, Ceilings, Values, ARRCO/AGIRC Rt FRA, AGFF Rates

Image: AGFF Rates page

This example illustrates the fields and controls on the AGFF Rates page. You can find definitions for the fields and controls later on this page.

Rates		
Find View All First 1 of 11 Last		
*Effective Date:	01/01/2009	Status: Active
Non Managers Slice 1		
From 0 To 2859	Payee: 0.800	Employer: 1.200
Non Managers Slice 2		
From 2859 To 8577	Payee: 0.900	Employer: 1.300
Article 36 & 4/4bis Slice A		
From 0 To 2859	Payee: 0.800	Employer: 1.200
Article 36 & 4/4bis Slice B		
From 2859 To 11436	Payee: 0.900	Employer: 1.300

Non Managers Slice 1

Displays the contribution rates that are paid on slice 1 for the AGFF contribution for both employer and payee. The non-managers slice 1 rate is applied to funding bases below the A ceiling.

Non Managers Slice 2

Displays the second rate of the AGFF contribution that is applied to non-management payees when the gross funding base is between the A ceiling and the A ceiling multiplied by 3, known as slice 2.

Article 36 & 4/4bis Slice A

Displays the AGFF contribution rates for slice A that is paid by payees categorized as *Article 36* and *Article 4/4 bis*.

Article 36 & 4/4bis Slice A

Displays the AGFF contributions rates for slice B that is paid by payees categorized as *Article 36* and *Article 4/4bis*.

Note: New AGFF contributions are not included in the *reintegration fiscale* (fiscal reintegration) calculation.

Viewing Delivered ARRCO and AGIRC Deductions

This section discusses:

- ARRCO deductions.
- AGIRC deductions.
- APEC deductions.
- AGFF deductions.

ARRCO Deductions

ARRCO Deduction	Description
ARC T1 NC E	Employer ARRCO contribution for non-manager on slice 2.
ARC T1 NC S	Payee ARRCO contribution for non-manager on slice 1.
ARC T2 NC E	Employer ARRCO contribution for non-manager on slice 2.
ARC T2 NC S	Payee ARRCO contribution for non-manager on slice 2.
ARC TA A36 E	Employer ARRCO contribution for Article 36 on slice A.
ARC TA A36 S	Payee ARRCO contribution for Article 36 on slice A.
ARC TA A4 E	Employer ARRCO contribution for Article 4 on slice A.
ARC TA A4 S	Payee ARRCO contribution for Article 4 on slice A.

AGIRC Deductions

AGIRC Deduction	Description
AGI CET E	Employer C.E.T. contribution for Article 4 on slice ABC.
AGI CET S	Payee C.E.T. contribution for Article 4 on slice ABC.
AGI GMP E	Employer GMP contribution for Articles 36 and 4.
AGI GMP S	Payee GMP contribution for Articles 36 and 4.

<i>AGIRC Deduction</i>	<i>Description</i>
AGI TB A36 E	Employer AGIRC contribution for Article 36 on slice B.
AGI TB A36 S	Payee AGIRC contribution for Article 36 on slice B.
AGI TB A4 E	Employer AGIRC contribution for Article 4 on slice B.
AGI TB A4 S	Payee AGIRC contribution for Article 4 on slice B.
AGI TC A36 E	Employer AGIRC contribution for Article 36 on slice C.
AGI TC A36 S	Payee AGIRC contribution for Article 36 on slice C.
AGI TC A4 E	Employer AGIRC contribution for Article 4 on slice C.
AGI TC A4 S	Payee AGIRC contribution for Article 4 on slice C.
SI TB A36 S	Payee AGIRC isolated amounts contribution for Article 36 on slice B.
SI TB A36 E	Employer AGIRC isolated amounts contribution for Article 36 on slice B.
SI TB A4 E	Employee AGIRC isolated amounts for Article 4 on slice B.
SI TB A4 S	Payee AGIRC isolated amounts for Article 4 on slice B.
SI TC A36 E	Employer AGIRC isolated amounts contribution for Article 36 on slice C.
SI TC A36 S	Payee AGIRC isolated amounts contribution for Article 36 on slice C.
SI TC A4 E	Employee AGIRC isolated amount for Article 4 on slice C.
SI TC A4 S	Payee AGIRC isolated amounts for Article 4 on slice C.

APEC Deductions

<i>APEC Deduction</i>	<i>Description</i>
APEC FF A4 E	Employer flat amount APEC contribution for Article 4.
APEC FF A4 S	Payee flat amount APEC contribution for Article 4.
APEC TB A4 E	Employer APEC contribution for Article 4 on slice B.
APEC TB A4 S	Payee APEC contribution for Article 4 on slice B.
SI APEC TB E	Employer APEC slice B on isolated amounts.
SI APEC TB S	Payee APEC slice B on isolated amounts.

AGFF Deductions

AGFF Deduction	Description
AGFF SI A36E	Employer AGFF contribution for Article 36 on isolated amounts.
AGFF SI A36S	Payee AGFF contribution for Article 36 on isolated amounts.
AGFF SI A4 E	Employer AGFF contribution for Article 4 on isolated amounts.
AGFF SI A4 S	Payee AGFF contribution for Article 4 on isolated amounts.
AGFF T1 NC E	Employer AGFF contribution for non-manager on slice 1.
AGFF T1 NC S	Payee AGFF contribution for non-manager on slice 1.
AGFF T2 NC E	Employer AGFF contribution for non-manager on slice 2.
AGFF T2 NC S	Payee AGFF contribution for non manager on slice 2.
AGFF TA A36E	Employer AGFF contribution for Article 36 on slice A.
AGFF TA A36S	Payee AGFF contribution for Article 36 on slice A.
AGFF TA A4 E	Employer AGFF contribution for Article 4 on slice A.
AGFF TA A4 S	Payee AGFF contribution for Article 4 on slice A.
AGFF TB A36E	Employer AGFF contribution for Article 36 on slice B.
AGFF TB A36S	Payee AGFF contribution for Article 36 on slice B.
AGFF TB A4 E	Employer AGFF contribution for Article 4 on slice B.
AGFF TB A4 S	Payee AGFF contribution for Article 4 on slice B.

Setting Up Contingency Fund Contributions

This section provides an overview of contingency funds calculation and discusses how to set up contingency funds for contribution calculation.

Understanding Contingency Fund Calculations

The contingency funds functionality for Global Payroll for France integrates with the contingency funds management functionality in HR for France. The system uses arrays to retrieve new and additional data from HR that the system needs to process contingency fund deductions. After retrieving the data from the contingency contracts definition, the system creates contingency fund deductions using the Global Payroll core multiple-resolutions functionality with accumulator drivers. The system retrieves all

contracts assigned to a given payee, and then generates as many instances of the contingency contribution deduction as there are contracts for the payee.

The delivered deduction elements are the PREVOYANCE S deduction for payee contingency contributions and PREVOYANCE E for employer contingency contributions. Both deductions are driven by the same driver accumulator PRV AC PILOTE, which has the following accumulator keys: membership number, contribution type, population category, and mandatory/optional flag. Then, for each unique accumulator instance—that is, for each unique set of keys—the system can generate both employee and employer contributions.

Contingency Fund Rates

To assign rates to contingency funds you must enter them directly in the contingency contract on the Pension/Contingency Contract page in the HR application. The system retrieves these rates by the arrays reading the contract. The system stores the rates in dedicated accumulators per contingency contract. The system uses the PRV AC TX PAT accumulator for the employer rate and the PRV AC TX SAL accumulator for the employee rate.

In previous releases customers used the Contingency Rates page to view the mandatory rates for contingency funds paid by the employer for management classes *Article 36* and *Article 4/4 bis*. If you are upgrading from a previous release, you must set the inactivation date of the contingency funds rates as defined on the former Contingency Rates page to reflect the date when you want to apply the new rules.

Contingency Fund Contributions and Fiscal Net

Mandatory and optional contracts impact the fiscal net differently. For mandatory contingency contributions, the system deducts the payee part from the fiscal net. For non-mandatory contingency contributions, the system adds the employer part to the fiscal net. The system stores the values for the fiscal net in the GEN AC NET FISCAL accumulator. This accumulator has two members: the PREVOYANCE E deduction for employer contributions and the PREVOYANCE S deduction for payee contributions. The variables PRV VR ALIM S and PRV VR ALIM P determine the percentage of deductions to contribute to each member of the fiscal net accumulator. If the contingency contribution is mandatory, the variable value is 100. If the contingency contribution is non-mandatory, the variable value is 0. The system applies these percentage values to the deductions within the fiscal net accumulator.

Contingency Fund Contributions and Net to Gross Calculation

Global Payroll for France delivers the section PRV SE COTIS GN that contains the deductions dedicated to the payee and employer contributions calculations. The system uses this section when processing net to gross calculation.

DADS Setup for Contingency Fund Contributions

You define DADS data type codes on the Institution Type page of the Pension/Ctgcy Institutions component within HR. The system uses the DADS code as the pension code for DADS. Navigate to Set Up HCM, Product Related, Workforce Monitoring, Regulatory Requirements FRA, Pension/Ctgcy Institutions.

DUCS Setup for Contingency Fund Contributions

As soon as the system calculates a set of contingency contributions (employee + employers on the same base) it automatically populates the DUCS writable array that the system later uses in the DUCS computation. The codes are stored in the delivered bracket PRV BR DU CODES. The system uses the

DUCS codes in the PRV BR DU CODES bracket plus the code that you define in the institution definition in the DUCS Code field on the Institution Type page of Pension/Ctgcy Institutions component with the HR application. The system uses the DUCS code as the institution number for DUCS.

To set up DUCS for contingency funds, you must set up the PRV BR CONTRIB bracket for calculation of contingency fund contributions. You can also define whether a DUCS contact is a recipient or sender for DUCS type 903 on the Contact Definition page of the DUCS Contacts FRA component.

In releases prior to 9.0, you had to set up the DUCS contribution list for contingency funds through the family contribution code 909 on the DUCS Contributions page. If you are upgrading from a release prior to 9.0 you must set the inactivation date of the family contribution code 909 to reflect the date when you want to apply the new rules.

Setting Up Contingency Funds for Contribution Calculation

To set up Global Payroll for France to calculate contingency funds contributions:

1. Set up contract data for contingency contracts in the HR application.

This includes setting up codes for the funds to which employees contribute, defining the institutions that manage the contingency funds, and defining the contingency contracts. Global Payroll calculation process uses this information to calculate contingency funds.

2. Set up the PRV BR CONTRIB bracket for calculation of contingency fund contributions.

Within the bracket you must define:

- The element that you want the system to use as the funding base of the contingency contribution calculation when processing payroll.
- A definition for all contingency funds contributions.
- The corresponding funding base DUCS code.
- The code for positive and negative amounts for DUCS.
- The element used to define the FTE for DUCS.

As part of the setup on for contingency contracts, you must enter the base calculation type on the Pension/Contingency Contracts page. If the Base Calculation Type field value is other than base times rate, you can select Other field value and enter a formula in the Formula Name field. Use of this option overrides all delivered functionality for contingency funds calculation. For example, the declaration does not trigger and the system does not retrieve the data from HR through the arrays.

Related Links

"Understanding Pension and Contingency Fund Data (*PeopleSoft HCM 9.2: Human Resources Meet Regulatory Requirements*)"

"Pension/Contingency Contracts Page (*PeopleSoft HCM 9.2: Human Resources Meet Regulatory Requirements*)"

Viewing Delivered Contingency Fund Deductions

This section discusses contingency fund deductions delivered by Global Payroll for France.

Note: The PeopleSoft system provides a query that you can run to view the names of all delivered elements designed for France. Instructions for running the query are provided in the *PeopleSoft Global Payroll*.

Contingency Fund Deductions

<i>Contingency Fund Deduction</i>	<i>Description</i>
PREVOYANCE S	Payee part of contingency fund contributions.
PREVOYANCE E	Employer part of contingency fund contributions.

Related Links

"Understanding How to View Delivered Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

Chapter 8

Defining Levies

Understanding Levies

Levies are deductions that don't fall into obvious categories, such as URSSAF, ASSEDIC, or AGIRC. Levies are paid to several organizations with different funding bases, with different conditions, and on different dates. They cover things like training, transport, apprenticeships, CSG and CRDS contributions, and the Levy on Salaries. Some of these levies are often grouped under the heading *Other Employers Deductions* on the payslip.

Levy	Description
Additional Transportation Levy	This levy is applies based on the decision of the local transportation organization and authorities. Payment is made on the same date as URSSAF contributions and is paid to URSSAF. The rate is recorded at the establishment level.
Levy on Contingency Funds	This levy is based on an employer's contributions to the optional contingency funds. So this is a contribution on contributions. This levy is paid to the URSSAF and is paid by employers with more than 10 payees.
Professional Training	<p>Employers must allocate a percentage of their total payroll to professional training. The levy rates vary depending on whether the employer has fewer than 10 payees.</p> <p>There is a specific contribution paid by organizations that have contractual employees. The funding base for this levy is gross salary. Levy rates vary depending on whether the employer has fewer than 10 payees or whether the employer has contractual payees.</p>
Transportation	<p>This levy applies to employers with more than nine payees in the same transportation area (<i>Syndicat de transport</i>). The rate can vary, depending on the transportation area, and the funding base is gross salary. Payment is made on the same date as URSSAF contributions and is paid to the URSSAF. The levy is paid only for areas where a transportation levy is applicable.</p> <hr/> <p>Note: This rate is recorded at the establishment level.</p> <hr/>
Participation of the Construction Effort	This levy applies to employers with 10 or more payees, and the funding base is gross salary. It is paid to a registered collector organization, or the employer manages it. The levy is paid at the end of the year and is based on salaries paid during the previous 12 months.

Levy	Description
Apprenticeship	The funding base of this levy is gross salary. The rate of this levy is based on region (Alsace-Moselle or other regions) and is paid to the tax office. The postal code of the establishment is used to determine which rate must be applied.
Apprenticeship Additional	The funding base of this levy is gross salary. This additional apprenticeship levy is paid by companies submitted to the apprenticeship levy.
CSG and CRDS	Most payees are subject to this levy. The rate is based on whether the levy is CSG taxable, CSG nontaxable, or CRDS and the funding base is 95 percent of the gross salary plus the employer's contributions to the contingency fund. Payments are made to the URSSAF at the same time as other URSSAF contributions.
Levy on Salaries	Only employers that do not, in whole or in part, pay value-added tax (VAT) pay this levy. The rate varies by established brackets, and it is paid to the tax office.
Participation in the Works Council	<p>Generally, an employer with more than 50 payees has a works council, but the use of works councils varies among employers. The levy is paid to the works council.</p> <p>Contributions to the works council budget vary from organization to organization and depend on rates, funding bases, employee participation, and so on. Contributions, paid by both the employer and employee, are based on a percentage of the gross salary, profit, or revenue.</p> <p>Because this levy varies among employers, the PeopleSoft system does not provide an element to manage it. The system does, however, offer two elements that contain sample contributions, indicating rates and funding bases.</p> <p>You can activate these elements and adapt them for your own use. It is your responsibility to maintain these elements.</p>

Headcount Limits and Rates

Some levy rates are based on the headcount of the organization.

The system calculates the headcount of an organization after the payroll process. The headcount results are used during payroll processing for the following month. Therefore, the headcount might be inaccurate for the current month and you might have to override the value.

For example, during the month of May, you might have eight payees and then hire four payees in June. The system uses the headcount calculated in May to determine whether your organization is eligible for specific contributions (for example, the Levy on Contingency contributions paid by organizations with more than 10 payees). Then, in June, the system does not trigger the Levy on Contingency contributions even though this contribution should be triggered. The best solution in such a case is to override the variable that stores the headcount. This variable is GEN VR EFFECTIF SO; you can override it at the pay entity or pay group level.

Note: PeopleSoft strongly recommends that you define your pay entity to be equal to your organization.

Organizations Not Liable for a Levy

Each levy rate for organizations with fewer than nine payees is stored as a rate that is used by all organizations. If your organization is not liable for a particular levy, you can override the GEN VR EFFECTIF SO variable if the levies depending on headcount will not be triggered correctly.

Note: Modifying GEN VR EFFECTIF SO affects all contributions (and possibly some other elements) that use headcount.

PeopleSoft strongly recommends that you define your pay entity to be equal to your organization.

Transportation Levy

The transportation rate is stored at the establishment level. Because the payroll process does not manage the headcount at the establishment level, you must manage whether the levy is due. Record a rate if the levy is due or record a rate equal to 0 if it is not due.

If a payee is an itinerant worker with a transportation rate that is different from the rate applied to the establishment to which the payee is linked, override the rate at the payee level.

Note: Update the rates at the establishment level.

DUCS Considerations

The following levies appear on the URSSAF report and their DUCS codes and descriptions are as follows:

- Transportation.
- Eight percent on employers' contribution to contingency funds.
- CSG taxable, nontaxable, and CRDS.

Related Links

[Understanding ARRCO, AGIRC, and Contingency Fund Contributions](#)

[Understanding URSSAF Contributions](#)

[Generating DUCS Files Using Application Framework](#)

[Understanding Employee Counts](#)

Steps to View and Adjust Ceilings and Rates for Levies

In Global Payroll for France, you can view and update contribution rate percentages for levies as the government issues new rates. You can also update and maintain ceiling information for the tax on salaries as the government issues new rules.

To view and update rates and ceilings:

1. View variables containing the rates for levies on the Rates and Elements page.
2. View the ceiling limits used to calculate the funding bases the tax on salaries levy on the Limits page.

3. View and if necessary adjust the monetary values of the ceilings for the tax on salaries levy on the Ceilings page.
4. View and if necessary adjust the contribution percentage rates of each category of levies on the pages of the Levy Rates FRA component.

Note: PeopleSoft maintains the rates and ceilings for levies. However, you can adjust the rates and ceilings manually through the application pages when there are statutory changes. You do not have to wait for PeopleSoft updates. If you manually adjust rates, you still need to evaluate the PeopleSoft updates to determine if you want to keep your changes or apply the delivered values.

Related Links

[Reviewing and Updating Contribution Rates and Limits](#)

Establishing Levy Rates

To establish levy rates, use the Levy Rates FRA (GPFR_TAX_RATES) component.

This section discusses how to:

- Establish levy rates for levies on contingency funds and professional training.
- Establish levy rates for apprenticeship, participation of the construction effort, CSG, and CRDS levels.
- Establish levy rates on salaries.

Pages Used to Establish Levy Rates

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
General Rates 1	GPFR_TAX_RATES	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Addl Rates, Ceilings, Values, Levy Rates FRA, General Rates 1	Establish the rates for levies on contingency funds and professional training.
General Rates 2	GPFR_TAX_RATES2	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Additional Rates, Ceilings, Values, Levy Rates FRA, General Rates 2	Establish the levy rates for the Apprenticeship, Participation of the Construction Effort, CSG, and CRDS levies.
Levy on Salaries Rates	GPFR_TAX_RATES3	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Additional Rates, Ceilings, Values, Levy Rates FRA, Levy on Salaries Rates	Establish the levy tax rate on salaries for organizations that do not pay VAT or pay VAT on only less than 10 percent of sales (such as banks and insurers).

General Rates 1 Page

Use the General Rates 1 page (GPFR_TAX_RATES) to establish the rates for levies on contingency funds and professional training.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Addl Rates, Ceilings, Values, Levy Rates FRA, General Rates 1

Image: General Rates 1 page

This example illustrates the fields and controls on the General Rates 1 page. You can find definitions for the fields and controls later on this page.

General Rates 1	
*Effective Date: 01/01/2008 Status: Active	
Levy on Contingency Funds	
Contributions	8.000
Professional Training	
More than 10 payees	
Capital Formation-Time	0.100
Individual Formation Time-off	0.200
Cooperative Education	0.500
Training of the Employees	0.900
Less than 10 payees	
Professional Training	0.400
Supplement Rate	0.150
Professional Training for Contractors	1.000

The Contingency levy is paid only by organizations with more than 10 payees.

There are two sets of contribution rates for the various training funds: one is for organizations with more than 10 payees and the other is for organizations with fewer than 10 payees.

The Professional Training for Contractors levy is for all organizations that employ contractors, regardless of the number of payees in the organization.

Note: The PeopleSoft system provides these rates.

Levy on Contingency Funds

Displays the employer's contribution levy on Contingency funds. The amount is based on the employer's contribution to optional contingency funds. The levy applies only to organizations with more than 10 payees. If an organization has some optional contingency fund contributions, it must update the funding base on the Levy on Contingency fund. It is the

employer's responsibility to include these contributions in the base for calculating the contingency levy. These contributions are added to the accumulator used by this levy (the TAX AC BAS PREV SG accumulator).

Professional Training

More than 10 Payees

Displays the levy for organizations with more than 10 payees. This levy is divided among four contributions used for varying purposes in the following fields: Capital Formation-Time, Individual Formation Time-off, Cooperative Education, and Training of the Employees.

Less than 10 payees

Displays the levy for organizations with fewer than 10 payees. The employer pays a mandatory levy for professional training and a supplement rate.

Professional Training for Contractors Displays the levy that is paid by organizations employing contractors, regardless of the size of the organization.

Note: Remember to add the correct contingency funds deduction elements to the base accumulator used by the contingency funds levy.

General Rates 2 Page

Use the General Rates 2 page (GPFR_TAX_RATES2) to establish the levy rates for the Apprenticeship, Participation of the Construction Effort, CSG, and CRDS levies.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Additional Rates, Ceilings, Values, Levy Rates FRA, General Rates 2

Image: General Rates 2 page

This example illustrates the fields and controls on the General Rates 2 page. You can find definitions for the fields and controls later on this page.

Rates	
*Effective Date:	01/01/2008
Status:	Active
Apprenticeship Levy	
Other Regions	0.500
Alsace-Moselle	0.260
Apprenticeship Additional Levy	
Other Regions	0.180
Alsace-Moselle	0.180
Other	
Participation of the Construction Effort	0.450
C.S.G. non Taxable	5.100
C.S.G. Taxable	2.400
C.R.D.S.	0.500

Apprenticeship Levy

This group box displays the contribution that an employer pays for financing apprenticeships. The rate for the apprenticeship levy depends on the postal code of the establishment to which the payee is linked.

Other Regions

Displays the rate that applies to all regions, except Alsace-Moselle.

Alsace-Moselle

Displays the apprenticeship levy for the Alsace-Moselle region.

Apprenticeship Additional Levy

This group box displays the additional contribution than an employer pays for financing the apprenticeships. The rate is determined by the government. Currently the rate is identical for all regions.

Other Regions	Displays the rate that applies to all regions, except Alsace-Moselle.
Alsace-Moselle	Displays the apprenticeship levy for the Alsace-Moselle region.

Other

This group box lists the remaining levies. CSG levies are paid by all payees to finance social security and retirement funds. The payee pays the CSG levies and the CRDS levy. The funding base for the CSG and CRDS levies consists of the gross salary, the employer's contribution to the contingency fund, and departure or modification allowances that exceed a predefined amount.

Participation of the Construction Effort	Displays the rate for the Participation of the Construction Effort levy. This levy is paid by the employer based on a percentage of the gross funding base.
C.S.G. non Taxable	Displays the rate for the portion of the CSG levy that is exempt from tax.
C.S.G Taxable	Displays the rate for the portion of the levy that is taxable.
C.R.D.S.	Display the rate for the CRDS levy that is paid by payees.

Related Links

"Defining Bracket Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

Establishing Levy Rates on Salaries

Use the Levy on Salaries Rates page (GPFR_TAX_RATES3) to establish the levy tax rate on salaries for organizations that do not pay VAT or pay VAT on only less than 10 percent of sales (such as banks and insurers).

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Additional Rates, Ceilings, Values, Levy Rates FRA, Levy on Salaries Rates

Image: Levy on Salaries Rates page

This example illustrates the fields and controls on the Levy on Salaries Rates page. You can find definitions for the fields and controls later on this page.

Rates	
*Effective Date:	01/01/2008
Status:	Active
Annual Bracket 1	
Rate 17:	4.250
Annual Bracket 2	
From 7250 To 14481	4.250
Annual Bracket 3	
From 14481	9.350

The funding base for this levy is the gross salary and employer contributions to retirement and contingency funds, where applicable. There may also be a deduction for organizations that partially pay VAT. Those employer contributions to retirement and contingency funds greater than the tax limits of 19 percent and 3 percent are included in the levy on the salary funding base.

There are three rates of contribution to this levy. The rates are expressed as a percentage of the funding base. The monetary amount ranges and limits appear to the left of the rate.

Annual Bracket 1	Displays the rate for the salary levy for earnings within annual bracket 1.
Annual Bracket 2	Displays the rate for the salary levy for earnings within annual bracket 2.
Annual Bracket 3	Displays the rate for the salary levy for earnings within annual bracket 3.

Related Links

[Tax and Limits](#)

Special VAT-Exempt Element Group

A special element group (TAX EG TAXSAL) indicates which organizations are exempt from VAT contributions and are therefore liable to pay the salary levy.

Reviewing Delivered Levy Deductions

The deductions for levies are delivered with the PeopleSoft system, but it is the organization's responsibility to maintain them.

Deduction	Description	Generation Control
TAX 8% PREV	The 8 percent contingency funds tax.	TAX GC 8%PREV
TAX APPR ADD	Additional tax for apprenticeship.	TAX GC STG EXCL
TAX APPRENTI	Tax for apprenticeship (all institutions).	TAX GC STG EXCL
TAX BGT CD E	Works council tax (employer).	None.
TAX BGT CE S	Works council tax (payee).	None.
TAX CONSTRUC	Tax on construction.	TAX GC CONSTR
TAX CGFORIND	Individual education tax.	TAX GC FORM
TAX CRDS	CRDS tax.	TAX GC CSG CRDS
TAX CSG IMPO	Taxable CSG tax.	TAX GC CSG CRDS
TAX CSG NIMP	Nontaxable CSG tax.	TAX GC CSG CRDS
TAX FOCAPTEM	Capital education tax	TAX GC FORM
TAX FORALTER	Sandwich course tax.	TAX GC FORM
TAX FORMCDD	CDD education tax.	TAX GC FORMCDD
TAX FORMSAL	Employee education tax.	TAX GC STG EXCL
TAX FORMSUPL	Additional education tax.	TAX GC FORMSUP
TAX SALAIRE1	Salary tax on bracket 1.	TAX GC SALAIRE
TAX SALAIRE2	Salary tax on bracket 2.	TAX GC SALAIRE
TAX SALAIRE3	Salary tax on bracket 3.	TAX GC SALAIRE
TAX TRANSPOR	Tax on transportation.	TAX GC TRANSPORT
TAX TRANS AD	Additional transportation tax contribution.	TAX GC TRANSP ADDI

Note: The PeopleSoft system provides a query that you can run to view the names of all delivered elements that are designed for France. Instructions for running the query are provided in the *PeopleSoft Global Payroll* .

Related Links

"Understanding How to View Delivered Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

Setting Up DUCS Reporting

Understanding DUCS Reporting

Global Payroll for France enables you to create files following the DUCS norm (V4.2 COPLAT) for submitting social security contribution information to government agencies. With Global Payroll for France, you can generate the following reports, declarations, and payments:

- URSSAF monthly, quarterly, and yearly declarations—*Tableau Récapitulatif des Cotisations* (TRC)—including *Versement en Lieu Unique* (VLU).
- ASSEDIC monthly, quarterly, and yearly declarations—*Bordereau de Déclaration Annuelle* (BDA)—including *Paiement Groupe* (PG).
- ARRCO and AGIRC monthly, quarterly, and annual reports.
- Electronic payments for each declaration.

Rather than having each establishment declare and pay its contributions to the URSSAF offices in each of its locations, a company can arrange to file the VLU. That way, a company can submit one report to the URSSAF office near its headquarters, on behalf of its establishments. Similarly, a company can arrange to file PG with ASSEDIC.

Note: To conform with the DUCS norm, these declarations are submitted in electronic files—with the exception of the annual BDA and TRC, which are paper reports.

Related Links

[Understanding ARRCO, AGIRC, and Contingency Fund Contributions](#)

[Understanding URSSAF Contributions](#)

[Understanding ARRCO, AGIRC, and Contingency Fund Contributions](#)

Understanding Global Payroll Rules for DUCS

The DUCS extraction is based on amounts calculated in Global Payroll. At the end of the payroll calculation process, the REP AR DU CONTS array reads the DUCS contributions setup information and runs the REP FM DU CONTS formula for each contribution included in the DUCS contributions setup information. Upon resolution, it writes the data to the REP WA DU CONTS writable array. This data is used in the DUCS extraction that uses the GPFR_DUCS_WA record.

Setting Up DUCS Information Without Application Framework

This section is intended for customers that are migrating to a newer release from an earlier version of Global Payroll for France. These customers are willing to continue using the DUCS design from previous releases.

To set up DUCS information, use the DUCS Definitions FRA (GPFR_DUCS), DUCS Contacts FRA (GPFR_DUCS_CONTACT), AF DUCS Contributions FRA (GPFR_DUCS_CONTS), DUCS Types FRA (GPFR_DUCS_PARAM0), and DUCS Parameters FRA (GPFR_DUCS_PARAM1) components.

This section provides an overview of DUCS setup and discusses how to:

- Review declaration codes for DUCS types.
- Review identifier qualification parameters.
- Review declaration type parameters for DUCS types.
- Review contribution family parameters.
- Review amount contribution type parameters.
- Review pay mode, bank account, and reference type parameters.
- View contribution specifics.
- Map address fields.
- Record DUCS contacts.
- Enter address and phone information for DUCS contacts.
- Define the DUCS structure.
- Override DUCS rates.

Pages Used to Set Up DUCS Information

Page Name	Definition Name	Navigation	Usage
DUCS Types FRA	GPFR_DUCS_PARAM0	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Types FRA, DUCS Types FRA	View declaration codes for each DUCS type in the system and establish new ones. Reference these DUCS types when preparing and generating DUCS files. The information on this page is delivered and maintained by the PeopleSoft system.

Page Name	Definition Name	Navigation	Usage
Identifier Code	GPFR_DUCS_PARAM1	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Parameters FRA, Identifier Code	View the parameters of the identifier qualification code used in the Contact table. The information on this page is delivered and maintained by the PeopleSoft system.
Declaration Type	GPFR_DUCS_PARAM2	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Parameters FRA, Declaration Type	Set declaration type parameters for each DUCS type. The information on this page is delivered and maintained by the PeopleSoft system.
Contributions	GPFR_DUCS_PARAM3	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Parameters FRA, Contributions	Set parameters for the contribution family. The information on this page is delivered and maintained by the PeopleSoft system.
Amounts Types	GPFR_DUCS_PARAM4	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Parameters FRA, Amounts Types	Set the parameters for the amount contribution type. The information on this page is delivered and maintained by the PeopleSoft system.
Pay Informations	GPFR_DUCS_PARAM5	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Parameters FRA, Pay Informations	Set the parameters for pay mode, bank account, and reference type. The information on this page is delivered and maintained by the PeopleSoft system.
DUCS Contributions FRA	GPFR_DUCS_COT	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Contributions FRA, DUCS Contributions FRA	View the contribution specifics for each recipient: URSSAF, ASSEDIC, and AGIRC or ARRCO. The PeopleSoft system provides contribution information for these contribution families. If you create or remove contributions to the payroll calculation, you need to modify the DUCS contribution setup. This page does not apply to contingency contributions.
Address Mapping FRA	GPFR_DUCS_ADDRESS	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, Address Mapping FRA, Address Mapping FRA	Define a correspondence between PeopleSoft address fields and DUCS address records.

Page Name	Definition Name	Navigation	Usage
Contact Definition	GPFR_DUCS_CONTACT	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Contacts FRA, Contact Definition	Record the list of contacts for DUCS. Specify the role of these contacts on the DUCS Definition page.
Address and Phone	GPFR_DUCS_CONTACT1	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Contacts FRA, Address and Phone	Enter address and phone information for DUCS contacts.
DUCS Definitions FRA	GPFR_DUCS	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Definitions FRA, DUCS Definitions FRA	Define how establishments are used in creating DUCS.
DUCS Override Rates FRA	GPFR_DUCS_OVR_RATE	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Override Rates FRA, DUCS Override Rates FRA	Override a DUCS rate.

Understanding DUCS Setup

Create a DUCS file by running a batch program, in which the system searches and compiles relevant data, writes it to a specific table, and then creates a flat file and a control report. If needed, you can change the payment before posting the file.

There are three kinds of setup:

- Basic setup.

For this setup, you use the delivered DUCS Types page and the DUCS Parameters component as follows:

- Define each DUCS type on the DUCS Types page.
- Define DUCS parameters in the DUCS Parameters component.

- Contributions setup.

The DUCS Contributions page shows which elements are calculated during the payroll process and then applied to the writable array. The table created contains the elements needed for each payee and segment. The PeopleSoft system comes with this component, but you must update it in the PeopleSoft delivered deductions setup if you make any additions.

- Organization setup.

This setup involves the DUCS Contacts component and the DUCS Definition page. The PeopleSoft system does not provide this data because it depends on the organization of each company.

- Define all DUCS contacts, recipients, transmitters, informants, editors, and establishments in the DUCS Contacts component.
- Assign these contacts their specific roles on the DUCS Definition page.

This is where the report information is connected with the transmission and banking information. Transmission of payment is done using the source bank information that you establish in the system.

DUCS Types FRA Page

Use the DUCS Types FRA page (GPFR_DUCS_PARAM0) to view declaration codes for each DUCS type in the system and establish new ones.

Use the DUCS Types FRA page (GPFR_DUCS_PARAM0) to view declaration codes for each DUCS type in the system and establish new ones.

Reference these DUCS types when preparing and generating DUCS files. The information on this page is delivered and maintained by the PeopleSoft system.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Types FRA, DUCS Types FRA


Reference these DUCS types when preparing and generating DUCS files. The information on this page is delivered and maintained by the PeopleSoft system.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Types FRA, DUCS Types FRA

Image: DUCS Types FRA page

This example illustrates the fields and controls on the DUCS Types FRA page. You can find definitions for the fields and controls later on this page.



DUCS Types FRA

Declaration Code: 902

***Description:**

***Regularizations:**

Declaration Code	Displays the declaration code. Valid values are <i>901</i> for URSSAF, <i>902</i> for ASSEDIC, and <i>903</i> for AGIRC and ARRCO.
Description	Displays the description associated with the declaration code.
Regularizations	<p>Select the type of method to use for retroactive changes. Values are:</p> <p><i>Additive</i>: The regularization amount is added to the current declaration period. The retroactively recalculated period is not changed.</p> <p><i>Rectificative</i>: The regularization amount is declared in a separate record in the DUCS` declaration..</p> <hr/> <p>Note: The regularization method to be used is defined by each organization. You must contact the organizations receiving these declarations to determine which method to use. The rectificative declaration is only available with DUCS norm 4.2.</p> <hr/>

Identifier Code Page

Use the Identifier Code page (GPFR_DUCS_PARAM1) to view the parameters of the identifier qualification code used in the Contact table.

The information on this page is delivered and maintained by the PeopleSoft system.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Parameters FRA, Identifier Code

Image: DUCS Parameters FRA - Identifier Code page

This example illustrates the fields and controls on the DUCS Parameters FRA - Identifier Code page. You can find definitions for the fields and controls later on this page.

Identifier Qualification		Find	View All	First	1-2 of 2	Last
*Identifier Type:	SIRET	*Identifier Code:	5			
*Identifier Type:	Other	*Identifier Code:	ZZZ			

Identifier Qualification

Identifier Type

Displays the identifier types:

SIRET: References a previously set up establishment.

Other: References any other legal entity.

Identifier Code

Displays the identifier code: 5 for SIRET, and ZZZ for other.

Declaration Type Page

Use the Declaration Type page (GPFR_DUCS_PARAM2) to set declaration type parameters for each DUCS type.

The information on this page is delivered and maintained by the PeopleSoft system.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Parameters FRA, Declaration Type

Image: DUCS Parameters FRA - Declaration Type page

This example illustrates the fields and controls on the DUCS Parameters FRA - Declaration Type page. You can find definitions for the fields and controls later on this page.

Identifier Code	Declaration Type	Contributions	Amounts Types	Pay Informations
<div>DUCS File Type</div> <div>Find View All First 1 of 11 Last</div> <div> <div>*File Type: 913</div> <div>Description: BRC with no VLU</div> <div>+ -</div> </div> <div> <div>*DUCS Type: 901</div> <div>Urssaf</div> <div><input checked="" type="checkbox"/> Multi Establishments</div> </div>				

DUCS File Type

Multi Establishments (multiple establishments)

This option is selected if multiple establishments are allowed. This occurs for VLU filed with URSSAF and PG filed with ASSEDIC.

DUCS Type	File Type	Description
URSSAF	913	BRC with no VLU
URSSAF	914	BRC with VLU
URSSAF	915	TRC with no VLU

DUCS Type	File Type	Description
URSSAF	916	TRC with VLU
ASSEDIC	920	ADV for one establishment
ASSEDIC	921	ADV for several establishments
ASSEDIC	922	BDA for one establishment
ASSEDIC	923	BDA for multiple establishments
AGIRC/ARRCO/Other	930	Quarterly declaration
AGIRC/ARRCO/Other	931	Monthly declaration
AGIRC/ARRCO/Other	932	Annual declaration

Contributions Page

Use the Contributions page (GPFR_DUCS_PARAM3) to set parameters for the contribution family.

The information on this page is delivered and maintained by the PeopleSoft system.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Parameters FRA, Contributions

Image: DUCS Parameters FRA - Contributions page

This example illustrates the fields and controls on the DUCS Parameters FRA - Contributions page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'Contributions' tab selected. Below the tabs, there is a 'Contribution Family' section. It includes a search bar with 'Find | View All' and a list of entries. The first entry is highlighted, showing the following details:

- *Contribution Family: 905
- Description: Urssaf
- *DUCS Type: 901

DUCS Type	Contribution Family	Description
URSSAF	905	URSSAF
ASSEDIC	906	ASSEDIC
AGIRC/ARRCO/Other	907	AGIRC

DUCS Type	Contribution Family	Description
AGIRC/ARRCO/Other	908	ARRCO
AGIRC/ARRCO/Other	912	AGFF
AGIRC/ARRCO/Other	950	APEC

Amounts Types Page

Use the Amounts Types page (GPFR_DUCS_PARAM4) to set the parameters for the amount contribution type.

The information on this page is delivered and maintained by the PeopleSoft system.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Parameters FRA, Amounts Types

Image: DUCS Parameters FRA - Amounts Types page

This example illustrates the fields and controls on the DUCS Parameters FRA - Amounts Types page. You can find definitions for the fields and controls later on this page.

Contribution Type	Description
920	URSSAF Gross
921	URSSAF A-Ceiling
925	URSSAF Gross Minus (negative value)
926	URSSAF A-Ceiling Minus (negative value)
930	ASSEDIC Gross Plus (positive value)
931	ASSEDIC Lump-Sum Plus (positive value)
932	ASSEDIC Gross Minus (negative value)
933	ASSEDIC Lump-Sum Minus (negative value)

Contribution Type	Description
940	IRC Gross Plus (positive value)
941	IRC Plus (positive value)
942	IRC Lump-Sum Plus (positive value)
948	IRC Fictitious Plus (positive value)
950	IRC Gross Minus (negative value)
951	IRC Minus (negative value)
952	IRC Lump-Sum Minus (negative value)
958	IRC Fictitious Minus (negative value)

Pay Informations Page

Use the Pay Informations page (GPFR_DUCS_PARAM5) to set the parameters for pay mode, bank account, and reference type.

The information on this page is delivered and maintained by the PeopleSoft system.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Parameters FRA, Pay Informations

Image: DUCS Parameters FRA - Pay Informations page

This example illustrates the fields and controls on the DUCS Parameters FRA - Pay Informations page. You can find definitions for the fields and controls later on this page.

Pay Mode

Displays the pay mode. Valid payment descriptions are 20 (Check), 30 (Transfer), 31 (Automatic Deduction), and Z10 (Telepayment).

Bank Account Type

Displays the bank account type and description. Values are: BF (Recipient bank account) and OR (Declarant bank account).

Reference Type

Displays the reference type: *PQ* for payment by check or transfer or *CR* for payment by telepayment or automatic deduction.

DUCS Contributions FRA Page

Use the DUCS Contributions FRA page (GPFR_DUCS_COT) to view the contribution specifics for each recipient: URSSAF, ASSEDIC, and AGIRC or ARRCO.

The PeopleSoft system provides contribution information for these contribution families. If you create or remove contributions to the payroll calculation, you need to modify the DUCS contribution setup. This page does not apply to contingency contributions.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Contributions FRA, DUCS Contributions FRA

Image: DUCS Contributions FRA - Contribution Type tab page

This example illustrates the fields and controls on the DUCS Contributions FRA - Contribution Type tab page. You can find definitions for the fields and controls later on this page.

DUCS Contributions FRA

Contribution Family: 906 Assedic

Contributions Customize | Find | View All | First 1-5 of 5 Last

Contribution Type	Type	Name	Description	Order Number
1 Variable		REP VR DUCS CD RAC	100 RAC A+B-Ceiling	1
2 Variable		REP VR DUCS CD RAC	100 RAC A+B-Ceiling	2
3 Character	201		201 ASF A-Ceiling	1
4 Character	202		202 ASF B-Ceiling	1
5 Character	301		301 FNGS	1

Contribution Type Tab

Displays the contribution type and order number.

Contribution Type

Displays the type of contribution.

Type

Displays the character value for the character contribution type.

Name

Displays the name of the element for the contribution type.

Description

Displays the description of the contribution type.

Order Number

Displays the order number of the contribution type.

Base Tab

Base	Displays the element type used for the base. The row number corresponds to the contribution type listed on the Contribution Type tab.
Element Name and Description	Displays the element used for the base and its description.

Rate Tab

Employee, Column Element 1, and Name	Displays the element and element type used for the employee contribution rate. The row number corresponds to the contribution type listed on the Contribution Type tab.
Employer, Column Element 2, and Description	Displays the element and element type used for the employer contribution rate. The row number corresponds to the contribution type listed on the Contribution Type tab.
AT, Column Element 3, and Description	Displays the element and element type used for the work accident. This element is used to group together URSSAF contributions for identical work accident (AT) rates. (There are several URSSAF contributions to be paid, and these contributions are grouped on the report. The sum is provided for contributions calculated for employees having the same AT rate.) The row number corresponds to the contribution type listed on the Contribution Type tab.

Amount Tab

Employee, Column Element 1, and Name	Displays the element and element type used for the employee contribution amount. The row number corresponds to the contribution type listed on the Contribution Type tab.
Employer, Column Element 2, and Description	Displays the element and element type used for the employer contribution amount. The row number corresponds to the contribution type listed on the Contribution Type tab.

Payee FTE Tab

Payee FTE, Column Element 1, and Name	Displays the element used to determine headcounts. The row number corresponds to the contribution type listed on the Contribution Type tab.
Payee FTE, lump sum cont (lump-sum contributions), Column Element 2, and Description	Displays the element that is used to calculate headcounts contributing to a lump-sum contribution (for example, the APEC lump-sum contribution).
Transportation	Select if the element is an URSSAF transportation contribution. When selected, the DUCS norm indicates that the contribution generates a TRS record instead of a COT record.

Additional Transportation

Select if the element is an URSSAF additional transportation contribution. When selected, the DUCS norm indicates that the contribution generates a TAT record instead of a COT record.

Amount Type 1 Tab**Positive**

As required, each contribution is assigned an amount type 1, as defined in the DUCS requirements. Once the total of contributions is calculated, the Positive amount type is reported in the DUCS file if this sum is positive.

Negative

As required, each contribution is assigned an amount type 1, as defined in the DUCS requirements. Once the total of contributions is calculated, the Negative amount type is reported in the DUCS file if this sum is negative.

Amount Type 2 Tab**Positive**

As required, each contribution is assigned an amount type 2, as defined in the DUCS requirements. Once the total of contributions is calculated, the Positive amount type is reported in the DUCS file if this sum is positive.

Negative

As required, each contribution is assigned an amount type 2, as defined in the DUCS requirements.

Related Links

[Understanding ARRCO, AGIRC, and Contingency Fund Contributions](#)

[Understanding URSSAF Contributions](#)

Address Mapping FRA Page

Use the Address Mapping FRA page (GPFR_DUCS_ADDRESS) to define a correspondence between PeopleSoft address fields and DUCS address records.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, Address Mapping FRA, Address Mapping FRA

Image: Address Mapping FRA page

This example illustrates the fields and controls on the Address Mapping FRA page. You can find definitions for the fields and controls later on this page.

This page allows users to define a correspondence between PeopleSoft address fields and DUCS address records. This mapping is recommended to extract the INSEE code declared in transportation and additional transportation contributions for each establishment.

See [Setting Up DADS Extraction](#).

Contact Definition Page

Use the Contact Definition page (GPFR_DUCS_CONTACT) to record the list of contacts for DUCS.

Specify the role of these contacts on the DUCS Definition page.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Contacts FRA, Contact Definition

Image: DUCS Contacts FRA - Contact Definition page

This example illustrates the fields and controls on the DUCS Contacts FRA - Contact Definition page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'Contact Definition' page for DUCS Contacts FRA. The page has two tabs: 'Contact Definition' and 'Address and Phone'. The 'Contact Definition' tab is active. The form contains the following fields and controls:

- Contact Definition:** GF0579
- *Description:** Groupe Mornay
- OPS Identification:** Find | View All | First | 1 of 1 | Last
- *DUCS Type:** 903 (Agirc Arrco Other)
- Contact Type:** Sender (selected), Recipient
- *Identifier Type:** SIRET
- Establishment ID:** GFZ01 (Etablissement Mornay)
- Reference 1:** GF0579

OPS Identification

DUCS Type

Select the DUCS type. Valid values are determined by what is established on the DUCS Types page.

Identifier Type

Select *Other*, *SIREN*, or *SIRET*.

Establishment ID

Enter the identification number, as requested in the DUCS requirements.

Reference 1

Enter the reference 1, as requested in the DUCS requirements. This field is specific for ARRCO, AGIRC, or contingency fund. Enter the number communicated by your retirement and contingency fund organizations.

Contact Type

Use this group box to define whether a DUCS contact is a recipient or sender for DUCS type 903 (Agirc Arrco Other).

Sender

Select to indicate that the contact is a sender of DUCS.

Recipient

Select to indicate that the contact is a recipient of DUCS.

Address and Phone Page

Use the Address and Phone page (GPFR_DUCS_CONTACT1) to enter address and phone information for DUCS contacts.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Contacts FRA, Address and Phone

Image: DUCS Contacts - Address and Phone page

This example illustrates the fields and controls on the DUCS Contacts - Address and Phone page. You can find definitions for the fields and controls later on this page.

The screenshot displays the 'Address and Phone' tab of the DUCS Contacts page. It shows the contact definition 'GF0579' for 'Groupe Mornay'. The 'Address Definition' section includes a dropdown for 'Address Type' (set to 'Establishment Address'), a text field for 'Establishment ID (Address)' (containing 'GFZ01'), and a search icon next to 'Etablissement Mornay'. The 'Phone Definition' section includes a text field for 'Service / Correspondent' (containing 'Correspondant Mornay'), a dropdown for 'Contact Type' (set to 'Establishment Phone'), and a text field for 'Establishment ID (Phone)' (containing 'GFZ01') with a search icon next to 'Etablissement Mornay'. The 'Label' section at the bottom has an empty 'Email Address' field.

Address Definition

Address Type

Select *Company Address*, *Establishment Address*, or *Other*.

Address

Enter the address. If the address type is:

Other: Click this link to access the secondary page for the address.

Company Address: Enter the company SIREN number.

Establishment Address: Enter the establishment SIRET number.

Phone Definition

Service / Correspondent	Enter the service or correspondent.
Contact Type	Select <i>Company Phone</i> , <i>Establishment Phone</i> , or <i>Other</i> .
Establishment ID (Phone)	Depending upon the contact type, the phone number may be hidden.

Label

Email Address	Enter the email address of the contact.
----------------------	---

DUCS Definitions FRA Page

Use the DUCS Definitions FRA page (GPFR_DUCS) to define how establishments are used in creating DUCS.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Definitions FRA, DUCS Definitions FRA

Image: DUCS Definitions FRA page

This example illustrates the fields and controls on the DUCS Definitions FRA page. You can find definitions for the fields and controls later on this page.

The screenshot displays the 'DUCS Definitions FRA' page. At the top, there are input fields for 'DUCS Code' (GFASSED01), 'DUCS Type' (902 Assedic), and '*DUCS Adressees' (GFASS046). Below these, a 'Declaration Definition' section contains various fields: '*Recipient Name ("MR")' (GFASS046), '*Transmitter Name ("FR")' (GF001 ASS), '*Informant Name ("DT")' (GFB), 'Editor Name ("AE")' (GFBUIL01), 'Payment Name ("PAI")' (empty), '*File Type' (920), 'Payment Type' (Z10), and 'Source Bank ID' (GF14001). Each field has a magnifying glass icon for lookup. Below the declaration section is an 'Establishments List' table with one entry: '1 *Establishment: GFB01', which is marked as the 'Main Establ'. The page includes navigation controls like 'Find', 'View All', 'First', '1 of 1', and 'Last'.

DUCS Addressee	Select the addressee from the DUCS Contact Definition component. This information is for your information only; it's not a DUCS requirement.
-----------------------	--

Declaration Definition

Recipient Name ("MR")

Select the recipient of the DUCS file. The Contact Definition field on the Contact Definition page determines available values. The recipient name corresponds to the recipient of the DUCS declaration as defined in the DUCS requirement book.

Transmitter Name ("FR")

Select the transmitter name. The Contact Definition field on the Contact Definition page determines available values. In general, it is the establishment responsible for sending the DUCS file.

Informant Name ("DT")

Select the informant name. The Contact Definition field on the Contact Definition page determines available values. You must indicate here the legal declaring entity (*Entité Juridique Déclarante*) as defined in the DUCS requirement book. For URSSAF and ASSEDIC, the informant should be companies, while for ARRCO, AGIRC, and contingency funds, it is the member.

Editor Name ("AE")

Select the editor name. The Contact Definition field on the Contact Definition page determines available values. You must indicate here the name of the party preparing the declaration for you.

Payment Name ("PAI")

Select the payment name. The payment name is the name of the contact who is in charge of the payment of the contributions. The Contact Definition field on the Contact Definition page determines available values.

File Type

Select a file type from the DUCS Parameters - Declaration Type page. Available values correspond to the relevant DUCS type.

Payment Type

Select a payment mode or method. Valid values are determined by the Pay Mode field on the DUCS Parameters - Pay Information page: *Check*, *Transfer*, *Automatic Deduction*, and *Telepayment*.

Source Bank ID

Select the bank account to be debited. You must have established a source bank account.

Establishments List

Establishment

Select the declared entities. For the URSSAF and the ASSEDIC, it is *Establishments*; for ARRCO, AGIRC, and contingency funds, it is the payment center (*centre payeur*). If you are setting up VLU or PG, enter at least two establishments; otherwise, enter one establishment. The Contact Definition field on the Contact Definition page determines available values.

Main Establ. (main establishment)

If you are setting up VLU or PG, select this check box to indicate the main establishment, as defined by the DUCS requirements. This information produce a type FZ record as defined in the DUCS requirement book.

Related Links

[Declaration Type Page](#)

[Pay Informations Page](#)

[Understanding Banking Setup and Processing for France](#)

DUCS Override Rates FRA page

Use the DUCS Override Rates FRA page (GPFR_DUCS_OVR_RATE) to override a DUCS rate.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Override Rates FRA, DUCS Override Rates FRA

Image: DUCS Override Rates FRA

This example illustrates the fields and controls on the DUCS Override Rates FRA. You can find definitions for the fields and controls later on this page.

DUCS Override Rates FRA										
DUCS Code: GFASSED01		ASSEDIC Certif 01								
DUCS Type: 902		Assedic								
Override DUCS Rates										
	*Contribution	*Year	Company	Establishment ID	Recipient Name ("MR")	Establishment	Rate Type	Rate to Override	Rate to Use	*Status
1	301	2006	GFD	GFC01			Non AT			Active

Use this page to override rates that have been incorrectly used and declared in a previous DUCS declaration.

Contribution

Enter the contribution type for which a rate override is necessary.

Year

Enter the year for which the override must apply.

Company and Establishment ID

Enter the company and establishment to which the override applies if the DUCS type is equal to 901 (URSSAF) or 902 (ASSEDIC).

Recipient Name ("MR") and Establishment

Enter the recipient name and establishment to which the override applies if the DUCS type is equal to 903 (AGIRC, ARRCO, or OTHER).

Rate Type

For URSSAF contribution type, select *Non AT* to override the global contribution type rate, or *AT rate* to override the work accident rate related to the contribution type you selected.

Rate to Override

Enter the current rate used for the contribution, year, company, and establishment.

Rate to Use

Enter the new rate to use.

Status

Select whether the rate override is *Active* or *Inactive*.

Setting Up DUCS Information Using Application Framework

This section is intended for new customers or existing customers migrating to a newer release of Global Payroll for France, that are willing to move to the DUCS design based on Application Framework.

To set up DUCS information, use the DUCS Definitions FRA (GPFR_DUCS), DUCS Contacts FRA (GPFR_DUCS_CONTACT), AF DUCS Contributions FRA (GPFR_DUCS_CONTS), DUCS Types FRA (GPFR_DUCS_PARAM0), and DUCS Parameters FRA (GPFR_DUCS_PARAM1) components.

This section provides an overview of DUCS setup and discusses how to:

- Review declaration codes for DUCS types.
- Review identifier qualification parameters.
- Review declaration type parameters for DUCS types.
- Review contribution family parameters.
- Review amount contribution type parameters.
- Review pay mode, bank account, and reference type parameters.
- View contribution specifics.
- Record DUCS contacts.
- Enter address and phone information for DUCS contacts.
- Define the DUCS structure.

Pages Used to Set Up DUCS Information

Page Name	Definition Name	Navigation	Usage
DUCS Types FRA	GPFR_DUCS_PARAM0	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Types FRA, DUCS Types FRA	View declaration codes for each DUCS type in the system and establish new ones. Reference these DUCS types when preparing and generating DUCS files. The information on this page is delivered and maintained by the PeopleSoft system.
Identifier Code	GPFR_DUCS_PARAM1	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Parameters FRA, Identifier Code	View the parameters of the identifier qualification code used in the Contact table. The information on this page is delivered and maintained by the PeopleSoft system.

Page Name	Definition Name	Navigation	Usage
Declaration Type	GPFR_DUCS_PARAM2	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Parameters FRA, Declaration Type	Set declaration type parameters for each DUCS type. The information on this page is delivered and maintained by the PeopleSoft system.
Contributions	GPFR_DUCS_PARAM3	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Parameters FRA, Contributions	Set parameters for the contribution family. The information on this page is delivered and maintained by the PeopleSoft system.
Amounts Types	GPFR_DUCS_PARAM4	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Parameters FRA, Amounts Types	Set the parameters for the amount contribution type. The information on this page is delivered and maintained by the PeopleSoft system.
Pay Informations	GPFR_DUCS_PARAM5	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Parameters FRA, Pay Informations	Set the parameters for pay mode, bank account, and reference type. The information on this page is delivered and maintained by the PeopleSoft system.
AF-DUCS Contributions FRA	GPFR_DUCS_CONTRIBS	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, AF-DUCS Contributions FRA, AF-DUCS Contributions FRA	View the BRC rows
Contact Definition	GPFR_DUCS_CONTACT	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Contacts FRA, Contact Definition	Record the list of contacts for DUCS. Specify the role of these contacts on the DUCS Definition page.
Address and Phone	GPFR_DUCS_CONTACT1	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Contacts FRA, Address and Phone	Enter address and phone information for DUCS contacts.
DUCS Definitions FRA	GPFR_DUCS	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Definitions FRA, DUCS Definitions FRA	Define how establishments are used in creating DUCS.

Understanding DUCS Setup

Create a DUCS file by running a batch program, in which the system searches and compiles relevant data, writes it to a specific table, and then creates a flat file and a control report. If needed, you can change the payment before posting the file.

There are three kinds of setup:

- Basic setup.

For this setup, you use the delivered DUCS Types page and the DUCS Parameters component as follows:

- Define each DUCS type on the DUCS Types page.
- Define DUCS parameters in the DUCS Parameters component.

- Contributions setup.

The BRC rows are set up in the details of the BRC Node Set of the DUCS 4.2 application of Application Framework

- Organization setup.

This setup involves the DUCS Contacts component and the DUCS Definition page. The PeopleSoft system does not provide this data because it depends on the organization of each company.

- Define all DUCS contacts, recipients, transmitters, informants, editors, and establishments in the DUCS Contacts component.
- Assign these contacts their specific roles on the DUCS Definition page.

This is where the report information is connected with the transmission and banking information. Transmission of payment is done using the source bank information that you establish in the system.

DUCS Types FRA Page

Use DUCS Types FRA page to view declaration codes for each DUCS type in the system and establish new ones. Reference these DUCS types when preparing and generating DUCS files. The information on this page is delivered and maintained by the PeopleSoft system.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Types FRA, DUCS Types FRA

Image: DUCS Types FRA page

This example illustrates the fields and controls on the DUCS Types FRA page. You can find definitions for the fields and controls later on this page.

The screenshot shows a web form titled "DUCS Types FRA". It contains three fields: "Declaration Code" with the value "902", "*Description:" with the value "Assedic", and "*Regularizations:" with a dropdown menu showing "Additive".

Declaration Code

Displays the declaration code. Valid values are *901* for URSSAF, *902* for ASSEDIC, and *903* for AGIRC and ARRCO.

Description

Displays the description associated with the declaration code.

Regularizations

Select the type of method to use for retroactive changes. Values are:

Additive: The regularization amount is added to the current declaration period. The retroactively recalculated period is not changed.

Rectificative: The regularization amount is declared in a separate record in the DUCS' declaration..

Note: The regularization method to be used is defined by each organization. You must contact the organizations receiving these declarations to determine which method to use. The rectificative declaration is only available with DUCS norm 4.2.

Identifier Code Page

Use the Identifier Code page (GPFR_DUCS_PARAM1) to view the parameters of the identifier qualification code used in the Contact table.

The information on this page is delivered and maintained by the PeopleSoft system.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Parameters FRA, Identifier Code

Image: DUCS Parameters FRA - Identifier Code page

This example illustrates the fields and controls on the DUCS Parameters FRA - Identifier Code page. You can find definitions for the fields and controls later on this page.

Identifier Qualification		Find View All	First	1-2 of 2	Last
*Identifier Type:	SIRET	*Identifier Code:	5	+	-
*Identifier Type:	Other	*Identifier Code:	ZZZ	+	-

Identifier Qualification

Identifier Type

Displays the identifier types:

SIRET: References a previously set up establishment.

Other: References any other legal entity.

Identifier Code

Displays the identifier code: 5 for SIRET, and ZZZ for other.

Declaration Type Page

Use the Declaration Type page (GPFR_DUCS_PARAM2) to set declaration type parameters for each DUCS type.

The information on this page is delivered and maintained by the PeopleSoft system.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Parameters FRA, Declaration Type

Image: DUCS Parameters FRA - Declaration Type page

This example illustrates the fields and controls on the DUCS Parameters FRA - Declaration Type page. You can find definitions for the fields and controls later on this page.

DUCS File Type

Multi Establishments (multiple establishments)

This option is selected if multiple establishments are allowed. This occurs for VLU filed with URSSAF and PG filed with ASSEDIC.

DUCS Type	File Type	Description
URSSAF	913	BRC with no VLU
URSSAF	914	BRC with VLU
URSSAF	915	TRC with no VLU
URSSAF	916	TRC with VLU
ASSEDIC	920	ADV for one establishment
ASSEDIC	921	ADV for several establishments
ASSEDIC	922	BDA for one establishment
ASSEDIC	923	BDA for multiple establishments
AGIRC/ARRCO/Other	930	Quarterly declaration
AGIRC/ARRCO/Other	931	Monthly declaration
AGIRC/ARRCO/Other	932	Annual declaration

Contributions Page

Use the Contributions page (GPFR_DUCS_PARAM3) to set parameters for the contribution family.

The information on this page is delivered and maintained by the PeopleSoft system.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Parameters FRA, Contributions

Image: DUCS Parameters FRA - Contributions page

This example illustrates the fields and controls on the DUCS Parameters FRA - Contributions page. You can find definitions for the fields and controls later on this page.

<i>DUCS Type</i>	<i>Contribution Family</i>	<i>Description</i>
URSSAF	905	URSSAF
ASSEDIC	906	ASSEDIC
AGIRC/ARRCO/Other	907	AGIRC
AGIRC/ARRCO/Other	908	ARRCO
AGIRC/ARRCO/Other	912	AGFF
AGIRC/ARRCO/Other	950	APEC

Amounts Types Page

Use the Amounts Types page (GPFR_DUCS_PARAM4) to set the parameters for the amount contribution type.

The information on this page is delivered and maintained by the PeopleSoft system.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Parameters FRA, Amounts Types

Image: DUCS Parameters FRA - Amounts Types page

This example illustrates the fields and controls on the DUCS Parameters FRA - Amounts Types page. You can find definitions for the fields and controls later on this page.

Contribution Type	Description
920	URSSAF Gross
921	URSSAF A-Ceiling
925	URSSAF Gross Minus (negative value)
926	URSSAF A-Ceiling Minus (negative value)
930	ASSEDIC Gross Plus (positive value)
931	ASSEDIC Lump-Sum Plus (positive value)
932	ASSEDIC Gross Minus (negative value)
933	ASSEDIC Lump-Sum Minus (negative value)
940	IRC Gross Plus (positive value)
941	IRC Plus (positive value)
942	IRC Lump-Sum Plus (positive value)
948	IRC Fictitious Plus (positive value)
950	IRC Gross Minus (negative value)
951	IRC Minus (negative value)
952	IRC Lump-Sum Minus (negative value)
958	IRC Fictitious Minus (negative value)

Pay Informations Page

Use the Pay Informations page (GPFR_DUCS_PARAM5) to set the parameters for pay mode, bank account, and reference type.

The information on this page is delivered and maintained by the PeopleSoft system.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Parameters FRA, Pay Informations

Image: DUCS Parameters FRA - Pay Informations page

This example illustrates the fields and controls on the DUCS Parameters FRA - Pay Informations page. You can find definitions for the fields and controls later on this page.

Pay Informations					
*Pay Mode:	20	Pay Mode Description:	Check		
Bank Account Type:		Bank Account Type Description:			
Reference Type:	PQ	Reference Type Description:	Social Reference		

Pay Mode

Displays the pay mode. Valid payment descriptions are 20 (*Check*), 30 (*Transfer*), 31 (*Automatic Deduction*), and Z10 (*Telepayment*).

Bank Account Type

Displays the bank account type and description. Values are: *BF* (*Recipient bank account*) and *OR* (*Declarant bank account*).

Reference Type

Displays the reference type: *PQ* for payment by check or transfer or *CR* for payment by telepayment or automatic deduction.

AF-DUCS Contributions FRA Page

Use the AF-DUCS Contributions FRA page (GPFR_DUCS_CONTRIBS) to .

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, AF-DUCS Contributions FRA, AF-DUCS Contributions FRA

Image: AF-DUCS Contributions FRA page

This example illustrates the fields and controls on the AF-DUCS Contributions FRA page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'AF-DUCS Contributions FRA' page. At the top, it displays 'Contribution Family: 906 Assedic'. Below this is a table titled 'Contributions' with columns: Contribution Type, Contribution Name, Element Name, Description, *Record Code, Order Number, *Set Number, and Details. The table contains two rows:

	Contribution Type	Contribution Name	Element Name	Description	*Record Code	Order Number	*Set Number	Details
1	Character	301		301 FNGS	COT	1	Set1	Details
2	Variable		REP VR DUCS CD RAC	100 RAC A+B-Ceiling	COT	1	Set1	Details

Contribution Type

Displays the type of contribution.

Contribution Name

Displays the name of the contribution for the contribution type.

Element Name

Displays the name of the element for the contribution type.

Description

Displays the description of the contribution type.

Details

Click to access the DUCS Contribution Details page. Use this page to set up the DUCS text file and PDF report.

Related Links

[Understanding ARRCO, AGIRC, and Contingency Fund Contributions](#)

[Understanding URSSAF Contributions](#)

Contact Definition Page

Use the Contact Definition page (GPFR_DUCS_CONTACT) to record the list of contacts for DUCS.

Specify the role of these contacts on the DUCS Definition page.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Contacts FRA, Contact Definition

Image: DUCS Contacts FRA - Contact Definition page

This example illustrates the fields and controls on the DUCS Contacts FRA - Contact Definition page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'Contact Definition' page for DUCS Contacts FRA. The page has two tabs: 'Contact Definition' and 'Address and Phone'. The 'Contact Definition' tab is active. The form contains the following fields and values:

- Contact Definition:** GF0579
- *Description:** Groupe Mornay
- OPS Identification:** Find | View All | First | 1 of 1 | Last
- *DUCS Type:** 903 (Agirc Arrco Other)
- Contact Type:** Sender (selected), Recipient
- *Identifier Type:** SIRET
- Establishment ID:** GFZ01 (Etablissement Mornay)
- Reference 1:** GF0579

OPS Identification

DUCS Type

Select the DUCS type. Valid values are determined by what is established on the DUCS Types page.

Identifier Type

Select *Other*, *SIREN*, or *SIRET*.

Establishment ID

Enter the identification number, as requested in the DUCS requirements.

Reference 1

Enter the reference 1, as requested in the DUCS requirements. This field is specific for ARRCO, AGIRC, or contingency fund. Enter the number communicated by your retirement and contingency fund organizations.

Contact Type

Use this group box to define whether a DUCS contact is a recipient or sender for DUCS type 903 (Agirc Arrco Other).

Sender

Select to indicate that the contact is a sender of DUCS.

Recipient

Select to indicate that the contact is a recipient of DUCS.

Address and Phonem Page

Use the Address and Phone page (GPFR_DUCS_CONTACT1) to enter address and phone information for DUCS contacts.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Contacts FRA, Address and Phone

Image: DUCS Contacts - Address and Phone page

This example illustrates the fields and controls on the DUCS Contacts - Address and Phone page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'Address and Phone' tab of the 'DUCS Contacts' page. The 'Contact Definition' is 'GF0579 Groupe Mornay'. The 'Address Definition' section includes 'Address Type' (Establishment Address) and 'Establishment ID (Address)' (GFZ01) with a magnifying glass icon and the text 'Etablissement Mornay'. The 'Phone Definition' section includes 'Service / Correspondent' (Correspondant Mornay), 'Contact Type' (Establishment Phone), and 'Establishment ID (Phone)' (GFZ01) with a magnifying glass icon and the text 'Etablissement Mornay'. The 'Label' section includes an 'Email Address' field.

Address Definition

Address Type

Select *Company Address*, *Establishment Address*, or *Other*.

Address

Enter the address. If the address type is:

Other: Click this link to access the secondary page for the address.

Company Address: Enter the company SIREN number.

Establishment Address: Enter the establishment SIRET number.

Phone Definition

Service / Correspondent	Enter the service or correspondent.
Contact Type	Select <i>Company Phone</i> , <i>Establishment Phone</i> , or <i>Other</i> .
Establishment ID (Phone)	Depending upon the contact type, the phone number may be hidden.

Label

Email Address	Enter the email address of the contact.
----------------------	---

DUCS Definitions Page

Use the DUCS Definitions FRA page (GPFR_DUCS) to define how establishments are used in creating DUCS.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DUCS Definitions FRA, DUCS Definitions FRA

Image: DUCS Definitions FRA page

This example illustrates the fields and controls on the DUCS Definitions FRA page. You can find definitions for the fields and controls later on this page.

The screenshot displays the 'DUCS Definitions FRA' page. At the top, there are input fields for 'DUCS Code' (GFASSED01), 'DUCS Type' (902 Assedic), and '*DUCS Adressees' (GFASS046). Below these, a 'Declaration Definition' section contains various fields: '*Recipient Name ("MR")' (GFASS046), '*Transmitter Name ("FR")' (GF001 ASS), '*Informant Name ("DT")' (GFB), 'Editor Name ("AE")' (GFBUIL01), 'Payment Name ("PAI")' (empty), '*File Type' (920), 'Payment Type' (Z10), and 'Source Bank ID' (GF14001). Each field has a magnifying glass icon for lookup. Below the declaration section is an 'Establishments List' table with one entry: '1 *Establishment: GFB01', which is marked as the 'Main Establ'. The page includes navigation controls like 'Find', 'View All', 'First', '1 of 1', and 'Last'.

DUCS Addressee	Select the addressee from the DUCS Contact Definition component. This information is for your information only; it's not a DUCS requirement.
-----------------------	--

Declaration Definition

Recipient Name ("MR")

Select the recipient of the DUCS file. The Contact Definition field on the Contact Definition page determines available values. The recipient name corresponds to the recipient of the DUCS declaration as defined in the DUCS requirement book.

Transmitter Name ("FR")

Select the transmitter name. The Contact Definition field on the Contact Definition page determines available values. In general, it is the establishment responsible for sending the DUCS file.

Informant Name ("DT")

Select the informant name. The Contact Definition field on the Contact Definition page determines available values. You must indicate here the legal declaring entity (*Entité Juridique Déclarante*) as defined in the DUCS requirement book. For URSSAF and ASSEDIC, the informant should be companies, while for ARRCO, AGIRC, and contingency funds, it is the member.

Editor Name ("AE")

Select the editor name. The Contact Definition field on the Contact Definition page determines available values. You must indicate here the name of the party preparing the declaration for you.

Payment Name ("PAI")

Select the payment name. The payment name is the name of the contact who is in charge of the payment of the contributions. The Contact Definition field on the Contact Definition page determines available values.

File Type

Select a file type from the DUCS Parameters - Declaration Type page. Available values correspond to the relevant DUCS type.

Payment Type

Select a payment mode or method. Valid values are determined by the Pay Mode field on the DUCS Parameters - Pay Information page: *Check*, *Transfer*, *Automatic Deduction*, and *Telepayment*.

Source Bank ID

Select the bank account to be debited. You must have established a source bank account.

Establishments List

Establishment

Select the declared entities. For the URSSAF and the ASSEDIC, it is *Establishments*; for ARRCO, AGIRC, and contingency funds, it is the payment center (*centre payeur*). If you are setting up VLU or PG, enter at least two establishments; otherwise, enter one establishment. The Contact Definition field on the Contact Definition page determines available values.

Main Establ. (main establishment)

If you are setting up VLU or PG, select this check box to indicate the main establishment, as defined by the DUCS requirements. This information produce a type FZ record as defined in the DUCS requirement book.

Related Links

[Declaration Type Page](#)

[Pay Informations Page](#)

"Using Banking Information with Local Country Processes (*PeopleSoft HCM 9.2: Global Payroll*)"

Setting Up DADS Reporting

Understanding DADS Reporting

The PeopleSoft system provides the means for preparing DADS. DADS setup is based on the rules delivered in Global Payroll for France and following the Unified DADS (DADS-U) norm, and it can be modified to fit your particular needs.

Understanding Global Payroll Rules for DADS

The amounts to be declared in the DADS file must be stored in Global Payroll results. Some elements—those beginning with the prefix DAS—have been created for the DADS (for example, DAS VR BASE TAX SAL1) and are stored in the payroll results. Some elements, already present in the payroll results, are declared in the DADS, for example, URS FM BASE A, which retrieves the URSSAF funding base limited to the A ceiling.

You can update the provided Not Maintained formulas to populate these accumulators in situations not managed by the PeopleSoft system.

<i>PeopleSoft Formula</i>	<i>Customer Formula</i>	<i>Function</i>
DAS FM BASE EXO	DAS FM BASE EX UTI	Used to update the accumulators DAS AC BASE BR EXO and DAS AC BASE PL EXO.
DAS FM BASE PL SPE	DAS FM BASE PL UTI	Used to update the accumulator DAS AC BASE PLF SP.
DAS FM BASE SPECIF	DAS FM BASE SP UTI	Used to update the accumulator DAS AC BASE BRT SP.
DAS FM SOMMES ISOL	DAS FM SOM ISO UTI	Used to update the accumulators DAS AC SI BRUTES and DAS AC SI PLAFONNE.

Writable Arrays Used to Support DADS

Two writable arrays are delivered by PeopleSoft: DAS WA SITUAT S41 and DAS WA SITUAT S45.

DAS WA SITUAT S41

This writable array is used for determining the changes in S41 situations. The S41 situations in the DADS file correspond to periods of time during which the employee parameters remain identical. For each

payroll segment calculated, an entry is created in the WA record. If a value stored in the writable array changes from one segment to the next, it may cause a change of situation in the DADS declaration.

DAS WA SITUAT S45

This writable array is used to prepare the declarations for contingency funds. The values stored in the array are used to populate the S45.G01.01 records. The writable array is populated based on the mandatory contingency contributions calculated for Executive and Acting Executive. For specific contingency contributions implemented by customers, the logic implemented for the mandatory contributions must also be implemented. The different elements stored in the writable array must be populated based on the contingency contributions parameter. Once these elements are populated, DAS WA SITUAT S45 must be called in order to store the information for the later extraction. Users must ensure that this array is called for each contingency fund to be declared for one employee. This can be set up by using a post-process formula that calls DAS WA SITUAT S45 in the definition of the contingency contributions or by inserting the writable array in a section, after each contingency contribution.

Understanding DADS Data Structures

The PeopleSoft system provides all the structures and records included in the DADS-U requirement book. Some of these structures or records apply to unsupported industries or rules; they are defined as inactive. The inactive records (included in active structures) can be modified and declared depending on the setup that you create to populate them. The population of the records depends on several data sources. Some are directly computed by the DADS processes, while some others come from the Global Payroll Results table.

Setting Up DADS Extraction

To set up DADS extraction, use the DADS Data Types FRA (GPFR_DA_DATTYP), DADS Reporting Estabs FRA (GPFR_DA_ESTREP), DADS Recipients FRA (GPFR_DA_RECIP), DADS Situations FRA (GPFR_DA_SIT), and DADS Sending References FRA (GPFR_DA_SNDREF) components.

Use the CI_GPFR_DA_DATTYP component interface to import data into the tables for the DADS Data Types FRA component. Use the CI_GPFR_DA_SIT component interface to import data into the tables for the DADS Situations FRA component.

This section discusses how to:

- Define data types.
- View structures and records.
- Set up elements.
- Define situations.
- Define reporting establishments.
- Define sending references.

Pages Used to Set Up DADS Extraction

Page Name	Definition Name	Navigation	Usage
DADS Data Types FRA	GPFR_DA_DATTYP	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DADS Data Types FRA, DADS Data Types FRA	View data types and translate values. This list contains information for each data type defined by unified DADS requirements.
DADS Situations FRA	GPFR_DA_SIT	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DADS Situations FRA, DADS Situations	Define the DADS beginning and end situation codes.
DADS Reporting Estabs FRA (reporting establishment)	GPFR_DA_ESTREP	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DADS Reporting Estabs FRA, DADS Reporting Estabs FRA	Define reporting establishments and contacts.
DADS Sending References FRA	GPFR_DA_SNDREF	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DADS Sending References FRA, DADS Sending References FRA	Define the layout of the output file. One file is a set of declared companies, which comprise groups of employees called establishments.
Application Definition	GPFR_AF_APPL	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, Define Application/NodeSet FRA, Application Definition	Define the labels for node sets, nodes and attributes for a given Application Framework application.
Define Parameter Template	GPFR_AF_PRM_TEMPLT	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, Define Application/NodeSet FRA, Define Parameter Template	Define parameters, grouped into functions, for a given application.
Node Set Definition	GPFR_AF_NODE_SET	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, Define Application/NodeSet FRA, Node Set Definition	Lists all possible node sets, such as DADS-U messages.

Page Name	Definition Name	Navigation	Usage
Security Record List	GPFR_AF_APP_SECRTY	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, Define Application/NodeSet FRA, Security Record List	In the event of incorrect setup, this transaction avoids the accidental deletion of important tables, such as the JOB table, while executing Data Object Names.
Node Set Nodes	GPFR_AF_NODE_SET_N	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, Define Node Set Details FRA, Node Set Nodes	Displays the list of node sets defined in the Define Application / Node Set component, on the Node Set Definition page, and the list of structures associated with each node set.
Node Set Attributes	GPFR_AF_NODE_SET_A	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, Define Node Set Details FRA, Node Set Attributes	Provides another view of the records associated with a node set, which enables you to see all of the records, for all structures.
Define Node FRA	GPFR_AF_NODE	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, Define Node FRA	Contains all of the data used for the processing of structures and records. However, you can override some parameters at the Run Control stage.
SQL Entity Definition/ Mapping	GPFR_AF_SQL_ENTITY	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, Define SQL Entity FRA, SQL Entity Definition/Mapping	Define an SQL entity for a given application.
SQL Entity Template	GPFR_AF_SQL_TMPLT	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, Define SQL Entity FRA, SQL Entity Template	Define an SQL entity template.
Define Data Object Name FRA	GPFR_AF_DON	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, Define Data Object Name FRA	Define a data object name, which is the final object executed to populate a given record. A DON is composed of one or more SQL sequences.
Define Mapping Code FRA	GPFR_AF_MAPCODE_PG	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, Define Mapping Code FRA	Defines the one-to-one mappings between HCM data and DADS-U official codes. Complex relationships between HCM data and DADS-U codes must be managed through a Data Object Name.

Page Name	Definition Name	Navigation	Usage
View SQL/DON Relationship FRA	GPFR_AF_SQLDON_REL	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, View SQL/DON Relationship FRA	View the relationships between SQL and data object names.
View DON/Attr Relationship FRA (view data object name/attribute relationship FRA)	GPFR_AF_DONATR_REL	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, View DON/Attr Relationship FRA	View the records that use a data object name.
Duplicate Objects FRA	GPFR_AF_DUP_DATA	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, Duplicate Objects FRA	Duplicate SQL entities and DONs, for customization purposes.

DADS Data Types Page

Use the DADS Data Types FRA page (GPFR_DA_DATTYP) to view data types and translate values.

This list contains information for each data type defined by unified DADS requirements.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DADS Data Types FRA, DADS Data Types FRA

Image: DADS Data Types FRA page

This example illustrates the fields and controls on the DADS Data Types FRA page. You can find definitions for the fields and controls later on this page.

DADS Data Types FRA

Data Type: ABSTYP ***Description:** Absence Type

Codes				Customize Find View All First 1-5 of 47 Last	
	*Data Type Code	*Status	*Code Description		
1	01	Inactive	Unused	+	-
2	02	Inactive	Maternity or Paternity	+	-
3	04	Active	Work Accident	+	-
4	05	Active	Disability (First Category)	+	-
5	06	Active	Disability (Second Category)	+	-

Translate Values			Customize Find View All First 1 of 1 Last	
	Read Code	Code		
1			+	-

Use data types to translate DADS records used in the report. When you add or modify a DADS data record, data types provide a view of the description instead of only the DADS record code number.

Read Code

Maps the field value to the DADS structure code that you specify in the associated Code field. The field value is extracted from the PeopleSoft application.

Code

DADS structure code translated from the Read Code field.

DADS Situations FRA Page

Use the DADS Situations FRA page (GPFR_DA_SIT) to define the DADS beginning and end situation codes.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DADS Situations FRA, DADS Situations

Image: DADS Situations FRA page

This example illustrates the fields and controls on the DADS Situations FRA page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'DADS Situations FRA' page with the following fields and values:

- Sequence Number:** 100
- Action:** Hire (dropdown menu)
- Reason Code:** (empty text box with a magnifying glass icon)
- Situation Change:** COMPANY (text box with a magnifying glass icon)
- Reason Begin:** Hire (dropdown menu)
- Reason End:** (empty dropdown menu)
- *Status:** Active (dropdown menu)

There is a '001' label to the right of the 'Reason Begin' dropdown.

In the DADS report, structure S41 contains social and fiscal data as well as gross salary, net salary, contribution funding base, and so forth. A new S41 is created each time an employee DADS situation changes. Using the DADS Situations FRA page, you can link PeopleSoft employee record changes to corresponding DADS situation changes.

Action

Enter the action that triggers the situation change.

Reason Code

Enter the reason for the action that triggers the DADS situation change.

Situation Change

Enter the type of situation change. Values vary depending on the employee record. Values are stored in the DADS writable array *DAS WA SITUAT S41*.

Reason Begin

Enter the reason corresponding to the new DADS situation. Values are defined in the *STREAS* data type. The code

corresponding to the Reason Begin is declared in the record S41.G01.00.002.001

Reason End

Select the reason corresponding to the end of the previous DADS situation. Values are defined in the *ENDREAS* data type.

If no value is selected in the Reason Begin field, this field corresponds to the end reason of the current DADS situation.

The code corresponding to the Reason End will be declared in the record S41.G01.00.004.001.

Note: The latest DADS norm provides up to 5 records for declaring the situation change code— S41.G01.00.002.001 to 005 for the Reason Begin code and S41.G01.00.004.001 to 005 for the Reason End code. The different records and codes are used when there are several changes that occur on the same date. For example, if an employee is promoted to manager and transferred to a new establishment on the same date, those two actions can be declared using situation change codes.

However, PeopleSoft only populates *one* reason begin and reason end code. The reason for this is that the codes 002 to 005 are optional and informational. PeopleSoft records only one code based on the sequence order used to record the situation change. In the example above, if the sequence order for the employee category change (from non-manager to manager) is 100 and the sequence order for the establishment transfer is 200, then only the category change reason codes will be declared.

Reporting Estabs FRA Page

Use the DADS Reporting Estabs FRA page (GPFR_DA_ESTREP) to define reporting establishments and contacts.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DADS Reporting Estabs FRA, DADS Reporting Estabs FRA

Image: DADS Reporting Estabs FRA page

This example illustrates the fields and controls on the DADS Reporting Estabs FRA page. You can find definitions for the fields and controls later on this page.

DADS Reporting Estabs FRA

Reporting Definition: GF5RD1 *Description: GF5 Reporting Establishment 1

*Reporting Establishment: GF5AR Etbl Administratif Regress

*Communication Mode: Electronic Mail

Communication Detail: JULES MARTIN

Name Prefix: [Dropdown]

Name: [Text Field]

Contacts Find | View All First 1 of 1 Last

Name Prefix: [Dropdown]

*Name: Jules Martin

*Status: Active

*Intervention Domain: Administrative

*Contact Email: Jules_Martin@laposte.net

*Contact Phone: [Text Field]

Contact Fax: [Text Field]

DADS Reporting Establishment page allows defining the reporting establishments and the contacts within these establishments. The reporting establishments created are referenced in the Sending Reference setup.

Reporting Establishment

Enter the establishment code. One reporting establishment must be set up for each declared company. Use this page to define the reporting establishment and the information related to the establishment (such as people to contact and communication mode with DADS) that is used in structure 10.

Communication Mode

Enter the transmission method for the DADS log file. Valid values are *Electronic Mail* and *Postal Mail*.

Communication Detail

Values vary depending on the communication mode:

Electronic Mail: Enter the email address.

Postal Mail: Enter specific contact data, such as a phone number.

Name Prefix

Enter the name prefix for person who can be contacted by the DADS organization representatives.

Name	Enter the name of the person who can be contacted by the DADS organization representatives.
Contacts	
Name Prefix	Enter the name prefix for the contact.
Name	Enter up to three active contacts for each reporting establishment.
Status	Select a status. A status of <i>Active</i> indicates that a contact must be used.
Intervention Domain	Select <i>Administrative</i> , <i>Computing</i> , or <i>Other</i> .
Contact Email	Enter the email address of the contact. <hr/> Note: The <i>underscore</i> character "_" may be used in this field. <hr/>
Contact Phone	Enter the phone number of the contact.
Contact Fax	Enter the fax number of the contact.

DADS Sending References FRA Page

Use the DADS Sending References FRA page (GPFR_DA_SNDREF) to define the layout of the output file.

One file is a set of declared companies, which comprise groups of employees called establishments.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Social Security / Insurance, DADS Sending References FRA, DADS Sending References FRA

Image: DADS Sending References FRA page

This example illustrates the fields and controls on the DADS Sending References FRA page. You can find definitions for the fields and controls later on this page.

DADS Sending References FRA

Sending reference: KF1SR *Description: Company KF1 sending references

*Transmitter Establishment: KF001 Paris - Headquarter

*Reporting Definition Contact: KF1RE Estab. KF001 Contacts for DADS ☐ No Employee

Declaration Find | View All First 1 of 1 Last

*Company: KF1 Business Institute - France

*Main Establishment: KF001 Paris - Headquarter

*Declaring Establishment: KF001 Paris - Headquarter

*Reporting Definition: KF1RE Estab. KF001 Contacts for DADS

Client Number: 123455

Establishments

☐ All ☒ Include ☐ Exclude

Establishments		Customize	Find	First	1-2 of 2	Last
	*Establishment	Description				
1	KF001	Paris - Headquarter				
2	KF002	Bordeaux - Le Banville				

Sending reference information is used in structures S10 and S20 to identify the transmitter and company of the declaration. It is also used in structure S80 to identify establishments to be included in the declaration.

Transmitter Establishment

Enter an establishment defined in the PeopleSoft HR Establishment table. The transmitter establishment is declared in record S10.G01.00.001 and S10.G01.00.001.002 (transmitter SIREN plus NIC number).

Reporting Definition Contact

Select an entry defined on the Reporting Establishment page. The reporting establishment contact must be indicated for the sending reference. A reporting establishment contact can be used several times for different sending references. Data from the reporting definition populates the records S10.G01.00.013.001 and S10.G01.00.013.002 (log file recipient SIREN and NIC) as well as the transmitter contact information (S10.G01.01 structure).

No Employee

Select if there are no employees to declare for the report.

If selected, all the establishments in the Establishment List in the page must have employed no staff during the declared year. The file generated must have a recipient type of None. No S30

structure must be present in the file; the record S20.G01.00.004.001 is equal to the code 05 for DADS-U empty and the record S20.G01.00.004.002 is equal to the code 55 for Code Type declaration None.

Company

Enter the company that is part of the DADS file for the defined sending reference. The company is declared in the record S20.G01.00.001 (SIREN number).

Main Establishment

Enter a main establishment. For each declared company, the main establishment must appear on the establishments list. The main establishment is declared in the record S20.G01.00.008 (main establishment NIC).

Declaring Establishment

Enter a declaring establishment. You can use the value that appears in the Main Establishment field. The declaring establishment is reported in the record S20.G01.00.010 (NIC number).

Reporting Definition

Select an entry defined on the Reporting Establishment page. The Reporting Establishment must be indicated for each company. The reporting definition information is used to declare the records S20.G01.00.014.001 to S20.G01.00.016 (SIREN plus NIC numbers).

Client Number

Optional. Enter a client number. The client number is declared in the record S20.G01.00.013. This field can be used when the transmitter of the DADS attributes a client to the companies he declares, for example for accounting firms performing declarations for their clients.

All

Select to declare all establishments.

Include

Select to declare only the establishments displayed on the page.

Exclude

Select to declare all establishments *except* those listed on the page.

Establishment and Description

Enter at least one establishment. The establishment lists the employees to be processed.

Understanding Overtime Payments

Understanding Overtime Payments

Global Payroll for France delivers a number of different earnings to process overtime hours. The majority of these earnings are defined with an override level of Positive Input, have a calculation rule of Unit x Rate x Percent, and have the Unit (overtime hours) component of their calculation rule set to *Payee Level*. This means that they must be assigned to individual payees before they can be processed, and require positive input for the *Unit* component. You can use these earning elements as delivered, modify them to suit your needs, or create your own overtime earning elements.

The delivered overtime earnings assume that overtime hours are calculated outside of Global Payroll for France and then entered into the system through positive input in one of three ways:

- If you are using PeopleSoft Time and Labor, the hour data is fed into the Global Payroll system through the automated positive input functionality.
- If your organization uses a third-party time and labor application, the calculation of the different types of work hours is done by that application, and then the data is passed to Global Payroll for processing through automated positive input.
- If you are not using a time and labor application to manage your hourly data, then you must enter the data manually.

Note: Some payees, such as executive managers, are not subject to normal overtime rules. Such payees may not be eligible for overtime. PeopleSoft does not control whether overtime must be paid for each category of payee. It is your responsibility to decide whether to input extra hours for these payees.

Warning! PeopleSoft does not restrict the input of hours that are over the legal limit. It is up to you to apply the law to your setup. If you want an automated method by which to control the input of hours to ensure that they do not exceed the legal limit, you can use PeopleSoft Time and Labor.

Related Links

"Understanding Positive Input (*PeopleSoft HCM 9.2: Global Payroll*)"

Understanding Paid Overtime

Global Payroll for France delivers several different earnings to pay payees for hours worked over the standard scheduled hours. For example HRS COMP 125, HRS SUP 125%, and HRS SUP 150% are used to pay employees for overtime hours at a rate that exceeds the standard hourly rate.

Related Links

[Earnings](#)

Understanding Time Off in Lieu of Pay

Some overtime may be taken as time off in lieu of pay. These overtime hours are known as *bonus* hours.

There are two different types of time off in lieu of pay:

- *Repos compensateur*.

This type of compensation adheres to statutory rules for its calculation. The rules stipulate that when a payee works over a certain number of hours in a week, the payee is entitled to receive some hours paid with a surcharge as well as some compensatory time off instead of being paid for the overtime.

PeopleSoft delivers the earning HRS REP COMP to process *repos compensateur*. To grant time off, use positive input to enter the hours of compensatory time in the *Unit* component of the earning's calculation rule (Unit x Rate x Percent). Because this earning is used to enter time off in lieu of compensation, it does not resolve to a payment amount. Instead, it contributes the units entered by positive input to the following two compensation hours accumulators:

- HRS AC RCOMP EX PP.

This accumulator stores the time off in lieu of compensation that can be taken by the payee. Each time a payee accumulates seven hours of time off in lieu, the accumulator HRS AC RCOMP EX PP increases by one day.

- HRS AC RCOMP NE PP.

This accumulator stores any time off in lieu of pay that is less than seven hours. Each time a payee accumulates seven hours of compensatory time off, this accumulator decreases by seven hours.

The hours that you enter using positive input are split between the HRS AC RCOMP EX PP and HRS AC RCOMP NE PP accumulators based on whether the payee can take time off or the payee has not yet acquired complete entitlement to time off. A payee is entitled to take time off once they accumulate seven hours.

To reduce the number of hours available to a payee when he or she takes time off, assign the absence take ABT REP COMP to the payee on the Absence Event Entry page with the begin and end dates of the absence, or enter partial hours if the payee takes less than a full day off. The system uses the formula ABS FM DRTS RCOMP to retrieve the hours entered on this page and to reduce the hours available in the *repos compensateur* accumulators.

Note: Payees can take time off in lieu of pay by the half-day or complete day. When a payee takes a paid half-day or complete day off, the entitlement is decreased accordingly.

Note: When payees acquire compensatory time off, the system prints a message on the payslip to notify them that the entitlement is available along with a message indicating the date by which they must use the time off. The date by which they must use the time off is the end of the current pay period plus two months.

Note: Global Payroll for France does not manage the loss of entitlements if a payee does not take time off in lieu of pay during the two months following the acquisition of the entitlement.

- *Récupération d'heures.*

This type of compensation is not controlled by regulations and companies can decide whether to apply this rule. It enables a payee to take some compensatory time off instead of being paid for overtime.

PeopleSoft delivers the earnings HRS BOS 100% and HRS BOS 10% to process *Récupération d'heures*. To grant time off, use positive input to enter the hours of compensatory time in the *Unit* component of each earning's calculation rule (Unit x Rate x Percent). The hours entered for the earning HRS BOS 100% (converts 100 percent of the hours to compensatory time off) and HRS BOS 10% (converts 10 percent of the hours to compensatory time off) are added to the accumulator HRS AC HRS BOS SG. Because these earnings are used to enter time off in lieu of compensation, they do not calculate a monetary amount; instead, they pass the hours entered in the *Unit* component to the HRS AC HRS BOS SG accumulator.

To reduce the number of hours available to a payee when he or she takes time off, assign the earning HRS BOS 100% or HRS BOS 10% to the payee using positive input and enter the hours taken (using a negative value) in the *Unit* component of each earning's calculation rule. The system then reduces the hours available in the *récupération d'heures* accumulator.

Note: When payees acquire a compensatory day off, the system prints a message on the payslip to notify them that the entitlement is available.

Related Links

"Absence Processing (*PeopleSoft HCM 9.2: Global Payroll*)"

"Understanding Positive Input (*PeopleSoft HCM 9.2: Global Payroll*)"

Delivered Overtime Elements

This section discusses the earning element and other delivered elements.

Earnings

PeopleSoft delivers earnings for overtime, but does not maintain these elements.

Global Payroll for France assumes that the pay period is monthly and that the pay period always starts on the first day of the month. If the pay period is monthly, but the pay period does not start on the first day of the month, you can modify the formula HRS FM PRIMES TX to put the first day of the month in the variable HRS VR PRIM DATE. If the pay period is not monthly, you should evaluate the delivered rules and adapt them to the pay periods used by your organization.

The usual calculation method for overtime earnings is Unit x Rate or Unit x Rate x Percent, where:

- *Unit* is a variable that stores the number of hours (entered by positive input).
- *Rate* is a formula that calculates the hourly rate.

- *Percent* is a variable that contains the percentage of the surcharge. Modify this percentage if your company is over the legal percentage.

Note: If you want to pay overtime hours at rates different than those stipulated by law, modify the earning elements to do so. In some cases—for example, HRS SUP 125%—PeopleSoft includes the surcharge percentage in the name of the element. If you modify the percentage in such a delivered element, then the name of the element and the percentage it represents will not match and this could prove confusing to your payroll personnel. In such cases, PeopleSoft recommends that you create your own elements.

Earning	Description
HRS COMP	Number of additional hours paid (100 percent).
HRS COMP 125	Number of additional hours paid (125 percent).
HRS BON 100%	Number of bonus hours paid (100 percent).
HRS BON 10%	Surcharge of 10 percent for bonus hours.
HRS BOS 100%	Converts 100% of overtime hours to compensatory time off (Récupération d'heures). This earning resolves to zero and is used to populate the bonus hours accumulator.
HRS BOS 10%	Converts 10% of overtime hours to compensatory time off (Récupération d'heures). This earning resolves to zero and is used to populate the bonus hours accumulator.
HRS SUP 125%	Number of overtime hours (125 percent).
HRS SUP 150%	Number of overtime hours (150 percent).
HRS DIMANCHE	Number of Sunday hours.
HRS DE NUIT	Number of night hours.
HRS CONGES	Number of holiday hours.
HRS REP COMP	Number of hours of time off in lieu of compensation. HRS REP COMP resolves to zero and is used to populate the time off in lieu of compensation entitlement accumulators.
JOURS SUP	Number of TEPA extra workdays

The element group HRS EG OVERTIME includes all of the earnings used to process overtime hours.

Note: PeopleSoft delivers a query that you can run to view the names of all delivered elements designed for France.

Managing Rates Used in Overtime Earning Calculations

In Global Payroll for France, the rate used to calculate overtime pay is based on the employee's base salary. If, during a month, the base salary changes and there is element segmentation of the base salary element, the overtime rate could change from one week to another. For this reason, for all of the earnings listed in the previous table except HRS REP COMP, you can override the system element RATE AS OF

DATE. This system element is used to determine the correct hourly rate for overtime work. By default, the RATE AS OF DATE is the segment end date, and the system retrieves the rate that is active as of this date. However, you can define the RATE AS OF DATE as the last day of the week if you want overtime pay to be calculated with the effective-dated rate code for the specific week in which the overtime hours were worked. For example, if your standard pay period is monthly, but you enter overtime on a weekly basis, you might need to override the RATE AS OF DATE when there is a salary change in the middle of the month, as the rate code values used in the calculation of overtime can vary based on salary amounts, and the correct rate to apply would be the rate in effect for the employee just prior to the salary change—not the rate in effect at the end of the monthly pay period. If you do not need to capture salary changes during the month and prefer to apply the same rate for the full month, you can simply record one positive input entry with the sum of each week's overtime hours.

Note: To override the *rate as of date*, enter a supporting element override for the system element RATE AS OF DATE at the same time that you enter positive input for the overtime earning. The system will then use the rate code that is "active" as of this date.

Managing Premiums

In some cases, the rates used to calculate overtime pay may consist of the rate code value plus a premium added to this value. In Global Payroll for France, the premiums that are added to the standard rate are contained in the accumulator HRS AC CAL PRIM SG. You are responsible for maintaining this accumulator, and for maintaining the formula HRS FM SALBAS TX H which retrieves the correct rate code values. To add a premium to the base salary used to calculate overtime pay, modify the HRS FM SALBAS TX H formula as follows:

ER[SALAIRE BASE] + AC[HRS AC CAL PRIM SG]>> FM[HRS FM SALBAS TX H]

Note: PeopleSoft does not deliver earnings that use the specific rate premium setup described here; if you decide to create such earnings, you should define the premium and add it to the accumulator HRS AC CAL PRIM SG so that it is considered in the overtime rate calculation.

Note: You can use the system element RATE AS OF DATE to retrieve the premiums of the current month or of the previous month. This is because some companies pay overtime hours with a one-month delay.

Other elements

Variables	Description
HRS VR TX MAX RED	Maximum employee contribution reduction rate (21.50% as of October 1, 2007)
HRS VR TX DED HS	Maximum employer contribution deduction per overtime hour for companies over 20 employees (0.50 EUR as of October 1, 2007)
HRS VR NB JRS AN	Number of workdays per year for fixed days contracts (<i>convention de forfait en jours</i>). The default value is 218 as of October 1, 2007. This number may be under 218 and is utilized to calculate the daily rate for extra workdays (JOURS SUP) compensation. Only workdays beyond the 218 threshold give credit to a 25% salary increase.

Variables	Description
HR VR 700 PCT	Used in accumulators (HRS AC SUP RED SG and HRS AC HRS SG) to convert JOURS SUP days into hours.
HRS VR DUCS E	Variable used for DUCS setup.
HRS VR DADS TYPE	Variable used to manage hour type for DADS-U report (01 for overtime hours, 02 for complementary hours, 03 for extra workdays.)
TAX VR TX CRDS	This variable is used to manage CRDS contribution and takes TEPA impact into account.
TAX VR TX CSG IMP	This variable is used to manage CSG contribution and takes TEPA impact into account.

Formulas	Description
HRS FM TX RED HS	Average contribution rate during the month when overtime or complementary hours are paid to the employee.
HRS FM TX JOUR	Daily salary rate for an employee with a fixed days contract.
HRS FM POST RED	Post process formula applying to 3 deductions: RED HRS SUP, RED HRS COMP et DED HRS E and enabling you to: <ul style="list-style-type: none"> • Make reductions negative, when triggered, to display a negative amount on payslip • Not to trigger reduction calculation when the gross salary amount is negative • Not to trigger reduction calculation when the gross amount of overtime or complementary hours is negative • Limit the reduction amount to the mandatory contribution total amount of the month (no credit for the next month's in case the potential reduction is greater than the contribution amount for the month.)
HRS FM CSG BASE HS	Overtime funding base for deductible CSG and CRDS contributions.
HRS FM CSG RATE HS	Total CSG and CRDS contribution rate applying to TEPA overtime hours.
URS FM FILLON	The fillon reduction formula was updated for TEPA as of October 1, 2007.
DAS FM GENERAL	The general DADS formula was updated for TEPA as of October 1, 2007.
URS FM FILL HRS MO	Inactive as of as of October 1, 2007.
URS FM FILL GEN	Inactive as of as of October 1, 2007.

Formulas	Description
URS FM FILL MAJO	Inactive as of as of October 1, 2007.
GEN FM PROR HRS	Inactive as of as of October 1, 2007.

Variables	Description
RED HRS SUP	Total employee contribution reduction amount related to overtime hours.
RED HRS COMP	Total employee contribution reduction amount related to complementary hours.
DED HRS E	Total employer contribution deduction amount related to overtime hours.
CSG-CRDS HS	Total CSG and CRDS amount related to TEPA overtime hours or extra workdays.

Variables	Description
JOURS SUP	To enter extra workdays beyond 218 days per year

Variables	Description
HRS AC SUP RED SG	Employee contribution reduction base for overtime hours.
HRS AC COMP RED SG	Employee contribution reduction base for complementary hours.
HRS AC HRS SG	Overtime hours number giving credit for employer contribution deduction.
HRS AC COT S SG	Employee mandatory contribution total amount for the month, which is the base for contribution reduction.
GEN AC RFR SG	Fiscal Revenue of Reference.
HRS AC RED SG	Total reduction base for the employee (used only for DUCS processing).
HRS AC DADS AMT	Employee contribution reduction base for overtime hours, in a DADS period.
HRS AC DADS UNIT	TEPA overtime hours number, in a DADS period.
GEN AC BRUT SG	The monthly gross accumulator has been updated to include TEPA elements.
URS AC COT S SG	The monthly gross accumulator has been updated to include employee contribution elements.

Variables	Description
URS AC COT E SG	The monthly gross accumulator has been updated to include employer contribution elements.
GEN AC NET FISCAL	The monthly fiscal net accumulator has been updated to include TEPA elements.
TAX AC ASS CSG SG	The monthly CSG base accumulator has been updated to include TEPA elements.

Variables	Description
TAX SE CSG CRDS	RED HRS SUP, RED HRS COMP, DED HRS E, CSG-CRDS HS deductions have been added to this section.
HRS SE HEURES SUP	JOURS SUP earning has been added to this section.

Variables	Description
URS EG COTISATIONS	RED HRS SUP, RED HRS COMP, DED HRS E deductions have been added to this element group.
HRS EG OVERTIME	JOURS SUP earning has been added to this element group.
TAX EG TAXES	The CSG-CRDS HS deduction has been added to this element group.

Additional delivered TEPA updates are:

- DUCS set up (included the 260 code for CSG and CRDS).
- The standard payslip (GPFR01) includes a row for deductible CSG and CRDS

Related Links

"Defining Earning Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

"Defining Deduction Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

"Understanding Positive Input (*PeopleSoft HCM 9.2: Global Payroll*)"

"Understanding How to View Delivered Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

Understanding Allowances

Understanding Allowance Types

A payee may be entitled to a variety of allowances, paid in addition to the regular salary. These allowances are in four main categories:

- Allowances linked to a breach of contract (termination):
 - Compensation in lieu of paid holidays not yet taken.
 - Severance allowance.
 - End of fixed-term contract allowance.
 - Retirement allowance.
- Transportation allowances:
 - Paris.
 - Provinces.
 - Mileage allowance.

Note: There are different allowance rates for people living in Paris and in the provinces. Motorists may also be entitled to a mileage allowance for driving to work.

- Benefits in kind:
 - Meal benefit in kind.
 - Lodging benefit in kind.
 - Car benefit in kind.
 - Other benefits in kind.
- Meal and travel allowances:
 - Meal/travel allowance.
 - Meal tickets.

Some allowances are subject to social contributions and taxes and some are not.

Related Links

[Understanding Allowance Types](#)

Understanding Allowance Calculation

This section discusses how Global Payroll for France determines eligibility for allowances and calculates the allowance values for:

- Compensation in lieu of paid holidays not taken (ICCP).
- Severance allowance.
- End of fixed-term contract allowance.
- Retirement allowance.
- Transportation allowances.
- Independent transportation allowance.
- Benefits in kind.
- Meal allowances.
- Meal tickets.

Related Links

"Understanding Overrides (*PeopleSoft HCM 9.2: Global Payroll*)"

"Reviewing Positive Input (*PeopleSoft HCM 9.2: Global Payroll*)"

[The AFB Process Section](#)

[Understanding Net Guarantee Processing](#)

Compensation in Lieu of Paid Holidays Not Taken

When a contract is terminated and the payee has not taken his or her vacation entitlement, he or she is entitled to payment in lieu of the holiday entitlement. In the case of termination because of gross misconduct (*faute lourde*), compensation in lieu of paid holidays is not paid for vacation acquired during the current period.

Earning	Description
CP ICCP A2, CP ICCP A1, and CP ICCP A	Triggered by a termination, irrespective of the Action/Reason code. These earnings calculate compensation in lieu of paid holiday up to three years in the past.
CP ICCP 1A	Calculates compensation for the current vacation year. This earning is dependent on the Action/Reason for the termination. The bracket IND BR FIN CONT assigns a value to the variable IND VR DR ICCP that determines whether the earning is processed. You must update the bracket to indicate the Action/Reason codes that trigger this earning.

Here is an example of how the allowance is calculated.

If a company's vacation year begins on June 1 and ends on May 31 of the following year and a payee leaves the company on October 2, 2010, the compensation in lieu of paid holiday earnings are calculated as follows:

- CP ICCP A2 retrieves the allowance for vacation not taken during the vacation year June 1, 2007 through May 31, 2008.
- CP ICCP A1 retrieves the allowance for vacation not taken during the vacation year June 1, 2008 through May 31, 2009.
- CP ICCP A retrieves the allowance for the vacation year June 1, 2009 through May 31, 2010.
- CP ICCP 1A retrieves the allowance for vacation granted (but not taken) between June 1, 2010 and October 2, 2010 (if the bracket retrieves a value for the variable IND VR DT ICCP equal to 1 for the departure reason).

The amount of compensation in lieu of paid holidays (days not taken) is calculated as follows:

1. The balance for the period is calculated using the 1/10th rule.
2. The balance for the period is calculated using the salary uphold rule.
3. The more favorable of the two balances is used.

Note: This allowance is paid with the final paycheck. It is liable to social contributions and is taxable.

Severance Allowance

Severance allowance is activated at the time of final pay. There is a statutory minimum severance allowance, but many companies have agreements that pay more than this amount.

Earning	Description
IND LICENC	This earning calculates the statutory severance allowance. The salary base for the allowance is the gross salary average of the last three months or the gross salary average of the last 12 months, whichever is greatest.
IND LICENC 2	This earning is provided as sample data. You can use it if you have a severance allowance defined by the collective agreement with rules that differ from the statutory ones. If you decide to use it, you must determine when you want it to be triggered and adapt the calculation to meet your needs.

Note: To qualify for this allowance, the payee should be laid off (except for reasons of gross misconduct) and should have had at least two years of uninterrupted service with the same employer. Fixed-term contractors, apprenticeship contractors, and other payees with some specific contracts are not eligible for the severance allowance.

These brackets are used to calculate this allowance:

- IND BR DT SPEC.

This bracket controls, based on contract type, entitlement to the different allowances that can be paid when a termination occurs.

- IND BR FIN CONT.

This bracket controls, by action/reason value, entitlement to the different allowances that can be paid when a termination occurs.

- IND BR IND LIC.

This bracket can be used to define the values used to calculate the severance allowance. By default, this bracket returns the values defined by law (that is, payment of 1/10th the monthly salary per year of seniority up to ten years, and payment of 1/15th the monthly salary per year of seniority after ten years of employment). You can modify these values as needed.

Related Links

[Understanding Allowance Brackets](#)

End of Fixed-Term Contract Allowance

PeopleSoft delivers the earning IND FIN CONT to calculate the end of fixed-term contract allowance.

As defined by PeopleSoft, this earning is calculated when:

- A payee is terminated with an action of TER (termination) and a reason of EAB (employer's anticipated breach) or EFT (end of fixed-term contract).

This entitlement is set up in the bracket IND BR FIN CONT by specifying the values of the action and reason variables (GEN VR ACTION and GEN VR MOTIF) that entitle a payee to the allowance. In this bracket, the return column variable IND VR DT IFC returns a 1 or a 0: a 1 if the allowance can be paid, and a 0 if the allowance cannot be paid.

- The payee has a contract type of CDD.

This entitlement is set up in the bracket IND BR DT SPEC by specifying the value of the contract type system element (CONTRACT TYPE) that entitles a payee to the allowance. In this bracket, the return column variable IND VR DP IFC returns a 1 or a 0: a 1 if the allowance can be paid, and a 0 if the allowance cannot be paid.

To modify this allowance, or to calculate the allowance when other action/reason values are entered in the Job Data component and for other contract types, you must specify the valid action/reasons and contract types in the brackets IND BR FIN CONT and IND BR DT SPEC.

See [IND BR FIN CONT \(End of Contract Entitlements\)](#), [IND BR DT SPEC \(Contract Type Specific Entitlements\)](#).

Retirement Allowance

The entitlement for retirement allowance varies depending on whether the retirement is voluntary or imposed by the employer. The payments are triggered with a generation control when the contract end date is included in the pay period. Enter the contract end date in the Contract Data page in PeopleSoft HR.

Earning	Description
IND DEP RET	This earning is used to calculate voluntary retirement allowances.
IND MISE RET	This earning is used to calculate statutory retirement allowances.

Eligibility for this allowance depends on contract type and the reason for termination. The calculation of the allowance amount is dependent on the employee's labor agreement and category.

The following brackets are used to calculate the retirement allowance:

- IND BR DT SPEC.
- IND BR FIN CONT.
- IND BR DEP RET.

Note: The bracket IND BR DEP RET retrieves the rule for calculating the voluntary retirement allowance IND DEP RET. The statutory retirement allowance, IND MISE RET, uses the same calculation rules and formulas as the severance allowance. It does not use the bracket IND BR DEP RET.

Related Links

[Understanding Allowance Brackets](#)

Transportation Allowances

Payees living or working in Paris and the area around Paris (*Région Parisienne*) are entitled to special transportation allowances based on the number of zones they have to travel through on the way to work. There is no legal transportation allowance for people living and working outside the Paris area.

The transportation allowance for payees living and working in or around Paris is paid at 50 percent of the cost of a weekly, monthly, or annual travel ticket. Payees living outside Paris, but working within it, or living inside and working outside, are entitled to a reduced allowance, as are people living and working outside the city but travelling across it to get to work.

The amount is contained in an earning, CARTE ORANGE, and is triggered by earning or deduction assignment or by positive input. The calculation rule for this earning is Unit x Rate x Percent.

The number of tickets to reimburse is the *unit* and is entered at the payee level (you must override the unit with the number of tickets that you want to pay back).

The calculation of the allowance also requires information stored in three variables. You must define the values of these variables using supporting element overrides.

Variable	Description	How it is Used
IND VR CO NZ	Area number of the <i>Carte Orange</i> (allowance code)	Enter the area number in this variable using a supporting element override. If you do not enter this value as an override or enter the wrong value, the payment will be in error. The valid area values are contained in the bracket IND BR C ORANGE.
IND VR CO FA	Frequency of ticket purchase	<p>IND VR CO FA is used to store the frequency of purchase of the transportation card. The possible values here are: <i>S</i> for a weekly transportation ticket and <i>A</i> for a yearly transportation ticket. If this variable is not populated, the system assumes, by default, that the purchase frequency is monthly. This variable is used to select the correct reimbursement amount. The bracket IND BR C ORANGE retrieves the amount (cost) of the weekly, monthly, and yearly transportation ticket.</p> <hr/> <p>Note: The ticket cost depends on the frequency stored in IND VR CO FA and is returned by the bracket IND BR C ORANGE (the cost populates the rate component in the calculation rule of the earning CARTE ORANGE).</p> <hr/>
IND VR CO%	Reimbursement percentage (default rate)	The variable IND VR CO% stores the percentage used in the calculation rule of the earning CARTE ORANGE. By default, this percentage is equal to 50 percent. However, you can override this percentage by entering a supporting element override.

Note: You can enter supporting element overrides on the Element Detail page of the Element Assignment by Payee component (GP_ED_PYE), or on the Element Detail page of the Payee Assignment by Element component (GP_ED_ELEM). You can also enter supporting element overrides on the Positive Input - Details page of the One Time (Positive Input) component (GP_PI_MNL_ERNDED).

Independent Transportation Allowance

Payees who do not use public transportation may be entitled to these allowances:

- Transportation allowance.

There is no legal obligation for payees living and working outside Paris to receive a transportation allowance. Special rules may be defined by collective agreements.

This allowance is managed using payee assignments and is calculated by the earning IND TRANSPOR. To trigger this earning, you must assign it to individual payees using the Element

Assignment by Payee (GP_ED_PYE) or Payee Assignment by Element (GP_ED_ELEM) components, or the One Time (Positive Input) component (GP_PI_MNL_ERNDED).

The amount that you want to reimburse must be entered in the amount field of the override if the amount is different from the statutory allowance.

- Mileage allowance.

The mileage allowance is stored in the earning IND KILOMETR. The calculation rule for this earning is rate x unit, where the unit is the number of kilometers traveled and the rate is the reimbursement rate.

The payment of the allowance is triggered by positive input and the user must override the unit and rate fields with the amounts needed.

Premium Reimbursement	Exemption from social security contributions Paris area	Exemption from social security contributions Provinces	Exemption from the income tax (*) and the tax on salaries Paris area	Exemption from the income tax (*) and the tax on salaries Provinces
Payment of the statutory independent transport allowance	Yes	Yes	Yes	Yes
50% reimbursement of the transportation ticket (Paris area)	Yes		Yes	
More than 50% (general case)	Yes, if the company can supply proof of the expenses.		Yes, up to a limit of 50% of the transportation ticket.	
Payee applying a fixed deduction for professional expenses	Yes, up to a limit of 50% of the transportation ticket.		Yes, up to a limit of 50% of the transportation ticket.	
Total or partial financial liability for transportation expenses (provinces)		Yes, up to the 2 nd class rate (SNCF or other transportation companies).	Yes, up to the limit of the statutory independent transport allowance.	Yes, up to the limit of the statutory independent transport allowance.
Payee applying a fixed deduction for professional expenses		Yes, up to the limit of the statutory independent transport allowance.	Yes, up to the limit of the statutory independent transport allowance.	Yes, up to the limit of the statutory independent transport allowance.

(*) Except if for real professional expenses deduction.

Note: Global Payroll for France manages only the Paris Carte Orange reimbursement and the reimbursement of independent transport allowance. PeopleSoft do not provide any logic to differentiate between other transportation premiums and reimbursement amounts that are liable or not liable for social security contributions and income tax. You must define the rules yourself.

Benefits in Kind

Benefits in kind are goods or services provided by the employer that are not essential for carrying out professional activities.

Each benefit in kind produces an earning included in the gross salary and liable for social security contributions, and a deduction of the same amount, on the net salary. This section discusses:

- Meal benefit in kind.
- Lodging benefit in kind.
- Meal and lodging benefits in kind and net guarantee calculation.
- Car benefit in kind.
- Other benefits in kind.

Meal Benefit In Kind

<i>Element</i>	<i>Description</i>
AN NOURRITUR	This earning calculates the meal benefit and is triggered by positive input. The calculation rule for the earning is rate x unit (number of meals), with the unit being entered as positive input. The rate is equal to a lump sum amount stored in the variable IND VR AN NOUR FOR.
AN NOUR REG	Note: This element is no longer used due to changes in the calculation of the meal benefit after 1 January 2003.
AN NOUR DED	This deduction reduces the net salary. It is equal to the benefit in kind, AN NOURRITUR, plus the adjustment AN NOUR REG calculated during the period. AN NOUR DED is calculated automatically by the payroll process.

Note: Apprentices are calculated using a specific formula.

Lodging Benefit In Kind

Lodging benefit in kind is calculated on the same fixed base as the meal benefit in kind, with two rates, depending on the monthly salary.

Element	Description
AN LOGEMENT	<p>This earning calculates the lodging benefit and is triggered by positive input.</p> <p>To process the earning, you must specify the number of rooms by entering a supporting element override for the variable IND VR AN L NP.</p> <p>The calculation of the benefit in kind is based on statutory values stored in the bracket IND BR AN LOGEMENT, and depends on the number of rooms in the accommodation and on the employee salary as compared to the monthly social security ceiling.</p>
AN LOGEM REG	<hr/> <p>Note: This element is no longer used due to changes in the calculation of the lodging benefit after 1 January 2003.</p> <hr/>
AN LOGE DED	<p>This deduction reduces the net salary. It is equal to the benefit in kind, AN LOGEMENT, plus the adjustment AN LOGEM REG calculated during the period. AN LOGE DED is calculated automatically by the payroll process.</p>

Note: Apprentices are calculated using a specific formula.

Lodging Benefit in Kind and the Net Guarantee Calculation

The lodging benefit in kind values vary depending on the gross salary, which is affected by the net guarantee process. At each iteration of this process, the gross salary is adjusted until the target net salary is reached. Because the gross salary can go above and below the social security ceiling after each iteration, the benefit in kind could also vary. This can cause instability in the net guarantee calculation. To avoid this, the lodging benefit in kind valuation is not included in the net guarantee iterative process.

Note: The lodging benefit is calculated in the process list after the IJSS section and before the net guarantee calculation section. This means that it is calculated without taking into account the IJSS adjustment value (the result of the Net Guarantee calculation). If you want to calculate the benefit in kind taking into account the net guarantee calculation, place the benefit in kind section IND SE AVT NATURE after the net guarantee sections GEN SE GARANTI NET and GEN SE IJSS AJUST. But in this case, the net guarantee calculation can't be guaranteed.

Note: PeopleSoft recommends that you do not include the benefit in kind calculation in the net guarantee iterative process.

Car Benefit in Kind

The real value of a car given to a payee is considered a benefit in kind. If a car belongs to the company, but is allocated to a payee, it is also considered a benefit in kind, calculated with the mileage allowances bracket. This bracket is provided by the tax office and is not managed by PeopleSoft.

Element	Description
AN VEHICLE	This earning has a calculation rule of Amount, with the Amount Type set to <i>Payee Level</i> . It stores the car benefit and is triggered by positive input.
AN VEHIC REG	This earning is used to supplement the car benefit in kind using the One Time (Positive Input) page.
AN VEHI DED	This is the deduction used for the car benefit in kind. It is deducted from net salary and is calculated automatically by the payroll process.

Other Benefits in Kind

Non-professional travel, company-sponsored lotteries, competitions, and other similar benefits are considered benefits in kind.

Element	Description
AN AUTRES	This earning has a calculation rule of Amount, with the Amount Type set to <i>Payee Level</i> . It stores other benefits in kind and is triggered by positive input.
AN VEHIC REG	This earning is used to supplement other benefits in kind using the One Time (Positive Input) page.
AN AUTRES DE	This is the deduction used for other benefits in kind. It is deducted from net salary and is calculated automatically by the payroll process.

Meal Allowances

There are two meal allowances, one for day workers and one for night workers. Because meal allowances may or may not be subject to contributions, PeopleSoft has defined four earnings.

Earning	Description
PANIER J I	<p>This daytime allowance is subject to contributions.</p> <p>To trigger the day meal allowance, you must enter positive input for the earning PANIER J I. The unit of positive input is equal to the number of meal allowances to be paid.</p> <p>Meal allowances are not subject to contributions if they are calculated using the legal meal allowance rate stored in the variable IND VR PR PANIER. If you want to pay meal allowances based on a value greater than the legal rate, you must specify the value to use by entering a supporting element override for the variable IND VR PANIER J. If the variable IND VR PANIER J is overridden by an amount over the legal rate, the portion over this rate is used as the rate for the earning PANIER J I.</p> <hr/> <p>Note: You can enter supporting element overrides on the Positive Input - Details page of the One Time (Positive Input) component (GP_PI_MNL_ERNDED).</p> <hr/>
PANIER J NI	<p>This daytime allowance is not subject to contributions.</p> <p>The earning PANIER J NI has as its unit the number of meals entered by positive input for the earning PANIER J I, and the rate is the statutory meal allowance rate stored in the variable IND VR PR PANIER.</p>
PANIER N I	<p>This night allowance is subject to contributions.</p> <p>To trigger night meal allowances, you must enter positive input for the earning PANIER N I. The unit of positive input is equal to the number of meal allowances to be paid.</p> <p>Meal allowances are not subject to contributions if they are calculated using the legal meal allowance rate stored in the variable IND VR PR PANIER. If you want to pay meal allowances based on a value greater than the legal rate, you must specify the value to use by entering a supporting element override for the variable IND VR PANIER N. If the variable IND VR PANIER N is overridden by an amount over the legal rate, the portion over this rate is used as the rate for the earning PANIER N NI.</p> <hr/> <p>Note: You can enter supporting element overrides on the Positive Input - Details page of the One Time (Positive Input) component (GP_PI_MNL_ERNDED).</p> <hr/>
PANIER N NI	<p>This night allowance is not subject to contributions.</p> <p>If the variable IND VR PANIER N is not overridden or the variable is overridden by an amount less than 1.5 times the legal rate, the night allowances is not be liable to contributions and is paid by the earning PANIER N NI.</p>

Note: For the meal allowances, you must enter a positive input for the earnings that are subject to contributions (PANIER J I and PANIER N I), but the process determines if these allowances are subject to contributions depending on the values of the variables IND VR PANIER J and IND VR PANIER N.

Here are two examples of how the PANIER J I and PANIER J NI earnings are calculated:

- Example 1:
 - Legal Meal Allowance Rate= 2,85.
 - Positive Input for the earning PANIER J I.
 - Unit = 2,25.
 - Supporting element override for the variable IND VR PANIER J = 4,50.
 - In this case, the earning PANIER J I is equal to $2,25 \times (4,50 - 2,85) = 3,71$.
 - And the earning PANIER J NI is equal to $2,25 \times 2,85 = 6,41$.
- Example 2:
 - Positive Input for the earning PANIER J I:
 - Unit = 2,25.
 - No supporting element override for the variable IND VR PANIER J.
 - In this case, the earning PANIER J I is equal to 0.
 - And the earning PANIER J NI is equal to $2,25 \times 2,85 = 6,41$.

Note: If the variable IND VR PANIER J is overridden by an amount under the value of the legal rate, the allowance paid is calculated by PANIER J NI and the base is equal to the legal rate (not to the amount defined for the variable IND VR PANIER J).

Meal Tickets

<i>Earning or Deduction</i>	<i>Description</i>
TR EMP NI	<p>This earning calculates the number of meal tickets not liable to contributions.</p> <p>TR EMP NI uses the bracket IND BR TIT REST to retrieve the amount of the employer's contribution to the meal ticket (stored in the return column variable IND BR TIT REST) that is not subject to social contributions. To process this earning, you must enter the number of meal tickets given to the payee using positive input.</p> <p>Because this earning calculates the number of meal tickets not liable to contributions, it is not included in the salary nor does it appear on the payslip as the monetary counterpart of the earning.</p>

Earning or Deduction	Description
TR EMP I	<p>This earning calculates the part of the meal tickets liable to contributions.</p> <p>TR EMP I uses the bracket IND BR TIT REST to retrieve the amount of the employer's contribution to the meal ticket that is subject to social contributions. This amount is stored in the return column variable IND VR TR EMP I.</p> <p>The Unit in the calculation rule of this earning is the number of meal tickets entered by positive input for the earning TR EMP NI. If the employer does not have to pay a contribution for the meal tickets given, the bracket IND BR TIT REST returns a 0 as the value of the variable IND VR TR EMP I.</p>
TR EMP I DED	<p>This deduction calculates the number of meal tickets liable to contribution. These meal tickets add to the gross salary; to offset this increase, you must subtract the monetary amount of the meal ticket from the net salary to avoid doubling the payment.</p> <p>This deduction uses the bracket IND BR TIT REST to retrieve the amount of the employer's contribution (stored in the return column variable IND VR TR EMP I) that is subject to social contributions and deducts it from the net salary. The unit of this deduction is the amount entered as positive input for the earning TR EMP NI.</p>
TR SAL DED	<p>This deduction retrieves the portion of the meal tickets that is paid directly by the payee. This deduction uses the bracket IND BR TIT REST to retrieve the payee's contribution to the meal ticket (stored in the return column variable IND VR TR SAL NI) and deducts it from the net salary. The unit of this deduction is the amount entered as positive input for the earning TR EMP NI.</p>

Related Links

[IND BR TIT REST \(Meal Tickets\)](#)

Understanding Allowance Brackets

This section discusses these allowance brackets:

- IND BR FIN CONT (End of Contract Entitlements).
- IND BR DT SPEC (Contract Type Specific Entitlements).
- IND BR IND LIC (Severance allowance entitlements).
- IND BR DEP RET (Retirement Allowance entitlements).
- IND BR C ORANGE (Paris transportation allowance).
- IND BR TIT REST (Meal tickets).

IND BR FIN CONT (End of Contract Entitlements)

This bracket is used to determine entitlement for the following allowances:

- Compensation In Lieu of Paid Holidays not Taken.
- Severance Allowance.
- End of Fixed-Term Contract Allowance.
- Retirement Allowance.

Note: This bracket works in combination with other brackets—including IND BR DT SPEC, IND BR IND LIC, and IND BR DEP RET—to determine entitlement for many of the allowances discussed in this topic.

Search Keys	Use/Description	Return Columns	Use/Description
GEN VR ACTION	<p>Contains the Action code that triggers the allowance.</p> <hr/> <p>Note: The value of GEN VR ACTION on the Data page of the Bracket is set to <i>TER</i> or <i>RET</i> because the bracket applies to termination allowances.</p> <hr/>	IND BR FIN CONT	The value of this element is not used.
GEN VR MOTIF	Contains the Reason code that triggers the allowance. You must update the reason codes in the bracket to indicate the reasons a payee may be entitled to the allowances.	IND VR DT ICCP	<p>This variable is used to trigger the allowance CP ICCP 1A (compensation in lieu of paid holiday) and must be assigned a value of true or false (<i>1</i> or <i>0</i>). <i>1</i> triggers the allowance, while <i>0</i> prevents payment.</p> <hr/> <p>Note: The variable must be set to <i>0</i> if the termination reason is gross misconduct.</p> <hr/>
		IND VR DT IFC	<p>This variable is used to determine entitlement to the end of fixed-term contract allowance IND FIN CONT and must be assigned a value of true or false (<i>1</i> or <i>0</i>). <i>1</i> triggers the allowance, while <i>0</i> prevents payment.</p>

Search Keys	Use/Description	Return Columns	Use/Description
		IND VR DT LIC	The variable IND VR DT LIC is used to determine entitlement to the severance allowance IND LICENC and IND LICENC 2. If the variable returns a value of true (1), the payee is entitled to the severance allowance as determined by the Action/Reason. If the value returned is equal to false (0), the Action/Reason does not give entitlement to the severance allowance.
		IND VR DT LIC ECO	This variable is used to determine if economic redundancy is the reason for a termination. This variable will be taken into consideration only if the variable IND VR DT LIC returns a value of true (1 for redundancy termination. If the variable returns a value of true (1), the payee is entitled to have his or her severance allowance doubled compared to the standard allowance (if notification of the redundancy occurred after May 7, 2002).
		IND VR DT D RET	<p>This variable is used to determine entitlement to the voluntary retirement allowance IND DEP RET and must be assigned a value of true or false (1 or 0). If the variable has a value of true (1), the payee is entitled to the allowance.</p> <hr/> <p>Note: An additional condition must be satisfied for this allowance to be paid, as determined by the bracket IND BR DT SPEC.</p> <hr/>

Search Keys	Use/Description	Return Columns	Use/Description
		IND VR DT M RET	<p>This variable is used to determine entitlement to the statutory retirement allowance IND MISE RET and must be assigned a value of true or false (1 or 0). If the variable has a value of true (1), the payee is entitled to the allowance.</p> <hr/> <p>Note: An additional condition must be satisfied for this allowance to be paid, as determined by the bracket IND BR DT SPEC.</p> <hr/>

Sample Values

GEN VR ACTION	GEN VR MOTIF	Bracket	IND VR DT ICCP
TER	ATC	1	1
TER	CON	1	1
TER	CDE	1	1
TER	DEA	1	1

Examples

If a payee is laid off and the reason for the payee's departure is gross misconduct (*faute lourde*), the payee is not eligible for the following:

- The severance allowance (the value of the bracket element should be zero).
- The end of fixed-term contract allowance (the return value of the variable IND VR DT IFC should be set to zero).

Note: For a departure reason equal to end of fixed-term contract, the variables IND VR DT IFC and IND VR DT ICCP should be set to 1.

- The paid vacation allowances for the current period (the return value of the variable IND VR DT ICCP should be set to zero).
- The retirement allowances (the return values of the variables IND VR DT M RET and IND VR DT D RET should be set to zero).

IND BR DT SPEC (Contract Type Specific Entitlements)

This bracket is used to determine entitlement for the following allowances:

- Severance Allowance.
- End of Fixed-Term Contract Allowance.
- Retirement Allowance.

Note: This bracket works in combination with other brackets—including IND BR FIN CONT, IND BR IND LIC, and IND BR DEP RET—to determine entitlement for a number of different allowances.

Search Keys	Use/Description	Return Columns	Use/Description
CONTRACT TYPE	<p>Because this bracket is for entitlements that vary by contract, the search key is CONTRACT TYPE.</p> <p>Currently, this bracket is defined for only two contract types: CDD and CDI. If you define a new contract type for which you want to grant an entitlement, you must update the bracket.</p>	IND BR DT SPEC	The bracket element IND BR DT SPEC is used to determine entitlement to the severance allowance IND LICENC and IND LICENC 2. If the bracket element returns a value of true (1), the payee is entitled to the severance allowance as determined by the contract type. If the value returned is equal to false (0), the contract type does not give entitlement to the severance allowance.
		IND VR DP IFC	This variable serves to determine entitlement for the end of fixed-term contract allowance IND FIN CONT and must be assigned a value of true or false (1 or 0). 1 means that the end of fixed term contract allowance can be paid for the type of contract defined, while 0 prevents payment.
		IND VR DP DEP RET	<p>This variable is used to determine entitlement to the voluntary retirement allowance IND DEP RET and must be assigned a value of true or false (1 or 0). If the variable returns a value of true (1), the allowance can be paid.</p> <hr/> <p>Note: An additional condition must be satisfied for this allowance to be paid, as determined by the bracket IND BR FIN CONT.</p> <hr/>

Search Keys	Use/Description	Return Columns	Use/Description
		IND VR DP MIS RET	<p>The variable IND VR MIS RET is used to determine entitlement to the statutory retirement allowance IND MISE RET and must be assigned a value of true or false (1 or 0). If the variable returns a value of true (1), the allowance can be paid.</p> <hr/> <p>Note: An additional condition must be satisfied for this allowance to be paid, as determined by the bracket IND BR FIN CONT.</p> <hr/>

Sample Values

CONTRACT TYPE	IND BR DT SPEC	IND VR DP IFC	IND VR DP DEP RET	IND VR DP MIS RET
CDD		1		
CDI	1		1	1

IND BR IND LIC (Severance Allowance Entitlements)

This bracket retrieves values used in the severance allowance calculation.

Note: This bracket works in combination with the brackets IND BR FIN CONT and IND BR DT SPEC to determine the severance allowance.

Search Keys	Use/Description	Return Columns	Use/Description
GP TEMP001 CHAR	If you want to define the bracket according to the labor agreement, populate this temporary variable with the labor agreement before the bracket is resolved. You must also specify the labor agreement value in the bracket definition and indicate the return values for the labor agreement.	IND BR IND LIC	The bracket element IND BR IND LIC returns values used to determine the salaries used in the severance allowance calculation. A return value of 1 indicates that the calculation should use the average salary of the last 12 months. A return value of 2 indicates that the calculation should use the average salary of the last three months. A return value of 3 indicates that the calculation should use the more favorable of the first two methods.

Search Keys	Use/Description	Return Columns	Use/Description
GP TEMP002 CHAR	If you want to define the bracket according to payee categories defined in the labor agreement, populate this temporary variable with the appropriate category before the bracket is resolved. Also, specify the payee category value in the bracket definition and indicate the return values for the payee category.	IND VR ANC 1	This variable is used to store the number of years of seniority linked to the entitlement variable IND VR DRT 1.
GEN VR INSTANCE	The variable GEN VR INSTANCE must be equal to 1 to trigger the earning IND LICENC 1 and 2 to trigger the earning IND LICENC 2	IND VR DRT 1	This variable stores the ratio applied to the base salary for the severance calculation for each year of seniority up to the number of years of seniority entered in the variable IND VR ANC 1.
		IND VR ANC 2	This variable stores the number of years of seniority linked to the entitlement variable IND VR DRT2.
		IND VR DRT 2	This variable stores the ratio applied to the base salary for the allowance calculation for each year of seniority up to the number of years of seniority entered in the variable IND VR ANC 2.
		IND VR ANC 3	This variable stores the number of years of seniority linked to the entitlement variable IND VR DRT3.
		IND VR DRT 3	This variable stores the ratio applied to the base salary for the allowance calculation for each year of seniority up to the number of years of seniority entered in entered in the variable IND VR ANC 3.
		IND VR PLAFOND	This variable stores the ceiling, in years, over which entitlement to the severance allowance is no longer calculated.

Sample Values

<i>GEN VR INSTANCE</i>	<i>IND BR IND LIC</i>	<i>IND VR ANC 1</i>	<i>IND VR DRT 1</i>	<i>IND VR ANC 2</i>	<i>IND VR DRT 2</i>	<i>IND VR ANC 3</i>	<i>IND VR PLAFOND</i>
1	3	10	0.1	99	0.166667		99
2	3	99		99		99	99

Example

Suppose that there are two payees, one with ten years of seniority and another with 15 years of seniority. Both payees' average salary over the past three months is equal to 1677 euros, and the average over the last 12 months is 1524 euros. In order to calculate the severance allowance, you must apply to the base salary (equal to either the average salary for the last three months or the last 12—whichever is highest), a factor of $1/10 \times$ years of seniority (up to a limit of ten years). After ten years, the factor applied to the base is $(1/10 + 1/15) \times$ years of seniority over ten years.

- Based on this rule, the payee with ten years of seniority (stored in the variable IND VR ANC 1) would have the following severance allowance:

Base salary of 1677 euros \times $1/10$ (stored in IND VR DRT 1) \times 10 years of seniority.

- Based on this rule, the payee with 15 years of seniority (stored in the variable IND VR ANC 1) would have the following severance allowance:

Base salary of 1677 euros \times $1/10$ (stored in IND VR DRT 1) \times 10 years of seniority, plus base salary of 1677 euros \times $(1/10 + 1/15)$ [stored in IND VR DRT 2] \times 5 years of seniority.

Note: The values currently specified in the bracket for GEN VR INSTANCE = 1 are the values defined by law. You are responsible for updating these values if they change. If you have a collective agreement with different rules, you can define the different slices (up to three) for the variables IND VR ANC 1, IND VR ANC 2, and IND VR ANC 3, and then define the entitlement for each slice in the variables IND VR DRT 1, 2, and 3.

The values currently specified for GEN VR INSTANCE = 2 are provided as sample data only. You must define and maintain these values yourself.

IND BR DEP RET (Retirement Allowance Entitlements)

This bracket retrieves values used in the retirement allowance calculation.

Note: This bracket works in combination with the brackets IND BR FIN CONT and IND BR DT SPEC to determine the retirement allowance.

Search Keys	Use/Description	Return Columns	Use/Description
LABOR AGREEMENT	LABOR AGREEMENT is one of three search keys in the bracket. If you create specific entitlements that vary by labor agreement, you must specify the labor agreements that determine the return column values.	IND BR DEP RET	<p>The value returned by the bracket element IND BR DEP RET determines the salary (base) used to calculate the retirement allowance. The bracket can return one of the following values:</p> <ul style="list-style-type: none"> If the bracket retrieves 1, the salary used to calculate the allowance is equal to 1/12th of the last 12 salaries. If the bracket retrieves 2, the salary used to calculate the allowance is equal to 1/3rd of the last three salaries. If the bracket retrieves 3, the salary used to calculate the allowance is the greater of 1/13th of the last three salaries and 1/12th of the last 12 salaries. <hr/> <p>Note: You must supply the value of this variable.</p>
EMPL CTG (Employee Category)	EMPL CTG is one of three search keys in the bracket. If the collective agreement defines different calculations depending on the employee categories of the payees, you must specify the employee categories that determine the return column values.	IND VR DRT 1	<p>The variable IND VR DRT 1 returns the number of months that the allowance should be paid.</p> <hr/> <p>Note: you must supply the value of this variable.</p>
GEN VR INSTANCE (Number of Years of Seniority)	<p>Regardless of whether the entitlement varies by labor agreement or payee category, the retirement allowance depends on the years of seniority stored in the variable GEN VR INSTANCE.</p> <hr/> <p>Note: This is the only search key that must be populated.</p>		

Sample Values

<i>GEN VR INSTANCE</i>	<i>IND BR DEP RET</i>	<i>IND VR DRT 1</i>
10	3	0.5
15	3	1
20	3	1.5
30	3	2

IND BR C ORANGE (Paris Transportation Allowance)

This bracket retrieves the values of the cost of a monthly, weekly, and yearly ticket Paris transportation ticket (*carte orange*).

Note: You must update the bracket each year with the cost of weekly, monthly and yearly tickets for each area number.

Sample Values

<i>IND VR CO NZ</i>	<i>IND BR C ORANGE</i>	<i>IND VR CO MOIS</i>	<i>IND VR CO ANNEE</i>
12	85	285	265
13	113	378	352
23	83	276	258
24	107	359	336

IND BR TIT REST (Meal Tickets)

This bracket retrieves values used in the calculation of meal tickets.

<i>Search Keys</i>	<i>Use/Description</i>	<i>Return Columns</i>	<i>Use/Description</i>
COMPANY	The values returned by this bracket depend on the company. You must define the company values used in the search key.	IND BR TIT REST	The bracket element retrieves the amount of the employer's contribution to the meal ticket that is not subject to social contributions.
		IND VR TR EMP I	This variable stores the amount of the employer's contribution to the meal ticket that is subject to social contributions.

Search Keys	Use/Description	Return Columns	Use/Description
		IND VR TR SAL NI	This variable stores the amount of the payee's contribution to the meal ticket.

Note: You must supply the values for the IND BR TIT REST bracket. PeopleSoft only provides sample values.

Sample Values

COMPANY	IND BR TIT REST	IND VR TR EMP 1	IND VR TR SAL NI
KF1	28	0	28
KF2	0	29	29

Related Links

[Understanding Allowance Earnings and Deductions](#)

Understanding Allowance Earnings and Deductions

Earning/Deduction	Description
CP ICCP A2	Compensation in lieu of paid holidays A-2.
CP ICCP A1	Compensation in lieu of paid holidays A-1.
CP ICCP A	Compensation in lieu of paid holidays A.
CP ICCP 1A	Compensation in lieu of paid holidays A+1.
CP ICCP MC	Additional amount for compensation in lieu of paid holidays.
IND LICENC	First severance allowance.
IND LICENC 2	Second severance allowance.
IND FIN CONT	End of fixed-term contract allowance.
IND MISE RET	Obligatory retirement allowance.
IND DEP RET	Voluntary retirement allowance.
CARTE ORANGE	Paris transportation allowance.
IND TRANSPOR	Transportation allowance.

<i>Earning/Deduction</i>	<i>Description</i>
IND KILOMETR	<p>Mileage allowance.</p> <p>This element is automatically segmented and prorated when it is assigned to a payee on the Element Assignment by Payee or Payee Assignment by Element pages and the assignment period covers only a portion of the pay period.</p>
AN NOURRITUR	<p>Meal benefit in kind.</p> <p>This element is automatically segmented and prorated when it is assigned to a payee on the Element Assignment by Payee or Payee Assignment by Element pages and the assignment period covers only a portion of the pay period.</p>
AN LOGEMENT	Lodging benefit in kind
AN VEHICULE	<p>Car benefit in kind</p> <p>This element is automatically segmented and prorated when it is assigned to a payee on the Element Assignment by Payee or Payee Assignment by Element pages and the assignment period covers only a portion of the pay period.</p>
AN AUTRES	<p>Other benefits in kind</p> <p>This element is automatically segmented and prorated when it is assigned to a payee on the Element Assignment by Payee or Payee Assignment by Element pages and the assignment period covers only a portion of the pay period.</p>
AN NOURR REG	Meal benefit in kind.
AN LOGEM REG	Lodging benefit in kind.
AN VEHIC REG	<p>Car benefit in kind.</p> <p>This element is automatically segmented and prorated when it is assigned to a payee on the Element Assignment by Payee or Payee Assignment by Element pages and the assignment period covers only a portion of the pay period.</p>
AN AUTRE REG	<p>Other benefits in kind</p> <p>This element is automatically segmented and prorated when it is assigned to a payee on the Element Assignment by Payee or Payee Assignment by Element pages and the assignment period covers only a portion of the pay period.</p>
PANIER J I	<p>Meal allowance liable to contributions</p> <p>This element is automatically segmented and prorated when it is assigned to a payee on the Element Assignment by Payee or Payee Assignment by Element pages and the assignment period covers only a portion of the pay period.</p>

Earning/Deduction	Description
PANIER N I	Night meal allowance liable to contributions This element is automatically segmented and prorated when it is assigned to a payee on the Element Assignment by Payee or Payee Assignment by Element pages and the assignment period covers only a portion of the pay period.
PANIER J NI	Meal allowance not liable to contributions.
PANIER N NI	Night meal allowance not liable to contributions.
AN NOUR DED	Meal benefit in kind.
AN LOGE DED	Lodging benefit in kind.
AN VEHI DED	Car benefit in kind.
AN AUTRES DE	Other benefits in kind.
TR EMP NI	Meal ticket: employer's contribution not liable.
TR EMP I	Meal ticket: employer's contribution liable.
TR EMP I DED	Meal ticket: employer's contribution liable (deduction).
TR SAL DED	Meal ticket: payee's contribution (deduction).

Note: PeopleSoft delivers a query that you can run to view the names of all delivered elements designed for France. Instructions for running the query are provided in the *PeopleSoft Global Payroll* .

Related Links

"Understanding How to View Delivered Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

"Defining Deduction Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

Chapter 13

Understanding AFB Rules

The AFB Process Section

AFB sections are triggered in the process list if the payee has an AFB collective agreement set up in PeopleSoft HR. This is verified by using the conditional formula AFB FM TEST CC, which is delivered as sample data and which you can modify to suit your needs.

Note: The formula AFB FM TEST CC determines whether the system element LABOR AGREEMENT is equal to the variable AFB VR VALUE. By default, the value of the variable AFB VR VALUE is equal to *AFB*. (AFB VR VALUE is a variable with a character format.) If the value of the system element LABOR AGREEMENT is equal to *AFB*, the sections managing the AFB rules are triggered. PeopleSoft does not provide the AFB collective agreement value in the HR tables. There are two solutions to handle this situation: you can create a labor agreement with a value equal to *AFB* for the banking collective agreement, or you can create the banking collective agreement with the value that you want, but you must modify the value of the variable AFB VR VALUE in order to have this value equal to the labor agreement name.

Related Links

[Understanding ARRCO, AGIRC, and Contingency Fund Contributions](#)
[Updating Elements for Wage Certificates](#)

AFB Compensation Elements

This section discusses:

- AFB earning elements.
- The AFB thirteenth payment.
- The AFB diploma premium.

AFB Earning Elements

The AFB collective agreement stipulates that the annual salary for a payee must be paid in 12 monthly payments, along with an additional amount for the thirteenth month, which is usually paid during the December payroll. However, with the agreement of the work council, companies can pay the annual salary by making 12 identical payments (rather than using the thirteenth amount).

The annual salary can be managed by creating either:

- one rate code for twelve months and one rate code for the thirteenth month, or,

- one rate code for thirteen months, or
- one rate code for twelve identical monthly payments.

If the employee was hired during the current year, or leaves before December, the thirteenth amount is calculated in proportion to the time worked using the formula: annual basic salary * 12 / 13 / calendar days of the year.

The daily rate is also calculated in proportion to the time worked for part-time payees.

Earning Element	Description
AFB SAL 13 M	Used to calculate 12 payments when a payee receives 13 payments.
AFB SAL 13EM	Used to calculate the thirteenth payment.
AFB SAL 12M	Used if the payee receives 12 identical amounts.

Note: These earnings are automatically segmented and prorated when they are assigned to payees on the Element Assignment by Payee or Payee Assignment by Element pages and the assignment period covers only a portion of the pay period.

See "Understanding Overrides (*PeopleSoft HCM 9.2: Global Payroll*)".

PeopleSoft does not maintain these earnings. The calculation rules and proration rules have been defined by PeopleSoft, but you may change them to fit your own requirements.

Note: One instance in which you might want to modify the proration rules is for the proration applied to the calculation of the thirteenth month. The formula ABS FM BASE 13EME calculates the amount of the thirteenth-month payment.

Note: The PeopleSoft system does not check whether earnings are below the statutory minimum. Statutory minimum earnings are defined by the collective agreement according to the defined category of the employee. The PeopleSoft system also does not check whether earnings paid comply with the salary scale stipulated by the collective agreement.

The AFB Thirteenth Payment

The extra earning element for the thirteenth payment—AFB SAL 13EM—is triggered by the generation control element AFB GC 13EME MOIS when the payee leaves or when the thirteenth payment is due. Payees choose in which month they want to receive the payment.

The earning is prorated based on calendar days, calendar half days, and hours worked in the year. :

Accumulator	Description
AFB AC JR CAL AN	Stores the number of calendar days of the year. This accumulator is populated only by the calendar days included in the segment period paid.

Accumulator	Description
AFB AC JR NPAY AN	Stores the number of calendar days unpaid. Populate this accumulator based on how your organization defines an unpaid day.
AFB AC JR DPAY AN	Stores the calendar days half paid. Populate this accumulator based on how your organization defines a half-paid day.
AFB AC HR THEO	Populated by the number of theoretical hours in the segments that make up a year.
AFB AC HR ABS AN	Stores the number of hours of absences.

The accumulators in the preceding table are used in the formula AFB FM BASE 13EME to calculate the thirteenth payment using a proration factor based on the amount of time the payee works for the company during the year.

The payment date is stored in the variable AFB VR DAT PAY 13M. The payment of the thirteenth month is triggered when the date that you indicate in this variable is included in the segment period.

The AFB Diploma Premium

A payee may be granted an extra earning, called a diploma premium. The earning, PRM DIPL AFB, is entered using positive input and is subject to contributions and income tax.

Note: All elements described here are delivered as sample data and are not maintained by PeopleSoft. You may modify the rules for these earnings as required by your company's needs. The only exception is the earning Diploma Premium, which is maintained by PeopleSoft.

AFB Transport Allowances

This section discusses:

- Transport allowance amounts.
- Other transport benefits.

Transport Allowance Amounts

There are two transport allowance amounts. One is for large cities (Paris and large cities listed in the labor agreement), and the other is for smaller cities (cities with more than 100,000 inhabitants listed in the labor agreement). The allowance amounts have two associated earning elements: PRM TR 1 NC and PRM TR 2 NC.

Using the Element Assignment by Payee or Payee Assignment by Element pages in the Global Payroll core application, assign the earning PRM TR 1 NC for Paris and large cities, or PRM TR 2 NC for cities with more than 100,000 inhabitants.

A payee is allowed to receive only one of these two allowances, so the two earnings are exclusive and should not be triggered for the same payee. The system does not control whether the two earnings are entered simultaneously; it is your responsibility to manage this process.

The earnings for smaller cities are not subject to tax or social security contributions because the limit is equal to the earnings. The other earnings are split into an amount subject to contributions and an amount not subject to contributions.

You assign the allowance to the payee. Global Payroll for France does not check whether the allowance for a large city is being paid to a payee working in a small city. However, the system does check whether the earning is subject to social security contributions and tax.

Other Transport Benefits

Payees may receive other transport benefits. For example, someone may work in Paris and receive an allowance for a *Carte Orange*.

Some payees may receive a car benefit in kind. A payee receiving an allowance for a *Carte Orange*, or a transport benefit in kind, is not eligible to receive a Premium 1 or Premium 2 transport allowance.

A generation control element verifies whether either of these allowances is being paid, and if either is being paid, a Premium 1 or Premium 2 allowance is not triggered, even if requested by the user.

AFB End of Contract Allowances

This section discusses:

- Severance allowance entitlement.
- Severance allowance calculation.
- Seniority and 2002.

Severance Allowance Entitlement

When a payee's contract is terminated prematurely for a nondisciplinary or economic reason (that is, the payee is laid off), the payee is entitled to a severance allowance as defined by the collective agreement. The allowance is paid in one sum and depends on various conditions, such as term of service and the reason for the layoff. The allowance amount depends on the salary base, years of service, and the payee's category.

Payees dismissed for disciplinary reasons, including those sentenced in court, receive the statutory allowance defined by the government because this is more favorable than the allowance defined by the collective agreement.

The severance allowance for a nondisciplinary or economic reasons is calculated by the earning IND LIC AFB.

Related Links

[Understanding Allowance Brackets](#)

Severance Allowance Calculation

The bracket AFB BR IND LIC returns values used to calculate the severance allowance. Entitlement to this allowance depends on the reason for a payee's termination. Although there are many reason codes defined in the HR application, only two confer entitlement to severance pay in the delivered bracket: *INS* (severance for insubordination) and *RED* (severance for staff reduction). If you want to add additional entitlement reasons, include the corresponding reason codes in this bracket.

The retirement allowance IND LIC AFB is triggered by the generation control element AFB GC IND LIC CC. This generation control element contains the actions or reasons that entitle a payee to the retirement allowance. The reasons listed in this generation control element must be the same as the reasons used as search keys in the bracket AFB BR IND LIC.

You must maintain the generation control element by populating it with whatever actions or reasons are required.

Severance Allowance for Nondisciplinary Dismissal

	<i>Managers</i>	<i>Technicians</i>
Seniority required.	The payee must have one year of seniority to have severance allowance.	Same as managers.
Base for calculation.	Base = 1/13 of the annual basic salary the payee had or would have had during the last 12 months.	Same as managers.
Semester calculation.	<p>The entitlements must be calculated for two periods as follows:</p> <p>The semester must be complete. From 15/09/2002 to 15/03/2003 is a complete semester. From 16/09/2002 to 15/03/2003 is not a complete semester.</p> <p>In case of unpaid absences, the length of service must be reduced for the corresponding calendar days. If the semester goes past 01/01/2002, the semester is a complete semester, and the corresponding allowance is calculated in two parts: the part corresponding to the period before 01/01/2002 and the part from 01/01/2002 and onward.</p>	Same as managers.
Semester completed before 01/01/2002.	$\frac{1}{2} \times (13/14,50)$ for each semester completed before this date. This value is retrieved by the variable AFB VR TX LIC < 02.	Same as managers.

	Managers	Technicians
Semester completed after 01/01/2002.	1/5 for each semester completed starting from this date. This value is retrieved by the variable AFB VR TX LIC > O2.	Same as managers.
Ceilings.	The ceiling is the upper limit for the two-semester sum; the ceiling varies with the hire date. In case of part-time periods, the ceiling is calculated in proportion to the time worked.	Same as managers.
Hired before 12/31/1999.	$24 \times (13 / 14,50) = 21,51724$ This value is retrieved by the variable AFB VR LIMIT CADR.	$18 \times (13 / 14,50) = 16,13793$ This value is retrieved by the variable AFB VR LIMIT TECH.
Hired from 01/01/2000.	15 This value is retrieved by the variable AFB VR LIMIT > O2.	Same as managers.
Severance allowance amount.	Base for calculation x semester number. Part-time periods must be included in the calculation. Part-time periods must be considered before 01/01/2002 and from 01/01/2002 and onward.	Same as managers.

The payee classification—manager or technician—triggers the correct ceiling for severance allowances paid before 2002. The formula SIT FM CLASSIF AFB stores the value *0* if the payee is a technician and *1* if the payee is a manager. Because PeopleSoft does not know how and where companies store the payee's category, you must update the formula.

Severance Allowance in Case of (Economic) Redundancy

	Managers	Technicians
Seniority required.	The payee must have one year of seniority to receive severance allowance.	Same as managers.
Base for calculation.	Base = 1/12 of the annual basic salary the payee had or would have had during the last 12 months. In case of an incomplete year, the annual salary must be rebuilt.	Same as managers.

	Managers	Technicians
Semester calculation.	<p>The entitlements must be calculated for two periods as follows:</p> <p>The semester must be complete. From 15/09/2002 to 15/03/2003 is a complete semester, and from 16/09/2002 to 15/03/2003 is not a complete semester. In case of unpaid absences, the length of service must be reduced for the corresponding calendar days.</p> <p>If a semester goes past 01/01/2002, the semester is a complete semester and the corresponding allowance is calculated in two parts: the part corresponding to the period before 01/01/2002 and the part from 01/01/2002 and onward.</p>	Same as managers.
Semester completed before 01/01/2002.	<p>$\frac{1}{2} \times \text{Base}$ for each semester completed before this date.</p> <p>This value is retrieved by the variable AFB VR TX LIC < O2.</p>	Same as managers.
Semester completed after 01/01/2002.	<p>$\frac{1}{4} \times \text{Base} \times \text{Base}$ for each semester completed starting from this date. This value is retrieved by the variable AFB VR TX LIC > O2.</p>	Same as managers.
Ceilings.	<p>The ceiling is the upper limit for the two-semester sum; the ceiling varies with the hire date. In case of part-time periods, the ceiling is calculated in proportion to the time worked.</p>	Same as managers.
Hired before 12/31/1999.	<p>24</p> <p>This value is retrieved by the variable AFB VR LIMIT CADR.</p>	<p>18</p> <p>This value is retrieved by the variable AFB VR LIMIT TECH.</p>
Hired from 01/01/2000.	<p>18</p> <p>This value is retrieved by the variable AFB VR LIMIT > O2.</p>	Same as managers.

	Managers	Technicians
Severance allowance amount.	Base for calculation x semester number. Part-time periods must be included in the calculation. Part-time periods must be considered before 01/01/2002 and from 01/01/2002 and onward.	Same as managers.

The payee classification—manager or technician—triggers the correct ceiling for severance allowances paid before 2002. The formula SIT FM CLASSIF AFB stores the value *0* if the payee is a technician and *1* if the payee is a manager. Because PeopleSoft does not know how and where companies store the payee's category, you must update the formula.

Bracket for AFB Labor Agreement Severance Allowance

The search key in the bracket AFB BR IND LIC is GEN VR MOTIF (severance reason), and the return column elements are the bracket AFB BR IND LIC and the variables AFB VR LIMIT TECH, AFB VR LIMIT CADR, AFB VR LIMIT > 02, AFB VR TX LIC < 02, AFB VR TX LIC > 02, and GEN VR IND LIC CC.

Element Name	Usage
AFB VR LIMIT TECH	Stores the entitlement limit used in the severance allowance calculation for banking technicians.
AFB VR LIMIT CADR	Stores the entitlement limit used in the severance allowance calculation for banking managers.
AFB VR LIMIT > 02	Stores the entitlement limit for all payee categories after 2002.
AFB VR TX LIC < 02	Stores the rate used to calculate the severance allowance before 2002.
AFB VR TX LIC > 02	Stores the rate used to calculate the severance allowance after 2002.
AFB BR IND LIC	Stores the multiplier applied to the annual salary (1 for a nondisciplinary reason and 13/12 for an economic reason).
GEN VR IND LIC CC	Stores an indicator with the value of <i>1</i> if the severance allowance defined by the collective agreement is resolved. This variable is checked to avoid the payment of the legal severance allowance if the labor agreement severance allowance has already been paid.

GEN VR MOTIF (Key)	AFB BR IND LIC (Return)	AFB VR LIMIT TECH (Variable)	AFB VR LIMIT CADR (Variable)	AFB VR LIMIT > 02 (Variable)	AFB VR TX LIC < 02 (Variable)	AFB VR TX LIC > 02 (Variable)	GEN VR IND LIC CC (Variable)
INS	1	21,517241	16,137931	15	0,448275	0,2	1
RED	1,083333	24	18	18	0,5	0,25	1

It is important that you understand the definition of this bracket because PeopleSoft delivers, but does not maintain, it. You must maintain this bracket to ensure that it functions properly.

If your organization applies the AFB collective agreement, use the sample values in this bracket and in the AFB BR IND DEP RET bracket to manage severance and retirement allowances. If you have a collective agreement other than AFB, don't use these brackets.

If you are applying the AFB collective agreement, and the agreement uses different values to calculate the allowance, you may need to change the parameters of the brackets, but you do not need to create any new brackets for this allowance.

Note: If you use the AFB BR IND LIC bracket, make sure that the return column variable GEN VR IND LIC CC is set to *1*. This variable tells the system that the allowances are being calculated using a labor agreement bracket and should not be calculated again based on the legal setup.

Related Links

"Defining Bracket Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

"Defining Variable Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

Seniority and 2002

The entitlement used to calculate severance allowance changed in 2002. The previous seniority values were frozen at the end of 2001, so the formula containing payee classifications automatically switched to a new effective date and calculated the new entitlements when the changes were introduced.

The HR files do not tell you if a person is classified as a technician or a manager. The formula SIT FM CLASSIF AFB stores the value *0* if the payee is a technician and *1* if the payee is a manager.

Note: The system used the formula SIT FM CLASSIF AFB until the end of 2001, and currently uses the formula for retro calculations. For calculating allowances in 2002 and onwards, the system does not use this formula.

You must maintain this formula, which needs to be populated so that it can retrieve a value for the payee's category. By default, the value in the formula is set to *0*. This means that if the formula is not updated, it retrieves values for technicians only.

AFB Retirement Allowances

This section discusses:

- Retirement allowance entitlement.

- Retirement allowance calculation.

Retirement Allowance Entitlement

The AFB labor agreement defines entitlement to the retirement allowance. In cases of voluntary retirement, the allowance defined by the collective agreement supersedes the one defined by law. In cases of compulsory retirement, the legal retirement allowance supersedes the allowance defined by the labor agreement. The earning used to calculate the retirement allowance for AFB is IND DRET AFB.

Retirement Allowance Calculation

The bracket AFB BR IND LIC returns values used to calculate the retirement allowance. Entitlement to this allowance depends on the reason for a payee's retirement. Although there are many reason codes defined in the HR application, only one confers entitlement to retirement pay in the delivered bracket: *VRE* (retirement for voluntary reasons). If you want to add additional entitlement reasons, include the corresponding reason codes in this bracket.

The retirement allowance IND DRET AFB is triggered by the generation control element AFB GC IND DRET CC. This generation control element contains the actions or reasons that entitle a payee to the retirement allowance. The reasons listed in this generation control element must be the same as the reasons used as search keys in the bracket AFB BR IND DEP RET.

You must maintain the generation control element by populating it with whatever actions or reasons are required.

Bracket for AFB Labor Agreement Retirement Allowance Parameters

The search keys for the bracket AFB BR IND DEP RET are GEN VR MOTIF (the retirement reason) and GEN VR AN ANC CONT (the number of years of seniority), and the return column elements are the bracket AFB BR IND DEP RET and the variable GEN VR IND RET CC.

Element Name	Usage
AFB BR IND LIC	The bracket AFB BR IND LIC resolves to the calculation rate, which is applied to the average salary of the last 12 months.
GEN VR IND RET CC	Stores an indicator with the value of 1 if the retirement allowance defined by the collective agreement is resolved. This variable is checked to avoid payment of the legal retirement allowance if the labor agreement retirement allowance has already been paid.

GEN VR MOTIF (Key)	GEN VR AN ANC (Key)	AFB BR IND DEP RET (Return)	GEN VR IND RET CC (Variable)
VRE	10	0,666666	1
VRE	15	1,25	1
VRE	20	2	1

GEN VR MOTIF (Key)	GEN VR AN ANC (Key)	AFB BR IND DEP RET (Return)	GEN VR IND RET CC (Variable)
VRE	30	2,5	1

It is important that you understand the definition of this bracket because PeopleSoft delivers, but does not maintain, it. You must maintain this bracket to ensure that it functions properly.

If your organization applies the AFB collective agreement, use the sample values in this bracket and in the AFB BR IND LIC bracket to manage severance and retirement allowances. If you have a collective agreement other than AFB, don't use these brackets.

If you are applying the AFB collective agreement, and the agreement uses different values to calculate the allowance, you may need to change the parameters of the brackets, but you do not need to create any new brackets for this allowance.

Note: If you use the AFB BR IND DEP RET bracket, make sure that the variable GEN VR IND RET CC is set to *1*. This variable, along with variable GEN VR IND LIC CC in the bracket AFB BR IND LIC, tells the system that the allowances are being calculated using a labor agreement bracket and should not be calculated again based on the legal setup.

Related Links

"Defining Bracket Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

"Defining Variable Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

Understanding Specific Contracts

Understanding Specific Contracts

Specific contracts confer exemptions from social contributions. They are usually set up between an employer and a government department or between an employer and payee, subject to controls from the DDTE. PeopleSoft delivers rules for common exemptions for professionalization contracts, apprentice contracts, trainee contracts, fixed-term contracts, other specific exempted contracts, and specific categories of payees.

Contracts affect areas of the payroll process in addition to the calculation of social contributions. For example, there may be unique earnings for payees with specific types of contracts, and payees with certain contracts may not be included in the employee headcount.

Note: Global Payroll for France delivers earnings for certain categories of payees. These earnings are described in subsequent sections of this topic.

Important! Sometimes the information needed to determine a contract employee's social contribution is not available from PeopleSoft HR. In these cases, the formula SIT FM assigns a default value. During the implementation of your system, you can create fields to manage the values not currently provided by PeopleSoft HR and you can create any needed elements (arrays, for example) to update the formula SIT FM.

Related Links

[SIT FM Formulas](#)

Professionalization Contracts

PeopleSoft Global Payroll for France doesn't provide rules for calculating compensation for payees with professionalization contracts; however, PeopleSoft does provide rules to manage minimum wage levels, social security contribution exemptions, and other conditions related to the professionalization contract.

This section provides an overview of the professionalization contract and discusses elements used to define professionalization contract rules.

Overview of Professionalization Contract

PeopleSoft Global Payroll for France delivers a number of rules to manage minimum salary requirements and contribution exemptions for payees with professionalization contracts, including:

- Minimum wage controls: Global Payroll for France controls that payee compensation falls within the statutory minimum wage (SMIC) based on age and educational level. For example, if an employee is

under 21 and doesn't have a professional baccalaureate, he/she qualifies for at least 55% of the SMIC. And if the employee is under 21 and has, at a minimum, a professional baccalaureate degree, he/she qualifies for at least 65% of the SMIC.

- Contribution exemptions: Global Payroll for France delivers two social security scheme codes—code 456 and code 457 (for Alsace Moselle)—to manage contribution exemptions. To view the rates and percentages associated with these schemes, access the URSSAF Rates and URSSAF Additional Setup pages.

Note: Contribution exemptions associated with the professionalization contract apply only to the portion of the salary that falls within the SMIC.

Note: To trigger the contribution exemptions associated with these social security codes, specify *CDP* (limited professionalization contract) or *CPI* (unlimited professionalization contract) as the contract type on the Contract Type/Clauses page in PeopleSoft HR, and then enter either code 465 or 457 in the Social Security Code field for each qualified payee.

See [Understanding URSSAF Contributions](#).

- Limitation on benefits in kind:

Benefits in kind cannot constitute more than 75% of the minimum wage. In other words, employees with professionalization contracts must receive at least 25% of their compensation in monetary form.

- Warning messages to enforce age limits for assigning professionalization contracts.

The system generates a warning message if a social security code for professionalization contracts is assigned to an employee who is 25 years of age or over and below 45.

- Warnings to prevent exemptions from extending beyond the contract end date.

At the end of the professionalization period in an unlimited contract, the specific compensation rules and social security exemptions associated with the contract must be stopped and the payee can then continue employment under a new social security scheme. To prevent the conditions of the professionalization period from extending beyond the contract end date, Global Payroll for France issues a warning to the user to assign payees to a new social security scheme. This warning is generated when the current pay period end date exceeds the contract end date.

Note: In the case of a limited professionalization contract, the payee cannot continue working under a new contract when the contract ends.

Note: All rules related to the professionalization contract have an effective date of 1 October 2004.

Note: The professionalization contract replaces the qualification, orientation, and adaptation contract rules delivered in earlier versions of Global Payroll for France.

Elements Used to Define Professionalization Contract Rules

This section discusses:

- Delivered elements for minimum wage (SMIC) controls.

- Delivered elements to limit benefits in kind.
- Delivered elements to generate age limit warnings.
- Delivered elements to prevent overextension of the professionalization contract.

Delivered Elements for Minimum Wage (SMIC) Controls

The percentage of the minimum wage (SMIC) that a payee is entitled to receive varies by age and educational level.

PeopleSoft delivers the bracket GEN BR SMIC PROF to return the applicable SMIC percentage based on age.

PeopleSoft delivers the bracket GEN BR NIVEAU ETUD to return an additional SMIC percentage based on educational level.

Note: You should review the information in this bracket and, if necessary, modify the additional SMIC percentage based on educational level to reflect the rules in effect in your organization.

The system adds the percentages returned by these brackets to calculate the minimum percentage that the payee should receive.

See [Brackets for Professionalization Contract Minimum Wage \(SMIC\) Controls](#).

Delivered Elements to Limit Benefits in Kind

PeopleSoft delivers a variable—IND VR AN COEF—to store the maximum percentage of a payee's compensation that can be comprised of benefits in kind. The value of this variable is set to .75 by the formula APP FM INIT for all payees with a professionalization contract.

PeopleSoft uses the formula APP FM BASE to put payments in error when the percentage of a payee's compensation consisting of payments in kind exceeds 75%. It does this by adding all payments in kind, and then dividing the resulting sum by all payments in kind plus any monetary compensation stored in the accumulator APP AC SAL ESP SG. If the resulting quotient is greater than .75, the formula puts the payment in error.

Delivered Elements to Generate Age Limit Warnings

PeopleSoft uses the formula APP FM INIT to generate a warning message when a payee 26 years of age or older and less than age 45 has been granted a professionalization contract. This message appears in the Payee Messages component.

Delivered Elements to Prevent Overextension of the Professionalization Contract

PeopleSoft delivers the formula GEN FM DT FIN PROF to prevent the conditions of the professionalization period from extending beyond the contract end date. This formula compares the value of the system element CONTRACT EX END DT — which contains the expected contract end date from the Contract Status/Content page — to the current date. If the two dates are not equal, and the segment end date for the calculation period is greater than the expected contract end date, the formula assigns a value of 1 (true) to the variable GEN VR FIN CT PROF. Otherwise, the value of the variable is 0 (false).

The value of this variable (GEN VR FIN CT PROF) is then "read" by a second formula, APP FM INIT. This formula determines if the variable is equal to 1 (true). If so, it generates a warning message that the professionalization contract should be terminated.

Important! By default, the value of the system element CONTRACT EX END DT is the same as the expected end date specified on the Contract Status/Content page. If the end date on Contract Status/Content page is incorrect, you can override the value of the system element with the correct end date. To do this, enter positive input at the payee level.

Apprentices

This section discusses:

- Apprentice contracts.
- Apprenticeship period.
- URSSAF contributions.
- ASSEDIC contributions.
- Levies.
- ARRCO/AGIRC contributions.
- Contingency funds.
- Counting employees.

Related Links

"Defining Bracket Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

"Defining Variable Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

[Bracket for Specific Contract Compensation Scale](#)

Apprentice Contracts

Apprentices, by law, may not earn less than a set percentage of the SMIC (legal minimum salary). The percentage depends on the age of the apprentice and the year of the contract. You enter the apprentice's salary and a control checks whether the earning is below the legal minimum. If this is the case, the system generates a warning message.

The bracket APP BR REMUN stores the minimum percentages to apply to the SMIC according to the year of contract and the age of the payee. The appropriate percentage is retrieved and checked with the standard SMIC control.

The age of the payee is calculated using the payee date of birth in PERSONAL_DATA. The year of the contract is calculated using the contract begin date in the contract data.

Year of contract	Percentage of the SMIC for apprentices under 18	Percentage of the SMIC for apprentices between 18 and 20	Percentage of the SMIC or of the conventional salary for apprentices over 21
1 st year	25 %	41 %	53 %
2 nd year	37 %	49 %	61 %
3 rd year	53 %	65 %	78 %

Note: The system does not calculate the minimum salary; it does check that the salary you entered is greater than the minimum required by law. Because the system does not manage the conventional salary (that is, the minimum salary required by the collective agreement) for apprentices over the age of 21, the system applies the percentages in the previous table on the SMIC only.

Apprenticeship Period

The normal length of an apprenticeship is two years. However, in some circumstances, this may be extended to three years. In this case, use the variable GEN VR ANC REINT to subtract or add a period of time from the contract begin date to compensate for the extension of the apprenticeship period.

There may be times when you need to modify the number of years for a contract calculated between the contract begin date and the first day of the period. You can override the variable GEN VR ANC REINT by the number of days to add or subtract for the calculation of the year of the contract.

URSSAF Contributions

Payees are assigned to a particular contribution class (*régime*) that determines their URSSAF contributions. Apprentices in organizations with more than ten payees have a specific contribution class of their own—*régime* code 128.

The funding base percentage for apprentices is a lump-sum amount determined by the government. This percentage varies according to the age of the payee and the year of the contract. The bracket APP BR BASE stores the lump-sum funding base in euros. You should update this bracket to comply with the law and to meet your particular needs.

For organizations with less than ten payees, neither employer nor payee is liable to pay URSSAF contributions for apprentices. No *régime* code is entered and no deductions are made.

The lump-sum funding base calculated for apprentices is not used in the base for the ceiling regularization. The contributions are paid each month based on the lump-sum funding base. If an apprentice ends his apprenticeship contract and continues his work for the same organization under a new contract type, the salaries he received during his apprenticeship contract won't be used in the annual ceiling regularization.

Related Links

[Understanding URSSAF Contributions](#)

"Defining Bracket Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

"Defining Variable Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

ASSEDIC Contributions

In organizations with less than ten payees, neither employer nor payee is required to pay ASSEDIC contributions for apprentices. No deductions are triggered.

In organizations with more than ten payees, ASSEDIC deductions are triggered, but they are subject to a generation control. Payee contributions are not triggered if the payee is an apprentice. No controls are provided for the employer's contribution.

Note: The system checks the contract type to determine whether a payee is an apprentice. Therefore, during setup, it is important to update the contract type with the correct value.

Levies

Levy deductions are not triggered for apprentices in organizations with less than ten payees.

For organizations with more than ten payees, these deductions are triggered. There are no CSG and CRDS deductions for apprentices.

The funding base percentage for apprentices is a lump-sum amount determined by the government. This percentage varies according to the age of the payee and the year of the contract. The bracket APP BR BASE stores the lump-sum funding base in euros. You should update this bracket to comply with the law and to meet your business requirements.

Related Links

[URSSAF Contributions](#)

ARRCO/AGIRC Contributions

Payees do not pay ARRCO/AGIRC contributions if they are apprentices. And if a payee is an apprentice, the ARRCO/AGIRC employer's contributions are due only if the organization has more than ten payees and these contributions are triggered.

Contingency Funds

Contingency fund contributions follow the same rules as for ARRCO/AGIRC. For organizations with more than ten payees, there is only a single contribution from the employer. For organizations with less than ten payees, no contribution is triggered.

Counting Employees

Apprentices are not included in the head count of employees. This may have an impact on contributions that depend on the number of employees in the organization (that is, more or less than ten).

Related Links

[Understanding Employee Counts](#)

Trainees

This section discusses:

- Trainee contracts.
- Earnings.
- Social security contributions.
- Trainee examples.

Warning! The tax rules described in this section may be updated after the release of this version of PeopleSoft Global Payroll for France. For information about tax updates, review the additional documentation for Global Payroll for France on My Oracle Support.

Trainee Contracts

Trainees are identified using the formula SIT FM STG URSSAF. If this formula retrieves the value GP TRUE (1), the payee is considered a trainee. If this formula retrieves the value GP FALSE (0), the payee is not considered a trainee.

Trainees are not covered by a work contract because they are not classified as salaried employees.

The training establishment may or may not be covered for work accident insurance (RT), and the training may or may not be mandatory. Both of these factors affect the trainees' earnings and contributions.

PeopleSoft delivers different earnings to identify whether the establishment is covered for work accident insurance.

Earnings

Earning	Description
STG OBL AT	For trainees undergoing mandatory training with AT coverage.
STG OBL NAT	For trainees undergoing mandatory training without AT coverage.
STG NOBL	For trainees undergoing non-mandatory training.

These earning are automatically segmented and prorated when they are assigned to payees on the Element Assignment by Payee or Payee Assignment by Element pages and the assignment period covers only a portion of the pay period.

See "Payee Overrides and Segmentation (*PeopleSoft HCM 9.2: Global Payroll*)".

All of these earnings add to the accumulator GEN AC BRUT SG. The delivered rules compare these earnings to the minimum salary or relevant percentage of the minimum salary.

PeopleSoft delivers variables specifically for trainees that you may need to define by entering supporting element overrides. There are two types of variables:

- Variables used in conjunction with the trainee earnings.

GEN VR STAG NB M and GEN VR STG NSIR affect the processing of trainee earnings listed in the previous table.

- Variables used for trainees who don't receive compensation.

In certain cases, contributions must be paid for trainees who are not paid. However, these trainees aren't assigned the trainee earnings, and contributions are therefore not triggered in the normal way. To indicate situations in which there is no compensation and contributions are due, PeopleSoft delivers variables GEN VR STG O AT, GEN VR STG ONAT, and GEN VR STG NOBL.

Variable	Description
GEN VR STAG NB M	<p>Used to indicate the period that an allowance covers. The default value is <i>1</i>, which means that compensation is paid each month. Override this variable if you pay trainees for multiple months in only one payroll. In such cases, the system needs to control that this compensation falls within the legal limits multiplied by the number of months.</p> <p>For example, if a trainee stays with an organization for two months for mandatory training and the trainee is paid at the end of the two month period, you must override GEN VR STAG NB M with <i>2</i> to ensure that the system correctly calculates the contributions.</p>
GEN VR STG NSIR	<p>Used to indicate whether the training lasts more or less than three months. This information is used to determine whether the compensation paid to the trainee is subject to income tax (that is, whether the accumulator GEN AC NET FISCAL is populated by the compensation amount).</p> <p>For mandatory training with a duration of three months or less, the variable is set to <i>1</i> (this is the default value). If you want to indicate that the training lasts more than three months, override the variable GEN VR STG NSIR by assigning the value zero (<i>0</i>) or by using the variable GP FALSE.</p>
GEN VR STG O AT	Used to indicate mandatory training with work accident coverage for trainees who don't receive compensation.
GEN VR STG ONAT	Used to indicate mandatory training without work accident coverage for trainees who don't receive compensation.
GEN VR STG NOBL	Used to indicate non-mandatory training for trainees who don't receive compensation.

Social Security Contributions

All trainees are subject to URSSAF, transportation, and CSG/CRDS contributions. URSSAF contributions are based on *régime* codes, but for trainees it is not necessary to enter the code. The system assigns the correct *régime* code based on such factors as the trainee's compensation level, whether training is mandatory or non-mandatory, and the work accident coverage.

Trainees are not subject to contributions for ASSEDIC, ARRCO/AGIRC, contingency funds, training tax, or levies.

Initially, the system triggers all contribution deductions. Then, a generation control for each contribution checks whether the payee is a trainee. Payment is not processed for contributions that do not apply to trainees. Transportation contributions are triggered by checking whether URSSAF contributions are being paid, because both have the same conditions of eligibility.

Description	Social Security Contributions: Payee's Part	Social Security Contributions: Employer's Part	CSG / CRDS
Compensation \leq 30% of the SMIC: AT risk covered	Not Liable	Not Liable	Not Liable
Compensation \leq 30% of the SMIC: AT risk not covered	Not Liable	Liable for 25% of the SMIC	Not Liable
Compensation $>$ 30% of the SMIC: AT risk covered	Liable	Liable except for AT deduction	Liable
Compensation $>$ 30% of the SMIC AT risk not covered	Liable	Liable	Liable

Some contributions can be paid on 25 percent of the SMIC even if the payee doesn't receive any compensation.

Description	Social Security contributions: Payee's Part	Social Security contributions: Employer's Part	CSG / CRDS
Training not compensated	No Contributions	Liable on 25% of the SMIC	No Contributions
Training compensated: compensation \leq 25% of the SMIC	Not Liable	Liable on 25% of the SMIC + benefits in kind	Not Liable
Training compensated: compensation \geq 25% of the SMIC	Liable	Liable	Liable

In this case, AT contributions are paid when the employer contributes on 25 percent of the SMIC or on the complete compensation.

Trainee Examples

This section discusses the following examples of trainee earnings and contributions:

- Example 1: mandatory training, four months, with insurance.
- Example 2: mandatory training, five months, no compensation or insurance.

Example 1: Mandatory Training, Four Months, with Insurance

Suppose that a payee is taking mandatory training and is covered for work accident insurance by the employer. Training lasts for four months and the payment is 152 euros per month. To process this trainee:

- Enter the compensation using the earning STG OBL AT.

The work accident coverage is deducted from the same earning.

- Update the variable GEN VR STG NSIR because the training period is longer than three months.

The salary becomes liable to income tax when the training exceeds three months.

Example 2: Mandatory Training, Five Months, No Compensation or Insurance

Suppose that a payee is taking mandatory training and is not covered for work accident insurance by the employer. Training lasts for five months and there is no payment.

To process this trainee, you would update the variable GEN VR STG ONAT to 1 (TRUE). In this case, the employer is liable for some contributions. These are calculated on 25 percent of the SMIC. There are no CSG/GRDS contributions.

Because there is no compensation, it is not necessary to update any earnings or deductions. The result of the process is that there are no payee contributions.

Work Initiative Contracts(Contrat Initiative Emploi)

This section discusses:

- Work initiative contracts.
- CIE and Return-to-work contracts (*Contrat de Retour à l'Emploi*).
- Fixed and unfixed term contracts.
- Contributions.
- Counting employees.

Work Initiative Contracts

The *Contrat Initiative Emploi* (CIE) helps unemployed people return to work. The payees eligible for this contract must meet certain requirements. Depending on the situation of the payee, the employer is entitled to help and exemptions from contributions.

There are two values in the Contract Type table used to identify the CIE contract:

- *INE* is the value for a CIE without a fixed term.
- *IND* is the value for a CIE with a fixed term.

CIE and Return-to-Work Contracts(Contrat de Retour à l'Emploi)

Before the CIE contract was created, there was a similar contract that helped the unemployed return to work called the *Contrat de Retour à l'Emploi* (CRE). When the CIE was introduced, many payees continued to work under old CRE contracts. Payees who are still working with CRE contracts follow

the same rules as payees under CIE. The only difference is the social security code used to manage the URSSAF contributions for these two contracts.

For the CRE, the social security code used is code 944 (945 for Alsace-Moselle) and is applied to payees over 50 years of age and unemployed for more than one year when they signed their contracts. For the CIE, two social security codes may be used: 956 for general cases or 960 for contracts concluded with people over 50 years of age (957 and 961 for Alsace-Moselle).

Fixed and Unfixed Term Contracts

The CIE may be a fixed-term contract (IND) or a contract without term (INE). CDD contracts are for a minimum of 12 months and a maximum of 24 months.

At the end of the CDD, the payee is not eligible for the end-of-contract allowance.

Related Links

[Understanding Allowance Calculation](#)

Contributions

Employers hiring people under CIE are entitled to exemption from social security contributions for illness, maternity, disability, death, and old age deductions. The exemption is applied to the part of the salary that does not exceed the SMIC. The part greater than the SMIC is then subject to the normal contributions based on the associated *régime*.

To manage work initiative contracts, assign the contract type *IND* or *INE* and social security code 956 (for normal cases) or 960 (for those over 50) to eligible payees on the Contract Type/Clauses page in PeopleSoft HR.

Note: In Alsace-Moselle, use social security codes 957 and 961 instead.

The limit for the contribution exemption is equal to the hourly SMIC value multiplied by the number of paid hours.

For the CDD, the exemption is granted for a maximum of 24 months. For the CDI, the exemption is granted for 24 months. For payees over 50 years of age and some other specific categories, the exemptions are granted for the complete duration of their contracts.

At the end of the two years exemption limit, you must modify the social security codes at the payee level for payees under 50 years of age. Payees who were over 50 years of age when their contracts were signed are still entitled to exemptions after two years, so you do not need to change their codes.

Related Links

[Understanding URSSAF Contributions](#)

Counting Employees

Payees with CIE contracts are not included in the organization head count, except for the valuation of the work accident rate made by Social Security. Payees with fixed-term contracts are not counted until the end of the contract. Payees without fixed-term contracts are not counted for two years after the hiring date.

The system does not count payees with the contract types *INE* or *IND*. Payees without fixed-term contracts are not counted in the staff of the organization until their contract type value equals *CDI*. The system does not check whether the contracts last more than two years.

Fixed-Term Contracts

This section discusses:

- Fixed-term contracts.
- Fixed-term contracts for students
- Seasonal and custom contracts.

Related Links

[Understanding Levies](#)

[Understanding Allowance Calculation](#)

[Understanding the Wage Certificates Process](#)

Fixed-Term Contracts

The fixed-term contract (or CDD) is for a duration specified in advance. The standard work contract in France is the contract without term (CDI), and the CDD is regarded as an exception. The CDD is limited to specific cases determined by law.

The fixed-term contract is liable for the same contributions as a contract without a fixed term. In general, the following applies to fixed-term contracts:

- An extra training contribution is paid by the employer.

The contribution is called TAX FORMCDD. A generation control triggers this contribution, checking that the contract is CDD.

- An end of contract allowance is paid to the payee.

The payee receives an allowance at the end of a fixed-term contract equivalent to 10 percent of the gross earning during the duration of the contract. The allowance is not paid if the contract ends prematurely.

- Special rules for paid vacation apply to payees on fixed-term contracts.

Usually a payee has to work for 28 days before entitlement, but this qualification period is waived for fixed-term contracts.

Fixed-Term Contracts for Students

A special fixed-term contract exists for students. The only difference between a student contract and a regular CDD contract is that there is no allowance paid at the end of the contract.

Use the same contract type for current CDDs as for fixed-term contracts for students. To prevent the payment of the end-of-contract allowance, you must create a contract type value for this kind of contract.

Then update the bracket IND BR DT SPEC by indicating a different allowance entitlements for this kind of contract. In this case, the variable IND VR DP IFC populated by this bracket must be set to zero to avoid the triggering of the end-of-contract allowance.

Related Links

[Understanding Allowance Types](#)

Seasonal and Custom Contracts

Some special CDD contracts are defined for seasonal activity, and some custom contracts are defined for special industries, such as show business. As with fixed-term contracts for students, there is no end-of-contract allowance paid.

The triggering of the end-of-contract allowance should be prevented. HR provides as sample data the value Seasonal Contract in the Contract Type table. But you must update the bracket IND BR DT SPEC to manage this case.

Related Links

[Understanding Allowance Types](#)

Specific Categories of Payees

This section discusses specific categories of payees that have special rules applied to their contributions:

- Payees under 18.
- Assignees.
- Organization managers or officials.
- Doctors.

Payees Under 18

There is a different minimum wage (SMIC) for payees under the age of 18 who have spent less than six months with their employers. They may earn 80 percent of the SMIC if they are under 17 years of age and 90 percent of the SMIC if they are between the ages of 17 and 18.

Global Payroll for France checks the age of the payee, and if it is below 18, the system checks that the earning is not below the statutory percentage of the SMIC.

Assignees

Payees are classified as assignees in HR if they are assigned to another organization (*secondee*) and work outside of France. To classify a payee, enter *Assignee* in the Employee Class field. When you do this, the system updates the formula SIT FM DETACHE used by the rules.

Secondes pay the same contributions as other payees, except for the AGIRC contribution for managers and the CSG/CRDS contribution.

A situation has been created to allow a payee's salary to be treated as an expatriate and to allow a *secondee* to opt out of ARRCO/AGIRC contributions.

The formula SIT FM DETACHE AGI triggers the contributions for expatriate *secondees*. By default, this formula is equal to GP TRUE, which means that the payee pays ARRCO/AGIRC contributions. If the payee is considered an expatriate by the ARRCO/AGIRC, update this formula to GP FALSE (or 0), and the retirement contributions aren't triggered.

If the *secondee* is fiscally domiciled out of France, the *secondee* does not have to pay the CSG/CRDS contributions. You must override the formula SIT FM DOMICILE FR with GP FALSE to indicate that the payee is not domiciled in France and does not have to pay CSG/CRDS contributions.

Organization Managers or Officials

The formula SIT FM MANDATAIRE is used to identify organization managers. The formula SIT FM MANDATAIRE is equal to True (1) if the field Employee Professional Status in Contract Data information is equal to *Company Officer*.

The formula SIT FM MANDAT RETR is used for ARRCO/AGIRC contributions. You must manage the formula SIT FM MANDAT RETR. If the condition in the formula SIT FM MANDAT RETR is TRUE, retirement contributions are triggered. SIT FM MANDAT RETR is used to trigger the retirement contributions when a payee is an organization officer. By default, this formula is equal to GP TRUE, which means that the retirement contributions are triggered. You can override this formula to avoid calculating the retirement contributions. Payees are classified as non-managers by default (condition FALSE, value zero). You can change this value to classify a payee as a organization official. Organization officials are not liable to ASSEDIC contributions. The formula SIT FM MANDATAIRE is used to trigger ASSEDIC.

If an organization manager is not affiliated with URSSAF, set up your own rules to manage the situation. If the manager is affiliated with URSSAF, enter the *régime* code.

There is no ceiling proration for managers who are classified as part-time employees or who work for multiple employers. The formula SIT FM MANDATAIRE is used to avoid triggering the ceiling proration. By default, the formula retrieves the value GP FALSE; you can override this formula with GP TRUE if a payee is an organization officer.

Organization managers are not classified as employees and do not have any contract data. This means that they cannot be assigned URSSAF *régime* codes in the usual way. There is a contract type called *No work contract*, which is assigned to managers to allow *régime* codes to be assigned.

Related Links

[Understanding URSSAF Contributions](#)

Doctors

The situation formula SIT FM DOCTEUR has the default value FALSE. You can override it at the payee level to indicate that a payee is a doctor.

When you override the formula to be TRUE, you are indicating that the payee is a doctor and that no ceiling proration (for part-time or multiple employers) should be applied to the ceilings. The URSSAF *régime* class to enter for a doctor is 336, or 337 for a doctor in Alsace-Moselle.

Brackets for Specific Contracts

This section discusses:

- Brackets for professionalization contract minimum wage (SMIC) controls.
- Bracket for specific contract compensation scale.
- Bracket for specific contract contribution bases.

Related Links

"Defining Bracket Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

"Defining Variable Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

Brackets for Professionalization Contract Minimum Wage (SMIC) Controls

The bracket GEN BR SMIC PROF returns the applicable SMIC percentage based on age. The payee's age is contained in the element GEN DR AGE ANNEES, which functions as the search key.

The bracket GEN BR NIVEAU ETUD returns an additional SMIC percentage based on educational level. The payee's educational level is contained in the system element HI EDUC LV, which functions as the search key.

Global Payroll uses the formula APP FM INIT to add the two percentages returned by these brackets to calculate the minimum SMIC percentage due to the payee. For example, if the percentage returned by the bracket GEN BR SMIC PROF is 55%, and the percentage returned by the bracket GEN BR NIVEAU ETUD is 10%, the formula calculates a minimum compensation level of 65% of SMIC.

GEN DR AGE ANNEES (Key)	GEN BR SMIC PROF
21	55
26	70
99	100

HI EDUC LV (Key)	GEN BR NIVEAU ETUD
A	0
B	0
C	0
D	0
E	0
F	10
G	10

<i>HI EDUC LV (Key)</i>	<i>GEN BR NIVEAU ETUD</i>
H	10
I	10
J	10
K	10
L	10

Note: You should review the information in this bracket and, if necessary, modify the additional SMIC percentage based on educational level to reflect the rules in effect in your organization.

Bracket for Specific Contract Compensation Scale

The bracket APP BR REMUN returns values for the specific contract compensation scale. It returns values for the apprenticeship contract and also for the qualification and orientation contract. The keys for this bracket are CONTRACT TYPE and APP VR ANNEE CONT, and the return column is APP BR REMUN. The variables APP VR REM-21 and APP VR REM+21 are populated based on the key as follows:

- The bracket APP BR REMUN retrieves the percentage for payees under 18 years old.
- The variable APP VR REM-21 retrieves the percentage for payees between 18 and 21 years old.
- The variable APP VR REM+21 retrieves the percentage for payees over 21 years old.

It's important that you understand the definition of this bracket because PeopleSoft delivers, but does not maintain, this bracket. You must maintain this bracket to ensure that your setup functions properly.

<i>CONTRACT TYPE (Key)</i>	<i>APP VR ANNEE CONT (Key)</i>	<i>APP BR REMUN (Return)</i>	<i>APP VR REM-21 (Variable)</i>	<i>APP VR REM+21 (Variable)</i>
<i>APP</i>	1	25	41	53
<i>APP</i>	2	37	49	61
<i>APP</i>	3	53	65	78
<i>QUA</i>	1	30	50	65
<i>QUA</i>	2	40	60	75
<i>ORI</i>		30	50	65

Bracket for Specific Contract Contribution Bases

The bracket APP BR BASE returns values for specific contract wages contribution bases. The key for this bracket is APP VR % BASE, and the return column is APP BR BASE. The variable APP VR BASE EUR is populated based on the key.

It's important that you understand the definition of this bracket because PeopleSoft delivers, but does not maintain, the bracket. You must maintain this bracket to ensure that your setup functions properly.

Note: The bracket APP BR BASE retrieves the lump sum funding base in euros.

The value returned by the bracket APP BR REMUN is used to determine if the minimum salary is correctly applied to the apprentice. This value is also used as the funding base for all the contributions paid. This value is calculated for a payee who is present for the entire month. The apprentice funding base is prorated depending on the number of days present during the period and depending on the paid hours of the payee.

If you don't want to apply this last proration or if you want to apply a different proration, modify the formula APP FM PRORAT BASE (defined as *Customer Maintained*) that is used to prorate the apprentice funding base following the number of paid hours.

SIT FM Formulas

PeopleSoft HR tables provide some of the data needed by Global Payroll for France and other data is provided by Global Payroll tables. Sometimes, however, the information needed to verify a particular situation does not exist in the tables. For such instances, PeopleSoft delivers formulas with the prefix SIT that you can update to meet the specific needs of your organization. PeopleSoft does not maintain these formulas.

You can update these formulas in one of two ways:

- Update the table where the information is missing or create the needed missing field.

This will automate the resolution of the information. Then you can use system elements, if they exist, to retrieve the new values (for example, if the new value created is in the Contract Type table, the system element Contract Type retrieves it). Or, you can create an array to retrieve the value of the field you created. This solution can be useful if the situation occurs often so that you do not have to manually update the formulas.

- Override the formulas with the correct value, as needed.

This solution is best for cases that do not occur often.

Understanding Vacation Accruals

Accruals

Global Payroll for France manages accruals for paid vacation.

Two different paid vacation accruals are calculated: the paid vacation accruals of the current accounting year and the accruals of the paid vacation balance of past accounting years. These accruals are considered future earnings of the payees during their vacations. The accruals calculation also includes the future contributions paid on these vacations.

PeopleSoft delivers, but doesn't maintain, the elements, formulas, accumulators, and sections used in the accruals process. You must ensure that the rules comply with regulations and with your company's needs.

Related Links

"Global Payroll Integrations (*PeopleSoft HCM 9.2: Global Payroll*)"

[Understanding Levies](#)

Paid Vacation Accruals Calculations

There are two accruals associated with a paid vacation: one for the current year and one for previous years. The formula PRO FM EC CP+CHARG retrieves the paid vacation accruals plus the theoretical contributions that apply to it for the current year (that is, for the paid vacation entitlements calculated beginning on June 1).

The formula PRO FM EP CP+CHARG retrieves the paid vacation accruals plus the theoretical contributions that apply to it for the previous years.

The calculation for determining the accrual compares one-tenth of the annual salary to a calculation based on the Salary Uphold rule and accepts the most favorable amount.

The formula PRO FM TX CHARGES calculates the employer's contribution rate based on the payee's gross salary.

To apply a lump-sum contribution rate for all payees (rather than calculating a different rate for all payees), override the formula PRO FM TX CHARGES by indicating in the override the rate you want to apply.

The calculation involves two formulas. PRO FM EC CP+CHARG produces the paid vacation accruals for the current year and PRO FM EP CP+CHARG calculates paid vacation accruals for the previous three years.

Related Links

[Understanding Allowance Types](#)

Understanding Integration with Learning Management Applications

Understanding Integration with Administer Training and Enterprise Learning Management

This section discusses:

- Integration between the Administer Training business process and Global Payroll for France.
- Integration between PeopleSoft Learning Management and Global Payroll for France.

Integration Between the Administer Training Business Process and Global Payroll for France

The Administer Training business process integrates with Global Payroll for France to enable Training Administration users to produce the 2483 report using French payroll data, track DIF balances, and compensate learners for DIF training and other training completed outside the normal work schedule.

The two applications interact as follows:

- Training Administration is the application that you use to track learning costs and to manage enrollment and other day-to-day tasks.
- DIF and skills development training hours entered on the enrollment pages in Training Administration are validated by training and payroll administrators and sent to Global Payroll for processing.
- Global Payroll for France calculates learners' DIF entitlement balances. Administer Training business process users can then import these balances from Global Payroll for France back into the training management application where they can be viewed by managers on the enrollment pages.
- Global Payroll for France generates learner and instructor data for the 2483 report and calculates the salary for DIF and skills development training completed outside of normally scheduled work hours.
- The Administer Training business process compiles Global Payroll and other HR information and generates the 2483 report.

Note: Detailed information about how to integrate the Administer Training business process with Global Payroll for France can be found in the *PeopleSoft HR : Administer Training*.

See "Understanding Training Costs (*PeopleSoft HCM 9.2: Human Resources Administer Training*)", "Understanding the French Training Report 2483 Process (*PeopleSoft HCM 9.2: Human Resources Administer Training*)", "Understanding Integration with Applications (*PeopleSoft HCM 9.2: Human Resources Administer Training*)".

Integration Between PeopleSoft Learning Management and Global Payroll for France

Enterprise Learning Management integrates with Global Payroll for France 8.9 and above indirectly, by way of the Administer Training business process in HR 8.9 and above. This integration enables Enterprise Learning Management users to produce the 2483 report using data generated in Global Payroll for France, track DIF balances, and compensate learners for DIF training hours and training hours completed outside the normal work schedule.

The three applications interact as follows:

- Enterprise Learning Management is the application that you use to set up the learning catalog, instructors, vendors, and so on. You also use this application to track learning costs and to manage enrollment and other day-to-day tasks.
- DIF and skills development training hours entered on the enrollment pages in Enterprise Learning Management are validated by training and payroll administrators and sent to Global Payroll for processing.
- Global Payroll for France calculates learners' DIF entitlement balances and returns the results to Enterprise Learning Management (indirectly through Training Administration). Enterprise Learning Management can then display DIF balances to learners and managers on the self-service pages and to administrators on the roster pages.
- Global Payroll for France generates learner and instructor data for the 2483 report and calculates the salary for DIF and skills development training completed outside of normally scheduled work hours.
- The Administer Training business process in HR compiles information provided by Enterprise Learning Management and Global Payroll and generates the 2483 report.

Note: Detailed information about the integration points and other data you need to set up to integrate Enterprise Learning Management with Administer Training and Global Payroll for France can be found in the *PeopleSoft Learning Management* and in the *PeopleSoft HR : Administer Training*.

Warning! If you are using Enterprise Learning Management to set up and track learning, do not use the Administer Training business process for these tasks. Use the Administer Training business process only to: 1) configure and generate the 2483 report, 2) approve training hours before sending them to Global Payroll for France for processing, and 3) run the import process for returning DIF balance data to HR where it can be picked up by Enterprise Learning Management.

Related Links

[Understanding Integration with Administer Training and Enterprise Learning Management](#)

"Understanding Integration with Applications (*PeopleSoft HCM 9.2: Human Resources Administer Training*)"

"Understanding the French Training Report 2483 Process (*PeopleSoft HCM 9.2: Human Resources Administer Training*)"

Processing DIF and Skills Development Training Hours

If you set up the Administer Training business process or Enterprise Learning Management to integrate with Global Payroll for France, both DIF and skills development training hours entered on the enrollment pages in these applications can be validated by training and payroll administrators and sent to Global Payroll for processing. Within the Global Payroll system, these hours are used to calculate training entitlements (earnings) due to payees.

This section provides an overview of how Global Payroll for France processes training hours.

Understanding How Global Payroll for France Processes Training Hours

When training and payroll administrators validate and save DIF and skills development training hours using the FRA Training Validation (GP) component, the system creates positive input for the current pay group, calendar, employee ID, and employee record number. This data triggers processing of one or more DIF and skills development entitlement (earning) elements in the next Global Payroll run.

Payroll Element	Description
HRS DIF PEND	<p>When DIF hours within the work schedule are > 0, the system assigns the earning HRS DIF PEND to the payee using positive input.</p> <p>This earning has a calculation rule of Amount. The amount is defined as the formula FOR FM DIF PENDANT.</p>
FOR VR HRS DIF	<p>This variable stores the DIF hours within the work schedule to process in the current payroll calendar. These hours are used by the formula FOR FM DIF PENDANT to calculate the earning element HRS DIF PEND.</p> <p>It is populated using a supporting element override.</p>

Payroll Element	Description
HRS DIF HORS	<p>When DIF hours outside the normal work schedule are > 0, the system assigns the earning HRS DIF HORS to the payee using positive input.</p> <p>This earning has a calculation rule of Unit x Rate, with the rate defined as the formula FOR FM TX DIF-DEV, and the unit defined as the formula FOR FM DIF HORS.</p>
FOR VR HRS DIF	<p>This variable stores DIF hours for training that takes place outside of the normal work schedule to process in the current payroll calendar.</p> <p>It is populated using a supporting element override.</p>
FOR VR DT DEB FOR	<p>This variable stores the topic cut start date for DIF training that occurs outside of normal work hours.</p> <p>It is populated using a supporting element override.</p>

Payroll Element	Description
HRS DEV HORS	<p>When skills development hours outside the normal work schedule > 0, the system assigns the earning HRS DEV HORS to the payee using positive input.</p> <p>This earning has a calculation rule of Unit x Rate, with the rate defined as the formula FOR FM TX DIF-DEV, and the unit defined through payee level input.</p>
FOR VR DT DEB FOR	<p>This variable stores the topic cut start date for skills development training that occurs outside of normal work hours.</p> <p>It is populated using a supporting element override.</p>

Related Links

"Understanding Integration with Applications (*PeopleSoft HCM 9.2: Human Resources Administer Training*)"

Calculating DIF and DIF in Advance Balances

Using the training hours entered through Administer Training or Enterprise Learning Management, Global Payroll for France calculates both DIF entitlement (FOR AC DROIT DIF) and DIF in advance (FOR VR DIF NEGATIF) balances for all trainees and loads this data into a table using the writable array FOR WA DIF HR. Users of Training Administration and Enterprise Learning Management can then import DIF balances and DIF in advance hours back into their learning management systems, making it available to learners and administrators who need to determine whether there are enough hours in a student's DIF balance to permit additional DIF allocations.

This section explains how each application imports DIF and DIF in advance balances generated in Global Payroll for France.

Note: The element FOR AC DROIT DIF stores the DIF entitlement balance and is calculated as the trainee's DIF allocation minus the DIF hours already used. The element FOR VR DIF NEGATIF stores the number of hours of additional DIF training (DIF in advance) that can be granted beyond what is available in the DIF balance.

Note: Depending on company policy, you can allocate DIF training hours that exceed the entitlement balance by allowing the DIF entitlement to go into negative numbers. For example, if a trainee's DIF entitlement balance is 2, you can grant a total of 7 DIF hours by enabling the DIF entitlement balance to drop to -5. To do this, access one of the supporting element override pages in PeopleSoft Global Payroll and set the value of FOR VR DIF NEGATIF to 5.

Importing DIF and DIF in Advance Balances into Administer Training

If you are a Training Administration user, complete these steps to import the balance data:

1. Run the payroll process in Global Payroll.

2. Run the import process using the DIF Payroll Import page (Enterprise Learning, Result Tracking, DIF Payroll Import FRA, DIF Payroll Import).

On this page you specify the begin and end dates of the payroll period for which you want to import the DIF and DIF in advance balance data and the pay group for which you want to retrieve the data.

Importing DIF and DIF in Advance Balances into Enterprise Learning Management

If you are an Enterprise Learning Management user, you import DIF and DIF in advance balances from Global Payroll indirectly, by way of Administer Training. To do this, complete these steps:

1. Run the payroll process in Global Payroll.
2. Import the DIF and DIF in advance balances into Administer Training using the DIF Payroll Import page (Enterprise Learning, Result Tracking, DIF Payroll Import FRA, DIF Payroll Import).
3. Run the full sync integration point: LM_DIF_BALANCE_FULLSYNC to load the balances in Administer Training into a staging table.
4. Run the Process FullSync Data (LM_LD_STGDAT) process to validate and load the balances into Enterprise Learning Management.

Related Links

"Understanding Integration with Applications (*PeopleSoft HCM 9.2: Human Resources Administer Training*)"

[Understanding Integration with Administer Training and Enterprise Learning Management](#)

Making Training Data Available for the 2483 Report

Global Payroll delivers the writable array FOR WA 2483 to make data generated by Global Payroll for France available to Administer Training for the generation of the 2483 report.

The data contained in the writable array includes:

- Instructors' gross salary (contained in the writable array field GROSS_AMT).
- Employees' DIF earnings for training outside of working hours (contained in the writable array field TRN_DIF_HORS).
- Employees' skills development earnings for training outside of working hours (contained in the writable array field TRN_DEV_HORS).
- Employees' gross salary when they are working as trainers full-time (contained in the writable array field TRN_FT_GROSS_AMT).

Note: Global Payroll for France populates the writable array when you run the payroll process.

Note: PeopleSoft uses the FOR WA 2483 writable array only when the 2483 report is based on HR or Enterprise Learning Management data.

Note: In addition to using Global Payroll for France data, the 2483 computation process uses information from the following sources: the PeopleSoft Administer Training business process in PeopleSoft HR, PeopleSoft Learning Management (if you are using Enterprise Learning Management to manage employee training in place of the Administer Training business process), contract data, and personal data.

Related Links

"Understanding the French Training Report 2483 Process (*PeopleSoft HCM 9.2: Human Resources Administer Training*)"

"Defining Writable Array Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

"Preparing and Running the Training 2483 Report (*PeopleSoft HCM 9.2: Human Resources Meet Regulatory Requirements*)"

The FOR WA 2483 Writable Array

Field Name	Description
COMPANY	Employee's company.
CONTRACT_NUM	Contract number.
ESTABID	Employee's establishment ID.
GPFR_SYSSRC	Temporary variable.
GPFR_TRN_NVALUE1to GPFR_TRN_NVALUE5	User assigned fields for decimal values.
GROSS_AMT	<p>Gross salary for the 2483 training report.</p> <p>According to legal requirements, the salary for instructors is composed of:</p> <ul style="list-style-type: none"> Employee gross salary before various deductions. Social security contributions to be paid by the employer. Legal taxes related to these salaries.
PAID_HOURS	Worked hours for the 2483 training report.
PRD_BGN_DT	Period begin date.
PRD_END_DT	Period end date.
RSLT_VER_NUM	Version number.
SEG_BGN_DT	Segment begin date.
SEG_END_DT	Segment end date.
TRN_DEV_HORS	Dev hours over std. hour (skills development earnings outside of working hours).
TRN_DEV_HORS_UN	Temporary variable.

Field Name	Description
TRN_DIF_HORS	DIF hours over std. hour (employees' DIF earnings for training outside of working hours)
TRN_DIF_HORS_UN	Temporary variable.
TRN_FT_GROSS_AMT	<p>Employee gross salary for full-time training.</p> <p>The GROSS_AMT field returns the gross salary whatever the employee job is. The TRN_FT_GROSS_AMT returns the salary employees receive during the period when they are working as part of the training staff on a full-time basis.</p> <p>The payroll system recognizes full-time instructor status if one of the following conditions applies:</p> <ul style="list-style-type: none">• The Full Time Instructor flag is selected on the Instructor Profile page, or• The JobCode and/or department list is considered to be dedicated to training jobs.

Understanding Retroactive Processing

Standard Retro Setup In Global Payroll for France

In Global Payroll for France, retroactive changes in the current year are processed using the corrective method, and retroactive changes in previous years are processed using the forwarding method.

Note: The default retroactive method for France is *corrective*; however, the standard retro method is defined as varying based on the calendar year, with *forwarding* defined as the retroactive method for calculations that go back to previous years.

This setup addresses the most common cases of retroactivity, and enables you to:

- Calculate retroactive changes to the gross salary.
- Apply the current contribution rates to the gross salary deltas.
- Declare contributions calculated retroactively.
- Manage most retroactive changes:
 - URSSAF scheme changes.
 - Contribution eligibility changes
 - Participation in unemployment (ASSEDIC) or retirement funds (AGIRC/ARRCO).
 - Change of establishment or company.
 - Retroactive hiring or departure.
 - Block recalculation of loans and garnishments.
 - Block recalculation of social contributions for completed years.

Note: Global Payroll for France does not deliver specific forwarding rules. If you decide to apply the delivered logic for processing retroactive changes—corrective for the current year and forwarding for past years—you must define your own forwarding rules.

Gross Salary Changes

This section discusses:

- Managing gross salary changes in the current year.

- Gross salary calculation steps and elements.
- Controlling retro calculations.

Managing Gross Salary Changes in the Current Year

The logic used to manage gross salary changes depends on the organization collecting the contributions:

- For URSSAF, ASSEDIC, and CSG/CRDS, the system performs a *partial* recalculation of the gross salary elements.
- For other contributions such as ARRCO and tax levies, Global Payroll for France performs a *full* recalculation of the gross salary elements.

This section provides an overview of both of these approaches.

Note: The explanations provided here deal specifically with recalculations in the current year using the corrective rules delivered by PeopleSoft. PeopleSoft does not deliver specific rules for processing retroactive changes in prior years.

Partial Recalculation

Some organizations such as URSSAF and ASSEDIC require that gross salary elements be submitted to the contribution rates in effect on the payment date. For example, if a payee receives a retroactive pay increase, the contribution rates of the current period should be applied to the gross salary deltas, rather than those in effect in the recalculated period (as the pay increase is only realized in the current period).

Global Payroll for France manages gross salary changes for URSSAF, ASSEDIC, and CSG/CRDS by:

- Recalculating the gross salary, taking into account the elements modified retroactively.
- Storing the recalculated gross in accumulators.
- Retrieving the old value of the gross rather than the recalculated gross to determine contributions in a prior period.

Note: The system recalculates the gross, taking into account the retroactive changes in salary. However, when calculating the funding base for URSSAF and ASSEDIC, the system does not use the recalculated gross but the "old value" of this gross.

- Recalculating funding bases, based on the old gross value, using standard rules.
- Using the annual regularization of contributions principle to process the recalculated gross deltas in the current period. Based on this principle, the system compares, in the current period, the gross salary effectively used (*submitted gross*) to calculate the funding bases, and the recalculated gross salary (*real gross*).
 - If no retro calculation is triggered or if the gross salary hasn't changed retroactively, the submitted gross and the real gross are equal, and there are no gross deltas to process.
 - If a retro calculation occurs with a change in the gross salary, the submitted gross and the real gross are different. This difference (positive or negative) corresponds to the gross delta and is

added to the gross calculated for the current period, where it is submitted to current contribution rates.

Note: The process described here is referred to as a *partial recalculation* because the gross salary used is the "old" or "previously calculated" gross.

Note: If a contribution rate changes retroactively but there is no change to the gross salary (no gross salary delta), the new rate is applied to the old value of the funding base. This is in keeping with the rule that the contribution rate to apply is the one in effect on the payment date.

Full Recalculation

For other contributions such as ARRCO, AGIRC, contingency funds, and tax levies, Global Payroll for France performs a *full* recalculation of the gross salary. In other words, the system does not retrieve the old gross values, but fully recalculates both the gross salary and the funding bases, and replaces the original calculations with the new ones (in keeping with the logic of the corrective retro method).

In addition, Global Payroll for France uses the full recalculation method whenever a retro mismatch situation occurs, regardless of the social organization. The reason for this is that mismatches produce reversal segments that completely cancel the initial calculations. This prevents the old value of the gross salary elements from being retrieved during retroactive processing.

Note: As a general rule, the full recalculation method is used to process gross salary changes for social organizations with rates that are fixed for the year. The partial recalculation method is used to process changes for social organizations with rates that occasionally vary during the year.

Warning! If the system *fully recalculates* the gross salary and funding bases in a situation in which rates *also change* between the recalculated and the current period, the gross retro deltas may be submitted to the old rate instead of the current rate. If this occurs, it is possible to manually enter, for a specific earning, the gross delta using positive input in the current period. However, you should consider the possible consequences of this solution, as it may prevent salary history from being correctly recorded in the system.

See "Understanding Complex Retro Processing (*PeopleSoft HCM 9.2: Global Payroll*)".

Gross Salary Calculation Steps and Elements

This section discusses:

- Gross salary and funding base calculation steps for URSSAF, ASSEDIC, and CSG/CRDS.
- Example of a gross salary recalculation for URSSAF.

Gross Salary and Funding Base Calculation Steps for URSSAF, ASSEDIC, and CSG/CRDS

Global Payroll for France goes through the following steps to calculate the gross salary and funding bases for each organization:

1. Initialization: The system determines the ceilings to use for the different organizations (URSSAF, ASSEDIC, and CSG/CRDS).

2. Gross salary calculation: The system calculates the different earnings and deductions included in the gross salary.
3. URSSAF, ASSEDIC, and CSG/CRDS-specific gross base calculation:
 - If there is a retroactive calculation, the system retrieves the old value of the base.
 - If the calculation is in the current period, the system calculates the gross deltas not submitted to contributions, and adds them to the current gross salary to determine the gross base.
4. Calculation of contribution funding bases: The system calculates the funding bases for the contributions by applying the ceiling limitations and exemptions based on the gross base for each organization (URSSAF, ASSEDIC, and so on).

Element Type	Name	Use
Accumulator	GEN AC BRUT SG	<p>The accumulator GEN AC BRUT SG is a generic accumulator storing all gross salary elements. It is used to populate the gross elements (accumulators or variables) for each organization:</p> <ul style="list-style-type: none"> • URSSAF: the segment accumulator URS AC BRUT SG stores the gross used in the URSSAF funding base calculation. • ASSEDIC: the segment accumulator ASS AC BRUT SG stores the gross used in the ASSEDIC funding base calculation. • ARRCO: the segment accumulator ARC AC BRUT SG stores the gross used in the ARRCO funding base calculation. • AGIRC: the segment accumulator AGI AC BRUT SG stores the gross used in the AGIRC funding base calculation. • Contingency Fund: the segment accumulator PRV AC BRUT SG stores the gross used in the contingency funding base calculation. • CSG/CRDS: the segment accumulator TAX AC ASS CSG SG stores the gross used in the CSG/CRDS funding base calculation.

<i>Element Type</i>	<i>Name</i>	<i>Use</i>
	URS AC BRUT AN	This accumulator stores the yearly gross salary submitted to URSSAF contributions.
	URS AC BRUT REEL AN	This accumulator stores the "real" URSSAF gross salary, which includes any gross deltas.
	ASS AC BRUT AN	This accumulator stores the yearly gross salary submitted to ASSEDIC contributions.
	ASS AC BRT REEL AN	This accumulator stores the "real" ASSEDIC gross salary, which includes any gross deltas.
	TAX AC ASS CSG AN	This accumulator stores the gross salary submitted to CSG/CRDS contributions.
	TAX AC BRT CSG AN	This accumulator stores the "real" CSG/CRDS gross salary, which includes any gross deltas.
Formula	URS FM BRUT REEL	<p>This formula is called in the contribution section URS SE COTISATION to manage the gross salary for URSSAF during retro corrective calculations.</p> <hr/> <p>Note: This formula can be removed from the section without affecting normal contribution calculations if you do not process corrective retro.</p> <hr/>
	ASS FM BRUT REEL	<p>This formula is called in the contribution section ASS SE COTISATIONS to manage the gross salary for ASSEDIC in retro corrective calculations.</p> <hr/> <p>Note: This formula can be removed from the section without affecting normal contribution calculations if you do not process corrective retro.</p> <hr/>

<i>Element Type</i>	<i>Name</i>	<i>Use</i>
	TAX FM BRT CSG REE	<p>This formula is called in the contribution section TAX SE CSG CRDS to manage the gross salary for CSG/CRDS in retro corrective calculations.</p> <hr/> <p>Note: This formula can be removed from the section without affecting normal contribution calculations if you do not process corrective retro.</p> <hr/>

The calculation process uses these elements as follows:

1. When a segment is processed in retro corrective mode, Global Payroll uses the formulas URS FM BRUT REEL, ASS FM BRUT REEL and TAX FM BRT CSG REEL to:
 - a. Retrieve the *old* value of the gross segment accumulator (URS AC BRUT SG, ASS AC BRUT SG, ARC AC BRUT SG, AGI AC BRUT SG, PRV AC BRUT SG, TAX AC ASS CSG SG).
 - b. Assign the old value to the gross segment accumulator processed in the retro calculation.
 - c. Add the recalculated gross value to the yearly *real* gross accumulator (URS AC BRUT REEL AN, ASS AC BRT REEL AN, TAX AC BRT CSG AN).
2. When a segment is processed in the current period or processed in retro forwarding mode, Global Payroll uses the formulas URS FM BRUT REEL, ASS FM BRUT REEL, and TAX FM BRT CSG REEL to:
 - a. Calculate the gross delta not submitted to contributions by subtracting the *submitted* gross accumulator (URS AC BRUT AN, ASS AC BRUT AN, TAX AC ASS CSG AN) from the *real* gross accumulator (URS AC BRUT REEL AN, ASS AC BRT REEL AN, TAX AC BRT CSG AN).
 - b. Add the delta calculated in step 2a to the current gross segment accumulator (URS AC BRUT SG, ASS AC BRUT SG, ARC AC BRUT SG, AGI AC BRUT SG, PRV AC BRUT SG, TAX AC ASS CSG SG).
 - c. Submit the amount calculated in step 2b to the funding base and contribution calculations for each social organization, using the contribution rates in effect in the current period.

Note: The URSSAF, ASSEDIC, and CSG/CRDS calculations described here are referred to as *partial recalculations* because the gross salary used is the "old" or "previously calculated" gross. By contrast, when calculating other contributions such as ARRCO and tax levies in corrective mode, the system *fully* recalculates the gross salary to determine the funding bases.

Example of a Gross Salary Recalculation for URSSAF

The following example of an URSSAF calculation illustrates the processing logic.

In this example:

- An employee is paid 100 EUR in January.
- In February, the employee's salary increases to 110 EUR. This change is retroactive to January.

	January	February
V1R1	Salary = 100 Retro = No Segment Gross Accum = 100 Annual Gross Accum = 100 Annual Real Gross Accum = 100	Salary = 110 Retro = No Segment Gross Accum = 110 + 110 - 100 = 120 Annual Gross Accum = 220 Annual Real Gross Accum = 220
V2R1	Salary = 110 Retro = Yes Segment Gross Accum = 100 (equal to the old value of the accumulator) Annual Gross Accum = 100 (stores the value of the segment gross accumulator used in the recalculation) Annual Real Gross Accum = 110 (stores the value of the recalculated gross salary)	

In the January recalculation (V2R1), the system uses the old value of the gross segment accumulator (URS AC BRUT SG) calculated in V1R1 (100) rather than the true, recalculated gross (110) stored in the annual *real* gross accumulator (URS AC BRT REEL AN). In the January recalculation period, the value of the annual submitted gross (URS AC BRUT AN) is therefore less than the value of the real gross (URS AC BRT REEL AN).

In February, the difference between the submitted and the real gross is eliminated, as the delta between these amounts—calculated by subtracting the submitted gross accumulator (URS AC BRUT AN) from the real gross accumulator (110 – 100)—is added to the current February segment gross (110), and the resulting amount is added to the total annual amount submitted to contributions (URS AC BRUT AN).

Controlling Retro Calculations

You can override the delivered partial recalculation of changes to the gross salaries for URSSAF, ASSEDIC, and CSG/CRDS by assigning a value of 1 to the following variables:

Social Organization	Variable
URSSAF	URS VR RTO CONTROL
ASSEDIC	ASS VR RTO CONTROL

Social Organization	Variable
CSG/CRDS	TAX VR RTO CONTROL

When you change the value of these variables to 1, the system fully recalculates and replaces the gross salaries in the recalculation period. If you do not override the variables URS VR RTO CONTROL, ASS VR RTO CONTROL, or TAX VR RTO CONTROL, the system uses the logic described earlier to manage the URSSAF, ASSEDIC, and CSG/CRDS gross accumulators.

Note: The only override value you can enter for the retro control variables is a value of 1. Other overrides are not considered. In other words, you are only authorized to force a full recalculation of the gross salary in cases of retroactivity.

Note: You can override the value of these variables at several different levels depending on your requirements: the pay entity level, the pay group level, or the payee level.

Variations on Standard Retro Processing

The standard solution for managing gross salary changes in the current year is:

- *Partial* recalculation of gross salary elements used to process contributions for URSSAF, ASSEDIC, and CSG/CRDS.
- *Full* recalculation of salary elements used to process contributions for ARRCO and tax levies.
- *Full* recalculation of salary elements in any situation in which there is a segment mismatch.

However, because different kinds of retroactive change require different solutions, PeopleSoft delivers several variations on the standard approach.

This section discusses variations that apply to:

- Gross salary changes with a change of establishment or company.
- Ceiling changes.
- Funding base exemption changes.
- Changes in the lump-sum funding base for apprentices.
- Contribution calculations for finalized years.
- Net guarantee.
- Contribution eligibility.
- Hiring and departure.
- Isolated amounts.
- Inactive segments.

Gross Salary Changes with a Change of Establishment or Company

Normally, when a payee moves from one *establishment* to another, the accumulators storing the gross salary deltas are submitted to contributions in the new establishment. The "old" establishment pays the gross salary deltas, while the current establishment processes the contributions on these deltas.

However, when there is a change in *company*, the accumulators storing the gross deltas are not included in the current period calculation for the new company. This is because *company* is used as the key for the accumulators that store the gross deltas, and these deltas are associated with the old company. To force the gross regularization to occur within the new company's contribution calculations, PeopleSoft forwards a "dummy" element from the recalculated period to a "dummy" element in the current period. If an employee changes company, an inactive segment is processed for the employee for the old company (assuming that company is defined as a Payment Key at the pay entity level).

At a technical level, PeopleSoft manages this type of change by:

- Verifying that the retro calculation system element is equal to *Corrective*.

If this condition is met, the "dummy" earning RETRO FICTIF is calculated and returns a value of 1.

Note: If you override the delivered Corrective retro method during implementation, the solution described here is not applied.

- Mapping the element RETRO FICTIF to a second "dummy" earning element, RTRO INACTIF. This second earning receives the value of 1 contained in RETRO FICTIF when there is corrective retro (according to the retro process override definition entered on the Retro Process Overrides page).
- Forwarding the earning RTRO INACTIF (with a value of 1) to the current period.

When this happens, there is no segment in the current period having the same payment keys as the recalculated segment. Because of this, an inactive segment is triggered in the current period for the "old" keys.

Note: If multiple segments are recalculated (for example, in December you recalculate all periods going back to September), the earning RTRO INACTIF will receive the value of 1 for each segment retroactively calculated as corrective (1 for September, 1 for October, 1 for November).

For this solution to work, when you define payee selection on the Calendar component (GP_CALENDAR) prior to processing a payroll, you must include active payees plus payees with pending retroactive changes. Based on this selection, inactive payees are considered in the calendar calculation as long as they have retro forwarded adjustments coming from the dummy element for the inactive segment.

Warning! Global Payroll for France supports the retro-corrective solution described here only if you define company as a payment key at the pay entity level. This restriction is based on legal requirements for calculating, for URSSAF and ASSEDIC, contributions limited to a ceiling on a yearly basis and for a unique company. PeopleSoft does not support the use of payment keys such as *contract number* and *establishment*.

Ceiling Changes

Changes to the ceiling values for URSSAF and ASSEDIC can affect funding base calculations even when there is no change to the gross salary. Global Payroll for France manages ceiling changes in corrective mode by using the old value of the gross to calculate the segment funding base, while applying the new ceiling values. Because of the ceiling changes, the final value of the funding base may be different from the initial value.

Funding Base Exemption Changes

Exemption changes can affect funding base calculations even when there is no change to the gross salary. Global Payroll for France manages these changes in corrective mode by using the old value of the gross to calculate the segment funding base, while applying the new exemptions. Because of the exemption changes, the final value of the funding base may be different from the initial value.

Note: Retroactive changes to funding base exemption percentages can result in the recalculated funding base being different from the initial funding base. This can lead to a situation in which there are multiple rates to declare for the same contribution in the same DUCS declaration. In such cases, the new DUCS norm enables you to declare the old rates for URSSAF and ASSEDIC.

See [Understanding DUCS Reporting](#).

Changes in the Lump Sum Funding Base for Apprentices

The gross salary is not used to determine the funding base for apprenticeship contracts. Instead, the system calculates a lump-sum funding base adjusted to the age of the apprentice and the duration of the contract. There is no annual regularization of contributions for the apprenticeship contribution as the lump-sum base is always under the ceiling. If the conditions used to calculate the lump sum funding base change retroactively, the recalculated lump-sum funding base is used, and this base is submitted to the rate in effect during the recalculated period.

Note: Gross salary changes do not impact funding base calculations for apprentices, because this calculation is independent of the salary.

Contribution Calculations for Finalized Years

Because it is not possible to change contributions after a calendar year has been declared in the DADS report, the URSSAF TRC, and the ASSEDIC BDA, Global Payroll for France does not manage the impacts of retroactive changes to gross salary elements in previous years. Customers must manage these by direct contact with the social organizations. In general, regularization changes for finalized years are declared manually.

Note: Global Payroll for France uses the forwarding method to manage retroactive calculations in past years. You can override this setup and use the corrective method to manage all employees or specific cases. However, doing so could result in contributions for previous years being including in the current DUCS declaration, which is forbidden by the social organizations.

Net Guarantee

To manage the net guarantee calculation when there is corrective retro processing, Global Payroll for France:

- Blocks the recalculation of the net guarantee amount during recalculation.

The net guarantee amount is defined as *Do Not Recalculate* during retro calculations. This means that even if the IJSS amount changes retroactively, the net guarantee amount remains identical to the initial calculation.

- Includes any IJSS deltas in the current period and then performs the net guarantee calculation.

Related Links

[Understanding Net Guarantee Processing](#)

Contribution Eligibility

An employee who is eligible for a specific set of contributions may be declared retroactively eligible for another set of contributions or ineligible for contributions. Conversely, an employee who is ineligible for contributions can be retroactively declared eligible for these contributions. Global Payroll for France has developed rules to manage such retroactive eligibility changes. These are described in the following sections.

Eligibility changes for URSSAF Contributions

<i>Retroactive Change</i>	<i>Description</i>
Change of Scheme	<p>Some URSSAF contribution rates vary based on the <i>régime</i> or scheme of the employee, while others depend on values defined for an establishment. Global Payroll for France manages changes from one scheme to another by recalculating and declaring contributions for the correct scheme. For the recalculated segment, URSSAF contributions are processed using the correct rates, and the gross salary used is the "old" gross salary. However, the gross deltas are processed using the contribution rates in effect in the current period.</p> <hr/> <p>Note: These retroactive changes are declared in the DUCS report as follows: initial contributions are cancelled by declaring a negative funding base on the old scheme, while new contributions are declared in the same way but with a positive funding base.</p> <hr/>

<i>Retroactive Change</i>	<i>Description</i>
Eligible Employee Becomes Retroactively Non-Eligible	<p>This situation can occur, for example, if an employee is retroactively declared an expatriate not subject to URSSAF contributions. In this case, URSSAF contributions are not processed in the recalculated periods, and the initial contributions are cancelled.</p> <hr/> <p>Note: The new DUCS norm enables organizations to declare regularized funding bases. Accordingly, the Global Payroll DUCS report for France reverses the initial declarations and displays negative funding bases for the recalculated periods with their corresponding rates.</p> <hr/>
Employee not Eligible Becomes Retroactively Eligible	<p>Normally, when URSSAF contributions are recalculated, the recalculation of the prior period is based on the value of the "old" URSSAF gross segment accumulator (URS AC BRUT SG), and any gross salary deltas are processed in the current period using the rates currently in effect. However, when an employee becomes retroactively eligible for URSSAF contributions, the original value of this accumulator is equal to 0 (the accumulator has no value because the URSSAF process was not triggered in the original calculation, and the accumulator was not populated).</p> <p>This can lead to a situation in which the entire funding base is submitted to the current rate: if the rate has increased during the year, the company will pay more contributions than it should, and if the rate has decreased during the year, the company will pay less contributions than it should. To avoid this situation, Global Payroll for France has created another accumulator that duplicates the URS AC BRUT SG accumulator. This accumulator (URS AC BRUT BIS SG) is always populated, even if URSSAF contributions are not calculated. If the old value of the "standard" gross accumulator is equal to 0, the process retrieves this second gross accumulator.</p> <hr/> <p>Warning! If you update the value of the standard URSSAF gross segment accumulator, you must also update the value of the second, duplicate accumulator.</p> <hr/>

<i>Retroactive Change</i>	<i>Description</i>
Employee Eligible for Exempt Scheme Becomes Eligible for the Normal Scheme	<p>If an employee who is eligible for an exempt scheme is retroactively assigned to a "normal" scheme, the variables URS VR BRT REG EX and URS VR BA REG EX (storing the exempted gross and the funding base) will not be populated, and the exempted rates will not apply when the prior period is recalculated. The exempt contributions will be cancelled in the recalculation, and will be declared as regularized in the DUCS report with negative funding bases.</p> <hr/> <p>Note: In cases like this, the base is recalculated based on the old value of the accumulator URS AC BRUT SG. Typically, this accumulator is split when an employee is assigned to an exempted scheme so that a portion of the accumulator can be processed using the exempt rates; however, this split does not occur during the recalculation. The recalculated contributions correctly take into account the old gross and use the "normal" rates. The amount not paid in the correct scheme during the initial calculation is declared based on the new DUCS norm rules.</p> <hr/>
Employee Eligible for Normal Scheme Becomes Eligible for Exempt Scheme	<p>If an employee who is eligible for a normal scheme is retroactively assigned to an exempt scheme, the funding base for the specific contracts is calculated retroactively. The old URSSAF gross is retrieved and split between the normal and the exempt rates.</p> <p>In the situation described here, the funding bases calculated for both schemes will be different from the initial calculation:</p> <ul style="list-style-type: none"> • For the normal scheme, the funding base may be equal to 0 if the salary is not over the SMIC. In this case, the contributions initially declared are cancelled in the DUCS declaration. • For the exempted schemes, the funding base was initially equal to 0. In this case, the funding bases are calculated for the exempted scheme in the prior period and are included in the DUCS declaration.

<i>Retroactive Change</i>	<i>Description</i>
Apprenticeship Contract Changes	<p>If an employee defined as an apprentice is retroactively linked to another scheme, the system retrieves the old gross accumulator and uses it to calculate the funding bases (limited to a ceiling or based on the gross). The initial calculation of contributions based on the lump sum funding base and exempted rates are cancelled in the DUCS declaration.</p> <p>If an employee associated with a normal scheme is retroactively defined as an apprentice, the old gross is retrieved but is not used to calculate the new apprenticeship scheme. The initial contribution declaration is cancelled and the new exempted contributions are reported based on the new DUCS norm for declaring regularizations.</p> <hr/> <p>Note: In the case of apprenticeship contracts, Global Payroll for France does not calculate the funding base based on the gross salary; it instead uses a lump-sum funding base that varies depending on the age of the apprentice and the duration of the contract.</p> <hr/>

Eligibility Changes for ASSEDIC Contributions

<i>Retroactive Change</i>	<i>Description</i>
Eligible Employee Becomes Retroactively Non-Eligible	<p>If an employee who was previously eligible becomes non-eligible, the ASSEDIC contributions are not recalculated. The initial contributions are cancelled in the DUCS declaration and the ASSEDIC accumulators are updated.</p>

<i>Retroactive Change</i>	<i>Description</i>
Employee not Eligible Becomes Retroactively Eligible	<p>Normally, when ASSEDIC contributions are recalculated, the recalculation of the prior period is based on the value of the "old" ASSEDIC gross segment accumulator (ASS AC BRUT SG), and any gross salary deltas are processed in the current period using the rates currently in effect. However, when an employee becomes retroactively eligible for ASSEDIC contributions, the original value of this accumulator is equal to 0 (the accumulator has no value because the ASSEDIC process was not triggered in the original calculation, and the accumulator was not populated).</p> <p>This can lead to a situation in which the entire funding base is submitted to the current rate: if the rate has increased during the year, the company will pay more contributions than it should, and if the rate has decreased during the year, the company will pay less contributions than it should. To avoid this situation, Global Payroll for France has created another accumulator that duplicates the ASS AC BRUT SG accumulator. This accumulator (ASS AC BRUT BIS SG) is always populated, even if ASSEDIC contributions are not calculated. If the old value of the "standard" gross accumulator is equal to 0, the process retrieves this second gross accumulator.</p> <hr/> <p><i>Warning!</i> If you update the value of the standard ASSEDIC gross segment accumulator, you must also update the value of the second, duplicate accumulator.</p> <hr/>

Eligibility Changes for Retirement and Contingency Contributions

<i>Retroactive Change</i>	<i>Description</i>
Change of Fund Without Category Change	<p data-bbox="865 279 1461 552">Retirement and contingency contributions are paid to specific funds. Each fund must deliver a "contract number" for the different categories of employees declared. This contract number is used as a key in the accumulators used to calculate the retirement funding bases following the annual regularization rule. So, if an employee changes from a fund to another, the accumulators keys change and the contribution calculation is based on "re-initialized" accumulator values.</p> <p data-bbox="865 583 1461 716">PeopleSoft manages this situation by fully recalculating the retirement and contingency fund contribution. This corrective calculation ensures that the right accumulators are used and that contributions are correctly resolved.</p> <hr data-bbox="865 743 1461 747"/> <p data-bbox="865 758 1461 890">Note: In this situation, the funding base regularizations are added to the current period funding base in the DUCS declaration, as the retirement and contingency fund rates don't change during the year.</p> <hr data-bbox="865 898 1461 903"/> <p data-bbox="865 940 1461 1241">Note: The annual gross accumulators for ARRCO and AGIRC are ARC AC BRUT ABA AN and AGI AC BRUT ABA AN. These accumulators are used to calculating the segment funding bases for ARRCO and AGIRC contributions. These accumulators are defined with four keys: Company, Contract Number, ARC VR CATEGORY or AGI VR CATEGORY (variables storing the employees' category), and ARC VR NUM MEMBRE or AGI VR NUM MEMBRE (variables storing the retirement contract number).</p> <hr data-bbox="865 1249 1461 1253"/>

<i>Retroactive Change</i>	<i>Description</i>
Change in Employee Category (Employee, Art 36, or Manager)	<p>Because the contributions processed for employees depend on their category, new contributions must be calculated in this situation. New accumulator instances must also be created, as the employee categories are used as keys for the retirement contributions accumulators (A4 for managers, A36 for employees viewed as managers by the retirement funds, and EMPL for employees).</p> <p>In the event of a category change, the system fully recalculates the contributions related to the new category, and updates the correct accumulators with their correct keys.</p> <hr/> <p>Note: For the DUCS report, the old contributions are cancelled and the recalculated contributions are declared in the current period. The old and the recalculated contributions are considered in the current DUCS declaration and their funding bases are regularized (as in general, there is no change in the rates during the year).</p> <p>Some contributions such as the lump sum APEC (<i>APEC forfaitaire</i>) are calculated and declared only in March for Art 36 and Manager categories. When this contribution is calculated or cancelled retroactively, it must be declared in the current DUCS report.</p> <hr/> <p>Note: In the event of retroactivity going back to prior years, the gross deltas should be forwarded to the current period and included in the retirement contributions for this period. In other words, the deltas should be processed for the retirement category and the retirement fund number of the current period.</p> <hr/>
Change In Contract Number	<p>Contract number is also used as a key in the accumulators used for the retirement contribution calculation. When the contract number changes retroactively, all contributions are fully recalculated to generate new values for the funding bases, and new accumulators are created (based on the new keys).</p> <hr/> <p>Note: In this situation, the contribution regularizations are fully declared in the DUCS report.</p> <hr/>

<i>Retroactive Change</i>	<i>Description</i>
Apprenticeship Contract Changes	<p>If an employee becomes an apprentice retroactively, no retirement or contingency contributions are calculated in the recalculated period, because a conditional formula attached to the Retirement and Contingency sections prevents them from being triggered for apprentices. Instead, the DUCS report deducts the contributions initially declared.</p> <p>If an apprentice becomes a non-apprentice retroactively, the retirement contributions are fully calculated in the retro period and are declared in the DUCS report.</p>
Employee not Eligible for Contributions Becomes Eligible	<p>If an employee is declared retroactively eligible, the contributions are calculated in the prior periods using the recalculated gross rather than the "old" value of the funding base. Contributions calculated in this way are added in full to the current DUCS declaration (as the rates do not change during the year).</p>

Eligibility Changes for Levies

<i>Retroactive Change</i>	<i>Description</i>
Employee Eligible for CSG and CRDS Becomes Retroactively Non-Eligible	<p>In this case, CSG and CRDS contributions are not processed in the recalculated periods, and the initial contributions are cancelled.</p> <hr/> <p>Note: The new DUCS norm enables organizations to declare regularized funding bases. Accordingly, the Global Payroll DUCS report for France reverses the initial declarations and displays negative funding bases for the recalculated periods with their corresponding rates.</p> <hr/>

<i>Retroactive Change</i>	<i>Description</i>
Employee not Eligible for CSG and CRDS Becomes Retroactively Eligible	<p>To manage cases in which an employee who is ineligible for CSG and CRDS contribution becomes retroactively eligible, Global Payroll for France applies the same solution developed for URSSAF and ASSEDIC. This solution consists in retrieving the value of a second accumulator—TAX AC CSG BIS SG—that duplicates the standard TAX AC ASS CSG SG accumulator. This accumulator (TAX AC CSG BIS SG) is always populated, even if tax contributions are not processed. If the old value of the "standard" gross accumulator is equal to 0, the process retrieves the second gross accumulator.</p> <p>See Contribution Eligibility.</p> <p>If an employee who is ineligible for the transportation levy becomes retroactively eligible, the system recalculates the levy based on the initial social security funding base. If the rate changes between the recalculated period and the current period, the new DUCS norm allows a regularized declaration.</p>
Changes in Eligibility for the Contingency Levy	Retroactive changes in eligibility for the contingency levy are processed using the <i>full</i> recalculation method.
Changes in Eligibility for the Training Levy	Retroactive changes in eligibility for the training levy are processed using the <i>full</i> recalculation method.
Changes in Eligibility for the Construction Levy	Retroactive changes in eligibility for the construction levy are processed using the <i>full</i> recalculation method.
Changes in Eligibility for the Tax on Salary Levy	Retroactive changes in eligibility for the tax on salary levy are processed using the <i>full</i> recalculation method.
Changes in Eligibility for the Work Council Levy	Retroactive changes in eligibility for the work council levy are processed using the <i>full</i> recalculation method.

See [Managing Gross Salary Changes in the Current Year](#).

Hiring and Departure

Global Payroll for France has developed solutions to manage retroactive hiring and departures, their impact on URSSAF, ASSEDIC, and other social contributions.

<i>Retroactive Change</i>	<i>Description</i>
Payee Hired Retroactively	<p>The solution used to manage this situation depends on the social organization.</p> <ul style="list-style-type: none"> For URSSAF, ASSEDIC, and CSG, Global Payroll for France employs the <i>partial</i> recalculation process. Because the old salary value retrieved is equal to 0 when an employee is hired retroactively (no prior version exists), the entire salary is treated as a gross delta and is submitted to contribution in the current period. For other contributions (retirement, contingency, levies), the gross salary is fully recalculated.
Retroactive Change in Hire Date	<p>Retroactive changes to an employee's hire date produces a <i>retro mismatch</i>. In this situation, the system <i>fully recalculates</i> the contributions.</p> <p>If, in addition to a hire change, a change of salary occurs, the system may not apply the current rates to the gross deltas as required by URSSAF and ASSEDIC (because it performs a full recalculation and replacement of the elements in the prior period). For this reason, you should evaluate the impacts retroactive hiring on your calculations.</p> <hr/> <p>Note: Other retro mismatch situations that you need to manage are: (1) change of company, (2) change of establishment, (3) and all changes to segment dates (for example, departures). In these situations, you need to determine whether the correction could negatively impact the contribution calculations and declarations.</p> <hr/>
Retroactive Departure	<p>In most cases, retroactive departures imply a segment mismatch and a <i>full recalculation</i> of all contributions in the current year. The termination allowances paid retroactively are then submitted to the "old" rates.</p> <hr/> <p>Note: This is a limitation of the delivered retroactive processing logic, as URSSAF and ASSEDIC require the use of rates in effect in the current period.</p> <hr/> <p>Note: There are some situations in which a retroactive departure does not imply a segment mismatch. This occurs, for example when an employee is retroactively terminated on the last day of the segment (in which case there is no change in the segment dates between the initial calculation and the recalculation). As there is no retro mismatch in this situation, a <i>partial recalculation</i> occurs and the gross deltas (if any) are processed in an inactive segment in the current period.</p> <hr/>
Retroactive Change in the Departure Date	<p>This situation produces a retro mismatch and a full recalculation of all contributions.</p>
Retroactive Hire and Departure in the Same Period	<p>In this situation, because no prior version exists, the system <i>partially recalculates</i> the URSSAF, ASSEDIC, and CSG/CRDS contributions. The gross deltas are submitted to contributions in the current period using an inactive segment.</p>

Isolated Amounts

Isolated amounts are amounts paid at or after termination that are submitted to specific AGIRC retirement contributions.

Global Payroll for France delivers specific rules for managing isolated amounts processed retroactively. These rules are triggered when:

- There is a retroactive termination.
- There is a retroactive payment of an amount after a termination.
- There is a retroactive termination or payment following a termination for an employee who has changed categories between the different recalculated segments.

Three elements have been created—using the retro process override setup—to retrieve any deltas created by the retroactive calculations:

- RETRO SI: This earning element retrieves the gross salary deltas of the accumulator GEN AC BRUT SG.
- RETRO SI AGI: This earning element retrieves the gross deltas of the accumulator AGI AC BRUT SG (AGIRC gross base segment accumulator).
- RETRO DELT SI: This earning element retrieves the deltas of the accumulator AGI AC SI MNT SG (isolated amounts segment accumulator).

Note: These elements are used in the formula RTO FM RECUP SI only when the segment processed is INACTIVE and the current calculation is not retroactive.

When processing isolated amounts at or after termination, the system:

1. Calculates the difference between RETRO SI and RETRO DLT SI.
2. Adds the results of this calculation to any isolated amounts in the current period.

The system stores the difference between RETRO SI and RETRO DLT SI in the variable RTO VR SI, and adds the value of this variable to the current isolated amounts accumulator AGI AC SI MNT SG.

Note: This calculation treats the gross salary deltas as isolated amounts, but processes only deltas that have not already been considered as isolated amounts and submitted to contributions.

When an employee changes category during the year (for example, from employee to manager), there is a possibility that this calculation will treat all gross deltas as isolated amounts, when only the gross deltas for periods when the payee was a manager should be considered. To avoid this, the system calculates the difference between RETRO SI and RETRO SI AGI. If there is a difference between these elements, the system knows that the employee changed category in the recalculated period. It stores this difference in the variable RTO VR SI AGI, and uses it to limit the isolated amounts delta (so that deltas for the periods when the employee was not eligible for AGIRC contributions are not included in the isolated amounts).

Inactive Segments

To process retroactivity in certain situations, Global Payroll for France triggers inactive segments in the current period. For example, this occurs in situations in which an employee changes company between the different segments recalculated.

Inactive segments have the following characteristics:

- No ceilings are calculated in inactive segments.

Because the employee is not considered "present" in inactive segments, there is no ceiling calculation. The progressive regularization of contributions occurs normally for the segment with a gross increase, but there is no change in the annual ceiling amount.

- The different elements (variables, accumulators) storing the worked/paid days or hours are set to 0 in the inactive segment.
- The inactive segment is not considered in the calculation of seniority days (stored in the accumulator GEN AC JOUR ANC).
- No SMIC control occurs in inactive segments, as no paid hours can be calculated for these segments.
- The fiscal and social reinstatement calculation is triggered for inactive segments.
- Inactive segments are declared in the DADS-U. The begin and end dates of these segments are set to 1 January (01/01) as required by the norm.

Loans and Garnishments

By law, loans and garnishments cannot be recalculated during retroactive processing.

Global Payroll defines loan elements with the Retro Recalculation option set to *Do Not Recalculate*. However, because loans are triggered by positive input, and positive input overrides the Retro Recalculation option, you should be careful not to enter new loan data in a closed period.

By contrast, Global Payroll defines garnishment elements with the Retro Recalculation option set to *Always Recalculate*. This can lead to situations in which garnishments are reprocessed in a prior period. For example, if there is retroactivity and a retro mismatch occurs, the system tries to recalculate all elements, including garnishments. To prevent this from happening, Global Payroll for France uses the array RTO AR RESULT PAIE to retrieve the original value of the garnishments in the payroll result tables whenever there is retroactive processing.

Note: The earnings/deductions for which the array RTO AR RESULT PAIE retrieves previously calculated values are those with a Category of *RTO* (Retro Element Retrieved in Array). If you want to use this array to prevent the recalculation of an earning/deduction that you have defined yourself, you should assign the earning/deduction to the same category.

See "Retroactivity Calculations (*PeopleSoft HCM 9.2: Global Payroll*)".

Reporting and Retroactivity

This section discusses:

- Declaration methods.
- Managing retroactive changes to rates in the DUCS declaration.
- Viewing and modifying the declaration method used for reporting.

Declaration Methods

The retroactive process impacts not only the calculation of social contributions for URSSAF, ASSEDIC, and AGIRC/ARRCO, but also the declaration of these contributions. PeopleSoft follows the DUCS norm for declaring contributions. The latest version of these norms supports corrective declarations, and PeopleSoft has taken advantage of the new standards to develop solutions for reporting retroactive changes.

There are two kinds of declarations for reporting retroactive changes to social contributions:

- Additive declarations.

In an additive declaration, the funding bases from recalculated periods are added to the funding base in the current period.

Note: Funding bases can be added together only when there is no difference in contribution rates between the recalculated periods and the current period, as the DUCS norm allows only one rate to be declared per period.

- Rectified declarations.

In a rectified declaration, separate "rectification" reports are issued for each period recalculated. In other words, bases are not combined and different rates can be attached to the base deltas as well as the current period base.

Note: Rectified declarations can be generated regardless of whether the rates used in the current and recalculated periods are the same or different.

<i>Reporting Organization</i>	<i>Declaration Code</i>	<i>Declaration Method</i>
URSSAF	901	Rectificative
ASSEDIC	902	Additive
AGIRC/ARRCO/OTHER	903	Additive

- URSSAF.

For the URSSAF declaration, the DUCS program differentiates contributions calculated in different periods. For example, if there is a retroactive base salary change in December going back to the beginning of the year in January, the DUCS declaration will consist of 11 rectified declarations (from January to November) and one normal declaration (for December).

If there is a difference in the rates between the current and prior periods, each retroactive change in a funding base must be declared separately and identified by the period regularized, just as is the case when only the funding base changes.

- ASSEDIC and AGIRC/ARRCO.

For ASSEDIC and AGIRC/ARRCO, the DUCS program combines contributions calculated in different periods as long as the rates are the same in the prior and current periods (the recalculated funding bases are added to the current period funding base).

If there is a difference in rates between current and prior periods when contributions are recalculated, the DUCS report will display the same contribution multiple times with the different rates and corresponding bases.

Note: Conflicting rates are retrieved only if for a specific DUCS type, the setup indicates that additive declarations are done.

Managing Retroactive Changes to Rates in the DUCS Declaration

When a company reprocesses prior periods to correct contribution rates that are above or below the official rates, the resulting calculations are recorded in the DUCS declaration as follows:

- The initial calculations done using incorrect rates are reversed in the current declaration.

Note: From the perspective of the social organization, it will appear that these reversals use an invalid rate.

- The recalculations done with the correct rates are declared for the full funding base.

When the social organization receives the "corrected" declaration, it may issue a rectification to force either immediate payment of missing contributions (if the original rate used was below the official rate), or a reduction in future payments (if the original rate used was above the official rate). This is because the "corrected" DUCS declaration displays invalid rates for the contributions that have been reversed.

To avoid this, Global Payroll for France provides an exception page (DUCS Override Rates FRA page) on which you can override the rates used in the actual payroll calculations with the rates you want to include in the current DUCS declaration. For example, if you use an incorrect rate to calculate the Work Accident contribution, you can use this page to replace the incorrect rate with a rate acceptable to the social organization.

Note: Overriding rates can create discrepancies between the contributions calculated in the system and the contributions declared in the DUCS report. These discrepancies can affect financial accounting, as the amounts recorded in the payroll system will differ from the amounts actually paid. You can track and manage these discrepancies using the DUCS Rate Override Audit report (GPFRDUCO). This report records the difference between the calculated and the declared amounts resulting from a rate override.

See [DUCS Override Rates FRA page](#).

Viewing and Modifying the Declaration Method Used for Reporting

You can view the declaration method defined by the official bodies for each organization on the DUCS Types page. If the rules for making retroactive declarations change, you can use this page to modify the method.

Note: The delivered declaration methods reflect the positions of the respective social organizations during the development of Global Payroll for France. You should consult the latest DUCS norms to verify that these declaration methods are still current. In particular, you may need to change the ASSEDIC setup to RECTIFICATIVE if the ASSEDIC chooses this declaration method.

See [DUCS Types FRA Page](#).

Delivered Retro Triggers

The different standard situations for which Global Payroll for France delivers retro triggers are:

- Changes to compensation data.
- Changes to the JOB record.

The trigger for job date changes is defined for the following fields: Action, Company, Establishment, Pay Group, Contract Number, Job Code, FTE, Paid FTE, Collective Agreement, and Employee Status.

Note: Most of the changes in the JOB record trigger retro, segmentation, and iterative processing.

- Changes to contract data.

This trigger is defined at the field level for the following fields: Contract Type, Contract Begin Date, Contract End Date, and Contract Number.

- Change to contract data specifically for France.

This trigger is defined for the following fields: Multiple Employer Rate, Gross Reduction Percentage, Category Status, and Social Security Code.

- Changes to absence events.

This trigger is defined at the record level.

- Changes to positive input.

This trigger is defined at the record level.

- Changes to Element Assignment by Payee and Payee Assignment by Element data.

This trigger is defined at the record level.

- Changes to supporting element overrides.

This trigger is defined at the record level.

- Changes to the employee schedules.

This trigger is defined at the record level.

Note: These triggers are provided as models of trigger definitions. You may need to modify these triggers and define additional triggers to manage situations that are unique to your organization.

Related Links

"Setting Up Trigger Definitions (*PeopleSoft HCM 9.2: Global Payroll*)"

Collective Changes to Contribution Calculation Elements

Collective changes to contribution calculation elements can be processed using mass triggers. The setup of these triggers is documented in *PeopleSoft Global Payroll*.

Related Links

"Setting Up Mass Triggers (*PeopleSoft HCM 9.2: Global Payroll*)"

Setting Up Termination Processing

Understanding The Termination Process

The termination process in Global Payroll for France identifies payees who have been terminated in PeopleSoft HR, processes these payees for final payment in an off-cycle run, and extracts Global Payroll and HR data from the system to generate ASSEDIC termination reports.

This section discusses:

- Termination process setup steps.
- Segmentation and retro triggers for termination processing.
- Elements used to identify payees for data extraction.
- ASSEDIC report generation for transfers.

Note: PeopleSoft uses the off-cycle advance payment functionality in the core Global Payroll application as the basis for the France-specific termination process. The system calculates earnings and deductions for terminated employees as advance payments outside of the normal payroll cycle. When employees receive their final payment, the system automatically blocks processing of the same payees in the normal, on-cycle calendar.

Termination Process Setup Steps

To set up terminations, configure the Global Payroll elements that control these termination process steps:

- Selection of terminated payees for off-cycle payroll processing.

The French termination process uses retro and segmentation triggers linked to the Action field in the JOB record to identify terminated payees; when a termination action is entered for a payee, these triggers generate a line of data that identifies the payee as terminated. Global Payroll for France can then select the payee for off-cycle processing, calculate the payee's earnings and deductions, and issue a final payment.

As part of the termination setup, you must configure the triggers that are used to identify payees as terminated and specify the actions in the JOB record that qualify as terminations in your organization. In addition, you must list these actions on the Extraction Setup page so that the system selects only payees with qualifying actions values when you create an off-cycle group for processing terminated payees.

Note: Global Payroll for France delivers a trigger (DEPART) that you can use to identify terminated payees; you can also define your own triggers.

See [Segmentation and Retro Triggers for Termination Processing](#), [Extraction Setup Page](#).

Note: We discuss the steps you must follow to process terminated payees with qualifying action values in the topic on processing terminations.

See [Understanding Termination Processing](#).

- Extraction of data for ASSEDIC reports.

Global Payroll for France uses a number of elements including arrays, variables, and formulas to identify the payees for whom HR and payroll data must be extracted to produce the ASSEDIC termination reports. Although Global Payroll for France delivers all of the elements required to select payees for data extraction, you must review and configure these element to ensure that they satisfy your business requirements. This includes identifying the specific termination actions in the JOB record that will trigger data extraction, specifying how different termination action and reason combinations are recorded in the ASSEDIC certificates, and defining other parameters of the extraction process.

See [Elements Used to Identify Payees For Data Extraction](#).

Important! To set up termination processing, you must configure *both* sets of elements described here—those that are used to select terminated employees for off-cycle payroll processing, and those that are used to select payees for data extraction.

Termination Setup

To set up termination processing for France:

1. Define retro and segmentation triggers to identify terminated payees using the Trigger Definition (GP_TRGR_SETUP) component in the Global Payroll core application. The system uses these triggers to determine:
 - How to process payroll elements when a termination is entered in the Action field in the JOB record.
 - Which payees to select for off-cycle payroll processing (the payees must have termination actions that match those specified in the retro and segmentation trigger definitions).

Note: PeopleSoft provides the sample trigger DEPART, which you can configure to suit your needs or use as a model for defining your own retro and segmentation triggers.

See [Segmentation and Retro Triggers for Termination Processing](#).

2. Identify the retro and segmentation triggers defined in Step 1 on the Extraction Setup page in Global Payroll for France.

The system selects (extracts) payees for off-cycle termination processing who have retro or segmentation triggers matching those identified on the Extraction Setup page.

See [Extraction Setup Page](#).

3. Review and configure the elements used to identify payees for whom data should be extracted from the database to generate ASSEDIC termination reports.

See [Elements Used to Identify Payees For Data Extraction](#).

4. Map actions/reasons that you have set up to trigger termination processing to the termination reasons that will appear in a payee's termination reports.

Do this on the Assedic Reasons page.

For example, if you terminate an employee with an action of *Layoff* and a reason of *RED* (redundancy), you can define the corresponding ASSEDIC reason as *Redundancy*. This reason will then appear on the payee's ASSEDIC certificate.

See [Assedic Reasons Page](#).

5. Map a variable element to the ASSEDIC certificate flag to trigger ASSEDIC data extraction and report generation for terminated payees.

Do this on the Element Mapping Codes FRA page.

PeopleSoft delivers the variable element GEN VR TEST DEPART for this purpose. When you terminate a payee and run the payroll process, Global Payroll for France sets the value of GEN VR TEST DEPART to GP TRUE (1). Later, when you run the data extraction process, the system retrieves ASSEDIC certificate data and generates the ASSEDIC reports only for employees having this variable set to 1 in their payroll results.

See [Elements Mapping Codes FRA Page](#).

Note: To run the data extraction process for the ASSEDIC reports, access the Extract Termination Data FRA page.

See [Extracting Data for Terminated Employees](#).

Segmentation and Retro Triggers for Termination Processing

PeopleSoft uses the trigger DEPART to identify payees with terminations in the JOB record. This trigger is associated with the JOB.Action field and initiates both segmentation and retroactive processing when the action value is *TER* (termination), *RET* (retirement), *XFR* (transfer), *TWP* (termination with pay), or *TWB* (termination with benefits). The termination process in Global Payroll for France detects when the DEPART trigger becomes active for payees in response to one of these termination actions, and can then include any payee with a retro or segmentation trigger in the next off-cycle termination run. When you set up Global Payroll for France, review this list of action values and add, remove, or modify the actions that trigger a termination on the Trigger Definitions and Trigger Definitions-Field Values pages in the Global Payroll core application to reflect the needs of your organization. When you create new triggers

for termination processing, you should eliminate the delivered PeopleSoft triggers on the Extraction Setup page in Global Payroll for France, and add your own triggers, as appropriate.

Image: Trigger Definitions-Field Values page showing JOB actions that trigger termination processing for France

Trigger Definitions-Field Values page showing JOB actions that trigger termination processing for France

Trigger Definitions

Field Values

Country: FRA France
Record (Table) Name: JOB
Field Name: ACTION

Field Values					
Sequence	Character Value	Trigger Event ID	Offset Days		
13	TER	DEPART	-1	+	-
14	RET	DEPART	-1	+	-
15	XFR	DEPART	-1	+	-
16	TWP	DEPART	-1	+	-
17	TWB	DEPART	-1	+	-

No Match on Field Value Option
☒ Do Not Trigger
☐ Trigger
Trigger Event ID:

Important! Global Payroll for France defines the action values that trigger retroactive processing with an offset of -1. If you add additional action values to this list, you should define them with an offset of -1 to ensure that retroactive terminations are processed correctly.

See [Understanding Trigger Setup for France](#).

It is up to you to define triggers that reflect the current business practices in your organization. PeopleSoft provides the trigger DEPART as a model for the kinds of triggers you may need to create.

Elements Used to Identify Payees For Data Extraction

<i>Element Type</i>	<i>Element Name</i>	<i>Use</i>
Generation Control	GEN GC TEST DEPART	<p>As delivered, this element tests whether one of the following termination actions has been entered for a payee in the JOB record: Retirement (RET), Retirement with Pay (RWP), Terminate Detail Assignment (TDL), Termination (TER), Terminated with Benefits (TWB), Terminated with Pay (TWP). You can modify, delete, or add the actions that you want in this generation control element.</p> <hr/> <p>Note: This generation control element is associated with the earning DEPART (below).</p> <hr/> <p>Note: Normally, the actions that trigger processing in the generation control element GEN GC TEST DEPART should match the JOB actions that you have set up to generate termination triggers on the Trigger Definitions component in the Global Payroll core application as well as the actions listed on the Assedic Reasons page.</p> <hr/>
Earning	DEPART	<p>If one of the actions included in the generation control element GEN GC TEST DEPART (above) appears in the segment period plus one day, the earning element DEPART is triggered. This earning is not used to retrieve a monetary amount to add to the salary, but to trigger processing of the formula GEN FM ACT DEPART (below).</p>
Formula	GEN FM ACT DEPART	<p>If the earning element DEPART is triggered, the GEN FM ACT DEPART formula is resolved. This formula calls an array—GEN AR DEPART—that retrieves the termination action and reason and populates the GEN VR ACTION and GEN VR MOTIF variables (see below). This formula also sets the GEN VR TEST DEPART variable to GP TRUE (see below).</p>

Element Type	Element Name	Use
Variable	GEN VR TEST DEPART	<p>If a payee leaves the company, the GEN VR TEST DEPART variable resolves to GP TRUE (or 1). Otherwise, the value of the variable is equal to GP FALSE (or 0).</p> <p>The system extracts ASSEDIC certificate data from HR and Global Payroll tables and generates the ASSEDIC reports only for employees having this variable set to 1 in the payroll result tables.</p> <p>You can define a variable other than GEN VR TEST DEPART to trigger data extraction for the ASSEDIC certificate. If you do this, map the new variable to the ASSEDIC certificate flag on the Element Mapping Codes FRA page, and make sure that you use the new element in place of GEN VR TEST DEPART wherever it appears in the system, including in the formula GEN FM ACT DEPART (see above).</p>
Variable	GEN VR ACTION	<p>This variable stores the termination action for a payee.</p> <p>When you set up termination processing, you must map the action-reason combinations stored in this variable and the variable GEN VR MOTIF (see below) to the termination reasons that you want to appear in the ASSEDIC termination certificates. Use the Assedic Reasons page to perform this mapping.</p> <p>See Assedic Reasons Page.</p>
Variable	GEN VR MOTIF	<p>This variable stores the termination reason for a payee.</p> <p>When you set up termination processing, you must map the action-reason combinations stored in this variable and the variable GEN VR ACTION (see above) to the termination reasons that you want to appear in the ASSEDIC termination certificates. Use the Assedic Reasons page to perform this mapping.</p> <p>See Assedic Reasons Page.</p>

ASSEDIC Report Generation for Transfers

In addition to generating ASSEDIC reports for terminated employees, you may need to generate ASSEDIC reports for transfers from one company to another. You can do this—without including the transferred employees in the off-cycle payroll process for terminated employees—by using the following delivered elements:

Element Type	Element Name	Use
Generation Control	GEN GC TEST TRNSFR	<p>This element tests whether a transfer action/reason has been entered for a payee in the JOB record. You can modify, delete, or add the actions that you want in this generation control element.</p> <hr/> <p>Note: This generation control element is associated with the earning TRANSFER (below). This element is identical in function to the GEN GC TEST DEPART generation control element described in the table in the preceding section.</p> <hr/>
Earning	TRANSFER	<p>If one of the action/reason combinations included in the generation control element GEN GC TEST TRNSFR (above) appears in the segment period plus one day, the earning element TRANSFER is triggered. This earning is not used to retrieve a monetary amount to add to the salary, but to trigger processing of a formula that sets the value of the GEN VR TEST TRNSFR variable to GP TRUE (see below).</p> <hr/> <p>Note: This element is identical in function to the DEPART element described in the table in the preceding section.</p> <hr/>
Variable	GEN VR TEST TRNSFR	<p>When you transfer a payee and run the payroll process, Global Payroll for France sets the value of GEN VR TEST DEPART to GP TRUE (1). Later, when you run the data extraction process for the ASSEDIC reports, the system retrieves ASSEDIC certificate data and generates the ASSEDIC reports only for employees having this variable set to 1 in their payroll results.</p>

<i>Element Type</i>	<i>Element Name</i>	<i>Use</i>
Variable (continue)	GEN VR TEST TRNSFR (continue)	<p>To use this variable to trigger data extraction for transferred employees, you must map it to the ASSEDIC certificate flag on the Element Mapping Codes FRA page described elsewhere in this topic. If you want, you can define a variable other than GEN VR TEST TRNSFR to trigger data extraction for the ASSEDIC certificate. If you do this, map the new variable to the ASSEDIC certificate flag on the Element Mapping Codes FRA page, and make sure that you use the new element in place of GEN VR TEST TRNSFR wherever it appears in the system.</p> <hr/> <p>Note: The GEN VR TEST TRNSFR variable is identical in function to GEN VR TEST DEPART variable described in the table in the preceding section. To run the data extraction process for the ASSEDIC certificate, use the Extract Termination Data FRA page.</p> <hr/> <p>See Extracting Data for Terminated Employees.</p>

Setting Up Terminations

To set up terminations, use the Terminations FRA (GPFR_TERM) and Element Mapping Codes FRA (GPFR_ILLNESS_SETUP) components.

This section discusses how to:

- Identify termination triggers.
- Set up the Assedic reasons.
- Map variable elements to the Assedic Certificate Flag GEN VR TEST DEPART.

Pages Used to Set Up Terminations

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Extraction Setup	GPFR_TERM_TRG	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Terminations, Terminations FRA, Extraction Setup	List retro and segmentation triggers you have created for the termination process. The system identifies payees with the specific triggers listed on this page and selects them for termination processing.
Assedic Reasons	GPFR_TERM	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Terminations, Terminations FRA, Assedic Reasons	Map actions/reasons that you set up to trigger termination processing to the termination reasons that will appear in a payee's ASSEDIC certificate.
Element Mapping Codes FRA	GPFR_ILLNESS_SETUP	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Reports, Element Mapping Codes FRA, Element Mapping Codes FRA	Define a variable element that the system will use to identify payees for whom Global Payroll and HR data should be extracted to generate the ASSEDIC certificates. The system extracts payroll and HR data only for employees having this variable set to 1 in the result tables.

Extraction Setup Page

Use the Extraction Setup page (GPFR_TERM_TRG) to list retro and segmentation triggers you have created for the termination process.

The system identifies payees with the specific triggers listed on this page and selects them for termination processing.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Terminations, Terminations FRA, Extraction Setup



Image: Extraction Setup page











This example illustrates the fields and controls on the Extraction Setup page. You can find definitions for the fields and controls later on this page.

Extraction Setup

Assedic Reasons

Triggers for Termination Selection

Customize | Find | View All |   First 1-2 of 2 Last

	*Country	*Trigger Type	*Trigger Event ID	Description		
1	FRA 	Retro 	DEPART 	Retro Termination		
2	FRA 	Segmentation 	DEPART 	Termination Segmentation		

Identify the retro and segmentation triggers you have created to initiate termination processing.

The system identifies payees with the specific triggers you specify on this page and extracts them for termination processing.

Note: You must ensure that any actions that generate a retro trigger also generate a segmentation trigger.

Assedic Reasons Page

Use the Assedic Reasons page (GPFR_TERM) to map actions/reasons that you set up to trigger termination processing to the termination reasons that will appear in a payee's ASSEDIC certificate.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Terminations, Terminations FRA, Assedic Reasons

Image: Assedic Reasons page

This example illustrates the fields and controls on the Assedic Reasons page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'Assedic Reasons' page with a table titled 'Actions and Reasons'. The table has three main columns: '*Action', '*Reason Code', and '*Reason of Breach of Contract'. Each row represents a specific termination action and its corresponding reason code and breach of contract reason. The table includes search icons for the reason codes and plus/minus buttons for the breach of contract reasons.

	*Action	*Reason Code	*Reason of Breach of Contract		
1	Layoff	RED	Redundancy	+	-
2	Retirement	RMT	Retirement	+	-
3	Termination	ATC	Agreement Breach of App or CDD	+	-
4	Termination	CDE	Definitive Closing of Estab	+	-
5	Termination	EAB	Employer's anticipated Breach	+	-
6	Termination	EAC	End of Apprenticeship Contract	+	-
7	Termination	EFT	End of Fixed-Term Contract	+	-
8	Termination	EPP	Employer's End Probation Time	+	-
9	Termination	LTC	Contract Judicial termination	+	-
10	Termination	PAB	Payee's Anticipated Breach	+	-

Actions and Reasons

Use the fields in this group box to map the action-reason combinations that you have set up to trigger termination processing to the termination reasons that will appear in a payee's ASSEDIC certificate. List the actions and reasons that trigger termination processing in the columns under Action and Reason Code. List the corresponding ASSEDIC reasons in the fields under Reason of Breach of Contract.

Action and Reason Code

Select an action and a reason code as defined in the Action Reason Table.

Compare the list of actions and reason codes on this page to those that you have set up to generate termination triggers in the Trigger Definitions (GP_TRGR_SETUP) component to make sure that they are the same. All actions and reasons that generate termination triggers should be listed here.

Note: It is important that you review all actions/reason codes you define for the termination process and map them to the corresponding ASSEDIC certificate termination reasons.

Reason for Breach of Contract

Select the reason for breach of contract that will appear in the ASSEDIC certificate when a payee is terminated using

the action and reason shown in the corresponding Action and Reason Code fields.

Related Links

"Creating Group Lists (*PeopleSoft HCM 9.2: Global Payroll*)"

Elements Mapping Codes FRA Page

Use the Element Mapping Codes FRA page (GPFR_ILLNESS_SETUP) to define a variable element that the system will use to identify payees for whom Global Payroll and HR data should be extracted to generate the ASSEDIC certificates.

The system extracts payroll and HR data only for employees having this variable set to 1 in the result tables.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Reports, Element Mapping Codes FRA, Element Mapping Codes FRA

Image: Element Mapping Codes FRA page

This example illustrates the fields and controls on the Element Mapping Codes FRA page. You can find definitions for the fields and controls later on this page.

Element Mapping Codes FRA

Description: 55 Assedic Certificate Flag

*Element Type: AA Assedic Certificate

Elements		Customize Find View All First 1-2 of 2 Last
*Entry Type	Element Name	
1 Variable	GEN VR TEST DEPART	+ -
2 Variable	GEN VR TEST TRNSFR	+ -

Use this page to select a variable that the system will use to identify payee data that needs to be extracted from the database to generate the termination reports. The system extracts termination report data from HR and Global Payroll tables only for employees having this variable set to 1 in the payroll result tables.

Note: Global Payroll for France delivers the variable GEN VR TEST DEPART for this purpose. If you want, you can define a different variable for your termination setup.

Note: To run the data extraction process for the ASSEDIC certificate, use the Extract Termination Data FRA page.

See [Extracting Data for Terminated Employees](#).

Chapter 19

Administering Garnishments

Understanding Garnishments

This section discusses:

- Garnishment types and priorities.
- Attachable and unattachable earnings.
- Garnishments and retroactive processing.
- Prerequisite.

Garnishment Types and Priorities

When a payee owes money to a third-party for alimony, tax debts, or other obligations, the employer may be required to deduct part of what is owed before the payee receives payment. This deduction, known as a garnishment, is taken every month, according to national guidelines. The size of the deduction depends on the payee's earnings and the number of dependents.

There are two types of garnishments: alimony and other debts. Alimony deductions take priority over other debts when a payee's earnings are not sufficient to cover multiple garnishments.

Other debts fall into the following three categories, which are listed in the order of processing priority:

1. Tax debts.
2. Penal sentences.
3. Ordinary debts.

In cases where there is more than one garnishment for the same type of debt (for example, three deductions for alimony), the system prioritizes deductions based on the order in which you entered them, rather than deducting a prorated amount for each debt.

You can define up to three deductions for each garnishment type (alimony, tax debt, penal sentence, and ordinary debt) in the same pay run.

Attachable and Unattachable Earnings

A payee's earnings can be split into attachable and unattachable amounts.

The attachable amount of a payee's income is the part that may be garnished:

- Obligatory attachable amount.

The obligatory attachable amount includes severance allowance, retirement pay over the taxable limit of 3049 euros, and profit-sharing allowances. These amounts are completely attachable and do not follow the usual garnishment calculation rules.

- Obligatory unattachable amount.

The obligatory unattachable amount consists of reimbursements of professional expenses (not including creditors), family allowances paid by the employer (not including creditors), and the RMI (legal minimum subsistence wage), which the government sets annually.

If there is not enough money to pay alimony from the attachable portion of the salary, it may be taken from the unattachable amount, provided the payee's salary doesn't fall below the RMI. Only alimony payments may be taken from this portion of the salary.

- Attachable amount.

Always place a garnishment against the attachable amount of a payee's earnings. The system uses a bracket element to calculate the attachable amount.

Garnishments and Retroactive Processing

By law, garnishments cannot be recalculated during retroactive processing.

To prevent recalculation of the delivered garnishment elements, Global Payroll for France uses the array RTO AR RESULT PAIE to retrieve the original value of the garnishments in the payroll result tables whenever there is retroactive processing.

Related Links

[Loans and Garnishments](#)

Prerequisite

The fraction of a payee's salary that is attachable varies according to the salary limits set by the government.

Before you enter garnishments, you should review and update the salary limits used in the garnishment calculations on the Garnishment Bracket page.

To access this page, select Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Garnishments/Court Orders, Bracket FRA.

Note: To see the names of the variables that store the values in the garnishment bracket, access the Rates and Elements page (Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Addl Rates, Ceilings, Values, Rates, Elements, Limits FRA) using the component name GPFR_GAR_RATES.

Note: PeopleSoft delivers and maintains the salary limit values in the garnishment bracket; however, you can update these limits following legislative changes if you want to record the new values prior to receiving updates from PeopleSoft.

Related Links

[Reviewing Garnishment Brackets](#)

Entering Garnishments

Use the Assign Garnishments FRA page to create a new garnishment. Enter the garnishment amount, the start date and end date, the type of garnishment, and other instructions.

When you save the garnishment data, the system does two things:

- Assigns a deduction to the payee.

View the assignment on the Element Assignment by Payee (GP_ED_PYE) component or the Payee Assignment by Element (GP_ED_ELEM) component.

- Creates a section override for the payee section named SAI SE SAISIES (the garnishments section). The override instructions appear on the Section Overrides page.

For the garnishment instructions to be processed, you must add the section SAI SE SAISIES to the process list that you use to calculate the payee's pay.

Note: To see the names of the deduction elements used for garnishment processing and the names of the variables that store the garnishment ID, start date, and initial amount, access the Rates and Elements page using the component name, GPFR_GAR_DAT.

Page Used to Enter Garnishments

Page Name	Definition Name	Navigation	Usage
Assign Garnishments FRA	GPFR_GAR_DAT	Global Payroll & Absence Mgmt, Payee Data, Garnishments/Court Orders, Assign Garnishments FRA, Assign Garnishments FRA	Set up a new garnishment or display the details of an existing garnishment.

Related Links

"Defining Element Definition Overrides (*PeopleSoft HCM 9.2: Global Payroll*)"

Assign Garnishments FRA page

Use the Assign Garnishments FRA page (GPFR_GAR_DAT) to set up a new garnishment or display the details of an existing garnishment.

Navigation

Global Payroll & Absence Mgmt, Payee Data, Garnishments/Court Orders, Assign Garnishments FRA, Assign Garnishments FRA

Image: Assign Garnishments FRA page: Garnishment Identification tab

This example illustrates the fields and controls on the Assign Garnishments FRA page: Garnishment Identification tab. You can find definitions for the fields and controls later on this page.

Assign Garnishments FRA

EmplID: KF0033 Morin, Mélanie Empl Record: 0

Garnishment Customize | Find | View All | First 1 of 1 Last

Garnishment Identification Recipient Status Elements

Garnishment ID	Type	Start Date	Amount
GARN01_2006	Tax	10/16/2006	1000

Garnishment Identification Tab

Garnishment ID

Enter the garnishment number on the garnishment notification. Enter up to 19 alphanumeric characters.

Type

Select the type of garnishment: *Alimony*, *Other*, *Penal*, or *Tax*.

Note: Enter up to three garnishments of each type for the same payee.

Start Date

(Required) Enter the date on which the payee's earnings become subject to garnishment. The date should fall within the current processing period. You cannot change this date once the system processes the first garnishment amount.

If you enter a start date that falls within an earlier processing period, the system will not begin to calculate the garnishment until you process a retroactive pay run. In addition, the results may be unpredictable and may require manual adjustment.

Amount

If the garnishment is for alimony, enter the amount of the monthly payment.

In all other cases, enter the initial amount of the garnishment. That is, enter the total amount owed according to the garnishment notice.

If you need to change the amount of the garnishment later, use positive input. See *Changing a Garnishment Balance* later in this section for more information.

Recipient Tab

Recipient ID

Select the garnishment recipient.

Recipient Name

Enter the name of the garnishment recipient. This field is required *only* if the recipient does not have a Recipient ID.

Bank Account Information

Select to add information about the bank account that will receive the garnishment payment. Specify the payment method, country code, bank ID, bank branch ID, account #, account name, and currency code.

Status Tab

Remove

Select this check box only if you want to remove a garnishment. To delete the garnishment, you must remove it first, save the page, and then click the minus (-) button to the right.

End Date

Enter the final payment date.

Status

Displays the status. Valid values are:

Created: Appears when you click the plus (+) button to add a new row.

Processed: Indicates that the system has created a section override for the payee. The status is set to *Processed* when you save the garnishment data.

Updated: Indicates that you modified the garnishment data.

Removed: Indicates that the system has deleted the deduction for the payee and has updated the section override (or deleted it if there are no other garnishments).

Error: Indicates that the system could not assign the deduction to the payee or create a section override due to a technical problem.

Elements Tab

Element Name

Displays the name of the deduction element that calculates the garnishment amount during payroll processing. The elements for garnishments are:

- Alimony Deductions: *PENSION AL 1*, *PENSION AL 2*, *PENSION AL 3*.
- Penal sentence deductions: *COND PENAL 1*, *COND PENAL 2*, *COND PENAL 3*.
- Tax debt deductions: *IMPOT 1*, *IMPOT 2*, *IMPOT 3*.

- Ordinary debt deductions: *CREANCE 1*, *CREANCE 2*, *CREANCE 3*.

Specifying Recipients for a Garnishment

Specify the recipient of the garnishment on the Recipient tab of the Assign Garnishments FRA page in Global Payroll for France. The recipient can be either a general or an individual recipient. Before you assign a garnishment to a recipient on this page, you must define the recipient using the Deduction Recipients component in the Global Payroll core application (Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Banking, Deduction Recipients).

Stopping, Removing, and Deleting Garnishments

You can stop or remove a garnishment, when necessary.

To stop a garnishment:

1. Access the Assign Garnishments FRA page for the payee.
2. Change the date in the End Date field and save your change.

To remove a garnishment:

1. Access the Assign Garnishments FRA page for the payee.
2. Select the Remove check box and save your change.

The system removes the deduction assigned to the payee and updates or deletes the section override for the payee. You cannot make additional changes to the garnishment.

To delete a garnishment:

1. Remove the garnishment according to the instructions for removing a garnishment.
2. Click the minus (-) button that appears to the right of the garnishment on any of the Assign Garnishments FRA pages, and save your change.

The system deletes the garnishment from the database.

Changing a Garnishment Balance

In Global Payroll for France you adjust a payee's garnishment balance by entering a supporting element override. For example, if you receive a notice from the court stating that a garnishment has been cancelled or reduced, use the Supporting Elements page (GP_PAYEE_SOVR) to enter the amount of the adjustment.

To enter an adjustment:

1. Access the Supporting Elements page (Global Payroll & Absence Mgmt, Payee Data, Create Overrides, Supporting Elements).
2. Enter *Variable* in the Element Type field.
3. In the Element Name field, enter or select the variable name that corresponds to the garnishment for which you are entering an adjustment.

Use this table to determine which variable corresponds to the garnishment you are adjusting:

Note: You will enter the adjustment amount using the variable associated with this garnishment.

Garnishment	Variable
PENSION AL 1 (alimony pension)	SAI VR AJUST ALI 1
PENSION AL 2 (alimony pension)	SAI VR AJUST ALI 2
PENSION AL 3 (alimony pension)	SAI VR AJUST ALI 3
IMPOT 1 (tax debt)	SAI VR AJUST IMP 1
IMPOT 2 (tax debt)	SAI VR AJUST IMP 2
IMPOT 3 (tax debt)	SAI VR AJUST IMP 3
CREANCE 1 (ordinary debt)	SAI VR AJUST CRE 1
CREANCE 2 (ordinary debt)	SAI VR AJUST CRE 2
CREANCE 3 (ordinary debt)	SAI VR AJUST CRE 3
COND PENAL 1 (penal sentence debt)	SAI VR AJUST PEN 1
COND PENAL 2 (penal sentence debt)	SAI VR AJUST PEN 2
COND PENAL 3 (penal sentence debt)	SAI VR AJUST PEN 3

Important! Each variable is exclusive to one deduction only.

4. Enter the begin date and end date of the period to which the adjustment applies. If you do not enter an end date equal to the end of the period for which you want to update the garnishment, the same adjustment will be processed over several periods.

The exception to this rule is if you want to increase (or decrease) an alimony garnishment for several periods. In this case, enter an end date equal to the last day of the final period in which you want to make an adjustment. In all cases, the adjustment is taken into account only in the first segment of the period processed.

5. On the same page, in the Numeric Value field, enter the monetary amount by which you want to increase or decrease the garnishment.

Related Links

"Entering Positive Input (*PeopleSoft HCM 9.2: Global Payroll*)"

Setting Maximum Amounts for Garnishments

In Global Payroll for France you specify the maximum garnishment amount for tax debt (IMPOT 1–3), ordinary debt (CREANCE 1–3), and penal sentence debt (COND PENAL 1–3) by entering a supporting element override.

Note: You do not need to set maximum garnishment amounts for PENSION AL 1–3 (alimony pension); these garnishments already have a maximum amount set by law. While the other types of garnishments are not restricted by law, individual court judgements may set a maximum garnishment amount.

To set maximum garnishment amounts for a payee:

1. Access the Supporting Elements page (Global Payroll & Absence Mgmt, Payee Data, Create Overrides, Supporting Elements).
2. Enter *Variable* in the Element Type field.
3. In the Element Name field, enter or select the variable name that corresponds to the garnishment that you want to limit.

Use this table to determine which variable corresponds to the garnishment you are updating:

Garnishment	Variable
IMPOT 1 (tax debt)	SAI VR MAX IMPOT 1
IMPOT 2 (tax debt)	SAI VR MAX IMPOT 2
IMPOT 3 (tax debt)	SAI VR MAX IMPOT 3
CREANCE 1 (ordinary debt)	SAI VR MAX CREAN 1
CREANCE 2 (ordinary debt)	SAI VR MAX CREAN 2
CREANCE 3 (ordinary debt)	SAI VR MAX CREAN 3
(penal sentence debt)	SAI VR MAX PENAL 1
COND PENAL 2 (penal sentence debt)	SAI VR MAX PENAL 2
COND PENAL 3 (penal sentence debt)	SAI VR MAX PENAL 3

4. In the Numeric Value field on the Values tab, enter the maximum garnishment amount.

Generating a Garnishment Report

Use the Generic Report component to produce the garnishment report FRPAY004.

Related Links

"Running Generic Reports (*PeopleSoft HCM 9.2: Global Payroll*)"

Administering Loans and Advances

Understanding Loans and Advances

Understanding Reimbursement Terms

Global Payroll for France is designed to manage many of the regulations that govern reimbursement terms for loans and advances. In addition to what the system already offers, you can also reconfigure the system to meet further needs, if necessary.

This section discusses:

- Reimbursement of loans and salary advances (avances).
- Reimbursement of permanent salary advances.
- Reimbursement of advances on salary (acomptes).
- Loan and advance processing relative to garnishment processing.

Reimbursement of Loans and Salary Advances (Avances)

Global Payroll for France is set up to process loan and salary advance paybacks once a month. If there are multiple segments within the month, the system processes paybacks during the first segment of the month. In addition, regulations limit the deduction for reimbursement of a salary advance or loan to a maximum of 10 percent of the net salary each month. If you request a deduction of more than 10 percent of the payee's net salary, the system generates an error message stating that the payment amount exceeds the 10 percent limit. This message is sent to the user and appears on the Payee Messages page.

If multiple salary advances and loans are owed, the system processes the payback amounts in a set order. The processing order for reimbursement of loans and salary advances is as follows:

1. Salary Advance (RETENUE AV1)
2. Salary Advance (RETENUE AV2)
3. Salary Advance (RETENUE AV3)
4. Loan (RETENUE PR1)
5. Loan (RETENUE PR2)
6. Loan (RETENUE PR3)

When the system processes the deduction payments for loans and salary advances, it does not consider the order in which the loans and salary advances were created. It always processes each loan and salary advance reimbursement in this order.

Note: The order in which loans and advances are processed reflects the order of the elements in the PRE SE PRET process section.

Special Circumstances for Reimbursement of Loans and Salary Advances in the Case of Departure

If a payee leaves the organization and the balance of his or her advance or loan is more than 1/10th of his or her net salary, the system automatically deducts the entire balance, but issues a warning stating that the payment exceeds the 1/10th limit. At that point, it is up to the organization to change the amount of the payback to comply with regulations.

Sometimes a payee is transferred to an affiliated organization—an organization whose payees are paid using the same payroll system—and the payee's net salary from the former organization cannot cover the balance of the loan or salary advance. In this circumstance, the organization can process the last deduction from the former organization's payslip and roll over the balance owed to the new organization.

Related Links

"Viewing Payee Messages (*PeopleSoft HCM 9.2: Absence Management*)"

Reimbursement of Permanent Salary Advances

The balance of a permanent advance is recovered automatically when a payee leaves the organization. However, you can recover a permanent advance prior to departure by specifying the reimbursement amount using positive input.

See [Setting Up Loans and Advances](#).

Reimbursement of Advances on Salary (Acomptes)

When a payee receives an advance on salary, he/she receives compensation before the regular payroll payment. You can then reduce the payee's next payslip by the amount advanced by entering the reimbursement amount using positive input.

See [Setting Up Loans and Advances](#).

Loan and Advance Processing Relative to Garnishment Processing

Global Payroll for France processes garnishments before it processes loans and salary advances (avances), permanent salary advances, or advances on salary (acomptes). If there is insufficient net pay to cover all loan and advance reimbursements after garnishments are deducted, the system avoids returning a negative net payment by processing the remaining loans and advances in subsequent pay periods.

Understanding Loans and Retroactive Processing

By law, loans cannot be recalculated during retroactive processing.

Global Payroll defines loan elements with the Retro Recalculation option set to *Do Not Recalculate*. However, because loans are triggered by positive input, and positive input overrides the Retro Recalculation option, you should be careful not to enter new loan data in a closed period.

Related Links

[Loans and Garnishments](#)

Setting Up Loans and Advances

This section provides an overview of setting up loans and advances, and discusses how to:

- Set up loans and salary advances.
- Set up permanent salary advances and advances on salary (acomptes).
- Specify the amount of a permanent salary advance and the amount to recover.

Pages Used to Set Up Loans and Advances

Page Name	Definition Name	Navigation	Usage
Request Advances/Loans FRA	GPFR_LOANS	Global Payroll & Absence Mgmt, Payee Data, Loans, Request Advances/Loans FRA, Request Advances/Loans FRA	Enter loan or salary advance details, create and modify the reimbursement schedule, and view past and current loan/salary advance balances.
One Time (Positive Input)	GP_PI_MNL_ERNDED	Global Payroll & Absence Mgmt, Payee Data, Assign Earnings and Deductions, One Time (Positive Input), One Time (Positive Input)	Use this page to set up reimbursements for permanent salary advances and an advances on salary (acomptes).
Positive Input - Details	GP_PI_MNL_SEC	Click the Details button on the One Time (Positive Input) page.	<ul style="list-style-type: none"> • Specify the initial amount of a permanent salary advance in the Initial capital of the Loan field. • Enter the amount of the permanent salary advance you want to recover in the Reimburs Permanent Advance field.

Understanding The Setup of Loans and Advances

This section discusses:

- Loans.
- Salary advances (avances).
- Permanent salary advances.

- Advances on salary (acomptes).

Loans

To set up a loan, use the Request Advances/Loans FRA page.

For each loan, PeopleCode automatically generates positive input for the following elements using a component interface:

- Deductions RETENUE PR1, RETENUE PR2, or RETENUE PR3.

The system allows each payee to have up to three loans at a given time. When you enter a loan into the system, Global Payroll for France first assigns deduction RETENUE PR1 to the payee, then RETENUE PR2, and finally RETENUE PR3.

- Calendar ID.
- Instance.
- The deduction's base (which is set to the reimbursement amount).
- Loan identification PIN (PRE VR IDENTIFIANT).
- Start date of the loan (PRE VR DATE DEBUT).
- Loan initial capital (PRE VR CAPITAL).

Salary Advances (Avances)

To set up an advance on salary, use the Request Advances/Loans FRA page.

For each advance on salary, PeopleCode automatically generates positive input for the following elements using a component interface:

- Deductions RETENUE AV1, RETENUE AV2, or RETENUE AV3.

The system allows each payee to have up to three advances at a given time. When you enter a salary advance into the system, Global Payroll for France first assigns deduction RETENUE AV1 to the payee, then RETENUE AV2, and finally RETENUE AV 3.

- Calendar ID.
- Instance.
- The deduction's base (which is set to the reimbursement amount).
- Salary advance identification PIN (PRE VR IDENTIFIANT).
- Start date of the salary advance (PRE VR DATE DEBUT).
- Salary advance initial amount (PRE VR CAPITAL).

Permanent Salary Advances

To set up a permanent salary advance:

1. Access the One Time (Positive Input) page (Global Payroll & Absence Mgmt, Payee Data, Assign Earnings and Deductions, One Time (Positive Input), One Time (Positive Input)) and assign the deduction RETENUE AVPE to the payee.

Note: The deduction RETENUE AVPE does not affect payroll results—it is used only to enter and track the initial amount of a permanent salary advance.

2. Click the Details link on the One Time (Positive Input) page (see step 1) to access the Positive Input - Details page.
3. On the Positive Input - Details page, enter the amount of the advance in the Initial Capital of Loan field (do not use the Amount field on the One Time (Positive Input) page to do this).

When you save your data, the system populates the supporting element PRE VR CAPITAL with the amount of the advance. When the advance is processed, the resolution formula for the permanent salary advance stores the value of PRE VR CAPITAL in the balance accumulator PRE AC AVPE. Later, when the payee departs, the system uses the deduction RETEN AVPE D to automatically recover the amount in the balance accumulator.

To recover all or part of an advance prior to a payee's departure:

1. Access the One Time (Positive Input) page (Global Payroll & Absence Mgmt, Payee Data, Assign Earnings and Deductions, One Time (Positive Input), One Time (Positive Input)).
2. Click the Details link on the One Time (Positive Input) page (see step 1) for the row containing the deduction RETENUE AVPE.

The Positive Input - Details page appears.

3. On the Positive Input - Details page, enter the amount you want to recover in the Reimburs Permanent Advance field.

The resolution formula for the advance verifies that the reimbursement amount does not exceed the amount in the balance accumulator PRE AC AVPE. If this amount exceeds the balance, Global Payroll for France puts the payment in error. If the amount requested does not exceed the balance, the system processes the RETEN AVPE D deduction to recover the advance.

Note: The balance of the permanent salary advance is stored in the accumulator PRE AC AVPE. To modify this balance, access the One Time (Positive Input) page, assign the deduction RETENUE AVPE, and override the value of the variable PRE VR CAPITAL.

If you want to know the amount of the balance for the permanent advance, look at the accumulator PRE AC AVPE calculated during the previous payroll.

Note: Note that the balance of a permanent salary advance—stored in the accumulator PRE AC AVPE—is recovered *automatically* when a payee leaves the organization. In other words, the steps in this section apply only when you want to recover a salary advance *prior to* a payee's departure.

Advances on Salary (Acomptes)

PeopleSoft delivers the deduction RETENUE ACOM to enable you to reduce a payee's net payment by the amount advanced. PeopleSoft does not deliver an earning element to pay the advance itself, and there is no automatic retrieval of the amount paid as no earning is provided. Nevertheless, you can create rules

that enable you to enter an earning for the payment and then automatically process a deduction in the next pay run.

To recover an advance on salary (acompte):

1. Access the One Time (Positive Input) page (Global Payroll & Absence Mgmt, Payee Data, Assign Earnings and Deductions, One Time (Positive Input), One Time (Positive Input)) and assign the deduction RETENUE ACOM to the payee.
2. Enter the amount to recover (deduct) in the Amount field on the One Time (Positive Input) page.

Related Links

"Entering Positive Input (*PeopleSoft HCM 9.2: Global Payroll*)"

Request Advances/Loans FRA Page

Use the Request Advances/Loans FRA page (GPFR_LOANS) to enter loan or salary advance details, create and modify the reimbursement schedule, and view past and current loan/salary advance balances.

Navigation

Global Payroll & Absence Mgmt, Payee Data, Loans, Request Advances/Loans FRA, Request Advances/Loans FRA

Image: Request Advances/Loans FRA page

This example illustrates the fields and controls on the Request Advances/Loans FRA page. You can find definitions for the fields and controls later on this page.

Request Advances/Loans FRA

Maurice Berger EMP ID: KF0001 Empl Record: 0

Loan Find | View All | First 1 of 1 Last

*Loan Identification: BERGER ADV *Loan or Advance: Loan + -

*Period Begin Date: 01/01/2004 31 *Loan Initial Amount: 2000.00 EUR

Payback Amount: 500.00 or Payback Periods:

Pay Group: GFPGMEN103 Deduction:

Create Schedule Remove Status:

Schedule Customize | Find | View All | First 1 of 1 Last

Amounts Balances

*Pay Group	*Calendar ID		
KFGMONTHLY	KFGMJAN01P	+	-

Loan

When you click the Create Schedule button, it is not possible to change any data in the Loan group box; instead, adjust data on the Amounts and Balances tabs, which are located in the Schedule group box.

Loan Identification	Enter a loan or salary advance ID. This character field is mandatory and must be unique to each payee.
Loan or Advance	<p>Select <i>Loan</i> to create a loan or <i>Advance</i> to create a salary advance.</p> <p><i>Loan</i> is the default value.</p>
Period Begin Date	Enter the date that the loan or salary advance begins. This date cannot be before the next calendar ID.
Loan Initial Amount	Enter the amount of the loan or salary advance. Also specify the currency.
Payback Amount	Enter the amount of each payback installment. After you create the schedule, this payback amount populates the Amount field in the Schedule group box. The Payback Periods field in the Loan group box must remain empty if you enter a payback amount in this field.
Payback Periods	Enter the number of payback periods here. If you enter the number of payback periods, the system divides the initial loan amount by the number of payback periods to determine the payback amount in each installment. The payback amount populates in the Amount field in the Schedule group box. The Payback Amount field in the Loan group box must remain empty if you enter the number of payback periods in this field.
Pay Group	Select the payee's pay group. This field is used to generate the schedule, but it is not required.
Deduction	<p>Displays the first free deduction element that the system assigns.</p> <p>If you are setting up a loan, the three possible deduction elements are <i>RETENUE PR1</i>, <i>RETENUE PR2</i>, and <i>RETENUE PR3</i>. If you are setting up a salary advance, the three possible deduction elements are <i>RETENUE AV1</i>, <i>RETENUE AV2</i>, and <i>RETENUE AV3</i>.</p>
Create Schedule	<p>Click this button to create the reimbursement schedule automatically. The system splits the initial loan amount into segments, using either the payback amount or the number of periods. It starts from the begin date and retrieves the different calendars available for the pay group listed. If more than one calendar has the same begin date and is available to the same pay group, the system uses the calendar that was created first; the other calendar is not used. After creating the schedule, all changes must be made in the Amounts and Balances tabs.</p> <p>This button is not mandatory for creating the reimbursement schedule. You can also create the schedule row by row. For example, if the payee changes his pay group, then you must manually change the schedule for each row affected.</p>

Remove	Select this check box to remove a loan or advance from the system.
Status	Displays <i>Removed</i> when the loan has been created (saved) and then removed.

Amounts Tab

This tab displays the payback amounts and their associated calendar IDs.

Pay Group	Displays the pay group entered in the Loan group box. Overwrite the pay group by selecting a new pay group.
Calendar ID	Displays the calendar ID for each reimbursement. You can change the calendar ID any time that the value in the Status field is <i>Created</i> , <i>Updated</i> , or <i>Awaiting</i> .
Skip	Select if you want to suspend a reimbursement for the calendar period.

Note: If you skip a reimbursement, ensure that the total amounts of all non-skipped reimbursements add up to the initial loan amount. In other words, when you skip a reimbursement, you must increase the amounts of the remaining payments to ensure that the full amount of the loan is paid. Or, you can add an extra monthly payment for the same amount as the skipped one.

Amount	Displays the amount of each reimbursement. The system evenly distributes the initial loan amount over the number of payback periods to obtain the payback amount for each period. The sum of all the amounts listed in the Amount fields must equal the amount in the Loan Initial Amount field. If you change the amount of one of the payments, check to make sure that all of your scheduled payments add up to the total amount of the loan. If the amounts do not equal the initial loan amount, the system does not validate the information. It also issues an error message and explains what to do to fix the error.
---------------	--

Balances Tab

This tab displays reimbursement balance information.

Balance	Displays the balance at the end of the calendar ID date.
Status	Displays one of these values: <i>Created:</i> Appears if the schedule row has been created, but the page has not been saved; thus, no positive input exists in the system for this row. <i>Awaiting:</i> Appears if positive input has been created and saved and is ready for payroll processing.

Processed: Appears if positive input has been created and the payroll is finalized. You cannot update a processed row. In order to determine whether positive input has been processed, the application reads the payroll results and checks if the pay run for each corresponding pay group and calendar have been finalized.

Error: Appears if the schedule row is not synchronized with positive input that was updated manually. In this situation, you must process a new payroll.

Updated: Appears if the row has been modified since its creation. This may happen even if positive input has already been generated. *Updated* appears if one of the following is true:

- The calendar is changed. If previously created, the old positive input is deleted and a new positive input row is created.
- The amount is changed. If previously created, the positive input is automatically updated.
- A payment is skipped. If previously created, the positive input is deleted.

Note: When an amount on this page has a status of *Processed*, the Amount field becomes unavailable for data entry and cannot be changed or skipped.

Removed: Appears if the positive input was generated and then removed before the pay run was finalized. This status appears when positive input has been deleted. For example, when the row is created, the page is saved, and then the row is skipped, or when the loan is created, saved, and then removed.

Deleting a Loan or Advance

Deleting a loan involves two steps:

- Step 1: Remove the loan.

To remove a loan from the system and cancel the positive input, select the Remove check box and save the page. When you remove the loan, the loan definition still exists, but the positive input is deleted.

- Step 2: Remove loan details.

To delete the loan details, click the minus sign in the top right corner of the page.

Note: You cannot delete a loan with a status of *Updated* or *Processed*.

Updates to Loans and Advances

When an amount on the Request Advances/Loans FRA page has a status of *Processed*, the amount cannot be changed or removed, and the row cannot be skipped. If you need to make a retroactive change, you have to make the change directly through positive input. When an amount on the loans page has a status equal to *Awaiting*, a change to the row produces a warning message informing you that you must recalculate the payroll for the employee if you want the change to be recorded.

Note: If you modify a loan or advance retroactively by making changes directly through positive input, the amounts deducted won't be synchronized with the data on the Request Advances/Loans FRA page.

One Time (Positive Input) Page

Use the One Time (Positive Input) page (GP_PI_MNL_ERNDED) to use this page to set up reimbursements for permanent salary advances and an advances on salary (acomptes).

Navigation

Global Payroll & Absence Mgmt, Payee Data, Assign Earnings and Deductions, One Time (Positive Input), One Time (Positive Input)

Image: One Time (Positive Input) page

This example illustrates the fields and controls on the One Time (Positive Input) page. You can find definitions for the fields and controls later on this page.

One Time (Positive Input)

Employee ID: KFGE0003 Name: [Pierre Artoux](#) Empl Record: 0
 Pay Group: KFGMONTHLY Description: Monthly Pay Group Pay Entity: KFGPAYENT
 Calendar ID: KFGMJAN01P Begin Date: 01/01/2001 End Date: 01/31/2001

Earnings and Deductions Customize | Find | View All | First 1 of 1 Last

*Entry Type	Element Name	Element Description	Instance	*Action Type
Earnings	HRS DIMANCHE	Sunday Hours	1	Override

To set up a permanent salary advance, enter the deduction RETENUE AVPE in the Element Name field with an action type of *Override*. Enter the amount of the advance in the Initial Capital of Loan field on the Positive Input - Details page.

To set up an advance on salary (acompte), enter the deduction RETENUE ACOM in the Element Name field with an action type of *Override*. Enter the amount of the advance in the Amount field on the Main Components tab.

Note: This page is documented in full in the *PeopleSoft Global Payroll*.

See "Understanding Positive Input (*PeopleSoft HCM 9.2: Global Payroll*)".

Positive Input - Details Page

Use the Positive Input - Details page (GP_PI_MNL_SEC) to .

Navigation

Click the Details button on the One Time (Positive Input) page.

Image: Positive Input - Details page

This example illustrates the fields and controls on the Positive Input - Details page. You can find definitions for the fields and controls later on this page.

One Time (Positive Input)
Positive Input - Details

Employee ID: KFGE0003 Name: Pierre Artoux Empl Record: 000
 Pay Group: KFGMONTHLY Description: Monthly Pay Group
 Calendar ID: KFGMJAN01P Begin Date: 01/01/2001 End Date: 01/31/2001
 Element: HRS DIMANCHE Element Name: Sunday Hours Instance: 001

▼ Specify Values OR Elements

Unit Value: 3.000000 Unit Element:
 Rate Value: Rate Element:
 Base Value: Base Element:
 Percent Value: Percent Element: Currency:
 Amount Value: Amount Element:
 Begin Date: End Date:

▼ Absence Dates

Absence Begin Date: Absence End Date:
 Period Begin Date: Period End Date:

▼ Other Data

Batch Code: Description of Pl:

▼ Supporting & Element Overrides

Business Unit: FRA01

Supporting & Element Overrides							Customize	Find	View All	1 of 1	First	Last
*Element Entry Type	Element Name	Description	Character Value	Lookup Character Value	Numeric Value	Date Value						
<input type="text"/>	<input type="text"/>		<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>						

Enter the amount of the permanent salary advance in the Initial Capital of the Loan field.

To recover a permanent salary advance prior to the departure of a payee, specify the amount to recover in the Reimburs. Permanent Advance field.

Note: This page is documented in full in the *PeopleSoft Global Payroll* .

Generating a Loans Report

Global Payroll for France provides a generic Loans and Advances report. This report is set up using the Generic Reports component. Access this component by selecting Global Payroll & Absence Mgmt, Absence and Payroll Processing, Create Generic Report, Generic Report.

Related Links

"Running Generic Reports (*PeopleSoft HCM 9.2: Global Payroll*)"

Viewing Delivered Loan and Advance Deductions

Name	Description
RETENUE ACOM	Advance on salary – Acompte
RETENUE AV1	Salary advance 1 – Advance
RETENUE AV2	Salary advance 2 – Advance
RETENUE AV3	Salary advance 3 – Advance
RETENUE PR1	Loan 1
RETENUE PR2	Loan 2
RETENUE PR3	Loan 3
RETENUE AVPE	Permanent advance
RETEN AVPE D	Permanent advance – departure

Note: PeopleSoft delivers a query that you can run to view the names of all delivered elements designed for France. Instructions for running the query are provided in the *PeopleSoft Global Payroll* .

Related Links

"Understanding How to View Delivered Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

Entering Absences

Understanding Absence Calculations

PeopleSoft delivers predefined rules for processing absences due to vacation, illness, maternity, work accidents, and other reasons. These rules conform to French statutory requirements. You can easily modify many of these rules to reflect absence policies that are specific to your organization or to collective agreements that may be in force for your employees.

This section discusses absence calculations.

Absence Units

When entering absences on the Absence Event Entry page, specify the from and to dates of each absence.

Later, when you run the Absence process, the system calculates the number of paid and unpaid units of time that the absence represents. During the payroll process, the system uses these units to determine the appropriate rate to apply when resolving the earning and deduction amounts associated with the absence.

<i>Type of Absence</i>	<i>Delivered Setting for Units</i>	<i>Valid Options</i>
Paid vacation	Working days	Working days, business days
Staff representative, work council, CHSCT, and union time	Hours	Hours
All other absences	Calendar days	Hours, business days, calendar days

For example, the system uses calendar days to determine the compensation rate that applies when an employee takes paid time off for family leave. The rate equals the employee's monthly base salary divided by the number of calendar days in the month.

You can change the units for all absences except staff representatives, work council, CHSCT, and union time. For paid vacation, you can select business days or working days by updating the variable element CPA VR JRS/1 SEM, as explained in *Changing the Day Weight (CPA VR JRS/1 SEM)*.

For other absences, you can select hours, business days, or calendar days. Make this selection by updating the bracket ABS BS ABS VALO as described in *Units for Earnings and Deduction Calculations (ABS BR ABS VALO)*.

When you run the payroll process, the system uses the selected units to calculate the rate it applies to resolve the deduction and earning elements.

Base

You can change the base salary that the system uses to calculate the compensation rate by updating the formula element ABS FM SAL BA THEO.

Percent

The Day Formula page for each take element includes fields that define the percent that the system applies to the earning and deduction amounts calculated for an absence.

For example, the first 30 days of an absence due to illness can be compensated at 90 percent, the next 30 days can be compensated at 66,66 percent, and so on. Percentages are predefined for the illness and work accident take elements delivered with Global Payroll for France.

Understanding Absence Take Elements

This section provides a summary of the elements delivered with Global Payroll for France for absences:

- Elements for miscellaneous absence.
- Elements for work accidents.
- Elements for paid vacation.
- Elements for family events.
- Elements for illness absence.
- Elements for maternity absence.
- Elements for staff representative absence.

The tables list the take elements, earnings, deductions, and the elements that retrieve the units and the percent that the system uses to calculate positive input.

The last three columns of each table identify the codes that appear in the User Defined 1, 2, and 3 fields on the take element Calculation page. (These values are stored by the TAKE CONFIG 1, TAKE CONFIG 2, and TAKE CONFIG 3 system elements.)

Related Links

[Understanding User-Defined \(TAKE CONFIG\) Fields](#)

Elements for Miscellaneous Absence

Take Elements/ Miscellaneous	Earning / Deduction Elements	Element that Retrieves Units for Positive Input	Element that Retrieves Percent for Positive Input	User-defined Fields
ABT AB N AUT N PAY	ANA DED H ANA DED JO ANA DED JC	ABS VR HR S SOLDE ABS VR JO S SOLDE ABS VR JC S SOLDE	None	Field 2: DIV Field 3: 1DER
ABT ADOPTION	CSS RET JC CSS RET H CSS RET JO	ABS VR JC S SOLDE ABS VR HR S SOLDE ABS VR JO S SOLDE	None	Field 2: EVF Field 3: 1DER
ABT AUT ABS PAYEES	AAP RET H AAP VAL H AAP RET JO AAP VAL JO AAP RET JC AAP VAL JC	ABS VR HR DED ABS FM GEN HRS ABS VR JO DED ABS FM GEN JO ABS VR JC DED ABS FM GEN JC	None	Field 2: DIV Field 3: 1DER
ABT AUT NON PAYEE	CSS RET JC CSS RET JO CSS RET H	ABS VR JC S SOLDE ABS VR JO S SOLDE ABS VR HR S SOLDE	None	Field 2: DIV
ABT CIF NONPAYE	CIF RET H	ABS VR CIF HRS	None	Field 2: CIF Field 3: 1DER
ABT CIF PAYE	CIF RET H CIF VAL H	ABS VR CIF HRS ABS VR CIF HRS	None	Field 2: CIF Field 3: 1DER
ABT CONGE PARENTAL	PAR DED JC PAR DED JO PAR DED H	ABS VR JC S SOLDE ABS VR JO S SOLDE ABS VR HR S SOLDE	None	Field 2: PAR Field 3: 1DER
ABT GREVE	GREVE RET H GREVE RET JO GREVE RET JC	ABS VR HR S SOLDE ABS VR JO S SOLDE ABS VR JC S SOLDE	None	Field 2: DIV Field 3: 1DER

Take Elements/ Miscellaneous	Earning / Deduction Elements	Element that Retrieves Units for Positive Input	Element that Retrieves Percent for Positive Input	User-defined Fields
ABT MAP CONSER	MAP CO DE H MAP CO DE JO MAP CO DE JC	ABS VR HR S SOLDE ABS VR JO S SOLDE ABS VR JC S SOLDE	None	Field 2: DIV Field 3: 1DER
ABT MAP DISCIPLI	MAP DI DE H MAP DI DE JO MAP DI DE JC	ABS VR HR S SOLDE ABS VR JO S SOLDE ABS VR JC S SOLDE	None	Field 2: DIV Field 3: 1DER
ABT PREAV N F	PRE NE VAL H PRE NE RET H PRE NE VA JO PRE NE RE JO PRE NE VA JC PRE NE RE JC	ABS VR HR S SOLDE ABS VR HR S SOLDE ABS VR JO S SOLDE ABS VR JO S SOLDE ABS VR JC S SOLDE ABS VR JC S SOLDE	None	Field 2: PREAV Field 3: 1DER
ABT REP COMP	RCL VAL H RCL RET H RCL VAL JO RCL RET JO RCL VAL JC RCL RET JC	ABS FM GEN HRS ABS VR HR DED ABS FM GEN JO ABS VR JO DED ABS FM GEN JC ABS VR JC DED	None	Field 2: REPOS Field 3: 1DER
ABT SABBATIQ	CSS RET JC CSS RET JO CSS RET H	ABS VR JC S SOLDE ABS VR JO S SOLDE ABS VR HR S SOLDE	None	Field 2: SABB Field 3: 1DER

Elements for Work Accidents

Take Element / Work Accident Relapse	Earning / Deduction Elements	Element that Retrieves Units for Positive Input	Element that Retrieves Percent for Positive Input	User-Defined Fields
ATT TRAVAIL	ACT TR VA H	ABS FM HEURES	ABS VR MAINT %1	Field 1: ATRV1
	ACT TR DE H	ABS VR HR DED	ABS VR MAINT %1	Field 2: AT
	ACT TR VA JO	ABS FM JRS OUV	ABS VR MAINT %1	Field 3: 1
	ACT TR DE JO	ABS VR JO DED		
	ACT TR VA JC	ABS FM JRS CAL		
	ACT TR DE JC	ABS VR JC DED		
ATT TRAVAIL2	ACT TR VA H	ABS FM HEURES	ABS VR MAINT %2	Field 1: ATRV2
	ACT TR DE H	ABS VR HR DED	ABS VR MAINT %2	Field 2: AT
	ACT TR VA JO	ABS FM JRS OUV	ABS VR MAINT %2	
	ACT TR DE JO	ABS VR JO DED		
	ACT TR VA JC	ABS FM JRS CAL		
	ACT TR DE JC	ABS VR JC DED		
ATT TRAVAIL3	ACT TR VA H	ABS FM HEURES	ABS VR MAINT %3	Field 1: ATRV3
	ACT TR DE H	ABS VR HR DED	ABS VR MAINT %3	Field 2: AT
	ACT TR VA JO	ABS FM JRS OUV	ABS VR MAINT %3	
	ACT TR DE JO	ABS VR JO DED		
	ACT TR VA JC	ABS FM JRS CAL		
	ACT TR DE JC	ABS VR JC DED		
ATT TRAVAIL4	ACT TR VA H	ABS FM HEURES	ABS VR MAINT %4	Field 1: ATRV4
	ACT TR DE H	ABS VR HR DED	ABS VR MAINT %4	Field 2: AT
	ACT TR VA JO	ABS FM JRS OUV	ABS VR MAINT %4	Field 3: DER
	ACT TR DE JO	ABS VR JO DED		
	ACT TR VA JC	ABS FM JRS CAL		
	ACT TR DE JC	ABS VR JC DED		
ATT TRAJ IJ1	ATR DED IJT1	DAY COUNT PD	None	IJ1
ATT TRAJ IJ2	ATR DED IJT2	DAY COUNT PD	None	DERN
ATT TRJ IJ RECH1	ATR DED IJR1	DAY COUNT PD	None	IJ1
ATT TRJ IJ RECH2	ATR DED IJR2	DAY COUNT PD	None	DERN

<i>Take Element / Work Accident Relapse</i>	<i>Earning / Deduction Elements</i>	<i>Element that Retrieves Units for Positive Input</i>	<i>Element that Retrieves Percent for Positive Input</i>	<i>User-Defined Fields</i>
ATT TRAJET	ACT TJ VA H ACT TJ DE H ACT TJ VA JO ACT TJ DE JO ACT TJ VA JC ACT TJ DE JC	ABS FM HEURES ABS VR HR DED ABS FM JRS OUV ABS VR JO DED ABS FM JRS CAL ABS VR JC DED	ABS VR MAINT %1 ABS VR MAINT %1 ABS VR MAINT %1	Field 1:ATRV1 Field 2:AT Field 3:1
ATT TRAJET2	ACT TJ VA H ACT TJ DE H ACT TJ VA JO ACT TJ DE JO ACT TJ VA JC ACT TJ DE JC	ABS FM HEURES ABS VR HR DED ABS FM JRS OUV ABS VR JO DED ABS FM JRS CAL ABS VR JC DED	ABS VR MAINT %2 ABS VR MAINT %2 ABS VR MAINT %2	Field 1:ATRV2 Field 2:AT
ATT TRAJET3	ACT TJ VA H ACT TJ DE H ACT TJ VA JO ACT TJ DE JO ACT TJ VA JC ACT TJ DE JC	ABS FM HEURES ABS VR HR DED ABS FM JRS OUV ABS VR JO DED ABS FM JRS CAL ABS VR JC DED	ABS VR MAINT %3 ABS VR MAINT %3 ABS VR MAINT %3	Field 1:ATRV3 Field 2:AT
ATT TRAJET4	ACT TJ VA H ACT TJ DE H ACT TJ VA JO ACT TJ DE JO ACT TJ VA JC ACT TJ DE JC	ABS FM HEURES ABS VR HR DED ABS FM JRS OUV ABS VR JO DED ABS FM JRS CAL ABS VR JC DED	ABS VR MAINT %4 ABS VR MAINT %4 ABS VR MAINT %4	Field 1:ATRV4 Field 2:AT Field 3:DER

Take Element / Work Accident Relapse	Earning / Deduction Elements	Element that Retrieves Units for Positive Input	Element that Retrieves Percent for Positive Input	User-Defined Fields
MLT PROFESSL	ACT TR VA H ACT TR DE H ACT TR VA JO ACT TR DE JO ACT TR VA JC ACT TR DE JC	ABS FM HEURES ABS VR HR DED ABS FM JRS OUV ABS VR JO DED ABS FM JRS CAL ABS VR JC DED	ABS VR MAINT %1 ABS VR MAINT %1 ABS VR MAINT %1	Field 1: ATRV1 Field 2: AT Field 3: 1
MLT PROFESS2	ACT TR VA H ACT TR DE H ACT TR VA JO ACT TR DE JO ACT TR VA JC ACT TR DE JC	ABS FM HEURES ABS VR HR DED ABS FM JRS OUV ABS VR JO DED ABS FM JRS CAL ABS VR JC DED	ABS VR MAINT %2 ABS VR MAINT %2 ABS VR MAINT %2	Field 1: ATRV2 Field 2: AT
MLT PROFESS3	ACT TR VA H ACT TR DE H ACT TR VA JO ACT TR DE JO ACT TR VA JC ACT TR DE JC	ABS FM HEURES ABS VR HR DED ABS FM JRS OUV ABS VR JO DED ABS FM JRS CAL ABS VR JC DED	ABS VR MAINT %3 ABS VR MAINT %3 ABS VR MAINT %3	Field 1: ATRV3 Field 2: AT
MLT PROFESS4	ACT TR VA H ACT TR DE H ACT TR VA JO ACT TR DE JO ACT TR VA JC ACT TR DE JC	ABS FM HEURES ABS VR HR DED ABS FM JRS OUV ABS VR JO DED ABS FM JRS CAL ABS VR JC DED	ABS VR MAINT %4 ABS VR MAINT %4 ABS VR MAINT %4	Field 1: ATRV4 Field 2: AT Field 3: DER

Take Element / Work Accident Relapse	Earning / Deduction Elements	Element that Retrieves Units for Positive Input	Element that Retrieves Percent for Positive Input	User-Defined Fields
ATT RECHUTE TRAV	ACT TR VA H ACT TR DE H ACT TR VA JO ACT TR DE JO ACT TR VA JC ACT TR DE JC	ABS FM HEURES ABS VR HR DED ABS FM JRS OUV ABS VR JO DED ABS FM JRS CAL ABS VR JC DED	ABS VR MAINT %1 ABS VR MAINT %1 ABS VR MAINT %1	Field 1: ATRV1 Field 2: ATRCH Field 3: 1
ATT RECHUT TR2	ACT TR VA H ACT TR DE H ACT TR VA JO ACT TR DE JO ACT TR VA JC ACT TR DE JC	ABS FM HEURES ABS VR HR DED ABS FM JRS OUV ABS VR JO DED ABS FM JRS CAL ABS VR JC DED	ABS VR MAINT %2 ABS VR MAINT %2 ABS VR MAINT %2	Field 1: ATRV2 Field 2: ATRCH
ATT RECHUT TR3	ACT TR VA H ACT TR DE H ACT TR VA JO ACT TR DE JO ACT TR VA JC ACT TR DE JC	ABS FM HEURES ABS VR HR DED ABS FM JRS OUV ABS VR JO DED ABS FM JRS CAL ABS VR JC DED	ABS VR MAINT %3 ABS VR MAINT %3 ABS VR MAINT %3	Field 1: ATRV3 Field 2: ATRCH
ATT RECHUT TR4	ACT TR VA H ACT TR DE H ACT TR VA JO ACT TR DE JO ACT TR VA JC ACT TR DE JC	ABS FM HEURES ABS VR HR DED ABS FM JRS OUV ABS VR JO DED ABS FM JRS CAL ABS VR JC DED	ABS VR MAINT %4 ABS VR MAINT %4 ABS VR MAINT %4	Field 1: ATRV4 Field 2: ATRCH Field 3: DER

Take Element / Work Accident Relapse	Earning / Deduction Elements	Element that Retrieves Units for Positive Input	Element that Retrieves Percent for Positive Input	User-Defined Fields
ATT RECHUTE TRAJ	ACT TJ VA H	ABS FM HEURES	ABS VR MAINT %1	Field 1: ATRV1
	ACT TJ DE H	ABS VR HR DED	ABS VR MAINT %1	Field 2: ATRCH
	ACT TJ VA JO	ABS FM JRS OUV	ABS VR MAINT %1	Field 3: 1
	ACT TJ DE JO	ABS VR JO DED		
	ACT TJ VA JC	ABS FM JRS CAL		
	ACT TJ DE JC	ABS VR JC DED		
ATT RECHUTE TJ2	ACT TJ VA H	ABS FM HEURES	ABS VR MAINT %2	Field 1: ATRV2
	ACT TJ DE H	ABS VR HR DED	ABS VR MAINT %2	Field 2: ATRCH
	ACT TJ VA JO	ABS FM JRS OUV	ABS VR MAINT %2	
	ACT TJ DE JO	ABS VR JO DED		
	ACT TJ VA JC	ABS FM JRS CAL		
	ACT TJ DE JC	ABS VR JC DED		
ATT RECHUTE TJ3	ACT TJ VA H	ABS FM HEURES	ABS VR MAINT %3	Field 1: ATRV3
	ACT TJ DE H	ABS VR HR DED	ABS VR MAINT %3	Field 2: ATRCH
	ACT TJ VA JO	ABS FM JRS OUV	ABS VR MAINT %3	
	ACT TJ DE JO	ABS VR JO DED		
	ACT TJ VA JC	ABS FM JRS CAL		
	ACT TJ DE JC	ABS VR JC DED		
ATT RECHUTE TJ4	ACT TJ VA H	ABS FM HEURES	ABS VR MAINT %4	Field 1: ATRV4
	ACT TJ DE H	ABS VR HR DED	ABS VR MAINT %4	Field 2: ATRCH
	ACT TJ VA JO	ABS FM JRS OUV	ABS VR MAINT %4	Field 2: DER
	ACT TJ DE JO	ABS VR JO DED		
	ACT TJ VA JC	ABS FM JRS CAL		
	ACT TJ DE JC	ABS VR JC DED		

Take Element / Work Accident Relapse	Earning / Deduction Elements	Element that Retrieves Units for Positive Input	Element that Retrieves Percent for Positive Input	User-Defined Fields
MLT PRO RECHUTE	ACT TR VA H	ABS FM HEURES	ABS VR MAINT %1	Field 1: ATRV1
	ACT TR DE H	ABS VR HR DED	ABS VR MAINT %1	Field 2: ATRCH
	ACT TR VA JO	ABS FM JRS OUV	ABS VR MAINT %1	Field 3: 1
	ACT TR DE JO	ABS VR JO DED		
	ACT TR VA JC	ABS FM JRS CAL		
	ACT TR DE JC	ABS VR JC DED		
MLT PRO RECH2	ACT TR VA H	ABS FM HEURES	ABS VR MAINT %2	Field 1: ATRV2
	ACT TR DE H	ABS VR HR DED	ABS VR MAINT %2	Field 2: ATRCH
	ACT TR VA JO	ABS FM JRS OUV	ABS VR MAINT %2	
	ACT TR DE JO	ABS VR JO DED		
	ACT TR VA JC	ABS FM JRS CAL		
	ACT TR DE JC	ABS VR JC DED		
MLT PRO RECH3	ACT TR VA H	ABS FM HEURES	ABS VR MAINT %3	Field 1: ATRV3
	ACT TR DE H	ABS VR HR DED	ABS VR MAINT %3	Field 2: ATRCH
	ACT TR VA JO	ABS FM JRS OUV	ABS VR MAINT %3	
	ACT TR DE JO	ABS VR JO DED		
	ACT TR VA JC	ABS FM JRS CAL		
	ACT TR DE JC	ABS VR JC DED		
MLT PRO RECH4	ACT TR VA H	ABS FM HEURES	ABS VR MAINT %4	Field 1: ATRV4
	ACT TR DE H	ABS VR HR DED	ABS VR MAINT %4	Field 2: ATRCH
	ACT TR VA JO	ABS FM JRS OUV	ABS VR MAINT %4	Field 3: DER
	ACT TR DE JO	ABS VR JO DED		
	ACT TR VA JC	ABS FM JRS CAL		
	ACT TR DE JC	ABS VR JC DED		
ATT TRAV IJ	ATR DED IJ 1	DAY COUNT PD	None	Field 1: ATIJ1
ATT TRAV IJ2	ATR DED IJ 2	DAY COUNT PD	None	Field 1: DERN
ATT TRV IJ RECH1	ATR DED IJR1	DAY COUNT PD	None	Field 1: ATRC1
ATT TRV IJ RECH2	ATR DED IJR2	DAY COUNT PD	None	Field 1: DERN

Elements for Paid Vacation

Take Element / Paid Vacation	Earning / Deduction Elements	Element that Retrieves Units for Positive Input	Element that Retrieves Percent for Positive Input	User-Defined Fields
CPT ANCIENTE	CP VAL A J CP DED A	DAY COUNT PD DAY COUNT PD	None	Field 2: CP
CPT AUTRES	CP DED A CP VAL A J	DAY COUNT PD DAY COUNT PD	None	Field 2: CP
CPT CG ANTICIP	CP DED 1A CP VAL 1AJ	CPA VR J A+1 CPA VR J A+1	None	Field 2: CP
CPT CG PAYES	CP DED A2 CP VAL A2J CP REG SA A2 CP DED A1 CP VAL A1J CP REG SA A1 CP DED A CP VAL A CP REG SA A	CPA VR J A-2 CPA VR J A-2 CPA VR J A-2 CPA VR J A-1 CPA VR J A-1 CPA VR J A-1 CPA VR J A CPA VR J A CPA VR J A	None	Field 2: CP
CPT FRACTMT	CP VAL A J CP DED A	DAY COUNT PD DAY COUNT PD	None	Field 2: CP

Elements for Family Events

Take Element / Family Events	Earning / Deduction Elements	Element that Retrieves Units for Positive Input	Element that Retrieves Percent for Positive Input	User-Defined Fields
EVT ALLAITEMENT	ALL RET JC ALL VAL JC ALL RET JO ALL VAL JO ALL RET H ALL VAL H	ABS VR JC DED ABD FM GEN JC ABS VR JO DED ABS FM GEN JO ABS VR HR DED ABS FM GEN HRS	None	Field 1: ALLAI Field 2: EVF Field 3: 1DER

Take Element / Family Events	Earning / Deduction Elements	Element that Retrieves Units for Positive Input	Element that Retrieves Percent for Positive Input	User-Defined Fields
EVT DEC BEAUX PARE	CPE VAL D H CPE RET D H CPE VAL D JO CPE RET D JO CPE VAL D JC CPE RET D JC	ABS FM GEN HRS ABS VR HR DED ABS FM GEN JO ABS VR JO DED ABS FM GEN JC ABS VR JC DED	None	Field 2: EVF Field 3: 1DER
EVT DEC COLLATERAU	CPE VAL D H CPE RET D H CPE VAL D JO CPE RET D JO CPE VAL D JC CPE RET D JC	ABS FM GEN HRS ABS VR HR DED ABS FM GEN JO ABS VR JO DED ABS FM GEN JC ABS VR JC DED	None	Field 2: EVF Field 3: 1DER
EVT DEC CONJOINT	CPE VAL D H CPE RET D H CPE VAL D JO CPE RET D JO CPE VAL D JC CPE RET D JC	ABS FM GEN HRS ABS VR HR DED ABS FM GEN JO ABS VR JO DED ABS FM GEN JC ABS VR JC DED	None	Field 2: EVF Field 3: 1DER
EVT DEC ENFANT	CPE VAL D H CPE RET D H CPE VAL D JO CPE RET D JO CPE VAL D JC CPE RET D JC	ABS FM GEN HRS ABS VR HR DED ABS FM GEN JO ABS VR JO DED ABS FM GEN JC ABS VR JC DED	None	Field 2: EVF Field 3: 1DER

Take Element / Family Events	Earning / Deduction Elements	Element that Retrieves Units for Positive Input	Element that Retrieves Percent for Positive Input	User-Defined Fields
EVT DEC PARENT	CPE VAL D H CPE RET D H CPE VAL D JO CPE RET D JO CPE VAL D JC CPE RET D JC	ABS FM GEN HRS ABS VR HR DED ABS FM GEN JO ABS VR JO DED ABS FM GEN JC ABS VR JC DED	None	Field 2: EVF Field 3: 1DER
EVT DEMENAGEMENT	CPE VAL DM H CPE RET DM H CPE VAL DM J CPE RET DM J CPE VL DM JC CPE RT DM JC	ABS FM GEN HRS ABS VR HR DED ABS FM GEN JO ABS VR JO DED ABS FM GEN JC ABS VR JC DED	None	Field 1: DEMEN Field 2: EVF Field 3: 1DER
EVT ENF MAL	CPE RET E H CPE RET E JO CPE RET E JC	ABS VR HR S SOLDE ABS VR JO S SOLDE ABS VR JC S SOLDE	None	Field 2: EVF Field 3: 1DER
EVT ENF MAL AFB	CPE VAL E H CPE RET E H CPE VAL E JO CPE RET E JO CPE VAL E JC CPE RET E JC	ABS FM GEN HRS ABS VR HR DED ABS FM GEN JO ABS VR JO DED ABS FM GEN JC ABS VR JC DED	None	Field 1: EM Field 2: EVF Field 3: 1DER
EVT MAR ENF	CPE VAL M H CPE RET M H CPE VAL M JO CPE RET M JO CPE VAL M JC CPE RET M JC	ABS FM GEN HRS ABS VR HR DED ABS FM GEN JO ABS VR JO DED ABS FM GEN JC ABS VR JC DED	None	Field 2: EVF Field 3: 1DER

Take Element / Family Events	Earning / Deduction Elements	Element that Retrieves Units for Positive Input	Element that Retrieves Percent for Positive Input	User-Defined Fields
EVT MAR SAL	CPE VAL M H CPE RET M H CPE VAL M JO CPE RET M JO CPE VAL M JC CPE RET M JC	ABS FM GEN HRS ABS VR HR DED ABS FM GEN JO ABS VR JO DED ABS FM GEN JC ABS VR JC DED	None	Field 2: EVF Field 3: 1DER
EVT NAIS/ADOP	CPE VAL N H CPE RET N H CPE VAL N JO CPE RET N JO CPE VAL N JC CPE RET N JC	ABS FM GEN HRS ABS VR HR DED ABS FM GEN JO ABS VR JO DED ABS FM GEN JC ABS VR JC DED	None	Field 2: ADOPT Field 3: 1DER

Elements for Illness Absence

Element / Illness	Earning / Deduction Elements	Element that Retrieves Units for Positive Input	Element that Retrieves Percent for Positive Input	User-Defined Fields
MLT MALADIE	MAL VAL H MAL DED H MAL VAL JO MAL DED JO MAL VAL JC MAL DED JC	ABS FM HEURES ABS VR HR DED ABS FM JRS OUV ABS VR JO DED ABS FM JRS CAL ABS VR JC DED	ABS VR MAINT %1 ABS VR MAINT %1 ABS VR MAINT %1	Field 1: MAL1 Field 2: MAL Field 3: 1
MLT MALADIE 2	MAL VAL H MAL DED H MAL VAL JO MAL DED JO MAL VAL JC MAL DED JC	ABS FM HEURES ABS VR HR DED ABS FM JRS OUV ABS VR JO DED ABS FM JRS CAL ABS VR JC DED	ABS VR MAINT %2 ABS VR MAINT %2 ABS VR MAINT %2	Field 1: MAL2 Field 2: MAL

<i>Element / Illness</i>	<i>Earning / Deduction Elements</i>	<i>Element that Retrieves Units for Positive Input</i>	<i>Element that Retrieves Percent for Positive Input</i>	<i>User-Defined Fields</i>
MLT MALADIE 3	MAL VAL H	ABS FM HEURES	ABS VR MAINT %3	<i>Field 1:</i> MAL3
	MAL DED H	ABS VR HR DED	ABS VR MAINT %3	<i>Field 2:</i> MAL
	MAL VAL JO	ABS FM JRS OUV	ABS VR MAINT %3	
	MAL DED JO	ABS VR JO DED		
	MAL VAL JC	ABS FM JRS CAL		
	MAL DED JC	ABS VR JC DED		
MLT MALADIE 4	MAL VAL H	ABS FM HEURES	ABS VR MAINT %4	<i>Field 1:</i> MAL4
	MAL DED H	ABS VR HR DED	ABS VR MAINT %4	<i>Field 2:</i> MAL
	MAL VAL JO	ABS FM JRS OUV	ABS VR MAINT %4	<i>Field 3:</i> DER
	MAL DED JO	ABS VR JO DED		
	MAL VAL JC	ABS FM JRS CAL		
	MAL DED JC	ABS VR JC DED		
MLT LG MALADIE	MAL VAL H	ABS FM HEURES	ABS VR MAINT %1	<i>Field 1:</i> LGM1
	MAL DED H	ABS VR HR DED	ABS VR MAINT %1	<i>Field 2:</i> MAL
	MAL VAL JO	ABS FM JRS OUV	ABS VR MAINT %1	<i>Field 3:</i> 1
	MAL DED JO	ABS VR JO DED		
	MAL VAL JC	ABS FM JRS CAL		
	MAL DED JC	ABS VR JC DED		
MLT LG MALAD2	MAL VAL H	ABS FM HEURES	ABS VR MAINT %2	<i>Field 1:</i> LGM2
	MAL DED H	ABS VR HR DED	ABS VR MAINT %2	<i>Field 2:</i> MAL
	MAL VAL JO	ABS FM JRS OUV	ABS VR MAINT %2	<i>Field 3:</i> DER
	MAL DED JO	ABS VR JO DED		
	MAL VAL JC	ABS FM JRS CAL		
	MAL DED JC	ABS VR JC DED		
MLT MT THERP IJ	MAL THERP IJ	DAY COUNT PD	None	IJ1

<i>Element / Illness</i>	<i>Earning / Deduction Elements</i>	<i>Element that Retrieves Units for Positive Input</i>	<i>Element that Retrieves Percent for Positive Input</i>	<i>User-Defined Fields</i>
MLT MT THERP	MAL VAL H	ABS FM HEURES	ABS VR MAINT %1	<i>Field 1:</i> MAL1
	MAL DED H	ABS VR HR DED	ABS VR MAINT %1	<i>Field 2:</i> THERP
	MAL VAL JO	ABS FM JRS OUV	ABS VR MAINT %1	<i>Field 3:</i> 1
	MAL DED JO	ABS VR JO DED		
	MAL VAL JC	ABS FM JRS CAL		
	MAL DED JC	ABS VR JC DED		
MLT MT THRP2	MAL VAL H	ABS FM HEURES	ABS VR MAINT %2	<i>Field 1:</i> MAL2
	MAL DED H	ABS VR HR DED	ABS VR MAINT %2	<i>Field 2:</i> THERP
	MAL VAL JO	ABS FM JRS OUV	ABS VR MAINT %2	
	MAL DED JO	ABS VR JO DED		
	MAL VAL JC	ABS FM JRS CAL		
	MAL DED JC	ABS VR JC DED		
MLT MT THRP3	MAL VAL H	ABS FM HEURES	ABS VR MAINT %3	<i>Field 1:</i> MAL3
	MAL DED H	ABS VR HR DED	ABS VR MAINT %3	<i>Field 2:</i> THERP
	MAL VAL JO	ABS FM JRS OUV	ABS VR MAINT %3	
	MAL DED JO	ABS VR JO DED		
	MAL VAL JC	ABS FM JRS CAL		
	MAL DED JC	ABS VR JC DED		
MLT MT THRP4	MAL VAL H	ABS FM HEURES	ABS VR MAINT %4	<i>Field 1:</i> MAL4
	MAL DED H	ABS VR HR DED	ABS VR MAINT %4	<i>Field 2:</i> THERP
	MAL VAL JO	ABS FM JRS OUV	ABS VR MAINT %4	<i>Field 3:</i> DER
	MAL DED JO	ABS VR JO DED		
	MAL VAL JC	ABS FM JRS CAL		
	MAL DED JC	ABS VR JC DED		
MLT THER N P	CSS RET H	ABS VR HR S SOLDE	None	<i>Field 2:</i> THERP <i>Field 3:</i> 1DER

<i>Element / Illness</i>	<i>Earning / Deduction Elements</i>	<i>Element that Retrieves Units for Positive Input</i>	<i>Element that Retrieves Percent for Positive Input</i>	<i>User-Defined Fields</i>
MLT CURE PAYEE	MAL VAL H	ABS FM HEURES	ABS VR MAINT %1	<i>Field 1:</i> MAL1
	MAL DED H	ABS VR HR DED	ABS VR MAINT %1	<i>Field 2:</i> MAL
	MAL VAL JO	ABS FM JRS OUV	ABS VR MAINT %1	
	MAL DED JO	ABS VR JO DED		
	MAL VAL JC	ABS FM JRS CAL		
	MAL DED JC	ABS VR JC DED		
MLT CURE PAY2	MAL VAL H	ABS FM HEURES	ABS VR MAINT %2	<i>Field 1:</i> MAL2
	MAL DED H	ABS VR HR DED	ABS VR MAINT %2	<i>Field 2:</i> MAL
	MAL VAL JO	ABS FM JRS OUV	ABS VR MAINT %2	<i>Field 3:</i> 1
	MAL DED JO	ABS VR JO DED		
	MAL VAL JC	ABS FM JRS CAL		
	MAL DED JC	ABS VR JC DED		
MLT CURE PAY3	MAL VAL H	ABS FM HEURES	ABS VR MAINT %3	<i>Field 1:</i> MAL3
	MAL DED H	ABS VR HR DED	ABS VR MAINT %3	<i>Field 2:</i> MAL
	MAL VAL JO	ABS FM JRS OUV	ABS VR MAINT %3	
	MAL DED JO	ABS VR JO DED		
	MAL VAL JC	ABS FM JRS CAL		
	MAL DED JC	ABS VR JC DED		
MLT CURE PAY4	MAL VAL H	ABS FM HEURES	ABS VR MAINT %4	<i>Field 1:</i> MAL4
	MAL DED H	ABS VR HR DED	ABS VR MAINT %4	<i>Field 2:</i> MAL
	MAL VAL JO	ABS FM JRS OUV	ABS VR MAINT %4	<i>Field 3:</i> DER
	MAL DED JO	ABS VR JO DED		
	MAL VAL JC	ABS FM JRS CAL		
	MAL DED JC	ABS VR JC DED		
MLT CURE NP	MAL DED H	ABS VR HR DED	None	<i>Field 2:</i> MAL
	MAL DED JO	ABS VR JO DED		<i>Field 3:</i> 1DER
	MAL DED JC	ABS VR JC DED		
MLT MAL IJSS	MAL DED IJ 1	DAY COUNT PD	None	<i>Field 1:</i> IJ1 <i>Field 2:</i> MAL

Element / Illness	Earning / Deduction Elements	Element that Retrieves Units for Positive Input	Element that Retrieves Percent for Positive Input	User-Defined Fields
MLT MAL IJ2	MAL DED IJ 2	DAY COUNT PD	None	Field 1:IJ2 Field 2:MAL
MLT MAL IJ3	MAL DED IJ3	DAY COUNT PD	None	Field 1:DERN Field 2:MAL
MLT LG MAL IJ	MAL DED LGM	DAY COUNT PD	None	Field 1:LGIJ Field 2:MAL
MLT CURE IJSS	CUR DED IJSS	DAY COUNT PD	ABS VR MAINT %1	Field 1:IJCR

Elements for Maternity Absence

Take Element / Maternity	Earning / Deduction Elements	Element that Retrieves Units for Positive Input	Element that Retrieves Percent for Positive Input	User-Defined Fields
MTT MATERN PAYEE	MAT VAL H	ABS FM HEURES	None	Field 1:MAT1
	MAT DED H	ABS VR HR DED		Field 2:MAT
	MAT VAL JO	ABS FM JRS OUV		Field 3:1DER
	MAT DED JO	ABS VR JO DED		
	MAT VAL JC	ABS FM JRS CAL		
	MAT DED JC	ABS VR JC DED		
MTT MATERN NON PAY	MAT DED H	ABS VR HR S SOLDE	None	Field 1:MAT1
	MAT DED JO	ABS VR JO S SOLDE		Field 2:MAT
	MAT DED JC	ABS VR JC S SOLDE		Field 3:1DER
MTT PATERNITE	PAT VAL H	ABS FM HEURES	None	Field 1:MAT1
	PAT DED H	ABS VR HR DED		Field 2:PATER
	PAT VAL JO	ABS FM JRS OUV		Field 3:1DER
	PAT DED JO	ABS VR JO DED		
	PAT VAL JC	ABS FM JRS CA		
	PAT DED JC	ABS VR JC DED		

Take Element / Maternity	Earning / Deduction Elements	Element that Retrieves Units for Positive Input	Element that Retrieves Percent for Positive Input	User-Defined Fields
MTT ADOPTION	MAT VAL H	ABS FM HEURES	ABS VR MAINT %1	Field 2:ADOPT
	MAT DED H	ABS VR HR DED	ABS VR MAINT %1	Field 3:1DER
	MAT VAL JO	ABS FM JRS OUV	ABS VR MAINT %1	
	MAT DED JO	ABS VR JO DED		
	MAT VAL JC	ABS FM JRS CAL		
	MAT DED JC	ABS VR JC DED		
MTT ADOPT NON PAY	MAT DED H	ABS VR HR S SOLDE	None	ADOPT
	MAT DED JO	ABS VR JO S SOLDE		1DER
	MAT DED JC	ABS VR JC S SOLDE		
MTT CG SUP	MAT VAL H	ABS FM HEURES	ABS VR MAINT %1	Field 1:MAT1
	MAT DED H	ABS VR HR DED	ABS VR MAINT %1	Field 2:MTSUP
	MAT VAL JO	ABS FM JRS OUV	ABS VR MAINT %1	Field 3: 1
	MAT DED JO	ABS VR JO DED		
	MAT VAL JC	ABS FM JRS CAL		
	MAT DED JC	ABS VR JC DED		
MTT CG SUP2	MAT VAL H	ABS FM HEURES	ABS VR MAINT %2	Field 1:MAT2
	MAT DED H	ABS VR HR DED	ABS VR MAINT %2	Field 2:MTSUP
	MAT VAL JO	ABS FM JRS OUV	ABS VR MAINT %2	Field 3:DER
	MAT DED JO	ABS VR JO DED		
	MAT VAL JC	ABS FM JRS CAL		
	MAT DED JC	ABS VR JC DED		
MTT MATERN IJSS	MAT DED IJSS	DAY COUNT	None	Field 1: DERN
MTT PATHO AV	MAL VAL H	ABS FM HEURES	ABS VR MAINT %1	Field 1:MAL1
	MAL DED H	ABS VR HR DED	ABS VR MAINT %1	Field 2:MAL
	MAL VAL JO	ABS FM JRS OUV	ABS VR MAINT %1	Field 3:1
	MAL DED JO	ABS VR JO DED		
	MAL VAL JC	ABS FM JRS CAL		
	MAL DED JC	ABS VR JC DED		

Take Element / Maternity	Earning / Deduction Elements	Element that Retrieves Units for Positive Input	Element that Retrieves Percent for Positive Input	User-Defined Fields
MTT PATHO AV 2	MAL VAL H	ABS FM HEURES	ABS VR MAINT %2	Field 1: MAL2
	MAL DED H	ABS VR HR DED	ABS VR MAINT %2	Field 2: MAL
	MAL VAL JO	ABS FM JRS OUV	ABS VR MAINT %2	
	MAL DED JO	ABS VR JO DED		
	MAL VAL JC	ABS FM JRS CAL		
	MAL DED JC	ABS VR JC DED		
MTT PATHO AV 3	MAL VAL H	ABS FM HEURES	ABS VR MAINT %3	Field 1: MAL3
	MAL DED H	ABS VR HR DED	ABS VR MAINT %3	Field 2: MAL
	MAL VAL JO	ABS FM JRS OUV	ABS VR MAINT %3	
	MAL DED JO	ABS VR JO DED		
	MAL VAL JC	ABS FM JRS CAL		
	MAL DED JC	ABS VR JC DED		
MTT PATHO AV 4	MAL VAL H	ABS FM HEURES	ABS VR MAINT %4	Field 1: MAL4
	MAL DED H	ABS VR HR DED	ABS VR MAINT %4	Field 2: MAL
	MAL VAL JO	ABS FM JRS OUV	ABS VR MAINT %4	Field 3: DER
	MAL DED JO	ABS VR JO DED		
	MAL VAL JC	ABS FM JRS CAL		
	MAL DED JC	ABS VR JC DED		
MTT PATHOLOGIQ	MAL VAL H	ABS FM HEURES	ABS VR MAINT %1	Field 1: MAL1
	MAL DED H	ABS VR HR DED	ABS VR MAINT %1	Field 2: MAL
	MAL VAL JO	ABS FM JRS OUV	ABS VR MAINT %1	Field 3: 1
	MAL DED JO	ABS VR JO DED		
	MAL VAL JC	ABS FM JRS CAL		
	MAL DED JC	ABS VR JC DED		

Take Element / Maternity	Earning / Deduction Elements	Element that Retrieves Units for Positive Input	Element that Retrieves Percent for Positive Input	User-Defined Fields
MTT PATHOLOGIQ2	MAL VAL H	ABS FM HEURES	ABS VR MAINT %2	Field 1: MAL2
	MAL DED H	ABS VR HR DED	ABS VR MAINT %2	Field 2: MAL
	MAL VAL JO	ABS FM JRS OUV	ABS VR MAINT %2	
	MAL DED JO	ABS VR JO DED		
	MAL VAL JC	ABS FM JRS CAL		
	MAL DED JC	ABS VR JC DED		
MTT PATHOLOGIQ3	MAL VAL H	ABS FM HEURES	ABS VR MAINT %3	Field 1: MAL3
	MAL DED H	ABS VR HR DED	ABS VR MAINT %3	Field 2: MAL
	MAL VAL JO	ABS FM JRS OUV	ABS VR MAINT %3	
	MAL DED JO	ABS VR JO DED		
	MAL VAL JC	ABS FM JRS CAL		
	MAL DED JC	ABS VR JC DED		
MTT PATHOLOGIQ4	MAL VAL H	ABS FM HEURES	ABS VR MAINT %4	Field 1: MAL4
	MAL DED H	ABS VR HR DED	ABS VR MAINT %4	Field 2: MAL
	MAL VAL JO	ABS FM JRS OUV	ABS VR MAINT %4	Field 3: DER
	MAL DED JO	ABS VR JO DED		
	MAL VAL JC	ABS FM JRS CAL		
	MAL DED JC	ABS VR JC DED		
MTT PATHO IJ AV	MAT DED IJSS	DAY COUNT	None	Field 1: DERN
MTT PATHO IJ AP1	MAL DED IJ 1	DAY COUNT PD	None	

Elements for Staff Representative Absence

Take Element / Staff Represent.	Earning / Deduction Elements	Element that Retrieves Units for Positive Input	Element that Retrieves Percent for Positive Input	User-Defined Fields
REP CE	RPP RET H	DAY COUNT	None	Field 1: DL
	RPP VAL H	DAY COUNT PD		Field 2: REP
	RPP VAL RG H	DAY COUNT UNP		Field 3: 1DER
REP CE SS DT	RPP RET H	DAY COUNT	None	Field 2: REP
	RPP VAL H	DAY COUNT		Field 3: 1DER

Take Element / Staff Represent.	Earning / Deduction Elements	Element that Retrieves Units for Positive Input	Element that Retrieves Percent for Positive Input	User-Defined Fields
REP CHSCT	RPP RET H	DAY COUNT	None	<i>Field 1: DL</i>
	RPP VAL H	DAY COUNT PD		<i>Field 2: REP</i>
	RPP VAL RG H	DAY COUNT UNP		<i>Field 3: 1DER</i>
REP DEL SYNDICAL	RPP RET H	DAY COUNT	None	<i>Field 1: DL</i>
	RPP VAL H	DAY COUNT PD		<i>Field 2: REP</i>
	RPP VAL RG H	DAY COUNT UNP		<i>Field 3: 1DER</i>
REP DELEGUE PERSON	RPP RET H	DAY COUNT	None	<i>Field 1: DL</i>
	RPP VAL H	DAY COUNT PD		<i>Field 2: REP</i>
	RPP VAL RG H	DAY COUNT UNP		<i>Field 3: 1DER</i>

Entering Absences

This section discusses how to:

- Enter absences due to illness.
- Enter absences due to work accidents.
- Enter absences due to a relapse.
- Enter absences for pathological leave.
- Enter absences for maternity and adoption.
- Enter absences that occur during public holidays.
- Enter absences for anticipated paid vacation.
- Enter absences that require manager approval.
- Select the half day box.

Note: Enter all absences on the Absence Event Entry component, as described in the *PeopleSoft Global Payroll*. This section provides additional instructions that are specific to France.

Pages Used to Enter Absences

Page Name	Definition Name	Navigation	Usage
Absence Event Entry	GP_ABS_EVENT	Global Payroll & Absence Mgmt, Payee Data, Maintain Absences, Absence Event, Absence Event Entry	Enter, update, and void absences. Start the Absence Forecasting process.
Absence Event Input Detail	GP_ABS_EVENT_SEC	Click the Details link on the Absence Event Entry page.	Enter detailed information for an absence, including the reason, processing action, manager approval, user-defined data, entitlement adjustment, and partial hours.

Related Links

"Understanding Processing Elements (*PeopleSoft HCM 9.2: Global Payroll*)"

"Understanding Generic Reports (*PeopleSoft HCM 9.2: Global Payroll*)"

Entering Absences Due to Illness

When you enter an absence due to illness, always select MLT MALADIE as the take element and enter the begin and end dates for the entire absence event. The system automatically does the following:

- Triggers the calculation of the daily social security allowance. (It does this by creating a second absence take using MLT MAL IJSS for each paid absence day.)
- When the entitlement balance is depleted, uses the entitlement balance for the next illness take element in the sequence (MLT MALADIE 2, MLT MALADIE 3, then MLT MALADIE 4).

When IJSS Allowance is Not Paid

If social security does not pay the IJSS allowance to the payee, do one of the following:

- Use the take element for unpaid authorized absences, ABT AUT N PAYEE, to record the absence.
- Use the take element for illness, MLT MALADIE, and the system creates a deduction for the absence, but does not create an earning.

The advantage of the second solution is that the payslip shows the true reason for the absence—that is, illness—whereas the other take only identifies the absence as authorized and unpaid.

If you uphold a payee's salary and are later informed of the non-payment of IJSS, you can change the reason for the absence. This triggers retroactive processing the next time that you run the absence process.

Related Links

[Absence Elements for Illness](#)

Entering Absences Due to Work Accidents

When you enter an absence due to a work accident, always select ATT TRAVAIL as the take element and enter the begin and end dates for the entire absence event. The system automatically does the following:

- Triggers the calculation of the daily social security allowance. (It does this by creating a second absence take using ATT TRAV IJ for each paid absence day.)
- When the entitlement balance is depleted, uses the entitlement balance for the next take element in the sequence (ATT TRAVAIL 2, ATT TRAVAIL 3, then ATT TRAVAIL 4).

For accidents on the way to work, always select ATT TRAJET as the take when entering the absence and enter the begin and end dates for the entire absence event. The system automatically does the following:

- Triggers the calculation of the daily social security allowance. (It does this by creating a second absence take using ATT TRAV IJ for each paid absence day.)
- When the entitlement balance is depleted, uses the entitlement balance for the next take element in the sequence (ATT TRAJET 2, ATT TRAJET 3, then ATT TRAJET 4).

For absences due to occupational disease, select MLT PROFESSL as the take element and enter the begin and end dates for the entire absence. The system automatically does the following:

- Triggers the calculation of the daily social security allowance. (It does this by creating a second absence take using ATT TRAV IJ for each paid absence day.)
- When the entitlement balance is depleted, uses the entitlement balance for the next take element in the sequence (MLT PROFESS 2, MLT PROFESS 3, then MLT PROFESS 4).

Related Links

[Absence Elements for Work Accidents](#)

Entering Absences Due to a Relapse

Employees who suffer a relapse from a work accident, an accident on the way to work, or occupational illness may be eligible for additional entitlements for the daily allowance. The relapse may also affect the calculation of effective work days for seniority and paid vacation calculations. Use the absence take elements designed specifically for relapses to record these absences.

For a relapse related to a work accident, use the take element ATT RECHUTE TRAV. The system automatically does the following:

- Triggers the calculation of the daily social security allowance. (It does this by creating a second absence take using ATT TRV IJ RECH1 for each paid absence day.)
- When the entitlement balance is depleted, uses the entitlement balance for the next take elements in the sequence (ATT RECHUT TR2, ATT RECHUT TR 3, then ATT RECHUT TR 4).

For a relapse related to an accident on the way to work, use the take element ATT RECHUTE TRAJ. The system automatically does the following:

- Triggers the calculation of the daily social security allowance. (It does this by creating a second absence take using ATT TRV IJ RECH1 for each paid absence day.)

- When the entitlement balance is depleted, uses the entitlement balance for the next take element in the sequence (ATT RECHUT TJ2, ATT RECHUT TJ 3, then ATT RECHUT TJ 4).

For a relapse related to an occupational disease, use the take element MLT PRO RECHUTE. The system automatically does the following:

- Triggers the calculation of the daily social security allowance. (It does this by creating a second absence take using ATT TRV IJ RECH1 for each paid absence day.)
- When the entitlement balance is depleted, uses the entitlement balance for the next take element in the sequence (MLT PRO RECH2, MLT PRO RECH 3, then MLT PRO RECH 4).

Entering Absences for Pathological Leave

Although Global Payroll for France delivers ten take elements for pathological leave, you need to use only two of these elements to record absences on the Absence Event Entry page:

- To record a pathological leave before maternity, use the take element MTT PATHO AV.

MTT PATHO AV is mapped to the take element MTT PATHO IJ AV, which automatically triggers the calculation of the daily social security allowance.

- To record a pathological leave after maternity, use the take element MTT PATHOLOGIQ.

MTT PATHOLOGIQ is mapped to the take element MTT PATHO IJAP1, which automatically triggers the calculation of the daily social security allowance.

Entering Absences for Maternity and Adoption

A woman who has been employed nine months or longer at the time she gives birth or adopts a child is eligible for paid maternity or adoption leave, as applicable.

Because entitlement for paid maternity or adoption leave is based on the number of children that the employee already has and whether the absence is before or after the birth, the system does not calculate entitlement automatically. Before entering the absence on the Absence Event Entry page, use the Supporting Element Overrides page to enter the correct number of calendar days to which the payee is entitled. Enter the override for the variable element ABS VR DTS MATERN (maternity) or MAT VR DTS ADOPT (adoption).

The take element you use to record a maternity or adoption leave depends on whether the payee is entitled to an IJSS allowance:

- For paid maternity or adoption leave, use MTT MATERN PAYEE or MTT ADOPTION.

Use these take elements when the payee's salary exceeds the social security ceiling. The system calculates IJSS allowances automatically.

- For unpaid maternity or adoption leave, use MTT MATERN NON PAY or MTT ADOPTION NON PAY.

Related Links

[Absence Elements for Maternity Leave](#)

Entering Absences That Occur During Public Holidays

You do not need to enter public holidays as absence events. Instead, define holidays on the Holiday Schedule page, and the system automatically takes these days into account when calculating absence take and entitlement.

If you want to differentiate between paid and unpaid holidays, use the unpaid absence take element (ABT AUT NON PAYEE), or create your own absence take rules to determine whether holidays should be paid.

Note: If a payee is absent during a period that includes a public holiday, the first absence reason is taken into account. For example, suppose that Easter falls during the period when a payee is out sick. For the payee, the Easter holiday is not compensated as a public holiday but as an illness. This is true for most absences where the payee's contract is suspended (for example, maternity and strike).

Entering Extra Days Off Before or After a Public Holiday

If you give employees paid time off (*les ponts*) on the days before or after a public holiday, use the absence take element Authorized Paid Absence (ABT AUT ABS PAYEES) to record the extra days off. These extra days off are compensated by the earning element for other paid absences (AAP VAL H).

Entering Absences for Anticipated Paid Vacation

Use the take element for anticipated paid vacation, CPT CG ANTICIP, to record an absence only if a payee has depleted the entitlement balance (CPE CG PAYES_SOLD) for the current period.

Related Links

[Absence Elements for Paid Vacation](#)

Entering Absences That Require Manager Approval

Select the Manager Approved check box on the Absence Event Entry Detail page when you enter an absence for any of the following take elements. The system processes the absence only if the check box is selected.

- ABT ADOPTION
- ABT AUT ABS PAYEES
- ABT AUT NON PAYEE
- ABT CIF NONPAYE
- ABT CONGE PARENTAL
- ABT REP COMP
- ABT SABBATIQ
- CPT ANCIENTE
- CPT AUTRES
- CPT CG ANTICIP

- CPT CG PAYES
- CPT FRACTMT
- EVT DEMENAGEMENT
- EVT MAR ENF
- EVT MAR SAL
- EVT NAIS/ADOP
- MLT CURE PAYEE
- MTT CG SUP

Selecting the Half Day Box

For some absences, it is necessary to select the Half Day check box to enter the absence event. However, the delivered absence setup does not allow you to enter two absences for the same day. Multiple entries are prohibited by the overlapping control. To change this, you must permit duplicates and prioritize each combination of absence takes that you can have on an absence day.

Half-day functionality enables the system to count half calendar days or half business days, whichever unit you use. If calculations are done in hours, the system automatically retrieves the number of hours of the day divided by two.

Note: This functionality has not been applied to any absence for which there might be either a waiting period or social security daily allowances, such as illness absences, work accident absences, and maternity. You may use the Half Day check box for these instances, but it is not a factor in rules calculation.

Use the Half Day check box for the following take elements:

- ABT AB N AUT N PAY
- ABT ADOPTION
- ABT AUT ABS PAYEES
- ABT AUT NON PAYEE
- ABT CONGE PARENTAL
- ABT GREVE
- ABT MAP CONSER
- ABT MAP DISCIPLI
- ABT PREAV N F
- ABT REP COMP
- ABT SABBATIQ

- EVT ALLAITEMENT
- EVT DEC BEAUX PARE
- EVT DEC COLLATERAU
- EVT DEC CONJOINT
- EVT DEC ENFANT
- EVT DEC PARENT
- EVT DEMENAGEMENT
- EVT ENF MAL
- EVT MAR ENF
- EVT MAR SAL
- EVT NAIS/ADOP
- EVT ENF MAL AFB

Chapter 22

Setting Up and Generating Wage Certificates

Understanding the Wage Certificates Process

Wage certificates are official *Cerfa* documents that provide proof that a payee is entitled to receive social security payments for sick leave, maternity leave, work accidents, or occupational illness. This topic describes how to generate those wage certificates.

To generate wage certificates:

1. Update the elements to be printed on the certificates, if necessary, on the Element Mapping Codes FRA page.

See [Updating Elements for Wage Certificates](#).

2. View or update any absence codes required for the certificates on the Element Group Members, List Set, and Element Group Attributes pages.

See [Maintaining Absence Codes for Wage Certificates](#).

3. Enter absences on the Absence Event Entry page.

See [Entering Absences](#).

4. Launch a process that retrieves the certificate data on the Certificates Data Retrieval page.

See [Retrieving Data for Wage Certificates](#).

5. View, add, or update the data retrieved for the certificates through the Update Ill/Mat Certifs FRA component or the Update ACC/MP Certifs FRA component, as appropriate.

See [Viewing and Updating Data for Illness and Maternity Certificates](#), [Viewing and Updating Data for Work Accidents and Occupational Illness Certificates](#).

6. Print wage certificates on the Certificates Report FRA page.

See [Printing Wage Certificates](#).

Common Elements Used to Set Up and Generate Wage Certificates

From

Displays the begin date of the period on which contributions were based.

The reference period starts three months before the month in which the absence begins. For example, if the absence begins in October 2010, the reference period is from July 2010 through September 2010, so *01/07/2010* appears in this field.

To	Displays the end date of the period on which contributions were based.
Print Requested	Indicates if the certificate has already been printed.
Printing Process	If you are ready to print the certificates, select this check box. A Launch button appears.
Launch	Select this button to access the Certificates Printing Process Details, where you can launch the printing process. If you prefer to print certificates for more than one employee at a time, navigate to the page as follows: Global Payroll France, Report, Certificates Printing Process. The Launch button appears only when you select the Printing Process check box.
Place for Signature	Displays the name of the city or other location where the certificate is signed.
Date of Signature	Displays the date that the certificate is signed.
Name	Displays the name of the person who signs the certificate on behalf of the employer.
Status of Signer	Displays the signer's position in the company: <i>Accountant, Compulsory Liquidator, Director, Manager, Managing Director, Other, Personnel Manager, or Receiver.</i>

Updating Elements for Wage Certificates

This section discusses how to update elements for wage certificates.

Page Used to Update Elements for Wage Certificates

Page Name	Definition Name	Navigation	Usage
Element Mapping Codes FRA	GPFR_ILLNESS_SETUP	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Reports, Element Mapping Codes FRA, Element Mapping Codes FRA	Update elements to be printed on wage certificates, if necessary, by mapping element types to element names.

Element Mapping Codes FRA Page

Use the Element Mapping Codes FRA page (GPFR_ILLNESS_SETUP) to update elements to be printed on wage certificates, if necessary, by mapping element types to element names.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Reports, Element Mapping Codes FRA, Element Mapping Codes FRA

Image: Element Mapping Codes FRA page

This example illustrates the fields and controls on the Element Mapping Codes FRA page. You can find definitions for the fields and controls later on this page.

PeopleSoft delivers the list of element codes that the system uses when printing certificates. Each element code is linked to an element—typically an accumulator. For example, if gross salary is required on a certificate, it is linked to the accumulator element for gross salary. Use the Element Mapping Codes FRA page to see which element a code is linked to. You can also change the linked element, when necessary.

Maintaining Absence Codes for Wage Certificates

This section provides an overview of absence codes and discusses how to:

- Insert absence takes for wage certificates.
- Maintain the list set for wage certificates.
- Assign absence codes for wage certificates.

Pages Used to Maintain Absence Codes for Wage Certificates

Page Name	Definition Name	Navigation	Usage
Element Group Members	GP_ELEMENT_GROUP	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Elements, Element Groups, Element Group Members	Insert elements into element groups.

Page Name	Definition Name	Navigation	Usage
Define List Set	GP_ELN_SET	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Elements, Define List Set	Assign element groups to an application.
Element Group Attributes	GP_ELN_SET_SEC	Click the Element Group Details button on the Define List Set page.	Enter the element and element group attribute values for a list set.

Understanding Absence Codes

When you generate payslips, attachments to payslips, and certificates for illnesses or work accidents, the system identifies the reason for a payee's absence by printing codes, rather than the names of the take elements, on the documents. You define these absence take mapping codes on the Define List Set page. The list set for this functionality is *Absence Reports*. The Absence Reports list set is based on the element group *REP EG ABS LISTE* that contains the list of absence takes that can be mapped to reports.

To display or modify absence codes used to identify absences in printed wage certificates:

1. Add newly created absence takes to the element group called *REP EG ABS LISTE* on the Element Group Members page.
2. Access the *ABSENCE REPORTS* list set on the Define List Set page and verify that the *REP EG ABS LISTE* element group is assigned to this list set.
3. Define absence codes for the new absence takes on the Element Group Attributes page to identify these absences in printed wage certificates.

Element Group Members Page

Use the Element Group Members page (GP_ELEMENT_GROUP) to insert elements into element groups.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Elements, Element Groups, Element Group Members

Image: Element Group Members page

This example illustrates the fields and controls on the Element Group Members page. You can find definitions for the fields and controls later on this page.

Element Group Name: REP EG ABS LISTE Absence Element List Owner: PS Non-Mnt

Definition Find | View All First 1 of 1 Last

*Effective Date: 01/01/2002 *Status: Active + -

*Element Group Use: Applications

Applications - Static/Dynamic

☒ Static (List of Elements)

☐ Dynamic (Where Clause)

Element Group Members Customize | Find | View 100 | First 1-5 of 102 Last

Element Type	*Element Name	Description	Application Default Sort Seq		
Abs Take	CPT CG PAYES	Paid Vacation take	1	+	-
Abs Take	CPT ANCIENTE	Seniority paid vacation days	2	+	-
Abs Take	CPT FRACTMT	Split days vacation take	3	+	-
Abs Take	CPT CG ANTICIP	Anticipated paid vacation days	4	+	-
Abs Take	CPT AUTRES	Other paid vacations	5	+	-

Version: P_8.90.00.00

For wage certificate processing, add new absence takes to the REP EG ABS LISTE element group.

Related Links

"Defining Element Groups (*PeopleSoft HCM 9.2: Global Payroll*)"

Define List Set Page

Use the Define List Set page (GP_ELN_SET) to assign element groups to an application.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Elements, Define List Set

Image: Define List Set page

This example illustrates the fields and controls on the Define List Set page. You can find definitions for the fields and controls later on this page.

Define List Set

Country: FRA France

List Set: ABSENCE REPORTS

*Description: Absence List for Reporting

*Application Country: FRA France

*Application: ABSENCE REPORT Absence Reporting

List Set Details Find | View All | First 1 of 1 Last

*Effective Date: 01/01/2002

Element Group Name	Description
REP EG ABS LISTE	Absence Element List

Create new Element Group

For wage certificate processing, verify that the REP EG ABS LISTE element group is assigned to the ABSENCE REPORTS list set. Click the Element Group Details button to access the Element Group Attributes page, where you can define the codes used to identify absences in printed wage certificates.

Related Links

"Setting Up List Sets (*PeopleSoft HCM 9.2: Global Payroll*)"

Element Group Attributes Page

Use the Element Group Attributes page (GP_ELN_SET_SEC) to enter the element and element group attribute values for a list set.

Navigation

Click the Element Group Details button on the Define List Set page.

Image: Element Group Attributes page

This example illustrates the fields and controls on the Element Group Attributes page. You can find definitions for the fields and controls later on this page.

Element Group Attributes

Country: FRA France
 List Set: ABSENCE REPORTS Absence List for Reporting
 Effective Date: 01/01/2002
 Element Group: REP EG ABS LISTE Absence Element List

Element Group Members and Attributes Customize | Find | View 100 | First 1-10 of 102 Last

Attributes | Type and Description

Element Name	Application Default Sort Seq	Pay Slip Absence Code	Annexe Absence Code	Column 6 Illness/Maternity	Column 14 Work Accident	Absence Type	DADS Absence Code	Unpaid Leave
CPT CG PAYS	1	CP	CP	COP				<input type="checkbox"/>
CPT ANCIENTE	2	AN	AN	COP				<input type="checkbox"/>
CPT FRACTMT	3	FR	FR	COP				<input type="checkbox"/>
CPT CG ANTICIP	4	CP	CP	COP				<input type="checkbox"/>
CPT AUTRES	5	CP	CP	COP				<input type="checkbox"/>
ABT AUT NON PAYEE	6	NP	NP	ABA	ABS AUT			<input checked="" type="checkbox"/>
EVT NAIS/ADOP	7	MT	MT	MAT	MAT	Maternity	13 Maternity	<input type="checkbox"/>
EVT MAR SAL	8	EF	EF	COP				<input type="checkbox"/>
EVT MAR ENF	9	EF	EF	COP				<input type="checkbox"/>
EVT DEC ENFANT	10	EF	EF	COP				<input type="checkbox"/>

If you have assigned new absence take elements to the REP EG ABS LISTE element group for wage certificate processing, define the codes used to identify these absences in printed wage certificates on the Element Group Attributes page.

Related Links

"Setting Up List Sets (*PeopleSoft HCM 9.2: Global Payroll*)"

Entering Absences

Enter all absences using the Absence Event Entry component, as described in the *PeopleSoft Global Payroll*. The "Entering Absences" topic of this book provides additional instructions that are specific to France.

Related Links

"Entering Updating, and Voiding Absence Events (*PeopleSoft HCM 9.2: Global Payroll*)"

[Entering Absences](#)

Retrieving Data for Wage Certificates

This section discusses how to:

- Retrieve data for wage certificates.
- Enter certification information.

Pages Used to Retrieve Data for Wage Certificates

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Extract Certificates Data FRA	GPFR_ILL_RNCTL	Global Payroll & Absence Mgmt, Social Security / Insurance, Extract Certificates Data FRA, Extract Certificates Data FRA	Initiate the Illness/Maternity Certificate Application Engine process (GPFR_ILL_AE). This process retrieves data for the wage certificates generated for maternity and illness leave.
Certification	GPFR_AT_CERTIF_SEC	Click the Certification by the Employer link on the Extract Certificates Data FRA page.	Enter the default information for the signature that will be generated for all certificates. If you do not complete this page, you must enter this information for each certificate before printing it.

Extract Certificates Data FRA Page

Use the Extract Certificates Data FRA page (GPFR_ILL_RNCTL) to initiate the Illness/Maternity Certificate Application Engine process (GPFR_ILL_AE).

This process retrieves data for the wage certificates generated for maternity and illness leave.

Navigation

Global Payroll & Absence Mgmt, Social Security / Insurance, Extract Certificates Data FRA, Extract Certificates Data FRA

Image: Extract Certificates Data FRA page

This example illustrates the fields and controls on the Extract Certificates Data FRA page. You can find definitions for the fields and controls later on this page.

Extract Certificates Data FRA

Run Control ID: PS [Report Manager](#) [Process Monitor](#) [Run](#)

Selection Criteria

☒ Illness/Maternity/Paternity ☒ Work Accident [Certification by the Employer](#)

Group Build

*Group ID: FRANCE France Group Build

Group As Of Date: 09/09/2006 Refinement Date: 10/09/2006 [Grp generation](#)

Beginning of Refinement period: 09/09/2006 End of the Refinement Period: 10/02/2006 [Select](#)

Retrieval	Print Requested	Employee ID	Empl Record	Name	Absence Take Element	Original Begin Date	Begin Date	End Date
<input type="checkbox"/>	<input type="checkbox"/>		0					

Illness/ Maternity/ Paternity

Select this check box if you want to generate data for wage certificates for illness, maternity, paternity, and long-term illness.

Work Accident

Select this check box if you want to generate data for wage certificates for work accidents and occupational disease.

Certification by the Employer

Click this link to access the Certification page, where you can enter the name of the person who will sign the certificate on behalf of the employer, the person's position, the name of the location where the certificate will be signed, and the date.

Group ID

Select the group for which you want to generate certificates. Define groups in HR.

Group As Of Date

If you want to rebuild the group before generating the certificates, enter the date that you want the system to use to identify group members.

Refinement Date

If you want to rebuild the group before generating the certificates, enter the refinement date here.

Grp generation (group generation)

Click this button if you want to rebuild the group before generating data for the certificates.

Beginning of the refinement period

Enter the start date of the period for which the system will search for absences.

The system looks only for absences that begin and end during the period of time you specify. That is, it looks for absences that begin on or after the date you enter in this field and end on or before the date you enter in the next field.

End of the Refinement Period

Enter the end date of the period for which the system will search for absences.

The system looks only for absences that begin and end during the period of time you specify.

Select

Click to search for payees that meet your selection criteria. The system displays matching payees in the Select Result section of the page.

Select Result

Retrieval

Select if you want the system to retrieve data for the payee named to the right. The check box is selected automatically if data for this absence has not been retrieved before.

Print Requested

Indicates whether a certificate has been printed for the absence. This check box is selected automatically if a certificate has been printed.

Absence Take Element

Displays the absence take element for the absence. This is absence code that was selected on the Absence Event Entry page.

Begin Date

Displays the begin date of the absence as entered on the Absence Event Entry page.

End Date

Displays the end date of the absence as entered on the Absence Event Entry page.

Certification Page

Use the Certification page (GPFR_AT_CERTIF_SEC) to enter the default information for the signature that will be generated for all certificates.

If you do not complete this page, you must enter this information for each certificate before printing it.

Navigation

Click the Certification by the Employer link on the Extract Certificates Data FRA page.

Image: Certification page

This example illustrates the fields and controls on the Certification page. You can find definitions for the fields and controls later on this page.

The screenshot shows a web form titled "Certification". Inside the form, there are four fields: "Place for Signature:" with a text input box, "Date of Signature:" with a date input box showing "10/16/2006" and a calendar icon, "Name:" with a text input box, and "Status of Signer:" with a dropdown menu.

The information that you enter on this page appears in the Certification group boxes on the Update Ill/Mat Certifs FRA and Update ACC/MP Certifs FRA components as well as on the printed wage certificate.

Place of Signature	Select the location where the file is generated.
Date of Signature	Select the date of the signature.
Name	Enter the name of the person signing the wage certificate.
Status of Signer	Select the value that best represents the position of the person providing the signature.

Related Links

[Viewing and Updating Extracted DUCS Data Using Application Framework](#)

[Viewing and Updating Extracted DADS Data](#)

Viewing and Updating Data for Illness and Maternity Certificates

This section provides an overview of illness and maternity certificates and discusses how to:

- Update administrative information.
- Update absences information.
- Update reference salaries.
- Enter social security information.
- Enter total insurance contributions and work hours.

Pages Used to View or Update Data for Illness and Maternity Certificates

Page Name	Definition Name	Navigation	Usage
Admin Information	GPFR_ILLNESS_1	Global Payroll & Absence Mgmt, Social Security / Insurance, Update Ill/Mat Certifs FRA, Admin Information	View or update the basic administrative information that will appear on certificates for illness, maternity, and paternity.
Right Study	GPFR_ILLNESS_2	Global Payroll & Absence Mgmt, Social Security / Insurance, Update Ill/Mat Certifs FRA, Right Study	View or update information about the absences due to maternity or illness. This page does not apply to long-term illness.
Reference Salaries	GPFR_ILLNESS_3	Global Payroll & Absence Mgmt, Social Security / Insurance, Update Ill/Mat Certifs FRA, Reference Salaries	View or update the reference salaries. The page displays the employee's gross pay for the last three months before the leave date. This page does not apply to long-term illness.
Subrogation	GPFR_ILLNESS_4	Global Payroll & Absence Mgmt, Social Security / Insurance, Update Ill/Mat Certifs FRA, Subrogation	Enter the information that the social security agency needs to pay the social security allowance to your organization, rather than directly to the payee.
Long-Term Illness	GPFR_ILLNESS_5	Global Payroll & Absence Mgmt, Social Security / Insurance, Update Ill/Mat Certifs FRA, Long-Term Illness	Enter the total insurance contributions and number of worked hours for a payee with a long-term illness. Use this page for long-term illnesses only.

Understanding the Illness and Maternity Certificates

The Certificate of Wages, registered under the number 11135-02, provides proof that a payee is entitled to receive social security payments for sick leave or maternity leave. Payees are entitled to these benefits if they worked the statutory minimum period during the reference period preceding the absence or if they paid the sickness contribution on the minimum number of SMIC hours.

Payees selected for this certificate are those whose absence begin date is in the specified period, and where absence begin date = original absence begin date (to avoid including relapses).

The Update Ill/Mat Certifs FRA component consists of five pages that display the data that the system retrieved when you launched the Certificates Data Retrieval process. This is the same data that is printed on the certificates. Add or update information on these pages, as needed.

The information that you enter is reflected on the certificates but does not update the Global Payroll or HR database.

The Long-Term Illness Certificate must be prepared for employees on a continuous leave of absence lasting up to 6 months. This certificate is used by the social security agency to calculate the rate for the daily allowances.

Related Links

[Understanding Absence Rules for Illness, Maternity, and Work Accidents](#)

Administrative Information Page

Use the Admin Information page (GPFR_ILLNESS_1) to view or update the basic administrative information that will appear on certificates for illness, maternity, and paternity.

Navigation

Global Payroll & Absence Mgmt, Social Security / Insurance, Update Ill/Mat Certifs FRA, Admin Information

Image: Update Ill/Mat Certifs FRA - Admin Information page

This example illustrates the fields and controls on the Update Ill/Mat Certifs FRA - Admin Information page. You can find definitions for the fields and controls later on this page.

Admin Information				
Employer				
Company:	GF8	Description:	Société Française 8	
Phone Number	01 88 88 11			
SIRET:	88888888888881	<input type="checkbox"/> Temporary Work Agency		
Employee				
National ID:	2880431864523	56	*Empl ID:	GF100ME801
First and Last Name	LEMERRE, Florence			
Job or Professional Category	GFJO03	Manager Training		
Overwritten Data Information				
<input type="checkbox"/> Data has been overwritten				

Note: You must run the Illness/Maternity Certificate Application Engine process (GPFR_ILL_AE) using the Extract Certificates Data FRA component before accessing the pages in the Update Ill/Mat Certifs FRA component.

Employer

Company

Select the company with which the employee was associated on the original date of the absence.

Phone Number

Displays the phone number for the company.

SIRET	Displays the SIRET identification number for the company.
Temporary Work Agency	Select if the employer is a temporary work agency.
Address	Click this link to access the Company Address page, which displays the address of the company that you selected.

Employee

National ID and EmplID	Displays the payee's national ID followed by the EmplID (employee ID).
First and Last Name	Displays the employee's first and last name.
Address	Click this link to access the Employee Address page, which displays the payee's address.
Job or Professional Category	Displays the employee's job or professional category.

Overwritten Data Information

Data has been overwritten	Select if you want to enter any information about the employer that differs from the information already stored in the HR (HR) database. The information only prints on the current certificate; the HR database is not updated.
----------------------------------	--

Right Study Page

Use the Right Study page (GPFR_ILLNESS_2) to view or update information about the absences due to maternity or illness.

This page does not apply to long-term illness.

Navigation

Global Payroll & Absence Mgmt, Social Security / Insurance, Update Ill/Mat Certifs FRA, Right Study

Image: Update Ill/Mat Certifs FRA - Right Study page

This example illustrates the fields and controls on the Update Ill/Mat Certifs FRA - Right Study page. You can find definitions for the fields and controls later on this page.

Last Date Worked

Enter the date of the last paid day on which the employee worked. Please note that you must enter the date yourself, it does not display by default.

Reason for Leaving

Displays the reason for the employee's absence as entered on the Absence Event Entry page: *Illness* or *Maternity*.

Situation at the Date of Leave

Enter the reason for the absence if the employee was unemployed, on vacation, in military service, or absent for some reason other than illness or maternity on the last date worked preceding the leave. Enter up to 30 characters.

Foreseen Date to Resume Work (resume work date)

Enter the date that the employee will return to work.

No Work Resumption at this Day

If the payee is has not yet returned from the absence, select this check box.

Work Resumption Partial Time

If the employee will resume work on a part-time basis, enter the reason for working part time: *Medical Reason* or *Personal Reason*.

Cases

Select a value to indicate what the contribution amount and hours are based on. *General* appears by default. Select *Particular* for seasonal workers, employees who work at home, and so on. Then enter the contribution amount and hours.

Amount of the Contribution

If *General* appears in the Case field, the amount of the contribution represents total contributions for sickness insurance, maternity insurance, disability insurance, and death insurance based on the wages earned during the six calendar months preceding the leave date.

If you select *Particular* in the Case field, enter the same information for the wages earned during the 12 preceding calendar months.

More Than 200 Worked Hours

This field appears if the Case field is set to *General*.

If the payee worked at least 200 hours during the last 3 calendar months or the last 90 consecutive days, the system automatically selects this check box and deselects the Amount of the Contribution field.

More Than 800 Worked Hours

This check box appears if you select *Particular* in the Case field. Select this check box if the payee worked more than 800 hours within the 12 calendar months or 365 consecutive days preceding the leave date.

From Date for the Period

Displays the begin date of the period of validity for the previous four fields. Typically, the period is 3, 6, or 12 months.

To

Displays the end date of the period of validity. Typically the period is 3, 6, or 12 months.

Reference Salaries Page

Use the Reference Salaries page (GPFR_ILLNESS_3) to view or update the reference salaries.

The page displays the employee's gross pay for the last three months before the leave date. This page does not apply to long-term illness.

Navigation

Global Payroll & Absence Mgmt, Social Security / Insurance, Update Ill/Mat Certifs FRA, Reference Salaries

Image: Update Ill/Mat Certifs FRA - Reference Salaries page: Base Salary tab

This example illustrates the fields and controls on the Update Ill/Mat Certifs FRA - Reference Salaries page: Base Salary tab. You can find definitions for the fields and controls later on this page.

Admin Information Right Study Reference Salaries Subrogation Long-Term Illness									
ID: GF100ME801		LEMERRE,Florence			Empl Record: 0				
Original Begin Date: 04/04/2008		Begin Date: 04/04/2008		End Date: 07/04/2008					
Reference Salary									
Customize Find View All First 1-3 of 3 Last									
Base Salary Not Full Time Period									
	From	To	Gross pay	Euro					
1	03/01/2008	03/31/2008		<input type="checkbox"/>				+	-
2	02/01/2008	02/29/2008		<input type="checkbox"/>				+	-
3	01/01/2008	01/31/2008		<input type="checkbox"/>				+	-
Regularization on past years									
<div> <div>PERIOD 1</div> <div>Amount: <input type="text"/></div> <div>Euros <input checked="" type="checkbox"/></div> <div>Reg 1 Bgn Dt: <input type="text"/></div> <div>Reg 1 End Dt: <input type="text"/></div> </div> <div> <div>PERIOD 2</div> <div>Amount: <input type="text"/></div> <div>Euros <input checked="" type="checkbox"/></div> <div>Reg 2 Bgn Dt: <input type="text"/></div> <div>Reg 2 End Dt: <input type="text"/></div> </div>									

Gross Pay

Displays the gross amount of the employee's earnings on which contributions to sickness, maternity, disability, and death insurance were based. CSG and other mandatory contributions are also deducted for maternity leave.

Euro

This check box is selected automatically if the salary is paid in euros.

Reference Salaries: Not Full Time Period Tab

Access the Not Full Time Period tab.

Image: Update Ill/Mat Certifs FRA - Reference Salaries page: Not Full Time Period tab

This example illustrates the fields and controls on the Update Ill/Mat Certifs FRA - Reference Salaries page: Not Full Time Period tab. You can find definitions for the fields and controls later on this page.

Admin Information Right Study **Reference Salaries** Subrogation Long-Term Illness

ID: GF100ME801 LEMERRE, Florence Empl Record: 0

Original Begin Date: 04/04/2008 Begin Date: 04/04/2008 End Date: 07/04/2008

Reference Salary Customize Find View All First 1-3 of 3 Last

Base Salary Not Full Time Period

	From	To	Absence Code	Worked Hours	Full Time Hours	Calculated Wage	Euro		
1	03/01/2008	03/31/2008					<input type="checkbox"/>	+	-
2	02/01/2008	02/29/2008					<input type="checkbox"/>	+	-
3	01/01/2008	01/31/2008					<input type="checkbox"/>	+	-

Regularization on past years

Euros

PERIOD 1 Amount: ☒ Reg 1 Bgn Dt: Reg 1 End Dt:

PERIOD 2 Amount: ☒ Reg 2 Bgn Dt: Reg 2 End Dt:

The Not Full Time Period tab appears data only if the payee worked part time during the reference period.

Absence Code

Displays the absence code associated with the absence.

Worked Hours

Displays the actual number of hours worked.

Full Time Hours

Displays the number of hours that the payee would have worked if able to work all of the full-time schedule.

Calculated Wage

Displays the full-time equivalent wage.

Euro

This check box is selected automatically if the salary is paid in euros.

Regularization on Past Years

Period 1 Amount

Enter an amount if you made retroactive adjustments outside of Global Payroll for France to a payee's contributions during the calendar year that precedes the reference period indicated in the Bgn Dt and End Dt fields. The system does not populate this field.

Do not enter the amount of retroactive adjustments that were made by Global Payroll for France. When Global Payroll for France calculates contribution amounts each month, it automatically adds or subtracts any retroactive adjustments, as applicable. Thus, the current period contributions already reflect any retro adjustments that may have been made.

Period 2 Amount

Enter the retroactive amount applicable to period 2, which is the calendar year that began two years before the reference period indicated in the Bgn Dt and End Dt fields. The system does not populate this field.

Subrogation Page

Use the Subrogation page (GPFR_ILLNESS_4) to enter the information that the social security agency needs to pay the social security allowance to your organization, rather than directly to the payee.

Navigation

Global Payroll & Absence Mgmt, Social Security / Insurance, Update Ill/Mat Certifs FRA, Subrogation

Image: Update Ill/Mat Certifs FRA - Subrogation page

This example illustrates the fields and controls on the Update Ill/Mat Certifs FRA - Subrogation page. You can find definitions for the fields and controls later on this page.

Admin Information	Right Study	Reference Salaries	Subrogation	Long-Term Illness
ID: GF100ME801		LEMERRE,Florence		Empl Record: 0
Original Begin Date: 04/04/2008		Begin Date: 04/04/2008		End Date: 07/04/2008
Subrogation				
Beginning of the Subrogation:		<input type="text"/>	To:	<input type="text"/>
Account of the employer				
Bank ID:		<input type="text"/>	Bank Branch ID:	<input type="text"/>
Account Nbr:		<input type="text"/>	Check Digit:	<input type="text"/>
Title of the Account		<input type="text"/>		<input checked="" type="checkbox"/> Payment in Euro
Certification				
Place for Signature:		<input type="text"/>		Date of Signature: 06/16/2009
Name:		<input type="text"/>		
Status of Signer:		<input type="text"/>		
Printing Process				
<input type="checkbox"/> Print Requested		<input type="checkbox"/> Launch Printing		

Beginning of the Subrogation

Enter the begin date for which you are submitting a claim for subrogation.

To Enter the end date for which you are submitting a claim for subrogation.

Account of the employer

Bank ID Enter the bank ID that the social security agency should use to deposit the funds.

Bank Branch ID Enter the bank branch ID that the social security agency should use to deposit the funds.

Account # Enter the account number that the social security agency should use to deposit the funds.

Check Digit Enter the digit of the check that the social security agency should use to deposit the funds.

Title of the Account Enter the title of the company's bank account into which the funds are to be deposited.

Payment in Euro Select if you want to receive the allowance in euros.

Certification

The values of the fields in the Certification group box can be predefined on the Certification page, which you access by clicking the Certification by the Employer link on the Extract Certificates Data FRA page (Global Payroll & Absence Mgmt, Social Security / Insurance, Extract Certificates Data FRA, Extract Certificates Data FRA). You can also enter the certification information directly on the Subrogation page.

See [Certification Page](#).

Printing Process

Print Requested Indicates whether a certificate has been printed for the absence. This check box is selected automatically if a certificate has been printed.

Launch Printing When you select this check box, the Launch button appears. Click this button to access the Certificates Report FRA page and print the certificate.

See [Printing Wage Certificates](#).

Term Illness Page

Use the Long-Term Illness page (GPFR_ILLNESS_5) to enter the total insurance contributions and number of worked hours for a payee with a long-term illness.

Use this page for long-term illnesses only.

Navigation

Global Payroll & Absence Mgmt, Social Security / Insurance, Update Ill/Mat Certifs FRA, Long-Term Illness

Image: Update Ill/Mat Certifs FRA - Long-Term Illness page

This example illustrates the fields and controls on the Update Ill/Mat Certifs FRA - Long-Term Illness page. You can find definitions for the fields and controls later on this page.

Admin Information	Right Study	Reference Salaries	Subrogation	Long-Term Illness
ID: GF100ME801 <u>LEMERRE,Florence</u>		Empl Record: 0		
Original Begin Date: 04/04/2008		Begin Date: 04/04/2008	End Date: 07/04/2008	
Long-Term Illness				
<input type="checkbox"/> Long-Term Illness		Last Date Worked: <input type="text"/>		
Contribution Amounts				
Amount of contributions paid for the sickness, maternity, disability and death insurances:				
- based on the earnings of the employee during the 12 calendar months preceding the date of absence:		<input type="text"/>	<input checked="" type="checkbox"/> Euro	
- based on the earnings during the first 6 months of this same period:		<input type="text"/>	<input checked="" type="checkbox"/> Euro	
Number of Worked Hours				
Nbr of working hours salaried or similar during				
- The 12 calendar months or 365 days preceding the date of absence		<input type="text"/>		
- The 3 months preceding the absence		<input type="text"/>		
Printing Process				
<input type="checkbox"/> Print Requested		<input type="checkbox"/> Launch Printing		

Long Term Illness

Long Term Illness

Select if you want to prepare a certificate for a long-term illness (absences entered with the take element MLT LG MALADIE).

Last Date Worked

Enter the last day that the employee worked. Please note that you must enter the date yourself, it does not display by default.

Contribution Amounts

In this group box, enter the amount of health insurance contributions that have been deducted from the employee's earnings in either the top or bottom field, as appropriate. If the amount that you enter is in euros, select the *Euro* check box.

Number of Worked Hours

In this group box, enter the total number of paid hours that the payee worked in either the top or bottom field, as appropriate.

Viewing and Updating Data for Work Accidents and Occupational Illness Certificates

Wage certificates for the payment of a daily allowance for industrial accidents or occupational illness are printed on *Cerfa* documents registered under the number 11137-01 and published by the Ministry for Employment and Solidarity (CNAMTS).

This section discusses how to:

- Generate data for certificates.
- Display a payee's earnings.
- Update salary, upholding, apprenticeship, and lost wages information.
- Enter social security information.

See [Absence Elements for Illness](#).

Note: For payees who join or leave the company mid-year, manually enter the data necessary to produce the certificate.

Pages Used for Work Accidents and Occupational Illness Certificates

Page Name	Definition Name	Navigation	Usage
Admin Information	GPFR_ATMP_1	Global Payroll & Absence Mgmt, Social Security / Insurance, Update ACC/MP Certifs FRA, Admin Information	Generate the data needed to produce certificates for work accidents and occupational illness.
Frames A and B	GPFR_ATMP_2	Global Payroll & Absence Mgmt, Social Security / Insurance, Update ACC/MP Certifs FRA, Frames A and B	Display the payee's earnings during the reference period. This page pertains to industrial accidents and occupational illness.
Frames C and D	GPFR_ATMP_3	Global Payroll & Absence Mgmt, Social Security / Insurance, Update ACC/MP Certifs FRA, Frames C and D	Display and update information about salary upholding, apprenticeships, and lost wages for industrial accidents and occupational illness.
Subrogation and Certification	GPFR_ATMP_4	Global Payroll & Absence Mgmt, Social Security / Insurance, Update ACC/MP Certifs FRA, Subrogation and Certification	Enter the information that the social security agency needs to pay the social security allowance to your organization, rather than directly to the payee. This information applies to industrial accidents and occupational illness.

Admin Information Page

Use the Admin Information page (GPFR_ATMP_1) to generate the data needed to produce certificates for work accidents and occupational illness.

Navigation

Global Payroll & Absence Mgmt, Social Security / Insurance, Update ACC/MP Certifs FRA, Admin Information

Image: Update ACC/MP Certifs FRA - Admin Information page

This example illustrates the fields and controls on the Update ACC/MP Certifs FRA - Admin Information page. You can find definitions for the fields and controls later on this page.

Admin Information	Frames A and B	Frames C and D	Subrogation and Certification
Company Information			
Company: <input type="text" value="GF8"/>		Société Française 8 Address	
Phone Number <input type="text"/>			
Establishment			
Establishment ID: <input type="text" value="GF8AR"/>		Etbl 8 Administration Address	
SIRET: <input type="text" value="88888888888881"/>		Risk Code: <input type="text" value="881AR"/>	
Phone Number: <input type="text" value="01 88 88 11"/>			
Employee			
National ID: <input type="text" value="2610431864523"/> <input type="text" value="56"/>		Sex: <input type="text" value="Female"/> Birthdate: <input type="text" value="04/19/1961"/>	
Nationality: <input type="text" value="French"/>			
First and Last Name <input type="text" value="Florence LEMERRE"/>		Address	
First Hire Date: <input type="text" value="01/01/2000"/>		Job Code: <input type="text" value="GFJO03"/> Manager Training	
Employee Category: <input type="text" value="Manager"/>		Professional Experience Date: <input type="text"/>	
<input type="checkbox"/> Are There Other Victims ?			

Note: You must run the Illness/Maternity Certificate Application Engine process (GPFR_ILL_AE) using the Extract Certificates Data FRA component before accessing the pages in the Update ACC/MP Certifs FRA component.

Company Information

Company Displays the payee's company on the date of the accident.

Phone Number Displays the phone number for the company.

Address Click this link to access the Company Address page, which displays the address of the company that you selected.

Establishment

This group box displays information about the establishment at which the employee works, as entered in HR.

Establishment ID	Displays the establishment with which the employee was associated on the original date of the absence.
SIRET	Displays the SIRET identification number for the establishment.
Risk Code	Displays the risk code for the establishment.
Phone Number	Displays the establishment's phone number.
Address	Click this link to access the Establishment Address page, which displays the address of the establishment that you selected.

Employee

National ID	Displays the payee's national ID followed by the key.
Sex	Displays the payee's gender: <i>Female</i> , <i>Male</i> , or <i>Unknown</i> .
Birthdate	Displays the payee's date of birth.
Nationality	Displays the payee's nationality: <i>EEC Resident</i> , <i>French</i> , or <i>Other</i> .
Address	Click this link to access the Employee Address page, which displays the employee's address.
First Hire Date	Displays the date on which the employee was first hired.
Job Code	Displays the employee's job code.
Employee Category	Displays a category: <i>Executive</i> , <i>Manager</i> , or <i>Workman</i> .
Professional Experience Date	Displays the employee's years of seniority in the job.
Are There Other Victims	For work accidents, select this check box if another person was injured in the accident.

Related Links

"Defining Establishments (*PeopleSoft HCM 9.2: Application Fundamentals*)"

Frames A and B Page

Use the Frames A and B page (GPFR_ATMP_2) to display the payee's earnings during the reference period.

This page pertains to industrial accidents and occupational illness.

Navigation

Global Payroll & Absence Mgmt, Social Security / Insurance, Update ACC/MP Certifs FRA, Frames A and B

Image: Update ACC/MP Certifs FRA - Frames A and B page: Base Salary tab

This example illustrates the fields and controls on the Update ACC/MP Certifs FRA - Frames A and B page: Base Salary tab. You can find definitions for the fields and controls later on this page.

Admin Information		Frames A and B		Frames C and D		Subrogation and Certification	
ID: GF100ME802		Florence LEMERRE		Empl Record: 0			
Original Begin Date: 04/06/2008		Begin Date: 04/06/2008		End Date: 04/13/2008			
Occupational Health Data							
Name & Address: <input type="text"/>							
Stop of Work							
Date of the Accident / Illness: <input type="text"/>		Last Date Worked: <input type="text"/>					
Return Date: <input type="text"/>		<input type="checkbox"/> No Work Resumption at this Day					
Reason for Absence: <input type="text" value="Industrial Accident"/>							
Frame A: Reference Period Basic Salary and Accessories. Customize Find View All First 1 of 1 Last							
Base Salary		Salary Accessories <input type="button" value="Add"/>					
Reference Period Begin Date	Reference Period End Date	Salary Payment Date	Gross Pay A	Euro			
1 03/01/2008	03/31/2008	03/31/2008	1050.00	<input checked="" type="checkbox"/>	<input type="button" value="+"/>	<input type="button" value="-"/>	
Frame B: Back Wages & Different periods Customize Find View All First 1 of 1 Last							
Wage Period Begin Date	Wage Period End Date	Wages Payment Date	Gross Pay B	Euro	Wage Share B		
1 <input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="checkbox"/>	<input type="text"/>	<input type="button" value="+"/>	<input type="button" value="-"/>

Common Page Information

Date of the Accident/Illness

Displays the date of the accident or the first medical observation (for an occupational illness). This is the same date entered in the Original Begin Date field on the Absence Event Entry page.

Last Date Worked

Enter the last date that the payee worked. Please note that you must enter the date yourself, it does not display by default.

Return Date

Enter the date on which the payee returned to work, if applicable.

No Work Resumption at this Day

If the payee has not yet returned from the absence, select this check box.

Reason for Absence

Displays the reason for the absence as recorded on the Absence Event Entry page: *Industrial Accident* or *Occupational Illness*.

Frame A: Reference Period Basic Salary and Accessories

Frame A displays the payee's monthly gross earnings for each month.

Base Salary Tab

The base salary represents the paid and unpaid earnings during the reference period, including any wages that were upheld during this period.

Reference Period Begin Date	Displays the begin date of the earliest segment in the selected period.
Reference Period End Date	Displays the end date of the latest segment in the selected period.
Salary Payment Date	Displays the date on which the payee was paid.
Gross Pay A	Displays the employee's gross pay.
Euro	This check box is selected automatically if the salary is paid in euros.

Salary Accessories Tab

Access the Salary Accessories tab.

Image: Update ACC/MP Certifs FRA - Frames A and B page: Salary Accessories tab

This example illustrates the fields and controls on the Update ACC/MP Certifs FRA - Frames A and B page: Salary Accessories tab. You can find definitions for the fields and controls later on this page.

	Reference Period Begin Date	Reference Period End Date	Advantages in kind and Tips	Allowances	Wage Share A	Business Expenses	Percentage of Deduction		
1	03/01/2008	03/31/2008			259.420350			+	-

Reference Period Begin Date	Displays the begin date of the earliest segment in the selected period.
Reference Period End Date	Displays the end date of the latest segment in the selected period.
Advantages in Kind and Tips	Displays the benefits in kind (<i>avantages en nature</i>) and tips (<i>pourboires</i>) not included in the base gross salary.
Allowances	Displays any allowances, premiums, or gratuities not included in the base gross salary.
Wage Share A	Displays the wage share of the contributions that correspond to the gross amount declared in columns 4, 5, and 6 of the certificate.

Business Expenses	Displays the amount of previously paid business expenses that are subject to contributions (that is, that are not part of the payee's standard gross pay).
Percentage of Deduction	Displays a supplemental deduction percentage if the payee's job qualifies for an additional deduction (journalists, for example).

Frame B: Back Wages & Different Periods Wages

Frame B displays any back wages or wages that were paid to the payee at different intervals than the basic pay. For example, it might show a quarterly allowance (earned during the period from January 1 to March 31) that was paid in the March payroll.

Wage Period Begin Date	Displays the begin date of the period to which the amount in the Gross Pay B field applies.
Wage Period End Date	Displays the end date of the period to which the amount in the Gross Pay B field applies.
Wages Payment Date	Displays the date on which the payee was paid the processed gross.
Gross Pay B	Displays the gross amount of the employee's earnings.
Euro	This check box is selected automatically if the salary is paid in euros.
Wage Share B	Displays the wage share of the contributions that correspond to the gross amount declared in column 12 of the certificate.

Frames C and D Page

Use the Frames C and D page (GPFR_ATMP_3) to display and update information about salary upholding, apprenticeships, and lost wages for industrial accidents and occupational illness.

Navigation

Global Payroll & Absence Mgmt, Social Security / Insurance, Update ACC/MP Certifs FRA, Frames C and D

Image: Update ACC/MP Certifs FRA - Frames C and D page

This example illustrates the fields and controls on the Update ACC/MP Certifs FRA - Frames C and D page. You can find definitions for the fields and controls later on this page.

Space D: Particular Cases

Minimum Wage of Apprentices

If the payee is an apprentice or trainee, enter the minimum wage for the category, level, or qualified employment in which the apprentice or the trainee would normally have been classified at the end of the training period or apprenticeship.

Contract Number and Date

If the payee is an apprentice, enter the number and date of the employment contract.

Space C: Upholding the Salary

Upholding the Salary

Select this check box if you upheld the payee's salary.

Upholding

If you selected the Upholding the Salary check box, indicate the type of salary upholding: *Integral Upholding* or *Partial Upholding*.

Frame C: If the Reference Period Was Not Fully Completed

Frame C displays information only if the reference period was not completed because of the absence.

Print

Select to print the row.

Absence code

Displays the reason for the absence.

The following are valid values:

MAL: Illness.

MLD: Long-term illness.

AT: Industrial accident.

MAT: Maternity.

CHOM: Total unemployment.

FERM: Closing of establishment.

COP: Vacation pay.

ABS AUT: Authorized unpaid vacation.

SN: National service.

ABA: Authorized absence.

Other absence codes you have defined.

From

Displays the begin date of the leave.

To

Displays the end date of the leave.

Lost Wages

Displays the wages lost during the absence period, if the salary was not upheld for this absence.

Euro

This check box is selected automatically if the salary is paid in euros.

Wage Share

Displays the portion of the employee's contributions that were lost because of the leave.

Subrogation and Certification Page

Use the Subrogation and Certification page (GPFR_ATMP_4) to enter the information that the social security agency needs to pay the social security allowance to your organization, rather than directly to the payee.

This information applies to industrial accidents and occupational illness.

Navigation

Global Payroll & Absence Mgmt, Social Security / Insurance, Update ACC/MP Certifs FRA, Subrogation and Certification

Image: Update ACC/MP Certifs FRA - Subrogation and Certification page

This example illustrates the fields and controls on the Update ACC/MP Certifs FRA - Subrogation and Certification page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'Update ACC/MP Certifs FRA - Subrogation and Certification' page. At the top, there are four tabs: 'Admin Information', 'Frames A and B', 'Frames C and D', and 'Subrogation and Certification'. The 'Subrogation and Certification' tab is selected. Below the tabs, the employee information is displayed: ID: GF100ME802, Name: Florence LEMERRE, and Empl Record: 0. The dates are: Original Begin Date: 04/06/2008, Begin Date: 04/06/2008, and End Date: 04/13/2008. The 'Subrogation' section has three fields: 'Beginning of the Subrogation', 'To', and 'Upholding'. The 'Account of the employer' section has six fields: 'Bank ID', 'Bank Branch ID', 'Account Nbr', 'Check Digit', 'Title of the Account', and a checkbox for 'Payment in Euro'. The 'Certification' section has four fields: 'Place for Signature', 'Date of Signature' (06/16/2009), 'Name', and 'Status of Signer'. The 'Printing Process' section has two checkboxes: 'Print Requested' and 'Launch Printing'.

Subrogation

Beginning of the Subrogation

Enter the begin date for which you are submitting a claim for subrogation.

To

Enter the end date for which you are submitting a claim for subrogation.

Upholding

Select *Integral Upholding* or *Partial Upholding*.

Account of the employer

Bank ID

Enter the bank ID that the social security agency should use to deposit the funds.

Bank Branch ID

Enter the bank branch ID that the social security agency should use to deposit the funds.

Account # (account number)

Enter the account number that the social security agency should use to deposit the funds.

Check Digit	Enter the digit of the check that the social security agency should use to deposit the funds.
Title of the Account	Enter the title of the bank account into which the funds are to be transferred.
Payment in Euro	Select if you want to receive the allowance in euros.

Certification

The values of the fields in the Certification group box can be predefined on the Certification page, which you access by clicking the Certification by the Employer link on the Extract Certificates Data FRA page (Global Payroll & Absence Mgmt, Social Security / Insurance, Extract Certificates Data FRA, Extract Certificates Data FRA). You can also enter the certification information directly on the Subrogation and Certification page.

See [Certification Page](#).

Printing Process

Print Requested	Indicates whether a certificate has been printed for the absence. This check box is selected automatically if a certificate has been printed.
Launch Printing	When you select this check box, the Launch button appears. Click this button to access the Certificates Report FRA page and print the certificate. See Printing Wage Certificates .

Printing Wage Certificates

Once you have reviewed the employee data for the wage certificates, you can print the certificates.

Page Used to Generate Wage Certificates

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Certificates Report FRA	GPFR_ILL_AT_RNCTL	Global Payroll & Absence Mgmt, Social Security / Insurance, Certificates Report FRA, Certificates Report FRA	<p>Use this page to generate these reports:</p> <ul style="list-style-type: none"> • Work Accident/ Occupational Disease Certificate (GPFRATMP). • Illness/Maternity/ Paternity Certificate (GPFRILL). • Long-Term Illness Certificate (GPFRLT).

Related Links

[Global Payroll for France Reports: A to Z](#)

Working with Payslips

Understanding Payslip Layout

PeopleSoft supplies a payslip model, which you may redesign to fit your needs.

The payslip has three different sections:


- The payslip's header: this section usually contains payee personal information, employer name and address, and pay period dates.
- The payslip's body: this section usually contains payee and employer earnings and deduction information.
- The payslip's footer: this section usually contains accumulator information and payslip observations.

Note: Every payslip and pay annex sheet lists the current segment dates, day by day, with the hours scheduled for that day. If for some reason the payee is absent for a day, an absence code is inserted, indicating the reason for the absence.

The following graphic illustrates the sample header of a payslip:

Image: Sample header of a payslip

Header of a Payslip

	Société Française 2 6 Rue de la Colline 75001 PARIS	Calculated Bulletin de paie Paie du 01/01/2002 au 31/01/2002
	Siret 888888888 888888 Ape 110 Organisme S.S. / /	
No. S.S. 268016 254896 07 Matricule 0F100K3850 Entrée 01/01/2000 Sortie Section Department H Resource QA082R Emploi Data Analyst Echecs 151 Catégorie	<div>RODRIGUEZ, Françoise 90 Avenue des Champs 75008 Paris</div>	

The following graphic illustrates the sample body of a payslip:

Image: Sample body of a payslip

Sample body of a Payslip

Base salary				3 000,00		01 M 7300
Illness	4 000,00	6,55	42,50	12,90	194,00	03 M 7400
Sickness A Ceiling	2 352,00			8,20	192,06	04 M 7100
Sickness without ceiling - empl.	2 000,00			1,60	48,00	05 E
RNA on A ceiling - empl.	2 352,00			0,17	2,75	06 E
RNA without ceiling - empl.	2 000,00			0,47	12,00	07 M 7400
Work accident - empl.	4 000,00			1,00	10,00	08 M 7400
Tax on transportation	2 000,00			2,50	75,00	09 M 7100
Family allowance - empl.	2 000,00			5,40	162,00	10 M 7300
Widow - payee	2 000,00	0,70	7,00			11 M 7400
						12 E
AGSEDEC A Ceiling	2 352,00	2,00	47,04	3,60	84,67	13 E
AGSEDEC B-Ceiling	548,00	2,00	12,95	3,60	23,33	14 E 7300
FNIS	2 000,00			0,20	6,00	15 M 7300
AGSEDEC A4 A ceiling A-Ceiling	2 352,00	3,00	70,56	4,50	105,84	16 M 7400
AGSEDEC A4 A ceiling A-Ceiling	2 352,00	0,50	14,54	1,20	24,24	17 M 7300
AGSEDEC A4 B Ceiling	548,00	7,50	40,60	12,50	81,00	18 M 7100
AGSEDEC A4 B-Ceiling	548,00	0,90	5,83	1,30	8,42	19 E
AGSEDEC A4 B-Ceiling	548,00	0,024	0,15	0,018	0,24	20 E
CAF	4 000,00	0,14	2,90	0,22	6,80	21 E 7300
08 Contingency funds tax	35,20			8,00	2,00	22 M 7100
Hand. Conting. Contr. A4 Empl.	2 352,00			1,50	25,20	23 M 7400
						24 M 7100
Tax for educational institution	2 000,00			0,50	15,00	25 M 7300
Capital-education tax	2 000,00			0,17	7,00	26 E
Individual-educ tax	4 000,00			0,10	3,00	27 E
Employee education tax	2 000,00			0,90	27,00	28 E 7100
Sandwich course tax	2 000,00			0,40	12,00	29 M 7300
Tax on construction	2 000,00			0,45	13,50	30 M 7300
Non Taxable CRR tax	2 882,52	0,70	17,05			31 M 7400
Salary tax on bracket 1	4 000,00			4,20	167,50	32 M 7400
						33 M 7400
Taxable CRR tax	2 882,52	2,40	59,20			
CRR	2 882,52	0,00	16,42			

The following graphic illustrates the sample footer for a payslip:

Image: Sample footer of a payslip

Sample footer of a Payslip

Mode de règlement : LE 01/01/2002					NET A PAYER 2 381,99EUR	
Cotisations	Précédent	Montant	Montant	Montant	Montant	Montant
Mensuel	2 381,99	2 000,00	238,11	1 400,62	2 381,99	
Annuel	2 381,99	2 000,00	238,11	1 400,62	2 381,99	
					Montant payé	Montant
					Montant en cours	20,00
					Montant précédent	
					Montant cumulé	

Document à conserver sans limitation de durée

Related Links

[Maintaining Absence Codes for Wage Certificates](#)

Setting up Payslips

To set up payslips, use the Templates FRA (GPFR_PAY_SLIP) component.

This section provides an overview of payslip setup and discusses how to:

- Associate pay groups with payslips.
- Set up sorting methods and order.
- Determine printed information.
- Determine accumulators for payslip footer.

Pages Used to Set up Payslips

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Payslip/PayGroup	GPFR_P_SLIP_GRP	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Payslips, Templates FRA, Payslip/PayGroup	Associate pay groups with an individual payslip. Payslips must be associated with at least one pay group before they are included in a pay run.
Payslip Sort keys	GPFR_P_SLIP_SK	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Payslips, Templates FRA, Payslip Sort keys	Set up the methods and order for sorting the different payslip forms.
Payslip Lines	GPFR_PAY_SLIP_1	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Payslips, Templates FRA, Payslip Lines	Determine what is printed on each line of the body of the payslip.
Payslip Totals	GPFR_PAY_SLIP_2	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Payslips, Templates FRA, Payslip Totals	Determine which accumulators to display in the footer of the payslip form.

Understanding Payslip Setup

The payslip displays elements such as earnings, deductions, absence hours, current and year-to-date totals, as well as a daily record. When setting up the payslip, you must define which of these elements to print on the payslip and define the format of the payslip.

The payslip setup consists of:

- Assigning at least one pay group to each payslip using the Payslip/Pay Group page.
- Defining the sort-order keys that will be used to sort the payslip's forms on the Payslip Sort Keys page.

- Selecting and defining elements (earnings, deductions, and accumulators) to be printed on the payslip. You must also put the earning and deduction elements in the order in which they should appear in the body of the payslip or annex.

Do this on the Payslip Lines page.

- Selecting the elements that must have totals printed on the payslip.

Do this on the Payslip Totals page.

When you install Global Payroll for France, the default installation refers to the delivered payroll elements.

Note: By law, some information is not allowed to appear on the payslip (*bulletin de paie*). If this information is relevant to a payee, it is printed on another form, called an annex (*annexe*). You are responsible for determining which information belongs on each form.

Important! To generate a payslip with the correct data, you must make sure that each department is attached to an establishment on the Department Profile page.

See "Maintaining Departments (*PeopleSoft HCM 9.2: Application Fundamentals*)".

Payslip/PayGroup Page

Use the Payslip/PayGroup page (GPFR_P_SLIP_GRP) to associate pay groups with an individual payslip.

Payslips must be associated with at least one pay group before they are included in a pay run.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Payslips, Templates FRA, Payslip/PayGroup

Image: Payslip/PayGroup page

This example illustrates the fields and controls on the Payslip/PayGroup page. You can find definitions for the fields and controls later on this page.

Payslip / Paygroups				
	Country	Description	Pay Group	Description
1	FRA	France	GFPGDUC\$	Pay Group DUCS 01
2	FRA	France	GFPGDUC\$	Pay Group DUCS 02
3	FRA	France	GFPGDUC\$	Pay Group DUCS 03
4	FRA	France	GFPGDUC\$	Pay Group DUCS04
5	FRA	France	GFPGMEN1	Pay Group GF1-1
6	FRA	France	GFPGMEN1	Pay Group GF1-2
7	FRA	France	GFPGMEN1	Pay Group GF1-3

Payslip ID

Displays the payslip ID that you selected. If you are using this page to create a new payslip ID, enter a description in the field next to the payslip ID.

Payslip/Paygroups

Pay Group

Select the pay group. Each payslip can have multiple pay groups. However, you can associate each pay group with only one payslip.

If you want to reassign a pay group to a new payslip ID, first click the Delete button to delete the pay group from the payslip with which it is initially associated. Then add the pay group to a different payslip ID.

Payslip Sort keys Page

Use the Payslip Sort keys page (GPFR_P_SLIP_SK) to set up the methods and order for sorting the different payslip forms.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Payslips, Templates FRA, Payslip Sort keys

Image: Payslip Sort keys page

This example illustrates the fields and controls on the Payslip Sort keys page. You can find definitions for the fields and controls later on this page.

Sort Key	System Element	Ascending/Descending
Sort Key 1: REP VR PS COMPANY	System Element COMPANY	SK 1 ASC
Sort Key 2: REP VR PS ESTABID	System Element ESTABID	SK 2 ASC
Sort Key 3:		SK 3
Sort Key 4:		SK 4
Sort Key 5:		SK 5

Each payee receives a payslip form per pay segment. The payee may also receive an annex, if necessary. The payslip and annex may be associated with up to five sort keys that are then used to sort the payslips.

Sort Key 1–5

Select the sort keys. You can select up to five sort keys, defined by variables. The information is sorted in the following order: Sort Key 1, Sort Key 2, Sort Key 3, Sort Key 4, and Sort Key 5.

For example, if you select the variable *REP VR PS COMPANY* (company ID) for Sort Key 1 and *REP VR PS ESTABID* (establishment ID) for Sort Key 2, the payslips are sorted first by company and then by establishment.

Note: Variables that you select must be defined as stored elements in the element definition.

A/D (ascending/descending)

Select the sort order: *ASC* to sort in ascending order, or *DSC* to sort in descending order. If you select ascending order, values appear in alphabetical order (A to Z) or numerical order (smallest to biggest).

Payslip Lines Page

Use the Payslip Lines page (GPFR_PAY_SLIP_1) to determine what is printed on each line of the body of the payslip.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Payslips, Templates FRA, Payslip Lines

Image: Payslip Lines page: Elements tab

This example illustrates the fields and controls on the Payslip Lines page: Elements tab. You can find definitions for the fields and controls later on this page.

	*Payslip / Annex	*Print Order	Employee Element Type	Column Element 1	Employer Element Type	Column Element 2		
1	Pay-slip	100.00	Earnings	SALAIRE BASE			+	-
2	Pay-slip	200.00	Earnings	STG OBL AT			+	-
3	Pay-slip	210.00	Earnings	STG OBL NAT			+	-
4	Pay-slip	220.00	Earnings	STG NOBL			+	-
5	Pay-slip	230.00	Earnings	STG GRATIF			+	-
6	Pay-slip	1000.00	Earnings	AFB SAL 12M			+	-

Common Page Information

Payslip/Annex

Select the document on which you want the elements to print:
Pay-slip (Bulletin de paie) or *Annex (Annexe)*.

Print Order

Enter the number that determines the order in which elements are printed on the payslip. All earning and deduction elements delivered by PeopleSoft print in the following order:

- Salary.
- Other Gross (overtime, premium, allowances, absences, and so on).
- URSSAF Contributions.
- ASSEDIC Contributions.
- AGIRC/ARRCO Contribution.
- Other Contributions.
- Other Net.

You may reorder the elements. When reordering, use decimal points for the print order if there are no whole numbers available. For example, if Element A has print order 100.00 and Element B has print order 101.00, and you want element Element C to print between the other two elements, assign it print order 100.50.

Elements Tab

Use this tab to specify and order earnings and deductions that are printed on the payslip.

Note: The rows on each tab correspond directly to the rows on all other tabs. For example, the element referenced in row 1 of the Retro tab is the same as the element in row 1 of the Description tab.

EE Element Type (employee element type) Select the element type for the payee's column in the payslip's body: *Earnings* or *Deductions*.

Element Name Select a payee's earning or deduction element. If you specify *Earnings* in the EE Element Type field, you may select only earning elements. If you specify *Deductions*, you may select only deduction elements.

ER Element Type (employer element type) Select the element type for the employer's column in the payslip's body: *Earnings* or *Deductions*. The employer's earning and deduction elements also appear on the payslip. The name of each element appears in the second Element Name field.

Element Name Select an employer's earning or deduction element. If you specify *Earnings* in the ER Element Type field, you may select only earning elements. If you specify *Deductions*, you may select only deduction elements.

Description Tab

Access the Description tab.

Image: Payslip Lines page: Description tab

This example illustrates the fields and controls on the Payslip Lines page: Description tab. You can find definitions for the fields and controls later on this page.

*Payslip / Annex	*Print Order	*Take Description from	*Description
1 Pay-slip	100.00	Employee Element	Base salary
2 Pay-slip	200.00	Employee Element	Mandatory training allowance
3 Pay-slip	210.00	Employee Element	Mandatory training allowance
4 Pay-slip	220.00	Employee Element	No mandatory training allowanc
5 Pay-slip	230.00	Employee Element	Training Allowance
6 Pay-slip	1000.00	Employee Element	Base salary paid with 12months

Use this page to view or change descriptions of earning or deduction elements.

Take Description from Select one of these values:

Employee Element to extract the payee element's description from the GP_PIN table.

Employer Element to extract the employer element's description from the GP_PIN table.

Description to enter your own description.

Description

If you select *Description* in the Take Description from field, enter the description for the element here. If you enter a new description here, it prints on the payslip. It does not, however, update the GP_PIN table.

Retro Tab

Access the Retro tab.

Image: Payslip Lines page: Retro tab

This example illustrates the fields and controls on the Payslip Lines page: Retro tab. You can find definitions for the fields and controls later on this page.

*Payslip / Annex	*Print Order	Description	*Retro Type	Detailed Instances		
1 Pay-slip	100.00	Base salary	Current and Deltas	<input type="checkbox"/>	+	-
2 Pay-slip	200.00	Mandatory training allowance	Current and Deltas	<input type="checkbox"/>	+	-
3 Pay-slip	210.00	Mandatory training allowance	Current and Deltas	<input type="checkbox"/>	+	-
4 Pay-slip	220.00	No mandatory training allowance	Current and Deltas	<input type="checkbox"/>	+	-
5 Pay-slip	230.00	Training Allowance	Current and Deltas	<input type="checkbox"/>	+	-
6 Pay-slip	1000.00	Base salary paid with 12months	Current and Deltas	<input type="checkbox"/>	+	-

Use this page to select the method for printing retro earnings and deductions.

Retro Type

Select a method for printing the retro earning or deduction element: *One Line*, *Current and Adjustment*, or *Current and Deltas*.

Detailed Instances

If you select this check box each instance of the earning or deduction prints separately on the payslip. You cannot select the check box if you selected the retro type of *One Line*.

If you select *Current and Adjustment*, only instances in the current period are printed separately.

The following example illustrates the differences among the three Retro Type options. Suppose that last year a payee had a fixed monthly salary of 20000. However, in January of this year, the payee received a raise of 1000 per month. Despite the raise, payroll mistakenly paid the payee 20000 for the months of January and February. In March, the system must pay 1000 in retro pay for both January and February, as well as pay March's salary of 21000.

If you select *One Line*, one line will include all current earnings and retro payments in a lump sum. Based on our example, 23000 appears on a single line.

If you select *Current and Adjustment*, the current salary appears on one line and the retro pay appears on the next line. Based on our example, the salary for March (21000) appears on one line and the retro adjustment and 2000 appears on the next line.

If you select *Current and Deltas*, the current salary appears on the first line, and each pay period's retro pay appears on an individual line. Based on our example, the salary for March (21000) appears on one line, and the adjusted monthly amounts (1000 for January and 1000 for February) appear on the following two lines.

Note: This page does not process retro earnings and deductions. Do not use this page to define the retro rules for payroll. Use this page only to define a printing method.

Spaces Tab

Access the Spaces tab.

Image: Payslip Lines page: Spaces tab

This example illustrates the fields and controls on the Payslip Lines page: Spaces tab. You can find definitions for the fields and controls later on this page.

Payslip/PayGroupPayslip Sort keysPayslip LinesPayslip Totals

Payslip ID: GFPR01Standard Payslip 04/19/2002

Body of the PayslipCustomizeFindView 100First1-6 of 350Last

ElementsDescriptionRetroSpaces

	*Payslip / Annex	*Print Order	Description	Nbr of Space Lines Before	Nbr of Space Lines After		
1	Pay-slip	100.00	Base salary	0	0	+	-
2	Pay-slip	200.00	Mandatory training allowance	0	0	+	-
3	Pay-slip	210.00	Mandatory training allowance	0	0	+	-
4	Pay-slip	220.00	No mandatory training allowanc	0	0	+	-
5	Pay-slip	230.00	Training Allowance	0	0	+	-
6	Pay-slip	1000.00	Base salary paid with 12months	0	0	+	-

Use this page to insert blank lines to space the elements on the payslip.

No. of Space Lines Before (number of space lines before) Enter the number of empty lines you require *before* the element description. The default value is 0 lines. The maximum number of lines you can enter is 99.

No. of Space Lines After (number of space lines after) Enter the number of empty lines you require *after* the element description. The default value is 0 lines. The maximum number of lines you can enter is 99.

Payslip Totals Page

Use the Payslip Totals page (GPFR_PAY_SLIP_2) to determine which accumulators to display in the footer of the payslip form.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Payslips, Templates FRA, Payslip Totals

Image: Payslip Totals page

This example illustrates the fields and controls on the Payslip Totals page. You can find definitions for the fields and controls later on this page.

Payslip/PayGroup Payslip Sort keys Payslip Lines Payslip Totals					
Payslip ID: GPFR01 Standard Payslip 04/19/2002					
Totals Customize Find View All First 1-7 of 12 Last					
	*Pay-slip / Annex	Column 1 Description	Column Element 1	Column Element 2	*Column Number
1	Pay-slip	Fiscal Net	GEN AC NET FISCAL	GEN AC NET FISC AN	1
2	Pay-slip	Gross	GEN AC BRUT SG	GEN AC BRUT AN	2
3	Pay-slip	EE Contrib	GEN AC COT SAL SG	GEN AC COT SAL AN	3
4	Pay-slip	ER Contrib	GEN AC COT PAT SG	GEN AC COT PAT AN	4
5	Pay-slip	SS Ceiling	URS AC PLAF A SG	URS AC PLAF A AN	5
6	Pay-slip	Entitlemt	CPE CG PAYES_DROI	CPA AC DROI PRC DT	11
7	Pay-slip	Taken	CPE CG PAYES_PRIS	CPA AC PRIS PRC DT	12

Pay-slip/Annex

Select whether the accumulator elements appears on the *Pay-slip* (*bulletin de paie*) or the *Annex* (*annexe*).

Col. No. (column number)

Select the column number to which you want to assign each accumulator. These columns appear in the footer section of the payslip. The payslip contains up to 14 different accumulators. The fourteen totals that appear on the payslip correspond to the 14 elements that appear on this page. The columns are separated into three sections: column numbers 1–10, 11–13, and 14.

The first section contains ten columns in a row that are designed for accumulating earnings and deductions. Each of the ten accumulators has two values: the top row displays the current total and the bottom row displays the year-to-date total. PeopleSoft delivers the accumulators in the following order:

- Column 1: Fiscal Net.
- Column 2: Gross.
- Column 3: Payee Contribution.
- Column 4: Employer Contribution.

- Column 5: Social Security Ceiling.
- Columns 6–10: Not delivered by PeopleSoft.

The second section contains three consecutive columns that display the holiday/vacation information. PeopleSoft delivers the accumulators in the following order:

- Column 11: Days Due.
- Column 12: Days Taken.
- Column 13: Balance.

Each of these three accumulators has two values: the top row displays the current year's information and the bottom row displays the previous year's information.

The final section contains a single column, column 14: RC (*Repos Compensateur*), which displays the time-off in lieu of compensation earned (in days and half-days) during this month and that may be spent by the payee during the next two months.

Note: If any amount resolves to zero, the header for that amount still prints on the payslip.

Descr. 1 (description 1)

Enter the description of the element. This description appears at the top of the column on the payslip form.

Element Name

Select the element name for the first amount (see above).
The system uses this element to retrieve an amount from the Accumulator Results Table.

Element Name

Select the element name for the second amount (see above).
The system uses this element to retrieve an amount from the Accumulator Results Table.

Adding Payslip Comments

To add payslip comments, use the Messages FRA (GPFR_PYSL_OBSRV) component.

This section discusses how to add payslip comments.

You can print comments in the footer of the payslip. You can enter up to four different lines for comments. When requested, the four lines will print on the payslip.

Page Used to Add Payslip Comments

Page Name	Definition Name	Navigation	Usage
Messages FRA	GPFR_PYSL_OBSRV	<ul style="list-style-type: none"> Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Payslips, Messages FRA, Messages FRA Global Payroll & Absence Mgmt, Payslips, Add Payslip Messages FRA, Messages FRA 	Create an observation ID to print comments or provide information on the payslip. View or edit existing observations associated with a given observation ID.

Messages FRA Page

Use the Messages FRA page (GPFR_PYSL_OBSRV) to create an observation ID to print comments or provide information on the payslip.

View or edit existing observations associated with a given observation ID.

Navigation

- Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Payslips, Messages FRA, Messages FRA
- Global Payroll & Absence Mgmt, Payslips, Add Payslip Messages FRA, Messages FRA

Image: Messages FRA page

This example illustrates the fields and controls on the Messages FRA page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'Messages FRA' page. At the top, the title 'Messages FRA' is displayed in blue. Below the title, there is a label 'Observation ID:' followed by the text 'FRA0000001'. Below this, there are four labels: 'Observation 1:', 'Observation 2:', 'Observation 3:', and 'Observation 4:'. Each label is followed by a text input field. The first two fields contain text: 'AS REQUESTED, YOUR 3 ADDITIONAL SUNDAYS HOURS' and 'ON JANUARY ARE NOW CALCULATED.' respectively. The last two fields are empty.

Define observation IDs to print comments or provide information to individual payees or groups of payees on the payslip.

To display comments and other information on a payslip:

- Define an observation ID with its associated comments and information on the Messages FRA page.
Enter the comments or information that you want to appear on the payslip in Observation fields 1–4.

2. Add the observation to the payslip of a single payee, or to all the payslips for a group of payees.

- For a single payee, do this on the payee-level Supporting Elements page.

On the Supporting Elements page, assign the Observation ID defined on the Messages FRA page to either the variable REP VR PS OBS (to display the observation in the body of the payslip) or the variable REP VR PS OBS A (to display the observation in the payslip annex).

- For a group of payees, use the Supporting Element Overrides page of the Pay Groups component, or the Supporting Element Overrides page of the Pay Entities component.

On the pay group or pay entity Supporting Element Overrides page, assign the Observation ID defined on the Messages FRA page to either the variable REP VR PS OBS (to display the observation in the body of the payslip) or the variable REP VR PS OBS A (to display the observation in the payslip annex).

Note: Carefully check the start and end date of the supporting element assignment to ensure that the payslip message is printed during the correct payroll period.

Example: Adding An Observation to a Payslip Using the Payee Level Supporting Elements page

This example illustrates how to assign a payslip observation to a single payee using the variable REP VR PS OBS on the Supporting Elements page.

Image: Assigning a payslip observation to a single payee on the Supporting Elements page

This example illustrates the fields and controls on the Assigning a payslip observation to a single payee on the Supporting Elements page. You can find definitions for the fields and controls later on this page.

Element Type	Element Name	Description	*Begin Date	End Date
Variable	REP VR PS OBS	Observation on the payslip	09/01/2009	09/30/2009

Note: You must specify the observation ID (*MESSAGE 1*) defined on the Messages FRA page in the Character Value field and enter the dates of the pay period in the Begin and End Date fields.

Related Links

"Defining Payee Overrides (*PeopleSoft HCM 9.2: Global Payroll*)"

"Defining Pay Group Overrides (*PeopleSoft HCM 9.2: Global Payroll*)"

"Defining Pay Entity Overrides (*PeopleSoft HCM 9.2: Global Payroll*)"

Printing Payslips

This section discusses how to print payslips using the report provided in Global Payroll for France.

Page Used to Print Payslips

Page Name	Definition Name	Navigation	Usage
Create/Print Payslips FRA	GPFR_RUNCTL_PYSL	Global Payroll & Absence Mgmt, Payslips, Create/Print Payslips FRA, Create/Print Payslips FRA	Print payslips for a group of employees.

Create/Print Payslips Page

Use the Create/Print Payslips FRA page (GPFR_RUNCTL_PYSL) to print payslips for a group of employees.

Navigation

Global Payroll & Absence Mgmt, Payslips, Create/Print Payslips FRA, Create/Print Payslips FRA

Image: Create/Print Payslips FRA page

This example illustrates the fields and controls on the Create/Print Payslips FRA page. You can find definitions for the fields and controls later on this page.

Create/Print Payslips FRA

Run Control ID: 01 [Report Manager](#) [Process Monitor](#) [Run](#)

*Calendar Group ID: G1GRP_JNJL04_MUL June & July 2004
 Stream Number: ☐ Process by stream
 Group List ID: K1GGL01 Integration Project Team
☐ Reprint

Calendar List		
Pay Group	Calendar ID	Payment Date

Streams			
Stream Number	Empl ID From	Empl ID To	Calculated

Calendar Group ID

Select the calendar group for which you want to create payslips.

Group List ID

If you want to print payslips for some of the employees in the calendar group, select the Group List ID.

Reprint

Select this check box if you want to reprint payslips for a payroll that has been approved or finalized.

Note: If the payroll is not approved or finalized, you can rerun the payslips without selecting this check box. The payslip has a draft status printed at the top of the payslip.

Setting Up and Viewing Payslips Online

To set up and view payslips online, use the Templates FRA (GPFR_PAY_SLIP), Admin Payslip/Results FRA (GPFR_ONPAY_SETUP), and Rvw Admin Payslip/Results FRA (GPFR_ONPAY) components.

This section provides an overview of the online payslip view and discusses how to:

- Creating a list of elements to view in the online payslip.
- View summary data.
- View the payslip body.
- View supporting elements.
- View earnings and deductions.
- View accumulator data.
- View absence data.
- View positive input.

Pages Used to Set Up and View Payslips Online

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Admin Payslip/Results FRA	GPFR_ONPAY_SETUP	Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Payslips, Admin Payslip/Results FRA, Admin Payslip/Results FRA	Create a list of payroll elements to view on the online payslip pages.
Summary	GPFR_ONPAY_SUM	Global Payroll & Absence Mgmt, Payslips, Rvw Admin Payslip/Results FRA, Summary	View summary information about a payee's pay run.
Body	GPFR_ONPAY_BODY	Global Payroll & Absence Mgmt, Payslips, Rvw Admin Payslip/Results FRA, Body	View basic information about earnings and deductions processed for a payee.

Page Name	Definition Name	Navigation	Usage
Supporting Elements	GPFR_ONPAY_CALPIN	Global Payroll & Absence Mgmt, Payslips, Rvw Admin Payslip/Results FRA, Supporting Elements	View the values of the supporting elements processed for a payee.
Earnings Deductions	GPFR_ONPAY_ERNDED	Global Payroll & Absence Mgmt, Payslips, Rvw Admin Payslip/Results FRA, Earnings Deductions	View detailed information about earnings and deductions processed for a payee.
Accumulators	GPFR_ONPAY_ACUM	Global Payroll & Absence Mgmt, Payslips, Rvw Admin Payslip/Results FRA, Accumulators	View accumulator data for a payee.
Absences	GPFR_ONPAY_ABS	Global Payroll & Absence Mgmt, Payslips, Rvw Admin Payslip/Results FRA, Absences	View absence data (daily data and generated positive input).
Positive Inputs	GPFR_ONPAY_PI	Global Payroll & Absence Mgmt, Payslips, Rvw Admin Payslip/Results FRA, Positive Inputs	View positive input for a payee.

Understanding the Online Payslip View

Global Payroll for France enables you to view payroll results online using the Rvw Admin Payslip/Results FRA component. The data that appears on the Summary page and Body page of this component is based on the payslip setup described earlier in this topic.

You can view all payroll data or a subset of data for a payee. To view a subset of data, create a list of viewable payroll elements using the Admin Payslip/Results FRA page (GPFR_ONPAY_SETUP). Then, enter the name of the list you have created in the Element List field in the Rvw Admin Payslip/Results FRA component to retrieve information about only the elements you are interested in.

Important! You must associate pay groups with payslip templates on the Payslip/PayGroup page of the Templates FRA (GPFR_PAY_SLIP) component in order to view payroll results online.

Common Elements Used in This Section

Element Name

This field appears on several pages in the Rvw Admin Payslip/Results component.

Enter the name of the element for which you want to view results and click Retrieve Results.

Element List

This field appears on several pages in the Rvw Admin Payslip/Results component.

Enter the name of the element list containing the payroll elements you want to view and click Retrieve Results to retrieve a subset of payroll data for a payee.

Note: Define element lists on the Admin Payslip/Results FRA page.

Calendar ID

This field appears on several pages in the Rvw Admin Payslip/Results component.

Enter the ID of the calendar (payroll or absence) for which you want to view payroll results and click Retrieve Results.

Admin Payslip/Results FRA Page

Use the Admin Payslip/Results FRA page (GPFR_ONPAY_SETUP) to create a list of payroll elements to view on the online payslip pages.

Navigation

Set Up HCM, Product Related, Global Payroll & Absence Mgmt, Payslips, Admin Payslip/Results FRA, Admin Payslip/Results FRA

Image: Admin Payslip/Results FRA page

This example illustrates the fields and controls on the Admin Payslip/Results FRA page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'Admin Payslip/Results FRA' page. At the top, there is a title bar. Below it, there are two input fields: 'Element List:' with the value 'PAI' and '*Description:' with the value 'HRS SUP'. Below these fields is a table titled 'Elements'. The table has columns for 'Entry Type' and 'Element Name'. There are two rows in the table. The first row has '1' in the first column, 'Earnings' in the second column, and 'HRS SUP 125%' in the third column. The second row has '2' in the first column, 'Earnings' in the second column, and 'HRS SUP 150%' in the third column. To the right of the table, there are navigation controls: 'Customize', 'Find', 'View All', 'First', '1-2 of 2', and 'Last'. Each row in the table has a magnifying glass icon and a '+'/- button.

Admin Payslip/Results FRA		
Element List: PAI *Description: HRS SUP		
Elements		
	Entry Type	Element Name
1	Earnings	HRS SUP 125%
2	Earnings	HRS SUP 150%

Use the Admin Payslip/Results FRA page to create subsets of payroll elements to view on the online payslip pages, so that you can quickly obtain information about a targeted group of earnings, deductions, or other elements. For example, all overtime earnings or all URSSAF contribution elements.

Entry Type

Specify the type of element you want to include in the element list.

Element Name

Specify the name of the element to include in the element list.

Summary Page

Use the Summary page (GPFR_ONPAY_SUM) to view summary information about a payee's pay run.

Navigation

Global Payroll & Absence Mgmt, Payslips, Rvw Admin Payslip/Results FRA, Summary

Image: Summary page

This example illustrates the fields and controls on the Summary page. You can find definitions for the fields and controls later on this page.

Summary			Body	Supporting Elements	Earnings Deductions	Accumulators	Absences	Positive Inputs																											
ID:	KFGE0001	Name:	Duval,Catherine		Empl Record:		0																												
Calendar Group ID:	KF M200601	2006 01 - Monthly																																	
Segment Information				Find First 1 of 1 Last																															
Job Description Company: KF1 Business Institute - France Estab ID: KF001 Paris - Headquarter Department: 10200 France Headquarters Job Code: 420090 Director-Operations				Payslip footer Accumulators Customize First 1-7 of 7 Last																															
Segment Description Begin Date: 01/01/2006 End Date: 01/31/2006 Calendar ID: KF M200601P MTHREG Pay Group: KFGMONTHLY Monthly Pay Group Currency: EUR euro Calc Time: 08/21/2006 8:31AM Calc Status: Finalized				<table border="1"> <thead> <tr> <th>Descr 1</th> <th>Segment Value</th> <th>Yearly Total</th> </tr> </thead> <tbody> <tr> <td>Fiscal Net</td> <td>1873.59</td> <td>1873.59</td> </tr> <tr> <td>Gross</td> <td>2286.74</td> <td>2286.74</td> </tr> <tr> <td>EE Contrib</td> <td>478.02</td> <td>478.02</td> </tr> <tr> <td>ER Contrib</td> <td>1197.51</td> <td>1197.51</td> </tr> <tr> <td>SS Ceiling</td> <td>1294.50</td> <td>1294.50</td> </tr> <tr> <td>Entitlemt</td> <td>20.00</td> <td></td> </tr> <tr> <td>Balance</td> <td>20.00</td> <td></td> </tr> <tr> <td>Net Paid</td> <td colspan="2">1808.72</td> </tr> </tbody> </table>					Descr 1	Segment Value	Yearly Total	Fiscal Net	1873.59	1873.59	Gross	2286.74	2286.74	EE Contrib	478.02	478.02	ER Contrib	1197.51	1197.51	SS Ceiling	1294.50	1294.50	Entitlemt	20.00		Balance	20.00		Net Paid	1808.72	
Descr 1	Segment Value	Yearly Total																																	
Fiscal Net	1873.59	1873.59																																	
Gross	2286.74	2286.74																																	
EE Contrib	478.02	478.02																																	
ER Contrib	1197.51	1197.51																																	
SS Ceiling	1294.50	1294.50																																	
Entitlemt	20.00																																		
Balance	20.00																																		
Net Paid	1808.72																																		

View a summary of the payroll results for a payee in a calendar run.

The information you see is based on the payslip defined for the payee's pay group using the Templates FRA component.

Note: You must associate pay groups with payslip templates on the Payslip/PayGroup page of the Templates FRA (GPFR_PAY_SLIP) component in order to view payroll results online.

Body Page

Use the Body page (GPFR_ONPAY_BODY) to view basic information about earnings and deductions processed for a payee.

Navigation

Global Payroll & Absence Mgmt, Payslips, Rvw Admin Payslip/Results FRA, Body

Image: Body page

This example illustrates the fields and controls on the Body page. You can find definitions for the fields and controls later on this page.

Summary **Body** Supporting Elements Earnings Deductions Accumulators Absences Positive Inputs

Catherine Duval EMP ID: KFGE0001 Empl Record: 0

Calendar Group ID: KF M200601 2006 01 - Monthly

Selection Criteria

Element Name: Calendar ID: **Retrieve Results**

Element List:

Selection on Amount: ☐ Positive Inputs Only

Segment Information Find First 1 of 1 Last

Begin Date: 01/01/2006 End Date: 01/31/2006

Earnings & Deductions Customize Find View All First 1-5 of 31 Last

	Description	Currency	Retro	Quantity or Base	Unit Value	Employee Rate	Employee Amount	Employer Rate	Employer Amount
1	Base salary						2286.74		
2	Illness			2286.74		0.750	-17.15	12.800	-292.70
3	Oldness A-Ceiling			1294.50		6.650	-86.08	8.300	-107.44
4	Oldness without ceiling - empl.			2286.74				1.600	-36.59
5	FNAL on A ceiling - empl.			1294.50				0.100	-1.29

Use the Body page to view earnings and deductions processed for a payee in a calendar run.

You can narrow down the search results by selecting elements by name, element list, or calendar ID, or by specifying negative or positive amounts only in the Selection on Amount field. You can also view only positive inputs by selecting the Positive Inputs Only check box.

The information you see is based on the payslip defined for the payee's pay group using the Templates FRA component.

Supporting Elements Page

Use the Supporting Elements page (GPFR_ONPAY_CALPIN) to view the values of the supporting elements processed for a payee.

Navigation

Global Payroll & Absence Mgmt, Payslips, Rvw Admin Payslip/Results FRA, Supporting Elements

Image: Supporting Elements page

This example illustrates the fields and controls on the Supporting Elements page. You can find definitions for the fields and controls later on this page.

The screenshot displays the 'Supporting Elements' page for employee Catherine Duval (EMP ID: KFGE0001). The page includes tabs for Summary, Body, Supporting Elements, Earnings Deductions, Accumulators, Absences, and Positive Inputs. The 'Supporting Elements' tab is active, showing search criteria and a table of elements.

Search Criteria:

- Element Name:
- Calendar ID:
- Retrieve Results:

Segment Information:

- Begin Date: 01/01/2006
- End Date: 01/31/2006
- Supporting Elements: [Customize](#) | [Find](#) | [View All](#) | [First](#) | [1-5 of 23](#) | [Last](#)

Value	Period	Element Type	Element Name	Amount	Character Value	Date Value
1	Formula	ABS FM PLFT SAL MO	2286.740000			
2	Variable	DAS VR BAS TAXSAL1	2286.740000			
3	Variable	DAS VR DATE PAIE	0.000000		01/31/2006	
4	Variable	DAS VR DUREE TRAV	30.000000			
5	Variable	DAS VR TOT HRS SAL	75.833333			

Use the Supporting Elements page to view all of the supporting elements processed for a payee.

You can narrow down the search results by selecting elements by name, element list, or calendar ID.

Earnings Deductions Page

Use the Earnings Deductions page (GPFR_ONPAY_ERNDED) to view detailed information about earnings and deductions processed for a payee.

Navigation

Global Payroll & Absence Mgmt, Payslips, Rvw Admin Payslip/Results FRA, Earnings Deductions

Image: Earnings Deductions page

This example illustrates the fields and controls on the Earnings Deductions page. You can find definitions for the fields and controls later on this page.

Summary Body Supporting Elements **Earnings Deductions** Accumulators Absences Positive Inputs

Catherine Duval EMP ID: KFGE0001 Empl Record: 0

Calendar Group ID: KF M200601 2006 01 - Monthly

Selection Criteria

Element Name: Calendar ID:

Element List: ☐ Positive Inputs Only

Segment Information Find First 1 of 1 Last

Begin Date: 01/01/2006 End Date: 01/31/2006

Earnings & Deductions Customize Find View All First 1-5 of 42 Last

Value	Period	Element Type	Element Name	Base	Description	Unit	Rate Value	Percent	Amount
1	Deduction	AGFF TA A4 E	1294.500000	Employer's AGFF slice A - A4		1.200000	15.530000		
2	Deduction	AGFF TA A4 S	1294.500000	Payee's AGFF slice A - A4 art		0.800000	10.360000		
3	Deduction	AGFF TB A4 E	992.240000	Employer's AGFF slice B - A4		1.300000	12.900000		
4	Deduction	AGFF TB A4 S	992.240000	Payee's AGFF slice B - A4 art		0.900000	8.930000		
5	Deduction	AGI CET E	2286.740000	Except. Temporary Contrib. Empl		0.220000	5.030000		

Use the Earnings Deductions page to view the base and component values (unit, rate, percent, and amount) calculated for each element in the pay run. You can also view the calendar in which each element was processed (source calendar), the slice begin and end dates, and other element data.

You can narrow down the search results by selecting earnings and deductions by name, element list, or calendar ID. You can also view only positive inputs by selecting the Positive Inputs Only check box.

Accumulator Page

Use the Accumulators page (GPFR_ONPAY_ACUM) to view accumulator data for a payee.

Navigation

Global Payroll & Absence Mgmt, Payslips, Rvw Admin Payslip/Results FRA, Accumulators

Image: Accumulators page

This example illustrates the fields and controls on the Accumulators page. You can find definitions for the fields and controls later on this page.

Summary | **Body** | **Supporting Elements** | **Earnings Deductions** | **Accumulators** | **Absences** | **Positive Inputs**

Catherine Duval EMP ID: KFGE0001 Empl Record: 0

Calendar Group ID: KF M200601 2006 01 - Monthly

Selection Criteria

Element Name: Calendar ID: **Retrieve Results**

Element List:

Segment Information Find First 1 of 1 Last

Begin Date: 01/01/2006 End Date: 01/31/2006

Accumulators Customize | Find | View 100 | First 1-5 of 142 Last

Value | Period | User Keys

Accumulator Period	Element Name	Description	From	Through	Amount
1 Segment	ABS AC BASE URS SG	Illness contribution base	01/01/2006	01/31/2006	2286.740000
2 MTD	ABS AC BRUT MO	Month gross salary	01/01/2006	01/31/2006	2286.740000
3 Segment	ABS AC BRUT-COTIS	Used for illness/mat certfict	01/01/2006	01/31/2006	1976.500000
4 Segment	ABS AC HR TPS COMP	Full time hours	01/01/2006	01/31/2006	75.833333
5 YTD	ABS AC NB MO PRES	# of month of presence / year	01/01/2006	12/31/2006	1.000000

Use this page to view the values of all accumulators processed in a pay run. You can also view the calendar in which each accumulator was processed (source calendar), the slice begin and end dates, and other accumulator data. If there are user keys associated with an accumulator, these appear on the User Keys tab.

You can narrow down the search results by selecting accumulators by name, element list, or calendar ID.

Absences Page

Use the Absences page (GPFR_ONPAY_ABS) to view absence data (daily data and generated positive input).

Navigation

Global Payroll & Absence Mgmt, Payslips, Rvw Admin Payslip/Results FRA, Absences

Image: Absences page

This example illustrates the fields and controls on the Absences page. You can find definitions for the fields and controls later on this page.

The screenshot displays the 'Absences' page for employee Catherine Duval (EMP ID: KFGE0001). The page is divided into several sections:

- Summary Tab:** Shows employee details and calendar group information.
- Selection Criteria:** Includes fields for Element Name, Calendar ID, and a Retrieve Results button.
- Segment Information:** Displays the Begin Date (01/01/2006) and End Date (01/31/2006).
- Absence Daily Data Table:** A table with columns: Absence Begin Date, Absence Take Element, Description, Day Count, Day Count Paid, Begin Entitlement Balance, and Entitlement Balance. It shows one record with a balance of 0.000000.
- Generate Positive Input Member List Table:** A table with columns: Begin Date, Take, Element Name, Description, Percent, and Unit. It shows one record.

Use this page to view information on absences and entitlements processed in a pay run, absence begin dates, the calendars in which the absence data was processed (source calendars), and any positive input generated for an absence.

You can narrow down the search results by selecting absence takes by name, element list, or calendar ID.

Positive Inputs Page

Use the Positive Inputs page (GPFR_ONPAY_PI) to view positive input for a payee.

Navigation

Global Payroll & Absence Mgmt, Payslips, Rvw Admin Payslip/Results FRA, Positive Inputs

Image: Positive Inputs page

This example illustrates the fields and controls on the Positive Inputs page. You can find definitions for the fields and controls later on this page.

Summary Body Supporting Elements Earnings Deductions Accumulators Absences Positive Inputs

Catherine Duval EMP ID: KFGE0001 Empl Record: 0

Calendar Group ID: KF M200601 2006 01 - Monthly

Selection Criteria

Element Name: Calendar ID: Retrieve Results

Element List:

Segment Information Find First 1 of 1 Last

Begin Date: 01/01/2006 End Date: 01/31/2006

Earnings & Deductions Customize Find View All First 1 of 1 Last

Value	Period	Element Type	Element Name	Description	Base	Unit	Rate	Percent	Amount	Currency
1										

Use this page to view the positive input values entered for all of the earnings and deductions processed in a pay run.

You can narrow down the search results by selecting earnings and deductions by name, element list, or calendar ID.

Setting Up and Running the Banking Processes

Understanding Banking Setup and Processing for France

To use the banking feature, start by entering setup data in PeopleSoft HR and the core Global Payroll application, and then run the banking processes in both Global Payroll and Global Payroll for France.

This section discusses:

- How to set up banking for France.
- How to run banking processes for France.

Note: This topic briefly describes the setup and processing steps you must complete in PeopleSoft HR and the Global Payroll core application before you can run the banking process for France. Because these steps are documented in detail at a later state, this topic focuses on the Global Payroll for France pages used in the banking process.

Understanding How to Set Up the Banking Process for France

Complete these setup tasks to use the banking feature for France:

- Set up banks and branches.
- Set up funding sources.
- Set up disbursement requirements.

Bank and Branch Setup

To set up bank and branch data:

1. Define banks using the Bank Table (BANK_EC) page.
2. Define bank branches on the (BANK_BRANCH_EC) page.

Complete these steps in the PeopleSoft HR application.

See "Understanding Banking (*PeopleSoft HCM 9.2: Global Payroll*)".

Funding Source Setup

Funding source setup refers to the source of the funds needed to pay employees and other workers.

To set up funding:

1. Specify the electronic funds transfer (EFT) formats you will be using on the Electronic Transfer Formats (EFT_NAME) page.

An EFT is a standard interbank file format.

Note: PeopleSoft does not deliver the EFT file format needed to transfer money to the bank. You must define this yourself.

2. Define source banks for payroll on the Source Bank Accounts (SRC_BANK) page.
3. Specify a default source bank for the pay entity on the Processing Details (GP_PYENT_PRCS_DTL) page.
4. Define the level at which payroll are funded on the Source Bank Link (GP_PE_SBANK_LNK) page.

For example, sources can be specified at the company, department, establishment, or pay group level within a pay entity.

Complete these steps in the PeopleSoft Global Payroll core application.

See "Understanding Banking (*PeopleSoft HCM 9.2: Global Payroll*)".

Disbursement Requirements Setup

Disbursements refer to payroll distributions.

Net pay disbursements go to payees, and deduction amounts can be distributed to recipients such as a healthcare provider or a government agency.

To set up disbursements:

1. Define deposit schedules on the Deposit Schedules (DEP_SCHED) page.
2. Define recipients using the Deduction Recipients (RECIPIENT) component.

Recipients can be entities (general recipients) or individuals (individual recipients).

3. Assign recipients to deductions.

This procedure varies with the recipient type.

- Link individual recipients to deductions and payees through the payee-level Deduction Recipients (GP_RCP_PYE) page.
- Link general recipients to deductions through the Recipient (GP_RCP_DED) page of the Deduction component.

Note: Global Payroll for France enables you to specify the recipient of a garnishment directly on the Recipient tab of the Assign Garnishments FRA page. You do not need to enter this information on the core application Deduction Recipients (GP_RCP_PYE) page.

4. Identify an individual's bank account information and disbursement details on the Maintain Bank Accounts (PYE_BANKACCT) and Specify Net Pay Elections (GP_NET_DIST) pages.

This is necessary for disbursing an individual's net pay electronically.

Note: Payees can manage their own personal payroll information, such as updating personal bank account information and payroll payment distribution instructions on self-service pages in PeopleSoft ePay. These pages are discussed in the *PeopleSoft ePay*.

Complete these steps in the PeopleSoft Global Payroll core application

Understanding How To Run the Banking Process for France

After completing the setup steps described above, run the following processes in the core Global Payroll application and then continue processing data in Global Payroll for France:

In the Global Payroll core application:

1. Run and finalize payrolls on the Payroll/Absence Run Control page.
2. Run the payment preparation (GP_PAYMENT) process on the Run Payment Prep Process (GP_PMT_PREPARE) page.

The payment preparation process is a batch job that takes the results of payroll calculations and populates the payment table (GP_PAYMENT). This table identifies each recipient, the amount owed, the source bank, and the account number.

In Global Payroll for France:

1. Run the payment preparation (GPFR_PAYMENT) process for France on the Payment Preparation (GPFR_BANK_POPULATE) page.

This populates the GPFR_PAYMENT table containing data for the EFT file and the Net Payment and Exceptions reports.

2. Run the FREFT SQR on the Payment File Generation (GPFR_BANK_EFT) page.

The FREFT SQR generates a flat output file (EFT) containing the details of each payment in the payroll run.

3. Run the GP FRTREP SQR and GPFREXRP SQR on the Payments Report (GPFR_BANK_REPORT) page.


This generates the Net Payment and Exceptions reports for all payment modes (transfer, check, and cash).

Note: These steps aren't necessary if you are processing payments using Single Euro Payment Area (SEPA) formats and standards.

See [Processing SEPA Payments](#).

Image: The banking process in Global Payroll

This diagram illustrates the process flow from Global Payroll core to Global Payroll for France:



General Processing Information

The payment preparation (GP_PAYMENT) process in the core Global Payroll application populates the GP_PAYMENT output table. The process sets the GP payment status to P (prepared).

The payment preparation (GPFR_PAYMENT) process for France populates the GPFR_PAYMENT output table.

The GPFR_PAYMENT output table contains the same basic information found in the GP_PAYMENT table, but sorted by source bank.

When you run the French payment preparation (GPFR_PAYMENT) process, the system:

- Selects payees with a payment status of P (prepared) in the GP_PAYMENT record.
- Sets the payment status for the selected payees to T (transferred) in GP_PAYMENT.
- Sets the payment status for the selected payees to P (prepared) in the GPFR_PAYMENT record.

Note: If you rerun the GP_PAYMENT process, cancel and rerun the GPFR_PAYMENT preparation process. You can delete the selected Calendar Run ID in GPFR_PAYMENT and the GP_PAYMENT status changes back from T (transferred) to P (prepared).

Running the Payment Preparation Process

This section discusses how to run the payment preparation process for France.

Page Used to Run the Payment Preparation Process for France

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Run Payment Prep Process FRA	GPFR_BANK_POPULATE	Global Payroll & Absence Mgmt, Payment Processing, Run Payment Prep Process FRA, Run Payment Prep Process FRA	Populate the GPFR_PAYMENT table containing data for EFT FILE and Net Payment and Exceptions reports.

Run Payment Prep Process FRA Page

Use the Run Payment Prep Process FRA page (GPFR_BANK_POPULATE) to populate the GPFR_PAYMENT table containing data for EFT FILE and Net Payment and Exceptions reports.

Navigation

Global Payroll & Absence Mgmt, Payment Processing, Run Payment Prep Process FRA, Run Payment Prep Process FRA

Image: Run Payment Prep Process FRA page

This example illustrates the fields and controls on the Run Payment Prep Process FRA page. You can find definitions for the fields and controls later on this page.

Select the calendar group ID of the payees whose payments you are preparing and click the Run button to run the payroll preparation (GPFR_PAYMENT) process.

Creating the EFT Payment File

This section discusses how to create the EFT file.

Page Used to Create an EFT Payment File

Page Name	Definition Name	Navigation	Usage
Create EFT Payment File FRA	GPFR_BANK_EFT	Global Payroll & Absence Mgmt, Payment Processing, Create EFT Payment File FRA, Create EFT Payment File FRA	<p>Run the Electronic File Transfer SQR process (GPFREFT) to create an EFT file.</p> <p>This file is sent to the bank so that funds can be transferred to payees' accounts. The file format consists of a line for each payee, containing the payee's name, bank account number, and amount of payment. Each line can contain up to 160 characters.</p>

Create EFT Payment File FRA Page

Use the Create EFT Payment File FRA page (GPFR_BANK_EFT) to run the Electronic File Transfer SQR process (GPFREFT) to create an EFT file.

This file is sent to the bank so that funds can be transferred to payees' accounts. The file format consists of a line for each payee, containing the payee's name, bank account number, and amount of payment. Each line can contain up to 160 characters.

Navigation

Global Payroll & Absence Mgmt, Payment Processing, Create EFT Payment File FRA, Create EFT Payment File FRA

Image: Create EFT Payment File FRA page

This example illustrates the fields and controls on the Create EFT Payment File FRA page. You can find definitions for the fields and controls later on this page.

Create EFT Payment File FRA

Run Control ID: PS [Report Manager](#) [Process Monitor](#)

Calendar Group ID:

Pay Entity:

EFT Details			Customize Find View All First 1 of 1 Last	
	*Source Bank ID	Description	File Name	
1	<input type="text"/>		<input type="text"/>	<input type="button" value="+"/> <input type="button" value="-"/>

Calendar Group ID Select the calendar group for which the payroll was run.

Pay Entity Select a pay entity.

Note: You must select both a calendar group ID and a pay entity.

Use All Source Banks Select to include all the source banks used by the Calendar Group and Pay Entity selected.

EFT Details

Source Bank ID Select one or more source banks for the EFT file.

You have the option to run and show multiple source banks in a single Net Payment Report, or to generate one report per source bank.

File Name Enter a name and location for the EFT file. Enter the complete name and path. Remember that the path is available on your server, but not on your desktop.

Creating Net Payment and Exceptions Reports

This section provides an overview of net payment and exceptions reports and discusses how to generate net payment and exceptions reports.

Page Used to Generate Net Payment and Exceptions Reports

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Net Payment Report FRA	GPFR_BANK_REPORT	Global Payroll & Absence Mgmt, Payment Processing, Net Payment Report FRA, Net Payment Report FRA	<ul style="list-style-type: none"> Run the Net Payment Report (GPFRTREP. SQR). Run the Exceptions Report (GPFREXP. SQR). <p>Select the Calendar Group ID and Pay Entity to use for the reports.</p>

Understanding Net Payment and Exceptions Reports

Once the GP_PAYMENT and GPFR_PAYMENT tables are populated, you can generate the following Structured Query Reports (SQRs):

- Payments report: lists details of each payment.

- Exceptions report: lists negative net payments excluded by the system when performing retroactive calculations.

Global Payroll provides rules to prevent the calculation of negative net payments in the current segment; however, when processing periods retroactively, the system may generate negative payments under some conditions. If this occurs, the French banking process ignores the negative amounts (as French banking norms do not authorize negative net payments), and you can run the exceptions report to determine whether negative payments have been excluded from the banking file.

Note: Note that the exceptions report is available only after payroll has been finalized and the banking process has been run, at which point it is too late in the process to modify payroll elements to prevent a negative net calculation. For this reason, Global Payroll for France provides an additional check for negative payments earlier in the calculation process: if a payee receives as negative net payment, the system issues a warning message that can be viewed on the Payee Messages page immediately after payroll has been calculated and before the payroll run has been finalized. You can then modify payroll data as needed to eliminate the negative payment before finalizing payroll and running the banking process.

Net Payment Report FRA Page

Use the Net Payment Report FRA page (GPFR_BANK_REPORT) to select the Calendar Group ID and Pay Entity to use for the reports.

Navigation

Global Payroll & Absence Mgmt, Payment Processing, Net Payment Report FRA, Net Payment Report FRA

Image: Net Payment Report FRA page

This example illustrates the fields and controls on the Net Payment Report FRA page. You can find definitions for the fields and controls later on this page.

Net Payment Report FRA

Run Control ID: PS [Report Manager](#) [Process Monitor](#)

Calendar Group ID: 2006 02 - Monthly

Pay Entity: Sample Data Pay entity

Type of Beneficiary

☒ Net to be paid ☐ Other Payments ☐ All

☐ One Report Per Source Bank

Report Details		Customize	Find	View All	First	1 of 1	Last
	*Source Bank ID	Description					
1	<input type="text" value="KFGBANK"/>	Credit Lyonnais					

Type of Beneficiary

Select the type of recipients to display in the payment report. Values are:

Net to be paid: Employee recipients.

Other Payments: Recipients other than employees.

All: All pay recipient types.

Use All Source Banks

Select to include all the source banks used by the Calendar Group and Pay Entity selected.

One Report Per Source Bank

Select to generate one report per source bank. If selected, you can specify *only* one Source Bank ID in the Report Details section of this page. You must run the reports separately for each source bank.

Source Bank ID

Select the source bank(s) for the EFT file.

Processing SEPA Payments for France

PeopleSoft Global Payroll for France enables you to process payments using the Single Euro Payment Area (SEPA) formats and standards through an integration with PeopleSoft Financial Gateway. If you process payments using SEPA, you must set up and process banking using a different set of steps.

This section discusses how to:

- Set up SEPA processing.
- Process SEPA payments.
- Send SEPA payments to PeopleSoft Financial Gateway.

Setting Up SEPA Processing

Before you can process SEPA payments using Global Payroll for France, in addition to the normal banking setup you must:

1. Ensure that an active SEPA application package is defined for France on the Banking Country Setup page.
2. Ensure that a SEPA SQL statement is defined for France on the Banking Preparation Definition page.
3. Define payment process settings on the Installation Settings page.
4. Set up Integration Broker for both Global Payroll for France and Financial Gateway.
5. Set up banks for France in your PeopleSoft Financials system.

Related Links

"Setting Up Country-Specific Banking Processing (*PeopleSoft HCM 9.2: Global Payroll*)"

Processing SEPA Payments

You process payments for SEPA using the same Global Payroll Banking Process (GP_PMT_PREP) that you use for non-SEPA banking. When a row of data exists for France on the Banking Country Setup component, however, GP_PMT_PREP executes SEPA logic.

Global Payroll for France uses the delivered CORE_BANK:SQL application package to process SEPA payments. The system references the banking preparation definition for France and for each defined sequence processes the SEPA SQL statement using the country, calendar run ID, and employee ID range selected on the Run Payment Prep Process run control page. The system loads the results into the GP_PAYMENT_FG record.

Note: This new SEPA logic supersedes the country-specific processes that you would normally run in PeopleSoft Global Payroll for France for non-SEPA banking. Therefore, when processing SEPA payments you do not have to run the payment preparation (GPFR_PAYMENT) process for France, the FREFT SQR, or the GP FRTREP SQR and GPFREXRP SQR.

Delivered Sequences

PeopleSoft Global Payroll for France delivers four Banking Preparation Definition sequences. They are:

- Employee SEPA
- Recipient SEPA
- Employee Non SEPA
- Recipient Non SEPA

Related Links

"Country-Specific Processing (*PeopleSoft HCM 9.2: Global Payroll*)"

Sending SEPA Payments to PeopleSoft Financial Gateway

You send generated SEPA payment details from PeopleSoft Global Payroll for France to PeopleSoft Financial Gateway. Financial Gateway then dispatches the payments to banks in compliance with SEPA rules and standards. You send SEPA payments to PeopleSoft Financial Gateway using the Payment File Generation page. This page enables you to:

- Identify the rows of GP_PAYMENT_FG that are to be prepared to be sent to Financial Gateway.
- Insert the prepared payment rows into staging tables and publish them to Financial Gateway through Integration Broker using the PAYMENT_REQUEST message.
- Generate Oracle Business Intelligent Publisher (BI Publisher or BIP) reports. The delivered report for PeopleSoft Global Payroll for France is GPFRPMT.

Related Links

"Sending Payments to PeopleSoft Financial Gateway (*PeopleSoft HCM 9.2: Global Payroll*)"

Processing Terminations

Understanding Termination Processing

PeopleSoft uses the off-cycle advance payment functionality in the core Global Payroll application as the basis for the France-specific termination process. The system calculates earnings and deductions for terminated employees as advance payments outside of the normal payroll cycle. When employees receive their final payment, the system automatically blocks processing of the same payees in the normal, on-cycle calendar.

Note: Core Global Payroll off-cycle processing functionality provides four off-cycle types: manual payments, reversals and corrections, unscheduled payments, and advances. Global Payroll for France uses advances to process early terminations.

The steps for processing terminations are as follows:

1. Terminate employees in PeopleSoft HR.

Enter the termination action/reason and the effective date of the termination on the Work Location page of the Job Data (JOB_DATA) component.

The termination process in Global Payroll for France is fully integrated with the termination process in PeopleSoft HR. To terminate payees, enter the termination actions and reasons in the Action and Reason fields in the JOB record; the system automatically detects the action-reason combinations that require termination processing based on the termination process setup.

See [Understanding Termination Processing](#).

2. Define the basic parameters of the off-cycle termination group—including the period of interest, the date of pay, and the payment method—on the Termination Group page of the Create Terminated EE Group FRA (GPFR_TERM_GROUP) component.
3. Retrieve the terminated payees and assign them to the off-cycle group on the Terminated Employees page of the Create Terminated EE Group FRA component.

The system retrieves only those payees with retro and segmentation triggers that match those listed on the Extraction Setup page, and that have termination dates within the period of interest defined in step 2.

4. Create an off-cycle calendar group for processing the terminated payees, and attach the off-cycle group to this calendar group.

To do this, use the Off-cycle Calendar Group page of the Create Terminated EE Group FRA component.

5. Process the off-cycle calendar group created in step 4 and generate payslips.

Process the off-cycle calendar group on the Calculate Absence and Payroll run control page.

Generate payslips on the Create/Print Payslips FRA page page.

6. Retrieve/extract employee data for the termination certificates.

Do this on Extract Termination Data FRA page.

7. Review and modify extracted employee data prior to generating the termination certificates.

To do this, use the pages in the Update Termination Data FRA component.

8. Generate the ASSEDIC termination reports.

To do this, use the Termination Report FRA page.

Delivered termination reports include the ASSEDIC Certificate (*Attestation ASSEDIC*), the Work Certificate (*Certificat de travail*), and the Last Payment Receipt (*Reçu pour Solde de Tout Compte*)


9. Prepare payments.

To do this, set up and run the banking process using the banking pages in the Global Payroll core application and Global Payroll for France.

See Understanding Banking Setup and Processing for France.

Image: Termination business process

This diagram provides a high-level view of the termination business process



This process can be summarized as follows:

1. Create the terminated employee group.
2. Review the off-cycle group. (Optional)
3. Review the off-cycle calendar group. (Optional)
4. Launch the payroll identification and calculation for the off-cycle calendar group to which terminated employees are attached.
5. Review payee messages.
6. Review payroll results.
7. Review payee status.
8. Determine if payroll is correct. If not correct, return to step 4.
9. Finalize termination group.

10. Prepare and edit payslip.
11. Launch the data extraction/retrieval process for the termination group.
12. Update the termination data if necessary.
13. Edit the termination reports.
14. Prepare payments.

Prerequisites

In order to generate the termination reports correctly, you must complete the following steps:

- Set up retro and segmentation triggers to detect terminated employees; map actions/reasons that you have set up to trigger termination processing to the termination reasons that will appear in a payee's termination reports; map variables to the ASSEDIC certificate flag to trigger ASSEDIC data extraction and report generation for terminated payees.

See [Understanding Termination Processing](#).

- Define organizational data in the Company, Establishment, and Location tables.
- Define employee personal data and job data.

Creating an Off-Cycle Group for Processing Terminated Payees

Use the pages in the Create Terminated EE Group FRA component to create an off-cycle group for processing terminated payees.

This section discusses how to:

- Create an off-cycle calendar group.
- Assign terminated employees to an off-cycle group.
- Create an off-cycle calendar group.

Pages Used to Create an Off-Cycle Group for Processing Terminated Payees

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Termination Group	GPFR_OFFCYCLE_GRP	Global Payroll & Absence Mgmt, Termination Processing, Create Terminated EE Group FRA, Termination Group	Create an off-cycle group for processing terminated payees.

Page Name	Definition Name	Navigation	Usage
Terminated Employees	GPFR_TER_EE_SEL	Global Payroll & Absence Mgmt, Termination Processing, Create Terminated EE Group FRA, Terminated Employees	Assign terminated payees to the off-cycle group.
Off-cycle Calendar Group	GPFR_OFFCYC_CALGRP	Global Payroll & Absence Mgmt, Termination Processing, Create Terminated EE Group FRA, Off-cycle Calendar Group	Create an off-cycle calendar group.

Termination Group Page



Use the Termination Group page (GPFR_OFFCYCLE_GRP) to create an off-cycle group for processing terminated payees.

Navigation

Global Payroll & Absence Mgmt, Termination Processing, Create Terminated EE Group FRA, Termination Group

Image: Termination Group page

This example illustrates the fields and controls on the Termination Group page. You can find definitions for the fields and controls later on this page.

Termination Group		Terminated Employees		Off-cycle Calendar Group	
Termination ID:	TEST	Pay Group:	GFPGMEN101		
Period ID:	GFM2004-08	Country:	FRA		
Period Begin Date:	08/01/2004	Period End Date:	08/31/2004		
*Description:	<input type="text" value="Employees term to 31/8/04"/>				
*Date of Pay:	<input type="text" value="10/18/2004"/> 				
*Payment Method:	<input type="text" value="Check"/> 				

Termination ID

This field identifies of the termination group.

Pay Group

Displays the pay group to which the terminated employees belong.

Period ID

Displays the pay period in which the terminations are being processed.

Country

Displays the value *France*.

Period Begin Date and Period End Date

These fields display the begin and end dates of the period.

Description

Enter a free form description of the termination group.

Date of Pay

Defaults to the current date. The date cannot be changed to a date prior to the Period Begin Date.

The payment date is applicable to all employees in the termination group. To modify the payment date for a single employee in the group, use the Global Payroll core off-cycle component.

Payment Method

Defaults to *Check*. Options include: *Check*, *Cash*, *(bank) Transfer*, *Post order*, and *Wire (transfer)*.

Terminated Employees page

Use the Terminated Employees page (GPFR_TER_EE_SEL) to assign terminated payees to the off-cycle group.

Navigation

Global Payroll & Absence Mgmt, Termination Processing, Create Terminated EE Group FRA, Terminated Employees

Image: Terminated Employees page

This example illustrates the fields and controls on the Terminated Employees page. You can find definitions for the fields and controls later on this page.

The screenshot displays the 'Terminated Employees' page with the following sections:

- Termination Group** (selected): TEST, Pay Group: GFPGMEN101, Period ID: GFM2004-08, Country: FRA, Period Begin Date: 08/01/2004, Period End Date: 08/31/2004.
- Retrieval Criteria**:
 - Calendar Group Details: Customize | Find | View All | First 1 of 1 Last
 - Table with 2 columns: Select, Calendar Group ID. Row 1: 1 ☐ GFCG08/2004FR101.
 - Begin Date: 08/01/2004, End Date: 08/31/2004 (with a calendar icon).
 - Retrieve button.
- Terminated Employees Selection**:
 - Select All, Deselect All buttons.
 - Terminated Employees Selection: Customize | Find | View All | First 1 of 1 Last
 - Employee Selection | Employee Details (selected) | SEE button.
 - Table with 11 columns: Select, Employee ID, Employment Record Number, Last Name, First Name, Contract Number, Termination Date, Action, Reason, Termination Period. Row 1: 1 ☐ , , 0, , , , , , , .

Calendar Group Details

Calendar Group ID

The system displays all calendar groups associated with the Period ID used to create the termination group. The displayed calendar groups are not finalized.

Select the calendar group in which you want the terminated employees to be processed.

Description

The system displays a description of all calendar groups.

Begin Date and End Date

Enter an end date to define a period of time within which to retrieve terminated employees. The begin date is populated automatically and cannot be changed. The end date must be within the calculation period.

Retrieve

Click to retrieve a list of terminated employees.

The process retrieves employees who meet the first two criteria and *either* the third or fourth criteria:

- Employees who have a retro or segmentation trigger specified on the Extraction Setup page.
- Employees who are part of the selected pay group.
- Employees with a segmentation trigger within the dates specified for retrieval. The trigger date minus one day must be included in the selection dates, OR
- Employees having a retro trigger status other than *Cancelled*.

Retroactive triggers are created for one EMPLID/Employee Record combination. So identifying an employee as retroactively terminated based only on the Retro triggers is not enough, since there is a risk of considering all the employee's records as terminated when the termination may be effective for only one record. Segmentation triggers, when created, should be for one employee/record.

In order to identify the employee and the job to be processed as retroactively terminated, the system looks at employees with a retro trigger, and for those employees, considers segmentation triggers with the same date as the retro trigger. This segmentation trigger identifies the record and the job to be considered in the list of terminated employees.

For this reason, you should confirm that the termination triggers are set up identically for both the segmentation and the retroactive triggers.

See [Understanding Termination Processing](#).

- Employees retrieved based on the previous criteria cannot have a status of finalized.

Terminated Employees Selection: Employee Selection

Select

By default, all employees retrieved are selected. You can manually deselect the check box of any employees who are not to be included in the termination group. You can select or deselect all employees by clicking the buttons at the top of the group box.

Note: The Select check box is designed specifically for employees who have several contracts in the period. To respect the chronological order in the calculation between contracts, if two contracts are displayed on the page for the same employee/record, you cannot deselect the first contract if the second contract is selected. Contracts can be selected only in chronological order and can be deselected only in the reverse chronological order.

Termination Date

The termination date corresponds to the contract number displayed.

Termination Period

The Termination Period field indicates why an employee was selected for termination processing.

The system displays *Current* if the employee was selected based on a segmentation trigger. The system displays *Retro* if the employee was selected based on a retro trigger.

Payee selection based on retroactive triggers is mandatory in the case of retroactive terminations. For example: after finalizing the January payroll, the payroll department discovers that an employee was effectively terminated on January 25.

The payroll administrator then enters the termination in the January calendar, producing a retroactive and a segmentation trigger with an effective date of January 25. When extracting terminated employees at the beginning of February, the payroll department specifies retrieval dates of 1 February to 15 February. If employee selection is not based on retroactive triggers, it would be impossible to retrieve the employee in this time frame. This is because the segmentation trigger is created in January, and has an effective date of January 25.

As noted earlier, however, the system picks up any employee with a retro trigger status other than *Cancelled*, regardless of the trigger effective date. In other words, it is possible for employees terminated retroactively to be selected even though their termination dates are not included within the retrieval Begin and End dates.

Note: A terminated group cannot be saved if no employee is selected. This situation can occur if you deselect All Employees or if the retrieval process finds no terminated employee corresponding to extraction criteria.

Terminated Employees Selection: Employee Details

Payment Method

This field is populated with the default payment method specified on the Termination Group page. You can override the default payment method for individual employees.

Off-cycle Calendar Group Page

Use the Off-cycle Calendar Group page (GPFR_OFFCYC_CALGRP) to create an off-cycle calendar group.

Navigation

Global Payroll & Absence Mgmt, Termination Processing, Create Terminated EE Group FRA, Off-cycle Calendar Group

Image: Off-cycle Calendar Group page

This example illustrates the fields and controls on the Off-cycle Calendar Group page. You can find definitions for the fields and controls later on this page.

The screenshot displays the 'Off-cycle Calendar Group' page within a web application. At the top, there are three tabs: 'Termination Group', 'Terminated Employees', and 'Off-cycle Calendar Group', with the third tab being the active one. Below the tabs, the page is divided into two columns of information:

- Left Column:**
 - Termination ID: TEST
 - Period ID: GFM2004-08
 - Period Begin Date: 08/01/2004
- Right Column:**
 - Pay Group: GFPGMEN101
 - Country: FRA
 - Period End Date: 08/31/2004

Below this information is a section titled 'Off-Cycle Calendar Group' with a blue header. Inside this section, there are three radio button options for group creation:

- ☒ Create New Group: This option is selected, and a text input field next to it contains the value 'TESTCGE'.
- ☐ Attach to an Existing Group: This option is unselected, and a text input field next to it is empty.
- ☐ Attach to a Group later: This option is unselected and has no associated input field.

At the bottom of the page, there is a 'Create Off-cycle Group' button. Below the button are two links: 'Off-Cycle Group Definition' and 'Calendar Group Definition'.

Create New Group	Select to create a new off-cycle calendar group. The name of the group is generated automatically and appears in the field to the right.
Attach to an Existing Group	Select to attach the termination group you created to an existing off-cycle calendar group, and enter the name of the calendar group in the field to the right.
Attach to a Group later	Select to attach the termination group you created to an off-cycle calendar group at a later date. You can save your termination group definition without attaching it to an off-cycle calendar group, and return later to define the calendar group.
Create Off-cycle Group	Click to create the off-cycle group.
Off-Cycle Group Definition	When the off-cycle termination group is created, no modifications are allowed to the group from the Global Payroll for France pages. Click the Off-Cycle Group Definition link to access the Global Payroll core Off-Cycle Requests component (GP_OFFCYCLE_SETUP) to make modifications.
Calendar Group Definition	When the off-cycle calendar group is created, no modifications are allowed to the group from the Global Payroll for France pages. Click the Calendar Group Definition link to access the Global Payroll core Calendar Groups component (GP_CALENDAR_RUN) to make modifications or create calendar groups manually.

Calculating and Finalizing the Off-Cycle Termination Group

Before running the Termination Data Application Engine process (GPFR_ASS_AE) to extract employee data for the termination reports, you must process and finalize the off-cycle payroll group containing the terminated employees.

Page Used to Calculate and Finalize Off-Cycle Termination Groups

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Calculate Absence and Payroll	GP_RUNCTL	<ul style="list-style-type: none"> Global Payroll & Absence Mgmt, Absence and Payroll Processing, Calculate Absence and Payroll, Calculate Absence and Payroll Global Payroll & Absence Mgmt, Absence and Payroll Processing, Off Cycle, Process Off Cycle, Calculate Absence and Payroll 	<p>Calculate and finalize off-cycle termination groups.</p> <p>This page is described in detail in the core Global Payroll .</p>

Extracting Data for Terminated Employees

This section provides an overview of the data extraction process and discusses how to run the data retrieval process.

Page Used to Extract Data for Terminated Employees

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Extract Termination Data FRA	GPFR_ASS_DATA_RUN	Global Payroll & Absence Mgmt, Termination Processing, Extract Termination Data FRA, Extract Termination Data FRA	Run the Termination Data process which retrieves information about terminated employees that is required for the termination reports.

Understanding the Data Extraction Process

After processing and finalizing the off-cycle payroll group containing the terminated employees, run the Termination Data Application Engine process (GPFR_ASS_AE) to extract the data needed to produce the ASSEDIC certificate, the Work Certificate, and the Last Payment Receipt from Global Payroll and HR records. The Application Engine process loads the data into staging tables where it can be prepared and updated prior to generating the termination reports.

The data retrieved for the termination reports comes from tables and records in Global Payroll and HR.

<i>Tables</i>	<i>Purpose</i>
GPFR_ASS_COMP	Displays and records data concerning company and establishment information.
GPFR_ASS_PAYEE	Displays and records data concerning the employee.

Tables	Purpose
GPFR_ASS_RUNCTL	Displays and records data concerning the process of mass edition. Enables the capture of the Frame 9 ASSEDIC certificate information and the selection of departing employees.
GPFR_ASS_SELECT	Displays and records the main data retrieval process information.
GPFR_ASS_PRINT	<p>Displays and records employees requiring an ASSEDIC certificate.</p> <hr/> <p>Note: Another record (GPFR_ASS_PRINT2) is built with the same definition. Its purpose is to make the connection between the payees to print and the queries defined for the Crystal report.</p> <hr/>
GPFR_ASS_WAGE_1	Displays and records data concerning the wages and period of pay during the last 12 months.
GPFR_ASS_WAGE_2	Displays and records data concerning bonus or compensation other than monthly salary.
GPFR_ASS_WAGE_3	Displays and records data concerning the amounts paid after the last complete month.
GPFR_ASS_WA	<p>Stores the results of accumulators after each payroll run. Application Engine reads this table to insert and update the record-dedicated writable array results concerning wages. The writable array for this functionality is GP WA AA ELMT.</p>
GPFR_ASS_SECU	Stores the security number required for Pôle Emploi control services.
GPFR_LPR_PAYEE	Stores employee information for the last payment receipt.
GPFR_WC_PAYEE	Stores employment begin and end dates, plus a comment for the employee that is used in the work certificate.
GPFR_WC_POS	Stores employees' job descriptions that are required for the work certificate.

Prerequisites

Verify that you have selected payees for the final payroll process using the delivered GEN VR TEST DEPART variable or a variable you have defined yourself. The employee's data is retrieved only if this variable equals 1 (meaning the employee has left during the month). You must identify the variable you are using on the Element Mapping Codes FRA page.

See [Elements Mapping Codes FRA Page](#).

Extract Termination Data FRA Page

Use the Extract Termination Data FRA page (GPFR_ASS_DATA_RUN) to run the Termination Data process which retrieves information about terminated employees that is required for the termination reports.

Navigation

Global Payroll & Absence Mgmt, Termination Processing, Extract Termination Data FRA, Extract Termination Data FRA

Image: Extract Termination Data FRA page

This example illustrates the fields and controls on the Extract Termination Data FRA page. You can find definitions for the fields and controls later on this page.

Extract Termination Data FRA

Run Control ID: PS [Report Manager](#) [Process Monitor](#) [Run](#)

Population Selection

*Calendar Group ID: Pay Entity:

Certification

Place for Signature: Date of Signature:

Name:

Status of Signer:

Person Responsible for Certif:

Phone Number: [Select](#)

Select Result [Customize](#) | [Find](#) | [View All](#) | [First](#) | [1 of 1](#) | [Last](#)

	Retrieval	Print Requested	Employee ID	Empl Record	Name	Termination Date
1	<input type="checkbox"/>	<input type="checkbox"/>		0		<input type="text" value="10/20/2006"/>

Population Selection

Use this group box to select the employees you want to include in the termination data retrieval process based on calendar group ID and pay entity.

Certification

Use this group box to enter details of the person who signs the termination reports.

Place for Signature

Enter the name of the city or other location where the certificate will be signed.

Date of Signature

Enter the date that the certificate will be signed.

Name	Enter the name of the person who signs the certificate on behalf of the employer.
Status of Signer	Select the signer's position in the company: <i>Accountant, Compulsory Liquidator, Director, Manager, Managing Director, Other, Personnel Manager, or Receiver.</i>
Person Responsible for Certif (person responsible for certificate)	Enter the name of the person who is responsible for the certificate.
Select	Click this button to search for employees who meet the selection criteria. The system displays matching employees in the Select Result group box.
Printing Process	Click to access the Termination Report FRA (GPFR_ASS_CER_RNCTL) component, which you use to generate the termination certificates.
Select Result	
Retrieval	Select if you want the system to retrieve data for the employee shown in the EmplID field. The check box is selected automatically if data has not been retrieved before.
Print Requested	Select to print a certificate for the employee. This check box is selected automatically if a certificate has already been printed for this employee.
Termination Date and Action	Displays the date of termination, followed by a description of the termination action in the JOB record.

Reviewing and Updating Retrieved Employee Data

After running the Extract Termination data process, use the Update Termination Data component to review the data retrieved and update it if necessary.

This section discusses how to:

- Review employer data for the ASSEDIC certificate.
- Review employee personal data and complementary fund information.
- Review employee job information (1).
- Review employee job information (2).
- Review contract termination information.
- Review employee salary information.
- Review employee bonus information.

- Review employee allowances.
- Review FNGS and termination reason information.
- Review work certificate information.
- Review last payment receipt information.
- Review certification information.

Pages Used to Review and Update Retrieved Employee Data

Page Name	Definition Name	Navigation	Usage
ASSEDIC Certificate 1	GPFR_ASS_CERTIF_1	Global Payroll & Absence Mgmt, Termination Processing, Update Termination Data FRA, ASSEDIC Certificate 1	Review and modify the employer's ASSEDIC certificate data.
2 and 3	GPFR_ASS_CERTIF_2	Global Payroll & Absence Mgmt, Termination Processing, Update Termination Data FRA, 2 and 3	Review ASSEDIC certificate data for the employee and complementary funds.
4	GPFR_ASS_CERTIF_3	Global Payroll & Absence Mgmt, Termination Processing, Update Termination Data FRA, 4	Review ASSEDIC certificate data related to the employee's job.
4 (end)	GPFR_ASS_CERTIF_4	Global Payroll & Absence Mgmt, Termination Processing, Update Termination Data FRA, 4 (end)	Review ASSEDIC certificate data related to the employee's job.
5 and 6	GPFR_ASS_CERTIF_5	Global Payroll & Absence Mgmt, Termination Processing, Update Termination Data FRA, 5 and 6	Review ASSEDIC certificate data related to the reasons for a contract termination.
7.1	GPFR_ASS_CERTIF_6	Global Payroll & Absence Mgmt, Termination Processing, Update Termination Data FRA, 7.1	Review ASSEDIC certificate data related to the employee's salary for the past 12 months. The data comes from the GP _PYE_PRC_STAT record, which the system creates during payroll processing and from the GPFR_ASS_WA record, dedicated to writable array accumulator results.

Page Name	Definition Name	Navigation	Usage
7.2 and 7.3	GPFR_ASS_CERTIF_7	Global Payroll & Absence Mgmt, Termination Processing, Update Termination Data FRA, 7.2 and 7.3	Review ASSEDIC certificate data related to the employee's bonus and other salary payments.
7.3	GPFR_ASS_CERTIF_8	Global Payroll & Absence Mgmt, Termination Processing, Update Termination Data FRA, 7.3	Review ASSEDIC certificate data related to the employee's allowances. This page is a continuation of Frame 7.3 and covers allowances paid after the last complete month paid.
8 and 9	GPFR_ASS_CERTIF_9	Global Payroll & Absence Mgmt, Termination Processing, Update Termination Data FRA, 8 and 9	Review ASSEDIC certificate data related to FNGS.
Work Certificate	GPFR_WC_PAYEE	Global Payroll & Absence Mgmt, Termination Processing, Update Termination Data FRA, Work Certificate	Review employee information for the Work Certificate.
Last Payment Receipt	GPFR_LPR_PAYEE	Global Payroll & Absence Mgmt, Termination Processing, Update Termination Data FRA, Last Payment Receipt	Review employee information for the Last Payment Receipt report.
Certification	GPFR_CERTIFICATION	Global Payroll & Absence Mgmt, Termination Processing, Update Termination Data FRA, Certification	Review information about the person who signs the termination reports.

ASSEDIC Certificate 1 Page

Use the ASSEDIC Certificate 1 page (GPFR_ASS_CERTIF_1) to review and modify the employer's ASSEDIC certificate data.

Navigation

Global Payroll & Absence Mgmt, Termination Processing, Update Termination Data FRA, ASSEDIC Certificate 1

Image: Termination Data FRA - ASSEDIC Certificate 1 page

This example illustrates the fields and controls on the Termination Data FRA - ASSEDIC Certificate 1 page. You can find definitions for the fields and controls later on this page.

The screenshot displays the 'ASSEDIC Certificate 1' page. At the top, there are tabs for navigating between different certificates (1, 2 and 3, 4, 4 (end), 5 and 6, 7.1, 7.2 and 7.3, 7.3, 8 and 9, and Work Certificate). Below the tabs, the employee's name 'Florence LEMERRE' is shown along with their ID 'GF100ME806' and 'Empl Record: 0'. The 'Company/Establishment' section contains fields for 'Company' (Société Française 8), 'Establishment' (Etl 8 Administration), 'Legal Status' (SA), 'Phone Number', 'SIRET' (8888888888881), 'APE Code' (511C), 'Nbr of Employees at past 12/31', 'ASSEDIC NUMBER', and 'Indicator of subscription'. At the bottom, there are two main sections: 'Overwrite Employer's Data' with an 'Override' checkbox, and 'Print Data' with a 'Printing Already Requested' checkbox and a 'Printing Process' button.

Company/Establishment

This is populated with the name of the company and establishment that employed the terminated employee. This information is extracted from the Company and Establishment tables.

Company

Displays the name of the company that employed the terminated employee. This information is extracted from the Company table.

Establishment

Displays the name of the establishment that employed the terminated employee. This information is extracted from the Establishment table.

Juridic Status

Displays the company's legal entity as specified in the Company table.

SIRET

Displays the SIRET code entered in the Establishment table.

APE Code

Displays the APE code entered in the Establishment table.

Nbr of Employees Past 12/31 (number of employees past 12/31)

Displays the number of employees in the establishment, as calculated by the previous December's URSSAF DUCS for this establishment.

ASSEDIC Number

Displays the ASSEDIC number entered in the Establishment table. The ASSEDIC number begins with a three-digit ASSEDIC code. GARP is defined with a number from 055 to

062. ASSEDIC is defined with another number. Each ASSEDIC is defined on the DUCS Contact Definition page.

Indicator of subscription

Displays the appropriate indicator: *ASSEDIC*, *GARP*, and *Other*. You can change this value.

Overwrite Employer's Data**Override**

Select if you want to override the company and establishment data.

Print Data**Printing Already Requested**

Select if the certificate has already been printed. To reprint, deselect the check box to activate the Printing Process button.

Printing Process

Click this button to open the Termination Reports run control page. You are prompted to add a new run control ID.

Note: If you want to print several certificates in one run, go directly to the Termination Report FRA page by selecting Global Payroll & Absence Mgmt, Termination Processing, Termination Reports FRA.

2 and 3 Page

Use the 2 and 3 page (GPFR_ASS_CERTIF_2) to review ASSEDIC certificate data for the employee and complementary funds.

Navigation

Global Payroll & Absence Mgmt, Termination Processing, Update Termination Data FRA, 2 and 3

Image: Termination Data FRA - 2 and 3 page

This example illustrates the fields and controls on the Termination Data FRA - 2 and 3 page. You can find definitions for the fields and controls later on this page.

Payee (Frame 2)

This group box displays the employee's name, address, and other personal data from the Personal Data component.

Does the Employee have any Relationship with Manager?

Select if the employee is related to the manager.

Manager or Managerial Status

Select if the employee is a manager.

Qualification Level

Displays the qualification level entered in the Job Data component.

Comp. Pension Fund (Frame 3)

ARRCO

Displays the ARRCO fund entered in the Pension/Contingency Funds component.

AGIRC

Displays the AGIRC fund entered in the Pension/Contingency Funds component.

Other

Displays any other fund entered in the Pension/Contingency Funds component.

4 Page

Use the 4 page (GPFR_ASS_CERTIF_3) to review ASSEDIC certificate data related to the employee's job.

Navigation

Global Payroll & Absence Mgmt, Termination Processing, Update Termination Data FRA, 4

Image: Termination Data FRA - 4 page

This example illustrates the fields and controls on the Termination Data FRA - 4 page. You can find definitions for the fields and controls later on this page.

ASSEDIC Certificate 1 2 and 3 **4** 4 (end) 5 and 6 7.1 7.2 and 7.3 7.3 8 and 9 Work Certificat

Name: Florence LEMERRE ID: GF100ME806 Empl Record: 0

Job

Duration of the Salaried Employment Hire Date: 01/01/2000 Term Date: 04/14/2008

Job Code: GFJO03 Manager Training

Notification date: Last Date Worked: 04/14/2008

Notice Period

☐ Notice Period Done

☐ Notice Period not Done

Special Security Fund: Number:

☐ Alsace-Moselle Local System

Job

This group box displays the employee's Hire Date, Termination Date, Job Code, Notification Date and Last Date Worked in the Job Data component.

Notice Period

Notice Period Done

Select if the employee has completed all or part of the required notice period. The related From and To fields appear in which you can enter the begin and end dates of the notice period.

Notice Period not Done

Select the Notice Period not Done check box if the employee has not completed the required notice period or if only part of the notice period has been completed. The Notice Period Paid and Notice Period not Paid check boxes appear.

Note: If only part of the notice period has been completed, select *both* the Notice Period Done and the Notice Period not Done check boxes.

Notice Period Paid

Select the Notice Period Paid check box if all or part of the notice period has been paid. The related From and To fields appear in which you can enter the begin and end dates of the paid period.

Notice Period not Paid

Select if all or part of the notice period has not been paid. The related From and To fields appear in which you can enter the begin and end dates of the notice period not paid.

Special Security Fund

Enter the special security fund, if any.

Number

Enter the number of the special security fund if you entered one in the Special Security Fund field.

Alsace-Moselle Local System

This check box is selected if the establishment postal code is in the Alsace-Moselle region (departments 57, 67, or 68).

4 (end) Page

Use the 4 (end) page (GPFR_ASS_CERTIF_4) to review ASSEDIC certificate data related to the employee's job.

Navigation

Global Payroll & Absence Mgmt, Termination Processing, Update Termination Data FRA, 4 (end)

Image: Termination Data FRA - 4 (end) page

This example illustrates the fields and controls on the Termination Data FRA - 4 (end) page. You can find definitions for the fields and controls later on this page.

ASSEDIC Certificate 1 2 and 3 4 4 (end) 5 and 6 7.1 7.2 and 7.3 7.3 8 and 9 V

Name: Florence LEMERRE ID: GF100ME806 Empl Record: 0

Job

CDD / CDI: CDI

Part Contract:

Particular Status:

Particular Job Categories

☐ Child Caregiver ☐ Intermittent Worker ☐ Household Employee

☐ Expatriate ☐ Home Worker ☐ Temporary Employee

☐ Other Particular Job

Number of Worked Hours

	Weekly:	Annual:
In The Company After Agreement or Collective Labor Agreement	35.00	
Employee's Hours	17.50	

Reason in Case of Difference: Partial Time

Job

CDD/CDI

Displays the type of employment contract, *CDD* (limited contract), or *CDI* (unlimited contract) that was entered on the Contract Data component.

Part Contract

Displays the particular contract entered on the Contract Data component: *Adaptation Contract*, *Apprenticeship Contract*, *Solidarity Contract*, *Other*, *Qualification Contract*, and *Orientation Contract*.

If you select *Other*, enter a description of the particular contract in the text box that appears.

Particular Status

Displays the particular status entered on the Contract Data component: *Managing Director*, *Board Member*, *Member of executive board*, *Member of supervisory board*, *Chairman of an association*, *EIG Member*, *Partner*, and *Other*.

If you select *Other*, enter a description of the particular status in the text box that appears.

Particular Job Categories

Select the check box for the specific job category that applies.

Number of Worked Hours

Weekly and Annual

Displays the standard number of weekly or annual work hours that are entered on either of the following:

- Business Unit Options Default page for the company.
- Job Data component for the employee.

Reason in Case of Difference

Displays the reason that the weekly or annual hours differ, if any: *Other Reason* and *Partial Time*.

5 and 6 Page

Use the 5 and 6 page (GPFR_ASS_CERTIF_5) to review ASSEDIC certificate data related to the reasons for a contract termination.

Navigation

Global Payroll & Absence Mgmt, Termination Processing, Update Termination Data FRA, 5 and 6

Image: Termination Data FRA - 5 and 6 page

This example illustrates the fields and controls on the Termination Data FRA - 5 and 6 page. You can find definitions for the fields and controls later on this page.

ASSEDIC Certificate 1 2 and 3 4 4 (end) 5 and 6 7.1 7.2 and 7.3 7.3 8 and 9 W

Name: Florence LEMERRE ID: GF100ME806 Empl Record: 0

Full Unemployment (Frame 5)

☐ Complete Unemployment ?

☐ Did You Ask for Allocation from DDTEFP ?

Reason for Breach (Frame 6)

Reason of Breach of Contract: 59 Resignation

Reason:

☐ Social Plan ? Social Plan Dt of Presentation to Personel Representatives

Payee Aged 55 and More

☐ Did the Employee refuse to subscribe to FNE Convention ?

Full Unemployment (Frame 5)

Complete Unemployment?

Select if the unemployment period follows ASSEDIC's definition of complete unemployment.

Did You Ask for Allocation from DDTEFP?

Select if you asked for DDTEFP (*Direction Du Travail, de l'Emploi, et de la Formation Professionnelle*) allocation. The related From, To, and Foreseen Date to Resume Work fields appear in which you can enter the begin and end dates of the period of compensation as well as the anticipated date for returning to work.

Reason for Breach (Frame 6)**Reason of Breach of Contract**

Displays the termination action/reason code entered on the Job Data component. If the action/reason code is 20 (other dismissal reason), 59 (resignation), or 60 (other breach reason), the Reason field appears (see below).

Note: The system populates this field based on the mappings between Job Data actions/reasons and ASSEDIC reasons on the Assedic Reasons page.

Reason

Enter the specific reason for the breach of contract for action/reason codes 20, 59, or 60.

Social Plan?

Select if the employee is laid off within a social plan. The Social Plan Date field appears.

Social Plan Dt (social plan date)

Enter the date of the social plan.

Payee Aged 55 and More**Did the Employee Refuse to Subscribe to FNE Convention?**

Select this check box if the employee refused to subscribe to the FNE convention.

7.1 Page

Use the 7.1 page (GPFR_ASS_CERTIF_6) to review ASSEDIC certificate data related to the employee's salary for the past 12 months.

The data comes from the GP_PYE_PRC_STAT record, which the system creates during payroll processing and from the GPFR_ASS_WA record, dedicated to writable array accumulator results.

Navigation

Global Payroll & Absence Mgmt, Termination Processing, Update Termination Data FRA, 7.1

Image: Termination Data FRA - 7.1 page

This example illustrates the fields and controls on the Termination Data FRA - 7.1 page. You can find definitions for the fields and controls later on this page.

ASSEDIC Certificate 1

2 and 3

4

4 (end)

5 and 6

7.1

7.2 and 7.3

7.3

8 and 9

Work Certificate

Name: Florence LEMERRE

ID: GF100ME806

Empl Record: 0

Salary of the 12 Previous Full Civil Months

Customize

Find

View All

First

1-3 of 3

Last

	Begin Date of Period Pay	To	Date of Pay	Worked Hours	Number of Days Partly Paid	Gross pay	Employee's ASSEDIC Amount	Text	Currency		
1	03/01/200	03/31/20	03/31/20	147.00		3000.00	72.00		EUR		
2	02/01/200	02/29/20	02/29/20	147.00		3000.00	72.00		EUR		
3	01/01/200	01/31/20	01/31/20	161.00		3000.00	72.00		EUR		

Begin Date of Period Pay

Displays the begin date of the pay period for this payee from the GP_PYE_PRC_STAT record (the Pay Process Stat record).

To

Displays the end date of the pay period for this payee from the GP_PYE_PRC_STAT record.

Date of Pay

Displays the actual pay date for this payee from the GP_PYE_PRC_STAT record.

Worked Hours

Displays the calculated work hours from the GPFR_ASS_WA record.

Number of Days Partly Paid

Displays the number of days partly paid from the GPFR_ASS_WA record.

Gross Pay

Displays the gross pay from the GPFR_ASS_WA record.

Employee's ASSEDIC Amount

Displays the employee's ASSEDIC amount from the GPFR_ASS_WA record.

Text

Enter additional comments.

Currency

Displays the currency from the GP_PYE_PRC_STAT record.

7.2 and 7.3 Page

Use the 7.2 and 7.3 page (GPFR_ASS_CERTIF_7) to review ASSEDIC certificate data related to the employee's bonus and other salary payments.

Navigation

Global Payroll & Absence Mgmt, Termination Processing, Update Termination Data FRA, 7.2 and 7.3

Image: Termination Data FRA - 7.2 and 7.3 page

This example illustrates the fields and controls on the Termination Data FRA - 7.2 and 7.3 page. You can find definitions for the fields and controls later on this page.

ASSEDIC Certificate 1 2 and 3 4 4 (end) 5 and 6 7.1 7.2 and 7.3 7.3 8 and 9 Work Certificate

Name: Florence LEMERRE ID: GF100ME806 Empl Record: 0

Bonus and Compensation of Different Periodicity (Frame 7) Customize Find View All 1 of 1 Last

	Payment Period Begin Date	Payment Period End Date	Date of Payment	Bonus or Allowance Type	Bonus' Amount	Currency
1						

Salary Paid (Frame 7.3)

From Date	To Date	Pay Date	Worked Hours	Gross Pay	Employee's ASSEDIC Amount
04/01/2008	04/14/2008	04/30/2008	70.00	4573.08	109.76

Currency Code in which was delivered the Leaving Employee's Final Pay EUR

Bonus and Compensation of Different Periodicity (Frame 7)

This group box displays the premiums or allowances for the 12 calendar months preceding the last day worked. The data comes from several result tables that the system creates during payroll processing, such as the GP_RSLT_ERN_DED, GP_PYE_PRC_STAT, and GP_PIN records.

Payment Period Begin Date	Displays the begin date of the bonus or allowance from the GP_RSLT_ERN_DED record.
Payment Period End Date	Displays the end date of the bonus or allowance from the GP_RSLT_ERN_DED record.
Date of Payment	Displays the payment date of the bonus or allowance from the GP_PYE_PRC_STAT record.
Bonus or Allowance Type	Displays the name of the bonus or allowance from the GP_PIN record.
Bonus' Amount	Displays the bonus or allowance amount from the GP_RSLT_ERN_DED record.
Currency	Displays the currency from the GP_PYE_PRC_STAT record.

Note: The GP_RSLT_ERN_DED record contains the results of earnings and deductions after batch processing.

Salary Paid (Frame 7.3)

This group box displays the amounts paid after the last complete month paid (after the amounts listed on the 7.1 page and corresponding to the employee's final pay). The data comes from several result tables that the system creates during payroll processing, such as the GP_RSLT_ERN_DED and GP_PYE_PRC_STAT records. It also draws data from the GPFR_ASS_WA record, dedicated to writable array accumulator results.

Note: The amounts on this page must be in the same currency as those on the Termination Data FRA - 7.1 page.

From Date	Displays the begin date of the bonus from the GP_RSLT_ERN_DED record.
To Date	Displays the end date of the bonus from the GP_RSLT_ERN_DED record.
Pay Date	Displays the payment date of the bonus from the GP_PYE_PRC_STAT record.
Worked Hours	Displays the number of hours worked, including overtime, for each period from the GPFR_ASS_WA record.
Gross Pay	Displays the employee's gross pay for the period specified from the GPFR_ASS_WA record.
Employee's ASSEDIC Amount	Displays the employee's ASSEDIC contribution amount from the GPFR_ASS_WA record.
Currency Code in which was delivered the Leaving Employee's Final Pay	Displays the currency code in which the departing employee's final pay was delivered from the GP_PYE_PRC_STAT record.

7.3 Page

Use the 7.3 page (GPFR_ASS_CERTIF_8) to review ASSEDIC certificate data related to the employee's allowances.

This page is a continuation of Frame 7.3 and covers allowances paid after the last complete month paid.

Navigation

Global Payroll & Absence Mgmt, Termination Processing, Update Termination Data FRA, 7.3

Image: Termination Data FRA - 7.3 page

This example illustrates the fields and controls on the Termination Data FRA - 7.3 page. You can find definitions for the fields and controls later on this page.

The screenshot shows a web application interface for 'Termination Data FRA - 7.3'. At the top, there is a navigation bar with tabs labeled 'ASSEDIC Certificate 1', '2 and 3', '4', '4 (end)', '5 and 6', '7.1', '7.2 and 7.3', '7.3' (selected), '8 and 9', and 'W'. Below the navigation bar, the employee information is displayed: 'Name: Florence LEMERRE', 'ID: GF100ME806', and 'Empl Record: 0'. The main section is titled 'Allowances' and contains several input fields and checkboxes. The 'Notice Period' field is empty. The 'Professional Fund' field is empty. The 'Paid Vacation' field contains the value '3173.08'. The 'Number of Working Days' field is empty. There are two columns of checkboxes for various allowances: 'Redundancy's Legal Allowance', 'Additional Redundancy's Allow', 'End Fixed-Term Contract Allow', 'Allowance for End of Mission', 'Allowance of Retirement', 'Negotiated Compensation Agreement?', 'Special Allowance of Dismissal', 'Allowance for Journalist', 'Allowance of Customer', 'Allowance for Crew', and 'Other Legal Allowances'. Below these checkboxes, there are two more input fields: 'Allowance for Negotiated Compensation Agreement' and 'Allowance for Collective Labor Agreement'. At the bottom, there is a section titled 'Sums' with two input fields: 'Sum of all Allowances:' and 'Amount for Legal Allowances:'.

This page displays accumulator values for various allowances from the record GPFR_ASS_WA , dedicated to writable array results. The Extract Termination Data process retrieves these values after the payroll process populates this record with the current accumulator amounts.

Allowances

If an allowance check box is selected, the page displays the amount of the selected allowance based on the results in the GPFR_ASS_WA record. Select the check box to manually enter an amount.

Notice Period	Displays the allowance notice period from the GPFR_ASS_WA record.
Professional Fund	Enter the name of the professional fund for the paid vacation amount.
Paid Vacation	Displays the amount of paid vacation from the GPFR_ASS_WA record.
Number of Working Days	Displays the number of working days from the GPFR_ASS_WA record.
Negotiated Compensation Agreement?	Select if the employee has a negotiated compensation agreement.

Allowance for Negotiated Compensation Agreement

Displays the amount of the negotiated compensation agreement allowance based on the results in the GPFR_ASS_WA record.

Allowance for Collective Labor Agreement

Displays the amount of the collective labor agreement allowance based on the results in the GPFR_ASS_WA record.

Sums**Sum of all Allowances**

Displays the total amount of legal, collective labor agreement, or negotiated financial compensation allowances for dismissal based on the results in the GPFR_ASS_WA record.

Amount for Legal Allowances

Displays the total amount of the legal allowances based on the results in the GPFR_ASS_WA record.

8 and 9 Page

Use the 8 and 9 page (GPFR_ASS_CERTIF_9) to review ASSEDIC certificate data related to FNGS.

Navigation

Global Payroll & Absence Mgmt, Termination Processing, Update Termination Data FRA, 8 and 9

Image: Termination Data FRA - 8 and 9 page

This example illustrates the fields and controls on the Termination Data FRA - 8 and 9 page. You can find definitions for the fields and controls later on this page.

ASSEDIC Certificate 1 2 and 3 4 4 (end) 5 and 6 7.1 7.2 and 7.3 7.3 **8 and 9** V

Name: Florence LEMERRE **ID:** GF100ME806 **Empl Record:** 0

Authentication from Employer

In the Event of Company Turnaround or Winding Up

FNGS Payment: **Reason**

Authentication (Frame 9)

Reason for Breach (recall):

Person Responsible for Certif:

Telephone:

FNGS (Frame 8)

FNGS Payment

Select an option that describes the processing of the FNGS payment to be printed on the ASSEDIC certificate:

No, will not be received.

No, is not received.

Yes, already received.

Yes, will be received.

If the FNGS won't be processed, the Reason field appears. If the FNGS will be processed, the For Which Claim field appears.

Reason

Enter the reason for the lack of payment to FNGS.

For Which Claim

Enter the claim description for the FNGS payment.

Reason for Breach

Reason for Breach (recall)

Displays the termination action/reason code, as entered in the Job Data component.

**Person Responsible for Certif
(person responsible for certificate)**

Displays the person responsible for the certificate, as entered on the Extract Termination Data page.

Telephone

Displays the telephone number of the person responsible for the certificate, as entered on the Extract Termination Data page.

Work Certificate Page

Use the Work Certificate page (GPFR_WC_PAYEE) to review employee information for the Work Certificate.

Navigation

Global Payroll & Absence Mgmt, Termination Processing, Update Termination Data FRA, Work Certificate

Image: Termination Data FRA - Work Certificate page

This example illustrates the fields and controls on the Termination Data FRA - Work Certificate page. You can find definitions for the fields and controls later on this page.

Name: Florence LEMERRE **ID:** GF100ME806 **Empl Record:** 0

Work Certificate

Employment Begin Date:

Employment End Date:

Employer's Comments:

Employments [Customize](#) | [Find](#) | [View All](#) | | [First](#) | **1 of 1** | [Last](#)

	*Begin Date	*End Date	Job Description		
1	01/01/2000	04/14/2008	Manager Training		

This page displays employee's hire and termination dates extracted from Job Data. The information on this page is printed on the Work Certificate, together with employer information.

Employer's Comments

(Optional) Enter any comments that you want to print on the Work Certificate.

Employments

This group box lists job descriptions for the jobs held by the employee while employed by the organization.

Last Payment Receipt Page

Use the Last Payment Receipt page (GPFR_LPR_PAYEE) to review employee information for the Last Payment Receipt report.

Navigation

Global Payroll & Absence Mgmt, Termination Processing, Update Termination Data FRA, Last Payment Receipt

Image: Termination Data FRA - Last Payment Receipt page

This example illustrates the fields and controls on the Termination Data FRA - Last Payment Receipt page. You can find definitions for the fields and controls later on this page.

Navigation tabs: 4, 4 (end), 5 and 6, 7.1, 7.2 and 7.3, 7.3, 8 and 9, Work Certificate, Last Payment Receipt, Certification.

Name: Florence LEMERRE ID: GF100ME806 Empl Record: 0

Last Payment Report

Last Payment: 3684.28

Currency Code: EUR euro

Last Payment Receipt

This group box displays the employee's final payment, as calculated by the payroll process.

Certification Page


Use the Certification page (GPFR_CERTIFICATION) to review information about the person who signs the termination reports.

Navigation

Global Payroll & Absence Mgmt, Termination Processing, Update Termination Data FRA, Certification

Image: Termination Data FRA - Certification page

This example illustrates the fields and controls on the Termination Data FRA - Certification page. You can find definitions for the fields and controls later on this page.



Navigation tabs: 4, 4 (end), 5 and 6, 7.1, 7.2 and 7.3, 7.3, 8 and 9, Work Certificate, Last Payment Receipt, Certification

Name: Florence LEMERRE ID: GF100ME806 Empl Record: 0

Certification

Place for Signature: Paris Date of Signature: 04/27/2006

Name: Mr Treyer

Status of Signer: Personnel Manager

Certification

The system populates this group box with information about the person who signs the termination reports, as specified on the Extract Termination Data FRA page.

Related Links

[Extracting Data for Terminated Employees](#)

Printing Termination Certificates

This section lists prerequisites and discusses how to run termination reports.

Page Used to Run Termination Reports

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Termination Report FRA	GPFR_ASS_CER_RUN	Global Payroll & Absence Mgmt, Termination Processing, Termination Report FRA, Termination Report FRA	<p>Use this page to generate the following reports for terminated employees:</p> <ul style="list-style-type: none"> ASSEDIC Certificate <i>(Attestation ASSEDIC)</i> <p>This is a statutory report that provides information about employee's ASSEDIC (or GARP in Paris) contributions.</p> Work Certificate <i>(Certificat de Travail)</i> <p>This report displays employer information, the terminated employee's name and address, and a list of the employee's jobs while employed by the company.</p> Last Payment Receipt <i>(Reçu pour Solde de Tout Compte)</i> <p>This report details the amount paid to the employee on termination. Employees are normally required to sign this report to confirm receipt of their final payment.</p>

Prerequisite

Access the writable array REP WA AA ELMT and review the mapping between payroll elements for France and fields in the termination certificates. The values displayed in these fields come from the elements to which they are mapped in the array. You can define your own elements to store values displayed in the certificates, and then map them to the appropriate fields using the REP WA AA ELMT array.

Note: To review the definition of a writable array, use the Writable Array (GP_WRITE_ARRAY) component in the Global Payroll core application.

Termination Reports Page

Use the Termination Report FRA page (GPFR_ASS_CER_RUN) to .

Navigation

Global Payroll & Absence Mgmt, Termination Processing, Termination Report FRA, Termination Report FRA

Image: Termination Report FRA page

This example illustrates the fields and controls on the Termination Report FRA page. You can find definitions for the fields and controls later on this page.

Termination Report FRA

Run Control ID: PS [Report Manager](#) [Process Monitor](#)

Selection Criteria

*Calendar Group ID:

Company:

Establishment ID:

Select Result [Customize](#) | [Find](#) | [View All](#) | | | First 1 of 1 Last

Print	EmplID	Empl Record	Name	Reason	Translate Long Name
1 <input type="checkbox"/>		0			

Selection Criteria

Select All

Click to select all employees in the specified Company and Establishment whose data has been retrieved. The termination data extraction process retrieves employee data required for the termination reports.

Select Result

The system populates this group box when you click the Select All button.

Print

Select this check box to print the termination reports for the employee listed. By default, this check box is selected if the reports have not been printed for the employee.

Managing Off-Cycle Payments

Understanding Off-Cycle Processing

This section discusses:

- Off-cycle processing.
- Types of off-cycle transactions.

Off-Cycle Processing

Off-cycle processing refers to processing payments and correcting payroll results outside of the normal payroll schedule. Off-cycle transactions are usually made to correct prior payments, enter manual payments, or to make early termination payments that can't wait until the next scheduled payroll run.

Types of Off-Cycle Transactions

The four types of off-cycle transactions are:

1. Manual payments.

Manual payments enable you to enter payments that you have calculated and paid outside of the payroll system. Examples include paying a new hire with a manual check, because their pay details were not entered in time for the normal pay run.

2. Reversals and corrections.

Reversals and corrections enable you to correct the results of a finalized payroll. Examples include reversing a sick leave payment when worker's compensation should have been paid.

3. Unscheduled payments.

Unscheduled payments enable you to enter one-time payments that fall outside the normal payroll process. Examples include one time bonuses or expense reimbursements.

4. Advances.

Advances enable you to pay payees before their normally scheduled pay run. Examples include salary due on termination.

Note: As delivered, Global Payroll for France does not support the use of any off-cycle type other than advances. Although you can modify the delivered setup to use other off-cycle types, Global Payroll for France cannot guarantee the accuracy of your payroll calculations.

Manual Payments

Global Payroll for France does not support manual payment processing.

- Global Payroll for France declares contribution amounts using the DUCS program. If you enter manual payments, the DUCS program does not take these amounts into account.
- The DADS report is based on specific calculations done during normal payroll processing. DADS data can't be populated using a manual payment process.
- Other reports based on payroll calculations such as the Illness Certificate and the ASSEDIC Certificate can't be produced if payments are entered manually.
- Global Payroll for France prepares data used by other processes and reports such as profit-sharing, the 2483 report, and the Employee Survey report. The data for these reports and processes is not available when payments are entered manually.
- Many calculations that occur during normal payroll processing provide values for future payroll calculations (paid vacation entitlements, seniority, base for absence salary upholding, and so on). Entering manual payments could result in these values not being populated, which would in turn produce false results in the future.

Warning! Global Payroll for France recommends that you do not use manual payment processing.

Related Links

"Recording Manual Payments (*PeopleSoft HCM 9.2: Global Payroll*)"

Reversals and Corrections

Global Payroll for France does not support reversal or correction processing.

Warning! Submitting reversals can have undesirable consequences for contribution declarations. PeopleSoft recommends the use of the delivered retroactive processing rules for France rather than reversal processing.

Related Links

"Correcting or Reversing Finalized Results (*PeopleSoft HCM 9.2: Global Payroll*)"

[Standard Retro Setup In Global Payroll for France](#)

Unscheduled Payments

Global Payroll for France does not support unscheduled payment processing.

Warning! Unscheduled payments can have undesirable consequences for social contribution declarations and annual declarations. PeopleSoft recommends that you do not use the unscheduled payment functionality in Global Payroll.

Related Links

"Making Additional Payments (*PeopleSoft HCM 9.2: Global Payroll*)"

Advance Payments

This section discusses advance payments.

Note: This section supplements the off-cycle documentation in the *PeopleSoft Global Payroll*.

Related Links

"Processing Advances (*PeopleSoft HCM 9.2: Global Payroll*)"

Understanding Advance Payments

Global Payroll for France uses the advance payment functionality in the Global Payroll core application as the basis for the delivered termination process. However, advance payments can be made outside of this process, for reasons other than termination.

- To set up an advance for a termination that needs to be processed immediately, before the next scheduled on-cycle pay run, use a combination of core and Global Payroll for France-specific pages.

Note: The delivered termination process uses French-specific pages that function as component interfaces to the Off-Cycle Requests (GP_OFFCYCLE_REQ) and Off-Cycle Calendar Group (GP_CALENDAR_RUN) components in the core Global Payroll application.

Note: This process and the required setup steps are documented in detail in these topics on processing terminations for France.

See [Understanding Termination Processing](#), [Understanding The Termination Process](#).

- To set up an advances for reasons other than off-cycle termination, use the pages in the core Off Cycle On Demand (GP_ONDEMAND) component.

Note: This component is described in detail in the off-cycle processing topic in the *PeopleSoft Global Payroll*.

See "Processing Advances (*PeopleSoft HCM 9.2: Global Payroll*)".

Generating DUCS

Understanding DUCS Processing

After you run the payroll process, the system has most of the data that you need to produce the DUCS file and the DUCS report. You must enter only the information that is unique to your process setup. You must also specify which data the process must select, where it must place the results, and what alterations to this data, if any, you want to make.

Note: The DUCS is a norm for declaring contributions. Contact the appropriate organization, such as URSSAF or ASSEDIC, to obtain the technical requirements book for the DUCS. This technical requirements book contains the description of the norm and stipulates the membership conditions.

The Application Framework (AF) feature was developed in response to the legislative changes related to social declarations in France. The existing DUCS Application Engine does not provide all customers with the system performance and flexibility required to produce a complex file on a monthly basis. The Application Framework tool enables customers to meet the declarative challenges in both the near and distant future.

For customers that are migrating to the latest release from a previous version, and are willing to continue using the DUCS design they are used to, the system enables you to continue producing DUCS files and reports without Application Framework – using the mechanism provided in previous releases of PeopleSoft Global Payroll for France.

For new customers, or existing customers that are migrating to the latest release and desire to take advantage of the features in the new DUCS design, you can produce DUCS files and reports using Application Framework.

Prerequisites

Before you can produce the DUCS file or the DUCS report, you must set up DUCS information for the organization.

Related Links

[Understanding DUCS Reporting](#)

Producing DUCS Files and Reports Without Application Framework

This section provides an overview of DUCS processing without Application Framework and discusses how to:

- Extract data for DUCS files and reports.
- Update DUCS file and report data.
- Generate DUCS files or DUCS reports.

Pages Used to Produce DUCS Files and Reports

Page Name	Definition Name	Navigation	Usage
Create DUCS Data FRA	GPFR_DUCS_RUNCNTL	Global Payroll & Absence Mgmt, Social Security / Insurance, Create DUCS Data FRA, Create DUCS Data FRA	Run the DUCS Preparation Application Engine process (GPFR_DUC_AE). This process creates the work tables that the system needs to produce the DUCS files and reports.
Update DUCS Data FRA	GPFR_DUCSF_UPDT	Global Payroll & Absence Mgmt, Social Security / Insurance, Update DUCS Data FRA, Update DUCS File	Update data that appears in DUCS files and reports.
Create DUCS/TRC/DRA File FRA	GPFR_DUCS_FILE	Global Payroll & Absence Mgmt, Social Security / Insurance, Create DUCS/TRC/DRA File FRA, Create DUCS/TRC/DRA File FRA	Generate a DUCS file or report. Run this process for each file or report that you want to generate.

Related Links

"Understanding Banking (*PeopleSoft HCM 9.2: Global Payroll*)"

Understanding DUCS Processing Without Application Framework

When you are finished setting up DUCS information, use the Create DUCS Data FRA page to run the process on specific populations and organizations, during a specific period. This sets up the tables needed to create the DUCS file and the DUCS report.

If needed, use the Update DUCS Data FRA page to adjust the data in the DUCS file and report before it is generated. You can change the amount paid and the authentication. For AGIRC and ARRCO, you can also change the credit or debit.

Use the Create DUCS/TRC/DRA File FRA page to create the DUCS information. You also use this page to select a destination for the data and an output type—that is, a file, a report, or both.

Create DUCS Data FRA Page

Use the Create DUCS Data FRA page (GPFR_DUCS_RUNCNTL) to run the DUCS Preparation Application Engine process (GPFR_DUC_AE).

This process creates the work tables that the system needs to produce the DUCS files and reports.

Navigation

Global Payroll & Absence Mgmt, Social Security / Insurance, Create DUCS Data FRA, Create DUCS Data FRA

Image: Create DUCS Data FRA page

This example illustrates the fields and controls on the Create DUCS Data FRA page. You can find definitions for the fields and controls later on this page.

The DUCS Preparation process extracts data from the PeopleSoft HR Management system, the GP Results tables, and the DUCS setup tables, and writes the data to specific DUCS tables.

Declared Period

Period Format

Select the period format. Options are *Monthly Declaration*, *Quarterly Declaration*, and *Yearly Declaration*.

Other Information

Test Indicator

Select *Try* if the generated file is a technical test. The information is sent to the addressee to verify that the file is correct. It is not used as a real declaration.

Payment Date

Enter the appropriate payment date. This is used to generate payment order.

Pay Groups

Pay Group

Select the pay groups for which the system generates a DUCS file or report.

Update DUCS Data FRA Page

Use the Update DUCS Data FRA page (GPFR_DUCSF_UPDT) to update data that appears in DUCS files and reports.

Navigation

Global Payroll & Absence Mgmt, Social Security / Insurance, Update DUCS Data FRA, Update DUCS File

Image: Update DUCS Data FRA page

This example illustrates the fields and controls on the Update DUCS Data FRA page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'Update DUCS Data FRA' page. At the top, it displays 'DUCS Code: GFASSED01' and 'ASSEDIC Certif 01'. Below that, 'DUCS Type: 902' and 'Assedic'. The 'GEN Segments' section has a header bar with 'Find | View All | First 1 of 6 Last'. The main form area contains the following fields:

- Declaration Number:** 1, Compagnie FRB
- Identification:** 777000027
- Reference Period:** 200511
- Declaration Amount:** (empty field)
- Credit to Subtract:** (empty field)
- Debit to Add:** (empty field)
- Authentication:** (empty field)

Below the GEN Segments is the 'PAI Segments' section with a header bar 'Customize | Find | View All | First 1 of 1 Last'. It contains a table with the following columns: Bank Number, Bank Office Number, Account Number, Amount, and Currency.

	Bank Number	Bank Office Number	Account Number	Amount	Currency
1					

GEN Segments

Declaration Number

Displays the declaration number.

Click the Show Next Row button to view multiple declaration numbers for the same DUCS code and DUCS type.

Identification

Displays the identification number that is set up in the DUCS Contacts FRA (GPFR_DUCS_CONTACT) component for the company of the declaration.

Reference Period

Displays the reference period.

Declaration Amount

Displays the declaration amount.

Credit to Subtract

Enter the amount to be subtracted from the ARRCO or AGIRC declaration, if applicable.

Debit to Add	Enter the amount to add to the ARRCO or AGIRC declaration, if applicable.
Authentication	Enter the authentication code.
PAI Segments	
Bank Number	Displays the bank number that you selected on the DUCS Definition page.
Bank Office Number	Displays the bank office number that corresponds to the bank number that you selected.
Bank Account Number	Displays the bank account number that corresponds to the account that you selected.
Amount	Displays the amount to be transferred to the bank. This field is populated by the extraction process and is equal to the contributions to be paid for the DUCS. You can modify this amount if necessary.

Create DUCS/TRC/DRA File FRA Page

Use the Create DUCS/TRC/DRA File FRA page (GPFR_DUCS_FILE) to generate a DUCS file or report.

Run this process for each file or report that you want to generate.

Navigation

Global Payroll & Absence Mgmt, Social Security / Insurance, Create DUCS/TRC/DRA File FRA, Create DUCS/TRC/DRA File FRA

Image: Create DUCS/TRC/DRA File FRA page

This example illustrates the fields and controls on the Create DUCS/TRC/DRA File FRA page. You can find definitions for the fields and controls later on this page.

Create DUCS/TRC/DRA File FRA

Run Control ID: DUCS1 [Report Manager](#) [Process Monitor](#)

Language:

DUCS

*DUCS Code:

*DUCS Type:

Output Information

*Output:

File Name:

Use this run control page to generate DUCS files and reports. This process uses the DUCS-specific tables that are generated during the extraction process.

DUCS

DUCS Code Select the DUCS code that you want to process.

DUCS Type Select the DUCS type that you want to process.

Output Information

Output Select an output type. Options are *File*, *Report*, and *Both*.

File Name To create a DUCS file or report, enter a complete valid path and file name; for example, C:\temp\fichier.txt. If you want to create a new report without writing over old ones, or if you are running a new process, use a new file name. Use a new file name for each DUCS process that you run; otherwise, you might inadvertently delete existing information that you need.

Run Click to launch the DUCS file generation process. The Process Scheduler Request page appears. Select one of the following report options: *DUCS File Generation*, *ASSEDIC Contributions Report*, and *URSSAF Contributions Report*.

Extracting DUCS Data Using Application Framework

After you complete the DUCS setup pages, you can extract DUCS information from the payroll tables.

This section discusses how to:

- Define extraction IDs.
- Enter extraction parameters
- Launch the Run Extraction process

Pages Used to Extract DUCS Data

Page Name	Definition Name	Navigation	Usage
Define Extraction Data	GPFR_AF_EXTR_DEFN	Global Payroll & Absence Mgmt, Absence & Payroll Processing, Define Calendars, Define Extraction Data FRA	Define an Extraction ID

Page Name	Definition Name	Navigation	Usage
Parameters	GPFR_AF_EXTR_PRM	Global Payroll & Absence Mgmt, Absence & Payroll Processing, Define Calendars, Define Extraction Data FRA, Parameters	Enter a sending reference and the frequency code for the extraction data.
Run Extraction FRA	GPFR_AF_EXTR_RUN	Global Payroll & Absence Mgmt, Social Security / Insurance, Run Extraction FRA	Run the DUCS extraction process.

Define Extraction Data Page

Use the Define Extraction Data page (GPFR_AF_EXTR_DEFN) to .

Navigation

Global Payroll & Absence Mgmt, Absence & Payroll Processing, Define Calendars, Define Extraction Data FRA

Image: Define Extraction Data page

This example illustrates the fields and controls on the Define Extraction Data page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'Define Extraction Data' page with the 'Parameters' tab selected. The page contains the following fields and controls:

- Extraction ID:** DUCS
- *Description:** (empty text box)
- Extraction Information** (blue header bar)
- *Country:** FRA (with a magnifying glass icon) → France
- *Application:** DUCS-4.2 (with a magnifying glass icon) → DUCS 4.2
- *Node Set:** AGIRC/ARRCO (with a magnifying glass icon) → AGIRC ARRCO and others
- *Period Format:** Month (dropdown menu)
- *Declared Year:** 2010 (text box)
- Used Dates:** End Dates (dropdown menu)
- Period Begin Date:** 01/01/2010 (calendar icon)
- Period End Date:** 01/31/2010 (calendar icon)
- Pay Groups** (table with columns: *Pay Group, Description, and action buttons)

	*Pay Group	Description		
<input type="checkbox"/>	1 GFPGDUCS01 (with a magnifying glass icon)	Pay Group DUCS 01	+	-

Period Format

Values are *Month, Other, Quarter, Year*.

Declared Year

Specify a value in this field only when the Period Format is *Year*.

Used Dates

These are the processed payroll results whose Payment Dates or Payroll Segment End Dates are within the Declaration Period.

Period Begin Date and Period End Date Specify the dates of the declaration period.

Pay Groups

You must enter at least one paygroup in this region of the page. If you have a single extraction ID for all of your paygroups, you should list them all in this region.

Parameters Page

Use the Parameters page (GPFR_AF_EXTR_PRM) to enter a sending reference and the frequency code for the extraction data.

Navigation

Global Payroll & Absence Mgmt, Absence & Payroll Processing, Define Calendars, Define Extraction Data FRA, Parameters

Image: Parameters page

This example illustrates the fields and controls on the Parameters page. You can find definitions for the fields and controls later on this page.

Parameters	
Extraction ID:	DUCS
DUCS Code	901DRA+E04
DUCS Type	901
Test Indicator	Try
DUCS Regularization	<input checked="" type="checkbox"/>
Sequence Order for Indicator	

Run Extraction FRA Page

Use the Run Extraction FRA page (GPFR_AF_EXTR_RUN) to run the DUCS extraction process.

Navigation

Global Payroll & Absence Mgmt, Social Security / Insurance, Run Extraction FRA


Image: Run Extraction FRA page (1 of 2)


This example illustrates the fields and controls on the Run Extraction FRA page (1 of 2). You can find definitions for the fields and controls later on this page.


Run Extraction FRA

Run Control ID: 1 [Report Manager](#) [Process Monitor](#) Run

Extraction Run

*Extraction ID:  ☐ Debug Mode

Stream Number: 

Group List ID: 

Level 0 Nodes

Select	Node Name	Description
<input checked="" type="checkbox"/>	PREP_PAYDATA_EXTRACT	Prepare Payroll Data Extraction
<input checked="" type="checkbox"/>	DUCS_SETUP_DATA	DUCS setup data for current extraction
<input checked="" type="checkbox"/>	PAYDATA_EXTRACTION	Extract Payroll Data
<input type="checkbox"/>	DELETE_EXTRACT_DATA	Delete Extracted Data
<input checked="" type="checkbox"/>	DUCS_CONTACT_DATA	Prepare Contact Data
<input checked="" type="checkbox"/>	CONTRIBUTION_DATA	Prepare DUCS Contribution Data
<input checked="" type="checkbox"/>	XML FILE	Generate XML File
<input checked="" type="checkbox"/>	REPORT	Generate PDF Report

Image: Run Extraction FRA page (2 of 2)

This example illustrates the fields and controls on the Run Extraction FRA page (2 of 2). You can find definitions for the fields and controls later on this page.

Other Nodes

Select Non level 0 Nodes

Select	Node Name Others	Description	Select Attributes
<input checked="" type="checkbox"/>	DEB	Begin Row	Select Attributes
<input checked="" type="checkbox"/>	FR1	Transmitter row 1	Select Attributes
<input checked="" type="checkbox"/>	FR2	Transmitter row 2	Select Attributes
<input checked="" type="checkbox"/>	FR3	Transmitter row 3	Select Attributes
<input checked="" type="checkbox"/>	DT1	Informant row 1	Select Attributes
<input checked="" type="checkbox"/>	DT2	Informant row 2	Select Attributes
<input checked="" type="checkbox"/>	DT3	Informant row 3	Select Attributes
<input checked="" type="checkbox"/>	MR1	Recipient row 1.	Select Attributes
<input checked="" type="checkbox"/>	MR2	Recipient row 2.	Select Attributes
<input checked="" type="checkbox"/>	MR3	Recipient row 3.	Select Attributes
<input checked="" type="checkbox"/>	AE1	Editor row 1.	Select Attributes
<input checked="" type="checkbox"/>	AE2	Editor row 2.	Select Attributes
<input checked="" type="checkbox"/>	AE3	Editor row 3.	Select Attributes
<input checked="" type="checkbox"/>	FZ1	Group account row 1.	Select Attributes
<input checked="" type="checkbox"/>	FZ2	Group account row 2.	Select Attributes

☒ [Select All](#)
☐ [Clear All](#)

When the process has successfully completed, the GPFR_AF_EXTRACT table is populated based on the Extraction ID definition and the Run Control parameters.

Extraction ID Select an Extraction ID to determine which nodes are displayed.

Debug Mode Select to generate a log file with the extraction run.

Group List ID Use this option when you generate test files, or corrective files.

Viewing and Updating Extracted DUCS Data Using Application Framework

This section provides an overview of extracting DUCS data and discusses how to:

- Select structures to view.
- Apply additional filters.
- Update data.

Pages Used to View and Update DUCS Data

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Node/Attr Filter	GPFR_DA_RUNCNTL	Global Payroll & Absence Mgmt, Social Security / Insurance, Update Extraction Data FRA, Node/Attr Filter	Select the structures and records you want to view.
Other Filters	GPFR_AF_UPDT_2	Global Payroll & Absence Mgmt, Social Security / Insurance, Update Extraction Data FRA, Other Filters	Select other filters that are displayed based on the structures and records previously selected.
Update Data	GPFR_AF_UPDT_FINAL	Global Payroll & Absence Mgmt, Social Security / Insurance, Update Extraction Data FRA, Update Data	Displays the results related to the filters selected on the Node/Attr Filter and the Other Filters pages.

Understanding Viewing and Updating Extracted DUCS Data

Use the Update Extraction Data FRA Component to view and update the extraction results and identify possible issues.

You can then update any incorrect data in the HR application and selectively rerun any employees or records that need to be updated. The system enables you to perform as many runs as you need for an Extraction ID, until the results in the GPFR_AF_EXTRACT table are correct. Each time the incorrect data is deleted, replaced by the new extracted data, and then inserted into any previously extracted data according to the DUCS norm sorting rules.

Important! If you update any data through this component, and then run the process again, your manual input is overridden. Both manual updates and Extraction ID runs populate the same extraction table, so manual updates are not stored separately. Therefore, if you need to make manual updates, you should perform them after the last run of a given Extraction ID.

Since there may be a large number of rows generated in the GPFR_AF_EXTRACT table, and checked by many different users, this component offers various levels of filtering, to enable you to easily view the data you need.

Node/Attr Filter Page

Use the Node/Attr Filter page (GPFR_DA_RUNCNTL) to select the structures and records you want to view.

Navigation

Global Payroll & Absence Mgmt, Social Security / Insurance, Update Extraction Data FRA, Node/Attr Filter

Image: Node/Attr Filter page

This example illustrates the fields and controls on the Node/Attr Filter page. You can find definitions for the fields and controls later on this page.

Node/Attr Filter
Other Filters
Update Data

Extraction ID: DUCS
Country: FRA France
Application: DUCS-4.2 DUCS 4.2
Type: AGIRC/ARRCO AGIRC ARRCO and others

Select Record Codes				Customize Find View All First 1-10 of 34 Last
	Select	Record Codes	Description	Field Name
1	<input checked="" type="checkbox"/>	PREP_PAYDATA_EXTRACT	Prepare Payroll Data Extraction	Field Name
2	<input checked="" type="checkbox"/>	DUCS_SETUP_DATA	DUCS setup data for current extraction	Field Name
3	<input checked="" type="checkbox"/>	PAYDATA_EXTRACTION	Extract Payroll Data	Field Name
4	<input checked="" type="checkbox"/>	DELETE_EXTRACT_DATA	Delete Extracted Data	Field Name
5	<input checked="" type="checkbox"/>	DUCS_CONTACT_DATA	Prepare Contact Data	Field Name
6	<input checked="" type="checkbox"/>	CONTRIBUTION_DATA	Prepare DUCS Contribution Data	Field Name
7	<input checked="" type="checkbox"/>	DEB	Begin Row	Field Name
8	<input checked="" type="checkbox"/>	FR1	Transmitter row 1	Field Name
9	<input checked="" type="checkbox"/>	FR2	Transmitter row 2	Field Name
10	<input checked="" type="checkbox"/>	FR3	Transmitter row 3	Field Name

Other Filters Page


Use the Other Filters page (GPFR_AF_UPDT_2) to select other filters that are displayed based on the structures and records previously selected.





Navigation

Global Payroll & Absence Mgmt, Social Security / Insurance, Update Extraction Data FRA, Other Filters

Image: Other Filters page

This example illustrates the fields and controls on the Other Filters page. You can find definitions for the fields and controls later on this page.



Node/Attr Filter Other Filters Update Data		
Extraction ID:	DUCS	
Country:	FRA	France
Application:	DUCS-4.2	DUCS 4.2
Type:	AGIRC/ARRCO	AGIRC ARRCO and others
Select Filters		
Company:	<input type="text"/>	
Establishment ID:	<input type="text"/>	
Empl ID:	<input type="text"/>	
Empl Record:	<input type="text"/>	
Group List ID:	<input type="text"/>	

Use the Other Filters page to select other filters that are displayed based on the structures and records previously selected.

Updating Data Page

Use the Update Data page (GPFR_AF_UPDT_FINAL) to displays the results related to the filters selected on the Node/Attr Filter and the Other Filters pages.

Navigation

Global Payroll & Absence Mgmt, Social Security / Insurance, Update Extraction Data FRA, Update Data

Image: Update Data page

This example illustrates the fields and controls on the Update Data page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'Update Data' page with the following components:

- Filter Tabs:** Node/Attr Filter, Other Filters, Update Data (selected).
- Filter Criteria:**
 - Country: FRA (France)
 - Application: DUCS-4.2 (DUCS 4.2)
 - Type: AGIRC/ARRCO (AGIRC ARRCO and others)
 - Extraction ID: DUCS
- Update Extraction Data Section:**
 - Company: [Searchable Field]
 - Estab ID: [Searchable Field]
 - Empl ID: [Searchable Field]
 - Empl Record: [Searchable Field]
 - Record Code: [Searchable Field]
 - Field Name: [Searchable Field]
 - Check Done: ☐ Check Done
 - Filter** button
- Update Data Table:**
 - Customize | Find | View All | First | 1-3 of 3 | Last
 - Node Data | Details | [PDF Icon]
 - Table with 6 columns: Record Code, Field Name, Description, Code, Value, Check Done.

Record Code	Field Name	Description	Code	Value	Check Done
1 FIN	001	Record Code		FIN	<input type="checkbox"/>
2 FIN	002	Declatration Number of sending		0	<input type="checkbox"/>
3 FIN	003	Filer			<input type="checkbox"/>

The Update Data page displays the results related to the filters you selected on the two first pages. You can then refine the data display by entering data in the Company, Estab ID (establishment ID), Empl ID, Empl Record, Structure, and Rubrique fields, then clicking the Filter button.

An export to Excel process is available, which shows the data displayed on the Update Data page.

Important! For technical reasons, regardless of the filters selected, the number of rows displayed on the Update Data page is limited to 5000. You may change this limit in PeopleTools, although you may then experience downgraded performance.

Check Done

Select to indicate that the data has been checked. The Check Done field is automatically deselected if you re-run the process on the same data.

Node Data

The Node Data tab enables you to view the structure and record names and values used to produce the final file. However, the values displayed here come from the HCM application in a raw format. These values are formatted according to the DUCS norm at the file generation step.

Details

The Details tab displays data that helps you check the extracted data, even though all of the displayed data is not required in each row of the final file. The Details tab displays the following information:

- Company

- Establishment ID
- Employee ID
- Employee Record Number
- Situation Begin Date
- Situation End Date

Generating DUCS Files Using Application Framework

This section discusses how to generate DUCS files

Page Used to Generate DUCS files

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Create File FRA	GPFR_AF_RUNFILE	Global Payroll & Absence Mgmt, Social Security / Insurance, Create File FRA	Generate the final DUCS file.

Create File FRA Page

Once the content of the GPFR_AF_EXTRACT table is complete and correct, Use the Create File FRA page (GPFR_AF_RUNFILE) to generate the final DUCS file.

Navigation

Global Payroll & Absence Mgmt, Social Security / Insurance, Create File FRA

Image: Create File FRA page

This example illustrates the fields and controls on the Create File FRA page. You can find definitions for the fields and controls later on this page.

Enter the following information on the run control page:

- Select an Extraction ID
- Select a test indicator, Test or Real.
- Select the File field to produce the final DUCS file.
- Indicate the path to the location of the generated file.
- Select the Report field to produce a PDF report with the generated DUCS file.

The content of this PDF document is the same as the generated DUCS file, with additional record descriptions.

The flat file is generated by a SQR program, which contains all of the DUCS norm formatting rules.

Counting Employees

Understanding Employee Counts

Several payroll reports are based on headcounts. For example, separate monthly headcounts (as well as other counts) of the men and women in an organization are required for ASSEDIC reporting. The headcount frequency and other requirements vary by report.

Global Payroll for France automatically performs the employee counts needed to meet ASSEDIC, URSSAF, DADS, AGIRC, and ARRCO reporting requirements. When you run the payroll process, the system performs the legally required counts of employees, non-employees, contributors, non-contributors, males, females, and so on. If you run DUCS without Application Framework, the system stores the results in the writable array REP WA DU COTI. You then run the DUCS File Preparation process, which summarizes the counts by company and establishment.

Adjusting Headcounts

At times, you may need to adjust headcounts. For example, you may need to increase the headcount for the number of employees that you do not process through Global Payroll for France—possibly some senior executives.

You may also need to add employees who were absent during the entire processing period. For example, in the case of a long-term absence, you might change the value of the Action/Reason field on the Job Data – Work Location page to *Paid Leave of Absence* or *Leave of Absence*. When you select *Leave of Absence*, the system automatically changes the employee's status to *Inactive*. If you exclude inactive payees from your payroll calculations, the system does not count these payees. Therefore, you need to increase the automatic headcount by the number of inactive payees who are still employed by your organization.

Which Counts Are Performed

The system automatically performs the following counts:

- Headcount for each establishment as of December 31.
These counts are done for the ASSEDIC certificate and for DADS-U.
- Headcounts for each establishment and company in accordance with DUCS requirements for ASSEDIC and URSSAF reporting.
- Monthly headcount per company, used in the next monthly payroll cycle.

Related Links

[Understanding DUCS Processing](#)

Viewing Headcounts by Company

This section discusses how to view headcounts by company. This section applies only if you process DUCS without Application Framework.

Page Used to View Headcounts by Company

Page Name	Definition Name	Navigation	Usage
Update Company Headcount FRA	GPFR_DUCS_COUN	Global Payroll & Absence Mgmt, Absence and Payroll Processing, Prepare Payroll, Update Company Headcount FRA, Update Company Headcount FRA	View the headcount values for each company that exists in the company reference table.

Update Company Headcount FRA Page

Use the Update Company Headcount FRA page (GPFR_DUCS_COUN) to view the headcount values for each company that exists in the company reference table.

Navigation

Global Payroll & Absence Mgmt, Absence and Payroll Processing, Prepare Payroll, Update Company Headcount FRA, Update Company Headcount FRA

Image: Update Company Headcount FRA page

This example illustrates the fields and controls on the Update Company Headcount FRA page. You can find definitions for the fields and controls later on this page.

Update Company Headcount FRA

Company: GFH Societe DUCS 8

Headcount per effective date [Find](#) | [View All](#) | [First](#) | 1 of 1 | [Last](#)

Period End Date: Current Headcount:

You can view the current payee headcount for each company in your organization after you run the DUCS process. The Update Company Headcount FRA page lists the count for each pay period. The system saves all counts for use in retro calculations.

Period End Date Displays the end date of the pay period for which the counts were generated.

Current Headcount Displays the total headcount for the company.

Adjusting DUCS Headcounts (without Application Framework)

This section discusses how to adjust DUCS headcounts. This section applies only if you process DUCS without Application Framework.

Page Used to Adjust DUCS Headcounts

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Adjust DUCS Headcount FRA	GPFR_DUCS_ADJ	Global Payroll & Absence Mgmt, Social Security / Insurance, Adjust DUCS Headcount FRA, Adjust DUCS Headcount FRA	Adjust the DUCS headcount to include employees who were excluded from the counting process. Because ASSEDIC requires separate counts for men and women, enter a separate count for each.

Adjust DUCS Headcount FRA Page

Use the Adjust DUCS Headcount FRA page (GPFR_DUCS_ADJ) to adjust the DUCS headcount to include employees who were excluded from the counting process.

Because ASSEDIC requires separate counts for men and women, enter a separate count for each.

Navigation

Global Payroll & Absence Mgmt, Social Security / Insurance, Adjust DUCS Headcount FRA, Adjust DUCS Headcount FRA

Image: Adjust DUCS Headcount FRA page

This example illustrates the fields and controls on the Adjust DUCS Headcount FRA page. You can find definitions for the fields and controls later on this page.

The Adjustment per Establishment page lets you adjust the number of men and women counted in an establishment.

After adjusting the figures, run the DUCS File Preparation process again so that next month's payroll process retrieves the correct headcounts.

Current Headcount	Displays the headcount for the selected establishment, as generated by the DUCS process.
Period End Date	Displays the end date of the last period for which the DUCS process was run.
Date Time	Displays the date and time of the last adjustment so that you can determine if the adjustment was made before or after the DUCS File Generation process was last run for the same period.
Adjusted Number of Men	Enter the adjustment to the total number of male employees. To make a negative adjustment, enter a minus sign (-) before the number.
Adjusted Number of Women	Enter the adjustment to the total number of female employees. To make a negative adjustment, enter a minus sign (-) before the number.

Generating DADS

Extracting DADS Data

After you complete the DADS setup pages, you can extract DADS information from the payroll tables.

This section discusses how to:

- Define extraction IDs.
- Enter extraction parameters
- Launch the Run Extraction process

Pages Used to Extract DADS Data

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Define Extraction Data	GPFR_AF_EXTR_DEFN	Global Payroll & Absence Mgmt, Absence & Payroll Processing, Define Calendars, Define Extraction Data FRA	Define an Extraction ID
Parameters	GPFR_AF_EXTR_PRM	Global Payroll & Absence Mgmt, Absence & Payroll Processing, Define Calendars, Define Extraction Data FRA, Parameters	Enter a sending reference and the frequency code for the extraction data.
Run Extraction FRA	GPFR_AF_EXTR_RUN	Global Payroll & Absence Mgmt, Social Security / Insurance, Run Extraction FRA	Run the DADS extraction process.

Define Extraction Data Page

Use the Define Extraction Data page (GPFR_AF_EXTR_DEFN) to .

Navigation

Global Payroll & Absence Mgmt, Absence & Payroll Processing, Define Calendars, Define Extraction Data FRA

Image: Define Extraction Data page

This example illustrates the fields and controls on the Define Extraction Data page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'Define Extraction Data' page with the 'Parameters' tab selected. The page contains several input fields and a table. The 'Extraction ID' is 'DADSY2008'. The '*Description' field is empty. The 'Extraction Information' section includes: '*Country:' 'FRA' (France), '*Application:' 'DADS0808' (DADSV08R08), '*Node Set:' 'COMPLETE' (Complete DADS-U (TDS IRC+HP)), '*Period Format:' 'Year', '*Declared Year:' '2008', 'Used Dates:' 'Payment Dt', 'Period Begin Date:' '01/01/2008', and 'Period End Date:' '12/31/2008'. Below this is a 'Pay Groups' table with one row: '1' 'GFPGMEN601' 'Pay Group GF6-1'. The table has columns for a checkbox, an index, a pay group name, a description, and add/remove buttons.

Period Format Values are *Month, Other, Quarter, Year*.

Declared Year Specify a value in this field only when the Period Format is *Year*.

Used Dates These are the processed payroll results whose Payment Dates or Payroll Segment End Dates are within the Declaration Period.

Period Begin Date and Period End Date Specify the dates of the declaration period.

Pay Groups

You must enter at least one paygroup in this region of the page. If you have a single extraction ID for all of your paygroups, you should list them all in this region.

Parameters page


Use the Parameters page (GPFR_AF_EXTR_PRM) to enter a sending reference and the frequency code for the extraction data.

Navigation

Global Payroll & Absence Mgmt, Absence & Payroll Processing, Define Calendars, Define Extraction Data FRA, Parameters

Image: Parameters page

This example illustrates the fields and controls on the Parameters page. You can find definitions for the fields and controls later on this page.



The screenshot shows a web-based interface with two tabs at the top: "Define Extraction Data" and "Parameters". The "Parameters" tab is selected. Below the tabs, the "Extraction ID" is displayed as "DADSY2008". Underneath, there is a section titled "Parameters" with a blue header. This section contains two fields: "Sending Reference" with the value "KF1SR" and a magnifying glass icon to its right, and "Frequency Code" with the value "A00 Yearly" and a dropdown arrow to its right.

On the Parameters Page, enter a previously defined sending reference and the frequency code *A00* for DADS-U,

Run Extraction FRA Page

Use the Run Extraction FRA page (GPFR_AF_EXTR_RUN) to run the DADS extraction process.

Navigation

Global Payroll & Absence Mgmt, Social Security / Insurance, Run Extraction FRA

Image: Run Extraction FRA page (1 of 2)

This example illustrates the fields and controls on the Run Extraction FRA page (1 of 2). You can find definitions for the fields and controls later on this page.

Run Extraction FRA

Run Control ID: 1

[Report Manager](#)[Process Monitor](#)

Run

Extraction Run

*Extraction ID: DADSY2008

☐ Debug Mode

Stream Number: 1

Group List ID: K1GGL01

Level 0 Nodes

Select Level 0 Nodes

Select	Node Name	Description
<input checked="" type="checkbox"/>	COMPANY-ESTABL	Company Establishment List
<input checked="" type="checkbox"/>	EMPLOYEE-LIST	Employee List
<input checked="" type="checkbox"/>	PREP_PAYROLL_EXTRACT	Payroll Extraction Preparation
<input checked="" type="checkbox"/>	PAYROLL-EXTRACTION	Report Data Payroll Extraction
<input checked="" type="checkbox"/>	DELETE-EXTRACT-DATA	Extracted Data Deletion

Image: Run Extraction FRA page (2 of 2)

This example illustrates the fields and controls on the Run Extraction FRA page (2 of 2). You can find definitions for the fields and controls later on this page.

Other Nodes			
Select Non level 0 Nodes			
Select	Node Name Others	Description	Select Attributes
<input checked="" type="checkbox"/>	S10.G01.00	Transmitter	Select Attributes
<input checked="" type="checkbox"/>	S10.G01.01	Transmitter Contact	Select Attributes
<input checked="" type="checkbox"/>	S20.G01.00	Company	Select Attributes
<input checked="" type="checkbox"/>	S20.G10.10	ANSP Approval	Select Attributes
<input checked="" type="checkbox"/>	S30.G01.00	Payee's Identification	Select Attributes
<input checked="" type="checkbox"/>	S30.G10.05	Employee ID	Select Attributes
<input checked="" type="checkbox"/>	S41.G01.00	Activity Period	Select Attributes
<input checked="" type="checkbox"/>	S41.G01.01	Complementary/Specific/CCI BTP Funds	Select Attributes
<input checked="" type="checkbox"/>	S41.G01.02	Specific Gross without Ceiling	Select Attributes
<input checked="" type="checkbox"/>	S41.G01.03	Specific Gross with Ceiling	Select Attributes
<input checked="" type="checkbox"/>	S41.G01.04	Isolated Amounts	Select Attributes
<input checked="" type="checkbox"/>	S41.G01.05	Specific CSG Bases	Select Attributes
<input checked="" type="checkbox"/>	S41.G01.06	Specific URSSAF Exemption Bases	Select Attributes
<input checked="" type="checkbox"/>	S41.G02.00	Industrial Tribunal Elections	Select Attributes
<input checked="" type="checkbox"/>	S41.G10.15	Public Status Employee's Highest Position (SPE reserved)	Select Attributes

☒ [Select All](#)
☐ [Clear All](#)

When the process has successfully completed, the GPFR_AF_EXTRACT table is populated based on the Extraction ID definition and the Run Control parameters.

Extraction ID Select an Extraction ID to determine which nodes are displayed.

Debug Mode Select to generate a log file with the extraction run.

Group List ID Use this option when you generate test files, or corrective files.

Viewing and Updating Extracted DADS Data

This section provides an overview of extracting DADS data and discusses how to:

- Select structures to view.
- Apply additional filters.
- Update data.

Pages Used to View and Update DADS Data

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Node/Attr Filter	GPFR_DA_RUNCNTL	Global Payroll & Absence Mgmt, Social Security / Insurance, Update Extraction Data FRA, Node/Attr Filter	Select the structures and records you want to view.
Other Filters	GPFR_AF_UPDT_2	Global Payroll & Absence Mgmt, Social Security / Insurance, Update Extraction Data FRA, Other Filters	Select other filters that are displayed based on the structures and records previously selected.
Update Data	GPFR_AF_UPDT_FINAL	Global Payroll & Absence Mgmt, Social Security / Insurance, Update Extraction Data FRA, Update Data	Displays the results related to the filters selected on the Node/Attr Filter and the Other Filters pages.

Understanding Viewing and Updating Extracted DADS Data

Use the Update Extraction Data FRA Component to view and update the extraction results and identify possible issues.

You can then update any incorrect data in the HR application and selectively rerun any employees or records that need to be updated. The system enables you to perform as many runs as you need for an Extraction ID, until the results in the GPFR_AF_EXTRACT table are correct. Each time the incorrect data is deleted, replaced by the new extracted data, and then inserted into any previously extracted data according to the DADS-U norm sorting rules.

Important! If you update any data through this component, and then re-run the process, your manual input is overridden. Both manual updates and Extraction ID runs populate the same extraction table, so manual updates are not stored separately. Therefore, if you need to make manual updates, you should perform them after the last run of a given Extraction ID.

Since there may be a large number of rows generated in the GPFR_AF_EXTRACT table, and checked by many different users, this component offers various levels of filtering, to enable you to easily view the data you need.

Node/Attr Filter Page

Use the Node/Attr Filter page (GPFR_DA_RUNCNTL) to select the structures and records you want to view.

Navigation

Global Payroll & Absence Mgmt, Social Security / Insurance, Update Extraction Data FRA, Node/Attr Filter

Image: Node/Attr Filter page

This example illustrates the fields and controls on the Node/Attr Filter page. You can find definitions for the fields and controls later on this page.

Node/Attr Filter
Other Filters
Update Data

Extraction ID: DADSY2008
Country: FRA France
Application: DADS0808 DADSV08R08
Message: COMPLETE Complete DADS-U (TDS IRC+IP)

Select Structure
Customize Find View All
First 1-10 of 52 Last

	Select	Structure	Description	Rubrique
1	<input checked="" type="checkbox"/>	COMPANY-ESTABL	Company Establishment List	Rubrique
2	<input checked="" type="checkbox"/>	EMPLOYEE-LIST	Employee List	Rubrique
3	<input checked="" type="checkbox"/>	PREP_PAYROLL_EXTRACT	Payroll Extraction Preparation	Rubrique
4	<input checked="" type="checkbox"/>	PAYROLL-EXTRACTION	Report Data Payroll Extraction	Rubrique
5	<input checked="" type="checkbox"/>	DELETE-EXTRACT-DATA	Extracted Data Deletion	Rubrique
6	<input checked="" type="checkbox"/>	S10.G01.00	Transmitter	Rubrique
7	<input checked="" type="checkbox"/>	S10.G01.01	Transmitter Contact	Rubrique
8	<input checked="" type="checkbox"/>	S20.G01.00	Company	Rubrique
9	<input checked="" type="checkbox"/>	S20.G10.10	ANSP Approval	Rubrique
10	<input checked="" type="checkbox"/>	S30.G01.00	Payee's Identification	Rubrique

Other Filters Page

Use the Other Filters page (GPFR_AF_UPDT_2) to select other filters that are displayed based on the structures and records previously selected.

Navigation

Global Payroll & Absence Mgmt, Social Security / Insurance, Update Extraction Data FRA, Other Filters

Image: Other Filters page

This example illustrates the fields and controls on the Other Filters page. You can find definitions for the fields and controls later on this page.

Use the Other Filters page to select other filters that are displayed based on the structures and records previously selected. For example, if only S10 and S20 structures have been selected, the Employee ID, Employee Record Number and Group List ID filters are not editable on the Other Filters page.

Updating Data Page

Use the Update Data page (GPFR_AF_UPDT_FINAL) to displays the results related to the filters selected on the Node/Attr Filter and the Other Filters pages.

Navigation

Global Payroll & Absence Mgmt, Social Security / Insurance, Update Extraction Data FRA, Update Data

Image: Update Data page

This example illustrates the fields and controls on the Update Data page. You can find definitions for the fields and controls later on this page.

Node/Attr Filter Other Filters Update Data

Country: FRA France
 Application: DADS0808 DADSV08R08
 Message: COMPLETE Complete DADS-U (TDS IRC+IP)
 Extraction ID: DADSY2008

Update Extraction Data

Company: Estab ID: Empl ID: Empl Record: Structure: Rubrique: Check Done:

☐ Check Done

Update Data Customize | Find | View 100 | First 1-10 of 106 Last

Structure	Rubrique	Description	Code	Value	Check Done
1 S10.G01.00	001.001	Transmitter SIREN		120027016	<input type="checkbox"/>
2 S10.G01.00	001.002	Transmitter NIC		00126	<input type="checkbox"/>
3 S10.G01.00	002	Transmitter Name		Paris - Headquarter	<input type="checkbox"/>
4 S10.G01.00	003.003	Transmitter Street Number			<input type="checkbox"/>
5 S10.G01.00	003.006	Transmitter Street Name		125 rue Sebastien Mercier	<input type="checkbox"/>
6 S10.G01.00	003.009	Transmitter Town			<input type="checkbox"/>
7 S10.G01.00	003.010	Transmitter ZIP Code		75015	<input type="checkbox"/>
8 S10.G01.00	003.012	Transmitter City		Paris	<input type="checkbox"/>
9 S10.G01.00	003.015	Transmitter Extended Address Code			<input type="checkbox"/>
10 S10.G01.00	004	Sending Reference		KF1SR	<input type="checkbox"/>

The Update Data page displays the results related to the filters you selected on the two first pages. You can then refine the data display by entering data in the Company, Estab ID (establishment ID), Empl ID, Empl Record, Structure, and Rubrique fields, then clicking the Filter button.

An export to Excel process is available, which shows the data displayed on the Update Data page.

Important! For technical reasons, regardless of the filters selected, the number of rows displayed on the Update Data page is limited to 5000. You may change this limit in PeopleTools, although you may then experience downgraded performance.

Check Done

Select to indicate that the data has been checked. The Check Done field is automatically deselected if you re-run the process on the same data.

Node Data

The Node Data tab enables you to view the structure and record names and values used to produce the final file. However, the values displayed here come from the HCM application in a raw format. These values are formatted according to the DADS-U norm at the file generation step.

Details

The Details tab displays data that helps you check the extracted data, even though all of the displayed data is not required in each row of the final file. The Details tab displays the following information:

- Company
- Establishment ID
- Employee ID
- Employee Record Number
- S41 Situation Begin Date
- S41 Situation End Date

Generating DADS Files

This section discusses how to generate DADS files

Page Used to Generate DADS files

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Create File FRA	GPFR_AF_RUNFILE	Global Payroll & Absence Mgmt, Social Security / Insurance > Create File FRA	Generate the final DADS file.

Create File FRA Page

Once the content of the GPFR_AF_EXTRACT table is complete and correct, Use the Create File FRA page (GPFR_AF_RUNFILE) to generate the final DADS file.

Navigation

Global Payroll & Absence Mgmt, Social Security / Insurance > Create File FRA

Image: Create File FRA page

This example illustrates the fields and controls on the Create File FRA page. You can find definitions for the fields and controls later on this page.

Enter the following information on the run control page:

- Select an Extraction ID
- Select a test indicator, Test or Real.
- Select the DADS-U File field to produce the final DADS-U file.
- Indicate the path to the location of the generated file.
- Select the Descriptive Report field to produce a PDF report with the generated DADS-U file.

The content of this PDF document is the same as the generated DADS-U file, with additional record descriptions.

The flat file is generated by a SQR program, which contains all of the DADS-U norm formatting rules.

Appendix A

Global Payroll for France Reports

Global Payroll for France Reports: A to Z

These tables list the Global Payroll for France reports sorted by report ID.

For more information about running these reports, refer to:

- The corresponding topic in this product documentation.
- *PeopleTools: PeopleSoft Process Scheduler*
- *PeopleTools: BI Publisher for PeopleSoft*.
- *PeopleTools: SQL Language Reference for PeopleSoft*

For samples of these reports, see the [Report Samples](#) that are published with this online documentation.

Report ID and Report Name	Description	Navigation	Run Control Page
FRPAY001 (GPGENRPT) Summary Salary Statement	A generic report based on previous setup. Note: This report is based on the generic reports functionality in the PeopleSoft Global Payroll core application.	Global Payroll & Absence Mgmt, Absence and Payroll Processing, Reports, Create Generic Reports, Generic Report	GP_GENRPT_RC
FRPAY003 (GPGENRPT) Loans and Advances Report	A generic report based on previous setup. Note: This report is based on the generic reports functionality in the PeopleSoft Global Payroll core application.	Global Payroll & Absence Mgmt, Absence and Payroll Processing, Reports, Create Generic Reports, Generic Report	GP_GENRPT_RC
FRPAY004 (GPGENRPT) Garnishments Report	A generic report based on previous setup. Note: This report is based on the generic reports functionality in the PeopleSoft Global Payroll core application.	Global Payroll & Absence Mgmt, Absence and Payroll Processing, Reports, Create Generic Reports, Generic Report	GP_GENRPT_RC

Report ID and Report Name	Description	Navigation	Run Control Page
FRPAY005 (GPGENRPT) Tax on Salaries Report	A generic report based on previous setup. Note: This report is based on the generic reports functionality in the PeopleSoft Global Payroll core application.	Global Payroll & Absence Mgmt, Absence and Payroll Processing, Reports, Create Generic Reports, Generic Report	GP_GENRPT_RC
GPFRASS ASSEDIC Certificate (BI Publisher)	Prints an ASSEDIC certificate that is delivered to payees at the moment of termination, expiration, or breach of employment contract. The certificate serves as evidence of eligibility for state unemployment funds.	Global Payroll & Absence Mgmt, Termination Processing, Termination Report FRA, Termination Reports	GPFR_ASS_CER_RUN
GPFRATMP Work Accident/Occupational Disease Certificate (BI Publisher)	Prints a certificate for occupational accident/illness.	Global Payroll & Absence Mgmt, Social Security / Insurance, Certificates Report FRA, Certificates Printing Process	GPFR_ILL_AT_RNCTL
GPFRDUCS DUCS report	Runs the DUCS report process.	Global Payroll & Absence Mgmt, Social Security / Insurance, Create DUCS Data FRA, Run Control	GPFR_DUCS_RUNCNTL
GPFRDUCS DUCS File Generation	Generates a DUCS file.	Global Payroll & Absence Mgmt, Social Security / Insurance, Create DUCS/ TRC/DRA File FRA, DUCS File Generation	GPFR_DUCS_FILE
GPFREFT Payment File Generation	Creates a flat output file (EFT) that contains the payment details for each payee. It is sent to the bank so that funds can be transferred to payees' accounts.	Global Payroll & Absence Mgmt, Payment Processing, Create EFT Payment File FRA, Payment File Generation	GPFR_BANK_EFT
GPFRILL Illness/Maternity/Paternity report (BI Publisher)	Prints a certificate for illness and maternity.	Global Payroll & Absence Mgmt, Social Security / Insurance, Certificates Report FRA, Certificates Printing Process	GPFR_ILL_AT_RNCTL
GPFRLPR Last Payment Receipt (BI Publisher)	Prints the Last Payment Receipt (Reçu pour Solde de Tout Compte) report that details the amount paid to the employee on termination.	Global Payroll & Absence Mgmt, Termination Processing, Termination Report FRA, Termination Reports	GPFR_ASS_CER_RUN

Report ID and Report Name	Description	Navigation	Run Control Page
GPFRLT Long-Term Illness Certificate (BI Publisher)	Prints a certificate for long-term illness.	Global Payroll & Absence Mgmt, Social Security / Insurance, Certificates Report FRA, Certificates Printing Process	GPFR_ILL_AT_RNCTL
GPFRPSL Payslip and Annex	Prints payslips and annexes for the payees associated with a pay group. The data in the header of the report, such as payee and organization name and address, is extracted from the HR data tables. All of the body and footer data comes from result tables for the payroll run process.	Global Payroll & Absence Mgmt, Payslips, Create/Print Payslips FRA, Create/Print Payslips FRA	GPFR_RUNCTL_PYSL
GPFRTRP Payments Report	Lists details of each payment.	Global Payroll & Absence Mgmt, Payment Processing, Net Payment Report FRA, Payments Report	GPFR_BANK_REPORT
GPFRXRP Exceptions Report	Lists payments held by the system when performing retroactive calculations.	Global Payroll & Absence Mgmt, Payment Processing, Net Payment Report FRA, Payments Report	GPFR_BANK_REPORT
GPFRWC Work Certificate (BI Publisher)	Generates the Work Certificate (<i>Certificat de Travail</i>) that is provided to terminated employees. It gives employee and employer details and lists the employee's jobs while employed by the company.	Global Payroll & Absence Mgmt, Termination Processing, Termination Report FRA, Termination Reports	GPFR_ASS_CER_RUN

